



Installing SnapCenter Plug-in for SQL Server

SnapCenter Software

Nirupama Sriram, Soumik Das
June 17, 2021

This PDF was generated from https://docs.netapp.com/us-en/snapcenter/protect-scsql/quick_start_to_install_snapcenter_plug-in_for_sql_server.html on June 24, 2021. Always check docs.netapp.com for the latest.

Table of Contents

- Installing SnapCenter Plug-in for SQL Server 1
 - Preparing for installation 1
 - Installing SnapCenter Server 4
 - Installing the Plug-in for Microsoft SQL Server 5

Installing SnapCenter Plug-in for SQL Server

Provides a condensed set of installation instructions for installing the SnapCenter Server and the SnapCenter Plug-in for Microsoft SQL Server.

Preparing for installation

Domain and workgroup requirements

SnapCenter Server can be installed on systems that are either in a domain or in a workgroup.


If you are using an Active Directory domain, you should use a Domain user with local administrator rights. The Domain user should be a member of the local Administrator group on the Windows host.

If you are using workgroups, you should use a local account that has local administrator rights.

Licensing requirements

The type of licenses you install depends on your environment.

License	Where required
SnapCenter Standard controller-based	Required for FAS or AFF storage controllers SnapCenter Standard license is a controller-based license and is included as part of the premium bundle. If you have the SnapManager Suite license, you also get the SnapCenter Standard license entitlement. If you want to install SnapCenter on a trial basis with FAS or AFF storage, you can obtain a Premium Bundle evaluation license by contacting the sales representative.
SnapCenter Standard capacity-based	Required with ONTAP Select and Cloud Volumes ONTAP If you are a Cloud Volumes ONTAP or ONTAP Select customer, you need to procure a per TB capacity-based license based on the data managed by SnapCenter. By default, SnapCenter ships a built-in 90-day 100 TB SnapCenter Standard capacity-based trial license. For other details, contact the sales representative.
SnapMirror or SnapVault	ONTAP Either SnapMirror or SnapVault license is required if replication is enabled in SnapCenter.
Additional licenses (optional)	See SnapCenter licenses .

License	Where required
SnapCenter Standard licenses (optional)	Secondary destinations <div>  <p>It is recommended, but not required, that you add SnapCenter Standard licenses to secondary destinations. If SnapCenter Standard licenses are not enabled on secondary destinations, you cannot use SnapCenter to backup resources on the secondary destination after performing a failover operation. However, a FlexClone license is required on secondary destinations to perform clone and verification operations.</p> </div>

Additional requirements

Storage and applications	Minimum requirements
ONTAP and application plug-in	See Interoperability Matrix Tool

Hosts	Minimum requirements
Operating System (64-bit)	See Interoperability Matrix Tool
CPU	<ul style="list-style-type: none"> • Server host: 4 cores • Plug-in host: 1 core
RAM	<ul style="list-style-type: none"> • Server host: 8 GB • Plug-in host: 1 GB
Hard drive space	Server host: <ul style="list-style-type: none"> • 4 GB for SnapCenter Server software and logs • 6 GB for SnapCenter repository • Each plug-in host: 2 GB for plug-in installation and logs, this is required only if plug-in is installed on a dedicated host.

Hosts	Minimum requirements
Third-party libraries	<p>Required on SnapCenter Server host and plug-in host:</p> <ul style="list-style-type: none"> • Microsoft .NET Framework 4.5.2 or later • Windows Management Framework (WMF) 4.0 or later • PowerShell 4.0 or later
Browsers	Chrome, Internet Explorer, and Microsoft Edge

Port type	Default port
SnapCenter port	8146 (HTTPS), bidirectional, customizable, as in the URL <i>https://server:8146</i>
SnapCenter SMCore communication port	8145 (HTTPS), bidirectional, customizable
Repository database	3306 (HTTPS), bidirectional
Windows plug-in hosts	<p>135, 445 (TCP)</p> <p>In addition to ports 135 and 445, the dynamic port range specified by Microsoft should also be open. Remote install operations use the Windows Management Instrumentation (WMI) service, which dynamically searches this port range.</p> <p>For information on the dynamic port range supported, see Service overview and network port requirements for Windows.</p>
SnapCenter Plug-in for Windows	8145 (HTTPS), bidirectional, customizable
ONTAP cluster or SVM communication port	<p>443 (HTTPS), bidirectional; 80 (HTTP), bidirectional</p> <p>The port is used for communication between the SnapCenter Server host, plug-in host, and SVM or ONTAP Cluster.</p>

SnapCenter Plug-in for Microsoft SQL Server requirements

You should have a user with local administrator privileges with local login permissions on the remote host. If you manage cluster nodes, you need a user with administrative privileges to all the nodes in the cluster.

You should have a user with sysadmin permissions on the SQL Server. The plug-in uses Microsoft VDI Framework, which requires sysadmin access.

If you were using SnapManager for Microsoft SQL Server and want to import data from SnapManager for Microsoft SQL Server to SnapCenter, see [Import archived backups](#)

Installing SnapCenter Server

Downloading and installing SnapCenter Server

Steps

1. Download the SnapCenter Server installation package from the [NetApp Support Site](#) and then double-click the exe.

After you initiate the installation, all the prechecks are performed and if the minimum requirements are not met appropriate error or warning messages are displayed. You can ignore the warning messages and proceed with installation; however, errors should be fixed.

2. Review the pre-populated values required for the SnapCenter Server installation and modify if required.

You do not have to specify the password for MySQL Server repository database. During SnapCenter Server installation the password is auto generated.



The special character “%” is not supported in the custom path for installation. If you include “%” in the path, installation fails.

3. Click **Install Now**.

Logging in to SnapCenter

Steps

1. Launch SnapCenter from a shortcut on the host desktop or from the URL provided by the installation (*https://server:8146* for default port 8146 where SnapCenter Server is installed).

2. Enter the credentials.

For a built-in domain admin username format, use: *NetBIOS\<username>* or *<username>@<domain>* or *<DomainFQDN>\<username>*.

For a built-in local admin username format, use *<username>*.

3. Click **Sign In**.

Adding a SnapCenter Standard controller-based license

Steps

1. Log in to the controller using the ONTAP command line and enter:

```
system license add -license-code <license_key>
```

2. Verify the license:

```
license show
```

Adding a SnapCenter capacity-based license

Steps

1. In the SnapCenter GUI left pane, click **Settings > Software**, and then in the License section, click **+**.
2. Select one of two methods for obtaining the license:
 - Enter your NetApp Support Site login credentials to import licenses.
 - Browse to the location of the NetApp License File and click **Open**.
3. On the **Notifications** page of the wizard, use the default capacity threshold of 90 percent.
4. Click **Finish**.

Setting up storage system connections

Steps

1. In the left pane, click **Storage Systems > New**.
2. In the Add Storage System page, perform the following:
 - a. Enter the name or IP address of the storage system.
 - b. Enter the credentials that are used to access the storage system.
 - c. Select the check boxes to enable Event Management System (EMS) and AutoSupport.
3. Click **More Options** if you want to modify the default values assigned to platform, protocol, port, and timeout.
4. Click **Submit**.

Installing the Plug-in for Microsoft SQL Server

Setting up Run As Credentials

Steps

1. In the left pane, click **Settings > Credentials > New**.
2. Enter the credentials.

For a built-in domain admin username format, use: *NetBIOS\<username>* or *<username>@<domain>* or *<DomainFQDN>\<username>*.

For a built-in local admin username format, use *<username>*.

Adding a host and installing the Plug-in for Microsoft SQL Server

Steps

1. In the SnapCenter GUI left pane, click **Hosts > Managed Hosts > Add**.
2. On the Hosts page of the wizard, perform the following:
 - a. Host Type: Select Windows host type.
 - b. Host name: Use the SQL host or specify the FQDN of a dedicated Windows host.

- c. Credentials: Select the valid credential name of the host that you created or create new credentials.
- 3. In the Select Plug-ins to Install section, select **Microsoft SQL Server**.
- 4. Click **More Options** to specify the following details:
 - a. Port: Either retain the default port number or specify the port number.
 - b. Installation Path: The default path is *C:\Program Files\NetApp\SnapCenter*. You can optionally customize the path.
 - c. Add all hosts in the cluster: Select this check box if you are using SQL in WSFC.
 - d. Skip preinstall checks: Select this check box if you already installed the plug-ins manually or you do not want to validate whether the host meets the requirements for installing the plug-in.
- 5. Click **Submit**.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.