


# Packet Tracer - Backing Up Configuration Files

## Topology



## Objectives

**Part 1: Establish Connectivity to TFTP Server**

**Part 2: Transfer Configuration from TFTP Server**

**Part 3: Backup Configuration and IOS to TFTP Server**

## Background / Scenario

This activity is designed to show how to restore a configuration from a backup and then perform a new backup. Due to an equipment failure, a new router has been put in place. Fortunately backup configuration files have been saved to a Trivial File Transfer Protocol (TFTP) Server. You are required to restore the files from the TFTP Server to get the router back online with as little down time as possible.

## Part 1: Establish Connectivity to the TFTP Server

**Note:** Because this is a new router, initial configuration will be performed using a console connection to the router.

- Click **PCA**, then the **Desktop** tab, followed by **Terminal** to access the **RTA** command line.
- Configure and activate the **Gigabit Ethernet 0/0** interface. The IP address should match the default gateway for the **TFTP Server**.
- Test connectivity to **TFTP Server**. Troubleshoot, if necessary.

## Part 2: Transfer Configuration from the TFTP Server

- From privileged EXEC mode, issue the following command:

```

Router# copy tftp running-config
Address or name of remote host []? 172.16.1.2
Source filename []? RTA-config
Destination filename [running-config]? <cr>
  
```

The router should return the following:

```

Accessing tftp://172.16.1.2/RTA-config...
Loading RTA-config from 172.16.1.2: !
  
```

```
[OK - 785 bytes]
785 bytes copied in 0 secs
RTA#
%SYS-5-CONFIG_I: Configured from console by console
RTA#
```

- b. Issue the command to display the current configuration. What changes were made?
- c. Issue the appropriate **show** command to display the interface status. Are all interfaces active?
- d. Correct any issues related to interface problems and test connectivity.

### Part 3: Backup Configuration and IOS to TFTP Server

- a. Change the hostname of **RTA** to **RTA-1**.
- b. Save the configuration to NVRAM.
- c. Copy the configuration to the **TFTP Server** using the **copy** command:

```
RTA-1# copy running-config tftp:
Address or name of remote host []? 172.16.1.2
Destination filename [RTA-1-config]? <cr>
```

- d. Issue the command to display the files in flash.
- e. Copy the IOS in flash to the **TFTP Server** using the following command:

```
RTA-1# copy flash tftp:
Source filename []? c1900-universalk9-mz.SPA.151-4.M4.bin
Address or name of remote host []? 172.16.1.2
Destination filename [c1900-universalk9-mz.SPA.151-4.M4.bin]? <cr>
```