

4.3.3.6 MRAPI_RWL_DELETE

NAME

mrapi_rwl_delete

SYNOPSIS

```
void mrapi_rwl_delete(
    MRAPI_IN mrapi_rwl_hndl_t rwl,
    MRAPI_OUT mrapi_status_t* status
);
```

DESCRIPTION

This function deletes the reader/writer lock. A reader/writer lock can only be deleted if it is not locked. If the reader/writer lock attributes indicate extended error checking is enabled then all subsequent lock requests will be notified that the reader/writer lock was deleted.

RETURN VALUE

On success, *status is set to MRAPI_SUCCESS. On error, *status is set to the appropriate error defined below. When extended error checking is enabled, if this function is called on a reader/writer lock that no longer exists, an MRAPI_ERR_RWL_DELETED error code will be returned. When extended error checking is disabled, the MRAPI_ERR_RWL_INVALID error will be returned.

ERRORS

MRAPI_ERR_RWL_INVALID	Argument is not a valid reader/writer lock handle.
MRAPI_ERR_RWL_LOCKED	The reader/writer lock was locked and cannot be deleted.
MRAPI_ERR_RWL_DELETED	If the reader/writer lock has been deleted then if MRAPI_ERROR_EXT attribute is set, MRAPI will return MRAPI_ERR_RWL_DELETED otherwise MRAPI will just return MRAPI_ERR_RWL_INVALID.
MRAPI_ERR_NODE_NOTINIT	The calling node is not initialized.

NOTE

SEE ALSO