

CCNA COMMANDS

CONTENTS

| | |
|---|-----------|
| BASIC | 2 |
| Interface | 3 |
| SSH | 4 |
| Port Security on Switch | 5 |
| VLAN | 5 |
| VTP | 6 |
| Trunk | 6 |
| Etherchannel | 7 |
| SVI..... | 7 |
| IVR | 8 |
| DHCP | 8 |
| DHCP Relay Agent | 9 |
| Spanning Tree Protocol | 10 |
| ROUTING | 11 |
| EIGRP..... | 11 |
| OSPF | 12 |
| RIP | 12 |
| ACL | 13 |
| NAT | 14 |
| HSRP Configuration | 16 |
| Troubleshoot | 17 |
| Common Port Numbers and Protocols | 18 |

BASIC

| Command | Purpose |
|---|---|
| #enable | Enter global configuration mode. |
| #configure terminal | To execute any command. |
| #hostname SW-01 | Configure the NAME of the Router or Switch. |
| #username admin secret admin | Set username and password . |
| #enable secret admin | Make the privilege level password. |
| #service password-encryption | Encrypt all passwords . |
| #line console 0 | Enter the console connection configuration mode. |
| #login | Instruct the router that you want it to check for a password. |
| #password admin | Set password for Line Console . |
| # line vty 0 15 | To enable telnet connectivity on the Cisco devices. |
| # copy running-config startup-config | To Save configuration. |
| # wr | Same as copy running-configuration startup-configuration. |

Interface

| Command | Purpose |
|---------------------------------------|---|
| #interface fastethernet 0/1 | To select a port for configuration. |
| #interface range fastethernet 0/1-6 | To select a range of ports for configuration. |
| #switchport mode access | To set the port to Access mode. |
| #no shutdown | To enable the port. |
| #description MNG | To set description for interface. |
| #speed 10 / auto | To configure the speed of interface. |
| #duplex auto / full / half | To prevent a duplex mismatch |
| #ip address 192.168.1.1 255.255.255.0 | To assign an IP address & Subnet Mask for interface . |
| #switchport access vlan 10 | To access the port to VLAN10. |
| #show interfaces status | Display the status of interfaces. |
| #show ip interface brief | Display interfaces IP address and status. |
| #show interface fastethernet 0/1 | Display the detail and status of the selected port. |
| #show cdp interface | Shows which interfaces are running CDP. |
| #interface Loopback 0 | Loopback interface acts as a place holder for the static IP add |
| #ip address 10.108.1.1 255.255.255.0 | To set an IP address for loopback . |

SSH

Secure Shell is a Secure Method for Remote Access as it includes Authentication and Encryption.

| Command | Purpose |
|------------------------------|--|
| #hostname SW-1 | Must change the hostname of the device from the default. |
| #username admin secret admin | Configure a local user and password. |
| #line vty 0 15 | Change parameters for remote access. |
| #login local | To tell the VTY ports to ask for password from remote user. |
| #privilege level 15 | Default Privilege Levels allows full access to all commands. |
| #ip ssh version 2 | Configures the Switch to run SSH Version 2. |
| #transport input ssh | This will restrict SSH into this device. |
| #transport output ssh | This will allow SSH to be initiated from this device. |
| #ip domain-name cisco.local | Configure a host domain . |
| #crypto key generate rsa | Make an encryption key - select 1024 bits. |
| #banner motd "welcome" | Display a MESSAGE when you login . |

Port Security on Switch

To Stop or Prevent Unauthorized Users to Access the LAN .

| Command | Purpose |
|---|---|
| #interface fastethernet 0/1 | Select the interface to configure. |
| # switchport mode access | Change from dynamic to access mode. |
| # switchport port-security | To activate port-security. |
| # switchport port-security maximum 25 | Only 25 MAC addresses are allowed . |
| #switchport port-security mac-address sticky | To memorize MAC addresses. |
| #switchport port-security violation protect restrict shutdown | To choose the violation response. |
| #spanning-tree bpduguard enable | To disable interface if receives BPDU. |
| # no cdp run | No one can see what devices are connected. |
| #ip dhcp snooping | Prevents unauthorized DHCP servers offering IP addresses to DHCP clients. |

VLAN

Virtual LAN - Segmentation of a Network helps to Increase Security, Reliability, and Efficiency of a Network.

| Command | Purpose |
|------------------------------|--|
| #vlan 10 | To create a VLAN. |
| #name IT | To name the VLAN. |
| # interface fastethernet 0/1 | Select a port . |
| # switchport mode access | To change the mode from dynamic to access . |
| #switchport access vlan 10 | To access the interface to VLAN 10. |
| #show vlan brief | Shows what VLANs exist , name , interface assigned . |

VTP

VLAN Trunking Protocol - When you configure a new VLAN on a VTP server, the VLAN will distribute through all switches in the domain .

| Command | Purpose |
|--|---|
| #vtp domain CSO | The name of the VTP domain. |
| #vtp password admin | The password for the VTP administrative domain. |
| #vtp version 3 | The VTP version. |
| #vtp mode server client transparent | Choose the VTP mode. |
| #show vtp status | Displays information about the VTP configuration on device. |

Trunk

A **Trunk** port is a port that is Assigned to carry Traffic for all the VLANs that are Accessible by a Specific Switch , a process known as Trunking . There are two methods of Encapsulation: IEEE 802.1Q & ISL .

| Command | Purpose |
|--|---|
| #interface Gigabitethernet 0/1 | Select a port to configure. |
| #switchport trunk encapsulation dot1q | To use IEEE 802.1Q encapsulation on frames. |
| #switchport mode trunk | To convert the link into a trunk link. |
| #switchport nonegotiate | To Prevents the interface from generating DTP frames. |
| #swithport trunk native vlan 99 | To carry untagged traffic. |
| #switchport trunk allowed vlan all none vlan-list | Define which VLANs allowed on the trunk. |
| #show interface trunk | Shows the ports that are trunk . |

Etherchannel

EtherChannel provides Incremental Trunk Speeds between Fast Ethernet, Gigabit Ethernet, and 10 Gigabit Ethernet . EtherChannel combines multiple Fast Ethernet up to 800Mbps _ Gigabit Ethernet up to 8Gbps _ and 10 Gigabit Ethernet up to 80Gbps.

| Command | Purpose |
|--|--|
| #interface portchannel 10 | Creates the port channel interface. |
| #switchport mode trunk | To convert the link into Trunk . |
| #interface range fastethernet 0/1-4 | Select a range of interface to configure. |
| #switchport mode trunk | To convert the links into Trunk . |
| #channel-group 10 mode active passive on desirable | Specifies the mode : PAgP supports only the auto and desirable LACP supports only the active and passive |
| #channel-protocol lacp pagp | Choose the EtherChannel protocol. |
| #show etherchannel summary | Display brief information of all port-channels. |

SVI

Switch Virtual Interface created on a specific VLAN can be used as a **Default Gateway** for the VLAN .

| Command | Purpose |
|--|--|
| #interface vlan 10 | The valid VLAN interface. |
| #no shutdown | To enable the vlan. |
| #ip address 192.168.10.1 255.255.255.0 | Assign an IP address as default gateway on vlan 10 . |

IVR

Inter VLAN Routing Enables Routers or Layer 3 Switches to Route Traffic between VLANs.

| Command | Purpose |
|---|--|
| Router#interface GigabitEthernet 0/0.10 | To create a sub-interface for VLAN 10. |
| Router#encapsulation dot1Q 10 | Use 802.1Q trunking. |
| Router #ip address 10.0.10.1 255.255.255.0 | Assign the default gateway ip address of vlan 10 . |
| #show ip interface brief | To see the subinterfaces with IP addresses . |

DHCP

Dynamic Host Configuration Protocol will Automates the process of Allocating IP addresses .

| Command | Purpose |
|--|--|
| # interface Vlan 10 | Select a valid vlan interface . |
| # ip address 192.168.10.1 255.255.255.0 | To set the default gateway of vlan 10 . |
| # no shutdown | To enable the vlan . |
| #ip dhcp excluded-address 192.168.10.0 192.168.1.10 | Set excluded IP Addresses . |
| #ip dhcp pool VLAN-10 | To create a DHCP pool , also will change the mode to DHCP pool configuration mode. |
| #network 192.168.10.0 255.255.255.0 | Set the Network with SM . |
| #default-router 192.168.10.1 | To set default gateway for vlan 10 . |
| #dns-server 192.168.10.2 | To Set a primary DNS server for the clients. |
| #show ip dhcp binding | Displays the IP DHCP server lease entry. |

DHCP Relay Agent

DHCP Relay Agent provides a way for DHCP clients to Communicate with DHCP Servers when None are available on its Local Subnet.

| Command | Purpose |
|---|---|
| #interface FastEthernet 0/1 | The interface that connect to server. |
| #description DHCP | To set description for the port. |
| #switchport trunk encapsulation dot1q | To use IEEE 802.1Q encapsulation on the frames. |
| #switchport mode trunk | To convert the link into trunk . |
| # ip dhcp snooping trust | Configure the interface as a trusted interface. |
| #interface vlan 100 | The DHCP Vlan. |
| #ip address 192.168.100.2 255.255.255.0 | To set gateway for dhcp vlan. |
| #ip helper-address 192.168.100.1 | Now set ip helper-address on Vlan so clients could receive IP add . |

| server (physical) | |
|---------------------|---------------|
| IP address | 192.168.100.1 |
| Subnet mask | 255.255.255.0 |
| Default gateway | 192.168.100.2 |
| DNS Server | 8.8.8.8 |
| DHCP Services | |
| ServerPool-10 | ON |
| Default gateway | 192.168.10.1 |
| DNS Server | 8.8.8.8 |
| Start IP address | 192.168.10.10 |

Spanning Tree Protocol

Spanning Tree Protocol (STP) is a Layer 2 Network Protocol used to Prevent Loop within a Network Topology.

| Command | Purpose |
|---|---|
| <code>#spanning-tree mode stp rstp</code> | To select which Spanning Tree Protocol (STP) protocol to run. |
| <code>#spanning-tree vlan 10,20 root primary secondary</code> | To set these vlans as primary . |
| <code>#spanning-tree vlan 10 priority 100</code> | The low value will have higher priority. |
| <code># spanning-tree hello-time 5</code> | How often the device broadcasts Hello messages to other devices. |
| <code># spanning-tree guard root</code> | So it cannot be selected as the root port even if it receives superior STP BPDUs. |
| <code>#spanning-tree portfast</code> | To be a "designated port" immediately without going through the normal listening and learning states. |
| <code>#spanning-tree bpdugaurd enable</code> | To shutdown an interface when it receives a BPDU, will reduce the risk of attacks on the network. |
| <code>#show switch spanning-tree</code> | To see the STP configuration. |

ROUTING

To Managing Data Traffic in Router .

| Types | Command |
|---------------|--|
| Static route | 172.16.0.0 255.255.0.0 gigabitethernet 0/1 |
| Next Hop | 172.16.0.0 255.255.0.0 10.10.10.1 |
| Default route | 0.0.0.0 0.0.0.0 10.10.10.1 |

Routing Protocols

EIGRP

Enhanced Interior Gateway Routing Protocol Enables Routers to Exchange Information more Efficiently than Earlier Network Protocols .

| Command | Purpose |
|---|--|
| #router eigrp 100 | Assign an ID to EIGRP. |
| #network 172.16.10.0 0.0.0.3 | Define the interfaces + Wildcard mask. Define the |
| #network 10.10.40.0 0.0.0.255 | interfaces + Wildcard mask. |
| #no auto-summary | EIGRP auto-summary will only create summary routes for directly connected networks, not for routes you learn from other EIGRP routers. |
| #redistribute eigrp 200 metric 1000000 100 255 1 1500 | To exchange routing information between different routing protocols – Eigrp metric { bandwidth delay reliability load MTU } |
| # show ip route | To display the Ipv4 routing table . |
| #show ip eigrp topology | To view all available routes for each destination. To list all |
| #show ip route eigrp | routes added in the routing table by EIGRP. |
| #show ip eigrp neighbors | To see the routers which became neighbors. |

OSPF

Open Shortest Path First - Can Recalculate the Routes in a Short Amount of Time .

| Command | Purpose |
|--|--|
| #router ospf 1 | Enables OSPF configuration mode. |
| #network 192.168.10.0 0.0.0.255 area 0 | To define network and area . |
| # ip ospf cost 1562 | To set an absolute OSPF cost for a link . |
| # ip ospf hello-interval seconds | Change hello timer from default 10 seconds. |
| # ip ospf dead-interval seconds | Change dead timer from default 40 seconds |
| #show ip ospf interface | Displays OSPF-related interface information. |
| #show ip ospf neighbor | Displays OSPF neighbors information . |

RIP

Routing Information Protocol is a Distance Vector Protocol that uses Hop Count as its Primary Metric.

| Command | Purpose |
|-----------------------|--|
| #router rip | Enable RIP routing mode . |
| #network 192.168.10.0 | To define the interfaces network which are connecte |
| #version 2 | Enable RIP routing protocol version 2. |
| #no auto-summary | To disable automatically summarize networks . |
| # show rip database | Displays information about routes in the Routing Information Base. |
| #show rip neighbors | Displays information about all RIP route gateways. |

ACL

Access Control List is an Ordered Set of Rules that you can use to Filter Traffic .

Standard-ACL

| Command | Purpose |
|--|--|
| #access-list 1 permit host 192.168.146.0 | Access-list standard (1-99) - To allow access for this host . |
| #access-list 1 deny 11.0.0.0 0.0.0.255 | To deny access for this host . |
| #ip access-group 1 out in | Set this on incoming outgoing interfaces . |

Extended-ACL

| Command | Purpose |
|--|--|
| #access-list 100 permit ip 10.0.0.1 0.0.0.0 host 192.168.0.1 | To allow all access to host 192.168.0.1. |
| #access-list 100 deny ip 10.0.0.2 0.0.0.0 host 192.168.0.1 | To deny all access to host 192.168.0.1. |
| #interface fastethernet 0/0 | Select the port. |
| #ip access-group 100 in | Set this on incoming outgoing interfaces . |
| #ip access-list extended 100 | Access list extended (100-199) . |
| #permit tcp 10.0.0.2 0.0.0.3 host 192.168.0.1 eq 80 | To allow access only for website 192.168.0.1 . |
| # permit tcp any any eq 80 | To allow web access for all. |
| #permit ip any any | Full access for all. |
| #deny udp 172.16.10.0 0.0.0.255 host 192.168.0.1 eq 53 | To deny DNS . |
| #deny icmp 10.10.10.0 0.0.0.3 host 192.168.0.1 | To deny ICMP . |

NAT

Network Address Translation

Static NAT is used to do a One-To-One Mapping between an Inside address and an Outside address.

| Command | Purpose |
|---|--|
| #ip nat inside source static 10.0.0.0 255.255.255.0 100.1.1.1 | 10.0.0.0 will translate to ip public 100.1.1.1 |
| #interface fastethernet 0/1 | Incoming port |
| #ip nat inside | |
| #interface fastethernet 0/2 | Outgoing port |
| #ip nat outside | |

Dynamic NAT is used when you have a Pool of Public IP addresses that you want to Assign to your Internal Hosts Dynamically.

| Command | Purpose |
|---|---------------------------------------|
| #interface fastethernet 0/0 | |
| #ip nat inside | Incoming interface . |
| #interface fastethernet 0/1 | |
| #ip nat outside | Outgoing interface . |
| #access-list 1 permit 10.0.0.0 0.0.0.255 | Define the network that have access . |
| #ip nat pool STUDY 5.5.5.1 5.5.5.11 netmask 255.255.255.0 | Define a pool of public ip address . |
| #ip nat inside source list 1 pool STUDY | Dynamic NAT command. |
| #show ip nat translations | To show NAT table. |

Overload NAT | PAT also known as **Port Address Translation**, is a technique used in computer networking.

It Allows for Multiple Devices on a Private Network to Access the Internet using a Single Public IP Address.

| Command | Purpose |
|--|--|
| #access list 1 permit 192.168.0.0 0.255.255.255 | Define the network that have access . |
| #ip nat pool STUDY 20.20.20.2 20.20.20.2 netmask 255.255.255.252 | Define a pool which include single ip public . |
| #ip nat inside source list 1 pool STUDY overload | PAT Command. |
| #interface fastethernet 0/1 | |
| #ip nat inside | Incoming port. |
| #interface fastethernet 0/2 | |
| #ip nat outside | Outgoing port. |

HSRP Configuration

Hot Standby Router Protocol is Cisco's Standard Method of providing High network Availability by providing First-hop Redundancy for IP hosts .

| Command | Purpose |
|---------------------------------|---|
| # interface gigabitethernet 0/1 | Enter the interface which you want to enable HSRP. |
| # standby 10 ip 172.167.10.10 | Create the HSRP group using its number and virtual IP address. |
| #standby 10 priority 120 | Assigning priority helps select the active and standby - The highest number represents the highest priority. |
| #standby preempt | If preemption is enabled , the switch with the highest priority becomes the designated active . |
| #standby 10 delay 300 | To postpone taking over the active role for the shown number of seconds. |
| # standby 1 timers 5 15 | Configure the time between hello packets and the time before other switch declare the active switch to be down. |
| # show standby | To see if HSRP is active. |
| #show standby brief | To see HSRP details. |

Troubleshoot

| Command | Purpose |
|--------------------------|--|
| #ping 172.16.10.10 | To reach the destination host. |
| #tracert 172.16.10.10 | Shows the path taken to reach the destination host . |
| #show process cpu | Shows cpu statistics . |
| #show arp | Display the arp cache. |
| #show users | Displays the users currently logged on. |
| #show reload | Reboots the device. |
| #clear crypto session | Debug crypto isakmp. |
| #ip routing | Activate IPv4 routing within the switch. |
| #show running-config | Display the running configuration – active. |
| #show startup-config | Display the startup configuration. |
| #show ip route connected | Show routing table entries for directly connected networks. |
| # show version | Display the software version that the switch runs. |
| #show inventory | To display the product inventory listing of all Cisco products installed in the networking device. |
| # show module | Display status and information for all modules. |
| #show clock | Display the clock. |
| #show cdp neighbors | Show directly connected cisco devices. |
| #show mac-address table | Display switch mac address table. |
| #show standby | See if HSRP is active. |

Common Port Numbers and Protocols

| Protocol | Port |
|---|--|
| File Transfer Protocol (FTP) | FTP Control=TCP port 21 FTP Data = TCP Port 20 |
| Secure Shell (SSH) | TCP Port 22 |
| Telnet | TCP Port 23 |
| Simple Mail Transfer Protocol (SMTP) | TCP Port 25 |
| Dynamic Host Configuration Protocol (DHCP) | UDP Port 67 (request from client to server) UDP Port 68 (reply from server to client) |
| Hypertext Transfer Protocol (HTTP) | TCP Port 80 |
| Secure Hypertext Transfer Protocol (HTTPS) | TCP Port 443 |
| Post Office Protocol – incoming mail (POP) | TCP Port 110 |
| Network Time Protocol (NTP) | UDP Port 123 |
| Simple Network Management Protocol (SNMP) | UDP Port 161 |
| Domain Name System name resolver (DNS) | TCP, UDP Port 53 |
| Trivial File Transfer Protocol(TFTP) | UDP Port 69 |
| Internet Message Access Protocol (IMAP) | TCP, UDP Port 143 |
| Remote Desktop Protocol (RDP) | TCP port 3389 |