


To update the IOCDS by using HCD option 2.11, complete the following steps:

1. From the HCD main panel, select option **2. Activate or process configuration data** (Figure 5-6). Ensure that the IODF is the production IODF that was created in 5.1, "Building the 8561 production IODF" on page 88 and then press **Enter**.



```
z/OS V2.4 HCD
Command ==> _____

Hardware Configuration

Select one of the following.

2_ 0. Edit profile options and policies
    1. Define, modify, or view configuration data
    2. Activate or process configuration data
    3. Print or compare configuration data
    4. Create or view graphical configuration report
    5. Migrate configuration data
    6. Maintain I/O definition files
    7. Query supported hardware and installed UIMs
    8. Getting started with this dialog
    9. What's new in this release

For options 1 to 5, specify the name of the IODF to be used.

I/O definition file . . . 'SYS6.IODF67' +
```

Figure 5-6 Hardware Configuration: Activate or process configuration data