





Getting started with 2D Tilezone

In the Unity editor you will find the main tile editing window under Windows > Tileset Editor. This window can be docked with other windows to save space. Your window should look something like this.



To start using the tileset editor you must first set up a material for the tiles. Create a new material (Assets > Create > Material) and assign a shader to it. The recommended shader to use is Unlit/Transparent Cutout for scenes that aren't affected by lighting, or Standard with the render mode set to cutout if you want to add in lights to the scene. Set the main texture of the shader to the tilesheet image you want to use. If you don't want to set up a material there is a material already set up called SpritesetMat.

Once you have a material set, up drag it into the box beside Material in the Tileset Editor window and you will see the tiles appear. Before you can create a layer to work on you must set up the tile size and spacing to match the tilesheet image used. You will know you have done this step correctly when the grid matches up with all the tiles in the image.



You can now click on Create New Layer to create a layer to work on. Note that you can extend the map size after you have created it, so don't worry if it is too small. You will now see that the box beside Layer to edit has the layer you just created in it. If you want to edit another layer then either drag the gameObject from the hierarchy to the box under Layer to edit or click the circle beside the box and select the layer from the list. You can now start editing using the tools provided.

Border Pixel Offset

The border pixel offset value is how much of the border pixel of each tile is cut off. This is to help hide visible seams between tiles. If you want a pixel perfect look to your game set this value to 0 and use the Pixel Perfect Camera.

The Tools




Various tools are at your disposal for editing the tile map in the scene view.

- Paint Brush Tool: Paint the selected tile(s) directly to the scene.
- Erase Tool: Remove tiles. Works the same as the Box Tool.
- Box Tool: Click and drag on the scene to draw a filled in rectangle of tiles.
- Rotate Tool: Click on a tile to rotate it 90 degrees anti-clockwise. Note that this won't work on an Auto Tile in the scene view. Edit Auto Tiles in the Tileset Editor window.
- Flip Tool: Click on a tile to flip it horizontally. This also won't work on Auto Tiles.
- Fill Tool: Click on a tile to fill in an area of tiles.
- Collisions: This tool is not for editing the scene view. Collisions changes the behaviour of the Tileset Editor window so that when you click on a tile you change the collision data of that tile.

If you have the Paint Brush Tool, the Box Tool, or the Fill tool selected and you hold down shift and click and drag a box on the scene view you will select those tiles for use.

Collisions



Clicking on a tile or dragging a box over multiple tiles in the Tileset Editor window with Collisions selected will toggle through either full collision, slope up right, slope up left, platform, or none. Platform (Top half of the square is blue) will set up the colliders to use Unity's built in Platform Effector 2D component and will set it up for one way collisions.

The collision mesh doesn't get automatically get updated, instead you need to click on Update Colliders. This may take a few seconds with larger maps.

Collision data can now easily be saved and loaded to save time.


2D Tilezone can now generate slopes from the tilesheet image, so you are no longer limited to using only flat or 45 degree angles. To use slopes generated from the image check the Slopes from image checkbox.

With this option selected any tile set to either slope up left, slope up right, or platform will automatically generate colliders from the pixels in the image, so there is no difference from slope up left and slope up right.

Using the Auto Tile feature.

The Auto Tile feature is a powerful feature that allows groups of tiles to connect up with each other in a logical way without you having to individually select each tile image. The Auto Tile feature has been set up in a way that works with most tile formats.

To start using Auto Tile set the Number of Auto Tiles to 1 or higher. An image will appear with a bunch of light grey tiles. These tiles are a general guideline as to what type of tile to place there. To place a tile select a tile or group of tiles from the tilesheet image in the tilesheet editor window, and click on the appropriate tile in the Auto Tile image. Tiles in the Auto Tile can also be flipped and rotated so you can easily get the tile needed without having to edit the tilesheet image in an external editor.



Notice that in the above image not all the tiles are filled in in the Auto Tile image. This is ok as 2D Tilezone will pick the next best tile. The tiles in the image above is the minimum needed to get good looking results.

If you have the Auto Tile Type set to Isometric Wall then the tiles filled in in the previous image are the only tiles used.

Once you have set up your Auto Tile you can select it with the tick box beside the image and draw on to the scene. You can use any of the drawing tools to place Auto Tiles.

- **Hide:** This button hides the Auto Tiles so you can see the guide image.
- **Link With:** Chooses which Auto Tiles this Auto Tile links with. You probably at least want it to link with itself.
- **Map edge link mode:** Choose how the Auto Tile will display for tiles on the edge of the map.
- **Auto Tile Type:** The type of Auto Tile, either Normal or Isometric Wall.
- **Save / Load:** Saves or loads Auto Tile data to/from a file.

In the inspector view with a layer selected there are a list of references to other layers. These are for joining layers together and having the Auto Tiles link up between layers.

Other Features

- **Update 3D Walls:** Check this box to have walls put in the Z direction. These walls will be invisible to the camera but can be used to block light for nice looking shadows, or for colliders if you wish to use 3D physics instead of 2D.
- **Export To PNG:** Exports the entire map to a PNG image.

To use either Update 3D Walls or Export To PNG the texture used in the material must have read/write checked in the Texture Import settings. This setting can only be seen if you set the texture type to advanced.

Setting up a Pixel Perfect Camera

To set up a Pixel Perfect Camera select the camera you wish to set up and go Add Component > 2D > Pixel Perfect Camera.

- **Pixels Per Unit:** The amount of pixels per one Unity unit. Set this to the tile size.
- **Zoom Factor:** How much to zoom in.

Technical Information

When it comes to programming your game you are likely to want some basic information about the tiles. The `TileInfo` class contains access to a bunch of information and functions to help you. Also contained are functions to modify tiles in game.

Tile class

The `Tile` class contains information about a single tile.

- `int xIndex, yIndex`: The x and y position of the tile on the tile sheet. The top left tile is `xIndex 0, yIndex 0`, and the next tile to the right is `xIndex 1, yIndex 0`.
- `bool flip`: Checked if the tile has been flipped horizontally.
- `int rotation`: The rotation of the tile. 0 = no rotation, 1 = 90 degrees anti-clockwise, 2 = 180 degrees, 3 = 270 degrees anti-clockwise.
- `int autoTileIndex`: The index of the Auto Tile this tile belongs to, or -1 if this tile isn't an autotile.
- `Vector2 GetBottomLeftUV (TileInfo tileInfo)`: Gets the uv of the bottom left of the tile. `tileInfo` is the map this tile belongs to.
- `CollisionType GetCollisionType(TileInfo tileInfo)` gets the collision type of this tile according to the information provided by `tileInfo`

The `Tile` class can also be compared to a `Vector2` and returns equal if `xIndex = Vector2.x` and `yIndex = Vector2.y`. Also `Tile` can be cast as a `Vector2`.

TileInfo class

The `TileInfo` class is automatically attached to any `Tile Layer` created in the `Tileset Editor`. The `TileInfo` class contains information about the whole map and contains an array of `Tile` objects.

Variables:

- `Tile[] tiles`: An array of all the tiles.
- `int mapWidth, mapHeight`: the width and height of the map in tiles.
- `int numberOfTiles`: The number of tiles not including empty tiles.(read only)
- `int tileSize`: The size of a tile in pixels.
- `int spacing`: The amount of space between tiles on the tilesheet.
- `CollisionType[] collisions`: an array of the collision types for each tile on the tilesheet.
- `int numberOfAutotiles`: The number of Auto Tiles this map has set up.
- `list<string> autoTileNames`: List of names for the auto tiles.
- `list<int> autoTileLinkMask`: List of link bitmasks for the auto tiles.
- `list<Tile> autoTileData`: List of tile data for the auto tiles.
- `list<AutoTileEdgeMode> autoTileEdgeMode`: List of edge modes for the auto tiles.

- `bool update3DWalls`: If checked 3D walls will be updated when `UpdateVisualMesh()` is called.
- `PolygonCollider2D mainCollider`: The main 2D collider
- `PolygonCollider2D platformCollider`: The collider for the platforms effected by `PlatformEffector2D`

Functions:

- `GetMapAtWorldPos(Vector2 worldPos)`: returns the first map found containing `worldPos`.
- `GetMapsAtWorldPos(Vector2 worldPos)`: returns all the maps found containing `worldPos`.
- `UpdateVisualMesh()`: Updates the mesh. Must be called after any modification to the tiles for the modification to be seen.
- `AddTile(Vector2 worldPos, Tile selectedTile)`: adds a tile to the map at the given world position.
- `AddTile(Vector2 worldPos, int autoTileIndex)`: adds an `AutoTile` to the map at the given world position.
- `FloodFill (Vector2 worldPos, Tile[,] selectedTiles, Vector2 originalPos, Tile originalTile)`: Performes a flood fill of tiles. Set `worldPos` and `originalPos` to the same value for a normal flood fill. `selectedTiles` is a 2D array of tiles, if only one tile is wanted create a 2D array with both dimensions at length 1.
- `FloodFill (Vector2 worldPos, int autoTileIndex, Vector2 originalPos, Tile originalTile)`: Flood fill for `Auto Tiles`.
- `RemoveTile (Vector2 worldPos)`: Removes the tile at the world position.
- `RotateTile (Vector2 worldPos)`: Rotates the tile 90 degrees anti-clockwise.
- `FlipTile (Vector2 worldPos)`: Flips the tile horizontally.
- `ResizeBoundsToFitWorldPos (Vector2 worldPos)`: Resizes the bounds to fit the world position. The map has a max size of 64 x 64 tiles.
- `UpdateColliders()`: Updates the 2D colliders. This might take a second or 2 for larger maps on slower computers.
- `WorldPointToMapIndex (Vector2 worldPos)`: Returns the index of the tile at the world position, or -1 if the position is out of the map bounds. This is a quick way of checking if the map contains the position.
- `LocalPointToWorldIndex (Vector2 localPos)`: Same as above but for a local position. If you already know that the position is in the map then this is the same as $(localPos.y * mapWidth + localPos.x)$.

PixelPerfectCamera class

`PixelPerfectCamera.SnapToPix(Transform transform)` can be called on any transform to snap it to a pixel.