



**Clarion**

# Language Reference Manual

**COPYRIGHT 1994-2009 SoftVelocity Incorporated. All rights reserved.**

This publication is protected by copyright and all rights are reserved by SoftVelocity Incorporated. It may not, in whole or part, be copied, photocopied, reproduced, translated, or reduced to any electronic medium or machine-readable form without prior consent, in writing, from SoftVelocity Incorporated.

This publication supports Clarion. It is possible that it may contain technical or typographical errors. SoftVelocity Incorporated provides this publication “as is,” without warranty of any kind, either expressed or implied.

**SoftVelocity Incorporated**

2335 East Atlantic Blvd. Suite 410

Pompano Beach, Florida 33062

(954) 785-4555

[www.softvelocity.com](http://www.softvelocity.com)

**Documentation for Clarion 7**

**Trademark Acknowledgements:**

SoftVelocity is a trademark of SoftVelocity Incorporated.

Clarion™ is a trademark of SoftVelocity Incorporated.

Microsoft®, Windows®, and Visual Basic® are registered trademarks of Microsoft Corporation.

All other products and company names are trademarks of their respective owners.

# Table of Contents

<b>Table of Contents</b>	<b>iii</b>
<b>1 - The Language Reference Manual</b>	<b>1</b>
Chapter Organization .....	1
Documentation Conventions and Symbols .....	3
Clarion Conventions .....	4
KEYWORD (short description of intended use) .....	4
Standard Time .....	5
Clarion Keycodes .....	6
<b>2 - Program Source Code Format</b>	<b>7</b>
Statement Format .....	7
Declaration and Statement Labels .....	8
Structure Termination .....	9
Field Qualification .....	10
Reserved Words .....	12
Special Characters .....	13
Program Format .....	15
PROGRAM (declare a program) .....	15
MEMBER (identify member source file) .....	18
MAP (declare PROCEDURE prototypes) .....	20
MODULE (specify MEMBER source file) .....	22
PROCEDURE (define a procedure) .....	23
CODE (begin executable statements) .....	26
DATA (begin routine local data section) .....	27
ROUTINE (declare local subroutine) .....	28
END (terminate a structure) .....	30
Statement Execution Sequence .....	31
PROCEDURE Calls .....	32
PROCEDURE Prototypes-Prototype Syntax .....	33
Prototype Parameter Lists .....	36
PROCEDURE Return Types .....	44
Prototype Attributes .....	46
C, PASCAL (parameter passing conventions) .....	46
DERIVED (prevent function overloading) .....	47
DLL (set procedure defined externally in .DLL) .....	48
PRIVATE (set procedure private to a CLASS or module) .....	49
PROC (set function called as procedure without warnings) .....	50
PROTECTED (set procedure private to a CLASS or derived CLASS) .....	51
RAW (pass address only) .....	52
REPLACE (set replacement constructor or destructor) .....	53
TYPE (specify PROCEDURE type definition) .....	54
VIRTUAL (set virtual method) .....	55
Procedure Overloading .....	56
Rules for Procedure Overloading .....	57
Name Mangling and C++ Compatibility .....	59
Compiler Directives .....	60
ASSERT (set assumption for debugging) .....	61
BEGIN (define code structure) .....	62
COMPILE (specify source to compile) .....	63
INCLUDE (compile code in another file) .....	65
ITEMIZE (enumeration data structure) .....	66
OMIT (specify source not to be compiled) .....	67

ONCE (prevent duplicate included data).....	69
SECTION (specify source code section).....	70
SIZE (memory size in bytes) .....	71
<b>3 - Variable Declarations</b>	<b>75</b>
BYTE (one-byte unsigned integer) .....	75
SHORT (two-byte signed integer) .....	76
USHORT (two-byte unsigned integer).....	78
LONG (four-byte signed integer) .....	80
ULONG (four-byte unsigned integer) .....	82
SIGNED (signed integer).....	84
UNSIGNED (unsigned integer).....	85
SREAL (four-byte signed floating point) .....	86
REAL (eight-byte signed floating point).....	88
BFLOAT4 (four-byte signed floating point).....	90
BFLOAT8 (eight-byte signed floating point) .....	92
DECIMAL (signed packed decimal) .....	94
PDECIMAL (signed packed decimal) .....	96
STRING (fixed-length string) .....	98
ASTRING (atomic string).....	100
CSTRING (fixed-length null terminated string).....	103
PSTRING (embedded length-byte string) .....	105
Implicit String Arrays and String Slicing .....	107
DATE (four-byte date) .....	109
TIME (four-byte time).....	111
Special Data Types: .....	114
ANY (any simple data type).....	114
LIKE (inherited data type).....	117
Implicit Variables .....	119
Reference Variables .....	120
Data Declarations and Memory Allocation .....	123
Global, Local, Static, and Dynamic .....	123
Data Declaration Sections .....	124
Variable Size Declarations .....	125
NEW (allocate heap memory) .....	126
DISPOSE (de-allocate heap memory) .....	129
Picture Tokens.....	131
Numeric and Currency Pictures.....	132
Scientific Notation Pictures.....	134
String Pictures .....	135
Date Pictures .....	136
Time Pictures.....	138
Pattern Pictures .....	139
Key-in Template Pictures .....	140
<b>4 - Entity Declarations</b>	<b>143</b>
Complex Data Structures: .....	143
GROUP (compound data structure) .....	143
CLASS (object declaration) .....	146
INTERFACE (class behavior definition) .....	155
File Structures.....	157
FILE (declare a data file structure) .....	157
INDEX (declare static file access index) .....	160
KEY (declare dynamic file access index) .....	161
MEMO (declare a text field).....	162
BLOB (declare a variable-length field) .....	163

RECORD (declare record structure) .....	166
Null Data Processing .....	167
FILE Structure Properties .....	168
Environment Files .....	175
View Structures: .....	178
VIEW (declare a "virtual" file) .....	178
PROJECT (set view fields) .....	181
JOIN (declare a "join" operation) .....	182
Queue Structures: .....	185
QUEUE (declare a memory QUEUE structure) .....	185
Additional QUEUE Programming Considerations .....	188
<b>5 - Declaration Attributes</b> .....	<b>195</b>
Variable and Entity Attributes: .....	195
AUTO (uninitialized variable) .....	195
BINARY (memo contains binary data) .....	196
BINDABLE (set runtime expression string variables) .....	197
CREATE (allow data file creation) .....	198
DIM (set array dimensions) .....	199
DLL (set variable defined externally in .DLL) .....	201
DRIVER (specify data file type) .....	203
DUP (allow duplicate KEY entries) .....	204
ENCRYPT (encrypt data file) .....	205
EXTERNAL (set defined externally) .....	206
FILTER (set view filter expression) .....	208
IMPLEMENTS(add methods to a CLASS) .....	211
Implementing of INTERFACES in Derived Classes .....	213
INNER (set inner join operation) .....	216
LINK (specify CLASS link into project) .....	217
LINK (specify CLASS link into project) .....	218
MODULE (specify CLASS member source file) .....	219
NOCASE (case insensitive KEY or INDEX) .....	220
OEM (set international string support) .....	221
OPT (exclude null KEY or INDEX entries) .....	222
ORDER (set view sort order expression) .....	223
OVER (set shared memory location) .....	225
OWNER (declare password for data encryption) .....	226
PRE (set label prefix) .....	227
PRIMARY (set relational primary key) .....	228
PRIVATE (set variable private to a CLASS module) .....	229
PROTECTED (set variable private to a CLASS or derived CLASS) .....	230
RECLAIM (reuse deleted record space) .....	231
STATIC (set allocate static memory) .....	232
THREAD (set thread-specific memory allocation) .....	234
TYPE (type definition) .....	236
<b>6 - Windows</b> .....	<b>237</b>
APPLICATION (declare an MDI frame window) .....	237
WINDOW (declare a dialog window) .....	242
MENUBAR (declare a pulldown menu) .....	248
TOOLBAR (declare a tool bar) .....	251
Window Overview .....	254
Window Controls and Input Focus .....	255
Field Equate Labels .....	256
Graphics Overview .....	258
Current Target .....	259

Graphics Coordinates .....	260
<b>7 – Reports</b>	<b>261</b>
Report Structures .....	261
REPORT (declare a report structure) .....	261
Page Overflow .....	264
BREAK (declare group break structure) .....	265
DETAIL (report detail line structure) .....	266
FOOTER (page or group footer structure) .....	268
FORM (page layout structure) .....	270
HEADER (page or group header structure) .....	271
Printer Control Properties .....	273
<b>8 – Controls</b>	<b>277</b>
BOX (declare a box control) .....	277
BUTTON (declare a pushbutton control) .....	279
CHECK (declare a checkbox control) .....	282
COMBO (declare an entry/list control) .....	285
ELLIPSE (declare an ellipse control) .....	290
ENTRY (declare a data entry control) .....	292
GROUP (declare a group of controls) .....	296
IMAGE (declare a graphic image control) .....	299
ITEM (declare a menu item) .....	301
LINE (declare a line control) .....	304
LIST (declare a window list control) .....	306
MENU (declare a menu box) .....	311
OLE (declare a window OLE or .OCX container control) .....	314
OPTION (declare a set of RADIO controls) .....	318
PANEL (declare a panel control) .....	322
PROMPT (declare a prompt control) .....	323
PROGRESS (declare a progress control) .....	325
RADIO (declare a radio button control) .....	327
REGION (declare a window region control) .....	330
SHEET (declare a group of TAB controls) .....	332
SPIN (declare a spinning list control) .....	336
STRING (declare a string control) .....	340
TAB (declare a page of a SHEET control) .....	344
TEXT (declare a multi-line text control) .....	346
<b>9 - Window and Report Attributes</b>	<b>349</b>
Attribute Property Equates .....	349
PROP:Text with Windows and Controls .....	351
ABSOLUTE (set fixed-position printing) .....	352
ALONE (set to print without page header, footer, or form) .....	353
ALRT (set window "hot" keys) .....	354
ANGLE (set control display or print angle) .....	356
AT (set position and size) .....	357
AUTO (set USE variable automatic re-display) .....	360
AUTOSIZE (set OLE object resizing) .....	361
AVE (set report total average) .....	362
BEVEL (set 3-D effect border) .....	363
BOXED (set controls group border) .....	364
CAP, UPR (set case) .....	365
CENTER (set centered window position) .....	366
CENTERED (set centered image) .....	367
CHECK (set on/off ITEM) .....	368

CLIP (set OLE object clipping) .....	369
CNT (set total count) .....	370
COLOR (set color) .....	371
COLUMN (set list box highlight bar) .....	373
COMPATIBILITY (set OLE control compatibility) .....	374
CREATE (create OLE control object) .....	375
CURSOR (set mouse cursor type) .....	376
DEFAULT (set enter key button) .....	377
DELAY (set repeat button delay) .....	378
DISABLE (set control dimmed at open) .....	379
DOCK (set dockable toolbox window) .....	380
DOCKED (set dockable toolbox window docked at open) .....	381
DOCUMENT (create OLE control object from file) .....	383
DOCUMENT (create OLE control object from file) .....	383
DRAGID (set drag-and-drop host signatures) .....	384
DROP (set list box behavior) .....	385
DROPID (set drag-and-drop target signatures) .....	386
EXTEND (set document formatting) .....	387
FILL (set fill color) .....	388
FLAT (set flat control) .....	389
FONT (set default font) .....	390
FORMAT (set LIST or COMBO layout) .....	393
FORMAT() Runtime Properties .....	398
FORMAT() Style Properties .....	401
FORMAT() Other List Box Properties .....	403
FORMAT() List Box Mouse Click Properties .....	405
FROM (set listbox data source) .....	407
FULL (set full-screen) .....	409
GRAY (set 3-D look background) .....	410
GRID (set list grid-line display color) .....	411
HLP (set on-line help identifier) .....	412
HSCROLL, VSCROLL, HVSCROLL (set scroll bars) .....	413
ICON (set icon) .....	414
ICONIZE (set window open as icon) .....	416
IMM (set immediate event notification) .....	417
INS, OVR (set typing mode) .....	419
JOIN (set joined TAB scroll buttons) .....	420
KEY (set execution keycode) .....	421
LANDSCAPE (set page orientation) .....	422
LAYOUT (set window orientation) .....	423
LEFT, RIGHT, ABOVE, BELOW (set TAB position) .....	424
LEFT, RIGHT, CENTER, DECIMAL (set justification) .....	425
LINEWIDTH (set line thickness) .....	427
LINK (create OLE control link to object from file) .....	428
MASK (set pattern editing data entry) .....	429
MAX (set maximize control or total maximum) .....	430
MAXIMIZE (set window open maximized) .....	432
MDI (set MDI child window) .....	433
MIN (set total minimum) .....	434
MODAL (set system modal window) .....	435
MSG (set status bar message) .....	436
NOBAR (set no highlight bar) .....	437
NOCASE (case insensitive report BREAK) .....	438
NOMERGE (set merging behavior) .....	439
NOSHEET (set "floating" TABs) .....	440
OPEN (open OLE control object from file) .....	441

PAGEAFTER (set page break after) .....	442
PAGEBEFORE (set page break first).....	443
PAGENO (set page number print).....	444
PAPER (set report paper size) .....	445
PASSWORD (set data non-display).....	446
PREVIEW (set report output to metafiles).....	447
RANGE (set range limits) .....	449
READONLY (set display-only).....	450
REPEAT (set repeat button rate) .....	451
REQ (set required entry) .....	452
RESET (set total reset).....	453
RESIZE (set variable height TEXT control).....	454
RIGHT (set MENU position) .....	455
ROUND (set round-cornered BOX).....	456
RTF (declare TEXT control as RichEdit).....	457
SCROLL (set scrolling control).....	458
SEPARATOR (set separator line ITEM).....	459
SINGLE (set TEXT for single line entry).....	460
SKIP (set Tab key skip or conditional print control).....	461
SMOOTH (set smooth progress bar increments).....	462
SPREAD (set evenly spaced TAB controls).....	463
STATUS (set status bar) .....	464
STD (set standard behavior) .....	465
STEP (set SPIN increment).....	466
STRETCH (set OLE object stretching).....	467
SUM (set total).....	468
SYSTEM (set system menu) .....	469
TALLY (set total calculation times).....	470
THOUS, MM, POINTS (set report coordinate measure).....	471
TILED (set tiled image).....	472
TIMER (set periodic event).....	473
TIP (set "balloon help" text).....	474
TOGETHER (set to print on a single page).....	475
TOOLBOX (set toolbox window behavior) .....	476
TRN (set transparent control).....	478
UP, DOWN (set TAB text orientation) .....	479
USE (set field equate label or control update variable).....	480
VALUE (set RADIO or CHECK control USE variable assignment).....	483
VERTICAL (set vertical progress bar display).....	484
VCR (set VCR control) .....	485
WALLPAPER (set background image).....	486
WITHNEXT (set widow elimination) .....	487
WITHPRIOR (set orphan elimination) .....	488
WIZARD (set "tableless" SHEET control) .....	489
ZOOM (set OLE object zooming) .....	490
<b>10 - Expressions</b> .....	<b>491</b>
Expressions Overview .....	491
Expression Evaluation .....	491
Arithmetic Operators.....	492
The Concatenation Operator .....	493
Logical Operators .....	494
Numeric Constants .....	495
String Constants .....	496
Numeric Expressions.....	497
String Expressions.....	498



Logical Expressions.....	499
Property Expressions .....	500
Runtime Expression Evaluation.....	503
BIND (declare runtime expression string variable).....	504
BINDEXPRESSION(declare runtime expression).....	506
EVALUATE (return runtime expression string result).....	507
POPBIND (restore runtime expression string name space).....	509
PUSHBIND (save runtime expression string name space).....	510
UNBIND (free runtime expression string variable) .....	511
<b>11 - Assignments</b>	<b>513</b>
Simple Assignments .....	513
Operating Assignments .....	514
Deep Assignment .....	515
Reference Assignments .....	517
CLEAR (clear a variable).....	519
Data Type Conversion Rules.....	520
Base Types.....	521
BCD Operations and Procedures.....	522
Simple Assignment Data Type Conversion.....	523
<b>12 - Execution Control</b>	<b>529</b>
ACCEPT (the event processor).....	529
CASE (selective execution structure).....	531
EXECUTE (statement execution structure).....	533
IF (conditional execution structure) .....	535
LOOP (iteration structure) .....	537
Execution Control Statements:.....	539
BREAK (immediately leave loop) .....	539
CYCLE (go to top of loop) .....	540
DO (call a ROUTINE) .....	542
EXIT (leave a ROUTINE) .....	543
GOTO (go to a label).....	544
RETURN (return to caller) .....	545
<b>13 - Built-in Procedures</b>	<b>547</b>
ABS (return absolute value) .....	547
ACCEPTED (return control just completed).....	548
ACOS (return arccosine) .....	549
ADD (add an entry).....	550
ADDRESS (return memory address) .....	554
AGE (return age from base date) .....	555
ALERT (set event generation key) .....	556
ALIAS (set alternate keycode).....	558
ALL (return repeated characters) .....	559
APPEND (add a new file record).....	560
ARC (draw an arc of an ellipse).....	561
ASK (get one keystroke).....	562
ASIN (return arcsine).....	563
ATAN (return arctangent) .....	564
BAND (return bitwise AND) .....	565
BEEP (sound tone on speaker).....	566
BLANK (erase graphics).....	567
BOR (return bitwise OR).....	568
BOX (draw a rectangle).....	569
BSHIFT (return shifted bits).....	570

BUILD (build keys and indexes) .....	571
BXOR (return bitwise exclusive OR) .....	574
BYTES (return size in bytes) .....	575
CALL (call procedure from a DLL) .....	577
CALLBACK (register or unregister a FileCallBackInterface) .....	578
CENTER (return centered string) .....	583
CHAIN (execute another program) .....	584
CHANGE (change control field value) .....	585
CHANGES (return changed queue) .....	586
CHOICE (return relative item position) .....	587
CHOOSE (return chosen value) .....	588
CHORD (draw a section of an ellipse) .....	590
CHR (return character from ASCII) .....	591
CLEAR (clear a variable) .....	592
CLIP (return string without trailing spaces) .....	593
CLIPBOARD (return windows clipboard contents) .....	594
CLOCK (return system time) .....	595
CLONE(duplicate existing control) .....	596
CLOSE (close a data structure) .....	598
COLORIALOG (return chosen color) .....	600
COMMAND (return command line) .....	601
COMMIT (terminate successful transaction) .....	602
CONTENTS (return contents of USE variable) .....	603
CONVERTANSITOOEM (convert ANSI strings to ASCII) .....	604
CONVERTOEMTOANSI (convert ASCII strings to ANSI) .....	605
COPY (copy a file) .....	606
COS (return cosine) .....	607
CREATE (create an empty data file) .....	608
CREATE (return new control created) .....	609
DATE (return standard date) .....	612
DAY (return day of month) .....	613
DEFORMAT (return unformatted numbers from string) .....	614
DELETE (delete a record) .....	615
DELETEREG (remove a value or key from Windows registry) .....	617
DESTROY (remove a control) .....	618
DIRECTORY (get file directory) .....	619
DISABLE (dim a control) .....	622
DISPLAY (write USE variables to screen) .....	623
DRAGID (return matching drag-and-drop signature) .....	624
DROPID (return drag-and-drop string) .....	625
DUPLICATE (check for duplicate key entries) .....	627
ELLIPSE (draw an ellipse) .....	628
EMPTY (empty a data file) .....	629
ENABLE (re-activate dimmed control) .....	630
ENDPAGE (force page overflow) .....	631
ERASE (clear screen control and USE variables) .....	633
ERROR (return error message) .....	634
ERRORCODE (return error code number) .....	635
ERRORFILE (return error filename) .....	636
EVENT (return event number) .....	637
EXISTS (return file or folder existence) .....	638
FIELD (return control with focus) .....	639
FILEDIALOG (return chosen file) .....	640
FILEDIALOGA (extended file dialog) .....	644
FILEERROR (return file driver error message) .....	648
FILEERRORCODE (return file driver error code number) .....	649

FIRSTFIELD (return first window control) .....	650
FIXFORMAT (fix a dynamic file).....	651
FLUSH (flush buffers).....	652
FOCUS (return control with focus) .....	653
FONTDIALOG (return chosen font).....	654
FONTDIALOGA (return chosen font and character set) .....	656
FORMAT (return formatted numbers into a picture).....	658
FORWARDKEY (pass keystrokes to control).....	659
FREE (delete all entries) .....	660
FREESTATE (free resources).....	661
GET (read a record or entry) .....	662
GETFONT (get font information) .....	666
GETGROUP (return reference to GROUP).....	667
GETINI (return INI file entry).....	668
GETNULLS(get the NULL state of a table) .....	669
GETPOSITION (get control or window position).....	670
GETREG(get Windows registry entry) .....	672
GETSTATE (return current state of data file) .....	674
HALT (exit program) .....	675
HELP (help window access).....	676
HIDE (blank a control) .....	677
HOLD (exclusive record access).....	678
HOWMANY (return dimensions) .....	680
IDLE (arm periodic procedure) .....	681
IMAGE (draw a graphic image) .....	682
INLIST (return entry in list) .....	683
INSTANCE (return variable's thread instance address).....	684
INSTRING (return substring position) .....	687
INT (truncate fraction).....	689
ISALPHA (return alphabetic character) .....	690
ISGROUP (return GROUP type or not).....	691
ISLOWER (return lower case character).....	692
ISSTRING (return field string type or not) .....	693
ISUPPER (return upper case character).....	694
KEYBOARD (return keystroke waiting).....	695
KEYCHAR (return ASCII code) .....	696
KEYCODE (return last keycode) .....	697
KEYSTATE (return keyboard status) .....	698
LASTFIELD (return last window control).....	699
LEFT (return left justified string) .....	700
LEN (return length of string) .....	701
LINE (draw a straight line).....	702
LOCALE (load environment file).....	703
LOCK (exclusive file access).....	704
LOCKTHREAD (re-lock the current execution thread).....	705
LOG10 (return base 10 logarithm) .....	706
LOG10 (return base 10 logarithm) .....	707
LOGE (return natural logarithm).....	708
LONGPATH (return long filename) .....	709
LOWER (return lower case) .....	710
MATCH (compare matching values) .....	711
MAXIMUM (return maximum subscript value).....	714
MESSAGE (return message box response).....	715
MONTH (return month of date).....	717
MOUSEY (return mouse vertical position) .....	718
NAME (return file name).....	719

NEXT (read next record in sequence).....	720
NOMEMO (read file record without reading memo).....	722
NOTIFICATION (receive information from sender thread).....	723
NOTIFY (send safe information to a receiver thread).....	725
NULL (return null file field).....	726
NUMERIC (return numeric string).....	728
OMITTED (return omitted parameters).....	729
OPEN (open a data structure).....	731
PACK (remove deleted records).....	735
PATH (return current directory).....	736
PEEK (read memory address).....	737
PENCOLOR (return line draw color).....	738
PENSTYLE (return line draw style).....	739
PENWIDTH (return line draw thickness).....	740
PIE (draw a pie chart).....	741
POINTER (return last queue entry position).....	743
POKE (write to memory address).....	744
POLYGON (draw a multi-sided figure).....	745
POPUP (return popup menu selection).....	746
POSITION (return record sequence position).....	749
POST (post user-defined event).....	752
PRAGMA (control pragma settings from source).....	753
PRESS (put characters in the buffer).....	755
PRESSKEY (put a keystroke in the buffer).....	756
PREVIOUS (read previous view record in sequence).....	757
PRINT (print a report structure).....	759
PRINTERDIALOG (return chosen printer).....	760
POPERERRORS (return error information).....	761
PUSHERRORS (write error information).....	763
PUT (re-write record).....	765
PUTINI (set INI file entry).....	769
PUTREG (write value to Windows registry).....	770
QUOTE (replace string special characters).....	773
RANDOM (return random number).....	774
RECORDS (return number of rows in data set).....	775
REGISTER (register event handler).....	777
REGET (re-get record).....	779
RELEASE (release a held record).....	781
REMOVE (erase a file).....	782
RENAME (change file directory name).....	783
RESET (reset record sequence position).....	784
RESTORESTATE (restore state of data file).....	787
RESUME (resume thread execution).....	788
ROLLBACK (terminate unsuccessful transaction).....	789
ROUND (return rounded number).....	790
RUN (execute command).....	791
RUNCODE (return program exit code).....	793
SELECT (select next control to process).....	794
SELECTED (return control that has received focus).....	796
SEND (send message to file driver).....	797
SET (initiate sequential file processing).....	798
SET3DLOOK (set 3D window look).....	801
SETCLIPBOARD (set windows clipboard contents).....	802
SETCLOCK (set system time).....	803
SETCOMMAND (set command line parameters).....	804
SETCURSOR (set temporary mouse cursor).....	805

SETDROPID (set DROPID return string) .....	807
SETFONT (specify font) .....	808
SETKEYCHAR (specify ASCII code) .....	810
SETKEYCODE (specify keycode) .....	811
SETLAYOUT (set window orientation) .....	812
SETNULL (set file field null) .....	813
SETNULLS(set the null state of columns).....	815
SETPATH (change current drive and directory).....	816
SETPENCOLOR (set line draw color).....	817
SETPENWIDTH (set line draw thickness).....	818
SETPOSITION (specify new control position).....	819
SETTARGET (set current window or report).....	820
SHORTPATH (return short filename).....	822
SHOW (write to screen).....	823
SHUTDOWN (arm termination procedure).....	824
SIN (return sine) .....	825
SORT (sort queue entries) .....	826
SQL (use SQL code) .....	828
SQLCALLBACK (register or unregister a SQLCallBackInterface) .....	830
SQRT (return square root).....	833
START (return new execution thread).....	834
STATUS (return file or window/report status).....	836
STOP (suspend program execution).....	838
STREAM (enable operating system buffering).....	839
STRPOS (return matching value position) .....	840
SUB (return substring of string).....	842
SUSPEND (suspend thread execution) .....	844
TAN (return tangent).....	845
THREADLOCKED (returns current execution thread locked state) .....	846
TIE(associate a string value to an ASTRING).....	847
TIED(retrieves a value associated with an ASTRING).....	848
TODAY (return system date).....	849
TYPE (write string to screen).....	850
UNFIXFORMAT (unfix a dynamic file) .....	851
UNHIDE (show hidden control) .....	852
UNLOAD (remove a CALLED DLL from memory) .....	853
UNLOCK (unlock a locked data file).....	854
UNLOCKTHREAD (unlock the current execution thread).....	855
UNQUOTE (remove string special characters) .....	856
UNREGISTER (unregister event handler).....	857
UNTIE(disassociate a string value from an ASTRING).....	858
UPDATE (write from screen to USE variables) .....	859
UPPER (return upper case).....	860
VAL (return ASCII value).....	861
WATCH (automatic concurrency check) .....	862
WHAT (return field from group) .....	863
WHERE (return field position in group) .....	864
WHO (return field name from group).....	865
YEAR (return year of date).....	866
<b>Appendix A - DDE, OLE, and OCX .....</b>	<b>867</b>
Dynamic Data Exchange- DDE Overview .....	867
DDE Events .....	868
DDEACKNOWLEDGE (send acknowledgement from DDE server) .....	869
DDEAPP (return server application).....	870
DDECHANNEL (return DDE channel number) .....	871

DDECLIENT (return DDE client channel).....	872
DDECLOSE (terminate DDE server link) .....	873
DDEEXECUTE (send command to DDE server) .....	874
DDEITEM (return server item).....	875
DDEPOKE (send unsolicited data to DDE server).....	876
DDEQUERY (return registered DDE servers).....	878
DDERead (get data from DDE server).....	879
DDESERVER (return DDE server channel).....	881
DDETOPIC (return server topic).....	882
DDEVALUE (return data value sent to server).....	883
DDEWRITE (provide data to DDE client) .....	884
Object Linking and Embedding.....	886
OLE Overview.....	886
OLE Container Properties .....	887
OLEDIRECTORY (get list of installed OLE/OCX).....	894
OLE custom control Overview .....	895
.OCX Control Properties .....	895
.OCX Control Properties .....	897
Calling OLE Object Methods .....	899
Method Syntax Overview.....	899
Parameter Passing to OLE/OCX Methods .....	901
OCX Library Procedures .....	904
OCXREGISTERPROPEdit (install property edit callback).....	904
OCXREGISTERPROPCHANGE (install property change callback).....	905
OCXREGISTEREVENTPROC (install event processing callback).....	906
OCXUNREGISTERPROPEdit (un-install property edit callback).....	907
OCXUNREGISTERPROPCHANGE (un-install prop change callback) .....	908
OCXUNREGISTEREVENTPROC (un-install event process callback) .....	909
OCXGETPARAMCOUNT (return number of parameters for current event).....	910
OCXGETPARAM (return current event parameter string) .....	911
OCXSETPARAM (set current event parameter string) .....	912
OCXLOADIMAGE (return an image object).....	913
<b>Appendix B - Events</b> .....	<b>915</b>
Modal Events.....	915
Field-Independent Events.....	917
EVENT:AlertKey .....	918
EVENT:BuildDone .....	918
EVENT:BuildFile .....	918
EVENT:BuildKey .....	918
EVENT:CloseDown .....	918
EVENT:CloseWindow.....	919
EVENT:Completed .....	919
DDE Events .....	920
EVENT:Docked .....	921
EVENT:Undocked .....	921
EVENT:GainFocus .....	921
EVENT:Iconize .....	921
EVENT:Iconized .....	921
EVENT:LoseFocus .....	921
EVENT:Maximize .....	922
EVENT:Maximized .....	922
EVENT:Move .....	922
EVENT:Moved .....	922
EVENT:NestedLoop .....	922
EVENT:Notify.....	922

EVENT:OpenWindow .....	923
EVENT:PreAlertKey .....	924
EVENT:Restore .....	924
EVENT:Restored .....	924
EVENT:Resume .....	924
EVENT:Size .....	924
EVENT:Sized .....	925
EVENT:Suspend .....	925
EVENT:Timer .....	925
Field-Specific Events .....	926
EVENT:Accepted .....	926
EVENT:AlertKey .....	926
EVENT:ColumnResize .....	926
EVENT:Contracted .....	926
EVENT:Contracting .....	927
EVENT:Drag .....	927
EVENT:Dragging .....	928
EVENT:Drop .....	928
EVENT:DroppedDown .....	928
EVENT:DroppingDown .....	928
EVENT:Expanded .....	928
EVENT:Expanding .....	929
EVENT:Locate .....	929
Mouse Events .....	930
EVENT:NewSelection .....	931
EVENT:PageDown .....	931
EVENT:PageUp .....	931
EVENT:PreAlertKey (Field Specific) .....	931
EVENT:Rejected .....	931
EVENT:ScrollBottom .....	932
EVENT:ScrollDown .....	932
EVENT:ScrollDrag .....	932
EVENT:ScrollTop .....	932
EVENT:ScrollTrack .....	932
EVENT:ScrollUp .....	932
EVENT:Selected .....	933
EVENT:Selecting .....	933
EVENT:TabChanging .....	933
<b>App C - Runtime Properties .....</b>	<b>935</b>
PROP:AcceptAll .....	935
PROP:Active .....	936
PROP:AlwaysDrop .....	936
PROP:ApplInstance .....	936
PROP:AssertHook .....	937
PROP:AssertHook2 .....	937
PROP:AutoPaper .....	938
PROP:BreakVar .....	938
PROP:Buffer .....	939
PROP:CharSet .....	940
PROP:Checked .....	941
PROP:Child and PROP:ChildIndex .....	941
PROP:ChoiceFreq .....	943
PROP:ClientHandle .....	944
PROP:ClientHeight .....	945
PROP:ClientWidth .....	945

PROP:ClientWndProc .....	945
PROP:ClientX .....	946
PROP:ClientY .....	946
PROP:ClipBits .....	947
PROP:CloseReportHook .....	947
PROP:CloseWindowHook .....	947
PROP:ColorDialogHook .....	948
PROP:ColorHighByte .....	948
PROP:CustomColor .....	948
PROP:DDEMode .....	949
PROP:DDETimeOut .....	949
PROP:DeferMove .....	949
PROP:Edit .....	951
PROP:Enabled .....	952
PROP:EventsWaiting .....	953
PROP:ExeVersion .....	953
PROP:FatalErrorHook .....	953
PROP:FileDialogHook .....	953
PROP:FlushPageNumFunc .....	954
PROP:FlushPreview .....	955
PROP:Follows .....	957
PROP:FontDialogHook .....	958
PROP:HaltHook .....	958
PROP:Handle .....	958
PROP:HeaderHeight .....	960
PROP:HscrollPos .....	960
PROP:IconList .....	961
PROP:ImageBits .....	962
PROP:ImageBlob .....	963
PROP:ImageInstance .....	963
PROP:InitAStringHook .....	963
PROP:Interface .....	963
PROP:InToolbar .....	964
PROP:IPRequestCount .....	964
PROP:Items .....	965
PROP:LazyDisplay .....	965
PROP:LFNSupport .....	966
PROP:LibHook .....	966
PROP:LibVersion .....	967
PROP:Line and PROP:LineCount .....	968
PROP:LineHeight .....	969
PROP:MaxHeight .....	969
PROP:MaxWidth .....	970
PROP:MenuBar .....	970
PROP:MessageHook .....	970
PROP:MinHeight .....	971
PROP:MinWidth .....	971
PROP:NextField .....	972
PROP:NextPageNo .....	973
PROP:NextTabStop and PROP:PrevTabStop .....	974
PROP:NoFrame .....	974
PROP:NoHeight and PROP:NoWidth .....	975
PROP:NoTips .....	975
PROP:NumTabs .....	976
PROP:OpenReportHook .....	977
PROP:OpenWindowHook .....	978



PROP:Parent .....	978
PROP:Pixels .....	980
PROP:Places .....	980
PROP:PrinterDialogHook .....	980
PROP:PrintMode .....	981
PROP:Progress .....	982
PROP:PropVScroll .....	982
PROP:RejectCode .....	983
PROP:ScreenText .....	984
PROP:SelStart (or PROP:Selected) and PROP:SelEnd .....	985
PROP:Size .....	986
PROP:SnapHeight and PROP:SnapWidth .....	987
PROP:StatusFont .....	989
PROP:StopHook .....	989
PROP:SystemPropHook .....	989
PROP:TabBarColor .....	990
PROP:TabBarLocation .....	991
PROP:TabBarStyle .....	991
PROP:TabBarVisible .....	991
PROP:TabRows .....	992
PROP:TabSheetStyle .....	993
PROP:Target .....	993
PROP:TemplImage .....	993
PROP:TemplImagePath .....	993
PROP:TemplImageStatus .....	993
PROP:TempNameFunc .....	993
PROP:TempPagePath .....	994
PROP:TempPath .....	994
PROP:ThemeActive .....	995
PROP:Thread .....	995
PROP:Threading .....	995
PROP:TipDelay and PROP:TipDisplay .....	996
PROP:TipsFont .....	996
PROP:ToolBar .....	996
PROP:Touched .....	997
PROP:Type .....	998
PROP:UpsideDown .....	999
PROP:UseAddress .....	1000
PROP:Visible .....	1001
PROP:VLBproc and PROP:VLBval .....	1002
PROP:Vscroll .....	1004
PROP:VscrollPos .....	1005
PROP:Watched .....	1006
PROP:WheelScroll .....	1006
PROP:WindowsVersion .....	1007
PROP:WndProc .....	1008
PROP:Xorigin and PROP:YOrigin .....	1010
Runtime VIEW and FILE Properties .....	1012
PROP:Completed .....	1013
PROP:ConnectString .....	1013
PROP:CurrentKey .....	1013
PROP:DataPath .....	1014
PROP:Details .....	1014
PROP:DriverLogoutAlias .....	1014
PROP:DuplicateKey .....	1015
PROP:FetchSize .....	1016

PROP:Field .....	1016
PROP:FieldsFile .....	1017
PROP:File .....	1017
PROP:Files .....	1018
PROP:FileSize .....	1019
PROP:FlushLog .....	1020
PROP:GlobalHelp .....	1021
PROP:Held .....	1021
PROP:Log .....	1022
PROP:Logout .....	1023
PROP:LogoutIsolationLevel .....	1024
PROP:MaxStatements .....	1024
PROP:Profile .....	1024
PROP:ProgressEvents .....	1025
PROP:Record .....	1027
PROP:SQLDriver .....	1027
PROP:StmtAttr .....	1027
PROP:SupportsOp .....	1027
PROP:SupportsType .....	1028
PROP:Text (MEMO/BLOB Property) .....	1028
PROP:Value .....	1029
PROP:Watched .....	1030
<b>App D - Error Codes</b> .....	<b>1031</b>
XML ErrorCodes .....	1031
Extended ERRORCODE 47 Errors .....	1032
Run Time Errors .....	1037
Trappable Run Time Errors .....	1037
Compiler Errors .....	1043
Specific Errors .....	1044
Unknown errors .....	1056
<b>App E - Legacy Statements</b> .....	<b>1057</b>
BOF (return beginning of file) {bmc C6H0007.BMP} .....	1057
EOF (return end of file) .....	1058
FUNCTION (define a function) .....	1059
POINTER (return relative record position) .....	1060
SHARE (open data file for shared access) .....	1061
<b>Index</b> .....	<b>1062</b>

# 1 - The Language Reference Manual

Clarion is an integrated environment for writing data processing applications and management information systems for microcomputers using the Windows operating environment. Clarion's programming language is the foundation of this environment. In this help file, the language is concisely documented in a modular fashion. Although this is not a text book, you should consult this help first when you want to know the precise syntax required to implement any declaration, statement, or function.

Wherever possible, we provide real-world example code for each item.

## Chapter Organization

**CHAPTER 1 - Introduction** provides an introduction to the Clarion Language Reference. It provides a brief overview of the contents of each chapter, and a guide to help the reader understand the documentation conventions used throughout the book.

**CHAPTER 2 - Program Source Code Format** provides the general layout of a Clarion Windows program. Punctuation, special characters, reserved words, and a detailed description of the "building blocks" required to create modular, structured Clarion source code are documented here.

**CHAPTER 3 - Variable Declarations** describes all the simple data types used to declare variables in a Clarion program. In addition, data display formatting masks, called "picture tokens," are defined and illustrated.

**CHAPTER 4 - Entity Declarations** describes all the complex data types used to declare GROUP, CLASS, FILE, VIEW, and QUEUE structures in a Clarion program.

**CHAPTER 5 - Declaration Attributes** describes all the attributes which can modify variable and entity declarations.

**CHAPTER 6 - Windows** describes the APPLICATION and WINDOW data structures and all their component structures.

**CHAPTER 7 - Reports** describes the REPORT data structure and all its component structures.

**CHAPTER 8 - Controls** describes all the controls that may be placed into APPLICATION, WINDOW, and REPORT data structures.

**CHAPTER 9 - Window and Report Attributes** describes all the attributes which can modify APPLICATION, WINDOW, and REPORT data structures and the controls they contain.

**CHAPTER 10 - Expressions** defines the syntax required to combine variables, procedures, and constants into numeric, string, or logical expressions.

**CHAPTER 11 - Assignments** defines all the methods to assign the value of an expression to variables. This chapter also discusses BCD operations and Clarion's Automatic Data Type Conversion.

**CHAPTER 12 - Execution Control** describes the compound executable statements that control program flow and operation.

**CHAPTER 13 - Built-in Procedures** documents all built-in Clarion library procedures.

**APPENDIX A - DDE, OLE, and OCX** documents the procedures that perform Dynamic Data Exchange (DDE), Object Linking and Embedding (OLE), and OLE Custom Controls (OCX).

**APPENDIX B - Event Equates** documents the EQUATE statements for events that help make Clarion code readable.

**APPENDIX C - Runtime Property Assignments** documents all the runtime properties.

**APPENDIX D - Error Codes** documents the runtime and compiler errors.

**APPENDIX E - Legacy Statements** documents language statements which are maintained only for backward compatibility with previous versions of Clarion.

## Documentation Conventions and Symbols

Symbols are used in the syntax diagrams as follows:

<u>Symbol</u>	<u>Meaning</u>
[ ]	Brackets enclose an optional (not required) attribute or parameter.
( )	Parentheses enclose a parameter list.
	Vertical lines enclose parameter lists, where one, but only one, of the parameters is allowed.

Coding example conventions used throughout this manual:

```

IF NOT SomeDate      !IF and NOT are keywords
  SomeDate = TODAY() !SomeDate is a data name
END                  !TODAY and END are keywords

```

**CLARION LANGUAGE KEYWORDS** Any word in "All Caps" is a Clarion Language keyword

**DataNames** Use mixed case with caps for readability

**Comments** Predominantly lower case

The purpose of these conventions is to make the code examples readable and clear.

Symbols are used in the syntax diagrams as follows:

<u>Symbol</u>	<u>Meaning</u>
[ ]	Brackets enclose an optional (not required) attribute or parameter.
( )	Parentheses enclose a parameter list.
	Vertical lines enclose parameter lists, where one, but only one, of the parameters is allowed.

Coding example conventions used throughout this manual:

```

IF NOT SomeDate      !IF and NOT are keywords
  SomeDate = TODAY() !SomeDate is a data name
END                  !TODAY and END are keywords

```

**CLARION LANGUAGE KEYWORDS** Any word in "All Caps" is a Clarion Language keyword

**DataNames** Use mixed case with caps for readability

**Comments** Predominantly lower case

The purpose of these conventions is to make the code examples readable and clear.

## Clarion Conventions

### KEYWORD (short description of intended use)

```
[label]  KEYWORD( | parameter1 | [ parameter2 ] ) [ATTRIBUTE1( )] [ATTRIBUTE2( )]  
          | alternate   |  
          | parameter  |  
          | list       |
```

---

**KEYWORD**     A brief statement of what the KEYWORD does.

*parameter1*     A complete description of parameter1, along with how it relates to parameter2 and the KEYWORD.

*alternate*  
*parameter list*     A complete description of mutually exclusive alternates to parameter1, along with how they relate to parameter2 and the KEYWORD.

*parameter2*     A complete description of parameter2, along with how it relates to parameter1 and the KEYWORD. Because it is enclosed in brackets, [ ], it is optional, and may be omitted.

**ATTRIBUTE1**     A sentence describing the relation of ATTRIBUTE1 to the KEYWORD.

**ATTRIBUTE2**     A sentence describing the relation of ATTRIBUTE2 to the KEYWORD.

A concise description of what the **KEYWORD** does. In many cases the KEYWORD will be an attribute of a keyword that was described in the preceding text. Sometimes a KEYWORD has no parameters and/or attributes.

**Events Generated:**     If the KEYWORD generates events, they are listed here.

**Return Data Type:**     The data type returned if the KEYWORD returns a value.

**Errors Posted:**     If KEYWORD posts errors which may be trapped by the ERROR and ERRORCODE functions, they are listed here.

**Related Procedures:**     If KEYWORD defines a data structure, the procedures which operate on that data structure are listed here.

#### Example:

```
FieldOne = FieldTwo + FieldThree     !This is a source code example  
FieldThree = KEYWORD(FieldOne,FieldTwo)     !Comments follow the "!" character
```

#### See Also:

Other pertinent keywords and topics

## Standard Time

A Clarion standard time is the number of hundredths of a second that have elapsed since midnight, plus one (1). The valid range is from 1 (defined as midnight) to 8,640,000 (defined as 11:59:59.99 PM). A standard time of one is exactly equal to midnight to allow a zero value to be used to detect no time entered. Although time is expressed to the nearest hundredth of a second, the system clock is only updated 18.2 times a second (approximately every 5.5 hundredths of a second).

The LONG data type with a time format (@T) display picture is normally used for a standard time. The TIME data type is a data format used in the Btrieve Record Manager. A TIME field is internally converted to LONG containing the Clarion standard time before any mathematical or time procedure operation is performed. Therefore, TIME should be used for external Btrieve file compatibility, and LONG should normally be used for other times.

**See Also:**

Time Pictures

CLOCK

SETCLOCK

## Clarion Keycodes

### Windows Keycode Mapping Format

---

Each key on the keyboard is assigned a keycode. Keycodes are 16-bit values where the low-order 8 bits (values from 0 to 255) represent the key that was pressed, and the high-order 8 bits indicate the state of the Shift, Ctrl, and Alt keys. Keycodes are returned by the `KEYCODE()` and `KEYBOARD()` procedures, and use the following format:

		A		C		S		CODE		
Bits:		10		9		8		7		0

CODE -	The Key pressed
A -	Alt key bit
C -	Ctrl key bit
S -	Shift key bit

Calculating a keycode's numeric value is generally unnecessary, since most of the possible key combinations are listed as `EQUATE` statements in `KEYCODES.CLW` (`INCLUDE` this file and use the equates instead of the numbers for better code readability).

### KEYCODES.CLW

---

Keycode equate labels assign mnemonic labels to Clarion keycodes. The keycode equates file (`KEYCODES.CLW`) is a Clarion source file which contains an `EQUATE` statement for each keycode. This file is located in the install `\LIBSRC` directory.

It may be merged into a source `PROGRAM` by placing the following statement in the global data section:

```
INCLUDE ( 'KEYCODES.CLW' )
```

This file contains `EQUATE` statements for most of the keycodes supported by Windows. These keycode `EQUATES` are used for greater code readability wherever you need to set or compare keyboard input.

#### See Also:

`KEYCODE`

`KEYBOARD`

`KEYCHAR`

`KEYSTATE`

`SETKEYCODE`

`ALERT`

`ALRT`

Keycode Equates List



## 2 - Program Source Code Format

### Statement Format

Clarion is a "statement oriented" language. A statement oriented language makes use of the fact that its source code is contained in ASCII text files so every line of code is a separate record in the file. Therefore, the Carriage Return/Line Feed record delimiter can be used to eliminate punctuation.

In general, the Clarion statement format is:

```
label STATEMENT[ (parameters) ] [ ,ATTRIBUTE[ (parameters) ] ] ...
```

Attributes specify the properties of the item and are only used on data declarations. Executable statements take the form of a standard procedure call, except assignment statements ( $A = B$ ) and control structures (such as IF, CASE, and LOOP).

A statement's label must begin in column one (1) of the source code. A statement without a label must not start in column one. A statement is terminated by the end of the line. A statement too long to fit on one line can be continued by a vertical bar ( | ). The semi-colon is an optional statement separator that allows you to place more than one statement on a line.

Being a statement oriented language eliminates from Clarion much of the punctuation required in other languages to identify labels and separate statements. Blocks of statements are initiated by a single compound statement, and are terminated by an END statement (or period).

**See Also:**

- Declaration and Statement Labels

- Structure Termination

- Field Qualification

- Reserved Words

- Special Characters

## Declaration and Statement Labels

The language statements in a source module can be divided into two general categories: data declarations and executable statements, or simply "data" and "code."

During program execution, data declarations reserve memory storage areas that are manipulated by executable statements. A label is required for the data to be referenced in executable code. All variables, data structures, PROCEDURES, and ROUTINES are referenced by labels.

A label defines a specific location in a PROGRAM. Any code statement may be identified and referenced by a label. This allows it to be used as the target of a GOTO statement. Each label on an executable statement adds ten bytes to the executable code size, even if not referenced.

The label on a PROCEDURE statement is the procedure's name. Using the label of a PROCEDURE in an executable statement executes the procedure, or in expressions, or parameter lists of other procedures, assigns the value returned by the procedure.

The rules for valid Clarion labels are:

- A label MUST begin in column one (1) of the source code.
- A label may contain letters (upper or lower case), numerals 0 through 9, the underscore character (`_`), and colon (`:`).
- The first character must be a letter or the underscore character.
- Labels are not case sensitive (i.e. `CurRent` and `CURRENT` are the same).
- A label may not be a reserved word.
- A period (`.`) is valid in a label for procedures defined in a CLASS structure in the form *ClassLabel.MethodLabel*

## Structure Termination

Compound data structures are created when data declarations are nested within other data declarations. There are many compound data structures within the Clarion language: APPLICATION, WINDOW, REPORT, FILE, RECORD, GROUP, VIEW, QUEUE, etc. These compound data structures must be terminated by a period (.) or the keyword END. IF, CASE, EXECUTE, LOOP, BEGIN, and ACCEPT are all executable control structures. They must also be terminated with a period or the END statement (a LOOP may optionally terminate with a WHILE or UNTIL statement).

## Field Qualification

Variables declared as members of complex data structures (GROUP, QUEUE, FILE, RECORD, etc.) may have duplicate labels, as long as the duplicates are not contained within the same structure. To explicitly reference fields with duplicate labels in separate structures, you may use the PRE attribute on the structures just as it is documented (Prefix:FieldLabel) to provide unique names for each field. However, the PRE attribute is not required for this purpose and may be omitted.

Any member of any complex structure can be explicitly referenced by prepending the label of the structure containing the field to the field label, separated by a period (StructureName.FieldLabel). You must use this Field Qualification syntax to reference any field in a complex structure that does not have a PRE attribute. You may use a colon (:) instead of a period (StructureName:FieldLabel) to reference member variables of any structure except CLASS and named reference variables (this syntax is only to provide backward compatibility with previous versions of Clarion for Windows).

If the variable is within nested complex data structures, you must prepend each successive level's structure label to the variable label to explicitly reference the variable (if the nested structure has a label). If any nested structure does not have a label, then that part is omitted from the qualification sequence. This is similar to anonymous unions in C++. This means that, in the case of a GROUP structure (without a PRE attribute) in which a nested GROUP structure has a label, the fields in the inner GROUP must be referenced as *OuterGroupLabel.InnerGroupLabel.FieldLabel*. If the inner GROUP structure does not have a label, the individual fields are referenced as *OuterGroupLabel.FieldLabel*. There is one exception to this rule: the label of a RECORD structure within a FILE may be omitted so that you can reference individual fields within the file as *FileLabel.FieldLabel* instead of *FileLabel.RecordLabel.FieldLabel*.

This Field Qualification syntax is also used to reference all members of CLASS structures--both data members and methods. To call a member method of a CLASS structure, you specify *ClassName.MethodLabel* wherever the call to the PROCEDURE is valid.

To reference an element of a GROUP structure with the DIM attribute, you must specify the array element number in the Field Qualification syntax at the exact level at which the DIM attribute appears.

**Example:**

```

MasterFile FILE, DRIVER('TopSpeed')
Record      RECORD
AcctNumber  LONG          !Reference as Masterfile.AcctNumber
            END
            END

Detail      FILE, DRIVER('TopSpeed')
            RECORD
AcctNumber  LONG          !Reference as Detail.AcctNumber
            END
            END

Memory      GROUP, PRE (Mem)
Message     STRING(30)    !May reference as Mem:Message or Memory.Message
            END

SaveQueue   QUEUE
Field1      LONG          !Reference as SaveQueue.Field1
Field2      STRING        !Reference as SaveQueue.Field2
            END

OuterGroup  GROUP
Field1      LONG          !Reference as OuterGroup.Field1
Field2      STRING        !Reference as OuterGroup.Field2
InnerGroup  GROUP
Field1      LONG          !Reference as OuterGroup.InnerGroup.Field1
Field2      STRING        !Reference as OuterGroup.InnerGroup.Field2
            END
            END

OuterGroup  GROUP, DIM(5)
Field1      LONG          !Reference as OuterGroup[1].Field1
InnerGroup  GROUP, DIM(5) !Reference as OuterGroup[1].InnerGroup
Field1      LONG          !Reference as OuterGroup[1].InnerGroup[1].Field1
            END
            END

```

**See Also:**

PRE

CLASS

Reference Variables

## Reserved Words

The following keywords are reserved and may not be used as labels for any purpose:

ACCEPT	AND	ASSERT	BEGIN	BREAK
BY	CASE	CATCH	CHOOSE	CODE
COMPILE	CONST	CYCLE	DATA	DO
ELSE	ELSIF	END	EXECUTE	EXIT
FINALLY	FUNCTION	GOTO	IF	INCLUDE
LOOP	MEMBER	NEW	NOT	NULL
OF	OMIT	OR	OROF	PRAGMA
PROCEDURE	PROGRAM	RETURN	ROUTINE	SECTION
THEN	THROW	TIMES	TO	TRY
UNTIL	WHILE	XOR		

The following keywords may be used as labels of data structures or executable statements. They may not be the label of any PROCEDURE statement. They may appear as the label of a parameter in a prototype only if the data type is also listed:

APPLICATION	CLASS	DETAIL	FILE	FOOTER
FORM	GROUP	HEADER	ITEM	ITEMIZE
JOIN	MAP	MENU	MENUBAR	MODULE
OLE	OPTION	QUEUE	PARENT	RECORD
REPORT	SELF	SHEET	TAB	TOOLBAR
VIEW	WINDOW			

**Note:**

SELF and PARENT cannot name local variables or parameters of any class or interface method.

## Special Characters

### Initiators:

!	Exclamation point begins a source code comment.
?	Question mark begins a field equate label, label, or when used as a single character in column one of source code, designates that the statement that follows only be executed in DEBUG mode.
@	"At" sign begins a picture token.
@@	Used in Clarion# only. You cannot use <i>reserved</i> keywords as labels or identifiers unless they include the @@ as a prefix (i.e., @@IF). You also should use @@ as prefix if you'd like to use <i>Construct</i> or <i>Destruct</i> as a label for a declaration that is not a class constructor or destructor.
*	Asterisk begins a parameter passed by address in a MAP prototype.
~	A leading tilde on a filename indicates a file linked into the project.
!~ <block of comments> ~!	Multi-line comments support (Clarion# only)
!!!	Initiates XML Documentation (Clarion# only)

### Terminators:

;	Semi-colon is an executable statement separator.
CR/LF	Carriage-return/Line-feed is an executable statement separator.
.	Period terminates a data or code structure (a substitute for END).
	Vertical bar is the source code line continuation character.
#	Pound sign declares an implicit LONG variable.
\$	Dollar sign declares an implicit REAL variable.
"	Double quote declares an implicit STRING variable.

**Delimiters:**

( )	Parentheses enclose a parameter list.
[ ]	Brackets enclose an array subscript list.
' '	Single quotes enclose a string constant.
{ }	Curly braces enclose a repeat count in a string constant, or a property parameter.
< >	Angle brackets enclose an ASCII code in a string constant, or indicate a parameter in a MAP prototype which may be omitted.
:	Colon separates the start and stop positions of a string "slice."
,	Comma separates parameters in a parameter list.

**Connectors:**

.	Period is a decimal point used in numeric constants, or connects a complex structure label to the label of one of its members.
:	Colon connects a prefix to a label.
\$	Dollar sign connects the WINDOW or REPORT label to a field equate label in a control's property assignment expression.

**Operators:**

+	Plus sign indicates addition.
-	Minus sign indicates subtraction.
*	Asterisk indicates multiplication.
/	Slash indicates division.
%	Percent sign indicates modulus division.
^	Carat indicates exponentiation.
<	Left angle bracket indicates less than.
>	Right angle bracket indicates greater than.
=	Equal sign indicates assignment or equivalence.
~	Tilde indicates the logical (Boolean) NOT operator.
&	Ampersand indicates concatenation.
&=	Ampersand equal indicates reference assignment or reference equivalence.
:=:	Executes a Deep Assignment statement.



## Program Format

### PROGRAM (declare a program)

**PROGRAM**

**MAP**

*Prototypes*

**. [MODULE( )**

*Prototypes*

**END ]**

**END**


*global data*

**CODE**

*Statements*

**[RETURN]**

*Procedures*



In Clarion#, you can add a default access modifier to the PROGRAM statement:

**PROGRAM[, PUBLIC|,INTERNAL]**

All declarations without explicit access modifier will have the default access modifier. The default for PROGRAM is PUBLIC.

---

**PROGRAM** The first declaration in a Clarion program source module. Required.

**MAP** Global procedure declarations. Required.

**MODULE** Declare member source modules.

*prototypes* PROCEDURE declarations.

*global data* Declare Global data which may be referenced by all procedures.

**CODE** Terminate the data declaration section and begin the executable code section of the PROGRAM.

*statements* Executable program instructions.

**RETURN** Terminate program execution. Return to operating system **control**.

*procedures* Source code for the procedures in the PROGRAM module.

The **PROGRAM** statement is required to be the first declaration in a Clarion program source module. It may only be preceded by source code comments. The PROGRAM source file name is used as the object (.OBJ) and executable (.EXE) file name, when compiled. The PROGRAM statement may have a label, but the label is ignored by the compiler.

A PROGRAM with PROCEDURES must have a MAP structure. The MAP declares the PROCEDURE prototypes. Any PROCEDURE contained in a separate source file must be declared in a MODULE structure within the MAP.

Data declared in the PROGRAM module, between the keywords PROGRAM and CODE, is Global data that may be accessed by any PROCEDURE in the PROGRAM. Its memory allocation is Static.

**Example:**

```

PROGRAM                                !Sample program declaration
INCLUDE('EQUATES.CLW') !Include standard equates
MAP
CalcTemp    PROCEDURE    !Procedure Prototype
END
CODE
CalcTemp                                !Call procedure

CalcTemp    PROCEDURE
Fahrenheit    REAL(0)    !Global data declarations
Centigrade    REAL(0)
Window WINDOW('Temperature Conversion'),CENTER,SYSTEM
    STRING('Enter Fahrenheit Temperature: '),AT(34,50,101,10)
    ENTRY(@N-04),AT(138,49,60,12),USE(Fahrenheit)
    STRING('Centigrade Temperature: '),AT(34,71,80,10),LEFT
    ENTRY(@N-04),AT(138,70,60,12),USE(Centigrade),SKIP
    BUTTON('Another'),AT(34,92,32,16),USE(?Another)
    BUTTON('Exit'),AT(138,92,32,16),USE(?Exit)
END

CODE                                !Begin executable code section
OPEN(Window)
ACCEPT
CASE ACCEPTED()
OF ?Fahrenheit
    Centigrade = (Fahrenheit - 32) / 1.8
    DISPLAY(?Centigrade)
OF ?Another
    Fahrenheit = 0
    Centigrade = 0
    DISPLAY
    SELECT(?Fahrenheit)
OF ?Exit
    BREAK
END
END
CLOSE(Window)
RETURN

```

**See Also:**

MAP

MODULE

PROCEDURE

PUBLIC

INTERNAL

Data Declarations and Memory Allocation

## MEMBER (identify member source file)

**MEMBER**( [ *program* ] )

[**MAP**

*Prototypes*

**END** ]

[*label*]      *local data*

*procedures*



In Clarion#, you can add a default access modifier to the PROGRAM statement:

**MEMBER**[, **PUBLIC**|, **INTERNAL**]

All declarations without an explicit access modifier will have the default access modifier. The default for MEMBER is INTERNAL.

---

**MEMBER**      The first statement in a source module that is not a PROGRAM source file. Required.

*program*      A string constant containing the filename (without extension) of a PROGRAM source file. If omitted, the module is a "universal member module" that you can compile in any program by adding it to the project.

**MAP**      Local procedure declarations. Any procedures declared here may be referenced by the procedures in the MEMBER module.

*prototypes*      PROCEDURE declarations.

*local data*      Declare Local Static data which may be referenced only by the procedures whose source code is in the MEMBER module.

*procedures*      Source code for the procedures in the MEMBER module.

**MEMBER** is the first statement in a source module that is not a PROGRAM source file. It may only be preceded by source code comments. It is required at the beginning of any source file that contains PROCEDURES that are used by a PROGRAM. The MEMBER statement identifies the *program* to which the source MODULE belongs.

A MEMBER module may have a local MAP structure (which may contain MODULE structures). The procedures *prototyped* in this MAP are available for use by the other procedures in the

MEMBER module. The source code for the procedures declared in this MEMBER MAP may either be contained in the MEMBER source file, or another file (if *prototyped* in a MODULE structure within the MAP).

If the *program* parameter is omitted from the MEMBER statement, you must have a MAP structure that *prototypes* the procedures it contains. You also need to INCLUDE any standard EQUATEs files that are used in your source code.

If the source code for a PROCEDURE *prototyped* in a MEMBER module's MAP is in a separate file, the *prototype* must be in a MODULE structure within the MAP. The source file MEMBER module containing the PROCEDURE definition must also contain its own MAP which declares the same *prototype* (that is, the *prototype* must appear in at least two MAP structures--the source module containing it and the source module using it). Any PROCEDURE not declared in the Global (PROGRAM) MAP must be declared in a local MAP(s) in the MEMBER MODULE which contains its source code.

Data declared in the MEMBER module, after the keyword MEMBER and before the first PROCEDURE statement, is Member Local data that may only be accessed by PROCEDURES within the module (unless passed as a parameter). Its memory allocation is Static.

**Example:**

```
!Source1 module contains:
  MEMBER('OrderSys')           !Module belongs to the OrderSys program

  MAP                          !Declare local procedures
  Func1 PROCEDURE (STRING),STRING !Func1 is known only in both module
    MODULE('Source2.clw')
  HistOrd2 PROCEDURE           !HistOrd2 is known only in both modules
  END
  END

  LocalData STRING(10)         !Declare data local to MEMBER module

  HistOrd PROCEDURE            !Declare order history procedure
  HistData STRING(10)         !Declare data local to PROCEDURE
  CODE
  LocalData = Func1(HistData)

  Func1 PROCEDURE (RecField)   !Declare local procedure
  CODE
  !Executable code statements

!Source2 module contains:
  MEMBER('OrderSys')           !Module belongs to the OrderSys program
  MAP                          !Declare local procedures
  HistOrd2 PROCEDURE           !HistOrd2 is known only in both modules
  MODULE('Source1.clw')
  Func1 PROCEDURE (STRING),STRING !Func1 is known only in both module
  END
  END

  LocalData STRING(10)         !Declare data local to MEMBER module

  HistOrd2 PROCEDURE           !Declare second order history procedure
  CODE
  LocalData = Func1(LocalData)
```

**See Also:** MAP, MODULE, PROCEDURE, CLASS, PUBLIC, INTERNAL

## MAP (declare PROCEDURE prototypes)

**MAP**

*prototypes*

[**MODULE**( )

*prototypes*

**END ]**

**END**

---

**MAP** Contains the *prototypes* which declare the procedures and external source modules used in a PROGRAM, MEMBER module, or PROCEDURE.

*prototypes* Declare PROCEDURES.

**MODULE** Declare a member source module that contains the definitions of the *prototypes* in the MODULE.

A **MAP** structure contains the *prototypes* which declare the PROCEDURES and external source modules used in a PROGRAM, MEMBER module, or PROCEDURE which are not members of a CLASS structure.

A MAP declared in the PROGRAM source module declares *prototypes* of PROCEDURES available for use throughout the program. A MAP in a MEMBER module declares *prototypes* of PROCEDURES that are explicitly available in that MEMBER module. The same *prototypes* may be placed in multiple MEMBER modules to make them explicitly available in each. A MAP can also be included within a PROCEDURE declaration. All prototypes of PROCEDURES declared in a local PROCEDURE MAP may only be referenced within the PROCEDURE itself.

A MAP structure is mandatory for any non-trivial Clarion program because the BUILTINS.CLW file is automatically included in your PROGRAM's MAP structure by the compiler. This file contains prototypes of most of the procedures in the Clarion internal library that are available as part of the Clarion language. This file is required because the compiler does not have these prototypes built into it (making it more efficient). Since the prototypes in the BUILTINS.CLW file use some constant EQUATES that are defined in the EQUATES.CLW file, this file is also automatically included by the compiler in every Clarion program.

### Example:

!One file contains:

```
PROGRAM          !Sample program in sample.cla
MAP              !Begin map declaration
LoadIt PROCEDURE !LoadIt procedure
END              !End of map
```

!A separate file contains:

```
MEMBER('Sample') !Declare MEMBER module
MAP              !Begin MODULE local map declaration
ComputeIt PROCEDURE ! compute it procedure
END              !End of map
```

```
ComputeIt PROCEDURE
```

```
LOC:Var LONG
```

```
MAP                                ! PROCEDURE local map
```

```
    Proc1
```

```
END
```

```
CODE
```

```
Proc1()
```

```
RETURN
```

```
Proc1 Procedure
```

```
CODE
```

```
LOC:Var += 1
```

```
RETURN
```

**See Also:**

PROGRAM

MEMBER

MODULE

PROCEDURE

PROCEDURE Prototypes

## MODULE (specify MEMBER source file)

**MODULE**(*sourcefile*)

*prototype*

**END**

---

**MODULE** Names a MEMBER module or external library file.

*sourcefile* A string constant which contains the filename (without extension) of the Clarion language source code file containing the definitions of the PROCEDURES. If the *sourcefile* is an external library, this string may contain any unique identifier.

*prototype* The prototype of a PROCEDURE whose definition is contained in the *sourcefile*.

A **MODULE** structure names a Clarion language MEMBER module or an external library file and contains the *prototypes* for the PROCEDURES contained in the *sourcefile*. A MODULE structure can only be declared within a MAP structure and is valid for use in any MAP structure, whether that MAP is in a PROGRAM module or MEMBER module.

**Example:**

```
!The "sample.clw" file contains:
PROGRAM                !Sample program in sample.clw
MAP                    !Begin map declaration
  MODULE('Loadit')      ! source module loadit.clw
LoadIt PROCEDURE        ! LoadIt procedure
  END                  ! end module
  MODULE('Compute')     ! source module compute.clw
ComputeIt PROCEDURE     ! compute it procedure
  END                  ! end module
END                    !End map

!The "loadit.clw" file contains:
MEMBER('Sample')       !Declare MEMBER module
MAP                    !Begin local map declaration
  MODULE('Process')     ! source module process.cla
ProcessIt PROCEDURE     ! process it procedure
  END                  ! end module
END                    !End map
```

**See Also:**

MEMBER

MAP

PROCEDURE Prototypes



## PROCEDURE (define a procedure)

*label*      **PROCEDURE** [ ( *parameter list* ) ]

*local data*

**CODE**

*statements*

[**RETURN**( [ *value* ] ) ]

---

**PROCEDURE**      Begins a section of source code that can be executed from within a PROGRAM.

*label*              Names the PROCEDURE. For a CLASS method's definition, this may contain the label of the CLASS prepended to the label of the PROCEDURE.

*parameter list*      A comma delimited list of names (and, optionally, their data types) of the parameters passed to the PROCEDURE. These names define the local references within the PROCEDURE to the passed parameters. For a CLASS method's definition, this may contain the label of the CLASS (named SELF) as an implicit first parameter (if the class is not prepended to the PROCEDURE's *label*), and must always contain both the data type and parameter name.

*local data*              Declare Local data visible only in this procedure.

**CODE**              Terminate the data declaration section and begin the executable code section of the PROCEDURE.

*statements*              Executable program instructions.

**RETURN**              Terminate procedure execution. Return to the point from which the procedure was called and return the *value* to the expression in which the procedure was used (if the procedure has been prototyped to return a value).

*value*              A numeric or string constant or variable which specifies the result of the procedure call.

**PROCEDURE** begins a section of source code that can be executed from within a PROGRAM. It is called by naming the PROCEDURE *label* (with its *parameter list*, if any) as an executable statement in the code section of a PROGRAM or PROCEDURE.

The *parameter list* defines the data type of each parameter (optional) followed by the label of the parameter as used within the PROCEDURE's source code (required). Each parameter is separated by a comma. The data type of each parameter (including the angle brackets if the parameter is omissible) is required along with the parameter's label if the procedure is overloaded (has multiple definitions). The *parameter list* may be exactly the same as it appears in the PROCEDURE's prototype, if that prototype contains labels for the parameters.

A PROCEDURE may contain one or more ROUTINES in its executable code *statements*. A ROUTINE is a section of executable code local to the PROCEDURE which is called with the DO statement.

A PROCEDURE terminates and returns to its caller when a RETURN statement executes. An implicit RETURN occurs at the end of the executable code. The end of executable code for the PROCEDURE is defined as the end of the source file, or the first encounter of a ROUTINE or another PROCEDURE.

A RETURN statement is required if the PROCEDURE has been prototyped to return a *value*. A PROCEDURE which has been prototyped to return a *value* can be used as an expression component, or passed as a parameter to another PROCEDURE. A PROCEDURE which has been prototyped to return a *value* may also be called in the same manner as a PROCEDURE without a RETURN *value*, if the program logic does not require the RETURN *value*. In this case, if the PROCEDURE prototype does not have the PROC attribute, the compiler will generate a warning which may be safely ignored.

Data declared within a PROCEDURE, between the keywords PROCEDURE and CODE, is Procedure Local data that can only be accessed by that PROCEDURE (unless passed as a parameter to another PROCEDURE). This data is allocated memory upon entering the procedure, and de-allocated when it terminates. If the data is smaller than the stack threshold (5K is the default) it is placed on the stack, otherwise it is allocated from the heap.

A PROCEDURE must have a prototype declared in a CLASS or the MAP of a PROGRAM or MEMBER module. If declared in the PROGRAM MAP, it is available to any other procedure in the program. If declared in a MEMBER MAP, it is available to other procedures in that MEMBER module.

**Example:**

```
PROGRAM                                !Example program code
MAP
OpenFile  PROCEDURE(FILE AnyFile) !Procedure prototype with parameter
ShoTime   PROCEDURE               !Procedure prototype without parameter
DayString PROCEDURE,STRING        !Procedure prototype with a return value
END

FileOne FILE,DRIVER('Clarion')      !Declare a file
      RECORD                        !begin record declaration
Name    STRING(20)
Number  LONG
      END                          ! end record declaration
      END                          !End file declaration

TodayString STRING(9)
CODE
TodayString = DayString()           !Procedure called with a return value
OpenFile(FileOne)                   !Call procedure to open file
ShoTime                               !Call ShoTime procedure
      !More executable statements

OpenFile PROCEDURE(FILE AnyFile) !Open any file
CODE                                     !Begin code section
OPEN(AnyFile)                         !Open the file
IF ERRORCODE() = 2                    !If file not found
      CREATE(AnyFile)                 !create it
END
RETURN                                !Return to caller
```

```

ShoTime PROCEDURE                                !Show time
Time LONG                                           !Local variable
Window WINDOW,CENTER
    STRING(@T3),USE(Time),AT(34,70)
    BUTTON('Exit'),AT(138,92),USE(?Exit)
END
CODE                                                !Begin executable code section
Time = CLOCK()                                     !Get time from system
OPEN(Window)
ACCEPT
CASE ACCEPTED()
OF ?Exit
BREAK
END
END
RETURN                                              !Return to caller

DayString PROCEDURE                                !Day string procedure
ReturnString STRING(9),AUTO                        !Uninitialized local stack variable
CODE                                                !Begin executable code section
EXECUTE (TODAY() % 7) + 1                          !Find day of week from system date
ReturnString = 'Sunday'
ReturnString = 'Monday'
ReturnString = 'Tuesday'
ReturnString = 'Wednesday'
ReturnString = 'Thursday'
ReturnString = 'Friday'
ReturnString = 'Saturday'
END
RETURN(ReturnString)                              !Return the resulting string

```

**See Also:**

PROCEDURE Prototypes

Data Declarations and Memory Allocation

Procedure Overloading

CLASS

ROUTINE

MAP

## CODE (begin executable statements)

### CODE

The **CODE** statement separates the data declaration section from the executable statement section within a PROGRAM, PROCEDURE, or ROUTINE. The first statement executed in a PROGRAM, PROCEDURE, or ROUTINE is the statement following CODE. The word "Code" is a reserved word, and may not be used as a label of a variable or procedure.

#### Example:

```
PROGRAM

!Global Data declarations go here

CODE
!Executable statements go here

OrdList PROCEDURE !Declare a procedure

!Local Data declarations go here

CODE                !This is the beginning of the "code" section
!Executable statements go here
```

#### See Also:

PROGRAM

PROCEDURE

## DATA (begin routine local data section)

### DATA

The **DATA** statement begins a local data declaration section in a ROUTINE. Any ROUTINE containing a DATA section must also contain a CODE statement to terminate the data declaration section. Variables declared in a ROUTINE data section may not have the STATIC or THREAD attributes.

#### Example:

```
SomeProc PROCEDURE
  CODE
  !Code statements
  DO Tally                !Call the routine
  !More code statements

Tally ROUTINE            !Begin routine, end procedure
  DATA
  CountVar BYTE          !Declare local variable
  CODE
  CountVar += 1          ! increment counter
  DO CountItAgain        !Call another routine
  EXIT                  !and exit the routine
```

#### See Also:

CODE

ROUTINE

## ROUTINE (declare local subroutine)

```
label      ROUTINE  
  
            [ DATA  
  
              local data  
  
            CODE ]  
  
            statements
```

---

**ROUTINE** Declares the beginning of a local subroutine.

*label* The name of the ROUTINE. This may not duplicate the label of any PROCEDURE.

**DATA** Begin data declaration statements.

*local data* Declare Local data visible only in this routine.

**CODE** Begin executable statements.

*statements* Executable program instructions.

### Remarks:

**ROUTINE** declares the beginning of a local subroutine. It is local to the PROCEDURE in which it is written and must be at the end of the CODE section of the PROCEDURE to which it belongs. All variables visible to the PROCEDURE are available in the ROUTINE. This includes all Procedure Local, Module Local, and Global data.

### Clarion#

In Clarion#, the DATA and CODE keywords are required.

A ROUTINE may contain its own local data which is limited in scope to the ROUTINE in which it is declared. If local data declarations are included in the ROUTINE, they must be preceded by a DATA statement and followed by a CODE statement. Since the ROUTINE has its own name scope, the labels of these variables may duplicate variable names used in other ROUTINES or even the procedure containing the ROUTINE.

A ROUTINE is called by the DO statement followed by the label of the ROUTINE. Program control following execution of a ROUTINE is returned to the statement following the calling DO statement. A ROUTINE is terminated by the end of the source module, or by another ROUTINE or PROCEDURE. The EXIT statement can also be used to terminate execution of a ROUTINE's code (similar to RETURN in a PROCEDURE).

A ROUTINE has some efficiency issues that are not obvious:

- DO and EXIT statements are very efficient.
- Accessing procedure-level local data is less efficient than accessing module-level or global data.
- Implicit variables used only within the ROUTINE are less efficient than using local variables.
- Each RETURN statement within a ROUTINE incurs a 40-byte overhead.

**Example:**

```
SomeProc PROCEDURE
CODE
!Code statements
DO Tally                !Call the routine
!More code statements

Tally ROUTINE           !Begin routine, end procedure
DATA
CountVar BYTE           !Declare local variable
CODE
CountVar += 1           ! increment counter
DO CountItAgain         !Call another routine
EXIT                   !and exit the routine
```

**See Also:**

PROCEDURE

EXIT

DO

DATA

CODE

## END (terminate a structure)

### END

**END** terminates a data declaration structure or a compound executable statement. It is functionally equivalent to a period (.).

By convention, the END statement is aligned in the same column as the beginning of the structure it terminates, and the code within the structure is indented for readability. END is usually used to terminate multi-line structures, while the period is used to terminate single-line statements. If multiple complex code structures are nested and they all terminate at the same place, multiple periods on one line are used instead of the END statements on multiple lines.

#### Example:

```
Customer FILE,DRIVER('Clarion')  !Declare a file
      RECORD                      !begin record declaration
Name      STRING(20)
Number    LONG
      END                        !end record declaration
      END                        !End file declaration

Archive FILE,DRIVER('Clarion')  !Declare a file
      RECORD                      !begin record declaration
Name      STRING(20)
Number    LONG
      END
      END                        !end both the record and file declarations

CODE

IF Number <> SavNumber            !Begin if structure
  DO GetNumber
END                                !End if structure

IF SomeCondition THEN BREAK END  !Terminate with END

CASE Action                      !Begin case structure
OF 1
  DO AddRec
  IF Number <> SavNumber            !Begin if structure
    DO SomeRoutine
  END                            !End if structure
OF 2
  DO ChgRec
OF 3
  DO DelRec
END                                !End case structure
```



## Statement Execution Sequence

In the CODE section of a Clarion program, statements are normally executed line-by-line, in the sequence in which they appear in the source module. Control statements and procedure calls are used to modify this execution sequence.

PROCEDURE calls modify the execution sequence by branching to the called procedure and executing the code contained in it. Control returns to the executable statement following the procedure call when a RETURN statement is executed in the called procedure, or there are no more statements in the called procedure to execute, returning the value (if the PROCEDURE returns a value).

Control structures--IF, CASE, LOOP, ACCEPT, and EXECUTE--change the execution sequence by evaluating expressions. The control structure conditionally executes statements contained within the structure based on the evaluation of the expression(s) in the structure. ACCEPT is also a loop-type of structure, but does not evaluate any expression.

Branching also occurs with the GOTO, DO, CYCLE, BREAK, EXIT, and RETURN statements. These statements immediately and unconditionally alter the normal execution sequence.

The START procedure begins a new execution thread, unconditionally branching to that thread at the next instance of ACCEPT following the START. However, the user may choose to activate another thread by clicking the mouse on the other thread's active window.

### Example:

```
PROGRAM

MAP
ComputeTime PROCEDURE(*GROUP) !Passing a group parameter
MatchMaster PROCEDURE         !Passing no parameters
END

ParmGroup GROUP                !Declare a group
FieldOne  STRING(10)
FieldTwo  LONG
END

CODE                            !Begin executable code
FieldTwo = CLOCK()              !Executes 1st
ComputeTime(ParmGroup)          !Executes 2nd, passes control to procedure
MatchMaster                     !Executes after procedure executes fully
```

## PROCEDURE Calls

*procname*[(*parameters*)]

*return* = *funcname*[(*parameters*)]

---

*procname*     The name of the PROCEDURE as declared in the procedure's prototype.

*parameters*     An optional parameter list passed to the PROCEDURE. A parameter list may be one or more variable labels or expressions. The *parameters* are delimited by commas and are declared in the prototype.

*return*         The label of a variable to receive the value returned by the PROCEDURE.

*funcname*       The name of a PROCEDURE which returns a value, as declared in the procedure's prototype.

A PROCEDURE is called by its label (including any parameter list) as a statement in the CODE section of a PROGRAM or PROCEDURE. The parameter list must match the parameter list declared in the procedure's prototype. Procedures cannot be called in expressions.

A PROCEDURE which returns a value is called by its label (including any parameter list) as a component of an expression or parameter list passed to another PROCEDURE. The parameter list must match the parameter list declared in the procedure's prototype. A PROCEDURE which returns a value may also be called by its label (including any parameter list), in the same manner as a PROCEDURE which doesn't return a value, if its return value is not needed. This will generate a compiler warning that can be safely ignored (unless the PROC attribute is placed on its prototype).

If the PROCEDURE is a method of a CLASS, the *procname* must begin with the label of an object instance of the CLASS followed by a period then the label of the PROCEDURE (*objectname.procname*).

### Example:

```
PROGRAM
MAP
ComputeTime PROCEDURE(*GROUP)           !Passing a group parameter
!PROCEDURE returning a value and passing no parameters:
MatchMaster PROCEDURE,BYTE,PROC
END
ParmGroup GROUP                          !Declare a group
FieldOne  STRING(10)
FieldTwo  LONG
END
CODE
FieldTwo = CLOCK()                       !Built-in procedure called as expression
ComputeTime(ParmGroup)                   !Call the compute time procedure
MatchMaster()                            !Call the procedure as a procedure
```

### See Also:

PROCEDURE

## PROCEDURE Prototypes-Prototype Syntax

*name*    **PROCEDURE** [(*parameter list*)] [,*return type*] [,*calling convention*] [,**RAW**] [,**NAME**( )] [,**TYPE**] [,**DLL**( )] [,**PROC**] [,**PRIVATE**] [,**VIRTUAL**] [,**PROTECTED**] [,**REPLACE**] [,**DERIVED**]

*name*[(*parameter list*)] [,*return type*] [,*calling convention*] [,**RAW**] [,**NAME**( )] [,**TYPE**] [,**DLL**( )] [, **PROC**] [, **PRIVATE**]

---

<i>name</i>	The label of a PROCEDURE statement that defines the executable code.
<b>PROCEDURE</b>	Required keyword.
<i>parameter list</i>	The data types of the parameters. Each parameter's data type may be followed by a label used to document the parameter (only). Each numeric value parameter may also include an assignment of the default value (a constant) to pass if the parameter is omitted.
<i>return type</i>	The data type the PROCEDURE will RETURN.
<i>calling convention</i>	Specify the C or PASCAL stack-based parameter calling convention.
<b>RAW</b>	Specifies that STRING or GROUP parameters pass only the memory address (without passing the length of the passed string). It also alters the behaviour of ? and *? parameters. This attribute is only for 3GL language compatibility and is not valid on a Clarion language procedure.
<b>NAME</b>	Specify an alternate, "external" name for the PROCEDURE.
<b>TYPE</b>	Specify the prototype is a type definition for procedures passed as parameters.
<b>DLL</b>	Specify the PROCEDURE is in an external .DLL.
<b>PROC</b>	Specify the PROCEDURE with a <i>return type</i> may be called as a PROCEDURE without a <i>return type</i> without generating a compiler warning.
<b>PRIVATE</b>	Specify the PROCEDURE may be called only from another PROCEDURE within the same MODULE (usually used in a CLASS).
<b>VIRTUAL</b>	Specify the PROCEDURE is a virtual method of a CLASS structure.
<b>PROTECTED</b>	Specify the PROCEDURE may be called only from another PROCEDURE within the same CLASS or any directly derived CLASS.
<b>REPLACE</b>	Specify the "Construct" or "Destruct" PROCEDURE in the derived CLASS completely replaces the constructor or destructor of its parent CLASS.
<b>DERIVED</b>	Specify the PROCEDURE is a derived method of a CLASS structure, There must be a matching prototype in the parent class.

All PROCEDURES in a PROGRAM must have a prototype declaration in a MAP or CLASS structure. A prototype declares to the compiler exactly what form to expect to see when the PROCEDURE is used in executable code.

There are two valid forms of prototype declarations listed in the syntax diagram on the previous page. The first one, using the PROCEDURE keyword, is valid for use everywhere and is the preferred form to use. The second form is supported only for backward compatibility with previous versions of Clarion.

A prototype contains:

- The *name* of the PROCEDURE.
- The keyword PROCEDURE is optional in a MAP structure, but required in a CLASS structure.
- An optional *parameter list* specifying all parameters that will be passed in.
- The data *return type*, if the prototype is for a PROCEDURE which will return a value.
- The parameter *calling convention*, if you are linking in objects that require stack-based parameter passing (such as objects that were not compiled with a Clarion TopSpeed compiler).
- The RAW, NAME, TYPE, DLL, PROC, PRIVATE, VIRTUAL, PROTECTED, and DERIVED attributes, as needed.

You can optionally specify the C (right to left) or PASCAL (left to right and compatible with Windows 32-bit) stack-based parameter *calling convention* for your PROCEDURE. This provides compatibility with third-party libraries written in other languages (if they were not compiled with a TopSpeed compiler). If you do not specify a *calling convention*, the default is the internal, register-based parameter passing convention used by all the TopSpeed compilers.

The RAW attribute allows you to pass just the memory address of a *\*?*, STRING, or GROUP parameter (whether passed by value or by reference) to a non-Clarion language procedure or function. Normally, STRING or GROUP parameters pass both the address and the length of the string. The RAW attribute eliminates the length portion. This is provided for compatibility with external library functions which expect only the address of the string.

The NAME attribute provides the linker an external name for the PROCEDURE. This is also provided for compatibility with libraries written in other languages. For example: in some C language compilers, with the C calling convention specified, the compiler adds a leading underscore to the function name. The NAME attribute allows the linker to resolve the name of the function correctly.

The TYPE attribute indicates the prototype does not reference a specific PROCEDURE. Instead, it defines a prototype *name* used in other prototypes to indicate the type of procedure passed to another PROCEDURE as a parameter.

The DLL attribute specifies that the PROCEDURE prototype on which it is placed is in a .DLL. The DLL attribute is required for 32-bit applications because .DLLs are relocatable in a 32-bit flat address space, which requires one extra dereference by the compiler to address the procedure.

The PRIVATE attribute specifies that only another PROCEDURE that is in the same MODULE may call it. This would most commonly be used on a prototype in a module's MAP structure, but may also be used in the global MAP.

When the *name* of a prototype is used in the *parameter list* of another prototype, it indicates the procedure being prototyped will receive the label of a PROCEDURE that receives the same *parameter list* (and has the same *return type*, if it returns a value). A prototype with the TYPE attribute may not also have the NAME attribute.

**Example:**

```

MAP
  MODULE('Test')
    MyProc1 PROCEDURE (LONG)
    MyProc2 PROCEDURE (<*LONG>)
    MyProc3 PROCEDURE (LONG=23)
  END
  MODULE('Party3.Obj')
    Func46 PROCEDURE (*CSTRING), REAL, C, RAW
    Func47 PROCEDURE (*CSTRING), *CSTRING, C, RAW
    Func48 PROCEDURE (REAL), REAL, PASCAL
    Func49 PROCEDURE (SREAL), REAL, C, NAME('_func49')
  END
  MODULE('STDFuncs.DLL')
    Func50 PROCEDURE (SREAL), REAL, PASCAL, DLL(dll_mode)
  END
END

```

!'test.clw' contains these procedures  
 !LONG value-parameter  
 !Omittable LONG variable-parameter  
 !Passes 23 if omitted  
 !A third-party library  
 !Pass CSTRING address-only to C function  
 !Returns pointer to a CSTRING  
 !PASCAL calling convention  
 !C convention and external function name  
 !A standard functions .DLL

**See Also:**

MAP

MEMBER

MODULE

NAME

PROCEDURE

RETURN

Prototype Parameter Lists


Procedure Overloading

CLASS

## Prototype Parameter Lists

### General Syntax

[CONST] [REF] *type* [ *label* ]  
<[CONST] [REF] *type* [ *label* ] >  
*type* [ *label* ] = *default*

<b>CONST</b>	An optional qualifier for the parameter which is valid only on a variable-parameter. This means that the parameter being passed by address may not be updated in the procedure. It is treated as if it were a constant value.
<b>REF</b> 	The <b>REF</b> keyword is added to Clarion# to provide compatibility with other .NET languages. It's used to mark a parameter as "passed by reference". The REF keyword can be used before the type name in the parameter declaration.
<i>type</i>	The data type of the parameter. This may be a value-parameter, variable-parameter, array, unspecified data type, entity, procedure-parameter, or a named GROUP, QUEUE, or CLASS.
<i>label</i>	An optional documentary label for the parameter. This label is not required and is placed in the prototype for documentation purposes only.
< >	Angle brackets indicate the parameter is omissible. The OMITTED procedure detects the omission. All parameter <i>types</i> can be omitted.
= <i>default</i>	A <i>default</i> value indicates the numeric parameter is omissible, and if omitted, the <i>default</i> value is passed. The OMITTED procedure will not detect the omission--a value is passed. Valid only on simple numeric <i>types</i> .

The *parameter list* in a PROCEDURE prototype is a comma-delimited list of the data *types* to pass to the PROCEDURE. The entire *parameter list* is enclosed in the parentheses following the PROCEDURE keyword (or the *name*). Each parameter's *type* may be followed by a space then a valid Clarion *label* for the parameter (which is ignored by the compiler and only documents the purpose of the parameter). Each numeric value-parameter (passed by value) may also include an assignment of a constant value to the *type* (or the documentary *label*, if present) that defines the default value to pass if the parameter is omitted.

Any parameter that may be omitted when the PROCEDURE is called must be included in the prototype's *parameter list* and enclosed in angle brackets ( < > ) unless a *default* value is defined for the parameter. The OMITTED procedure allows you to test for unpassed parameters at runtime (except those parameters which have a *default* value).

**Example:**

```

MAP
  MODULE('Test')
MyProc1 PROCEDURE(LONG)                !LONG value-parameter
MyProc2 PROCEDURE(<LONG>)                !Omittable LONG value-parameter
MyProc3 PROCEDURE(LONG=23)              !Passes 23 if omitted
MyProc4 PROCEDURE(LONG Count, REAL Sum) !LONG passing a Count and REAL passing a Sum
MyProc5 PROCEDURE(LONG Count=1, REAL Sum=0) !Count defaults to 1 and Sum to 0
  END
END

```

**See Also:**

MAP

MEMBER

MODULE

PROCEDURE

CLASS

REF

**Value-parameters**

Value-parameters are "passed by value." A copy of the variable passed in the parameter list of the "calling" PROCEDURE is used in the "called" PROCEDURE. The "called" PROCEDURE cannot change the value of the variable passed to it by the "caller." Simple assignment data conversion rules apply; Value-parameters actually passed are converted to the data type in the PROCEDURE prototype. Valid value-parameters are:

BYTE    SHORT    USHORT    LONG    ULONG    SREAL    REAL    DATE    TIME    STRING

**Example:**

```

MAP
  MODULE('Test')
MyProc1 PROCEDURE(LONG)                !LONG value-parameter
MyProc2 PROCEDURE(<LONG>)                !Omittable LONG value-parameter
MyProc3 PROCEDURE(LONG=23)              !Passes 23 if omitted
MyProc4 PROCEDURE(LONG Count, REAL Sum) !LONG passing a Count and REAL passing a Sum
MyProc5 PROCEDURE(LONG Count=1, REAL Sum=0) !Count defaults to 1 and Sum to 0
  END
  MODULE('Party3.Obj')
Func48 PROCEDURE(REAL),REAL,PASCAL      !PASCAL calling convention
Func49 PROCEDURE(SREAL),REAL,C,NAME('_func49') !C convention and external function name
  END
END

```

## Variable-parameters

---

**Variable-parameters** are "passed by address." A variable passed by address has only one memory address. Changing the value of the variable in the "called" PROCEDURE also changes its value in the "caller." Variable-parameters are listed by data type with a leading asterisk (\*) in the PROCEDURE prototype in the MAP. Valid variable-parameters are:

*BYTE	*SHORT	*USHORT	*LONG	*ULONG	*SREAL	*REAL	*BFLOAT4	*BFLOAT8
*DECIMAL	*PDECIMAL	*DATE	*TIME	*STRING	*PSTRING	*CSTRING	*GROUP	

### Example:

```
MAP
  MODULE ('Test')
MyProc2 PROCEDURE (<*LONG>)                !Omittable LONG variable-parameter
MyFunc1 PROCEDURE (*SREAL),REAL,C          !SREAL variable-parameter, REAL return, C call conv
MyProc6 PROCEDURE (CONST *CSTRING Value)    !Value retains a constant value in procedure
  END
  MODULE ('Party3.Obj')
Func4  PROCEDURE (*CSTRING),REAL,C,RAW      !Pass CSTRING address-only to C function
Func47 PROCEDURE (*CSTRING),CSTRING,C,RAW   !Returns pointer to a CSTRING
  END
END
```

## Passing Arrays

---

To pass an entire array as a parameter, the prototype must declare the array's data type as a Variable-parameter ("passed by address") with an empty subscript list. If the array has more than one dimension, commas (as position holders) must indicate the number of dimensions in the array. The calling statement must pass the entire array to the PROCEDURE, not just one element.

### Example:

```
MAP
MainProc PROCEDURE
AddCount PROCEDURE (*LONG[, ] Total,*LONG[, ] Current) !Passing two 2-dimensional arrays
  END
  CODE
  MainProc                                           !Call first procedure
MainProc PROCEDURE
TotalCount LONG,DIM(10,10)
CurrentCnt LONG,DIM(10,10)
  CODE
  AddCount(TotalCount,CurrentCnt)                   !Call the procedure passing the arrays
AddCount PROCEDURE (*LONG[, ] Total,*LONG[, ] Current) !Procedure expects two arrays
  CODE
  LOOP I# = 1 TO MAXIMUM(Total,1)                    !Loop through first subscript
    LOOP J# = 1 TO MAXIMUM(Total,2)                  !Loop through second subscript
      Total[I#,J#] += Current[I#,J#]                !increment TotalCount from CurrentCnt
    END
  END
  CLEAR(Current)                                     !Clear CurrentCnt array
```



## Parameters of Unspecified Data Type

You can write general purpose procedures which perform operations on passed parameters where the exact data type of the parameter may vary from one call to the next by using **untyped value-parameters** and **untyped variable-parameters**. These are polymorphic parameters; they may become any other simple data type depending upon the data type passed to the procedure.

**Untyped value-parameters** are represented in the prototype with a question mark (?). When the procedure executes, the parameter is dynamically typed and acts as a data object of the base type (LONG, DECIMAL, STRING, or REAL) of the passed variable, or the base type of whatever it was last assigned. This means that the "assumed" data type of the parameter can change within the PROCEDURE, allowing it to be treated as any data type.

An untyped value-parameter is "passed by value" to the PROCEDURE and its assumed data type is handled by Clarion's automatic Data Conversion Rules. Data types which may be passed as untyped value-parameters:

BYTE	SHORT	USHORT	LONG	ULONG	SREAL
REAL	BFLOAT4	BFLOAT8	DECIMAL	PDECIMAL	DATE
TIME	STRING	PSTRING	CSTRING		
GROUP (treated as a STRING)	Untyped value- parameter (?)	Untyped Variable- parameter (*)			

The RAW attribute is valid for use if the untyped value-parameter (?) is being passed to external library functions written in other languages than Clarion. This converts the data to a LONG then passes the data as a C/C++ "void \*" parameter (which eliminates "type inconsistency" warnings).

**Untyped variable-parameters** are represented in the PROCEDURE prototype with an asterisk and a question mark (\*?). Within the procedure, the parameter acts as a data object of the type of the variable passed in at runtime. This means the data type of the parameter is fixed during the execution of the PROCEDURE.

An untyped variable-parameter is "passed by address" to the PROCEDURE. Therefore, any changes made to the passed parameter within the PROCEDURE are made directly to the variable which was passed in. This allows you to write polymorphic procedures.

Within a procedure which receives an untyped variable-parameter, it is not safe to make any assumptions about the data type coming in. The danger of making assumptions is the possibility of assigning an out-of-range value which the variable's actual data type cannot handle. If this happens, the result may be disastrously different from that expected. **See Also:** ANYANY (any simple data type)

Data types which may be passed as untyped variable-parameters:

BYTE	SHORT	USHORT	LONG	ULONG	SREAL	REAL	BFLOAT4
BFLOAT8	DECIMAL	PDECIMAL	DATE	TIME	STRING	PSTRING	CSTRING
Untyped variable- parameter (*)							

The RAW attribute is valid for use if the untyped variable-parameter (\*?) is being passed to external library functions written in other languages than Clarion. This has the same effect as passing a C or C++ "void \*" parameter.

Arrays may not be passed as either kind of untyped parameter.

**Example:**

```
PROGRAM
MAP
Proc1 PROCEDURE(?)           !Untyped value-parameter
Proc2 PROCEDURE(*?)          !Untyped variable-parameter
Proc3 PROCEDURE(*?)          !Untyped variable-parameter (set to crash)
Max  PROCEDURE(?,?,?)       !Procedure returning Untyped value-parameter
END

GlobalVar1 BYTE(3)           !BYTE initialized to 3
GlobalVar2 DECIMAL(8,2,3)
GlobalVar3 DECIMAL(8,1,3)
MaxInteger LONG
MaxString  STRING(255)
MaxFloat   REAL

CODE
Proc1(GlobalVar1)             !Pass in a BYTE, value is 3
Proc2(GlobalVar2)             !Pass it a DECIMAL(8,2), value is 3.00 - it prints 3.33
Proc2(GlobalVar3)             !Pass it a DECIMAL(8,1), value is 3.0 - it prints 3.3
Proc3(GlobalVar1)             !Pass it a BYTE and watch it crash
MaxInteger = Max(1,5)          !Max procedure returns the 5
MaxString = Max('Z','A')      !Max procedure returns the 'Z'
MaxFloat = Max(1.3,1.25)       !Max procedure returns the 1.3

Proc1 PROCEDURE(? ValueParm)
CODE                               !ValueParm starts at 3 and is a LONG
ValueParm = ValueParm & ValueParm !Now Contains '33' and is a STRING
ValueParm = ValueParm / 10         !Now Contains 3.3 and is a REAL

Proc2 PROCEDURE(*? VariableParm)
CODE
VariableParm = 10 / 3             !Assign 3.33333333... to passed variable

Proc3 PROCEDURE(*? VariableParm)
CODE
LOOP
  IF VariableParm >= 256 THEN BREAK. !If passed a BYTE, BREAK will never happen
  VariableParm += 10
END

Max PROCEDURE(Val1,Val2)          !Find the larger of two passed values
CODE
IF Val1 > Val2                    !Check first value against second
  RETURN(Val1)                   ! return first, if largest
ELSE                              !otherwise
  RETURN(Val2)                   ! return the second
END
```

**See Also:**

MAP

MEMBER

MODULE

PROCEDURE

CLASS

## Entity-parameters

**Entity-parameters** pass the name of a data structure to the "called" PROCEDURE. Passing the entity allows the "called" PROCEDURE to use those Clarion commands that require the label of the structure as a parameter. Entity-parameters are listed by entity type in the PROCEDURE prototype in the MAP. Entity-parameters are always "passed by address." Valid entity-parameters are:

**FILE      VIEW      KEY      INDEX      QUEUE      WINDOW      REPORT      BLOB**

A REPORT can be passed as the parameter to a procedure prototyped to receive a WINDOW, since internally they use the same passing structure.

**Example:**

```
MAP
  MODULE('Test')
MyFunc2  PROCEDURE(FILE),STRING      !FILE entity-parameter, returning a STRING
ProcType PROCEDURE(FILE),TYPE        !Procedure-parameter type definition
MyFunc4  PROCEDURE(FILE),STRING,PROC !May be called as a procedure without warnings
MyProc6  PROCEDURE(FILE),PRIVATE     !May only be called by other procs in TEST.CLW
  END
END
```

## Procedure-parameters

**Procedure-parameters** pass the name of another PROCEDURE to the "called" PROCEDURE. Procedure-parameters are listed by the name of a prototype of the same type in the PROCEDURE prototype in the MAP (which may or may not have the TYPE attribute). When called in executable code, the "called" PROCEDURE must be passed the name of a PROCEDURE whose prototype is exactly the same as the procedure named in the "called" procedure's prototype.

Each parameter in the list may be followed by a valid Clarion label which is completely ignored by the compiler. This label is used only to document the parameter to make the prototype more readable, or to duplicate the PROCEDURE definition statement. Each passed parameter's definition may also include the assignment of a constant value to the data type (or the documentary label, if present) that defines the default value to pass if the parameter is omitted.

**Example:**

```
MAP
  MODULE('Test')
ProcType PROCEDURE(FILE),TYPE        !Procedure-parameter type definition
MyFunc3  PROCEDURE(ProcType),STRING !ProcType procedure-parameter, returning a STRING,
  END                                     !must be passed a procedure that takes a FILE
  END                                     !as a parameter
```

## Passing Named GROUPs, QUEUEs, and CLASSes

Passing a GROUP as a Variable-Parameter, or a QUEUE as an Entity-Parameter, to a PROCEDURE does not allow you to reference the component fields within the structure in the receiving PROCEDURE. You can alternatively pass a "named" GROUP or QUEUE to achieve this. You may also name a CLASS in the same manner to allow the receiving procedure to access the public data members and methods of the CLASS.

To reference the component fields within the structure, place the label of a GROUP, QUEUE, or CLASS structure in the receiving PROCEDURE's prototype *parameter list* as the data type for the parameter. This passes the parameter "by address" and allows the receiving procedure to reference the component fields of the structure (and the public methods of a CLASS pass in this manner).

The data actually passed as the parameter must always have a similar structure (defined with the same data types) for its component fields. The GROUP or QUEUE actually passed can be a "superset" of the named parameter, as long as the first fields in the "superset" group are the same as the GROUP or QUEUE named in the prototype. The actually passed CLASS object can also be a derived class of the CLASS named in the prototype. The "extra" fields in the passed GROUP, QUEUE, or CLASS are not available for use in the receiving procedure.

The GROUP, QUEUE, or CLASS named in the *parameter list* does not need to have the TYPE attribute, and does not have to be declared before the procedure's prototype, but it must be declared before the PROCEDURE that will receive the parameter is called. This is the only instance in the Clarion language where the compiler allows such a "forward reference."

Use Field Qualification syntax to reference the members of the passed group in the receiving procedure (LocalName.MemberName). The member fields of the structure are referenced by the labels given them in the group named as the data type in the prototype--not the labels of the fields in the structure actually passed in. This allows the receiving procedure to be completely generic, regardless of what actual data structure is passed to it.

**Example:**

```
PROGRAM
MAP
MyProc PROCEDURE
AddQue PROCEDURE(PassGroup PassedGroup, NameQue PassedQue)
    END                !AddQue receives a GROUP defined like PassGroup and
                        ! a QUEUE defined like NameQue

PassGroup  GROUP,TYPE  !Type definition -- no memory allocated
F1         STRING(20)  !  GROUP with 2 STRING(20) fields
F2         STRING(20)
            END

NameGroup  GROUP       !Name group
First     STRING(20)   !first name
Last      STRING(20)   !last name
Company   STRING(30)   !This extra field is not available to the receiving
            END        !procedure (AddQue) since PassGroup only has two fields

NameQue    QUEUE,TYPE  !Name Queue, Type definition -- no memory allocated
First     STRING(20)
Last      STRING(20)
            END

CODE
MyProc

MyProc  PROCEDURE
LocalQue  NameQue      !Local Name Queue, declared exactly the same as NameQue

CODE
NameGroup.First = 'Fred'
NameGroup.Last  = 'Flintstone'
AddQue(NameGroup,LocalQue)                !Pass NameGroup and LocalQue to AddQue procedure

NameGroup.First = 'Barney'
```

```
NameGroup.Last = 'Rubble'
AddQue (NameGroup, LocalQue)

NameGroup.First = 'George'
NameGroup.Last = 'O' 'Jungle'
AddQue (NameGroup, LocalQue)

LOOP X# = 1 TO RECORDS (LocalQue)      !Look at what's in the LocalQue now
  GET (LocalQue, X#)
  MESSAGE (CLIP (LocalQue.First) & ' ' & LocalQue.Last)
END

AddQue  PROCEDURE (PassGroup PassedGroup, NameQue PassedQue)
CODE
PassedQue.First = PassedGroup.F1      !Effectively: LocalQue.First = NameGroup.First
PassedQue.Last  = PassedGroup.F2      !Effectively: LocalQue.Last = NameGroup.Last
ADD (PassedQue)                       !Add an entry into the PassedQue (LocalQue)
ASSERT (NOT ERRORCODE ())
```

**See Also:**

MAP

MEMBER

MODULE

PROCEDURE

CLASS

## PROCEDURE Return Types

A PROCEDURE prototyped with a return value must RETURN a value. The data type to return is listed, separated by a comma, after the optional parameter list.

### Value RETURN types:

---

**BYTE    SHORT    USHORT    LONG    ULONG    SREAL**  
**REAL    DATE    TIME    STRING    Untyped value-parameter (?)**

An untyped value-parameter return value (?) indicates the data type of the value returned by the PROCEDURE is not known. This functions in exactly the same manner as an untyped value-parameter. When the value is returned from the PROCEDURE, standard Clarion Data Conversion Rules apply, no matter what data type is returned.

### Variable RETURN types:

---

**CSTRING    \*STRING    \*BYTE    \*SHORT    \*USHORT    \*LONG**  
**\*ULONG    \*SREAL    \*REAL    \*DATE    \*TIME**  
**Untyped variable-parameter (\*?)**

Variable return types are provided just for prototyping external library functions (written in another language) which return only the address of data--they are not valid for use on Clarion language procedures.

Functions which return pointers (the address of some data) should be prototyped with an asterisk prepended to the return data type (except CSTRING). The compiler automatically handles the returned pointer at runtime. Functions prototyped this way act just like a variable defined in the program--when the function is used in Clarion code, the data referenced by the returned pointer is automatically used. This data can be assigned to other variables, passed as parameters to procedures, or the ADDRESS function may return the address of the data.

CSTRING is an exception because all the others are fixed length datums, and a CSTRING is not. So, any C function that returns a pointer to a CSTRING can be prototyped as "char \*" at the C end, but the compiler thunks the procedure and copies the datum onto the stack. Therefore, just like the other pointer return values, when the function is used in Clarion code the data referenced by the returned pointer is automatically used (the pointer is dereferenced).

As an example of this, assume that the XYZ() function returns a pointer to a CSTRING, CStringVar is a CSTRING variable, and LongVar is a LONG variable. The simple Clarion assignment statement, CStringVar = XYZ(), places the data referenced by the XYZ() function's returned pointer, in the CStringVar variable. The assignment, LongVar = ADDRESS(XYZ()), places the memory address of that data in the LongVar variable.

An untyped variable-parameter return value (\*?) indicates the data type of the variable returned by the PROCEDURE is not known. This functions in exactly the same manner as an untyped variable-parameter.

### Reference RETURN types:

---

**\*FILE    \*KEY    \*WINDOW    \*VIEW**

**Named CLASS (\*ClassName)**

**Named QUEUE (\*QueueName)**

A PROCEDURE may return a reference which may either be assigned to a reference variable, or used in a parameter list wherever the referenced object would be appropriate. A PROCEDURE that returns \*WINDOW may also return the label of an APPLICATION or REPORT structure. NULL is a valid value to return.

**Example:**

```
MAP
  MODULE('Party3.Obj') !A third-party library
Func46 PROCEDURE(*CSTRING),REAL,C,RAW
      !Pass CSTRING address-only to C function, return REAL
Func47 PROCEDURE(*CSTRING),CSTRING,C,RAW
      !Returns pointer to a CSTRING
Func48 PROCEDURE(REAL),REAL,PASCAL
      !PASCAL calling convention, return REAL
Func49 PROCEDURE(SREAL),REAL,C,NAME('_func49')
      !C convention and external function name, return REAL
  END
END
```

**See Also:**

MAP

MEMBER

MODULE

NAME

PROCEDURE

RETURN

Reference Variables

## Prototype Attributes

### C, PASCAL (parameter passing conventions)

**C**

**PASCAL**

---

The **C** and **PASCAL** attributes of a PROCEDURE prototype specifies that parameters are always passed on the stack. In 32-bit programs, both C and PASCAL conventions pass the parameters to the stack from right to left. The difference is in who (callee(C) or caller(PASCAL)) is cleaning the stack on return. Also, in C/C++ there is a difference in mangling of the external name, but in Clarion, name mangling is the same for both C and PASCAL. PASCAL is also completely compatible with the Windows API calling convention for 32-bit compiled applications--it is the Windows-standard calling convention (and also disables name mangling).

These calling conventions provide compatibility with third-party libraries written in other languages (if they were not compiled with a TopSpeed compiler). If you do not specify a calling convention in the prototype, the default calling convention is the internal, register-based parameter passing convention used by all the TopSpeed compilers.

**Example:**

```
MAP
  MODULE('Party3.Obj')
Func46 PROCEDURE(*CSTRING,*REAL),REAL,C,RAW      !A third-party library
Func49 PROCEDURE(*CSTRING,*REAL),REAL,PASCAL,RAW !Pass REAL then CSTRING, address-only
  END
END
```

**See Also:**

PROCEDURE Prototypes



## DERIVED (prevent function overloading)

### DERIVED

The **DERIVED** attribute of a PROCEDURE prototype specifies that the PROCEDURE on whose prototype it is placed is a VIRTUAL procedure. It can be used by itself or in addition to the VIRTUAL attribute on the prototype.

Use DERIVED to force a compile error when non-matching prototypes between a DERIVED virtual method and its PARENT are found. This prevents function overloading when a VIRTUAL method is the intention.

#### Example:

```
ClassA CLASS
```

```
Method1 PROCEDURE (LONG, <LONG>) ,VIRTUAL
      END
```

```
ClassB CLASS (ClassA)
```

```
Method1 PROCEDURE (LONG,<LONG>) ,DERIVED
      END
```

```
ClassC CLASS (ClassA)
```

```
Method1 PROCEDURE (LONG,<LONG>) ,VIRTUAL ,DERIVED
      END
```

```
ClassD CLASS (ClassA)
```

```
Method1 PROCEDURE (STRING) ,DERIVED  !Will produce compiler error:
      END                               !must match parent prototype
```

#### See Also:

CLASS

VIRTUAL

## DLL (set procedure defined externally in .DLL)

**DLL**( [ *flag* ] )

---

**DLL** Declares a PROCEDURE defined externally in a .DLL.

*flag* A numeric constant, equate, or Project system define which specifies the attribute as active or not. If the *flag* is zero, the attribute is not active, just as if it were not present. If the *flag* is any value other than zero, the attribute is active. Uniquely, it may be an undefined label, in which case the attribute is active.

The **DLL** attribute specifies that the PROCEDURE on whose prototype it is placed is defined in a .DLL. The DLL attribute is required for 32-bit applications because .DLLs are relocatable in a 32-bit flat address space, which requires one extra dereference by the compiler to address the procedure.

### Example:

```
MAP
  MODULE('STDFuncs.DLL')          !A standard functions .DLL
Func50 PROCEDURE(SREAL),REAL,PASCAL,DLL(dll_mode) !
  END
END
```

### See Also:

EXTERNAL

## PRIVATE (set procedure private to a CLASS or module)

### PRIVATE

The **PRIVATE** attribute specifies that the PROCEDURE on whose prototype it is placed may be called only from another PROCEDURE within the same source MODULE. This encapsulates it from other modules.

PRIVATE is normally used on method prototypes in CLASS structures, so that the method may only be called from the other CLASS methods in the module. PRIVATE methods are not inherited by CLASSES derived from the CLASS containing the PRIVATE method's prototype, although they can be VIRTUAL if the derived CLASS is contained in the same module.

#### Example:

```
MAP
  MODULE ('STDFuncs.DLL')                !A standard functions .DLL
Func49 PROCEDURE (SREAL), REAL, PASCAL, PROC
Proc50 PROCEDURE (SREAL), PRIVATE        !Callable only from Func49
  END
END

OneClass CLASS, MODULE ('OneClass.CLW'), TYPE
BaseProc  PROCEDURE (REAL Parm)          !Public method
Proc      PROCEDURE (REAL Parm), PRIVATE !Declare a private method
  END

TwoClass OneClass                        !Instance of OneClass

CODE
TwoClass.BaseProc(1)                     !Legal call to BaseProc
TwoClass.Proc(2)                         !Illegal call to Proc

!In OneClass.CLW:
MEMBER()

OneClass.BaseProc PROCEDURE (REAL Parm)
CODE
SELF.Proc(Parm)                          !Legal call to Proc

OneClass.Proc PROCEDURE (REAL Parm)
CODE
RETURN (Parm)
```

#### See Also:

CLASS

## PROC (set function called as procedure without warnings)

### PROC

---

The **PROC** attribute may be placed on a PROCEDURE prototyped with a return value. This allows you to use it as normal a PROCEDURE call, not only in expressions and assignments, for those instances in which you do not need the return value. The PROC attribute suppresses the compiler warnings you would otherwise get from such use.

#### Example:

```
MAP
  MODULE('STDFuncs.DLL')      !A standard functions .DLL
Func50 PROCEDURE (SREAL) , REAL, PASCAL, PROC
  END
END
```

#### See Also:

PROCEDURE

## PROTECTED (set procedure private to a CLASS or derived CLASS)

### PROTECTED

The **PROTECTED** attribute specifies that the PROCEDURE on whose prototype it is placed is visible only to the PROCEDURES declared within the same CLASS structure (the other methods of that CLASS) and the methods of any CLASS derived from the CLASS. This encapsulates the PROCEDURE from being called from any code external to the CLASS within which it is prototyped or subsequently derived CLASSES.

#### Example:

```
OneClass CLASS,MODULE('OneClass.CLW'),TYPE
BaseProc  PROCEDURE (REAL Parm)           !Public method
Proc      PROCEDURE (REAL Parm),PROTECTED !Declare a protected method
END

TwoClass OneClass                          !Instance of OneClass

ThreeClass CLASS (OneClass),MODULE('ThreeClass.CLW') !Derived from OneClass
ThreeProc  PROCEDURE (REAL Parm)           !Declare a Public method
END

CODE
TwoClass.BaseProc (1)                      !Legal call to BaseProc
TwoClass.Proc (2)                          !Illegal call to Proc

!In OneClass.CLW:
MEMBER ()

OneClass.BaseProc PROCEDURE (REAL Parm)
CODE
SELF.Proc (Parm)                          !Legal call to Proc

OneClass.Proc      PROCEDURE (REAL Parm)
CODE
RETURN (Parm)

!In ThreeClass.CLW:
MEMBER ()

ThreeClass.NewProc PROCEDURE (REAL Parm)
CODE
SELF.Proc (Parm)                          !Legal call to Proc
```

#### See Also:

CLASS

## RAW (pass address only)

### RAW

The **RAW** attribute of a PROCEDURE prototype specifies that STRING or GROUP parameters pass the memory address only. This allows you to pass just the memory address of a \*, STRING, or GROUP parameter, whether passed by value or by reference, to a non-Clarion language procedure or function. Normally, STRING or GROUP parameters pass the address and the length of the string. The RAW attribute eliminates the length portion. For a prototype with a ? parameter, the parameter is taken as a LONG but passed as a "void \*" which just eliminates linker warnings. This is provided for compatibility with external library functions that expect only the address of the string.

If a function is prototyped with one of the following return types: ?, \*? or \*STRING, and the prototype has the RAW attribute, the return value is treated as a LONG.

#### Example:

```
MAP
  MODULE('Party3.Obj')                !A third-party library
Func46 PROCEDURE(*CSTRING),REAL,C,RAW !Pass CSTRING address-only to C function
  END
END
```

#### See Also:

PROCEDURE Prototypes

Prototype Parameter Lists

## REPLACE (set replacement constructor or destructor)



### REPLACE

The **REPLACE** attribute specifies that the PROCEDURE on whose prototype it is placed completely replaces the constructor or destructor from its parent class. REPLACE is valid only on a PROCEDURE labelled either "Construct" or "Destruct" and declared within a CLASS structure which is derived from a class which also contains a matching "Construct" or "Destruct" PROCEDURE. If the PROCEDURE label is "Construct" the method is a Constructor--automatically called when the object is instantiated. An object is instantiated when it comes into scope or when created with a NEW statement. If the PROCEDURE label is "Destruct" the method is a Destructor--automatically called when the object is destroyed. An object is destroyed when it goes out of scope or when destroyed with a DISPOSE statement.

#### Example:

```

PROGRAM
SomeQueue QUEUE, TYPE
F1      STRING(10)
END

OneClass CLASS, MODULE('OneClass.CLW'), TYPE
ObjectQueue &SomeQueue      !Declare a reference to a named queue
Construct   PROCEDURE        !Declare a Constructor
Destruct    PROCEDURE        !Declare a Destructor
END

TwoClass CLASS(OneClass), MODULE('TwoClass.CLW'), TYPE
Construct   PROCEDURE, REPLACE !Declare a replacement Constructor
END

MyClass OneClass              !Instance of OneClass
YourClass &TwoClass           !Reference to TwoClass
CODE                          !MyClass object comes into scope,
                              !autocalling OneClass.Construct
YourClass &= NEW(TwoClass)    !YourClass object comes into scope,
                              !autocalling TwoClass.Construct
DISPOSE(YourClass)           !YourClass object goes out of scope,
                              !autocalling OneClass.Destruct
RETURN                       !MyClass object goes out of scope,
                              !autocalling OneClass.Destruct

!OneClass.CLW contains:
OneClass.Construct PROCEDURE
CODE
SELF.ObjectQueue = NEW(SomeQueue) !Create the object's queue
OneClass.Destruct PROCEDURE
CODE
FREE(SELF.ObjectQueue)           !Free the queue entries
DISPOSE(SELF.ObjectQueue)        ! and remove the queue
!TwoClass.CLW contains:
TwoClass.Construct PROCEDURE
CODE
SELF.ObjectQueue = NEW(SomeQueue) !Create the object's queue
SELF.ObjectQueue.F1 = 'First Entry'
ADD(SELF.ObjectQueue)

```

See Also: NEW, DISPOSE, CLASS

## TYPE (specify PROCEDURE type definition)

### TYPE

The **TYPE** attribute specifies a prototype that does not reference an actual PROCEDURE. Instead, it defines a prototype *name* to use in other prototypes to indicate the type of procedure passed to another PROCEDURE as a parameter.

When the *name* of the TYPED prototype is used in the *parameter list* of another prototype, the procedure being prototyped will receive, as a passed parameter, the label of a PROCEDURE that has the same type of *parameter list* (and has the same *return type*, if it returns a value).

#### Example:

```
MAP
ProcType PROCEDURE (FILE) , TYPE      !Procedure-parameter type definition
MyFunc3  PROCEDURE (ProcType) , STRING !ProcType procedure-parameter, returning a STRING,
END                                     ! must be passed the label of a procedure that
                                     !takes a FILE as a required parameter
```

#### See Also:

PROCEDURE Prototypes

Prototype Parameter Lists



## VIRTUAL (set virtual method)

### VIRTUAL

The **VIRTUAL** attribute specifies that the PROCEDURE on whose prototype it is placed is a virtual method of the CLASS containing the prototype. This allows methods in a parent CLASS to access methods in a derived CLASS. The VIRTUAL attribute must be placed on both the method's parent class prototype and the derived class's prototype.

#### Example:

```
OneClass CLASS                                !Base class
BaseProc  PROCEDURE (REAL Parm)              !Non-virtual method
Proc      PROCEDURE (REAL Parm),VIRTUAL !Declare a virtual method
END

TwoClass CLASS (OneClass)                    !Derived class of OneClass
Proc      PROCEDURE (REAL Parm),VIRTUAL !Declare a virtual method
END

ClassThree OneClass                          !Another Instance of a OneClass object
ClassFour  TwoClass                          !Another Instance of a TwoClass object

CODE
OneClass.BaseProc (1)                        !BaseProc calls OneClass.Proc
TwoClass.BaseProc (2)                        !BaseProc calls TwoClass.Proc
ClassThree.BaseProc (3)                      !BaseProc calls OneClass.Proc
ClassFour.BaseProc (4)                       !BaseProc calls TwoClass.Proc

OneClass.BaseProc PROCEDURE (REAL Parm)
CODE
SELF.Proc (Parm)                            !Calls virtual method, either OneClass.Proc
                                           ! TwoClass.Proc, depending on which
                                           ! class instance is executing
```

#### See Also:

CLASS

DERIVED

## Procedure Overloading

Procedure Overloading means allowing multiple PROCEDURE definitions to use the same name. This is one form of polymorphism. In order to allow this each PROCEDURE using a shared name must receive different parameters so the compiler can decide, based on the parameters passed which PROCEDURE to call.

The idea here is to allow more than one procedure of the same name, but with different prototypes, so separate (but usually similar) operations can occur on different data types. From an efficiency viewpoint, Procedure Overloading is much more efficient than coding a single procedure with omittable parameters, for those cases where you may or may not receive multiple parameters.

The Clarion language also allows polymorphic procedures through the use of the ? and \*? parameters, but Procedure Overloading extends this polymorphic ability to also include Entity-parameters and "named group" parameters.

One example of Procedure Overloading is the Clarion OPEN statement, which initializes an entity for use in the program. Depending on what type of entity is passed to it (a FILE, a WINDOW, a VIEW, ...), it performs related but physically different functions.

### See Also:

- Rules for Procedure Overloading

- Name Mangling and C++ Compatibility

## Rules for Procedure Overloading

The Clarion language has built-in data type conversion which can make overload resolution difficult for the compiler. Therefore, there are rules governing how the compiler resolves functional overloading, which are applied in the following order:

1. Entity-parameters are resolved to FILE, KEY, WINDOW, and QUEUE. If a prototype can be chosen on the basis of these alone then the compiler does (most of the Clarion built in procedures fall into this category). Note that KEY and VIEW are implicitly derived from FILE, just as APPLICATION and REPORT are implicitly derived from WINDOW.
2. All "named group" parameters must match a group of their own structure. Procedure-parameters are matched by structure. CLASSES must match by name, not simply by structure.
3. A prototype must match in the number and placement of non-omittable parameters. This is the third criteria (not the first) so that the compiler can usually guess which prototype the user was aiming at and give a more meaningful error message.
4. If there are no matching prototypes then allow derivation. At this point a KEY would be allowed to match a FILE and a group that is derived would match one of its base classes. If one level of derivation does not work, the compiler continues up the tree. All QUEUES now match QUEUE and GROUP etc. CLASSES derive before other parameter types.
5. Variable-parameters (unnamed) must exactly match the actual data type passed. A \*GROUP matches a \*STRING. Any variable-parameter matches \*?.
6. All Value-parameters are considered to have the same type.

### Example:

```
MAP
Func  PROCEDURE (WINDOW)      ! 1
Func  PROCEDURE (FILE)        ! 2
Func  PROCEDURE (KEY)          ! 3
Func  PROCEDURE (FILE,KEY)     ! 4
Func  PROCEDURE (G1)           ! 5
Func  PROCEDURE (G0)           ! 6
Func  PROCEDURE (KEY,G0)       ! 7
Func  PROCEDURE (FILE,G1)      ! 8
Func  PROCEDURE (SHORT = 10)   ! 9
Func  PROCEDURE (LONG)         ! 10
Func  PROCEDURE ()             ! Illegal, indistinguishable from 9
Func  PROCEDURE (*SHORT)       ! 11
Func1  PROCEDURE (*SHORT)
Func1a PROCEDURE (*SHORT)
Func2  PROCEDURE (*LONG)
Func  PROCEDURE (Func1)        ! 12
Func  PROCEDURE (Func1a)       ! Illegal, same as 12
Func  PROCEDURE (Func2)        ! 13
END

G0 GROUP
END
G1 GROUP (G0)
END
```

CODE

```
Func(A:Window)    ! Calls 1 by rule 1
Func(A:File)      ! Calls 2 by rule 1
Func(A:Key)       ! Calls 3 by rule 1
Func(A:View)      ! Calls 2 by rule 4
Func(A:Key,A:Key) ! Calls 4 by rule 4 (would call key,key if present)
Func(A:G0)        ! Calls 6 by rule 2
Func(A:G1)        ! Calls 5 by rule 2
Func(A:Func2)     ! Calls 13 by rule 2
Func(A:Key,A:G1)  ! Error - Ambiguous. If rule 4 is used then 7 & 8 are both possible
Func(A:Short)     ! Error - Ambiguous. Calls 9 or 11
Func(A:Real)      ! Calls 9 by rule 6
Func              ! Calls 9 by rule 3
```

**See Also:**

CLASS

## Name Mangling and C++ Compatibility

Each overloaded function will have a link-time name composed of the procedure label and a "mangled" argument list (the NAME attribute can be used to disable name mangling). This is designed so that some degree of cross-calling between C++ and Clarion is possible. On the C++ side you need:

```
#pragma name(prefix=>"")
```

and the name in all caps. On the Clarion side you need a MODULE structure with a null string as its parameter:

```
MODULE('')
END
```

The only procedures that can be cross-called are those whose prototypes only contain data types from the following list. Clarion Variable-parameters (passed by address) correspond to reference parameters on the C side unless they are omissible, in which case they correspond to pointer parameters.

<u>Clarion</u>	<u>C++</u>
BYTE	unsigned char
USHORT	unsigned short
SHORT	short
LONG	long
ULONG	unsigned long
SREAL	float
REAL	double
*CSTRING (with RAW)	char&
<*CSTRING> (with RAW)	char*
<*GROUP> (with RAW)	void*

Note that for C++ compatibility the return type of a PROCEDURE is not mangled into the name. A corollary effect is that procedures cannot be distinguished by return type.

### Example:

```
//C++ prototypes:
#pragma name(prefix=>"")
void HADD(short,short);
void HADD(long*,unsigned char);
void HADD(short unsigned &);
void HADD(char *,void *);
```

```
!Clarion prototypes:
MODULE('')
  hADD(short,short)
  HaDD(<*long>,byte)
  HAdD(*ushort)
  HADd(<*CSTRING>,<*GROUP>),RAW
END
```

### See Also:

NAME

## Compiler Directives

Compiler Directives are statements that tell the compiler to take some action at compile time. These statements are not included in the executable program object code which the compiler generates. Therefore, there is no run-time overhead associated with their use.

- ASSERT (set assumption for debugging)
- BEGIN (define code structure)
- COMPILE (specify source to compile)
- EQUATE (assign label)
- INCLUDE (compile code in another file)
- ITEMIZE (enumeration data structure)
- OMIT (specify source not to be compiled)
- ONCE (prevent duplicate included data)
- SECTION (specify source code section)
- SIZE (memory size in bytes)

## ASSERT (set assumption for debugging)

**ASSERT**(*expression*, [*message*] )

**ASSERT** Specifies an assumption for debugging purposes.

*expression* A Boolean expression that *should* always evaluate as true (any value other than blank or zero).

*message* An optional string expression (up to 64K) which displays in the dialog window.

The **ASSERT** statement specifies an *expression* to evaluate at the exact point in the program where the ASSERT is placed. This may be any kind of Boolean expression and should be formulated such that the expected evaluation result is always true (any value other than blank or zero). The purpose of ASSERT is to catch erroneous assumptions for the programmer.

If debug is on and the *expression* is false (blank or zero), an error message displays indicating the specific line number and source code module where the asserted *expression* was false. The user is invited to GPF the program at that point, which allows Clarion's post-mortem debuggers to activate.

If debug is off, the *expression* is still evaluated, but no error message is displayed if the result is false. To activate error messages in release build (debug is off), you can add the following project define to your application:

```
asserts=>on
```

### Example:

```
MyQueue QUEUE
F1      LONG
      END
CODE
LOOP X# = 1 TO 10
    MyQueue.F1 = X#
    ADD (MyQueue)
    ASSERT (~ERRORCODE(), 'ADD MyQueue Error ' & ERROR())
END
LOOP X# = 1 TO 10
    GET (MyQueue, X#)
    ASSERT (~ERRORCODE())      !This error only happens if the ADD above fails
END

*****
!- Get Single Configuration Record
Access:CONFIG.Open()
SET (CONFIG)
ASSERT (~Access:Config.Next(), 'Config record missing')
```

## BEGIN (define code structure)

```
BEGIN
    statements
END
```

---

**BEGIN**      Declares a single code statement structure.

*statements*   Executable program instructions.

The **BEGIN** compiler directive tells the compiler to treat the *statements* as a single structure. The BEGIN structure must be terminated by a period or the END statement.

BEGIN is usually used in an EXECUTE control structure to allow several lines of code to be treated as one.

**Example:**

```
EXECUTE Value
  Proc1      !Execute if Value = 1
  BEGIN      !Execute if Value = 2
    Value += 1
    Proc2
  END
  Proc3      !Execute if Value = 3
END
```

**See Also:**

EXECUTE



## COMPILE (specify source to compile)

**COMPILE**(*terminator* [,*expression*])

**COMPILE** Specifies a block of source code lines to be included in the compilation.

*terminator* A string constant that marks the last line of a block of source code.

*expression* An expression allowing conditional execution of the COMPILE. The expression is either an EQUATE whose value is zero or one, or EQUATE = integer.

The **COMPILE** directive specifies a block of source code lines to be included in the compilation. The included block begins with the COMPILE directive and ends with the line that contains the same string constant as the *terminator*. The entire terminating line is included in the COMPILE block.

The optional *expression* parameter permits conditional COMPILE. The form of the *expression* is fixed. It is the label of an EQUATE statement, or a Conditional Switch set in the Project System, and may be followed by an equal sign ( = ) and an integer constant.

The code between COMPILE and the *terminator* is compiled only if the *expression* is true. If the *expression* contains an EQUATE that has not yet been defined, then the referenced EQUATE is assumed to be zero (0).

Although the *expression* is not required, COMPILE without an *expression* parameter is not necessary because all source code is compiled unless explicitly omitted. COMPILE and OMIT are opposites.

### Example:

```

    OMIT('***',_WIDTH32_)           !OMIT only if application is 32-bit
    SIGNED    EQUATE (SHORT)
    UNSIGNED  EQUATE (USHORT)
    ***
    COMPILE('***',_WIDTH32_)        !COMPILE only if application is 32-bit
    SIGNED    EQUATE (LONG)
    UNSIGNED  EQUATE (ULONG)
    ***

    COMPILE('EndOfFile',OnceOnly = 0) !COMPILE only the first time encountered because the
    OnceOnly EQUATE(1)                ! OnceOnly EQUATE is defined after the COMPILE that
                                      ! references it, so a second pass during the same
                                      ! compilation will not re-compile the code
                                      ! Specify the Demo EQUATE value

    Demo EQUATE(1)
    CODE
    COMPILE('EndDemoChk',Demo = 1)    !COMPILE only if Demo equate is turned on
    DO DemoCheck                      !Check for demo limits passed
    ! EndDemoChk                      !End of conditional COMPILE code
    ! EndOfFile

!The following example below shows how OMIT and COMPILE can be nested
COMPILE ('**32bit**',_width32_) !outer COMPILE

    COMPILE ('*debug*',_debug_)
    DEBUGGER::BUTTONLIST Equate('&Continue|&Halt|&Debug')
    !end- COMPILE ('*debug*',_debug_)
```

```
OMIT ('*debug*',_debug_)
DEBUGGER::BUTTONLIST Equate('&Continue|&Halt')
!end- OMIT ('*debug*',_debug_)

!end- COMPILE ('**32bit**',_width32_) !end outer COMPILE

OMIT ('**32bit**',_width32_)
DEBUGGER::BUTTONLIST Equate('&Continue|&Halt')
!end- OMIT ('**32bit**',_width32_)
```

**Note:**

The compiler reads and parses source/include files by blocks. If the end of an OMIT/COMPILE block (terminator string) is found in the current block, the compiler either will skip the text up to terminator or will continue to parse the file - depending on whether you are using OMIT or COMPILE and what condition. If the terminator string is found within the current block and parsing is continuing, nested OMIT/COMPILE statements are allowed. If the terminator string is not found, nested OMIT/COMPILE statement in this block is not allowed.

In summary, nesting of OMIT/COMPILE statements is dependent on the current compiler block. Use of conditions in OMIT/COMPILE statements and possibility to define complex conditions as EQUATEs are allowed to avoid excessive nesting of OMIT/COMPILE statements.

**See Also:**

Predefined Compiler Flags

OMIT

EQUATE

## INCLUDE (compile code in another file)

**INCLUDE**(*filename* [,*section*]) [,ONCE]

- 
- INCLUDE** Specifies source code to be compiled which exists in a separate file which is not a MEMBER module.
- filename* A string constant that contains the DOS file specification for a source file. If the extension is omitted, .CLW is assumed.
- section* A string constant which is the *string* parameter of the SECTION directive marking the beginning of the source code to be included.
- ONCE The **ONCE** attribute precludes any INCLUDED data from being compiled more than once, which can result in compile warnings or errors. Regarding the use of the *section* attribute, ONCE is applied on the entire *filename*, so subsequent uses of INCLUDE( *filename*, *section* ) will be ignored.

The **INCLUDE** directive specifies source code to be compiled which exists in a separate file which is not a MEMBER module. Starting on the line of the INCLUDE directive, the source file, or the specified *section* of that file, is compiled as if it appeared in sequence within the source module being compiled. You can nest INCLUDEs up to 3 deep, so you can INCLUDE a file that includes a file that includes a file but that latter file must not include anything.

The compiler uses the Redirection file (*CurrentReleaseName*.RED) to find the file, searching the path specified for that type of *filename* (usually by extension). This makes it unnecessary to provide a complete path in the *filename* to be included. A discussion of the Redirection file is in the *User's Guide* and the *Project System* chapter of the *Programmer's Guide*.

### Example:

```
GenLedger PROCEDURE      !Declare procedure
  INCLUDE('filedefs.clw') !Include file definitions here
  CODE                   !Begin code section
  INCLUDE('Setups','ChkErr') !Include error check from setups.clw
```

### See Also:

SECTION

ONCE

## ITEMIZE (enumeration data structure)

```
[label] ITEMIZE( [ seed ] ) [,PRE( )]  
           equates  
END
```

---

*label*        An optional label for the ITEMIZE structure.

**ITEMIZE**    An enumeration data structure.

*seed*        An integer constant or constant expression specifying the value of the first EQUATE in the structure.

**PRE**        Declare a label prefix for variables within the structure.

*equates*    Multiple consecutive EQUATE declarations which specify positive integer values in the range 0 to 4,294,967,295.

An **ITEMIZE** structure declares an enumerated data structure. If the first *equate* does not declare a value and there is no *seed* value specified, its value is one (1). All following *equates* following the first increment by one (1) if no value is specified for the subsequent *equate*. If a value is specified on a subsequent *equate*, all *equates* following that continue incrementing by one (1) from the specified value.

*Equates* within the ITEMIZE structure are referenced by prepending the prefix to the label of the *equate* (PRE attribute--PRE:EquateLabel). If the ITEMIZE structure has an empty prefix, then the *equates* are referenced by prepending the ITEMIZE *label* to the label of the *equate* (*label*:EquateLabel). If there is no prefix or *label*, then the *equates* are referenced by their own label without a prefix.

**Example:**

```
ITEMIZE  
False EQUATE(0)            !False = 0  
True EQUATE                !True = 1  
END  
  
Color ITEMIZE(0),PRE !Seed value is zero  
Red EQUATE                !Color:Red = 0  
White EQUATE              !Color:White = 1  
Blue EQUATE                !Color:Blue = 2  
Pink EQUATE(5)             !Color:Pink = 5  
Green EQUATE               !Color:Green = 6  
Last EQUATE  
END  
  
Stuff ITEMIZE(Color:Last + 1),PRE(My)    !Constant expression as seed  
X EQUATE                    !My:X = Color:Last + 1  
Y EQUATE                    !My:Y = Color:Last + 2  
Z EQUATE                    !My:Z = Color:Last + 3  
END
```

**See Also:** EQUATE,PRE

## OMIT (specify source not to be compiled)

**OMIT**(*terminator* [,*expression*])

**OMIT** Specifies a block of source code lines to be omitted from the compilation.

*terminator* A string constant that marks the last line of a block of source code.

*expression* An expression allowing conditional execution of the OMIT. The expression is either an EQUATE whose value is zero or one, or EQUATE = integer.

The **OMIT** directive specifies a block of source code lines to be omitted from the compilation. These lines may contain source code comments or a section of code that has been "stubbed out" for testing purposes. The omitted block begins with the OMIT directive and ends with the line that contains the same string constant as the *terminator*. The entire terminating line is included in the OMIT block.

The optional *expression* parameter permits conditional OMIT. The form of the *expression* is fixed. It is the label of an EQUATE statement, or a Conditional Switch set in the Project System, and may be followed by an equal sign (=) and an integer constant.

The OMIT directive executes only if the *expression* is true. Therefore, the code between OMIT and the *terminator* is compiled only if the *expression* is not true. If the *expression* contains an EQUATE that has not yet been defined, then the referenced EQUATE is assumed to be zero (0). COMPILE and OMIT are opposites.

**Example:**

```
OMIT('**END**')           !Unconditional OMIT
!Main Program Loop
**END**
OMIT('***',_WIDTH32_)     !OMIT only if application is 32-bit
SIGNED EQUATE (SHORT)
***
COMPILE('***',_WIDTH32_)  !COMPILE only if application is 32-bit
SIGNED EQUATE (LONG)
***
OMIT('EndOfFile',OnceOnly) !Compile only the first time encountered because the
OnceOnly EQUATE (1)        ! OnceOnly EQUATE is defined after the COMPILE that
                           ! references it, so a second pass during the same
                           ! compilation will not re-compile the code

Demo EQUATE (0)            !Specify the Demo EQUATE value
CODE
OMIT('EndDemoChk',Demo = 0) !OMIT only if Demo is turned off
DO DemoCheck               !Check for demo limits passed
!EndDemoChk                !End of omitted code
! EndOfFile
```

!The following example below shows how OMIT and COMPILE can be nested  
COMPILE ('\*\*32bit\*\*',\_width32\_) !outer COMPILE

```
COMPILE ('*debug*',_debug_)
DEBUGGER::BUTONLIST Equate('&Continue|&Halt|&Debug')
!end- COMPILE ('*debug*',_debug_)
```

```
OMIT ('*debug*',_debug_)
  DEBUGGER::BUTTONLIST Equate('&Continue|&Halt')
!end- OMIT ('*debug*',_debug_)

!end- COMPILE ('**32bit**',_width32_) !end outer COMPILE

OMIT ('**32bit**',_width32_)
  DEBUGGER::BUTTONLIST Equate('&Continue|&Halt')
!end- OMIT ('**32bit**',_width32_)
```

**Note:**

The compiler reads and parses source/include files by blocks. If the end of an OMIT/COMPILE block (terminator string) is found in the current block, the compiler either will skip the text up to terminator or will continue to parse the file - depending on whether you are using OMIT or COMPILE and what condition. If the terminator string is found within the current block and parsing is continuing, nested OMIT/COMPILE statements are allowed. If the terminator string is not found, nested OMIT/COMPILE statement in this block is not allowed.

In summary, nesting of OMIT/COMPILE statements is dependent on the current compiler block. Use of conditions in OMIT/COMPILE statements and possibility to define complex conditions as EQUATEs are allowed to avoid excessive nesting of OMIT/COMPILE statements.

**See Also:**

Predefined Compiler Flags

COMPILE

EQUATE

## ONCE (prevent duplicate included data)

### ONCE

---

The **ONCE** attribute precludes any data contained in the INCLUDE from being compiled more than once resulting in compile warnings or errors.

#### Example:

```
INCLUDE ( 'KEYCODES.CLW' ) ,ONCE
```

#### See Also:

INCLUDE

## SECTION (specify source code section)

**SECTION**(*string*)

---

**SECTION** Identifies the beginning of a block of executable source code or data declarations.

*String* A string constant which names the SECTION.

The **SECTION** compiler directive identifies the beginning of a block of executable source code or data declarations which may be INCLUDED in source code in another file. The SECTION's *string* parameter is used as an optional parameter of the INCLUDE directive to include a specific block of source code. A SECTION is terminated by the next SECTION or the end of the file.

**Example:**

```
SECTION('FirstSection')      !Begin section

FieldOne STRING(20)
FieldTwo LONG

SECTION('SecondSection')     !End previous section, begin new section

IF Number <> SavNumber
  DO GetNumber
END

SECTION('ThirdSection')      !End previous section, begin new section

CASE Action
OF 1
  DO AddRec
OF 2
  DO ChgRec
OF 3
  DO DelRec
END                          !Third section ends at end of file
```

**See Also:**

INCLUDE



## SIZE (memory size in bytes)



```

| variable |
SIZE( | constant | )
| picture |

```

**SIZE** Supplies the amount of memory used for storage.

*variable* The label of a previously declared variable.

*constant* A numeric or string constant.

*picture* A picture token.

**SIZE** directs the compiler to supply the amount of memory (in bytes) used to store the *variable*, *constant*, or *picture*.

SIZE can also be used at run time. The compiler is smart in handling SIZE. If the size of the data is known at compile time, the compiler will use it. Otherwise, the compiler generates code to evaluate SIZE at run time.

For example, at run time:

- The size of a STRING, CSTRING, PSTRING and GROUP (including RECORD) pointed to by a given reference variable is retrieved from that variable.
- The size of a BLOB is retrieved by the call to appropriate RTL functions.
- The size of an array with variable dimensions is calculated on the basis of the size of one entry and number of actual elements of that array.

**Example:**

```
SavRec  STRING(1),DIM(SIZE(Cus:Record)           !Dimension the string to size of record

StringVar STRING(SIZE('SoftVelocity Corporation')) !A string long enough for the constant

LOOP I# = 1 TO SIZE(ParseString)                 !Loop for number of bytes in the string

PicLen = SIZE(@P(###)###-####P)                 !Save size of the picture

tmp    LONG
str1   STRING(15)
str2   CSTRING(16)
str3   &STRING
str4   &CSTRING

CODE

str3 &= NEW(STRING(17))
str4 &= NEW(CSTRING(18))

tmp = SIZE(str1)    ! returns 15
tmp = SIZE(str2)    ! returns 16
tmp = SIZE(str3)    ! returns 17
tmp = SIZE(str4)    ! returns 18
```

**See Also:**

LEN

Prop:Size

FILE Structure Properties





## 3 - Variable Declarations

### BYTE (one-byte unsigned integer)

label **BYTE**(*initial value*) [, **DIM**( )] [, **OVER**( )] [, **NAME**( )] [, **EXTERNAL**] [, **DLL**] [, **STATIC**] [, **THREAD**]  
 [, **AUTO**] [, **PRIVATE**] [, **PROTECTED**]

**BYTE**            A one-byte unsigned integer.

```
Format: magnitude
      | ..... |
Bits:  7       0
Range: 0 to 255
```

*initial value*    A numeric constant. If omitted, the initial value is zero, unless the **AUTO** attribute is present.

**DIM**             Dimension the variable as an array.

**OVER**            Share a memory location with another variable.

**NAME**            Specify an alternate, "external" name for the field.

**EXTERNAL**       Specify the variable is defined, and its memory is allocated, in an external library. Not valid within **FILE**, **QUEUE**, or **GROUP** declarations.

**DLL**             Specify the variable is defined in a .DLL. This is required in addition to the **EXTERNAL** attribute.

**STATIC**          Specify the variable's memory is permanently allocated.

**THREAD**          Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the **STATIC** attribute on Procedure Local data.

**AUTO**            Specify the variable has no *initial value*.

**PRIVATE**        Specify the variable is not visible outside the module containing the **CLASS** methods. Valid only in a **CLASS**.

**PROTECTED**     Specify the variable is not visible outside base **CLASS** and derived **CLASS** methods. Valid only in a **CLASS**.

**BYTE** declares a one-byte unsigned integer.

**Example:**

```
Count1 BYTE                    !Declare one byte integer
Count2 BYTE,OVER(Count1) !Declare OVER the one byte integer
Count4 BYTE,DIM(5)            !Declare as a 5 element array
Count4 BYTE(5)                !Declare with initial value
```

## SHORT (two-byte signed integer)

label **SHORT**(*[initial value]*) [, **DIM**( )] [, **OVER**( )] [, **NAME**( )] [, **EXTERNAL**] [, **DLL**] [, **STATIC**]  
[, **THREAD**] [, **AUTO**] [, **PRIVATE**] [, **PROTECTED**]

---

**SHORT**      A two-byte signed integer.

```
Format: ±      magnitude
        | . | ..... |
Bits: 15  14                0
Range: -32,768 to 32,767
```

*initial value*      A numeric constant. If omitted, the initial value is zero, unless the **AUTO** attribute is present.

**DIM**              Dimension the variable as an array.

**OVER**             Share a memory location with another variable.

**NAME**            Specify an alternate, "external" name for the field.

**EXTERNAL**       Specify the variable is defined, and its memory is allocated, in an external library. Not valid within **FILE**, **QUEUE**, or **GROUP** declarations.

**DLL**             Specify the variable is defined in a .DLL. This is required in addition to the **EXTERNAL** attribute.

**STATIC**          Specify the variable's memory is permanently allocated.

**THREAD**          Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the **STATIC** attribute on Procedure Local data.

**AUTO**            Specify the variable has no *initial value*.

**PRIVATE**        Specify the variable is not visible outside the module containing the **CLASS** methods. Valid only in a **CLASS**.

**PROTECTED**     Specify the variable is not visible outside base **CLASS** and derived **CLASS** methods. Valid only in a **CLASS**.

**SHORT** declares a two-byte signed integer, using the Intel 8086 word integer format. The high-order bit of this configuration is the sign bit (0 = positive, 1 = negative). Negative values are represented in standard two's complement notation.

**Example:**

```
Count1 SHORT                                !Declare two-byte signed integer
Count2 SHORT,OVER(Count1)                   !Declare OVER the two-byte signed integer
Count3 SHORT,DIM(4)                         !Declare it an array of 4 shorts
Count4 SHORT(5)                             !Declare with initial value
Count5 SHORT,EXTERNAL                       !Declare as external
Count6 SHORT,EXTERNAL,DLL                   !Declare as external in a .DLL
Count7 SHORT,NAME('SixCount')              !Declare with external name
ExampleFile FILE,DRIVER('Clarion')         !Declare a file
Record      RECORD
Count7      SHORT,NAME('Counter') !Declare with external name
            END
            END
```

## USHORT (two-byte unsigned integer)

label **USHORT**(*[initial value]*) [**DIM**( )] [**OVER**( )] [**NAME**( )] [**EXTERNAL**] [**DLL**] [**STATIC**]  
[**THREAD**] [**AUTO**] [**PRIVATE**] [**PROTECTED**]

---

**USHORT**      A two-byte unsigned integer.

Format: magnitude  
          | .....|  
Bits: 15           0  
Range: 0 to 65,535

*initial value*      A numeric constant. If omitted, the initial value is zero, unless the **AUTO** attribute is present.

**DIM**              Dimension the variable as an array.

**OVER**             Share a memory location with another variable.

**NAME**            Specify an alternate, "external" name for the field.

**EXTERNAL**       Specify the variable is defined, and its memory is allocated, in an external library. Not valid within **FILE**, **QUEUE**, or **GROUP** declarations.

**DLL**             Specify the variable is defined in a .DLL. This is required in addition to the **EXTERNAL** attribute.

**STATIC**          Specify the variable's memory is permanently allocated.

**THREAD**          Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the **STATIC** attribute on Procedure Local data.

**AUTO**            Specify the variable has no *initial value*.

**PRIVATE**        Specify the variable is not visible outside the module containing the **CLASS** methods. Valid only in a **CLASS**.

**PROTECTED**     Specify the variable is not visible outside base **CLASS** and derived **CLASS** methods. Valid only in a **CLASS**.

**USHORT** declares a two-byte unsigned integer in the Intel 8086 word format. There is no sign bit in this configuration.



**Example:**

```
Count1 USHORT                                !Declare two-byte unsigned integer
Count2 USHORT,OVER(Count1)                   !Declare OVER the two-byte unsigned integer
Count3 USHORT,DIM(4)                         !Declare it an array of 4 unsigned shorts
Count4 USHORT(5)                             !Declare with initial value
Count5 USHORT,EXTERNAL                       !Declare as external
Count6 USHORT,EXTERNAL,DLL                   !Declare as external in a .DLL
Count7 USHORT,NAME('SixCount')              !Declare with external name
ExampleFile FILE,DRIVER('Btrieve')          !Declare a file
Record      RECORD
Count8      USHORT,NAME('Counter') !Declare with external name
            END
            END
```

**Win 32** only

**Abstract**

<i>initial value</i>	A numeric constant. If omitted, the initial value is zero, unless the AUTO attribute is present.
----------------------	--

1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44 45 46 47 48 49 50 51 52 53 54 55 56 57 58 59 60 61 62 63 64 65 66 67 68 69 70 71 72 73 74 75 76 77 78 79 80 81 82 83 84 85 86 87 88 89 90 91 92 93 94 95 96 97 98 99 100 101 102 103 104 105 106 107 108 109 110 111 112 113 114 115 116 117 118 119 120 121 122 123 124 125 126 127 128 129 130 131 132 133 134 135 136 137 138 139 140 141 142 143 144 145 146 147 148 149 150 151 152 153 154 155 156 157 158 159 160 161 162 163 164 165 166 167 168 169 170 171 172 173 174 175 176 177 178 179 180 181 182 183 184 185 186 187 188 189 190 191 192 193 194 195 196 197 198 199 200 201 202 203 204 205 206 207 208 209 210 211 212 213 214 215 216 217 218 219 220 221 222 223 224 225 226 227 228 229 230 231 232 233 234 235 236 237 238 239 240 241 242 243 244 245 246 247 248 249 250 251 252 253 254 255 256 257 258 259 260 261 262 263 264 265 266 267 268 269 270 271 272 273 274 275 276 277 278 279 280 281 282 283 284 285 286 287 288 289 290 291 292 293 294 295 296 297 298 299 300 301 302 303 304 305 306 307 308 309 310 311 312 313 314 315 316 317 318 319 320 321 322 323 324 325 326 327 328 329 330 331 332 333 334 335 336 337 338 339 340 341 342 343 344 345 346 347 348 349 350 351 352 353 354 355 356 357 358 359 360 361 362 363 364 365 366 367 368 369 370 371 372 373 374 375 376 377 378 379 380 381 382 383 384 385 386 387 388 389 390 391 392 393 394 395 396 397 398 399 400 401 402 403 404 405 406 407 408 409 410 411 412 413 414 415 416 417 418 419 420 421 422 423 424 425 426 427 428 429 430 431 432 433 434 435 436 437 438 439 440 441 442 443 444 445 446 447 448 449 450 451 452 453 454 455 456 457 458 459 460 461 462 463 464 465 466 467 468 469 470 471 472 473 474 475 476 477 478 479 480 481 482 483 484 485 486 487 488 489 490 491 492 493 494 495 496 497 498 499 500 501 502 503 504 505 506 507 508 509 510 511 512 513 514 515 516 517 518 519 520 521 522 523 524 525 526 527 528 529 530 531 532 533 534 535 536 537 538 539 540 541 542 543 544 545 546 547 548 549 550 551 552 553 554 555 556 557 558 559 560 561 562 563 564 565 566 567 568 569 570 571 572 573 574 575 576 577 578 579 580 581 582 583 584 585 586 587 588 589 590 591 592 593 594 595 596 597 598 599 600 601 602 603 604 605 606 607 608 609 610 611 612 613 614 615 616 617 618 619 620 621 622 623 624 625 626 627 628 629 630 631 632 633 634 635 636 637 638 639 640 641 642 643 644 645 646 647 648 649 650 651 652 653 654 655 656 657 658 659 660 661 662 663 664 665 666 667 668 669 670 671 672 673 674 675 676 677 678 679 680 681 682 683 684 685 686 687 688 689 690 691 692 693 694 695 696 697 698 699 700 701 702 703 704 705 706 707 708 709 710 711 712 713 714 715 716 717 718 719 720 721 722 723 724 725 726 727 728 729 730 731 732 733 734 735 736 737 738 739 740 741 742 743 744 745 746 747 748 749 750 751 752 753 754 755 756 757 758 759 760 761 762 763 764 765 766 767 768 769 770 771 772 773 774 775 776 777 778 779 780 781 782 783 784 785 786 787 788 789 790 791 792 793 794 795 796 797 798 799 800 801 802 803 804 805 806 807 808 809 810 811 812 813 814 815 816 817 818 819 820 821 822 823 824 825 826 827 828 829 830 831 832 833 834 835 836 837 838 839 840 841 842 843 844 845 846 847 848 849 850 851 852 853 854 855 856 857 858 859 860 861 862 863 864 865 866 867 868 869 870 871 872 873 874 875 876 877 878 879 880 881 882 883 884 885 886 887 888 889 890 891 892 893 894 895 896 897 898 899 900 901 902 903 904 905 906 907 908 909 910 911 912 913 914 915 916 917 918 919 920 921 922 923 924 925 926 927 928 929 930 931 932 933 934 935 936 937 938 939 940 941 942 943 944 945 946 947 948 949 950 951 952 953 954 955 956 957 958 959 960 961 962 963 964 965 966 967 968 969 970 971 972 973 974 975 976 977 978 979 980 981 982 983 984 985 986 987 988 989 990 991 992 993 994 995 996 997 998 999 1000 1001 1002 1003 1004 1005 1006 1007 1008 1009 1010 1011 1012 1013 1014 1015 1016 1017 1018 1019 1020 1021 1022 1023 1024 1025 1026 1027 1028 1029 1030 1031 1032 1033 1034 1035 1036 1037 1038 1039 1040 1



The equivalent of a Win32 LONG in Clarion.NET is the CLALONG type. Use of LONG in Clarion.NET programs are equivalent to the INT64 .NET data type.

**Example:**

```
Count1 LONG                                !Declare four-byte signed integer
Count2 LONG,OVER(Count1)                  !Declare OVER the four-byte signed integer
Count3 LONG,DIM(4)                        !Declare it an array of 4 longs
Count4 LONG(5)                            !Declare with initial value
Count5 LONG,EXTERNAL                      !Declare as external
Count6 LONG,EXTERNAL,DLL                  !Declare as external in a .DLL
Count7 LONG,NAME('SixCount')             !Declare with external name
ExampleFile FILE,DRIVER('Clarion')       !Declare a file
Record RECORD
Count8 LONG,NAME('Counter')              !Declare with external name
END
END
```

## ULONG (four-byte unsigned integer)

label    **ULONG**(*[initial value]*)    [,DIM( )] [,OVER( )] [,NAME( )] [,EXTERNAL] [,DLL] [,STATIC]  
              [,THREAD] [,AUTO] [,PRIVATE] [,PROTECTED]

**ULONG**      A four-byte unsigned integer.

```
Format:      magnitude
          |.....|
Bits:  31                                0
Range: 0 to 4,294,967,295
```

<i>initial value</i>	A numeric constant. If omitted, the initial value is zero, unless the AUTO attribute is present.
----------------------	--

**DIM** Dimension the variable as an array.

**OVER** Share a memory location with another variable.

**NAME** Specify an alternate, "external" name for the field.

<b>EXTERNAL</b>	Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.
-----------------	--

**DLL** Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.

**STATIC** Specify the variable's memory is permanently allocated.

<b>THREAD</b>	Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the <b>STATIC</b> attribute on Procedure Local data.
---------------	--

**AUTO** Specify the variable has no *initial value*.

<b>PRIVATE</b>	Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.
----------------	---

<b>PROTECTED</b>	Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.
------------------	--

**ULONG** declares a four-byte unsigned integer, using the Intel 8086 long integer format. There is no sign bit in this configuration.

**Example:**

```
Count1 ULONG                                !Declare four-byte unsigned integer
Count2 ULONG,OVER(Count1)                   !Declare OVER four-byte unsigned integer
Count3 ULONG,DIM(4)                         !Declare it an array of 4 unsigned longs
Count4 ULONG(5)                             !Declare with initial value
Count5 ULONG,EXTERNAL                       !Declare as external
Count6 ULONG,EXTERNAL,DLL                   !Declare as external in a .DLL
Count7 ULONG,NAME('SixCount')              !Declare with external name
ExampleFile FILE,DRIVER('Btrieve')         !Declare a file
Record      RECORD
Count8      ULONG,NAME('Counter') !Declare with external name
            END
            END
```

## SIGNED (signed integer)

label **SIGNED**(*[initial value]*) [, **DIM**( )] [, **OVER**( )] [, **NAME**( )] [, **EXTERNAL**] [, **DLL**] [, **STATIC**]  
[, **THREAD**] [, **AUTO**] [, **PRIVATE**] [, **PROTECTED**]

---

<b>SIGNED</b>	A signed integer defined as a LONG.
<i>initial value</i>	A numeric constant. If omitted, the initial value is zero, unless the AUTO attribute is present.
<b>DIM</b>	Dimension the variable as an array.
<b>OVER</b>	Share a memory location with another variable.
<b>NAME</b>	Specify an alternate, "external" name for the field.
<b>EXTERNAL</b>	Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.
<b>DLL</b>	Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.
<b>STATIC</b>	Specify the variable's memory is permanently allocated.
<b>THREAD</b>	Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.
<b>AUTO</b>	Specify the variable has no <i>initial value</i> .
<b>PRIVATE</b>	Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.
<b>PROTECTED</b>	Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.

**SIGNED** declares a signed integer which is a LONG. The SIGNED data type is most useful for prototyping Windows API calls.

**Example:**

```
Count1 SIGNED    !Declares a LONG
```

## UNSIGNED (unsigned integer)

label    **UNSIGNED**(*[initial value]*)    **[DIM( )]** **[OVER( )]** **[NAME( )]** **[EXTERNAL]** **[DLL]** **[STATIC]**  
**[THREAD]** **[AUTO]** **[PRIVATE]** **[PROTECTED]**

<b>UNSIGNED</b>	An unsigned integer which is a LONG.
<i>initial value</i>	A numeric constant. If omitted, the initial value is zero, unless the AUTO attribute is present.
<b>DIM</b>	Dimension the variable as an array.
<b>OVER</b>	Share a memory location with another variable.
<b>NAME</b>	Specify an alternate, "external" name for the field.
<b>EXTERNAL</b>	Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.
<b>DLL</b>	Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.
<b>STATIC</b>	Specify the variable's memory is permanently allocated.
<b>THREAD</b>	Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.
<b>AUTO</b>	Specify the variable has no <i>initial value</i> .
<b>PRIVATE</b>	Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.
<b>PROTECTED</b>	Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.

**UNSIGNED** declares an unsigned integer which is a LONG. This is not actually a data type but an EQUATE defined in EQUATES.CLW.

The UNSIGNED data type is most useful for prototyping Windows API calls which take a LONG (or ULONG) parameter in their 32-bit version.

**Example:**

Count1 UNSIGNED !Declares a LONG

## SREAL (four-byte signed floating point)

label **SREAL**(*[initial value]*) [, **DIM**( )] [, **OVER**( )] [, **NAME**( )] [, **EXTERNAL**] [, **DLL**] [, **STATIC**]  
[, **THREAD**] [, **AUTO**] [, **PRIVATE**] [, **PROTECTED**]

---

**SREAL**      A four-byte floating point number.

Format:	±	exponent	significand
			.....
Bits:	31	30	23 0
Range:	0, ± 1.175494e-38 .. ± 3.402823e+38 (6 significant digits)		

*initial value*      A numeric constant. If omitted, the initial value is zero, unless the **AUTO** attribute is present.

**DIM**      Dimension the variable as an array.

**OVER**      Share a memory location with another variable.

**NAME**      Specify an alternate, "external" name for the field.

**EXTERNAL**      Specify the variable is defined, and its memory is allocated, in an external library. Not valid within **FILE**, **QUEUE**, or **GROUP** declarations.

**DLL**      Specify the variable is defined in a .DLL. This is required in addition to the **EXTERNAL** attribute.

**STATIC**      Specify the variable's memory is permanently allocated.

**THREAD**      Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the **STATIC** attribute on Procedure Local data.

**AUTO**      Specify the variable has no *initial value*.

**PRIVATE**      Specify the variable is not visible outside the module containing the **CLASS** methods. Valid only in a **CLASS**.

**PROTECTED**      Specify the variable is not visible outside base **CLASS** and derived **CLASS** methods. Valid only in a **CLASS**.

**SREAL** declares a four-byte floating point signed numeric variable, using the Intel 8087 short real (single precision) format.



**Example:**

```
Count1 SREAL                                !Declare four-byte signed floating point
Count2 SREAL,OVER(Count1)                   !Declare OVER the four-byte
                                           !signed floating point
Count3 SREAL,DIM(4)                         !Declare it an array of 4 floats
Count4 SREAL(5)                             !Declare with initial value
Count5 SREAL,EXTERNAL                       !Declare as external
Count6 SREAL,EXTERNAL,DLL                   !Declare as external in a .DLL
Count7 SREAL,NAME('SixCount')              !Declare with external name

ExampleFile FILE,DRIVER('Btrieve')         !Declare a file
Record      RECORD
Count8      SREAL,NAME('Counter')           !Declare with external name
           END
           END
```

## REAL (eight-byte signed floating point)

label **REAL**(*[initial value]*) [**DIM**( )] [**OVER**( )] [**NAME**( )] [**EXTERNAL**] [**DLL**] [**STATIC**] [**THREAD**]  
[**AUTO**] [**PRIVATE**] [**PROTECTED**]

---

**REAL**            An eight-byte floating point number.

Format:		±	exponent		significand	
Bits:	63	62	52		0	
Range:	0, ± 2.225073858507201e-308 .. ± 1.79769313496231e+308					
	(15 significant digits)					

*initial value*    A numeric constant. If omitted, the initial value is zero, unless the AUTO attribute is present.

**DIM**            Dimension the variable as an array.

**OVER**           Share a memory location with another variable.

**NAME**           Specify an alternate, "external" name for the field.

**EXTERNAL**      Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.

**DLL**            Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.

**STATIC**         Specify the variable's memory is permanently allocated.

**THREAD**         Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.

**AUTO**            Specify the variable has no *initial value*.

**PRIVATE**        Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.

**PROTECTED**     Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.

**REAL** declares an eight-byte floating point signed numeric variable, using the Intel 8087 long real (double precision) format.

**Example:**

```
Count1 REAL                                !Declare eight-byte signed floating point
Count2 REAL,OVER(Count1)                  !Declare OVER the eight-byte
                                           !signed floating point
Count3 REAL,DIM(4)                        !Declare it an array of 4 reals
Count4 REAL(5)                            !Declare with initial value
Count5 REAL,EXTERNAL                      !Declare as external
Count6 REAL,EXTERNAL,DLL                  !Declare as external in a .DLL
Count7 REAL,NAME('SixCount')             !Declare with external name
ExampleFile FILE,DRIVER('Clarion')       !Declare a file
Record      RECORD
Count8      REAL,NAME('Counter')         !Declare with external name
           END
           END
```

## BFLOAT4 (four-byte signed floating point)

label **BFLOAT4**(*[initial value]*) [, **DIM**( )] [, **OVER**( )] [, **NAME**( )] [, **EXTERNAL**] [, **DLL**] [, **STATIC**]  
[, **THREAD**] [, **AUTO**] [, **PRIVATE**] [, **PROTECTED**]

---

**BFLOAT4**     A four-byte floating point number.

Format:	exponent	±	significand
	.....	.	.....
Bits:	31	23 22	0
Range:	0, ± 5.87747e-39	.. ± 1.70141e+38	(6 significant digits)

*initial value*     A numeric constant. If omitted, the initial value is zero, unless the **AUTO** attribute is present.

**DIM**     Dimension the variable as an array.

**OVER**     Share a memory location with another variable.

**NAME**     Specify an alternate, "external" name for the field.

**EXTERNAL**     Specify the variable is defined, and its memory is allocated, in an external library. Not valid within **FILE**, **QUEUE**, or **GROUP** declarations.

**DLL**     Specify the variable is defined in a .DLL. This is required in addition to the **EXTERNAL** attribute.

**STATIC**     Specify the variable's memory is permanently allocated.

**THREAD**     Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the **STATIC** attribute on Procedure Local data.

**AUTO**     Specify the variable has no *initial value*.

**PRIVATE**     Specify the variable is not visible outside the module containing the **CLASS** methods. Valid only in a **CLASS**.

**PROTECTED**     Specify the variable is not visible outside base **CLASS** and derived **CLASS** methods. Valid only in a **CLASS**.

**BFLOAT4** declares a four-byte floating point signed numeric variable, using the Microsoft BASIC (single precision) format. This data type is normally used for compatibility with existing data since it is internally converted to a **REAL** before all arithmetic operations.

**Example:**

```
Count1 BFLOAT4                                !Declare four-byte signed floating point
Count2 BFLOAT4,OVER(Count1)                   !Declare OVER the four-byte
                                              ! signed floating point
Count3 BFLOAT4,DIM(4)                         !Declare array of 4 single-precision reals
Count4 BFLOAT4(5)                             !Declare with initial value
Count5 BFLOAT4,EXTERNAL                       !Declare as external
Count6 BFLOAT4,EXTERNAL,DLL                   !Declare as external in a .DLL
Count7 BFLOAT4,NAME('SixCount')              !Declare with external name
ExampleFile FILE,DRIVER('Btrieve')           !Declare a file
Record      RECORD
Count8      BFLOAT4,NAME('Counter')           !Declare with external name
              END
              END
```

## BFLOAT8 (eight-byte signed floating point)

label **BFLOAT8**(*[initial value]*) [, **DIM**( )] [, **OVER**( )] [, **NAME**( )] [, **EXTERNAL**] [, **DLL**] [, **STATIC**]  
[, **THREAD**] [, **AUTO**] [, **PRIVATE**] [, **PROTECTED**]

---

**BFLOAT8**      An eight-byte floating point number.

Format:	exponent	±	significand
	.....	.	.....
Bits:	63	55	54 0
Range:	0, ± 5.877471754e-39 .. ± 1.7014118346e+38 (15 significant digits)		

*initial value*      A numeric constant. If omitted, the initial value is zero, unless the **AUTO** attribute is present.

**DIM**              Dimension the variable as an array.

**OVER**             Share a memory location with another variable.

**NAME**            Specify an alternate, "external" name for the field.

**EXTERNAL**       Specify the variable is defined, and its memory is allocated, in an external library. Not valid within **FILE**, **QUEUE**, or **GROUP** declarations.

**DLL**              Specify the variable is defined in a .DLL. This is required in addition to the **EXTERNAL** attribute.

**STATIC**          Specify the variable's memory is permanently allocated.

**THREAD**          Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the **STATIC** attribute on Procedure Local data.

**AUTO**             Specify the variable has no *initial value*.

**PRIVATE**         Specify the variable is not visible outside the module containing the **CLASS** methods. Valid only in a **CLASS**.

**PROTECTED**      Specify the variable is not visible outside base **CLASS** and derived **CLASS** methods. Valid only in a **CLASS**.

**BFLOAT8** declares an eight-byte floating point signed numeric variable, using the Microsoft BASIC (double precision) format. This data type is normally used for compatibility with existing data since it is internally converted to a **REAL** before all arithmetic operations.

**Example:**

```
Count1 BFLOAT8                                !Declare eight-byte signed floating point
Count2 BFLOAT8,OVER(Count1)                   !Declare OVER
Count3 BFLOAT8,DIM(4)                         !Declare it an array of 4 reals
Count4 BFLOAT8(5)                             !Declare with initial value
Count5 BFLOAT8,EXTERNAL                       !Declare as external
Count6 BFLOAT8,EXTERNAL,DLL                   !Declare as external in a .DLL
Count7 BFLOAT8,NAME('SixCount')              !Declare with external name
ExampleFile FILE,DRIVER('Btrieve')           !Declare a file
Record      RECORD
Count8      BFLOAT8,NAME('Counter')           !Declare with external name
            END
            END
```

label **DECIMAL**(*length* [,*places*] [,*initial value*]) [,**DIM**( )] [,**OVER**( )] [,**NAME**( )] [,**EXTERNAL**] [,**DLL**]  
[,**STATIC**] [,**THREAD**] [,**AUTO**] [,**PRIVATE**] [,**PROTECTED**]

```

Format:  ±                               magnitude
        | . | ..... |
Bits: 127 124                                0
Range: -9,999,999,999,999,999,999,999,999,999 to
        +9,999,999,999,999,999,999,999,999,999

```

<b>PRIVATE</b>	Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.
----------------	---



**PROTECTED** Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.

**DECIMAL** declares a variable length packed decimal signed numeric variable. Each byte of a DECIMAL holds two decimal digits (4 bits per digit). The left-most byte holds the sign in its high-order nibble (0 = positive, anything else is negative) and one decimal digit. Therefore, DECIMAL variables always contain a fixed "odd" number of digits (DECIMAL(10) and DECIMAL(11) both use 6 bytes).

**Example:**

```
Count1 DECIMAL(5,0)                !Declare three-byte signed packed decimal
Count2 DECIMAL(5),OVER(Count1)      !Declare OVER the three-byte
                                     !signed packed decimal
Count3 DECIMAL(5,0),DIM(4)          !Declare it an array of 4 decimals
Count4 DECIMAL(5,0,5)               !Declare with initial value
Count5 DECIMAL(5,0),EXTERNAL        !Declare as external
Count6 DECIMAL(5,0),EXTERNAL,DLL    !Declare as external in a .DLL
Count7 DECIMAL(5,0),NAME('SixCount') !Declare with external name

Storage STRING(16)
Count8 DECIMAL(31,0),OVER(Storage)  !Declare with OVER attribute
ExampleFile FILE,DRIVER('TopSpeed') !Declare a file
Record      RECORD
Count9      DECIMAL(5,0),NAME('Counter') !Declare with external name
            END
            END
```

## PDECIMAL (signed packed decimal)

label **PDECIMAL**(*length* [,*places*] [,*initial value*]) [,**DIM**( )] [,**OVER**( )] [,**NAME**( )] [,**EXTERNAL**] [,**DLL**]  
[,**STATIC**] [,**THREAD**] [,**AUTO**] [,**PRIVATE**] [,**PROTECTED**]

---

**PDECIMAL**     A packed decimal floating point number.

<b>Format:</b>		<b>magnitude</b>		<b>±</b>
		.....		.
<b>Bits:</b>	127		4	0
<b>Range:</b>	-9,999,999,999,999,999,999,999,999,999 to +9,999,999,999,999,999,999,999,999,999			

- length*     A required numeric constant containing the total number of decimal digits (integer and fractional portion combined) in the variable. The maximum *length* is 31.
- places*     A numeric constant that fixes the number of decimal digits in the fractional portion (to the right of the decimal point) of the variable. It must be less than or equal to the *length* parameter. If omitted, the variable will be declared as an integer.
- initial value*     A numeric constant. If omitted, the initial value is zero, unless the **AUTO** attribute is present.
- DIM**     Dimension the variable as an array.
- OVER**     Share a memory location with another variable.
- NAME**     Specify an alternate, "external" name for the field.
- EXTERNAL**     Specify the variable is defined, and its memory is allocated, in an external library. Not valid within **FILE**, **QUEUE**, or **GROUP** declarations.
- DLL**     Specify the variable is defined in a .DLL. This is required in addition to the **EXTERNAL** attribute.
- STATIC**     Specify the variable's memory is permanently allocated.
- THREAD**     Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the **STATIC** attribute on Procedure Local data.
- AUTO**     Specify the variable has no *initial value*.
- PRIVATE**     Specify the variable is not visible outside the module containing the **CLASS** methods. Valid only in a **CLASS**.

**PROTECTED** Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.

**PDECIMAL** declares a variable length packed decimal signed numeric variable in the Btrieve and IBM/EBCDIC type of format. Each byte of an PDECIMAL holds two decimal digits (4 bits per digit). The right-most byte holds the sign in its low-order nibble (0Fh or 0Ch = positive, 0Dh = negative) and one decimal digit. Therefore, PDECIMAL variables always contain a fixed "odd" number of digits (PDECIMAL(10) and PDECIMAL(11) both use 6 bytes).

**Example:**

```
Count1 PDECIMAL(5,0)                !Declare three-byte signed packed decimal
Count2 PDECIMAL(5),OVER(Count1)      !Declare OVER the three-byte
                                     ! signed packed decimal
Count3 PDECIMAL(5,0),DIM(4)          !Declare it an array of 4 decimals
Count4 PDECIMAL(5,0,5)               !Declare with initial value
Count5 PDECIMAL(5,0),EXTERNAL        !Declare as external
Count6 PDECIMAL(5,0),EXTERNAL,DLL    !Declare as external in a .DLL
Count7 PDECIMAL(5,0),NAME('SixCount') !Declare with external name
ExampleFile FILE,DRIVER('Btrieve')  !Declare a file
Record      RECORD
Count8      PDECIMAL(5,0),NAME('Counter') !Declare with external name
            END
            END
```

## STRING (fixed-length string)



		<i>length</i>		
label	<b>STRING</b>	(   <i>string constant</i>   )		[, <b>DIM</b> ( )][, <b>OVER</b> ( )][, <b>NAME</b> ( )][, <b>EXTERNAL</b> ][, <b>DLL</b> ][, <b>STATIC</b> ]
		<i>picture</i>		[, <b>THREAD</b> ][, <b>AUTO</b> ][, <b>PRIVATE</b> ][, <b>PROTECTED</b> ]

---

**STRING**      A character string.

**Format:** A fixed number of bytes.  
**Size:** 4MB

<i>length</i>	A numeric constant, variable, or expression that defines the number of bytes in the STRING. String variables are not initialized unless given a <i>string constant</i> .
<i>string constant</i>	The initial value of the STRING. The length of the STRING (in bytes) is set to the length of the <i>string constant</i> .
<i>picture</i>	Used to format the values assigned to the STRING. The length is the number of bytes needed to contain the formatted STRING.
<b>DIM</b>	Dimension the variable as an array.
<b>OVER</b>	Share a memory location with another variable.
<b>NAME</b>	Specify an alternate, "external" name for the field.
<b>EXTERNAL</b>	Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.
<b>DLL</b>	Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.
<b>STATIC</b>	Specify the variable's memory is permanently allocated.
<b>THREAD</b>	Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.
<b>AUTO</b>	Specify the variable has no <i>initial value</i> .
<b>PRIVATE</b>	Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.
<b>PROTECTED</b>	Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.

**STRING** declares a fixed-length character string. The memory assigned to the STRING is initialized to all blanks unless the AUTO attribute is present.

It is now possible to declare STRING types of variable size to the compiler. Restrictions are the same as for variable-size arrays: declarations are available in the procedure or routine local scope only, and all variables used in the expression must be known at the time of the variable's creation. **See Also:** Variable Size Declarations

In addition to its explicit declaration, all STRING variables are also implicitly declared as `STRING(1),DIM(length of string)`. This allows each character in the STRING to be addressed as an array element. If the STRING also has a DIM attribute, this implicit array declaration is the last (optional) dimension of the array (to the right of the explicit dimensions).

You may also directly address multiple characters within a STRING using the "string slicing" technique. This technique performs similar action to the SUB function, but is much more flexible and efficient (but does no bounds checking). It is more flexible because a "string slice" may be used on both the destination and source sides of an assignment statement and the SUB function can only be used as the source. It is more efficient because it takes less memory than individual character assignments or the SUB function.

To take a "slice" of the STRING, the beginning and ending character numbers are separated by a colon (:) and placed in the implicit array dimension position within the square brackets ([]) of the STRING. The position numbers may be integer constants, variables, or expressions. If variables are used, there must be at least one blank space between the variable name and the colon separating the beginning and ending number (to prevent PREFIX confusion).

**Example:**

```

Name          STRING(20)                !Declare 20 byte name field
ArrayString    STRING(5),DIM(20)         !Declare array
Company        STRING('SoftVelocity Corporation') !The software company - 20 bytes
Phone          STRING(@P(###)###-####P)  !Phone number field - 13 bytes
ExampleFile    FILE,DRIVER('Clarion')    !Declare a file
Record         RECORD
NameField      STRING(20),NAME('Name')    !Declare with external name
              END
              END

CODE
NameField = 'Tammi'                      !Assign a value
NameField[5] = 'y'                       ! change fifth letter
NameField[5:6] = 'ie'                    ! and change a "slice"
                                           ! the fifth and sixth letters

ArrayString[1] = 'First'                  !Assign value to first element
ArrayString[1,2] = 'u'                    !Change first element 2nd character
ArrayString[1,2:3] = NameField[5:6]      !Assign slice to slice

```

<b>ASTRING</b>	A reference to a character string.
<i>stringtoken</i>	The initial string token of the ASTRING.
<b>DIM</b>	Dimension the variable as an array.
<b>OVER</b>	The ASTRING reference may share a memory location with another variable.
<b>NAME</b>	Specify an alternate, "external" name for the field.
<b>EXTERNAL</b>	Specify the variable is defined, and its memory is allocated, in an external library.
<b>DLL</b>	Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.
<b>STATIC</b>	Specifies the memory for the ASTRING reference variable is permanently allocated.
<b>THREAD</b>	Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.
<b>AUTO</b>	Specify the variable has no initial string token.
<b>PRIVATE</b>	Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.
<b>PROTECTED</b>	Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.

ASTRINGs are not supported by any of the file drivers.

ASTRINGS may be passed as parameters to procedures by value or by reference. They may also be passed as an untyped value or untyped variable parameters. An ASTRING can be returned from a procedure only as a value.

Proper matching of ASTRING types when used in expressions, procedure parameters, and in queue processing is essential.

Regarding expressions, If one operand of the expression is an ASTRING, the other must also be an ASTRING. If that is not possible, the use of STRING and CSTRING types in expressions is faster and needs far less resources. Every string used as an initial value of ASTRING variables is allocated twice in memory as a minimum.

If the parameter prototype of procedure is declared as ASTRING, the actual parameter receiving the passed value should also be defined as an ASTRING type. Otherwise, the value of the actual parameter is added to the ASTRING's hash table.

#### Example:

In CLASS definition:

```
Match PROCEDURE (ASTRING DocumentToSearch, ASTRING SearchExp), BYTE
```

PROCEDURE definition:

```
FuzzyClass.Match PROCEDURE (ASTRING Doc, ASTRING Query)
```

If a QUEUE has ASTRING fields defined, and the program wants to perform a GET by KEY from this queue, the values of any ASTRING fields used in the key must also be ASTRINGS. Otherwise, the value of the actual parameter is added to the ASTRING's hash table.

#### Example:

```
DbNameQueue QUEUE, TYPE
```

```
FileName ASTRING
```

```
FieldName ASTRING
```

```
Ptr USHORT
```

```
END
```

```
NameQueue &DbNameQueue, PROTECTED
```

```
SELF.NameQueue.FileName = SELF.TriggerQueue.FileName !SELF.TriggerQueue.FileName is ASTRING
```

```
GET (SELF.NameQueue, SELF.NameQueue.Filename)
```

#### More example prototypes:

```
PROC1 (ASTRING a)
```

```
PROC2 (*ASTRING a)
```

```
PROC3 (? a)
```

```
PROC4 (*? a)
```

```
PROC5 (), ASTRING
```

**Additional ASTRING Example:**

```
PROGRAM

MAP

END

FLAG LONG
AS1  ASTRING,OVER(FLAG)
AS2  ASTRING

CODE

AS1 = 'SoftVelocity'    ! storage is allocated for the string 'SoftVelocity'
AS2 = 'SoftVelocity'    ! storage is not allocated again, instead AS1 and
                        ! AS2 share the same reference value.
AS2 = 'Hello'           ! new storage allocated for the new text string
                        ! Hello
AS2 = 'SoftVelocity'    ! No new storage is allocated, the reference for
                        ! AS1 now equals AS2 again

IF FLAG = 0
    MESSAGE('AS1 is NULL')
ELSE
    MESSAGE('AS1 = ' & AS1)
END
```



## CSTRING (fixed-length null terminated string)

```

          | length          |
label  CSTRING  (| string constant |)  [,DIM( )] [,OVER( )] [,NAME( )] [,EXTERNAL] [,DLL]
          | picture        |          [,STATIC] [,THREAD] [,AUTO] [,PRIVATE] [,PROTECTED]

```

**CSTRING**      A character string.

**Format:** A fixed number of bytes.

**Size:** 4MB at design time. Can be extended using NEW at runtime.

*length*            A numeric constant that defines the number of bytes of storage the string will use. This must include a position for the terminating null character. String variables are not initialized unless given a *string constant*.

*string constant*    A string constant containing the initial value of the string. The length of the string is set to the length of the *string constant* plus the terminating null character.

*picture*            The picture token used to format the values assigned to the string. The length of the string is the number of bytes needed to contain the formatted string and the terminating null character.

**DIM**                Dimension the variable as an array.

**OVER**              Share a memory location with another variable.

**NAME**              Specify an alternate, "external" name for the field.

**EXTERNAL**        Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.

**DLL**                Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.

**STATIC**            Specify the variable's memory is permanently allocated.

**THREAD**           Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.

**AUTO**              Specify the variable has no *initial value*.

**PRIVATE**          Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.

**PROTECTED**       Specify the variable is not visible outside base CLASS and derived CLASS

methods. Valid only in a CLASS.

**CSTRING** declares a character string terminated by a null character (ASCII zero). The memory assigned to the CSTRING is initialized to a zero length string unless the AUTO attribute is present.

CSTRING matches the string data type used in the "C" language and the "ZSTRING" data type of the Btrieve Record Manager. Storage and memory requirements are fixed-length, however the terminating null character is placed at the end of the data entered. CSTRING should be used to achieve compatibility with outside files or procedures.

In addition to its explicit declaration, all CSTRINGs are implicitly declared as a STRING(1),DIM(*length of string*). This allows each character in the CSTRING to be addressed as an array element. If the CSTRING also has a DIM attribute, this implicit array declaration is the last (optional) dimension of the array (to the right of the explicit dimensions).

You may also directly address multiple characters within a CSTRING using the "string slicing" technique. This technique performs similar action to the SUB function, but is much more flexible and efficient (but does no bounds checking). It is more flexible because a "string slice" may be used on both the destination and source sides of an assignment statement and the SUB function can only be used as the source. It is more efficient because it takes less memory than individual character assignments or the SUB function.

To take a "slice" of the CSTRING, the beginning and ending character numbers are separated by a colon (:) and placed in the implicit array dimension position within the square brackets ([]) of the CSTRING. The position numbers may be integer constants, variables, or expressions. If variables are used, there must be at least one blank space between the variable name and the colon separating the beginning and ending number (to prevent PREFIX confusion).

Since a CSTRING must be null-terminated, the programmer must be responsible for ensuring that an ASCII zero is placed at the end of the data if the field is only accessed through its array elements or as a "slice" (not as a whole entity). Also, a CSTRING can have "junk" stored after the null terminator. Because of this they do not work well inside GROUPs.

**Example:**

```
Name          CSTRING(21)                !Declare 21 byte field - 20 bytes data
OtherName      CSTRING(21),OVER(Name)     !Declare field over name field
Contact        CSTRING(21),DIM(4)         !Array 21 byte fields - 80 bytes data
Company        CSTRING('SoftVelocity Corporation') !21 byte string - 20 bytes data
Phone          CSTRING(@P(###)###-####P) !Declare 14 bytes - 13 bytes data
ExampleFile    FILE,DRIVER('Btrieve')     !Declare a file
Record         RECORD
NameField      CSTRING(21),NAME('ZstringField') !Declare with external name
              END
              END

CODE
Name = 'Tammi'                !Assign a value
Name[5] = 'y'                 ! then change fifth letter
Name[6] = 's'                 ! then add a letter
Name[7] = '<0>'                 ! and handle null terminator
Name[5:6] = 'ie'              ! and change a "slice"
                              ! -- the fifth and sixth letters

Contact[1] = 'First'          !Assign value to first element
Contact[1,2] = 'u'            !Change first element 2nd character
Contact[1,2:3] = Name[5:6]    !Assign slice to slice
!Example that extends the size of the CSTRING
CS &CSTRING
StringSize      LONG
CODE
StringSize = 0FFFFFFh        !16MB
```

```
CS &= NEW CSTRING(stringSize)
```

## PSTRING (embedded length-byte string)

```

          |  length          |
label  PSTRING  ( |  string constant  | )  [,DIM( )] [,OVER( )] [,NAME( )] [,EXTERNAL] [,DLL]
          |  picture          |  [,STATIC] [,THREAD] [,AUTO] [,PRIVATE] [,PROTECTED]

```

**PSTRING**      A character string.

**Format:** A fixed number of bytes.  
**Size:** 2 to 256 bytes.

*length*      A numeric constant that defines the number of bytes in the string. This must include the length-byte.

*string constant*      A string constant containing the initial value of the string. The length of the string is set to the length of the *string constant* plus the length-byte.

*picture*      The picture token used to format the values assigned to the string. The length of the string is the number of bytes needed to contain the formatted string plus the first position length byte. String variables are not initialized unless given a *string constant*.

**DIM**      Dimension the variable as an array.

**OVER**      Share a memory location with another variable.

**NAME**      Specify an alternate, "external" name for the field.

**EXTERNAL**      Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.

**DLL**      Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.

**STATIC**      Specify the variable's memory is permanently allocated.

**THREAD**      Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.

**AUTO**      Specify the variable has no *initial value*.

**PRIVATE**      Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.

**PROTECTED**      Specify the variable is not visible outside base CLASS and derived CLASS

methods. Valid only in a CLASS.

**PSTRING** declares a character string with a leading length byte included in the number of bytes declared for the string. The memory assigned to the PSTRING is initialized to a zero length string unless the AUTO attribute is present. PSTRING matches the string data type used by the Pascal language and the "LSTRING" data type of the Btrieve Record Manager. Storage and memory requirements are fixed-length, however, the leading length byte will contain the number of characters actually stored. PSTRING is internally converted to a STRING intermediate value for string operations during program execution. PSTRING should be used to achieve compatibility with outside files or procedures.

In addition to its explicit declaration, all PSTRINGS are implicitly declared as a PSTRING(1),DIM(*length of string*). This allows each character in the PSTRING to be addressed as an array element. If the PSTRING also has a DIM attribute, this implicit array declaration is the last (optional) dimension of the array (to the right of the explicit dimensions).

You may also directly address multiple characters within a PSTRING using the "string slicing" technique. This technique performs similar action to the SUB function, but is much more flexible and efficient (but does no bounds checking). It is more flexible because a "string slice" may be used on both the destination and source sides of an assignment statement and the SUB function can only be used as the source. It is more efficient because it takes less memory than individual character assignments or the SUB function. To take a "slice" of the PSTRING, the beginning and ending character numbers are separated by a colon (:) and placed in the implicit array dimension position within the square brackets ([]) of the PSTRING. The position numbers may be integer constants, variables, or expressions. If variables are used, there must be at least one blank space between the variable name and the colon separating the beginning and ending number (to prevent PREFIX confusion).

Since a PSTRING must have a leading length byte, the programmer must be responsible for ensuring that its value is always correct if the field is only accessed through its array elements or as a "slice" (not as a whole entity). The PSTRING's length byte is addressed as element zero (0) of the array (BLOB and PSTRING are the only exceptions in Clarion where an array has a zero element). Therefore, the valid range of array indexes for a PSTRING(30) would be 0 to 29. Also, a PSTRING can have 'junk' stored outside the active portion of the string. Because of this they do not work well inside GROUPS.

**Example:**

```
Name          PSTRING(21)                !Declare 21 byte field - 20 bytes data
OtherName      PSTRING(21),OVER(Name)      !Declare field over name field
Contact        PSTRING(21),DIM(4)          !Array 21 byte fields - 80 bytes data
Company        PSTRING('SoftVelocity Corporation') !21 byte string - 20 bytes data
Phone          PSTRING(@P(###)###-####P)   !Declare 14 bytes - 13 bytes data
ExampleFile    FILE,DRIVER('Btrieve')      !Declare a file
Record         RECORD
NameField      PSTRING(21),NAME('LstringField') !Declare with external name
              END
              END

CODE
Name = 'Tammi'           !Assign a value
Name[5] = 'y'            ! then change fifth letter
Name[6] = 's'            ! then add a letter
Name[0] = '<6>'           ! and handle length byte
Name[5:6] = 'ie'         ! and change a "slice" -- the 5th and 6th letters
Contact[1] = 'First'     !Assign value to first element
Contact[1,2] = 'u'       !Change first element 2nd character
Contact[1,2:3] = Name[5:6] !Assign slice to slice
```

## Implicit String Arrays and String Slicing

In addition to their explicit declaration, all STRING, CSTRING and PSTRING variables have an implicit array declaration of one character strings, dimensioned by the length of the string. This is directly equivalent to declaring a second variable as:

```
StringVar    STRING(10)
StringArray  STRING(1),DIM(SIZE(StringVar)),OVER(StringVar)
```

This implicit array declaration allows each character in the string to be directly addressed as an array element, without the need of the second declaration. The PSTRING's length byte is addressed as element zero (0) of the array, as is the first byte of a BLOB (the only two cases in Clarion Win32 where an array has a zero element).

### Note:

In the Clarion# language, all string arrays are zero-based. See examples below.

If the string also has a DIM attribute, this implicit array declaration is the last (optional) dimension of the array (to the right of the explicit dimensions). The MAXIMUM procedure does not operate on the implicit dimension, you should use SIZE instead.

You may also directly address multiple characters within a string using the "string slicing" technique. This technique performs a similar function to the SUB procedure, but is much more flexible and efficient (but does no bounds checking). It is more flexible because a "string slice" may be used as either the *destination* or *source* sides of an assignment statement, while the SUB procedure can only be used as the source. It is more efficient because it takes less memory than either individual character assignments or the SUB procedure.

To take a "slice" of the string, the beginning and ending character numbers are separated by a colon (:) and placed in the implicit array dimension position within the square brackets ([]) of the string. The position numbers may be integer constants, variables, or expressions (internally computed as LONG base type). If variables are used, there must be at least one blank space between the variable name and the colon separating the beginning and ending number (to prevent PREFIX confusion).

Individual elements may be cleared with the use of the CLEAR statement. For example:

CLEAR( MyString[ n : m ] ) or CLEAR( MyString[ n : m ], 0 ) for clear with spaces ( 20h )

CLEAR( MyString[ n : m ], -1 ) for clear with lowest value ( 00h )

CLEAR( MyString[ n : m ], 1 ) for clear with highest value ( 0FFh )

### Clarion (Win32) Example:

```
Name      STRING(15)
CONTACT    STRING(15),DIM(4)
Five       EQUATE(5)
Six        EQUATE(6)

CODE
Name = 'Tammi'           ! Assign a value
Name[5] = 'y'           ! then change fifth letter
Name[6] = 's'           ! then add a letter
Name[0] = '<6>'          ! and handle length byte if Name was a PSTRING
Name[5:6] = 'ie'        ! and change a "slice" -- the fifth and sixth letters
```

```
Name[Five : Six]           ! need a space between equates and variables
Contact[1] = 'First'       ! Assign value to first element
Contact[1,2] = 'u'         ! Change first element 2nd character
Contact[1,2:3] = Name[5:6] ! Assign slice to first element 2nd & 3rd characters
```

### Clarion# (Clarion.NET) Example:

```
CODE

ns = 'abcdefghijklmnopqrstuvwxy'
cs = ns

! all of the
following are expected, at position zero is the first character
i# = 0
SUB(ns,i#,1) !returns 'a'
SUB(cs,i#,1) !returns 'a'
ns[i#]       !returns 'a' (slice)
cs[i#]       !returns 'a' (slice)
```

### See Also:

STRING  
CSTRING  
PSTRING  
BLOB

## DATE (four-byte date)

label **DATE** [**DIM**( )] [**OVER**( )] [**NAME**( )] [**EXTERNAL**] [**DLL**] [**STATIC**] [**THREAD**] [**AUTO**]  
 [**PRIVATE**] [**PROTECTED**]

**DATE** A four-byte date.

```

Format:      year      mm      dd
             | ..... | .... | .... |
Bits: 31      15      7      0
Range:
year:  1 to 9999
month: 1 to 12
day:   1 to 31

```

- DIM** Dimension the variable as an array.
- OVER** Share a memory location with another variable.
- NAME** Specify an alternate, "external" name for the field.
- EXTERNAL** Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.
- DLL** Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.
- STATIC** Specify the variable's memory is permanently allocated.
- THREAD** Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.
- AUTO** Specify the variable has no *initial value*.
- PRIVATE** Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.
- PROTECTED** Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.

**DATE** declares a four-byte date variable. This format matches the "DATE" field type used by the Btrieve Record Manager. A DATE used in a numeric expression is converted to the number of days elapsed since December 28, 1800 (Clarion Standard Date - usually stored as a LONG). The valid Clarion Standard Date range is January 1, 1801 through December 31, 9999. Using an out-of-range date produces unpredictable results. DATE fields should be used to achieve compatibility with outside files or procedures.

**Example:**

```
DueDate      DATE                !Declare a date field
OtherDate    DATE,OVER(DueDate)  !Declare field over date field
ContactDate  DATE,DIM(4)         !Array of 4 date fields
ExampleFile  FILE,DRIVER('Btrieve') !Declare a file
Record       RECORD
DateRecd     DATE,NAME('DateField') !Declare with external name
            END
            END
```

While a DATE data type has a unique long integer internal D-M-Y format any code using it will automatically convert it to or from a Clarion Standard Date. The only way to obtain the DATE in internal format must be done with a LONG or STRING over the DATE. In the below example code the number 5 is the standard date for Jan, 2 1801.

```
BT_Date  DATE
BT_Raw   LONG,OVER(BT_Date)  !Obtain DATE in internal format
      BT_Date = 5
      Message(Format(BT_Date,@d8-) &' - '& BT_Date &' - '& BT_Raw )
      !displays: 2-Jan-1801 - 5 - 118030594
      !118030594 => 07090102h  0709h => 1801
```

**Additional Example:**

!Extracts date parts w/o multiple calls to MONTH,DAY,YEAR or using FORM AT() and slicing.

```
GetMDY  PROCEDURE(LONG ClaDate, *LONG OutMonth, *LONG OutDay, *LONG Out
Year)
```

```
BTDate  DATE,AUTO
```

```
BT      GROUP,OVER(BTDate)  !Note Little Endian reversal
```

```
Day     BYTE
```

```
Month   BYTE
```

```
Year    USHORT
```

```
      END
```

```
      CODE
```

```
      BTDate = ClaDate ! Convert LONG (Clarion Standard Date) to a Btrieve
date DDMYYYYY
```

```
      OutMonth = BT.Month
```

```
      OutDay   = BT.Day
```

```
      OutYear  = BT.Year
```

```
      RETURN
```

See Also: Standard Date



## TIME (four-byte time)

label **TIME** [**DIM**( )] [**OVER**( )] [**NAME**( )] [**EXTERNAL**] [**DLL**] [**STATIC**] [**THREAD**] [**AUTO**]  
 [**PRIVATE**] [**PROTECTED**]

**TIME** A four-byte time.

```

Format:   hh      mm      ss      hs
          |  ....  |  ....  |  ....  |  ....  |
Bits: 31      23      15      7      0
Range:
hours:      0 to 23
minutes:    0 to 59
seconds:    0 to 59
seconds/100: 0 to 99

```

- DIM** Dimension the variable as an array.
- OVER** Share a memory location with another variable.
- NAME** Specify an alternate, "external" name for the field.
- EXTERNAL** Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.
- DLL** Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.
- STATIC** Specify the variable's memory is permanently allocated.
- THREAD** Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.
- AUTO** Specify the variable has no *initial value*.
- PRIVATE** Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.
- PROTECTED** Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.

**TIME** declares a four byte time variable. This format matches the "TIME" field type used by the Btrieve Record Manager. A TIME used in a numeric expression is converted to the number of hundredths of a second elapsed since midnight (Clarion Standard Time - usually stored as a LONG). TIME fields should be used to achieve compatibility with outside files or procedures.

**Example:**

```
CheckoutTime  TIME                !Declare checkout time field
OtherTime     TIME,OVER(CheckoutTime) !Declare field over time field
ContactTime   TIME,DIM(4)          !Array of 4 time fields
ExampleFile   FILE,DRIVER('Btrieve') !Declare a file
Record        RECORD
TimeRecd      TIME,NAME('TimeField') !Declare with external name
              END
              END
```

While a TIME data type has a unique long integer, the internal format will automatically convert it to or from a Clarion Standard Time.

Here are some example of functions frequently needed. The first is normally done with FORMAT and String functions. The second is done with Multiplication.

```
GetTime PROCEDURE (LONG ClaTime, *LONG OutHour, *LONG OutMin, *LONG OutSec,<*LONG OutHS>)
```

```
BTTime  TIME,AUTO
```

```
BT      GROUP,OVER(BTTime)  !Note Little Endian reversal
```

```
HS      BYTE
```

```
Sec     BYTE
```

```
Min     BYTE
```

```
Hour    BYTE
```

```
      END
```

```
      CODE
```

```
      BTTime = ClaTime ! Convert LONG (Clarion Standard Time) to a Btrieve Time HHSSMMHH with Cla$storebtdate
```

```
      IF ~OMITTED(5) THEN OutHS = BT.HS.
```

```
      OutSec = BT.Sec
```

```
      OutMin = BT.Min
```

```
      OutHour = BT.Hour
```

```
      RETURN
```

```
!-----
```

```
Time PROCEDURE (LONG InHour, LONG InMin, LONG InSec, LONG InHS=0) !LONG
```

```
BTTime  TIME,AUTO
```

```
BT      GROUP,OVER(BTTime)  !Note Little Endian reversal
```

```
HS      BYTE
```

```
Sec     BYTE
```

```
Min     BYTE
```

```
Hour      BYTE
      END
      CODE
      BT.HS   = InHS
      BT.Sec  = InSec
      BT.Min  = InMin
      BT.Hour = InHour
      RETURN BTime !Converts TIME to (Clarion Standard Time)
!-----
Time2 PROCEDURE (LONG InHour, LONG InMin, LONG InSec, LONG InHS=0) !LONG
CTime LONG, AUTO
      CODE
      CTime = InHour * 60 * 6000 + InMin * 6000 + InSec * 100 + InHS
      IF CTime THEN CTime += 1.
      RETURN CTime
```

**See Also:** DATE

Standard Time

## Special Data Types:

### ANY (any simple data type)

label    **ANY** [.DIM( )] [.NAME( )] [.EXTERNAL] [.DLL] [.STATIC] [.THREAD] [.PRIVATE] [.PROTECTED]

---

<b>ANY</b>	A variable that may contain any value (numeric or string) or a reference to any simple data type.
<b>DIM</b>	Dimension the variable as an array.
<b>NAME</b>	Specify an alternate, "external" name for the field.
<b>EXTERNAL</b>	Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.
<b>DLL</b>	Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.
<b>STATIC</b>	Specify the variable's memory is permanently allocated.
<b>THREAD</b>	Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.
<b>PRIVATE</b>	Specify the variable is not visible outside the module containing the CLASS methods. Valid only in a CLASS.
<b>PROTECTED</b>	Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.

**ANY** declares a variable that may contain any value (numeric or string) or a reference to any simple data type. This allows an ANY variable to be used as a "generic" data type. An ANY variable may be declared within a CLASS, GROUP, or QUEUE structure, and may not be declared within a FILE structure. ANY can be named in the USE attribute of any control in a window or report, provided that the ANY contains a reference to a variable rather than a value. (See the rules of reference variables as USE variables).

When an ANY variable is the *destination* of a simple assignment statement (*destination* = *source*), it receives the **value** of the *source* expression. An ANY variable uses REAL as its base type for numeric operations, which can mean loss of precision when assigned DECIMAL values with more than 14 significant digits. When an ANY variable is the *destination* of a reference assignment statement (*destination* &= *source*), it receives a **reference** to the *source* variable. You cannot pass an ANY variable as a variable-parameter (by address) unless the receiving procedure is prototyped to receive an untyped variable parameter (\*?) and the passed ANY contains a reference.

When an ANY variable is declared in a QUEUE structure, there are some special considerations that must be followed. This is due to the internal representation of an ANY and its polymorphic characteristics.

**Use of CLEAR() and reference assignments with QUEUE entries.**

Once an ANY variable in a QUEUE has been assigned a value, another simple assignment statement will assign a new value to the ANY. This means the previous value is replaced by the new value. If the first value has already been added to the QUEUE, then that entry will "point at" a value that no longer exists.

Once an ANY variable in a QUEUE has been reference assigned a variable (AnyVar &= SomeVariable), another reference assignment statement will assign a new variable to the ANY. This means the previous "pointer" is disposed of and replaced by the new "pointer." If the first reference has already been added to the QUEUE, then that entry will "point at" a "pointer" that no longer exists.

In both cases, the QUEUE record (or fields of ANY type only) must be CLEAR()ed before setting new values for the next ADD() or PUT().

In addition, you need to reference assign a NULL to the ANY variable (AnyVar &= NULL), prior to deleting the QUEUE entry, in order to avoid memory leaks.

As explained above, the ANY variable maintains its own data area where it keeps the value or "pointer" to the referenced variable. An assignment of a new value to the ANY variable using the &= operator disposes its previous internal data. The CLEAR(*variable*) statement sets the memory location occupied by the ANY variable to NULL, *without* disposing of its internal data.

**Example:**

```
MyQueue  QUEUE
AnyField  ANY                      !Declare a variable to contain any value
Type      STRING(1)
END

DueDate  DATE                      !Declare a date field

CODE
MyQueue.AnyField = 'SoftVelocity' !Assign a string value
MyQueue.Type = 'S'                !Flag data type
ADD(MyQueue)
CLEAR(MyQueue)                   !Clear the reference
MyQueue.AnyField &= DueDate       !Assign a Reference to a DATE
MyQueue.Type = 'R'               !Flag data type
ADD(MyQueue)
LOOP X# = RECORDS(MyQueue) TO 1 BY -1 !Process the QUEUE
  GET(MyQueue,X#)
  ASSERT (~ERRORCODE())
  CASE MyQueue.Type
    OF 'S'
      DO StringRoutine
    OF 'R'
      DO ReferenceRoutine
  END
MyQueue.AnyField &= NULL          !Reference assign NULL before deleting
DELETE(MyQueue)
ASSERT (~ERRORCODE())
END
```

**Use of ANY in CLASS/GROUP definitions.**

If you do a reference assignment, or assign a value to an ANY that is a member of a CLASS or GROUP, you must clear the reference *before* destroying the class, otherwise the memory allocated by the reference assignment will not be freed.

**Example:**

```
AClass CLASS
AnyVar    ANY,PRIVATE
AMethod  PROCEDURE(FILE f)
Destruct PROCEDURE()
        END

TextFile FILE,DRIVER('ASCII')
        RECORD
Line      STRING(255)
        END
        END

CODE
    AClass.AMethod(TextFile)

AClass.AMethod PROCEDURE(FILE TextFile)
AGroup &GROUP
CODE
    AGroup &= TextFile{PROP:Record}
    SELF.AnyVar &= WHAT(AGroup, 1)

AClass.Destruct PROCEDURE()
CODE
    SELF.AnyVar &= NULL !Without this line the program will leak memory
```



The ANY data type is represented with the special dedicated **Clarion.ClaAny** class.

The ANY data type of Clarion .NET is compatible with the ANY data type of the WIN 32 Clarion.

**Remarks:**

1. Unlike WIN32 Clarion, you can use the type ANY in a NEW statement.
2. You can't assign a reference to array to an ANY variable

**See Also:**

Simple Assignment Statements

Reference Assignment Statements

## LIKE (inherited data type)

*new declaration* **LIKE**(*like declaration*) [,**DIM**( )] [,**OVER**( )] [,**PRE**( )] [,**NAME**( )] [,**EXTERNAL**]  
[,**DLL**][,**STATIC**] [,**THREAD**] [,**BINDABLE**]

---

<b>LIKE</b>	Declares a variable whose data type is inherited from another variable.
<i>new declaration</i>	The label of the new data element declaration.
<i>like declaration</i>	The label of the data element declaration whose definition will be used. This may be any simple data type, or a reference to any simple data type (except &STRING), or the label of a GROUP or QUEUE structure.
<b>DIM</b>	Dimension the variables into an array.
<b>OVER</b>	Share a memory location with another variable or structure.
<b>PRE</b>	Declare a label prefix for variables within the <i>new declaration</i> structure (if the <i>like declaration</i> is a complex data structure). This is not required, since you may use the <i>new declaration</i> in the Field Qualification syntax to directly reference any member of the new structure.
<b>NAME</b>	Specify an alternate, "external" name for the field.
<b>EXTERNAL</b>	Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.
<b>DLL</b>	Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.
<b>STATIC</b>	Specify the variable's memory is permanently allocated.
<b>THREAD</b>	Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.
<b>BINDABLE</b>	Specify all variables in the group may be used in dynamic expressions.

**LIKE** tells the compiler to define the *new declaration* using the same definition as the *like declaration*, including all attributes. If the original *like declaration* changes, so does the *new declaration*.

The *new declaration* may use the DIM and OVER attributes. If the *like declaration* has a DIM attribute, the *new declaration* is already an array. If a further DIM attribute is added to the *new declaration*, the array is further dimensioned.

The PRE and NAME attributes may be used, if appropriate. If the *like declaration* already has these attributes, the *new declaration* will inherit them and compiler errors can occur. To correct this, specify a PRE or NAME attribute on the *new declaration* to override the inherited attribute.

If the *like declaration* names a QUEUE, LIKE does not create a new QUEUE, because the *like declaration* is simply treated as a GROUP. The *like declaration* QUEUE is converted to a *new declaration* GROUP. The same is true if the *like declaration* is a RECORD structure. Similarly, if the *like declaration* is a MEMO, the *new declaration* becomes a STRING of the maximum size of the MEMO.

You may use LIKE to create a new instance of a CLASS. However, simply declaring the new instance by naming the CLASS as the data type performs an implicit LIKE. For either type of instance declaration, the DIM, OVER, PRE, and NAME attributes are invalid; all other attributes are valid for a CLASS instance declaration.

**Example:**

```
Amount      REAL                !Define a field
QTDAmount   LIKE (Amount)       !Use same definition
YTDAmount   LIKE (QTDAmount)    !Use same definition again
MonthlyAmts LIKE (Amount),DIM(12) !Use same definition for array, 12 elements
AmtPrPerson LIKE (MonthlyAmts),DIM(10)
                !Use same definition for array of 120 elements (12,10)

Construct GROUP                !Define a group
Field1      LIKE (Amount)      ! Construct.field1 - real
Field2      STRING(10)         ! Construct.field2 - string(10)
                END

NewGroup    LIKE (Construct)    !Define new group, containing
                ! NewGroup.field1 - real
                ! NewGroup.field2 - string(10)

MyQue       QUEUE              !Define a queue
Field1      STRING(10)
Field2      STRING(10)
                END

MyGroup     LIKE (MyQue)        !Define new GROUP, like the QUEUE

AmountFile  FILE,DRIVER('Clarion'),PRE (Amt)
Record      RECORD
Amount      REAL                !Define a field
QTDAmount   LIKE (Amount)       !Use same definition
                END
                END

Animal      CLASS
Feed        PROCEDURE(short amount),VIRTUAL
Die         PROCEDURE
Age         LONG
Weight      LONG
                END
Cat         LIKE (Animal) !New instance of an Animal CLASS
Bird        Animal        !New instance of an Animal CLASS (implicit LIKE)
```

**See Also:**

DIM

OVER

PRE

NAME

Field Qualification



## Implicit Variables

Implicit variables are not declared in data declarations. They are created by the compiler when it first encounters them. Implicit variables are automatically initialized to blank or zero; they do not have to be explicitly assigned values before use. You may always assume that they contain blanks or zero before your program's first assignment to them. Implicit variables are generally used for: array subscripts, true/false switches, intermediate variables in complex calculations, loop counters, etc.

The Clarion language provides three types of implicit variables:

- #      A label terminated by a # names an implicit LONG.
- \$      A label terminated by a \$ names an implicit REAL.
- "      A label terminated by a " names an implicit STRING(32).

Any implicit variable used in the global data declaration area (between the keywords PROGRAM and CODE) is Global data, assigned static memory and visible throughout the program. Any implicit variable used between the keywords MEMBER and PROCEDURE is Module data, assigned static memory and visible only to the procedures defined in the module. Any other implicit variable is Local data, assigned dynamic memory on the program's stack and visible only in the procedure. Implicits used in ROUTINES incur more overhead than those not in ROUTINES, so should be used sparingly, if at all.

Since the compiler dynamically creates implicit variables as they are encountered, there is a danger that problems may arise that can be difficult to trace. This is due to the lack of compile-time error and type checking on implicit variables. For example, if you incorrectly spell the name of a previously used implicit variable, the compiler will not tell you, but will simply create a new implicit variable with the new spelling. When your program checks the value in the original implicit variable, it will be incorrect. Therefore, implicit variables should be used with care and caution, and only within a limited scope (or not at all).

### Example:

```
LOOP Counter# = 1 TO 10                      !Implicit LONG loop counter
  ArrayField[Counter#] = Counter# * 2      !to initialize an array
END
```

```
Address" = CLIP(City) & ', ' & State & ' ' & Zip
!Implicit STRING(32)
```

```
MESSAGE(Address")
!Used to display a temporary value
```

```
Percent$ = ROUND((Quota / Sales),.1) * 100
!Implicit REAL
```

```
MESSAGE(FORMAT(Percent$, @P%<<< .##P))
!Used to display a temporary value
```

### See Also:

Data Declarations and Memory Allocation

## Reference Variables

A reference variable contains a reference to another data declaration (its "target"). You declare a reference variable by prepending an ampersand (&) to the data type of its target (such as, &BYTE, &FILE, &LONG, etc.) or by declaring an ANY variable. Depending upon the target's data type, the reference variable may contain the target's memory address, or a more complex internal data structure (describing the location and type of target data).

### Valid reference variable declarations:

---

&BYTE	&SHORT	&USHORT	&LONG	&ULONG	&DATE	&TIME
&REAL	&SREAL	&BFLOAT8	&BFLOAT4	&DECIMAL	&PDECIMAL	&STRING
&CSTRING	&PSTRING	&GROUP	&QUEUE	&FILE	&KEY	&BLOB
&VIEW	&WINDOW	ANY				

The &STRING, &CSTRING, &PSTRING, &DECIMAL, and &PDECIMAL declarations do not require length parameters, since all the necessary information about the specific target data item is contained in the reference itself. This means a &STRING reference variable may contain a reference to any length STRING variable.

A reference variable declared as &WINDOW can target an APPLICATION, WINDOW, or REPORT structure. References to these structures are internally treated as the same by the Clarion runtime library.

An ANY variable can contain a reference to any of the simple data types, and so, is equivalent to any of the above except &GROUP, &QUEUE, &FILE, &KEY, &BLOB, &VIEW, and &WINDOW.

### Reference Assignment

---

The &= operator executes a reference assignment statement (destination &= source) to assign the *source's* reference to the *destination* reference variable. You may also use a reference assignment statement in conditional expressions.

The NULL built-in variable is used to "un-reference" a reference variable or to detect an "un-referenced" reference variable in a conditional expression.

### Reference Variable Usage

---

The label of a reference variable is syntactically correct every place in executable code where its target is allowed. This means that, any statement that takes the label of a WINDOW as a parameter can also take the label of an &WINDOW reference variable which has been reference-assigned a WINDOW structure.

When used in a code statement, the reference variable is automatically "dereferenced" to supply the statement with the value of its target. The only exception is reference assignment statements, when the reference assigns the reference to the data item it is referencing. For example:

```
Var1      LONG          !Var1 is a LONG
RefVar1 &LONG          !RefVar1 is a reference to a LONG
RefVar2 &LONG          !RefVar2 is also a reference to a LONG
CODE
RefVar1 &= Var1        !RefVar1 now references Var1
RefVar2 &= RefVar1     !RefVar2 now also references Var1
RefVar1 &= NULL        !RefVar1 now references nothing
```

### Reference Variable Declarations

---

Reference variables may not be declared within FILE or VIEW structures, but they may be declared within GROUP, QUEUE, and CLASS structures. Issuing CLEAR(StructureName) for a GROUP, QUEUE, or CLASS structure containing a reference variable is equivalent to reference assigning NULL to the reference variable.

Global references cross thread boundaries, and so, may be used to reference data items in other execution threads.

A reference variable used in any attribute of a control, field, WINDOW or REPORT declaration must receive its value (i.e., a reference to some typed allocated storage) before processing this declaration on enter to the scope where it is declared. For example, if a WINDOW is declared in a procedure, the reference variable can be declared and receive its value before entry into the procedure, or be declared in the same procedure before the WINDOW and receive its value in the constructor of some class declared before the WINDOW.

### Named QUEUE and CLASS References

In addition to the data types listed above, you may also have references to "named" QUEUES (&QueueName) and to named CLASSES (&ClassName). This allows you to use references to pass "named group" parameters, which allow the receiving procedure access to the component fields of the named structure.

A reference to a named QUEUE or CLASS may be a "forward reference." That is, the named QUEUE or CLASS does not have to have been declared previous to the reference variable declaration which "points at" it. However, the forward reference must be resolved before the reference variable can be used. In the case where the reference variable is contained within a CLASS declaration, the forward reference must be resolved before the object is instantiated, else the reference will be blank and unusable.

There are several advantages to using forward references. You can have a QUEUE of object references which each contains a reference to a QUEUE of object references which each contains a reference to a QUEUE of object references ... For example, you could create a queue of siblings within a CLASS structure like this:

```
FamilyQ      QUEUE
Sibling      &FamilyClass    !A forward reference
END

FamilyClass CLASS
Family      &FamilyQ      !
END
```

Another advantage is the ability to truly "hide" the targets of PRIVATE references in CLASS declarations. For example:

```
!An include file (MyFile.inc) contains:
WidgetManager CLASS,TYPE
WidgetList      &WidgetQ,PRIVATE !
DoSomething      PROCEDURE
END

!Another file (MyFile.CLW) contains:
MEMBER('MyApp')
INCLUDE('MyFile.INC')

WidgetQ      QUEUE,TYPE
Widget      STRING(40)
WidgetNumber LONG
END

MyWidget      WidgetManager !Actual instantiation must follow
                                ! forward reference resolution
MyWidget.DoSomething PROCEDURE
CODE
SELF.WidgetList &= NEW(WidgetQ) !Valid code
SELF.WidgetList.Widget = 'Widget One'
SELF.WidgetList.WidgetNumber = 1
```

```
ADD (SELF.WidgetList)
```

In this example, references to SELF.WidgetList are valid only within the MyFile.CLW file.

#### Example:

```
App1  APPLICATION('Hello')
      END
```

```
App2  APPLICATION('Buenos Dias')
      END
```

```
AppRef &WINDOW  !Reference to an APPLICATION, WINDOW, or REPORT
```

```
Animal  CLASS
Feed    PROCEDURE (SHORT amount),VIRTUAL
Die     PROCEDURE
Age     LONG
Weight  LONG
      END
```

```
Carnivore CLASS (Animal),TYPE
Feed      PROCEDURE (Animal)
      END
```

```
Cat     CLASS (Carnivore)
Feed    PROCEDURE (SHORT amount),VIRTUAL
Potty   BYTE
      END
```

```
Bird     Animal          !Instance of an Animal CLASS
AnimalRef &Animal        !Reference to an Animal CLASS
```

```
CODE
IF CTL:Language = 'Spanish' !If spanish language user
  AppRef &= App2            ! reference spanish application frame
ELSE
  AppRef &= App1            ! else reference english application frame
END
OPEN (AppRef)              !Open the referenced application frame window

IF SomeCondition
  AnimalRef &= Cat          !Reference the Cat
ELSE
  AnimalRef &= Bird         !Reference the Bird
END
AnimalRef.Feed(10)         !Feed whatever is referenced
```

#### Note:

In Clarion.NET, we have removed the requirement to use & to declare a reference to an object in the data section. See the New in Clarion# topic for more information.

**See Also:** Reference Assignment Statements, CLASS, GROUP, QUEUE, ANY

## Data Declarations and Memory Allocation

### Global, Local, Static, and Dynamic

Data declarations automatically allocate memory to store the data values. Global, Local, Static, and Dynamic are terms that describe types of memory allocation.

The terms "Global" and "Local" refer to the visibility of data (also known as its "scope"):

- "Global" means the data is visible to all procedures in the program.
- "Local" means the data has limited visibility. This may be limited to one PROCEDURE or ROUTINE, or limited to a specific set of procedures in a single source module.

The terms "Static" and "Dynamic" refer to the persistence of the data's memory allocation:

- "Static" means the data is allocated memory that is not released until the entire program is finished executing.
- "Dynamic" means the data is allocated memory at run time. Data declared locally for the PROCEDURE or ROUTINE is allocated on the stack of the thread called to that PROCEDURE or ROUTINE. The stack memory allocated for such data is released on returning to the caller.
- "Dynamic" also means that data is allocated by the program in the heap with the use of an explicit NEW, or implicitly, by some runtime library statements (assignment to ANY variables, ADDing to a QUEUE, etc.). Memory blocks allocated in the heap exist until their explicit releasing: DISPOSE for NEWed variables, FREE or DELETE for QUEUEs, etc.

## Data Declaration Sections

There are four general areas where data can be declared in a Clarion program:

- In the PROGRAM module, after the keyword PROGRAM and before the CODE statement. This is the **Global data** section.
- In a MEMBER module, after the keyword MEMBER and before the first PROCEDURE statement. This is the **Module data** section.
- In a PROCEDURE, after the keyword PROCEDURE and before the CODE statement. This is the **Local data** section.
- In a ROUTINE, after the keyword DATA and before the CODE statement. This is the **Routine Local data** section.

**Global data** is visible to executable statements and expressions in every PROCEDURE in the PROGRAM. Global data is always in scope. Global data is allocated Static memory and is available to every PROCEDURE in the PROGRAM.

**Module data** is visible only to the set of PROCEDURES contained in the MEMBER module. It may be passed as a parameter to PROCEDURES in other MEMBER modules, if required. Module data first comes into scope when any PROCEDURE in the MODULE is called. Module data is also allocated Static memory.

**Local data** is visible only within the PROCEDURE in which it is declared, or any Local Derived Methods declared within the PROCEDURE. Local data comes into scope when the PROCEDURE is called and goes out of scope when a RETURN statement (explicit or implicit) executes. It may be passed as a parameter to any other PROCEDURE. Local data is allocated Dynamic memory. The memory is allocated on the program's stack for variables smaller than the stack threshold (5K default), otherwise they are automatically placed onto the heap. This can be overridden by using the STATIC attribute, making its value persistent between calls to the procedure. FILE declarations are always allocated static memory (on the heap), even when declared in a Local Data section.

Dynamic memory allocation for Local data allows a PROCEDURE to be truly recursive, receiving a new copy of its local variables each time it is called.

**Routine Local data** is visible only within the ROUTINE in which it is declared. It may be passed as a parameter to any PROCEDURE. Routine Local data comes into scope when the ROUTINE is called and goes out of scope when an EXIT statement (explicit or implicit) executes. Routine Local data is allocated Dynamic memory. The memory is allocated on the program's stack for variables smaller than the stack threshold (5K default), otherwise they are automatically placed onto the heap. A ROUTINE has its own name scope, so the labels used for Routine Local data may duplicate variable names used in other ROUTINES or even the procedure containing the ROUTINE. Variables declared in a ROUTINE may not have the STATIC or THREAD attributes.

### See Also:

PROGRAM

MEMBER

PROCEDURE

CLASS

PROCEDURE Prototypes

STATIC

THREAD

## Variable Size Declarations

It is now possible to declare variables of STRING-like and DECIMAL/PDECIMAL types of variable size to the compiler.

Restrictions are the same as for variable-size arrays (see below): declarations are available in the procedure or routine local scope only, and all variables used in the expression must be known at the time of the variable's creation.

### Example:

```

PROGRAM

MAP
  TestProc (LONG)
END

CODE
  TestProc(200) !can also be an initialized variable

TestProc    PROCEDURE (LONG VarLength)

VarString   STRING (VarLength)

CODE
  VarString = 'String of up to 200 characters'
```

### Variable-size arrays

Consider the following example:

```

VariableArray ROUTINE

  DATA

  Element      LONG(100)                !assign number of elements
  DynArray     CSTRING(100),DIM(Element) !declare a variable length array

  CODE

  !process DynArray
```

There are 3 restrictions when using this technique:

- 1) The dimensioned variable (*Element*) must be locally declared in the respective PROCEDURE or ROUTINE data section and have no STATIC, THREAD or EXTERNAL attributes applied.
- 2) The dimensioned variable can not be a field component of any compound structure (GROUP, QUEUE, CLASS, RECORD)
- 3) All variables used in dimension expressions must be initialized at the moment of array initialization, i.e., they must be declared with an initial value before the array declaration, or they must be declared in outer scope and receive a value before the call to the PROCEDURE or ROUTINE, or they can be a parameter of the PROCEDURE.

## NEW (allocate heap memory)

*reference* &= **NEW**( *datatype* )

---

<i>reference</i>	The label of a reference variable that matches the <i>datatype</i> .
<b>NEW</b>	Creates a new instance of the <i>datatype</i> on the heap.
<i>datatype</i>	The label of a previously declared CLASS or QUEUE structure, or any simple data type declaration. This may contain a variable as the parameter of the data type to allow truly dynamic declarations.

The **NEW** statement creates a new instance of the *datatype* on the heap. NEW is only valid on the *source* side of a reference assignment statement. Memory allocated by NEW is automatically initialized to blank or zero when allocated, and must be explicitly de-allocated with the DISPOSE statement (else you'll create a "memory leak").

The use of parentheses around the *datatype* is optional.

**Example for WIN32 based code:**

```
StringRef &STRING           !A reference to any STRING variable
LongRef  &LONG              !A reference to any LONG variable

Animal CLASS
Feed     PROCEDURE(short amount)
Weight   LONG
        END
AnimalRef &Animal           !A reference to any Animal CLASS

NameQ QUEUE
Name     STRING(30)
        END
QueRef   &NameQ             !A reference to any QUEUE with only a STRING(30)

CODE
AnimalRef &= NEW(Animal)    !Create new instance of an Animal class

QueRef &= NEW(NameQ)        !Create new instance of a NameQ QUEUE

StringRef &= NEW(STRING(50)) !Create new STRING(50) variable

X# = 35                     !Assign 35 to a variable and then
StringRef &= NEW(STRING(X#)) !use that variable to Create a new STRING(35)

LongRef &= NEW(LONG)        !Create new LONG variable
```

---

The following information below applies **ONLY** to the Clarion# language.





## **Clarion# - NEW as Operator or Modifier**

In Clarion#, the **NEW** keyword can be used as an operator or as a modifier.

### **NEW Operator**

The **NEW** operator is used to create objects and invoke constructors, for example:

```
MyClass  Class1
CODE
    MyClass = NEW Class1()
```

If the **NEW** operator fails to allocate memory, it throws the "OutOfMemory" exception.

### **NEW Modifier**

Use the **NEW** modifier to explicitly hide a member inherited from a base class. To hide an inherited member, declare it in the derived class using the same name and signature, and then apply the **NEW** modifier to the declaration.

Consider the following class:

```
MyBaseClass CLASS, PUBLIC
X            LONG, PUBLIC
Invoke      PROCEDURE ()
            END
```

Declaring a method with the name *Invoke* in a derived class and using the **NEW** modifier will hide the *Invoke* method in the base class.

For example:

```
MyDerivedClass CLASS (MyBaseClass) , PUBLIC
X            LONG, PUBLIC
Invoke      PROCEDURE () , PUBLIC, NEW
            END
```

It is an error to use both **NEW** and **DERIVED** on the same member. Using the **NEW** modifier in a declaration that does not hide an inherited member generates a warning.

## **Clarion# - NEW as Operator in Expression**

Clarion# supports the syntax implemented in Clarion 6.0. But, in Clarion# you can also use **NEW** as an operator in any expression.

**Example:**

```

C CLASS
T  PROCEDURE (LONG) , LONG
  END

CODE

I# = (NEW C) .T(3)

```

## **Clarion# - Creating arrays with NEW**

In Clarion#, it is now possible to dynamically create arrays with optional initializers. The syntax of this type of operator is as follows:

Variant without initializers:

```
NEW < elementType >[dim1,...,dimN]
```

Variant with initializers:

```
NEW < elementType >[,...][initdim1elem1, initdim1elem2,...,initdim1elemN]
```

**Example:**

```

Arr BYTE[,]
CODE
Arr &= NEW BYTE[,]{{1,2},{4,5},{6,7}} !creates an array of dim(3,2)
                                     !and initializes the elements

```

**See Also:** DISPOSE

## DISPOSE (de-allocate heap memory)

**DISPOSE**( *reference* )

**DISPOSE**      De-allocates heap memory previously allocated by a NEW statement.

*reference*      The label of a reference variable previously used in a reference assignment with the NEW statement. This *reference* may be NULL and no ill effects will occur.

The **DISPOSE** statement de-allocates the heap memory previously allocated by a NEW statement. If DISPOSE is not called, the memory is not returned to the operating system for re-use (creating a "memory leak"). However, if you DISPOSE of a *reference* that is still in use (such as a QUEUE being displayed in a LIST control) you will quite likely cause a GPF that will be very difficult to track down.

DISPOSE(SELF) is a legal statement to de-allocate the current object instance. However, if used, it must be the last statement in the procedure, or any following references to the object will cause problems.

There is a way to pass a &STRING reference to a procedure in a way that it can be disposed in that procedure. Although a \*STRING cannot be disposed, consider the following code:

```
MyProc  PROCEDURE (*STRING S)
Ref &STRING,AUTO
CODE
Ref &= S
DISPOSE (Ref)
```

The Parameter/result of \*STRING type can be considered as a read only &STRING value: you can change the string it points to but you can't set it to reference to another string. DISPOSE sets the reference passed to it as a parameter to NULL and hence \*STRING parameters and

results can't be DISPOSEd directly but assigning their reference to a reference variable gives a solution. This is also true for any other data type.



In WIN 32 Clarion (e.g., Clarion 6/7) **DISPOSE** is used to explicitly de-allocate memory allocated by NEW statement. In Clarion .NET DISPOSE doesn't free memory, but the destructor (DESTRUCT/Dispose method) of the corresponding class that is executed.

### Example:

```
StringRef &STRING            !A reference to any STRING variable

Animal CLASS,TYPE
Feed      PROCEDURE(short amount),VIRTUAL
Weight    LONG
```

```
        END
AnimalRef &Animal          !A reference to any Animal CLASS

NameQ  QUEUE
Name   STRING(30)
      END
QueRef &NameQ              !A reference to any QUEUE with only a STRING(30)

CODE
AnimalRef &= NEW(Animal) !Create new instance of an Animal class
DISPOSE(AnimalRef)      !De-allocate the Animal

QueRef &= NEW(NameQ)      !Create new instance of a NameQ QUEUE
DISPOSE(QueRef)          !De-allocate the queue

StringRef &= NEW(STRING(50)) !Create new STRING(50) variable
DISPOSE(StringRef)        !De-allocate the STRING(50)
```

### See Also:

NEW

## Picture Tokens

Picture tokens provide a masking format for displaying and editing variables. There are seven types of picture tokens: numeric and currency, scientific notation, string, date, time, pattern, and key-in template.

- Numeric and Currency Pictures

- Scientific Notation Pictures

- String Pictures

- Date Pictures

- Time Pictures

- Pattern Pictures

- Key-in Template Pictures

## Numeric and Currency Pictures

**@N** [*currency*] [*sign*] [*fill*] *size* [*grouping*] [*places*] [*sign*] [*currency*] [**B**]

---

<b>@N</b>	All numeric and currency pictures begin with @N.
<i>currency</i>	Either a dollar sign (\$) or any string constant enclosed in tildes (~). When it precedes the <i>sign</i> indicator and there is no <i>fill</i> indicator, the <i>currency</i> symbol "floats" to the left of the high order digit. If there is a <i>fill</i> indicator, the <i>currency</i> symbol remains fixed in the left-most position. If the <i>currency</i> indicator follows the <i>size</i> and <i>grouping</i> , it appears at the end of the number displayed.
<i>sign</i>	Specifies the display format for negative numbers. If a hyphen ( - ) precedes the <i>fill</i> and <i>size</i> indicators, negative numbers will display with a leading minus sign. If a hyphen follows the <i>size</i> , <i>places</i> , and <i>currency</i> indicators, negative numbers will display with a trailing minus sign. If parentheses are placed in both positions, negative numbers will be displayed enclosed in parentheses. To prevent ambiguity, a trailing minus <i>sign</i> should always have <i>grouping</i> specified.
<i>fill</i>	Specifies leading zeros, spaces, or asterisks (*) in any leading zero positions, and suppresses default <i>grouping</i> . If the <i>fill</i> is omitted, leading zeros are suppressed.  0 (zero) Produces leading zeroes  _ (underscore) Produces leading spaces  * (asterisk) Produces leading asterisks
<i>size</i>	The <i>size</i> is required to specify the total number of significant digits to display, including the number of digits in the <i>places</i> indicator and any formatting characters.
<i>grouping</i>	A <i>grouping</i> symbol, other than a comma (the default), can appear right of the <i>size</i> indicator to specify a three digit group separator.  . (period) Produces periods  _ (underscore) Produces spaces
<i>places</i>	Specifies the decimal separator symbol and the number of decimal digits. The number of decimal digits must be less than the <i>size</i> . The decimal separator may be a period (.), grave accent ( ` ) (produces periods <i>grouping</i> unless overridden), or the letter "v" (used only for STRING field storage declarations--not for display).  . (period) Produces a period  ` (grave accent) Produces a comma

**v** Produces no decimal separator

**B** Specifies blank display whenever its value is zero.

The numeric and currency pictures format numeric values for screen display or in reports. If the value is greater than the maximum value the picture can display, a string of pound signs (#) is displayed.

**Example:**

<u>Numeric</u>	<u>Result</u>	<u>Format</u>
@N9	4,550,000	Nine digits, group with commas (default)
@N_9B	4550000	Nine digits, no grouping, leading blanks if zero
@N09	004550000	Nine digits, leading zero
@N*9	***45,000	Nine digits, asterisk fill, group with commas
@N9_	4 550 000	Nine digits, group with spaces
@N9.	4.550.000	Nine digits, group with periods

<u>Decimal</u>	<u>Result</u>	<u>Format</u>
@N9.2	4,550.75	Two decimal places, period decimal separator
@N_9.2B	4550.75	Two decimal places, period decimal separator, no grouping, blank if zero
@N_9`2	4550,75	Two decimal places, comma decimal separator
@N9.`2	4.550,75	Comma decimal separator, group with periods
@N9_`2	4 550,75	Comma decimal separator, group with spaces

<u>Signed</u>	<u>Result</u>	<u>Format</u>
@N-9.2B	-2,347.25	Leading minus sign, blank if zero
@N9.2-	2,347.25-	Trailing minus sign
@N(10.2)	(2,347.25)	Enclosed in parens when negative

**Dollar**

<u>Currency</u>	<u>Result</u>	<u>Format</u>
@N\$9.2B	\$2,347.25	Leading dollar sign, blank if zero
@N\$10.2-	\$2,347.25-	Leading dollar sign, trailing minus when negative
@N\$(11.2)	\$(2,347.25)	Leading dollar sign, in parens when negative

**International**

<u>Currency</u>	<u>Result</u>	<u>Format</u>
@N12_`2~ F~	1 5430,50 F	France
@N~L. ~12`	L. 1.430.050	Italy
@N~£~12.2	£1,240.50	United Kingdom
@N~kr~12`2	kr1.430,50	Norway
@N~DM~12`2	DM1.430,50	Germany
@N12_`2~ mk~	1 430,50 mk	Finland
@N12`2~ kr~	1.430,50 kr	Sweden

**Storage-Only Pictures:**

```
Variable1 STRING(@N_6v2)           !Declare as 6 bytes stored without decimal
CODE
Variable1 = 1234.56                 !Assign value, stores '123456' in file
MESSAGE (FORMAT(Variable1,@N_7.2)) !Display with decimal point: '1234.56'
```

## Scientific Notation Pictures

@Emsn[B]

---

<b>@E</b>	All scientific notation pictures begin with @E (or @e).
<b>m</b>	Determines the total number of characters in the format provided by the picture.
<b>s</b>	Specifies the decimal separation character, and the grouping character when the <b>n</b> value is greater than 3.  .(period)                      period and comma  .. (period period)              period and period  ' (grave accent)                comma and period  _(underscore period)          period and space
<b>n</b>	Indicates the number of digits that appear to the left of the decimal point.
<b>B</b>	Specifies that the format displays as blank when the value is zero.

The scientific notation picture formats very large or very small numbers. The format is a decimal number raised by a power of ten. These pictures are intended to be used as display only, not intended for editing.

**Example:**

<u>Picture</u>	<u>Value</u>	<u>Result</u>
@E9.0	1,967,865	.20E+007
@E12.1	1,967,865	1.9679E+006
@E12.1B	0	
@E12.1	-1,967,865	-1.9679E+006
@E12.1	.000000032	3.2000E-008
@E15_.4	1,967,865	1 967.865E+003



## String Pictures

*@Slength*

---

**@S**            All string pictures begin with @S.

*length*        Determines the number of characters in the picture format.

A string picture describes an unformatted string of a specific *length*.

**Example:**

**Name** `STRING(@S20)`    !A 20 character string field

## Date Pictures

**@Dn [s] [direction [range] ] [B]**

---

<b>@D</b>	All date pictures begin with @D.
<b>n</b>	Determines the date picture format. Date picture formats range from 1 through 18. A leading zero (0) indicates a zero-filled day or month.
<b>s</b>	A separation character between the month, day, and year components. If omitted, the slash ( / ) appears.  . (period)                      Produces periods  ` (grave accent)              Produces commas  - (hyphen)                      Produces hyphens  _ (underscore)                Produces spaces
<i>direction</i>	A right or left angle bracket (> or <) that specifies the "Intellidate" direction (> indicates future, < indicates past) for the <i>range</i> parameter. Valid only on ENTRY date pictures with two-digit years.
<i>range</i>	An integer constant in the range of zero (0) to ninety-nine (99) that specifies the "Intellidate" century for the <i>direction</i> parameter. Valid only on ENTRY date pictures with two-digit years. If omitted, the default value is 80.
<b>B</b>	Specifies that the format displays as blank when the value is zero.

Dates may be stored in numeric variables (usually LONG), a DATE field (for Btrieve compatibility), or in a STRING declared with a date picture. A date stored in a numeric variable is called a "Clarion Standard Date." The stored value is the number of days since December 28, 1800. The date picture token converts the value into one of the date formats.

The century for dates in any picture with a two-digit year is resolved using "Intellidate" logic. Date pictures that do not specify *direction* and *range* parameters assume the date falls in the range of the next 19 or previous 80 years. The *direction* and *range* parameters allow you to change this default. The *direction* parameter specifies whether the *range* specifies the future or past value. The opposite *direction* then receives the opposite value (100-*range*) so that any two-digit year results in the correct century.

For example, the picture @D1>60 specifies using the appropriate century for each year 60 years in the future and 39 years in the past. If the current year is 1996, when the user enters "5/01/40," the date is in the year 2040, and when the user enters "5/01/60," the date is in the year 1960.

For those date pictures which contain month names, the actual names are customizable in an Environment file (.ENV). See the Internationalization section for more information.

**Example:**

<u>Picture</u>	<u>Format</u>	<u>Result</u>
@D1	mm/dd/yy	10/31/59
@D1>40	mm/dd/yy	10/31/59
@D01	mm/dd/yy	01/01/95
@D2	mm/dd/yyyy	10/31/1959
@D3	mmm dd,yyyy	OCT 31,1959
@D4	mmmmmmmmmm dd, yyyy	October 31, 1959
@D5	dd/mm/yy	31/10/59
@D6	dd/mm/yyyy	31/10/1959
@D7	dd mmm yy	31 OCT 59
@D8	dd mmm yyyy	31 OCT 1959
@D9	yy/mm/dd	59/10/31
@D10	yyyy/mm/dd	1959/10/31
@D11	yyymmdd	591031
@D12	yyyymmdd	19591031
@D13	mm/yy	10/59
@D14	mm/yyyy	10/1959
@D15	yy/mm	59/10
@D16	yyyy/mm	1959/10
@D17		Windows Control Panel setting for Short Date
@D18		Windows Control Panel setting for Long Date
Alternate separators		
@D1.	mm.dd.yy	Period separator
@D2-	mm-dd-yyyy	Dash separator
@D5_	dd mm yy	Underscore produces space separator
@D6`	dd,mm,yyyy	Grave accent produces comma separator

**See Also:**

Standard Date

FORMAT

DEFORMAT

Environment Files

## Time Pictures

**@Tn[s][B]**

---

- @T** All time pictures begin with **@T**.
- n** Determines the time picture format. Time picture formats range from 1 through 8. A leading zero (0) indicates zero-filled hours.
- s** A separation character. By default, colon ( : ) characters appear between the hour, minute, and second components of certain time picture formats. The following **s** indicators provide an alternate separation character for these formats.
- |                  |                  |
|------------------|------------------|
| . (period)       | Produces periods |
| ' (grave accent) | Produces commas  |
| - (hyphen)       | Produces hyphens |
| _ (underscore)   | Produces spaces  |
- B** Specifies that the format displays as blank when the value is zero.

Times may be stored in a numeric variable (usually a LONG), a TIME field (for Btrieve compatibility), or in a STRING declared with a time picture. A time stored in a numeric variable is called a "Standard Time." The stored value is the number of hundredths of a second since midnight. The picture token converts the value to one of the eight time formats.

For those time pictures which contain string data, the actual strings are customizable in an Environment file (.ENV). See the Internationalization section for more information.

**Example:**

<u>Picture</u>	<u>Format</u>	<u>Result</u>
@T1	hh:mm	17:30
@T2	hhmm	1730
@T3	hh:mmXM	5:30PM
@T03	hh:mmXM	05:30PM
@T4	hh:mm:ss	17:30:00
@T5	hhmmss	173000
@T6	hh:mm:ssXM	5:30:00PM
@T7		Windows Control Panel setting for Short Time
@T8		Windows Control Panel setting for Long Time

**Alternate separators**

@T1.	hh.mm	Period separator
@T1-	hh-mm	Dash separator
@T3_	hh mmXM	Underscore produces space separator
@T4'	hh,mm,ss	Grave accent produces comma separator

**See Also:** Standard Time, FORMAT, DEFORMAT, Environment Files

## Pattern Pictures

**@P[<][#][x]P[B]**

---

<b>@P</b>	All pattern pictures begin with the @P delimiter and end with the P delimiter. The case of the delimiters must be the same.
<b>&lt;</b>	Specifies an integer position that is blank for leading zeroes.
<b>#</b>	Specifies an integer position.
<b>X</b>	Represents optional display characters. These characters appear in the final result string.
<b>P</b>	All pattern pictures must end with P. If a lower case @p delimiter is used, the ending P delimiter must also be lower case.
<b>B</b>	Specifies that the format displays as blank when the value is zero.

Pattern pictures contain optional integer positions and optional edit characters. Only the integer positions will be stored. Any character other than < or # is considered an edit character which will appear in the formatted picture string. The @P and P delimiters are case sensitive. Therefore, an upper case "P" can be included as an edit character if the delimiters are both lower case "p" and vice versa.

Pattern pictures do not recognize decimal points, in order to permit the period to be used as an edit character. Therefore, the value formatted by a pattern picture should be an integer. If a floating point value is formatted by a pattern picture, only the integer portion of the number will appear in the result.

### Example:

<u>Picture</u>	<u>Value</u>	<u>Result</u>
@P###-##-####P	215846377	215-84-6377
@P<#/#/#/##P	103159	10/31/59
@P(###)###-####P	3057854555	(305) 785-4555
@P###/###-####P	7854555	000/785-4555
@p<#:##PMp	530	5:30PM
@P<# ' <# "P	506	5' 6"
@P<#1b. <#oz.P	902	91b. 2oz.
@P4##A-#P	112	411A-2
@PA##.C#P	312.45	A31.C2

## Key-in Template Pictures

**@K[@][#][<][x][\][?][^][\_][|][K][B]**

---

<b>@K</b>	All key-in template pictures begin with the @K delimiter and end with the K delimiter. The case of the delimiters must be the same.
<b>@</b>	Specifies only uppercase and lowercase alphabetic characters.
<b>#</b>	Specifies an integer 0 through 9.
<b>&lt;</b>	Specifies an integer that is blank for high order zeros.
<b>x</b>	Represents optional constant display characters (any displayable character). These characters appear in the final result string.
<b>\</b>	Indicates the following character is a display character. This allows you to include any of the picture formatting characters (@, #, <, \, ?, ^, _,  ) within the string as a display character.
<b>?</b>	Specifies any character may be placed in this position.
<b>^</b>	Specifies only uppercase alphabetic characters in this position.
<b>_</b>	Underscore specifies only lowercase alphabetic characters in this position.
<b> </b>	Allows the operator to "stop here" if there are no more characters to input. Only the data entered and any display characters up to that point will be in the string result.
<b>K</b>	All key-in template pictures must end with K. If a lower case @k delimiter is used, the ending K delimiter must also be lower case.
<b>B</b>	Specifies that the format displays as blank when the value is zero.

Key-in pictures may contain integer positions ( # < ), alphabet character positions ( @ ^ \_ ), any character positions ( ? ), and display characters. Any character other than a formatting indicator is considered a display character, which appears in the formatted picture string. The @K and K delimiters are case sensitive. Therefore, an upper case "K" may be included as a display character if the delimiters are both lower case "k" and vice versa.

Key-in pictures are used specifically with STRING, PSTRING, and CSTRING fields to allow custom field editing control and validation. Using a key-in picture containing any of the alphabet indicators ( @ ^ \_ ) on a numeric entry field produces unpredictable results.

Using the Insert typing mode for a key-in picture could produce unpredictable results. Therefore, key-in pictures always receive data entry in Overwrite mode, even if the INS attribute is present.

**Example:**

<u>Picture</u>	<u>Value Entered</u>	<u>Result String</u>
@K###-##-####K	215846377	215-84-6377
@K##### -####K	33064	33064
@K##### -####K	330643597	33064-3597
@K<# ^^^ ##K	10AUG59	10 AUG 59
@K(###)@@@-##\@##K	305abc4555	(305)abc-45@55
@K###/?##-####K	7854555	000/785-4555
@k<# :##^Mk	530P	5:30PM
@K<# ' <#"K	506	5' 6"
@K4#_#A-#K	1g12	41g1A-2





## 4 - Entity Declarations

### Complex Data Structures:

#### GROUP (compound data structure)

```
label  GROUP( [ group ] )      [,PRE( )] [,DIM( )] [,OVER( )] [,NAME( )] [,EXTERNAL] [,DLL] [,STATIC]
                                     [,THREAD] [,BINDABLE] [, TYPE] [,PRIVATE] [,PROTECTED]
```

*declarations*

**END**

---

<b>GROUP</b>	A compound data structure.
<i>group</i>	The label of a previously declared GROUP or QUEUE structure from which it will inherit its structure. This may be a GROUP or QUEUE with the TYPE attribute.
<b>PRE</b>	Declare a label prefix for variables within the structure. Not valid on a GROUP within a FILE structure.
<b>DIM</b>	Dimension the variables into an array.
<b>OVER</b>	Share a memory location with another variable or structure.
<b>NAME</b>	Specify an alternate, "external" name for the field.
<b>EXTERNAL</b>	Specify the variable is defined, and its memory is allocated, in an external library. Not valid within FILE, QUEUE, or GROUP declarations.
<b>DLL</b>	Specify the variable is defined in a .DLL. This is required in addition to the EXTERNAL attribute.
<b>STATIC</b>	Specify the variable's memory is permanently allocated.
<b>THREAD</b>	Specify memory for the variable is allocated once for each execution thread. Also implicitly adds the STATIC attribute on Procedure Local data.
<b>BINDABLE</b>	Specify all variables in the group may be used in dynamic expressions.
<b>TYPE</b>	Specify the GROUP is a type definition for GROUPs passed as parameters.
<b>PRIVATE</b>	Specify the GROUP and all the component fields of the GROUP are not visible outside the module containing the CLASS methods. Valid only in a CLASS.
<b>PROTECTED</b>	Specify the variable is not visible outside base CLASS and derived CLASS methods. Valid only in a CLASS.
<i>declarations</i>	Multiple consecutive variable declarations.

A **GROUP** structure allows multiple variable declarations to be referenced by a single label. It may be used to dimension a set of variables, or to assign or compare sets of variables in a single statement. In large complicated programs, a GROUP structure is helpful for keeping sets of related data organized. A GROUP must be terminated by a period or the END statement.

The structure of a GROUP declared with the *group* parameter begins with the same structure as the named *group*; the GROUP inherits the fields of the named *group*. The GROUP may also contain its own *declarations* that follow the inherited fields. If the group parameter names a QUEUE or RECORD structure, only the fields are inherited and not the functionality implied by the QUEUE or RECORD.

When referenced in a statement or expression, a GROUP is treated as a STRING composed of all the variables within the structure. A GROUP structure may be nested within another data structure, such as a RECORD or another GROUP.

Because of their internal storage format, numeric variables (other than DECIMAL) declared in a group do not collate properly when treated as strings. For this reason, building a KEY on a GROUP that contains numeric variables may produce an unexpected collating sequence.

A GROUP with the BINDABLE attribute makes all the variables within the GROUP available for use in a dynamic expression. The contents of each variable's NAME attribute is the logical name used in the dynamic expression. If no NAME attribute is present, the label of the variable (including prefix) is used. Space is allocated in the .EXE for the names of all of the variables in the structure. This creates a larger program that uses more memory than it normally would. Therefore, the BINDABLE attribute should only be used when a large proportion of the constituent fields are going to be used.

A GROUP with the TYPE attribute is not allocated any memory; it is only a type definition for GROUPs that are passed as parameters to PROCEDURES. This allows the receiving procedure to directly address component fields in the passed GROUP. The parameter declaration on the PROCEDURE statement can instantiate a local prefix for the passed GROUP as it names the passed GROUP for the procedure, however this is not necessary if you use the Field Qualification syntax instead of prefixes. For example, PROCEDURE(LOC:PassedGroup) declares the procedure uses the LOC: prefix (along with the individual field names used in the type definition) to directly address component fields of the GROUP passed as the parameter.

The data elements of a GROUP with the DIM attribute (a structured array) are referenced using standard Field Qualification syntax with each subscript specified at the GROUP level at which it is dimensioned.

The WHAT and WHERE procedures allow access to the fields by their relative position within the GROUP structure.

**Example:**

```

      PROGRAM
PassGroup  GROUP,TYPE                !Type-definition for passed GROUP parameters
F1         STRING(20)                ! first field
F2         STRING(1)                 ! middle field
F3         STRING(20)                ! last field
      END

      MAP
      MyProc1(PassGroup)              !Passes a GROUP defined the same as PassGroup
      END

NameGroup  GROUP                     !Name group
First     STRING(20)                 ! first name
Middle    STRING(1)                 ! middle initial
Last      STRING(20)                 ! last name
      END                             !End group declaration

NameGroup2 GROUP(PassGroup)          !Group that inherits PassGroup's fields
      ! resulting in NameGroup2.F1, NameGroup2.F2,
      ! and NameGroup2.F3
      END                             ! fields declared in this group

DateTimeGrp GROUP,DIM(10)            !Date/time array
Date      LONG                      ! Referenced as DateTimeGrp[1].Date
StartStopTime LONG,DIM(2)            ! Referenced as DateTimeGrp[1].Time[1]
      END                             !End group declaration

FileNames GROUP,BINDABLE             !Bindable group
FileName  STRING(8),NAME('FILE')     !Dynamic name: FILE
Dot       STRING('.')                !Dynamic name: Dot
Extension STRING(3),NAME('EXT')      !Dynamic name: EXT
      END

      CODE
      MyProc1(NameGroup)              !Call proc passing NameGroup as parameter
      MyProc1(NameGroup2)            !Call proc passing NameGroup2 as parameter

MyProc1  PROCEDURE(PassedGroup)      !Proc to receive GROUP parameter
LocalVar STRING(20)
      CODE
      LocalVar = PassedGroup.F1       !Assign value in the first field to LocalVar
      !from passed parameter

```

**See Also:**

Field Qualification

WHAT

WHERE

WHO

ISGROUP

HOWMANY

## CLASS (object declaration)




```
label  CLASS( [ parentclass ] )      [,EXTERNAL] [,IMPLEMENTS] [,DLL( )] [,STATIC] [,THREAD] [,BINDABLE]
                                           [,MODULE( )] [, LINK( )] [, TYPE] [, DIM(dimension)] [,NETCLASS] [,PARTIAL]

      [ data members and
        methods ]

      END
```

---

<b>CLASS</b>	An object containing <i>data members</i> and <i>methods</i> that operate on the data.
<i>parentclass</i>	The label of a previously declared CLASS structure whose data and methods the new CLASS inherits. This may be a CLASS with the TYPE attribute.
<b>EXTERNAL</b>	Specify the object is defined, and its memory is allocated, in an external library.
<b>IMPLEMENTS</b>	Specify an INTERFACE for the CLASS. This adds additional methods to the implementation of the CLASS.
<b>DLL</b>	Specify the object is defined in a .DLL. This is required in addition to the EXTERNAL attribute.
<b>STATIC</b>	Specify the <i>data members</i> ' memory is permanently allocated.
<b>THREAD</b>	Specify memory for all class variables are allocated once for each execution thread. Also causes Constructors and Destructors to be called on thread start and exit.
<b>BINDABLE</b>	Specify all variables in the class may be used in dynamic expressions.
<b>MODULE</b>	Specify the source code module containing the CLASS's member PROCEDURE definitions. This serves the same function as the MODULE structure within a MAP structure. If omitted, the member PROCEDURE definitions must all be in the same source code module containing the CLASS declaration.
<b>LINK</b>	Specify the source code module containing the CLASS's member PROCEDURE definitions is automatically added to the compiler's link list. This eliminates the need to specifically add the file to the project.
<b>TYPE</b>	Specify the CLASS is only a type definition and not also an object instance of the CLASS.
<i>data members and methods</i>	Data declarations and PROCEDURE prototypes. The <i>data members</i> may only be data declarations appropriate to a GROUP structure, and may include references to the same class (recursive classes). The WHAT and WHERE procedures allow access to the <i>data members</i> by their relative position within the CLASS structure.

<b>DIM</b>	Declares a CLASS as an array.
	
<i>dimension</i>	A positive numeric constant which specifies the number of elements in this <i>dimension</i> of the array.
<b>NETCLASS</b>	Switch off the generation of additional Clarion-specific code for the CLASS
	
<b>PARTIAL</b>	Identifies a CLASS definition that is split into more than one physical file
	

A **CLASS** structure declares an object which contains *data members* (properties) and the *methods* (PROCEDURES) that act on that data. A CLASS structure must be terminated by a period or the END statement.

### Derived CLASSES (Inheritance)

A CLASS declared with the *parentclass* parameter creates a *derived class* which inherits all the *data members and methods* of the named *parentclass*. The *derived class* may also contain its own *data members and methods*.

All *data members* explicitly declared in the *derived class* create new variables, and cannot be declared with the same labels as *data members* in the *parentclass*.

Any *method* prototyped in the *derived class* with the same name as a *method* in the *parentclass* overrides the inherited *method* if both have the same parameter lists. If the two *methods* have different parameter lists, they create polymorphic functions in the *derived class* that must obey the rules of Procedure Overloading.

### Object Properties (Encapsulation)

Each instance of a CLASS, whether a base class, derived class, or a declared instance of either, contains its own set of *data members* (properties) specific to that instance. These may be private or public. However, there is only one copy of any inherited *methods* (residing in the CLASS that declared it) which any instance of that CLASS, or any of its *derived classes*, calls.

The *methods* of a CLASS with the TYPE attribute cannot be directly called (as *ClassName.Method*)--they must be called only as a member *methods* of the objects declared as the type (as *Object.Method*).

### VIRTUAL Methods (Polymorphism)

If there is a *method* prototyped in the CLASS with the same label as a *method* in the *parentclass* with the VIRTUAL attribute, it must also be prototyped with the VIRTUAL attribute in the *derived class*.

The VIRTUAL attribute on both prototypes creates virtual methods that allow the *methods* in a *parentclass* to call the same named VIRTUAL *methods* in the *derived class* to perform functions specific to the *derived class* that the *parentclass* does not know about.

VIRTUAL *methods* in the *derived class* may directly call the *parentclass* method of the same name by prepending PARENT to the method's name. This allows incremental derivation wherein

a *derived class* method may simply call down to the *parentclass* method to perform its functionality, then extend it for the requirements of the *derived class*.

VIRTUAL methods in the derived class may optionally use the DERIVED attribute. This will cause the compiler to verify that a virtual method with the same name and calling signature exists in the base class. This prevents potential issues that can end up defining new virtual methods instead of overriding existing ones.

## Scoping Issues

---

The scope of an object is dependent upon where it is declared. Generally, a declared object comes into scope at the CODE statement following its declaration and goes out of scope at the end of the related executable code section. A dynamically instantiated object (using NEW) shares the scope of the executable code section in which it is instantiated.

An Object declared:

- As Global data is in scope throughout the application.
- As Module data is in scope throughout the module.
- As Local data is in scope only in the procedure, except ...

Methods prototyped in a derived CLASS declaration within a procedure's Local data section are Local Derived Methods and share the declaring procedure's scope for all local data declarations and routines. The methods must be defined within the same source module as the procedure within which the CLASS is declared and must immediately follow the procedure within that source--that is, they must come after any ROUTINES and before any other procedures that may be in the same source module. This means the procedure's Local data declarations and ROUTINES are all visible and can be referenced within these methods.

**Example:**

```
SomeProc      PROCEDURE
MyLocalVar    LONG
MyDerivedClass CLASS(MyClass)  !Derived class with a virtual method
MyProc        PROCEDURE,VIRTUAL
                END

CODE
!SomeProc main executable code goes here
!SomeProc ROUTINES goes here
MyRoutine ROUTINE
!Routine code goes here

!MyDerivedClass methods immediately follow:

MyDerivedClass.MyProc PROCEDURE
CODE
MyLocalVar = 10                !MyLocalVar is still in scope, and available for use
DO MyRoutine                   !MyRoutine is still in scope, and available for use

!Any other procedures in the same module go here, following all
!derived class methods
```

## Instantiation

---

You declare an instance of a CLASS (an object) by simply naming the CLASS as the data type of the new instance, or by executing the NEW procedure in a reference assignment statement to a reference variable for that named CLASS. Either way, the new instance inherits all the *data members and methods* of the CLASS for which it is an instance. All the attributes of a CLASS except MODULE and TYPE are valid on an instance declaration.

If there is no TYPE attribute on the CLASS, the CLASS structure itself declares both the CLASS and an object instance of that CLASS. A CLASS with the TYPE attribute does not create an object instance of the CLASS.

For example, the following CLASS declaration declares the CLASS as a data type and an object of that type:

```
MyClass CLASS           !Both a data type declaration and an object instance
MyField LONG
MyProc PROCEDURE
END
```

while this only declares the CLASS as a data type:

```
MyClass CLASS,TYPE      !Only a data type declaration
MyField LONG
MyProc PROCEDURE
END
```

It is preferable to directly declare object instances as the CLASS data type rather than as a reference to the CLASS. This results in smaller quicker code and does not require you to use NEW and DISPOSE to explicitly create and destroy the object instance. The advantage of using NEW and DISPOSE is explicit control over the lifetime of the object. For example:

```
MyClass CLASS,TYPE
MyField LONG
MyProc PROCEDURE
END
OneClass MyClass          !Declared object instance, smaller and quicker
TwoClass &MyClass          !Object reference, must use New and DISPOSE
CODE
!execute some code here
TwoClass &= NEW(MyClass)   !The lifetime of the object starts here
!execute some code here
DISPOSE(TwoClass)         ! and extends only to here
!execute some code here
```

Another advantage of declaring the object is the ability to declare the object with any of the attributes available for the CLASS declaration itself (except TYPE and MODULE). For instance, you can declare an object with the THREAD attribute, whether the CLASS is declared with THREAD or not.

The lifetime of an object depends on how it is instantiated:

- An object declared in the Global data section or a Module's data section is instantiated at the CODE statement following the PROGRAM statement and de-instantiated when the application terminates.
- A reference to an object is instantiated by the NEW statement, and de-instantiated by the DISPOSE statement.
- An object declared in a procedure's Local data section is instantiated at the CODE statement following the PROCEDURE statement and de-instantiated when a RETURN (implicit or explicit) executes to terminate the procedure.

## Threading

### Note:

The constructors and destructors for threaded classes are called for every thread. Every new thread gets new instances of CLASSES and variables declared at the global or module level with the THREAD attribute. The RTL calls constructors for the threaded classes when the thread is

started and the destructors when the thread is ended. In previous Clarion versions they were called only when the main thread started and ended.

## Data (Property) Initialization

---

The simple data type *data members* of an object are automatically allocated memory and initialized to blank or zero (unless the AUTO attribute is specified) when the object comes into scope. The allocated memory is returned to the operating system when the object goes out of scope.

The reference variable *data members* of an object are not allocated memory and are not initialized when the object comes into scope—you must specifically execute a reference assignment or a NEW statement. These references variables are not automatically cleared when the object goes out of scope, so you must DISPOSE of all NEWed properties before the object goes out of scope.

## Constructors and Destructors

---

A CLASS *method* labelled "Construct" is a constructor method which is automatically invoked when the object comes into scope, immediately after the *data members* of the object are allocated and initialized.



The "Construct" *method* may not receive any parameters and may not use the VIRTUAL attribute. You may explicitly call the "Construct" method in addition to its automatic invocation.



Multiple Constructors with parameters are now supported.

If an object is an instance of a derived CLASS and both the *parentclass* and the derived CLASS contain constructors and the derived CLASS's constructor does not have the REPLACE attribute, then the *parentclass* constructor is automatically invoked at the beginning of the derived CLASS's constructor. If the derived CLASS's constructor does have the REPLACE attribute, then only derived CLASS's constructor is automatically invoked (the derived CLASS's constructor method can explicitly call PARENT.Construct if it needs to).

A CLASS *method* labelled "Destruct" is a destructor method which is automatically invoked when the object leaves scope, immediately before the *data members* of the object are de-allocated. The "Destruct" *method* may not receive any parameters. You may explicitly call the "Destruct" method in addition to its automatic invocation.

If an object is an instance of a derived CLASS and both the *parentclass* and the derived CLASS contain destructors and the derived CLASS's destructor does not have the REPLACE attribute, then the *parentclass* destructor is automatically invoked at the end of the derived CLASS's destructor. If the derived CLASS's destructor does have the REPLACE attribute, then only derived CLASS's destructor is automatically invoked (the derived CLASS's destructor method can explicitly call PARENT.Destruct if it needs to).

## Public, PRIVATE, and PROTECTED (Encapsulation)

---

Public *data members and methods* of a CLASS or derived CLASS are declared without either the PRIVATE or PROTECTED attributes. Public *data members and methods* are visible to all the *methods* of the declaring CLASS, and derived CLASSES, and any code where the object is in scope.



Private *data members and methods* are declared with the PRIVATE attribute. Private *data members and methods* are visible only to the *methods* of the CLASS within which they are declared and any other procedures contained in the same source code module.

Protected *data members and methods* are declared with the PROTECTED attribute. Protected *data members and methods* are visible only to the *methods* of the CLASS within which they are declared, and to the *methods* of any CLASS derived from the CLASS within which they are declared.

## Method Definition

The PROCEDURE definition of a *method* (its executable code, not its prototype) is external to the CLASS structure. The *method's* definition must either prepend the label of the CLASS to the label of the PROCEDURE, or name the CLASS (and label it SELF) as the first (implicit) parameter in the list of parameters passed in to the PROCEDURE.

Remember that on the PROCEDURE definition statement you are assigning labels for use within the method to all the passed parameters, and so, since the CLASS's label is the data type of the implicit first parameter, you must use SELF as the assigned label for the CLASS name parameter. For example, for the following CLASS declaration:

```
MyClass CLASS
MyProc  PROCEDURE (LONG PassedVar)      !The method takes 1 parameter
      END
```

you may define the MyProc PROCEDURE either as:

```
MyClass.MyProc PROCEDURE (LONG PassedVar)      !Prepend the CLASS name to
      CODE                                     !the method's label
```

or as:

```
MyProc PROCEDURE (MyClass SELF, LONG PassedVar) !The CLASS name is the
      CODE
      ! implicit first parameter's data type, labeled SELF
```

## Referencing an Object's properties and methods in your code

You must reference the *data members* of a CLASS using Clarion's Field Qualification syntax. To do this, you prepend the label of the CLASS (if it is an object instance of itself) or the label of an object instance of the CLASS to the label of the *data member*.

For example, for the following CLASS declarations:

```
MyClass CLASS      !Without TYPE, this is also an object instance
MyField  LONG      ! in addition to a class type declaration
MyProc   PROCEDURE
      END
MyClass2 MyClass   !Declare another object instance of MyClass
```

you must reference the two MyField variables from procedures external to the object as:

```
MyClass.MyField = 10  !References the MyClass CLASS declaration's object
MyClass2.MyField = 10 !References the MyClass2 declaration's object
```

You may call the *methods* of a CLASS either using Field Qualification syntax (by prepending the label of the CLASS to the label of the *method*), or by passing the label of the CLASS as the first (implicit) parameter in the list of parameters passed to the PROCEDURE.

For example, for the following CLASS declaration:

```
MyClass CLASS
MyProc  PROCEDURE
      END
```

you may call the MyProc PROCEDURE either as:

```
CODE
MyClass.MyProc
```

or as:

```
CODE
MyProc(MyClass)
```

## **SELF and PARENT**

---

Within the *methods* of a CLASS, the *data members and methods* of the current object's instance are referenced with SELF prepended to their labels instead of the name of the CLASS. This allows the *methods* to generically reference the *data members and methods* of the currently executing instance of the CLASS, without regard to whether it is executing the *parentclass*, a *derived class*, or any instance of either. This is also the mechanism that allows a *parentclass* to call virtual *methods* of a *derived class*.

For example, expanding on the previous example, MyField is referenced within the MyClass.MyProc method as:

```
MyClass.MyProc PROCEDURE
CODE
    SELF.MyField = 10    !Assign to the current object instance's property
```

The *data members and methods* of a *parentclass* can be directly referenced from within the methods of a *derived class* with PARENT prepended to their labels instead of SELF.

For example:

```
MyDerivedClass.MyProc PROCEDURE
CODE
    !execute some code
    PARENT.MyProc        !Call the base class method
    !execute some more code
```

### **Note:**

Methods of derived CLASSES cannot have a formal parameter with the label PARENT, and additionally no method can have an explicit formal parameter with the label SELF.

For example:

```
MyDerivedClass.MyProc PROCEDURE(MyDerivedClass Parent) !Illegal use of Parent
```

The compiler produces a "Redefining system intrinsics" warning for any explicit attempt to declare any data with the labels SELF or PARENT used in this context.

## **Nested CLASSES**



In Clarion .Net nested classes are supported. You can declare a class inside of another class. The only restriction is that only inline methods, properties, and indexers can be used in the nested class. See also INLINE.

### **CLASS Conceptual Example:**

```
PROGRAM
MAP.                                     !MAP required to get BUILTINS.CLW
```

```

OneClass CLASS                                !Base class
NameGroup GROUP                             !Reference as OneClass.NameGroup
First    STRING(20)                          !reference as OneClass.NameGroup.First
Last     STRING(20)                          !reference as OneClass.NameGroup.Last
END
BaseProc PROCEDURE (REAL Parm)               !Declare method prototype
Func     PROCEDURE (REAL Parm),STRING,VIRTUAL !Declare virtual method prototype
Proc     PROCEDURE (REAL Parm),VIRTUAL       !Declare virtual method prototype
END                                           !End CLASS declaration

TwoClass CLASS (OneClass),MODULE('TwoClass.CLW') !Derived from OneClass
Func     PROCEDURE (LONG Parm),STRING         !replaces OneClass.Func
Proc     PROCEDURE (STRING Msg, LONG Parm)    !Functionally overloaded
END

ClassThree CLASS (TwoClass),MODULE('Class3.CLW') !Derived from TwoClass
Func     PROCEDURE (<STRING Msg>, LONG Parm),STRING,VIRTUAL
Proc     PROCEDURE (REAL Parm),VIRTUAL
END

ClassFour ClassThree                         !Declare an instance of ClassThree
ClassFive ClassThree                         !Declare an instance of ClassThree

CODE
OneClass.NameGroup = '|OneClass Method'      !Assign values to each instance of NameGroup
TwoClass.NameGroup = '|TwoClass Method'
ClassThree.NameGroup = '|ClassThree Method'
ClassFour.NameGroup = '|ClassFour Method'
MESSAGE (OneClass.NameGroup & OneClass.Func(1.0)) !Calls OneClass.Func
MESSAGE (TwoClass.NameGroup & TwoClass.Func(2))  !Calls TwoClass.Func

MESSAGE (ClassThree.NameGroup & ClassThree.Func('|Call ClassThree.Func',3.0))
!Calls ClassThree.Func

MESSAGE (ClassFour.NameGroup & ClassFour.Func('|Call ClassFour.Func',4.0))
!Also Calls ClassThree.Func

OneClass.BaseProc(5)                         !BaseProc Calls OneClass.Proc & Func
BaseProc(TwoClass,6)                         !BaseProc Also calls OneClass.Proc & Func
TwoClass.Proc('Second Class',7)             !Calls TwoClass.Proc (overloaded)
ClassThree.BaseProc(8)                       !BaseProc Calls ClassThree.Proc & Func
ClassFour.BaseProc(9)                       !BaseProc Also Calls ClassThree.Proc & Func
Proc(ClassFour,'Fourth Class',10)           !Calls TwoClass.Proc (overloaded)

OneClass.BaseProc PROCEDURE (REAL Parm)      !Definition of OneClass.BaseProc
CODE
MESSAGE (Parm & SELF.NameGroup & '|BaseProc executing|calling SELF.Proc Virtual method')
SELF.Proc(Parm)                             !Calls virtual method
MESSAGE (Parm & SELF.NameGroup & '|BaseProc executing|calling SELF.Func Virtual method')
MESSAGE (SELF.NameGroup & SELF.Func(Parm))    !Calls virtual method

OneClass.Func PROCEDURE (REAL Parm)          !Definition of OneClass.Func
CODE
RETURN ('|Executing OneClass.Func - ' & Parm)

Proc PROCEDURE (OneClass SELF,REAL Parm)     !Definition of OneClass.Proc
CODE
MESSAGE (SELF.NameGroup & '|Executing OneClass.Proc - ' & Parm)

```

```

!The TwoClass.CLW file contains:
MEMBER('ClassPrg')

Func      PROCEDURE(TwoClass SELF, LONG Parm)      !Definition of TwoClass.Func
CODE
RETURN('|Executing TwoClass.Func - ' & Parm)

TwoClass.Proc  PROCEDURE(STRING Msg, LONG Parm)      !Definition of TwoClass.Proc
CODE
MESSAGE(Msg & '|Executing TwoClass.Proc - ' & Parm)

!The Class3.CLW file contains:
MEMBER('ClassPrg')

ClassThree.Func  PROCEDURE(<STRING Msg>, LONG Parm) !Definition of ClassThree.Func
CODE
SELF.Proc(Msg, Parm)                                !Call TwoClass.Proc (overloaded)
RETURN(Msg & '|Executing ClassThree.Func - ' & Parm)

ClassThree.Proc  PROCEDURE(REAL Parm)                !Definition of ClassThree.Proc
CODE
SELF.Proc('Called from ClassThree.Proc', Parm)      !Call TwoClass.Proc
MESSAGE(SELF.NameGroup & '|Executing ClassThree.Proc - ' & Parm)

See Also:
VIRTUAL
DERIVED
Field Qualification
MODULE
PROCEDURE Prototypes
Procedure Overloading
WHAT
WHERE

```

## INTERFACE (class behavior definition)

```
label  INTERFACE ( [ parentinterface ] )  [ , TYPE ] [ , COM ]
      [ methods ]
      END
```

---

**INTERFACE**     A collection of methods to be used by the class that implements the interface.

*parentinterface*     The label of a previously declared INTERFACE structure whose methods are inherited by the new INTERFACE. This may be an INTERFACE with the TYPE attribute.

**TYPE**             Specify the INTERFACE is only a type definition. TYPE is implicit on an INTERFACE but may be explicitly specified.

**COM**                Specify that all methods defined in the interface use a PASCAL calling convention. Used for COM implementation.

*methods*            PROCEDURE prototypes

An **INTERFACE** is a structure, which contains the *methods* (PROCEDURES) that define the behavior to be implemented by a CLASS. It cannot contain any property declarations. All methods defined within the INTERFACE are implicitly virtual. A period or the END statement must terminate an INTERFACE structure.

### Derived INTERFACES (Inheritance)

---

An INTERFACE declared with the *parentinterface* parameter creates a *derived interface* that inherits all the *methods* of the named *parentinterface*. The *derived interface* may also contain its own *methods*.

Any *method* prototyped in the *derived interface* with the same name as a *method* in the *parentinterface* overrides the inherited *method* if both have the same parameter lists. If the two *methods* have different parameter lists, they create polymorphic functions in the *derived interface* that must follow the rules of Procedure Overloading.

See also the Implementing INTERFACES in Derived Classes topic for more detailed information regarding this section.

### VIRTUAL Methods (Polymorphism)

---

All methods in an INTERFACE are implicitly virtual, although the virtual attribute may be explicitly specified for clarity.

### Method Definition

---

The PROCEDURE definition of a *method* (its executable code, not its prototype) is defined by the CLASS that is implementing the INTERFACE. All methods for an interface must be defined in the IMPLEMENTING class.

### Referencing INTERFACE methods in your code

---

You must call the *methods* of an INTERFACE by using dot notation syntax (by prepending the label of the CLASS to the label of the INTERFACE to the label of the *method*).

For example, using the following INTERFACE and CLASS declaration:

```
MyInterface INTERFACE
MyProc      PROCEDURE
            END
MyClass     CLASS, IMPLEMENTS (MyInterface)
            END
```

You may call the MyProc PROCEDURE as:

```
CODE
MyClass.MyInterface.MyProc
```

**See Also:**

IMPLEMENTS

Implementing INTERFACES in Derived Classes

## File Structures

### FILE (declare a data file structure)

```
label    FILE,DRIVER( )    [,CREATE] [,RECLAIM] [,OWNER( )] [,ENCRYPT] [,NAME()] [,PRE(
)]

                                [,BINDABLE] [,TYPE] [,THREAD] [,EXTERNAL] [,DLL] [,OEM]
```

```
label    [INDEX( )]
```

```
label    [KEY( )]
```

```
label    [MEMO( )]
```

```
label    [BLOB]
```

```
[label]  RECORD
```

```
[label]  fields
```

```
END
```

```
END
```

---

*label*            A valid Clarion label for the FILE, INDEX, KEY, MEMO, BLOB, RECORD, or *field* (PROP:Label).

**FILE**            Declares a data file.

**DRIVER**        Specifies the data file type (PROP:DRIVER). The DRIVER attribute is required on all FILE structure declarations.

**CREATE**        Allows the file to be created with the CREATE statement during program execution (PROP:CREATE).

**RECLAIM**      Specifies reuse of deleted record space (PROP:RECLAIM).

**OWNER**        Specifies the password for data encryption (PROP:OWNER).

**ENCRYPT**      Encrypt the data file (PROP:ENCRYPT).

**NAME**        Set DOS filename specification (PROP:NAME).

**PRE**        Declare a label prefix for the structure.

**BINDABLE**    Specify all variables in the RECORD structure may be used in dynamic expressions.

**TYPE**        Specify the FILE is a type definition for FILEs passed as parameters.

<b>THREAD</b>	Specify that memory for the record buffer and file structure is separately allocated for each execution thread, when the file is opened on the thread (PROP:THREAD).
<b>EXTERNAL</b>	Specify the FILE is defined, and the memory for its record buffer is allocated, in an external library.
<b>DLL</b>	Specify the FILE is defined in a .DLL. This is required in addition to the EXTERNAL attribute.
<b>OEM</b>	Specify string data is converted from OEM ASCII to ANSI when read from disk and ANSI to OEM ASCII before writing to disk (PROP:OEM).
<b>INDEX</b>	Declare a static file access index which must be built at run time.
<b>KEY</b>	Declare a dynamically updated file access index.
<b>MEMO</b>	Declare a variable length text field up to 64K in length.
<b>BLOB</b>	Declare a variable length memo field which may be greater than 64K in length.
<b>RECORD</b>	Declare a record structure for the <i>fields</i> . A RECORD structure is required in all FILE structure declarations.

*fields*            Data elements in the RECORD structure.

**FILE** declares a data file structure which is an exact description of a data file residing on disk. The label of the FILE structure is used in file processing statements and procedures to effect operations on the disk file. The FILE structure must be terminated by a period or the END statement.

All attributes of the FILE, KEY, INDEX, MEMO, data declaration statements, and the data types which a FILE may contain, are dependent upon the support of the file driver. Anything in the FILE declaration which is not supported by the file system specified in the DRIVER attribute will cause a file driver error when the FILE is opened. Attribute and/or data type exclusions for a specific file system are listed in each file driver's documentation.

At run-time, the RECORD structure is assigned memory for a data buffer where records from the disk file may be processed by executable statements. This record buffer is always allocated static memory on the heap, even if the FILE is declared in a local data section. A RECORD structure is required in a FILE structure. Memory for a data buffer for any MEMO fields is allocated only when the FILE is opened, and de-allocated when the FILE is closed. The memory for BLOB fields is allocated as needed once the FILE is open.

A FILE with the BINDABLE attribute declares all the variables within the RECORD structure as available for use in a dynamic expression, without requiring a separate BIND statement for each (allowing BIND(file) to enable all the fields in the file). The contents of each variable's NAME attribute is the logical name used in the dynamic expression. If no NAME attribute is present, the label of the variable (including any prefix) is used. Space is allocated in the .EXE for the names of all of the variables in the structure. This creates a larger program that uses more memory than it normally would. Therefore, the BINDABLE attribute should only be used when a large proportion of the constituent fields are going to be used.



A FILE with the THREAD attribute declares a separate record buffer (and file control block) for each execution thread that OPENS the FILE. If the thread does not OPEN the file, no record buffer is allocated for the file on that thread. If a NAME attribute is defined for the file and declared as "STRING, STATIC", it will need to explicitly declare the THREAD attribute if a different file name will be opened on each thread (or PROP:Name may be used to specify the file name).

**Note:**

**Any FILE declared in the local scope of a PROCEDURE or ROUTINE is treated as threaded, regardless of the presence of the THREAD attribute in its declaration.**

A FILE with the EXTERNAL attribute is declared and may be referenced in Clarion code, but is not allocated memory. The memory for the FILE's record buffer is allocated by the external library. This allows a Clarion program access to FILES declared as public in external libraries.

**Related Procedures:**

BUFFER	BUILD	CLOSE	COPY	CREATE	EMPTY	FLUSH	LOCK
NAME	OPEN	PACK	RECORDS	REMOVE	RENAME	SEND	SHARE
STATUS	STREAM	UNLOCK	ADD	APPEND	BOF	BYTES	DELETE
DUPLICATE	EOF	GET	HOLD	NEXT	NOMEMO	POINTER	POSITION
PREVIOUS	PUT	RELEASE	REGET	RESET	SET	SKIP	WATCH

**Examples:**

```
Names FILE, DRIVER('Clarion') !Declare a file structure
Rec   RECORD                  !Required record structure
Name  STRING(20)              !containing one or more data elements
      END
      END                      !End file and record declaration

AsciiFileName  STRING(260), STATIC

AsciiFile FILE, DRIVER('ASCII', '/FILEBUFFERS=8'), NAME(AsciiFileName), |
      PRE(ASC), CREATE, THREAD
Record   RECORD, PRE()
Line     STRING(1024)
      END
      END

Services FILE, DRIVER('TOPSPEED'), RECLAIM, PRE(SER), BINDABLE, CREATE, THREAD
ServiceIDKey  KEY(SER:ServiceID), NOCASE, OPT, PRIMARY
ServTypeDescKey KEY(SER:ServiceType, SER:ServiceDesc), NOCASE, OPT
Notes        MEMO(1000)
Record       RECORD, PRE()
ServiceID     LONG
ServiceDesc   STRING(20)
ServiceType   STRING(12)
Notes        STRING(30)
      END
      END
```

**See Also:** KEY, INDEX, MEMO, BLOB, RECORD, EXTERNAL, THREAD

## INDEX (declare static file access index)

*label*    **INDEX**(*[-/+][field]*,...,*[-/+][field]*) [**NAME**( )] [**NOCASE**] [**OPT**]

---

<i>label</i>	The label of the INDEX (PROP:Label).
<b>INDEX</b>	Declares a static index into the data file.
<b>-/+</b>	The - ( <i>minus sign</i> ) preceding an index component <i>field</i> specifies descending order for that component. If omitted, or + ( <i>plus sign</i> ) the component is sorted in ascending order.
<i>field</i>	The label of a field in the RECORD structure of the FILE in which the INDEX is declared. The <i>field</i> is an index component. Fields declared with the DIM attribute (arrays) may not be used as index components.
<b>NAME</b>	Specifies the disk file specification for the INDEX (PROP:NAME).
<b>OPT</b>	Excludes those records with null values (zero or blank) in all index component fields (PROP:OPT).
<b>NOCASE</b>	Specifies case insensitive sort order (PROP:NOCASE).

**INDEX** declares a "static key" for a FILE structure. An INDEX is updated only by the BUILD statement. It is used to access records in a different logical order than the "physical order" of the file. An INDEX may be used for either sequential file processing or direct random access.

An INDEX always allows duplicate entries. An INDEX may have more than one component *field*. The order of the components determines the sort sequence of the index. The first component is the most general, and the last component is the most specific. Generally, a data file may have up to 255 indexes (and/or keys) and each index may be up to 255 bytes, but the exact numbers are file driver dependent.

An INDEX declared without a *field* creates a "dynamic index." A dynamic index may use any field (or fields) in the RECORD as components (except arrays). The component fields of a dynamic index are defined at run time in the second parameter of the BUILD statement. The same dynamic index declaration may be built and re-built using different components each time.

### Example:

```
Names    FILE, DRIVER('TopSpeed'), PRE(Nam)
NameNdx    INDEX(Nam:Name), NOCASE    !Declare the name index
NbrNdx    INDEX(Nam:Number), OPT    !Declare the number index
DynamicNdx INDEX()    !Declare a dynamic index
Rec    RECORD
Name    STRING(20)
Number    SHORT
          END
          END
```

**See Also:** SET, GET, KEY, BUILD

## KEY (declare dynamic file access index)

*label* **KEY**(*[-/+]**field*,...,*[-/+]**[field]*) [**DUP**] [**NAME**( )] [**NOCASE**] [**OPT**] [**PRIMARY**]

---

<i>label</i>	The label of the KEY (PROP:Label).
<b>KEY</b>	Declares a dynamically maintained index into the data file.
<i>-/+</i>	The - ( <i>minus sign</i> ) preceding a key component <i>field</i> specifies descending order for that component. If omitted, or + ( <i>plus sign</i> ), the component is sorted in ascending order.
<i>field</i>	The label of a field in the RECORD structure of the FILE in which the KEY is declared. The <i>field</i> is a key component. A field declared with the DIM attribute (an array) may not be used as a key component.
<b>NAME</b>	Specifies the disk file specification of the KEY (PROP:NAME).
<b>DUP</b>	Allows multiple records with duplicate values in their key component fields (PROP:DUP).
<b>NOCASE</b>	Specifies case insensitive sort order (PROP:NOCASE).
<b>OPT</b>	Excludes, from the KEY, those records with null (zero or blank) values in all key component fields (PROP:OPT).
<b>PRIMARY</b>	Specifies the KEY is the file's relational primary key (a unique key containing all records in the file) (PROP:PRIMARY).

A **KEY** is an index into the data file which is automatically updated whenever records are added, changed, or deleted. It is used to access records in a different logical order than the "physical order" of the file. A KEY may be used for either sequential file processing or direct random access.

A KEY may have more than one component *field*. The order of the components determines the sort sequence of the key. The first component is the most general, and the last component is the most specific. Generally, a data file may have up to 255 keys (and indexes) and each key may be up to 255 bytes, but the exact numbers are file driver dependent.

### Example:

```
Names      FILE,DRIVER('Clarion'),PRE(Nam)
NameKey    KEY(Nam:Name),NOCASE,DUP      !Declare the name key
NbrKey     KEY(Nam:Number),OPT          !Declare the number key
Rec        RECORD
Name       STRING(20)
Number     SHORT
           END
           END
CODE
Nam:Name = 'Soft Velocity'              !Initialize key field
GET(Names,Nam:NameKey)                  !Get the record
SET(Nam:NbrKey)                          !Set sequential by number
```

## MEMO (declare a text field)

*label*    **MEMO**(*length*) [,**BINARY**] [,**NAME**( )]

---

*label*                      The label of the MEMO (PROP:Label).

**MEMO**                      Declares a fixed-length string which is stored variable-length on disk per record.

*length*                    A numeric constant that determines the maximum number of characters. The maximum range is unlimited in 32-bit applications (dependent on the file driver's MEMO support).

**BINARY**                   Declares the MEMO a storage area for binary data (PROP:BINARY).

**NAME**                      Specifies the disk filename for the MEMO field (PROP:NAME).

**MEMO** declares a fixed-length string field which is stored variable-length on disk. The *length* parameter defines the maximum size of a memo. A MEMO must be declared before the RECORD structure. Memory is allocated for a MEMO field's buffer when the file is opened, and is de-allocated when the file is closed. MEMO fields are usually displayed in TEXT fields in SCREEN and REPORT structures.

Generally, up to 255 MEMO fields may be declared in a FILE structure. The exact size and number of MEMO fields, and their manner of storage on disk, is file driver dependent.

You can also use string slicing operations for MEMOs.

### Example:

```
Names    FILE,DRIVER('Clarion'),PRE(Nam)
NameKey   KEY(Nam:Name)
NbrKey    KEY(Nam:Number)
Notes     MEMO(4800)            !Memo, 4800 bytes
Rec       RECORD
Name       STRING(20)
Number     SHORT
           END
           END
```

**See Also:** String Slicing, PROP:ImageBits

## BLOB (declare a variable-length field)

*label*     **BLOB** [, **BINARY**] [, **NAME**( )]

---

*Label*             The label of the BLOB (PROP:Label).

**BLOB**             Declares a variable-length string stored on disk per record which may be greater than 64K

**BINARY**          Declares the BLOB a storage area for binary data (PROP:BINARY).

**NAME**             Specifies the disk filename for the BLOB field (PROP:NAME).

**BLOB** (Binary Large Object) declares a string field which is completely variable-length and may be greater than 64K in size. A BLOB must be declared before the RECORD structure. Generally, up to 255 BLOB fields may be declared in a FILE structure (the exact number and their manner of storage on disk is file driver dependent).

A BLOB may not be used as a variable--you may not name a BLOB as a control's USE attribute, or directly assign data to or from the BLOB.

You can use PROP:Handle to get the Windows handle to the BLOB entity and assign one BLOB to another: get the handle of both BLOB entities and then assign one BLOB's handle to the other BLOB's handle. A BLOB may not be accessed "as a whole;" you must either use Clarion's string slicing syntax to access the data (unlimited in 32-bit), or PROP:ImageBlob. The individual bytes of data in the BLOB are numbered starting with zero (0), not one (1). PROP:Handle when used with BLOB returns a Windows Global Memory Object Handle for use with low-level Windows GlobalXxxx() API calls that require it.

The SIZE procedure returns the number of bytes contained in the BLOB field for the current record in memory. You can also get (and set) the size of a BLOB using PROP:Size. You may set the size of the BLOB before assigning data to a new BLOB using string slicing, but it is not necessary as the size is automatically set by the string slice operation. You can also use PROP:ImageBlob to store and retrieve graphic images without first setting PROP:Size. It is a good idea to first set PROP:Size to zero (0) before assigning data to a BLOB that has not previously contained data, to eliminate any "junk" leftover from any previously accessed BLOB. When assigning from one BLOB to another using PROP:Handle, you may need to use PROP:Size to adjust the size of the destination BLOB to the size of the source BLOB. PROP:Touched can be used to determine if the contents of the BLOB has changed since it was retrieved from disk.

**Example:**

```
ArchiveFile PROCEDURE
Names    FILE,DRIVER('TopSpeed')
NameKey  KEY(Name)
Notes    BLOB           !Can be larger than 64K
Rec      RECORD
Name     STRING(20)
        END
        END

ArcNames FILE,DRIVER('TopSpeed')
Notes    BLOB
Rec      RECORD
Name     STRING(20)
        END
        END

CODE
SET(Names)
LOOP
    NEXT(Names)
    IF ERRORCODE() THEN BREAK.
    ArcNames.Rec = Names.Rec           !Assign rec data to Archive
    ArcNames.Notes{PROP:Handle} = Names.Notes{PROP:Handle} !Assign BLOB to Archive
    IF ERRORCODE() = 80
        MESSAGE('BLOB size is too large')
        BREAK
    END
    ArcNames.Notes{PROP:Size} = Names.Notes{PROP:Size} ! and adjust the size
    ADD(ArcNames)
END

StoreFileInBlob PROCEDURE !Stores any disk file into a BLOB
DosFileName STRING(260),STATIC
LastRec      LONG
SavPtr       LONG(1) !Start at 1
FileSize     LONG

DosFile      FILE,DRIVER('DOS'),PRE(DOS),NAME(DosFileName)
Record       RECORD
F1           STRING(2000)
            END
            END

BlobStorage  FILE,DRIVER('TopSpeed'),PRE(STO)
File         BLOB,BINARY
Record       RECORD
FileName     STRING(64)
            END
            END

CODE
IF NOT FILEDIALOG('Choose File to Store',DosFileName,,0010b) THEN RETURN.
OPEN(BlobStorage) !Open the BLOB file
STO:FileName = DosFileName ! and store the filename
OPEN(DosFile) !Open the file
FileSize = BYTES(DosFile) !Get size of file
STO:File{PROP:Size} = FileSize ! and set the BLOB to store the file
LastRec = FileSize % SIZE(DOS:Record) !Check for short record at end of file
LOOP INT(FileSize/SIZE(DOS:Record)) TIMES
```

```

GET(DosFile,SavPtr)                !Get each record
ASSERT(NOT ERRORCODE())
STO:File[SavPtr - 1 : SavPtr + SIZE(DOS:Record) - 2] = DOS:Record
                                !String slice data into BLOB
SavPtr += SIZE(DOS:Record)         !Compute next record pointer
END
IF LastRec                        !If short record at end of file
  GET(DosFile,SavPtr)             !Get last record
  ASSERT(BYTES(DosFile) = LastRec) ! size read should match computed size
  STO:File[SavPtr - 1 : SavPtr + LastRec - 2] = DOS:Record
END
ADD(BlobStorage)
ASSERT(NOT ERRORCODE())
CLOSE(DosFile);CLOSE(BlobStorage)

```

**See Also:**

PROP:ImageBlob

PROP:Size

Implicit String Arrays and String Slicing

BLOBtoFILE

FILEtoBLOB

PROP:Handle

PROP:ClientHandle

## RECORD (declare record structure)

```
[label]  RECORD [,PRE( )] [,NAME(
        )]

        fields

        END
```

---

**RECORD**       Declares the beginning of the data structure within the FILE declaration.

*fields*        Multiple variable declarations.

**PRE**         Specify a label prefix for the structure.

**NAME**        Specifies an external name for the RECORD structure.

The **RECORD** statement declares the beginning of the data structure within the FILE declaration. A RECORD structure is required in a FILE declaration. Each *field* is an element of the RECORD structure. The length of a RECORD structure is the sum of the length of its fields. When the label of a RECORD structure is used in an assignment statement, expression, or parameter list, it is treated as a GROUP data type.

At run time, static memory is allocated as a data buffer for the RECORD structure. The *fields* in the record buffer are available whether the file is open or closed.

If the *fields* contain variable declarations with initial values, that initial value is only used to determine the size of the variable, the record buffer is not initialized to the value. For example, a STRING('abc') field declaration creates a three-byte string, but its value is not automatically initialized to 'abc' unless the program's executable code assigns it that value.

Records from the data file on disk are read into the data buffer with the NEXT, PREVIOUS, GET, or REGET statements. Data in the *fields* are processed, then written to the data file as a single RECORD unit by the ADD, APPEND, PUT, or DELETE statements.

The WHAT and WHERE procedures allow access to the *fields* by their relative position within the RECORD structure.

### Example:

```
Names  FILE,DRIVER('Clarion')  !Declare a file structure
Record  RECORD                  ! begin record declaration
Name    STRING(20)              ! declare name field
Number  SHORT                   ! declare number field
        END
        END                      !End file, end record declaration
```

### See Also:

FILE, NEXT, PREVIOUS, GET, REGET, ADD, APPEND, PUT, DELETE, WHAT, WHERE



## Null Data Processing

The concept of a null "value" in a field of a FILE indicates that the user has never entered data into the field. Null actually means "value not known" for the field. This is completely different from a blank or zero value, and makes it possible to detect the difference between a field which has never had data, and a field which has a (true) blank or zero value.

In expressions, null does not equal blank or zero. Therefore, any expression which compares the value of a field from a FILE with another value will always evaluate as unknown if the field is null. This is true even if the value of both elements in the expression are unknown (null) values. For example, the conditional expression `Pre:Field1 = Pre:Field2` will evaluate as true only if both fields contain known values. If both fields are null, the result of the expression is also unknown.

```
Known = Known      !Evaluates as True or False
Known = Unknown    !Evaluates as unknown
Unknown = Unknown  !Evaluates as unknown
Unknown <> 10       !Evaluates as unknown
1 + Unknown        !Evaluates as unknown
```

The only four exceptions to this rule are boolean expressions using OR and AND where only one portion of the entire expression is unknown and the other portion of the expression meets the expression criteria:

```
Unknown OR True    !Evaluates as True
True OR Unknown    !Evaluates as True
Unknown AND False  !Evaluates as False
False AND Unknown !Evaluates as False
```

Support for null "values" in a FILE is entirely dependent upon the file driver. Some file drivers support the null field concept (SQL drivers, for the most part), while others do not. Consult the documentation for the specific file driver to determine whether or not your file system's driver supports nulls.

### See Also:

NULL

SETNULL

SETNULLS

SETNONULL

GETNULLS

## FILE Structure Properties

The following is a short list of properties that are particularly targeted to the components of a FILE structure. See also Runtime FILE and VIEW Properties for a more comprehensive list.

### Multi-File Properties

PROP:BINARY	PROP:Dim	PROP:Label
PROP:NAME	PROP:Over	PROP:Places
PROP:Size	PROP:Type	

### File Properties

PROP:BLOB	PROP:Blobs	PROP:CREATE
PROP:Driver	PROP:DriverString	PROP:ENCRYPT
PROP:Fields	PROP:FileDriver	PROP:KEY
PROP:Keys	PROP:Memos	PROP:OEM
PROP:OWNER	PROP:RECLAIM	PROP:PRE
PROP:THREAD		

### Key Properties

PROP:Ascending	PROP:Components	PROP:DUP
PROP:FIELD	PROP:Fields	PROP:NOCASE
PROP:OPT	PROP:PRIMARY	

The following properties are all elements of a FILE data structure. They describe the attributes, fields, keys, memos, and blobs that may occur within a FILE structure. All these FILE structure properties are READ ONLY except: PROP:NAME (which can be used to change the name of a field in a file), PROP:OWNER, and PROP:DriverString. Assigning values to these properties overrides any values in the relevant declared attributes

Some properties are specific to the FILE and take the label of the FILE structure as the *target*, others are specific to a KEY (or INDEX) and take the label of the KEY (or INDEX) as the *target*, and others are specific to a BLOB and take the label of the BLOB as the *target*. Several

properties are arrays, which take the number of the specific field or key as their element number to identify which field or key to return.

Each field that appears within the RECORD structure receives a positive number. In the RECORD structure, field declarations begin with 1 and increment by 1 for each subsequent field, in the order in which they appear within the RECORD structure. Terminating END statements for GROUP structures are not numbered, as they are not a field declaration.

MEMO and BLOB fields are numbered negatively. MEMO and BLOB declarations begin with -1 and decrement by 1 for each subsequent MEMO and BLOB, in the order in which they appear within the FILE structure.

**See Also:** File Structure Properties Example Program

## **Multi-Use File Structure Properties**

### **PROP:Label**

Returns the label of a declaration statement.

When no array element number is specified and the *target* is the label of a KEY (or INDEX), PROP:Label returns the label of the KEY (or INDEX).

When a positive array element number is specified and the *target* is a FILE, PROP:Label returns the label of the specified field within the RECORD structure.

When a negative array element number is specified and the *target* is a FILE, PROP:Label returns the label of the specified MEMO within the FILE structure.

When a positive array element number is specified and the *target* is a BLOB, PROP:Label returns the label of the specified BLOB.

### **PROP:NAME**

The NAME attribute of the declaration statement.

When no array element number is specified and the *target* is the label of a FILE, PROP:Name returns the contents of the FILE statement's NAME attribute.

When a positive array element number is specified and the *target* is the label of a FILE, PROP:Name returns the NAME attribute of the specified field within the RECORD structure.

When a negative array element number is specified and the *target* is the label of a FILE, PROP:Name returns the NAME attribute of the specified MEMO or BLOB within the FILE structure.

When no array element number is specified and the *target* is the label of a KEY (or INDEX), PROP:Name returns the NAME attribute of the specified KEY (or INDEX).

### **PROP:Size**

An array that returns the declared size of the specified MEMO, STRING, CSTRING, PSTRING, DECIMAL, or PDECIMAL field. The array index is the index of the field within the record structure.

file{PROP:Size, 1} !returns the size of the first field in the file.

file{PROP:Size, -1} !returns the size of the first MEMO.

**PROP:Type**

The data type of the declaration statement.

When no array element number is specified and the *target* is the label of a KEY (or INDEX), PROP:Type returns either "KEY" or "INDEX."

When a positive array element number is specified and the *target* is the label of a FILE, PROP:Type returns a STRING that identifies the data type of the specified field within the RECORD structure.

PROP:Type now returns the type of the MEMO or BLOB. When a negative array element number is specified and the target is the label of a FILE, PROP:Type returns either "MEMO" or "BLOB"

**FILE Statement Properties**

These properties all take the label of a FILE as their *target*.

**PROP:BLOB**

Used with all database drivers that support the creation of BLOB columns:

```
blobRef &= file{PROP:Blob, N}
```

where *N* references the Blob Number to allocate (where a file may have multiple BLOBs)

This property is used to get a reference to a BLOB. *N* can be positive or negative. This will return a reference to the ABS(*N*)'th blob. Where *N* is the *n*'th memo or blob. If *N* is a memo, NULL is returned.

Example:

```
AFile FILE, DRIVER('TOPSPEED'), PRE(EMP)
```

```
M1      MEMO
```

```
B1      BLOB
```

```
RECORD
```

```
..
```

```
ABlob &BLOB
```

```
CODE
```

```
ABlob &= AFile{PROP:Blob, 1} !Returns NULL
```

```
ABlob &= AFile{PROP:Blob, -1}!Returns NULL
```

```
ABlob &= AFile{PROP:Blob, 2} !ABlob is a reference to AFile.B1
```

```
ABlob &= AFile{PROP:Blob, -2}!ABlob is a reference to AFile.B1
```

**PROP:Blobs**

Returns the number of BLOB fields in the FILE structure.

**PROP:CREATE**

The CREATE attribute on the FILE statement. A toggle attribute which contains a null string (") if absent, and '1' if present.

**PROP:DRIVER**

The DRIVER attribute. Returns the file driver of the FILE.

**PROP:DriverString**

A FILE property that returns the second parameter of the DRIVER() attribute of a file.

**PROP:ENCRYPT**

The ENCRYPT attribute on the FILE statement. A toggle attribute which contains a null string (") if absent, and '1' if present.

**PROP:FileDriver**

Valid if you have the Dynamic File Driver system installed. You can now dynamically change the file driver of a statically defined file driver using

```
filelabel{PROP:FileDriver} = ADDRESS(OtherFile).
```

A file with the THREAD attribute will need to have its driver changed every time a thread comes into existence.

**PROP:Key**

An array that returns a reference to the specified KEY or INDEX in the FILE structure. This reference can be used as the source side of a reference assignment statement.

**PROP:Keys**

Returns the number of KEY and INDEX declarations in the FILE structure.

**PROP:Memos**

Returns the number of MEMO fields in the FILE structure.

**PROP:OWNER**

The OWNER attribute on the FILE statement.

**PROP:OEM**

The OEM attribute on the FILE statement. A toggle attribute which contains a null string (") if absent, and '1' if present.

**Prop:PRE**

A Write-Only property for use in the dynamic file system to let you set the prefix of a dynamic file. This makes it easier to create duplicates of existing files without having to put the prefix in the name of all the components of the file.

**PROP:RECLAIM**

The RECLAIM attribute on the FILE statement. A toggle attribute which contains a null string (") if absent, and '1' if present.

## **PROP:THREAD**

The THREAD attribute on the FILE statement. A toggle attribute which contains a null string (") if absent, and '1' if present.

## **Key Properties**

These properties all take the label of a KEY (or INDEX) as their *target*.

## **PROP:Ascending**

An array that returns '1' if the specified key component is in ascending order, and a null string (") if in descending order.

## **PROP:Components**

Returns the number of component fields of a KEY or INDEX.

## **PROP:DUP**

The DUP attribute on the KEY statement. A toggle attribute which contains a null string (") if absent, and '1' if present.

## **PROP:Field**

An array that returns the field number (within the RECORD structure) of the specified component field of a KEY or INDEX. This field number can be used as the array element number for PROP:Label or PROP:Name.

## **PROP:NOCASE**

The NOCASE attribute on the KEY or INDEX statement. A toggle attribute which contains a null string (") if absent, and '1' if present.

## **PROP:OPT**

The OPT attribute on the KEY or INDEX statement. A toggle attribute which contains a null string (") if absent, and '1' if present.

## **PROP:PRIMARY**

The PRIMARY attribute on the KEY statement. A toggle attribute which contains a null string (") if absent, and '1' if present.

## **Field Properties**

The following properties all take the label of a FILE as their *target*.

### **PROP:BINARY**

The BINARY attribute on the MEMO or BLOB statement in the FILE structure. A toggle attribute which contains a null string (") if absent, and '1' if present.

### **PROP:Dim**

An array property of a file that returns the product of the array dimensions specified in the DIM attribute of the specified field. For example, for a field DIM(3,2) PROP:Dim returns 6.

### **PROP:Fields**

There are several forms of the PROP:Fields property:

*keylabel*{PROP:Fields}

Returns the number of fields in the key definition

*filelabel*{PROP:Fields}

Returns the number of fields declared in the RECORD structure.

*filelabel*{PROP:Fields, *n*}

Returns the number of fields in the group. The value of this property is only defined if *file*{PROP:Type, *n*} returns 'GROUP'.

*viewlabel*{PROP:Fields}

Returns the number of fields declared in a VIEW.

*viewlabel*{PROP:Fields, *n*}

Returns the number of fields projected for the *n* file. If *n* is 0 then the total number of projects in the view is returned.

**Prop:Fields Example:**

```
v VIEW(PFile),ORDER('PFile:String1'),FILTER('PFile:ID = 3')
  PROJECT(PFile:ID, PFile:String1)
    JOIN(Child1:Keyname, PFile:ID)          !File Child1 has 4 fields
    JOIN(Child2:Keyname, Child1:ID)         !File Child2 has 4 fields
    JOIN(Child3, 'Child3:LinkField = Child2:ID')
      PROJECT(Child3:String2)
    END
  END
  JOIN(Child2Child1:KeyName, Child1:ID) !File Child2Child1 has 4 fields
END
END
END
```

```
v{PROP:Fields, 0} will return 15
v{PROP:Fields, 1} will return 2
v{PROP:Fields, 2} will return 4
v{PROP:Fields, 3} will return 4
v{PROP:Fields, 4} will return 1
v{PROP:Fields, 5} will return 4
```

See also: JOIN

**PROP:Over**

An array property of a file that returns the field number of the field referenced in the OVER attribute on the specified field.



## Environment Files

An environment file contains internationalization settings for an application. On program initialization, the Clarion run-time library attempts to locate an environment file with the same name and location as your application's program file (*appname*.ENV). If an environment file is not found, the run-time library defaults to standard English/ASCII. You can also use these settings to specify internationalization settings for the Clarion environment by creating a CLARION.ENV file. (the Database Browser uses these settings when displaying data files).

The LOCALE procedure can be used to load environment files at run-time to dynamically change the international settings. LOCALE can also be used to set individual entries. International support is dependent on support in the File Driver (generally for the OEM attribute); consult the File Driver documentation for information on international support in specific drivers.

As a checklist, the following values need to be consistent for any development machine you're using with your target solution:

- A default character set (*charset*): **SYSTEM{PROP:CharSet}** or value of the **CLASYSTEMCHARSET** parameter in the program's ENV file (see below).
- The *charset* parameter of the **FONT** set to a control or Window
- The system locale setting in the *Regional and Language Options* in the Windows Control Panel, e.g., the code page using by Windows for ANSI<->UNICODE strings conversion by default.

---

The following settings can be set in an environment file:

**CLASYSTEMCHARSET=WINDOWS**

or

**CLASYSTEMCHARSET="charset numeric value"**

**CLASYSTEMCHARSET** specifies the value of the system charset. If **CLASYSTEMCHARSET** is not set or it is set to **WINDOWS**, the system charset is equivalent to **CHARSET:ANSI**. Setting this in the .ENV file is equivalent to setting the **SYSTEM{PROP:CharSet}** property.

If you are setting **PROP:CharSet** in your program, you can use the following syntax:

```
SYSTEM{PROP:CharSet} = CHARSET:GREEK
```

However the ENV file does not support symbolic constants like **CHARSET:GREEK**, so in an ENV file you must use the numeric value instead, as in

```
CLASYSTEMCHARSET = 161
```

For a list of all Character Sets and their numeric values, see the PROP:CharSet Help topic.

---

**CLACHARSET=WINDOWS**

**CLACHARSET=OEM**

This determines the character set used by the entries in the .ENV file. **WINDOWS** is the default if this setting is omitted from the environment file. Use the **OEM** setting if you are using a DOS editor to edit the .ENV file, or if it has to be compatible with Clarion for DOS.

Otherwise, specify WINDOWS or omit the entry. This should always be the first setting in the environment file.

---

**CLACOLSEQ=WINDOWS****CLACOLSEQ="*string*"**

Specifies a specific collating sequence for use at run-time. This collating sequence is used for building KEY and INDEX files, as well as for sorting QUEUES and all string/character comparisons.

If the WINDOWS setting is used, then the default collation sequence is defined by Windows' Country setting (in the Control Panel). If this entry is omitted from the environment file, then the default ANSI ordering is used, not the windows default.

Using the WINDOWS setting, the ordering can 'interleave' characters of differing case (AaBbCc ...), so code such as:

```
CASE SomeString[1]
OF 'A' TO 'Z'
```

includes 'b' TO 'z' as well. Use the ISUPPER and ISLOWER procedures in preference to this kind of code if WINDOWS (or other non-default) collation sequences are used.

In addition to the WINDOWS setting, you may specify a *string* of characters (in double quotes) to explicitly define the collation sequence to use. Only those characters that need to have their sort order specified need be included; all other characters not listed remain in their same relative order. For example, if CLACOLSEQ="CA" is specified for the standard English sort (ABCD ...) the resulting sort order is "CBAD." This is a change from the Clarion for DOS versions of this setting that needed exactly 222 characters, but it is backward compatible.

**NOTE: You should always read and write files using the same collation sequence.**

Using a different sequence may result in keys becoming out of order and records becoming inaccessible. Specifying CLACOLSEQ=WINDOWS means that the collation sequence may change if the user changes the Country in Windows' Control Panel. If the collation sequence changes, use BUILD to rebuild the keys in your data files.

---

**CLAAMP=WINDOWS****CLAAMP="*AMstring*", "*PMstring*"**

This specifies the text used to indicate AM or PM as a part of a time display field. The WINDOWS setting specifies use of the AM/PM strings set up in the Windows Control Panel. The *AMstring* and *PMstring* settings are the same as in Clarion for DOS, except that they take notice of the setting of CLACHARSET.

---

**CLAMONTH="Month1", "Month2", ... , "Month12"**

Specifies the text returned by procedures and picture formats involving the month full name.

---

**CLAMON="AbbrevMonth1", "AbbrevMonth2", ... , "AbbrevMonth12"**

Specifies the text returned by procedures and picture formats involving the abbreviated month name.

---

**CLADIGRAPH="*DigraphChar1Char2*, ... "**

This allows *Digraph* characters to collate correctly. A *Digraph* is a single logical character that is a combination of two characters (*Char1* and *Char2*). The *Digraph* is collated as the two characters that combine to create it. They are more common in non-English languages. For

example, with CLADIGRAPH="ÆAe,æae" specified, the word "Jæger" sorts before "Jager" (since "Jae" comes before "Jag").

Multiple *DigraphChar1Char2* combinations may be defined, separated by commas. This setting takes notice of the CLACHARSET setting.

---

### CLACASE=WINDOWS

**CLACASE="UpperString","LowerString"**

Allows you to specify upper and lower case letter pairs.

The WINDOWS setting uses the default upper/lower case pair sets as defined by the Windows Country setting (in the Control Panel). If this entry is omitted from the environment file, then the default ANSI ordering is used, not the windows default.

The *UpperString* and *LowerString* parameters specify a set of uppercase characters and each one's lowercase equivalent. The length of the *UpperString* and *LowerString* parameters must be equal. CLACASE takes notice of the setting of CLACHARSET. ANSI characters less than 127 are not affected.

---

### CLABUTTON="OK","&Yes","&No","&Abort","&Retry","&Ignore",Cancel,"&Help"

This defines the text used by the buttons of the MESSAGE procedure. The text is specified as a list of comma separated strings in the following order: OK, YES, NO, ABORT, RETRY, IGNORE, CANCEL, HELP. The default is as specified above.

---

### CLAMSGerrornumber="ErrorMessage"

This allows run-time error messages to be overridden with translated strings. The *errornumber* is a standard Clarion error code number appended to CLAMSG. *ErrorMessage* is the string value used to replace that error number's default message. For example, CLAMSG2="No File Found" makes "No File Found" the return value of the ERROR() procedure when ERRORCODE() = 2.

---

### CLALFN=OFF

This disables use of long filenames in the program.

---

#### Example:

```
CLACHARSET=WINDOWS
CLACOLSEQ="ÅÄÅÆAaääääääæBbCcCcDdEeEeëëëëFfGgHhIiIiIiIjJkKlLlMmNnNñOöOöóóPpQ
qRrSsStTtUüUüúüüVvWwXxYyZzÿ"
CLAMPMPM="AM", "PM"
CLAMONTH="January", "February", "March", "April", "May", "June", "July", "August",
"September", "October", "November", "December"
CLAMON="Jan", "Feb", "Mar", "Apr", "May", "Jun", "Jul", "Aug", "Sep", "Oct", "Nov", "Dec"
CLADIGRAPH="ÆAe,æae"
CLACASE="ÅÄÅÆÇÑÖÜ", "åäæçéñöü"
CLABUTTON="OK", "&Si", "&No", "&Abortar", "&Volveratratar", "&Ignora", "Cancelar", "&A
yuda"
CLAMSG2="No File Found"
```

See Also: LOCALE

## View Structures:

### VIEW (declare a "virtual" file)

```
label  VIEW(primary file) [,FILTER( )] [,ORDER( )]
        [PROJECT( )]
        [JOIN( )
          [PROJECT( )]
          [JOIN( )
            [PROJECT( )]
          ]
        ]
      END]
    END
  END
```

---

<b>VIEW</b>	Declares a "virtual" file as a composite of related files.
<i>label</i>	The name of the VIEW.
<i>primary file</i>	The label of the primary FILE of the VIEW.
<b>FILTER</b>	Declares an expression used to filter valid records for the VIEW (PROP:FILTER).
<b>ORDER</b>	Declares an expression or list of expressions used to define the sorted order of records for the VIEW (PROP:ORDER or PROP:SQLOrder).
<b>PROJECT</b>	Specifies the fields from the <i>primary file</i> , or the secondary related file specified by a JOIN structure, that the VIEW will retrieve. If omitted, all fields from the file are retrieved.
<b>JOIN</b>	Declares a secondary related file.

**VIEW** declares a "virtual" file as a composite of related data files. The data elements declared in a VIEW do not physically exist in the VIEW, because the VIEW structure is a logical construct. VIEW is a separate method of addressing data physically residing in multiple, related FILE structures. At run-time, the VIEW structure is not assigned memory for a data buffer, so the fields used in the VIEW are placed in their respective FILE structure's record buffer.

A VIEW structure must be explicitly OPENed before use, and all primary and secondary related files used in the VIEW must have been previously OPENed.

Either a SET statement on the VIEW's primary file before the OPEN(view), or a SET(view) statement after the OPEN(view), must be issued to set the VIEW's processing order and starting point, then NEXT(view) or PREVIOUS(view) allow sequential access to the VIEW.

The VIEW data structure is designed for sequential access, but also allows random access using the REGET statement. The REGET statement is also available for VIEW, but only to specify the primary and secondary related file records that should be current in their respective record buffers after the VIEW is CLOSED. If no REGET statement is issued immediately before the CLOSE(view) statement, the primary and secondary related file record buffers are set to no current record.

The processing sequence of the primary and secondary related files is undefined after the VIEW is CLOSED. Therefore, SET or RESET must be used to establish sequential file processing order, if necessary, after closing the VIEW.

The VIEW data structure is designed to facilitate database access on client-server systems. It accomplishes two relational operations at once: the relational "Join" and "Project" operations. On client-server systems, these operations are performed on the file server, and only the result of the operation is sent to the client. This can dramatically improve performance of network applications.

A relational "Join" retrieves data from multiple files, based upon the relationships defined between the files. The JOIN structure in a VIEW structure defines the relational "Join" operation. There may be multiple JOIN structures within a VIEW, and they may be nested within each other to perform multiple-level "Join" operations. The VIEW structure defaults to a "left outer join," where all records for the VIEW's *primary file* are retrieved whether the secondary file named in a JOIN structure contains any related records or not. The secondary file fields are implicitly CLEARED (zero or blank) for those primary file records without related secondary records. You can override the default left outer join by specifying the INNER attribute on the JOIN (creating an "inner join") so that only those *primary file* records with related secondary file records are retrieved.

A relational "Project" operation retrieves only specified data elements from the files involved, not their entire record structure. Only those fields explicitly declared in PROJECT statements in the VIEW structure are retrieved if there are any PROJECT statements declared. Therefore, the relational "Project" operation is automatically implemented by the VIEW structure. The contents of any fields that are not contained in PROJECT statements are undefined.

The FILTER attribute restricts the VIEW to a sub-set of records. The FILTER expression may include any of the fields explicitly declared in the VIEW structure and restrict the VIEW based upon the contents of any of the fields. This makes the FILTER operate across all levels of the "Join" operation.

**Note:**

**VIEWS have no THREAD attribute by syntax, but VIEWS declared in the local scope of a PROCEDURE or ROUTINE are treated as threaded. A VIEW declared in the global or module scope is treated as threaded if at least one joined FILE is threaded.**

**Related Procedures:**

BUFFER    CLOSE    FLUSH    OPEN    RECORDS    DELETE    HOLD    NEXT  
 POSITION    PREVIOUS    PUT    RELEASE    REGET    RESET    SET    SKIP  
 WATCH

**Example:**

```
Customer  FILE,DRIVER('Clarion'),PRE(Cus) !Declare customer file layout
AcctKey   KEY(Cus:AcctNumber)
Record    RECORD
AcctNumber LONG
OrderNumber LONG
Name      STRING(20)
Addr      STRING(20)
```

```
City          STRING(20)
State         STRING(20)
Zip           STRING(20)
END
```

```
Header        FILE,DRIVER('Clarion'),PRE(Hea) !Declare header file layout
AcctKey       KEY(Hea:AcctNumber)
OrderKey      KEY(Hea:OrderNumber)
Record        RECORD
AcctNumber    LONG
OrderNumber   LONG
ShipToName    STRING(20)
ShipToAddr    STRING(20)
ShipToCity    STRING(20)
ShipToState   STRING(20)
ShipToZip     STRING(20)
END
END
```

```
Detail        FILE,DRIVER('Clarion'),PRE(Dtl) !Declare detail file layout
OrderKey      KEY(Dtl:OrderNumber)
Record        RECORD
OrderNumber   LONG
Item          LONG
Quantity      SHORT
END
END
```

```
Product       FILE,DRIVER('Clarion'),PRE(Pro) !Declare product file layout
ItemKey       KEY(Pro:Item)
Record        RECORD
Item          LONG
Description   STRING(20)
Price         DECIMAL(9,2)
END
END
```

```
ViewOrder VIEW(Customer)                                !Declare VIEW structure
    PROJECT(Cus:AcctNumber,Cus:Name)
    JOIN(Hea:AcctKey,Cus:AcctNumber)                    !Join Header file
    PROJECT(Hea:OrderNumber)
    JOIN(Dtl:OrderKey,Hea:OrderNumber)                  !Join Detail file
    PROJECT(Det:Item,Det:Quantity)
    JOIN(Pro:ItemKey,Dtl:Item)                          !Join Product file
    PROJECT(Pro:Description,Pro:Price)
END
END
END
END
```

**See Also:**

JOIN

PROJECT

## PROJECT (set view fields)

**PROJECT**( *fields* )

**PROJECT**       Declares the fields retrieved for the VIEW.

*fields*            A comma delimited list of fields (including prefixes) from the primary file of the VIEW, or the secondary related file named in the JOIN structure, containing the PROJECT declaration.

The **PROJECT** statement declares *fields* retrieved for a relational "Project" operation. A relational "Project" operation retrieves only the specified *fields* from the file, not the entire record structure.

A PROJECT statement may be declared in the VIEW, or within one of its component JOIN structures. If there is no PROJECT declaration in the VIEW or JOIN structure, all fields in the relevant file are retrieved.

If a PROJECT statement is present in the VIEW or JOIN structure, only the fields explicitly declared in the PROJECT are guaranteed to be retrieved. The contents of any fields that are not contained in PROJECT statements are undefined. Depending on the abilities of the particular database engine you are using, other fields may be retrieved. However, you should not rely on this as future changes or changes in the database driver may preclude these fields from being retrieved.

### Example:

```

Detail    FILE,DRIVER('Clarion'),PRE(Dtl) !Declare detail file layout
OrderKey  KEY(Dtl:OrderNumber)
Record    RECORD
OrderNumber LONG
Item      LONG
Quantity  SHORT
Description STRING(20) !Line item comment
          END
          END

Product   FILE,DRIVER('Clarion'),PRE(Pro) !Declare product file layout
ItemKey   KEY(Pro:Item)
Record    RECORD
Item      LONG
Description STRING(20) !Product description
Price     DECIMAL(9,2)
          END
          END

ViewOrder VIEW(Detail)
  PROJECT(Det:OrderNumber,Det:Item,Det:Description)
  JOIN(Pro:ItemKey,Det:Item)
  PROJECT(Pro:Description,Pro:Price)
  END
  END

```

## JOIN (declare a "join" operation)

```
JOIN( | secondary key ,linking fields| ) [, INNER ]  
    | secondary file ,expression |  
    [PROJECT( )]  
    [JOIN( )  
    [PROJECT( )]  
    END]  
    END
```

---

<b>JOIN</b>	Declares a secondary file for a relational "Join" operation.
<i>secondary key</i>	The label of a KEY which defines the secondary FILE and its access key.
<i>linking fields</i>	A comma-delimited list of fields in the related file that contain the values the <i>secondary key</i> uses to get records.
<i>secondary file</i>	The label of the secondary FILE.
<i>expression</i>	A string constant containing a single logical expression for joining the files (PROP:JoinExpression or PROP:SQLJoinExpression). This expression may include any of the logical and Boolean operators.
<b>INNER</b>	Specifies an "inner join" instead of the default "left outer join"--the only records retrieved from the VIEW's <i>primary file</i> parent are those with at least one related record in the JOIN's <i>secondary file</i> .
<b>PROJECT</b>	Specifies the fields from the secondary related file specified by a JOIN structure that the VIEW will retrieve. If omitted, all fields from the file are retrieved.

The **JOIN** structure declares a secondary file for a relational "Join" operation. A relational "Join" retrieves data from multiple files, based upon the relationships defined between the files. There may be multiple JOIN structures within a VIEW, and they may be nested within each other to perform multiple-level "Join" operations.

The *secondary key* defines the access key for the secondary file. The *linking fields* name the fields in the file to which the secondary file is related, that contain the values used to retrieve the related records. For a JOIN directly within the VIEW, these fields come from the VIEW's primary file. For a JOIN nested within another JOIN, these fields come from the secondary file of the JOIN in which it is nested. Non-linking fields in the *secondary key* are allowed as long as they appear in the list of the key's component fields after all the linking fields.

When data is retrieved, if there are no matching secondary file records for a primary file record, blank or zero values are supplied in the fields specified in the PROJECT. This type of relational "Join" operation is known as a "left outer join."



The *expression* parameter allows you to join files which contain related fields but no keys defined for the relationship. PROP:JoinExpression and PROP:SQLJoinExpression are array properties whose the array element number references the ordinal position of the JOIN in the VIEW to affect. PROP:SQLJoinExpression is an SQL-only version of PROP:JoinExpression. If the first character of the expression assigned to PROP:JoinExpression or PROP:SQLJoinExpression is a plus sign (+) the new expression is concatenated to the existing join expression.

**Example:**

```
Customer  FILE,DRIVER('Clarion'),PRE(Cus) !Declare customer file layout
AcctKey   KEY(Cus:AcctNumber)
Record    RECORD
AcctNumber LONG
OrderNumber LONG
Name      STRING(20)
          END
          END

Header    FILE,DRIVER('Clarion'),PRE(Hea) !Declare header file layout
AcctKey   KEY(Hea:AcctNumber)
OrderKey  KEY(Hea:AcctNumber,Hea:OrderNumber)
Record    RECORD
AcctNumber LONG
OrderNumber LONG
Total     DECIMAL(11,2)    !Total cash paid
Discount  DECIMAL(11,2)    !Discount amount given
OrderDate LONG
          END
          END

Detail    FILE,DRIVER('Clarion'),PRE(Dtl) !Declare detail file layout
OrderKey  KEY(Dtl:AcctNumber,Dtl:OrderNumber)
Record    RECORD
AcctNumber LONG
OrderNumber LONG
Item      LONG
Quantity  SHORT
          END
          END

Product   FILE,DRIVER('Clarion'),PRE(Pro) !Declare product file layout
ItemKey   KEY(Pro:Item)
Record    RECORD
Item      LONG
Description STRING(20)
Price     DECIMAL(9,2)
          END
          END

ViewOrder1 VIEW(Header)                                !Declare VIEW structure
  PROJECT(Hea:AcctNumber,Hea:OrderNumber)
  JOIN(Dtl:OrderKey,Hea:AcctNumber,Hea:OrderNumber) !Join Detail file
  PROJECT(Dtl:ItemDtl:Quantity)
  JOIN(Pro:ItemKey,Dtl:Item)                        !Join Product file
  PROJECT(Pro:Description,Pro:Price)
  END
END
```

```
ViewOrder2 VIEW(Customer)                                !Declare VIEW structure
  JOIN(Header,'Cus:AcctNumber = Hea:AcctNumber AND ' & |
    ' (Hea:Discount + Hea:Total) * .1 > Hea:Discount')
  PROJECT(Hea:AcctNumber,Hea:OrderNumber)
  JOIN(Dtl:OrderKey,Hea:AcctNumber,Hea:OrderNumber) !Join Detail file
  PROJECT(Dtl:ItemDtl:Quantity)
  END
END
```

**See Also:**

INNER

## Queue Structures:

### QUEUE (declare a memory QUEUE structure)

```

label      QUEUE( [ group ]  [,PRE] [,STATIC] [,THREAD] [,TYPE] [,BINDABLE] [,EXTERNAL]
                )              [,DLL]

fieldlabel  variable [,NAME( )]

                END

```

---

**QUEUE**       Declares a memory queue structure.

*label*        The name of the QUEUE.

*group*        The label of a previously declared GROUP, QUEUE, or RECORD structure from which it will inherit its structure. This may be a GROUP, QUEUE, or RECORD with or without the TYPE attribute.

**PRE**         Declare a *fieldlabel* prefix for the structure.

**STATIC**      Declares a QUEUE, local to a PROCEDURE, whose buffer is allocated in static memory.

**THREAD**      Specify memory for the queue is allocated once for each execution thread. This implies the STATIC attribute on Procedure Local data.

**TYPE**        Specify the QUEUE is just a type definition for other QUEUE declarations.

**BINDABLE**    Specify all variables in the queue may be used in dynamic expressions.

**EXTERNAL**    Specify the QUEUE is defined, and its memory is allocated, in an external library.

**DLL**         Specify the QUEUE is defined in a .DLL. This is required in addition to the EXTERNAL attribute.

*fieldlabel*    The name of the *variables* in the queue.

*variable*      Data declaration. The sum of the memory required for all declared *variables* in the QUEUE must not be greater than 4MB.

**QUEUE** declares a memory QUEUE structure. The *label* of the QUEUE structure is used in queue processing statements and procedures. When used in assignment statements, expressions, or parameter lists, a QUEUE is treated like a GROUP data type.

The structure of a QUEUE declared with the *group* parameter begins with the same structure as the named *group*; the QUEUE inherits the fields of the named *group*. The QUEUE may also contain its own *declarations* that follow the inherited fields. If the QUEUE will not contain any other fields, the name of the *group* from which it inherits may be used as the data type without the QUEUE or END keywords.

A QUEUE may be thought of as a "memory file" internally implemented as a "dynamic array" of QUEUE entries. When a QUEUE is declared, a data buffer is allocated (just as with a file). Each entry in the QUEUE is run-length compressed during an ADD or PUT to occupy as little memory as necessary, and de-compressed during GET. There is an 8 byte per-entry overhead for queues with uncompressed records, and 12 bytes per entry for queues with compressed records.

The data buffer for a Procedure local QUEUE (declared in the data section of a PROCEDURE) is allocated on the stack (unless it has the STATIC attribute or is too large). The memory allocated to the entries in a procedure-local QUEUE without the STATIC attribute is allocated only until you FREE the QUEUE, or you RETURN from the PROCEDURE--the QUEUE is automatically FREEd upon RETURN.

For a Global data, Module data, or Local data QUEUE with the STATIC attribute, the data buffer is allocated static memory and the data in the buffer is persistent between procedure calls. The memory allocated to the entries in the QUEUE remains allocated until you FREE the QUEUE.

The *variables* in the QUEUE's data buffer are not automatically initialized to any value, they must be explicitly assigned values. Do not assume that they contain blanks or zero before your program's first assignment to them.

As entries are added to the QUEUE, memory for the entry is dynamically allocated then the data copied from the buffer to the entry and compressed. As entries are deleted from the QUEUE, the memory used by the deleted entry is freed. The maximum number of entries in a QUEUE is theoretically  $2^{26}$  (67,108,864), but is actually dependant upon available virtual memory. The actual memory used by each entry in the QUEUE is dependent on the data compression ratio achieved by the runtime library.

A QUEUE with the BINDABLE attribute makes all the variables within the QUEUE available for use in a dynamic expression, without requiring a separate BIND statement for each (allowing BIND(queue) to enable all the fields in the queue). The contents of each variable's NAME attribute is the logical name used in the dynamic expression. If no NAME attribute is present, the label of the variable (including prefix) is used. Space is allocated in the .EXE for the names of all of the variables in the structure. This creates a larger program that uses more memory than it normally would. Therefore, the BINDABLE attribute should only be used when a large proportion of the constituent fields are going to be used.

A QUEUE with the TYPE attribute is not allocated any memory; it is only a type definition for QUEUES that are passed as parameters to PROCEDURES. This allows the receiving procedure to directly address component fields in the passed QUEUE. The parameter declaration on the PROCEDURE statement instantiates a local prefix for the passed QUEUE as it names the passed QUEUE for the procedure. For example, PROCEDURE(LOC:PassedGroup) declares the procedure uses the LOC: prefix (along with the individual field names used in the type declaration) to directly address component fields of the QUEUE actually passed as the parameter.

The WHAT and WHERE procedures allow access to the fields by their relative position within the QUEUE structure.

#### **Related Procedures:**

ADD	CHANGES	DELETE	FREE	GET	POINTER	POSITION
PUT	RECORDS	SORT				

#### **See Also:**

PRE, STATIC, NAME, FREE, THREAD, WHAT, WHERE

**Example:**

```
NameQue  QUEUE,PRE (Nam)           !Declare a queue
Name      STRING (20)
Zip       DECIMAL (5,0) ,NAME ('SortField')
          END                       !End queue structure

NameQue2  QUEUE (NameQue) ,PRE (Nam2) !Queue that inherits Name and Zip fields
Phone     STRING (10)                ! and adds a Phone field
          END

NameQue3  NameQue2                   !Declare a second QUEUE with exactly
                                     ! the same structure as NameQue2
```

## Additional QUEUE Programming Considerations

This topic expands on important issues in understanding how supported processing statements and optional parameters can affect a QUEUE.

### **ADD, GET, PUT to a QUEUE by KEY**

There are three ( 3 ) forms of the QUEUE *key* parameter: *sequence*, *string* and *function*. Each one is described as follows:

*sequence* [ $\pm$ ]*key1* [, [ $\pm$ ]*key2*...]

A list of up to 16 labels of QUEUE fields, separated by commas and with an optional + or - sign preceding the label. If the key component is specified with -, it is used in descending order. Reference field types (including ANY) and arrays are not permitted.

*Name*

A string constant, variable or expression. Its value must contain a list of up to 16 NAME attributes of QUEUE fields with an optional leading + or - sign, separated with commas. If the key component is specified with -, it is used in descending order. Reference field types (including ANY) and arrays are not permitted.

When comparing two keys using one of the two forms above, the keys are considered *equal* if all key components are equal.

A key is considered *greater than* another key, if its *n*th key component is greater than the second key, and the extra component defined is in ascending order (with all other key components being equal.)

Finally, a key is considered *less than* another key if its *n*th key component is greater than the second key, and the extra component defined is in descending order (with all other key components being equal.)

There is also a third form of KEY types regarding QUEUES:

*Function*

The label of the function containing two parameters of a \*GROUP or named GROUP passed by address, and having a SIGNED return value. Both parameters must use the same parameter type, and cannot be omitted. The RAW, C and PASCAL attributes are not permitted in the prototype declaration.

The first parameter of the FUNCTION is the *target* parameter, or record that is about to be acted on. The second parameter is a *comparison* value, used to determine the position where the first parameter is to be placed or retrieved.

Using ADD, PUT or GET by FUNCTION will read or write from a positional value returned by the function.

If the function returns zero (0) the queue record of the first parameter is treated as equal to the second. In this case, no record is ADDED or PUT, since the values are equal.

If the function returns a negative value, the ADD or PUT of the record passed as a first parameter is treated as having less value than record passed as second parameter and is written accordingly.

If the function returns a positive value, the ADD or PUT of the record passed as a first parameter is treated as having a greater value than record passed as second parameter and is written accordingly.

## Using Multiple Sort Orders

The following topic describes the internal paradigm regarding QUEUES with multiple sort orders.

Prior to Clarion 5, it was possible to use the GET(Queue,Key) form to obtain a POINTER to the first or last record in a range.

For example:

```

Q QUEUE
A LONG
B STRING(20)
END

CODE
...
SORT(Q, Q.A, Q.B)      !sort the queue in a,b sequence
Q.A = 1                 !set to the first record
CLEAR (Q.B)             !clear secondary field to make sure
GET (Q, Q.A)           !GET to first record
first# = POINTER(Q)     !GET fails, but stores the POINTER where record would have existed
Q.A = 5                 !set to the last record or beyond
CLEAR (Q.B)             !again, clear secondary sort field
GET (Q, Q.A)           !GET will fail
last# = POINTER(Q)-1    !and returns where new record will be

```

After this code executes, *first#* contains a pointer to the first record of the **Q.A** field in a range (in this example range is 1 through 4), and *last#* contains a pointer to the last record with value of **Q.A** within this range.

This technique is not possible for queues with multiple sort orders. Even if one set of key components is a subset of another one, sort orders based on them are handled separately.

Hence, if the program uses a partial key seed value in the GET(Queue,Key) statement, the queue logic must build the sort order based on specified key if it does not exist, and perform the GET operation using this sort order. In other words, the GET never fails.

Sort orders based on "full" and "partial" keys can be different because of queue rules: ADD adds a new record after all other records with the same key, and PUT updates an existing record after all other records with the same key. The new POSITION(Queue) function implements the behavior that an attempted GET on a partial key value used to have.

Every active QUEUE can have up to 16 sort orders that exist in memory *simultaneously*.

For the purpose of this topic, sort orders not defined as the current active sort, but exist in memory by prior QUEUE actions (described later), are defined as a **memory key**.

All memory keys share the same queue of records, but each one orders the records according to the key that it is based on.

At any point in time during the life of the queue, one of the memory keys is the "default". The default memory key is the one that a SORT has been performed on most recently. If no SORT has been executed, the default memory key can be either unsorted, or sorted by the ADD(key) or PUT(key) methods ("sorting as you go")

The unsorted key is often used for non-keyed operations (i.e., POINTER()).

**FREE()** removes all memory keys.

The memory key based on the last key used in the keyed ADD, GET, PUT, or a SORT statement is called the **active key**. It is considered active while this particular statement is executing. If the active key did not exist before the keyed statement, it is created by taking the initial sequence of records defined by the default sort order, and is resorted using the new memory key.

**SORT** makes the active key the **default**. For example, if the active key existed before the SORT, no resorting is performed, because it doesn't need to.

**GET(Queue,Key)** retrieves the first record using the active key's (Key parameter) sort order that matches current content of the queue buffer. If no records can be found, the buffer is not changed and value of next call to POINTER() is undefined.

**GET(Queue,Pointer)** retrieves record with the relative position equal to the Pointer position in the default memory key.

ADD and PUT work differently for default key and all other memory keys. All memory keys that are not the default are updated using their key values always, even for non-keyed operations. Hence, their current sort is always correct.

For the original sort order, the situation is a little more complex. Here, the traditional rules are in effect:



**PUT(Queue):**

Writes the record back to the same relative position in the original sort order as the GET or ADD retrieved it. If the original sort order was modified since the last GET or ADD, it is marked as unsorted.

**PUT(Queue,Pointer):**

If the passed *Pointer* is equal to relative position in the original sort order of the record that has been retrieved by GET or ADD, the statement is equivalent to PUT(queue). Otherwise, the record is removed from its old position in the original sort order and is added to the one specified by the new pointer value. If the original sort order becomes broken after that, it is marked as unsorted.

**PUT(Queue,Key)**

If *Key* is a key that the original sort order is based on, and the key value is not changed, PUT updates the record value in original sort order. If the key value is changed, the record's value is removed from its old position and added to a new one, based on the new key value. The original sort order always remains unbroken in this case.

If *Key* is not a key that the original sort order is based on, the original sort order is marked as unsorted, the record's entry is removed from its old position, and a new one added immediately before the first record it finds with the key value based on *Key*.

Because the search algorithm is based on the history of work with this queue and its memory keys, it is impossible to say where the new position will be. Use the POINTER() function to return it.

**ADD(Queue)**

Equivalent to **ADD(Queue,RECORDS(Queue)+1)**

**ADD(Queue,Pointer)**

The record in the queue buffer is added to given relative position in the original sort order. If the original sort order becomes broken after that, it is marked as unsorted.

**ADD(Queue,Key)**

The record in the queue buffer is added immediately before first record in the original sort order that has greater key value, or, to the end of the sort order if records with greater key value are not found. If *Key* is a key that the original sort order is based on, this is the correct position and the default sort order remains unbroken. Otherwise, it is marked as unsorted. Similar to using PUT on another key value, the position of the added record is unknown if the default sort order is not based on the *Key*.

**Example 1:**

**Q** QUEUE

**A** LONG

**B** LONG

**END**

**CODE**

**FREE** (Q)

**Q.A** = 1

**Q.B** = 5

**ADD** (Q, Q.A)

There is only one sort order based on the **(Q.A)** key; it is the active memory key

**SORT** (Q, Q.A, Q.B)

Now, there are two sort orders that exist, based on a **(Q.A)** and **(Q.A,Q.B)** keys. The latter key is now the active memory key.

The order of records is now:

**(Q.A):** (1, 5)

**(Q.A,Q.B)** (1, 5)

If we now execute:

**Q.A** = 1

**Q.B** = 1

**ADD** (Q, Q.A, Q.B)

The order of records is now:

**(Q.A):** (1, 5) (1, 1)

**(Q.A,Q.B):** (1, 1) (1, 5)

Executing the statement:

```
GET (Q, Q.A)
```

Retrieves the **(1, 5)** record, because it is the first record matching the key value in the current queue buffer based on **(Q.A)**.

### Example 2:

```
Q  QUEUE
A    LONG
B    LONG
END
```

```
CODE
```

```
FREE (Q)
Q.A = 1
Q.B = 5
ADD (Q)
```

There is one original sort order; and it is the active key.

```
SORT (Q, Q.A, Q.B)
```

Now, there is one sort order here based on the **(Q.A,Q.B)** key. It is now the new active key.

The current order of records is:

```
(Q.A,Q.B)  (1, 5)
```

After executing the following:

```
Q.A = 1
Q.B = 1
ADD (Q, Q.A, Q.B)
```

The new order of records becomes:

**(Q.A,Q.B)**    **(1, 1) (1, 5)**

Executing:

**GET (Q, Q.A)**

The sort order based on **(Q.A)** does not exist. Hence, it is created as a new sequence of records in default order resorted with the **(Q.A)** key.

The memory keys after this GET:

**(Q.A)**            **(1, 1) (1, 5)**

**(Q.A,Q.B)**    **(1, 1) (1, 5)**

The GET retrieves the **(1, 1)** record because it is the first record with the key value that matches the current queue buffer based on **(Q.A)**.

## 5 - Declaration Attributes

### Variable and Entity Attributes:

#### AUTO (uninitialized variable)

##### AUTO

The **AUTO** attribute allows a non-static or non-threaded variable to be allocated uninitialized stack memory. Without the AUTO attribute, a numeric variable is initialized to zero and a string variable is initialized to all blanks when its memory is assigned at run-time.

The AUTO attribute is used when you do not need to rely on an initial blank or zero value because you intend to assign some other value to the variable. This saves a small amount of run-time memory by eliminating the internal code necessary to perform the automatic initialization for the variable.

When an ANY data type is declared outside of a structure, the AUTO attribute is ignored. When a structure containing an ANY has the AUTO attribute, you must first CLEAR the entire structure before you can access variables of type ANY.

##### Example:

```
SomeProc  PROCEDURE
SaveCustID LONG, AUTO      !Non-initialized local variable
```

##### See Also:

Data Declarations and Memory Allocation

## BINARY (memo contains binary data)

### BINARY

The **BINARY** attribute (PROP: BINARY) of a MEMO or BLOB declaration specifies the MEMO or BLOB will receive data that is not just ASCII characters. This attribute is normally used to store graphic images for display in an IMAGE field on screen. OEM conversion is not applied to MEMO or BLOB fields with the BINARY attribute. Some file drivers (Clarion, Btrieve, xBase) assume that the data in a BINARY MEMO or BLOB field is zero-padded, while non-BINARY data is space-padded.

#### Example:

```
Names  FILE, DRIVER('Clarion'), PRE(Nam)
NbrKey  KEY(Nam: Number)
Picture MEMO(48000), BINARY      !Binary memo - 48,000 bytes
Rec      RECORD
Number    SHORT
          END
        END
```

#### See Also:

MEMO

BLOB

IMAGE

OEM

## BINDABLE (set runtime expression string variables)

### BINDABLE

The **BINDABLE** attribute declares a GROUP, QUEUE, FILE, or VIEW whose constituent variables are all available for use in a runtime expression string. The contents of each variable's NAME attribute is the logical name used in the dynamic expression. If no NAME attribute is present, the label of the variable (including prefix) is used. Space is allocated in the .EXE for the names of all of the variables in the structure. This creates a larger program that uses more memory than it normally would. Therefore, the BINDABLE attribute should only be used when a large proportion of the constituent fields are going to be used.

The BIND(group) form of the BIND statement must still be used in the executable code before the individual fields in the QUEUE structure may be used.

#### Example:

```
Names    QUEUE, BINDABLE                                !Bindable Record structure
Name     STRING(20)
FileName STRING(8), NAME('FName')                      !Dynamic name: FName
Dot       STRING(1)                                     !Dynamic name: Dot
Extension STRING(3), NAME('EXT')                        !Dynamic name: EXT
END

CODE
BIND(Names)

Names    FILE, DRIVER('Clarion'), BINDABLE              !Bindable Record structure
Record   RECORD
Name     STRING(20)
FileName STRING(8), NAME('FName')                      !Dynamic name: FName
Dot       STRING(1)                                     !Dynamic name: Dot
Extension STRING(3), NAME('EXT')                        !Dynamic name: EXT
END

CODE
OPEN(Names)
BIND(Names)

FileNames GROUP, BINDABLE                               !Bindable group
FileName  STRING(8), NAME('FILE')                       !Dynamic name: FILE
Dot       STRING('.')                                   !Dynamic name: Dot
Extension STRING(3), NAME('EXT')                        !Dynamic name: EXT
END
```

#### See Also:

BIND

UNBIND

EVALUATE

## CREATE (allow data file creation)

### CREATE

The **CREATE** attribute (PROP:CREATE) of a FILE declaration allows a disk file to be created by the CREATE statement from within the PROGRAM where the FILE is declared. This adds some overhead, as all the file information must be contained in the executable program.

#### Example:

```
Names FILE, DRIVER('Clarion'), CREATE      !Declare a file, allow create
Rec   RECORD
Name   STRING(20)
      END
      END
```



## DIM (set array dimensions)

**DIM**(*dimension*,...,*dimension*)

**DIM** Declares a variable as an array.

*dimension* A positive numeric constant which specifies the number of elements in this *dimension* of the array.

The **DIM** attribute declares a variable as an array. The variable is repeated the number of times specified by the *dimension* parameters. Multi-dimensional arrays may be thought of as nested. Each *dimension* in the array has a corresponding subscript. Therefore, referencing a variable in a three dimensional array requires three subscripts. There is no limit to the number of dimensions, and the total size of an array is unlimited. Zero or negative array elements are invalid.

Subscripts identify which element of the array is being referenced. A subscript list contains a subscript for each *dimension* of the array. Each subscript is separated by a comma and the entire list is enclosed in brackets ([ ]). A subscript may be a numeric constant, expression, or function. The entire array may be referenced by the label of the array without a subscript list.

A GROUP structure array is a special case. Each level of nesting adds subscripts to the GROUP. Data declared within the GROUP is referenced using standard Field Qualification syntax with each subscript specified at the GROUP level at which it is dimensioned.

In general, there is a limit to size of data objects declared in global, module or local scope: 4MB. The compiler can report different errors depending from the type of data object exceeding this limit. Particularly, arrays with variable dimensions may be of a slightly greater size than 4MB.



The **CLASS** declaration supports the **DIM** attribute. It provides for creating arrays of objects of any type (for a CLASS declared without the TYPE attribute).

**Example:**

```

Scr    GROUP           !Characters on a DOS text-mode screen
Row    GROUP,DIM(25)  !Twenty-five rows
Pos     GROUP,DIM(80) !Two thousand positions
Attr    BYTE          !Attribute byte
Char    BYTE          !Character byte
      END             !Terminate the group structures
      END
      END
! In the group above:
!   Scr                is a 4,000 byte GROUP
!   Scr.Row            is a 4,000 byte GROUP
!   Scr.Row[1]         is a 160 byte GROUP
!   Scr.Row[1].Pos     is a 160 byte GROUP
!   Scr.Row[1].Pos[1]  is a 2 byte GROUP
!   Scr.Row[1].Pos[1].Attr is a single BYTE
!   Scr.Row[1].Pos[1].Char is a single BYTE

Month  STRING(10),DIM(12) !Dimension the month to 12
CODE
  CLEAR(Month)            !Assign blanks to the entire array
  Month[1] = 'January'    !Load the months into the array
  Month[2] = 'February'
  Month[3] = 'March'

```

**See Also:**

MAXIMUM

Prototype Parameter Lists (Passing Arrays)

## DLL (set variable defined externally in .DLL)

`DLL( [ flag ] )`

**DLL** Declares a variable, FILE, QUEUE, GROUP, or CLASS defined externally in a .DLL.

*flag* A numeric constant, equate, or Project system define which specifies the attribute as active or not. If the *flag* is zero, the attribute is not active, just as if it were not present. If the *flag* is any value other than zero, the attribute is active.

The **DLL** attribute specifies that the declaration (this may any variable declaration, or a FILE, QUEUE, GROUP, or CLASS structure) on which it is placed is defined in a .DLL. A declaration with DLL attribute must also have the EXTERNAL attribute. The DLL attribute is required for 32-bit applications because .DLLs are relocatable in a 32-bit flat address space, which requires one extra dereference by the compiler to address the variable. The DLL attribute is not valid on variables declared within FILE, QUEUE, CLASS, or GROUP structures.

The declarations in all libraries (or .EXEs) must be EXACTLY the same (with the appropriate addition of the EXTERNAL and DLL attributes). If they are not exactly the same, data corruption could occur. Any incompatibilities between libraries cannot be detected by the compiler or linker, therefore it is the programmer's responsibility to ensure that consistency is maintained.

When using EXTERNAL and DLL on declarations shared by .DLLs and .EXE, only one .DLL should define the variable, FILE, CLASS, or QUEUE without the EXTERNAL and DLL attributes. All the other .DLLs (and the .EXE) should declare the variable, FILE, CLASS, or QUEUE with the EXTERNAL and DLL attributes. This ensures that there is only one memory allocation for the variable, FILE, CLASS, or QUEUE and all the .DLLs and the .EXE will reference the same memory when referring to that variable, FILE, or QUEUE.

One suggested way of coding large systems using many .DLLs and/or .EXEs that share the same variables would have one .DLL containing the actual data definition that only contains FILE and global variable definitions that are shared among all (or most) of the .DLLs and .EXEs. This makes one central library in which the actual file definitions are maintained. This one central .DLL is linked into all .EXEs that use those common files. All other .DLLs and/or .EXEs in the system would declare the common variables with the EXTERNAL and DLL attributes.

There is a pre-defined flag used by the IDE Project System and the Application Generator.

`_ABCDIIMode_` Used by the ABC template chain on all CLASS definitions to indicate that the CLASS is declared in an external .DLL. A project DEFINE is used to toggle the DLL mode.

**Example:**

```

TotalCount LONG,EXTERNAL,DLL(dll_mode)      !A variable declared in an external .DLL
Cust      FILE,PRE(Cus),EXTERNAL(''),DLL(1) !File defined in PROGRAM module of a .DLL
CustKey   KEY(Cus:Name)
Record    RECORD
Name      STRING(20)
          END
          END

DLLQueue  QUEUE,PRE(Que),EXTERNAL,DLL(1) !A queue declared in an external .DLL
TotalCount LONG
          END

EditEntryClass CLASS(EditClass),TYPE,MODULE('ABEIP.CLW'),LINK('ABEIP.CLW',|_ABCLinkMode_),DLL
(_ABCDllMode_)
CreateControl    PROCEDURE,VIRTUAL,PROTECTED
                END
    
```

**See Also:**

EXTERNAL

## DRIVER (specify data file type)

**DRIVER**( *filetype* [,*driver string*] )

---

<b>DRIVER</b>	Specifies the file system the file uses.
<i>filetype</i>	A string constant containing the name of the file manager (Btrieve, Clarion, etc.).
<i>driver string</i>	A string constant or variable containing any additional instructions to the file driver. All the valid values for this parameter are listed in each file driver's documentation.

The **DRIVER** attribute (PROP:DRIVER) specifies which file driver is used to access the data file. DRIVER is a required attribute of all FILE declarations.

Clarion programs use file drivers for physical file access. A file driver acts as a translator between a Clarion program and the file system, eliminating different access commands for each file system. File drivers allow access to files from different file systems without changes in the Clarion syntax.

The specific implementation method of each Clarion file access command is dependent on the file driver. Some commands may not be available in a file driver due to limitations in the file system. Each file driver is documented in the help and *Database Drivers* PDF. Any unsupported file access commands, FILE declaration attributes, data types, and/or file system idiosyncrasies are listed there.

If the file is declared without the THREAD attribute, the *driver string* variable (PROP:DriverString) used with the DRIVER attribute should also be declared without the THREAD attribute.

### Example:

```
Names FILE,PRE(NAM),DRIVER('Clarion') !Begin file declaration
```

```
Record RECORD
```

```
Name STRING(20)
```

```
END
```

```
END
```

```
!Use commas to separate multiple driver strings:
```

```
A FILE,PRE(ASC),DRIVER('BASIC','/ALWAYSQUOTE=OFF,/COMMA=9,/ENDOFRECORD=1,13')
```

```
Record RECORD
```

```
Name STRING(20)
```

```
END
```

```
END
```

## DUP (allow duplicate KEY entries)

### DUP

---

The **DUP** attribute (PROP:DUP) of a KEY declaration allows multiple records with the same key values to occur in a FILE. If the DUP attribute is omitted, attempting to ADD or PUT records with duplicate key values will generate the "Creates Duplicate Key" error, and the record will not be written to the file. During sequential processing using the KEY, records with duplicate key values are accessed in the physical order their entries appear in the KEY. The GET and SET statements generally access the first record in a set of duplicates.

The DUP attribute is unnecessary on INDEX declarations because an INDEX always allows duplicate entries.

#### Example:

```
Names      FILE,DRIVER('Clarion'),PRE(Nam)
NameKey    KEY(Nam:Name),DUP           !Declare name key, allow duplicate names
NbrKey     KEY(Nam:Number)              !Declare number key, no duplicates allowed
Rec        RECORD
Name       STRING(20)
Number     SHORT
           END
           END
```

#### See Also:

KEY

GET

SET

## ENCRYPT (encrypt data file)

### ENCRYPT

---

The **ENCRYPT** attribute (PROP:ENCRYPT) is used in conjunction with the OWNER attribute to disguise the information in a data file. ENCRYPT is only valid with an OWNER attribute. Even with a "hex-dump" utility, the data in an encrypted file is extremely difficult to decipher.

**Example:**

```
Names  FILE, DRIVER('Clarion'), OWNER('Clarion'), ENCRYPT
Record RECORD
Name    STRING(20)
        END
        END
```

**See Also:**

OWNER

EXTERNAL

## EXTERNAL (set defined externally)

**EXTERNAL**( *member* )

---

**EXTERNAL** Specifies the variable, FILE, QUEUE, GROUP, or CLASS is defined in an external library.

*member* A string constant (valid only on FILE, GROUP, or QUEUE declarations) containing the filename (without extension) of the MEMBER module containing the actual FILE, GROUP or QUEUE definition (the one without an EXTERNAL attribute) respectively. If the FILE, GROUP or QUEUE is defined in a PROGRAM module or in a "universal member module" (i.e., MEMBER statement for that module has no parameter), an empty string ("") can be used as a parameter of the EXTERNAL attribute, or the parameter can be omitted.

The **EXTERNAL** attribute specifies the variable, FILE, QUEUE, GROUP, or CLASS on which it is placed is defined in an external library. Therefore, a variable, FILE, QUEUE, GROUP, or CLASS with the EXTERNAL attribute is declared and may be referenced in the Clarion code, but is not allocated memory--the memory for the variable, FILE, QUEUE, GROUP, or CLASS is allocated by the external library. This allows the Clarion program access to any variable, FILE, QUEUE, GROUP, or CLASS declared as public in external libraries. The EXTERNAL attribute is not valid on variables declared inside FILE, QUEUE, GROUP, or CLASS structures.

When using EXTERNAL(*member*) to declare a FILE shared by multiple libraries (.LIBs, or .DLLs and .EXE), only one library should define the FILE without the EXTERNAL attribute. All the other libraries (and the .EXE) should declare the FILE with the EXTERNAL attribute. This ensures that there is only one record buffer allocated for the FILE and all the libraries and the .EXE will reference the same memory when referring to data elements from that FILE.

The declarations in all libraries (or .EXEs) must be EXACTLY the same (with the appropriate addition of the EXTERNAL and DLL attributes). For example, the FILE declarations in all libraries (or .EXEs) that reference common files must contain exactly the same keys, memos, and fields declared in exactly the same order. If they are not exactly the same, data corruption could occur. Any incompatibilities between libraries cannot be detected by the compiler or linker, therefore it is the programmer's responsibility to ensure that consistency is maintained.

Do not place the OWNER, ENCRYPT, or NAME attributes on a FILE which has the EXTERNAL attribute. These attributes should only be on the FILE structure declared without the EXTERNAL, because the EXTERNAL declaration is actually a re-declaration of a FILE already declared elsewhere. Therefore, these attributes are unnecessary.

One suggested way of coding large systems using many .DLLs and/or .EXEs that share the same files would have one .DLL containing the actual FILE definition that only contains FILE and global variable definitions that are shared among all (or most) of the .DLLs and .EXEs. This makes one central library in which the actual file definitions are maintained. This one central .DLL is linked into all .EXEs that use those common files. All other .DLLs and/or .EXEs in the system would declare the common FILES with the EXTERNAL attribute.

### Example:

```
PROGRAM
MAP
  MODULE ('LIB.LIB')
AddCount PROCEDURE                                !External library procedure
  END
END
```



```

TotalCount LONG,EXTERNAL           !A variable declared in an external library

!A File defined in a PROGRAM module whose .LIB is linked into this program
Cust  FILE,DRIVER('TopSpeed'),PRE(Cus),EXTERNAL('')
CustKey  KEY(Cus:Name)
Record  RECORD
Name    STRING(20)
      END
      END

!A File defined in a MEMBER module whose .LIB is linked into this program
Contact  FILE,DRIVER('TopSpeed'),PRE(Con),EXTERNAL('LIB01')
ContactKey  KEY(Con:Name)
Record    RECORD
Name      STRING(20)
      END
      END

!*****
! The LIB.CLW file contains:
PROGRAM
MAP
MODULE('LIB01')
AddCount PROCEDURE                !Library procedure
      END
      END

TotalCount LONG                    !The TotalCount variable definition
!The Cust File definition where the record buffer is allocated
Cust  FILE,DRIVER('TopSpeed'),PRE(Cus)
CustKey  KEY(Cus:Name)
Record  RECORD
Name    STRING(20)
      END
      END

CODE
!Executable code ...
!*****
! The LIB01.CLW file contains:
MEMBER('LIB')

!The Contact File definition where the record buffer is allocated
Contact  FILE,DRIVER('TopSpeed'),PRE(Con)
ContactKey  KEY(Con:Name)
Record    RECORD
Name      STRING(20)
      END
      END

AddCount PROCEDURE
CODE
TotalCount += 1

```

**See Also:**

DLL

NAME

EXTERNAL - Thread Considerations

## **FILTER (set view filter expression)**

**FILTER**(*expression*)

---

**FILTER** Specifies a filter *expression* used to evaluate records to include in the VIEW.

*expression* A string constant containing a logical expression.

The **FILTER** attribute (PROP:FILTER) specifies a filter *expression* used to evaluate records to include in the VIEW.

The *expression* may reference any field in the VIEW, at all levels of JOIN structures. The entire *expression* must evaluate as true for a record to be included in the VIEW. The *expression* may contain any valid Clarion language logical expression. The *expression* is evaluated at runtime (just like the EVALUATE procedure), therefore you must BIND all variables used in the *expression*.

### **Use of MATCH with PROP:Filter and SQL Databases**

The use of PROP:Filter as an SQL filter generator for SQL databases now supports converting the MATCH(*s1*, *s2*, *n*) function result to an appropriate SQL filter for all values of *n*, except Match:Regular. If you use the Match:Regular mode, the filter will be evaluated on the client side just like all other non-SQL convertible filters.

Other conversion rules:

**MATCH**(*s1*,*s2*,**Match:Simple**) will be converted to

*s1* = *s2*

for all SQL drivers.

**MATCH**(*s1*,*s2*,**Match:Soundex**) will be converted to

{fn **SOUNDEX**(*s1*)} = {fn **SOUNDEX**(*s2*)}

for all ODBC back ends that support the SOUNDEX function.

**MATCH**(*s1*,*s2*,**Match:Soundex**) will be converted to

**SOUNDEX**(*s1*) = **SOUNDEX**(*s2*)

for the Oracle Accelerator.

`MATCH(s1,s2,Match:Simple + Match:NoCase)` will be converted to

```
{fn UPPER(s1)} = {fn UPPER(s2)}
```

for all ODBC drivers.

`MATCH(s1,s2,Match:Simple + Match:NoCase)` will be converted to

```
UPPER(s1) = UPPER(s2)
```

for the Oracle Accelerator.

`MATCH(s1,s2) !Match:Wild mode`

Will be converted to

```
s1 LIKE %
```

if the s2 parameter is using an asterisk (\*), or

```
s1 LIKE _
```

if the s2 parameter is using a question mark (?) wild card.

This is valid for all SQL drivers.

Adding the *Match:NoCase* mode to the *Match:Wild* mode is converted to

```
{fn UPPER(s1)} LIKE % Or {fn UPPER(s1)} LIKE _
```

for all ODBC drivers.

Adding the *Match:NoCase* mode to the *Match:Wild* mode is converted to

UPPER(s1) LIKE % OF UPPER(s1) LIKE \_

for the Oracle Accelerator.

### Example:

```
BRW1::View:Browse VIEW(Members)
    PROJECT(Mem:MemberCode,Mem:LastName,Mem:FirstName)
    END
KeyValue STRING(20)

!Get only orders for customer 9999 since order number 100
ViewOrder VIEW(Customer),FILTER('Cus:AcctNumber = 9999 AND Hea:OrderNumber > 100')
    PROJECT(Cus:AcctNumber,Cus:Name)
    JOIN(Hea:AcctKey,Cus:AcctNumber)      !Join Header file
    PROJECT(Hea:OrderNumber)
    JOIN(Dtl:OrderKey,Hea:OrderNumber)    !Join Detail file
    PROJECT(Det:Item,Det:Quantity)
    JOIN(Pro:ItemKey,Dtl:Item)            !Join Product file
    PROJECT(Pro:Description,Pro:Price)
    END
    END
    END
    END !view

CODE
BIND('KeyValue',KeyValue)
BIND(Mem:Record)
KeyValue = 'Smith'
BRW1::View:Browse{PROP:Filter} = 'Mem:LastName = KeyValue'  !Specify filter condition
OPEN(BRW1::View:Browse)                                     !Open the view
SET(BRW1::View:Browse)                                     !and set to the beginning
                                                             !of the filtered
                                                             !and ordered result set
CODE
OPEN((Customer,22h); OPEN((Header,22h); OPEN((Product,22h); OPEN(Detail,22h)
BIND('Cus:AcctNumber',Cus:AcctNumber)
BIND('Hea:OrderNumber',Hea:OrderNumber)
SET(Cus:AcctKey)
OPEN(ViewOrder)
LOOP
    NEXT(ViewOrder)
    IF ERRORCODE() THEN BREAK.
    !Process the valid record
END
UNBIND('Cus:AcctNumber',Cus:AcctNumber)
UNBIND('Hea:OrderNumber',Hea:OrderNumber)
CLOSE(Header); CLOSE(Customer); CLOSE(Product); CLOSE(Detail)
```

### See Also:

BIND

UNBIND

EVALUATE

SQL

## IMPLEMENTS(add methods to a CLASS)

**IMPLEMENTS**(*interface*)

**IMPLEMENTS** Adds additional methods to a CLASS.

*interface* A previously defined INTERFACE structure whose methods will be defined by the CLASS that is implementing the specified interface.

When a class IMPLEMENTS an interface, it inherits all methods that are defined in the INTERFACE. A class may IMPLEMENT multiple INTERFACES. The class normally defines all methods declared in each INTERFACE that is implemented.

We now have support for the re-implementing of INTERFACES in derived classes. With the new implementation, if the child class has the IMPLEMENTS attribute for an interface already implemented above it in the hierarchy, the compiler builds a new interface VMT. See the IMPLEMENTS Inheritance topic

**Example 1:**

```
MyInterface INTERFACE                ! Interface structure
MyProc1      PROCEDURE              ! Method prototype
MyProc2      PROCEDURE              ! Method prototype
                                END

MyClass CLASS, IMPLEMENTS (MyInterface) ! Class
                                END

MyClass.MyInterface.MyProc1          !Method declaration
CODE

MyClass.MyInterface.MyProc2          !Method declaration
CODE
```

**Example 2:**

```
MyInterface INTERFACE                ! Interface structure
MyProc1      PROCEDURE              ! Method prototype
MyProc2      PROCEDURE,BOOL         ! Method prototype
                                END

MyClass CLASS, IMPLEMENTS (MyInterface) ! Class

MyProc1Worker PROCEDURE,VIRTUAL      ! Method prototype
MyProc2Worker PROCEDURE,BOOL,VIRTUAL ! Method prototype
                                END
```

```
MyClass.MyProc1Worker      PROCEDURE
CODE
```

```
MyClass.MyProc2Worker      PROCEDURE
CODE
RETURN CHOOSE (YEAR (TODAY ())) > 2000)
```

```
MyClass.MyInterface.MyProc1      !Method declaration
CODE
!implementation stub calls class method to do real work:
self.MyProc1Worker
return
```

```
MyClass.MyInterface.MyProc2      !Method declaration
CODE
!implementation stub calls class method to do real work
return self.MyProc2Worker()
```

```
MyDerivedClass CLASS (MyClass) ! ,IMPLEMENTS (MyInterface) not allowed
!Interface already implemented by parent
MyProc2Worker      PROCEDURE, BOOL, DERIVED
END
```

```
MyDerivedClass.MyProc2Worker      PROCEDURE
BoolRt BOOL
CODE
BoolRt = parent.MyProc2Worker()
IF MONTH (TODAY ()) = 1 THEN BoolRt = 0.
RETURN BoolRt
```

### See Also:

INTERFACE

IMPLEMENTS Inheritance

## Implementing of INTERFACES in Derived Classes

In versions of Clarion prior to 6.3, a derived child class cannot have the IMPLEMENTS attribute for the same INTERFACES implemented by the parent class. When this rule is violated the compiler warns about a duplicate field label in the Child class, and if the user ignores the warning in effect he/she loses the derived child class implementations of the interface.

In the current release, if the duplicate label WARNING is ignored then calling the child's interface of the method actually executes the Parent's implementation.

This version supports the re-implementing of INTERFACES in derived classes. With the new implementation, if the child class has the IMPLEMENTS attribute for an interface already implemented above it in the hierarchy, the compiler builds a new interface VMT.

### Example:

```
IFace      INTERFACE
M1         PROCEDURE ()
M2         PROCEDURE ()
END

Base       CLASS, TYPE, IMPLEMENTS (IFace)
X          PROCEDURE ()
END

Child      CLASS (Base), TYPE, IMPLEMENTS (IFace)
XY         PROCEDURE ()
END
```

In Clarion 6.3 and greater, the Virtual Memory table (VMT) pointed to by `Base.IFace` contains pointers to functions `Base.IFace.M1` and `Base.IFace.M2` while the VMT pointed to by `Child.IFace` contains pointers to functions `Child.IFace.M1` and `Child.IFace.M2`.

More important, if a child class has the IMPLEMENTS attribute for an interface implemented above it in the hierarchy, **not all of the interface's methods have to be overridden**.

In the example code above, the `child` class may only re-implement the `m2` method. If some of the interface's methods are not re-implemented in a child class, the compiler generates stub functions for them, which contain the proper jump instructions to the nearest implementation going up in the hierarchy. So in the above example, if the `child.IFace.M1` method is not implemented explicitly, the compiler will generate code for it which calls the implementation in the Parent class! This is a huge advantage and flexibility in Clarion 6.3.

The example code below shows a very simple program using these concepts.

```
PROGRAM
MAP
END

IFace INTERFACE
MyIProc PROCEDURE
MyIProc2 PROCEDURE
MyIProc3 PROCEDURE
END

Base CLASS, IMPLEMENTS (IFace)
cMyProc PROCEDURE
END

Child CLASS (Base), IMPLEMENTS (IFace) !Valid only in Clarion 6.3 and greater
bMyProc PROCEDURE
END

AnotherChild CLASS (Base)
IChild &IFace
END

CODE
Base.cMyProc
Child.bMyProc
Child.cMyProc !Calls Base.cMyProc
Base.IFace.MyIProc
Child.IFace.MyIProc !comments:
!Prior to C 6.3, if the user ignores the "duplicate label warning" it really
!calls the parent's base.iface.MyIProc method. In C6.3 and greater, it calls
!the child.iface.MyIProc implementation.

Child.IFace.MyIProc2 !Calls Base.IFace.MyIProc2
Child.IFace.MyIProc3 !Calls Base.IFace.MyIProc3

!procs/methods
Base.cMyProc PROCEDURE
CODE
MESSAGE('Base.cMyProc')

Child.bMyProc PROCEDURE
CODE
MESSAGE('Child.bMyProc')

! interface implements
Base.IFace.MyIProc PROCEDURE
CODE
MESSAGE('Base.IFace.MyIProc')

Base.IFace.MyIProc2 PROCEDURE
CODE
MESSAGE('Base.IFace.MyIProc2')

Base.IFace.MyIProc3 PROCEDURE
CODE
MESSAGE('Base.IFace.MyIProc3')

Child.IFace.MyIProc PROCEDURE
CODE
MESSAGE('Child.IFace.MyIProc')
```



An important note regarding the above example. Consider this CLASS definition:

```
Child CLASS (Base) , IMPLEMENTS (IFace)
bMyProc  PROCEDURE
    END
```

The `Child` class actually only implements ONE method from the `IFace` interface, but the code calls *all three* interface methods.

**See Also:**

INTERFACE

IMPLEMENTS

## INNER (set inner join operation)

### INNER

The **INNER** attribute (PROP:INNER) specifies the JOIN structure declares an "inner join" instead of the default "left outer join."

The VIEW structure defaults to a "left outer join," where all records for the VIEW's *primary file* are retrieved whether the secondary file named in the JOIN structure contains any related records or not. Specifying the INNER attribute on the JOIN creates an "inner join" so that only those *primary file* records with related secondary file records are retrieved. Inner joins are normally more efficient than outer joins.

PROP:INNER is an array property of a VIEW indicating the presence or absence of the INNER attribute on a specific JOIN. Each array element returns one ('1') if the JOIN has the INNER attribute and blank ("") if it does not. The JOINS are numbered within the VIEW starting with 1 as they appear within the VIEW structure.

PROP:INNER is read-only for non-SQL views and read/write for SQL based views.

#### Example:

```
AVIEW VIEW(BaseFile)
    JOIN(ParentFile,'BaseFile.parentID = ParentFile.ID')          !JOIN 1
    JOIN(GrandParent.PrimaryKey, ParentFile.GrandParentID)      !JOIN 2
    END
    END
    JOIN(OtherParent.PrimaryKey,BaseFile.OtherParentID),INNER !JOIN 3
    END
    END

! AVIEW{PROP:Inner,1} returns ''
! AVIEW{PROP:Inner,2} returns ''
! AVIEW{PROP:Inner,3} returns '1'

ViewOrder VIEW(Customer),ORDER('-Hea:OrderDate,Cus:Name')
    PROJECT(Cus:AcctNumber,Cus:Name,Cus:Zip)
    JOIN(Hea:AcctKey,Cus:AcctNumber),INNER      !Inner Join on Header
    PROJECT(Hea:OrderNumber,Hea:OrderDate)      ! gets only customers with orders
    JOIN(Dtl:OrderKey,Hea:OrderNumber),INNER    !Inner join on Detail file
    PROJECT(Det:Item,Det:Quantity)              ! is natural and more efficient
    JOIN(Pro:ItemKey,Dtl:Item),INNER            !Inner join on Product file
    PROJECT(Pro:Description,Pro:Price)          ! is natural and more efficient
    END
    END
    END
    END
```

#### See Also:

JOIN

## LINK (specify CLASS link into project)

**LINK**( *linkfile*, [ *flag* ] )

---

<b>LINK</b>	Names a file to add to the link list for the current project.
<i>linkfile</i>	A string constant naming an file (without an extension .OBJ is assumed) to link into the project. Normally, this would be the same as the parameter to the MODULE attribute, but may explicitly name a .LIB or .OBJ file.
<i>flag</i>	A numeric constant, equate, or Project system define which specifies the attribute as active or not. If the <i>flag</i> is zero or omitted, the attribute is not active, just as if it were not present. If the <i>flag</i> is any value other than zero, the attribute is active.

A **LINK** attribute of a CLASS structure names a *linkfile* to add to the compiler's link list for the project. LINK is only valid on a CLASS structure.

**Example:**

```
OneClass CLASS,MODULE('OneClass'),LINK('OneClass',1)      !Link in OneClass.OBJ
LoadIt      PROCEDURE
ComputeIt    PROCEDURE
            END
```

**See Also:**

CLASS

MEMBER

MODULE

## LINK (specify CLASS link into project)

**LINK**( *linkfile*, [ *flag* ] )

---

**LINK** Names a file to add to the link list for the current project.

*linkfile* A string constant naming an file (without an extension .OBJ is assumed) to link into the project. Normally, this would be the same as the parameter to the MODULE attribute, but may explicitly name a .LIB or .OBJ file.

*flag* A numeric constant, equate, or Project system define which specifies the attribute as active or not. If the *flag* is zero or omitted, the attribute is not active, just as if it were not present. If the *flag* is any value other than zero, the attribute is active.

A **LINK** attribute of a CLASS structure names a *linkfile* to add to the compiler's link list for the project. LINK is only valid on a CLASS structure.

**Example:**

```
OneClass CLASS,MODULE('OneClass'),LINK('OneClass',1)      !Link in OneClass.OBJ
LoadIt      PROCEDURE
ComputeIt    PROCEDURE
END
```

**See Also:**

CLASS

MEMBER

MODULE

## MODULE (specify CLASS member source file)

**MODULE**(*sourcefile*)

**MODULE** Names a MEMBER module or external library file.

*sourcefile* A string constant. If the *sourcefile* contains Clarion language source code, this specifies the filename (extension is optional) of the source file that contains the PROCEDURES. If the *sourcefile* is an external library, this string may contain any unique identifier.

A **MODULE** attribute of a CLASS structure names a MEMBER module or external library file which contains the PROCEDURE definitions for the CLASS's member methods. MODULE is only valid on a CLASS structure.

**Example:**

```
OneClass CLASS,MODULE('OneClass')    !Method definitions in OneClass.CLW
LoadIt    PROCEDURE                  !LoadIt procedure prototype
ComputeIt PROCEDURE                  !ComputeIt procedure prototype
      END
```

**See Also:**

CLASS

MEMBER

LINK

PROCEDURE Prototypes

## NOCASE (case insensitive KEY or INDEX)

### NOCASE

---

The **NOCASE** attribute (PROP:NOCASE) of a KEY or INDEX declaration makes the sorted sequence of alphabetic characters insensitive to the ASCII upper/lower case sorting convention. All alphabetic characters in key fields are converted to upper case as they are written to the KEY. This case conversion has no effect on the case of the stored data. The NOCASE attribute has no effect on non-alphabetic characters.

#### Example:

```
Names      FILE,DRIVER('Clarion'),PRE(Nam)
NameKey    KEY(Nam:Name),NOCASE      !Declare name key, make case insensitive
NbrKey     KEY(Nam:Number)           !Declare number key
Rec        RECORD
Name       STRING(20)
Number     SHORT
           END
           END
```

#### See Also:

INDEX

KEY

## OEM (set international string support)

### OEM

The **OEM** attribute (PROP:OEM) specifies that the FILE on which it is placed contains non-English language string data that was stored by a DOS based program or needs to be read by a DOS based program. These strings are automatically translated from the OEM ASCII character set data contained in the file to the ANSI character set for display in Windows. All string data in the record is automatically translated from the ANSI character set to the OEM ASCII character set before the record is written to disk.

The specific OEM ASCII character set used for the translation comes from the DOS code page loaded by the *country*.SYS file. This makes the data file specific to the language used for that code page, and means the data may not be useable on a computer with a different code page loaded. This attribute may not be supported by all file systems; consult the specific file driver's documentation.

#### Example:

```
Cust  FILE,DRIVER('TopSpeed'),PRE(Cus),OEM  !Contains international strings
CustKey  KEY(Cus:Name)
Record  RECORD
Name    STRING(20)
      END
      END

Screen WINDOW('Window')
      ENTRY(@S20),USE(Cus:Name)
      BUTTON('&OK'),USE(?Ok),DEFAULT
      BUTTON('&Cancel'),USE(?Cancel)
      END

CODE
OPEN(Cust)          !Open Cust file
SET(Cust)
NEXT(Cust)          !Get record, ASCII strings are automatically
                   ! translated to ANSI character set
OPEN(Screen)        !Open window and display ANSI data
ACCEPT
CASE FIELD()
OF ?Ok
CASE EVENT()
OF EVENT:Accepted
  PUT(Cust)          !Put record, ANSI strings are automatically
                   ! translated to the OEM ASCII character set
                   ! per the loaded DOS code page

  BREAK
END
END
END
CLOSE(Screen)
CLOSE(Cust)
```

#### See Also:

Environment Files

LOCALE

## OPT (exclude null KEY or INDEX entries)

### OPT

---

The **OPT** attribute (PROP:OPT) excludes entries in the KEY or INDEX for records with "null" values in all fields comprising the KEY or INDEX. For the purpose of this attribute, a "null" value is defined as zero in a numeric field or all blank spaces (20h) in a string field.

#### Example:

```
Names    FILE,DRIVER('Clarion'),PRE(Nam)  !Declare a file structure
NameKey  KEY(Nam:Name),OPT                 !Declare name key, exclude blanks
NbrKey   KEY(Nam:Number),OPT               !Declare number key, exclude zeroes
Rec      RECORD
Name     STRING(20)
Number   SHORT
          END
          END
```

#### See Also:

INDEX

KEY



## ORDER (set view sort order expression)

**ORDER**(*expression list*)

---

**ORDER** Specifies an *expression list* used to sort the records in the VIEW.

*expression list* A single string constant containing one or more expressions. Each expression in the list must be separated by a comma from the preceding expression.

The **ORDER** attribute (PROP:ORDER) specifies an *expression list* used to sort the records in the VIEW. The expressions within the *expression list* evaluate from left to right, with the leftmost expression defining the most significant sort and the rightmost defining the least significant sort. Expressions that begin with a unary minus (-) sort in descending order.

The *expression* may reference any field in the VIEW, at all levels of JOIN structures. The expressions in the *expression list* may contain any valid Clarion language expression. The *expression list* is evaluated at runtime (just like the EVALUATE procedure), therefore you must BIND all variables used in the *expression*.

For non-SQL file systems, the VIEW will use keys to do most of the sorting wherever possible, sorting only groups of records which have the same key values, keeping one 'bucket' sorted. Therefore, additional sort fields on top of a key can be quite efficient.

For SQL file systems, PROP:SQLOrder is an SQL-only equivalent to PROP:ORDER. For both of these properties, if the first character of the expression assigned to them is a plus sign (+) then that expression is concatenated to the existing order expression. For PROP:SQLOrder, if the first character of the expression assigned is a minus sign (-) then the existing order expression is concatenated to that expression. If the first character is not plus (or minus), the new expression overrides the existing expression.

**Example:**

```
!Orders sorted in descending date order, then customer name (by name within each date)
ViewOrder VIEW(Customer), ORDER('-Hea:OrderDate,Cus:Name')
    PROJECT(Cus:AcctNumber,Cus:Name,Cus:Zip)
    JOIN(Hea:AcctKey,Cus:AcctNumber)                !Join Header file
    PROJECT(Hea:OrderNumber,Hea:OrderDate)
    JOIN(Dtl:OrderKey,Hea:OrderNumber)              !Join Detail file
    PROJECT(Det:Item,Det:Quantity)
    JOIN(Pro:ItemKey,Dtl:Item)                      !Join Product file
    PROJECT(Pro:Description,Pro:Price)
    END
    END
    END
    END
CODE
ViewOrder{PROP:ORDER} = '-Hea:OrderDate,Pro:Price-Det:DiscountPrice'
!Orders sorted by greatest discount within descending order date

!ABC Implementation example of PROP:SQLORDER
!For browse, after files and window are opened

BRW1::View:Browse{PROP:SQLOrder} = 'Phone'

!where Phone is a column name in SQL database
!For reports, after files and progress window are opened:

Process:View{PROP:SQLOrder} = 'au_lname'

!where au_lname is a column name in SQL database
```

**See Also:**

BIND

UNBIND

EVALUATE

## OVER (set shared memory location)



**OVER**(*overvariable*)

**OVER** Allows one memory address to be referenced two different ways.

*overvariable* The label of a variable that already occupies the memory to be shared.

The **OVER** attribute allows one memory address to be referenced two different ways. The variable declared with the OVER attribute must not be larger than the *overvariable* it is being declared OVER (it may be smaller, though).

You may declare a variable OVER an *overvariable* which is part of the parameter list passed into a PROCEDURE.

A field within a GROUP structure cannot be declared OVER a *variable* outside that GROUP structure.

### Example:

```
SomeProc PROCEDURE (PassedGroup)      !Proc receives a GROUP parameter

NewGroup GROUP, OVER (PassedGroup)    !Redeclare passed GROUP parameter
Field1  STRING(10)                    !Compiler warning issued that
Field2  STRING(2)                     !NewGroup must not be larger
      END                             !than PassedGroup

CustNote FILE, PRE (Csn)               !Declare CustNote file
Notes   MEMO(2000)                     !The memo field
Record  RECORD
CustID   LONG
      END
      END

CsnMemoRow STRING(10), DIM(200), OVER (Csn:Notes)
      !Csn:Notes memo may be addressed
      ! as a whole or in 10-byte chunks
```

### See Also:

DIM

## OWNER (declare password for data encryption)

**OWNER**(*password*)

---

**OWNER**            Specifies a file encryption password.

*password*            A string constant or variable.

The **OWNER** attribute (PROP:OWNER) specifies the *password* which is used by the ENCRYPT attribute to encrypt the data. An "Invalid Data File" error occurs if the *password* does not match the password that was actually used to encrypt the file.

An OWNER attribute without an accompanying ENCRYPT attribute is allowed by some file systems.

If the file is declared without the THREAD attribute, the variable used with the OWNER attribute should also be declared without the THREAD attribute.

**Example:**

```
Customer FILE, DRIVER('Clarion'), OWNER('abCdeF'), ENCRYPT !Encrypt data password "abCdeF"
Record   RECORD
Name     STRING(20)
        END
        END
```

**See Also:**

ENCRYPT

EXTERNAL

## PRE (set label prefix)

**PRE**( [ *prefix* ] )

**PRE** Provides a label prefix for complex data structures.

*prefix* Acceptable characters are alphabet letters, numerals 0 through 9, and the underscore character. A *prefix* must start with an alpha character or underscore. By convention, a *prefix* is 1-3 characters, although it can be longer.

The **PRE** attribute provides a label prefix for a FILE, QUEUE, GROUP, REPORT, or ITEMIZE structure. PRE is also valid on a LIKE declaration to provide a separate prefix when LIKE is used to declare another copy of a complex data structure.

PRE is used to distinguish between identical variable names that occur in different structures. When a data element from a complex data structure is referenced in executable statements, assignments, and parameter lists, the *prefix* is attached to its label by a colon (Pre:Label).

PRE is essentially a legacy attribute which is being replaced by a more flexible method to distinguish between identical variable names that occur in different structures: Field Qualification syntax. When referenced in executable statements, assignments, and parameter lists, the label of the structure containing the field is attached to the field label by a period (GroupName.Label).

### Example:

```
MasterFile FILE, DRIVER('Clarion'), PRE(Mst)      !Declare master file layout
Record      RECORD
AcctNumber  LONG   !Referenced as Mst:AcctNumber or MasterFile.AcctNumber
END
END

Detail      FILE, DRIVER('Clarion'), PRE(Dtl)      !Declare detail file layout
Record      RECORD
AcctNumber  LONG   !Referenced as Dtl:AcctNumber or Detail.AcctNumber
END
END

SaveQueue   QUEUE, PRE(Sav)
AcctNumber  LONG   !Referenced as Sav:AcctNumber or SaveQueue.AcctNumber
END
END

G1          GROUP, PRE(Mem)                        !Declare some memory variables
Message     STRING(30)                             !with the Mem prefix
END
END

G2          LIKE(G1), PRE(Me2)                     !Another GROUP LIKE the first containing same
CODE                                                !variables using the "Me2" prefix
IF Dtl:AcctNumber <> Mst:AcctNumber !Is it a new account
  Mem:Message = 'New Account'      !display message
  Me2:Message = 'Variable in LIKE group'
END
IF Detail.AcctNumber <> Masterfile.AcctNumber !Same expression
  G1.Message = 'New Account'      ! display message
  G2.Message = 'Same Variable in LIKE group'
END
END
```

**See Also:** Reserved Words, Field Qualification

## PRIMARY (set relational primary key)

### PRIMARY

The **PRIMARY** attribute (PROP:PRIMARY) specifies the KEY is unique, includes all records in the file, and does not allow "null" values in any of the fields comprising the KEY. This is the definition of a file's "Primary Key" per the relational database theory as expressed by E. F. Codd.

#### Example:

```
Names      FILE, DRIVER('TopSpeed'), PRE (Nam)      !Declare a file structure
NameKey     KEY (Nam:Name), OPT                      !Declare name key, exclude blanks
NbrKey      KEY (Nam:Number), PRIMARY                !Declare number key as the primary key
Rec         RECORD
Name        STRING (20)
Number      SHORT
            END
            END
```

#### See Also:

KEY

## PRIVATE (set variable private to a CLASS module)

### PRIVATE

The **PRIVATE** attribute specifies that the variable on which it is placed is visible only to the PROCEDURES defined within the source module containing the methods of the CLASS structure (whether members of the CLASS or not). This encapsulates the data from other CLASSES.

PRIVATE is also valid when used with static (threaded or non-threaded) variables outside of a CLASS structure. If a static variable is declared with the PRIVATE attribute, the compiler generates it without a public external name. Hence, it can only be used by procedures defined in the same source module.

#### Example:

```
OneClass CLASS,MODULE('OneClass.CLW'),TYPE
PublicVar LONG !Declare a Public variable
PrivateVar LONG,PRIVATE !Declare a Private variable
BaseProc PROCEDURE(REAL Parm)!Declare a Public method
END
TwoClass OneClass !Instance of OneClass
CODE
TwoClass.PublicVar = 1 !Legal assignment
TwoClass.PrivateVar = 1 !Illegal assignment

!OneClass.CLW contains:
MEMBER()
MAP
SomeLocalProc PROCEDURE
END
OneClass.BaseProc PROCEDURE(REAL Parm)
CODE
SELF.PrivateVar = Parm !Legal assignment
SomeLocalProc PROCEDURE
CODE
TwoClass.PrivateVar = 1 !Legal assignment
```

#### See Also:

CLASS

PROTECTED

## PROTECTED (set variable private to a CLASS or derived CLASS)

### PROTECTED

The **PROTECTED** attribute specifies that the variable on which it is placed is visible only to the PROCEDURES declared within the same CLASS structure (the methods of that CLASS) and any CLASS derived from the CLASS in which it is declared. This encapsulates the data from any code external to the specific CLASS and its derived CLASSES.

The purpose of the **PROTECTED** attribute is to provide a level of encapsulation between public and **PRIVATE**. All **PROTECTED** data and methods are available for use within their own **CLASS** and derived **CLASSES**, but not available to any code outside those specific **CLASSES**.

You could think of these as "semiprivate".

#### Example:

```
OneClass CLASS,MODULE('OneClass.CLW'),TYPE
PublicVar    LONG                !Declare a Public variable
ProtectedVar LONG,PROTECTED      !Declare a Protected variable
BaseProc     PROCEDURE(REAL Parm) !Declare a Public method
END

TwoClass OneClass                !Instance of OneClass
CODE
  TwoClass.PublicVar = 1          !Legal assignment
  TwoClass.ProtectedVar = 1       !Legal assignment, illegal if PRIVATE

!OneClass.CLW contains:
MEMBER()
MAP
SomeLocalProc PROCEDURE
END

OneClass.BaseProc PROCEDURE(REAL Parm)
CODE
  SELF.ProtectedVar = Parm        !Legal assignment

SomeLocalProc PROCEDURE
CODE
  TwoClass.ProtectedVar = 1        !Legal assignment
```

#### See Also:

CLASS



## RECLAIM (reuse deleted record space)

### RECLAIM

---

The **RECLAIM** attribute (PROP:RECLAIM) specifies that the file driver adds new records to the file in the space previously used by a record that has been deleted, if available. Otherwise, the record is added at the end of the file. Implementation of RECLAIM is file driver specific and may not be supported in all file systems.

#### Example:

```
Names  FILE, DRIVER('Clarion'), RECLAIM !Reuse deleted record space
Record RECORD
Name    STRING(20)
        END
        END
```

## STATIC (set allocate static memory)

### STATIC

---

The STATIC attribute specifies permanent memory allocation to a variable, GROUP, or data buffer of a QUEUE. If it is used with variables declared within a PROCEDURE, they are allocated statically instead of using stack memory. STATIC makes values contained in the local variable or QUEUE data buffer "persistent" from one call to the procedure to the next. Static local variables that require initialization are initialized once only during the first call to the respective procedure or routine. Regarding a QUEUE structure, only the data buffer is allocated static memory -- QUEUE entries are always allocated memory dynamically on the heap.



A class method (except CONSTRUCT, DESTRUCT and methods defined in local classes (classes declared locally in a procedure)), field, property, or event can be STATIC. This makes them callable on a class even when no instance of the class has been created. If any instances of the class are created, they cannot be used to access the static member. Only one copy of static fields and events exists, and static methods and properties can only access static fields and static events. Static members are often used to represent data or calculations that do not change in response to object state; for instance, a math library might contain static methods for calculating sine and cosine.

A static member belongs to the type itself rather than to a specific object.

To access a static member of a class use the following syntax:

*class\_name.member\_name*

**Example:**

```

AAA          CLASS

GETINSTANCE  PROCEDURE () ,AAA,STATIC

                END

...

! Accessing the static method
FF      &AAA

FF&=AAA.GETINSTANCE ()

SomeProc  PROCEDURE
SaveQueue QUEUE,STATIC      !Static QUEUE data buffer
Field1    LONG              !Value retained between
Field2    STRING            !procedure calls
                END

AcctFile   STRING(64),STATIC  !STATIC needed for use as
                                !variable in NAME attribute

Transactions  FILE,DIVER('Clarion'),PRE(TRA),NAME(AcctFile)
AccountKey    KEY(TRA:Account),OPT,DUP
Record        RECORD
Account       SHORT          !Account code
Date          LONG           !Transaction Date
Amount        DECIMAL(13,2)   !Transaction Amount
                END
                END

```

**See Also:**

Data Declarations and Memory Allocation

## THREAD (set thread-specific memory allocation)

### THREAD

---

The **THREAD** attribute declares a variable, FILE, GROUP, QUEUE, or CLASS which is allocated memory separately for each execution thread in the program. This makes the values dependent upon which thread is executing.

A threaded variable must be allocated static memory, so Local data with the THREAD attribute is automatically considered STATIC. This attribute creates runtime "overhead," particularly on Global or Module data. Therefore, it should be used only when necessary.

In multi-DLL applications, if the THREAD attribute is declared on any of the above valid types, any reference to these types in an associated executable or another DLL must also include the THREAD attribute.

#### Variable and GROUP Usage

---

The THREAD attribute declares a static variable which is allocated memory separately for each execution thread in the program. This makes the value contained in the variable dependent upon which thread is executing. Whenever a new execution thread is begun, a new instance of the variable, specific to that thread, is created and initialized to blank or zero (unless the AUTO attribute is also present).

#### FILE Usage

---

The THREAD attribute (PROP:THREAD--valid only for a FILE) on a FILE declaration allocates memory for its record buffer, file control block, and other file structure elements separately for each execution thread as each thread is started. This makes the values contained in the record buffer and other file elements dependent upon which thread is executing. Memory for its record buffer, file control block, and other file elements is deallocated when the thread is closed.

Instances of a threaded FILE are considered independent FILEs. Therefore, a FILE must be OPENed and CLOSEd for each new instance.

#### QUEUE Usage

---

The THREAD attribute on a QUEUE declaration declares a static QUEUE data buffer which is allocated memory separately for each execution thread in the program. This makes the values contained in the QUEUE dependent upon which thread is executing. Whenever a new execution thread is begun, a new instance of the QUEUE, specific to that thread, is created.

**Example:**

```

PROGRAM
MAP
Thread1  PROCEDURE
Thread2  PROCEDURE
END

Names    FILE, DRIVER('Clarion'), PRE(Nam), THREAD  !Threaded file
NbrNdx   INDEX(Nam: Number), OPT
Rec      RECORD
Name     STRING(20)
Number   SHORT
        END
        END

GlobalVar LONG, THREAD      !Each execution thread gets its own copy OF GlobalVar

CODE
START(Thread1)
START(Thread2)

Thread1  PROCEDURE
LocalVar LONG, THREAD      !Local threaded variable (automatically STATIC)
CODE
OPEN(Names)                !OPEN creates new record buffer instance
SET(Names)                 !containing the first record in the file
NEXT(Names)

Thread2  PROCEDURE
SaveQueue QUEUE, THREAD    !Static QUEUE data buffer Thread-specific QUEUE
Name     STRING(20)
Number   SHORT
        END
CODE
OPEN(Names)                !OPEN creates another new record buffer instance
SET(Names)                 !containing the last record in the file
PREVIOUS(Names)

```

**See Also:**

START

Data Declarations and Memory Allocation

STATIC

AUTO

Thread Design Considerations

## TYPE (type definition)

### TYPE

The **TYPE** attribute creates a type definition for a FILE, GROUP, QUEUE, or CLASS (a "named structure"). The label of the named structure can then be used as a data type to define other similar FILES, GROUPS, QUEUES, or CLASSES (or you can use LIKE). TYPE may also be used to define named structures passed to PROCEDURES, allowing the receiving procedure to directly address components of the type definition using Field Qualification syntax.

A FILE, GROUP, QUEUE, or CLASS declaration with the TYPE attribute is not allocated any memory. While the data members of a CLASS with the TYPE attribute are not allocated memory, the methods prototyped in the CLASS must be defined for use by any subsequent objects declared as that type. EXTERNAL and DLL are irrelevant.

When a type definition is used to pass a named structure as a parameter to a PROCEDURE, the receiving procedure may directly address component fields in the passed QUEUE using the Field Qualification syntax. This is the preferred method of addressing the components of the passed structure.

There is also a legacy method of addressing the components of the passed structure. The named structure parameter declaration on the PROCEDURE definition statement (not the prototype) can instantiate a local prefix for the passed QUEUE as it names the passed QUEUE for the procedure. For example, PROCEDURE(LOC:PassedQueue) declares the procedure uses the LOC: prefix (along with the individual field names used in the type definition) to directly address component fields of the QUEUE passed as the parameter using the same type of syntax that the PRE attribute specifies. However, using Field Qualification syntax is preferable--locally instantiated prefixes are only maintained for backward compatibility.

#### Example:

```
MAP
MyProc1  PROCEDURE(PassQue) !Passes a QUEUE defined the same as PassGroup
END

PassQue QUEUE,TYPE          !Type-definition for passed QUEUE parameters
First   STRING(20)          !first name
Middle  STRING(1)           !middle initial
Last    STRING(20)          !last name
END

NameQue  QUEUE(PassQue)      !Name queue-- same structure as PassQue
END                                           !End queue declaration

CODE
MyProc1(NameQue)              !Call proc passing NameQue as parameter

MyProc1 PROCEDURE(PassedQue) !Proc to receive QUEUE parameter
LocalVar STRING(20)
CODE
LocalVar = PassedQue.First  !Assign NameQue.First to LocalVar from parameter
```

**See Also:** Field Qualification, Prototype Parameters Lists, CLASS, GROUP, FILE

## 6 - Windows

### APPLICATION (declare an MDI frame window)



```

label  APPLICATION('title')  [,AT( )] [,CENTER] [,SYSTEM] [,MAX] [,ICON( )] [,STATUS( )] [,HLP( )]
                                     [,CURSOR( )] [,TIMER( )] [,ALRT( )] [,ICONIZE] [,MAXIMIZE] [,MASK]
                                     [,FONT( )] [,MSG( )] [,IMM] [,AUTO] [,PALETTE()] [,LAYOUT( )]
                                     [,WALLPAPER( )]  [,| TILED| ]      [,| HSCROLL| ]      [,| DOUBLE| ]
                                                         | CENTERED|      | VSCROLL|      | NOFRAME|
                                                         | HVSCROLL|      | RESIZE|

[ MENUBAR
    multiple menu and/or item declarations
END ]

[ TOOLBAR
    multiple control field declarations
END ]

END

```

---

**APPLICATION** Declares a Multiple Document Interface (MDI) frame.

*Label* A valid Clarion label (required).

*Title* Specifies the title text for the application window (PROP:Text).

**AT** Specifies the initial size and location of the application window (PROP:AT). If omitted, default values are selected by the runtime library.

**CENTER** Specifies that the window's initial position is centered in the screen by default (PROP:CENTER). This attribute takes effect only if at least one parameter of the **AT** attribute is omitted.

**SYSTEM** Specifies the presence of a system menu (PROP:SYSTEM).

**MAX** Specifies the presence of a maximize control (PROP:MAX).

<b>ICON</b>	Specifies the presence of a minimize control, and names a file or standard icon identifier for the icon displayed when the window is minimized (PROP:ICON).
<b>STATUS</b>	Specifies the presence of a status bar at the base of the application window (PROP:STATUS).
<b>HLP</b>	Specifies the "Help ID" associated with the APPLICATION window and provides the default for any child windows (PROP:HLP).
<b>CURSOR</b>	Specifies a mouse cursor to be displayed when the mouse is positioned over the APPLICATION window (PROP:CURSOR). If omitted, the Windows default cursor is used.
<b>TIMER</b>	Specifies periodic timed event generation (PROP:TIMER).
<b>ALRT</b>	Specifies "hot" keys active for the APPLICATION (PROP:ALRT).
<b>ICONIZE</b>	Specifies the APPLICATION is opened as an icon (PROP:ICONIZE).
<b>MAXIMIZE</b>	Specifies the APPLICATION is maximized when opened (PROP:MAXIMIZE).
<b>MASK</b>	Specifies pattern input editing mode of all ENTRY controls in the TOOLBAR (PROP:MASK).
<b>FONT</b>	Specifies the default font for all controls in the toolbar (PROP:FONT).
<b>MSG</b>	Specifies a string constant containing the default text to display in the status bar for all controls in the APPLICATION (PROP:MSG).
<b>IMM</b>	Specifies the window generates events whenever it is moved or resized (PROP:IMM).
<b>AUTO</b>	Specifies all toolbar controls' USE variables re-display on screen each time through the ACCEPT loop (PROP:AUTO).
<b>PALETTE</b>	Specifies the number of hardware colors used for graphics in the window (PROP:PALETTE).
<b>LAYOUT</b>	Indicates the orientation of window controls and field sequence. A style of (1) essentially "flips" the window controls' display as a mirror image of the layout specified in the Window Formatter. Default field navigation moves from right to left.
<b>WALLPAPER</b>	Specifies the background image to display in the window's client area (PROP:WALLPAPER). The image stretches to fill the entire client area of the window unless the TILED or CENTERED attribute is also present.
<b>TILED</b>	Specifies the WALLPAPER image displays at its default size and is tiled to fill the entire client area of the window (PROP:TILED).
<b>CENTERED</b>	Specifies the WALLPAPER image displays at its default size and is centered in the entire client area of the window (PROP:CENTERED).
<b>HSCROLL</b>	Specifies horizontal scroll bar is automatically added to the application frame when any portion of a child window lies horizontally outside the visible area (PROP:FSCROLL).



<b>VSCROLL</b>	Specifies a vertical scroll bar is automatically added to the application frame when any portion of a child window lies vertically outside the visible area (PROP:VSCROLL).
<b>HVSCROLL</b>	Specifies both vertical and horizontal scroll bars are automatically added to the application frame when any portion of a child window lies outside the visible area.
<b>DOUBLE</b>	Specifies a double-width frame around the window (PROP:DOUBLE).
<b>NOFRAME</b>	Specifies a window with no frame (PROP:NOFRAME).
<b>RESIZE</b>	Specifies a thick frame around the window which does allow window resizing (PROP:RESIZE).
<b>MENUBAR</b>	Defines the menu structure (optional). The menu specified in an APPLICATION is the "Global menu."
<b>TOOLBAR</b>	Defines a toolbar structure (optional). The toolbar specified in an APPLICATION is the "Global toolbar."

**APPLICATION** declares a Multiple Document Interface (MDI) frame window. MDI is a part of the standard Windows interface, and is used by Windows applications to present several "views" in different windows. This is a way of organizing and grouping these. The MDI frame window (APPLICATION structure) acts as a "parent" for all the MDI "child" windows (WINDOW structures with the MDI attribute). These MDI "child" windows are clipped to the APPLICATION frame and automatically moved when the frame is moved, and can be totally concealed by minimizing the parent.

There may be only one APPLICATION window open at any time in a Clarion Windows program, and it must be opened before any MDI "child" windows may be opened. However, non-MDI windows may be opened before or after the APPLICATION is opened, and may be on the same execution thread as the APPLICATION.

An MDI "child" window must not be on the same execution thread as the APPLICATION. Therefore, any MDI "child" window called directly from the APPLICATION must be in a separate procedure so the START procedure can be used to begin a new execution thread. Once started, multiple MDI "child" windows may be called in the new thread.

A "conventional" APPLICATION window would have the ICON, MAX, STATUS, RESIZE, and SYSTEM attributes. This creates an application frame window with minimize and maximize buttons, a status bar, a resizable frame, and a system menu. It would also have a MENUBAR structure containing the global menu items, and may have a TOOLBAR with "shortcuts" to global menu items. These attributes create a standard Windows look and feel for the application frame.

An APPLICATION window may not contain controls except within its MENUBAR and TOOLBAR structures, and cannot be used for any output. For output, document windows or dialog boxes are required (defined using the WINDOW structure).

When the APPLICATION window is first opened, it remains hidden until the first DISPLAY statement or ACCEPT loop is encountered. This enables any changes to be made to the appearance before it is displayed. Events for the APPLICATION window are processed by the first ACCEPT loop encountered after the APPLICATION window is first opened.

**Events Generated:**

EVENT:PreAlertKey	The user pressed an ALRT attribute hot key.
EVENT:AlertKey	The user pressed an ALRT attribute hot key.
EVENT:CloseWindow	The window is closing.
EVENT:CloseDown	The application is closing.
EVENT:OpenWindow	The window is opening.
EVENT:LoseFocus	The window is losing focus to another thread.
EVENT:GainFocus	The window is gaining focus from another thread.
EVENT:Timer	The TIMER attribute has triggered.
EVENT:Move	The user is moving the window. CYCLE aborts the move.
EVENT:Moved	The user has moved the window.
EVENT:Size	The user is resizing the window. CYCLE aborts the resize.
EVENT:Sized	The user has resized the window.
EVENT:Restore	The user is restoring the window's previous size. CYCLE aborts the resize.
EVENT:Restored	The user has restored the window's previous size.
EVENT:Maximize	The user is maximizing the window. CYCLE aborts the resize.
EVENT:Maximized	The user has maximized the window.
EVENT:Iconize	The user is minimizing the window. CYCLE aborts the resize.
EVENT:Iconized	The user has minimized the window.
EVENT:Completed	AcceptAll (non-stop) mode has finished processing all the window's controls.
EVENT:DDErequest	A client has requested a data item from this Clarion DDE server application.
EVENT:DDEadvise	A client has requested continuous updates of a data item from this Clarion DDE server application.
EVENT:DDEexecute	A client has executed a DDEEXECUTE statement to this Clarion DDE server application.
EVENT:DDEpoke	A client has sent unsolicited data to this Clarion DDE server application.
EVENT:DDEdata	A DDE server has supplied an updated data item to this Clarion client application.

EVENT:DDEclosed      A DDE server has terminated the DDE link to this Clarion client application.

#### Related Procedures:

ACCEPT, ALERT, EVENT, POST, REGISTER, UNREGISTER, YIELD, ACCEPTED, CHANGE, CHOICE, CLOSE, CONTENTS, CREATE, DESTROY, DISABLE, DISPLAY, ENABLE, ERASE, FIELD, FIRSTFIELD, FOCUS, GETFONT, GETPOSITION, HELP, HIDE, INCOMPLETE, LASTFIELD, MESSAGE, MOUSEX, MOUSEY, OPEN, POPUP, SELECT, SELECTED, SET3DLOOK, SETCURSOR, SETFONT, SETPOSITION, SETTARGET, UNHIDE, UPDATE

#### Example:

```
!An MDI application frame window with system menu, minimize and maximize
! buttons, a status bar, scroll bars, and a resizable frame, containing the
! main menu and toolbar for the application:
MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS |
,HVSCROLL,RESIZE
  MENUBAR
    MENU('&File'),USE(?FileMenu)
    ITEM('&Open...'),USE(?OpenFile)
    ITEM('&Close'),USE(?CloseFile),DISABLE
    ITEM('E&xit'),USE(?MainExit)
  END
  MENU('&Edit'),USE(?EditMenu)
  ITEM('Cu&t'),USE(?CutText),KEY(CtrlX),STD(STD:Cut),DISABLE
  ITEM('&Copy'),USE(?CopyText),KEY(CtrlC),STD(STD:Copy),DISABLE
  ITEM('&Paste'),USE(?PasteText),KEY(CtrlV),STD(STD:Paste),DISABLE
  END
  MENU('&Window'),STD(STD:WindowList),LAST
  ITEM('&Tile'),STD(STD:TileWindow)
  ITEM('&Cascade'),STD(STD:CascadeWindow)
  ITEM('&Arrange Icons'),STD(STD:ArrangeIcons)
  END
  MENU('&Help'),USE(?HelpMenu)
  ITEM('&Contents'),USE(?HelpContents),STD(STD:HelpIndex)
  ITEM('&Search...'),USE(?HelpSearch),STD(STD:HelpSearch)
  ITEM('&How to Use Help'),USE(?HelpOnHelp),STD(STD:HelpOnHelp)
  ITEM('&About MyApp...'),USE(?HelpAbout)
  END
  END
  TOOLBAR
    BUTTON('E&xit'),USE(?MainExitButton)
    BUTTON('&Open'),USE(?OpenButton),ICON(ICON:Open)
  END
  END
CODE
OPEN(MainWin)           !Open APPLICATION
ACCEPT                  !Display APPLICATION and accept user input
CASE ACCEPTED()         !Which control was chosen?
OF ?OpenFile            !Open... menu selection
OROF ?OpenButton        !Open button on toolbar
  START(OpenFileProc)   !Start new execution thread
OF ?MainExit            !Exit menu selection
OROF ?MainExitButton    !Exit button on toolbar
  BREAK                !Break ACCEPT loop
OF ?HelpAbout           !About... menu selection
  HelpAboutProc         !Call application information procedure
END
END
CLOSE(MainWin)          !Close APPLICATION
```

## WINDOW (declare a dialog window)



```
label  WINDOW( 'title ' ) [,AT( )] [,CENTER] [,SYSTEM] [,MAX] [,ICON( )] [,STATUS( )] [,HLP( )]
                                     [,CURSOR( )] [,MDI] [,MODAL] [,MASK] [,FONT( )] [,GRAY] [,TIMER( )]
                                     [,ALRT( )] [,ICONIZE] [,MAXIMIZE] [,MSG( )] [,PALETTE( )] [,DROPID( )] [,IMM]
                                     [,AUTO] [,COLOR( )] [,TOOLBOX] [,DOCK( )] [,DOCKED( )] [,LAYOUT( )]
                                     [,| TILED| ]          [,| HSCROLL| ]          [,| DOUBLE| ]
                                     | CENTERED |          | VSCROLL |          | NOFRAME|
                                     | HVSCROLL|          | RESIZE|
                                     [ MENUBAR
                                     menus and/or items
                                     END ]
                                     [ TOOLBAR
                                     Controls
                                     END ]
                                     Controls
                                     END
```

---

<b>WINDOW</b>	Declares a document window or dialog box.
<i>label</i>	A valid Clarion label. A <i>label</i> is required.
<i>title</i>	A string constant containing the window's title text (PROP:Text).
<b>AT</b>	Specifies the initial size and location of the window (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CENTER</b>	Specifies that the window's initial position is centered on screen relative to its parent window, by default (PROP:CENTER). This attribute takes effect only if at least one parameter of the AT attribute is omitted.
<b>SYSTEM</b>	Specifies the presence of a system menu (PROP:SYSTEM).
<b>MAX</b>	Specifies the presence of a maximize control (PROP:MAX).
<b>ICON</b>	Specifies the presence of a minimize control, and names a file or standard icon

	identifier for the icon displayed when the window is minimized (PROP:ICON).
<b>STATUS</b>	Specifies the presence of a status bar for the window (PROP:STATUS).
<b>HLP</b>	Specifies the "Help ID" associated with the window (PROP:HLP).
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the window (PROP:CURSOR). This cursor is inherited by the WINDOW's controls unless overridden on the individual control.
<b>MDI</b>	Specifies that the window conforms to normal MDI child-window behavior (PROP:MDI).
<b>MODAL</b>	Specifies the window is "system modal" and must be closed before the user may do anything else (PROP:MODAL).
<b>MASK</b>	Specifies pattern input editing mode of all entry controls in this window (PROP:MASK).
<b>FONT</b>	Specifies the default font for all controls in this window (PROP:FONT).
<b>GRAY</b>	Specifies that the window has a gray background for use with 3-D look controls (PROP:GRAY).
<b>TIMER</b>	Specifies periodic timed event generation (PROP:TIMER).
<b>ALRT</b>	Specifies "hot" keys active when the window has focus (PROP:ALRT).
<b>ICONIZE</b>	Specifies the window is opened as an icon (PROP:ICONIZE).
<b>MAXIMIZE</b>	Specifies the window is maximized when opened (PROP:MAXIMIZE).
<b>MSG</b>	Specifies a string constant containing the default text to display in the status bar for all controls in the window (PROP:MSG).
<b>PALETTE</b>	Specifies the number of hardware colors used for graphics in the window (PROP:PALETTE).
<b>DROPID</b>	Specifies the window may serve as a drop target for drag-and-drop actions (PROP:DROPID).
<b>IMM</b>	Specifies the window generates events whenever it is moved or resized (PROP:IMM).
<b>AUTO</b>	Specifies all window controls' USE variables re-display on screen each time through the ACCEPT loop (PROP:AUTO).
<b>COLOR</b>	Specifies a background color for the WINDOW and default background and selected colors for the controls in the WINDOW (PROP:COLOR).
<b>TOOLBOX</b>	Specifies the window is "always on top" and its controls never retain focus (PROP:TOOLBOX).
<b>DOCK</b>	Specifies a window with the TOOLBOX attribute is dockable (PROP:DOCK).

<b>DOCKED</b>	Specifies a window with the DOCK attribute is opened docked (PROP:DOCKED).
<b>LAYOUT</b>	Indicates the orientation of window controls and field sequence. A style of (1) essentially "flips" the window controls' display as a mirror image of the layout specified in the Window Formatter. Default field navigation moves from right to left. (PROP:LAYOUT)
<b>WALLPAPER</b>	Specifies the background image to display in the window's client area (PROP:WALLPAPER). The image stretches to fill the entire client area of the window unless the TILED or CENTERED attribute is also present.
<b>TILED</b>	Specifies the WALLPAPER image displays at its default size and is tiled to fill the entire client area of the window (PROP:TILED).
<b>CENTERED</b>	Specifies the WALLPAPER image displays at its default size and is centered in the entire client area of the window (PROP:CENTERED).
<b>HSCROLL</b>	Specifies a horizontal scroll bar is automatically added to the window when any scrollable portion of the window lies horizontally outside the visible area (PROP:HSCROLL).
<b>VSCROLL</b>	Specifies a vertical scroll bar is automatically added to the window when any scrollable portion of the window lies vertically outside the visible area (PROP:VSCROLL).
<b>HVSCROLL</b>	Specifies both vertical and horizontal scroll bars are automatically added to the window when any scrollable portion of the window lies outside the visible area.
<b>DOUBLE</b>	Specifies a double-width frame around the window (PROP:DOUBLE).
<b>NOFRAME</b>	Specifies a window with no frame (PROP:NOFRAME).
<b>RESIZE</b>	Specifies a thick frame around the window, which does allow window resizing (PROP:RESIZE).
<b>MENUBAR</b>	Defines a menu structure (optional).
<i>menus and/or items</i>	MENU and/or ITEM declarations that define the menu selections.
<b>TOOLBAR</b>	Defines a toolbar structure (optional).
<i>controls</i>	Control declarations that define tools available on the TOOLBAR, or the control fields in the WINDOW.

A **WINDOW** declares a document window or dialog box which may contain controls, and may be used to display output to the user. When the WINDOW is first opened, it remains hidden until the first DISPLAY statement or ACCEPT loop is encountered. This enables any changes to be made to the appearance before it is displayed. Any previously opened WINDOW on the same execution thread is disabled. Events for the WINDOW are processed by the first ACCEPT loop encountered after the WINDOW is first opened.

A WINDOW automatically receives a single-width border frame unless one of the DOUBLE, NOFRAME, or RESIZE attributes are specified. Screen coordinates are measured in dialog units.

A dialog unit is defined as one-quarter the average character width and one-eighth the average character height of the font specified in the WINDOW's FONT attribute (or the system font, if no FONT attribute is specified on the WINDOW).

A WINDOW with the MODAL attribute is system modal; it takes exclusive control of the computer. This means that any other program running in the background halts its execution until the MODAL WINDOW is closed. Therefore, the MODAL attribute should be used only when absolutely necessary. Also, the RESIZE attribute is ignored, and the WINDOW cannot be moved when the MODAL attribute is present.

A WINDOW without the MDI attribute, when opened in an MDI program on an MDI execution thread, is application modal. This means that the user must respond before moving to any other window in the application. The user may, however, move to any other program running in Windows at the time. Non-MDI windows may be opened either before or after an APPLICATION is opened, and may be on the same execution thread as the APPLICATION or any MDI child window (application modal) or their own thread (not application modal).

A WINDOW with the MDI attribute is an MDI "child" window. MDI "child" windows are clipped to the APPLICATION frame and automatically moved when the frame is moved, and can be totally concealed by minimizing the parent APPLICATION. MDI "child" windows are modeless; the user may change to the top window of another execution thread, within the same application or any other application running in Windows, at any time. An MDI "child" window must not be on the same execution thread as the APPLICATION. Therefore, any MDI "child" window called directly from the APPLICATION must be in a separate procedure so the START procedure can be used to begin a new execution thread. Once started, multiple MDI "child" windows may be called in the new thread.

The MENUBAR specified in a WINDOW with the MDI attribute is automatically merged into the "Global menu" (from the APPLICATION) when the WINDOW receives focus unless either the WINDOW's or APPLICATION's MENUBAR has the NOMERGE attribute. A MENUBAR specified in a WINDOW without the MDI attribute is never merged into the "Global menu"--it always appears in the window itself.

The TOOLBAR specified in a WINDOW with the MDI attribute is automatically merged into the "Global toolbar" (from the APPLICATION) when the WINDOW receives focus, unless either the WINDOW's or APPLICATION's TOOLBAR has the NOMERGE attribute. The toolbar specified in a WINDOW without the MDI attribute is never merged into the "Global toolbar"--it always appears in the window itself.

A WINDOW with the TOOLBOX attribute is automatically "always on top" and its controls do not retain focus (just as if they all had the SKIP attribute). This creates a window whose controls all behave in the same manner as controls in the toolbar. Normally, a WINDOW with the TOOLBOX attribute would be executed in its own thread.

#### Events Generated:

EVENT:PreAlertKey	The user pressed an ALRT attribute hot key.
EVENT:AlertKey	The user pressed an ALRT attribute hot key.
EVENT:CloseWindow	The window is closing.
EVENT:CloseDown	The application is closing.
EVENT:OpenWindow	The window is opening.
EVENT:LoseFocus	The window is losing focus to another thread.

EVENT:GainFocus	The window is gaining focus from another thread.
EVENT:Docked	A TOOLBOX window has been docked.
EVENT:Undocked	A TOOLBOX window has been undocked.
EVENT:Timer	The TIMER attribute has triggered.
EVENT:Move	The user is moving the window. CYCLE aborts the move.
EVENT:Moved	The user has moved the window.
EVENT:Size	The user is resizing the window. CYCLE aborts the resize.
EVENT:Sized	The user has resized the window.
EVENT:Restore	The user is restoring the window's previous size. CYCLE aborts the resize.
EVENT:Restored	The user has restored the window's previous size.
EVENT:Maximize	The user is maximizing the window. CYCLE aborts the resize.
EVENT:Maximized	The user has maximized the window.
EVENT:Iconize	The user is minimizing the window. CYCLE aborts the resize.
EVENT:Iconized	The user has minimized the window.
EVENT:Completed	AcceptAll (non-stop) mode has finished processing all the window's controls.
EVENT:DDErequest	A client has requested a data item from this Clarion DDE server application.
EVENT:DDEadvise	A client has requested continuous updates of a data item from this Clarion DDE server application.
EVENT:DDEexecute	A client has executed a DDEEXECUTE statement to this Clarion DDE server application.
EVENT:DDEpoke	A client has sent unsolicited data to this Clarion DDE server application.
EVENT:DDEdata	A DDE server has supplied an updated data item to this Clarion client application.
EVENT:DDEclosed	A DDE server has terminated the DDE link to this Clarion client application.



**Related Procedures:**

ACCEPT, ALERT, EVENT, POST, REGISTER, UNREGISTER, YIELD,  
 ACCEPTED, CHANGE, CHOICE, CLOSE, CONTENTS, CREATE, DESTROY,  
 DISABLE, DISPLAY, ENABLE, ERASE, FIELD, FIRSTFIELD, FOCUS,  
 GETFONT, GETPOSITION, HELP, HIDE, INCOMPLETE, LASTFIELD,  
 MESSAGE, MOUSEX, MOUSEY, OPEN, POPUP, SELECT, SELECTED,  
 SET3DLOOK, SETCURSOR, SETFONT, SETPOSITION, SETTARGET,  
 UNHIDE, UPDATE

**Example:**

```
!MDI child window with system menu, minimize and maximize buttons, status bar,
! scroll bars, a resizable frame, with menu and toolbar which are merged into
the
!application's menubar and toolbar:
MDIChild WINDOW('Child One'),MDI,SYSTEM,MAX,ICON('Icon.ICO'),STATUS,HVSCROLL,RESIZE
MENUBAR
  MENU('File'),USE(?FileMenu)
  ITEM('Close'),USE(?CloseFile)
END
MENU('Edit'),USE(?EditMenu)
  ITEM('Undo'),USE(?UndoText),KEY(CtrlZ),STD(STD:Undo)
  ITEM('Cu&t'),USE(?CutText),KEY(CtrlX),STD(STD:Cut)
  ITEM('Copy'),USE(?CopyText),KEY(CtrlC),STD(STD:Copy)
  ITEM('Paste'),USE(?PasteText),KEY(CtrlV),STD(STD:Paste)
END
END
TOOLBAR
  BUTTON('Cut'),USE(?CutButton),ICON(ICON:Cut),STD(STD:Cut)
  BUTTON('Copy'),USE(?CopyButton),ICON(ICON:Copy),STD(STD:Copy)
  BUTTON('Paste'),USE(?PasteButton),ICON(ICON:Paste),STD(STD:Paste)
END
TEXT,HVSCROLL,USE(Pre:Field)
BUTTON('&OK'),USE(?Exit),DEFAULT
END

!Non-MDI, system menu, maximize button, status bar, non-resizable frame,
NonMDI WINDOW('Dialog Window'),SYSTEM,MAX,STATUS
  TEXT,HVSCROLL,USE(Pre:Field),MSG('Enter some text here')
  BUTTON('&OK'),USE(?Exit),DEFAULT
END

!System-modal window with non-resizable frame, with only a message and Ok button:
ModalWin WINDOW('Modal Window'),MODAL
  IMAGE(ICON:Exclamation)
  STRING('An ERROR has occurred')
  BUTTON('&OK'),USE(?Exit),DEFAULT
END
```

**See Also:**

ACCEPT

APPLICATION

## MENUBAR (declare a pulldown menu)



```
MENUBAR [,USE( )] [, NOMERGE ]
```

```
  [ MENU( )
```

```
    [ ITEM( ) ]
```

```
    [ MENU( )
```

```
      [ ITEM( ) ]
```

```
    END ]
```

```
  END ]
```

```
  [ ITEM( ) ]
```

```
END
```

---

<b>MENUBAR</b>	Declares the menu for an APPLICATION or WINDOW.
<b>USE</b>	A field equate label to reference the menubar structure in executable code(PROP:USE). PROP:MenuBar can also be used at runtime to get the Field Equate Label.
<b>NOMERGE</b>	Specifies menu merging behavior.
<b>MENU</b>	A menu item with an associated drop box containing other menu selections.
<b>ITEM</b>	A menu item for selection.

The **MENUBAR** structure declares the pulldown menu selections displayed for an APPLICATION or WINDOW. MENUBAR must appear in the source code before any TOOLBAR or controls.

On an APPLICATION, the MENUBAR defines the Global menu selections for the program. These are active and available on all MDI "child" windows (unless the window's own MENUBAR structure has the NOMERGE attribute). If the NOMERGE attribute is specified on the APPLICATION's MENUBAR, then the menu is a local menu displayed only when no MDI child windows are open and there is no global menu.

On an MDI WINDOW, the MENUBAR defines menu selections that are automatically merged with the Global menu. Both the Global and the window's menu selections are then active while the MDI "child" window has input focus. Once the window loses focus, its specific menu selections are removed from the Global menu. If the NOMERGE attribute is specified on an MDI WINDOW's MENUBAR, the menu overwrites and replaces the Global menu.

On a non-MDI WINDOW, the MENUBAR is never merged with the Global menu. A MENUBAR on a non-MDI WINDOW always appears in the WINDOW, not on any APPLICATION which may have been previously opened.

Events generated by local menu items are sent to the WINDOW's ACCEPT loop in the normal way. Events generated by global menu items are sent to the active event loop of the thread which opened the APPLICATION (in a normal multi-thread application this means the APPLICATION's own ACCEPT loop).

Dynamic changes to menu items which reference the currently active window affect only the currently displayed menu, even if global items are changed. Changes made to the Global menu items when the APPLICATION is the current window, or which reference the global APPLICATION window affect the global portions of all menus, whether already open or not.

When a WINDOW's MENUBAR is merged into an APPLICATION's MENUBAR, the global menu selections appear first, followed by the local menu selections, unless the FIRST or LAST attributes are specified on individual menu selections.

A two-column drop menu can be achieved by assigning PROP:Max = 1 to the ITEM which should begin the second column.

#### Example:

!An MDI application frame window with main menu for the application:

MainWin APPLICATION('My Application')

**MENUBAR**

MENU('File'),USE(?FileMenu)

ITEM('Open...'),USE(?OpenFile)

ITEM('Close'),USE(?CloseFile),DISABLE

ITEM('E&xit'),USE(?MainExit),LAST

END

MENU('Edit'),USE(?EditMenu)

ITEM('Cu&t'),USE(?CutText),KEY(CtrlX),STD(STD:Cut),DISABLE

ITEM('Copy'),USE(?CopyText),KEY(CtrlC),STD(STD:Copy),DISABLE

ITEM('Paste'),USE(?PasteText),KEY(CtrlV),STD(STD:Paste),DISABLE

END

MENU('Window'),STD(STD:WindowList),LAST

ITEM('Tile'),STD(STD:TileWindow)

ITEM('Cascade'),STD(STD:CascadeWindow)

END

MENU('Help'),USE(?HelpMenu),LAST

ITEM('Contents'),USE(?HelpContents),STD(STD:HelpIndex)

ITEM('Search for Help On...'),USE(?HelpSearch),STD(STD:HelpSearch)

ITEM('How to Use Help'),USE(?HelpOnHelp),STD(STD:HelpOnHelp)

ITEM('About MyApp...'),USE(?HelpAbout)

END

END

END

!An MDI child window with menu for the window, merged into the

! application's menubar:

MDIChild WINDOW('Child One'),MDI

**MENUBAR**

MENU('File'),USE(?FileMenu) !Merges into File menu

ITEM('Pick...'),USE(?PickFile) !Added to menu selections

END

MENU('Edit'),USE(?EditMenu) !Merges into Edit menu

ITEM('Undo'),USE(?UndoText),KEY(CtrlZ),STD(STD:Undo) !Added to menu

END

END

TEXT,HVSCROLL,USE(Pre:Field)

```
    BUTTON('&OK'),USE(?Exit),DEFAULT
END
```

```
!An MDI window with its own menu, overwriting the main menu:
MDIChild2 WINDOW('Dialog Window'),MDI,SYSTEM,MAX,STATUS
    MENUBAR,NOMERGE
        MENU('File'),USE(?FileMenu)
            ITEM('Close'),USE(?CloseFile)
        END
        MENU('Edit'),USE(?EditMenu)
            ITEM('Undo'),USE(?UndoText),KEY(CtrlZ),STD(STD:Undo)
            ITEM('Cu&t'),USE(?CutText),KEY(CtrlX),STD(STD:Cut)
            ITEM('Copy'),USE(?CopyText),KEY(CtrlC),STD(STD:Copy)
            ITEM('Paste'),USE(?PasteText),KEY(CtrlV),STD(STD:Paste)
        END
    END
    TEXT,HVSCROLL,USE(Pre:Field),MSG('Enter some text here')
    BUTTON('&OK'),USE(?Exit),DEFAULT
END
```

```
!A non-MDI window with its own menu:
NonMDI WINDOW('Dialog Window'),SYSTEM,MAX,STATUS
    MENUBAR
        MENU('File'),USE(?FileMenu)
            ITEM('Close'),USE(?CloseFile)
        END
        MENU('Edit'),USE(?EditMenu)
            ITEM('Undo'),USE(?UndoText),KEY(CtrlZ),STD(STD:Undo)
            ITEM('Cu&t'),USE(?CutText),KEY(CtrlX),STD(STD:Cut)
            ITEM('Copy'),USE(?CopyText),KEY(CtrlC),STD(STD:Copy)
            ITEM('Paste'),USE(?PasteText),KEY(CtrlV),STD(STD:Paste)
        END
    END
    TEXT,HVSCROLL,USE(Pre:Field),MSG('Enter some text here')
    BUTTON('&OK'),USE(?Exit),DEFAULT
END
```

## TOOLBAR (declare a tool bar)



```

TOOLBAR  [,AT( )] [,USE( )] [,CURSOR( )] [,FONT( )] [,NOMERGE] [,COLOR] [,LAYOUT]
           [,WALLPAPER( )]  [, | TILED| ]
           | CENTERED|

```

*controls*

**END**

---

<b>TOOLBAR</b>	Declares tools for an APPLICATION or WINDOW.
<b>AT</b>	Specifies the initial size of the toolbar. If omitted, default values are selected by the runtime library.
<b>USE</b>	A field equate label to reference the toolbar in executable code (PROP:USE). At runtime, PROP:TOOLBAR can also be used to return the Field Equate Label of a window's toolbar.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the TOOLBAR. If omitted, the WINDOW or APPLICATION structure's CURSOR attribute is used, else the Windows default cursor is used.
<b>FONT</b>	Specifies the default display font for the controls in the TOOLBAR.
<b>NOMERGE</b>	Specifies tools merging behavior.
<b>COLOR</b>	Specifies a background color for the TOOLBAR and default background and selected colors for the controls in the TOOLBAR.
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>WALLPAPER</b>	Specifies the background image to display in the toolbar (PROP:WALLPAPER). The image stretches to fill the entire toolbar unless the TILED or CENTERED attribute is also present.
<b>TILED</b>	Specifies the WALLPAPER image displays at its default size and is tiled to fill the entire toolbar (PROP:TILED).
<b>CENTERED</b>	Specifies the WALLPAPER image displays at its default size and is centered in the toolbar (PROP:CENTERED).

*controls*      Control field declarations that define the available tools.

The **TOOLBAR** structure declares the tools displayed for an APPLICATION or WINDOW. On an APPLICATION, the TOOLBAR defines the Global tools for the program. If the NOMERGE attribute is specified on the APPLICATION's TOOLBAR, the tools are local and are displayed only when no MDI child windows are open; there are no global tools. Global tools are active and available on all MDI "child" windows unless an MDI "child" window's TOOLBAR structure has the NOMERGE attribute. If so, the "child" window's tools overwrite the Global tools.

On an MDI WINDOW, the TOOLBAR defines tools that are automatically merged with the Global toolbar. Both the Global and the window's tools are then active while the MDI "child" window has input focus. Once the window loses focus, its specific tools are removed from the Global toolbar. If the NOMERGE attribute is specified on an MDI WINDOW's TOOLBAR, the tools overwrite and replace the Global toolbar. On a non-MDI WINDOW, the TOOLBAR is never merged with the Global menu. A TOOLBAR on a non-MDI WINDOW always appears in the WINDOW, not on any APPLICATION which may have been previously opened.

Events generated by local tools are sent to the WINDOW's ACCEPT loop in the normal way. Events generated by global tools are sent to the active event loop of the thread which opened the APPLICATION. In a normal multi-thread application, this means the APPLICATION's own ACCEPT loop.

TOOLBAR controls generate events in the normal manner. However, they do not retain focus, and cannot be operated from the keyboard unless accelerator keys are provided. As soon as user interaction with a TOOLBAR control is done, focus returns to the window and local control which previously had it. Toolbar controls are not part of the normal TAB key navigation sequence, and act like controls with the SKIP attribute applied. In addition, toolbar buttons/radios/checks cannot hold input focus (again like a SKIPPed control). Focus is moved to a toolbar control by one of the following methods:

- by clicking on the control with the mouse
- by an explicit SELECT statement (i.e., SELECT(?ToolbarButton))
- by hotkey – (but it is important to know that the prompt and the control it references are treated as two different controls.)

Therefore, pressing of the hotkey defined by the prompt will not automatically move focus to the next control. If you need to emulate TAB navigation among toolbar controls, TAB and Shift-TAB keystrokes must be trapped and translated to the required SELECT statements.

Dynamic changes to tools which reference the currently active window affect only the currently displayed toolbar, even if global tools are changed. Changes made to the Global toolbar when the APPLICATION is the current window, or which reference the global APPLICATION's window affect the global portions of all toolbars, whether already open or not. This means that, when an MDI child window is active, the APPLICATION frame's TOOLBAR controls displayed on the APPLICATION frame are actually copies of the frame's controls. This allows each MDI child to modify its own set of toolbar controls without affecting the controls displayed for other MDI child windows. The events for these controls are still processed by the APPLICATION's ACCEPT loop. For example, assuming a button declared in the APPLICATION's TOOLBAR has a field number of 150. The MDI Child window's procedure can modify the appearance of that button by directly setting the properties of control number 150, which would change its appearance only while the MDI Child window's procedure is active and has focus.

When a WINDOW's TOOLBAR is merged into an APPLICATION's TOOLBAR, the global tools appear first, followed by the local tools. The toolbars are merged so that the fields in the WINDOW's toolbar begin just right of the position specified by the value of the width parameter of the APPLICATION TOOLBAR's AT attribute. The height of the displayed toolbar is the maximum height of the "tallest" tool, whether global or local. If any part of a control falls below the bottom, the height is increased accordingly.

**Example:**

```

!An MDI application frame window containing the
! main menu and toolbar for the application:
MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS |
,HVSCROLL,RESIZE
    MENUBAR
        ITEM('E&xit'),USE(?MainExit)
    END
    TOOLBAR
        BUTTON('Exit'),USE(?MainExitButton)
    END
END

!An MDI child window with toolbar for the window, merged into the
! application's toolbar:
MDIChild WINDOW('Child One'),MDI
    TOOLBAR
        BUTTON('Cut'),USE(?CutButton),STD(STD:Cut)
        BUTTON('Copy'),USE(?CopyButton),STD(STD:Copy)
        BUTTON('Paste'),USE(?PasteButton),STD(STD:Paste)
    END
    TEXT,HVSCROLL,USE(Pre:Field)
    BUTTON('&OK'),USE(?Exit),DEFAULT
END

!An MDI window with its own toolbar, overwriting the main toolbar:
MDIChild2 WINDOW('Dialog Window'),MDI,SYSTEM,MAX,STATUS
    TOOLBAR,NOMERGE
        BUTTON('Cut'),USE(?CutButton),STD(STD:Cut)
        BUTTON('Copy'),USE(?CopyButton),STD(STD:Copy)
        BUTTON('Paste'),USE(?PasteButton),STD(STD:Paste)
    END
    TEXT,HVSCROLL,USE(Pre:Field),MSG('Enter some text here')
    BUTTON('&OK'),USE(?Exit),DEFAULT
END

```

## Window Overview



In most Windows programs there are three types of screen windows used: application windows, document windows, and dialog boxes. An application window is the first window opened in a Windows program, and it usually contains the main menu as the entry point to the rest of the program. All other windows in the program are document windows or dialog boxes.

Along with these three screen window types, there are two user interface design conventions that are used in Windows programs: the Single Document Interface (SDI), and the Multiple Document Interface (MDI).

An SDI program usually only contains linear logic that allows the user to take only one execution path (thread) at a time; it does not open separate execution threads which the user may move between. This is the same type of program logic used in most DOS programs. An SDI program would not contain a Clarion APPLICATION structure as its application window. The Clarion WINDOW structure (without an MDI attribute) is used to define an SDI program's application window, and the subsequent document windows or dialog boxes opened on top of it.

An MDI program allows the user to choose multiple execution paths (threads) and change from one to another at any time. This is a very common Windows program user interface. It is used by applications as a way of organizing and grouping windows which present several execution paths for the user to take.

A Clarion APPLICATION structure defines the MDI application window. The MDI application window acts as a parent for all the MDI child windows (document windows and dialog boxes), in that the child windows are clipped to its frame and automatically moved when the application frame is moved. They can also be concealed en masse by minimizing the parent. There may be only one APPLICATION open at any time in a Clarion Windows program.

Document windows and dialog boxes are very similar in that they are both defined as Clarion WINDOW structures. They differ in the conventional context in which they are commonly used and the conventions regarding appearance and attributes. In many cases, the difference is not distinguishable and does not matter. The generic term for both document windows and dialog boxes is "window" and that is the term used throughout this text.

Document windows usually display data. By convention they are movable and resizable. They usually have a title, a system menu, and maximize button. For example, in the Windows environment, the "Main" program group window that appears when you DOUBLE-CLICK on the "Main" icon in the Program Manager's desktop, is a document window.

Dialog boxes usually request information from the user or alert the user to some condition, usually prior to performing some action requested by the user. They may or may not be movable, and so, may or may not have a system menu and title. By convention, they are not resizable, although they can have a maximize button which gives the dialog two alternate sizes. A dialog box may be system modal (the user must respond before doing anything else in Windows), application modal (the user must respond before doing anything in the application), or modeless. For example, in the Clarion environment, the window that appears from the File menu's Open selection is an application modal dialog box that requests the name of the file to open.

### See Also:

- Window Controls and Input Focus
- Field Equate Labels



## Window Controls and Input Focus



The objects placed in an APPLICATION or WINDOW structure are "controls." "Control" is a standard Windows term used to refer to any screen object--command buttons, text entry fields, radio buttons, list boxes, etc. In most DOS programs, the term "field" is usually used to refer to these objects. In this document, the terms "control" and "field" are generally interchangeable.

Controls appear only in MENUBARs, TOOLBARs, or WINDOW structures. Controls are available to the user to select and/or edit the data they contain only when it has "input focus." This occurs when the user uses the TAB key, the mouse, or an accelerator key combination to highlight the control.

A WINDOW also has "input focus" when it is the top WINDOW in the currently active execution thread. Since Clarion for Windows allows multi-threaded programs, the concept of which WINDOW currently has focus is important. Only the thread whose uppermost WINDOW has focus is active. The user may edit data in the WINDOW's control fields only when it has focus.

## Field Equate Labels



### Control Numbering

---

In WINDOW structures, every control (field) with a USE attribute is assigned a number by the compiler. By default, these field numbers begin with one (1) and are assigned to controls in the order they appear in the WINDOW structure code (the window itself is numbered zero). The actual assigned numbers can be overridden in the second parameter of the control's USE attribute.

The order of appearance in the WINDOW structure code determines the "natural" selection order of controls (which may be altered during program execution with the SELECT statement). The order of appearance in the WINDOW structure code is independent of the control's placement on the screen. Therefore, there is not necessarily any correlation between a control's position on screen and the field number assigned by the compiler.

In APPLICATION structures, every menu selection in the MENUBAR, and every control with a USE attribute placed in the TOOLBAR, is assigned a number by the compiler. By default, these numbers begin with negative one (-1) and are decremented by one (1) in the order the menu selections and controls appear in the APPLICATION structure code.

### Equates for Control Numbers

---

There are a number of statements that use these compiler-assigned field numbers as parameters to indicate which controls are affected by the statement. It would be very tedious to "hard code" these numbers in order to use these statements. Therefore, Clarion provides a mechanism to address this problem: Field Equate Labels.

Field Equate Labels always begin with a question mark (?) followed by the label of the variable named in the control's USE attribute. The leading question mark indicates to the compiler a Field Equate Label. Field Equate Labels are very similar to normal EQUATE compiler directives. The compiler substitutes the field number for the Field Equate Label at compile time. This makes it unnecessary to know field numbers in advance.

Two or more controls with exactly the same USE variable in one WINDOW or APPLICATION structure would attempt to create the same Field Equate Label for all (each referencing a different field number). Therefore, when the compiler encounters this condition, all the Field Equate Labels for that USE variable are discarded. This makes it impossible to reference any of these controls in executable code, preventing confusion about which control you really want to reference. You can eliminate this problem by explicitly specifying the Field Equate Label for use by each control in the third parameter to the controls' USE attribute.

### Array and Complex Structure Field Equates

---

Field Equate Labels for USE variables which are array elements always begin with a question mark ( ? ) followed by the name of the USE variable followed by an underscore and the array element number. For example, the field equate for USE(ArrayField[1]) would be ?ArrayField\_1. Multi-dimensioned arrays are treated similarly (?ArrayField\_1\_1, ?ArrayField\_1\_2, ...). You can override this default by explicitly specifying the Field Equate Label for use by each control in the third parameter to the controls' USE attribute.

Field Equate Labels for USE variables which are elements of a complex data structure always begin with a question mark ( ? ) followed by the name of the USE variable with colons (:) replacing the periods (.). For example, the field equate for USE(Phones.Rec.Name) would be

?Phones:Rec:Name. This is done because Clarion labels may contain colons, but not periods, and a field equate is a label.

## Using Field Equate Labels

Some controls' have USE attributes that can only be Field Equate Labels (a unique label with a leading question mark). This simply provides a way of referencing these fields in code or property assignment statements.

In executable code, there are many statements which use the field equate label to reference the control to affect (such as the DISPLAY statement). In all these statements, using a question mark (?) alone, without the USE variable name appended), always indicates performing the action on the current control that has input focus.

### Example:

```
Window WINDOW('Dialog Window'),SYSTEM,MAX,STATUS
    TEXT,HVSCROLL,USE(Pre:Field)           !FEQ = ?Pre:Field
    ENTRY(@N3),HVSCROLL,USE(Pre:Array[1]) !FEQ = ?Pre:Array_1
    ENTRY(@N3),HVSCROLL,USE(File.MyField) !FEQ = ?File:MyField
    IMAGE(ICON:Exclamation),USE(?Image)    !USE attribute is a Field Equate Label
    BUTTON('&OK'),USE(?Ok)                  !USE attribute is a Field Equate Label
END

CODE
OPEN(Window)
?Ok{PROP:DEFAULT} = TRUE                   !Field Equates used in property assignments
?Image{PROP:Text} = 'MyImage.GIF'
ACCEPT
    DISPLAY(?)                             !Re-Display control with current input focus
END
```

## Graphics Overview



Clarion supplies a set of "graphics primitives" procedures to allow drawing in windows (WIN32 Only) and reports: ARC, BLANK, BOX, CHORD, ELLIPSE, IMAGE, LINE, PIE, POLYGON, ROUNDBOX, SHOW, and TYPE. Controls always appear on top of any graphics drawn to the window. This means the graphics appear to underlay any controls in the window, so they don't get in the way of the controls the user needs to access.

## Current Target

Graphics are always drawn to the "current target." Unless overridden with SETTARGET, the "current target" is the last window opened (and not yet closed) on the current execution thread and is the window with input focus. Drawings in a window are persistent--redraws are handled automatically by the runtime library.

### Graphics in Reports

---

Graphics can also be drawn to a report. To do this, SETTARGET must first be used to nominate the REPORT as the "current target." Optionally, SETTARGET can nominate a specific report band to receive the graphics.

### Consistent Graphics

---

Every window or report has its own current pen width, color, and style. Therefore, to consistently use the same pen (which does not use the default settings) across multiple windows, the SETPENWIDTH, SETPENCOLOR, and SETPENSTYLE statements should be issued for each window.

## Graphics Coordinates

The graphics coordinate system starts with the x,y coordinates (0,0) at the top left corner of the window. The coordinates are specified in dialog units (unless overridden by the THOUS, MM, or POINTS attributes when used on graphics placed in a REPORT). A dialog unit is defined as one-quarter the average character width and one-eighth the average character height of the font specified in the window's FONT attribute (or the system font, if no FONT attribute is specified on the window).

Graphics drawn outside the currently visible portion of the window will appear if the window is scrolled. The size of the virtual screen over which the window may scroll automatically expands to include all graphics drawn to the window. Drawing graphics outside the visible portion of the window automatically causes the scroll bars to appear (if the window has the HSCROLL, VSCROLL, or HVSCROLL attribute).

## 7 - Reports

### Report Structures

#### REPORT (declare a report structure)

```

label  REPORT([jobname]),      AT( ) [, FONT( )] [, PRE( )] [, LANDSCAPE] [, PREVIEW] [, PAPER]
                                     [,COLOR( )]      [| THOUS| ]
                                               | MM|
                                               | POINTS|

                                     [FORM
                                     controls
                                     END ]

                                     [HEADER
                                     controls
                                     END ]

label  DETAIL
                                     controls
                                     END

label  [BREAK( )
                                     group break structures
                                     END ]

                                     [FOOTER
                                     controls
                                     END ]

END

```

---

**REPORT**      Declares the beginning of a report data structure.

*label*          The name by which the REPORT structure is addressed in executable code.

<i>jobname</i>	Names the print job for the Windows Print Manager (PROP:Text). If omitted, the print job name will be "JOB_CWDEFAULT".
<b>AT</b>	Specifies the size and location of the area for printing report detail, relative to the top left corner of the page (PROP:AT).
<b>FONT</b>	Specifies the default font for all controls in this report (PROP:FONT). If omitted, the printer's default font is used.
<b>PRE</b>	Specifies the label prefix for the report or structure.
<b>LANDSCAPE</b>	Specifies printing the report in landscape mode (PROP:LANDSCAPE). If omitted, printing defaults to portrait mode.
<b>PREVIEW</b>	Specifies report output to Windows metafiles; one file per report page (PROP:PREVIEW).
<b>PAPER</b>	Specifies the paper size for the report output. If omitted, the default printer's paper size is used.
<b>COLOR</b>	Specifies a background color for the REPORT and default background colors for the bands in the REPORT (PROP:COLOR).
<b>THOUS</b>	Specifies thousandths of an inch as the measurement unit used for all attributes which use coordinates (PROP:THOUS).
<b>MM</b>	Specifies millimeters as the measurement unit used for all attributes which use coordinates (PROP:MM).
<b>POINTS</b>	Specifies points as the measurement unit used for all attributes which use coordinates (PROP:POINTS). There are 72 points per inch, vertically and horizontally.
<b>FORM</b>	Page layout structure defining pre-printed items on every page.
<i>controls</i>	Report output controls.
<b>HEADER</b>	Page header structure, printed at the start of each page.
<b>DETAIL</b>	Report detail structure.
<b>BREAK</b>	A group break structure, defining the variable which causes a group break to occur when its value changes.
<i>group break structures</i>	Group break HEADER, FOOTER, and DETAIL structures, and/or other nested BREAK structures.
<b>FOOTER</b>	Page footer structure, printed at the end of each page.

The **REPORT** statement declares the beginning of a report data structure. A REPORT structure must terminate with a period or END statement. Within the REPORT, the FORM, HEADER, DETAIL, FOOTER, and BREAK structures are the components that format the output of the report. A REPORT must be explicitly opened with the OPEN statement.



A REPORT with the PREVIEW attribute sends the report output to Windows metafiles containing one report page per file. The PREVIEW attribute names a QUEUE to receive the names of the metafiles. You can then create a window to display the report in an IMAGE control, using the QUEUE field contents (the file names) to set the IMAGE control's {PROP:Text} property. This allows the end user to view the report before printing.

The REPORT's AT attribute defines the area of each page devoted to printing DETAIL structures. This includes any HEADERS and FOOTERS that are contained within a BREAK structure (group headers and footers).

Only DETAIL structures can (and must) be printed with the PRINT statement. All other report structures (HEADER, FOOTER, and FORM) automatically print at the appropriate place in the report.

The FORM structure prints on every page except pages containing DETAIL structures with the ALONE attribute. Its format is determined once at the beginning of the report. This makes it the logical place to design a pre-printed form template, which is filled in by the subsequent HEADER, DETAIL, and FOOTER structures. The page HEADER and FOOTER structures are not within a BREAK structure. They automatically print whenever a page break occurs.

The BREAK structure defines a group break. It may contain its own HEADER, FOOTER, and DETAIL structures, and/or other nested BREAK structures. It may also contain multiple DETAIL structures. The HEADER and FOOTER structures that are within a BREAK structure are the group header and footer. They are automatically printed when the value in a specified group break variable changes.

A REPORT data structure never defaults as the current target for runtime property assignment the way the most recently opened WINDOW or APPLICATION structure does. Therefore, the REPORT *label* must be explicitly named as the target, or the SETTARGET statement must be used to make the REPORT the current target, before using runtime property assignment to a REPORT control. Since the graphics commands draw graphics only to the current target, the SETTARGET statement must be used to make the REPORT the current target before using the graphics procedures on a REPORT.

## Page-based Printing

---

Clarion reports use a page-based printing paradigm instead of the line-based paradigm used by some older report generators. Instead of printing each line as its values are generated, nothing is sent to the printer until an entire page is ready to print. This means that the "print engine" in the Clarion runtime library can do a lot of work for you, based on the attributes you specify in the REPORT structure.

Some of the things that the "print engine" in the Clarion runtime library does for you are:

- Prints "pre-printed" forms on each page, that are then filled in by the data
- Calculates totals (count, sum, average, minimum, maximum)
- Automatically handles page breaks, including page headers and footers
- Automatically handles group breaks, including group headers and footers
- Provides complete widow/orphan control.

This automatic functionality makes the executable code required to print a complex report very small, making your programming job easier. Since the "print engine" is page-based, the concepts of headers and footers lose their context indicating both page positioning and print sequence, and only retain their meaning of print sequence. Headers are printed at the beginning of a print sequence, and footers are printed at the end--their actual positioning on the page is irrelevant. For example, you could position the page footer, containing page totals, to print at the top of the page.

**See Also:** PROP:AutoPaper

## Page Overflow

**Page Overflow** occurs when the PRINT statement cannot fit a DETAIL structure on a page. This may be due to a lack of space, or the presence of the PAGEBEFORE or PAGEAFTER attribute on a DETAIL structure. The following steps occur during page overflow, in this sequence:

1. If the REPORT has a page FOOTER, it prints at the position specified by its AT attribute.
2. The page counter is incremented.
3. If the REPORT has a FORM structure, it prints at the position specified by its AT attribute.
4. If the REPORT has a page HEADER, it prints at the position specified by its AT attribute.

### Related Procedures:

CLOSE, OPEN, ENDPAGE, PRINT

### Example:

```
CustRpt REPORT, AT(1000,1000,6500,9000), THOUS, FONT('Arial',12), PRE(Rpt)
      FORM, AT(1000,1000,6500,9000)
      IMAGE('LOGO.BMP'), AT(0,0,1200,1200), USE(?I1)
      END
      HEADER, AT(1000,1000,6500,1000)
      STRING('ABC Company'), AT(3000,500,1500,500), FONT('Arial',18)
      END
Break1  BREAK(Pre:Key1)
      HEADER, AT(0,0,6500,1000)
      STRING('Group Head'), AT(3000,500,1500,500), FONT('Arial',18)
      END
Detail  DETAIL, AT(0,0,6500,1000)
      STRING(@N$11.2), AT(6000,1500,500,500), USE(Pre:F1)
      END
      FOOTER, AT(0,0,6500,1000)
      STRING('Group Total: '), AT(5500,500,1500,500)
      STRING(@N$11.2), AT(6000,500,500,500), USE(Pre:F1), SUM, RESET(Break1)
      END
      END
      FOOTER, AT(1000,1000,6500,1000)
      STRING('Page Total: '), AT(5500,1500,1500,500)
      STRING(@N$11.2), AT(6000,1500,500,500), USE(Pre:F1), SUM, PAGE
      END
      END                                     !End report declaration

CODE
OPEN(CustReport)
SET(DataFile)
LOOP
  NEXT(DataFile)
  IF ERRORCODE()
    BREAK
  END
  PRINT(Rpt:Detail)
END
CLOSE(CustReport)
```

## BREAK (declare group break structure)

*label* **BREAK**(*variable*) [, **USE**( )] [, **NOCASE**]

*group break structures*

**END**

**BREAK** Declares a group break structure.

*label* The name by which the structure is addressed in executable code.

*variable* The variable whose change in value signals the group break (PROP:BreakVar).

**USE** A field equate label to reference the BREAK structure in executable code (PROP:USE).

**NOCASE** Specifies the check for a changed value in the *variable* is case insensitive.

*group break structures* Group break HEADER, FOOTER, and DETAIL structures, and/or other nested BREAK structures.

The **BREAK** structure declares the *variable* which signals a group break when the value in the *variable* changes. A BREAK structure must be terminated with a period or END statement. It may contain its own HEADER, FOOTER, and DETAIL structures, and/or other nested BREAK structures. Only one HEADER and FOOTER are allowed in a BREAK structure; it may contain multiple DETAIL and/or BREAK structures.

The HEADER and FOOTER structures that are declared within a BREAK structure are the group header and footer. They automatically print surrounding equivalent values in the group break *variable*.

### Example:

```
CustRpt REPORT           !Declare customer report
Break1  BREAK(SomeVariable)
        HEADER           !begin group header declaration
        !report controls
        END               !end header declaration
GroupDet DETAIL
        !report controls
        END               !end detail declaration
        FOOTER           ! begin group footer declaration
        !report controls
        END               !end footer declaration
        END               !end group break declaration
        END               !End report declaration
```

<i>label</i>	<b>DETAIL</b>	<b>,AT( )</b> <b>[,FONT( )]</b> <b>[,ALONE]</b> <b>[,ABSOLUTE]</b> <b>[,PAGEBEFORE( )]</b> <b>[,PAGEAFTER( )]</b>
		<b>[,WITHPRIOR( )]</b> <b>[,WITHNEXT( )]</b> <b>[,USE( )]</b> <b>[,COLOR( )]</b> <b>[,TOGETHER]</b>
<i>controls</i>		
	<b>END</b>	

<b>DETAIL</b>	Declares items to be printed as the body of the report.
<i>label</i>	The name by which the structure is addressed in executable code.
<b>AT</b>	Specifies the offset and minimum width and height of the DETAIL, relative to the size of the area specified by the REPORT's AT attribute (PROP:AT).
<b>FONT</b>	Specifies the default font for all controls in this structure (PROP:FONT). If omitted, the REPORT's FONT attribute (if present) is used, or else the printer's default font is used.
<b>ALONE</b>	Declares the DETAIL structure must be printed on a page without FORM, (page) HEADER, or (page) FOOTER structures (PROP:ALONE).
<b>ABSOLUTE</b>	Declares the DETAIL prints at a fixed position relative to the page (PROP:ABSOLUTE).
<b>PAGEBEFORE</b>	Declares the DETAIL prints at the start of a new page, after activating normal page overflow actions (PROP:PAGEBEFORE).
<b>PAGEAFTER</b>	Declares the DETAIL prints, and then starts a new page by activating normal page overflow actions (PROP:PAGEAFTER).
<b>WITHPRIOR</b>	Declares the DETAIL prints on the same page as the DETAIL, or group HEADER or FOOTER that immediately precedes it during printing (PROP:WITHPRIOR).
<b>WITHNEXT</b>	Declares the DETAIL prints on the same page as the DETAIL, or group HEADER or FOOTER that immediately follows it during printing (PROP:WITHNEXT).
<b>USE</b>	A field equate label to reference the DETAIL structure in executable code (PROP:USE).

**COLOR** Specifies a background color for the DETAIL and the default background color for the controls in the DETAIL (PROP:COLOR).

**TOGETHER** Specifies that the DETAIL, or group HEADER or FOOTER structure (contained within a BREAK structure), is to only print on a single page, rather than being automatically split if there is not sufficient room for it (PROP:Together).

*controls* Report output control fields.

The **DETAIL** structure declares items to be printed as the body of the report. A DETAIL structure must be terminated with a period or END statement. A REPORT may have multiple DETAIL structures.

A DETAIL structure is never automatically printed, therefore DETAIL structures are always explicitly printed by the PRINT statement. This means that a *label* is required for each DETAIL you wish to PRINT.

The DETAIL structure may be printed whenever necessary. Since you may have multiple DETAIL structures, they provide the ability to optionally print alternate print formats. This is determined by the logic in the executable code which prints the report.

DETAIL structures print within the detail print area specified by the REPORT statement's AT attribute. The DETAIL structure's AT attribute specifies the relative position, width and height of the detail to print. If there is horizontal room within the detail print area for multiple DETAIL structures, they print side-by-side.

**Example:**

```
CustRpt REPORT           !Declare customer report
    HEADER               !begin page header declaration
        !structure elements
    END                 !end header declaration
CustDetail1 DETAIL       !begin detail declaration
    !structure elements
        END             !end detail declaration
CustDetail2 DETAIL       !begin detail declaration
    !structure elements
        END             !end detail declaration
    END                 !End report declaration

CODE
OPEN(CustRpt)
SET(SomeFile)
LOOP
    NEXT(SomeFile)
    IF ERRORCODE() THEN BREAK.
    IF SomeCondition
        PRINT(CustDetail1)
    ELSE
        PRINT(CustDetail2)
    END
END
CLOSE(CustRpt)
```

**See Also:**

PRINT

AT

## FOOTER (page or group footer structure)

```
FOOTER    ,AT( ) [,FONT( )] [,ABSOLUTE] [,PAGEBEFORE( )] [,PAGEAFTER( )]
          [,WITHPRIOR( )] [,WITHNEXT( )] [,ALONE] [,USE( )] [,COLOR( )]
          [,TOGETHER]

          controls

END
```

---

<b>FOOTER</b>	Declares a page or group footer structure.
<b>AT</b>	Specifies the size and location of the FOOTER (PROP:AT).
<b>FONT</b>	Specifies the default font for all controls in this structure (PROP:FONT). If omitted, the REPORT's FONT attribute (if present) is used, or else the printer's default font is used.
<b>ABSOLUTE</b>	Declares the FOOTER prints at a fixed position relative to the page (PROP:ABSOLUTE). Valid only on a FOOTER within a BREAK structure.
<b>PAGEBEFORE</b>	Declares the FOOTER prints at the start of a new page, after activating normal page overflow actions (PROP:PAGEBEFORE). Valid only on a FOOTER within a BREAK structure.
<b>PAGEAFTER</b>	Declares the FOOTER prints, and then starts a new page by activating normal page overflow actions (PROP:PAGEAFTER). Valid only on a FOOTER within a BREAK structure.
<b>WITHPRIOR</b>	Declares the FOOTER prints on the same page as the DETAIL, group HEADER, or FOOTER that immediately precedes it during printing (PROP:WITHPRIOR). Valid only on a FOOTER within a BREAK structure.
<b>WITHNEXT</b>	Declares the FOOTER prints on the same page as the DETAIL, group HEADER, or FOOTER that immediately follows it during printing (PROP:WITHNEXT). Valid only on a FOOTER within a BREAK structure.
<b>ALONE</b>	Declares the (group) FOOTER structure must be printed on a page without FORM, (page) HEADER, or (page) FOOTER structures (PROP:ALONE).
<b>USE</b>	A field equate label to reference the FOOTER structure in executable code (PROP:USE).
<b>COLOR</b>	Specifies a background color for the FOOTER and the default background color for the controls in the FOOTER (PROP:COLOR).
<b>TOGETHER</b>	Specifies that the DETAIL, or group HEADER or FOOTER structure (contained within a BREAK structure), is to only print on a single page, rather than being automatically split if there is not sufficient room for it (PROP:Together).

*controls*            Report output control fields.

The **FOOTER** structure declares the output which prints at the end of each page or group. A FOOTER structure must be terminated with a period or END statement.

A FOOTER structure that is not within a BREAK structure is a page footer. Only one page FOOTER is allowed in a REPORT. The page FOOTER is automatically printed whenever a page break occurs, at the page-relative position specified by its AT attribute.

The BREAK structure defines a group break. It may contain its own HEADER, FOOTER, and DETAIL structures, and/or other nested BREAK structures. It may also contain multiple DETAIL structures. The HEADER and FOOTER structures that are within a BREAK structure are the group header and footer. They are automatically printed when the value in a specified group break variable changes, at the next position available in the detail print area (specified by the REPORT's AT attribute). Only one FOOTER is allowed in a BREAK structure.

**Example:**

```
CustRpt  REPORT           !Declare customer report
          FOOTER           !begin page FOOTER declaration
          !report controls
          END               !end FOOTER declaration
Break1   BREAK(SomeVariable)
GroupDet  DETAIL
          !report controls
          END               !end detail declaration
          FOOTER           !begin group footer declaration
          !report controls
          END               !end footer declaration
          END               !end group break declaration
          END               !End report declaration
```

## FORM (page layout structure)

**FORM** ,AT( ) [,FONT( )] [,USE( )] [,COLOR( )]

*controls*

**END**

---

<b>FORM</b>	Declares a report structure which prints on each page.
<b>AT</b>	Specifies the size and location, relative to the top left corner of the page, of the FORM (PROP:AT).
<b>FONT</b>	Specifies the default font for all controls in this report structure (PROP:FONT). If omitted, the REPORT's FONT attribute (if present) is used, or else the printer's default font is used.
<b>USE</b>	A field equate label to reference the FORM structure in executable code (PROP:USE).
<b>COLOR</b>	Specifies a background color for the FORM and the default background color for the controls in the FORM (PROP:COLOR).

*controls*          Report output control fields.

**FORM** declares a report structure which prints on every page of the report (except pages containing DETAIL structures with the ALONE attribute). A FORM structure must be terminated with a period or END statement. Only one FORM is allowed in a REPORT structure. The FORM structure automatically prints during page overflow.

The printed output of the FORM is determined only once at the beginning of the report. The page positioning of the FORM does not affect the page positioning of any other report structure. Once printed, all other structures may "overwrite" the FORM. Therefore, FORM is most often used to design pre-printed forms which are filled in by the subsequent HEADER, DETAIL, and FOOTER structures. It may also be used to generate "watermarks" or page border graphics.

### Example:

```
CustRpt REPORT      !Declare customer report
    FORM
        IMAGE('LOGO.BMP'),AT(0,0,1200,1200),USE(?I1)
        STRING(@N3),AT(6000,500,500,500),PAGE NO
    END
GroupDet DETAIL
    !report controls
    END
END                !End report declaration
```



## HEADER (page or group header structure)

```

HEADER ,AT(    [,FONT( )] [,ABSOLUTE] [,PAGEBEFORE( )] [,PAGEAFTER( )]
)

                [,WITHPRIOR( )] [,WITHNEXT( )] [,ALONE] [,USE( )] [,COLOR( )]
                [,TOGETHER]

```

*controls*

**END**

---

<b>HEADER</b>	Declares a page or group header structure.
<b>AT</b>	Specifies the size and location of the HEADER (PROP:AT).
<b>FONT</b>	Specifies the default font for all controls in this structure (PROP:FONT). If omitted, the REPORT's FONT attribute (if present) is used, or else the printer's default font is used.
<b>ABSOLUTE</b>	Declares the HEADER prints at a fixed position relative to the page (PROP:ABSOLUTE). Valid only on a HEADER within a BREAK structure.
<b>PAGEBEFORE</b>	Declares the HEADER prints at the start of a new page after activating normal page overflow actions (PROP:PAGEBEFORE). Valid only on a HEADER within a BREAK structure.
<b>PAGEAFTER</b>	Declares the HEADER prints, and then starts a new page by activating normal page overflow actions (PROP:PAGEAFTER). Valid only on a HEADER within a BREAK structure.
<b>WITHPRIOR</b>	Declares the HEADER prints on the same page as the DETAIL, group HEADER, or FOOTER that immediately precedes it during printing (PROP:WITHPRIOR). Valid only on a HEADER within a BREAK structure.
<b>WITHNEXT</b>	Declares the HEADER prints on the same page as the DETAIL, group HEADER, or FOOTER that immediately follows it during printing (PROP:WITHNEXT). Valid only on a HEADER within a BREAK structure.
<b>ALONE</b>	Declares the (group) HEADER structure must be printed on a page without FORM, (page) HEADER, or (page) FOOTER structures (PROP:ALONE).
<b>USE</b>	A field equate label to reference the HEADER structure in executable code (PROP:USE).

- COLOR** Specifies a background color for the HEADER and the default background color for the controls in the HEADER (PROP:COLOR).
- TOGETHER** Specifies that the DETAIL, or group HEADER or FOOTER structure (contained within a BREAK structure), is to only print on a single page, rather than being automatically split if there is not sufficient room for it (PROP:Together).

*controls* Report output control fields.

The **HEADER** structure declares the output which prints at the beginning of each page or group. A HEADER structure must be terminated with a period or END statement.

A HEADER structure that is not within a BREAK structure is a page header. Only one page HEADER is allowed in a REPORT. The page HEADER is automatically printed whenever a page break occurs, at the page-relative position specified by its AT attribute.

The BREAK structure defines a group break. It may contain its own HEADER, FOOTER, and DETAIL structures, and/or other nested BREAK structures. It may also contain multiple DETAIL structures. The HEADER and FOOTER structures that are within a BREAK structure are the group header and footer. They are automatically printed when the value in a specified group break variable changes, at the next position available in the detail print area (specified by the REPORT's AT attribute). Only one HEADER is allowed in a BREAK structure.

**Example:**

```
CustRpt REPORT      !Declare customer report
    HEADER          ! begin page header declaration
        !report controls
    END              ! end header declaration
Break1 BREAK(SomeVariable)
    HEADER          ! begin group header declaration
        !report controls
    END              ! end header declaration
GroupDet DETAIL
    !report controls
    END              ! end detail declaration
    END              ! end group break declaration
    END              !End report declaration
```

## Printer Control Properties

These properties control report and printer behavior. All of these properties can be used with either the PRINTER built-in variable or the label of the report as the *target*, however they may not all make sense with both. These properties are contained in the PRNPROP.CLV file, which you must explicitly INCLUDE in your code in order to use them.

### PROPPRINT:DevMode

The entire device mode (devmode) structure as defined in the Windows Software Development Kit. This provides direct API access to all printer properties. Consult a Windows API manual before using this.

The devmode structure is different in 32-bit (consult a Windows API manual). However, the following properties are the most common and useful:

DM_ORIENTATION	DM_PAPERSIZE	DM_PAPERLENGTH
DM_PAPERWIDTH	DM_SCALE	DM_COPIES
DM_DEFAULTSOURCE	DM_PRINTQUALITY	DM_POSITION
DM_DISPLAYORIENTATION	DM_DISPLAYFIXEDOUTPUT	DM_COLOR
DM_DUPLEX	DM_YRESOLUTION	DM_TTOPTION
DM_COLLATE	DM_FORMNAME	DM_LOGPIXELS
DM_BITSPERPEL	DM_PELSWIDTH	DM_PELSHEIGHT
DM_DISPLAYFLAGS	DM_NUP	DM_DISPLAYFREQUENCY
DM_ICMMETHOD	DM_ICMINTENT	DM_MEDIATYPE
DM_DITHERTYPE	DM_PANNINGWIDTH	DM_PANNINGHEIGHT

### PROPPRINT:Collate

Specify the printer should collate the output: 0=off, 1=on (not supported by all printers).

### PROPPRINT:Color

Color or monochrome print flag: 1=mono, 2=color (not supported by all printers).

### PROPPRINT:Context

Returns the handle to the printer's device context after the first PRINT statement for the report, or an information context before the first PRINT statement. This may not be set for the built-in Global PRINTER variable and is normally only read (not set).

### PROPPRINT:Copies

The number of copies to print (not supported by all printers).

### PROPPRINT:Device

The name of the Printer as it appears in the Windows Printer Dialog. If multiple printer names start with the same characters, the first encountered is used (not case sensitive). May be set for the PRINTER built-in variable only before the report is open.

### **PROPPRINT:Driver**

The printer driver's filename (without the .DLL extension).

### **PROPPRINT:Duplex**

The duplex printing mode (not supported by all printers). Equates(DUPLEX::xxx) for the standard choices are listed in the PRNPROP.CLW file.

### **PROPPRINT:Extend**

PROPPRINT:Extend can be set to TRUE or FALSE at runtime, and references the REPORT target. This determines whether or not the runtime library generates extra information inside the WMF files, which is being used to generate the new report output formats (XML, HTML, PDF etc.).

Set this property to FALSE (0) if you do not want alternate output formats and prefer smaller, compact WMF files (this is default behavior).

PROP:Extend is the runtime property that can be used to set the information for the EXTEND attribute.

### **PROPPRINT:FontMode**

The TrueType font mode. Equates (FONTMODE:xxx) for the modes are listed in the PRNPROP.CLW file.

### **PROPPRINT:FromMin**

When set for the built-in PRINTER variable, this forces the value into the "From:" page number in the PRINTERDIALOG. Specify -1 to disable ranges

### **PROPPRINT:FromPage**

The page number on which to start printing. Specify -1 to print from the start.

### **PROPPRINT:Paper**

Standard paper size. Equates (PAPER:xxx) for the standard sizes are listed in the PRNPROP.CLW file. This defines the dimensions of the .WMF files that are created by the Clarion runtime library's "print engine."

### **PROPPRINT:PaperBin**

The paper source. Equates (PAPERBIN:xxx) for the standard locations are listed in the PRNPROP.CLW file.

### **PROPPRINT:PaperHeight**

The paper height in tenths of millimeters (mm/10). There are 25.4 mm per inch. Used when setting PROPPRINT:Paper to PAPER:Custom (not normally used for laser printers).

### **PROPPRINT:PaperWidth**

The paper width in tenths of millimeters (mm/10). There are 25.4 mm per inch. Used when setting PROPPRINT:Paper to PAPER:Custom (not normally used for laser printers).

### **PROPPRINT:Percent**

The scaling factor used to enlarge or reduce the printed output, in percent (not supported by all printers). This defaults to 100 percent. Set this value to print at the desired percentage (if your printer and driver support scaling). For example, set to 200 to print at double size, or 50 to print at half size.

### **PROPPRINT:Port**

Output port name (LPT1, COM1, etc.).

### **PROPPRINT:PrintToFile**

The Print to File flag: 0=off, 1=on.

### **PROPPRINT:PrintToName**

The output filename when printing to a file.

### **PROPPRINT:Resolution**

The print resolution in Dots Per Inch (DPI). Equates (RESOLUTION:xxx) for the standard resolutions are listed in the PRNPROP.CLW file. Must be issued before the report is open.

### **PROPPRINT: SupportCopies**

A READ-ONLY property that returns TRUE if the current printer supports output of multiple copies.

### **PROPPRINT:SupportCollate**

A READ-ONLY property that returns TRUE if the current printer supports collating of copies.

Click [here](#) for an example that demonstrates the usage of PROP:SupportCopies and PROPPRINT:SupportCollate.

### **PROPPRINT:ToMax**

When set for the built-in PRINTER variable, this forces the value into the "To:" page number in the PRINTERDIALOG. Specify -1 to disable ranges

### **PROPPRINT:ToPage**

The page number on which to end printing. Specify -1 to print to end.

### **PROPPRINT:Yresolution**

Vertical print resolution in Dots Per Inch (DPI). Equates (RESOLUTION:xxx) for the standard resolutions are listed in the PRNPROP.CLW file.

#### **Example:**

```
SomeReport  REPORT
            END

CODE
PRINTER{PROPPRINT:Device} = 'Epson'           !Pick 1st Epson in the list

PRINTER{PROPPRINT:Port} = 'LPT2:'             !Send report to LPT2

PRINTER{PROPPRINT:Percent} = 250              !page printed 2.5 times normal

PRINTER{PROPPRINT:Copies} = 3                 !print 3 copies of each page
PRINTER{PROPPRINT:Collate} = False            !print 1,1,1,2,2,2,3,3,3,...
```

<code>PRINTER{PROPPRINT:Collate} = True</code>	<code>!print 1,2,3..., 1,2,3...,</code>
<code>PRINTER{PROPPRINT:PrintToFile} = True</code>	<code>!print to a file</code>
<code>PRINTER{PROPPRINT:PrintToName} = 'OUTPUT.RPT'</code>	<code>!filename to print to</code>
<code>OPEN(SomeReport)</code>	<code>!Open report after setting PRINTER properties</code>
<code>SomeReport{PROPPRINT:Paper} = PAPER:User</code>	<code>!Custom paper size</code>
<code>SomeReport{PROPPRINT:PAPERHeight} = 6 * 254</code>	<code>!6" form height</code>
<code>SomeReport{PROPPRINT:PAPERWidth} = 3.5 * 254</code>	<code>!3.5" form width</code>

## 8 - Controls

### BOX (declare a box control)

```
BOX ,AT( )    [,USE( )] [,DISABLE] [,COLOR( )] [,FILL( )] [,ROUND] [,FULL] [,SCROLL] [,HIDE]
              [,LINEWIDTH( )] [,LAYOUT( )] [,EXTEND( )]
```

---

<b>BOX</b>	Places a rectangular box on the window or report.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>USE</b>	A field equate label to reference the control in executable code (PROP:USE).
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW (or APPLICATION) is first opened (PROP:DISABLE).
<b>COLOR</b>	Specifies the color for the border of the control (PROP:COLOR). If omitted, there is no border.
<b>FILL</b>	Specifies the fill color for the control (PROP:FILL). If omitted, the box is not filled with color.
<b>ROUND</b>	Specifies the box corners are rounded (PROP:ROUND). If omitted, the corners are square.
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL). Not valid in a REPORT.
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL). Not valid in a REPORT.
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened. UNHIDE must be used to display it (PROP:HIDE). In a REPORT, specifies the control does not print unless UNHIDE is used to allow it to print
<b>LINEWIDTH</b>	Specifies the width of the BOX's border (PROP:LINEWIDTH).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>EXTEND</b>	Specifies special document formatting information. This information contains a valid string of attributes that are assigned to a designated REPORT control for a given document type. Valid only in a REPORT.

The **BOX** control places a rectangular box on the WINDOW, TOOLBAR, or REPORT at the position and size specified by its AT attribute. This control cannot receive input focus and does not generate events. It is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !Unfilled, black border:
    BOX,AT(0,0,20,20)
    !Unfilled, black border, dimmed:
    BOX,AT(0,20,20,20),USE(?Box1),DISABLE
    !Unfilled, rounded, black border:
    BOX,AT(20,20,20,20),ROUND
    !Filled, black border:
    BOX,AT(40,40,20,20),FILL(COLOR:ACTIVEBORDER)
    !Unfilled, active border color border:
    BOX,AT(60,60,20,20),COLOR(COLOR:ACTIVEBORDER)
    !Scrolls with screen:
    BOX,AT(480,180,20,20),SCROLL
END

CustRpt  REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail  DETAIL,AT(0,0,6500,1000)
    BOX,AT(0,0,20,20),USE(?B1)                !Unfilled, black border
    BOX,AT(20,20,20,20),ROUND                !Unfilled, rounded, black border
    BOX,AT(40,40,20,20),FILL(COLOR:ACTIVEBORDER) !Filled, black border
    BOX,AT(60,60,20,20),COLOR(COLOR:ACTIVEBORDER) !Unfilled, active border color border
END
```

**See Also:**

PANEL



## BUTTON (declare a pushbutton control)



```

BUTTON(text),AT( ) [,CURSOR( )] [,USE( )] [,DISABLE] [,KEY( )] [,MSG( )] [,HLP( )] [,SKIP]
        [,STD( )] [,FONT( )] [,ICON( )] [,DEFAULT] [,IMM] [,REQ] [,FULL] [,SCROLL] [,ALRT( )]
        [,HIDE] [,DROPID( )] [,TIP( )] [,FLAT] [,REPEAT( )] [,DELAY( [ ,| LEFT| ] [,TRN] [,LAYOUT]
        [,COLOR( )]                                     | RIGHT|

```

<b>BUTTON</b>	Places a command button on the WINDOW or TOOLBAR.
<i>text</i>	A string constant containing the text to display on the button face, along with any ICON specified (PROP:Text). This may contain an ampersand (&) to indicate the "hot" letter (accelerator key) for the button.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are set by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used.
<b>USE</b>	A field equate label to reference the control in executable code (PROP:USE).
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to and presses the button (PROP:KEY).
<b>MSG</b>	Specifies a string constant containing the text to display in the status bar when the control has focus (PROP:MSG).
<b>HLP</b>	Specifies a string constant containing the help system identifier for the control (PROP:HLP).
<b>SKIP</b>	Specifies the control does not receive input focus and may only be accessed with the mouse or accelerator key (PROP:SKIP).
<b>STD</b>	Specifies an integer constant or equate that identifies a "Windows standard action" the control executes (PROP:STD).
<b>FONT</b>	Specifies the display font for the control (PROP:FONT).

<b>ICON</b>	Specifies an image file or standard icon to display on the button face (PROP:ICON).
<b>DEFAULT</b>	Specifies the BUTTON is automatically pressed when the user presses the ENTER key (PROP:DEFAULT).
<b>IMM</b>	Specifies the control generates an event when the left mouse button is pressed, continuing as long as it is depressed (PROP:IMM). If omitted, an event is generated only when the left mouse button is pressed and released on the control.
<b>REQ</b>	Specifies that when the BUTTON is pressed, the runtime library automatically checks all ENTRY controls in the same WINDOW with the REQ attribute to ensure they contain data other than blanks or zeroes (PROP:REQ).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL).
<b>ALRT</b>	Specifies "hot" keys active for the control (PROP:ALRT).
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID).
<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip).
<b>FLAT</b>	Specifies the button appears flat except when the mouse cursor passes over the control (PROP:FLAT). Requires the ICON attribute.
<b>REPEAT</b>	Specifies the rate at which EVENT:Accepted generates when the button with the IMM attribute is held down by the user (PROP:REPEAT). Requires the IMM attribute.
<b>DELAY</b>	Specifies the delay between the first and second generation of EVENT:Accepted for a button with the IMM attribute (PROP:DELAY). Requires the IMM attribute.
<b>LEFT</b>	Specifies that the icon appears to the left of the <i>text</i> (PROP:LEFT).
<b>RIGHT</b>	Specifies that the icon appears to the right of the <i>text</i> (PROP:RIGHT).
<b>TRN</b>	Specifies that the characters print or display transparently without obliterating the background over which the control is placed.
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>COLOR</b>	Specifies a background color for the control (PROP:COLOR).

The **BUTTON** control places a pushbutton on the WINDOW or TOOLBAR (not valid in a REPORT) at the position and size specified by its AT attribute.

A BUTTON with the IMM attribute generates EVENT:Accepted as soon as the left mouse button is pressed on the control and continues to do so until it is released. This allows the BUTTON control's executable code to execute continuously until the mouse button is released. The rate and delay before continuous event generation can be set by the REPEAT and DELAY attributes. A BUTTON without the IMM attribute generates EVENT:Accepted only when the left mouse button is pressed and then released on the control.

A BUTTON with the REQ attribute is a "required control fields check" button. REQ attributes of ENTRY or TEXT control fields are not checked until a BUTTON with the REQ attribute is pressed or the INCOMPLETE procedure is called. Focus is given to the first required control which is blank or zero.

A BUTTON with an ICON attribute displays the image on the button face in addition to its *text* parameter (which appears below the image, by default). The *text* parameter also serves for accelerator "hot" key definition.

#### Events Generated:

EVENT:Selected	The control has received input focus.
EVENT:Accepted	The control has been pressed by the user.
EVENT:PreAlertKey	The user pressed an ALRT attribute hot key.
EVENT:AlertKey	The user pressed an ALRT attribute hot key.
EVENT:Drop	A successful drag-and-drop to the control.

#### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    BUTTON('1'),AT(0,0,20,20),USE(?B1)
    BUTTON('2'),AT(20,0,20,20),USE(?B2),KEY(F10Key)
    BUTTON('3'),AT(40,0,20,20),USE(?B3),MSG('Button 3')
    BUTTON('4'),AT(60,0,20,20),USE(?B4),HLP('Button4Help')
    BUTTON('5'),AT(80,0,20,20),USE(?B5),STD(STD:Cut)
    BUTTON('6'),AT(100,0,20,20),USE(?B6),FONT('Arial',12)
    BUTTON('7'),AT(120,0,20,20),USE(?B7),ICON(ICON:Question)
    BUTTON('8'),AT(140,0,20,20),USE(?B8),DEFAULT
    BUTTON('9'),AT(160,0,20,20),USE(?B9),IMM
    BUTTON('10'),AT(180,0,20,20),USE(?B10),CURSOR(CURSOR:Wait)
    BUTTON('11'),AT(200,0,20,20),USE(?B11),REQ
    BUTTON('12'),AT(220,0,20,20),USE(?B12),ALRT(F10Key)
    BUTTON('13'),AT(240,0,20,20),USE(?B13),SCROLL
END

CODE
OPEN(MDIChild)
ACCEPT
CASE ACCEPTED()
OF ?B1
    !Perform some action
END
END
```

#### See Also:

CHECK, OPTION, RADIO

## CHECK (declare a checkbox control)

```
CHECK(text)      ,AT( ) [,CURSOR( )] [,USE( )] [,DISABLE] [,KEY( )] [,MSG( )] [,HLP( )] [,SKIP]  
                [,FONT( )] [,ICON( )] [,FULL] [,SCROLL] [,ALRT( )] [,HIDE] [,DROPID( )] [,TIP( )]  
                [,LEFT] [,VALUE( )] [,TRN] [,COLOR( )] [,FLAT] [,LAYOUT] [,EXTEND( )  
                | RIGHT|
```

---

<b>CHECK</b>	Places a check box on the WINDOW, TOOLBAR, or REPORT.
<i>text</i>	A string constant containing the text to display next to the check box (PROP:Text). This may contain an ampersand (&) to indicate the "hot" letter for the check box.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used. Not valid in a REPORT.
<b>USE</b>	The label of a variable to receive the value of the check box (PROP:USE). Zero (0) indicates OFF (un-checked) or one (1) indicates ON (checked) unless the VALUE attribute specifies other values.
<b>DISABLE</b>	Specifies the control appears dimmed in the WINDOW or APPLICATION (PROP:DISABLE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to and toggles the box (PROP:KEY). Not valid in a REPORT.
<b>MSG</b>	Specifies a string constant containing the text to display in the status bar when the control has focus (PROP:MSG). Not valid in a REPORT.
<b>HLP</b>	Specifies a string constant containing the help system identifier for the control (PROP:HLP). Not valid in a REPORT.
<b>SKIP</b>	Specifies the control does not receive input focus and may only be accessed with the mouse or accelerator key (PROP:SKIP). Not valid in a REPORT.
<b>FONT</b>	Specifies the display font for the control (PROP:FONT).
<b>ICON</b>	Specifies an image file or standard icon to display on the button face of a "latching" pushbutton (PROP:ICON). Not valid in a REPORT.
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW or REPORT band for any missing AT attribute width or height parameter (PROP:FULL).

<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL). Not valid in a REPORT.
<b>ALRT</b>	Specifies "hot" keys active for the control (PROP:ALRT).
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened, or the control is not printed in the REPORT (PROP:HIDE). UNHIDE must be used to display or print it.
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID). Not valid in a REPORT.
<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip). Not valid in a REPORT.
<b>LEFT</b>	Specifies that the <i>text</i> appears to the left of the check box (PROP:LEFT).
<b>RIGHT</b>	Specifies that the <i>text</i> appears to the right of the check box (PROP:RIGHT). This is the default position.
<b>VALUE</b>	Specifies the true and false values the USE variable receives when the box is checked by the user (PROP:Value).
<b>TRN</b>	Specifies the control transparently displays over the background (PROP:TRN).
<b>COLOR</b>	Specifies a background color for the control's text (PROP:COLOR).
<b>FLAT</b>	Specifies the button appears flat except when the mouse cursor passes over the control (PROP:FLAT). Requires the ICON attribute. Not valid in a REPORT.
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>EXTEND</b>	Specifies special document formatting information. This information contains a valid string of attributes that are assigned to a designated REPORT control for a given document type. Valid only in a REPORT.

The **CHECK** control places a check box on the WINDOW, TOOLBAR, or REPORT at the position and size specified by its AT attribute. It is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

A CHECK in a window with an ICON attribute appears as a "latched" button with the image displayed on the button face. When the button appears "up" the CHECK is off; when it appears "down" the CHECK is on.

By default, when the CHECK is off the USE variable receives a value of zero (0); and when the CHECK is on, the USE variable receives a value of one (1). The VALUE attribute and its runtime properties (PROP:TrueValue and PROP:FalseValue) can be used to change this default behavior and automatically set the USE variable to values other than the defaults. If you designate a STRING variable as the USE variable, you must explicitly assign a VALUE attribute.

**Events Generated:**

EVENT:Selected      The control has received input focus.

EVENT:Accepted      The control has been toggled by the user.

EVENT:PreAlertKey    The user pressed an ALERT attribute hot key.

EVENT:AlertKey      The user pressed an ALERT attribute hot key.

EVENT:Drop          A successful drag-and-drop to the control.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    CHECK('1'),AT(0,0,20,20),USE(C1)
    CHECK('2'),AT(0,20,20,20),USE(C2),VALUE('T','F')
END

CustRpt  REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail DETAIL,AT(0,0,6500,1000)
    CHECK('1'),AT(0,0,20,20),USE(C1)
    CHECK('2'),AT(20,80,20,20),USE(C2),LEFT
    CHECK('3'),AT(0,100,20,20),USE(C3),FONT('Arial',12)
END
END

CODE
OPEN(MDIChild)
ACCEPT
CASE ACCEPTED()
OF ?C1
    IF C1 = 1 THEN DO C1Routine.
OF ?C2
    IF C2 = 'T' THEN DO C2Routine.
END
END
```

**See Also:**

BUTTON

OPTION

RADIO

## COMBO (declare an entry/list control)



```
COMBO(picture),FROM( ) ,AT( ) [,CURSOR( )] [,USE( )] [,LAYOUT( )][,DISABLE] [,KEY( )] [,MSG( )] [,HLP( )]
    [,SKIP][,FONT( )][,FORMAT( )][,DROP][,COLUMN][,VCR][,FULL][,GRID( )][,SCROLL]
    [,ALRT( )][,HIDE][,READONLY][,REQ][,NOBAR][,DROPID( )][,TIP( )] [,FLAT][,TRN][,COLOR()]
    [, MARK( )]    [, HSCROLL]    [, LEFT]    [, INS]    [, UPR] [, MASK]
    | IMM|          | VSCROLL|      | RIGHT|      | OVR|      | CAP|
    | HVSCROLL|      | CENTER|
    | DECIMAL|
```

<b>COMBO</b>	Places a data entry field with an associated list of data items on the WINDOW or TOOLBAR.
<i>picture</i>	A display picture token that specifies the input format for the data entered into the control (PROP:Text).
<b>FROM</b>	Specifies the origin of the data displayed in the list (PROP:FROM).
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, the runtime library chooses a value.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used.
<b>USE</b>	A field equate label to reference the control in executable code or the label of the variable that receives the value selected by the user (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display and entry orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to the control (PROP:KEY).
<b>MSG</b>	Specifies a string constant containing the text to display in the status bar when the control has focus (PROP:MSG).

<b>HLP</b>	Specifies a string constant containing the help system identifier for the control (PROP:HLP).
<b>SKIP</b>	Specifies the control receives input focus to enter text only with the mouse or accelerator key and does not retain focus (PROP:SKIP).
<b>FONT</b>	Specifies the display font for the control (PROP:FONT).
<b>FORMAT</b>	Specifies the display format of the data (PROP:FORMAT).
<b>DROP</b>	Specifies a drop-down list box and the number of elements the drop-down portion contains (PROP:DROP).
<b>COLUMN</b>	Specifies a field-by-field highlight bar on multi-column list boxes (PROP:COLUMN).
<b>VCR</b>	Specifies a VCR-type control that appears left of any horizontal scroll bar (PROP:VCR).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL).
<b>GRID</b>	Specifies the color of the grid lines between columns in the list (PROP:GRID).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL).
<b>ALRT</b>	Specifies "hot" keys active for the control (PROP:ALRT).
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>READONLY</b>	Specifies the control does not allow data entry (PROP:READONLY).
<b>NOBAR</b>	Specifies the highlight bar is displayed only when the LIST has focus (PROP:NOBAR).
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID).
<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip).
<b>FLAT</b>	Specifies that the control does not have a 3D border drawn around it (PROP:FLAT). This applies both the ENTRY and LIST sub-controls.
<b>TRN</b>	Specifies the control transparently displays over the background (PROP:TRN).
<b>COLOR</b>	Specifies background and selected colors for the control (PROP:COLOR).
<b>REQ</b>	Specifies the control may not be left blank or zero (PROP:REQ).
<b>MARK</b>	Specifies multiple item selection mode (PROP:MARK).



<b>IMM</b>	Specifies generation of an event whenever the user presses any key (PROP:IMM).
<b>HSCROLL</b>	Specifies that a horizontal scroll bar is automatically added to the list box when any portion of the data item lies horizontally outside the visible area (PROP:HSCROLL).
<b>VSCROLL</b>	Specifies that a vertical scroll bar is automatically added to the list box when any data items lie vertically outside the visible area (PROP:VSCROLL).
<b>HVSCROLL</b>	Specifies that both vertical and horizontal scroll bars are automatically added to the list box when any portion of the data items lies outside the visible area.
<b>LEFT</b>	Specifies that the data is left justified within the control (PROP:LEFT).
<b>RIGHT</b>	Specifies that the data is right justified within the control (PROP:RIGHT).
<b>CENTER</b>	Specifies that the data is centered within the control (PROP:CENTER).
<b>DECIMAL</b>	Specifies that the data is aligned on the decimal point within the control (PROP:DECIMAL).
<b>INS / OVR</b>	Specifies Insert or Overwrite entry mode (PROP:INS and PROP:OVR). This is valid only on windows with the MASK attribute).
<b>UPR / CAP</b>	Specifies all upper case or proper name capitalization (First Letter Of Each Word Capitalized) data entry (PROP:UPR and PROP:CAP).
<b>MASK</b>	Specifies pattern input editing mode of the ENTRY portion of the control (PROP:MASK).

The **COMBO** control places a data entry field with an associated list of data items on the WINDOW or TOOLBAR (not valid in a REPORT) at the position and size specified by its AT attribute (a combination of an ENTRY and LIST control). The user may type in data or select an item from the list. The entered data is not automatically validated against the entries in the list. The data entry portion of the COMBO acts as an "incremental locator" to the list--as the user types each character, the highlight bar is positioned to the closest matching entry.

A COMBO with the DROP attribute displays only the currently selected data item on screen until the control has focus and the user presses the down arrow key, or CLICKS ON the the icon to the right of the displayed data item. When either of these occurs, the selection list appears ("drops down") to allow the user to select an item.

A COMBO with the IMM attribute generates an EVENT:NewSelection every time the user moves the highlight bar to another selection, or presses any key (all keys are implicitly ALRTed). This allows an opportunity for the source code to re-fill the display QUEUE, or get the currently highlighted record to display other fields from the record. A COMBO with the VCR attribute has scroll control buttons like a **Video Cassette Recorder** to the left of the horizontal scroll bar (if there is one). These buttons allow the user to use the mouse to scroll through the list.

Regarding the runtime alignment properties (PROP:Left, PROP:LeftOffset, PROP:Right, PROP:RightOffset, PROP:Center, PROP:CenterOffset, PROP:Decimal, PROP:DecimalOffset) applied to the drop (list) box, these properties are applied only to the ENTRY part of the COMBO control by default. To apply these properties to the LIST component, use them in conjunction with the PROP:ListFeq property:

?Drop {PROP:Left} = TRUE ! Set static part left aligned

(?Drop {PROP:ListFeq}) {PROP:Right} = TRUE ! Set list part right aligned

Alignment properties defined for drop boxes in the WINDOW declaration are applied to both ENTRY and LIST by default.

**Events Generated:**

EVENT:Selected	The control has received input focus.
EVENT:Accepted	The user has either selected an entry from the list or entered data directly into the control, and moved on to another control.
EVENT:Rejected	The user has entered an invalid value for the entry picture.
EVENT:NewSelection	The current selection in the list has changed (highlight bar has moved up or down) or the user pressed any key (only with the IMM attribute).
EVENT:PreAlertKey	The user pressed an ALRT attribute hot key.
EVENT:AlertKey	The user pressed an ALRT attribute hot key.
EVENT:Drop	A successful drag-and-drop to the control.
EVENT:ScrollUp	The user pressed the up arrow (only with the IMM attribute).
EVENT:ScrollDown	The user pressed the down arrow (only with the IMM attribute).
EVENT:PageUp	The user pressed PgUp (only with the IMM attribute).
EVENT:PageDown	The user pressed PgDn (only with the IMM attribute).
EVENT:ScrollTop	The user pressed Ctrl-PgUp (only with the IMM attribute).
EVENT:ScrollBottom	The user pressed Ctrl-PgDn (only with the IMM attribute).
EVENT:PreAlertKey	The user pressed a printable character (only with the IMM attribute) or an ALRT attribute hot key.
EVENT:AlertKey	The user pressed a printable character (only with the IMM attribute) or an ALRT attribute hot key.
EVENT:Locate	The user pressed the locator VCR button (only with the IMM attribute).
EVENT:ScrollDrag	The user moved the scroll bar's "thumb" and its new position is in PROP:VScrollPos (only with the IMM attribute).

EVENT:ScrollTrack	The user is moving the scroll bar's "thumb" and its new position is in PROP:VScrollPos (only with the IMM attribute).
EVENT:DroppingDown	The user pressed the down arrow button (only with the DROP attribute).
EVENT:DroppedDown	The list has dropped (only with the DROP attribute).
EVENT:ColumnResize	A column in the list has been resized.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    COMBO(@S8),AT(0,0,20,20),USE(C1),FROM(Que)
    COMBO(@S8),AT(20,0,20,20),USE(C2),FROM(Que),KEY(F10Key)
    COMBO(@S8),AT(40,0,20,20),USE(C3),FROM(Que),MSG('Button 3')
    COMBO(@S8),AT(60,0,20,20),USE(C4),FROM(Que),HLP('Check4Help')
    COMBO(@S8),AT(80,0,20,20),USE(C5),FROM(Q) |
    ,FORMAT('5C~List~15L~Box~'),COLUMN
    COMBO(@S8),AT(100,0,20,20),USE(C6),FROM(Que),FONT('Arial',12)
    COMBO(@S8),AT(120,0,20,20),USE(C7),FROM(Que),DROP(8)
    COMBO(@S8),AT(140,0,20,20),USE(C8),FROM(Que),HVSCROLL,VCR
    COMBO(@S8),AT(160,0,20,20),USE(C9),FROM(Que),IMM
    COMBO(@S8),AT(180,0,20,20),USE(C10),FROM(Que),CURSOR(CURSOR:Wait)
    COMBO(@S8),AT(200,0,20,20),USE(C11),FROM(Que),ALRT(F10Key)
    COMBO(@S8),AT(220,0,20,20),USE(C12),FROM(Que),LEFT
    COMBO(@S8),AT(240,0,20,20),USE(C13),FROM(Que),RIGHT
    COMBO(@S8),AT(260,0,20,20),USE(C14),FROM(Que),CENTER
    COMBO(@N8.2),AT(280,0,20,20),USE(C15),FROM(Que),DECIMAL
    COMBO(@S8),AT(300,0,20,20),USE(C16),FROM('Apples|Peaches|Pumpkin|Pie')
    COMBO(@S8),AT(320,0,20,20),USE(C17),FROM('TBA')
END

CODE
OPEN(MDIChild)
?C17{PROP:From} = 'Live|Long|And|Prosper'      !Runtime FROM attribute assignment
ACCEPT
CASE ACCEPTED()
OF ?C1
    LOOP X# = 1 to RECORDS(Que)                  !Check for user's entry in Que
        GET(Que,X#)
        IF C1 = Que THEN BREAK.                  !Break loop if present
    END
    IF X# > RECORDS(Que)                          !Check for BREAK
        Que = C1                                  !and add the entry
        ADD(Que)
    END
END
END
END
```

See Also: LIST, ENTRY, PROP:ListFeq

## ELLIPSE (declare an ellipse control)

**ELLIPSE ,AT( )**      **[,USE( )]** **[,DISABLE]** **[,COLOR( )]** **[,FILL( )]** **[,FULL]** **[,SCROLL]** **[,HIDE]** **[,LAYOUT( )]**  
**[,LINEWIDTH]** **[,EXTEND( )]**

<b>ELLIPSE</b>	Places a "circular" figure on the WINDOW, TOOLBAR, or REPORT.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>USE</b>	Specifies a field equate label to reference the control in executable code (PROP:USE).
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>COLOR</b>	Specifies the color for the border of the ellipse (PROP:COLOR). If omitted, the ellipse has no border.
<b>FILL</b>	Specifies the fill color for the control (PROP:FILL). If omitted, the ellipse is not filled with color.
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL). Not valid in a REPORT.
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL). Not valid in a REPORT.
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>LINEWIDTH</b>	Specifies the width of the ELLIPSE's border (PROP:LINEWIDTH).
<b>EXTEND</b>	Specifies special document formatting information. This information contains a valid string of attributes that are assigned to a designated REPORT control for a given document type. Valid only in a REPORT.

The **ELLIPSE** control places a "circular" figure on the WINDOW, TOOLBAR, or REPORT at the position and size specified by its AT attribute. It is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. The ellipse is drawn inside a "bounding box" defined by the *x*, *y*, *width*, and *height* parameters of its AT attribute. The *x* and *y* parameters specify the starting point, and the *width* and *height* parameters specify the horizontal and vertical size of the "bounding box." This control cannot receive input focus and does not generate events.

**Example:**

```

MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !Filled, full screen, black border:
    ELLIPSE,FILL(COLOR:MENU),FULL
    !Unfilled, black border:
    ELLIPSE,AT(0,0,20,20)
    !Dimmed:
    ELLIPSE,AT(0,20,20,20),USE(?Box1),DISABLE
    !Unfilled, rounded, black border:
    ELLIPSE,AT(20,20,20,20),ROUND
    !Filled, black border:
    ELLIPSE,AT(40,40,20,20),FILL(COLOR:ACTIVEBORDER)
    !Unfilled, active border color border:
    ELLIPSE,AT(60,60,20,20),COLOR(COLOR:ACTIVEBORDER)
    !Scrolls with screen:
    ELLIPSE,AT(480,180,20,20),SCROLL
END

CustRpt  REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail DETAIL,AT(0,0,6500,1000)
    !Unfilled, black border:
    ELLIPSE,AT(0,0,20,20)
    !Unfilled, black border, dimmed:
    ELLIPSE,AT(0,20,20,20),USE(?Ellipse1),DISABLE
    !Unfilled, rounded, black border:
    ELLIPSE,AT(20,20,20,20),ROUND
    !Filled, black border:
    ELLIPSE,AT(40,40,20,20),FILL(COLOR:ACTIVEBORDER)
    !Unfilled, active border color border
    ELLIPSE,AT(60,60,20,20),COLOR(COLOR:ACTIVEBORDER)
END
END

```

## ENTRY (declare a data entry control)



**ENTRY**(*picture*)     ,**AT**()[,**CURSOR**()] [,**USE**()] [,**LAYOUT**( )] [,**DISABLE**] [,**KEY**()] [,**MSG**()] [,**HLP**()] [,**SKIP**][,**FONT**()]  
                             [,**IMM**][,**PASSWORD**][,**REQ**][,**FULL**][,**SCROLL**][,**ALRT**()][,**HIDE**][,**TIP**( )][,**FLAT**][,**TRN**][,**READONLY**]  
                             [**DROPID**( )]     [,| **INS**| ]     [,| **CAP**| ]     [,| **LEFT**| ] [,**COLOR**( )] [,**MASK**]  
   | **OVR**|               | **UPR**|               | **RIGHT**|  
   | **CENTER**|  
   | **DECIMAL**|

---

<b>ENTRY</b>	Places a data entry field on the WINDOW or TOOLBAR.
<i>picture</i>	A display picture token that specifies the input format for the data entered into the control (PROP:Text).
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used.
<b>USE</b>	The label of the variable that receives the value entered into the control by the user (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display and entry orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION opens (PROP:DISABLE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to the control (PROP:KEY).
<b>MSG</b>	Specifies a string constant containing the text to display in the status bar when the control has focus (PROP:MSG).
<b>HLP</b>	Specifies a string constant containing the help system identifier for the control (PROP:HLP).
<b>SKIP</b>	Specifies the control receives input focus to enter text only with the mouse or accelerator key and does not retain focus (PROP:SKIP).
<b>FONT</b>	Specifies the display font for the control (PROP:FONT).

<b>IMM</b>	Specifies immediate event generation whenever the user presses any key (PROP:IMM).
<b>PASSWORD</b>	Specifies non-display of the data entered (password mode) (PROP:PASSWORD).
<b>REQ</b>	Specifies the control may not be left blank or zero (PROP:REQ).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL).
<b>ALRT</b>	Specifies "hot" keys active for the control (PROP:ALRT).
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip).
<b>FLAT</b>	Specifies that the control does not have a 3D border drawn around it (PROP:FLAT).
<b>TRN</b>	Specifies the control transparently displays over the background (PROP:TRN).
<b>READONLY</b>	Specifies the control does not allow data entry (PROP:READONLY).
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID).
<b>INS / OVR</b>	Specifies Insert or Overwrite entry mode (PROP:INS and PROP:OVR). This is valid only on windows with the MASK attribute.
<b>UPR / CAP</b>	Specifies all upper case or proper name capitalization (First Letter Of Each Word Capitalized) data entry (PROP:UPR and PROP:CAP).
<b>LEFT</b>	Specifies that the data entered is left justified within the area specified by the AT attribute (PROP:LEFT).
<b>RIGHT</b>	Specifies that the data entered is right justified within the area specified by the AT attribute (PROP:RIGHT).
<b>CENTER</b>	Specifies that the data entered is centered within the area specified by the AT attribute (PROP:CENTER).
<b>DECIMAL</b>	Specifies that the data entered is aligned on the decimal point within the area specified by the AT attribute (PROP:DECIMAL).
<b>COLOR</b>	Specifies background and selected colors for the control (PROP:COLOR).
<b>MASK</b>	Specifies pattern input editing mode of the ENTRY control (PROP:MASK).

The **ENTRY** control places a data entry field on the WINDOW or TOOLBAR (not valid in a REPORT) at the position and size specified by its AT attribute. Data entered is formatted according to the *picture*, and the variable specified in the USE attribute receives the data entered when the user has completed data entry and moves on to another control. Data entry scrolls horizontally to allow the user to enter data to the full length of the variable. Therefore, the right and left arrow keys move within the data in the ENTRY control.

Standard Windows behavior (Cut, Copy, and Paste) are automatically available using CTRL+X, CTRL+C, and CTRL+V while the ENTRY control has focus. Undo is also implemented using CTRL+Z (before the user leaves the control).

An ENTRY control with the PASSWORD attribute displays asterisks when the user enters data (and Cut and Copy are disabled ). This is useful for password-type variables. An ENTRY control with the SKIP attribute is used for seldom-used data entry. Display-only data should be declared with the READONLY attribute.

The LAYOUT attribute is used with ENTRY controls to change the order that text is entered (Left-to-Right or Right-to-Left). Mixed text should always be avoided and may not display correctly (e.g. Arabic text mixed with English text).

The MASK attribute specifies pattern input editing mode of the control. This means that, as the user types in data, each character is automatically validated against the control's picture for proper input (numbers only in numeric pictures, etc.). This forces the user to enter data in the format specified by the control's display picture. If omitted, Windows free-input is allowed in the control. This is Windows' default data entry mode. Free-input means the user's data is formatted to the control's picture only after entry (on EVENT:Accepted). This allows users to enter data as they choose and it is automatically formatted to the control's picture after entry. If the user types in data in a format different from the control's picture, the libraries attempt to determine the format the user used, and convert the data to the control's display picture. For example, if the user types "January 1, 1995" into a control with a display picture of @D1, the runtime library formats the user's input to "1/1/95." This action occurs only after the user completes data entry and moves to another control. If the runtime library cannot determine what format the user used, it will not update the USE variable and will simply generate EVENT:Rejected.

**Events Generated:**

EVENT:Selected	The control has received input focus.
EVENT:Accepted	The user has completed data entry in the control.
EVENT:Rejected	The user has entered an invalid value for the entry picture.
EVENT:PreAlertKey	The user pressed an ALRT attribute hot key.
EVENT:AlertKey	The user pressed an ALRT attribute hot key.
EVENT:Drop	A successful drag-and-drop to the control.
EVENT:NewSelection	The user entered a character (with IMM attribute only).



**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    ENTRY(@S8),AT(0,0,20,20),USE(E1)
    ENTRY(@S8),AT(20,0,20,20),USE(E2),KEY(F10Key)
    ENTRY(@S8),AT(40,0,20,20),USE(E3),MSG('Button 3')
    ENTRY(@S8),AT(60,0,20,20),USE(E4),HLP('Entry4Help')
    ENTRY(@S8),AT(80,0,20,20),USE(E5),DISABLE
    ENTRY(@S8),AT(100,0,20,20),USE(E6),FONT('Arial',12)
    ENTRY(@S8),AT(120,0,20,20),USE(E7),REQ,INS,CAP
    ENTRY(@S8),AT(140,0,20,20),USE(E8),SCROLL,OVR,UPR
    ENTRY(@S8),AT(180,0,20,20),USE(E9),CURSOR(CURSOR:Wait),IMM
    ENTRY(@S8),AT(200,0,20,20),USE(E10),ALRT(F10Key)
    ENTRY(@N8.2),AT(280,0,20,20),USE(E11),DECIMAL(10)
END
```

**See Also:**

TEXT

PROMPT

Entry Control Properties

## GROUP (declare a group of controls)

```
GROUP(text)      ,AT() [,CURSOR()][,USE()] [,LAYOUT( )] [,DISABLE][,KEY()][,MSG()][,HLP()][,FONT()][,TIP()]  
                [,BOXED][,FULL][,SCROLL][,HIDE][,ALRT()][,SKIP][,DROPID()][,COLOR()][,BEVEL()]  
  
                controls  
  
END
```

---

<b>GROUP</b>	Declares a group of controls that may be referenced as one entity.
<i>text</i>	A string constant containing the prompt for the group of controls (PROP:Text). This may contain an ampersand (&) to indicate the "hot" letter for the prompt. The <i>text</i> is displayed on screen only if the BOXED attribute is also present.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control, or any control within the GROUP (PROP:CURSOR). If omitted, the window's CURSOR attribute is used, else the Windows default cursor is used. Not valid in a REPORT.
<b>USE</b>	A field equate label to reference the control in executable code (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the GROUP control and the controls in the GROUP appear dimmed when the WINDOW or APPLICATION is first opened (PROP:DISABLE). Not valid in a REPORT.
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to the first control in the GROUP (PROP:KEY). Not valid in a REPORT.
<b>MSG</b>	Specifies a string constant containing the default text to display in the status bar when any control in the GROUP has focus (PROP:MSG). Not valid in a REPORT.
<b>HLP</b>	Specifies a string constant containing the default help system identifier for any control in the GROUP (PROP:HLP). Not valid in a REPORT.
<b>FONT</b>	Specifies the display font for the control and the default for all the controls in the GROUP (PROP:FONT).

<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip). Not valid in a REPORT.
<b>BOXED</b>	Specifies a single-track border around the group of controls with the text at the top of the border (PROP:BOXED).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW or REPORT band for any missing AT attribute width or height parameter (PROP:FULL).
<b>SCROLL</b>	Specifies the GROUP control and the controls in the GROUP scroll with the window (PROP:SCROLL).
<b>HIDE</b>	Specifies the GROUP control and the controls in the GROUP do not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display them.
<b>ALRT</b>	Specifies "hot" keys active for the controls in the GROUP (PROP:ALRT).
<b>SKIP</b>	Specifies the controls in the GROUP do not receive input focus and may only be accessed with the mouse or accelerator key (PROP:SKIP). Not valid in a REPORT.
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID). Not valid in a REPORT.
<b>COLOR</b>	Specifies default background and selected colors for the controls in the GROUP (PROP:COLOR).
<b>BEVEL</b>	Specifies custom 3-D effect borders (PROP:BEVEL). Not valid in a REPORT.
<i>controls</i>	Control declarations that may be referenced as the GROUP.

The **GROUP** control declares a group of controls to reference as one entity. It is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. GROUP allows the user to use the cursor keys instead of the TAB key to move between the *controls* in the GROUP, and provides default MSG and HLP attributes for all controls in the GROUP. This control cannot receive input focus.

**Events Generated:**

EVENT:Drop    A successful drag-and-drop to the control.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    GROUP('Group 1'),USE(?G1),KEY(F10Key)
        ENTRY(@S8),AT(0,0,20,20),USE(?E1)
        ENTRY(@S8),AT(20,0,20,20),USE(?E2)
    END
    GROUP('Group 2'),USE(?G2),MSG('Group 2'),CURSOR(CURSOR:Wait)
        ENTRY(@S8),AT(40,0,20,20),USE(?E3)
        ENTRY(@S8),AT(60,0,20,20),USE(?E4)
    END
    GROUP('Group 3'),USE(?G3),AT(80,0,20,20),BOXED
        ENTRY(@S8),AT(80,0,20,20),USE(?E5)
        ENTRY(@S8),AT(100,0,20,20),USE(?E6)
    END
END

CustRpt  REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail  DETAIL,AT(0,0,6500,1000)
    GROUP('Group 1'),USE(!G1),AT(80,0,20,20),BOXED
        STRING(@S8),AT(80,0,20,20),USE(E5)
        STRING(@S8),AT(100,0,20,20),USE(E6)
    END
    GROUP('Group 2'),USE(?G2),FONT('Arial',12)
        STRING(@S8),AT(120,0,20,20),USE(E7)
        STRING(@S8),AT(140,0,20,20),USE(E8)
    END
END
END
```

**See Also:**

PANEL

## IMAGE (declare a graphic image control)

```

IMAGE(file),      AT( ) [, USE( )] [, DISABLE]      [ , FULL ]      [, SCROLL] [, HIDE] [, LAYOUT]
                                     [ , TILED ]      [, HSCROLL ] [, EXTEND ( )]
                                     | CENTERED |      | VSCROLL |
                                     | HVSCROLL |

```

---

<b>IMAGE</b>	Places a graphic image on the WINDOW, TOOLBAR, or REPORT.
<i>file</i>	A string constant or equate (see below) containing the name of the file to display (PROP:Text). The named file is automatically linked into the .EXE as a resource.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>USE</b>	A field equate label to reference the control in executable code (PROP:USE).
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION opens (PROP:DISABLE).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL). Not valid in a REPORT.
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL). Not valid in a REPORT.
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION opens (PROP:HIDE). UNHIDE must be used to display it.
<b>TILED</b>	Specifies the image displays at its default size and is tiled to fill the entire area of the IMAGE (PROP:TILED).
<b>CENTERED</b>	Specifies the image displays at its default size and is centered in the area of the IMAGE (PROP:CENTERED).
<b>HSCROLL</b>	Specifies a horizontal scroll bar is automatically added to the IMAGE control when the graphic image is wider than the area specified for display (PROP:HSCROLL). Not valid in a REPORT.
<b>VSCROLL</b>	Specifies a vertical scroll bar is automatically added to the IMAGE control when the graphic image is taller than the area specified for display (PROP:VSCROLL). Not valid in a REPORT.
<b>HVSCROLL</b>	Specifies both vertical and horizontal scroll bars are automatically added to the IMAGE control when the graphic image is larger than the display area. Not valid

in a REPORT.

<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>EXTEND</b>	Specifies special document formatting information. This information contains a valid string of attributes that are assigned to a designated REPORT control for a given document type. Valid only in a REPORT. See also EXTEND

The **IMAGE** control places a graphic image on the WINDOW (or TOOLBAR) at the position specified by its AT attribute. It is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. The image is stretched to fill the area specified by the AT attribute unless the TILED or CENTERED attribute is present. The displayed *file* may be a bitmap (.BMP), PaintBrush (.PCX), Graphic Interchange Format (.GIF), JPEG (.JPG), or Windows metafile (.WMF). The *file* may be an icon (.ICO) or Icon Equate in an IMAGE on a WINDOW but not on a REPORT, because Windows does not support printing icons. The type of *file* is determined by its extension.

This control cannot receive input focus and does not generate events.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    IMAGE('PIC.BMP'),AT(0,0,20,20),USE(?I1)
    IMAGE('PIC.WMF'),AT(40,0,20,20),USE(?I3),SCROLL
END
```

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail DETAIL,AT(0,0,6500,1000)
    IMAGE('PIC.BMP'),AT(0,0,20,20),USE(?I1)
    IMAGE('PIC.WMF'),AT(40,0,20,20),USE(?I2)
    IMAGE('PIC.JPG'),AT(60,0,20,20),USE(?I3)
END
END
```

**See Also:**

PALETTE

How to Assign an Image to Display at Runtime

PROP:ClipBits, PROP:ImageBits, PROP:ImageBlob

**Note:**

There are many other properties associated with the processing of an Image control at runtime. See PROP:HScroll, PROP:VScroll, PROP:HScrollPos, PROP:VScrollPos, PROP:XOrigin, PROP:YOrigin, PROP:ImageInstance, and PROP:PrintMode.

## ITEM (declare a menu item)



```
ITEM(text)  [,AT( )] [,USE( )] [,KEY( )] [,MSG( )] [,HLP( )] [,STD( )] [,CHECK] [,DISABLE] [,COLOR] [,LEFT( )] [,HIDE]
           [,SEPARATOR] [,ICON( )] [,FONT( )]  [,| FIRST| ]
           | LAST|
```

---

<b>ITEM</b>	Declares a menu choice within a MENUBAR or MENU structure.
<i>Text</i>	A string constant containing the display text for the menu item (PROP:Text).
<b>AT</b>	Specifies the width and height of the menu item (PROP:AT). If omitted, default values are selected by the runtime library. The first two parameters of the AT attribute are ignored. The fixed width specified by the AT attribute includes (and therefore must be greater than) the text offset specified by the LEFT attribute. The specified width of the area to draw the item can be less than the width of the default area provided by Windows, and the runtime library uses the full width of the specified area.
<b>USE</b>	A field equate label to reference the menu item in executable code, or the variable used with CHECK (PROP:USE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately executes the menu item (PROP:KEY).
<b>MSG</b>	Specifies a string constant containing the text to display in the status bar when the menu item is highlighted (PROP:MSG).
<b>HLP</b>	Specifies a string constant containing the help system identifier for the menu item (PROP:HLP).
<b>STD</b>	Specifies an integer constant or equate that identifies a "Windows standard action" the menu item executes (PROP:STD).
<b>CHECK</b>	Specifies an on/off ITEM (PROP:CHECK).
<b>DISABLE</b>	Specifies the menu item appears dimmed when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>COLOR</b>	Specifies the background, foreground, and selected color for the menu item control.(see <a href="#">COLOR</a> )
<b>LEFT</b>	Specifies the offset in dialog units from the left edge of the menu structure.
<b>HIDE</b>	Specifies the ITEM does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.

<b>SEPARATOR</b>	Specifies the ITEM displays a solid horizontal line across the menu box at run-time to delimit groups of menu selections. The USE attribute may be specified with SEPARATOR.
<b>ICON</b>	Specifies an image file or standard icon to display on the menu item (PROP:ICON).
<b>FONT</b>	Specifies the display font for the control (PROP:FONT).
<b>FIRST</b>	Specifies the ITEM appears at the top of the menu when menus are merged (PROP:FIRST).
<b>LAST</b>	Specifies the ITEM appears at the bottom of the menu when menus are merged (PROP:LAST).

**ITEM** declares a menu choice within a MENUBAR or MENU structure. The *text* string may contain an ampersand ( & ) which designates the following character as an accelerator "hot" key which is automatically underlined. If the ITEM is on the menu bar, pressing the Alt key together with the accelerator key highlights and executes the ITEM. If the ITEM is in a MENU, pressing the accelerator key, alone, when the menu is displayed, highlights and executes the ITEM. If there is no ampersand in the *text*, the first non-blank character in the *text* string is the accelerator key for the ITEM, which will not be underlined. To include an ampersand as part of the *text*, place two ampersands together (&&) in the *text* string and only one will display. The KEY attribute designates a separate "hot" key for the item. This may be any valid Clarion keycode to immediately execute the ITEM's action.

A cursor bar highlights individual ITEMS within the MENU structure. Each ITEM is usually associated with some code to be executed upon selection of that ITEM, unless the STD attribute is present. The STD attribute specifies a standard Windows action the menu item performs, such as Tile or Cascade the windows. The SEPARATOR attribute creates an ITEM which serves only to delimit groups of menu selections so it should not have a *text* parameter. The USE attribute may be used with a SEPARATOR. It creates a solid horizontal line across the menu box. An ITEM that is not within a MENU structure is placed on the menu bar. This creates a menu bar selection which has no related drop-down menu. The normal convention to indicate this to the user is to terminate the *text* displayed for the item with an exclamation point (!). For example, the *text* for the ITEM might contain 'Exit!' to alert the user to the executable nature of the menu choice.

**Events Generated:**

EVENT:Accepted      The control has been pressed by the user.



**Example:**

```

MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS,HVSCROLL,RESIZE
MENUBAR
  ITEM('E&xit!'),USE(?MainExit),FIRST
  MENU('File'),USE(?FileMenu),FIRST
    ITEM('Open...'),USE(?OpenFile),HLP('OpenFileHelp'),FIRST
    ITEM('Close'),USE(?CloseFile),HLP('CloseFileHelp'),DISABLE
    ITEM('Auto Increment'),USE(ToggleVar),CHECK
  END
  MENU('Edit'),USE(?EditMenu),KEY(CtrlE),HLP('EditMenuHelp')
    ITEM('Undo'),USE(?UndoText),KEY(CtrlZ),STD(STD:Undo),DISABLE
    ITEM,SEPARATOR
    ITEM('Cu&t'),USE(?CutText),KEY(CtrlX),STD(STD:Cut),DISABLE
    ITEM('Copy'),USE(?CopyText),KEY(CtrlC),STD(STD:Copy),DISABLE
    ITEM('Paste'),USE(?PasteText),KEY(CtrlV),STD(STD:Paste),DISABLE
  END
  MENU('Window'),STD(STD:WindowList),MSG('Arrange or Select Window'),LAST
    ITEM('Tile'),STD(STD:TileWindow)
    ITEM('Cascade'),STD(STD:CascadeWindow)
    ITEM('Arrange Icons'),STD(STD:ArrangeIcons)
    ITEM,SEPARATOR,USE(?FileSeparator1)
  END
  MENU('Help'),USE(?HelpMenu),LAST,RIGHT
    ITEM('Contents'),USE(?HelpContents),STD(STD:HelpIndex)
    ITEM('Search for Help On...'),USE(?HelpSearch),STD(STD:HelpSearch)
    ITEM('How to Use Help'),USE(?HelpOnHelp),STD(STD:HelpOnHelp)
    ITEM('About MyApp...'),USE(?HelpAbout),MSG('Copyright Info'),LAST
  END
END !Menubar
END !Application

```

## LINE (declare a line control)

**LINE** [,AT( )] [,USE( )] [,DISABLE] [,COLOR( )] [,FULL] [,SCROLL] [,HIDE] [,LINEWIDTH( )] [,LAYOUT()] [,EXTEND( )]

---

<b>LINE</b>	Places a straight line on the WINDOW, TOOLBAR, or REPORT.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>USE</b>	A field equate label to reference the control in executable code (PROP:USE).
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION opens (PROP:DISABLE).
<b>COLOR</b>	Specifies the color for the line (PROP:COLOR). If omitted, the color is black.
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW or REPORT band for any missing AT attribute width or height parameter (PROP:FULL).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL). Not valid in a REPORT.
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>LINEWIDTH</b>	Specifies the thickness of the LINE (PROP:LINEWIDTH).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>EXTEND</b>	Specifies special document formatting information. This information contains a valid string of attributes that are assigned to a designated REPORT control for a given document type. Valid only in a REPORT.

The **LINE** control places a straight line on the WINDOW, TOOLBAR, or REPORT at the position and size specified by its AT attribute. It is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. The *x* and *y* parameters of the AT attribute specify the starting point of the line. The *width* and *height* parameters of the AT attribute specify the horizontal and vertical distance to the end point of the line. If these are both positive numbers, the line slopes to the right and down from its starting point. If the *width* is negative, the line slopes left; if the *height* is negative, the line slopes left. If either the *width* or *height* is zero, the line is horizontal or vertical. This control cannot receive input focus and does not generate events.

<u>Width</u>	<u>Height</u>	<u>Result</u>
positive	positive	right and down from start point
negative	positive	left and down from start point
positive	negative	right and up from start point
negative	negative	left and up from start point
zero	positive	vertical, down from start point
zero	negative	vertical, up from start point
positive	zero	horizontal, right from start point
negative	zero	horizontal, left from start point

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    LINE,AT(60,60,20,20),COLOR(COLOR:ACTIVEBORDER)    !Border color
    LINE,AT(480,180,20,20),SCROLL                      !Scrolls with screen
END

CustRpt    REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail DETAIL,AT(0,0,6500,1000)
    LINE,AT(60,60,20,20),COLOR(COLOR:ACTIVEBORDER) !Border color
    LINE,AT(480,180,20,20),USE(?L2)
    END
END
```

## LIST (declare a window list control)

```
LIST ,AT( ) [,FROM( )] [,CURSOR( )] [,USE( )] [,DISABLE] [,KEY( )] [,MSG( )] [,HLP( )] [,SKIP]
    [,FONT( )] [,FORMAT( )] [,DROP] [,COLUMN] [,VCR] [,FULL] [,SCROLL] [,NOBAR] [,FLAT]
    [,ALRT( )] [,HIDE] [,DRAGID( )] [,DROPID( )] [,TIP( )] [,GRID( )] [,TRN] [,COLOR( )] [,LAYOUT( )]
    [,| MARK( )|]          [,| HSCROLL|]      [,| LEFT|]
    | IMM|                  | VSCROLL|         | RIGHT|
                           | HVSCROLL|        | CENTER|
                           | DECIMAL|
```

---

<b>LIST</b>	Places a scrolling list of data items on the WINDOW, TOOLBAR, or REPORT.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, the runtime library chooses a value.
<b>FROM</b>	Specifies the origin of the data displayed in the list (PROP:FROM).
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used. Not valid in a REPORT.
<b>USE</b>	A field equate label to reference the control in executable code, or the label of the variable that receives the value selected by the user (PROP:USE).
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION opens (PROP:DISABLE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to the control (PROP:KEY). Not valid in a REPORT.
<b>MSG</b>	Specifies a string constant containing the text to display in the status bar when the control has focus (PROP:MSG). Not valid in a REPORT.
<b>HLP</b>	Specifies a string constant containing the help system identifier for the control (PROP:HLP). Not valid in a REPORT.
<b>SKIP</b>	Specifies the control does not receive input focus and may only be accessed with the mouse or accelerator key (PROP:SKIP). Not valid in a REPORT.
<b>FONT</b>	Specifies the display font for the control (PROP:FONT).
<b>FORMAT</b>	Specifies the display format of the data in the list (PROP:FORMAT). This can include icons, colors, and tree controls.

<b>DROP</b>	Specifies a drop-down list box and the number of elements the drop-down portion contains (PROP:DROP). Not valid in a REPORT.
<b>COLUMN</b>	Specifies cell-by-cell highlighting on multi-column lists (PROP:COLUMN). Not valid in a REPORT.
<b>VCR</b>	Specifies a VCR-type control to the left of any horizontal scroll bar (PROP:VCR). Not valid in a REPORT.
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL). Not valid in a REPORT.
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL). Not valid in a REPORT.
<b>NOBAR</b>	Specifies the highlight bar is displayed only when the LIST has focus (PROP:NOBAR). Not valid in a REPORT.
<b>FLAT</b>	Specifies that the control does not have a 3D border drawn around it (PROP:FLAT).
<b>ALRT</b>	Specifies "hot" keys active for the control (PROP:ALRT). Not valid in a REPORT.
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION opens (PROP:HIDE). UNHIDE must be used to display it.
<b>DRAGID</b>	Specifies the control may serve as a drag host for drag-and-drop actions (PROP:DRAGID). Not valid in a REPORT.
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID). Not valid in a REPORT.
<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip). Not valid in a REPORT.
<b>GRID</b>	Specifies the color of the grid lines between columns in the list (PROP:GRID).
<b>TRN</b>	Specifies the control transparently displays over the background (PROP:TRN).
<b>COLOR</b>	Specifies background and selected colors for the control (PROP:COLOR).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>MARK</b>	Specifies multiple items selection mode (PROP:MARK). Not valid in a REPORT.
<b>IMM</b>	Specifies generation of an event whenever the user presses any key (PROP:IMM). Not valid in a REPORT.
<b>HSCROLL</b>	Specifies that a horizontal scroll bar is automatically added to the list box when any portion of the data item lies horizontally outside the visible area (PROP:HSCROLL). Not valid in a REPORT.

<b>VSCROLL</b>	Specifies that a vertical scroll bar is automatically added to the list box when any data items lie vertically outside the visible area (PROP:VSCROLL). Not valid in a REPORT.
<b>HVSCROLL</b>	Specifies that both vertical and horizontal scroll bars are automatically added to the list box when any portion of the data items lies outside the visible area. Not valid in a REPORT.
<b>LEFT</b>	Specifies that the data is left justified within the LIST (PROP:LEFT).
<b>RIGHT</b>	Specifies that the data is right justified within the LIST (PROP:RIGHT).
<b>CENTER</b>	Specifies that the data is centered within the LIST (PROP:CENTER).
<b>DECIMAL</b>	Specifies that the data is aligned on the decimal point within the LIST (PROP:DECIMAL).

The **LIST** control places a scrolling list of data items on the WINDOW, TOOLBAR, or REPORT at the position and size specified by its AT attribute. It is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. The data items displayed in the LIST come from a QUEUE or STRING specified by the FROM attribute and are formatted by the parameters specified in the FORMAT attribute (which can include colors, icons, and tree control parameters).

The CHOICE procedure returns the QUEUE entry number (the value returned by POINTER(queue)) of the selected item when the EVENT:Accepted event has been generated by the LIST. The data displayed in the LIST is automatically refreshed every time through the ACCEPT loop, whether the AUTO attribute is present or not.

A LIST with the DROP attribute displays only the currently selected data item on screen until the control has focus and the user presses the down arrow key, or CLICKS ON the the icon to the right of the displayed data item. When either of these occurs, the selection list appears ("drops down") to allow the user to select an item.

A LIST with the IMM attribute generates an event every time the user moves the highlight bar to another selection, or presses any key (all keys are implicitly ALRTed). This allows an opportunity for the source code to re-fill the display QUEUE, or get the currently highlighted record to display other fields from the record. If VSCROLL is also present, the vertical scroll bar is always displayed and when the end-user CLICKS on the scroll bar, events are generated but the list does not move (executable code should perform this action). You can interrogate the PROP:VscrollPos property to determine the scroll thumb's position from 0 (top) to 255 (bottom).

A LIST with the VCR attribute has scroll control buttons like a Video Cassette Recorder to the left of the horizontal scroll bar (if there is one). These buttons allow the user to use the mouse to scroll through the list.

A LIST with the DRAGID attribute can serve as a drag-and-drop host, providing information to be moved or copied to another control. A LIST with the DROPID attribute can serve as a drag-and-drop target, receiving information from another control. These attributes work together to specify drag-and-drop "signatures" that define a valid target for the operation. The DRAGID() and DROPID() procedures, along with the SETDROPID procedure, are used to perform the data exchange.

## REPORT Usage

LIST is valid only in a DETAIL structure. Its purpose is to allow the report format to duplicate the screen appearance of the LIST's FORMAT setting. When the first instance of the DETAIL structure containing the LIST prints, any headers in the FORMAT attribute print along with the current FROM attribute entry. When the last DETAIL structure containing the LIST prints, the LIST footers print along with the current FROM attribute entry.

### Events Generated:

EVENT:Selected	The control has received input focus.
EVENT:Accepted	The user has selected an entry from the control.
EVENT:NewSelection	The current selection in the list has changed (the highlight bar has moved up or down).
EVENT:ScrollUp	The user pressed the up arrow (only with the IMM attribute).
EVENT:ScrollDown	The user pressed the down arrow (only with the IMM attribute).
EVENT:PageUp	The user pressed PGUP (only with the IMM attribute).
EVENT:PageDown	The user pressed PGDN (only with the IMM attribute).
EVENT:ScrollTop	The user pressed CTRL+PGUP (only with IMM attribute).
EVENT:ScrollBottom	The user pressed CTRL+PGDN (only with IMM attribute).
EVENT:Locate	The user pressed the locator VCR button (only with the IMM attribute).
EVENT:ScrollDrag	The user moved the scroll bar's "thumb" and its new position is in PROP:VScrollPos (only with the IMM attribute).
EVENT:ScrollTrack	The user is moving the scroll bar's "thumb" and its new position is in PROP:VScrollPos (only with the IMM attribute).
EVENT:PreAlertKey	The user pressed a printable character (only with the IMM attribute) or an ALRT attribute hot key.
EVENT:AlertKey	The user pressed a printable character (only with the IMM attribute) or an ALRT attribute hot key.
EVENT:Dragging	The mouse cursor is over a potential drag target (only with the DRAGID attribute).
EVENT:Drag	The mouse cursor has been released over a drag target (only with the DRAGID attribute).
EVENT:Drop	The mouse cursor has been released over a drag target (only with the DROPID attribute).
EVENT:DroppingDown	The user has requested the droplist drop down (only with the DROP attribute). CYCLE aborts the dropdown.

EVENT:DroppedDown	The user has dropped the droplist (only with the DROP attribute).
EVENT:Expanding	The user has clicked on a tree expansion box (only with the T in the FORMAT attribute string). CYCLE aborts the expansion.
EVENT:Expanded	The user has clicked on a tree expansion box (only with the T in the FORMAT attribute string).
EVENT:Contracting	The user has clicked on a tree contraction box (only with the T in the FORMAT attribute string). CYCLE aborts the contraction.
EVENT:Contracted	The user has clicked on a tree contraction box (only with the T in the FORMAT attribute string).
EVENT:ColumnResize	A column in the list has been resized.

**Example:**

```

Q      QUEUE
F1     STRING(1)
F2     STRING(4)
      END

MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
      LIST,AT(0,0,20,20),USE(?L1),FROM(Que),IMM
      LIST,AT(20,0,20,20),USE(?L2),FROM(Que),KEY(F10Key)
      LIST,AT(40,0,20,20),USE(?L3),FROM(Que),MSG('Button 3')
      LIST,AT(60,0,20,20),USE(?L4),FROM(Que),HLP('Check4Help')
      LIST,AT(80,0,20,20),USE(?L5),FROM(Q),FORMAT('5C~List~15L~Box~'),COLUMN
      LIST,AT(100,0,20,20),USE(?L6),FROM(Que),FONT('Arial',12)
      LIST,AT(120,0,20,20),USE(?L7),FROM(Que),DROP(6)
      LIST,AT(140,0,20,20),USE(?L8),FROM(Que),HVSCROLL,VCR
      LIST,AT(180,0,20,20),USE(?L10),FROM(Que),CURSOR(CURSOR:Wait)
      LIST,AT(200,0,20,20),USE(?L11),FROM(Que),ALRT(F10Key)
      LIST,AT(220,0,20,20),USE(?L12),FROM(Que),LEFT
      LIST,AT(240,0,20,20),USE(?L13),FROM(Que),RIGHT
      LIST,AT(260,0,20,20),USE(?L14),FROM(Que),CENTER
      LIST,AT(280,0,20,20),USE(?L15),FROM(Que),DECIMAL
      LIST,AT(300,0,20,20),USE(?L16),FROM('Apples|Peaches|Pumpkin|Pie')
      LIST,AT(320,0,20,20),USE(?L17),FROM('TBA')
      END

CustRpt  REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail DETAIL,AT(0,0,6500,1000)
      LIST,AT(80,0,20,20),USE(?L1),FROM(Q),FORMAT('5C~List~15L~Box~')
      END
      END

CODE
OPEN(MDIChild)
?L1{PROP:From} = 'Live|Long|And|Prosper'    !Runtime FROM attribute assignment

```

**See Also:** COMBO, DRAGID, DROPID, SETDROPID



## MENU (declare a menu box)



```

MENU(text)    [,AT( )] [,USE( )] [,KEY( )] [,MSG( )] [,HLP( )] [,STD( )] [,RIGHT] [,DISABLE] [,COLOR] [,LEFT( )] [,HIDE]
               [,ICON( )] [,FONT( )]      [,| FIRST|]
               | LAST|

END

```

---

<b>MENU</b>	Declares a menu box within a MENUBAR.
<i>text</i>	A string constant containing the display text for the menu selection (PROP:Text).
<b>AT</b>	Specifies the width and height of the menu box ( <a href="#">PROP:AT</a> ). If omitted, default values are selected by the runtime library. The first two parameters of the AT attribute are ignored. The fixed width specified by the AT attribute includes (and therefore must be greater than) the text offset specified by the LEFT attribute. The specified width of the area to draw the menu box can be less than the width of the default area provided by Windows, and the runtime library uses the full width of the specified area.
<b>USE</b>	A field equate label to reference the menu selection in executable code(PROP:USE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately opens the menu (PROP:KEY).
<b>MSG</b>	Specifies a string constant containing the text to display in the status bar when the menu is pulled down (PROP:MSG).
<b>HLP</b>	Specifies a string constant containing the help system identifier for the menu (PROP:HLP).
<b>STD</b>	Specifies an integer constant or equate that identifies a "Windows standard behavior" for the menu (PROP:STD).
<b>RIGHT</b>	Specifies the MENU appears at the far right of the action bar (PROP:RIGHT).
<b>DISABLE</b>	Specifies the menu appears dimmed when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>COLOR</b>	Specifies the background, foreground, and selected color for the menu control .(see. <a href="#">COLOR</a> )

<b>LEFT</b>	Specifies the offset in dialog units from the left edge of the menu structure.
<b>HIDE</b>	Specifies the MENU does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>ICON</b>	Specifies an image file or standard icon to display on the menu (PROP:ICON).
<b>FONT</b>	Specifies the display font for the control (PROP:FONT).
<b>FIRST</b>	Specifies the MENU appears at the left or top of the menu when merged (PROP:FIRST).
<b>LAST</b>	Specifies the MENU appears at the right or bottom of the menu when merged (PROP:LAST).

**MENU** declares a drop-down or cascading menu box structure within a MENUBAR structure. When the MENU is selected, the MENU and/or ITEM statements within the structure are displayed in a menu box. A menu box usually appears (drops down) immediately below its *text* on the menu bar (or above, if there is no room below). When selected with ENTER or RIGHT ARROW, any subsequent menu drop-box appears (cascades) immediately to the right of the MENU *text* in the preceding menu box (or left, if there is no room to the right). LEFT ARROW backs up to the preceding menu. The KEY attribute designates a separate accelerator key for the field. This may be any valid Clarion keycode to immediately pull down the MENU.

The *text* string may contain an ampersand ( & ) which designates the following character as the accelerator "hot" key which is automatically underlined. If the MENU is on the menu bar, pressing the Alt key together with the accelerator key highlights and displays the MENU. If the MENU is within another MENU, pressing the accelerator key, alone, highlights and executes the MENU. If there is no ampersand in the *text*, the first non-blank character in the *text* string is the accelerator key for the MENU, but it will not be underlined. To include an ampersand as part of the *text*, place two ampersands together (&&) in the *text* string and only one will display.

**Example:**

```

!An MDI application frame window with main menu for the application:
MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS,HVSCROLL,RESIZE
MENUBAR
MENU('File'),USE(?FileMenu),FIRST
ITEM('Open...'),USE(?OpenFile)
ITEM('Close'),USE(?CloseFile),DISABLE
ITEM('E&xit'),USE(?MainExit)
END
MENU('Edit'),USE(?EditMenu),KEY(CTRL),HLP('EditMenuHelp')
ITEM('Undo'),USE(?UndoText),KEY(CTRLZ),STD(STD:Undo),DISABLE
ITEM('Cu&t'),USE(?CutText),KEY(CTRLX),STD(STD:Cut),DISABLE
ITEM('Copy'),USE(?CopyText),KEY(CTRLC),STD(STD:Copy),DISABLE
ITEM('Paste'),USE(?PasteText),KEY(CTRLV),STD(STD:Paste),DISABLE
ITEM,SEPARATOR,USE(?FileSeprator1)
END
MENU('Window'),STD(STD:WindowList),MSG('Arrange or Select Window'),LAST
ITEM('Tile'),STD(STD:TileWindow)
ITEM('Cascade'),STD(STD:CascadeWindow)
ITEM('Arrange Icons'),STD(STD:ArrangeIcons)
END
MENU('Help'),USE(?HelpMenu),LAST,RIGHT
ITEM('Contents'),USE(?HelpContents),STD(STD:HelpIndex)
ITEM('Search for Help On...'),USE(?HelpSearch),STD(STD:HelpSearch)
ITEM('How to Use Help'),USE(?HelpOnHelp),STD(STD:HelpOnHelp)
ITEM('About MyApp...'),USE(?HelpAbout)
END
END
END

```

## OLE (declare a window OLE or .OCX container control)



```
OLE ,AT( )      [,CURSOR( )] [,USE()] [,LAYOUT][,DISABLE] [,KEY()] [,MSG()] [,HLP()] [,SKIP] [,FULL] [,TIP()]
                [,SCROLL] [,ALRT( )] [,HIDE] [,FONT( )] [,DROPID( )] [,COMPATIBILITY( )]
                [,| CREATE( )|]      [,| CLIP|]      [,property( value )]
                | OPEN( )|            | AUTOSIZE|
                | LINK( )|            | STRETCH|
                | DOCUMENT( )|      | ZOOM|

[ MENUBAR
    multiple menu and/or item declarations
END ]

END
```

---

<b>OLE</b>	Places an OLE (Object Linking and Embedding) or .OCX control on the WINDOW or TOOLBAR.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the control.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used.
<b>USE</b>	A Field Equate Label or the label of a variable to receive the "value" of the control (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to the control (PROP:KEY).

<b>MSG</b>	Specifies a string constant containing the text to display in the status bar when the control has focus (PROP:MSG).
<b>HLP</b>	Specifies a string constant containing the help system identifier for the control (PROP:HLP).
<b>SKIP</b>	Specifies the control does not receive input focus and may only be accessed with the mouse or accelerator key (PROP:SKIP).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL).
<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL).
<b>ALRT</b>	Specifies "hot" keys active for the control (PROP:ALRT).
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>FONT</b>	Specifies the display font for the control (PROP:FONT).
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID).
<b>COMPATIBILITY</b>	Specifies a compatibility mode for certain OLE or .OCX objects that require it (PROP:COMPATIBILITY).
<b>CREATE</b>	Specifies the control creates a new OLE object or .OCX (PROP:CREATE).
<b>OPEN</b>	Specifies the control opens an object from an OLE Compound Storage file (PROP:AT). When the object is opened, the saved version of the container properties are reloaded, so properties do not need to be re-specified.
<b>LINK</b>	Specifies the OLE object is a link to an object from a file, for example an Excel spreadsheet (PROP:LINK).
<b>DOCUMENT</b>	Specifies the OLE object is an object from a file, for example an Excel spreadsheet (PROP:DOCUMENT).
<b>CLIP</b>	Specifies the OLE object only displays what fits into the size of the OLE container control's AT attribute (PROP:CLIP). If the object is larger than the OLE container control, only the top left corner displays.
<b>AUTOSIZE</b>	Specifies the OLE object automatically resizes itself when the OLE container control's AT attribute parameters change at runtime using PROP:AT, (PROP:AUTOSIZE).
<b>STRETCH</b>	Specifies the OLE object stretches to completely fill the size specified by the OLE container control's AT attribute (PROP:STRETCH).

<b>ZOOM</b>	Specifies the OLE object stretches to fill the size specified by the OLE container control's AT attribute while maintaining the object's aspect ratio (PROP:ZOOM).
<i>property</i>	A string constant containing the name of a custom property setting for the control.
<i>value</i>	A string constant containing the property value number or EQUATE for the <i>property</i> .
<b>MENUBAR</b>	Defines a menu structure for the control. This is exactly the same type of structure as a MENUBAR in an APPLICATION or WINDOW structure and is merged into the application's menu.
<i>menus and/or items</i>	MENU and/or ITEM declarations that define the menu selections.

The **OLE** control places an OLE or .OCX control on the WINDOW or TOOLBAR (not valid in a REPORT) at the position and size specified by its AT attribute. The *property* attribute allows you to specify any additional property settings the OLE or .OCX control may require. These are properties that need to be set for the OLE or .OCX control to properly function, and are not standard Clarion properties (such as AT, CURSOR, or USE). The custom control should only receive values for these properties that are defined for that control. Valid properties and values for those properties would be defined in the custom control's documentation. You may have multiple *property* attributes on a single OLE control.

**Events Generated:**

EVENT:Selected	The control has received input focus.
EVENT:Accepted	The user has completed using the control.
EVENT:PreAlertKey	The user pressed an ALRT attribute hot key.
EVENT:AlertKey	The user pressed an ALRT attribute hot key.
EVENT:Drop	A successful drag-and-drop to the control.

**Example:**

```
PROGRAM
MAP
  INCLUDE ('OCX.CLW')
END

W WINDOW('OCX Controls'), AT(, , 200, 200), RESIZE, STATUS(-1, -1), SYSTEM
  MENUBAR
    ITEM('E&xit!'), USE(?Exit)
    ITEM(' &About!'), USE(?About)
    ITEM(' &Properties!'), USE(?Property)
  END
  OLE, AT(0, 0, 0, 0), USE(?oc1), HIDE, CREATE('COMCTL.ImagelistCtrl.1').
  OLE, AT(0, 0, 150, 20), USE(?oc2), CREATE('TOOLBAR.ToolbarCtrl.1').
END
```

```

CODE
OPEN(W)
?oc1{'ListImages.Add(1,xyz,' & ocxloadimage('IRCLOCK.BMP') & '')}
?oc1{'ListImages.Add(2,abc,' & ocxloadimage('IRCLOCK2.BMP') & '')}
?oc2{'ImageList'} = ?oc1{PROP:Object}
LOOP X# = 1 TO 3
  ?oc2{'Buttons.Add(,,,1)'}; ?oc2{'Buttons.Add(,,,2)'}
END
ACCEPT
CASE EVENT()
OF EVENT:Accepted
CASE FIELD()
OF ?Exit
BREAK
OF ?About
  ?oc1{'AboutBox'}           !Display the OCX control's About Box
OF ?Property
  ?oc1{PROP:DoVerb} = -7     !Display the OCX control's properties dialog
END
END
END

```

**See Also:**

Object Linking and Embedding  
 OLE (.OCX) Custom Controls  
 OCX Library Procedures

## OPTION (declare a set of RADIO controls)

**OPTION**(*text*), **AT**( )     [**CURSOR**( )] [**USE**( )] [**LAYOUT**( )][**DISABLE**] [**KEY**( )] [**MSG**( )] [**HLP**( )] [**BOXED**]  
                                  [**FULL**] [**SCROLL**] [**HIDE**] [**FONT**( )] [**ALRT**( )] [**SKIP**] [**DROPID**( )] [**TIP**( )] [**TRN**]  
                                  [**COLOR**( )] [**BEVEL**( )] [**EXTEND**( )]

*radios*

**END**

---

<b>OPTION</b>	Declares a set of RADIO controls.
<i>text</i>	A string constant containing the prompt for the set of controls (PROP:Text). This may contain an ampersand (&) to indicate the "hot" letter for the prompt. The <i>text</i> is displayed on screen only if the BOXED attribute is also present.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used. Not valid in a REPORT.
<b>USE</b>	The label of a variable to receive the choice (PROP:USE). If this is a string variable, it receives the value of the RADIO string (with any accelerator key ampersand stripped out) selected by the user. If a numeric variable, it receives the ordinal position within the OPTION of the RADIO button selected by the user (the value returned by the CHOICE() procedure).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to the currently selected RADIO in the OPTION control (PROP:KEY). Not valid in a REPORT.
<b>MSG</b>	Specifies a string constant containing the default text to display in the status bar when any control in the OPTION has focus (PROP:MSG). Not valid in a REPORT.



<b>HLP</b>	Specifies a string constant containing the default help system identifier for any control in the OPTION (PROP:HLP). Not valid in a REPORT.
<b>BOXED</b>	Specifies a single-track border around the RADIO controls with the text at the top of the border (PROP:BOXED).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW or REPORT band for any missing AT attribute width or height parameter (PROP:FULL).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL). Not valid in a REPORT.
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>FONT</b>	Specifies the display font for the control and the default for all the controls in the OPTION (PROP:FONT).
<b>ALRT</b>	Specifies "hot" keys active for the controls in the OPTION (PROP:ALRT). Not valid in a REPORT.
<b>SKIP</b>	Specifies the controls in the OPTION do not receive input focus and may only be accessed with the mouse or accelerator key (PROP:SKIP). Not valid in a REPORT.
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID). Not valid in a REPORT.
<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip). Not valid in a REPORT.
<b>COLOR</b>	Specifies a background color for the control (PROP:COLOR).
<b>BEVEL</b>	Specifies custom 3-D effect borders (PROP:BEVEL). Not valid in a REPORT.
<b>TRN</b>	Specifies the text or USE variable characters transparently display over the background (PROP:Trn).
<b>EXTEND</b>	Specifies special document formatting information. This information contains a valid string of attributes that are assigned to a designated REPORT control for a given document type. Valid only in a REPORT.
<i>radios</i>	Multiple RADIO control declarations.

The **OPTION** control declares a set of RADIO controls which offer the user a list of choices. It is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. The multiple RADIO controls in the OPTION structure define the choices offered to the user. On a REPORT, the OPTION control prints a group of RADIO controls which display a list of choices. The selected choice is identified by a filled RADIO button.

Input focus changes between the OPTION's RADIO controls are signalled only to the individual RADIO controls affected. This means the EVENT:Selected events generated when the user changes input focus within an OPTION structure are field-specific events for the affected RADIO controls, not the OPTION structure which contains them. There is no EVENT:Selected generated for an OPTION structure. However, the RADIO control does not receive EVENT:Accepted, the OPTION structure receives the EVENT:Accepted when the user has selected a RADIO.

A string variable as the OPTION structure's USE attribute receives the text of the RADIO control selected by the user, and the CHOICE(?Option) procedure returns the number of the selected RADIO button. If the contents of the OPTION structure's USE attribute is a numeric variable, it receives the number of the RADIO button selected by the user (the value returned by the CHOICE procedure).

No RADIO button selected is a valid option, which occurs only when the OPTION structure's USE variable does not contain a value related to one of its component RADIO controls. This condition only lasts until the user has selected one of the RADIOS.

While OPTIONS can alert keys via ALRT, the EVENT:AlertKey and EVENT:PreAlertKey events are posted to the active RADIO control with focus.

**Events Generated:**

- |                   |   |
|-------------------|---|
| EVENT:Accepted    | One of the OPTION's RADIO controls has been selected by the user. |
| EVENT:PreAlertKey | The user pressed an ALRT attribute hot key.                       |
| EVENT:AlertKey    | The user pressed an ALRT attribute hot key.                       |
| EVENT:Drop        | A successful drag-and-drop to the control.                        |

**Example:**

```

MDIChild WINDOW('Child One'),AT(0,0,320,89),HVSCROLL,GRAY,MAX,MDI
    OPTION('Option 1'),AT(24,15,56,48),USE(OptVar1),HLP('~Option1Help')
        RADIO('Radio 1'),AT(31,24,41,12),USE(?R1)
        RADIO('Radio 2'),AT(31,37,38,14),USE(?R2)
    END
    OPTION('Option 2'),AT(97,16,56,47),USE(OptVar2),SCROLL,MSG('Option 2')
        RADIO('Radio 3'),AT(101,24,41,12),USE(?R3)
        RADIO('Radio 4'),AT(101,39,41,12),USE(?R4)
    END
    OPTION('Option 3'),AT(164,17,59,47),USE(OptVar3),BOXED
        RADIO('Radio 5'),AT(169,27,41,12),USE(?R5)
        RADIO('Radio 6'),AT(169,40,41,12),USE(?R6)
    END
    OPTION('Option 4'),AT(235,11,56,54),USE(OptVar4),FONT('Arial',12,,)
        RADIO('Radio 7'),AT(242,19,41,12),USE(?R7)
        RADIO('Radio 8'),AT(242,39,41,12),USE(?R8)
    END
END

CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail DETAIL,AT(, , 6500,1000)
    OPTION('Option'),AT(83,10,2000,865),USE(OptVar),BOXED
        RADIO('Radio 1'),AT(156,219,979,219),USE(?R1)
        RADIO('Radio 2'),AT(156,500,1000,219),USE(?R2)
    END
END
END

```

**See Also:**

RADIO  
 BUTTON  
 CHECK

## PANEL (declare a panel control)



**PANEL**, **AT**( ) [, **USE**( )] [, **LAYOUT**( )] [, **DISABLE**] [, **FULL**] [, **FILL**( )] [, **SCROLL**] [, **HIDE**] [, **BEVEL**( )]

---

<b>PANEL</b>	Defines an area in the WINDOW or TOOLBAR.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>USE</b>	A field equate label to reference the control in executable code (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control is disabled when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL).
<b>FILL</b>	Specifies the fill color for the control (PROP:FILL). If omitted, the panel is not filled with color.
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL).
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>BEVEL</b>	Specifies custom 3-D effect borders (PROP:BEVEL).

The **PANEL** control defines an area WINDOW or TOOLBAR (not valid in a REPORT) at the position and size specified by its AT attribute. Typically, the purpose of a PANEL is to frame the area with a custom BEVEL. This control cannot receive input focus and does not generate events.

### Example:

```
MDIChild WINDOW('Child One'), AT(0,0,320,200), MDI, MAX, HVSCROLL
    PANEL, AT(10,100,20,20), USE(?P1), BEVEL(-2,2)
END
```

### See Also:

BOX

GROUP

## PROMPT (declare a prompt control)



```
PROMPT(text) ,AT( ) [,CURSOR( )] [,USE( )] [,LAYOUT( )][,DISABLE] [,FONT( )] [,FULL] [,SCROLL] [,TRN]
    [,HIDE] [,DROPID( [,| LEFT | ] [,COLOR( )
    )]
    | RIGHT |
    | CENTER |
```

<b>PROMPT</b>	Places a prompt for the next active control following it, in the WINDOW or TOOLBAR.
<i>text</i>	A string constant containing the text to display (PROP:Text). This may contain an ampersand (&) to indicate the "hot" letter for the prompt.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used.
<b>USE</b>	A field equate label to reference the control in executable code (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>FONT</b>	Specifies the font used to display the text (PROP:FONT).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL).
<b>TRN</b>	Specifies the control transparently displays over the background (PROP:TRN).
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID).
<b>LEFT</b>	Specifies that the prompt is left justified (PROP:LEFT).

<b>RIGHT</b>	Specifies that the prompt is right justified (PROP:RIGHT).
<b>CENTER</b>	Specifies that the prompt is centered (PROP:CENTER).
<b>COLOR</b>	Specifies a background color for the control (PROP:COLOR).

The **PROMPT** control places a prompt for the next active control following the PROMPT in the WINDOW or TOOLBAR structure (not valid in a REPORT). The prompt *text* is placed at the position and size specified by its AT attribute.

The *text* may contain an ampersand (&) to indicate the letter immediately following the ampersand is the "hot" letter for the prompt. By default, the "hot" letter displays with an underscore below it to indicate its special purpose. This "hot" letter, when pressed in conjunction with the ALT key, changes input focus to the next control following the PROMPT in the WINDOW or TOOLBAR structure, which is capable of receiving focus.

Disabling or hiding the control directly following the PROMPT in the window structure does not automatically disable or hide the PROMPT; it must also be explicitly disabled or hidden, otherwise the PROMPT will then refer to the next currently active control following the disabled control. This allows you to place one PROMPT control on the window that will apply to any of multiple controls (if only one will be active at a time). If the next active control is a BUTTON, it is pressed when the user presses the PROMPT's "hot key."

To include an ampersand as part of the prompt *text*, place two ampersands together (&&) in the *text* string and only one will display.

This control cannot receive input focus.

**Events Generated:**

EVENT:Drop    A successful drag-and-drop to the control.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    PROMPT('Enter Data: '),AT(10,100,20,20),USE(?P1),CURSOR(CURSOR:Wait)
    ENTRY(@S8),AT(100,100,20,20),USE(E1)
    PROMPT('Enter More Data: '),AT(10,200,20,20),USE(?P2),CURSOR(CURSOR:Wait)
    ENTRY(@S8),AT(100,200,20,20),USE(E2)
    ENTRY(@D1),AT(100,200,20,20),USE(E3)
END

CODE
OPEN(MDIChild)
    IF SomeCondition
        HIDE(?E2)        !Prompt will refer to E3
    ELSE
        HIDE(?E3)        !Prompt will refer to E2
    END
```

**See Also:**

ENTRY  
TEXT

## PROGRESS (declare a progress control)



**PROGRESS**, AT ( ) [,CURSOR( )] [,USE( )] [,LAYOUT( )][,DISABLE] [,FULL] [,SCROLL] [,HIDE]  
 [,TRN] [,COLOR( )] [,DROPID( )] [,RANGE( )] [,SMOOTH( )]  
 [,VERTICAL( )]

---

<b>PROGRESS</b>	Places a control that displays the current progress of a batch process in the WINDOW or TOOLBAR.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used.
<b>USE</b>	The label of the variable containing the value of the current progress, or a field equate label to reference the control in executable code (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL).
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>TRN</b>	Specifies the control transparently displays over the background (PROP:TRN).
<b>COLOR</b>	Specifies a background color for the control (PROP:COLOR).
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID).
<b>RANGE</b>	Specifies the range of values the progress bar displays (PROP:RANGE). If omitted, the default range is zero (0) to one hundred (100).

- SMOOTH** Specifies a smooth incremental display of the progress control instead of the standard "block" format(PROP:Smooth).
- VERTICAL** Specifies to allow the progress control to operate from the bottom of the control to the top. If your progress control is positioned in a horizontal (left to right) display format, you should resize the progress control accordingly.

The **PROGRESS** control declares a control that displays a progress bar in a WINDOW or TOOLBAR (not valid in a REPORT). This usually displays the current percentage of completion of a batch process.

If a variable is named as the USE attribute, the progress bar is automatically updated whenever the value in that variable changes. If the USE attribute is a field equate label, you must directly update the display by assigning a value (within the range defined by the RANGE attribute) to the control's PROP:progress property (an undeclared property equate -- see *Undeclared Properties*).

This control cannot receive input focus.

**Events Generated:**

EVENT:Drop A successful drag-and-drop to the control.

**Example:**

```
BackgroundProcess PROCEDURE      !Background processing batch process

ProgressVariable LONG

Win WINDOW('Batch Processing...'),AT(, ,400,400),TIMER(1),MDI,CENTER
    PROGRESS,AT(100,100,200,20),USE(ProgressVariable),RANGE(0,200)
    PROGRESS,AT(100,140,200,20),USE(?ProgressBar),RANGE(0,200)
    BUTTON('Cancel'),AT(190,300,20,20),STD(STD:Close)
END

CODE
OPEN(Win)
OPEN(File)
?ProgressVariable{PROP:rangehigh} = RECORDS(File)
?ProgressBar{PROP:rangehigh} = RECORDS(File)
SET(File)                          !Set up a batch process
ACCEPT
CASE EVENT()
OF EVENT:CloseWindow
    BREAK
OF EVENT:Timer                      !Process records when timer allows it
    ProgressVariable += 3           !Auto-updates 1st progress bar
    LOOP 3 TIMES
    NEXT(File)
    IF ERRORCODE()
        BREAK
    END
    ?ProgressBar{PROP:progress} = ?ProgressBar{PROP:progress} + 1
                                !Manually update 2nd progress bar
    !Perform some batch processing code HERE
    END
END
END
CLOSE(File)
```



## RADIO (declare a radio button control)

```

RADIO(text) ,AT( ) [,CURSOR( )] [,USE( )] [,LAYOUT( )] [,DISABLE] [,KEY( )] [,MSG( )] [,HLP( )] [,SKIP]
    [,FONT( )] [,ICON( )] [,FULL] [,SCROLL] [,HIDE] [,ALRT( )] [DROPID( )] [VALUE( )]
    [,TIP( )] [,TRN] [,COLOR( )]      [, LEFT] [,EXTEND( )]
    [,FLAT]

    | RIGHT|

```

<b>RADIO</b>	Places a radio button on the WINDOW or TOOLBAR.
<i>text</i>	A string constant containing the text to display for the radio button (PROP:Text). This may contain an ampersand (&) to indicate the "hot" letter for the radio button.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used. Not valid in a REPORT.
<b>USE</b>	A field equate label to reference the control in executable code (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION opens (PROP:DISABLE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately selects the radio button (PROP:KEY). Not valid in a REPORT.
<b>MSG</b>	Specifies a string constant containing the text to display in the status bar when the control has focus (PROP:MSG). Not valid in a REPORT.
<b>HLP</b>	Specifies a string constant containing the help system identifier for the control (PROP:HLP). Not valid in a REPORT.
<b>SKIP</b>	Specifies the control does not receive input focus and may only be accessed with the mouse or accelerator key (PROP:SKIP). Not valid in a REPORT.
<b>FONT</b>	Specifies the display font for the control (PROP:FONT).
<b>ICON</b>	Specifies an image file or standard icon to display on the face of a "latching" button (PROP:ICON). Not valid in a REPORT.

<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL). Not valid in a REPORT.
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL). Not valid in a REPORT.
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>ALRT</b>	Specifies "hot" keys active for the control (PROP:ALRT). Not valid in a REPORT. If you need to alert the same key on every RADIO control then assign it to the parent OPTION control.
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID). Not valid in a REPORT.
<b>VALUE</b>	Specifies the value the OPTION structure's USE variable receives when the radio button is selected by the user (PROP:VALUE).
<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip). Not valid in a REPORT.
<b>TRN</b>	Specifies the control transparently displays over the background (PROP:TRN).
<b>COLOR</b>	Specifies a background color for the control (PROP:COLOR).
<b>FLAT</b>	Specifies the button appears flat except when the mouse cursor passes over the control (PROP:FLAT). Requires the ICON attribute. Not valid in a REPORT.
<b>LEFT</b>	Specifies the text appears to the left of the radio button (PROP:LEFT).
<b>RIGHT</b>	Specifies the text appears to the right of the radio button (PROP:RIGHT). This is the default position.
<b>EXTEND</b>	Specifies special document formatting information. This information contains a valid string of attributes that are assigned to a designated REPORT control for a given document type. Valid only in a REPORT.

The **RADIO** control places a radio button on the WINDOW, TOOLBAR, or REPORT at the position and size specified by its AT attribute. It is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. A RADIO control may only be placed within an OPTION control. When selected by the user, the RADIO *text* (with any accelerator key ampersand stripped out) is placed in the OPTION's USE variable, unless the VALUE attribute is used. On a REPORT, the RADIO selected by the user (the value in the OPTION's USE variable) is displayed as a filled RADIO button.

A RADIO with an ICON attribute appears as a "latched" pushbutton with the image on the button face. When the button appears "up" the RADIO is off; when it appears "down" the RADIO is on and the OPTION's USE variable receives the value in the selected RADIO's *text* parameter (unless the VALUE attribute is used).

There is an EVENT:Selected is generated for a RADIO control, but the OPTION structure containing it receives the EVENT:Accepted.

**Events Generated:**

EVENT:Selected      The control has received input focus.

EVENT:PreAlertKey    The user pressed an ALERT attribute hot key.

EVENT:AlertKey      The user pressed an ALERT attribute hot key.

EVENT:Drop          A successful drag-and-drop to the control.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
  OPTION('Option 1'),USE(OptVar1)
    RADIO('Radio 1'),AT(0,0,20,20),USE(?R1),KEY(F10Key)
    RADIO('Radio 2'),AT(20,0,20,20),USE(?R2),MSG('Radio 2')
  END
  OPTION('Option 2'),USE(OptVar2)
    RADIO('Radio 3'),AT(40,0,20,20),USE(?R3),FONT('Arial',12)
    RADIO('Radio 4'),AT(60,0,20,20),USE(?R4),CURSOR(CURSOR:Wait)
  END
  OPTION('Option 3'),USE(OptVar3)
    RADIO('Radio 5'),AT(80,0,20,20),USE(?R5),HLP('Radio5Help')
    RADIO('Radio 6'),AT(100,0,20,20),USE(?R6)
  END
  OPTION('Option 4'),USE(OptVar4)
    RADIO('Radio 7'),AT(120,0,20,20),USE(?R7),ICON('Radio1.ICO')
    RADIO('Radio 8'),AT(140,0,20,20),USE(?R8),ICON('Radio2.ICO')
  END
  OPTION('Option 5'),USE(OptVar5)
    RADIO('Radio 9'),AT(100,20,20,20),USE(?R9),LEFT
    RADIO('Radio 10'),AT(120,20,20,20),USE(?R10),LEFT
  END
  OPTION('Option 6'),USE(OptVar6),SCROLL
    RADIO('Radio 11'),AT(200,0,20,20),USE(?R11),SCROLL
    RADIO('Radio 12'),AT(220,0,20,20),USE(?R12),SCROLL
  END
END

CustRpt  REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail  DETAIL,AT(0,0,6500,1000)
  OPTION('Option'),USE(OptVar),AT(80,0,20,20),BOXED
    RADIO('Radio 1'),AT(80,0,20,20),USE(?R1)
    RADIO('Radio 2'),AT(100,0,20,20),USE(?R2)
    RADIO('Radio 3'),AT(100,0,20,20),USE(?R2),LEFT
  END
END
END
```

**See Also:**

OPTION

CHECK

BUTTON

## REGION (declare a window region control)



**REGION** ,AT( ) [,CURSOR( )] [,USE( )] [,LAYOUT( )] [,DISABLE] [,FILL] [,COLOR( )] [,IMM] [,FULL]  
[,SCROLL] [,HIDE] [,DRAGID( )] [,DROPID( )]  
[,BEVEL( )]

---

<b>REGION</b>	Defines an area in the WINDOW or TOOLBAR.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used.
<b>USE</b>	A field equate label to reference the control in executable code (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control is disabled when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>FILL</b>	Specifies the red, green, and blue component values that create the fill color for the control (PROP:FILL). If omitted, the region is not filled with color.
<b>COLOR</b>	Specifies the border color of the control (PROP:COLOR). If omitted, there is no border.
<b>IMM</b>	Specifies control generates an event whenever the mouse is moved in the region (PROP:IMM).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL).
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>DRAGID</b>	Specifies the control may serve as a drag host for drag-and-drop actions (PROP:DRAGID).
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID).
<b>BEVEL</b>	Specifies custom 3-D effect borders (PROP:BEVEL).

The **REGION** control defines an area on a WINDOW or TOOLBAR (not valid in a REPORT) at the position and size specified by its AT attribute. Generally, tracking the position of the mouse is the reason for defining a REGION. The MOUSEX and MOUSEY procedures can be used to determine the exact position of the mouse when the event occurs. Use of the IMM attribute causes some excess code and speed overhead at runtime, so it should be used only when necessary. This control cannot receive input focus.

A REGION with the DRAGID attribute can serve as a drag-and-drop host, providing information to be moved or copied to another control. A REGION with the DROPID attribute can serve as a drag-and-drop target, receiving information from another control. These attributes work together to specify drag-and-drop "signatures" that define a valid target for the operation. The DRAGID() and DROPID() procedures, along with the SETDROPID procedure, are used to perform the data exchange. Since a REGION can be defined over any other control, you can write drag-and-drop code between any two controls. Simply define REGION controls to handle the required drag-and-drop functionality.

**Events Generated:**

EVENT:Accepted	The mouse has been clicked by the user in the region.
EVENT:MouseIn	The mouse has entered the region (only with the IMM attribute).
EVENT:MouseOut	The mouse has left the region (only with the IMM attribute).
EVENT:MouseMove	The mouse has moved within the region (only with the IMM attribute).
EVENT:Dragging	The mouse cursor is over a potential drag target (only with the DRAGID attribute).
EVENT:Drag	The mouse cursor has been released over a drag target (only with the DRAGID attribute).
EVENT:Drop	The mouse cursor has been released over a drag target (only with the DROPID attribute).

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    REGION,AT(10,100,20,20),USE(?R1),BEVEL(-2,2)
    REGION,AT(100,100,20,20),USE(?R2),CURSOR(CURSOR:Wait)
    REGION,AT(10,200,20,20),USE(?R3),IMM
    REGION,AT(100,200,20,20),USE(?R4),COLOR(COLOR:ACTIVEBORDER)
    REGION,AT(10,300,20,20),USE(?R5),FILL(COLOR:ACTIVEBORDER)
END
```

**See Also:**

PANEL

## SHEET (declare a group of TAB controls)



```
SHEET ,AT( ) [,CURSOR( )][,USE( )] [,LAYOUT( )] [,DISABLE][,KEY( )][,FULL][,SCROLL][,HIDE][,FONT()][  
    [,DROPID()][,WIZARD][,SPREAD][,HSCROLL][,JOIN][,NOSHEET][,COLOR()][  
    [,UP ] [,DOWN ]    [,| LEFT (<width>)| ] [,IMM ]  
        | RIGHT (<width>)|  
        | ABOVE (<width>)|  
        | BELOW (<width>)|  
  
    tabs  
  
END
```

---

<b>SHEET</b>	Declares a group of TAB controls.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used.
<b>USE</b>	The label of a variable to receive the current TAB choice (PROP:USE). If this is a string variable, it receives the value of the TAB string (with any ampersands stripped out) selected by the user. If a numeric variable, it receives the number of the TAB selected by the user (the value returned by the CHOICE() procedure).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION opens (PROP:DISABLE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to the currently selected TAB in the SHEET control (PROP:KEY).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL).
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.

<b>FONT</b>	Specifies the display font for the control and the default for all the controls in the SHEET (PROP:FONT).
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID).
<b>WIZARD</b>	Specifies the SHEET's TAB controls do not appear (PROP:WIZARD). The user moves from TAB to TAB under program control.
<b>SPREAD</b>	Specifies the TABs are evenly spaced on one line (PROP:SPREAD).
<b>HSCROLL</b>	Specifies the TABs display all on one row instead of multiple rows, no matter how many TABs there are (PROP:HSCROLL). Right and left (or up and down) scroll buttons appear at either end of the TABs to scroll through the TABs.
<b>JOIN</b>	Specifies the TABs display all on one row instead of multiple rows, no matter how many TABs there are (PROP:JOIN). Right and left (or up and down) scroll buttons appear together at the right (or bottom) end of the TABs to scroll through the TABs.
<b>NOSHEET</b>	Specifies the TABs display without a visible sheet (PROP:NOSHEET).
<b>COLOR</b>	Specifies a background color for the control (PROP:COLOR).
<b>UP</b>	Specifies the TAB text is vertical reading upwards (PROP:UP).
<b>DOWN</b>	Specifies the TAB text is vertical reading downwards (PROP:DOWN).
<b>LEFT</b>	Specifies the TABs appear to the left of the sheet (PROP:LEFT).
<b>RIGHT</b>	Specifies the TABs appear to the right of the sheet (PROP:RIGHT).
<b>ABOVE</b>	Specifies the TABs appear above the sheet (PROP:ABOVE). This is the default position.
<b>BELOW</b>	Specifies the TABs appear below the sheet (PROP:BELOW).
<b>IMM</b>	Specifies EVENT:NewSelection generates whenever the user clicks on a TAB (PROP:IMM).
<i>tabs</i>	Multiple TAB control declarations.

The **SHEET** control declares a group of TAB controls that offer the user multiple "pages" of controls for the window (not valid in a REPORT). The TAB controls in the SHEET structure define the "pages" displayed.

Input focus changes between the SHEET's TAB controls are signalled only to the SHEET control affected. This means the events generated when the user changes input focus within a SHEET structure are field-specific events for the affected SHEET structure, not the individual TAB control.

A string variable as the SHEET structure's USE attribute receives the text of the TAB control selected by the user, and the CHOICE(*?Option*) procedure returns the number of the selected TAB control. If the SHEET structure's USE attribute is a numeric variable, it receives the number of the TAB control selected by the user (the same value returned by the CHOICE procedure).

You can use the SELECT statement to force navigation to a specific tab by specifying the TAB control's position number within the sheet as the second parameter:  
SELECT(?Sheet,TabNumber).

**Events Generated:**

- EVENT:TabChanging    Focus is about to pass to another tab.
- EVENT:NewSelection    Focus has passed to another tab, or the user clicked on a TAB in a non-WIZARD SHEET with the IMM attribute.
- EVENT:Drop            A successful drag-and-drop to the control.

If the SHEET control has a WIZARD attribute, EVENT:NewSelection is not posted on any tab changed by the setting of the PROP:ChoiceFeq property. This is by design, because tab changing behavior for wizard-like SHEETs is under full program control. The EVENT:NewSelection is a notification to the program that a new TAB (for SHEETs) is activated. If a SHEET has the WIZARD attribute, tabs can be changed only by the program (not as result of mouse clicks, hotkey pressing and other events handled by the RTL). Therefore, the program always knows when the active TAB has been changed.

If a SHEET control DOES NOT have a WIZARD attribute, the setting of PROP:ChoiceFeq will allow the posting of EVENT:NewSelection.

The LEFT/RIGHT/ABOVE/BELOW attributes of a SHEET control can have a *width* parameter, which specifies the width of the TAB.



**Example:**

```

MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    SHEET,AT(0,0,320,175),USE(SelectedTab)
    TAB('Tab One'),USE(?TabOne)
        OPTION('Option 1'),USE(OptVar1),KEY(F10Key),HLP('Option1Help')
        RADIO('Radio 1'),AT(20,0,20,20),USE(?R1)
        RADIO('Radio 2'),AT(40,0,20,20),USE(?R2)
    END
    OPTION('Option 2'),USE(OptVar2),MSG('Option 2')
        RADIO('Radio 3'),AT(60,0,20,20),USE(?R3)
        RADIO('Radio 4'),AT(80,0,20,20),USE(?R4)
    END
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P1)
    ENTRY(@S8),AT(100,140,32,20),USE(E1)
    PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P2)
    ENTRY(@S8),AT(100,240,32,20),USE(E2)
    END
    TAB('Tab Two'),USE(?TabTwo)
        OPTION('Option 3'),USE(OptVar3)
        RADIO('Radio 1'),AT(20,0,20,20),USE(?R5)
        RADIO('Radio 2'),AT(40,0,20,20),USE(?R6)
    END
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P3)
    ENTRY(@S8),AT(100,140,32,20),USE(E3)
    PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P4)
    ENTRY(@S8),AT(100,240,32,20),USE(E4)
    END
    END
    BUTTON('Ok'),AT(100,180,20,20),USE(?Ok)
    BUTTON('Cancel'),AT(200,180,20,20),USE(?Cancel)
    END

```

**See Also:**

TAB

## SPIN (declare a spinning list control)



**SPIN**(*picture*) ,**AT**( ) [, **CURSOR**()] [, **USE**()] [, **LAYOUT**( )] [, **DISABLE**] [, **KEY**()] [, **MSG**()] [, **HLP**()] [, **SKIP**] [, **FONT**()] [, **FULL**] [, **SCROLL**] [, **ALRT**()] [, **HIDE**] [, **READONLY**] [, **REQ**] [, **IMM**] [, **TIP**()] [, **FLAT**] [, **TRN**] [, **DROPID**()] [, **COLOR**()] [, **REPEAT**( )] [, **DELAY**( )] [, **MASK**] [, **UPR**] [, **LEFT**] [, **INS**] [, **RANGE**()] [, **STEP**] [, **HSCROLL**] [, **CAP**] [, **RIGHT**] [, **OVR**] [, **FROM**( )] [, **VSCROLL**] [, **CENTER**] [, **HVSCROLL**] [, **DECIMAL**]

---

<b>SPIN</b>	Places a "spinning" list of data items on the WINDOW or TOOLBAR.
<i>picture</i>	A display picture token that specifies the format for the data displayed in the control (PROP:Text).
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used.
<b>USE</b>	A field equate label to reference the control in executable code or the label of the variable that receives the value selected by the user (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION opens (PROP:DISABLE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to the control (PROP:KEY).
<b>MSG</b>	Specifies a string constant containing the text to display in the status bar when the control has focus (PROP:MSG).
<b>HLP</b>	Specifies a string constant containing the help system identifier for the control (PROP:HLP).
<b>SKIP</b>	Specifies the control receives input focus to enter text only with the mouse or accelerator key and does not retain focus (PROP:SKIP).

<b>FONT</b>	Specifies the display font for the control (PROP:FONT).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL).
<b>ALRT</b>	Specifies "hot" keys active for the control (PROP:ALRT).
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>READONLY</b>	Specifies the control does not allow data entry (PROP:READONLY).
<b>REQ</b>	Specifies the control may not be left blank or zero (PROP:REQ).
<b>IMM</b>	Specifies immediate event generation whenever the user presses any key (PROP:IMM).
<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip).
<b>FLAT</b>	Specifies that the control does not have a 3D border drawn around it (PROP:FLAT).
<b>TRN</b>	Specifies the control transparently displays over the background (PROP:TRN).
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID).
<b>COLOR</b>	Specifies background and selected colors for the control (PROP:COLOR).
<b>REPEAT</b>	Specifies the rate at which EVENT:NewSelection generates when the spin buttons are held down by the user (PROP:REPEAT).
<b>DELAY</b>	Specifies the delay between the first and second generation of EVENT:NewSelection when the spin buttons are held down by the user (PROP:DELAY).
<b>MASK</b>	Specifies pattern input editing mode of the ENTRY portion of the control (PROP:MASK).
<b>UPR / CAP</b>	Specifies all upper case or proper name capitalization (First Letter Of Each Word Capitalized) entry (PROP:UPR and PROP:CAP).
<b>LEFT</b>	Specifies that the data is left justified within the area specified by the AT attribute (PROP:LEFT).
<b>RIGHT</b>	Specifies that the data is right justified within the area specified by the AT attribute (PROP:RIGHT).
<b>CENTER</b>	Specifies that the data is centered within the area specified by the AT attribute (PROP:CENTER).

<b>DECIMAL</b>	Specifies that the data is aligned on the decimal point within the area specified by the AT attribute (PROP:DECIMAL).
<b>INS / OVR</b>	Specifies Insert or Overwrite entry mode (PROP:INS and PROP:OVR). Valid only on windows with the MASK attribute.
<b>RANGE</b>	Specifies the range of values the user may choose (PROP:RANGE).
<b>STEP</b>	Specifies the increment/decrement amount of the choices within the specified RANGE (PROP:STEP). If omitted, the STEP is 1.0.
<b>FROM</b>	Specifies the origin of the choices displayed for the user (PROP:FROM).
<b>HSCROLL</b>	Specifies the spin buttons are side by side, pointing right and left (PROP:HSCROLL).
<b>VSCROLL</b>	Specifies the spin buttons are one above the other, pointing right and left (PROP:VSCROLL).
<b>HVSCROLL</b>	Specifies the spin buttons are side by side, pointing up and down.

The **SPIN** control places a "spinning" list of data items on the WINDOW or TOOLBAR (not valid in a REPORT) at the position and size specified by its AT attribute. The "spinning" list displays only the current selection with a pair of buttons to the right to allow the user to "spin" through the available selections (similar to a slot machine wheel).

If the SPIN control offers the user regularly spaced numeric choices, the RANGE attribute specifies the valid range of values from which the user may choose. The STEP attribute then works in conjunction with RANGE to increment/decrement those values by the specified amount. If the choices are not regular, or are string values, the FROM attribute is used instead of RANGE and STEP. The FROM attribute provides the SPIN control its list of choices from a memory QUEUE or a string. Using the FROM attribute, you may provide the user any type of choices in the SPIN control. The user may select an item from the list or type in the desired value, so this control also acts as an ENTRY control.

**Events Generated:**

EVENT:Selected	The control has received input focus.
EVENT:Accepted	The user has either selected a value or entered data directly into the control, and moved on to another control.
EVENT:Rejected	The user has entered an invalid value for the entry picture.
EVENT:NewSelection	The user has changed the displayed value.
EVENT:PreAlertKey	The user pressed an ALRT attribute hot key.
EVENT:AlertKey	The user pressed an ALRT attribute hot key.
EVENT:Drop	A successful drag-and-drop to the control.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    SPIN(@S8),AT(0,0,20,20),USE(SpinVar1),FROM(Que)
    SPIN(@N3),AT(20,0,20,20),USE(SpinVar2),RANGE(1,999),KEY(F10Key)
    SPIN(@N3),AT(40,0,20,20),USE(SpinVar3),RANGE(5,995),STEP(5)
    SPIN(@S8),AT(60,0,20,20),USE(SpinVar4),FROM(Que),HLP('Check4Help')
    SPIN(@S8),AT(80,0,20,20),USE(SpinVar5),FROM(Que),MSG('Button 3')
    SPIN(@S8),AT(100,0,20,20),USE(SpinVar6),FROM(Que),FONT('Arial',12)
    SPIN(@S8),AT(120,0,20,20),USE(SpinVar7),FROM(Que),DROP
    SPIN(@S8),AT(160,0,20,20),USE(SpinVar8),FROM(Que),IMM
    SPIN(@S8),AT(220,0,20,20),USE(SpinVar9),FROM('Mr|Mrs|Ms'),LEFT
END
```

## STRING (declare a string control)

**STRING**(*text*) ,AT( ) [,USE( )] [,LAYOUT( )] [,DISABLE] [,FONT( )] [,FULL] [,SCROLL] [,HIDE]

[,TRN] [,DROPID( )] [,COLOR( )] [,ANGLE( )] [,SKIP]

[,| LEFT| ] [,| PAGENO | ] [,EXTEND( )]

| RIGHT| | CNT( )[, RESET( ) / PAGE ] [, TALLY( ) ]|

| CENTER| | SUM( )[, RESET( ) / PAGE ] [, TALLY( ) ]|

| DECIMAL| | AVE( )[, RESET( ) / PAGE ] [, TALLY( ) ]|

| MIN( )[, RESET( ) / PAGE ] [, TALLY( ) ]|

| MAX( )[, RESET( ) / PAGE ] [, TALLY( ) ]|

---

<b>STRING</b>	Places the <i>text</i> on the WINDOW, TOOLBAR, or REPORT.
<i>text</i>	A string constant containing the text to display, or a display picture token to format the variable specified in the USE attribute (PROP:Text).
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>USE</b>	A field equate label to reference the control in executable code, or a variable whose contents are displayed in the format of the picture token declared instead of string text (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION opens (PROP:DISABLE).
<b>FONT</b>	Specifies the font used to display the text (PROP:FONT).
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW or REPORT band for any missing AT attribute width or height parameter (PROP:FULL).
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL). Not valid in a REPORT.

<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>TRN</b>	Specifies the text or USE variable characters transparently display over the background (PROP:TRN).
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID). Not valid in a REPORT.
<b>SKIP</b>	Specifies not to print the control if the content is blank, and to move all following controls in the band upward to "fill in" the blank (PROP:SKIP). Valid only in a REPORT.
<b>LEFT</b>	Specifies that the text is left justified within the area specified by the AT attribute (PROP:LEFT).
<b>RIGHT</b>	Specifies that the text is right justified within the area specified by the AT attribute (PROP:RIGHT).
<b>CENTER</b>	Specifies that the text is centered within the area specified by the AT attribute (PROP:CENTER).
<b>DECIMAL</b>	Specifies that the text is aligned on the decimal point within the area specified by the AT attribute (PROP:DECIMAL).
<b>COLOR</b>	Specifies a background color for the control (PROP:COLOR).
<b>ANGLE</b>	Specifies displaying or printing the control at a specified angle measured counter-clockwise from the horizontal or the report's orientation (PROP:ANGLE).
<b>PAGENO</b>	Specifies the current page number is printed in the format of the picture token declared instead of string text (PROP:PAGENO). Valid only in a REPORT.
<b>CNT</b>	Specifies the number of details printed is printed in the format of the picture token declared instead of string text (PROP:CNT). Valid only in a REPORT.
<b>SUM</b>	Specifies the sum of the USE variable is printed in the format of the picture token declared instead of string text (PROP:SUM). Valid only in a REPORT.
<b>AVE</b>	Specifies the average value of the USE variable is printed in the format of the picture token declared instead of string text (PROP:AVE). Valid only in a REPORT.
<b>MIN</b>	Specifies the minimum value of the USE variable is printed in the format of the picture token declared instead of string text (PROP:MIN). Valid only in a REPORT.

<b>MAX</b>	Specifies the maximum value of the USE variable is printed in the format of the picture token declared instead of string text (PROP:MAX). Valid only in a REPORT.
<b>RESET</b>	Specifies the CNT, SUM, AVE, MIN, or MAX is reset when the specified group break occurs (PROP:RESET). Valid only in a REPORT.
<b>PAGE</b>	Specifies the CNT, SUM, AVE, MIN, or MAX is reset to zero when the page break occurs (PROP:PAGE). Valid only in a REPORT.
<b>TALLY</b>	Specifies when to calculate the CNT, SUM, AVE, MIN, or MAX (PROP:TALLY). Valid only in a REPORT.
<b>EXTEND</b>	Specifies special document formatting information. This information contains a valid string of attributes that are assigned to a designated REPORT control for a given document type. Valid only in a REPORT.

The **STRING** control places the *text* on the WINDOW, TOOLBAR, or REPORT at the position and size specified by its AT attribute. It is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

If the *text* parameter is a picture token instead of a string constant, the contents of the variable named in the USE attribute are formatted to that display picture, at the position and size specified by the AT attribute. This makes the STRING with a USE variable a "display-only" control for the variable. The data displayed in the STRING is automatically refreshed every time through the ACCEPT loop, whether the AUTO attribute is present or not.

There is a difference between ampersand (&) use in STRING and PROMPT controls. An ampersand in a STRING displays as part of the *text*, while an ampersand in a PROMPT defines the prompt's "hot" letter.

A STRING with the TRN attribute displays or prints characters transparently, without obliterating the background. This means only the pixels required to create each character are written to screen. This allows the STRING to be placed directly on top of an IMAGE without destroying the background picture.

This control cannot receive input focus.

**Events Generated:**

EVENT:Drop    A successful drag-and-drop to the control.



**Example:**

```

MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    STRING('String Constant'),AT(10,0,20,20),USE(?S1)
    STRING(@S30),AT(10,20,20,20),USE(StringVar1)
    STRING(@S30),AT(10,20,20,20),USE(StringVar2),CURSOR(CURSOR:Wait)
    STRING(@S30),AT(10,20,20,20),USE(StringVar3),FONT('Arial',12)
END

CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
Break1  BREAK(Pre:Key1)
        HEADER,AT(0,0,6500,1000)
        STRING('Group Head'),AT(3000,500,1500,500),FONT('Arial',18)
        END
Detail  DETAIL,AT(0,0,6500,1000)
        STRING(@N$11.2),AT(6000,1500,500,500),USE(Pre:F1)
        END
        FOOTER,AT(0,0,6500,1000)
        STRING('Group Total: '),AT(5500,500,1500,500)
        STRING(@N$11.2),AT(6000,500,500,500),USE(Pre:F1),SUM,RESET(Pre:Key1)
        END
        END
END
END

```

## TAB (declare a page of a SHEET control)



TAB( *text* )[,USE()] [,DISABLE] [,LAYOUT( )] [,KEY()] [,MSG()] [,HLP()] [,REQ] [DROPID()]  
[,TIP()]

                  [,COLOR()] [,FONT()][,HIDE]

*controls*

END

---

<b>TAB</b>	Declares a group of controls that constitute one of the multiple "pages" of controls contained within a SHEET structure.
<i>text</i>	A string constant containing the text to display on the TAB (PROP:Text).
<b>USE</b>	Specifies a field equate label to reference the control in executable code (PROP:USE).
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION is first opened (PROP:DISABLE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display orientation (PROP:LAYOUT)
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to the control (PROP:KEY).
<b>MSG</b>	Specifies a string constant containing the default text to display in the status bar when any control in the TAB has focus (PROP:MSG).
<b>HLP</b>	Specifies a string constant containing the default help system identifier for any control in the TAB (PROP:HLP).
<b>REQ</b>	Specifies that when another TAB is selected, the runtime library automatically checks all ENTRY controls in the same TAB structure with the REQ attribute to ensure they contain data other than blanks or zeroes (PROP:REQ).
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID).
<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip).
<b>COLOR</b>	Specifies a background color for the control and the default for all controls on the TAB (PROP:COLOR).

<b>FONT</b>	Specifies the font used to display the text on the tab (PROP:FONT). This does not affect the <i>controls</i> placed in the TAB.
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<i>controls</i>	Multiple control declarations.

The **TAB** structure declares a group of controls that constitute one of the multiple "pages" of controls contained within a SHEET structure (not valid in a REPORT). The multiple TAB controls in the SHEET structure define the "pages" displayed to the user. The SHEET structure's USE attribute receives the *text* of the TAB control selected by the user.

Input focus changes between the SHEET's TAB controls are signalled only to the SHEET control affected. This means the events generated when the user changes input focus within a SHEET structure are field-specific events for the SHEET control, and the individual TAB controls do not generate events.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
SHEET,AT(0,0,320,175),USE(SelectedTab)
TAB('Tab One'),USE(?TabOne)
  OPTION('Option 1'),USE(OptVar1),KEY(F10Key),HLP('Option1Help')
  RADIO('Radio 1'),AT(20,0,20,20),USE(?R1)
  RADIO('Radio 2'),AT(40,0,20,20),USE(?R2)
END
  OPTION('Option 2'),USE(OptVar2),MSG('Option 2')
  RADIO('Radio 3'),AT(60,0,20,20),USE(?R3)
  RADIO('Radio 4'),AT(80,0,20,20),USE(?R4)
END
  PROMPT('Enter Data:'),AT(100,100,20,20),USE(?P1)
  ENTRY(@S8),AT(100,140,32,20),USE(E1)
  PROMPT('Enter More Data:'),AT(100,200,20,20),USE(?P2)
  ENTRY(@S8),AT(100,240,32,20),USE(E2)
END
TAB('Tab Two'),USE(?TabTwo)
  OPTION('Option 3'),USE(OptVar3)
  RADIO('Radio 1'),AT(20,0,20,20),USE(?R5)
  RADIO('Radio 2'),AT(40,0,20,20),USE(?R6)
END
  OPTION('Option 4'),USE(OptVar4)
  RADIO('Radio 3'),AT(60,0,20,20),USE(?R7)
  RADIO('Radio 4'),AT(80,0,20,20),USE(?R8)
END
  PROMPT('Enter Data:'),AT(100,100,20,20),USE(?P3)
  ENTRY(@S8),AT(100,140,32,20),USE(E3)
  PROMPT('Enter More Data:'),AT(100,200,20,20),USE(?P4)
  ENTRY(@S8),AT(100,240,32,20),USE(E4)
END
END
  BUTTON('Ok'),AT(100,180,20,20),USE(?Ok)
  BUTTON('Cancel'),AT(200,180,20,20),USE(?Cancel)
END
```

**See Also:**

SHEET

## TEXT (declare a multi-line text control)

```
TEXT ,AT( )[,CURSOR( )] [,USE( )] [,LAYOUT( )] [,DISABLE] [,KEY( )] [,MSG( )] [,HLP( )] [,BOXED] [,SKIP] [,FONT( )]
    [,REQ] [,FULL] [,SCROLL] [,ALRT( )] [,HIDE] [,READONLY] [,FLAT] [,DROPID( )] [,UPR] [,TRN]
    [,TIP( )]    [,| HSCROLL |] [,| LEFT|]    [,COLOR( )] [,SINGLE] [,RESIZE] [,EXTEND( )]
                [, VSCROLL |]    [, RIGHT|]
                [, HVSCROLL |] [, CENTER|]
                |
```

---

<b>TEXT</b>	Places a multi-line data entry field on the WINDOW, TOOLBAR, or REPORT.
<b>AT</b>	Specifies the initial size and location of the control (PROP:AT). If omitted, default values are selected by the runtime library.
<b>CURSOR</b>	Specifies a mouse cursor to display when the mouse is positioned over the control (PROP:CURSOR). If omitted, the WINDOW's CURSOR attribute is used, else the Windows default cursor is used. Not valid in a REPORT.
<b>USE</b>	The label of the variable that receives the value entered into the control by the user (PROP:USE).
<b>LAYOUT</b>	Specifies the control's left-to-right or right-to-left display and entry orientation (PROP:LAYOUT)
<b>DISABLE</b>	Specifies the control appears dimmed when the WINDOW or APPLICATION opens (PROP:DISABLE).
<b>KEY</b>	Specifies an integer constant or keycode equate that immediately gives focus to the control (PROP:KEY). Not valid in a REPORT.
<b>MSG</b>	Specifies a string constant containing the text to display in the status bar when the control has focus (PROP:MSG). Not valid in a REPORT.
<b>HLP</b>	Specifies a string constant containing the help system identifier for the control (PROP:HLP). Not valid in a REPORT.
<b>BOXED</b>	Specifies a single-track border around a TEXT control, with the text at the top of the border (PROP:BOXED). This attribute only works if the TEXT control is transparent or the parent window does not have the GRAY attribute applied.
<b>SKIP</b>	Specifies the control receives input focus to enter text only with the mouse or accelerator key and does not retain focus (PROP:SKIP). In a REPORT, SKIP specifies not to print the control if the content is blank, and to move all following controls in the band upward to "fill in" the blank.
<b>FONT</b>	Specifies the display font for the control (PROP:FONT).

<b>REQ</b>	Specifies the control may not be left blank or zero (PROP:REQ). Not valid in a REPORT.
<b>FULL</b>	Specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter (PROP:FULL). Not valid in a REPORT.
<b>SCROLL</b>	Specifies the control scrolls with the window (PROP:SCROLL). Not valid in a REPORT.
<b>ALRT</b>	Specifies "hot" keys active for the control (PROP:ALRT). Not valid in a REPORT.
<b>HIDE</b>	Specifies the control does not appear when the WINDOW or APPLICATION is first opened (PROP:HIDE). UNHIDE must be used to display it.
<b>READONLY</b>	Specifies the control does not allow data entry (PROP:READONLY). Not valid in a REPORT.
<b>FLAT</b>	Specifies that the control does not have a 3D border drawn around it (PROP:FLAT).
<b>DROPID</b>	Specifies the control may serve as a drop target for drag-and-drop actions (PROP:DROPID). Not valid in a REPORT.
<b>UPR</b>	Specifies all upper case entry (PROP:UPR).
<b>TIP</b>	Specifies the text that displays as "balloon help" when the mouse cursor pauses over the control (PROP:ToolTip). Not valid in a REPORT.
<b>HSCROLL</b>	Specifies that a horizontal scroll bar is automatically added to the text field when any portion of the data lies horizontally outside the visible area (PROP:HSCROLL). Not valid in a REPORT.
<b>VSCROLL</b>	Specifies that a vertical scroll bar is automatically added to the text field when any of the data lies vertically outside the visible area (PROP:VSCROLL).
<div style="background-color: #00FFFF; padding: 2px; display: inline-block;"><b>Tip</b></div> <p>Use this when the USE variable size is larger than the TEXT field size.</p>	
<b>HVSCROLL</b>	Specifies that both vertical and horizontal scroll bars are automatically added to the text field when any portion of the data lies outside the visible area. Not valid in a REPORT.
<b>LEFT</b>	Specifies that the text is left justified within the area specified by the AT attribute (PROP:LEFT).
<b>RIGHT</b>	Specifies that the text is right justified within the area specified by the AT attribute (PROP:RIGHT).
<b>CENTER</b>	Specifies that the text is centered within the area specified by the AT attribute (PROP:CENTER).
<b>COLOR</b>	Specifies a background color for the control (PROP:COLOR).
<b>SINGLE</b>	Specifies the control is only for single line data entry (PROP:SINGLE). This is specifically to allow use of TEXT controls instead of ENTRY for Hebrew or Arabic data entry. Not valid in a REPORT.
<b>RESIZE</b>	Specifies adjusting the print height for the control according to the actual content (PROP:RESIZE). Valid only in a REPORT.

<b>TRN</b>	Specifies the text or USE variable characters transparently display over the background (PROP:TRN).
<b>RTF</b>	Specifies that the contents of the text field supports Rich Text Format.
<b>EXTEND</b>	Specifies special document formatting information. This information contains a valid string of attributes that are assigned to a designated REPORT control for a given document type. Valid only in a REPORT. (See EXTEND)

The **TEXT** control places a multi-line data entry field on the WINDOW (or TOOLBAR) at the position and size specified by its AT attribute. It is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. The variable specified in the USE attribute receives the data entered when the user has completed data entry and moves on to another control. The entered data automatically "word-wraps" to fit in the text box.

The capacity of a TEXT control varies depending on the operating system.

TEXT controls populated in the Report Formatter always show a "flat" or two-dimensional border. In the Window Formatter, these controls will show a three-dimensional border if the window has a GRAY attribute, and the transparent (TRN) and flat (FLAT) attributes for the control are not enabled. The BOXED attribute must be active for any border to be drawn.

**Events Generated:**

EVENT:Selected	The control has received input focus.
EVENT:Accepted	The user has completed data entry in the control.
EVENT:PreAlertKey	The user pressed an ALERT attribute hot key.
EVENT:AlertKey	The user pressed an ALERT attribute hot key.
EVENT:Drop	A successful drag-and-drop to the control.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    TEXT,AT(0,0,40,40),USE(E1),ALRT(F10Key),CENTER
    TEXT,AT(20,0,40,40),USE(E2),KEY(F10Key),HLP('Text4Help')
    TEXT,AT(40,0,40,40),USE(E3),SCROLL,OVR,UPR
    TEXT,AT(60,0,40,40),USE(E4),CURSOR(CURSOR:Wait),RIGHT
    TEXT,AT(80,0,40,40),USE(E5),DISABLE,FONT('Arial',12)
    TEXT,AT(100,0,40,40),USE(E6),HVSCROLL,LEFT
    TEXT,AT(120,0,40,40),USE(E7),REQ,INS,CAP,MSG('Text Field 7')
END
```

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
Detail  DETAIL,AT(0,0,6500,1000)
    TEXT,AT(0,0,40,40),USE(E1)
    TEXT,AT(100,0,40,40),USE(E6),FONT('Arial',12)
    TEXT,AT(120,0,40,40),USE(E7),CAP
    TEXT,AT(140,0,40,40),USE(E8),UPR
    TEXT,AT(160,0,40,40),USE(E9),LEFT
    TEXT,AT(180,0,40,40),USE(E10),RIGHT
    TEXT,AT(200,0,40,40),USE(E11),CENTER
    END
END
```

## 9 - Window and Report Attributes

### Attribute Property Equates

Each attribute has a corresponding runtime property listed in its description (PROP:*attribute*). These attributes are valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. Equates for all runtime properties are contained in the PROPERTY.CLW file. This file also contains equates for the standard values used by some of these properties. Some properties are "read-only" and their value may not be changed, and others are "write-only" properties whose value cannot be determined. These restrictions are noted as applicable.

#### Attribute Property Parameters

Many attributes take no parameter—they are either present or absent. Therefore, their corresponding runtime properties simply toggle the attribute on or off. Assigning an empty string ("") or zero (0) turns them off. Assigning '1' or 1 turns them on. Typically, the standard equates for TRUE and FALSE are used for this purpose. Querying any of these properties returns a blank string when the attribute is not active for the window, report, or control. Examples of these types of attribute properties are: PROP:ABOVE, PROP:ABSOLUTE, and PROP:ALONE.

##### Example:

```
?MyControl{PROP:DISABLE} = TRUE           !disables the referenced control
```

Many attributes take a single parameter whose presence specifies both the presence of the attribute and its value. Assigning an empty string ("") or zero (0) turns them off. Assigning any other valid value turns them on. Examples of these types of attribute properties are PROP:TIMER and PROP:DROP.

##### Example:

```
MyWindow{PROP:TIMER} = 100                !set the window's timer to 1 second
```

#### Arrayed Properties

A number of attribute properties are actually arrays which either contain multiple values (such as PROP:ALERT, which may contain up to 255 separately alerted keycodes) or which may be referenced as arrays to directly address their multiple parameters instead of using separately declared equates for each of the individual parameters (like PROP:AT, whose parameters may be addressed either as {PROP:AT,n} or as the separately declared equates for each of the individual parameters: PROP:Xpos, PROP:Ypos, PROP:Width, and PROP:Height).

**Example:**

```
CheckField STRING(1)
```

```
Screen WINDOW
```

```
    ENTRY(@N3),USE(Ctl:Code)
    ENTRY(@S30),USE(Ctl:Name),REQ
    CHECK('True or False'),USE(CheckField)
    IMAGE('SomePic.BMP'),USE(?Image)
    BUTTON('OK'),USE(?OkButton),KEY(EnterKey)
    BUTTON('Cancel'),USE(?CanxButton),KEY(EscKey)
END
```

```
CODE
```

```
OPEN(Screen)
```

```
Screen{PROP:AT,1} = 0           !Position window to top left corner
Screen{PROP:AT,2} = 0
Screen{PROP:GRAY} = 1          !Give window 3D look
Screen{PROP:STATUS,1} = -1      !Create status bar with two sections
Screen{PROP:STATUS,2} = 180
Screen{PROP:STATUS,3} = 0       !Terminate status bar array
Screen{PROP:StatusText,2} = FORMAT(TODAY(),@D2) !Put date in status bar section 2:
?CtlCode{PROP:ALRT,1} = F10Key  !Alert F10 on Ctl:Code entry control
?CtlCode{PROP:Text} = '@N4'     !Change entry picture token
?Image{PROP:Text} = 'MyPic.BMP' !Change image control filename
?OkButton{PROP:DEFAULT} = '1'   !Put DEFAULT attribute on OK button

?MyButton{PROP:ICON} = 'C:\Windows\MORICONS.DLL[10]'
!Display 11th icon in MORICONS.DLL (zero-based)

?MyButton{PROP:ICON} = 'C:\Windows\MORICONS.DLL[0]'
!Display first icon in MORICONS.DLL (zero-based)

?CheckField{PROP:TrueValue} = 'T'           !Checked/unchecked values for CHECK control
?CheckField{PROP:FalseValue} = 'F'
ACCEPT
END
```



## PROP:Text with Windows and Controls

PROP:Text is the *text* parameter of an APPLICATION(*text*), WINDOW(*text*), or any *control*(*text*). This property represents the parameter to any control or window declaration, and could contain any value that is valid as the parameter to the specific control's declaration.

There is also a usage of PROP:Text that applies to Memos and Blobs.

**Example:**

```
?Image{PROP:Text} = 'My.BMP'           !a new bitmap for the referenced IMAGE control
?Prompt{PROP:Text} = 'New Prompt text' !new text in the referenced PROMPT control
?Entry{PROP:Text} = '@N03'             !new picture for the referenced ENTRY control
```

**See Also:** Attribute Property Equates

## ABSOLUTE (set fixed-position printing)

### ABSOLUTE

---

The **ABSOLUTE** attribute (PROP:ABSOLUTE) ensures that the DETAIL, or group HEADER or FOOTER structure (contained within a BREAK structure), always prints at a fixed position on the page. When ABSOLUTE is present, the position specified by the x and y parameters of the structure's AT attribute is relative to the top left corner of the page. ABSOLUTE has no effect on following structures printed without the ABSOLUTE attribute.

#### Example:

```
CustRpt REPORT,AT(1000,2000,6500,9000),THOUS
      HEADER
      !structure elements
      END
CDetail1 DETAIL,AT(0,0,6500,1000)
      !structure elements
      END
CDetail2 DETAIL,AT(1000,1000,6500,1000),ABSOLUTE !fixed position detail
      !structure elements
      END
END
```

## ALONE (set to print without page header, footer, or form)

### ALONE

---

The **ALONE** attribute (PROP:ALONE) specifies that the DETAIL, or group HEADER or FOOTER structure (contained within a BREAK structure), is to print on the page without any FORM, or page HEADER or FOOTER (not within a BREAK structure). The normal use is for report title and grand total pages.

#### Example:

```
CustRpt    REPORT
TitlePage  DETAIL,ALONE      !Title page detail structure
           !structure elements
           END
CustDetail DETAIL
           !structure elements
           END
           FOOTER
           !structure elements
           END
           END
```

## ALRT (set window "hot" keys)



**ALRT**(*keycode*)

---

**ALRT** Specifies a "hot" key active while the APPLICATION, WINDOW, or control on which it is placed has focus.

*keycode* A numeric constant keycode or keycode EQUATE.

The **ALRT** attribute (PROP:ALRT) specifies a "hot" key active while the APPLICATION, WINDOW, or control on which it is placed has focus.

When the user presses an ALRT "hot" key, two events (field-independent if the ALRT is on an APPLICATION or WINDOW, field-specific if the ALRT is on a control), EVENT:PreAlertKey and EVENT:AlertKey, are generated (in that order). If the code does not execute a CYCLE statement when processing EVENT:PreAlertKey, you "shortstop" the library's default action on the alerted keypress. If the code does execute a CYCLE statement when processing EVENT:PreAlertKey, the library performs its default action for the alerted keypress. In either case, EVENT:AlertKey is generated following EVENT:PreAlertKey. When EVENT:AlertKey is generated, the USE variable of the control with input focus is not automatically updated (use UPDATE if this is required).

You may have multiple ALRT attributes on one APPLICATION, WINDOW, or control (up to 255). The ALERT statement and the ALRT attribute of a window or control are completely separate. This means that clearing ALERT keys has no effect on any keys alerted by ALRT attributes.

PROP:ALRT is an array, containing up to 255 keycodes. The array element number actually used is internally assigned to the first free array element if the specified element number is larger than the current number of assigned keycodes. For example, assuming there are no keys alerted at all, if you specify assigning to element number 255, it is actually assigned to element number 1. Subsequently assigning another keycode to element number 255 (still free), it is actually assigned to element number 2. Explicitly assigning a keycode to element number 1, however, overwrites any other keycode already assigned to element number 1. In fact this happens to *any* element that has a keycode and if an additional alert assignment is made to an element that is already assigned.

**Example:**

```

WinOne WINDOW,AT(0,0,160,400)
    ENTRY,AT(6,40),USE(SomeVar1),ALRT(MouseLeft) !Mouse click alerted for control
    ENTRY,AT(60,40),USE(SomeVar2),ALRT(F10Key)    !F10 alerted for control
END

CODE
OPEN(WinOne)
ACCEPT
CASE FIELD()
OF ?SomeVar1
CASE EVENT()
OF EVENT:PreAlertKey !Pre-check alert events
CYCLE                !Allow standard MouseLeft action to process
OF EVENT:AlertKey    !Alert processing
DO ClickRoutine
END
OF ?SomeVar2
CASE EVENT()
OF EVENT:AlertKey    !Alert processing
DO F10Routine
END
END
END
END
!*****example showing how to clear an alerted key
LOOP I# = 1 TO 255
    IF Window{Prop:ALRT,I#} = AltA    !clear the AltA keycode
        Window{Prop:ALRT,I#} = 0
        BREAK
    END
END
END

```

**See Also:**    **ALERT**

## ANGLE (set control display or print angle)



**ANGLE**( *size* )

---

**ANGLE** Defines the orientation of a STRING control.

*size* An integer constant or constant expression that specifies the amount of rotation, in tenths of degrees. If positive, the angle is measured counter-clockwise from the report's horizontal orientation. Valid values are between 3600 and -3600.

The **ANGLE** attribute (PROP:ANGLE) specifies displaying or printing the STRING control at a specified angle measured counter-clockwise from the horizontal of the window or horizontal orientation of the report (either Portrait or Landscape). This allows you to display or print text at any angle in addition to the standard horizontal. The FONT for the STRING control must be a TrueType font.

**Example:**

```
WinOne WINDOW,AT(0,0,160,400),FONT('Arial')
    !Display Horizontal text
    STRING('String Constant'),AT(6,40),USE(?String1)
    !Display Vertical text
    STRING('String Constant'),AT(6,40),USE(?String2),ANGLE(900)
    !Display upside-down text
    STRING('String Constant'),AT(6,40),USE(?String3),ANGLE(1800)
END

CustRpt REPORT,AT(1000,1000,6500,9000),THOUS,FONT('Arial',10)
Detail  DETAIL,AT(0,0,6500,1000)
    !Print Horizontal text
    STRING('String Constant'),AT(500,500,1500,500)
    !Print Vertical text
    STRING('String Constant'),AT(500,500,1500,500),ANGLE(900)
    !Print upside-down text
    STRING('String Constant'),AT(500,500,1500,500),ANGLE(1800)
END
END
```

## AT (set position and size)

**AT**([*x*] [,*y*] [,*width*] [,*height*])

---

<b>AT</b>	Defines the position and size of the structure or control on which it is placed.
<i>x</i>	An integer constant or constant expression that specifies the horizontal position of the top left corner (PROP:Xpos, equivalent to {PROP:At,1}). If omitted, the runtime library provides a default value.
<i>y</i>	An integer constant or constant expression that specifies the vertical position of the top left corner (PROP:Ypos, equivalent to {PROP:At,2}). If omitted, the runtime library provides a default value.
<i>width</i>	An integer constant or constant expression that specifies the width (PROP:Width, equivalent to {PROP:At,3}). If omitted, the runtime library provides a default value.
<i>height</i>	An integer constant or constant expression that specifies the height (PROP:Height, equivalent to {PROP:At,4}). If omitted, the runtime library provides a default value.

The **AT** attribute (PROP:AT) is used for positioning Windows and Controls (Win32), and for report structures in both Clarion Win32 and Clarion#. The **AT** attribute defines the position and size of the structure or control on which it is placed. The *x,y* position is relative and dependent upon the statement on which the AT attribute is placed.

The values contained in the *x*, *y*, *width*, and *height* parameters are measured in dialog units for an APPLICATION or WINDOW. The *x*, *y*, *width*, and *height* parameters on a REPORT without the THOUS, MM, or POINTS attribute are also measured in dialog units.

Dialog units are defined as one-quarter the average character width by one-eighth the average character height. The actual size of a dialog unit is dependent upon the size of the default font for the window or report. This measurement is based on the font specified in the FONT attribute of the window or report, or the system default font specified by Windows (if there is no FONT attribute on the window or report).

### Window Usage

---

The *x* and *y* parameters are relative to the top left corner of the video screen when the AT attribute is on an APPLICATION structure, or a WINDOW without the MDI attribute that is opened before an APPLICATION structure is opened by the program.

The *x* and *y* parameters are relative to the top left corner of the APPLICATION's client area when the AT attribute is placed on a WINDOW with the MDI attribute, or a WINDOW without the MDI attribute opened after an APPLICATION structure has been opened.

The *width* and *height* parameters specify the size of the "client area" or "workspace" of an APPLICATION. This is the area below the MENUBAR and above the status bar which defines the area in which the TOOLBAR is placed and MDI "child" windows are opened. On a WINDOW, they specify the size of the "workspace" which may contain control fields.

### Window Control Usage

---

The *x* and *y* parameters are relative to the top left corner of the APPLICATION or WINDOW's client area.

## REPORT Structure Usage

---

The AT attribute on a REPORT structure defines the position and size of the area of the page devoted to printing report detail. This is the area in which all DETAIL structures and any group HEADER and FOOTER structures contained within BREAK structures will print.

## Print Structure Usage

---

The AT attribute on print structures performs two different functions, depending upon the structure on which it is placed.

When placed on a FORM, or page HEADER or FOOTER (not within a BREAK structure), the AT attribute defines the position and size on the page at which the structure prints. The position specified by the *x* and *y* parameters is relative to the top left corner of the page.

When placed on a DETAIL, or group HEADER or FOOTER (contained within a BREAK structure), the print structure prints according to the following rules (unless the ABSOLUTE attribute is also present):

- The *width* and *height* parameters of the AT attribute specify the minimum print size of the structure.
- The structure actually prints at the next available position within the detail print area (specified by the REPORT's AT attribute).
- The position specified by the *x* and *y* parameters of the structure's AT attribute is an offset from the next available print position within the detail print area.
- The first print structure on the page prints at the top left corner of the detail print area (at the offset specified by its AT attribute).
- Next and subsequent print structures print relative to the ending position of the previous print structure. If there is room to print the next structure beside the previous structure, it prints there. If not, it prints below the previous.

## REPORT Control Usage

---

The *x* and *y* parameters are relative to the top left corner of the print structure containing the control.



**Example:**

```

WinOne WINDOW,AT(0,0,380,200),MDI !top left corner, relative to app frame
      END

WinTwo WINDOW,AT(0,0,380,200)      !Top left corner, relative to video screen
      END

!Measurement in dialog units
WinOne WINDOW,AT(0,0,160,400)
      ENTRY,AT(8,40,80,8)          !Approx. 2 characters in, 5 down, 20 wide, 1 high
      END

CustRpt REPORT,AT(1000,1000,6500,9000),THOUS !AT specifies detail print area
Detail  DETAIL,AT(0,0,6500,1000)             !AT specifies band size and
                                             !relative position offset from
                                             !last printed detail
      STRING('String Constant'),AT(500,500,1500,500)
                                             !AT specifies control size and
                                             !offset within the detail band
      END
END

CustRpt REPORT,AT(1000,2000,6500,7000),THOUS !1" margins all around
      HEADER,AT(1000,1000,6500,1000)         !Page relative position
      !structure elements                    !1" band across top of page
      END
CustD1  DETAIL,AT(0,0,6500,1000)              !Detail relative position
      !structure elements                    !1" band across page
      END
CustD2  DETAIL,ABSOLUTE,AT(1000,8000,6500,1000) !Page relative position
      !structure elements                    !1" band near page bottom
      END
      FOOTER,AT(1000,9000,6500,1000)         !Page relative position
      !structure elements                    !1" band across page bottom
      END
END

CustRpt1 REPORT,AT(1000,1000,6500,9000),THOUS !1" margins all around for
                                             ! detail area on 8.5" x 11"
      !report declarations
      END

CustRpt2 REPORT,AT(72,72,468,648),POINTS     !1" margins all around for
                                             !detail area on 8.5" x 11"
      !report declarations
      END

```

**See Also:**

SETPOSITION

GETPOSITION

PROP:NoHeight/PROP:NoWidth

## AUTO (set USE variable automatic re-display)



### AUTO

---

The **AUTO** attribute (PROP:AUTO) specifies all window and toolbar controls' USE variables re-display on screen each time through the ACCEPT loop. This incurs some overhead, but ensures the data displayed is current, without requiring explicit DISPLAY statements.

#### Example:

```
WinOne WINDOW,AT(,,380,200),MDI,CENTER,AUTO !All controls values always display
      !controls
      END
CODE
!ACCEPT automatically re-displays changed USE variables
ACCEPT
END
```

## AUTOSIZE (set OLE object resizing)



### AUTOSIZE

---

The **AUTOSIZE** attribute (PROP:AUTOSIZE, write-only) specifies the OLE object automatically resizes itself when the OLE container control's AT attribute parameters change at runtime using property syntax to change the values of PROP:AT.

## AVE (set report total average)

**AVE**( [ *variable* ] )

---

<b>AVE</b>	Calculates the average (arithmetic mean) of the STRING controls' USE variable is printed.
<i>variable</i>	The label of a numeric variable to receive the intermediate values calculated for the AVE. This allows you to create totals on other totals. The value in the <i>variable</i> is internally updated by the print engine, so it is only useful for use within the REPORT structure.

The **AVE** attribute (PROP:AVE) specifies printing the average (arithmetic mean) of the STRING controls' USE variable. Unless the TALLY attribute is present, the result is calculated as follows:

- An AVE field in a DETAIL structure is calculated each time the DETAIL structure containing the control PRINTs.
- An AVE field in a group FOOTER structure is calculated each time any DETAIL structure in the BREAK structure containing the control PRINTs.
- An AVE field in a page FOOTER structure is calculated each time any DETAIL structure in any BREAK structure PRINTs.
- An AVE field in a HEADER is meaningless, since no DETAIL structures will have been printed at the time the HEADER is printed.

The average is reset only if the RESET or PAGE attribute is also specified. The STRING control using this attribute would usually be placed in a group or page FOOTER.

### Example:

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
Break1  BREAK(LocalVar),USE(?BreakOne)
Break2  BREAK(Pre:Key1),USE(?BreakTwo)
Detail  DETAIL,AT(0,0,6500,1000),USE(?DetailOne)
        STRING(@N$11.2),AT(6000,1500,500,500),USE(Pre:F1)
        END
        FOOTER,AT(0,0,6500,1000),USE(?BreakOneGroupFoot)
        STRING('Group Average: '),AT(5500,500)
        STRING(@N$11.2),AT(6000,500),USE(Pre:F1),AVE(LocalVar),RESET(Break2)
        END
        END
        FOOTER,AT(0,0,6500,1000),USE(?BreakOneGroupFoot)
        STRING('Grand Average: '),AT(5500,500)
        STRING(@N$11.2),AT(6000,500),USE(LocalVar),AVE,TALLY(?BreakTwo)
        END
        END
        END
```

## BEVEL (set 3-D effect border)



**BEVEL**( *outer* [,*inner*] [,*style*] )

<b>BEVEL</b>	Specifies a 3-D effect border on a control.
<i>outer</i>	An integer constant or constant expression that specifies the width of the outer edge of the bevel (PROP:BevelOuter, equivalent to {PROP:Bevel,1}). If negative, the outer edge appears to be lowered; if positive, the outer edge appears to be raised.
<i>inner</i>	An integer constant or constant expression that specifies the width of the inner edge of the bevel (PROP:BevelInner, equivalent to {PROP:Bevel,2}). If negative, the inner edge appears to be lowered; if positive, the inner edge appears to be raised. If omitted, there is no inner edge to the border.
<i>style</i>	An integer constant or constant expression that specifies fine control of the bevel, overriding the signs of the <i>outer</i> and <i>inner</i> parameters (PROP:BevelStyle, equivalent to {PROP:Bevel,3}).

The **BEVEL** attribute (PROP:BEVEL) of a PANEL, OPTION, GROUP, or REGION control specifies a 3-D effect border. The signs of the *outer* and *inner* parameters determine whether the control appears to be raised or lowered. The *style* parameter allows fine control of the bevel. This parameter is a bitmap with the bits apportioned for each edge as follows:

Bits:	15 - 12		11 - 08		07 - 04		03 - 00
Edge:	left		top		right		bottom

Each of these four-bit nibbles is further divided into two two-bit sections that govern the appearance of the inner and outer parts of the edge. The low order two bits of each nibble defines the outer part, while the high order bits define the inner:

Binary:	00b		01b		10b		11b
Result:	no edge		raised		lowered		gray

Combining these into nibbles creates the definition of one edge of the bevel:

0110b	=	raised inner, lowered outer
1001b	=	lowered inner, raised outer

### Example:

```
Win1 WINDOW,AT(0,0,160,400)
  PANEL,AT(25,15,50,50),USE(?Panel1),BEVEL(5,-5) !Raised outer, lowered inner
  PANEL,AT(0,0,,),USE(?Panel2),FULL,BEVEL(2,2,111010110101001b)
    !left   = all gray
    !top    = inner raised, outer raised
    !right  = inner lowered, outer lowered
    !bottom = inner lowered, outer raised
  REGION,AT(0,80,5,,),USE(?ResizeBar),FULL,IMM,BEVEL(2,2,0101000010100000b)
    !A vertical resize bar
END
```

## BOXED (set controls group border)



### BOXED

---

The **BOXED** attribute (PROP:BOXED) specifies a single-track border around a TEXT control, or a GROUP or OPTION structure. The *text* parameter appears in a gap at the top of the border box. If BOXED is omitted, the *text* parameter is not printed or displayed on screen.

## CAP, UPR (set case)



**CAP**

**UPR**

---

The **CAP** and **UPR** attributes specify the automatic case of text entered into ENTRY or TEXT controls when the MASK attribute is on the window or of text printed in a TEXT control.

The UPR attribute (PROP:UPR) specifies all upper case.

The CAP attribute (PROP:CAP) specifies "Proper Name Capitalization," where the first letter of each word is capitalized and all other letters are lower case. The user can override this default behavior by pressing the SHIFT key to allow an upper case letter in the middle of a name (allowing for names such as, "McDowell") or SHIFT while CAPS-LOCK is on, forcing a lower case first letter (allowing for names such as, "von Richtofen").

## CENTER (set centered window position)



### CENTER

---

The **CENTER** attribute (PROP:CENTER) indicates that the window's default position is centered. A WINDOW structure with the MDI attribute is centered on the APPLICATION. An APPLICATION structure is centered on the screen. A non-MDI WINDOW is centered on its parent (the window currently with focus when the non-MDI WINDOW is opened).

This attribute has no meaning unless at least one parameter of the AT attribute is omitted. This means that the CENTER attribute provides a default value for any omitted AT parameter.

For multi-monitor systems: Child and Owned Windows with the CENTER attribute (or PROP:CENTER = TRUE) applied are centered in the client area of their Parent/Owner window. Other windows with the CENTER attribute applied are centered in the monitor where most parts of the previous window in the same thread are displayed; if there are no other windows in the same thread, the window is displayed in the primary monitor.

#### Example:

```
WinOne WINDOW,AT(,,380,200),MDI,CENTER !Window centered relative to application frame
      END
```

```
WinTwo WINDOW,AT(,,380,200),CENTER      !Window centered relative to its parent:
      END
```



## CENTERED (set centered image)



### CENTERED

The **CENTERED** attribute (PROP:CENTERED) indicates an image displayed at its default size and centered in its display area:

- On an IMAGE control, the image is centered in the area specified by the AT attribute.
- On a TOOLBAR with the WALLPAPER attribute, the toolbar's background image is centered in the toolbar.
- On an APPLICATION or WINDOW with the WALLPAPER attribute, the window's background image is centered in the client area of the window.

#### Example:

```
MDIChild WINDOW('Child One'),MDI,SYSTEM,MAX
  MENUBAR
    MENU('Edit'),USE(?EditMenu)
    ITEM('Undo'),USE(?UndoText),KEY(CtrlZ),STD(STD:Undo)
    ITEM('Cu&t'),USE(?CutText),KEY(CtrlX),STD(STD:Cut)
    ITEM('Copy'),USE(?CopyText),KEY(CtrlC),STD(STD:Copy)
    ITEM('Paste'),USE(?PasteText),KEY(CtrlV),STD(STD:Paste)
  END
END
TOOLBAR,USE(?Toolbar),WALLPAPER('MyWall.GIF'),CENTERED
  BUTTON('Cut'),USE(?CutButton),ICON(ICON:Cut),STD(STD:Cut),FLAT
  BUTTON('Copy'),USE(?CopyButton),ICON(ICON:Copy),STD(STD:Copy),FLAT
  BUTTON('Paste'),USE(?PasteButton),ICON(ICON:Paste),STD(STD:Paste),FLAT
END
END

WinOne WINDOW,AT(, ,380,200),MDI,WALLPAPER('MyWall.GIF'),CENTERED
END
WinOne WINDOW,AT(, ,380,200),MDI
  IMAGE('MyWall.GIF'),AT(0,0,380,200),CENTERED
END
```

#### See Also:

WALLPAPER

TILED

## CHECK (set on/off ITEM)



### CHECK

---

The **CHECK** attribute (PROP:CHECK) specifies an ITEM that may be either ON or OFF. When ON, a check appears to the left of the menu selection and the USE variable receives the value one (1). When OFF, the check to the left of the menu selection disappears and the USE variable receives the value zero (0).

## CLIP (set OLE object clipping)



### CLIP

---

The **CLIP** attribute (PROP:CLIP, write-only) specifies the OLE object only displays what fits into the size of the OLE container control's AT attribute. If the object is larger than the OLE container control, only the top left corner displays.

## CNT (set total count)

CNT( [ *variable* ] )

---

**CNT**                Calculates the number of times DETAIL structures have been printed.

*variable*           The label of a numeric variable to receive the intermediate values calculated for the CNT. This allows you to create totals on other totals. The value in the *variable* is internally updated by the print engine, so it is only useful for use within the REPORT structure.

The **CNT** attribute (PROP:CNT) specifies an automatic count of the number of times DETAIL structures have been printed. Unless the TALLY attribute is present, the result is calculated as follows:

- A CNT field in a DETAIL structure increments each time the DETAIL structure containing the control PRINTs. This provides a "running" count.
- A CNT field in a group FOOTER structure increments each time any DETAIL structure in the BREAK structure containing the control PRINTs. This provides a total of the number of DETAIL structures printed in the group.
- A CNT field in a page FOOTER structure increments each time any DETAIL structure in any BREAK structure PRINTs. This provides a total of the number of DETAIL structures printed on the page (or report).
- A CNT field in a HEADER is meaningless, since no DETAIL structures will have been printed at the time the HEADER is printed.

The CNT is reset only if the RESET or PAGE attribute is also specified.

**Example:**

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
Break1  BREAK(LocalVar),USE(?BreakOne)
Break2  BREAK(Pre:Key1),USE(?BreakTwo)
Detail  DETAIL,AT(0,0,6500,1000),USE(?DetailOne)
        STRING(@N$11.2),AT(6000,1500,500,500),USE(Pre:F1)
        END
        FOOTER,AT(0,0,6500,1000),USE(?BreakOneGroupFoot)
        STRING('Group Count: '),AT(5500,500)
        STRING(@N$11.2),AT(6000,500),USE(Pre:F1),CNT(LocalVar),RESET(Break2)
        END
        END
        FOOTER,AT(0,0,6500,1000),USE(?BreakOneGroupFoot)
        STRING('Grand Count: '),AT(5500,500)
        STRING(@N$11.2),AT(6000,500),USE(LocalVar),CNT,TALLY(?BreakTwo)
        END
        END
        END
```

## COLOR (set color)

**COLOR**( *color* [, *selected fore* ] [, *selected back* ] )

---

<b>COLOR</b>	Specifies display or print color.
<i>color</i>	Specifies the background color (PROP:Background or PROP:FillColor, equivalent to {PROP:Color,1}). Foreground color is specified in the FONT attribute. See also PROP:FILL
<i>selected fore</i>	Specifies the default foreground color for the selected text on a control that can receive focus (PROP:SelectedColor, equivalent to {PROP:Color,2}). Not valid in a REPORT.
<i>selected back</i>	Specifies the default background color for the selected text on a control that can receive focus (PROP:SelectedFillColor, equivalent to {PROP:Color,3}). Not valid in a REPORT.

The **COLOR** attribute (PROP:COLOR) specifies the default background and selected foreground and background colors. This attribute is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

The color values in each of the three parameters are constants which contain the red, green, and blue components to create the color in the three low-order bytes of a LONG value (bytes 0, 1, and 2: Red = 000000FFh, Green = 0000FF00h, and Blue = 00FF0000h), or EQUATES for a standard Windows color value (which are all negative values). EQUATES for Windows' standard colors are contained in the EQUATES.CLW file. Each of the runtime properties returns COLOR:None if the associated parameter is absent. When COLOR:None is set, the runtime library uses the brush color in use by the parent container.

Windows automatically finds the closest match to the specified color value for the hardware on which the program is run. Windows standard colors may be reconfigured by the user in the Windows Control Panel. Any control using a Windows standard color is automatically repainted with the new color when this occurs.

### WINDOW and TOOLBAR Usage

---

On a WINDOW or TOOLBAR, the COLOR attribute specifies the background display color of the WINDOW or TOOLBAR and the default background and selected foreground and background colors for all controls in the WINDOW or TOOLBAR without their own COLOR attribute.

### Window Control Usage

---

The COLOR attribute specifies the display color of a LINE control. On a BOX, ELLIPSE, or REGION control, the *color* parameter specifies the color used for the control's border. On all other controls, the *color* parameter specifies the background control color, overriding the user's standard Windows color scheme for that control type.

For most of those controls that can receive focus, the *selected fore* and *selected back* parameters specify the foreground and background colors of the selected text or item.

## Report Usage

On a REPORT statement, the COLOR attribute specifies the background print color of the REPORT and the default background color for all DETAIL, HEADER, FOOTER, or FORM in the REPORT without a COLOR attribute.

The COLOR attribute specifies the background print color of the DETAIL, HEADER, FOOTER, or FORM on which it is placed, and the default background color for all controls in the DETAIL, HEADER, FOOTER, or FORM without a COLOR attribute.

The COLOR attribute specifies the print color of a LINE control, specifies the border color of a BOX or ELLIPSE control, or the background color of any other control.

### Example:

```
WinOne WINDOW,AT(0,0,160,400),COLOR(00FF0000h,0000FF00h,000000FFh)
      !Blue background, Green selected foreground, Red selected background
      TOOLBAR,COLOR(00FF0000h,0000FF00h,000000FFh)
      !Blue background, Green selected foreground, Red selected background
      BOX,AT(20,20,20,20),COLOR(COLOR:ACTIVEBORDER) !Windows' active border color
      END
      BOX,AT(100,100,20,20),COLOR(00FF0000h)           !Blue
      BOX,AT(140,140,20,20),COLOR(0000FF00h)           !Green
      BOX,AT(180,180,20,20),COLOR(000000FFh)           !Red
      END

CustRpt  REPORT,AT(1000,1000,6500,9000),THOUS,COLOR(00FF0000h)  !Blue background
CustDetail DETAIL,AT(0,0,6500,1000)
      ELLIPSE,AT(60,60,200,200),COLOR(COLOR:ACTIVEBORDER)  !Color EQUATE
      BOX,AT(360,60,200,200),COLOR(00FF0000h)              !Pure Red
      END
      END

RptOne REPORT,AT(0,0,160,400),COLOR(00FF0000h)  !Blue default background
      HEADER,COLOR(0000FF00h)                    !Green page header background
      !structure elements
      END

CustD1 DETAIL                                !uses the default background color
      !structure elements
      END
      FOOTER,COLOR(000000FFh)                    !Red page footer background
      !structure elements
      END
      END
```

### See Also:

FONT

## COLUMN (set list box highlight bar)



### COLUMN

---

The **COLUMN** attribute (PROP:COLUMN) specifies a field-by-field highlight bar on a LIST or COMBO control with multiple display columns. PROP:COLUMN returns zero (0) if off, else it returns the currently highlighted column number.

## COMPATIBILITY (set OLE control compatibility)



**COMPATIBILITY**( *mode* )

---

**COMPATIBILITY** Specifies OLE control compatibility setting.

*mode* An integer constant for the compatibility setting.

The **COMPATIBILITY** attribute (PROP:COMPATIBILITY, write-only) specifies a compatibility mode for certain OLE or .OCX objects that require it. The *mode* should in general be zero (0), however some OLE objects (like Windows bitmap editor) do not work unless it is set to one (1).

**Example:**

```
WinOne WINDOW,AT(0,0,200,200)
    OLE,AT(10,10,160,100),USE(?OLEObject),CREATE('Excel.Sheet.5'),COMPATIBILITY(0)
END
END
```



## CREATE (create OLE control object)



**CREATE**( *server* [, *object* ] )

**CREATE** Specifies creating a new object for the OLE control.

*server* A string constant containing the name of an OLE Server application, as it appears in the operating system's registry.

*object* A string constant containing the name of the OLE Compound Storage file and the object within it to open.

The **CREATE** attribute (PROP:CREATE, write-only) specifies the OLE control creates a new OLE or .OCX object. The *server* value is the object name as it appears in the Operating System's Registry Settings (in Win95, this information is available in REGEDIT.EXE under HKEY\_CLASSES\_ROOT, or in the Microsoft System Information program that comes with Microsoft Office--MSINFO32.EXE).

When the *object* parameter is present, CREATE operates just as the OPEN attribute does, opening the saved *object* for the OLE control from an OLE Compound Storage file (and ignoring the *server* parameter). When the object is opened, the saved version of the container properties are re-loaded, so properties do not need to be specified on an object opened. The *object* parameter syntax must take the form: *Filename!ObjectName*.

### Considerations when working with OLE objects

There are several potential problems if you CREATE an OLE control in the window for one thread and attempt to work with it from a different thread. This is because the Windows Operating System can load additional DLLs into process memory on creation of an OLE object. This creates several potential problems:

- The initialization code for the OLE control can be executed in the context of the current thread and the initialized data would not be available for the control when it is running in the thread of its host window.
- Extra DLLs can be unloaded from the process memory after closing the thread that created the OLE control, so the Virtual Memory Tables of interfaces used by the OLE control will point to deallocated memory.

As a result, *it's impossible to guarantee correct operation of OLE controls if they are created in a window other than the current thread.*

### Example:

```
WinOne WINDOW,AT(0,0,200,200)
    OLE,AT(10,10,160,100),USE(?OLEObject),CREATE('Excel.Sheet.5')
END
END
```

## CURSOR (set mouse cursor type)



**CURSOR**(*file*)

---

**CURSOR** Specifies a mouse cursor to display.

*file* A string constant containing the name of a .CUR file, or an EQUATE naming a Windows-standard mouse cursor. The .CUR file is linked into the .EXE as a resource.

The **CURSOR** attribute (PROP:CURSOR) specifies a mouse cursor to be displayed when the mouse is positioned over the APPLICATION, WINDOW, TOOLBAR, or control. This cursor is inherited by the controls in the APPLICATION, WINDOW, or TOOLBAR unless overridden.

EQUATE statements for the Windows-standard mouse cursors are contained in the EQUATES.CLW file. The following list is a representative sample of these (see EQUATES.CLW for the complete list):

CURSOR:None	No mouse cursor
CURSOR:Arrow	Normal windows arrow cursor
CURSOR:IBeam	Capital "I" like a steel I-beam
CURSOR:Wait	Hourglass
CURSOR:Cross	Large plus sign
CURSOR:UpArrow	Vertical arrow
CURSOR:Size	Four-headed arrow
CURSOR:Icon	Box within a box
CURSOR:SizeNWSE	Double-headed arrow slanting left
CURSOR:SizeNESW	Double-headed arrow slanting right
CURSOR:SizeWE	Double-headed horizontal arrow
CURSOR:SizeNS	Double-headed vertical arrow
CURSOR:DragWE	Double-headed horizontal arrow

### Example:

```
!Window with custom cursor
WinTwo WINDOW,CURSOR('CUSTOM.CUR')
    TOOLBAR,CURSOR('CURSOR:Cross') !Toolbar with large plus sign cursor
    BUTTON('Cut'),USE(?CutButton),STD(STD:Cut)
    BUTTON('Copy'),USE(?CopyButton),STD(STD:Copy)
    BUTTON('Paste'),USE(?PasteButton),STD(STD:Paste)
END
    REGION,AT(20,20,20,20),CURSOR(CURSOR:IBeam) !Region with I-beam cursor
    REGION,AT(100,100,20,20)
END
```

## DEFAULT (set enter key button)



### DEFAULT

---

The **DEFAULT** attribute (PROP:DEFAULT) specifies a **BUTTON** that is automatically pressed when the user presses the **ENTER** key. Only one active **BUTTON** on a window should have this attribute.

## DELAY (set repeat button delay)



**DELAY**( *time* )

---

**DELAY** Specifies the delay between first and second event generation.

*time* An integer constant containing the time delay to set, in hundredths of a second.

The **DELAY** attribute (PROP:DELAY) specifies the delay between first and second event generation for automatically repeating buttons. For a BUTTON control with the IMM attribute, this is the time between the first and second EVENT:Accepted. For a SPIN control, this is the time between the first and second EVENT:NewSelection generated by the spin buttons.

The purpose of the DELAY attribute is to change the delay time from its default value so that users do not inadvertently begin repeating the action when that is not their intention. Assigning a zero to PROP:DELAY resets the default setting, any other value sets the repeat delay for the control.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    BUTTON('Press Me'),AT(10,10,40,20),USE(?PressMe),IMM,DELAY(100) !1 second
    SPIN(@n3),AT(60,10,40,10),USE(SpinVar),RANGE(0,999),DELAY(100) !1 second
END
```

```
CODE
OPEN(MDIChild)
?PressMe{PROP:Delay} = 50 !Reset delay to 1/2 second
?SpinVar{PROP:Delay} = 50 !Reset delay to 1/2 second
?PressMe{PROP:Repeat} = 5 !Set repeat to 5 hundredths of a second
?SpinVar{PROP:Repeat} = 5 !Set repeat to 5 hundredths of a second
```

**See Also:**

IMM

REPEAT

## DISABLE (set control dimmed at open)



### DISABLE

---

The **DISABLE** attribute (PROP:Disable) specifies a control that is disabled when the WINDOW or APPLICATION is opened. The disabled control may be activated with the ENABLE statement. PROP:Disable returns a (1) if the control is DISABLEd and a (0) if ENABLEd.

**See Also:** DISABLE (dim a control)

## DOCK (set dockable toolbox window)



**DOCK**( *positions* )

---

**DOCK** Specifies a dockable TOOLBOX.

*Positions* A bitmap specifying the edges available for docking.

The **DOCK** attribute (PROP:DOCK) specifies a non-MDI WINDOW with the TOOLBOX attribute which may be docked to an edge of the application frame. The following EQUATEs for standard *positions* values are contained in EQUATES.CLW:

DOCK:Left	EQUATE (1)
DOCK:Top	EQUATE (2)
DOCK:Right	EQUATE (4)
DOCK:Bottom	EQUATE (8)
DOCK:Float	EQUATE (16)
DOCK:All	EQUATE (31)

**Example:**

```
Win1 WINDOW('Tools'),TOOLBOX,DOCK(DOCK:Left+DOCK:Right) !Dockable left and right only
    BUTTON('Date'),USE(?Button1)
    BUTTON('Time'),USE(?Button2)
END
```

**See Also:**

DOCKED

TOOLBOX

## DOCKED (set dockable toolbox window docked at open)



**DOCKED**( *position* )

**DOCKED** Specifies a dockable TOOLBOX docked at open.

*position* A bitmap specifying the edge to which it is docked.

The **DOCKED** attribute (PROP:DOCKED) specifies a non-MDI WINDOW with the DOCK attribute is docked when the window is opened. The following EQUATES for standard *position* values are contained in EQUATES.CLW:

DOCK:Left	EQUATE (1)
DOCK:Top	EQUATE (2)
DOCK:Right	EQUATE (4)
DOCK:Bottom	EQUATE (8)
DOCK:Float	EQUATE (16)
DOCK:All	EQUATE (31)

### Example:

```
Win1 WINDOW('Tools'), TOOLBOX, DOCK(DOCK:All), DOCKED(DOCK:Top)  !Dockable anywhere
      BUTTON('Date'), USE(?Button1)                               !Docked at top on open
      BUTTON('Time'), USE(?Button2)
END
```

### See Also:

DOCK

TOOLBOX





## DOCUMENT (create OLE control object from file)



**DOCUMENT**( *filename* )

**DOCUMENT** Specifies creating an object for the OLE control from a data file specific to an OLE server application.

*filename* A string constant containing the name of the file.

The **DOCUMENT** attribute (PROP:DOCUMENT, write-only) specifies creating an object for the OLE control from a data file specific to an OLE server application. The *filename* parameter syntax must be a fully-qualified pathname, unless the file exists in the same directory as the OLE Controller application.

### Example:

```
WinOne WINDOW,AT(0,0,200,200)
  OLE,AT(10,10,160,100),USE(?OLEObject),DOCUMENT('Book1.XLS') !Excel Spreadsheet
  MENUBAR
    MENU('&Clarion App')
      ITEM('&Deactivate Object'),USE(?DeactOLE)
    END
  END
END
END
END
```

## DRAGID (set drag-and-drop host signatures)



**DRAGID**( *signature* [, *signature*] )

---

**DRAGID** Specifies a LIST or REGION control that can serve as a drag-and-drop host.

*signature* A string constant containing an identifier used to indicate valid drop targets. Any *signature* that begins with a tilde (~) indicates that the information can also be dragged to an external (Clarion) program. A single DRAGID may contain up to 16 *signatures*.

The **DRAGID** attribute (PROP:DRAGID, an array) specifies a LIST or REGION control that can serve as a drag-and-drop host. DRAGID works in conjunction with the DROPID attribute. The DRAGID *signature* strings (up to 16) define validation keys to match against the *signature* parameters of the target control's DROPID. This provides control over where successful drag-and-drop operations are allowed.

A drag-and-drop operation occurs when the user drags information from a control with the DRAGID attribute to a control with the DROPID attribute. For a successful drag-and-drop operation, both controls must have at least one identical *signature* string in their respective DRAGID and DROPID attributes.

### Example:

```
WinOne WINDOW,AT(0,0,160,400)
    !Allows drags, but not drops:
    LIST,AT(120,0,20,20),USE(?List1),FROM(Que1),DRAGID('FromList1')
    !Allows drops from List1, but no drags
    LIST,AT(120,120,20,20),USE(?List2),FROM(Que2),DROPID('FromList1')
END
```

### CODE

```
OPEN(WinOne)
!Drag and Drop Ids can also be assigned at runtime
?List2{PROP:DropID,1} = 'FromList1'
?List1{PROP:DragID,1} = 'FromList1'
!*****
ACCEPT
CASE EVENT()
OF EVENT:Drag      !When a drag event is attempted
    IF DRAGID()    !check for success
        SETDROPID(Que1) !and setup info to pass
    END
OF EVENT:Drop      !When drop event is successful
    Que2 = DROPID() !get dropped info
    ADD(Que2)       !and add it to the queue
END
END
```

### See Also:

DROPID

## DROP (set list box behavior)

{bmc NewC7.bmp}

**DROP**( *count* [, *width* ] )

**DROP** Specifies the list appears only when the user presses an arrow cursor key or clicks on the drop icon.

*count* An integer constant that specifies the number of elements displayed.

*width* An integer constant that specifies the width of the dropped list, in dialog units (PROP:DropWidth, equivalent to {PROP:DROP,2}).

The **DROP** attribute (PROP:DROP) specifies that the selection list appears only when the user presses an arrow cursor key or clicks on the drop icon to the right of the currently selected value display. Once it drops into view, the list displays *count* number of elements. If the DROP attribute is omitted, the LIST or COMBO control always displays the number of data items specified by the *height* parameter of the control's AT attribute in the selection list.

The DROP attribute does not work on a WINDOW with the MODAL attribute and should not be used.

You can assign the name of another icon to the control's PROP:Icon property to override the default down-arrow drop icon.

### Example:

```
WinOne WINDOW,AT(0,0,160,400)
    LIST,AT(120,0,20,20),USE(?L7),FROM(Que1),DROP(6)
    COMBO(@S8),AT(120,120,20,20),USE(?C7),FROM(Que2),DROP(8)
END
CODE
OPEN(WinOne)
?C7{PROP:Icon} = 'MyDrop.ICO' !Change the drop icon on the COMBO control
```

## DROPID (set drag-and-drop target signatures)



**DROPID**( *signature* [, *signature*] )

---

**DROPID** Specifies a control that can serve as a drag-and-drop target.

*signature* A string constant containing an identifier used to indicate valid drag hosts. A single DROPID may contain up to 16 *signatures*. Any *signature* that begins with a tilde (~) indicates that the information can also be dropped from an external (Clarion) program. A DROPID *signature* of '~FILE' indicates the target accepts a comma-delimited list of filenames dragged from the Windows File Manager.

The **DROPID** attribute (PROP:DROPID, an array) specifies a control that can serve as a drag-and-drop target. DROPID works in conjunction with the DRAGID attribute. The DROPID *signature* strings (up to 16) define validation keys to match against the *signature* parameters of the host control's DRAGID. This provides control over where successful drag-and-drop operations are allowed.

A drag-and-drop operation occurs when the user drags information from a control with the DRAGID attribute to a control with the DROPID attribute. For a successful drag-and-drop operation, both controls must have at least one identical *signature* string in their respective DRAGID and DROPID attributes.

### Example:

```
WinOne WINDOW,AT(0,0,160,400)
    !Allows drags, but not drops:
    LIST,AT(120,0,20,20),USE(?List1),FROM(Que1),DRAGID('FromList1')
    !Allows drops from List1 or the Windows File Manager, but no drags:
    LIST,AT(120,120,20,20),USE(?List2),FROM(Que2),DROPID('FromList1','~FILE')
END

CODE
OPEN(WinOne)
!Drag and Drop Ids can also be assigned at runtime
?List2{PROP:DropID,1} = 'FromList1'
?List1{PROP:DragID,1} = 'FromList1'
!*****
ACCEPT
CASE EVENT()
OF EVENT:Drag           !When a drag event is attempted
    IF DRAGID()         !check for success
        SETDROPID(Que1) !and setup info to pass
    END
OF EVENT:Drop           !When drop event is successful
    Que2 = DROPID()     !get dropped info
    ADD(Que2)           !and add it to the queue
END
END
```

### See Also:

DRAGID

## EXTEND (set document formatting)



**EXTEND**( [*attributelist* [,*attributelist*...] )

---

<b>EXTEND</b>	Specifies the attributes needed for a particular document type.
<i>attributelist</i>	A string constant, variable, or EQUATE containing an optional type of output document and its associated attributes as described below:
<i>type</i>	A string constant that specifies which output format receives the attribute list
<i>attribute</i>	A string constant containing the valid formatting required for the designated document type.

The **EXTEND** attribute is a multi purpose storage tag, used to store information in the generated report WMF file. The information is later parsed and extracted from the WMF and passed to appropriate processing code.

Each *attributelist* may designate an optional document *type*, and associated attributes for that document type, using the following syntax:

**[type](attribute [attribute...])**

Current possible values for *type* are HTML, XML, TXT, PDF, or ALL. The **EXTEND** attribute (PROP:EXTEND) specifies a valid string of attributes that are assigned to a designated REPORT control for a given document *type*.

The contents of *attribute* are dependant on the target type. If a vertical bar ( | ) or parentheses ( " ) is needed to appear in the attribute, then the attribute needs to be surrounded by single quotes ( ' ).

### Examples:

```
ALL (HIDE=1 | HW=412 | HH=172) , PDF (SKIP=3) , TXT (SKIP=3) , HTML (SKIP=3) , XML (TagType=1 | Tag Name=Header)
```

```
ALL (HIDE=1 | HW=412 | HH=172) , PDF (SKIP=3) , TXT (SKIP=3) , HTML (SKIP=3)
```

```
XML (TagType=1 | TagParentName=Header | TagName=Street | ValueFromText=1)
```

```
ALL (HIDE=1 | HW=302 | HH=172) , PDF (SKIP=33) , TXT (SKIP=33) , HTML (SKIP=33) , XML (TagProcess Once=33 | TagType=1 | NameFromText=1 | TagValue=)
```

```
XML (TagType=1 | TagName=Street | ValueFromText=1 | TagParentName= Ship to )
```

```
ALL (HIDE=1 | HW=238 | HH=172) , PDF (SKIP=34) , TXT (SKIP=34) , HTML (SKIP=34) , XML (TagType=1 | NameFromText=1 | TagValue= | TagParentName=Lines)
```

## FILL (set fill color)

**FILL**(*rgb*)

---

**FILL** Specifies the fill color of a BOX, ELLIPSE or PANEL control.

*rgb* A LONG or ULONG integer constant containing the red, green, and blue components that create the color in the three low-order bytes (bytes 0, 1, and 2) or an EQUATE for a standard Windows color value.

The **FILL** attribute (PROP:FILL) specifies the display or print fill color of a BOX or ELLIPSE control. If omitted, the control is not filled with color. PROP:FILL returns COLOR:None if the FILL attribute is absent. This attribute is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

**Example:**

```
CustRpt  REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail  DETAIL,AT(0,0,6500,1000)
            ELLIPSE,AT(60,60,200,200),FILL(COLOR:ACTIVEBORDER)  !Color EQUATE
            BOX,AT(360,60,200,200),FILL(00FF0000h)               !Pure Red
            END
        END

WinOne WINDOW,AT(0,0,160,400)
        !Windows' active border color
        BOX,AT(20,20,20,20),FILL(COLOR:ACTIVEBORDER)
        BOX,AT(100,100,20,20),FILL(00FF0000h)  !Blue
        BOX,AT(140,140,20,20),FILL(0000FF00h)  !Green
        BOX,AT(180,180,20,20),FILL(000000FFh)  !Red
    END
```

## FLAT (set flat control)



### FLAT

The **FLAT** attribute (PROP:FLAT) specifies the BUTTON, CHECK, or RADIO with an ICON attribute appears flat until the mouse cursor passes over it. This attribute is typically used on controls placed in a TOOLBAR.

This feature works best if the ICON attribute names a .GIF file to display, as the image will automatically be "grayed" when the control is not active (the mouse cursor is not directly over the control).

The **FLAT** attribute is also supported in LIST,COMBO, ENTRY, and SPIN controls. Activating FLAT for these controls results in a "flatter" appearance (removes the recessed appearance).

PROP:FLAT is a read/write property.

#### Example:

```
WinOne WINDOW,AT(0,0,160,400)
  TOOLBAR
    CHECK('1'),AT(0,0,20,20),USE(C1),ICON('Check1.GIF'),FLAT
    BUTTON,AT(120,0,20,20),USE(?B7),ICON('Button1.GIF')
    OPTION('Option 4'),USE(OptVar4)
    RADIO('Radio 7'),AT(120,0,20,20),USE(?R7),ICON('Radio1.GIF'),FLAT
    RADIO('Radio 8'),AT(140,0,20,20),USE(?R8),ICON('Radio2.GIF'),FLAT
  END
END
END

CODE
OPEN(WinOne)
?B7{PROP:FLAT} = TRUE
```

## FONT (set default font)



**FONT**([*typeface*] [,*size*] [,*color*] [,*style*] [,*charset* ])

---

<b>FONT</b>	Specifies the default display font for the TOOLBAR .
<i>typeface</i>	A string constant containing the name of the font (PROP:FontName, equivalent to {PROP:Font,1}). If omitted, the system font is used.
<i>size</i>	An integer constant containing the size (in points) of the font (PROP:FontSize, equivalent to {PROP:Font,2}). If omitted, the system default font size is used.
<i>color</i>	A LONG integer constant containing the red, green, and blue values for the color of the font in the low-order three bytes, or an EQUATE for a standard Windows color value (PROP:FontColor, equivalent to {PROP:Font,3}). If omitted, black is used.
<i>style</i>	An integer constant or constant expression or EQUATE specifying the strike weight and style of the font (PROP:FontStyle, equivalent to {PROP:Font,4}). If omitted, the weight is GDI default.
<i>charset</i>	An integer constant or constant expression or EQUATE specifying the character set for the specified FONT (PROP:FontCharSet) or (PROP:Font,5). This provides support for international character sets. If omitted, the default character set for the FONT is used.

The **FONT** attribute (PROP:FONT) specifies the default display font for controls. When the property assignment's *target* is the SYSTEM built-in variable, PROP:FONT sets the font for the MESSAGE procedure.

The *typeface* parameter may name any font registered in the Windows system. For a report, the printer driver must support the specified *typeface* (this includes the TrueType fonts for most printers).

The EQUATES.CLW file contains EQUATE values for standard *style* values. A *style* in the range zero (0) to one thousand (1000) specifies the strike weight of the font. You may add to that values that indicate italic, underline, or strikeout text. The following EQUATES are in EQUATES.CLW:

FONT:thin	EQUATE (100)
FONT:regular	EQUATE (400)
FONT:bold	EQUATE (700)
FONT:italic	EQUATE (01000H)
FONT:underline	EQUATE (02000H)
FONT:strikeout	EQUATE (04000H)



The *charset* parameter may name any *character set* registered in the Windows system. For a report, the printer driver must support the specified *character set*. The EQUATES.CLW file contains EQUATE values for standard *character set* values. The SYSTEM Property, can be used to set the Character Set property at the system level (i.e., SYSTEM{PROP:CharSet} = CHARSET:GREEK).

CHARSET:ANSI	EQUATE(0)
CHARSET:DEFAULT	EQUATE(1)
CHARSET:SYMBOL	EQUATE(2)
CHARSET:MAC	EQUATE(77)
CHARSET:SHIFTJIS	EQUATE(128)
CHARSET:HANGEUL	EQUATE(129)
CHARSET:JOHAB	EQUATE(130)
CHARSET:GB2312	EQUATE(134)
CHARSET:CHINESEBIG5	EQUATE(136)
CHARSET:GREEK	EQUATE(161)
CHARSET:TURKISH	EQUATE(162)
CHARSET:HEBREW	EQUATE(177)
CHARSET:ARABIC	EQUATE(178)
CHARSET:BALTIC	EQUATE(186)
CHARSET:CYRILLIC	EQUATE(204)
CHARSET:THAI	EQUATE(222)
CHARSET:EASTEUROPE	EQUATE(238)
CHARSET:OEM	EQUATE(255)

## Window Usage

---

The FONT attribute on a WINDOW or APPLICATION structure specifies the default display font for all controls in the WINDOW or APPLICATION that do not have a FONT attribute. This is also the default font for newly created controls on the window, and is the font used by the SHOW and TYPE statements when writing to the window.

The FONT attribute on a TOOLBAR structure specifies the default display font for all controls in the TOOLBAR that do not have a FONT attribute.

Setting any of the runtime properties (PROP:*property*) of the FONT attribute for the WINDOW, APPLICATION, or TOOLBAR does not affect the existing controls already displayed. Controls CREATED after the property has been reset are affected, however.

The FONT attribute on a control declaration overrides any FONT specified on the WINDOW, APPLICATION, or TOOLBAR.

## Report Usage

---

The FONT attribute on a REPORT structure specifies the default print font for all controls in the REPORT. This font is used when the control does not have its own FONT attribute and the print structure containing the control also has no FONT attribute.

The FONT attribute on FORM, DETAIL, HEADER, and FOOTER structures specifies the default print font for all controls in the structures that do not have a FONT attribute.

The FONT attribute on a control declaration overrides any FONT specified on the REPORT or print structure.

### Example:

```
LRFont WINDOW('LR FontExample'),AT(, ,289,192), |
  FONT('Arial',12,COLOR:Maroon,Font:bold+Font:italic,CHARSET:ANSI),GRAY
  !14 point Arial typeface, Red, normal:
  LIST,AT(120,0,20,20),USE(?L7),FROM(Que1),Font('Arial',14,0FFh)
  !14 point Arial typeface, Black, Bold:
  LIST,AT(120,120,20,20),USE(?C7),FROM(Que2),Font('Arial',14,0,700)
  !14 point Arial typeface, Black, Bold Italic
  LIST,AT(120,240,20,20),USE(?C7),FROM(Que2),Font('Arial',14,0,700+01000h)
END

CustRpt REPORT,AT(1000,1000,6500,9000),THOUS, |
  FONT('Arial',12,,Font:Bold+Font:Italic)
  !report declarations
END

!A Window using 14 point Times New Roman, Bold and Italic
Win WINDOW,Font('Times New Roman',14,00H,Font:italic+Font:bold)
  STRING('This is Times 14 pt Bold Italic'),AT(42,14),USE(?String1)
END

CODE
OPEN(Win)
Win{PROP:FontSize} = 20           !Set default font size for CREATED controls
CREATE(100,CREATE:string)         !Create a control
100{PROP:Text} = 'This is 20 point'
SETPOSITION(100,82,24)
UNHIDE(100)
ACCEPT
END
```

### See Also:

SETFONT

GETFONT

FONTDIALOG

FONTDIALOGA

COLOR

CREATE

## FORMAT (set LIST or COMBO layout)



**FORMAT**(*format string*)

**FORMAT** Specifies the display or print format of the data in the LIST or COMBO control.

*format string* A string constant specifying the display format.

The **FORMAT** attribute (PROP:FORMAT) specifies the display format of the data in the LIST or COMBO control. The *format string* contains the information for formatting of data. PROP:FORMAT is updated whenever the user dynamically changes the format of the LIST or COMBO at runtime.

The *format string* contains "field-specifiers" which map to the fields of the QUEUE being displayed. Multiple "field-specifiers" may be grouped together as a "field-group" in square brackets ([ ]) to display as a single unit.

Only the fields in the QUEUE for which there are "field-specifiers" are included in the display. This means that, if there are two fields specified in the *format string* and three fields in the QUEUE, only the two specified in the *format string* are displayed in the LIST or COMBO control.

### "Field-specifier" format:

Each column in the LIST is formatted with the following components. The format for a particular column is returned or set by PROPLIST:Format.

*width justification [ (indent) ] [ modifiers ]*

<i>width</i>	A required integer defining the width of the field (PROPLIST:Width). Specified in dialog units.
<i>justification</i>	A single capital letter ( <b>L</b> , <b>R</b> , <b>C</b> , or <b>D</b> ) that specifies <b>Left</b> (PROPLIST:Left), <b>Right</b> (PROPLIST:Right), <b>Center</b> (PROPLIST:Center), or <b>Decimal</b> (PROPLIST:Decimal) justification. One is required.
<i>Indent</i>	An optional integer, enclosed in parentheses, that specifies the indent from the justification. This may be negative. With left ( <b>L</b> ) (PROPLIST:LeftOffset) justification, <i>indent</i> defines a left margin ; with right ( <b>R</b> ) (PROPLIST:RightOffset) or decimal ( <b>D</b> ) (PROPLIST:DecimalOffset), it defines a right margin; and with center ( <b>C</b> ) (PROPLIST:CenterOffset), it defines an offset from the center of the field (negative = left offset).
<i>Modifiers:</i>	Optional special characters (listed below) to modify the display format of the field or group. Multiple <i>modifiers</i> may be used on one field or group.

### Modifiers:

- \* An asterisk (PROPLIST:Color) indicates color information for the field is contained in four LONG fields that immediately follow the data field in the QUEUE (or FROM attribute string). The four colors are normal foreground, normal background, selected foreground, and selected background (in that order). Not valid in a REPORT.

**Note:**

Color may also be set by using a list box style. (see "Y" below)

**B** (color) Specifies the color to use for the selection bar frame (PROPLIST:BarFrame)

**E** ([color1][,color2][,color3][,color4]) Parameters of the E modifier are normal foreground, normal background, selected foreground and selected background colors respectively. These colors are used as the default for a list column. If the column also includes the \* modifier, these default colors can be overridden by values from the list source (queue, VLB, etc.). Default colors are used if the \* modifier is not specified for the column, or color value set in the list source is equal to COLOR:None. In the Listbox Formatter, the default colors can be set on the Appearance tab.

The default column colors can be set or changed from the program using the following properties: PROPLIST:TextColor, PROPLIST:BackColor, PROPLIST:TextSelected and PROPLIST:BackSelected.

**I** An I (PROPLIST:Icon) indicates an icon displays in the column, at the left edge of the column (prepended to the data). An icon number is contained in a LONG field immediately following the data field in the QUEUE (or FROM attribute string). The LONG field contains a number that refers to an entry in a list of icons associated with the LIST control through the PROP:IconList runtime property. If an asterisk is also specified for color, this LONG must follow all the color information. Not valid in a REPORT. To display the icon only, and not the contents of the data field, make the display picture @P\_PB.

**J** A J (PROPLIST:IconTrn) indicates a transparent icon displays in the column. The same information as I applies to J. Not valid in a REPORT.

**T** [ (suppress) ] A T (PROPLIST:Tree) indicates the LIST is a tree control. The tree level is contained in a LONG field that immediately follows the data field in the QUEUE (or FROM attribute string). If \* and I are also specified, this LONG must follow all their LONG fields. The expanded/contracted state of the tree level is determined by the sign of the tree level LONG field's value (positive value=expanded and negative value=contracted). Not valid in a REPORT.

The optional *suppress* parameter can contain a **1** (PROPLIST:TreeOffset) to indicate the root is level number one (1) instead of zero (0), allowing -1 to indicate a contracted root. It can also contain an **R** (PROPLIST:TreeRoot) to suppress the connecting lines to the root level, an **L** (PROPLIST:TreeLines) to suppress the connecting lines between all levels, a **B** (PROPLIST:TreeBoxes) to suppress expansion boxes, and an **I** (PROPLIST:TreeIndent) to suppress level indentation (which also implicitly suppresses both lines and boxes).

<b>Y</b>	A Y (PROPLIST:CellStyle) indicates a pre-defined style for the field (column) is contained in a LONG field that immediately follows the data field in the QUEUE (or FROM attribute string). The LONG field contains a number that refers to an entry in an array of styles associated with the LIST control through the PROPSTYLE: runtime properties (see below). Not valid in a REPORT.
<b>Z(style)</b>	A 'Z' followed by a 'style' (PROPLIST:ColStyle) sets the default style for an entire column.

The style for an entire column may be set with PROPLIST:ColStyle. Using PROPLIST:ColStyle, the LONG field is not necessary in the QUEUE but without the LONG field you cannot assign different styles to individual cells in the column.

*~header~ [ justification [ (indent) ] ]*

A header string enclosed in tildes (PROPLIST:Header), followed by optional justification parameter (**L** = PROPLIST:HeaderLeft, **R** = PROPLIST:HeaderRight, **C** = PROPLIST:HeaderCenter, or **D** = PROPLIST:HeaderDecimal, ) and/or indent value in parentheses (PROPLIST:HeaderLeftOffset, PROPLIST:HeaderRightOffset, PROPLIST:HeaderCenterOffset, or PROPLIST:HeaderDecimalOffset), displays the header at the top of the list. The header uses the same justification and indent as the field, if not specifically overridden.

<b>@picture@</b>	The <i>picture</i> (PROPLIST:Picture) formats the field for display. The trailing @ is required to define the end of the <i>picture</i> , so that display pictures such as @N12~Kr~ can be used in the format string without creating ambiguity.
<b>?</b>	A question mark (PROPLIST:Locator) defines the locator field for a COMBO list box with a selector field. For a drop-down multi-column list box, this is the value displayed in the current-selection box. Not valid in a REPORT.
<b>#number#</b>	The <i>number</i> enclosed in pound signs (#) (PROPLIST:FieldNo) indicates the QUEUE field to display. Following fields in the format string without an explicit <i>#number#</i> are taken in order from the fields following the <i>#number#</i> field. For example, #2# on the first field in the format string indicates starting with the second field in the QUEUE, skipping the first. If the number of fields specified in the format string are >= the number of fields in the QUEUE, the format "wraps around" to the start of the QUEUE.
<b>_</b>	An underscore (PROPLIST:Underline) underlines the field.
<b>/</b>	A slash (PROPLIST:LastOnLine) causes the next field to appear on a new line (only used on a field within a group).
<b> </b>	A vertical bar (PROPLIST:RightBorder) places a vertical line to the right of the field.
<b>M</b>	An M (PROPLIST:Resize) allows the field or group of fields to be dynamically re-sized at runtime. This allows the user to drag the right vertical bar (if present) or right edge of the data area. Not valid in a REPORT.
<b>F</b>	An F (PROPLIST:Fixed) creates a fixed column in the list that stays on screen when the user horizontally pages through the fields (by the HSCROLL attribute). Fixed fields or groups must be at the start of the list. This is ignored if placed on a field within a group. Not valid in a REPORT.

- S**(*integer*) An **S** followed by an *integer* (PROPLIST:Scroll) in parentheses adds a scroll bar to the group. The *integer* defines the total number of dialog units to scroll. This allows large fields to be displayed in a small column width. This is ignored if placed on a field within a group. Not valid in a REPORT.
- P** A **P** modifier adds a tool tip (PROPLIST:Tip) to the group. The column's tip text by default is derived from the next queue field that follows the queue field used to hold the actual column's data. If the designated queue field is empty, the **Q** modifier (see below) designates a string value to use as a default tool tip. Also valid with a VLB (Virtual List Box). Not valid in a REPORT.
- Q** (string) A **Q** followed by a string (PROPLIST:DefaultTip) designates the default column tip text to be displayed if the value of the designated **P** modifier is an empty string. Not valid in a REPORT.

### "Field-group" format:

---

[ *multiple field-specifiers* ] [ ( *size* ) ] [ *modifiers* ]

- multiple field-specifiers* A list of field-specifiers contained in square brackets ( [ ] ) that cause them to be treated as a single display unit.
- size* An optional integer, enclosed in parentheses, that specifies the width of the group (PROPLIST:Width). If omitted, the size is calculated from the enclosed fields.
- Modifiers* The "field-group" *modifiers* act on the entire group of fields. These are the same *modifiers* listed above for a field (except the \*, I, T, and #*number*# *modifiers* which are not appropriate to groups). Add PROPLIST:Group to the appropriate field property to affect the group properties. PROPLIST:GroupNo can be used to return the group number of a target column.

### Example:

```
?List{PROPLIST:GroupNo,LOC:COL}
```

returns the group number of the column variable (LOC:COL). A Column not in a group is considered a group by itself.

```
?List{PROPLIST:GroupNo + PROPLIST:Group,LOC:COL}
```

returns the number of columns in the target group, 0 if the group is really a column.

## Display QUEUE Field Format

---

The order of fields that appear in the QUEUE to display in the LIST is important. Since there are several modifiers which require separate fields in the QUEUE to hold formatting data, the following is the order in which those fields must appear in the QUEUE:

1. The field containing the data to display (always).
2. The \* flag's foreground color field (if the \* is present, or PROPLIST:Color is set).
3. The \* flag's background color field (if the \* is present, or PROPLIST:Color is set).
4. The \* flag's selected foreground color field (if the \* is present, or PROPLIST:Color is set).
5. The \* flag's selected background color field (if the \* is present, or PROPLIST:Color is set).
6. The **I** or **J** flag's icon field (if the I or J is present, or PROPLIST:Icon or PROPLIST:IconTrn is set).
7. The **T** flag's tree level field (if the T is present, or PROPLIST:Tree is set).
8. The **Y** flag's style field (if the Y is present, or PROPLIST:CellStyle is set).
9. The **P** flag's tool tip field (if the P is present, or PROPLIST:Tip is set)

## FORMAT() Runtime Properties



The properties of the individual fields and groups in a multi-column LIST or COMBO control can also be set using the property equates for each (the PROPLIST:Item listed above for each property). These properties eliminate the need to create a complete FORMAT attribute string just to change a single property of a single field in the LIST.

These are all property arrays that require an explicit array element number following the property equate (separated by a comma) to specify which column in the LIST or COMBO is affected. All of them contain blank (") if missing, and a one (1) if present.

### Example:

```
PROGRAM
MAP
DisplayList      PROCEDURE
PrintList        PROCEDURE
RandomAlphaData  PROCEDURE(*STRING)
END

TreeDemo  QUEUE                !Data list box FROM queue
FName      STRING(20)
ColorNFG   LONG(COLOR:White)  !Normal Foreground color for FName
ColorNBG   LONG(COLOR:Maroon) !Normal Background color for FName
ColorSFG   LONG(COLOR:Yellow) !Selected Foreground color for FName
ColorSBG   LONG(COLOR:Blue)   !Selected Background color for FName
IconField  LONG                !Icon number for FName
TreeLevel  LONG                !Tree Level
LName      STRING(20)
Init       STRING(4)
END

CODE
DisplayList
PrintList

DisplayList      PROCEDURE
Win WINDOW('List Boxes'),AT(0,0,366,181),SYSTEM,DOUBLE
LIST,AT(0,34,366,146),FROM(TreeDemo),USE(?Show),HVSCROLL,
FORMAT('80L*IT~First Name~*80L~Last Name~16C~Initials~')
END

CODE
LOOP X# = 1 TO 20
RandomAlphaData(TreeDemo.FName)
TreeDemo.IconField = ((X#-1) % 4) + 1      !Assign icon number
TreeDemo.TreeLevel = ((X#-1) % 4) + 1      !Assign tree level
RandomAlphaData(TreeDemo.LName)
RandomAlphaData(TreeDemo.Init)
ADD(TreeDemo)
END
OPEN(Win)
?Show{PROP:iconlist,1} = ICON:VCRback      !Icon 1 = <
?Show{PROP:iconlist,2} = ICON:VCRrewind    !Icon 2 = <<
?Show{PROP:iconlist,3} = ICON:VCRplay      !Icon 3 = >
?Show{PROP:iconlist,4} = ICON:VCRfastforward !Icon 4 = >>
ACCEPT
END
```



```

RandomAlphaData PROCEDURE(Field)      !MAP Prototype is: RandomAlphaData(*STRING)
CODE
  CLEAR(Field)
  RandomSize# = RANDOM(1,SIZE(Field)) !Random fill size
  Field[1] = CHR(RANDOM(65,90))       !Start with a random upper case letter
  LOOP Z# = 2 to RandomSize#          !Fill each character with
    Field[Z#] = CHR(RANDOM(97,122))    !a random lower case letter
  END

PrintList PROCEDURE

DemoQ      QUEUE
FName      STRING(20)
ColorNFG1  LONG
ColorNBG1  LONG
ColorSFG1  LONG(COLOR:Black) !Printed Foreground color for FName
ColorSBG1  LONG(COLOR:White) !Printed Background color for FName
LName      STRING(20)
ColorNFG2  LONG
ColorNBG2  LONG
ColorSFG2  LONG(COLOR:Black) !Printed Foreground color for LName
ColorSBG2  LONG(COLOR:White) !Printed Background color for LName
Init       STRING(4)
ColorNFG3  LONG
ColorNBG3  LONG
ColorSFG3  LONG(COLOR:Black) !Printed Foreground color for Init
ColorSBG3  LONG(COLOR:White) !Printed Background color for Init
Wage       REAL
ColorNFG4  LONG
ColorNBG4  LONG
ColorSFG4  LONG(COLOR:Black) !Printed Foreground color for Wage
ColorSBG4  LONG(COLOR:White) !Printed Background color for Wage
END

CustRpt    REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail DETAIL,AT(0,0,6500,200)
          LIST,AT(0,0,6000,200),FORMAT(' '),FROM(DemoQ),USE(?Show)
          END
          END

CODE
LOOP X# = 1 TO 20
  CLEAR(DemoQ)
  RandomAlphaData(DemoQ.FName)
  RandomAlphaData(DemoQ.LName)
  RandomAlphaData(DemoQ.Init)
  DemoQ.Wage = RANDOM(100000,1000000)/100
  ADD(DemoQ)
END
OPEN(CustRpt)
SETTARGET(CustRpt)
IF RANDOM(0,1)
  ?Show{PROP:Format} = '2000L*~First Name~2000L*~Last Name~500L*~Intls~1000L*~Wage~| '
ELSE
  ?Show{PROP:Format} = '2000L*~First Name~2000L*~Last Name~500L*~Intls~1000D(400)*~Wage~| '
  ?Show{PROPLIST:Header,1} = 'First Field'          !Change first field's header text
  ?Show{PROPLIST:Header + PROPLIST:Group,1} = 'First Group'
END
          !Change first group's header text

```

```
LOOP X# = 1 TO RECORDS (DemoQ)
  GET (DemoQ,X#)
  PRINT (CustDetail)
END
CLOSE (CustRpt)
FREE (DemoQ)
```

## FORMAT() Style Properties



The following properties are used to set up the array of styles available to a column with the **Y** modifier or for use with PROPLIST:ColStyle. These define an array of available styles. Assigning the array element number to the Y modifier's LONG field or to PROPLIST:ColStyle sets the display style for the individual cell or column.

### **PROPSTYLE:BackColor**

An array property that sets or returns the background color for the style number specified as the array element.

### **PROPSTYLE:BackSelected**

An array property that sets or returns the selected background color for the style number specified as the array element.

### **PROPSTYLE:BarFrame**

An array property that sets or returns the selected bar frame color for the style number specified as the array element.

```
?List{PROPSTYLE:BarFrame, 1} = COLOR:Blue
```

If PROPSTYLE:BarFrame is set for a style where the default frame color is not set, the runtime library uses one on the base selection bar's background color.

If the barframe color matches the selection bar color, the focus rectangle is not drawn if the list box has focus

### **PROPSTYLE:CharSet**

An array property that sets or returns the font character set for the style number specified as the array element.

### **PROPSTYLE:FontColor**

An array property that sets or returns the font color for the style number specified as the array element.

### **PROPSTYLE:FontName**

An array property that sets or returns the font name for the style number specified as the array element.

### **PROPSTYLE:FontSize**

An array property that sets or returns the font size for the style number specified as the array element.

### **PROPSTYLE:FontStyle**

An array property that sets or returns the font style (strike weight, etc.) for the style number specified as the array element.

### **PROPSTYLE:Picture**

An array property that sets or returns the display picture associated with the style number specified as the array element.

### **PROPSTYLE:TextColor**

An array property that sets or returns the text color for the style number specified as the array element (same as fontcolor).

### **PROPSTYLE:TextSelected**

An array property that sets or returns the selected text color for the style number specified as the array element.

**Example:**

```
?list{PROPSTYLE:FontName, 1}      = 'Arial'      !setup positive value style
?list{PROPSTYLE:FontSize, 1}      = 11
?list{PROPSTYLE:FontStyle, 1}     = FONT:Regular
?list{PROPSTYLE:TextColor, 1}     = COLOR:Yellow
?list{PROPSTYLE:BackColor, 1}     = COLOR:Black
?list{PROPSTYLE:TextSelected, 1}  = COLOR:Yellow
?list{PROPSTYLE:BackSelected, 1}  = COLOR:Blue
?list{PROPSTYLE:Picture, 1}       = '@n11.2'

?list{PROPSTYLE:FontName, 2}      = 'Arial'      !setup negative value style
?list{PROPSTYLE:FontSize, 2}      = 11
?list{PROPSTYLE:FontStyle, 2}     = FONT:Bold
?list{PROPSTYLE:TextColor, 2}     = COLOR:Red
?list{PROPSTYLE:BackColor, 2}     = COLOR:White
?list{PROPSTYLE:TextSelected, 2}  = COLOR:Red
?list{PROPSTYLE:BackSelected, 2}  = COLOR:Yellow
?list{PROPSTYLE:Picture, 2}       = '@n(13.2) '

?list{PROPLIST:ColStyle,1} = 1           !Column 1 uses the positive style
?list{PROPLIST:ColStyle,2} = 2           !Column 2 uses the negative style
```

## FORMAT() Other List Box Properties



The following properties are not part of the FORMAT attribute string, but may be used to dynamically affect the appearance of the LIST or COMBO control.

### PROPLIST:BackColor

An array property that sets or returns the default background color for the text in the column number specified as the array element. This coloring can be overridden on a per-cell basis by the standard cell coloring mechanism.

### PROPLIST:BackSelected

An array property that sets or returns the default selected background color for the text in the column number specified as the array element. This coloring can be overridden on a per-cell basis by the standard cell coloring mechanism.

### PROPLIST:BarFrame

An array property that sets or returns the default color of the frame of the selection bar in the column number specified as the array element:

```
?List{PROPLIST:BarFrame,2} = COLOR:Red
!Set Selection Frame of second column to RED
?List{PROPLIST:BarFrame} = 0C66A32h
!Set ALL columns to the target color
```

The last statement above is equivalent to

```
?List {PROPLIST:BarFrame, 1} = 0C66A32h
```

and sets the listbox's default color for the entire selection bar's frame for any column where the bar frame color is not set explicitly.

If PROPSTYLE:BarFrame is set for a style where the default frame color is not set, the runtime library uses one on the base selection bar's background color.

If the bar frame color matches the selection bar color, the focus rectangle is not drawn if the list box has focus.

If a bar frame color is defined, and the listbox does not use the NOBAR attribute, and the list box has no focus, the selection bar is drawn as a frame around the current row/field using the default bar frame color. The selected background is not used to draw the current row/field under these conditions.

### PROPLIST:Exists

An array property that returns:

- TRUE or FALSE if called with the column number > 0. If the column number specified as the array element exists, PROPLIST:Exists returns TRUE (i.e., ?List{PROPLIST:Exists,1} tests whether column 1 exists in the list). This is useful for generic list box processing.
- total number of list box columns if called with the column number 0
- total number of columns in the specified group if called for the group, for example:

```
?List {PROPLIST:Exists + PROPLIST:Group, ColumnNumber}
```

**PROPLIST:OldTreeColor**

If set to TRUE value (the default), the background color of the tree and icon area of a relational tree is set to the list box normal background color.

If set to FALSE, the background color of the tree and icon area of a relation tree is set to the background color of the row or field (depending on the FORMAT string) normal background. (as the default in Clarion 6.3 Build 9058)

**PROPLIST:Style**

PROPLIST:Style is actually more similar to PROPLIST:Group. It is a property number modifier which designates that a property is applied not to a column, but to style, e.g.:

```
?List {PROPLIST:TextColor, number} = SomeColor
```

sets the text color to cells of column *number*.

```
?List{PROPLIST:TextColor+PROPLIST:Style,N} = SomeColor
```

sets the text color to the style number *N*. If a cell or column is using the *N* style, the text for that cell or column will have the *SomeColor* color.

**PROPLIST:TextColor**

An array property that sets or returns the default text color for the text in the column number specified as the array element. This coloring can be overridden on a per-cell basis by the standard cell coloring mechanism.

**PROPLIST:TextSelected**

An array property that sets or returns the default selected text color for the text in the column number specified as the array element. This coloring can be overridden on a per-cell basis by the standard cell coloring mechanism.

**Example:**

```
WinView WINDOW('View'),AT(, ,340,200),SYSTEM,CENTER
    LIST,AT(0,0,300,200),USE(?List),FROM(Que),FORMAT('80L~F1~80L~F2~80L~F3~')
END

CODE
OPEN(WinView)
LOOP X# = 1 TO 255
    IF ?List{PROPLIST:Exists,X#} = 1          !If there is a column with this number
        ?List{PROPLIST:TextColor,X#} = COLOR:Red
        ?List{PROPLIST:BackColor,X#} = COLOR:White
        ?List{PROPLIST:TextSelected,X#} = COLOR:Yellow
        ?List{PROPLIST:BackSelected,X#} = COLOR:Blue
    ELSE
        BREAK
    END
END
END
```

## FORMAT() List Box Mouse Click Properties



The following runtime properties return the mouse position within the LIST or COMBO control when pressed or released. They can also be written to, which has no effect except to temporarily change the value that the property returns when next read (within the same ACCEPT loop iteration). This may make coding easier in some circumstances.

PROPLIST:MouseDownField	Returns the field number when the mouse is pressed. Same as list column as in PROP:COLUMN
PROPLIST:MouseDownRow	Returns the row number when the mouse is pressed.
PROPLIST:MouseDownZone	Returns the zone number when the mouse is pressed.
PROPLIST:MouseMoveField	Returns the field number when the mouse is moved. Same as list column as in PROP:COLUMN
PROPLIST:MouseMoveRow	Returns the row number when the mouse is moved.
PROPLIST:MouseMoveZone	Returns the zone number when the mouse is moved.
PROPLIST:MouseUpField	Returns the field number when the mouse is released. Same as list column as in PROP:COLUMN
PROPLIST:MouseUpRow	Returns the row number when the mouse is released.
PROPLIST:MouseUpZone	Returns the zone number when the mouse is released.

The three "Row" properties all return zero (0) for header text and negative one (-1) if below the last displayed item.

Equates for the following Zones are listed on EQUATES.CLW:

LISTZONE:Field	On a field in the LIST
LISTZONE:Right	On the field's right border resize zone
LISTZONE:Header	On a field or group header
LISTZONE:ExpandBox	On an expand box in a Tree
LISTZONE:Tree	On the connecting lines of a Tree
LISTZONE:Icon	On an icon (Tree or not)
LISTZONE:Nowhere	Anywhere else

### Example:

```
Que  QUEUE
F1    STRING(50)
F2    STRING(50)
F3    STRING(50)
END
```

```
WinView WINDOW('View'),AT(, ,340,200),SYSTEM,CENTER
LIST,AT(20,0,300,200),USE(?List),FROM(Que),HVSCROLL, |
FORMAT('80L~F1~80L~F2~80L~F3~'),ALRT(MouseLeft)
END
```

```
SaveFormat  STRING(20)
SaveColumn  BYTE
Columns     BYTE,DIM(3)
```

```
CODE
OPEN(WinView)
Columns[1] = 1
Columns[2] = 2
Columns[3] = 3
DO BuildListQue
ACCEPT
CASE EVENT()
OF EVENT:PreAlertKey
    CYCLE                                !Allow standard LIST clicks to process
OF EVENT:AlertKey
    IF ?List{PROPLIST:MouseDownRow} = 0 |           !Check for click in header
        AND ?List{PROPLIST:MouseDownZone}<>LISTZONE:Right !but not the resize zone
        EXECUTE Columns[?List{PROPLIST:MouseDownField}] !Check which header
            SORT(Que,Que.F1)
            SORT(Que,Que.F2)
            SORT(Que,Que.F3)
        END
        SaveFormat = ?List{PROPLIST:Format,?List{PROPLIST:MouseDownField}}
        ?List{PROPLIST:Format,?List{PROPLIST:MouseDownField}} = ?List{PROPLIST:Format,1}
        ?List{PROPLIST:Format,1} = SaveFormat
        SaveColumn = Columns[?List{PROPLIST:MouseDownField}]
        Columns[?List{PROPLIST:MouseDownField}] = Columns[1]
        Columns[1] = SaveColumn
        DISPLAY
    END
END
END
FREE(Que)

BuildListQue ROUTINE
LOOP Y# = 1 TO 9
    Que.F1 = 'Que.F1 - ' & Y#
    Que.F2 = 'Que.F2 - ' & RANDOM(10,99)
    Que.F3 = 'Que.F3 - ' & RANDOM(100,999)
    ADD(Que)
    ASSERT(NOT ERRORCODE())
END
```



## FROM (set listbox data source)



**FROM**(*source*)

---

<b>FROM</b>	Specifies the source of the data displayed or printed in a LIST control.
<i>source</i>	The label of a QUEUE or field within a QUEUE, or a string constant or variable (normally a GROUP) containing the data items to display or print in the LIST. If the QUEUE has been dynamically created with NEW, the corresponding DISPOSE <u>must</u> come after the window has been closed.

The **FROM** attribute (PROP:FROM, write-only) specifies the source of the data elements displayed in a LIST, COMBO, or SPIN control, or printed in a LIST control.

If a string constant is specified as the *source*, the individual data elements must be delimited by a vertical bar (|) character. To include a vertical bar as part of one data element, place two adjacent vertical bars in the string (||), and only one will be displayed. To indicate that an element is empty, place at least one blank space between the two vertical bars delimiting the elements (| |). Normally, a valid event will move the selected data element's contents into the control's USE variable. However, an *alternate* value can also be specified in the FROM attribute by including an additional vertical bar followed by a pound symbol (#), and followed by the alternate value. This technique is also useful for the display of special characters. For example, to display the # character in the listbox using a string as a source for FROM, it's enough if the previous entry is defined with alternate value:

```
... ,FROM(' ||!|@|#@|#|$|%|^|&|*')
```

### Window Usage

---

For a SPIN control, the *source* would usually be a QUEUE field or string. If the *source* is a QUEUE with multiple fields, only the first field is displayed in the SPIN.

For LIST and COMBO controls, the data elements are formatted for display according to the information in the FORMAT attribute. If the label of a QUEUE is specified as the *source*, all fields in the QUEUE are displayed as defined by the FORMAT attribute. If the label of one field in a QUEUE is specified as the *source*, only that field is displayed. Queue elements that contain vertical bar characters are treated as a single list entry.

### Report Usage

---

If the label of a QUEUE is specified as the *source*, all fields in the QUEUE are printed. If the label of one field in a QUEUE is specified as the *source*, only that field is printed. Only the current QUEUE entry in the queue's data buffer is printed in the LIST. If a string constant or variable is specified as the *source*, the entire string (all entries in the vertical bar delimited list of data elements) is printed in the LIST. The data elements are formatted for printing in the LIST according to the information in the FORMAT attribute.

**Example:**

```
TD      QUEUE,AUTO
FName   STRING(20)
LName   STRING(20)
Init    STRING(4)
Wage    REAL
      END

CustRpt  REPORT,AT(1000,1000,6500,9000),THOUS
CustDetail  DETAIL,AT(0,0,6500,1000)
      LIST,AT(0,34,366,146),FORMAT('80L80L16L60L'),FROM(TD),USE(?Show1)
      LIST,AT(0,200,100,146),FORMAT('80L'),FROM(Fname),USE(?Show2)
      END
      END

Que1    QUEUE,PRE(Q1)
F1      LONG
F2      STRING(8)
      END

Win1    WINDOW,AT(0,0,160,400)
      LIST,AT(120,0,20,20),USE(?L1),FROM(Que1),FORMAT('5C~List~15L~Box~'),COLUMN
      COMBO(@S8),AT(120,120,20,20),USE(?C1),FROM(Q1:F2)
      SPIN(@N8.2),AT(280,0,20,20),USE(SpinVar1),FROM(Q1:F1)
      SPIN(@S4),AT(280,0,20,20),USE(SpinVar2),FROM('Mr.|Mrs.|Ms.|Dr. ')
      !Assign a numeric value to SpinVar3:
      SPIN(@S4),AT(280,0,20,20),USE(SpinVar3),FROM('Mr.|#1|Mrs.|#2|Ms.|#3|Dr.|#4')
      END
```

## FULL (set full-screen)



### FULL

---

The **FULL** attribute (PROP:FULL) specifies the control expands to occupy the entire size of the WINDOW for any missing AT attribute width or height parameter.

FULL may not be specified for TOOLBAR controls.

**See Also:**

PROP:NoHeight/PROP:NoWidth

## GRAY (set 3-D look background)



### GRAY

---

The **GRAY** attribute (PROP:GRAY) indicates that the WINDOW has a gray background, suitable for use with three-dimensional dialog controls. All controls on a WINDOW with the GRAY attribute are automatically given a three-dimensional appearance. Controls in a TOOLBAR are always automatically given a three-dimensional appearance, without the GRAY attribute.

This attribute is not valid on an APPLICATION structure.

The three-dimensional look may be disabled by SET3DLOOK.

#### Example:

```
!A Window with 3-D controls
Win1 WINDOW,GRAY
END
```

#### See Also:

SET3DLOOK

## GRID (set list grid-line display color)



**GRID**(*rgb*)

**GRID** Specifies list box grid-line display color.

*rgb* A LONG or ULONG integer constant, or constant EQUATE, containing the red, green, and blue components that create the color in the three low-order bytes (bytes 0, 1, and 2), or an EQUATE for a standard Windows color value.

The **GRID** attribute (PROPLIST:GRID) specifies the display color of grid-lines in a COMBO, or LIST control. EQUATEs for Windows' standard colors are contained in the EQUATES.CLW file. Windows automatically finds the closest match to the specified *rgb* color value for the hardware on which the program is run.

### Example:

```
WinOne WINDOW,AT(0,0,400,400)
      LIST,AT(0,34,366,146),FROM(TreeDemo),USE(?Show),HVSCROLL,GRID(COLOR:Red)|
      FORMAT('80L*IT~First Name~*80L~Last Name~16C~Initials~')
END
```

## HLP (set on-line help identifier)



**HLP**(*helpID*)

---

**HLP** Specifies the *helpID* for the APPLICATION, WINDOW, or control.

*helpID* A string constant specifying the key used to access the Help system. This may be either a Help keyword or a "context string."

The **HLP** attribute (PROP:HLP) specifies the *helpID* for the APPLICATION or WINDOW. Help, if available, is automatically displayed by Windows whenever the user presses the F1 key.

If the user presses the F1 key to request help when the APPLICATION window is foremost and no menus are active, the APPLICATION's *helpID* is used to locate the Help text. Otherwise, the library automatically uses the *helpID* of the active menu of uppermost control or window, searching up the hierarchy until an object with that *helpID* is found. The *helpID* of the APPLICATION is at the top of the hierarchy.

The *helpID* may contain a Help keyword or a "context string."

- A Help keyword is a word or phrase displayed in the Help Search dialog. When the user presses the F1 key, if only one topic in the help file specifies this keyword, the help file is opened at that topic; if more than one topic specifies the keyword, the search dialog is opened for the user.
- A "context string" is identified by a leading tilde (~) in the *helpID*, followed by a unique identifier (no spaces allowed) associated with exactly one help topic. When the user presses the F1 key, the help file is opened at the specific topic associated with that "context string." If the tilde is missing, the *helpID* is assumed to be a help keyword.

### Example:

```
!A Window with a help context string:
MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS,HLP('~App')
    MENUBAR
        MENU('&File'),USE(?FileMenu)
            ITEM('&Open...'),USE(?OpenFile),HLP('~OpenFileHelp')
        END
    END
END

!A Window with a help keyword:
Win2 WINDOW,HLP('Window One Help')
    ENTRY(@s30),USE(SomeVariable),HLP('~Entry1Help')      !A help context string
    ENTRY(@s30),USE(SomeVariable),HLP('Control Two Help') !A help keyword
END
```

## HSCROLL, VSCROLL, HVSCROLL (set scroll bars)



**HSCROLL**

**VSCROLL**

**HVSCROLL**

The **HSCROLL**, **VSCROLL**, and **HVSCROLL** attributes place scroll bars on an APPLICATION or WINDOW structure, or a COMBO, LIST, IMAGE, or TEXT control. HSCROLL (PROP:HSCROLL) adds a horizontal scroll bar to the bottom, VSCROLL (PROP:VSCROLL) adds a vertical scroll bar on the right side, and HVSCROLL adds both.

The HSCROLL attribute is also available for a SHEET control. This specifies the TABs display all on one row instead of multiple rows, no matter how many TABs there are. Right and left (or up and down) scroll buttons appear at both ends of the TABs to allow the user to scroll through all the TABs. PROP:BrokenTabs may be set to FALSE to turn off the "broken tab" visual effect.

The vertical scroll bar allows a mouse to scroll the display up or down. The horizontal scroll bar allows a mouse to scroll the control's display left or right. The scroll bars appear whenever any scrollable portion of the control lies outside the visible area on screen.

When you place VSCROLL on a LIST with the IMM attribute, the vertical scroll bar is always present, even when the list is not full. When the user clicks on the scroll bar, events are generated, but the list contents do not move (executable code should perform this task). You can interrogate the PROP:VscrollPos property to determine the scroll thumb's position in the range 0 (top) to 100 (bottom).

HSCROLL, VSCROLL, and HVSCROLL are also valid on a SPIN control and specify optional spin button arrangements from the default (one above the other, pointing up and down). HSCROLL places the spin buttons side by side pointing left and right, VSCROLL places the spin buttons one above the other pointing left and right, and HVSCROLL places the spin buttons side by side, pointing up and down.

### Example:

```
!A Window with a horizontal scroll bar:
Win1 WINDOW,HSCROLL,RESIZE
    END
```

```
!A Window with a vertical scroll bar:
Win2 WINDOW,VSCROLL,RESIZE
    END
```

```
!A Window with both scroll bars:
Win2 WINDOW,HVSCROLL,RESIZE
    END
```

## ICON (set icon)



**ICON**( *file* )

---

**ICON** Specifies an icon to display for the APPLICATION, WINDOW, or control.

*file* A string constant containing the name of the image file (.ICO, .GIF, .JPG, .PCX) or an EQUATE for the Windows standard icon to display. The image file is automatically linked into the .EXE as a resource.

The **ICON** attribute (PROP:ICON) specifies an icon to display for the APPLICATION, WINDOW, or control.

On an APPLICATION or WINDOW, ICON also specifies the presence of a minimize control, and must name an .ICO file as its *file* parameter. The minimize control appears in the top right corner of the window as an underscore. When the user clicks the mouse on it, the window shrinks to an icon without halting its execution. When an APPLICATION or non-MDI WINDOW is minimized, the icon *file* is displayed in the operating system's desktop; when a WINDOW with the MDI attribute is minimized, the icon *file* is displayed in the APPLICATION's client area.

On a BUTTON, RADIO, or CHECK control, ICON specifies an image to display as the control. The image *file* displays on the button face of the control. For RADIO and CHECK controls, the ICON attribute creates "latched" pushbuttons, where the control button appears "down" when on and "up" when off.

EQUATE statements for the Windows-standard icons are contained in the EQUATES.CLW file. The following list is a representative sample of these (see EQUATES.CLW for the complete list):

ICON:None	No icon
ICON:Application	
ICON:Question	?
ICON:Exclamation	!
ICON:Asterisk	*
ICON:VCRtop	>>
ICON:VCRrewind	<<
ICON:VCRback	<
ICON:VCRplay	>
ICON:VCRfastforward	>>
ICON:VCRbottom	<<
ICON:VCRlocate	?

If the name of the icon file to assign to PROP:Icon has a number in square brackets appended to its end (IconFile.DLL[1]), this indicates the file contains multiple icons and the number specifies which to assign (using zero-based numbering). If the name of the icon file has a tilde (~) prepended to it (~IconFile.ICO), this indicates the file has been linked into the project as a resource and is not on disk.



**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL,ICON('MyIcon.ICO')
    OPTION('Option'),USE(OptVar)
        RADIO('Radio 1'),AT(120,0,20,20),USE(?R1),ICON('Radio1.ICO')
        RADIO('Radio 2'),AT(140,0,20,20),USE(?R2),ICON('Radio2.GIF')
    END
    CHECK('&A'),AT(0,120,20,20),USE(?C7),ICON(ICON:Asterisk)
    BUTTON('&1'),AT(120,0,20,20),USE(?B7),ICON(ICON:Question)
END
```

**See Also:**

ICONIZE

MAX

MAXIMIZE

IMM

## ICONIZE (set window open as icon)



### ICONIZE

---

The **ICONIZE** attribute (PROP:ICONIZE) specifies the APPLICATION or WINDOW is opened minimized as the icon specified by the ICON attribute. When an APPLICATION or non-MDI WINDOW is minimized, the icon *file* is displayed in the operating system's desktop; when a WINDOW with the MDI attribute is minimized, the icon *file* is displayed in the APPLICATION.

With the SYSTEM built-in variable as the property assignment *target*, PROP:ICONIZE returns 1 if the Windows PIF setting for the application is set to open the application iconized.

#### Example:

```
!A Window with a minimize button, opened as the icon:
Win2 WINDOW,ICON('MyIcon.ICO'),ICONIZE
END
```

#### See Also:

ICON

IMM

## IMM (set immediate event notification)



### IMM

The **IMM** attribute (PROP:IMM) specifies immediate event generation.

### Window Usage

On a WINDOW or APPLICATION the IMM attribute specifies immediate event generation whenever the user moves or resizes the window. It generates one the following events before the action is executed:

- EVENT:Move
- EVENT:Size
- EVENT:Restore
- EVENT:Maximize
- EVENT:Iconize

If the code that handles these events executes a CYCLE statement, the action is not performed. This allows you to prevent the user from moving or resizing the window. Once the action has been performed, one or more of the following events are generated:

- EVENT:Moved
- EVENT:Sized
- EVENT:Restored
- EVENT:Maximized
- EVENT:Iconized

Multiple post-action events generate because some actions have multiple results. For example, if the user CLICKS on the maximize button, EVENT:Maximize generates. If there is no CYCLE statement executed for this event, the action is performed, then EVENT:Maximized, EVENT:Moved, and EVENT:Sized all generate. This occurs because the window was maximized, which also moves and resizes it at the same time.

### Control Usage

On a REGION control, the IMM attribute generates an event whenever the mouse enters (EVENT:MouseIn), moves within (EVENT:MouseMove), or leaves (EVENT:MouseOut) the area specified by the REGION's AT attribute. The exact position of the mouse can be determined by the MOUSEX and MOUSEY procedures.

On a BUTTON control, the IMM attribute indicates the BUTTON generates EVENT:Accepted when the left mouse button is pressed down on the control, instead of on its release. EVENT:Accepted repeatedly generates as long as the user keeps the mouse button pressed. The DELAY and REPEAT attributes on the BUTTON can change the rate the events generate.

The IMM attribute specifies immediate event generation each time the user presses any keystroke on a LIST or COMBO control, usually requiring the QUEUE to be re-filled. This means all keys are implicitly ALRTed for the control. When the user presses a character, EVENT:NewSelection generates.

For an ENTRY or SPIN control, EVENT:NewSelection generates whenever the control's contents or the cursor position changes. To do something only when the content changes, you must save the previous contents then compare against the current contents (probably using PROP:ScreenText).

For a SHEET control, EVENT:NewSelection generates whenever the user clicks on a TAB (even when that TAB is already the currently selected TAB). This can be useful when there are multiple SHEET controls on the same window.

**Example:**

```
Win2 WINDOW('Some Window'),AT(58,11,174,166),MDI,DOUBLE,MAX,IMM
    LIST,AT(109,48,50,50),USE(?List),FROM('Que'),IMM
    BUTTON('&Ok'),AT(111,108,,),USE(?Ok)
    BUTTON('&Cancel'),AT(111,130,,),USE(?Cancel)
END
CODE
OPEN(Win2)
ACCEPT
CASE EVENT()
OF EVENT:Move                !Prevent user from moving window
    CYCLE
OF EVENT:Maximized           !When Maximized
    ?List{PROP:Height} = 100 ! resize the list
OF EVENT:Restored            !When Restored
    ?List{PROP:Height} = 50  ! resize the list
END
END
```

**See Also:**

RESIZE

MAX

ICON

DELAY

REPEAT

## INS, OVR (set typing mode)



**INS**

**OVR**

---

The **INS** and **OVR** attributes (PROP:INS and PROP:OVR) specify the typing mode for an ENTRY or TEXT control when the MASK attribute is present on the window. INS specifies insert mode while OVR specifies overwrite mode. These modes are only active on windows with the MASK attribute.

## JOIN (set joined TAB scroll buttons)



### JOIN

---

The **JOIN** attribute (PROP:JOIN) on a SHEET control specifies the TABs display all on one row instead of multiple rows, no matter how many TABs there are. Right and left (or up and down) scroll buttons appear together at the right end (or top) of the TABs to allow the user to scroll through all the TABs.

## KEY (set execution keycode)



**KEY**(keycode)

**KEY** Specifies a "hot" key for the control

*keycode* A Clarion Keycode or keycode equate label.

The **KEY** attribute (PROP:KEY) specifies a "hot" key to immediately give focus to the control or execute the control's associated action.

The following controls receive focus: COMBO, CUSTOM, ENTRY, GROUP, LIST, OPTION, PROMPT, SPIN, TEXT.

The following controls both receive focus and immediately execute: BUTTON, CHECK, CUSTOM, RADIO, MENU, ITEM.

### Example:

```
MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS
MENUBAR
  MENU('&Edit'),USE(?EditMenu)
  ITEM('Cu&t'),USE(?CutText),KEY(CtrlX),STD(STD:Cut),DISABLE
  ITEM('&Copy'),USE(?CopyText),KEY(CtrlC),STD(STD:Copy),DISABLE
  ITEM('&Paste'),USE(?PasteText),KEY(CtrlV),STD(STD:Paste),DISABLE
END
END
TOOLBAR
  COMBO(@S8),AT(120,120,20,20),USE(?C1),FROM(Q1:F2),KEY(F1Key)
  LIST,AT(120,0,20,20),USE(?L1),FROM(Que1),KEY(F2Key)
  SPIN(@N8.2),AT(280,0,20,20),USE(SpinVar1),FROM(Q),KEY(F3Key)
  TEXT,AT(20,0,40,40),USE(E2),KEY(F4Key)
  PROMPT('Enter &Data in E2:'),AT(10,200,20,20),USE(?P2),KEY(F5Key)
  ENTRY(@S8),AT(100,200,20,20),USE(E2),KEY(F6Key)
  BUTTON('&1'),AT(120,0,20,20),USE(?B7),KEY(F7Key)
  CHECK('&A'),AT(0,120,20,20),USE(?C7),KEY(F8Key)
  OPTION('Option'),USE(OptVar),KEY(F9Key)
  RADIO('Radio 1'),AT(120,0,20,20),USE(?R1),KEY(F10Key)
  RADIO('Radio 2'),AT(140,0,20,20),USE(?R2),KEY(F11Key)
END
END
END
```

## LANDSCAPE (set page orientation)

### LANDSCAPE

---

The **LANDSCAPE** attribute (PROP:LANDSCAPE) on a REPORT indicates the report is to print in landscape mode by default. If the LANDSCAPE attribute is omitted, printing defaults to portrait mode.

**Example:**

```
Report REPORT,PRE('Rpt'),LANDSCAPE      !Defaults to landscape mode
      !Report structure declarations
END
```



## LAYOUT (set window orientation)



**LAYOUT** ( *style* )

*style* A byte value that designates whether the orientation of window controls and field sequence is set to Default, Left to Right, or Right to Left.

The **LAYOUT** attribute (PROP:LAYOUT) on a WINDOW or APPLICATION indicates the orientation of window controls and field sequence. A style of (1) essentially "flips" the window controls' display as a mirror image of the layout specified in the Window Formatter. Default field navigation moves from right to left.

A style of (0) maintains the original layout specified in the Window Formatter. Default field navigation moves from left to right.

Setting the LAYOUT in the Application Frame will cascade its setting to all child window that have the default setting active (which is no LAYOUT attribute placed on the window).

### Note:

The justification set in the format string for a list box column will always override the mirroring specified by the LAYOUT attribute, (i.e., "left" means "left" rather than "near" and "right" means "right" rather than "far"). Column order, origin coordinates and direction always follow the LAYOUT setting.

### Example:

```
AppFrame APPLICATION('Example Application - BROWSES (ABC Templates)'), |
    AT(,,548,344),FONT('MS Sans Serif',8,,),LAYOUT(1), |
    CENTER,ICON('LOG1.ICO'),STATUS(-1,80,120,45),SYSTEM,MAX,RESIZE
!Sets all windows in the application to Right-to-Left style
```

## LEFT, RIGHT, ABOVE, BELOW (set TAB position)



**LEFT**( [*width*] )

**RIGHT**( [*width*] )

**ABOVE**( [*width*] )

**BELOW**( [*width*] )

---

*width*            An integer constant specifying the width of the TAB controls in dialog units. For the LEFT attribute, this is PROP:LeftOffset (equivalent to {PROP:LEFT,2}). For RIGHT, this is PROP:RightOffset (equivalent to {PROP:RIGHT,2}). For ABOVE, this is PROP:AboveSize (equivalent to {PROP:ABOVE,2}). For BELOW, this is PROP:BelowSize (equivalent to {PROP:BELOW,2}).

The **LEFT**, **RIGHT**, **ABOVE**, and **BELOW** attributes of a SHEET control specify the position of the TAB controls. LEFT (PROP:LEFT) specifies the TABs appear to the left of the sheet, RIGHT (PROP:RIGHT) specifies the TABs appear to the right of the sheet, ABOVE (PROP:ABOVE) specifies the TABs appear at the top of the sheet (the default position), and BELOW (PROP:BELOW) specifies the TABs appear at the bottom of the sheet.

The *width* parameter allows you to set the size of the TAB controls. The text that appears on the TAB is always horizontal unless you specify the UP or DOWN attribute.

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
  SHEET,AT(0,0,320,175),USE(SelectedTab),BELOW    !Place Tabs below sheet
  TAB('Tab One'),USE(?TabOne)
  OPTION('Option 1'),USE(OptVar1),KEY(F10Key),HLP('Option1Help')
  RADIO('Radio 1'),AT(20,0,20,20),USE(?R1)
  RADIO('Radio 2'),AT(40,0,20,20),USE(?R2)
  END
  PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P1)
  ENTRY(@S8),AT(100,140,32,20),USE(E1)
  PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P2)
  ENTRY(@S8),AT(100,240,32,20),USE(E2)
  END
  TAB('Tab Two'),USE(?TabTwo)
  PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P3)
  ENTRY(@S8),AT(100,140,32,20),USE(E3)
  PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P4)
  ENTRY(@S8),AT(100,240,32,20),USE(E4)
  END
  END
  BUTTON('Ok'),AT(100,180,20,20),USE(?Ok)
  BUTTON('Cancel'),AT(200,180,20,20),USE(?Cancel)
  END
```

## LEFT, RIGHT, CENTER, DECIMAL (set justification)

**LEFT**( [*offset*] )

**RIGHT**( [*offset*] )

**CENTER**( [*offset*] )

**DECIMAL**( [*offset*] )

---

*offset*            An integer constant specifying the amount of offset from the justification point. This is in dialog units (unless overridden by the THOUS, MM, or POINTS attribute on a REPORT). For the LEFT attribute, this is PROP:LeftOffset (equivalent to {PROP:LEFT,2}). For RIGHT, this is PROP:RightOffset (equivalent to {PROP:RIGHT,2}). For CENTER, this is PROP:CenterOffset (equivalent to {PROP:CENTER,2}). For DECIMAL, this is PROP:DecimalOffset (equivalent to {PROP:DECIMAL,2}).

The **LEFT**, **RIGHT**, **CENTER**, and **DECIMAL** attributes specify the justification of data printed. LEFT (PROP:LEFT) specifies left justification, RIGHT (PROP:RIGHT) specifies right justification, CENTER (PROP:CENTER) specifies centered text, and DECIMAL (PROP:DECIMAL) specifies numeric data aligned on the decimal point. These attributes are valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

On the LEFT attribute, *offset* specifies the amount of indentation from the left. On the RIGHT attribute, *offset* specifies the amount of indentation from the right. The *offset* parameter on the CENTER attribute specifies an offset value from the center (negative = left offset). On the DECIMAL attribute, *offset* specifies the decimal point's indentation from the right.

### Window Usage

---

The following controls allow LEFT or RIGHT only (without an *offset* parameter):  
BUTTON, CHECK, RADIO.

The following controls allow LEFT(*offset*), RIGHT(*offset*), CENTER(*offset*), or DECIMAL(*offset*):  
COMBO, ENTRY, LIST, SPIN, STRING.

The TEXT control allows LEFT, RIGHT, and CENTER (without an *offset* parameter).

### Report Usage

---

The following controls allow LEFT or RIGHT only (without an *offset* parameter):  
CHECK, GROUP, OPTION, RADIO.

The following controls allow LEFT(*offset*), RIGHT(*offset*), CENTER(*offset*), or DECIMAL(*offset*):  
LIST, STRING.

The TEXT control allows LEFT, RIGHT, and CENTER (without an *offset* parameter).

**Example:**

```
Rpt    REPORT,AT(1000,1000,6500,9000),THOUS
Detail DETAIL,AT(0,0,6500,1000)
      LIST,AT(0,20,100,146),FORMAT('800L'),FROM(Fname),USE(?Show2),LEFT(100)
      END
      END

WinOne WINDOW,AT(0,0,160,400)
      COMBO(@S8),AT(120,120,20,20),USE(?C1),FROM(Q1:F2),RIGHT(4)
      LIST,AT(120,0,20,20),USE(?L1),FROM(Que1),CENTER
      SPIN(@N8.2),AT(280,0,20,20),USE(SpinVar1),FROM(Q),DECIMAL(8)
      TEXT,AT(20,0,40,40),USE(E2),LEFT(8)
      ENTRY(@S8),AT(100,200,20,20),USE(E2),LEFT(4)
      CHECK('&A'),AT(0,120,20,20),USE(?C7),LEFT
      OPTION('Option'),USE(OptVar)
      RADIO('Radio 1'),AT(120,0,20,20),USE(?R1),LEFT
      RADIO('Radio 2'),AT(140,0,20,20),USE(?R2),RIGHT
      END
      END
```

## LINEWIDTH (set line thickness)

**LINEWIDTH**( *width* )

**LINEWIDTH** Specifies the LINE control and BOX and ELLIPSE border thickness.

*width* A positive integer constant specifying the thickness in pixels (in WINDOW structures). For REPORT structures, the thickness is based on the report's unit of measurement.

The **LINEWIDTH** attribute (PROP:LINEWIDTH) specifies the thickness of the LINE control and the BOX and ELLIPSE controls' border. This attribute is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

### Example:

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
Detail  DETAIL,AT(0,0,6500,1000),USE(?DetailOne)
        LINE,AT(105,78,-49,0),USE(?Line1),LINEWIDTH(10)!10 thous of an inch
        BOX,AT(182,27,50,50),USE(?Box1),LINEWIDTH(3)  !Box with 3 thous inch border
        STRING(@N$11.2),AT(6000,1500,500,500),USE(Pre:F1)
        END
    END

window WINDOW('Caption'),AT(,,260,100),GRAY
        LINE,AT(105,78,-49,0),USE(?Line1),LINEWIDTH(3)  !3 pixel line
        BOX,AT(182,27,50,50),USE(?Box1),LINEWIDTH(3)    !Box with 3 pixel border
    END
```

## LINK (create OLE control link to object from file)



**LINK**( *filename* )

---

**LINK** Specifies creating a link to an object for the OLE control from a data file specific to an OLE server application.

*filename* A string constant containing the name of the file.

The **LINK** attribute (PROP:LINK, write-only) specifies creating a link to an object for the OLE control from a data file specific to an OLE server application. The *filename* parameter syntax must be a fully-qualified pathname, unless the file exists in the same directory as the OLE Controller application.

**Example:**

```
WinOne WINDOW,AT(0,0,200,200)
  OLE,AT(10,10,160,100),USE(?OLEObject),LINK('Book1.XLS')  !Excel Spreadsheet
  MENUBAR
    MENU('&Clarion App')
      ITEM('&Deactivate Object'),USE(?DeactOLE)
    END
  END
END
END
END
```

## MASK (set pattern editing data entry)



### MASK

The **MASK** attribute (PROP:MASK) specifies pattern input editing mode for all controls in the window (when placed on the WINDOW statement). Toggling the value of PROP:MASK for a window only affects controls created after—it does not affect any existing controls.

Pattern input editing mode means that, as the user types in data, each character is automatically validated against the control's picture for proper input (numbers only in numeric pictures, etc.). This forces the user to enter data in the format specified by the control's display picture.

If MASK is omitted, Windows free-input is allowed in the controls. Free-input means the user's data is formatted to the control's picture only after entry. This allows users to enter data as they choose and it is automatically formatted to the control's picture after entry. If the user types in data in a format different from the control's picture, the libraries attempt to determine the format the user used, and convert the data to the control's display picture. For example, if the user types "January 1, 1995" into a control with a display picture of @D1, the runtime library formats the user's input to "1/1/95." This action occurs only after the user completes data entry and moves to another control. If the runtime library cannot determine what format the user used, it will not update the USE variable. It then beeps and leaves the user on the same control with the data they entered, to allow them to try again.

#### Example:

```
!A Window with pattern input editing enabled
Win2 WINDOW, MASK
END

!Window with controls with pattern input editing enabled
Win2 WINDOW, MASK
    COMBO(@P(###) ###-####P), AT(120,120,20,20), USE(Phone), FROM(Q1:F2)
    SPIN(@N8.2), AT(280,0,20,20), USE(SpinVar1), FROM(Q)
    ENTRY(@D2), AT(100,200,20,20), USE(DateField)
END
```

## MAX (set maximize control or total maximum)

MAX( [ *variable* ] )

---

**MAX** Specifies a maximize control on an APPLICATION or WINDOW, or calculates the maximum value a REPORT STRING control's USE variable has contained so far.

*variable* The label of a numeric variable to receive the intermediate values calculated for the MAX (valid only in a REPORT). This allows you to create totals on other totals. The value in the *variable* is internally updated by the print engine, so it is only useful for use by other "totaling" controls within the REPORT structure.

The **MAX** attribute (PROP:MAX) specifies a maximize control on an APPLICATION or WINDOW, or calculates the maximum value a REPORT STRING control's USE variable has contained so far. This attribute is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

### Window Usage

---

The maximize control appears in the top right corner of the window as a box containing either an upward pointing triangle. When the user clicks the mouse on it, an APPLICATION or non-MDI WINDOW expands to occupy the full screen, an MDI WINDOW expands to occupy the entire APPLICATION. Once expanded, the maximize control appears as an upward pointing triangle above a downward pointing triangle. Click the mouse on it again, and the window returns to its previous size and the maximize control appears as an upward pointing triangle.

### Report Usage

---

The MAX attribute specifies printing the maximum value the STRING control's USE variable has contained so far. Unless the TALLY attribute is present, the result is calculated as follows:

- A MAX field in a DETAIL structure is evaluated each time the DETAIL structure containing the control PRINTs. This provides a "running" maximum value.
- A MAX field in a group FOOTER structure is evaluated each time any DETAIL structure in the BREAK structure containing the control PRINTs. This provides the maximum value of the variable in the group.
- A MAX field in a page FOOTER structure is evaluated each time any DETAIL structure in any BREAK structure PRINTs. This is the maximum value of the variable in the page (or report to date).
- A MAX field in a HEADER is meaningless, since no DETAIL structures will have been printed at the time the HEADER is printed.

The MAX value is reset only if the RESET or PAGE attribute is also specified.



**Example:**

!A Window with a maximize button:

```
Win2 WINDOW,MAX
```

```
END
```

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
```

```
Break1 BREAK(LocalVar),USE(?BreakOne)
```

```
Break2 BREAK(Pre:Key1),USE(?BreakTwo)
```

```
Detail DETAIL,AT(0,0,6500,1000),USE(?DetailOne)
```

```
    STRING(@N$11.2),AT(6000,1500,500,500),USE(Pre:F1)
```

```
    END
```

```
    FOOTER,AT(0,0,6500,1000),USE(?BreakOneGroupFoot)
```

```
        STRING('Group Maximum: '),AT(5500,500)
```

```
        STRING(@N$11.2),AT(6000,500),USE(Pre:F1),MAX(LocalVar),RESET(Break2)
```

```
    END
```

```
END
```

```
FOOTER,AT(0,0,6500,1000),USE(?BreakOneGroupFoot)
```

```
    STRING('Grand Maximum: '),AT(5500,500)
```

```
    STRING(@N$11.2),AT(6000,500),USE(LocalVar),MAX,TALLY(?BreakTwo)
```

```
END
```

```
END
```

```
END
```

**See Also:**

ICONIZE

ICON

MAXIMIZE

IMM

TALLY

RESET

PAGE

## MAXIMIZE (set window open maximized)



### MAXIMIZE

---

The **MAXIMIZE** attribute (PROP:MAXIMIZE) specifies the APPLICATION or WINDOW is opened maximized. When maximized, an APPLICATION or non-MDI WINDOW expands to occupy the full screen, and an MDI WINDOW expands to occupy the entire APPLICATION.

With the SYSTEM built-in variable as the property assignment *target*, PROP:MAXIMIZE returns 1 if the Windows PIF setting for the application is set to open the application maximized.

#### Example:

```
!A Window with a maximize button, opened maximized:
Win2 WINDOW,MAX,MAXIMIZE
END
```

#### See Also:

MAX

IMM

## MDI (set MDI child window)



### MDI

The **MDI** attribute (PROP:MDI, read-only) specifies a WINDOW that acts as a "child" window to an APPLICATION. MDI windows are clipped to the APPLICATION frame—they display only in the APPLICATION's client area. MDI windows automatically move when the APPLICATION frame is moved, and are totally concealed by minimizing the APPLICATION. An MDI WINDOW cannot open until there is an active APPLICATION.

### Modeless Windows

MDI "child" windows are modeless; the user may change to the top window of another execution thread, within the same application or any other application running in Windows, at any time. An MDI "child" window must not be on the same execution thread as the APPLICATION. Therefore, any MDI "child" window called directly from the APPLICATION must be in a separate procedure so the START procedure can be used to begin a new execution thread. Once started, multiple MDI "child" windows may be called in the new thread.

### Application Modal Windows

A non-MDI WINDOW operates independently of any previously opened APPLICATION. It will, however, disable an APPLICATION if it or any of its MDI "child" windows are on the same execution thread as the non-MDI window. This makes a non-MDI window opened in an MDI thread an "application modal" window which effectively disables the application while the user has the window open (unless it is opened in its own separate execution thread). It does not, however, prevent the user from changing to another application running under Windows. An MDI window may not be opened on the same thread as an already open non-MDI window.

#### Example:

```
Win2 WINDOW,MDI      !An MDI child Window
END
```

#### See Also:

MODAL

THREAD

## MIN (set total minimum)

**MIN**( [ *variable* ] )

---

**MIN**                Calculates the minimum value the STRING control's USE variable has contained so far.

*variable*            The label of a numeric variable to receive the intermediate values calculated for the MIN. This allows you to create totals on other totals. The value in the *variable* is internally updated by the print engine, so it is only useful for use within the REPORT structure.

The **MIN** attribute (PROP:MIN) specifies printing the minimum value the STRING control's USE variable has contained so far. Unless the TALLY attribute is present, the result is calculated as follows:

- A MIN field in a DETAIL structure is evaluated each time the DETAIL structure containing the control PRINTs. This provides a "running" minimum value.
- A MIN field in a group FOOTER structure is evaluated each time any DETAIL structure in the BREAK structure containing the control PRINTs. This provides the minimum value of the variable in the group.
- A MIN field in a page FOOTER structure is evaluated each time any DETAIL structure in any BREAK structure PRINTs. This is the minimum value of the variable in the page (or report to date).
- A MIN field in a HEADER is meaningless, since no DETAIL structures will have been printed at the time the HEADER is printed.

The MIN value is reset only if the RESET or PAGE attribute is also specified.

### Example:

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
Break1  BREAK(LocalVar),USE(?BreakOne)
Break2  BREAK(Pre:Key1),USE(?BreakTwo)
Detail  DETAIL,AT(0,0,6500,1000),USE(?DetailOne)
        STRING(@N$11.2),AT(6000,1500,500,500),USE(Pre:F1)
        END
        FOOTER,AT(0,0,6500,1000),USE(?BreakOneGroupFoot)
        STRING('Group Minimum: '),AT(5500,500)
        STRING(@N$11.2),AT(6000,500),USE(Pre:F1),MIN(LocalVar),RESET(Break2)
        END
        END
        FOOTER,AT(0,0,6500,1000),USE(?BreakOneGroupFoot)
        STRING('Grand Minimum: '),AT(5500,500)
        STRING(@N$11.2),AT(6000,500),USE(LocalVar),MIN,TALLY(?BreakTwo)
        END
        END
        END
```

## MODAL (set system modal window)



### MODAL

---

MODAL has no effect for 32-bit applications, and has been deprecated in this release. The Microsoft Win32 API does not support system modal windows.

### Application Modal Windows

---

A WINDOW without the MODAL attribute, may be either "application-modal" or "modeless." An application-modal window is a non-MDI window opened as the top window of an MDI execution thread. An application-modal window restricts the user from moving to another execution thread in the same application, but does not restrict them from changing to another Windows program.

### Modeless Windows

---

A modeless window is an MDI "child" WINDOW (with the MDI attribute) without the MODAL attribute. From a modeless window, The top window on other execution threads may be selected by the mouse, keyboard, or menu commands. If so, the other window takes focus and becomes uppermost on the video display. Any window not on the top of its execution thread may not be selected to receive focus, even from a modeless window.

#### Example:

```
Win2 WINDOW,MODAL    !A system-modal Window
END
```

#### See Also:

MDI

THREAD

## MSG (set status bar message)



**MSG**( *text* )

---

**MSG** Specifies *text* to display in the status bar.

*text* A string constant containing the message to display in the status bar.

The **MSG** attribute (PROP:MSG) specifies *text* to display in the first zone of the status bar.

On a control declaration, MSG specifies the *text* to display when the control has focus. If the control has non-persistent focus (has the SKIP attribute, or is placed in a TOOLBAR or a window with the TOOLBOX attribute) the *text* displays whenever the mouse cursor is positioned over the control.

On an APPLICATION or WINDOW structure, MSG specifies *text* to display in the first zone of the status bar when the control with focus has no MSG attribute of its own.

### Example:

```
MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS
    MENUBAR
        MENU('&File'),USE(?FileMenu)
            ITEM('&Open...'),USE(?OpenFile),MSG('Open a file')
            ITEM('&Close'),USE(?CloseFile),DISABLE,MSG('Close the open file')
            ITEM(),SEPARATOR
            ITEM('E&xit'),USE(?MainExit),MSG('Exit the program')
        END
    END
END

WinOne WINDOW,AT(0,0,160,400),MSG('Enter Data')      !Default MSG to use
    COMBO(@S8),AT(120,120,20,20),USE(?C1),FROM(Q1:F2),MSG('Enter or Select')
    TEXT,AT(20,0,40,40),USE(E2)                      !Default MSG used
    ENTRY(@S8),AT(100,200,20,20),USE(E2)             !Default MSG used
    CHECK('&A'),AT(0,120,20,20),USE(?C7),MSG('On or Off')
    OPTION('Option 1'),USE(OptVar),MSG('Pick One or Two')
    RADIO('Radio 1'),AT(120,0,20,20),USE(?R1)
    RADIO('Radio 2'),AT(140,0,20,20),USE(?R2)
END
END
```

### See Also:

STATUS

## NOBAR (set no highlight bar)



### NOBAR

---

The **NOBAR** attribute (PROP:NOBAR) specifies the currently selected element in the LIST is only highlighted when the LIST control has focus.

## NOCASE (case insensitive report BREAK)

### NOCASE

The **NOCASE** attribute (PROP:NOCASE) of a BREAK structure in a REPORT declaration makes the comparison for detecting a changed value (indicating a group break) insensitive to the ASCII upper/lower case sorting convention. All characters in the break field and the saved comparison value are converted to upper case before the comparison. This case conversion has no effect on the case of the stored data. The NOCASE attribute has no effect on non-alphabetic characters.

#### Example:

```
Report REPORT
    BREAK(BreakVariable),NOCASE !Case insensitive group break
    HEADER
        STRING(@n4),USE(BreakVariable)
    END
Detail    DETAIL
    STRING(@n4),USE(SomeField)
    END
END
END
```

#### See Also:

BREAK



## NOMERGE (set merging behavior)



### NOMERGE

The **NOMERGE** attribute (PROP:NOMERGE) indicates that the MENUBAR or TOOLBAR on a WINDOW should not merge with the Global menu or toolbar.

The NOMERGE attribute on an APPLICATION's MENUBAR indicates that the menu is local and to be displayed only when no MDI "child" windows are open and that there is no Global menu. The NOMERGE attribute on an APPLICATION's TOOLBAR indicates that the tools are local and display only when no MDI "child" windows are open--there are no Global tools.

Without the NOMERGE attribute, an MDI WINDOW's menu and toolbar are automatically merged with the global menu and toolbar, and then displayed in the APPLICATION menu and toolbar. When NOMERGE is specified, the WINDOW's menu and toolbar overwrite the Global menu and toolbar. The menu and toolbar displayed when the WINDOW has focus are only the WINDOW's own menu and toolbar. However, they are still displayed on the APPLICATION.

A MENUBAR or TOOLBAR specified in a non-MDI WINDOW is never merged with the Global menu or toolbar--they appear in the WINDOW.

#### Example:

**!An MDI application frame window with local-only menu and toolbar:**

```
MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS
    MENUBAR,NOMERGE
        ITEM('E&xit'),USE(?MainExit)
    END
    TOOLBAR,NOMERGE
        BUTTON('Exit'),USE(?MainExitButton)
    END
END
```

**!MDI window with its own menu and toolbar, overwriting the application's:**

```
MDIChild WINDOW('Dialog Window'),MDI,SYSTEM,MAX,STATUS
    MENUBAR,NOMERGE
        MENU('Edit'),USE(?EditMenu)
            ITEM('Cu&t'),USE(?CutText),KEY(CtrlX),STD(STD:Cut)
            ITEM('Copy'),USE(?CopyText),KEY(CtrlC),STD(STD:Copy)
            ITEM('Paste'),USE(?PasteText),KEY(CtrlV),STD(STD:Paste)
        END
    END
    TOOLBAR,NOMERGE
        BUTTON('Cut'),USE(?CutButton),STD(STD:Cut)
        BUTTON('Copy'),USE(?CopyButton),STD(STD:Copy)
        BUTTON('Paste'),USE(?PasteButton),STD(STD:Paste)
    END
    TEXT,HVSCROLL,USE(Pre:Field),MSG('Enter some text here')
    BUTTON('&OK'),USE(?Exit),DEFAULT
END
```

#### See Also:

MENUBAR

TOOLBAR

## NOSHEET (set "floating" TABs)



### NOSHEET

---

The **NOSHEET** attribute (PROP:NOSHEET) on a SHEET control specifies the TABs display without a visible sheet to contain the controls. This creates a "floating tab" effect.

## OPEN (open OLE control object from file)



**OPEN**( *object* )

**OPEN** Specifies opening a saved object for the OLE control from an OLE Compound Storage file.

*object* A string constant containing the name of the OLE Compound Storage file and the object within it to open.

The **OPEN** attribute (PROP:OPEN, write-only) specifies opening a saved *object* for the OLE control from an OLE Compound Storage file. When the object is opened, the saved version of the container properties are reloaded, so properties do not need to be specified on an object opened. The *object* parameter syntax must take the form: *Filename\!ObjectName*.

**Example:**

```
WinOne WINDOW,AT(0,0,200,200)
      OLE,AT(10,10,160,100),USE(?OLEObject),OPEN('SavFile.OLE\!MyObject')
      MENUBAR
      MENU('&Clarion App')
      ITEM('&Deactivate Object'),USE(?DeactOLE)
      END
    END
  END
END
```

## PAGEAFTER (set page break after)

PAGEAFTER( [*newpage*] )

**PAGEAFTER** Specifies the structure is printed, then initiates page overflow.

*newpage* An integer constant or constant expression that specifies the page number to print on the next page (PROP:PageAfterNum, equivalent to {PROP:PageAfter,2}). If zero (0) or omitted, forced page overflow does not occur. If negative one (-1) , the current page number increments during page overflow.

The **PAGEAFTER** attribute (PROP:PAGEAFTER) specifies that the DETAIL, or group HEADER or FOOTER structure (contained within a BREAK structure), initiates page overflow after it is printed. This means that the print structure on which the PAGEAFTER attribute is present is printed, followed by the page FOOTER, and then the FORM and page HEADER.

The *newpage* parameter, if present, resets automatic page numbering at the number specified.

**Example:**

```
CustRpt  REPORT
        HEADER
        !structure elements
        END
Break1   BREAK(SomeVariable)
        HEADER
        !structure elements
        END
CustDetail DETAIL
        !structure elements
        END
        FOOTER, PAGEAFTER(-1)      !Group Footer, initiates page overflow
        !structure elements
        END
        END
        FOOTER
        !structure elements
        END
        END
```

**See Also:** PROP:NextPageNo

## PAGEBEFORE (set page break first)

PAGEBEFORE( [ *newpage* ] )

**PAGEBEFORE** Specifies the structure is printed on a new page, after page overflow.

*newpage* An integer constant or constant expression that specifies the page number to print on the new page (PROP:PageBeforeNum, equivalent to {PROP:PageBefore,2}). If zero (0) or omitted, forced page overflow does not occur. If negative one (-1), the current page number increments during page overflow.

The **PAGEBEFORE** attribute (PROP:PAGEBEFORE) specifies that the DETAIL, or group HEADER or FOOTER structure (contained within a BREAK structure), is printed on a new page, after page overflow. This means that first, the page FOOTER is printed, then the FORM and page HEADER. The print structure on which the PAGEBEFORE attribute is present is printed only after these page overflow actions are complete.

The *newpage* parameter, if present, resets automatic page numbering at the number specified.

### Example:

```
CustRpt REPORT
  HEADER
    !structure elements
  END
Break1    BREAK(SomeVariable)
          HEADER,PAGEBEFORE(-1)    !Group Header, initiates page overflow
          !structure elements
          END
CustDetail DETAIL
          !structure elements
          END
          FOOTER
          !structure elements
          END
          END
          FOOTER
          !structure elements
          END
END
```

**See Also:** PROP:NextPageNo

## PAGENO (set page number print)

PAGENO( [ *variable* ] )

---

<b>PAGENO</b>	Calculates the current page number contained in the STRING control's USE variable.
<i>variable</i>	The label of a numeric variable to receive the current page number. This allows you to create totals on other totals. The value in the <i>variable</i> is internally updated by the print engine, so it is only useful for use within the REPORT structure.

The **PAGENO** attribute (PROP:PAGENO) specifies the STRING control prints the current page number.

**See Also:** PROP:NextPageNo

## PAPER (set report paper size)

**PAPER**( [*type*] [,*width*] [,*height*])

---

<b>PAPER</b>	Defines the paper size for the report.
<i>type</i>	An integer constant or EQUATE that specifies a standard Windows paper size. EQUATES for these are contained in the EQUATES.CLW file.
<i>width</i>	An integer constant or constant expression that specifies the width of the paper (PROPPRINT:paperwidth, equivalent to {PROPPRINT:PAPER,2})
<i>height</i>	An integer constant or constant expression that specifies the height of the paper (PROPPRINT:paperheight, equivalent to {PROPPRINT:PAPER,3}).

The **PAPER** attribute (PROPPRINT:PAPER) on a REPORT structure defines the paper size for the report. The *width* and *height* parameters are only required when **PAPER:User** is selected as the *type*. Not all printers support all paper sizes.

The values contained in the *width* and *height* parameters always default to 1/1000 inch units, regardless of the absence or presence of the THOUS, MM, or POINTS attribute.

### Example:

```
CustRpt1 REPORT,AT(1000,1000,6500,9000),THOUS,PAPER(PAPER:User,8500,7000)
    !print on 8.5" x 7" paper
    !report declarations
END

CustRpt2 REPORT,AT(72,72,468,648),POINTS,PAPER(PAPER:A4)
    !print on A4 size paper
    !report declarations
END
```

**See Also:** PROP:AUTOPAPER

## PASSWORD (set data non-display)



### PASSWORD

---

The **PASSWORD** attribute (PROP:PASSWORD) specifies non-display of the data entered in the ENTRY control. When the user types in data, asterisks are displayed on screen for each character entered. The Windows standard Cut and Copy features are disabled when the PASSWORD attribute is active.



## PREVIEW (set report output to metafiles)

**PREVIEW**(*queue*)

**PREVIEW** Specifies report output goes to Windows metafiles containing one report page per file.

*queue* The label of a QUEUE or a field in a QUEUE to receive the names of the metafiles.

The **PREVIEW** attribute (PROP:PREVIEW, write-only) on a REPORT sends the report output to Windows metafiles containing one report page per file. The PREVIEW attribute names a *queue* to receive the names of the metafiles. The filenames are temporary filenames internally created by the Clarion library and are complete file specifications (up to 64 characters, including drive and path), unless you use PROP:TempNameFunc to provide your own names for these files. The temporary files listed in the preview queue are deleted from disk when you CLOSE the REPORT. To prevent the files from being deleted from the disk, delete them from the queue.

You can create a window to display the report in an IMAGE control, using the *queue* containing the file names to set the IMAGE control's {PROP:Text} property. This allows the end user to view the report before printing. A runtime-only property, {PROP:FlushPreview}, when set to ON, flushes the metafiles to the printer.

### Example:

SomeReport PROCEDURE

```
WMFQue    QUEUE                                !Queue to contain .WMF filenames
PageImage STRING(64)
END
```

```
NextEntry BYTE(1)                                !Queue entry counter variable
```

```
Report    REPORT,PREVIEW(WMFQue.PageImage) !Report with PREVIEW attribute
DetailOne DETAIL
          !Report controls
          END
          END
```

```
ViewReport WINDOW('View Report'),AT(0,0,320,200),MDI,MAX,HVSCROLL
          IMAGE(''),AT(0,0,320,180),USE(?ImageField)
          BUTTON('View Next Page'),AT(0,180,60,20),USE(?NextPage),DEFAULT
          BUTTON('Print Report'),AT(80,180,60,20),USE(?PrintReport)
          BUTTON('Exit Without Printing'),AT(160,180,60,20),USE(?ExitReport)
          END
```

```
CODE
OPEN(Report)
SET(SomeFile)                                !Code to generate the report
LOOP
  NEXT(SomeFile)
  IF ERRORCODE() THEN BREAK.
  PRINT(DetailOne)
END
ENDPAGE(Report)
OPEN(ViewReport)
GET(WMFQue,NextEntry)                        !Open report preview window
                                              !Get first queue entry
```

```

?ImageField{PROP:text} = WMFQue.PageImage !Load first report page
ACCEPT
CASE ACCEPTED()
OF ?NextPage
    NextEntry += 1 !Increment entry counter
    IF NextEntry > RECORDS(WMFQue) !Check for end of report
        CYCLE
    END
    GET(WMFQue,NextEntry) !Get next queue entry
    ?ImageField{PROP:text} = WMFQue.PageImage !Load next report page
    DISPLAY !and display it
OF ?PrintReport
    Report{PROP:flushpreview} = TRUE !Flush files to printer
    BREAK !and exit procedure
OF ?ExitReport
    BREAK !Exit procedure
END
END
CLOSE(ViewReport) !Close window
FREE(WMFQue) !Free the queue memory
CLOSE(Report) !Close report (deletes all .WMF files)
RETURN !and return to caller

```

**See Also:** ENDPAGE, PAGENO, PROP:NextPageNo

## RANGE (set range limits)



**RANGE**(*lower,upper*)

**RANGE** Specifies the valid range of data values the user may select in a SPIN control, or the range of values displayed in a PROGRESS control.

*lower* A numeric constant that specifies the lower inclusive limit of valid data (PROP:RangeLow, equivalent to {PROP:Range,1}).

*upper* A numeric constant that specifies the upper inclusive limit of valid data (PROP:RangeHigh, equivalent to {PROP:Range,2}).

The **RANGE** attribute (PROP:RANGE) specifies the valid range of data values the user may select in a SPIN control. RANGE also defines the range of values that are displayed in a PROGRESS control. This attribute works in conjunction with the STEP attribute on SPIN controls. On a SPIN control, the STEP attribute provides the user with the valid choices within the range.

If no RANGE is set, and the FROM attribute is not used, PROP:RangeHigh returns "+Infinity", and PROP:RangeLow returns "-Infinity". When using the CREATE statement to create a SPIN control, these values are intentionally reversed, so that PROP:RangeHigh and PROP:RangeLow must be explicitly set.

PROP:RangeLow and PROP:RangeHigh are also applicable for LIST and COMBO controls with vertical scrollbars (Read Only). PROP:RangeLow returns the lower limit of possible PROP:VScrollPos values, and PROP:RangeHigh returns upper limit. The limits or boundaries mentioned in the description of PROP:VScrollPos are correct only if number of records in the list box source is less or equal to number of visible rows (i.e., for page loaded browses).

### Example:

```
WinOne WINDOW,AT(0,0,160,400)
    SPIN(@N4.2),AT(280,0,20,20),USE(SpinVar1),RANGE(.05,9.95),STEP(.05)
    SPIN(@n3),AT(280,0,20,20),USE(SpinVar2),RANGE(5,995),STEP(5)
END
```

**See Also:** SPIN

## READONLY (set display-only)



### READONLY

---

The **READONLY** attribute (PROP:READONLY) specifies a display-only COMBO, ENTRY, SPIN or TEXT control. The control may receive input focus with the mouse, but may not enter data. If the user attempts to change the displayed value, a beep warns the user that data entry is not allowed.

## REPEAT (set repeat button rate)



**REPEAT**( *time* )

**REPEAT** Specifies the rate of event generation.

*time* An integer constant containing the rate to set, in hundredths of a second.

The **REPEAT** attribute (PROP:REPEAT) specifies rate of event generation for automatically repeating buttons. For a BUTTON control with the IMM attribute, this is the generation rate for EVENT:Accepted. For a SPIN control, this is the generation rate for EVENT:NewSelection generated by the spin buttons.

Assigning a zero (0) to PROP:REPEAT resets the default setting, any other value sets the repeat rate for the control.

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    BUTTON('Press Me'),AT(10,10,40,20),USE(?PressMe),IMM,REPEAT(100)    !1/second
    SPIN(@n3),AT(60,10,40,10),USE(SpinVar),RANGE(0,999),REPEAT(100)    !1/second
END
CODE
OPEN(MDIChild)
?PressMe{PROP:Delay} = 50    !Set delay to 1/2 second
?SpinVar{PROP:Delay} = 50    !Set delay to 1/2 second
?PressMe{PROP:Repeat} = 5    !Reset repeat to 5 hundredths of a second
?SpinVar{PROP:Repeat} = 5    !Reset repeat to 5 hundredths of a second
```

### See Also:

IMM

DELAY

## REQ (set required entry)



### REQ

---

The **REQ** attribute (PROP:REQ) specifies an ENTRY, TEXT, COMBO or SPIN control that may not be left blank or zero. The REQ attribute on these controls are not checked until a BUTTON with the REQ attribute is pressed, or the INCOMPLETE() procedure is called.

When a BUTTON with the REQ attribute is pressed, or the INCOMPLETE() procedure is called, all controls with the REQ attribute are checked to ensure they contain data. The first control encountered in this check that does not contain data immediately receives input focus.

**See Also:** INCOMPLETE, BUTTON

## RESET (set total reset)

**RESET**(*breaklevel*)

**RESET**            Resets the CNT, SUM, AVE, MIN, or MAX to zero (0).

*breaklevel*        The label of a BREAK structure.

The **RESET** attribute (PROP:RESET) specifies the group break at which the CNT, SUM, AVE, MIN, or MAX is reset to zero (0). PROP:RESET returns zero (0) if not present, else it returns the breaklevel nesting depth.

### Example:

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
Break1  BREAK(Pre:Key1)
        HEADER,AT(0,0,6500,1000)
          STRING('Group Head'),AT(3000,500,1500,500),FONT('Arial',18)
        END
Detail  DETAIL,AT(0,0,6500,1000)
        STRING(@N$11.2),AT(6000,1500,500,500),USE(Pre:F1)
        END
        FOOTER,AT(0,0,6500,1000)
          STRING('Group Total: '),AT(5500,500,1500,500)
          STRING(@N$11.2),AT(6000,500,500,500),USE(Pre:F1),SUM,RESET(Break1)
        END
      END
    END
```

## RESIZE (set variable height TEXT control)

### RESIZE

The **RESIZE** attribute (PROP:RESIZE) specifies height of the TEXT control varies according to the amount of data to print in it, up to the maximum height specified by the control's AT attribute.

The *height* parameter in the AT attribute of the DETAIL, HEADER, or FOOTER structure containing the TEXT control must not be set (let it default) for the RESIZE attribute to have any effect.

#### Example:

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
Detail  DETAIL,AT(0,0,6500,)                      !Detail height defaults
        STRING(@N$11.2),AT(500,500,500,),USE(Pre:F1)
        TEXT,AT(500,1000,500,5000),USE(Pre:Mem01),RESIZE !Print height up to 5"
        END
END
```



## RIGHT (set MENU position)



### RIGHT

---

The **RIGHT** attribute (PROP:RIGHT) specifies the MENU is placed at the right end of the action bar.

## ROUND (set round-cornered BOX)

### ROUND

---

The **ROUND** attribute (PROP:ROUND) specifies a BOX control with rounded corners. This attribute is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

## RTF (declare TEXT control as RichEdit)

**RTF**( *savetarget* )

---

**RTF**                Declare a TEXT field with RTF attributes.

*savetarget*        A byte or EQUATE that specifies that the TEXT control will be saved to a Field (TEXT:FIELD or 0) or File (TEXT:FILE or 1)

The RTF attribute declares a TEXT control as one with Rich Text Control attributes. The necessary code is generated and used to manipulate the text within the control as Rich Text. This attribute is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

Clarion's implementation of Rich Text allows the rich text field to be saved to a field or a separate text file. The minimum size of a target field is 256 characters. This is needed in order to maintain the rich text header information. If the field contains a lot of formatting a larger field size will be needed.

The components of a rich text control include a Toolbar, Format Bar, and Ruler. These components of the rich text control are optional. They may be shown or hidden at runtime. They default to showing at runtime. The bars may not be modified at design time in the window formatter. When the control is placed on the window, it is a basic TEXT control.

## SCROLL (set scrolling control)



### SCROLL

---

The **SCROLL** attribute (PROP:SCROLL) specifies a control that moves with the window when the WINDOW scrolls. This allows "virtual" windows larger than the physical video display.

The presence of the SCROLL attribute means that the control stays fixed at a position in the window relative to the top left corner of the virtual window, whether that position is currently in view or not. This means that the control appears to move as the window scrolls.

If the SCROLL attribute is omitted, the control stays fixed at a position in the window relative to the top left corner of the currently visible portion of the window. This means that the control appears to stay in the same position on screen while the rest of the window scrolls, which is useful for controls which should stay visible to the user at all times (such as Ok or Cancel buttons).

Mixing controls with and without the SCROLL attribute on the same WINDOW can result in multiple controls appearing to occupy the same screen position. This occurs because the controls with SCROLL move and the controls without SCROLL do not. This condition is temporary and scrolling the window further will correct the situation. The situation can be avoided entirely by careful placement of controls in the window. For example, you can place all controls without SCROLL at the bottom of the window then place all controls with SCROLL above them extending to the right and left. This would create a window that is designed to scroll horizontally (the WINDOW should have the HSCROLL attribute and not the VSCROLL or HVSCROLL attributes).

## SEPARATOR (set separator line ITEM)



### SEPARATOR

The **SEPARATOR** attribute specifies an ITEM in a MENU that displays a horizontal line to group ITEMS within the MENU. The USE attribute may be specified for the ITEM.

**Example:**

```
ITEM,SEPARATOR,USE(?FileSeperator1)
```

## **SINGLE (set TEXT for single line entry)**



### **SINGLE**

---

The **SINGLE** attribute (PROP:SINGLE) specifies the control is only for single line data entry. This is specifically to allow use of TEXT controls instead of ENTRY for data entry in languages that write from right to left (such as Hebrew or Arabic).

## SKIP (set Tab key skip or conditional print control)

### SKIP

The **SKIP** attribute (PROP:SKIP) on a window control specifies user access to the control is only with the mouse or an accelerator key, not the TAB key. This attribute is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. Data entry controls receive input focus only during data entry and the control does not retain focus, while non-data entry controls do not receive or retain input focus (the same behavior demonstrated by controls in a toolbar or toolbox).

When the mouse is over a control with the SKIP attribute, the control's MSG attribute displays in the status bar.

The SKIP attribute on a report control specifies the STRING or TEXT control prints only if its USE variable contains data. If the USE variable does not contain data, the STRING or TEXT control does not print and all controls following in the band "move up" to fill in the space. This is most useful for label printing to prevent extra blank lines in addresses. The SKIP attribute for a STRING or TEXT control is ignored by the print engine if the top or bottom edge of control's position overlaps another control not using the SKIP attribute (or using the SKIP attribute but containing some printed data).

#### Example:

```
CustRpt REPORT,AT(1000,1000,6000,9000),THOUS
Detail  DETAIL,AT(0,0,2000,1000)                                !Fixed height detail
        STRING(@s35),AT(250,250,500,),USE(Pre:Name)
        STRING(@s35),AT(250,350,500,),USE(Pre:Address1)
        STRING(@s35),AT(250,450,500,),USE(Pre:Address2),SKIP !don't print if blank
        STRING(@s35),AT(250,550,500,),USE(CityStateZip)  ! and move this up
END
END
```

## **SMOOTH (set smooth progress bar increments)**



### **SMOOTH**

---

The SMOOTH attribute (PROP:Smooth) activates a smooth incremental display of the progress control instead of the standard "block" format. Valid only for a PROGRESS control.



## SPREAD (set evenly spaced TAB controls)



### SPREAD

---

The **SPREAD** attribute (PROP:SPREAD) specifies a SHEET's TAB controls are evenly spaced.

## STATUS (set status bar)



**STATUS**( [*widths*] )

---

**STATUS** Specifies the presence of a status bar.

*Widths* A list of integer constants (separated by commas) specifying the size of each zone in the status bar. If omitted, the status bar has one zone the width of the window.

The **STATUS** attribute (PROP:STATUS) specifies the presence of a status bar at the base of the APPLICATION or WINDOW. The status bar of an MDI WINDOW is always displayed at the bottom of the APPLICATION. A WINDOW without the MDI attribute displays its status bar at the base of the WINDOW. If the STATUS attribute is not present on the APPLICATION or WINDOW, there is no status bar.

The status bar may be divided into multiple zones specified by the *widths* parameters. The size of each zone is specified in dialog units. A negative value indicates the zone is expandable, but has a minimum width indicated by the parameter's absolute value. If no *widths* parameters are specified, a single expanding zone with no minimum width is created, which is equivalent to a STATUS(-1).

PROP:STATUS contains the *widths* of each status bar section in separate array elements. A zero (0) value is required in the last element to terminate the array.

The first zone of the status bar is always used to display MSG attributes. The MSG attribute string is displayed in the status bar as long as its control field still has input focus. A control or menu item without a MSG attribute causes the status bar to revert to its former state (either blank or displaying the text previously displayed in the zone).

Text may be placed in, or retrieved from, any zone of the status bar using runtime property assignment to PROP:StatusText. PROP:StatusText is an array containing the text of each section of the status bar. A zero (0) value is required in the last element to terminate the array. The text remains present until replaced.

### Example:

**!An APPLICATION with a one-zone status bar:**

```
MainWin APPLICATION, STATUS
      END
```

**!A WINDOW with a two-zone status bar:**

```
Win1 WINDOW, STATUS(160,160)
      END
```

CODE

```
OPEN(Win1)
```

```
Win1{PROP:STATUS,3} = 160
```

**!Add a status bar zone**

```
Win1{PROP:STATUS,4} = 0
```

**!and terminate the array**

```
Win1{PROP:StatusText,3} = 'Hello Zone 3' !Put text in the new zone
```

**See Also:** MSG

## STD (set standard behavior)



**STD**(*behavior*)

**STD** Specifies standard Windows *behavior*.

*behavior* An integer constant or EQUATE specifying the identifier of a standard windows behavior.

The **STD** attribute (PROP:STD) specifies the control activates some standard Windows action. This action is automatically executed by the runtime library and does not generate any events (that is, the control does not receive an EVENT:Accepted).

EQUATE statements for the standard Windows actions are contained in the EQUATES.CLW file. The following list is a representative sample of these (see EQUATES.CLW for the complete list):

STD:WindowList	List of open MDI windows
STD:TileWindow	Tile Windows
STD:CascadeWindow	Cascade Windows
STD:ArrangeIcons	Arrange Icons
STD:HelpIndex	Help Contents
STD:HelpSearch	Help Search dialog

### Example:

```
MDIChild WINDOW('Child One'),MDI,SYSTEM,MAX
  MENUBAR
    MENU('Edit'),USE(?EditMenu)
      ITEM('Undo'),USE(?UndoText),KEY(CTRLZ),STD(STD:Undo)
      ITEM('Cu&t'),USE(?CutText),KEY(CTRLX),STD(STD:Cut)
      ITEM('Copy'),USE(?CopyText),KEY(CTRLC),STD(STD:Copy)
      ITEM('Paste'),USE(?PasteText),KEY(CTRLV),STD(STD:Paste)
    END
  END
  TOOLBAR
    BUTTON('Cut'),USE(?CutButton),ICON(ICON:Cut),STD(STD:Cut)
    BUTTON('Copy'),USE(?CopyButton),ICON(ICON:Copy),STD(STD:Copy)
    BUTTON('Paste'),USE(?PasteButton),ICON(ICON:Paste),STD(STD:Paste)
  END
END
```

## STEP (set SPIN increment)



**STEP**(*count*)

---

**STEP** Specifies a SPIN control RANGE attribute's increment/decrement value.

*count* A numeric constant specifying the amount to increment or decrement.

The **STEP** attribute (PROP:STEP) specifies the amount by which a SPIN control's value is incremented or decremented within its valid RANGE. The default STEP value is 1.0.

**Example:**

```
WinOne WINDOW,AT(0,0,160,400)
    SPIN(@N4.2),AT(280,0,20,20),USE(SpinVar1),RANGE(.05,9.95),STEP(.05)
    SPIN(@N3),AT(280,0,20,20),USE(SpinVar2),RANGE(5,995),STEP(5)
    SPIN(@T3),AT(280,0,20,20),USE(SpinVar3),RANGE(1,8640000),STEP(6000)
END
```

## STRETCH (set OLE object stretching)



### STRETCH

---

The **STRETCH** attribute (PROP:STRETCH, write-only) specifies the OLE object stretches to completely fill the size specified by the OLE container control's AT attribute. This attribute does not preserve the object's aspect ratio.

## SUM (set total)

**SUM**( [ *variable* ] )

---

<b>SUM</b>	Calculates the the sum of the values contained in the STRING control's USE variable.
<i>variable</i>	The label of a numeric variable to receive the intermediate values calculated for the SUM. This allows you to create totals on other totals. The value in the <i>variable</i> is internally updated by the print engine, so it is only useful for use within the REPORT structure.

The **SUM** attribute (PROP:SUM) specifies printing the sum of the values contained in the STRING control's USE variable. Unless the TALLY attribute is present, the result is calculated as follows:

- A SUM field in a DETAIL structure increments each time the DETAIL structure containing the control PRINTs. This provides a "running" total.
- A SUM field in a group FOOTER structure increments each time any DETAIL structure in the BREAK structure containing the control PRINTs. This provides the sum of the value contained in the variable in the group.
- A SUM field in a page FOOTER structure increments each time any DETAIL structure in any BREAK structure PRINTs. This is the sum of the values contained in the variable in the page.
- A SUM field in a HEADER is meaningless, since no DETAIL structures will have been printed at the time the HEADER is printed.

The SUM value is reset only if the RESET or PAGE attribute is also specified.

### Example:

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
Break1  BREAK(LocalVar),USE(?BreakOne)
Break2  BREAK(Pre:Key1),USE(?BreakTwo)
Detail  DETAIL,AT(0,0,6500,1000),USE(?DetailOne)
        STRING(@N$11.2),AT(6000,1500,500,500),USE(Pre:F1)
        END
        FOOTER,AT(0,0,6500,1000),USE(?BreakOneGroupFoot)
        STRING('Group Total: '),AT(5500,500)
        STRING(@N$11.2),AT(6000,500),USE(Pre:F1),SUM(LocalVar),RESET(Break2)
        END
        END
        FOOTER,AT(0,0,6500,1000),USE(?BreakOneGroupFoot)
        STRING('Grand Total: '),AT(5500,500)
        STRING(@N$11.2),AT(6000,500),USE(LocalVar),SUM,TALLY(?BreakTwo)
        END
        END
        END
```

## SYSTEM (set system menu)



### SYSTEM

The **SYSTEM** attribute (PROP:SYSTEM) specifies the presence of a Windows system menu (also called the control menu) on the APPLICATION or WINDOW. This menu contains standard Windows menu selections, such as: Close, Minimize, Maximize (the window), and Switch To (another window). The actual selections available on a given window depend upon the attributes set for that window.

#### Example:

!An APPLICATION with a system menu:

```
MainWin APPLICATION,SYSTEM
      END
```

!A WINDOW with a system menu:

```
Win1 WINDOW,SYSTEM
      END
```

## TALLY (set total calculation times)

**TALLY**( *points* )

---

**TALLY** Specifies when to calculate an AVE, CNT, MAX, MIN, or SUM.

*points* A comma delimited list of the labels of the DETAIL and/or BREAK structures on which to calculate the total.

The **TALLY** attribute (PROP:TALLY) specifies when to calculate an AVE, CNT, MAX, MIN, or SUM. The appropriate total is calculated each time any of the DETAIL structures named in the *points* list prints, or in the case of a BREAK structure, when the group break occurs.

**Example:**

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
Break1  BREAK(LocalVar),USE(?BreakOne)
Break2  BREAK(Pre:Key1),USE(?BreakTwo)
        HEADER,AT(0,0,6500,1000),USE(?GroupHead)
        STRING('Group Head'),AT(3000,500,1500,500),FONT('Arial',18)
        END
Detail  DETAIL,AT(0,0,6500,1000),USE(?DetailOne)
        STRING(@N$11.2),AT(6000,1500,500,500),USE(Pre:F1)
        END
        END
        FOOTER,AT(0,0,6500,1000),USE(?BreakOneGroupFoot)
        STRING('Group Total:'),AT(5500,500,1500,500)
        STRING(@N$11.2),AT(6000,500,500,500),USE(Pre:F1),CNT,TALLY(Break2)
        END
        END
        END

CODE
OPENCustRpt)
CustRpt$?Pre:F1{PROP:Tally} = ?BreakOne !Change the TALLY to Break1
```



## THOUS, MM, POINTS (set report coordinate measure)

**THOUS**

**MM**

**POINTS**

---

The **THOUS**, **MM**, and **POINTS** attributes specify the coordinate measures used to position controls on the REPORT or WINDOW (using runtime properties).

**THOUS** (PROP:THOUS) specifies thousandths of an inch, **MM** (PROP:MM) specifies millimeters, and **POINTS** (PROP:POINTS) specifies points (there are seventy-two points per inch, both vertically and horizontally).

If all these attributes are omitted, the measurements default to dialog units. Dialog units are defined as one-quarter the average character width by one-eighth the average character height. The size of a dialog unit is dependent upon the size of the default font for the report. This measurement is based on the font specified in the FONT attribute of the REPORT, or the system default font specified by Windows.

## TILED (set tiled image)



### TILED

The **TILED** attribute (PROP:TILED) indicates that the image displayed in the IMAGE control, or the window or toolbar's background image (specified in the WALLPAPER attribute) displays at its default size and is tiled to fill the entire window, toolbar, or area specified by the IMAGE's AT attribute.

#### Example:

```
WinOne WINDOW,AT(, ,380,200),MDI
    IMAGE('MyWall.GIF'),AT(0,0,380,200),TILED
END
MDIChild WINDOW('Child One'),MDI,SYSTEM,MAX
    MENUBAR
        MENU('Edit'),USE(?EditMenu)
            ITEM('Undo'),USE(?UndoText),KEY(CtrlZ),STD(STD:Undo)
            ITEM('Cu&t'),USE(?CutText),KEY(CtrlX),STD(STD:Cut)
            ITEM('Copy'),USE(?CopyText),KEY(CtrlC),STD(STD:Copy)
            ITEM('Paste'),USE(?PasteText),KEY(CtrlV),STD(STD:Paste)
        END
    END
    TOOLBAR,USE(?Toolbar),WALLPAPER('MyWall.GIF'),TILED
        BUTTON('Cut'),USE(?CutButton),ICON(ICON:Cut),STD(STD:Cut),FLAT
        BUTTON('Copy'),USE(?CopyButton),ICON(ICON:Copy),STD(STD:Copy),FLAT
        BUTTON('Paste'),USE(?PasteButton),ICON(ICON:Paste),STD(STD:Paste),FLAT
    END
END

WinOne WINDOW,AT(, ,380,200),MDI,WALLPAPER('MyWall.GIF'),TILED
END
```

#### See Also:

CENTERED

WALLPAPER

## TIMER (set periodic event)



**TIMER**(*period*)

**TIMER** Specifies a periodic event.

*period* An integer constant or constant expression specifying the interval between timed events, in hundredths of a second. If zero (0), no timed events generate.

The **TIMER** attribute (PROP:TIMER) specifies generation of a periodic field-independent event (EVENT:Timer) whenever the time *period* passes. The FOCUS() procedure returns the number of the control that currently has focus at the time of the event.

Value of timer has the UINT type. The Clarion IDE limits the timer value to 65365. If a higher value is required, it must be set using the property assignment statement.

### Example:

```
RunClock PROCEDURE
ShowTime LONG
TimerValue UNSIGNED

!A WINDOW with a timed event occurring every second:
Win1 WINDOW, TIMER(100)
    STRING(@T4), USE (ShowTime)
END
CODE
OPEN (Win1)
!You can also set the TIMER at runtime like this:
!TimerValue = 100000 !1000 second delay
!Win1{PROP:TIMER} = TimerValue
ShowTime = CLOCK()
ACCEPT
CASE EVENT()
OF EVENT:Timer
    ShowTime = CLOCK()
    DISPLAY
END
END
CLOSE (Win1)
```

**See Also:** Event:Timer

## TIP (set "balloon help" text)



**TIP**( *string* )

---

**TIP** Specifies the text to display when the mouse cursor pauses over the control.

*string* A string constant or expression that specifies the text to display and how the text is formatted (single or multi-line TIP).

The **TIP** attribute (PROP:Tip) on a control specifies the text to display in a "balloon help" box when the mouse cursor pauses over the control. Although there is no specific limit on the number of characters, the *string* (or any single line of a multi-line TIP) should not be longer than can be displayed on the screen.

Multi-line tip conventions are as follows for both the TIP Attribute, TIP( ), or the TIP Property,{PROP:Tip}=:

All of the following will produce a two line TIP.

```
'Line1' & CHR(10) & 'Line2' !CHR(10) = Line Feed
'Line1<13,10>Line2'         !<13,10> = Carriage Return, Line Feed
'Line1<10>Line2'            !<10> = Line Feed
```

Although it is valid on any control that can gain focus for user input, this attribute is most commonly used on BUTTON controls with the ICON attribute that are placed on the TOOLBAR. This allows the user to quickly determine the control's purpose without accessing the on-line Help system.

Automatic TIP attribute display can be disabled for any single control or window by setting the PROP:NoTips undeclared property to one (1). It can be disabled for an entire application by setting the PROP:NoTips for the built-in variable SYSTEM to one (1).

The amount of tool tip delay is an operating system setting under the user's control.

### Example:

```
Win WINDOW,AT(0,0,160,400)
  TOOLBAR
    BUTTON('E&xit'),USE(?MainExitButton),ICON(ICON:hand),TIP('Exit Window')
    BUTTON('&Open'),USE(?OpenButton),ICON(ICON:Open),TIP('Open'<10>'a File')!Multi-line TIP
  END
  COMBO(@S8),AT(120,120,20,20),USE(?C1),FROM(Q1:F2)
  ENTRY(@S8),AT(100,200,20,20),USE(E2)
END
```

**See Also:** TipDelay/TipDisplay, TipsFont, NoTips

## TOGETHER (set to print on a single page)

### TOGETHER

---

The **TOGETHER** attribute (PROP:Together) specifies that the DETAIL, or group HEADER or FOOTER structure (contained within a BREAK structure), is to only print on a single page, rather than being automatically split if there is not sufficient room for it. The normal use is for structures with multiple lines that need to be printed together, as in mailing labels.

#### Example:

```
CustRpt    REPORT
TitlePage  DETAIL !Title page detail structure
           !structure elements
           END
CustDetail DETAIL, TOGETHER !Print all detail elements together
           !structure elements
           END
           FOOTER
           !structure elements
           END
           END
```

## TOOLBOX (set toolbox window behavior)



### TOOLBOX

The **TOOLBOX** attribute (PROP:TOOLBOX) specifies a WINDOW that is "always on top" and may be docked if the DOCK attribute is also present. Neither the WINDOW nor its controls retain input focus. This creates control behavior as if all the controls in the WINDOW had the SKIP attribute.

Normally, a WINDOW with the TOOLBOX attribute executes in its own execution thread to provide a set of tools to the window with input focus. The MSG attributes of the controls in the window appear in the status bar when the mouse cursor is positioned over the control.

#### Example:

```
PROGRAM
MAP
    UseTools
    Tools
END

MainWin APPLICATION('My Application')
    MENUBAR
        MENU('File'),USE(?FileMenu)
        ITEM('E&xit'),USE(?MainExit),LAST
    END
    MENU('Edit'),USE(?EditMenu)
    ITEM('Use Tools'),USE(?UseTools)
    END
END
END

Pre:Field        STRING(400)
UseToolsThread   BYTE
ToolsThread      BYTE

CODE
OPEN(MainWin)
ACCEPT
CASE ACCEPTED()
OF ?MainExit
    BREAK
OF ?UseTools
    UseToolsThread = START(UseTools)
END
END

UseTools PROCEDURE                                !A procedure that uses a toolbox
MDIChild WINDOW('Use Tools Window'),MDI
    TEXT,HVSCROLL,USE(Pre:Field)
    BUTTON('&OK'),USE(?Exit),DEFAULT
END

CODE
OPEN(MDIChild)                                    !Open the window
DISPLAY                                             !and display it
```

```

ToolsThread = START(Tools)           !Pop up the toolbox
ACCEPT
  CASE EVENT()                       !Check for user-defined events
    OF 401h                          !posted by toolbox controls
!append date to end of field
    Pre:Field = CLIP(Pre:Field) & ' ' & FORMAT(TODAY(),@D1)
    OF 402h
!append time to end of field
    Pre:Field = CLIP(Pre:Field) & ' ' & FORMAT(CLOCK(),@T1)
  END
  CASE ACCEPTED()
    OF ?Exit
      POST(400h,,ToolsThread)       !Signal to close tools window
      BREAK
    END
  END
END
CLOSE(MDICHild)

Tools PROCEDURE !The toolbox procedure
Win1 WINDOW('Tools'),TOOLBOX
  BUTTON('Date'),USE(?Button1)
  BUTTON('Time'),USE(?Button2)
END
CODE
OPEN(Win1)
ACCEPT
  IF EVENT() = 400h THEN BREAK.      !Check for close window signal
  CASE ACCEPTED()
    OF ?Button1
      POST(401h,,UseToolsThread)    !Post datestamp signal
    OF ?Button2
      POST(402h,,UseToolsThread)    !Post timestamp signal
  END
END
CLOSE(Win1)

```

**See Also:**

DOCK

## TRN (set transparent control)

### TRN

The **TRN** attribute (PROP:TRN) on a control specifies the characters print or display transparently, without obliterating the background over which the control is placed. This attribute is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. Only the dots or pixels required to create each character are printed or displayed. This allows you to place the control directly on top of an IMAGE without destroying the background picture.

#### Example:

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
      FORM,AT(0,0,6500,9000)
      IMAGE('PIC.BMP'),USE(?I1)AT(0,0,6500,9000)      !Full page image
      !Transparent string on the image:
      STRING('String Constant'),AT(10,0,20,20),USE(?S1),TRN
      END
END

WinOne WINDOW,AT(0,0,160,400)
      IMAGE('PIC.BMP'),USE(?I1),FULL                  !Full window image
      !Transparent string on image
      STRING('String Constant'),AT(10,0,20,20),USE(?S1),TRN
      END
```



## UP, DOWN (set TAB text orientation)



UP

DOWN

The **UP** and **DOWN** attributes of a SHEET control specify the orientation of the text on the TAB controls. UP (PROP:UP) specifies the TAB text appears vertical reading upwards, while DOWN (PROP:DOWN) specifies the TAB text appears vertical reading downwards. If both UP and DOWN attributes are present, the TAB text appears inverted (PROP:UpsideDown).

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
  SHEET,AT(0,0,320,175),USE(SelectedTab),RIGHT,DOWN !Tabs right reading down
    TAB('Tab One'),USE(?TabOne)
      PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P1)
      ENTRY(@S8),AT(100,140,32,20),USE(E1)
      PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P2)
      ENTRY(@S8),AT(100,240,32,20),USE(E2)
    END
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P3)
    ENTRY(@S8),AT(100,140,32,20),USE(E3)
    PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P4)
    ENTRY(@S8),AT(100,240,32,20),USE(E4)
  END
  BUTTON('Ok'),AT(100,180,20,20),USE(?Ok)
  BUTTON('Cancel'),AT(200,180,20,20),USE(?Cancel)
END
```

## USE (set field equate label or control update variable)



```
USE( | label | [, number] [, equate] )  
    | variable |
```

<b>USE</b>	Specifies a variable or field equate label.
<i>label</i>	A field equate label to reference the control or structure in executable code. This must begin with a question mark (?) and meet all the requirements of a valid Clarion label.
<i>variable</i>	The label of the variable to receive the value the user enters in the control. The variable's label (with a leading question mark - <i>?VariableLabel</i> ) becomes the field equate label for the control, unless the <i>equate</i> parameter is used.
<i>number</i>	An integer constant that specifies the number the compiler equates to the field equate label for the control (PROP:Feq, equivalent to {PROP:USE,2}).
<i>equate</i>	A field equate label to reference the control in executable code when the named <i>variable</i> has already been used in the same structure. This provides a mechanism to provide a unique field equate when the <i>variable</i> would not.

The **USE** attribute (PROP:USE) specifies a field equate label for the control or structure, or a variable for the control to update.

USE with a *label* parameter simply provides a mechanism for executable source code statements to reference the control or structure. USE with a *variable* parameter supplies the control with a variable to update by operator entry (on a window control) or to provide the value to print (on a report control).

The USE attribute's *number* parameter allows you to specify the actual field number the compiler assigns to the control. This *number* also is used as the new starting point for subsequent field numbering for controls without a *number* parameter in their USE attribute. Subsequent controls without a *number* parameter in their USE attribute are incremented (or decremented) relative to the last *number* assigned.

Two or more controls with exactly the same USE *variable* in one WINDOW or APPLICATION structure would create the same Field Equate Label for all, therefore, when the compiler encounters this condition, all Field Equate Labels for that USE variable are discarded. This makes it impossible to reference any of these controls in executable code, preventing confusion about which control you really want to reference. It also allows you to deliberately create this condition to display the contents of the variable in multiple controls with different display pictures. You may eliminate this situation by using *equate* parameters on these controls.

Writing to PROP:USE changes the USE attribute to use the name of the variable assigned. Reading it returns the contents of the current USE variable. PROP:Feq sets and returns the field number for the control.

## Window Usage

Some controls or structures only allow a field equate *label* as the USE parameter, not a *variable*. These are: PROMPT, IMAGE, LINE, BOX, ELLIPSE, GROUP, RADIO, REGION, MENU, BUTTON, and TOOLBAR.

USE with a *variable* parameter supplies the control with a variable to update by operator entry. This is applicable to an ITEM with the CHECK attribute, ENTRY, OPTION, SPIN, TEXT, LIST, COMBO, CHECK, and CUSTOM.

**PROP>ListFeq** is equivalent to {PROP:USE,3} and sets the field equate label for the list portion of a COMBO control or a LIST control with the DROP attribute. **See Also:** PROP:Selected

**PROP:ButtonFeq** is equivalent to {PROP:USE,4} and sets the field equate label for the drop button portion of a COMBO control (not valid for drop list controls).

## Report Usage

Some controls and structures only allow a field equate *label* as the USE parameter, not a *variable*. These are: IMAGE, LINE, BOX, ELLIPSE, GROUP, RADIO, FORM, BREAK, DETAIL, HEADER, and FOOTER.

USE with a *variable* parameter supplies the control with a variable to update by operator entry. This is applicable to an OPTION, TEXT, LIST, CHECK, or CUSTOM. STRING controls may use either a field equate *label* or *variable*.

All controls and structures in a REPORT are automatically assigned numbers by the compiler. By default, these numbers start at one (1) and increment by one (1) for each control in the REPORT. The USE attribute's *number* parameter allows you to specify the actual field number the compiler assigns to the control or structure. This *number* also is used as the new starting point for subsequent numbering for controls and structures without a *number* parameter in their USE attribute. Subsequent controls and structures without a *number* parameter in their USE attribute are incremented relative to the last *number* assigned.

### Example:

```
MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS
  MENUBAR
    MENU('&File'),USE(?FileMenu)
    ITEM('&Open...'),USE(?OpenFile)
    ITEM('&Close'),USE(?CloseFile),DISABLE
    ITEM('E&xit'),USE(?MainExit)
  END
END
TOOLBAR,USE(?Toolbar)
  BUTTON('Exit'),USE(?MainExitButton)
  ENTRY(@S8),AT(100,160,20,20),USE(E2)
  ENTRY(@S8),AT(100,200,20,20),USE(E3,100)           !Field number 100
  ENTRY(@S8),AT(100,240,20,20),USE(E2,,?Number2:E2)  !
END
END

CustRpt REPORT,AT(1000,1000,6500,9000),THOUS
Detail  DETAIL,AT(0,0,6500,1000),USE(?Detail)          !Line item detail
        STRING('Group Total:'),AT(5500,500,1500,500),USE(?Constant) !Field equate label
        STRING(@N$11.2),AT(6000,1500,500,500),USE(Pre:F1)         !USE variable
        END
END

CODE
```

```
OPEN(MainWin)
DISABLE(?E2)           !Disable first entry control
DISABLE(100)           !Disable second entry control
DISABLE(?Number2:E2)   !Disable third entry control
PrintRpt(CustRpt,?Detail) !Pass report and detail equate to print proc
  ACCEPT
END

PrintRpt PROCEDURE(RptToPrint,DetailNumber)
  CODE
  OPEN(RptToPrint)      !Open passed report
  PRINT(RptToPrint,DetailNumber) !Print its detail
  CLOSE(RptToPrint)     !Close passed report
```

**See Also:**

Field Equate Labels

## VALUE (set RADIO or CHECK control USE variable assignment)



```
VALUE (| string |)
      | truevalue , falsevalue |
```

**VALUE** Specifies the value assigned to the OPTION structure's USE variable when the RADIO control is selected by the user, or the values assigned to the CHECK control's USE variable when checked and un-checked by the user.

*string* A string constant containing the value to assign to the OPTION's USE variable.

*truevalue* A string constant containing the value to assign to the CHECK's USE variable when the user has checked the box (PROP:TrueValue, equivalent to {PROP:Value,1}).

*falsevalue* A string constant containing the value to assign to the CHECK's USE variable when the user has un-checked the box (PROP:FalseValue, equivalent to {PROP:Value,2}).

The **VALUE** attribute (PROP:VALUE) on a RADIO control specifies the value that is automatically assigned to the OPTION structure's USE variable when the RADIO control is selected by the user. This attribute overrides the RADIO control's *text* parameter.

The VALUE attribute on a CHECK control specifies the values that are automatically assigned to the control's USE variable when the user checks and un-checks the box. This attribute overrides the default assignment of zero and one.

All automatic type conversion rules apply to the values assigned to the control's USE variable. Therefore, if the *string*, *truevalue*, or *falsevalue* contains only numeric data and the USE variable is a numeric data type, it receives the numeric value.

PROP:VALUE may also be used on an ENTRY, SPIN, or COMBO control to interrogate the value that would be placed into the control's USE variable by UPDATE (or when the control loses focus) without actually updating the USE variable. This can cause EVENT:Rejected to generate, if appropriate.

### Example:

```
Win WINDOW,AT(0,0,180,400)
  OPTION('Option 1'),USE(OptVar1),MSG('Pick One or Two')
  RADIO('Radio 1'),AT(120,0,20,20),USE(?R1),VALUE('10') !OptVar1 gets 10
  RADIO('Radio 2'),AT(140,0,20,20),USE(?R2),VALUE('20') !OptVar1 gets 20
END
  OPTION('Option 2'),USE(OptVar2),MSG('Pick One or Two')
  RADIO('Radio 1'),AT(120,0,20,20),USE(?R1),VALUE('10') !OptVar2 gets '10'
  RADIO('Radio 2'),AT(140,0,20,20),USE(?R2),VALUE('20') !OptVar2 gets '20'
END
  CHECK('Check 1'),AT(160,0),USE(Check1),VALUE('T','F')
END
```

## VERTICAL (set vertical progress bar display)



### VERTICAL

---

The **VERTICAL** attribute (PROP:Vertical) allows the progress control to operate from the bottom of the control to the top. If your progress control is positioned in a horizontal (left to right) display format, you should resize the progress control accordingly. Valid only for a PROGRESS control.

## VCR (set VCR control)



VCR( [*field*] )

**VCR** Places Video Cassette Recorder (VCR) style buttons on a LIST or COMBO control.

*field* A field equate label that specifies the ENTRY control to use as a locator for a LIST or COMBO (PROP:VcrFeq, equivalent to {PROP:VCR,2}). This ENTRY control must appear before the LIST or COMBO control in the WINDOW structure.

The **VCR** attribute (PROP:VCR) places **V**ideo **C**assette **R**ecorder (VCR) style buttons on a LIST or COMBO control. The VCR style buttons affect the scrolling characteristics of the data displayed in the LIST or COMBO. There are seven buttons displayed as the VCR:

<	Top of list	(EVENT:ScrollTop)
<<	Page Up	(EVENT:PageUp)
<	Entry Up	(EVENT:ScrollUp)
?	Locate	(EVENT:Locate)
>	Entry Down	(EVENT:ScrollDown)
>>	Page Down	(EVENT:PageDown)
>	Bottom of list	(EVENT:ScrollBottom)

The *field* parameter names the control to get focus when the user presses the ? button. When the user enters data and then presses TAB on the locator *field*, the LIST or COMBO scrolls to its closest matching entry. If no *field* parameter is named, the ? button still appears but does nothing. To avoid even displaying the ? button, you may set PROP:VCR to TRUE instead of adding the VCR attribute to the LIST or COMBO control declaration.

### Example:

```
MDIC WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    LIST,AT(140,0,20,20),USE(?L1),FROM(Que),HVSCROLL
    ENTRY(@S8),AT(100,200,20,20),USE(E2)                !Locator control for L2
    LIST,AT(140,100,20,20),USE(?L2),FROM(Que),HVSCROLL,VCR(?E2) !VCR with Locator active
END
CODE
OPEN(MDIC)
?L1{PROP:VCR} = TRUE                !VCR buttons without the ? button
ACCEPT
END
```

## WALLPAPER (set background image)



**WALLPAPER**(*image*)

---

**WALLPAPER** Specifies a background image to display in the toolbar or window's client area.

*image* A string constant specifying the name of the file to display.

The **WALLPAPER** attribute (PROP:WALLPAPER) specifies displaying the *image* as a background for the toolbar or window's client area. The image is stretched to fill the entire toolbar or window's client area unless either the **TILED** or **CENTERED** attributes are present.

### Example:

```
MDIChild WINDOW('Child One'),MDI,SYSTEM,MAX
    MENUBAR
        MENU('Edit'),USE(?EditMenu)
        ITEM('Undo'),USE(?UndoText),KEY(CtrlZ),STD(STD:Undo)
        ITEM('Cu&t'),USE(?CutText),KEY(CtrlX),STD(STD:Cut)
        ITEM('Copy'),USE(?CopyText),KEY(CtrlC),STD(STD:Copy)
        ITEM('Paste'),USE(?PasteText),KEY(CtrlV),STD(STD:Paste)
    END
END
TOOLBAR,USE(?Toolbar),WALLPAPER('MyWall.GIF')
    BUTTON('Cut'),USE(?CutButton),ICON(ICON:Cut),STD(STD:Cut),FLAT
    BUTTON('Copy'),USE(?CopyButton),ICON(ICON:Copy),STD(STD:Copy),FLAT
    BUTTON('Paste'),USE(?PasteButton),ICON(ICON:Paste),STD(STD:Paste),FLAT
END
END

WinOne WINDOW,AT(,380,200),MDI,WALLPAPER('MyWin.GIF')
END
```

### See Also:

**CENTERED**

**TILED**



## WITHNEXT (set widow elimination)

**WITHNEXT**( [*siblings*] )

**WITHNEXT** Specifies the structure is always printed on the same page as print structures PRINTed immediately following it.

*siblings* An integer constant or constant expression that specifies the number of following print structures to print on the same page. If omitted, the default value is one.

The **WITHNEXT** attribute (PROP:WITHNEXT) specifies that the DETAIL, or group HEADER or FOOTER structure (contained within a BREAK structure), is always printed on the same page as the specified number of print structures PRINTed immediately following it. This ensures that the structure is never printed on a page by itself, eliminating "widow" print structures. A "widow" print structure is defined as a group header, or first detail item in a related group of items, printed on the preceding page, separated from the rest of its related items.

The *siblings* parameter, if present, sets the number of following print structures that must be printed on the same page with the structure. To be counted, the following print structures must come from the same, or nested, BREAK structures. They must be related items. Any print structures not within the same, or nested, BREAK structures are printed but not counted as part of the required number of *siblings*.

### Example:

```
CustRpt  REPORT
Break1   BREAK(SomeVariable)
          HEADER,WITHNEXT(2)    !Always print with 2 siblings
          !structure elements
          END
CustDetail DETAIL,WITHNEXT()    !Always print with 1 sibling
          !structure elements
          END
          FOOTER
          !structure elements
          END
          END
          END
```

## WITHPRIOR (set orphan elimination)

WITHPRIOR( [*siblings*] )

**WITHPRIOR** Specifies the structure is always printed on the same page as print structures PRINTed immediately preceding it.

*siblings* An integer constant or constant expression that specifies the number of preceding print structures to print on the same page. If omitted, the default value is one.

The **WITHPRIOR** attribute (PROP:WITHPRIOR) specifies that the DETAIL, or group HEADER or FOOTER structure (contained within a BREAK structure), is always printed on the same page as the specified number of print structures PRINTed immediately preceding it. This ensures that the structure is never printed on a page by itself, eliminating "orphan" print structures. An "orphan" print structure is defined as a group footer, or last detail item in a related group of items, that is printed on the following page separated from the rest of its related items.

The *siblings* parameter, if present, sets the number of preceding print structures that must be printed on the same page with the structure. To be counted, the preceding print structures must come from the same, or nested, BREAK structures. They must be related items. Any print structures not within the same, or nested, BREAK structures are printed, but not counted as part of the required number of *siblings*.

### Example:

```
CustRpt  REPORT
Break1   BREAK(SomeVariable)
          HEADER
          !structure elements
          END
CustDetail DETAIL,WITHPRIOR()      !Always print with 1 sibling
          !structure elements
          END
          FOOTER,WITHPRIOR(2)      !Always print with 2 siblings
          !structure elements
          END
          END
          END
```

## WIZARD (set "tableless" SHEET control)



### WIZARD

---

The **WIZARD** attribute (PROP:WIZARD) specifies a SHEET control that does not display its TAB controls. This allows the program to direct the user through each TAB in a specified sequence (usually with "Next" and "Previous" buttons).

## ZOOM (set OLE object zooming)



### ZOOM

---

The **ZOOM** attribute (PROP:ZOOM, write-only) specifies the OLE object stretches to fill the size specified by the OLE container control's AT attribute while maintaining the object's aspect ratio.

# 10 - Expressions

## Expressions Overview

An expression is a mathematical, string, or logical formula that produces a value. An expression may be the source variable of an assignment statement, a parameter of a procedure, a subscript of an array (a dimensioned variable), or the condition of an IF, CASE, LOOP, or EXECUTE structure. Expressions may contain constant values, variables, and procedures which return values, all connected by logical and/or arithmetic or string operators.

**Related Topic:** Expression Evaluation

## Expression Evaluation

Expressions are evaluated in the standard algebraic order of operations. The precedence of operations is controlled by operator type and placement of parentheses. Each operation produces an (internal) intermediate value used in subsequent operations. Parentheses may be used to group operations within expressions. Expressions are evaluated beginning with the inner-most set of parentheses and working through to the outer-most set.

Precedence levels for expression evaluation, from highest to lowest, and left-to-right within each level, are:

Level 1	( )	Parenthetical Grouping
Level 2	-	Unary Minus (Negative sign)
Level 3	procedure call	Gets the RETURN value
Level 4	^	Exponentiation
Level 5	* / %	Multiplication, Division, Modulus Division
Level 6	+ -	Addition, Subtraction
Level 7	&	Concatenation
Level 8	= <>	Logical Comparisons
Level 9	NOT, AND, OR/XOR	Boolean expressions

Expressions may produce numeric values, string values, or logical values (true/false evaluation). An expression may contain no operators at all; it may be a single variable, constant value, or procedure call which returns a value.

## Arithmetic Operators

An arithmetic operator combines two operands arithmetically to produce an intermediate value. The operators are:

- +** Addition ( $A + B$  gives the sum of A and B)
- Subtraction ( $A - B$  gives the difference of A and B)
- \*** Multiplication ( $A * B$  multiples A by B)
- /** Division ( $A / B$  divides A by B)
- ^** Exponentiation ( $A ^ B$  raises A to power of B)
- %** Modulus Division ( $A \% B$  gives the remainder of A divided by B)

### Note:

The sign of the Modulus Division result can be controlled by the `compatible_modulus` #PRAGMA define. See SoftVelocity #PRAGMAS

There are also "shortcut" arithmetic operator assignments that simplify your code. For more information, see Operating Assignments.

## The Concatenation Operator

The ampersand ( & ) concatenation operator is used to append one string or string variable to another. The length of the resulting string is the sum of the lengths of the two values being concatenated. Numeric data types may be concatenated with strings or other numeric variables or constants. In many cases, the CLIP procedure should be used to remove any trailing spaces from a string being concatenated to another string.

### Example:

```
CLIP(FirstName) & ' ' & Initial & '. ' & LastName  !Concatenate full name
'SoftVelocity Corporation' & ', Inc.'              !Concatenate two constants
```

### See Also:

CLIP

Numeric Expressions

Data Conversion Rules

FORMAT

## Logical Operators

A logical operator compares two operands or expressions and produces a true or false condition. There are two types of logical operators: conditional and Boolean. Conditional operators compare two values or expressions. Boolean operators connect string, numeric, or logical expressions together to determine true-false logic. Operators may be combined to create complex operators.

<b>Conditional Operators</b>	<b>=</b>	Equal sign
	<b>&lt;</b>	Less than
	<b>&gt;</b>	Greater than

<b>Boolean Operators</b>	<b>NOT</b>	Boolean (logical) NOT
	<b>~</b>	Tilde (logical NOT)
	<b>AND</b>	Boolean AND
	<b>OR</b>	Boolean OR
	<b>XOR</b>	Boolean eXclusive OR

<b>Combined operators</b>	<b>&lt;&gt;</b>	Not equal
	<b>~=</b>	Not equal
	<b>NOT =</b>	Not equal
	<b>&lt;=</b>	Less than or equal to
	<b>=&lt;</b>	Less than or equal to
	<b>~&gt;</b>	Not greater than
	<b>NOT &gt;</b>	Not greater than
	<b>&gt;=</b>	Greater than or equal to
	<b>=&gt;</b>	Greater than or equal to
	<b>~&lt;</b>	Not less than
	<b>NOT &lt;</b>	Not less than

During logical evaluation, any non-zero numeric value or non-blank string value indicates a true condition, and a null (blank) string or zero numeric value indicates a false condition.

### Examples:

<u>Logical Expression</u>	<u>Result</u>
A = B	True when A is equal to B
A < B	True when A is less than B
A > B	True when A is greater than B
A <> B, A ~= B, A NOT = B	True when A is not equal to B
A ~< B, A >= B, A NOT < B	True when A is not less than B
A ~> B, A <= B, A NOT > B	True when A is not greater than B
~ A, NOT A	True when A is null or zero
A AND B	True when A is true and B is true
A OR B	True when A is true, or B is true, or both are true
A XOR B	True when A is true or B is true, but not both.



## Numeric Constants

Numeric constants are fixed numeric values. They may occur in data declarations, in expressions, and as parameters of procedures or attributes. A numeric constant may be represented in decimal (base 10--the default), binary (base 2), octal (base 8), hexadecimal (base 16), or scientific notation formats. Formatting characters, such as dollar signs and commas, are not permitted in numeric constants; only leading plus or minus signs and the decimal point are allowed.

Decimal (base ten) numeric constants may contain an optional leading minus sign (hyphen character), an integer, and an optional decimal with a fractional component. Binary (base two) numeric constants may contain an optional leading minus sign, the digits 0 and 1, and a terminating B or b character. Octal (base eight) numeric constants contain an optional leading minus sign, the digits 0 through 7, and a terminating O or o character. Hexadecimal (base sixteen) numeric constants contain an optional leading minus sign, the digits 0 through 9, alphabet characters A through F (representing the numbers 10 through 15) and a terminating H or h character. If the left-most character is a letter A through F, a leading zero must be used.

**Example:**

```
-924      !Decimal constants
76.346
+76.346
```

```
1011b    !Binary constants
-1000110B
```

```
3403o    !Octal constants
-7041312O
```

```
-1FFBh   !Hexadecimal constants
0CD1F74FH
```

## String Constants

A string constant is a set of characters enclosed in single quotes (apostrophes). The maximum length of a string constant is 255 characters. Characters that cannot be entered from the keyboard may be inserted into a string constant by enclosing their ASCII character codes in angle brackets (<>). ASCII character codes may be represented in decimal, hexadecimal, binary, or octal numeric constant format.

In a string constant, a left angle bracket ( < ) initiates a scan for a right angle bracket. Therefore, to include a left angle bracket in a string constant requires two left angle brackets in succession. To include an apostrophe as part of the value inside a string constant requires two apostrophes in succession. Two apostrophes ( " ), with no characters (or just spaces) between them, represents a null, or blank, string. Consecutive occurrences of the same character within a string constant may be represented by *repeat count* notation. The number of times the character is to be repeated is placed within curly braces ( { } ) immediately following the character to repeat. To include a left curly brace ( { ) as part of the value inside a string constant requires two left curly braces ( { { ) in succession.

The ampersand (&) is always valid in a string constant. However, depending on the assignment's destination, it may be interpreted as an underscore for a hot letter (for example, a PROMPT control's display *text*). In this case, you double it up (&&) to end up with a single ampersand in the screen display.

### Example:

'string constant'	!A string constant
'It''s a girl!'	!With embedded apostrophe
'<27,15>'	!Using decimal ASCII codes
'A << B'	!With embedded left angle, A < B
'*{20}'	!Twenty asterisks, repeat-count notation
' '	!A null (blank) string

## Numeric Expressions

Numeric expressions may be used as parameters of procedures, the condition of IF, CASE, LOOP, or EXECUTE structures, or as the source portion of an assignment statement where the destination is a numeric variable. A numeric expression may contain arithmetic operators and the concatenation operator, but they may not contain logical operators. When used in a numeric expression, string constants and variables are converted to numeric intermediate values. If the concatenation operator is used, the intermediate value is converted to numeric after the concatenation occurs.

### Example:

```
Count + 1           !Add 1 to Count
(1 - N * N) / R     !N times N subtracted from 1 then divided by R
305 & 7854555       !Concatenate area code with phone number
```

### See Also:

Data Conversion Rules

## String Expressions

String expressions may be used as parameters of procedures and attributes, or as the source portion of an assignment statement when the destination is a string variable. String expressions may contain a single string or numeric variable, or a complex combination of sub-expressions, procedures, and operations.

### Example:

```
StringVar    STRING(30)
Name         STRING(10)
Weight       STRING(3)
Phone        LONG
            CODE
!Concatenate a constant and variable
StringVar = 'Address:' & Cus:Address

!Concatenate constant values
!and FORMAT procedure's return value
StringVar = 'Phone:' & ' 305-' & FORMAT(Phone,@P###-####P)

!Concatenate a constant and variable
StringVar = Weight & 'lbs.'
```

### See Also:

CLIP

The Concatenation Operator

Data Conversion Rules

FORMAT

## Logical Expressions

Logical expressions evaluate true-false conditions in IF, LOOP UNTIL, and LOOP WHILE control structures. Control is determined by the final result (true or false) of the expression. Logical expressions are evaluated from left to right. The right operand of an AND, OR, or XOR logical expression will only be evaluated if it could affect the result. Parentheses should be used to eliminate ambiguous evaluation and to control evaluation precedence. The level or precedence for the logical operators is as follows:

Level 1	Conditional operators
Level 2	~, NOT
Level 3	AND
Level 4	OR, XOR

### Example:

```
LOOP UNTIL KEYBOARD()      !True when user presses any key
  !some statements
END
```

```
IF A = B THEN RETURN.      !RETURN if A is equal to B
```

```
LOOP WHILE ~ Done#        !Loop while false (Done# = 0)
  !some statements
END
```

```
IF A >= B OR (C > B AND E = D) THEN RETURN.
!True if a >= b, also true if
!both c > b and e = d.
!The second part of the expression
!(after OR) is evaluated only if the
!first part is not true.
```

### See Also:

IF (conditional execution structure)

LOOP

## Property Expressions

`[target] [$] [control] { property [,element] }`

---

<i>target</i>	The label of an APPLICATION, WINDOW, REPORT, VIEW, or FILE structure, the label of a BLOB, or one of the built-in variables: TARGET, PRINTER, or SYSTEM. If omitted, TARGET is assumed.
<i>\$</i>	Required delimiter when both <i>target</i> and <i>control</i> are specified. Omit if either <i>target</i> or <i>control</i> is omitted.
<i>control</i>	A field number or field equate label for the control in the <i>target</i> structure (APPLICATION, WINDOW, or REPORT) to affect. If omitted, the <i>target</i> must be specified. The <i>control</i> must be omitted if the <i>target</i> is a FILE, BLOB, or the PRINTER or SYSTEM built-in variables.
<i>property</i>	An integer constant, EQUATE, or variable that specifies the property (attribute) to change. It can also be a string when referencing an OCX or OLE container property.
<i>element</i>	An integer constant or variable that specifies which element to change (for <i>properties</i> which are arrays).

This property expression syntax allows you access to all the attributes (properties) of APPLICATION, WINDOW, or REPORT structures, or any control within these structures. To specify an attribute of an APPLICATION, WINDOW, REPORT, VIEW, or FILE structure (not a component control), omit the *control* portion of the property expression. To specify a control in the current window, omit the *target* portion of the property expression.

REPORT data structures are never the *target* by default. Therefore, either SETTARGET must be used to change the *target* to the REPORT, or the REPORT structure's label must be explicitly specified as the *target* before you can change any property of the structure, or any control it contains.

Property expressions may be used in Clarion language statements anywhere a string expression is allowed, or as the destination or source of simple assignment statements. They may not be used in operating assignment statements (such as +=, \*=, etc.). Assigning a new value to a property is a simple assignment with the property as the destination and the new value as the source. Determining the current value of a property is a simple assignment where the property is the source and the variable to receive its value is the destination. A Property expression may also be used as an executable statement (without an assignment statement) when the property expression is a method call for an OLE or OCX control.

All properties are treated as string data at runtime; the compiler automatically performs any necessary data type conversion. Any property without parameters is binary (toggle). Binary properties are either "present" or "missing" and return a '1' if present, and "" (null) if missing. Changing the value of a binary property to "" (null), '0' (zero), or any non-numeric string sets it to missing. Changing it to any other value sets it to "present."

Most properties can be both examined (read) and changed (written). However, some properties are "read-only" and cannot be changed. Assigning a value to a "read-only" property has no effect at all. Other properties are "write-only" properties that are meaningless if read. Some properties are arrays that contain multiple values. The syntax for addressing a particular property array *element* uses a comma (not square brackets) as the delimiter between the *property* and the *element* number.

## Built-in Variables

There are three built-in variables in the Clarion for Windows runtime library: TARGET, PRINTER, and SYSTEM. These are only used with the property assignment syntax to identify the *target* in a property expression.

TARGET normally references the window that currently has focus. It can also be set to reference a window in another execution thread or the currently printing REPORT, enabling you to affect the properties of controls and windows in other execution threads and dynamically change report control properties while printing. The SETTARGET statement and SYSTEM {PROP:Target} property changes the TARGET variable's reference.

PRINTER references the Printer Properties (only) to be used by the next REPORT opened (and any subsequent reports).

SYSTEM specifies global properties used by the entire application. There are a number of runtime properties that may use the SYSTEM variable to set or query application-wide properties.

### Example:

```
MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS,RESIZE
    MENUBAR
        MENU('File'),USE(?FileMenu)
            ITEM('Open...'),USE(?OpenFile)
            ITEM('Close'),USE(?CloseFile),DISABLE
            ITEM('E&xit'),USE(?MainExit)
        END
        MENU('Help'),USE(?HelpMenu)
            ITEM('Contents'),USE(?HelpContents),STD(STD:HelpIndex)
            ITEM('Search for Help On...'),USE(?HelpSearch),STD(STD:HelpSearch)
            ITEM('How to Use Help'),USE(?HelpOnHelp),STD(STD:HelpOnHelp)
            ITEM('About MyApp...'),USE(?HelpAbout)
        END
    END
    TOOLBAR
        BUTTON('Open'),USE(?OpenButton),ICON(ICON:Open)
    END
END

CODE
OPEN(MainWin)
MainWin{PROP:Text} = 'A New Title'           !Change window title
?OpenButton{PROP:ICON} = ICON:Asterisk      !Change button icon
?OpenButton{PROP:AT,1} = 5                   !Change button x position
?OpenButton{PROP:AT,2} = 5                   !Change button y position
IF MainWin$?HelpContents{PROP:STD} <> STD:HelpIndex
    MainWin$?HelpContents{PROP:STD} = STD:HelpIndex
END
MainWin{PROP:MAXIMIZE} = 1                   !Expand to full screen
```

```

ACCEPT
CASE ACCEPTED()
    OF ?OpenFile
        !Which control was chosen?
    OROF ?OpenButton
        !Open... menu selection
    START(OpenFileProc)
        !Open button on toolbar
    OF ?MainExit
        !Start new execution thread
    OROF ?MainExitButton
        !Exit menu selection
    BREAK
        !Exit button on toolbar
    OF ?HelpAbout
        !Break ACCEPT loop
    HelpAboutProc
        !About... menu selection
    END
        !Call application information procedure
END
CLOSE(MainWin)
RETURN
!Close APPLICATION

```

**See Also:**

SETTARGET

Runtime Properties



## Runtime Expression Evaluation

Clarion has the ability to evaluate expressions dynamically created at runtime, rather than at development time. This allows a Clarion program to construct expressions "on the fly." This also makes it possible to allow an end-user to enter the expression to evaluate.

An expression is a mathematical or logical formula that produces a value; it is not a complete Clarion language statement. Expressions may only contain constant values, variables, or procedure calls which return a value, all connected by logical and/or arithmetic operators. An expression may be used as the source side of an assignment statement, a parameter of a procedure, a subscript of an array (a dimensioned variable), or the conditions of IF, CASE, LOOP, or EXECUTE structures.

Any program variable, and most of the internal Clarion procedures, can be used as part of a runtime expression string. User-defined procedures that fall within certain specific guidelines (described in the BIND statement documentation) may also be used in runtime expression strings.

All of the standard Clarion expression syntax is available for use in runtime expression strings. This includes parenthetical grouping and all the arithmetic, logical, and string operators. Dynamic expressions are evaluated just as any other Clarion expression and all the standard operator precedence level rules described in the Expression Evaluation section (see page 3) apply.

It takes three steps to use runtime expression strings:

- The variables that are allowed to be used in the expressions must be explicitly declared with the BIND statement.
- The expression must be built. This may involve concatenating user choices or allowing the user to directly type in their own expression.
- The expression is passed to the EVALUATE procedure which returns the result. If the expression is not a valid Clarion expression, ERRORCODE is set.

Once the expression is evaluated, its result is used just as the result of any hard-coded expression would be. For example, a runtime expression string could provide a filter expression to eliminate certain records when viewing or printing a database (the FILTER expression of a VIEW structure is an implicit runtime expression string).

### See Also:

BIND (declare runtime expression string variable)  
EVALUATE (return runtime expression string result)  
POPBIND (restore runtime expression string name space)  
PUSHBIND (save runtime expression string name space)  
UNBIND (free runtime expression string variable)

## BIND (declare runtime expression string variable)

**BIND**( | *name,variable* | )

| *name,procedure* |

| *group* |

---

<b>BIND</b>	Identifies variables allowed to be used in dynamic expressions.
<i>name</i>	A string constant containing the identifier used in the dynamic expression. This may be the same as the <i>variable</i> or <i>procedure</i> label.
<i>variable</i>	The label of any variable (including fields in FILE, GROUP, or QUEUE structures) or passed parameter. If it is an array, it must have only one dimension.
<i>procedure</i>	The label of a Clarion language PROCEDURE which returns a STRING, REAL, or LONG value. If parameters are passed to the <i>procedure</i> , they must be STRING value-parameters (passed by value, not by address) and may not be omissible.
<i>group</i>	The label of a GROUP, RECORD, or QUEUE structure declared with the BINDABLE attribute.

The **BIND** statement declares the logical name used to identify a variable, EQUATE, or user-defined procedure in runtime expression strings. A variable or user-defined procedure must be identified with the BIND statement before it can be used in an expression string for either the EVALUATE procedure or a VIEW structure's FILTER attribute.

BIND( <i>name,variable</i> )	The specified <i>name</i> is used in the expression in place of the label of the <i>variable</i> .
BIND( <i>name,procedure</i> )	The specified <i>name</i> is used in the expression in place of the label of the <i>procedure</i> .
BIND( <i>group</i> )	Declares all the variables within the GROUP, RECORD, or QUEUE (with the BINDABLE attribute) available for use in a dynamic expression. The contents of each variable's NAME attribute is the logical name used in the dynamic expression. If no NAME attribute is present, the label of the variable (including prefix) is used.

A GROUP, RECORD, or QUEUE structure declared with the BINDABLE attribute has space allocated in the .EXE for the names of all of the data elements in the structure. This creates a larger program that uses more memory than it normally would. Also, the more variables that are bound at one time, the slower the EVALUATE procedure will work. Therefore, BIND(*group*) should only be used when a large proportion of the constituent fields are going to be used.

**Example:**

```

PROGRAM
MAP
  AllCapsFunc (STRING) ,STRING           !Clarion procedure
END
Header      FILE,DRIVER('Clarion') ,PRE(Hea) ,BINDABLE  !Declare header file layout
OrderKey    KEY(Hea:OrderNumber)
Record      RECORD
OrderNumber LONG
ShipToName  STRING(20)
            END
            END

StringVar STRING(20)
CODE
BIND('ShipName',Hea:ShipToName)
BIND('SomeFunc',AllCapsFunc)
BIND('StringVar',StringVar)
StringVar = 'SMITH'
CASE EVALUATE('StringVar = SomeFunc(ShipName)')
OF ''
  IF ERRORCODE()
    MESSAGE('Error ' & ERRORCODE() & ' -- ' & ERROR())
  ELSE
    MESSAGE('Unkown error evaluating expression')
  END
OF '0'
  DO NonSmithProcess
OF '1'
  DO SmithProcess
END

AllCapsFunc PROCEDURE(PassedString)
CODE
RETURN(UPPER(PassedString))

```

**See Also:**

UNBIND  
 BINDEXPRESSION  
 EVALUATE  
 PUSHBIND  
 POPBIND  
 FILTER

## BINDEXPRESSION(declare runtime expression)

**BINDEXPRESSION**( *| name,expression |* )

---

**BINDEXPRESSION** Identifies variables allowed to be used in dynamic expressions.

*name* A string constant containing the identifier used in the dynamic expression.

*expression* A mathematical formula containing any valid combination of variables, functions, operators, and constants.

The **BINDEXPRESSION** statement declares the logical name used to identify an expression used in runtime expression strings.

The **EVALUATE** statement must parse an expression every time it is called. If some expression is evaluated frequently, this can be time consuming.

**BINDEXPRESSION** parses the expression only once and is saved in a pre-compiled form under the given *name*. Later, this expression can be used in **EVALUATE** as a stand alone, or as a part of another expression in **EVALUATE**, or in another **BINDEXPRESSION**.

**Example:**

```
    BIND('Var', Var)
    BINDEXPRESSION('Power2', 'Var * Var')
    ...

Var = 10

P2 = EVALUATE ('Power2')
...
BINDEXPRESSION ('Circle', '3.14159 * Power2')
BINDEXPRESSION ('color:red',color:red)
MESSAGE('color:red = ' & color:red & '|Eval(color:red)= ' &|
EVALUATE('color:red') )           !Shows same number twice

BINDEXPRESSION ('Match:Soundex',Match:Soundex)
FILTER ('MATCH(Cus:Name,NameWanted,Match:Soundex) ')
```

**See Also:**

BIND (declare runtime expression string variable)

EVALUATE (return runtime expression string result)

## EVALUATE (return runtime expression string result)

**EVALUATE**(*expression*)

**EVALUATE**     Evaluates runtime expression strings.

*expression*     A string constant or variable containing the expression to evaluate.

The **EVALUATE** procedure evaluates the *expression* and returns the result as a STRING value. If the *expression* does not meet the rules of a valid Clarion expression, the result is a null string (""), and ERRORCODE is set. A logical *expression* returns a string containing either zero ('0') or one ('1'), while an arithmetic *expression* returns the actual result of the *expression* (in a string). The more variables are bound at one time, the slower the EVALUATE procedure works. Therefore, BIND(*group*) should only be used when most of the *group*'s fields are needed, and UNBIND should be used to free all variables and user-defined procedures not currently required for use in dynamic expressions. **PATH()**, **SHORTPATH()** and **LONGPATH()** can now be used in expressions evaluated by the EVALUATE statements in runtime application and in the templates.

Field Qualification syntax (dot syntax) cannot be used in the *expression*. Variables should be bound using the standard prefix notation.

**Return Data Type:**     STRING

**Errors Posted:**

1010	Illegal Expression
1011	Variable Not Found
1012	Mismatched
1015	Some parameters of built-in functions that are used in the expression are omitted

**Example:**

```

MAP
AllCapsFunc PROCEDURE (STRING) , STRING                !Clarion procedure
END
Header      FILE, DRIVER('Clarion') , PRE (Hea) , BINDABLE !Declare header file layout
t
OrderKey    KEY (Hea:OrderNumber)
Record      RECORD
OrderNumber LONG
ShipToName  STRING (20)
            END
            END

StringVar   STRING (20)
```

```

CODE
BIND('ShipName',Hea:ShipToName)
BIND('SomeFunc',AllCapsFunc)
BIND('StringVar',StringVar)
StringVar = 'SMITH'
CASE EVALUATE('StringVar = SomeFunc(ShipName)')
OF ''
    IF ERRORCODE()
        MESSAGE('Error ' & ERRORCODE() & ' -- ' & ERROR())
    END
OF '0'
    DO NonSmithProcess
OF '1'
    DO SmithProcess
END

AllCapsFunc PROCEDURE(PassedString)
CODE
RETURN(UPPER(PassedString))

!***Additional Examples

BIND('Value1',Self.Value1)
BIND('StrVar',StringVar)

Self.Value1 = '15 + 10'
Evaluate(Value1)      !Returns 25

StringVar = 'True'
Evaluate('StrVar')    !Returns the characters 'True' (without the quotes)

```

**See Also:**

BIND  
 BINDEXPRESSION  
 FILTER  
 POPBIND  
 PUSHBIND  
 UNBIND

## POPBIND (restore runtime expression string name space)

### POPBIND

The **POPBIND** statement restores the previous BIND statement's *name* space for variables and procedures previously bound. This restores the previous scope used by previous BIND statements.

#### Example:

```
SomeProc PROCEDURE
```

```
OrderNumber  LONG
Item          LONG
Quantity      SHORT
```

```
CODE
BIND('OrderNumber',OrderNumber)
BIND('Item',Item)
BIND('Quantity',Quantity)
```

```
AnotherProc                                !Call another procedure
```

```
UNBIND('OrderNumber',OrderNumber)
UNBIND('Item',Item)
UNBIND('Quantity',Quantity)
```

```
AnotherProc PROCEDURE
```

```
OrderNumber  LONG
Item          LONG
Quantity      SHORT
```

```
CODE
PUSHBIND                                !Create new scope for BIND
BIND('OrderNumber',OrderNumber)         !Bind variables with same names in new scope
BIND('Item',Item)
BIND('Quantity',Quantity)
```

```
!Do some Processing
```

```
UNBIND('OrderNumber')
UNBIND('Item')
UNBIND('Quantity')
POPBIND                                !Restore previous scope for BIND
```

#### See Also:

PUSHBIND

EVALUATE

## PUSHBIND (save runtime expression string name space)

**PUSHBIND**( [ *clearflag* ] )

---

**PUSHBIND**      Creates a new scope for subsequent BIND statements.

*clearflag*      An integer constant or variable containing either zero (0) or one (1). When zero, the BIND statement's *name* space is cleared of all variables and procedures previously bound. When one, all variables and procedures previously bound are left in place. If omitted, the *clearflag* is zero.

The **PUSHBIND** statement creates a new scope for subsequent BIND statements. This scope terminates with the next POPBIND statement. This creates a new scope for subsequent BIND statements, allowing you to create new BIND *names* for variables with the same *name* without creating conflicts with the *names* from a previous scope.

**Example:**

```
SomeProc PROCEDURE
OrderNumber LONG
Item          LONG
Quantity      SHORT

CODE
BIND('OrderNumber',OrderNumber)
BIND('Item',Item)
BIND('Quantity',Quantity)

AnotherProc                                !Call another procedure

UNBIND('OrderNumber',OrderNumber)
UNBIND('Item',Item)
UNBIND('Quantity',Quantity)

AnotherProc PROCEDURE
OrderNumber LONG
Item          LONG
Quantity      SHORT

CODE
PUSHBIND                                !Create new scope for BIND
BIND('OrderNumber',OrderNumber) !Bind variables with same names in new scope
BIND('Item',Item)
BIND('Quantity',Quantity)

!Do some Processing

UNBIND('OrderNumber')
UNBIND('Item')
UNBIND('Quantity')
POPBIND                                !Restore previous scope for BIND
```

**See Also:**

POPBIND, EVALUATE



## UNBIND (free runtime expression string variable)

UNBIND( [*name*] )

**UNBIND**       Frees variables from use in runtime expression strings.

*name*           A string constant that specifies the identifier used by the dynamic expression evaluator. If omitted, all bound variables are unbound.

The **UNBIND** statement frees logical names previously bound by the BIND statement. The more variables that are bound at one time, the slower the EVALUATE procedure works. Therefore, UNBIND should be used to free all variables and user-defined procedures not currently available for use in runtime expression strings.

**Example:**

```

PROGRAM
MAP
  AllCapsFunc (STRING) ,STRING           !Clarion procedure
END

Header      FILE,DRIVER('Clarion'),PRE(Hea) !Declare header file layout
AcctKey      KEY(Hea:AcctNumber)
OrderKey     KEY(Hea:OrderNumber)
Record       RECORD
AcctNumber   LONG
OrderNumber  LONG
ShipToName   STRING(20)
ShipToAddr   STRING(20)
ShipToCity   STRING(20)
ShipToState  STRING(20)
ShipToZip    STRING(20)
            END
            END

Detail       FILE,DRIVER('Clarion'),PRE(Dtl),BINDABLE !Bindable RECORD structure
OrderKey     KEY(Dtl:OrderNumber)
Record       RECORD
OrderNumber  LONG
Item         LONG
Quantity     SHORT
            END
            END

CODE
BIND('ShipName',Hea:ShipToName)
BIND(Dtl:Record)
BIND('SomeFunc',AllCapsFunc)
UNBIND('ShipName')           !UNBIND the variable
UNBIND('SomeFunc')           !UNBIND the Clarion language procedure
UNBIND                       !UNBIND all bound variables

AllCapsFunc PROCEDURE(PassedString)
CODE
RETURN(UPPER(PassedString))

```



# 11 - Assignments

## Simple Assignments

*destination*      =      *source*

*destination*      The label of a variable or runtime property.

*source*            A numeric or string constant, variable, procedure, expression, or data structure property.

The = sign assigns the value of *source* to the *destination*; it copies the value of the *source* expression into the *destination* variable. If *destination* and *source* are different data types, the value the *destination* receives from the *source* is dependent upon the Data Conversion Rules.

### Example:

```
StringVar  STRING(10)
LongVar    LONG
RealVar     REAL
CODE
StringVar = 'JONES'           !Variable = string constant
RealVar = 3.14159             !Variable = numeric constant
RealVar = Sqrt(1 - Sine * Sine) !Variable = procedure return value
LongVar = B + C + 3           !Variable = numeric expression
StringVar = CLIP(FirstName) & ' ' Initial & ' ' & LastName
                                !Variable = string expression

StringVar = '10'              !Assign numeric data to string then
Longvar = StringVar           !Automatic data conversion results
                                !and Longvar will contain: 10
```

### See Also:

Data Conversion Rules

Property Expressions

# Operating Assignments

<i>destination</i>	+=	<i>source</i>
<i>destination</i>	-=	<i>source</i>
<i>destination</i>	*=	<i>source</i>
<i>destination</i>	/=	<i>source</i>
<i>destination</i>	^=	<i>source</i>
<i>destination</i>	%=	<i>source</i>

*destination*      Must be the label of a variable. This may not be a runtime property.

*source*            A constant, variable, procedure, or expression.

Operating assignment statements perform their operation on the *destination* and *source*, then assign the result to the *destination*. Operating assignment statements are more efficient than their functionally equivalent operations.

**Example:**

<u>Operating Assignment</u>	<u>Functional Equivalent</u>
A += 1	A = A + 1
A -= B	A = A - B
A *= -5	A = A * -5
A /= 100	A = A / 100
A ^= I + 1	A = A ^ (I + 1)
A %= 7	A = A % 7

**See Also:**

Data Conversion Rules

Property Expressions

## Deep Assignment



*destination*    **:=**    *source*

*destination*    The label of a GROUP, RECORD, or QUEUE data structure, or an array.

*source*    The label of a GROUP, RECORD, or QUEUE data structure, or a numeric or string constant, variable, procedure, or expression.

The **:=** sign executes a deep assignment statement which performs multiple individual component variable assignments from one data structure to another. The assignments are only performed between the variables within each structure that have exactly matching labels, ignoring all prefixes. The compiler looks within nested GROUP structures to find matching labels. Any variable in the *destination* which does not have a label exactly matching a variable in the *source*, is not changed.

Deep assignments are performed just as if each matching variable were individually assigned to its matching variable. This means that all normal data conversion rules apply to each matching variable assignment. For example, the label of a nested *source* GROUP may match a nested *destination* GROUP or simple variable. In this case, the nested *source* GROUP is assigned to the *destination* as a STRING, just as normal GROUP assignment is handled.

The name of a *source* array may match a *destination* array. In this case, each element of the *source* array is assigned to its corresponding element in the *destination* array. If the *source* array has more or fewer elements than the *destination* array, only the matching elements are assigned to the *destination*.

If the *destination* is an array variable that is not part of a GROUP, RECORD, or QUEUE, and the *source* is a constant, variable, or expression, then each element of the *destination* array is initialized to the value of the *source*. This is a much more efficient method of initializing an array to a specific value than using a LOOP structure and assigning each element in turn.

The *destination* or *source* may also name a CLASS structure, which, in this case, will be treated as a GROUP. However, if you do so, you violate the concept of encapsulation, since deep assignment is a structure piercing operation. Therefore, it is not recommended.

Finally, whenever possible it is always more efficient to use a direct assignment of two matching structures in lieu of deep assignments.

### Example:

```
Group1 GROUP
S      SHORT
L      LONG
      END
```

```
Group2 GROUP
L      SHORT
S      REAL
T      LONG
      END
```

**ArrayField** SHORT,DIM(1000)

CODE

```
Group2 :=: Group1      !Is equivalent to:
                        !Group2.S = Group1.S
                        !Group2.L = Group1.L
                        !and performs all necessary data conversion

ArrayField :=: 7        !Is equivalent to:
                        !LOOP I# = 1 to 1000
                        ! ArrayField[I#] = 7
                        !END
```

**See Also:**

GROUP

RECORD

QUEUE

DIM

## Reference Assignments

*destination*    &=    *Source*

---

*destination*    The label of a reference variable.

*source*            This may be:

- The label of a variable or data structure of the same type as referenced by the *destination*.
- The label of another reference variable of the same type as the *destination*.
- A call to a PROCEDURE which returns the data type the *destination* will receive.
- An expression (yielding a LONG value, such as the return value of the ADDRESS procedure) that defines the memory address of a variable of the same type as referenced by the *destination* (which must be a reference to any simple data type except STRING, CSTRING, PSTRING, or GROUP).
- The NULL built-in variable.

The &= sign executes a reference assignment statement. A reference assignment statement assigns a *reference to the source variable to the destination reference variable*. When used in a conditional expression (such as an IF statement), a reference assignment statement determines reference equality (are the two reference variables "pointing at" the same thing?).

Depending upon the data type being referenced, the *destination* reference variable may receive the *source's* memory address, or a more complex internal data structure (describing the location and type of *source* data).

When the *source* is the built-in variable NULL, the reference assignment statement may either clear the *destination* reference variable, or detect an unreferenced reference variable (when the reference assignment statement is placed in a conditional expression). **This is the recommended technique for testing for NULL in Clarion# programs.**

The declarations of the *destination* reference variable and its *source* must match exactly (unless the *destination* is declared as an ANY variable); reference assignment does not perform automatic type conversion. For example, a reference assignment statement to a *destination* declared as &QUEUE must have a *source* that is either another &QUEUE reference variable or the label of a QUEUE structure. However, if the *destination* is a reference to a string (&STRING), the *source* may also be a data structure that is normally treated as string data when addressed as a single unit (GROUP, RECORD, QUEUE, MEMO).

Casting (i.e., converting the value of a token from one type of data to another) of the address to a reference variable is not valid if the target reference variable is of the &STRING, &CSTRING, &PSTRING and &GROUP types. Reference variables of these types are not just address specific, but contain additional information.

If the *destination* reference variable is declared as an ANY variable, the *source* cannot be:

- a variable of &WINDOW, &REPORT, &FILE, &VIEW, &KEY, &BLOB, named-CLASS, reference-to-named-CLASS and reference-to-named-INTERFACE types
- a call to a PROCEDURE which returns a result of \*WINDOW, \*REPORT, \*FILE, \*VIEW, \*KEY, named- CLASS or named-INTERFACE types
- a call to a PROCEDURE with the RAW attribute which returns a result of ?, \*? or \*STRING types
- an expression returning a LONG value.

**Note:**

In Clarion# (Clarion.NET), reference assignments to objects are no longer required. Use the equal operator (=) for all reference type assignments. See the New in Clarion# topic for more information.

**Example:**

```
Queue1  QUEUE
ShortVar  SHORT
LongVar1  LONG
LongVar2  LONG
      END

QueueRef  &QUEUE           !Reference a QUEUE, only
Queue1Ref &Queue1          !Reference to a QUEUE defined exactly as Queue1, only

LongRef   &LONG             !Reference a LONG, only

LongRef2  &LONG             !Reference a LONG, only

CODE
QueueRef  &= Queue1         !Assign QUEUE reference
Queue1Ref &= Queue1         !Assign QUEUE reference

IF Queue1Ref &= QueueRef     !Are they referencing the same QUEUE?
  MESSAGE('Both Pointing at same QUEUE')
END

IF SomeCondition             !Evaluate some condition
  LongRef &= Queue1.LongVar1 !and reference an appropriate variable
ELSE
  LongRef &= Queue1.LongVar2
END
LongRef += 1                 !Increment either LongVar1 or LongVar2
                              !depending upon which variable is referenced

IF LongRef2 &= NULL          !Detect unreferenced reference variable and
  LongRef2 &= LongRef        !create a second reference to the same data
END

LongRef &= ADDRESS(Queue1.LongVar1) !Reference assign the address of
                                     !a simple data type
```

**See Also:**

Reference Variables, ANY, NEW



## CLEAR (clear a variable)

**CLEAR**(*label* [,*n*])

<b>CLEAR</b>	Clears the value from a variable.
<i>label</i>	The label of a variable (except BLOB types), GROUP, RECORD, QUEUE, CLASS, or FILE structure. If the variable has a DIM attribute, the entire array is cleared.
<i>N</i>	A numeric constant; either 1 or -1. If omitted or zero, numeric variables are cleared to zero, STRING variables are cleared to spaces, and PSTRING and CSTRING variables are set to zero length.

The **CLEAR** statement clears the value from the *label* variable.

The presence of the *n* parameter indicates a cleared value other than zero or blank. If *n* is 1, the *label* variable is set to the highest possible value for that data type. For the STRING, PSTRING and CSTRING data types, that is all ASCII 255. If *n* is -1, the *label* variable is set to the lowest possible value for that data type. For the STRING data type, that is all ASCII zeroes (0). For the PSTRING and CSTRING data types, that is a zero length string.

If the *label* parameter names a GROUP, RECORD, or QUEUE structure, all variables in the structure are cleared and all reference variables in the structure are set to NULL. If the *label* parameter names a FILE structure and the *n* parameter is omitted, all variables in the FILE structure (including any MEMO and/or BLOB fields) are cleared. If the *label* parameter names a CLASS structure or an object derived from a CLASS, all variables in the object are cleared and all reference variables are set to NULL.

If the variable has a DIM attribute, a single element can be cleared (i.e., CLEAR(MyName[n])), or the entire array is cleared if just the array name is specified (i.e., CLEAR(MyName)). For a STRING, it is possible to clear a range of elements by using string slicing (i.e., CLEAR(MyString[n:m])).

### Example:

```
MyQue QUEUE
F1      LONG
F2      STRING(20)
F3      &CSTRING    !Reference to a CSTRING
F4      ANY          !ANY can be a reference variable to any simple data type
END

CODE
CLEAR(MyQue)        !Equivalent to:
                    ! MyQue.F1 = 0
                    ! MyQue.F2 = ''
                    ! MyQue.F3 &= NULL
                    ! MyQue.F4 &= NULL

CLEAR(Count)        !Clear a variable
CLEAR(Cus:Record)    !Clear the record structure
CLEAR(Customer)      !Clear the record structure and any memos and blobs
CLEAR(Amount,1)      !Clear variable to highest possible value
CLEAR(Amount,-1)     !Clear variable to lowest possible value
```

**See Also:** Reference Assignment Statements, GROUP, RECORD, QUEUE, DIM

## Data Type Conversion Rules

The Clarion language provides automatic conversion between data types. However, some assignments can produce an unequal source and destination. Assigning an "out of range" value can produce unpredictable results.

**See Also:**

- Base Types

- BCD Operations and Procedures

- Type Conversion and Intermediate Results

- Simple Assignment Data Type Conversion

## Base Types

To facilitate this automatic data type conversion, Clarion internally uses four Base Types to which all data items are automatically converted when any operation is performed on the data. These types are: STRING, LONG, DECIMAL, and REAL. These are all standard Clarion data types.

The STRING Base Type is used as the intermediate type for all string operations. The LONG, DECIMAL, and REAL Base Types are used in all arithmetic operations. Which numeric type is used, and when, is determined by the original data types of the operands and the type of operation being performed on them. The "normal" Base Type for each data type is:

### Base Type LONG:

BYTE  
SHORT  
USHORT  
LONG  
DATE  
TIME  
Integer Constants  
Strings declared with @P pictures

### Base Type DECIMAL:

ULONG  
DECIMAL  
PDECIMAL  
STRING(@Nx.y)  
Decimal Constants

### Base Type REAL:

SREAL  
REAL  
BFLOAT4  
BFLOAT8  
STRING(@Ex.y)  
Scientific Notation Constants  
Untyped (? and \*?) Parameters

### Base Type STRING:

STRING  
CSTRING  
PSTRING  
String Constants

DATE and TIME data types are first converted to Clarion Standard Date and Clarion Standard Time intermediate values and have a LONG Base Type for all operations. For the most part, Clarion's internal use of these Base Types is transparent to the programmer and do not require any consideration when planning applications. However, for business programming with numeric data containing fractional portions (currency, for instance), using data types that have the DECIMAL Base Type has some significant advantages over REAL Base Types.

- DECIMAL supports 31 significant digits of accuracy for data storage while REAL only supports 15.
- DECIMAL automatically rounds to the precision specified by the data declaration, while REAL can create rounding problems due to the translation of decimal (base 10) numbers to binary (base 2) for processing by the CPU's Floating Point Unit (or Floating Point emulation software).
- On machines without a Floating Point Unit, DECIMAL is substantially faster than REAL.
- DECIMAL operations are closely linked with conventional (decimal) arithmetic.

## BCD Operations and Procedures

Clarion has a Binary Coded Decimal (BCD) library of operations and procedures that execute in a manner similar to the manner in which decimal arithmetic is performed on paper. These operations use internal intermediate values with 31 digits accuracy on both sides of the decimal point.

The big advantage of the BCD operations is that it is very easy to "see" what is happening because they execute just as you would with pencil and paper. Simply imagine doing the computation long hand and throwing away numbers that go off the end of the page (rounding to the right).

Having 31 fixed decimal places either side of the decimal point there are numbers that cannot be represented in a BCD system which can be represented by a REAL. Therefore, understanding what is going on is useful.

Generally, the only cases where underflow will affect you is in division operations, usually when dividing by a multiple of 3. For example:

```
100000/3 = 33333.3333333333333333333333333333  
(100000/3)-  
INT(100000/3)*100000 = 33333.33333333333333333333333300000
```

BCD computation times are very data sensitive; the time taken is proportional to how long the computation would take you by hand. Therefore, the longer the numbers involved, the longer the execution times. However, standard "tricks of the trade" (such as multiplying by a power of ten by shifting the decimal point) are spotted, making the BCD libraries fast in real world applications.

The following operations may execute as BCD operations:

<b>Addition (+), Subtraction (-), Multiplication (*)</b>	Performed as a BCD operation when neither operand has a REAL Base Type (both are LONG or DECIMAL) and one has the DECIMAL Base Type. Any digits appearing to the right of 1 <sup>^</sup> 31 disappear (wrap), and any to the left of 1 <sup>^</sup> -30 are rounded up.
<b>Division (/)</b>	Performed as a BCD operation when neither operand has a REAL Base Type (both are LONG or DECIMAL). Any digits appearing to the right of 1 <sup>^</sup> 31 disappear (wrap), and any to the left of 1 <sup>^</sup> -30 are rounded up.
<b>Exponentiation (^)</b>	Performed as a BCD operation when the first operand is a DECIMAL or LONG Base Type and the second operand is a LONG Base Type. Any digits appearing to the right of 1 <sup>^</sup> 31 disappear (wrap), and any to the left of 1 <sup>^</sup> -30 are rounded.
<b>ABS()</b>	Removes the sign from a DECIMAL variable or intermediate value and returns the DECIMAL value.
<b>INT()</b>	Truncates a DECIMAL intermediate value and returns a DECIMAL value.
<b>ROUND()</b>	If the second parameter is a LONG or DECIMAL Base Type, then rounding is performed as a BCD operation which returns a DECIMAL value. ROUND is very efficient as a BCD operation and should be used to compare REALs to DECIMALs at decimal width.

## Simple Assignment Data Type Conversion

The rules of simple assignment data type conversion from source into destination are as follows:

### BYTE =

#### (SHORT, USHORT, LONG, or ULONG)

The destination receives the low-order 8 bits of the source.

#### (DECIMAL, PDECIMAL, REAL, SREAL, BFLOAT8, or BFLOAT4)

The source is first converted to a LONG, which truncates any decimal portion, then the destination receives the low-order 8 bits of the LONG.

#### (STRING, CSTRING, or PSTRING)

The source must be a numeric value with no formatting characters. The source is converted to a LONG, which truncates any decimal portion, then the destination receives the low-order 8 bits of the LONG.

### SHORT =

#### BYTE

The destination receives the value of the source.

#### (USHORT, LONG, or ULONG)

The destination receives the low-order 16 bits of the source.

#### (DECIMAL, PDECIMAL, REAL, SREAL, BFLOAT8, or BFLOAT4)

The source is first converted to a LONG, which truncates any decimal portion, then the destination receives the low-order 16 bits of the LONG.

#### (STRING, CSTRING, or PSTRING)

The source must be a numeric value with no formatting characters. The source is first converted to a LONG, which truncates any decimal portion, then the destination receives the low-order 16 bits of the LONG.

### USHORT =

#### BYTE

The destination receives the value of the source.

#### (SHORT, LONG, or ULONG)

The destination receives the low-order 16 bits of the source.

#### (DECIMAL, PDECIMAL, REAL, SREAL, BFLOAT8, or BFLOAT4)

The source is first converted to a LONG, which truncates any decimal portion, then the destination receives the low-order 16 bits of the LONG.

#### (STRING, CSTRING, or PSTRING)

The source must be a numeric value with no embedded formatting characters. The source is first converted to a LONG, which truncates any decimal portion, then the destination receives the low-order 16 bits of the LONG.

## **LONG =**

### **(BYTE, SHORT, USHORT, or ULONG)**

The destination receives the value and the sign of the source.

### **(DECIMAL, PDECIMAL, REAL, SREAL, BFLOAT8, or BFLOAT4)**

The destination receives the value of the source, including the sign, up to  $2^{31}$ . If the number is greater than  $2^{31}$ , the destination receives the result of modulo  $2^{31}$ . Any decimal portion is truncated.

### **(STRING, CSTRING, or PSTRING)**

The source must be a numeric value with no embedded formatting characters. The source is first converted to a REAL, which is then converted to the LONG.

## **DATE =**

### **(BYTE, SHORT, USHORT, or ULONG)**

The destination receives the Btrieve format for the Clarion Standard Date for the value of the source.

### **(DECIMAL, PDECIMAL, REAL, SREAL, BFLOAT8, or BFLOAT4)**

The source is first converted to a LONG as a Clarion Standard Date, which truncates any decimal portion, then the destination receives the Btrieve format for the Clarion Standard Date.

### **(STRING, CSTRING, or PSTRING)**

The source must be a numeric value with no embedded formatting characters. The source is first converted to a LONG as a Clarion Standard Date, which truncates any decimal portion, then the destination receives the Btrieve format for the Clarion Standard Date.

## **TIME =**

### **(BYTE, SHORT, USHORT, or ULONG)**

The destination receives the Btrieve format for the Clarion Standard Time for the value of the source.

### **(DECIMAL, PDECIMAL, REAL, SREAL, BFLOAT8, or BFLOAT4)**

The source is first converted to a LONG as a Clarion Standard Time, which truncates any decimal portion, then the destination receives the Btrieve format for the Clarion Standard Time.

### **(STRING, CSTRING, PSTRING)**

The source must be a numeric value with no embedded formatting characters. The source is first converted to a LONG as a Clarion Standard Time, which truncates any decimal portion, then the destination receives the Btrieve format for the Clarion Standard Time.

**ULONG =****(BYTE, SHORT, or USHORT)**

The source is first converted to a LONG, then the destination receives the entire 32 bits of the LONG.

**LONG**

The destination receives the entire 32 bits of the source.

**(DECIMAL, PDECIMAL, REAL, SREAL, BFLOAT8, or BFLOAT4)**

The source is first converted to a LONG, which truncates any decimal portion, then the destination receives the entire 32 bits of the LONG.

**(STRING, CSTRING, or PSTRING)**

The source must be a numeric value with no embedded formatting characters. The source is first converted to a LONG, which truncates any decimal portion, then the destination receives the entire 32 bits of the LONG.

**REAL =****(BYTE, SHORT, USHORT, LONG, or ULONG)**

The destination receives the full integer portion and the sign of the source.

**(DECIMAL, PDECIMAL, SREAL, BFLOAT8, or BFLOAT4)**

The destination receives the sign, integer portion, and the decimal portion of the source.

**(STRING, CSTRING, PSTRING)**

The source must be a numeric string value with no embedded formatting characters. The destination receives the sign, integer, and decimal portion of the number. Trailing spaces are ignored.

**SREAL =****(BYTE, SHORT, USHORT, LONG, or ULONG)**

The destination receives the sign and value of the source.

**(DECIMAL, PDECIMAL, or REAL)**

The destination receives the sign, integer, and fractional portion of the source.

**(STRING, CSTRING, or PSTRING)**

The source must be a numeric string value with no embedded formatting characters. The destination receives the sign, integer, and decimal portion of the number. Trailing spaces are ignored.

**BFLOAT8 =****(BYTE, SHORT, USHORT, LONG, or ULONG)**

The destination receives the sign and value of the source.

**(DECIMAL, PDECIMAL, or REAL)**

The destination receives the sign, integer, and fractional portion of the source.

**(STRING, CSTRING, or PSTRING)**

The source must be a numeric string value with no embedded formatting characters. The destination receives the sign, integer, and decimal portion of the number. Trailing spaces are ignored.

## **BFLOAT4 =**

**(BYTE, SHORT, USHORT, LONG, or ULONG)**

The destination receives the sign and value of the source.

**(DECIMAL, PDECIMAL, or REAL)**

The destination receives the sign, integer, and fractional portion of the source.

**(STRING, CSTRING, or PSTRING)**

The source must be a numeric string value with no embedded formatting characters. The destination receives the sign, integer, and decimal portion of the number. Trailing spaces are ignored.

## **DECIMAL =**

**(BYTE, SHORT, USHORT, LONG, ULONG, or PDECIMAL)**

The destination receives the sign and the value of the source, wrapping or rounding as appropriate.

**(REAL, or SREAL)**

The destination receives the sign, integer, and the high order part of the fraction from the source. The high order fractional portion is rounded in the destination.

**(STRING, CSTRING, PSTRING)**

The source must be a numeric string value with no embedded formatting characters. The destination receives the sign, integer, and decimal portion of the number. Trailing spaces are ignored.

## **PDECIMAL =**

**(BYTE, SHORT, USHORT, LONG, ULONG, or DECIMAL)**

The destination receives the sign and the value of the source, wrapping or rounding as appropriate.

**(REAL, SREAL, BFLOAT8, or BFLOAT4)**

The destination receives the sign, integer, and the high order part of the fraction from the source. The high order fractional portion is rounded in the destination.

**(STRING, CSTRING, or PSTRING)**

The source must be a numeric string value with no embedded formatting characters. The destination receives the sign, integer, and decimal portion of the number. Trailing spaces are ignored.

## **STRING =**

**(BYTE, SHORT, USHORT, LONG, or ULONG)**

The destination receives the sign and the unformatted number. The value is left justified in the destination.

**(DECIMAL, PDECIMAL, REAL, SREAL, BFLOAT8, or BFLOAT4)**

The destination receives the sign, integer, and fractional portion of the source (rounded into the string's picture format). The value is left justified in the destination.



**CSTRING =****(BYTE, SHORT, USHORT, LONG, or ULONG)**

The destination receives the sign and the unformatted number. The value is left justified in the destination.

**(DECIMAL, PDECIMAL, REAL, SREAL, BFLOAT8, or BFLOAT4)**

The destination receives the sign, integer, and fractional portion of the source (rounded into the string's picture format). The value is left justified in the destination.

**PSTRING =****(BYTE, SHORT, USHORT, LONG, or ULONG)**

The destination receives the sign and the unformatted number. The value is left justified in the destination.

**(DECIMAL, PDECIMAL, REAL, SREAL, BFLOAT8, or BFLOAT4)**

The destination receives the sign, integer, and fractional portion of the source (rounded into the string's picture format). The value is left justified in the destination.



## 12 - Execution Control

### ACCEPT (the event processor)



**ACCEPT**

*statements*

**END**

---

**ACCEPT**      The event handler.

*statements*      Executable code statements.

The **ACCEPT** loop is the event handler that processes events generated by Windows for the APPLICATION or WINDOW structures. An ACCEPT loop and a window are bound together, in that, when the window is opened, the next ACCEPT loop encountered will process all events for that window.

ACCEPT operates in the same manner as a LOOP--the BREAK and CYCLE statements can be used within it. The ACCEPT loop cycles for every event that requires program action. ACCEPT waits until the Clarion runtime library sends it an event that the program should process, then cycles through to execute its *statements*. During the time ACCEPT is waiting, the Clarion runtime library has control, automatically handling common events from Windows that do not need specific program action (such as screen re-draws).

The current contents of all STRING control USE variables (in the top window of each thread) automatically display on screen each time the ACCEPT loop cycles to the top. This eliminates the need to explicitly issue a DISPLAY statement to update the video display for display-only data. USE variable contents for any other control automatically display on screen for any event generated for that control, unless PROP:Auto is turned on to automatically display all USE variables each time through the ACCEPT loop.

Within the ACCEPT loop, the program determines what happened by using the following procedures:

EVENT()	Returns a value indicating what happened. Symbolic constants for events are in the EQUATES.CLW file.
FIELD()	Returns the field number for the control to which the event refers, if the event is a field-specific event.
ACCEPTED()	Returns the field number for the control to which the event refers for the EVENT:Accepted event.
SELECTED()	Returns the field number for the control to which the event refers for the EVENT:Selected event.
FOCUS()	Returns the field number of the control that has input focus, no matter what event occurred.

MOUSEX()           Returns the x-coordinate of the mouse cursor.

MOUSEY()           Returns the y-coordinate of the mouse cursor.

Two events cause an implicit BREAK from the ACCEPT loop. These are the events that signal the close of a window (EVENT:CloseWindow) or close of a program (EVENT:CloseDown). The program's code need not check for these events as they are handled automatically. However, the code may check for them and execute some specific action, such as displaying a "You sure?" window or handling some housekeeping details. A CYCLE statement at that point returns to the top of the ACCEPT loop without exiting the window or program.

Similarly, there are several other events whose action can also be terminated by a CYCLE statement: EVENT:Move, EVENT:Size, EVENT:Restore, EVENT:Maximize, and EVENT:Iconize. A CYCLE statement in response to any of these events stops the normal action and prohibits generation of the related EVENT:Moved, EVENT:Sized, EVENT:Restored, EVENT:Maximized, or EVENT:Iconized.

**Example:**

```
CODE
OPEN(Window)
ACCEPT                   !Event handler
CASE FIELD()
OF 0                   !Handle Field-independent events
CASE EVENT()
OF EVENT:Move
CYCLE                   !Do not allow user to move the window
OF ?Field1           !Handle events for Field1
CASE EVENT()
OF EVENT:Selected
! pre-edit code for field1
OF EVENT:Accepted
! completion code for field1
END
END !CASE FIELD
END !ACCEPT LOOP
```

**See Also:**

EVENT

Modal Events

APPLICATION

WINDOW

FIELD

FOCUS

ACCEPTED

SELECTED

CYCLE

BREAK

## CASE (selective execution structure)

```

CASE condition
  OF expression [ TO expression ]
    statements
  [ OROF expression [ TO expression ] ]
    statements
  [ ELSE ]
    statements
END

```

---

<b>CASE</b>	Initiates a selective execution structure.
<i>condition</i>	A numeric or string variable or expression.
<b>OF</b>	The <i>statements</i> following an <b>OF</b> are executed when the <i>expression</i> following the OF option is equal to the <i>condition</i> of the CASE. There may be many OF options in a CASE structure.
<i>expression</i>	A numeric or string constant, variable, or expression.
<b>TO</b>	<b>TO</b> allows a range of values in an OF or OROF. The <i>statements</i> following the OF (or OROF) are executed if the value of the <i>condition</i> falls within the inclusive range specified by the <i>expressions</i> . The <i>expression</i> following OF (or OROF) must contain the lower limit of the range. The <i>expression</i> following TO must contain the upper limit of the range.
<b>OROF</b>	The <i>statements</i> following an <b>OROF</b> are executed when either the <i>expression</i> following the OROF or the OF option is equal to the <i>condition</i> of the CASE. There may be many OROF options associated with one OF option. An OROF may optionally be put on a separate line. An OROF does not terminate preceding <i>statements</i> groups, so control "falls into" the OROF <i>statements</i> .
<b>ELSE</b>	The <i>statements</i> following <b>ELSE</b> are executed when all preceding OF and OROF options have been evaluated as not equivalent. ELSE is not required; however, when used, it must be the last option in the CASE structure.
<i>statements</i>	Any valid Clarion executable source code.

A **CASE** structure selectively executes the first set of *statements* encountered for which there is equivalence between the *condition* and *expression* or range of *expressions*. CASE structures may be nested within other executable structures and other executable structures may be nested within CASE structures. The CASE structure must terminate with an END statement (or period).

For those situations where the program's logic could allow using either a CASE structure or a complex IF/ELSIF structure, the CASE structure will generally generate more efficient object code. EXECUTE generates the most efficient object code for those special cases where the condition evaluates to an integer in the range of 1 to n.

Regarding the use of the OF-TO and OROF-TO clauses, *both* expressions are evaluated even if the value of the CASE-expression is less than the lower boundary of the specified range.

For example:

```
CASE A
OF Func1() TO Func2()
...
END
```

In this case, both **Func1()** and **Func2()** are called even if **A < Func1()**.

**Example:**

```
CASE ACCEPTED()                                !Evaluate field edit routine
OF ?Name                                        !If field is Name
  ERASE(?Address,?Zip)                          !erase Address through Zip
  GET(NameFile,NameKey)                        !get the record

CASE Action                                    !Evaluate Action
OF 1                                           !adding record - does not exist
  IF NOT ERRORCODE()                          !should be a file error
    ErrMsg = 'ALREADY ON FILE'                !otherwise display error message
    DISPLAY(?Address,?Zip)                    !display address through zipcode
    SELECT(?Name)                             !re-enter the name
  END
OF 2 OROF 3                                    !change or delete - record exists
  DISPLAY(?Address,?Zip)                      !display address through zipcode
END                                           !end case action

CASE Name[1]                                  !Get first letter of name
OF 'A' TO 'M'                                 !Process first half of alphabet
OROF 'a' TO 'm'
  DO FirstHalf
OF 'N' TO 'Z' OROF 'n' TO 'z'                !Process second half of alphabet
  DO SecondHalf
END                                           !End case sub(name)

OF ?Address                                    !If field is address
  DO AddressVal                               !call validation routine
END                                           !End case accepted()
```

**See Also:**

EXECUTE

IF

## EXECUTE (statement execution structure)

**EXECUTE** *expression*

*statement 1*

*statement 2*

[ **BEGIN**

*statements*

**END** ]

*statement n*

[ **ELSE** ]

*statement*

**END**

---

**EXECUTE** Initiates a single statement execution structure.

*expression* A numeric expression or a variable that contains a numeric integer.

*statement 1* A single statement that executes only when the *expression* is equal to 1.

*statement 2* A single statement that executes only when the *expression* is equal to 2.

**BEGIN** **BEGIN** marks the beginning of a structure containing a number of lines of code. The BEGIN structure will be treated as a single statement by the EXECUTE structure. The BEGIN structure is terminated by a period or the keyword END.

*statement n* A single statement that executes only when the *expression* is equal to *n*.

**ELSE** The *statement* following **ELSE** executes when the *expression* evaluates to a value outside the range of 1 to *n*, where *n* is defined as the total number of single statements between the EXECUTE and the ELSE.

*statement* A single statement that executes only when the *expression* is outside the valid range.

An **EXECUTE** structure selects a single executable statement (or executable code structure) based on the value of the *expression*. The EXECUTE structure must terminate with an END statement (or period).

If the *expression* equals 1, the first statement (*statement 1*) executes. If *expression* equals 2, the second statement (*statement 2*) executes, and so on. If the value of the *expression* is zero, or greater than the total number of statements (or structures) within the EXECUTE structure, the *statement* in the ELSE clause executes. If no ELSE clause is present, program execution continues with the next statement following the EXECUTE structure.

EXECUTE structures may be nested within other executable structures and other executable code structures (IF, CASE, LOOP, EXECUTE, and BEGIN) may be nested within an EXECUTE. For those situations where the program's logic could allow using either an EXECUTE, CASE, or an IF/ELSIF structure, the EXECUTE structure will generate more efficient object code, and is the preferred method.

**Example:**

```

EXECUTE Transact      !Evaluate Transact
  ADD(Customer)       !Execute if Transact = 1
  PUT(Customer)       !Execute if Transact = 2
  DELETE(Customer)    !Execute if Transact = 3
END                  !End execute

EXECUTE CHOICE()      !Evaluate CHOICE() procedure
  OrderPart           !Execute if CHOICE() = 1
  BEGIN               !Execute if CHOICE() = 2
    SavVendor" = Vendor
    UpdVendor
    IF Vendor <> SavVendor"
      Mem:Message = 'VENDOR NAME CHANGED'
    END
  END
  CASE VendorType     !Execute if CHOICE() = 3
  OF 1
    UpdPartNo1
  OF 2
    UpdPartNo2
  END
  RETURN              !Execute if CHOICE() = 4
END                  !End execute

EXECUTE SomeValue
  DO OneRoutine
  DO TwoRoutine
ELSE
  MESSAGE('SomeValue did not contain a 1 or 2')
END

```

**See Also:**

BEGIN  
CASE  
IF



## IF (conditional execution structure)

```

IF logical expression [ THEN ]
    statements
[ ELSIF logical expression [ THEN ]
    statements ]
[ ELSE
    statements ]
END

```

---

<b>IF</b>	Initiates a conditional statement execution structure.
<i>logical expression</i>	A variable, procedure, or expression which evaluates a condition. Control is determined by the result (true or false) of the expression. Zero (or blank) evaluates as false, anything else is true.
<b>THEN</b>	The <i>statements</i> following THEN execute when the preceding <i>logical expression</i> is true. If used, THEN must only appear on the same line as <b>IF</b> or <b>ELSIF</b> .
<i>statements</i>	An executable statement, or a sequence of executable statements.
<b>ELSIF</b>	The <i>logical expression</i> following an <b>ELSIF</b> is evaluated only when all preceding <b>IF</b> or <b>ELSIF</b> conditions were evaluated as false.
<b>ELSE</b>	The <i>statements</i> following <b>ELSE</b> execute only when all preceding <b>IF</b> and <b>ELSIF</b> options evaluate as false. ELSE is not required, however, when used, it must be the last option in the IF structure.

An **IF** structure controls program execution based on the outcome of one or more *logical expressions*. IF structures may have any number of ELSIF statement groups. IF structures may be "nested" within other executable structures. Other executable structures may be nested within an IF structure. Each IF structure must terminate with an END statement (or period).

**Example:**

```

IF Cus:TransCount = 1                                !If new customer
  AcctSetup                                           !call account setup procedure
ELSIF Cus:TransCount > 10 AND Cus:TransCount < 100  !If regular customer
  DO RegularAcct                                     !process the account
ELSIF Cus:TransCount > 100                           !If special customer
  DO SpecialAcct                                    !process the account
ELSE                                                  !Otherwise
  DO NewAcct                                         !process the account
  IF Cus:Credit
    CheckCredit
  ELSE
    CLEAR(Cus:CreditStat)
  END
  ! verify credit status
END
IF ERRORCODE()
  ErrHandler(Cus:AcctNumber,Trn:InvoiceNbr)         !Handle errors
END

```

**See Also:**

EXECUTE

CASE

## LOOP (iteration structure)

```

label  LOOP [      | count TIMES | ]
        | i = initial TO limit [ BY step ] |
        | UNTIL logical expression |
        | WHILE logical expression |
        statements
        | END |
        | UNTIL      logical expression |
        | WHILE      logical expression |

```

---

<b>LOOP</b>	Initiates an iterative statement execution structure.
<i>count</i>	An integer constant, variable, or expression specifying the number of TIMES <i>statements</i> in the LOOP execute.
<b>TIMES</b>	Executes <i>count</i> number of iterations of the <i>statements</i> .
<i>i</i>	The label of a variable which automatically increments (or decrements, if <i>step</i> is negative) on each iteration.
= <i>initial</i>	A numeric constant, variable, or expression specifying the value of the increment variable ( <i>i</i> ) on the first pass through the LOOP structure.
TO <i>limit</i>	A numeric constant, variable, or expression specifying the terminating value for the LOOP. When <i>i</i> is greater than <i>limit</i> (or less than, if the <i>step</i> is a negative value) the LOOP structure control sequence terminates. The <i>i</i> variable contains the last incremental value greater than (or less than) the <i>limit</i> after the LOOP terminates. Functions used in expressions used as a <i>limit</i> are only evaluated once (unlike the conditions of UNTIL and WHILE below).
BY <i>step</i>	A numeric constant, variable, or expression specifying the quantity by which the <i>i</i> variable increments (or decrements, if the value is negative) on each iteration of the LOOP. If BY <i>step</i> is omitted, <i>i</i> increments by 1.
<b>UNTIL</b>	When placed on the LOOP statement, UNTIL evaluates the <i>logical expression</i> before each iteration. When terminating the LOOP structure, UNTIL evaluates the <i>logical expression</i> after each iteration. If the <i>logical expression</i> evaluates to true, the LOOP terminates.
<b>WHILE</b>	When placed on the LOOP statement, WHILE evaluates the <i>logical expression</i> before each iteration. When terminating the LOOP structure, WHILE evaluates the <i>logical expression</i> after each iteration. If the <i>logical expression</i> evaluates to false, the LOOP terminates.

*logical expression*      A numeric or string variable, expression, or procedure. A *logical expression* evaluates a condition. Control is determined by the result (true or false) of the expression. A zero numeric or blank string value evaluates as false, anything else is true.

*statements*      An executable statement, or a sequence of executable statements.

A **LOOP** structure repetitively executes the *statements* within its structure. LOOP structures may be nested within other executable code structures. Other executable code structures may be nested within a LOOP structure. Each LOOP structure must terminate with an END statement (or period), an UNTIL, or a WHILE statement.

A LOOP with no condition at the top or bottom iterates continuously until a BREAK or RETURN statement executes. BREAK discontinues the LOOP and continues program execution with the statement following the LOOP structure. All statements within a LOOP structure executes unless a CYCLE statement executes. CYCLE immediately sends program execution back to the top of the LOOP for the next iteration, without executing any further statements in the LOOP following the CYCLE.

LOOP UNTIL or LOOP WHILE *logical expressions* are always evaluated at the top of the LOOP, before the LOOP *statements* execute. Therefore, if the *logical expression* is false on the first pass, the LOOP *statements* will not execute even once. To create a LOOP that always executes its *statements* at least once, the UNTIL or WHILE clause must terminate the LOOP structure.

**Example:**

```
LOOP                                     !Continuous loop
Char = GetChar()                        !get a character
IF Char <> CarrReturn                    !if it's not a carriage return
    Field = CLIP(Field) & Char          !append the character
ELSE                                    !otherwise
    BREAK                               !break out of the loop
END                                     !End if
END                                     !end loop

IF ERRORCODE()                          !On error
    LOOP 3 TIMES                        !loop three times
        BEEP                           !sound the alarm
    END                                !End loop
END                                    !end if

LOOP I# = 1 TO 365 BY 7                  !Loop, increment I# by 7 each time
    GET(DailyTotal,I#)                 !read every 7th record
    DO WeeklyJob
END                                     !I# contains 372 when the LOOP terminates

LOOP I# = 10 TO 1 BY -1                 !Loop, decrementing I# by 1 each time
    DO SomeRoutine
END                                     !I# contains zero (0) when the LOOP terminates

SET(MasterFile)                        !Point to first record
LOOP UNTIL EOF(MasterFile)              !Process all the records
    NEXT(MasterFile)                   !read a record
    ProcMaster                          !call the procedure
END

LOOP WHILE KEYBOARD()                  !Empty the keyboard buffer
    ASK                                !without processing keystrokes
UNTIL KEYCODE() = EscKey                !but break the loop for Escape
```

## Execution Control Statements:

### BREAK (immediately leave loop)

**BREAK** [ *label* ]

**BREAK** Transfers control to the first statement following the terminator of a LOOP or ACCEPT structure.

*label* The label on the LOOP or ACCEPT statement from which to break. This must be the label of a nested loop structure containing the BREAK statement.

The **BREAK** statement immediately terminates processing in the LOOP or ACCEPT structure and transfers control to the first statement following the terminating END, WHILE, or UNTIL statement of the LOOP, or the terminating END statement of the ACCEPT structure.

BREAK may only be used in a LOOP or ACCEPT loop structure. The use of the optional *label* argument allows you to cleanly break out of multiple levels of nested loops, eliminating one common use of GOTO.

#### Example:

```

LOOP                                !Loop
  ASK                               !wait for a keystroke
  IF KEYCODE() = EscKey             !if Esc key pressed
    BREAK                           !break out of the loop
  ELSE                               !otherwise
    BEEP                             !sound the alarm
  END
END

Loop1 LOOP                          !Loop1 is the label
  DO ParentProcess
    Loop2 LOOP                      !Loop2 is the label
      DO ChildProcess
        IF SomeCondition
          BREAK Loop1              !Break out of both nested loops
        END
      END
    END
  END

ACCEPT                              !ACCEPT loop structure
CASE ACCEPTED()
OF ?Ok
  CallSomeProc
OF ?Cancel
  BREAK                            !break out of the loop
END
END

```

#### See Also:

LOOP

CYCLE

ACCEPT

## CYCLE (go to top of loop)

**CYCLE** [ *label* ]

---

**CYCLE** Transfers control back to the top of a LOOP or ACCEPT structure.

*label* The label on the LOOP or ACCEPT statement to which to return. This must be the label of a nested loop structure containing the CYCLE statement.

The **CYCLE** statement passes control immediately back to the top of the LOOP or ACCEPT loop. CYCLE may only be used in a LOOP or ACCEPT loop structure. The use of the optional *label* argument allows you to cleanly go back to the top of outer levels of nested loops, eliminating one common use of GOTO.

In an ACCEPT loop, for certain events, CYCLE terminates an automatic action before it is performed. This behavior is documented for each event so affected:

- Event:Iconize
- Event:Maximize
- Event:Move
- Event:PreAlertKey
- Event:Restore
- Event:Size
- Event:Contracting
- Event:Expanding
- EVENT:CloseDown
- EVENT:CloseWindow
- EVENT:DDEPoke
- EVENT:DDEExecute

**Example:**

```

SET(MasterFile)           !Point to first record
LOOP                      !Process all the records
NEXT(MasterFile)          !read a record
IF ERRORCODE() THEN BREAK. !Get out of loop at end of file
DO MatchMaster            !check for a match
IF NoMatch                !if match not found
    CYCLE                 !jump to top of loop
END
DO TransVal               !validate the transaction
PUT(MasterFile)           !write the record
END

Loop1 LOOP                !Loop1 is the label
    DO ParentProcess
Loop2 LOOP                !Loop2 is the label
    DO ChildProcess
    IF SomeCondition
        CYCLE Loop1       !Cycle back to top of outer loop
    END
END
END

```

**See Also:**

LOOP

BREAK

ACCEPT

## DO (call a ROUTINE)

**DO** *label*

---

**DO**                Executes a ROUTINE.

*label*             The label of a ROUTINE statement.

The **DO** statement is used to execute a ROUTINE local to a PROGRAM or PROCEDURE. When a ROUTINE completes execution, program control reverts to the statement following the DO statement. A ROUTINE may only be called within the CODE section containing the ROUTINE's source code.

**Example:**

```
DO NextRecord      !Call the next record routine
DO CalcNetPay      !Call the calc net pay routine
```

**See Also:**

EXIT

ROUTINE



## EXIT (leave a ROUTINE)

### EXIT

---

The **EXIT** statement immediately leaves a ROUTINE and returns program control to the statement following the DO statement that called it. This is different from RETURN, which completely exits the PROCEDURE even when called from within a ROUTINE.

An EXIT statement is not required. A ROUTINE with no EXIT statement terminates automatically when the entire sequence of statements in the ROUTINE is complete.

#### Example:

```
CalcNetPay ROUTINE
  IF GrossPay = 0    !If no pay
    EXIT            ! exit the routine
  END
  NetPay = GrossPay - FedTax - Fica
  QtdNetPay += NetPay
  YtdNetPay += NetPay
```

#### See Also:

DO

RETURN

## GOTO (go to a label)

**GOTO** *target*

---

**GOTO** Unconditionally transfers program control to another statement.

*target* The label of another executable statement within the PROGRAM, PROCEDURE, or ROUTINE.

The **GOTO** statement unconditionally transfers control from one statement to another. The *target* of a GOTO must not be the label of a ROUTINE or PROCEDURE.

The scope of GOTO is limited to the currently executing ROUTINE or PROCEDURE--it may not *target* a label outside the ROUTINE or PROCEDURE in which it is used.

Extensive use of GOTO is generally not considered good structured programming practice. LOOP is usually considered a better alternative.

**Example:**

```
ComputeIt PROCEDURE (Level)
CODE
  IF Level = 0
    GOTO PassCompute          !Skip rate calculation if no Level
  END
  Rate = Level * Markup       !Compute Rate
  RETURN (Rate)               !and return it
PassCompute RETURN (999999)   !Return bogus number
```

**See Also:**

LOOP

## RETURN (return to caller)

**RETURN** [*expression*]

**RETURN** Terminates a PROGRAM or PROCEDURE.

*expression* The *expression* passes the return value of a PROCEDURE prototyped to return a value back to the expression in which the PROCEDURE was used. This may be NULL if the PROCEDURE returns a reference.

The **RETURN** statement terminates a PROGRAM or PROCEDURE and passes control back to the caller. When RETURN is executed from the CODE section of a PROGRAM, the program is terminated, all files and windows are closed, and control is passed to the operating system.

RETURN is required in a PROCEDURE prototyped to return a value and optional in a PROGRAM or PROCEDURE which does not return a value. If RETURN is not used in a PROCEDURE or PROGRAM, an implicit RETURN occurs at the end of the executable code. The end of executable code is defined as the end of the source file, or the beginning of another PROCEDURE or ROUTINE.

RETURN from a PROCEDURE (whether explicit or implicit) automatically closes any local APPLICATION, WINDOW, REPORT, or VIEW structure opened in the PROCEDURE. It does not automatically close any Global or Module Static APPLICATION, WINDOW, REPORT, or VIEW. It also closes and frees any local QUEUE structure declared without the STATIC attribute.

An *expression* in parentheses is also a valid expression by the syntax definition of expressions. If a variable is enclosed in parentheses, it is dereferenced to a value of that variable and then casted to one of the base types. Regarding the use of parenthesis with RETURN, if a function has a variable or reference RETURN type, the returned variable used in the RETURN statement must not be enclosed in parentheses.

### Example:

```
IF Done#
  RETURN                               !Quit when done
END

DayOfWeek PROCEDURE (Date)             !Procedure to return the day of the week
RetVal  STRING(9)
CODE
EXECUTE Date % 7                       !Determine what day of week Date is
  RetVal = 'Monday'
  RetVal = 'Tuesday'
  RetVal = 'Wednesday'
  RetVal = 'Thursday'
  RetVal = 'Friday'
  RetVal = 'Saturday'
ELSE
  RetVal = 'Sunday'
END
RETURN RetVal                          !and RETURN the correct day string
```

**See Also:** PROCEDURE, PROCEDURE Return Types



## 13 - Built-in Procedures

### ABS (return absolute value)

*ABS(expression)*

---

**ABS**                Returns absolute value.

*expression*        A constant, variable, or expression.

The **ABS** procedure returns the absolute value of an *expression*. The absolute value of a number is always positive (or zero).

**Return Data Type:**    REAL or DECIMAL

**Example:**

```
C = ABS (A - B)                    !C is absolute value of the difference
IF B < 0
  B = ABS (B)                      !If b is negative make it positive
END
```

**See Also:**

BCD Operations and Procedures

## ACCEPTED (return control just completed)



### ACCEPTED( )

The **ACCEPTED** procedure returns the field number of the control on which an EVENT:Accepted event occurred. ACCEPTED returns zero (0) for all other events.

Positive field numbers are assigned by the compiler to all WINDOW controls, in the order their declarations occur in the WINDOW structure. Negative field numbers are assigned to all APPLICATION controls. In executable code statements, field numbers are usually represented by field equate labels--the label of the USE variable preceded by a question mark (?FieldName).

Controls with a USE *variable* get EVENT:Accepted, but not those with a USE *field equate*.

**Return Data Type:**      SIGNED

#### Example:

```
CASE ACCEPTED ( )           !Process post-edit code
OF ?Cus:Company
  !Edit field value
OF ?Cus:CustType
  !Edit field value
END
```

#### See Also:

ACCEPT

EVENT

## ACOS (return arccosine)

**ACOS**(*expression*)

**ACOS** Returns inverse cosine.

*expression* A numeric constant, variable, or expression for the value of the cosine.

The **ACOS** procedure returns the inverse cosine. The inverse of a cosine is the angle that produces the cosine. The return value is the angle in radians.  $\pi$  is a constant which represents the ratio of the circumference and radius of a circle. There are  $2\pi$  radians (or 360 degrees) in a circle.

**Return Data Type:** REAL

### Example:

```
PI      EQUATE (3.1415926535898)    !The value of PI
Rad2Deg EQUATE (57.295779513082)    !Number of degrees in a radian
Deg2Rad EQUATE (0.0174532925199)    !Number of radians in a degree
CODE
  InvCosine = ACOS (CosineAngle)    !Get the Arccosine
```

### See Also:

TAN

ATAN

SIN

ASIN

COS

## ADD (add an entry)

```
| file |  
| file ,length|  
ADD( | queue| )  
| queue, [+]key,..., [-]key]|  
| queue, name|  
| queue, function|  
| queue, pointer|
```

---

**ADD**            Writes a new record to a FILE or QUEUE.

*file*            The label of a FILE declaration.

*length*          An integer constant, variable, or expression which contains the number of bytes in the RECORD buffer to write to the *file*. If omitted or out of range, *length* defaults to the length of the RECORD structure.

*queue*           The label of a QUEUE structure, or the label of a passed QUEUE parameter.

+ -              The leading plus or minus sign specifies the *key* is sorted in ascending or descending sequence. If omitted, ascending sequence is the default.

*key*             The label of a field declared within the QUEUE structure. If the QUEUE has a PRE attribute, the *key* must include the prefix.

*name*            A string constant, variable, or expression containing the NAME attribute of QUEUE fields, separated by commas, and optional leading + or - signs for each attribute. This parameter is case sensitive.

*function*       The label of the function containing two parameters of a \*GROUP or named GROUP passed by address, and having a SIGNED return value. Both parameters must use the same parameter type, and cannot be omitted. The RAW, C and PASCAL attributes are not permitted in the prototype declaration. See Additional Queue Considerations.

*pointer*         A numeric constant, variable, or numeric expression. The *pointer* must be in the range from 1 to the number of entries in the memory queue.

The **ADD** statement writes a new record to a FILE or QUEUE.



## FILE Usage

---

All KEYS associated with the *file* are also updated during each ADD. If there is no room for the record on disk, the "Access Denied" error is posted. If an error is posted, no record is added to the file.

You can use the DUPLICATE procedure to check whether the ADD will return the "Creates Duplicate Key" error. The DUPLICATE procedure assumes that the contents of the RECORD structure data buffer are duplicated at the current record pointer location. Therefore, when using DUPLICATE prior to Adding a record, the record pointer should be cleared with: GET(*file*,0).

ADD( <i>file</i> )	Adds a new record to the <i>file</i> by writing the entire contents of the data file's record buffer to disk.
ADD( <i>file,length</i> )	Adds a new record to the <i>file</i> by writing <i>length</i> number of bytes from the data file's record buffer to disk. The <i>length</i> must be greater than zero and not greater than the length of the RECORD. This form of ADD is not supported by all file drivers--check your file driver documentation.

## QUEUE Usage

---

ADD writes a new entry from the QUEUE structure data buffer to the QUEUE. If there is not enough memory to ADD a new entry, the "Insufficient Memory" error is posted.

ADD( <i>queue</i> )	Appends a new entry to the end of the QUEUE.
ADD( <i>queue,pointer</i> )	Places a new entry at the relative position specified by the <i>pointer</i> parameter. If there is an entry already at the relative <i>pointer</i> position, it is "pushed down" to make room for the new entry. All following pointers are readjusted to account for the new entry. For example, an entry added at position 10 pushes entry 10 to position 11, entry 11 to position 12, etc. If <i>pointer</i> is zero or greater than the number of entries in the QUEUE, the entry is added at the end.
ADD( <i>queue,key</i> )	Inserts a new entry in a sorted memory queue. Multiple <i>key</i> parameters may be used (up to 16), separated by commas, with optional leading plus or minus signs to indicate ascending or descending sequence. The entry is inserted immediately after all other entries with matching <i>key</i> values. Using only this form of ADD will build the QUEUE in sorted order.

<code>ADD(queue,name)</code>	Inserts a new queue entry in a sorted memory queue. The <i>name</i> string must contain the NAME attributes of the fields, separated by commas, with optional leading plus or minus signs to indicate ascending or descending sequence. The entry is inserted immediately after all other entries with matching field values. If there are no entries, <code>ADD(queue,name)</code> may be used to build the QUEUE in sorted order.
<code>ADD(queue,function)</code>	Using ADD by FUNCTION will write from a positional value returned by the function. If the function returns zero (0) the queue record of the first parameter is treated as equal to the second. In this case, no record is added, since the values are equal. If the function returns a negative value, the ADD of the record passed as a first parameter is treated as having less value than record passed as second parameter and is written accordingly. If the function returns a positive value, the ADD of the record passed as a first parameter is treated as having a greater value than record passed as second parameter and is written accordingly.

If the QUEUE contains any reference variables or fields with the ANY data type, you must first CLEAR the QUEUE entry before assigning new values to the component fields of the QUEUE. This avoids possible memory leaks, since these data types automatically allocate memory.

**Errors Posted:**

05	Access Denied
08	Insufficient Memory
37	File Not Open
40	Creates Duplicate Key
75	Invalid Field Type Descriptor

**Example:**

```

NameQue  QUEUE
Name      STRING(20),NAME('FirstField')
Zip       DECIMAL(5,0),NAME('SecondField')
AnyField  ANY
          END

CODE
ADD(Customer)                !Add a new customer file record
IF ERRORCODE() THEN STOP(ERROR()). !and check for errors

NameQue.Name = 'Jones'      !Assign data
NameQue.Zip = 12345
NameQue.AnyField &= NEW(STRING(10)) !Create a new STRING(10) field in the QUEUE
ADD(NameQue)                !Add an entry to the end of the QUEUE
CLEAR(NameQue)              !Clear ANY for next entry

NameQue.Name = 'Taylor'    !Assign data
NameQue.Zip = 12345
NameQue.AnyField &= NEW(STRING(20)) !Create a new STRING(20) field in the QUEUE
ADD(NameQue,+NameQue.Name,-NameQue.Zip) !Ascending name, descending zip order
CLEAR(NameQue)              !Clear ANY for next entry

NameQue.Name = 'Adams'     !Assign data
NameQue.Zip = 12345
NameQue.AnyField &= NEW(STRING(30)) !Create a new STRING(30) field in the QUEUE
ADD(NameQue,1)              !Add an entry at position 1
CLEAR(NameQue)              !Clear ANY for next entry

Que:Name = 'Smith'         !Assign data
Que:Zip = 12345
NameQue.AnyField &= NEW(STRING(40)) !Create a new STRING(40) field in the QUEUE
ADD(NameQue,+FirstField,-SecondField) !Ascending name, descending zip order
CLEAR(NameQue)              !Clear ANY for next entry

```

**See Also:**

SORT  
 CLEAR  
 Reference Variables  
 PUT  
 GET  
 DUPLICATE  
 APPEND

## ADDRESS (return memory address)



**ADDRESS**(| *variable* | )

---

**ADDRESS**      Returns memory address of a variable.

*variable*      The label of a data item or PROCEDURE.

The **ADDRESS** procedure returns the address of the specified data item or PROCEDURE.

The ADDRESS procedure allows you to pass the address of a *variable* or *procedure* to external libraries written in other languages, or to reference assign the address to a reference variable.

**Return Data Type:**      LONG

### Example:

```
MAP
  ClarionProc                                !A Clarion language procedure
  MODULE ('External.Obj')                    !An external library
    ExternVarProc (LONG)                     !C procedure receiving variable address
    ExternProc (LONG)                        !C procedure receiving procedure address
  END
END

Var1 CSTRING(10)                             !Define a null-terminated string
CODE
  ExternVarProc (ADDRESS (Var1))              !Pass address of Var1 to external procedure
  ExternProc (ADDRESS (ClarionProc))          !Pass address of ClarionProc
ClarionProc PROCEDURE                        !A Clarion language procedure
CODE
  RETURN
```

### See Also:

PEEK

POKE

Reference Assignment Statements

## AGE (return age from base date)

**AGE**(*birthdate* [,*base date*])

**AGE** Returns elapsed time.

*birthdate* A numeric expression for a standard date.

*base date* A numeric expression for a standard date. If this parameter is omitted, the operating system date is used for the computation.

The **AGE** procedure returns a string containing the time elapsed between two dates. The age return string is in the following format:

```
1 to 60 days           - 'nn DAYS'
61 days to 24 months - 'nn MOS'
(2 years + 1 month) to 999 years - 'nnn YRS'
```

**Return Data Type:** STRING

**Example:**

```
Message = Emp:Name & 'is ' & AGE(Emp:DOB,TODAY()) & ' old today.'
```

**See Also:**

Standard Date

DAY

MONTH

YEAR

TODAY

DATE

## ALERT (set event generation key)



**ALERT**(*[first-keycode]* [,*last-keycode*])

---

**ALERT** Specifies keys that generate an event.

*first-keycode* A numeric keycode or keycode equate label. This may be the lower limit in a range of keycodes.

*last-keycode* The upper limit keycode, or keycode equate label, in a range of keycodes.

**ALERT** specifies a key, or an inclusive range of keys, as event generation keys for the currently active window. The **ALERT** statement with no parameters clears all **ALERT** keys. The current list of key codes can be found in the `KEYCODES.CLW` source file.

Two field-independent events, `EVENT:PreAlertKey` and `EVENT:AlertKey`, generate when the user presses the **ALERT**ed key (in that order). If the code does not execute a `CYCLE` statement when processing `EVENT:PreAlertKey`, you "shortstop" the library's default action on the alerted keypress. If the code does execute `CYCLE` when processing `EVENT:PreAlertKey`, the library performs its default action for the alerted keypress. In either case, `EVENT:AlertKey` generates following `EVENT:PreAlertKey`.

Any key with a keycode may be used as the parameter of an **ALERT** statement. **ALERT** generates field-independent events, since it is not associated with any particular control. When `EVENT:AlertKey` is generated by an **ALERT** key, the `USE` variable of the control that currently has input focus is not automatically updated (use `UPDATE` if this is required).

The **ALERT** statement alerts its keys separately from the **ALRT** attribute of a window or control. This means that clearing all **ALERT** keys has no effect on any keys alerted by **ALRT** attributes.

**Example:**

```

Screen WINDOW,ALRT(F10Key),ALRT(F9Key) !F10 and F9 alerted
    LIST,AT(109,48,50,50),USE(?List),FROM(Que),IMM
    BUTTON('&Ok'),AT(111,108,,),USE(?Ok)
    BUTTON('&Cancel'),AT(111,130,,),USE(?Cancel)
END

CODE
OPEN(Screen)
ALERT                                !Turn off all alerted keys
ALERT(F1Key,F12Key)                 !Alert all function keys
ALERT(279)                           !Alert the Ctrl-Esc key
ACCEPT
CASE EVENT()
OF EVENT:PreAlertKey                !Pre-check alert events
    IF KEYCODE() <> F4Key            !Dis-Allow F4 key standard library action, and allow
        CYCLE                        !all other F keys to perform their standard functions
    END
OF EVENT:AlertKey                    !Alert processing
    CASE KEYCODE()
    OF 279                            !Check for Ctrl+Esc
        BREAK
    OF F9Key                          !Check for F9
        F9HotKeyProc                  !Call hot key procedure
    OF F10Key                         !Check for F10
        F10HotKeyProc                 !Call hot key procedure
    END
END
END
END

```

**See Also:**

UPDATE

ALRT

## ALIAS (set alternate keycode)

**ALIAS**( [*keycode*, [*new keycode*] ] )

---

**ALIAS** Changes the keycode generated when the original key is pressed.

*keycode* A numeric keycode or keycode EQUATE. If both parameters are omitted, all ALIASed keys are reset to their original values.

*new keycode* A numeric keycode or keycode EQUATE. If omitted, the *keycode* is reset to its original value.

**ALIAS** changes the *keycode* to generate the *new keycode* when the user presses the original key. ALIAS does not affect keypresses generated by PRESSKEY. The effect of ALIAS is global, throughout all execution threads, no matter where the ALIAS statement executes. Therefore, to only change the *keycode* locally, you must reset ALIASed keys when the window loses focus.

Keycode values 0800h through 0FFFFh are unassigned and may be used as a *new keycode*. The practical effect of this is to disable the original key if your program does not test for the *new keycode*.

**Example:**

```
ALIAS (EnterKey, TabKey)  !Allow user to press enter instead of tab
ALIAS (F3Key, F1Key)      !Move help to F3
ALIAS                     !Clear all aliased keys
```

**See Also:**

KEYCODE



## ALL (return repeated characters)

`ALL(string [,length])`

---

**ALL** Returns repeated characters.

*string* A string expression containing the character sequence to be repeated.

*length* The length of the return string. If omitted the *length* of the return string is 255 characters.

The **ALL** procedure returns a string containing repetitions of the character sequence *string*.

**Return Data Type:**      STRING

**Example:**

```
Starline = ALL('*',25)      !Get 25 asterisks
Dotline  = ALL('.',255)     !Get 255 dots
```

## APPEND (add a new file record)

**APPEND**(*file* [,*length*])

---

**APPEND**            Writes a new record to a FILE.

*file*                The label of a FILE declaration.

*length*             An integer constant, variable, or expression which contains the number of bytes to write to the *file*. The *length* must be greater than zero and not greater than the length of the RECORD. If omitted or out of range, *length* defaults to the length of the RECORD structure.

The **APPEND** statement writes a new record from the RECORD structure data buffer to the data file. No KEYS associated with the *file* are updated during an APPEND. After APPENDING records, the KEYS must be rebuilt with the BUILD command.

APPEND is usually used in batch processes, to speed the process of adding a large number of records at one time to the *file*. For most every file system, it is much faster to add 5000 records to a *file* using APPEND (and then issue BUILD at the end of the process to rebuild all the keys at once) than it is to use ADD to add the same 5000 records (which automatically updates the keys with each new record added).

If an error is posted, no record is added to the file. If there is no room for the record on disk, the "Access Denied" error is posted.

### Errors Posted:

05            Access Denied  
37            File Not Open

### Example:

```
LOOP                            !Process an input file
NEXT (InFile)                  !getting each record in turn
IF ERRORCODE ()                !break loop on error
  BREAK
END
Cus:Record = Inf:Record        !Copy the data to Customer file
APPEND (Customer)              !and APPEND a customer record
IF ERRORCODE ()                !check for errors
  STOP (ERROR ())
END
END
BUILD (Customer)                !Re-build Keys
```

### See Also:

BUILD

ADD

## ARC (draw an arc of an ellipse)

**ARC**( *x* , *y* , *width* , *height* , *startangle* , *endangle* [, *attributelist*] )

---

<b>ARC</b>	Draws an arc of an ellipse on the current window or report.
<i>X</i>	An integer expression that specifies the horizontal position of the starting point.
<i>Y</i>	An integer expression that specifies the vertical position of the starting point.
<i>Width</i>	An integer expression that specifies the width.
<i>Height</i>	An integer expression that specifies the height.
<i>startangle</i>	An integer expression that specifies the starting point of the arc, in tenths of degrees (10 = 1 degree) measured counter-clockwise from three o'clock.
<i>endangle</i>	An integer expression that specifies the ending point of the arc, in tenths of degrees (10 = 1 degree) measured counter-clockwise from three o'clock.
<i>attributelist</i>	A string constant, variable, or EQUATE containing an optional type of output document and its associated attributes. Only valid when the target is a REPORT. See EXTEND

The **ARC** procedure places an arc of an ellipse on the current target. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. The ellipse is drawn inside a "bounding box" defined by the *x*, *y*, *width*, and *height* parameters. The *x* and *y* parameters specify the starting point, and the *width* and *height* parameters specify the horizontal and vertical size of the "bounding box."

The *startangle* and *endangle* parameters specify what sector of the ellipse will be drawn, as an arc.

The border color is the current pen color set by SETPENCOLOR; the default color is the Windows system color for window text. The border width is the current width set by SETPENWIDTH; the default width is one pixel. The border style is the current pen style set by SETPENSTYLE; the default style is a solid line.

### Example:

```
MDIChild WINDOW('Child One'), AT(0,0,320,200), MDI, MAX, HVSCROLL
    !window controls
END

CODE
OPEN(MDIChild)
ARC(100,50,100,50,0,900)    !Draw 90 degree arc from 3 to 12 o'clock, as
                           !the top-right quadrant of ellipse
```

### See Also:

Current Target, SETPENCOLOR . SETPENWIDTH, SETPENSTYLE

## ASK (get one keystroke)

### ASK

---

**ASK** reads a single keystroke from the keyboard buffer. Program execution stops to wait for a keystroke. If there is already a keystroke in the keyboard buffer, ASK gets one keystroke without waiting. The ASK statement also allows any TIMER attribute events to generate and cycle their own ACCEPT loop. This means any batch processing code can allow other threads to execute their TIMER attribute tasks during the batch process.

#### Example:

```
ASK                !Wait for a keystroke
LOOP WHILE KEYBOARD() !Empty the keyboard buffer
  ASK              !without processing keystrokes
END
```

#### See Also:

KEYCODE

KEYBOARD

## ASIN (return arcsine)

**ASIN**(*expression*)

**ASIN** Returns inverse sine.

*expression* A numeric constant, variable, or expression for the value of the sine.

The **ASIN** procedure returns the inverse sine. The inverse of a sine is the angle that produces the sine. The return value is the angle in radians.  $\pi$  is a constant which represents the ratio of the circumference and radius of a circle. There are  $2\pi$  radians (or 360 degrees) in a circle.

**Return Data Type:** REAL

### Example:

```
PI          EQUATE (3.1415926535898)      !The value of PI
Rad2Deg     EQUATE (57.295779513082)      !Number of degrees in a radian
Deg2Rad     EQUATE (0.0174532925199)      !Number of radians in a degree
CODE
  InvSine = ASIN(SineAngle)              !Get the Arcsine
```

### See Also:

TAN

ATAN

SIN

COS

ACOS

## ATAN (return arctangent)

**ATAN**(*expression*)

---

**ATAN** Returns inverse tangent.

*expression* A numeric constant, variable, or expression for the value of the tangent.

The **ATAN** procedure returns the inverse tangent. The inverse of a tangent is the angle that produces the tangent. The return value is the angle in radians.  $\pi$  is a constant which represents the ratio of the circumference and radius of a circle. There are  $2\pi$  radians (or 360 degrees) in a circle.

**Return Data Type** REAL

**Example:**

```
PI           EQUATE (3.1415926535898)    !The value of PI
Rad2Deg      EQUATE (57.295779513082)    !Number of degrees in a radian
Deg2Rad      EQUATE (0.0174532925199)    !Number of radians in a degree
CODE
  InvTangent = ATAN(TangentAngle)        !Get the Arctangent
```

**See Also:**

TAN

SIN

ASIN

COS

ACOS

## BAND (return bitwise AND)

**BAND**(*value*,*mask*)

**BAND** Performs bitwise AND operation.

*value* A numeric constant, variable, or expression for the bit *value* to be compared to the bit *mask*. The *value* is converted to a LONG data type prior to the operation, if necessary.

*mask* A numeric constant, variable, or expression for the bit *mask*. The *mask* is converted to a LONG data type prior to the operation, if necessary.

The **BAND** procedure compares the *value* to the *mask*, performing a Boolean AND operation on each bit. The return value is a LONG integer with a one (1) in the bit positions where the *value* and the *mask* both contain one (1), and zeroes in all other bit positions.

BAND is usually used to determine whether an individual bit, or multiple bits, are on (1) or off (0) within a variable.

**Return Data Type:** LONG

### Example:

`!BAND(0110b,0010b) returns 0010b !0110b = 6, 0010b = 2`

RateType	BYTE	!Type of rate
Female	EQUATE(0001b)	!Female mask
Male	EQUATE(0010b)	!Male mask
Over25	EQUATE(0100b)	!Over age 25 mask

```

CODE
IF BAND(RateType,Female) |      !If female
  AND BAND(RateType,Over25)    ! and over 25
  DO BaseRate                  !use base premium
ELSIF BAND(RateType,Male)      !If male
  DO AdjBase                   !adjust base premium
END

```

### See Also:

BOR

BXOR

BSHIFT

## BEEP (sound tone on speaker)

**BEEP**( *[sound]* )

---

**BEEP**                Generates a sound through the system speaker.

*sound*                A numeric constant, variable, expression, or EQUATE for the Windows sound to issue.

The **BEEP** statement generates a sound through the system speaker. These are standard Windows sounds available through the [sounds] section of the WIN.INI file. Standard EQUATE values similar to these are listed in the EQUATES.CLW file:

```
BEEP:SystemDefault
BEEP:SystemHand
BEEP:SystemQuestion
BEEP:SystemExclamation
BEEP:SystemAsterisk
```

**Example:**

```
IF ERRORCODE()           !If unexpected error
  BEEP(BEEP:SystemDefault) !sound a standard beep
  STOP(ERROR())           !stop for the error
END
```



## BLANK (erase graphics)

**BLANK**( [*x*] [*y*] [,*width*] [,*height*] )

---

<b>BLANK</b>	Erases all graphics written to the specified area of the current window or report.
<i>X</i>	An integer expression that specifies the horizontal position of the starting point. If omitted, the default is zero.
<i>Y</i>	An integer expression that specifies the vertical position of the starting point. If omitted, the default is zero.
<i>Width</i>	An integer expression that specifies the width. If omitted, the default is the width of the window.
<i>Height</i>	An integer expression that specifies the height. If omitted, the default is the height of the window.

The **BLANK** procedure erases all graphics written to the specified area of the current window or report. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. Controls are not erased. BLANK with no parameters erases the entire window or report.

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !window controls
END
CODE
OPEN(MDIChild)
ARC(100,50,100,50,0,900) !Draw arc
BLANK                    !Then erase it
```

### See Also:

Current Target

## BOR (return bitwise OR)

**BOR**(*value*,*mask*)

---

**BOR**                Performs bitwise OR operation.

*Value*                A numeric constant, variable, or expression for the bit *value* to be compared to the bit *mask*. The *value* is converted to a LONG data type prior to the operation, if necessary.

*Mask*                A numeric constant, variable, or expression for the bit *mask*. The *mask* is converted to a LONG data type prior to the operation, if necessary.

The **BOR** procedure compares the *value* to the *mask*, performing a Boolean OR operation on each bit. The return value is a LONG integer with a one (1) in the bit positions where the *value*, or the *mask*, or both, contain a one (1), and zeroes in all other bit positions.

BOR is usually used to unconditionally turn on (set to one), an individual bit, or multiple bits, within a variable.

**Return Data Type:**    LONG

**Example:**

```
!BOR(0110b,0010b) returns 0110b    !0110b = 6, 0010b = 2
```

```
RateType    BYTE                            !Type of rate
Female      EQUATE(0001b)                  !Female mask
Male        EQUATE(0010b)                  !Male mask
Over25      EQUATE(0100b)                  !Over age 25 mask
CODE
RateType = BOR(RateType,Over25) !Turn on over 25 bit
RateType = BOR(RateType,Male)    !Set rate to male
```

**See Also:**

BAND

BXOR

BSHIFT

## BOX (draw a rectangle)

**BOX**( *x* , *y* , *width* , *height* [, *fill*] [, *attributelist*])

---

<b>BOX</b>	Draws a rectangular box on the current window or report.
<i>x</i>	An integer expression that specifies the horizontal position of the starting point.
<i>y</i>	An integer expression that specifies the vertical position of the starting point.
<i>width</i>	An integer expression that specifies the width.
<i>height</i>	An integer expression that specifies the height.
<i>fill</i>	A LONG integer constant, constant EQUATE, or variable containing the red, green, and blue components that create the color in the three low-order bytes (bytes 0, 1, and 2) or an EQUATE for a standard Windows color value.
<i>attributelist</i>	A string constant, variable, or EQUATE containing an optional type of output document and its associated attributes. Only valid when the target is a REPORT. See EXTEND

The **BOX** procedure places a rectangular box on the current window or report. The position and size of the box are specified by *x*, *y*, *width*, and *height* parameters. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

The *x* and *y* parameters specify the starting point, and the *width* and *height* parameters specify the horizontal and vertical size of the box. The box extends to the right and down from its starting point.

The border color is the current pen color set by SETPENCOLOR; the default color is the Windows system color for window text. The border width is the current width set by SETPENWIDTH; the default width is one pixel. The border style is the current pen style set by SETPENSTYLE; the default style is a solid line.

### Example:

```
MDIChild WINDOW('Child One'), AT(0,0,320,200), MDI, MAX, HVSCROLL
    !window controls
    END
CODE
    OPEN(MDIChild)
    BOX(100,50,100,50,00FF0000h)    !Red box
```

### See Also:

Current Target  
 SETPENCOLOR  
 SETPENWIDTH  
 SETPENSTYLE

## BSHIFT (return shifted bits)

**BSHIFT**(*value*,*count*)

---

**BSHIFT**      Performs the bit shift operation.

*value*            A numeric constant, variable, or expression. The *value* is converted to a LONG data type prior to the operation, if necessary.

*count*            A numeric constant, variable, or expression for the number of bit positions to be shifted. If *count* is positive, *value* is shifted left. If *count* is negative, *value* is shifted right.

The **BSHIFT** procedure shifts a bit *value* by a bit *count*. The bit value may be shifted left (toward the high order), or right (toward the low order). Zero bits are supplied to fill vacated bit positions when shifting.

**Return Data Type:**    LONG

**Example:**

```
!BSHIFT(0110b,1)    returns 1100b
!BSHIFT(0110b,-1)  returns 0011b
```

```
Varswitch = BSHIFT(20,3)            !Multiply by eight
Varswitch = BSHIFT(Varswitch,-2) !Divide by four
```

**See Also:**

BAND

BOR

BXOR

## BUILD (build keys and indexes)

```

| file |

BUILD(  | index | [, components [, filter ] ] )

| key |

```

---

<b>BUILD</b>	Builds keys and indexes.
<i>file</i>	The label of a FILE declaration.
<i>index</i>	The label of an INDEX declaration.
<i>key</i>	The label of a KEY declaration.
<i>components</i>	A string constant or variable containing the list of the component fields on which to BUILD the dynamic INDEX. The fields must be separated by commas, with leading plus (+) or minus (-) to indicate ascending or descending sequence (if supported by the file driver).
<i>filter</i>	A string constant, variable, or expression containing a logical expression with which to filter out unneeded records from the dynamic <i>index</i> . This requires that you name <i>components</i> for the <i>index</i> . You must BIND all variables used in the <i>filter</i> expression.

The **BUILD** statement re-builds keys and indexes in a FILE..

BUILD( <i>file</i> )	Builds all the KEYs declared for the file. The file must be closed, LOCKed, or opened with <i>access mode</i> set to 12h (ReadWrite/DenyAll) or 22h (ReadWrite/DenyWrite).
BUILD( <i>key</i> ) or BUILD( <i>index</i> )	Builds only the specified KEY or INDEX. The file must be closed, LOCKed, or opened with <i>access mode</i> set to either 12h (ReadWrite/DenyAll) or 22h (ReadWrite/DenyWrite).
BUILD( <i>index,components,filter</i> )	Builds a dynamic INDEX. This form does not require exclusive access to the file, however, the file must be open (with any valid <i>access mode</i> ). The dynamic INDEX is created as a temporary file, exclusive to the user who BUILDS it. The temporary file is automatically deleted when the file is closed. If a <i>filter</i> is specified, the resulting INDEX will contain only those records which meet the <i>filter</i> criteria. The <i>filter</i> must be in a format supported by the file driver.

BUILD will generate events to the currently open window if you assign a value (an integer from 1 to 100) to PROP:ProgressEvents for the affected FILE before you issue the BUILD. The larger the value you assign to PROP:ProgressEvents, the more events are generated and the slower the BUILD will progress. These events allow you to indicate to the user the progress of the BUILD. This can keep end-users informed that BUILD is still working while building large files (so they don't re-boot thinking the machine has locked up).

It is not valid to make any calls to the *file* being built except to query its properties, call NAME(*file*), or CLOSE(*file*) (which aborts the process and is not recommended). Issuing a CYCLE statement in response to any of the events generated (except EVENT:BuildDone) cancels the operation. During the BUILD operation, *file*{PROP:Completed} returns the percentage completed of the re-build and you can use *file*{PROP:CurrentKey} to get a key reference then either *key*{PROP:Name} or *key*{PROP:Label} to return the name of the current key being built.

**Errors Posted:**

37	File Not Open
40	Creates Duplicate Key
63	Exclusive Access Required
76	Invalid Index String
93	BUILD Cancelled

**Events Generated:**

EVENT:BuildFile	BUILD( <i>file</i> ) is rebuilding the data portion of the <i>file</i> .
EVENT:BuildKey	BUILD( <i>key</i> ) or BUILD( <i>index</i> ) is rebuilding the key, or BUILD( <i>file</i> ) is rebuilding the keys in the <i>file</i> .
EVENT:BuildDone	The BUILD is complete. If the user cancelled the BUILD, ERRORCODE 93 is set.

**Example:**

```

Names      FILE,DRIVER('TopSpeed'),PRE(Nam)  !Declare a file structure
NameKey     KEY(Nam:Name),OPT                 !Declare name key
NbrNdx      INDEX(Nam:Number),OPT             !Declare number index
DynNdx      INDEX()                          !Declare a dynamic index
Rec         RECORD
Name        STRING(20),NAME('Nam:Name')
Number      SHORT,NAME('Nam:Number')
            END
            END

CODE
OPEN(Names,12h)                               !Open file, exclusive read/write
BUILD(Names)                                  !Build all keys on Names file
BUILD(Nam:NbrNdx)                             !Build the number index

!Build dynamic index ascending number, ascending name:
BUILD(Nam:DynNdx,'+Nam:Number,+Nam:Name')

BIND('Nam:Name',Nam:Name)                     !BIND the filter variable

!Build dynamic index of names that start with A:
BUILD(Nam:DynNdx,'+Nam:Name','UPPER(Nam:Name[1]) = A')

UNBIND('Nam:Name')                           !UNBIND the filter variable

```

**See Also:**

OPEN

SHARE

BIND

PROP:ProgressEvents

PROP:Completed

## BXOR (return bitwise exclusive OR)

**BXOR**(*value*,*mask*)

---

**BXOR**            Performs bitwise exclusive OR operation.

*value*            A numeric constant, variable, or expression for the bit *value* to be compared to the bit *mask*. The *value* is converted to a LONG data type prior to the operation, if necessary.

*mask*            A numeric constant, variable, or expression for the bit *mask*. The *mask* is converted to a LONG data type prior to the operation, if necessary.

The **BXOR** procedure compares the *value* to the *mask*, performing a Boolean XOR operation on each bit. The return value is a LONG integer with a one (1) in the bit positions where either the *value* or the *mask* contain a one (1), but not both. Zeroes are returned in all bit positions where the bits in the *value* and *mask* are alike.

BXOR is usually used to toggle on (1) or off (0) an individual bit, or multiple bits, within a variable.

**Return Data Type:**    LONG

**Example:**

```
!BXOR(0110b,0010b) returns 0100b    !0110b = 6, 0100b = 4, 0010b = 2
```

```
RateType  BYTE           !Type of rate
Female    EQUATE(0001b)  !Female mask
Male      EQUATE(0010b)  !Male mask
Over25    EQUATE(0100b)  !Over age 25 mask
Over65    EQUATE(1100b)  !Over age 65 mask
CODE
RateType = BXOR(RateType,Over65)  !Toggle over 65 bits
```

**See Also:**

BAND

BOR

BSHIFT



## BYTES (return size in bytes)

**BYTES**(*file*)

---

**BYTES**                Returns number of bytes in FILE, or most recently read.

*file*                    The label of a FILE.

The **BYTES** procedure returns the size of a FILE in bytes or the number of bytes in the last record successfully accessed. Following an OPEN statement, BYTES returns the size of the file. *file*{PROP:FileSize} is equivalent to BYTES after a file open and will also return the size of the file. After the *file* has been successfully accessed by GET, REGET, NEXT, PREVIOUS, ADD, or PUT, the BYTES procedure returns the number of bytes accessed in the RECORD. The BYTES procedure may be used to return the number of bytes read in a variable length record.

In SQL tables, if BYTES(*file*) is used before the file is opened, then it returns the number of rows in the table. If it is used after the file is opened and a successful record retrieval, it returns the number of bytes in the record buffer.

**Return Data Type:**        LONG

**Example:**

```
DosFileName  STRING(260),STATIC
LastRec      LONG
SavPtr       LONG(1)           !Start at 1
FileSize     LONG

DosFile      FILE,DRIVER('DOS'),PRE(DOS),NAME(DosFileName)
Record       RECORD
F1           STRING(2000)
            END
            END

BlobStorage  FILE,DRIVER('TopSpeed'),PRE(STO)
File         BLOB,BINARY
Record       RECORD
FileName     STRING(64)
            END
            END

CODE
IF NOT FILEDIALOG('Choose File to Store',DosFileName,,0010b)
  RETURN
END
OPEN(BlobStorage)           !Open the BLOB file
STO:FileName = DosFileName  !and store the filename
OPEN(DosFile)               !Open the file
FileSize = BYTES(DosFile)   !Get size of file
STO:File{PROP:Size} = FileSize !and set the BLOB to store the file
LastRec = FileSize % SIZE(DOS:Record) !Check for short record at end of file
LOOP INT(FileSize/SIZE(DOS:Record)) TIMES
  GET(DosFile,SavPtr)       !Get each record
  ASSERT(NOT ERRORCODE())
  !String slice data into BLOB:
  STO:File[SavPtr - 1 : SavPtr + SIZE(DOS:Record) - 2] = DOS:Record
  SavPtr += SIZE(DOS:Record) !Compute next record pointer
END
IF LastRec                  !If short record at end of file
  GET(DosFile,SavPtr)       !Get last record
  ASSERT(BYTES(DosFile) = LastRec) ! size read should match computed size
  STO:File[SavPtr - 1 : SavPtr + LastRec - 2] = DOS:Record
END
ADD(BlobStorage)
ASSERT(NOT ERRORCODE())
CLOSE(DosFile);CLOSE(BlobStorage)
```

**See Also:**

OPEN

PROP:FileSize

## CALL (call procedure from a DLL)

**CALL**( *file*, *procedure* [, *flags*] )

---

<b>CALL</b>	Calls a procedure that has not been prototyped in the application's MAP structure from a Windows standard .DLL.
<i>file</i>	A string constant, variable, or expression containing the name (including extension) of the .DLL to open. This may include a full path.
<i>procedure</i>	A string constant, variable, or expression containing the name of the <i>procedure</i> to call (which may not receive parameters or return a value). This can also be the ordinal number indicating the <i>procedure's</i> position within the .DLL.
<i>flags</i>	An UNSIGNED integer constant, variable, or expression containing bitmap flag settings.

The **CALL** procedure calls a *procedure* from a Windows-standard .DLL. The *procedure* does not need to be prototyped in the application's MAP structure. If it is not already loaded by Windows, the .DLL *file* is loaded into memory. The .DLL *file* is automatically unloaded from memory when the *procedure* terminates unless the lowest *flags* bit is set to one (1). A .DLL *file* left loaded may be explicitly unloaded with the UNLOAD procedure.

**CALL** returns zero (0) for a successful *procedure* call. If unsuccessful, it can return one of the following mapped error values, or any other valid Windows level error code:

- 1 Procedure name cannot be resolved in a specified .DLL
- 2 File not found
- 3 Path not found
- 5 Attempted to load a task, not a .DLL
- 6 Library requires separate data segments for each task
- 10 Wrong Windows version
- 11 Invalid .EXE file (DOS file or error in program header)
- 12 OS/2 application
- 13 DOS 4.0 application
- 14 Unknown .EXE type
- 15 Attempt to load an .EXE created for an earlier version of Windows.  
This error will not occur if Windows is run in Real mode.
- 16 Attempt to load a second instance of an .EXE file containing multiple, writeable data segments.
- 17 EMS memory error on the second loading of a .DLL
- 18 Attempt to load a protected-mode-only application while Windows is running in Real mode

**Return Data Type:** SIGNED

### Example:

```
X# = CALL('CUSTOM.DLL','1')  !Call first procedure in CUSTOM.DLL
IF X# THEN STOP(X#).         !Check for successful execution
```

### See Also:

UNLOAD

Calling Stored Procedures (SQL)

## CALLBACK (register or unregister a FileCallbackInterface)



**CALLBACK**(*entity*, *FileCallbackInterface*, [*flag*])

---

**CALLBACK** Register or unregister a FileCallbackInterface.

*Entity* The label of a FILE or VIEW.

*FileCallbackInterface* The label of the interface that implements the FileCallbackInterface. The methods of the FileCallbackInterface are called automatically before (method FunctionCalled) and after (method FunctionDone) each file operation.

*Flag* An integer constant, variable, EQUATE, or expression that indicates whether or not to unregister an interface associated with a FILE or VIEW. A value of one (1 or TRUE) unregisters the interface. If omitted, the interface is registered with the *entity*.

The **CALLBACK** method registers a callback interface with the specified *entity*. The methods of the registered interface are called whenever a file operation is done. Multiple interfaces can be registered with an entity.

To unregister an interface, set the *flag* to TRUE. Any registered interfaces must be unregistered before the object that implements the interface is removed.

If a VIEW has callbacks registered with it and the primary FILE of that VIEW also has callbacks registered, then all the callbacks registered for the VIEW are called *before* the callbacks for the primary FILE.

To distinguish if a callback method is being called by a FILE operation or a VIEW operation you need to check the new Params.View field. It will be NULL for FILE operations and equal to the VIEW that is being used for VIEW operations.

### Example:

PROGRAM

```
MAP
END
INCLUDE ( 'FILECB.INC' ) , ONCE
```

```
!Data file
People      FILE , DRIVER ( ' TOPSPEED ' ) , PRE ( PEO ) , CREATE , BINDABLE , THREAD
KeyId       KEY ( PEO : Id ) , NOCASE , OPT
KeyLastName KEY ( PEO : LastName ) , DUP , NOCASE
Record      RECORD , PRE ( )
Id           LONG
FirstName    STRING ( 30 )
LastName     STRING ( 30 )
Gender       LONG
            END
            END
```

```

!Log File
LogFile      FILE,DRIVER('BASIC','/ALWAYSQUOTE=OFF /COMMA=1,1'),CREATE,NAME('logfile.txt')
Record       RECORD
Operation    STRING(200)
            END
            END

!FileCallBack Class
FCB CLASS,IMPLEMENTS(FileCallBackInterface)
    END

    CODE
    CALLBACK(People, FCB.FileCallBackInterface) !Register FCB interface
    CREATE(Logfile)                             !Create log file
    OPEN(Logfile)                               !Open log file
    OPEN(People)                                !Open data file
    SET(PEO:KeyId, PEO:KeyId)                   !Set and
    LOOP                                       !loop thru
        NEXT(People)                           !data until
        IF ERRORCODE()
            BREAK                               !end of file
        END
    END
    CLOSE(People)                               !Close data file

!Unregister FCB interface:
CALLBACK(People, FCB.FileCallBackInterface, TRUE)

!This method is called prior to each operation of the data file.
!The log file is updated with the file operation that is being executed.

FCB.FileCallBackInterface.FunctionCalled |
    PROCEDURE(SIGNED opCode, *Params Parameters, *CSTRING ErrCode, *CSTRING ErrMsg)
p LIKE(Params)
    CODE
    p = Parameters
    IF p.View &= NULL !used to detect VIEW or FILE callback
        f = 'FILE'
    ELSE
        f = 'VIEW'
    END
    CASE opCode
    OF DriverOp:ADD
        logFile.Operation = 'ADD(f)'
    OF DriverOp:APPEND
        logFile.Operation = 'APPEND(f)'
    OF DriverOp:CLOSE
        logFile.Operation = 'CLOSE(f)'
    OF DriverOp:COPY
        logFile.Operation = 'COPY(f, ''&CLIP(Parameters.Text)&'')'
    OF DriverOp:CREATE
        logFile.Operation = 'CREATE(f)'
    OF DriverOp:DELETE
        logFile.Operation = 'DELETE(f)'
    OF DriverOp:NEXT
        logFile.Operation = 'NEXT(f)'
    OF DriverOp:OPEN
        logFile.Operation = 'OPEN(f, '&Parameters.openMode&')'
    OF DriverOp:PUT
        logFile.Operation = 'PUT(f)'

```

```
    OF DriverOp:SETkeykey
      logFile.Operation = 'SET(k,k)'
    END
    ADD(logFile)
    RETURN TRUE

!This method is called after each operation to the data file.
!This simply returns a TRUE according to the rules of the FileCallBackInterface.
FCB.FileCallBackInterface.FunctionDone |
  PROCEDURE(SIGNED opCode, Params Parameters, *CSTRING ErrCode, *CSTRING ErrMsg)
CODE
  RETURN TRUE
```

### Additional Example:

```
PROGRAM
INCLUDE('FILECB.INC')
MAP
  viewTest(VIEW v)
  check(String msg)
  Test(String Name, FILE log, FILE f, VIEW v1, VIEW v2)
END

Dept FILE,DRIVER('Memory'),NAME('DEPT'),PRE(DEP),CREATE
PK_DEPT KEY(DEP:DEPTNO),PRIMARY
Record RECORD
DEPTNO    BYTE
DNAME     CSTRING(15)
LOC       CSTRING(14)
          END
END

LogFile FILE,DRIVER('ASCII'),CREATE,NAME('CB.LOG')
Record RECORD
Line      STRING(100)
          END
END

MyClass CLASS,IMPLEMENTS(FileCallBackInterface),TYPE
Name      CSTRING(30),PRIVATE
logf      &FILE,PRIVATE
baseF     &FILE,PRIVATE
line      ANY,PRIVATE
inView    BOOL,PRIVATE
Init      PROCEDURE(STRING n, FILE f, FILE log)
Kill      PROCEDURE()
          END

MemoryFile MyClass
ISAMView   MyClass

iView1 VIEW(Dept).
iView2 VIEW(Dept).

CODE
CREATE(LogFile)
Check('Create LogFile')
OPEN(LogFile)
Check('OPEN LogFile')
MemoryFile.Init('Memory', Dept, LogFile)
ISAMView.Init('ISAMView', iView1, LogFile)
```

```

CREATE (Dept)
Check('Create Dept')
Test('Memory', LogFile, Dept, iView1, iView2)
MemoryFile.Kill()
ISAMView.Kill()
MESSAGE('Done')

viewTest PROCEDURE(VIEW v)
CODE
    OPEN(v)
    SET(v)
    NEXT(v)
    CLOSE(v)

Check PROCEDURE(STRING msg)
CODE
    IF ERRORCODE()
    IF ERRORCODE() = 90
        HALT(1, msg & ' caused system error ' & FILEERRORCODE() & ' : ' |
            & FILEERROR())
    END
    HALT(1, msg & ' caused error ' & ERRORCODE() & ' : ' & ERROR())
END

Test PROCEDURE(STRING msg, FILE log, FILE f, VIEW v1, VIEW v2)

g    &GROUP
1    ANY
CODE
    g &= log{PROP:Record}
    1 &= WHAT(g, 1)
    1 = '!File Operations'
    ADD(log)
    OPEN(f)
    Check(msg & ' OPEN')
    SET(f)
    NEXT(f)
    1 = '!View 1 Operations'
    ADD(log)
    viewTest(v1)
    1 = '!View 2 Operations'
    ADD(log)
    viewTest(v2)
    1 = '!Done'
    ADD(log)
    CLOSE(f)

MyClass.Init      PROCEDURE(STRING n, FILE f, FILE log)
g &GROUP
CODE
    CALLBACK(f, SELF.FileCallBackInterface)
    SELF.logf &= log
    SELF.basef &= f
    SELF.Name = CLIP(n)
    g &= SELF.logf{PROP:Record}
    SELF.line &= WHAT(g, 1)

MyClass.Kill      PROCEDURE()
CODE
    CALLBACK(SELF.baseF, SELF.FileCallBackInterface, TRUE)
    Check('Uncallback ' & SELF.Name)
    SELF.line &= NULL

```

```
MyClass.FileCallBackInterface.FunctionCalled PROCEDURE(SIGNED opCode, |
*Params Parameters, *CSTRING ErrCode, *CSTRING ErrMsg)

p      LIKE(Params)
f      CSTRING(5),AUTO
logit  BOOL(true)

CODE
  p = Parameters
  IF p.View &= NULL
    f = 'FILE'
  ELSE
    f = 'VIEW'
  END
  CASE opCode
  OF DriverOp:Create
    SELF.line = 'CREATE(' & f & ' ' & SELF.Name & ')'
  OF DriverOp:NEXT
    SELF.line = 'NEXT(' & f & ' ' & SELF.Name & ')'
  OF DriverOp:OPEN
    SELF.line = 'OPEN(' & f & ' ' & SELF.Name & ', '&Parameters.openMode&')'
  OF DriverOp:PUT
    SELF.line = 'PUT(' & f & ' ' & SELF.Name & ')'
  OF DriverOp:VIEWSTART
    SELF.InView = TRUE
    logit = FALSE
  OF DriverOp:VIEWSTOP
    SELF.InView = FALSE
    logit = FALSE
  ELSE
    logit = FALSE
  END
  IF logit AND ~SELF.InView
    ADD(SELF.logF)
  END
  RETURN TRUE

MyClass.FileCallBackInterface.FunctionDone |
  PROCEDURE(SIGNED opCode, Params Parameters, *CSTRING ErrCode, |
    *CSTRING ErrMsg)
CODE
  RETURN TRUE
```

The program above will produce a log file that looks like this:

```
CREATE(FILE Memory)
!File Operations
OPEN(FILE Memory,34)
NEXT(FILE Memory)
!View 1 Operations
OPEN(FILE ISAMView,34)
OPEN(VIEW Memory,34)
NEXT(FILE ISAMView)
NEXT(VIEW Memory)
!View 2 Operations
OPEN(VIEW Memory,34)
NEXT(VIEW Memory)
!Done
```

**See Also:**

FileCallbackInterface  
Trigger Properties



## CENTER (return centered string)

**CENTER**(*string* [,*length*])

---

**CENTER**       Returns centered string.

*string*         A string constant, variable or expression.

*length*         The length of the return string. If omitted, the length of the *string* parameter is used.

The **CENTER** procedure first removes leading and trailing spaces from a *string*, then pads it with leading and trailing spaces to center it within the *length*, and returns a centered string.

**Return Data Type:**     STRING

**Example:**

```
!CENTER('ABC',5) returns ' ABC '  
!CENTER('ABC ') returns ' ABC '  
!CENTER(' ABC') returns ' ABC '
```

```
Message = CENTER(Message)     !Center the message  
Rpt:Title = CENTER(Name,60)   !Center the name
```

**See Also:**

LEFT

RIGHT

## CHAIN (execute another program)

**CHAIN**(*program*)

---

**CHAIN** Terminates the current program and executes another.

*program* A string constant or variable containing the name of the program and optional command line parameters to execute. This may be any .EXE or .COM program.

**CHAIN** terminates the current program, closing all files and returning its memory to the operating system, and executes another *program*.

**Example:**

```
PROGRAM                                !MainMenu program code
CODE
EXECUTE CHOICE ()
CHAIN('Ledger')                       !Execute LEDGER.EXE
CHAIN('Payroll /Test=1 /N=2')         !Execute PAYROLL.EXE with parameters
RETURN                                !Return to O/S
END

PROGRAM                                !Ledger program code
CODE
EXECUTE CHOICE ()
CHAIN('MainMenu')                     !Return to MainMenu program
RETURN                                !Return to O/S
END

PROGRAM                                !Payroll program code
CODE
EXECUTE CHOICE ()
CHAIN('MainMenu')                     !Return to MainMenu program
RETURN                                !Return to O/S
END
```

**See Also:**

RUN

## CHANGE (change control field value)



**CHANGE**(*control,value*)

**CHANGE** Changes the *value* displayed in a *control* in an APPLICATION or WINDOW structure.

*control* Field number or field equate label of a window control field.

*value* A constant, variable, or valid expression containing the *control's* new value.

The **CHANGE** statement changes the *value* displayed in a *control* in an APPLICATION or WINDOW structure. CHANGE updates the *control's* USE variable with the *value*, clears all pending events, and then displays that new *value* in the control field.

For example:

**CHANGE(?dLocator, CLIP(dLocator) & 'D')**

**Example:**

```
Screen WINDOW,PRE (Scr)
    ENTRY (@N3) ,USE (Ctl:Code)
    ENTRY (@S30) ,USE (Ctl:Name)
    BUTTON ('OK') ,USE (?OkButton) ,KEY (EnterKey)
    BUTTON ('Cancel') ,USE (?CanxButton) ,KEY (EscKey)
END

CODE
OPEN (Screen)
ACCEPT
CASE EVENT ()
OF EVENT:Selected
CASE SELECTED ()
OF ?Ctl:Code
    CHANGE (?Ctl:Code,4)           !Change Ctl:Code to 4 and display it
    ?Ctl:Code{PROP:Touched} = TRUE !Force Accepted Event
OF ?Ctl:Name
    CHANGE (?Ctl:Name,'ABC Company') !Change Ctl:Name to ABC Company and display
    ?Ctl:Name{PROP:Touched} = TRUE !Force Accepted Event
END
OF EVENT:Accepted
CASE ACCEPTED ()
OF ?OkButton
    BREAK
OF ?CanxButton
    CLEAR (Ctl:Record)
    BREAK
END
END
```

**See Also:** DISPLAY, UPDATE, ERASE, CONTENTS, PROP:ScreenText

## CHANGES (return changed queue)

**CHANGES**( *queue* )

---

**CHANGES** Returns a "hash" value for the QUEUE.

*queue* The label of a QUEUE structure, or the label of a passed QUEUE parameter.

The **CHANGES** procedure returns a LONG integer containing a unique "hash" value for the current QUEUE contents. Saving this value then later comparing the saved value to the current return value from CHANGES allows you to easily detect that the contents of the QUEUE have changed (in any way at all).

**Return Data Type:** LONG

### Example:

```
SaveHash  LONG
Que       QUEUE
Name      STRING(10)
END

CODE
Que.Name = 'Jones'
ADD(Que)                                !Add the entry
ASSERT(~ERRORCODE())
SaveHash = CHANGES(Que)                !Save the "hash" value
Que.Name = 'Jones II'
ADD(Que)                                !Add another entry
ASSERT(~ERRORCODE())
IF SaveHash <> CHANGES(Que) !This should be a true expression here
  MESSAGE('CHANGES procedure worked correctly')
END
```

### See Also:

QUEUE

## CHOICE (return relative item position)



**CHOICE**( [*control*] )

**CHOICE** Returns a user selection number.

*control* A field equate label of a LIST, COMBO, SHEET, or OPTION control.

The **CHOICE** procedure returns the sequence number of a selected item in an OPTION structure, SHEET structure, LIST box, or COMBO control. With no parameter, CHOICE returns the sequence number of the selected item in the last control (LIST, SHEET, OPTION, or COMBO) that generated a Field-specific event to cycle the ACCEPT loop. CHOICE(*control*) returns the current selection number of any LIST, SHEET, OPTION, or COMBO in the currently active window.

CHOICE returns the sequence number of the selected RADIO control within an OPTION structure. The sequence number is determined by relative position within the OPTION. The first control listed in the OPTION structure's code is relative position 1, the second is 2, etc.

CHOICE returns the memory QUEUE entry number of the selected item when a LIST or COMBO box is completed.

**Return Data Type:** SIGNED

### Example:

```
CODE
ACCEPT
  EXECUTE CHOICE () !Perform menu option
  AddRec           !procedure to add record
  PutRec           !procedure to change record
  DelRec           !procedure to delete record
  RETURN           !return to caller
END
END
```

**See Also:** LIST, SHEET, COMBO, OPTION, QUEUE, RADIO, PROP:Selected  
PROP:ChoiceFEQ

## CHOOSE (return chosen value)

```
CHOOSE(  | expression ,value, value [,value...] | )  
        | condition [,truevalue, falsevalue ] |
```

---

<b>CHOOSE</b>	Returns the chosen value from a list of possible values.
<i>expression</i>	An arithmetic expression which determines which <i>value</i> parameter to return. This expression must resolve to a positive integer.
<i>value</i>	A variable, constant, or expression for the procedure to return.
<i>condition</i>	A logical expression which determines which of the two <i>value</i> parameters to return. If no <i>truevalue</i> or <i>falsevalue</i> parameters are present, one (1) is returned when the <i>expression</i> is true, and zero (0) is returned when the <i>expression</i> is false.

The **CHOOSE** procedure evaluates the *expression* or *condition* and returns the appropriate *value* parameter. If the *expression* resolves to a positive integer, that integer selects the corresponding *value* parameter for the CHOOSE procedure to return. If the *expression* evaluates to an out-of-range integer, then CHOOSE returns the last *value* parameter.

When the *condition* evaluates as true, then CHOOSE returns the *truevalue* parameter. When the *condition* evaluates to false, then CHOOSE returns the second *falsevalue* parameter. If no *value* parameters are present, CHOOSE returns one (1) for true, and zero (0) for false.

The return data type is dependent upon the data types of the *value* parameters:

<u>All Value Parameters</u>	<u>Return Data Type</u>
LONG	LONG
DECIMAL or LONG	DECIMAL
STRING	STRING
DECIMAL, LONG, or STRING	DECIMAL
anything else	REAL

**Return Data Type:** LONG, DECIMAL, STRING, or REAL

**Example:**

```

CHOOSE(4, 'A', 'B', 'C', 'D', 'E')    returns 'D'
CHOOSE(1 > 2, 'A', 'B')                returns 'B'
CHOOSE(1 > 2)                          returns zero (0)

!Hide or unhide control, based on the value in SomeField:
?MyControl{PROP:Hide} = CHOOSE(SomeField = 0, TRUE, FALSE)

!VIEW filter to select "overweight" people of both sexes
MyView{PROP:Filter} = 'Weight > CHOOSE(Sex = 'M', 250, 200)'

CHOOSE(Date % 7 + 1, 'Sunday', 'Monday', 'Tuesday', 'Wednesday', |
        'Thursday', 'Friday', 'Saturday')
CHOOSE(Date % 7 + 1, 'Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat')

CHOOSE(Date % 7 % 6 + 1, 'Weekend', 'Weekday')
CHOOSE(INRANGE(Date % 7, 1, 5), 'Weekend', 'Weekday')

CHOOSE(INLIST(Emp:Sex, 'M', 'F'), 'Male', 'Female', 'Unknown')

```

**See Also:**

INLIST

## CHORD (draw a section of an ellipse)

**CHORD**( *x* , *y* , *width* , *height* , *startangle* , *endangle* [, *fill*] [, *attributelist*])

---

<b>CHORD</b>	Draws a closed sector of an ellipse on the current window or report.
<i>X</i>	An integer expression that specifies the horizontal position of the starting point.
<i>Y</i>	An integer expression that specifies the vertical position of the starting point.
<i>Width</i>	An integer expression that specifies the width.
<i>Height</i>	An integer expression that specifies the height.
<i>startangle</i>	An integer expression that specifies the starting point of the chord, in tenths of degrees (10 = 1 degree) measured counter-clockwise from three o'clock.
<i>endangle</i>	An integer expression that specifies the ending point of the chord, in tenths of degrees (10 = 1 degree) measured counter-clockwise from three o'clock.
<i>Fill</i>	A LONG integer constant, constant EQUATE, or variable containing the red, green, and blue components that create the color in the three low-order bytes (bytes 0, 1, and 2) or an EQUATE for a standard Windows color value.
<i>attributelist</i>	A string constant, variable, or EQUATE containing an optional type of output document and its associated attributes. Only valid when the target is a REPORT. See EXTEND

The **CHORD** procedure places a closed sector of an ellipse on the current window or report. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. The ellipse is drawn inside a "bounding box" defined by the *x*, *y*, *width*, and *height* parameters. The *x* and *y* parameters specify the starting point, and the *width* and *height* parameters specify the horizontal and vertical size of the "bounding box." The *startangle* and *endangle* parameters specify what sector of the ellipse will be drawn, as an arc. The two end points of the arc are also connected with a straight line.

The border color is the current pen color set by SETPENCOLOR; the default color is the Windows system color for window text. The border width is the current width set by SETPENWIDTH; the default width is one pixel. The border style is the current pen style set by SETPENSTYLE; the default style is a solid line.

### Example:

```
MDIChild WINDOW('Child One'), AT(0,0,320,200), MDI, MAX, HVSCROLL
    !window controls
END

CODE
OPEN(MDIChild)
CHORD(100,50,100,50,0,900,00FF0000h)    !Red 90 degree crescent
```

**See Also:** Current Target, SETPENCOLOR, SETPENWIDTH, SETPENSTYLE



## CHR (return character from ASCII)

**CHR**(*code*)

---

**CHR** Returns the display character.

*code* A numeric expression containing a numeric ASCII character code.

The **CHR** procedure returns the ANSI character represented by the ASCII character *code* parameter.

**Return Data Type:**      STRING

**Example:**

```
Stringvar = CHR(122)      !Get lower case z  
Stringvar = CHR(65)      !Get upper case A
```

**See Also:**

VAL

## CLEAR (clear a variable)

**CLEAR**(*label* [,*n*])

<b>CLEAR</b>	Clears the value from a variable.
<i>label</i>	The label of a variable (except BLOB types), GROUP, RECORD, QUEUE, CLASS, or FILE structure. If the variable has a DIM attribute, the entire array is cleared.
<i>N</i>	A numeric constant; either 1 or -1. If omitted or zero, numeric variables are cleared to zero, STRING variables are cleared to spaces, and PSTRING and CSTRING variables are set to zero length.

The **CLEAR** statement clears the value from the *label* variable.

The presence of the *n* parameter indicates a cleared value other than zero or blank. If *n* is 1, the *label* variable is set to the highest possible value for that data type. For the STRING, PSTRING and CSTRING data types, that is all ASCII 255. If *n* is -1, the *label* variable is set to the lowest possible value for that data type. For the STRING data type, that is all ASCII zeroes (0). For the PSTRING and CSTRING data types, that is a zero length string.

If the *label* parameter names a GROUP, RECORD, or QUEUE structure, all variables in the structure are cleared and all reference variables in the structure are set to NULL. If the *label* parameter names a FILE structure and the *n* parameter is omitted, all variables in the FILE structure (including any MEMO and/or BLOB fields) are cleared. If the *label* parameter names a CLASS structure or an object derived from a CLASS, all variables in the object are cleared and all reference variables are set to NULL.

If the variable has a DIM attribute, a single element can be cleared (i.e., CLEAR(MyName[n])), or the entire array is cleared if just the array name is specified (i.e., CLEAR(MyName)). For a STRING, it is possible to clear a range of elements by using string slicing (i.e., CLEAR(MyString[n:m])).

### Example:

```
MyQue QUEUE
F1      LONG
F2      STRING(20)
F3      &CSTRING    !Reference to a CSTRING
F4      ANY          !ANY can be a reference variable to any simple data type
END

CODE
CLEAR(MyQue)          !Equivalent to:
                      ! MyQue.F1 = 0
                      ! MyQue.F2 = ''
                      ! MyQue.F3 &= NULL
                      ! MyQue.F4 &= NULL

CLEAR(Count)          !Clear a variable
CLEAR(Cus:Record)      !Clear the record structure
CLEAR(Customer)        !Clear the record structure and any memos and blobs
CLEAR(Amount,1)        !Clear variable to highest possible value
CLEAR(Amount,-1)       !Clear variable to lowest possible value
```

**See Also:** Reference Assignment Statements, GROUP, RECORD, QUEUE, DIM, CLASS

## CLIP (return string without trailing spaces)

**CLIP**(*string*)

---

**CLIP**                Removes trailing spaces.

*string*              A string expression.

The **CLIP** procedure removes trailing spaces from a *string*. The return string is a substring with no trailing spaces. CLIP is frequently used with the concatenation operator in string expressions using STRING data types.

CLIP is not normally needed with CSTRING data types, since these have a terminating character. CLIP is also not normally needed with PSTRING data types, since these have a length byte.

When used in conjunction with the LEFT procedure, you can remove both leading and trailing spaces (frequently called ALLTRIM in other languages).

**Return Data Type:**    STRING

**Example:**

```
Name = CLIP>Last) & ', ' & CLIP(First) & Init & '.'    !Full name in military order
```

```
Name = CLIP(First) & CLIP(' ' & Middle) & ' ' & Last !Full name with or with middle
```

```
AllTrimVar = CLIP(LEFT(MyVar))                      !Trim leading and trailing spaces at once
```

**See Also:**

LEFT

## CLIPBOARD (return windows clipboard contents)

**CLIPBOARD**( [*format*] )

---

**CLIPBOARD** Returns the current contents of the Windows clipboard.

*format* An integer constant or variable that defines the format of the clipboard's contents. If omitted, the default is *CF\_TEXT*.

The **CLIPBOARD** procedure returns the current contents of the windows clipboard. The *format* parameter defaults to *CF\_TEXT* (as defined in the Windows API) but any of the other *CF\_* values can be specified (see a Windows API reference book for details). If the data in the clipboard is not in the specified *format*, **CLIPBOARD** returns a null string (""). The following clipboard formats are predefined in the Windows API:

<i>CF_TEXT</i>	1
<i>CF_BITMAP</i>	2
<i>CF_METAFILEPICT</i>	3
<i>CF_SYLK</i>	4
<i>CF_DIF</i>	5
<i>CF_TIFF</i>	6
<i>CF_OEMTEXT</i>	7
<i>CF_DIB</i>	8
<i>CF_PALETTE</i>	9
<i>CF_PENDATA</i>	10
<i>CF_RIFF</i>	11
<i>CF_WAVE</i>	12

Return Data Type: STRING

Example:

```
Que1 QUEUE
  STRING(30)
END
Que2 QUEUE
  STRING(30)
END
WinOne WINDOW,AT(0,0,160,400)
  LIST,AT(120,0,20,20),USE(?List1),FROM(Que1),DRAGID('List1')
  LIST,AT(120,120,20,20),USE(?List2),FROM(Que2),DROPID('List1','~FILE')
END
CODE
OPEN(WinOne)
ACCEPT
CASE EVENT()
OF EVENT:Drag
  !When a drag event is attempted
  IF DRAGID()
    !check for success
    SETCLIPBOARD(Que1)
    !and setup info to pass
  END
OF EVENT:Drop
  !When drop event is successful
  Que2 = CLIPBOARD()
  !get dropped info
  ADD(Que2)
  !and add it to the queue
END
END
```

See Also: SETCLIPBOARD

## CLOCK (return system time)

**CLOCK( )**

---

The **CLOCK** procedure returns the time of day from the operating system time in standard time (expressed as hundredths of a second since midnight, plus one). Although the time is expressed to the nearest hundredth of a second, the system clock is only updated 18.2 times a second (approximately every 5.5 hundredths of a second). The timestamps that you can obtain from Windows NT operating systems are limited to a maximum resolution of 10 or 15 milliseconds.

**Return Data Type:**     LONG

**Example:**

```
Time = CLOCK()  !Save the system time
```

**See Also:**

Standard Time

[SETCLOCK](#)

## CLONE(duplicate existing control)

**CLONE**(*destination control*, *source control* [,*parent*] [,*position*] [,*window*])

---

**CLONE** Duplicates an existing control.

*destination control* A field number or field equate label for the control to create.

*source control* A field number or field equate label for the control to duplicate.

*Parent* A field number or field equate label that specifies the OPTION, GROUP, SHEET, TAB, MENU, HEADER, FOOTER, DETAIL, BREAK, or FORM to contain the new *control*. If omitted, the control has no *parent*.

*Position* An integer constant, expression, or variable that specifies the position within a MENU to place a new ITEM *control*. If omitted, the ITEM is added to the end.

*Window* The label of an APPLICATION, WINDOW, or REPORT structure, or a reference to any of those structures where the control to duplicate exists.

**CLONE** dynamically duplicates an existing control to the currently active window. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. It returns the field equate label of the new control. The destination control inherits all properties of the source control. The position of the destination control should be modified using SETPOSITION() or PROP:AT if it will not be positioned on top of the source control.

CLONE may only be used to duplicate controls. It may not be used to duplicate report bands, menu items, or OLE controls.

**Return Data Type:** SIGNED

**Example:**

PROGRAM

```
INCLUDE('EQUATES.CLW')
INCLUDE('KEYCODES.CLW')
```

```
MAP
END
```

```
WINDOW WINDOW('Clone - example'),AT(, ,260,100),GRAY
    BUTTON('Ok'),AT(198,30,31,15),USE(?OkButton)
    BUTTON('Clone It'),AT(199,54,31,15),USE(?CloneButton)
END
```

```
WINDOW2 WINDOW('Window2'),AT(, ,260,100),GRAY
    BUTTON('Clone Me'),AT(98,30,31,15),USE(?CloneMe)
END
```

```
?Cloned          EQUATE(100)
CODE
OPEN(WINDOW)
ACCEPT
CASE ACCEPTED()
OF ?CloneButton
    OPEN(WINDOW2)
    SETTARGET(WINDOW)
    CLONE(?Cloned, ?CloneMe,,WINDOW2)
    CLOSE(WINDOW2)
    ?Cloned{PROP:YPOS} = ?Cloned{PROP:Ypos} + ?Cloned{PROP:Height} +10
    ?Cloned{PROP:Width} = ?Cloned{PROP:Width} + 20
    ?Cloned{PROP:Text} = 'Cloned Button'
OF ?OkButton
    BREAK
END
END
```

**See Also:** CREATE, SETPOSITION, SETTARGET, UNHIDE

## CLOSE (close a data structure)

**CLOSE**( *entity* )

---

**CLOSE**            Closes a data structure.

*entity*            The label of a FILE, VIEW, APPLICATION, WINDOW, or REPORT structure.

**CLOSE** terminates processing on the active *entity*. Any memory used by the active *entity* is released when it is closed.

### FILE Usage

---

CLOSE(file) closes an active FILE. Generally, this flushes DOS buffers and frees any memory used by the open file other than the RECORD structure's data buffer. If the file is a member of a transaction set, error 56 (LOGOUT active) is posted.

### VIEW Usage

---

CLOSE(view) closes an active VIEW. A VIEW declared within a procedure is implicitly closed upon RETURN from the procedure, if it has not already been explicitly CLOSEd. If the CLOSE(view) statement is not immediately preceded by a REGET statement, the state of the primary and secondary related files in the VIEW are undefined. The contents of their record buffers are undefined and a SET or RESET statement may be required before performing sequential processing on the file.

### APPLICATION and WINDOW Usage

---

CLOSE(window) closes an active APPLICATION or WINDOW structure. Memory used by the active window is released when it is closed and the underlying screen is automatically re-drawn. When a window is closed, if it is not the top-most window on its execution thread, all windows opened subsequent to the window being closed are automatically closed first. This occurs in the reverse order from which they were opened. An APPLICATION or WINDOW that is declared local to (within) a PROCEDURE is automatically closed when the program RETURNS from the procedure.

### REPORT Usage

---

CLOSE(report) closes an active REPORT structure, which prints the last page FOOTER (unless the last structure printed has the ALONE attribute) and any required group FOOTER structures, and closes the REPORT. If the REPORT has the PREVIEW attribute, all the temporary metafiles are deleted. RETURN from a procedure in which a REPORT is opened automatically closes the REPORT.

#### Errors Posted:

56    LOGOUT active



**Example:**

```

Customer      FILE,DRIVER('Clarion'),PRE(Cus) !Declare customer file layout
AcctKey       KEY(Cus:AcctNumber)
Record        RECORD
AcctNumber    LONG
OrderNumber   LONG
Name          STRING(20)
Addr          STRING(20)
City          STRING(20)
State         STRING(20)
Zip           STRING(20)
              END
              END

ViewCust      VIEW(Customer)                  !Declare VIEW structure
              PROJECT(Cus:AcctNumber,Cus:Name)
              END

CODE
OPEN(Customer,22h)
SET(Cus:AcctKey)
OPEN(ViewCust)                               !Open the customer view
!executable statements
CLOSE(ViewCust)                              !and close it again

CLOSE(Customer)                              !Close the customer file
CLOSE(MenuScr)                               !Close the menu screen
CLOSE(CustEntry)                             !Close customer data entry screen
CLOSE(CustRpt)                               !Close the report

```

**See Also:**

OPEN  
 LOGOUT  
 ACCEPT

## COLORDIALOG (return chosen color)

**COLORDIALOG**( [*title*] ,*rgb* [, *suppress*] )

<b>COLORDIALOG</b>	Displays the Windows standard color choice dialog box to allow the user to choose a color.
<i>title</i>	A string constant or variable containing the title to place on the color choice dialog. If omitted, a default <i>title</i> is supplied by Windows.
<i>rgb</i>	A LONG integer variable to receive the selected color.
<i>suppress</i>	An integer constant or variable containing either zero (0) or one (1). If one, the list of standard colors is suppressed. If omitted or zero (0) the list of standard colors is displayed.

The **COLORDIALOG** procedure displays the Windows standard color choice dialog box and returns the color chosen by the user in the *rgb* parameter. Any existing value in the *rgb* parameter sets the default color choice presented to the user in the color choice dialog. The color chosen by the user may be either an RGB value (a positive value) or one of the Windows standard element colors (a negative value).

COLORDIALOG returns zero (0) if the user pressed the Cancel button, or one (1) if the user pressed the Ok button on the color choice dialog.

**Return Data Type:** SIGNED

### Example:

```
MDIChild1 WINDOW('Child One') ,AT(0,0,320,200) ,MDI ,MAX ,HVSCROLL
    !window controls
END
```

ColorNow LONG

```
CODE
IF NOT COLORDIALOG('Choose Box Color',ColorNow)
    ColorNow = 000000FFh          !Default to Red if user pressed Cancel
END
OPEN(MDIChild1)
BOX(100,50,100,50,ColorNow)     !User-defined color for box
```

### See Also:

COLOR

FONT

## COMMAND (return command line)

**COMMAND**( [ *flag* ] )

**COMMAND** Returns command line parameters.

*flag* A string constant or variable containing the parameter for which to search, or the number of the command line parameter to return. If omitted or an empty string (""), all command parameters are returned as entered on the command line, appended to a leading space.

The **COMMAND** procedure returns the value of the *flag* parameter from the command line. If the *flag* is not found, **COMMAND** returns an empty string. If the *flag* is multiply defined, only the first occurrence encountered is returned.

**COMMAND** searches the command line for *flag=value* and returns *value*. There must be no blanks between *flag*, the equal sign, and *value*. The returned *value* terminates at the first comma or blank space. If a blank or comma is desired in a command line parameter, everything to the right of the equal sign must be enclosed in double quotes (*flag="value"*).

**COMMAND** will also search the command line for a *flag* containing a leading slash (/). If found, **COMMAND** returns the value of *flag* without the slash. If the *flag* only contains a number, **COMMAND** returns the parameter at that numbered position on the command line. A *flag* of '0' returns the minimum path the operating system used to find the command. This minimum path always includes the command (without command line parameters) but may not include the path (if the operating system found it in the current directory). A *flag* containing '1' returns the first command line parameter. The **COMMAND** search is not case sensitive.

**Return Data Type:** STRING

### Example:

```
IF COMMAND('/N')           !Was /N on the command line?
  DO SomeProcess
END
IF COMMAND('Option') = '1' !Was Option=1 on the command line?
  DO OneProcess
END
CommandString = COMMAND('') !Get all command parameters
CommandItself = COMMAND('0') !Get the command itself
SecondParm = COMMAND('2')    !Get second parameter from command line
```

### See Also:

SETCOMMAND

## COMMIT (terminate successful transaction)

### COMMIT

The **COMMIT** statement terminates an active transaction. Execution of a COMMIT statement assumes that the transaction was completely successful and no ROLLBACK is necessary. Once COMMIT has been executed, ROLLBACK of the transaction is impossible.

COMMIT informs the file driver involved in the transaction that the temporary files containing the information necessary to restore the database to its previous state may be deleted. The file driver then performs the actions necessary to its file system to successfully terminate a transaction.

#### Errors Posted:

48	Unable to Log Transaction
91	No Logout Active

#### Example:

```

LOGOUT(1,OrderHeader,OrderDetail)  !Begin Transaction
DO ErrorHandler                    !always check for errors
ADD(OrderHeader)                   !Add Parent record
DO ErrorHandler                    !always check for errors
LOOP X# = 1 TO RECORDS(DetailQue)  !Process stored detail records
  GET(DetailQue,X#)                !Get one from the QUEUE
  DO ErrorHandler                  !always check for errors
  Det:Record = DetailQue           !Assign to record buffer
  ADD(OrderDetail)                 !and add it to the file
  DO ErrorHandler                  !always check for errors
END
COMMIT                             !Terminate successful transaction
ASSERT(~ERRORCODE())

ErrorHandler ROUTINE                !Error routine
IF NOT ERRORCODE() THEN EXIT.       !Bail out if no error
Err" = ERROR()                     !Save the error message
ROLLBACK                           !Rollback the aborted transaction
ASSERT(~ERRORCODE())
BEEP                               !Alert the user
MESSAGE('Transaction Error - ' & Err)
RETURN                             !and get out
```

#### See Also:

LOGOUT

ROLLBACK

## CONTENTS (return contents of USE variable)



**CONTENTS**(*control*)

---

**CONTENTS** Returns the value in the USE variable of a control.

*control* A field number or field equate label.

The **CONTENTS** procedure returns a string containing the value in the USE variable of an ENTRY, OPTION RADIO, or TEXT control.

A USE variable may be longer than its associated control field display picture OR may contain fewer characters than its total capacity. The CONTENTS procedure always returns the full length of the USE variable.

**Return Data Type:** STRING

**Example:**

```
IF CONTENTS(?LastName) = '' AND CONTENTS(?FirstName) = '' !If first and last name blank,
  MessageField = 'Must Enter a First or Last Name' ! display error message
END
```

**See Also:**

PROP:ScreenText

CHANGE

## CONVERTANSITOOEM (convert ANSI strings to ASCII)

CONVERTANSITOOEM( *string* )

---

**CONVERTANSITOOEM** Translates ANSI strings to OEM ASCII.

*string*                      The label of the string to convert. This may be a single variable or a any structure that is treated as a GROUP (RECORD, QUEUE, etc.).

The **CONVERTANSITOOEM** statement translates either a single string or the strings within a GROUP from the ANSI (Windows display) character set into the OEM character set (ASCII with extra characters defined by the active code page).

This procedure is not required on data files if the OEM attribute is set on the file.

**Example:**

```
Customer  FILE,DRIVER('Clarion'),PRE(Cus)  !Declare file without OEM attribute
AcctKey   KEY(Cus:AcctNumber)
Record    RECORD
AcctNumber LONG
OrderNumber LONG
Name      STRING(20)
Addr      STRING(20)
          END
          END

Win WINDOW,SYSTEM
    STRING(@s20),USE(Cus:Name)
    END

CODE
OPEN(Customer)
SET(Customer)
NEXT(Customer)
CONVERTOEMTOANSI(Cus:Record)          !Convert all strings from ASCII to ANSI
OPEN(Win)
ACCEPT
    !Process window controls
    END
CONVERTANSITOOEM(Cus:Record)          !Convert back to ASCII from ANSI
PUT(Customer)
```

**See Also:**

CONVERTOEMTOANSI

OEM

## CONVERTOEMTOANSI (convert ASCII strings to ANSI)

**CONVERTOEMTOANSI**( *string* )

**CONVERTOEMTOANSI** Translates OEM ASCII strings to ANSI.

*string*                      The label of the string to convert. This may be a single variable or a any structure that is treated as a GROUP (RECORD, QUEUE, etc.).

The **CONVERTOEMTOANSI** statement translates either a single string or the strings within a GROUP from the the OEM character set (ASCII with extra characters defined by the active code page) into ANSI (Windows display) character set.

This procedure is not required on data files if the OEM attribute is set on the file.

### Example:

```
Customer  FILE,DRIVER('Clarion'),PRE(Cus)  !Declare file without OEM attribute
AcctKey   KEY(Cus:AcctNumber)
Record    RECORD
AcctNumber LONG
OrderNumber LONG
Name      STRING(20)
Addr      STRING(20)
          END
          END

Win WINDOW,SYSTEM
    STRING(@s20),USE(Cus:Name)
    END

CODE
OPEN(Customer)
SET(Customer)
NEXT(Customer)
CONVERTOEMTOANSI(Cus:Record)          !Convert all strings from ASCII to ANSI
OPEN(Win)
ACCEPT
    !Process window controls
    END
CONVERTANSITOOEM(Cus:Record)          !Convert back to ASCII from ANSI
PUT(Customer)
```

### See Also:

CONVERTANSITOOEM

OEM

## COPY (copy a file)

**COPY**(*file*,*new file*)

---

<b>COPY</b>	Duplicates a file.
<i>file</i>	The label of a FILE structure, or a string constant or variable containing the file specification of the file to copy.
<i>new file</i>	A string constant or variable containing a file specification. If the file specification does not contain a drive and path, the current drive and directory are assumed. If only the path is specified, the filename and extension of the original <i>file</i> are used for the <i>new file</i> .

The **COPY** statement duplicates a FILE and enters the specification for the *new file* in the operating system's directory listing. The *file* to copy must be closed, or the "File Already Open" error is posted. If the file specification of the *new file* is identical to the original *file*, the COPY statement is ignored.

Since some file drivers use multiple physical disk files for one logical FILE structure, the default filename and extension assumptions are dependent on the file driver. If any error is posted, the file is not copied.

### Errors Posted:

02	File Not Found
03	Path Not Found
05	Access Denied
52	File Already Open

### Example:

```
FromFolder  CSTRING(250)
ToFolder    CSTRING(250)
TheFile     STRING(256),STATIC
SomeFile    FILE,DRIVER('DOS'),NAME(TheFile)
Record      RECORD
F1          STRING(1)
            END
            END
            END

CODE
TheFile = 'Names.DAT'
COPY(TheFile,'A:') !Copy file to floppy
COPY('C:\AUTOEXEC.BAT','A:\AUTOEXEC.BAT') !Copy file to floppy
FromFolder = 'z:\my folder\file1.tps'
ToFolder = 'z:\backup area' !Use double quotes to handle folders with spaces
COPY(FromFolder,ToFolder)
```

### See Also:

CLOSE



## COS (return cosine)

**COS**(*radians*)

**COS** Returns cosine.

*radians* A numeric constant, variable or expression for the angle in radians.  $\pi$  is a constant which represents the ratio of the circumference and radius of a circle. There are  $2\pi$  radians (or 360 degrees) in a circle.

The **COS** procedure returns the trigonometric cosine of an angle measured in *radians*. The cosine is the ratio of the length of the angle's adjacent side divided by the length of the hypotenuse.

**Return Data Type:** REAL

### Example:

```
PI      EQUATE(3.1415926535898)  !The approx. value of PI
Rad2Deg EQUATE(57.295779513082)  !Number of degrees in a radian
Deg2Rad EQUATE(0.0174532925199)  !Number of radians in a degree
CODE
Angle = 45 * Deg2Rad              !Translate 45 degrees to Radians
CosineAngle = COS(Angle)          !Get the cosine of 45 degree angle
```

### See Also:

TAN

ATAN

SIN

ASIN

ACOS

## CREATE (create an empty data file)

**CREATE**(*file*)

---

**CREATE**        Creates an empty data file.

*file*            The label of the FILE to be created.

The **CREATE** statement adds an empty data file to the operating system directory. If the *file* already exists, it is deleted and recreated as an empty file. The *file* must be closed, or the "File Already Open" error is posted. CREATE does not open the file for access.

**Errors Posted:**

03	Path Not Found
04	Too Many Open Files
05	Access Denied
52	File Already Open
54	No Create Attribute

**Example:**

```
CREATE (Master)      !Create a new master file
CREATE (Detail)      !Create a new detail file
```

**See Also:**

CLOSE

## CREATE (return new control created)

**CREATE**( *control* , *type* [, *parent* ] [, *position* ] )

**CREATE**      Creates a new control.

*Control*      A field number or field equate label for the control to create. The valid range of field numbers is -4000h to 4000h. If the control equal to 0, the CREATE procedure returns the next available field number and assigns that to the control being created.

*Type*      An integer constant, expression, EQUATE, or variable that specifies the type of control to create.

*Parent*      A field number or field equate label that specifies the OPTION, GROUP, SHEET, TAB, MENU, HEADER, FOOTER, DETAIL, BREAK, or FORM to contain the new *control*. If omitted, the control has no *parent*.

*Position*      An integer constant, expression, or variable that specifies the position within a MENU to place a new ITEM *control*. If omitted, the ITEM is added to the end.

**CREATE** dynamically creates a new control in the currently active APPLICATION or WINDOW, returning the value of the *control* parameter. If the field creation fails, a 0 is returned. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

When first created, the new *control* is initially hidden, so its properties can be set using the runtime property assignment syntax, SETPOSITION, and SETFONT. It appears on screen only by issuing an UNHIDE statement for the *control*.

You can also use CREATE to create report controls. To do this, you must first use SETTARGET to make the report the currently active TARGET, and you must also specify a *parent* for the control.

EQUATE statements for the *type* parameter are contained in the EQUATES.CLW file. The following list is a comprehensive sample of these (see EQUATES.CLW for the complete list):

CREATE:ssstring	STRING(picture),USE(variable)
CREATE:string	STRING(constant)
CREATE:image	IMAGE()
CREATE:region	REGION()
CREATE:line	LINE()
CREATE:box	BOX()
CREATE:ellipse	ELLIPSE()
CREATE:entry	ENTRY()
CREATE:button	BUTTON()
CREATE:prompt	PROMPT()
CREATE:option	OPTION()

CREATE:radio	RADIO()
CREATE:check	CHECK()
CREATE:group	GROUP()
CREATE:list	LIST()
CREATE:combo	COMBO()
CREATE:spin	SPIN()
CREATE:text	TEXT()
CREATE:custom	CUSTOM()
CREATE:droplist	LIST(),DROP()
CREATE:dropcombo	COMBO(),DROP()
CREATE:menu	MENU()
CREATE:item	ITEM()
CREATE:toolbar	TOOLBAR()

Note: The CREATE:Toolbar constant is a modifier to instruct the runtime library that the control must be created *inside* the toolbar rather than inside window client area:

```
CREATE (0, CREATE:Button + CREATE:Toolbar)
!creates a button on the toolbar if it exists

CREATE (0, CREATE:Button)
!creates a button in the window client area
```

**Return Data Type:** SIGNED

**Example:**

PROGRAM

```
INCLUDE('keycodes.clw')

MAP
END

TestGroup GROUP,PRE(CTL)
CODE LONG
Name STRING(30)
END

X SHORT
Y SHORT
Width SHORT
Height SHORT

Code4Entry STRING(10)
?Code4Entry EQUATE(100) !Create an arbitrary field equate number for CREATE t
o use
FEQ EQUATE(101)
UseVarText1 &STRING

Window WINDOW,VSCROLL,GRAY,MAXIMIZE
```

```

ENTRY (@N3) , AT (3,32) , USE (Ctl:Code)
ENTRY (@S30) , AT (98,8) , USE (Ctl:Name)
BUTTON ('OK') , AT (5,7) , USE (?OkButton)
BUTTON ('Cancel') , AT (45,7) , USE (?CanxButton)
END

CODE
OPEN (Window)
ACCEPT
CASE ACCEPTED ()
OF ?Ctl:Code
IF Ctl:Code = 4
    CREATE (?Code4Entry,CREATE:entry)                !Create the control
    ?Code4Entry{PROP:use} = Code4Entry                !Set USE variable
    ?Code4Entry{PROP:text} = '@s10'                  !Set entry picture
    GETPOSITION (?Ctl:Code,X,Y,Width,Height)
    ?Code4Entry{PROP:Xpos} = X + Width + 40           !Set x position
    ?Code4Entry{PROP:Ypos} = Y                       !Set y position
    UNHIDE (?Code4Entry)                             !Display the new control
ELSIF Ctl:Code = 5
    CREATE (FEQ, CREATE:text)
    UseVarText1 &= NEW (STRING (10000))
    FEQ {PROP:use} = UseVarText1
    GETPOSITION (?Ctl:Code,X,Y,Width,Height)
    FEQ {PROP:Xpos} = X + Width + 40                 !Set x position
    FEQ {PROP:Ypos} = Y + 5                          !Set y position
    FEQ {PROP:width} = 300
    FEQ {PROP:height} = 100
    FEQ {PROP:Vscroll} = TRUE
    UNHIDE (FEQ)                                     !Display the new control
END
OF ?OkButton
BREAK
OF ?CanxButton
CLEAR (TestGroup)
BREAK
END
END
DISPOSE (UseVarText1)
CLOSE (Window)

RETURN

```

See Also: CLONE , DESTROY , SETPOSITION , SETTARGET ,

## DATE (return standard date)

**DATE**(*month,day,year*)

---

<b>DATE</b>	Return standard date.
<i>month</i>	A numeric constant, variable, or expression for the <i>month</i> .
<i>day</i>	A numeric constant, variable, or expression for the <i>day</i> of the month.
<i>year</i>	A numeric constant, variable or expression for the <i>year</i> . The valid range for a <i>year</i> value is 00 through 99 (using "Intellidate" logic), or within the Clarion standard date range.

The **DATE** procedure returns a standard date for a given *month*, *day*, and *year*. The *month* and *day* parameters do allow positive out-of-range values. A *month* value of 13 is interpreted as January of the next year. A *day* value of 32 in January is interpreted as the first of February. Consequently, DATE(12,32,97), DATE(13,1,97), and DATE(1,1,98) all produce the same result.

The century for a two-digit *year* parameter is resolved using the default "Intellidate" logic, which assumes the date falls in the range of the next 20 or previous 80 years from the current operating system date. For example, assuming the current year is 1998, if the *year* parameter is "15," the date returned is in the year 2015, and if the *year* parameter is "60," the date returned is in 1960.

**Return Data Type:** LONG

### Example:

```
HireDate = DATE (Hir:Month,Hir:Day,Hir:Year)           !Compute hire date
FirstOfMonth = DATE (MONTH (TODAY ()),1, YEAR (TODAY ())) !Compute First day of month
DaysInMonth = DAY (DATE (mn + 1,0,yr))                 !Compute days in a month
```

### See Also:

Standard Date

DAY

MONTH

YEAR

TODAY

## DAY (return day of month)

**DAY**(*date*)

---

**DAY** Returns day of month.

*date* A numeric constant, variable, expression, or the label of a STRING, CSTRING, or PSTRING variable declared with a date picture token. The *date* must be a standard date. A variable declared with a date picture token is automatically converted to a standard date intermediate value.

The **DAY** procedure computes the day of the month (1 to 31) for a given standard date.

**Return Data Type:** LONG

**Example:**

```
OutDay = DAY(TODAY())      !Get the day from today's date
DueDay = DAY(TODAY()+2)    !Calculate the return day
```

**See Also:**

Standard Date

MONTH

YEAR

TODAY

DATE

## DEFORMAT (return unformatted numbers from string)

**DEFORMAT**(*string* [,*picture*])

---

**DEFORMAT**    Removes formatting characters from a numeric string.

*string*            A string expression containing a numeric string.

*picture*            A picture token, or the label of a CSTRING variable containing a picture token. If omitted, the picture for the *string* parameter is used. If the *string* parameter was not declared with a picture token, the return value will contain only characters that are valid for a numeric constant.

The **DEFORMAT** procedure removes formatting characters from a numeric string, returning only the numbers contained in the string. When used with a date or time *picture* (except those containing alphabetic characters), it returns a STRING containing the Clarion Standard Date or Time.

**Return Data Type:**    STRING

**Example:**

!DEFORMAT('\$1,234.56')	returns 1234.56
!DEFORMAT('309-53-9954')	returns 309539954
!DEFORMAT('40A1-7',@P##A1-#P)	returns 407
!DEFORMAT('-10000')	returns -10000
!DEFORMAT(' -10000')	returns 10000

!Get phone number for modem to dial:

DialString = 'ATDT1' & DEFORMAT(PHONE,@P(###)###-####P) & '<13,10>'

ClarionDate = DEFORMAT(dBaseDate,@D1)    !Clarion Standard date from mm/dd/yy string

Data = '45,123'

Number = DEFORMAT(Data)

!Assign a formatted number to a string

!then remove non-numeric characters

**See Also:**

FORMAT

Standard Date

Standard Time

Picture Tokens



## DELETE (delete a record)

**DELETE**( *entity* )

---

**DELETE**            Removes a record from a FILE, VIEW, or QUEUE structure.

*entity*              The label of a FILE, VIEW, or QUEUE structure.

The **DELETE** statement removes a record.

### FILE Usage

---

DELETE(file) removes the last record successfully accessed by NEXT, PREVIOUS, GET, REGET, ADD, or PUT. The key entries for that record are also removed from the KEYS. DELETE does not clear the record buffer. Therefore, data values from the record just deleted still exist and are available for use until the record buffer is overwritten. If no record was previously accessed, or the record is held by another workstation, DELETE posts the "Record Not Available" error and no record is deleted.

### VIEW Usage

---

DELETE(view) removes the last VIEW primary file record that was successfully accessed by a NEXT or PREVIOUS statement. The key entries for that record are also removed from the KEYS. DELETE does not remove records from any secondary JOIN files in the VIEW. If no record was previously accessed, or the record is held by another workstation, DELETE posts the "Record Not Available" error and no record is deleted. The specific disk action DELETE performs in the file is file driver dependent.

DELETE only deletes the primary file record in the VIEW because the VIEW structure performs both relational Project and Join operations at the same time. Therefore, it is possible to create a VIEW structure that, if all its component files were updated, would violate the Referential Integrity rules set for the database. The common solution to this problem in SQL-based database products is to delete only the Primary file record. Therefore, Clarion has adopted this same industry standard solution.

### QUEUE Usage

---

DELETE(queue) removes the QUEUE entry at the position of the last successful GET or ADD and de-allocates its memory. If no previous GET or ADD was executed, the "Entry Not Found" error is posted. DELETE does not affect the current POINTER procedure return value, however, once the entry is deleted, the POINTER value for all subsequent entries in the QUEUE decrement by one (1).

If the QUEUE contains any reference variables or fields with the ANY data type, you must reference assign a NULL to each reference variable and ANY field in the queue structure before the DELETE statement. This will avoid memory leaks by freeing up the memory used by the ANY or reference variables before the DELETE statement.

#### Errors Posted:

- 05            Access Denied
- 08            Insufficient Memory

- 30      Entry Not Found  
33      Record Not Available

**Example:**

```
Customer  FILE,DRIVER('Clarion'),PRE(Cus)  !Declare customer file layout
AcctKey    KEY(Cus:AcctNumber)
Record     RECORD
AcctNumber LONG
Name       STRING(20)
Addr       STRING(20)
City       STRING(20)
State      STRING(20)
Zip        STRING(20)
           END
           END

CustView   VIEW(Customer)                  !Declare VIEW structure
           PROJECT(Cus:AcctNumber,Cus:Name)
           END

NameQue     QUEUE,PRE(Que)
Name        STRING(20),NAME('FirstField')
Zip         DECIMAL(5,0),NAME('SecondField')
           END

CODE
DO BuildQue
LOOP X# = RECORDS(NameQue) TO 1 BY -1      !Call routine to build the queue
!Loop backwards through queue
  GET(NameQue,X#)                          !geting each entry
  ASSERT(NOT ERRORCODE())
  IF NameQue.Name[1] = 'J'                  !Evaluate a condition
    DELETE(NameQue)                        !and delete only specific entries
    ASSERT(NOT ERRORCODE())
  END
END

OPEN(Customer)
Cus:AcctNumber = 12345                      !Initialize key field
SET(Cus:AcctKey,Cus:AcctKey)
OPEN(CustView)
NEXT(CustView)                             !Get that record
  IF ERRORCODE()
    STOP(ERROR())
  END
DELETE(CustView)                           !Delete the customer record
CLOSE(CustView)                            !Close the VIEW

Cus:AcctNumber = 12345                      !Initialize key field
GET(Customer,Cus:AcctKey)                  !Get that record
IF ERRORCODE() THEN STOP(ERROR()).
DELETE(Customer)                           !Delete the customer record
```

**See Also:** HOLD, NEXT, PREVIOUS, PUT, GET, ADD, ANY, CLEAR

Reference Variables

## DELETereg (remove a value or key from Windows registry)

**DELETereg** (LONG root, STRING keyname [.STRING valuenamE])

<b>DELETereg</b>	Deletes a named entry from the system registry.
<i>root</i>	The root section of the registry from which to delete the value. Valid values for this are defined in <b>equates.clw</b> and are as follows: <div style="margin-left: 20px;">             REG_CLASSES_ROOT              REG_CURRENT_USER              REG_LOCAL_MACHINE              REG_USERS              REG_PERFORMANCE_DATA              REG_CURRENT_CONFIG              REG_DYN_DATA           </div>
<i>keyname</i>	The name of the key to delete, or the key to delete from.
<i>valuenamE</i>	The name of the value to delete. If omitted the whole key is deleted.

### Vista and Clarion Built-in Registry Functions

On Vista, a (non-elevated) app can READ the registry key HKLM (local machine) with no problems, but as far as writing to the Registry it needs to use HKCU (current user).

If you code sign your executable and run with elevated privileges then you can write to HKLM

#### Example:

```

PROGRAM
MAP
END

INCLUDE('EQUATES')
CurrentPath CSTRING(100)
ColorScheme CSTRING(100)

CODE
DELETereg(REG_LOCAL_MACHINE,'SOFTWARE\SoftVelocity\Clarion7','root')
!remove the root directory entry of the Clarion 6 install
DELETereg(REG_CURRENT_USER,'Control Panel\Current')
!since a specific value is not specified,
!the entire "Current" key will be removed

```

**See Also:** GETREG, PUTREG

## DESTROY (remove a control)



**DESTROY**( [ *first control* ] [, *last control* ] )

---

**DESTROY**      Removes window controls.

*first control*      Field number or field equate label of a control, or the first control in a range of controls. If omitted, defaults to zero (0).

*last control*      Field number or field equate label of the last control in a range of controls.

The **DESTROY** statement removes a control, or range of controls, from an APPLICATION or WINDOW structure. When removed, the control's resources are returned to the operating system.

DESTROYing a GROUP, OPTION, MENU, TAB, or SHEET control also destroys all controls contained within it.

**Example:**

```
Screen WINDOW,PRE(Scr)
    ENTRY(@N3),USE(Ctl:Code)
    ENTRY(@S30),USE(Ctl:Name)
    BUTTON('OK'),USE(?OkButton),KEY(EnterKey)
    BUTTON('Cancel'),USE(?CanxButton),KEY(EscKey)
END

CODE
OPEN(Screen)
DESTROY(?Ctl:Code)           !Remove a control
DESTROY(?Ctl:Code,?Ctl:Name) !Remove range of controls
DESTROY(2)                   !Remove the second control
```

**See Also:**

CREATE

## DIRECTORY (get file directory)

**DIRECTORY**( *queue*, *path*, *attributes* )

**DIRECTORY** Gets a file directory listing (just like the DIR command in DOS).

*queue* The label of the QUEUE structure that will receive the directory listing.

*path* A string constant, variable, or expression that specifies the path and filenames directory listing to get. This may include the wildcard characters (\* and ?).

*attributes* An integer constant, variable, or expression that specifies the attributes of the files to place in the *queue*.

The **DIRECTORY** procedure returns a directory listing of all files in the *path* with the specified *attributes* into the specified *queue*.

The *queue* parameter must name a QUEUE with a structure that begins the same as the following structure contained in EQUATES.CLW:

```
ff_:queue  QUEUE,PRE(ff_),TYPE
name       STRING(13)
date       LONG
time       LONG
size       LONG
attrib     BYTE    !A bitmap, the same as the attributes EQUATES
END
```

or the following structure (for long filename support):

```
FILE:queue QUEUE,PRE(File),TYPE
name       STRING(FILE:MAXFILENAME) !FILE:MAXFILENAME is an EQUATE
shortname  STRING(13)
date       LONG
time       LONG
size       LONG
attrib     BYTE    !A bitmap, the same as the attributes EQUATES
END
```

Your QUEUE may contain more fields, but must begin with these fields. It will receive the returned information about each file in the *path* that has the *attributes* you specify. The date and time fields will contain standard Clarion date and time information (the conversion from the operating system's storage format to Clarion standard format is automatic).

The *attributes* parameter is a bitmap which specifies what filenames to place in the *queue*. The following equates are contained in EQUATES.CLW:

```
ff_:NORMAL    EQUATE(0)    !Always active
ff_:READONLY  EQUATE(1)    !Not for use as attributes parameter
ff_:HIDDEN    EQUATE(2)
ff_:SYSTEM    EQUATE(4)
ff_:DIRECTORY EQUATE(10H)
ff_:ARCHIVE   EQUATE(20H)  ! NOT Win95 compatible
```

The *attributes* bitmap is an OR filter: if you add the equates, you get files with any of the attributes you specify. This means that, when you just set the *attributes* to `ff_:NORMAL`, you only get files (no sub-directories) without the hidden, system, or archive bits set. If you add `ff_:DIRECTORY` to `ff_:NORMAL`, you will get files AND sub-directories from the *path*. Since `ff_:NORMAL` is an equate for zero (0), you will always get files.

## Short filenames used in applications

Applications should avoid the use of the short filenames returned by `DIRECTORY`. This includes *never* using the `DIRECTORY(ff_:Queue...)` syntax, which retrieves only short names. Instead, use the `DIRECTORY(FILE:QUEUE...)` syntax, and avoid using the *ShortName* field.

Short file names do not exist under all file systems. The short file name returned in the queue is sometimes the long file name, truncated to 13 bytes. Under Windows NT/2000/XP systems, the registry key **NtfsDisable8dot3NameCreation** allows turning off short file names. Files created after this key is enabled will not have a short file name generated.

### Note:

Setting *NtfsDisable8dot3NameCreation*=1 in the Windows system registry improves performance. This setting may become more popular and eventually can be the default. Developers using short file names in applications released to the general public may run into problems in the near future.

### Tip

Sometimes you can run into a user running your applications on a Novell server *without* the long file name NLM loaded, so you can't rely on *all* file systems supporting long file names. Therefore, the safest strategy is to name your files with legal 8.3 short names, and as noted above, only use the long file name queue field returned by `DIRECTORY`.

Example:

```
DirectoryList  PROCEDURE
```

```
AllFiles  QUEUE(File:queue),PRE(FIL)      !Inherit exact declaration of File:queue
END
```

```
LP        LONG
Recs      LONG
```

```
CODE
```

```
DIRECTORY(AllFiles,'*.*',ff_:DIRECTORY)    !Get all files and directories
Recs = RECORDS(AllFiles)
LOOP LP = Recs TO 1 BY -1
  GET(AllFiles,LP)
  IF BAND(FIL:Attrib,ff_:DIRECTORY) AND FIL:ShortName <> '..' AND FIL:ShortName <> '.'
    CYCLE                                     !Let sub-directory entries stay
  ELSE
    DELETE(AllFiles)                         !Get rid of all other entries
  END
END
```

**Additional Example:**

PROGRAM

MAP

```
GetFileSize    PROCEDURE (STRING FileName2Get, <*LONG OutDate>,<*LONG OutTime>),ULONG
END
```

```
MySize        ULONG
```

CODE

```
MySize = GetFileSize('myfile.zip')
```

```
GetFileSize    PROCEDURE (STRING FileName2Get, <*LONG OutDate>,<*LONG OutTime>)
```

```
FilesQ        QUEUE (FILE:Queue),PRE (FilesQ)
```

```
END
```

CODE

```
DIRECTORY (FilesQ,FileName2Get,ff_:NORMAL+ff_:READONLY+ff_:HIDDEN+ff_:SYSTEM)
```

```
GET (FilesQ,1)
```

```
IF ERRORCODE()
```

```
    CLEAR(FilesQ) !Return 0 if file not found
```

```
END
```

```
IF ~OMITTED(2)
```

```
    OutDate=FilesQ:Date
```

```
END
```

```
IF ~OMITTED(3)
```

```
    OutTime=FilesQ:Time
```

```
END
```

```
RETURN FilesQ:Size
```

```
!Note: Return as ULONG to work with files over 2GB in size
```

**See Also:**

SHORTPATH

LONGPATH

PATH

FILEDIALOG

## DISABLE (dim a control)



**DISABLE**( [ *first control* ] [, *last control* ] )

---

**DISABLE**       Dims controls on the window.

*first control*     Field number or field equate label of a control, or the first control in a range of controls. If omitted, defaults to zero (0).

*last control*      Field number or field equate label of the last control in a range of controls.

The **DISABLE** statement disables a control or a range of controls on an APPLICATION or WINDOW structure. When disabled, the control appears dimmed on screen.

### Example:

```
Screen WINDOW,PRE(Scr)
    ENTRY(@N3),USE(Ctl:Code)
    ENTRY(@S30),USE(Ctl:Name)
    BUTTON('OK'),USE(?OkButton),KEY(EnterKey)
    BUTTON('Cancel'),USE(?CanxButton),KEY(EscKey)
END

CODE
OPEN(Screen)
DISABLE(?Ctl:Code)           !Disable a control
DISABLE(?Ctl:Code,?Ctl:Name) !Disable range of controls
DISABLE(2)                   !Disable the second control
```

### See Also:

ENABLE

HIDE

UNHIDE



## DISPLAY (write USE variables to screen)



**DISPLAY**( [*first control*] [,*last control*] )

**DISPLAY** Writes the contents of USE variables to their associated controls.

*first control* Field number or field equate label of a control, or the first control in a range of controls.

*last control* Field number or field equate label of the last control in a range of controls.

**DISPLAY** writes the contents of the USE variables to their associated controls on the active window. **DISPLAY** with no parameters writes the USE variables for all controls on the screen. Using *first control* alone, as the parameter of **DISPLAY**, writes a specific USE variable to the screen. Both *first control* and *last control* parameters are used to display the USE variables for an inclusive range of controls on the screen.

The current contents of the USE variables of all controls are automatically displayed on screen each time the **ACCEPT** loop cycles if the window has the **AUTO** attribute present. This eliminates the need to explicitly issue a **DISPLAY** statement to update the video display. Of course, if your application performs some operation that takes a long time and you want to indicate to the user that something is happening without cycling back to the top of the **ACCEPT** loop, you should **DISPLAY** some variable that you have updated.

### Example:

```

DISPLAY                !Display all controls on the screen
DISPLAY(2)              !Display control number 2
DISPLAY(3,7)            !Display controls 3 through 7
DISPLAY(?MenuControl)   !Display the menu control
DISPLAY(?TextBlock,?Ok) !Display range of controls
  
```

### See Also:

Field Equate Labels

**UPDATE**

**ERASE**

**CHANGE**

**AUTO**

## DRAGID (return matching drag-and-drop signature)



**DRAGID**( [*thread*] [, *control*] )

**DRAGID** Returns matching host and target signatures on a successful drag-and-drop operation.

*thread* The label of a numeric variable to receive the thread number of the host control. If the host control is in an external program, *thread* receives zero (0).

*control* The label of a numeric variable to receive the field equate label of the host control.

The **DRAGID** procedure returns the matching host and target control signatures on a successful drag-and-drop operation. If the user aborted the operation, DRAGID returns an empty string ("), otherwise it returns the first signature that matched between the two controls.

**Return Data Type:**      **STRING**

### Example:

```
Que1 QUEUE
      STRING(30)
      END
Que2 QUEUE(Que1)           !Que2 declared same as Que1
      END
Que3 QUEUE(Que1)           !Que3 declared same as Que1
      END
WinOne WINDOW,AT(0,0,360,400)
      !Allows drags, but not drops:
      LIST,AT(120,0,20,20),USE(?List1),FROM(Que1),DRAGID('List1')
      !Allows drops from List1 or List3, but no drags:
      LIST,AT(120,120,20,20),USE(?List2),FROM(Que2),DROPID('List1','List3')
      !Allows drags, but not drops:
      LIST,AT(120,240,20,20),USE(?List3),FROM(Que3),DRAGID('List3')
      END
CODE
OPEN(WinOne)
ACCEPT
CASE EVENT()
  OF EVENT:Drop             !When drop event is successful
    CASE DRAGID()           !check for which host dropped it
      OF 'List1'
        Que2 = Que1         !get dropped info from Que1
      OF 'List3'
        Que2 = Que3         !get dropped info from Que3
      END
    ADD(Que2)               !add either one to the drop queueue
  END
END
```

**See Also:** DROPID, SETDROPID

## DROPID (return drag-and-drop string)



**DROPID**( [*thread*] [, *control*] )

---

**DROPID** Returns matching host and target signatures on a successful drag-and-drop operation.

*thread* The label of a numeric variable to receive the thread number of the target control. If the target control is in an external program, *thread* receives zero (0).

*control* The label of a numeric variable to receive the field equate label of the target control.

The **DROPID** procedure returns the matching host and target control signatures on a successful drag-and-drop operation (just as DRAGID does), or the specific string set by the SETDROPID procedure. The DROPID procedure returns a comma-delimited list of filenames dragged from the Windows File Manager when '~FILE' is the DROPID attribute.

**Return Data Type:**        STRING

**Example:**

```
DragDrop    PROCEDURE
Que1 QUEUE
    STRING(90)
END

Que2 QUEUE
    STRING(90)
END

WinOne WINDOW('Test Drag Drop'),AT(10,10,240,320),SYSTEM,MDI
    !Drag but no drop:
    LIST,AT(12,0,200,80),USE(?List1),FROM(Que1),DRAGID('List1')
    !Allows drops from List1 or the Windows File Manager, but no drags:
    LIST,AT(12,120,200,80),USE(?List2),FROM(Que2),DROPID('List1','~FILE')
END

CODE
OPEN(WinOne)
ACCEPT
CASE EVENT()
OF EVENT:Drag
    IF DRAGID()
        !When a drag event is attempted
        !check for success
        GET(Que1,CHOICE())
        SETDROPID(Que1)
        !and setup info to pass
    END
OF EVENT:Drop
    !When drop event is successful
    IF INSTRING(' ',DROPID(),1,1) !Check for multiple files from File Manager
        Que2 = |
        !and only get first
        SUB(DROPID(),1,INSTRING(' ',DROPID(),1,1)-1)
        ADD(Que2)
        !and add it to the queue
    ELSE
        Que2 = DROPID()
        !get dropped info, from List1 or File Manager
        ADD(Que2)
        !and add it to the queue
    END
END
END
```

**See Also:**

DRAGID

SETDROPID

## DUPLICATE (check for duplicate key entries)

```
DUPLICATE(  | key | )
           | file |
```

**DUPLICATE** Checks duplicate entries in unique keys.

*key* The label of a KEY declaration.

*file* The label of a FILE declaration.

The **DUPLICATE** procedure returns a non-zero value (true) if writing the current record to the data file would post the "Creates Duplicate Key" error. With a *key* parameter, only the specified KEY is checked. With a *file* parameter, all KEYs declared without a DUP attribute are checked. DUPLICATE is most useful to detect potential duplicate key errors before writing to disk.

The DUPLICATE procedure assumes that the contents of the RECORD structure data buffer are duplicated at the current record pointer location. Therefore, when using DUPLICATE prior to ADDing a record, the record pointer should be cleared with: GET(*file*,0).

**Return Data Type:** LONG

### Example:

```
IF Action = 'ADD' THEN GET(Vendor,0) .           !If adding, clear the file pointer
IF DUPLICATE(Vendor)                           !If this vendor already exists
  SCR:MESSAGE = 'Vendor Number already assigned' !display message
  SELECT(?)                                     !and stay on the field
END
```

### See Also:

GET

ADD

DUP

## ELLIPSE (draw an ellipse)

**ELLIPSE**( *x* , *y* , *width* , *height* [, *fill*] [, *attributelist*])

---

<b>ELLIPSE</b>	Draws an ellipse on the current window or report.
<i>X</i>	An integer expression that specifies the horizontal position of the starting point.
<i>Y</i>	An integer expression that specifies the vertical position of the starting point.
<i>Width</i>	An integer expression that specifies the width.
<i>Height</i>	An integer expression that specifies the height.
<i>Fill</i>	A LONG integer constant, constant EQUATE, or variable containing the red, green, and blue components that create the color in the three low-order bytes (bytes 0, 1, and 2) or an EQUATE for a standard Windows color value.
<i>attributelist</i>	A string constant, variable, or EQUATE containing an optional type of output document and its associated attributes. Only valid when the target is a REPORT. See EXTEND

The **ELLIPSE** procedure places an ellipse on the current window or report. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#. The ellipse is drawn inside a "bounding box" defined by the *x*, *y*, *width*, and *height* parameters. The *x* and *y* parameters specify the starting point, and the *width* and *height* parameters specify the horizontal and vertical size of the "bounding box."

The border color is the current pen color set by SETPENCOLOR; the default color is the Windows system color for window text. The border width is the current width set by SETPENWIDTH; the default width is one pixel. The border style is the current pen style set by SETPENSTYLE; the default style is a solid line.

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !window controls
END
CODE
OPEN(MDIChild)
ELLIPSE(100,50,100,50,00FF0000h)    !Red ellipse
```

### See Also:

Current Target  
SETPENCOLOR  
SETPENWIDTH  
SETPENSTYLE

## EMPTY (empty a data file)

**EMPTY**(*file*)

---

**EMPTY**           Deletes all records from a FILE.

*file*               The label of a FILE.

**EMPTY** deletes all records from the specified *file*. **EMPTY** requires exclusive access to the file. Therefore, the file must be opened with *access mode* set to 12h (Read/Write Deny All) or 22h (Read/Write Deny Write).

**Errors Posted:**

37           File Not Open

63           Exclusive Access Required

**Example:**

```
OPEN(Master,18)       !Open the master file
EMPTY(Master)         !and start a new one
```

**See Also:**

OPEN

SHARE

## ENABLE (re-activate dimmed control)



**ENABLE**( [ *first control* ] [, *last control* ] )

---

**ENABLE**        Reactivates disabled controls.

*first control*     Field number or field equate label of a control, or the first control in a range of controls. If omitted, defaults to zero (0).

*last control*      Field number or field equate label of the last control in a range of controls.

The **ENABLE** statement reactivates a control, or range of controls, that were dimmed by the **DISABLE** statement, or were declared with the **DISABLE** attribute. Once reactivated, the control is again available to the operator for selection. If the *first control* and *last control* parameters are omitted, **ENABLE** reactivates all controls on the window.

**Example:**

```
CODE
OPEN(Screen)
DISABLE(?Control2)           !Control2 is deactivated
IF Ctl:Password = 'Supervisor'
    ENABLE(?Control2)         !Re-activate Control2
END
```

**See Also:**

DISABLE

HIDE

UNHIDE



## ENDPAGE (force page overflow)

**ENDPAGE**( *report* [, *printfooters* ] )

---

**ENDPAGE**      Forces page overflow.

*report*            The label of a REPORT structure.

*printfooters*    An integer constant or variable. If omitted or zero (0), this prints group footers by forcing a group BREAK (usually used to terminate a report for preview). If one (1), group BREAKs are left open and no group footers print (usually used during a continuing report).

The **ENDPAGE** statement initiates page overflow and flushes the print engine's print structure buffer. If the REPORT has the PREVIEW attribute, this has the effect of ensuring that the entire report is available to view.

**Example:**

SomeReport PROCEDURE

```
WMFQue QUEUE                                !Queue to contain .WMF filenames
    STRING(64)
END
```

```
NextEntry  BYTE(1)                          !Queue entry counter variable
```

```
Report     REPORT,PREVIEW(WMFQue)           !Report with PREVIEW attribute
DetailOne  DETAIL
            !Report controls
            END
        END
```

```
ViewReport WINDOW('View Report'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    IMAGE('',AT(0,0,320,180),USE(?ImageField)
    BUTTON('View Next Page'),AT(0,180,60,20),USE(?NextPage),DEFAULT
    BUTTON('Print Report'),AT(80,180,60,20),USE(?PrintReport)
    BUTTON('Exit Without Printing'),AT(160,180,60,20),USE(?ExitReport)
END
```

CODE

```
OPEN(Report)
SET(SomeFile)                                !Code to generate the report
LOOP
    NEXT(SomeFile)
    PRINT(DetailOne)
END
ENDPAGE(Report)                             !Flush the buffer
OPEN(ViewReport)                             !Open report preview window
GET(WMFQue,NextEntry)                       !Get first queue entry
?ImageField{PROP:text} = WMFQue             !Load first report page
ACCEPT
CASE ACCEPTED()
OF ?NextPage
    NextEntry += 1                           !Increment entry counter
    IF NextEntry > RECORDS(WMFQue) THEN CYCLE. !Check for end of report
    GET(WMFQue,NextEntry)                   !Get next queue entry
    ?ImageField{PROP:text} = WMFQue         !Load next report page
    DISPLAY                                 !and display it
OF ?PrintReport
    Report{PROP:flushpreview} = ON          !Flush files to printer
    BREAK                                   !and exit procedure
OF ?ExitReport
    BREAK                                   !Exit procedure
. .
CLOSE(ViewReport)                           !Close window
FREE(WMFQue)                                !Free the queue memory
CLOSE(Report)                               !Close report (deleting all .WMF files)
RETURN                                       ! and return to caller
```

**See Also:**

Page Overflow

PREVIEW

## ERASE (clear screen control and USE variables)



**ERASE**( [*first control*] [,*last control*] )

**ERASE**            Blanks controls and clears their USE variables.

*first control*      Field number or field equate label of a control, or the first control in a range of controls. If omitted, defaults to zero (0).

*last control*       Field number or field equate label of the last control in a range of controls.

The **ERASE** statement erases the data from controls in the window and clears their corresponding USE variables. ERASE with no parameters erases all controls in the window. Using *first control* alone, as the parameter of ERASE, clears a specific USE variable and its associated control. Both *first control* and *last control* parameters are used to clear the USE variables and associated controls for an inclusive range of controls in the window.

### Example:

```
ERASE (?)           !Erase the currently selected control
ERASE              !Erase all controls on the screen
ERASE (3,7)        !Erase controls 3 through 7
ERASE (?Name,?Zip) !Erase controls from name through zip
ERASE (?City,?City+2) !Erase City and 2 controls following City
```

### See Also:

Field Equate Labels

CHANGE

## ERROR (return error message)

### ERROR()

The **ERROR** procedure returns a string containing a description of any error that was posted. If no error was posted, ERROR returns an empty string. You should interrogate ERROR immediately after the statement which you suspect may post an error because processing any other statement which *could* post an error will clear the internal errorcode.

**Return Data Type:**        STRING

#### Example:

```
PUT (NameQueue)                !Write the record
IF ERROR() = 'Queue Entry Not Found' !If not found
  ADD (NameQueue)              !add new entry
  IF ERRORCODE()               !Check for unexpected error
    STOP (ERROR())
  END
END
```

#### See Also:

ERRORCODE

ERRORFILE

FILEERROR

FILEERRORCODE

POPERRORS

PUSHERRORS

Trappable Run Time Errors

## ERRORCODE (return error code number)

**ERRORCODE()**

---

The **ERRORCODE** procedure returns the code number for any error that was posted. If no error was posted, ERRORCODE returns zero. You should interrogate ERRORCODE immediately after the statement that you suspect may post an error because processing any other statement that could post an error will clear the internal error code.

**Return Data Type:**        LONG

**Example:**

```
ADD(Location)           !Add new entry
IF ERRORCODE() = 8      !If not enough memory
  MESSAGE('Out of Memory') !display message
END
```

**See Also:**

ERROR

ERRORFILE

FILEERROR

FILEERRORCODE

POPERRORS

PUSHERRORS

Trappable Run Time Errors

## ERRORFILE (return error filename)

### ERRORFILE()

The **ERRORFILE** procedure returns the name of the file for which an error was posted. If the file is open, the full DOS file specification is returned. If the file is not open, the contents of the FILE statement's NAME attribute is returned. If the file is not open and the file has no NAME attribute, the label of the FILE statement is returned. If no error was posted, or the posted error did not involve a file, ERRORFILE returns an empty string.

**Return Data Type:**     STRING

#### Example:

```
ADD(Location)                      !Add new entry
IF ERRORCODE()
  MESSAGE('Error with ' & ERRORFILE()) !Display error filename
END
```

#### See Also:

ERRORCODE

ERROR

FILEERRORCODE

FILEERROR

POPERRORS

PUSHERRORS

Trappable Run Time Errors

## EVENT (return event number)



### EVENT( )

The **EVENT** procedure returns a number indicating what caused ACCEPT to alert the program that something has happened that it may need to handle. There are EQUATES listed in EQUATES.CLW for all the events the program may need to handle.

There are two types of events generated by ACCEPT: field-specific and field-independent events. Field-specific events affect a single control, while field-independent events affect the window or program. The type of event can be determined by the values returned by the ACCEPTED, SELECTED, and FIELD procedures. If you need to know which field has input focus on a field-independent event, use the FOCUS procedure.

*For field-specific events:*

The FIELD procedure returns the field number of the control on which the event occurred. The ACCEPTED procedure returns the field number if the event is EVENT:Accepted. The SELECTED procedure returns the field number if the event is EVENT:Selected.

*For field-independent events:*

The FIELD, ACCEPTED, and SELECTED procedures all return zero (0).

**Return Data Type:** SIGNED

#### Example:

```
ACCEPT
CASE EVENT( )
OF EVENT:Selected
CASE SELECTED( )
OF ?Control1
!Pre-edit code here
OF ?Control2
!Pre-edit code here
END
OF EVENT:Accepted
CASE ACCEPTED( )
OF ?Control1
!Post-edit code here
OF ?Control2
!Post-edit code here
END
END
END
```

**See Also:** ACCEPT, FIELD, FOCUS, ACCEPTED, SELECTED, Modal Events

## EXISTS (return file or folder existence)

**EXISTS**( *file* )

---

**EXISTS**            Returns TRUE if the *file* is available on disk.

*file*                An expression containing the DOS filename.

The **EXISTS** procedure returns true (1) if the *file* is available on disk. If the *file* is not available, EXISTS returns false (0). You can also use EXISTS to check for the existence of any folder.

**Return Data Type:**    LONG

### Example:

```
SomeFile  CSTRING(FILE:MaxFilePath),STATIC

Customer  FILE,DRIVER('ASCII','/CLIP = on'),CREATE,NAME(SomeFile)
Record    RECORD
_Line     STRING(1024)
          END
          END
          CODE
SomeFile = 'customer.tps'
IF EXISTS(SomeFile) !or EXISTS(NAME(Customer)) is also valid
  OPEN(Customer)
ELSE
  CREATE(Customer)
END

IF EXISTS('C:\Clarion6\BIN\') !Is there a Clarion 6 BIN folder
DO InstallCheck
END
```

### See Also:

OPEN  
STATUS  
CREATE  
NAME



## FIELD (return control with focus)

{bmc NewC7.bmp}

FIELD( )

The **FIELD** procedure returns the field number of the control which has focus at the time of any field-specific event. This includes both the EVENT:Selected and EVENT:Accepted events. FIELD returns zero (0) for field-independent events.

Positive field numbers are assigned by the compiler to all WINDOW controls, in the order their declarations occur in the WINDOW structure. Negative field numbers are assigned to all APPLICATION controls. In executable code statements, field numbers are usually represented by field equate labels--the label of the USE variable preceded by a question mark (?FieldName).

**Return Data Type:** SIGNED

### Example:

```
Screen WINDOW
    ENTRY (@N4),USE (Control1)
    ENTRY (@N4),USE (Control2)
    ENTRY (@N4),USE (Control3)
    ENTRY (@N4),USE (Control4)
END

CODE
ACCEPT
    IF NOT ACCEPTED()
        CYCLE
    END
    CASE FIELD()
        !Control edit control
    OF ?Control1
        !Field number 1
        IF Control1 = 0
            !if no entry
            BEEP
            !sound alarm
            SELECT(?)
            !stay on control
        END
    OF ?Control2
        !Field number 2
        IF Control2 > 4
            !if status is more than 4
            Scr:Message = 'Control must be less than 4'
            ERASE(?)
            !clear control
            SELECT(?)
            !edit the control again
        ELSE
            !value is valid
            CLEAR(Scr:Message)
            !clear message
        END
    OF ?Control4
        !Field number 4
        BREAK
        !exit processing loop
    END
END
!end case, end loop
```

**See Also:** ACCEPT, ACCEPTED, SELECTED, FOCUS, EVENT

## FILEDIALOG (return chosen file)

**FILEDIALOG**( [*title*] ,*file* [,*extensions*] [,*flag*] )

---

**FILEDIALOG** Displays Windows standard file choice dialogs to allow the user to choose a file.

*title* A string constant or variable containing the title to place on the dialog. If omitted, Windows supplies a default.

*file* The label of the string variable to receive the selected filename(s).

*extensions* A string constant or variable containing the available file extension selections for the "List Files of Type" drop list. If omitted, the default is all files (\*.\*) .

*flag* An integer constant or variable containing a bitmap to indicate the type of file action to perform.

The **FILEDIALOG** procedure displays Windows standard file choice dialogs and returns the file chosen by the user in the *file* parameter. Any existing value in the *file* parameter sets the default file choice presented to the user in the file choice dialog.

FILEDIALOG displays either the standard *Open...* dialog or the standard *Save...* dialog. By default, on the *Open...* dialog, the user is warned if the file they choose does not exist and the file is not opened. On the *Save...* dialog, the user is warned if the file does exist and the file is not saved.

The *extensions* parameter string must contain a description followed by the file mask. All elements in the string must be delimited by the vertical bar (|) character. For example, the *extensions* string:

'All Files | \*.\* | Clarion Source | \*.CLW;\*.INC;\*.EQU;\*.INT | Clarion Templates|\*.TPL;\*.TPW'

defines three selections for the "List Files of Type" drop list. The first extension listed in the *extensions* string is the default. Multiple extensions are separated by a semicolon (;) character.

The *flag* parameter is a bitmap that indicates the type of file action to perform (see EQUATES.CLW for symbolic constants). For bit number:

- 0 If zero (0000b), the *Open...* dialog displays.
- 1 If one (0001b), the *Save...* dialog displays.
- 2 If two (0010b), saves and restores the current directory path.
- 4 If four (0100b), doesn't report errors if the file does exist on *Save...* or does not exist on *Open...*
- 8 If eight (1000b), returns multiple selections when the user selects multiple files. When using long filename dialog, it returns a vertical bar (|) delimited string of filenames (with the full path on the first selection returned, unless a single file is selected, where the path and file is returned on a single selection). The string is space-delimited when using short filename dialog. Not valid when used with File:Save or File:Directory.

- 16 If sixteen (10000b), uses long filename dialog in 32-bit programs.
- 32 If thirty-two (100000b), displays a directory select dialog for selecting a directory path.
- 64 If sixty-four (1000000b), and the specified and typed file name does not exist, the dialog displays a prompt to create a new file with the given name. If the user chooses to create the file, the FILEDIALOG function completes and returns the typed file name; otherwise the dialog remains open. This flag can't be combined with the FILE:Directory flag.
- 128 If one-hundred twenty eight (10000000b), and the specified file name is typed without an extension, the default extension is appended. The default extension is the one used in the first mask for the first filter pair. If there are meta-characters (\* or ?) in the default extension, the flag is ignored. The flag is also ignored if either or both of the FILE:Multi and FILE:Directory flags are used. To type in the file name without an extension if the FILE:AddExtension is specified, the file name *must* be enclosed in quotes (i.e., "myfile"). Due to a Windows restriction, if the default extension is longer than 3 characters, only the first 3 characters are appending to the file name.

The following is a comprehensive sample of these flags simplified to equates (see EQUATES.CLW for the complete list):

FILE:Save	EQUATE(1)
FILE:KeepDir	EQUATE(2)
FILE:NoError	EQUATE(4)
FILE:Multi	EQUATE(8)
FILE:LongName	EQUATE(10H)
FILE:Directory	EQUATE(20H)
FILE:CreatePrompt	EQUATE(40H)
FILE:AddExtension	EQUATE(80H)

FILEDIALOG returns zero (0) if the user pressed the Cancel button, or one (1) if the user pressed the Ok button on the file choice dialog. If the user changes directories using the file dialog, your application's current directory also changes (unless you set FILE:KeepDir). This is a feature of the Windows operating system. If you do not want users to change your application's current directory but do want them to be able look in other directories, either save the current directory with the PATH() procedure before calling FILEDIALOG then restore it with the SETPATH() statement, or set FILE:KeepDir.

**Return Data Type:**    BOOL

**Example:**

```
ViewTextFile PROCEDURE
ViewQue QUEUE                !LIST control display queue
    STRING(255)
END

FileName    STRING(64),STATIC  !Filename variable

ViewFile    FILE,DRIVER('ASCII'),NAME(FileName),PRE(Vew)
Record      RECORD
    STRING(255)
    END
END

MDIChild1 WINDOW('View Text File'),AT(0,0,320,200),MDI,SYSTEM,HVSCROLL
    LIST,AT(0,0,320,200),USE(?L1),FROM(ViewQue),HVSCROLL
END

CODE
IF NOT FILEDIALOG('Choose File to View',FileName,'Text|*.TXT|Source|*.CLW',FILE:LongName)
    RETURN                !Return if no file chosen
END
OPEN(ViewFile)            !Open the file
IF ERRORCODE() THEN RETURN END!aborting on any error
SET(ViewFile)              !Start at top of file
LOOP
    NEXT(ViewFile)         !Reading each line of text
    IF ERRORCODE() THEN BREAK END !Break loop at end of file
    ViewQue = Vew:Record    !Assign text to queue
    ADD(ViewQue)            !and add a queue entry
END
CLOSE(ViewFile)            !Close the file
OPEN(MDIChild1)            !and open the window
ACCEPT                     !Allow the user to read the text and
END                         !break out of ACCEPT loop only from
                           !system menu close option
FREE(ViewQue)              !Free the queue memory
RETURN                     !and return to caller

!*****
```

!This example shows using FILEDIALOG for multi-file selection:

```
SelectFiles    PROCEDURE (SelectFileQueue DFQ)

Found          CSTRING(10000),AUTO
Path           CSTRING(File:MaxFilePath),AUTO
Separator      STRING(1),AUTO
Pos            UNSIGNED,AUTO
NameStart      UNSIGNED,AUTO

CODE
Found=SELF.DefaultFile
IF FILEDIALOG('Pick 1 or more files',Found, |
'All Files | *.* | Clarion Source | *.CLW;*.INC;*.EQU;*.INT|Clarion Templates|*.TPL;*.TPW', |
FILE:KeepDir+FILE:Multi+FILE:LongName)
  Separator='|'
  Pos=INSTRING(Separator,Found,1,1)
  IF Pos
    !Multi-Selected files
    ASSERT(Pos > 1)
    Path = CHOOSE(Found[Pos-1] <> '\', Found[1 : Pos-1]&'\'', Found[1 : Pos-1])
    LOOP
      NameStart = Pos+1
      Pos = INSTRING(Separator,Found,1,NameStart)
      IF ~Pos THEN Pos=LEN(Found)+1.
      DFQ.Name = Path&Found[NameStart : Pos-1]
      ADD(DFQ)
    WHILE Pos<=LEN(Found)
  ELSE
    DFQ.Name=Found
    ADD(DFQ)
    !Single file only selected
  END
END
```

!\*\*\*\*\*  
!This example shows using FILEDIALOG for multi-file selection:

```
FILEDIALOG('Test', FileName, 'Text files|*.txt|All files|*.*', |
FILE:LongName + FILE:NoError + FILE:AddExtension)
```

!If the user types AAA and pressed the Open button, the returned file  
!name is '<current directory>\AAA.txt'; if the user typed "AAA",  
!result is '<current directory>\AAA'

#### See Also:

FILEDIALOGA

SETPATH

SHORTPATH

LONGPATH

DIRECTORY

GETFONT

SETFONT

PROP:FontDialogHook

## FILEDIALOGA (extended file dialog)

**FILEDIALOGA**( [*title*] ,*file* [,*extensions*] [,*flag*] [,*index*] )

---

**FILEDIALOGA** Displays Windows standard file choice dialogs to allow the user to choose a file.

<i>title</i>	A string constant or variable containing the title to place on the dialog. If omitted, Windows supplies a default.
<i>file</i>	The label of the string variable to receive the selected filename(s).
<i>extensions</i>	A string constant or variable containing the available file extension selections for the "List Files of Type" drop list. If omitted, the default is all files (*.*)).
<i>flag</i>	An integer constant or variable containing a bitmap to indicate the type of file action to perform.
<i>index</i>	A signed integer variable used to select a different default extension by specifying the index number.

The **FILEDIALOGA** procedure displays Windows standard file choice dialogs and returns the file chosen by the user in the *file* parameter. Any existing value in the *file* parameter sets the default file choice presented to the user in the file choice dialog.

**FILEDIALOGA** displays either the standard *Open...* dialog or the standard *Save...* dialog. By default, on the *Open...* dialog, the user is warned if the file they choose does not exist and the file is not opened. On the *Save...* dialog, the user is warned if the file does exist and the file is not saved.

The *extensions* parameter string must contain a description followed by the file mask. All elements in the string must be delimited by the vertical bar (|) character. For example, the *extensions* string:

```
'All Files | *.* | Clarion Source | *.CLW;*.INC;*.EQU;*.INT | Clarion  
Templates | *.TPL;*.TPW'
```

defines three selections for the "List Files of Type" drop list. The first extension listed in the *extensions* string is the default. Multiple extensions are separated by a semicolon (;) character.

The *flag* parameter is a bitmap that indicates the type of file action to perform (see EQUATES.CLW for symbolic constants). For bit number:

- 0 If zero (0000b), the *Open...* dialog displays.
- 1 If one (0001b), the *Save...* dialog displays.
- 2 If two (0010b), saves and restores the current directory path.
- 4 If four (0100b), doesn't report errors if the file does exist on *Save...* or does not exist on *Open...*
- 8 If eight (1000b), returns multiple selections when the user selects multiple files. When using long filename dialog, it returns a vertical bar (|) delimited string of filenames (with the full path on the first selection returned, unless a single file is selected, where the path and file is returned on a single selection). The string is space-delimited when using short filename dialog. Not valid when used with File:Save or File:Directory.

- 16 If sixteen (10000b), uses long filename dialog in 32-bit programs.
- 32 If thirty-two (100000b), displays a directory select dialog for selecting a directory path.
- 64 If sixty-four (1000000b), and the specified and typed file name does not exist, the dialog displays a prompt to create a new file with the given name. If the user chooses to create the file, the FILEDIALOGA function completes and returns the typed file name; otherwise the dialog remains open. This flag can't be combined with the FILE:Directory flag.
- 128 If one-hundred twenty eight (10000000b), and the specified file name is typed without an extension, the default extension is appended. The default extension is one used in the first mask for the first filter pair (if the last parameter of FILEDIALOGA is omitted), or for the filter pair with number contained in the integer variable passed as the last parameter of FILEDIALOGA (*index*). If there are meta-characters (\* or ?) in the default extension, the flag is ignored. The flag is also ignored if either or both of the FILE:Multi and FILE:Directory flags are used. To type in the file name without an extension if the FILE:AddExtension is specified, the file name *must* be enclosed in quotes (i.e., "myfile"). Due to a Windows restriction, if the default extension is longer than 3 characters, only the first 3 characters are appending to the file name.

The following is a comprehensive sample of these flags simplified to equates (see EQUATES.CLW for the complete list):

FILE:Save	EQUATE(1)
FILE:KeepDir	EQUATE(2)
FILE:NoError	EQUATE(4)
FILE:Multi	EQUATE(8)
FILE:LongName	EQUATE(10H)
FILE:Directory	EQUATE(20H)
FILE:CreatePrompt	EQUATE(40H)
FILE:AddExtension	EQUATE(80H)

Finally, the *index* parameter is a SIGNED integer used to specify a different default extension other than the first one in the *extensions* list. For example:

```
'All Files | *.* | Clarion Source | *.CLW;*.INC;*.EQU;*.INT | Clarion Templates|*.TPL;*.TPW'
```

The extensions string consists of pairs: <description>|<mask>, and the index parameter references such pairs. Therefore, in the example above, an *index* value of 2 will display the 'Clarion Source' description and associated extensions; an index value of 3 will display 'Clarion Templates', etc.

If **FILEDIALOGA** returns a non-zero value (i.e., the dialog is completed with Open or Save button), the index parameter is set to the index of the extension pair that was used for file selection.

**FILEDIALOGA** returns zero (0) if the user pressed the Cancel button, or one (1) if the user pressed the Ok button on the file choice dialog. If the user changes directories using the file dialog, your application's current directory also changes (unless you set FILE:KeepDir). This is a feature of the Windows operating system. If you do not want users to change your application's current directory but do want them to be able look in other directories, either save the current directory with the PATH() procedure before calling **FILEDIALOGA** then restore it with the SETPATH() statement, or set FILE:KeepDir.

**Return Data Type:**            BOOL

**Example:**

```
ViewTextFile PROCEDURE
ViewQue QUEUE                   !LIST control display queue
    STRING(255)
END

FileName    STRING(64),STATIC   !Filename variable

ViewFile    FILE,DRIVER('ASCII'),NAME(FileName),PRE(Vew)
Record      RECORD
    STRING(255)
END
END

MDIChild1 WINDOW('View Text File'),AT(0,0,320,200),MDI,SYSTEM,HVSCROLL
    LIST,AT(0,0,320,200),USE(?L1),FROM(ViewQue),HVSCROLL
END

Fxt    SIGNED(2) !File Extension
CODE
IF NOT FILEDIALOGA('Choose File to View',FileName,'Text|*.TXT|Source|*.CLW',FILE:LongName,Fxt)
    RETURN                   !Return if no file chosen
END
OPEN(ViewFile)              !Open the file
IF ERRORCODE() THEN RETURN END!aborting on any error
SET(ViewFile)              !Start at top of file
LOOP
    NEXT(ViewFile)           !Reading each line of text
    IF ERRORCODE() THEN BREAK END !Break loop at end of file
    ViewQue = Vew:Record      !Assign text to queue
    ADD(ViewQue)             !and add a queue entry
END
CLOSE(ViewFile)             !Close the file
OPEN(MDIChild1)             !and open the window
ACCEPT                     !Allow the user to read the text and
END                         !break out of ACCEPT loop only from
                           !system menu close option
FREE(ViewQue)              !Free the queue memory
RETURN                     !and return to caller
```



```

!*****
!This example shows using FILEDIALOGA for multi-file selection:
  PROGRAM
  MAP
  END

FN          STRING(260)
ExtPickInOut SIGNED,AUTO
ExtFound     SIGNED,AUTO
  CODE
  ExtPickInOut = 2 !default to CSV
  IF ~FILEDIALOGA('Pick file to save',fn,'Text|*.TXT|Comma Delimited    |
(*.CSV)|*.CSV|Tab Delimited (*.TSV)|*.TSV', FILE:Save+ FILE:LongName, |
ExtPickInOut)
    RETURN
  END
  ExtFound = INLIST(UPPER(SUB(CLIP(FN),-4,4)),'.TXT','.CSV','.TSV')
  IF ~ExtFound !No extension so add one based on selected file type
    ExtFound=ExtPick
    fn=clip(fn) & CHOOSE(ExtPickInOut, '.TXT', '.CSV', '.TSV', '')
  END

!This code assumes a 3 byte extension. There are a other possible ways to test
!for an extension.

```

**See Also:**

FILEDIALOG

SETPATH

SHORTPATH

LONGPATH

DIRECTORY

GETFONT

SETFONT

PROP:FontDialogHook

## FILEERROR (return file driver error message)

**FILEERROR()**

The **FILEERROR** procedure returns a string containing the "native" error message from the file system (file driver) being used to access a data file. Valid only when **ERRORCODE()** = 90 or **ERRORCODE()** = 47.

**Return Data Type:**        **STRING**

**Example:**

```
PUT(NameFile)           !Write the record
IF ERRORCODE() = 90      !Back-end-specific error occurred
  MESSAGE(FILEERROR())
  RETURN
END
```

**See Also:**

ERRORCODE

ERROR

ERRORFILE

FILEERRORCODE

Trappable Run Time Errors

## FILEERRORCODE (return file driver error code number)

FILEERRORCODE( )

---

The **FILEERRORCODE** procedure returns a string containing the code number for the "native" error message from the file system (file driver) being used to access a data file. Valid only when ERRORCODE() = 90 or ERRORCODE() = 47.

**Return Data Type:**      STRING

**Example:**

```
PUT(NameFile)           !Write the record
IF ERRORCODE() = 90      !Back-end-specific error occurred
  MESSAGE(FILEERRORCODE())
  RETURN
END
```

**See Also:**

FILEERROR

ERRORFILE

ERRORCODE

ERROR

Trappable Run Time Errors

Extended Errorcode 47 Errors

## FIRSTFIELD (return first window control)



**FIRSTFIELD()**

---

The **FIRSTFIELD** procedure returns the lowest field number in the currently active window (or REPORT) as specified by SETTARGET. This does not include any controls in a TOOLBAR or MENUBAR.

**Return Data Type:**    SIGNED

**Example:**

```
DISABLE (FIRSTFIELD() ,LASTFIELD())    !Dim all control fields
```

**See Also:**

LASTFIELD

## FIXFORMAT (fix a dynamic file)

**FIXFORMAT**( *file* )

---

*file*      The label of a FILE structure, which must be a reference variable.

**FIXFORMAT** fixes a dynamic file so that it can be used like any other file.

If you pass a file that was not created using NEW(*file*), **FIXFORMAT** posts the following error codes that can be trapped by the ERRORCODE function:

Errorcode	Equate	Reason
80	<i>NoDriverSupport</i>	File passed that was not created with NEW( <i>file</i> )
47	<i>InvalidFileErr</i>	Structure is invalid

If Error code 47 is posted, the FILEERRORCODE statement can be used to return extended information. See the ErrorCode 47 Extended information topic for more information.

**See Also:** UNFIXFORMAT

## FLUSH (flush buffers)

**FLUSH**(*file*)

---

**FLUSH** Terminates a STREAM operation, flushing the operating system buffers to disk, or flushes the BUFFER statement's buffers.

*file* The label of a FILE or VIEW.

The **FLUSH** statement terminates a STREAM operation. It flushes the operating system buffers, which updates the directory entry for that *file*. FLUSH will also flush the file driver's buffers allocated by the BUFFER statement. If both STREAM and BUFFER are active, all buffers are flushed.

Support for this statement is dependent upon the file system and its specific action is described in the file driver documentation (if different from that described here).

**Example:**

```
STREAM(History)           !Use DOS buffering
SET(Current)              !Set to top of current file
LOOP
  NEXT(Current)
  IF ERRORCODE() THEN BREAK END
  His:Record = Cur:Record
  ADD(History)
END
FLUSH(History)            !End streaming, flush buffers
OPEN(MyView)
BUFFER(MyView,10,5,2,300) !10 records per page, 5 pages behind and 2 read-ahead,
                          !with a 5 minute timeout
                          !Process records
FLUSH(MyView)           !Flush buffers
```

**See Also:**

STREAM

BUFFER

## FOCUS (return control with focus)



**FOCUS()**

The **FOCUS** procedure returns the field number of the control which has received the last EVENT:SELECTED event among the other controls (not menu items) of the active window.

Positive field numbers are assigned by the compiler to all WINDOW controls, in the order their declarations occur in the WINDOW structure. Negative field numbers are assigned to all APPLICATION controls. In executable code statements, field numbers are usually represented by field equate labels--the label of the USE variable preceded by a question mark (?FieldName).

**Return Data Type:** SIGNED

### Example:

```
W WINDOW
  ENTRY (@N4) ,USE (Control1)
  ENTRY (@N4) ,USE (Control2)
  ENTRY (@N4) ,USE (Control3)
END
CODE
OPEN (W)
ACCEPT
CASE EVENT ()
  OF EVENT:LoseFocus
  OROF EVENT:CloseWindow
    CASE FOCUS ()          !Control edit control
      OF ?Control1         !Field number 1
        UPDATE (?Control1)
      OF ?Control2         !Field number 2
        UPDATE (?Control2)
      OF ?Control3         !Field number 3
        UPDATE (?Control3)
    END
  END
END
END
```

### See Also:

ACCEPTED

SELECTED

FIELD

EVENT

## FONTDIALOG (return chosen font)

**FONTDIALOG**(*[title]* ,*typeface* [*,size*] [*,color*] [*,style*] [*,added*] )

---

<b>FONTDIALOG</b>	Displays the standard Windows font choice dialog box to allow the user to choose a font.
<i>title</i>	A string constant or variable containing the title to place on the font choice dialog. If omitted, a default <i>title</i> is supplied by Windows.
<i>typeface</i>	A string variable (STRING in Clarion, CLASTRING in Clarion#) to receive the name of the chosen font.
<i>size</i>	A SREAL to receive the size (in points) of the chosen font.
<i>color</i>	A SIGNED integer variable to receive the red, green, and blue values for the color of the chosen font in the low-order three bytes.
<i>style</i>	A SIGNED integer variable to receive the strike weight and style of the chosen font.
<i>added</i>	An integer constant or variable that specifies adding screen or printer fonts, or both, to the list of available fonts. Zero (0) adds screen fonts, one (1) adds printer fonts, and two (2) adds both. If omitted, only Windows registered fonts are listed. Not valid in Clarion#

The **FONTDIALOG** procedure displays the Windows standard font choice dialog box to allow the user to choose a font. When called, any values in the parameters set the default font values presented to the user in the font choice dialog. They also receive the user's choice when the user presses the Ok button on the dialog. FONTDIALOG returns zero (0) if the user pressed the Cancel button, or one (1) if the user pressed the Ok button.

The **FONTDIALOG** procedure is limited to fonts of the ANSI or Default character set, to use another character set use the **FONTDIALOGA** function.

**Return Data Type:**        BOOL



**Example:**

```
MDIChild1 WINDOW('View Text File'),AT(0,0,320,200),MDI,SYSTEM,HVSCROLL
           !window controls
           END

Typeface   STRING(31) !or CLASTRING for Clarion#
FontSize   SREAL
FontColor   SIGNED
FontStyle   SIGNED

CODE
OPEN(MDIChild1)                                !open the window
IF FONTDIALOG('Choose Display Font',Typeface,FontSize,FontColor,FontStyle,0)
    SETFONT(0,Typeface,FontSize,FontColor,FontStyle) !Set window font
ELSE
    SETFONT(0,'Arial',12)                        !Set default font
END
ACCEPT
    !Window handling code
END
```

**See Also:**

FONT(set default font)  
Font Support Quick Summary

## FONTDIALOGA (return chosen font and character set)

**FONTDIALOGA**(*[title]* ,*typeface* [*,size*] [*,color*] [*,style*] [*,charset*] [*,added*] )

---

<b>FONTDIALOGA</b>	Displays the standard Windows font choice dialog box to allow the user to choose a font and a character set.
<i>title</i>	A string constant or variable containing the title to place on the font choice dialog. If omitted, a default <i>title</i> is supplied by Windows.
<i>typeface</i>	A string variable (STRING in Clarion, CLASTRING in Clarion#) to receive the name of the chosen font.
<i>size</i>	A SREAL variable to receive the size (in points) of the chosen font.
<i>color</i>	A SIGNED integer variable to receive the red, green, and blue values for the color of the chosen font in the low-order three bytes.
<i>style</i>	A SIGNED integer variable to receive the strike weight and style of the chosen font.
<i>charset</i>	A SIGNED integer variable to receive the character set value.
<i>added</i>	An integer constant or variable that specifies adding screen or printer fonts, or both, to the list of available fonts. Zero (0) adds screen fonts, one (1) adds printer fonts, and two (2) adds both. If omitted, only Windows registered fonts are listed. Not valid in Clarion#.

The **FONTDIALOGA** procedure displays the Windows standard font choice dialog box to allow the user to choose a font and character set. When called, any values in the parameters set the default font values presented to the user in the font choice dialog. They also receive the user's choice when the user presses the Ok button on the dialog. FONTDIALOGA returns zero (0) if the user pressed the Cancel button, or one (1) if the user pressed the Ok button.

If you don't need a specific character set then you can use the FONTDIALOG procedure.

**Return Data Type:**    BOOL

**Example:**

```
Typeface    STRING(31) !Use CLASTRING in Clarion#
FontSize    SREAL
FontColor   SIGNED
FontStyle   SIGNED
CharSet     SIGNED
Added       SIGNED

CODE
OPEN(MDICHild1)                                !open the window
IF FONTDIALOGA('Choose Display Font',Typeface,FontSize,FontColor,FontStyle,CharSet,0)
    SETFONT(0,Typeface,FontSize,FontColor,FontStyle,CharSet) !Set window font
ELSE
    SETFONT(0,'Arial',12)                          !Set default font
END
ACCEPT
    !Window handling code
END
```

**See Also:**

FONT(set default font)  
Font Support Quick Summary

## FORMAT (return formatted numbers into a picture)

**FORMAT**(*value*,*picture*)

---

**FORMAT** Returns a formatted numeric string.

*value* A numeric expression for the *value* to be formatted.

*picture* A picture token or the label of a STRING variable or expression containing a picture token.

The **FORMAT** procedure returns a numeric string formatted according to the *picture* parameter.

**Return Data Type:** STRING

**Example:**

**!Format the Social Security number:**

```
Rpt:SocSecNbr = FORMAT(Emp:SSN,@P###-##-####P)
```

**!Change phone format from dashes to parenthesis:**

```
Phone = FORMAT(DEFORMAT(Phone,@P###-###-####P),@P(###)###-####P)
```

**!Format a date as a string:**

```
DateString = FORMAT(DateLong,@D1)
```

**See Also:**

DEFORMAT

Picture Tokens

## FORWARDKEY (pass keystrokes to control)



**FORWARDKEY**(*targetcontrol*)

---

**FORWARDKEY** Passes a keystroke to another control.

*targetcontrol*      A field number or field equate label for the control to receive the passed keystroke.

**FORWARDKEY** passes a keystroke to another control. This imitates the action of the keystroke as if the target control was the control in focus when the keystroke occurred.

**Example:**

```
FORWARDKEY(?LIST)      !pass the keystroke to the list box
```

## FREE (delete all entries)

**FREE**(*queue* )

---

**FREE**                Deletes all entries from a QUEUE.

*queue*                The label of a QUEUE structure, or the label of a passed QUEUE parameter.

**FREE** deletes all entries from a QUEUE and de-allocates the memory they occupied. It also de-allocates the memory used by the QUEUE's "overhead." **FREE** does not clear the QUEUE's data buffer.

If the QUEUE contains any reference variables or fields with the ANY data type, you must first **CLEAR** each QUEUE entry before **FREE**ing the QUEUE. This will avoid memory leaks by freeing up the memory used by the ANY variables before the **FREE** statement removes the pointer to the allocated memory.

### Errors Posted:

08   Insufficient Memory

### Example:

```
FREE(Location)        !Free the location queue
FREE(NameQue)        !Free the name queue
```

### See Also:

ANY

CLEAR

## FREESTATE (free resources)

**FREESTATE**(*file*, *savedstate*)

---

**FREESTATE** Releases all resources allocated by GETSTATE

*file* The label of a FILE declaration.

*savedstate* A LONG numeric variable which represents the value returned by the GETSTATE procedure.

FREESTATE releases all resources allocated by GETSTATE.

**Example:**

```
MyFunction PROCEDURE (FILE MyFile)
```

```
CurState LONG
```

```
CODE
```

```
! File will be in the same state on exit of this procedure as it was on entry
CurState = GETSTATE(MyFile)      !save current state of file
SET(MyFile)                       !ready to access file
NEXT(MyFile)                      !read a record
CLEAR(MyFile)                    !clear record buffer
RESTORESTATE(MyFile, CurState)    !restore file to initial state
FREESTATE(MyFile, CurState)       !release resources
```

**See Also:**

GETSTATE

RESTORESTATE

## GET (read a record or entry)

```
| file , key|  
GET( | file , filepointer [, length ]| )  
      | key , keypointer|  
      | queue , pointer|  
      | queue , [+]key,...,-key|  
      | queue , name|  
      | queue , function|
```

---

<b>GET</b>	Retrieves a specific record from a FILE or entry from a QUEUE.
<i>file</i>	The label of a FILE declaration.
<i>key</i>	The label of a KEY or INDEX declaration.
<i>filepointer</i>	A numeric constant, variable, or expression for the value returned by the POINTER( <i>file</i> ) procedure.
<i>length</i>	An integer constant, variable, or expression which contains the number of bytes to read from the <i>file</i> . The <i>length</i> must be greater than zero and not greater than the RECORD length. If omitted or out of range, <i>length</i> defaults to the length of the RECORD structure.
<i>keypointer</i>	A numeric constant, variable, or expression for the value returned by the POINTER( <i>key</i> ) procedure.
<i>queue</i>	The label of a QUEUE structure.
<i>pointer</i>	A numeric constant, variable, or numeric expression. The <i>pointer</i> must be in the range from 1 to the number of entries in the memory queue.
<b>+ -</b>	The leading plus or minus sign specifies the <i>key</i> is sorted in ascending or descending sequence.
<i>key</i>	The label of a field declared within the QUEUE structure. If the QUEUE has a PRE attribute, the <i>key</i> must include the prefix.



<i>name</i>	A string constant, variable, or expression containing the NAME attribute of QUEUE fields, separated by commas, and optional leading + or - signs for each attribute. This parameter is case sensitive.
<i>function</i>	The label of the function containing two parameters of a *GROUP or named GROUP passed by address, and having a SIGNED return value. Both parameters must use the same parameter type, and cannot be omitted. The RAW, C and PASCAL attributes are not permitted in the prototype declaration. See Additional Queue Considerations.

The **GET** statement locates a specific record in a FILE or specific entry in a QUEUE and retrieves it.

### FILE Usage

---

The GET statement locates a specific record in the data file and reads it into the RECORD structure data buffer. Direct access to the record is achieved by relative record position within the file, or by matching key values. If the GET is unsuccessful, the previous content of the RECORD buffer is not affected.

GET( <i>file</i> , <i>key</i> )	Gets the first record from the file (as listed in the <i>key</i> ) which contains values matching the values in the component fields of the <i>key</i> .
GET( <i>file</i> , <i>filepointer</i> [, <i>length</i> ])	Gets a record from the file based on the <i>filepointer</i> relative position within the <i>file</i> . If <i>filepointer</i> is zero, the current record pointer is cleared and no record is retrieved.
GET( <i>key</i> , <i>keypointer</i> )	Gets a record from the file based on the <i>keypointer</i> relative position within the <i>key</i> .

The values for *filepointer* and *keypointer* are file driver dependent. They could be: record number; relative byte position within the file; or, some other kind of "seek position" within the file. If the *filepointer* or *keypointer* value is out of range, or there are no matching *key* values in the data file, the "Record Not Found" error is posted.

The DUPLICATE procedure assumes that the contents of the RECORD structure data buffer are duplicated at the current record pointer location. Therefore, when using DUPLICATE prior to ADDing a record, the record pointer should be cleared with: GET(*file*,0).

### QUEUE Usage

---

GET reads an entry into the QUEUE structure data buffer for processing. If GET does not find a match, the "Entry Not Found" error is posted.

GET( <i>queue</i> , <i>pointer</i> )	Retrieves the entry at the relative entry position specified by the <i>pointer</i> value in the order the QUEUE entries were added, or last SORTed. If <i>pointer</i> is zero, the value returned by the POINTER procedure is set to zero.
--------------------------------------	--

GET( <i>queue</i> , <i>key</i> )	Searches for the first QUEUE entry that matches the value in the <i>key</i> field(s). Multiple <i>key</i> parameters may be used (up to 16), separated by commas. If the QUEUE has not been SORTed on the field(s) used as the <i>key</i> parameter(s), the <i>key</i> indicates an "alternate sort order" which is then cached (making a subsequent SORT on those same fields very efficient).
GET( <i>queue</i> , <i>name</i> )	Searches for a QUEUE entry that matches the value in the <i>name</i> field(s). The <i>name</i> string must contain the NAME attributes of the fields, separated by commas, with optional leading plus or minus signs to indicate ascending or descending sequence. If the QUEUE has not been SORTed on the <i>named</i> field(s), the <i>name</i> indicates an "alternate sort order" which is then cached (making a subsequent SORT on those same fields very efficient).
GET( <i>queue</i> , <i>function</i> )	GET by FUNCTION will read from a positional value returned by the function. See Additional Queue Considerations.

**Errors Posted:**

08	Insufficient Memory
30	Entry Not Found
35	Record Not Found
36	File Not Open
43	Record Is Already Held
75	Invalid Field Type Descriptor

**Example:**

```

NameQue  QUEUE,PRE (Que)
Name      STRING(20),NAME('FirstField')
Zip       DECIMAL(5,0),NAME('SecondField')
END

Customer  FILE,DRIVER('Clarion'),PRE (Cus)
NameKey   KEY (Cus:Name),OPT
NbrKey    KEY (Cus:Number),OPT
Rec       RECORD
Name      STRING(20)
Number    SHORT
END
END

CODE
DO BuildQue                                !Call routine to build the queue
GET (NameQue,1)                            !Get the first entry
IF ERRORCODE() THEN STOP(ERROR()) END

Que:Name = 'Jones'                         !Initialize key field
GET (NameQue,Que:Name)                    !Get the matching record

IF ERRORCODE()
  STOP(ERROR())
END

Que:Name = Fil:Name                        !Initialize to value in Fil:Name
GET (NameQue,Que:Name)                    !Get the matching record
IF ERRORCODE() THEN STOP(ERROR()) END

Que:Name = 'Smith'                        !Initialize the key fields
Que:Zip = 12345
GET (NameQue,'FirstField,SecondField')    !Get the matching record
IF ERRORCODE() THEN STOP(ERROR()) END

LOOP X# = 1 TO RECORDS (NameQue)
  GET (NameQue,X#)                        !Loop through every entry in the QUEUE
  IF ERRORCODE() THEN STOP(ERROR()) END
  !Process the entry
END

Cus:Name = 'Clarion'                      !Initialize key field
GET (Customer,Cus:NameKey)                !get record with matching value
IF ERRORCODE() THEN STOP(ERROR()) END

GET (Customer,3)                          !Get 3rd rec in physical file order
IF ERRORCODE() THEN STOP(ERROR()) END

GET (Cus:NameKey,3)                       !Get 3rd rec in keyed order
IF ERRORCODE() THEN STOP(ERROR()) END

```

**See Also:** SORT, PUT. POINTER(queue). POINTER. DUPLICATE, HOLD, WATCH

## GETFONT (get font information)



**GETFONT**( *control* [, *typeface* ] [, *size* ] [, *color* ] [, *style* ] [, *charset*])

---

**GETFONT** Gets display font information.

<i>control</i>	A field number or field equate label for the control from which to get the information. If <i>control</i> is zero (0), it specifies the WINDOW.
<i>typeface</i>	A string variable to receive the name of the font.
<i>size</i>	An integer variable to receive the size (in points) of the font.
<i>color</i>	A LONG integer variable to receive the red, green, and blue values for the color of the font in the low-order three bytes. If the value is negative, the <i>color</i> represents a system color.
<i>style</i>	An integer variable to receive the strike weight and style of the font.
<i>charset</i>	A LONG integer variable to receive the character set value.

**GETFONT** gets the display font information for the *control*. If the *control* parameter is zero (0), GETFONT gets the default display font for the window.

**Example:**

```
TypeFace  STRING(31)
Size      BYTE
Color     LONG
Style     LONG
CharSet   LONG

CODE
OPEN(Screen)
GETFONT(0,TypeFace,Size,Color,Style,CharSet)    !Get font info for the window
```

**See Also:**

SETFONT , FONTDIALOG, FONTDIALOGA , FONT(set default font)

## GETGROUP (return reference to GROUP)

**GETGROUP**( *group*, *number* [,*dimension*] )

**GETGROUP** Returns a reference to a specified *group* structure.

*group* The label of a GROUP or QUEUE declaration.

*number* An integer expression specifying the ordinal position of a GROUP or QUEUE in the specified *group*.

*dimension* An optional dimension element number, if applicable.

The **GETGROUP** statement returns a GROUP reference to the *number* specified field from a target *group* structure. If the *number* specified field is a dimensioned field, then **GETGROUP** returns a reference to the *dimension* element of the *number* field. **GETGROUP** returns a NULL reference if the *number* specified is not a GROUP. **GETGROUP** will also return NULL if the number specified is a dimensioned group and no dimension is specified. This function can be used to access a field that is part of a dimensioned GROUP.

**Return Data Type:** STRING

### Example:

```
MyGroup  GROUP
SubGroup GROUP,DIM(3)
number   LONG,DIM(5)
        END
        END

gr &GROUP
lr ANY

CODE
  gr &= GETGROUP(MyGroup, 1, 2)
  lr &= WHAT(gr, 1, 4)
  !lr now references MyGroup.SubGroup[2].number[4]
```

### See Also:

HOWMANY

ISGROUP

WHAT

WHERE

WHO

## GETINI (return INI file entry)

**GETINI**( *section* ,*entry* [,*default*] [,*file*] )

---

**GETINI** Returns the value for an INI file entry.

*section* A string constant or variable containing the name of the portion of the INI file which contains the *entry*.

*entry* A string constant or variable containing the name of the specific setting for which to return the value.

*default* A string constant or variable containing the default value to return if the *entry* does not exist (up to 1023 characters). If omitted and the entry does not exist, GETINI returns an empty string.

*file* A string constant or variable containing the name of the INI file to search. A file name without a full path (e.g. 'Autolog.ini') looks for the file in the Windows directory. To look for the file in the current directory enter a dot path (e.g. '.\Autolog.ini'). If the *file* does not exist, GETINI returns an empty string. If omitted, GETINI searches the WIN.INI file.

The **GETINI** procedure returns the value of an *entry* in a Windows-standard INI file (maximum file size is 64K). A Windows-standard INI file is an ASCII text file with the following format:

```
[some section name]
entry=value
next entry=another value
```

For example, WIN.INI contains entries such as:

```
[intl]
sLanguage=enu
sCountry=United States
iCountry=1
```

The GETINI procedure searches the specified *file* for the *entry* within the *section* you specify. It returns everything on the *entry*'s line of text that appears to the right of the equal sign (=).

**Return Data Type:** STRING

### Example:

```
Value STRING(30)
CODE
Value = GETINI('intl','sLanguage')    !Get the language entry
```

### See Also:

PUTINI

## GETNULLS(get the NULL state of a table)



**GETNULLS**(*table*)

**GETNULLS** Gets the NULL state of a table.

*table* The label of a FILE.

The **GETNULLS** procedure returns a string containing the NULL state of the table. The size of the return string is file driver dependent. For the AS400 Accelerator, MSSQL Accelerator, ODBC Accelerator, Oracle Accelerator, Scalable/Pervasive Accelerator, and SQLAnywhere Accelerator the size of the return string is 4 times the number of columns in the table. This function is valid on all SQL tables.

**Return Data Type:** STRING

### Example:

```
StorageString STRING(255)
Rec           STRING(2048)
```

### CODE

```
StorageString = GETNULLS(table)  !Get NULL state of table
Rec = table.record               !Save record buffer
! Do Table Processing
table.record = Rec               !Restore record buffer
SETNULLS(table, StorageString)  !Set NULL state of table columns
```

### Errors Posted:

80 Function Not Supported

### See Also:

NULL

SETNULL

SETNULLS

SETNONULL

## GETPOSITION (get control or window position)



```
GETPOSITION([ control ][, x ][, y ][, width ][, height ] )  
           | window |
```

---

**GETPOSITION** Gets the position and size of an APPLICATION, WINDOW, REPORT or control.

<i>control</i>	A field number or field equate label for the control from which to get the information. If <i>control</i> is zero (0), it specifies the window.
<i>window</i>	The label of an APPLICATION, WINDOW, or REPORT structure, or a reference to any of those structures.
<i>x</i>	An integer variable to receive the horizontal position of the top left corner.
<i>y</i>	An integer variable to receive the vertical position of the top left corner.
<i>width</i>	An integer variable to receive the width.
<i>height</i>	An integer variable to receive the height.

**GETPOSITION** gets the position and size of an APPLICATION, WINDOW, REPORT, or control. The *window* parameter is used to get the position and/or dimensions of a window that currently is not on top or has focus. The position and size values are dependent upon the presence or absence of the SCROLL attribute on the *control*. If SCROLL is present, the values are relative to the virtual window. If SCROLL is not present, the values are relative to the top left corner of the currently visible portion of the window. This means the values returned always match those specified in the AT attribute or most recent SETPOSITION.

The values in the *x*, *y*, *width*, and *height* parameters are measured in dialog units. Dialog units are defined as one-quarter the average character width by one-eighth the average character height. The size of a dialog unit is dependent upon the size of the default font for the window. This measurement is based on the font specified in the FONT attribute of the window, or the system default font specified by Windows.



**Example:**

```
Screen WINDOW,PRE(Scr)
    ENTRY(@N3),USE(Ctl:Code)
    ENTRY(@S30),USE(Ctl:Name)
    BUTTON('OK'),USE(?OkButton),KEY(EnterKey)
    BUTTON('Cancel'),USE(?CanxButton),KEY(EscKey)
END

X      SHORT
Y      SHORT
Width  SHORT
Height SHORT
CODE
OPEN(Screen)
GETPOSITION(?Ctl:Code,X,Y,Width,Height)
```

**See Also:**

SETPOSITION

PROP:Pixels

## GETREG(get Windows registry entry)

**GETREG**(*root*, *keyname* [, *valuename*] [, *\*? valuetype*] ),STRING

---

**GETREG** Gets the value of a specific key and/or value from the system registry.

*Root* A LONG integer, variable or expression that contains the root section of the registry from which to obtain the value. Valid values for this are defined in equates.clw and are as follows:

**REG\_CLASSES\_ROOT**

**REG\_CURRENT\_USER**

**REG\_LOCAL\_MACHINE**

**REG\_USERS**

**REG\_PERFORMANCE\_DATA**

**REG\_CURRENT\_CONFIG**

**REG\_DYN\_DATA**

*keyname* A STRING constant, variable or expression that contains the key name of the key whose value is to be queried. This may contain a path separated by backslash '\ ' characters.

*valuename* A STRING constant, variable or expression that contains the name of the value to be queried, if omitted, the value associated directly with the key is returned.

*valuetype* An optional integer variable that receives the type of value. It can be used for correct interpreting of the returned *valuename*.

Supported types are:

**REG\_NONE** - value is ignored

**REG\_SZ** - value is a string

**REG\_EXPAND\_SZ** - value is a string that can contain unexpanded environment variables

**REG\_MULTI\_SZ** - value is a string that consists of substrings separated with '<0>' characters; last substring is terminated with two consecutive '<0>' characters. NOTE: this value result can not be assigned to a CSTRING

**REG\_DWORD** - value is a 32 bit number

**REG\_DWORD\_LITTLE\_ENDIAN** - value is a 32 bit number

**REG\_DWORD\_BIG\_ENDIAN** - value is a 32 bit number

**REG\_QWORD** - value is a 64 bit number

**REG\_QWORD\_LITTLE\_ENDIAN** - value is a 64 bit number

**REG\_BINARY** - value string is a binary data of any form

The REG\_\* constants are declared in EQUATES.CLW

The **GETREG** function returns the value of named entry in the system registry as a Clarion string. If the requested entry does not exist, an empty string is returned.

### Vista and Clarion Built-in Registry Functions

On Vista, a (non-elevated) app can READ the registry key HKLM (local machine) with no problems, but as far as writing to the Registry it needs to use HKCU (current user).

If you code sign your executable and run with elevated privileges then you can write to HKLM

**Return Data Type:**   STRING

#### Example:

```
PROGRAM

MAP
END

INCLUDE('EQUATES')
CurrentPath CSTRING(100)
ColorScheme CSTRING(100)

CODE
  CurrentPath =|
    GETREG(REG_LOCAL_MACHINE,'SOFTWARE\SoftVelocity\Clarion7','root')
    !Returns root directory of Clarion 7 install

  ColorScheme =|
    GETREG(REG_CURRENT_USER,'Control Panel\Current','Color Schemes')
    !get the current user's color scheme
```

#### See Also:

PUTREG, DELETEREG

## GETSTATE (return current state of data file)

**GETSTATE**(*file* [ ,*saveblob* ])

---

**GETSTATE** Identifies a file's current state including the record buffer, file pointer, file sequencing order, and the error state of the system.

*file* The label of a FILE declaration.

*saveblob* An integer constant or variable containing either zero (0) or one (1). If one, the state of the BLOB is also returned. If omitted or zero (0) the BLOB state is not returned.

**GETSTATE** returns the current state of the data file. This includes the record buffer, MEMOs, BLOBs, file pointer, file sequencing order, and the current error state of the system. Use **GETSTATE** to store the file's state so it can be restored using **RESTORESTATE**. This set of functions, (including **FREESTATE**), allow for easy interruption and resumption of sequential file processes.

**GETSTATE** can now save the state of BLOBs if the second parameter is set to TRUE. It defaults to not saving BLOBs.

**Return Data Type:** LONG

### Example:

```
MyFunction PROCEDURE(FILE MyFile)
```

```
CurState LONG
```

```
CODE
```

```
!File will be in the same state on exit of this procedure as it was on entry
```

```
CurState = GETSTATE(MyFile,1)      !save current state of file and BLOB
SET(MyFile)                        !ready to access file
NEXT(MyFile)                       !read a record
CLEAR(MyFile)                     !clear record buffer
RESTORESTATE(MyFile, CurState)     !restore file to initial state
FREESTATE(MyFile, CurState)        !release resources
```

### See Also:

FREESTATE

RESTORESTATE

## HALT (exit program)

**HALT**([*errorlevel*] [,*message*])

**HALT** Immediately terminates the program.

*errorlevel* A positive integer constant or variable which is the exit code to pass to DOS, setting the DOS ERRORLEVEL. If omitted, the default is zero.

*message* A string constant or variable which is typed on the screen after program termination.

The **HALT** statement immediately returns to the operating system, setting the *errorlevel* and optionally displaying a *message* after the program terminates. All standard runtime library procedures for application closedown are performed (all open windows and files are closed and flushed and all allocated memory is returned to the operating system) without executing any further Clarion code in the application.

**HALT** should not be used in multi-DLL applications, and should only be used as a debugging technique.

### Example:

```

PasswordProc PROCEDURE
Password  STRING(10)
Window WINDOW,CENTER
    ENTRY(@s10),AT(5,5),USE(PASSWORD),HIDE
    END
CODE
OPEN(Window)
ACCEPT
CASE ACCEPTED()
OF ?Password)
    IF Password <> 'Pay$MeMoRe'
        HALT(0,'Incorrect Password entered.')
    END
END
END
END

```

### See Also:

STOP

## HELP (help window access)

**HELP**(*[helpfile]* [,*window-id*])

---

<b>HELP</b>	Opens a help file and activates a help window.
<i>helpfile</i>	A string constant or the label of a STRING variable that has the DOS directory file specification for the help file. If the file specification does not contain a complete path and filename, the help file is assumed to be in the current directory. If the file extension is omitted, ".HLP" is assumed. If the <i>helpfile</i> parameter is omitted, a comma is required to hold its position.
<i>window-id</i>	A string constant or the label of a STRING variable that contains the key used to access the help system. This may be either a help keyword or a "context string."

The **HELP** statement opens a designated *helpfile*, and activates the window named by the *window-id*. While an ASK or ACCEPT is controlling program execution, the active help window is displayed when the operator presses F1 (the "Help" key).

If the *window-id* parameter is omitted, the *helpfile* is nominated but not opened. If the *helpfile* parameter is omitted, the current help file is opened, and the window identified by *window-id* is activated. If both parameters are omitted, the current *helpfile* is opened at the current topic.

The *window-ID* may contain a Help keyword. This is a keyword that is displayed in the Help Search dialog. When the user presses F1, if only one topic in the help file specifies this keyword, the help file is opened at that topic; if more than one topic specifies the keyword, the search dialog is opened for the user.

A "context string" is identified by a leading tilde (~) in the *window-ID*, followed by a unique identifier associated with exactly one help topic. If the tilde is missing, the *window-ID* is assumed to be a help keyword. When the user presses F1, the help file is opened at the specific topic associated with that "context string."

Newly started threads inherit the help file settings from the previous thread that started it.

### Example:

```
HELP('C:\HLPDIR\LEDGER.HLP')  !Open the gen ledger help file
HELP(, '~CustUpd')            !Activate customer update help window
HELP                          !Display the help window
```

### See Also:

ASK

ACCEPT

HLP

## HIDE (blank a control)



**HIDE**( [ *first control* ] [, *last control* ] )

**HIDE** Hides window controls.

*first control* Field number or field equate label of a control, or the first control in a range of controls. If omitted, defaults to zero (0).

*last control* Field number or field equate label of the last control in a range of controls.

The **HIDE** statement hides a control, or range of controls, on an APPLICATION or WINDOW structure. When hidden, the control does not appear on screen.

### Example:

```
Screen WINDOW,PRE(Scr)
    ENTRY(@N3),USE(Ctl:Code)
    ENTRY(@S30),USE(Ctl:Name)
    BUTTON('OK'),USE(?OkButton),KEY(EnterKey)
    BUTTON('Cancel'),USE(?CanxButton),KEY(EscKey)
END

CODE
OPEN(Screen)
HIDE(?Ctl:Code)           !Hide a control
HIDE(?Ctl:Code,?Ctl:Name) !Hide range of controls
HIDE(2)                   !Hide the second control
```

### See Also:

UNHIDE

ENABLE

DISABLE

## HOLD (exclusive record access)

**HOLD**( *entity* [,*seconds*])

---

**HOLD**                Arms record locking.

*entity*                The label of a FILE opened for shared access or a VIEW whose component files are opened for shared access.

*seconds*              A numeric constant or variable which specifies the maximum wait time in seconds.

The **HOLD** statement arms record locking for a following GET, REGET, NEXT, or PREVIOUS statement in a multi-user environment. The GET, REGET, NEXT, or PREVIOUS flags the record as "held" when it successfully gets the record. Generally, this excludes other users from writing to, but not reading, the record. The specific action HOLD takes is file driver dependent. When the *entity* parameter is the label of a VIEW structure, HOLD operates on the primary file in the VIEW, only.

HOLD( *entity* )                      Arms HOLD so that the following GET, REGET, NEXT, or PREVIOUS attempts to hold the record until it is successful. If it is held by another workstation, GET, REGET, NEXT, or PREVIOUS will wait until the other workstation releases it.

HOLD(*entity* , *seconds* )            Arms HOLD for the following GET, REGET, NEXT, or PREVIOUS to post the "Record Is Already Held" error after unsuccessfully trying to hold the record for *seconds*.

A user may only HOLD one record at a time. If a second record is to be accessed in the same file, the previously held record must be released (see RELEASE).

A common problem to avoid is "deadly embrace." This occurs when two workstations attempt to hold the same set of records in two different orders and both are using the HOLD(*entity*) form of HOLD. One workstation has already held a record that the other is trying to HOLD, and vice versa. You can avoid this problem by using the HOLD(*entity*,*seconds*) form of HOLD, and trapping for the "Record Is Already Held" error after the GET, REGET, NEXT, or PREVIOUS statement.



**Example:**

```

ViewOrder  VIEW(Customer)  !Declare VIEW structure
            PROJECT (Cus:AcctNumber,Cus:Name)
            JOIN (Hea:AcctKey,Cus:AcctNumber)      !Join Header file
            PROJECT (Hea:OrderNumber)
            JOIN (Dtl:OrderKey,Hea:OrderNumber)    !Join Detail file
            PROJECT (Det:Item,Det:Quantity)
            JOIN (Pro:ItemKey,Dtl:Item)            !Join Product file
            PROJECT (Pro:Description,Pro:Price)
            END
            END
            END
            END
CODE
OPEN (Customer,22h)
OPEN (Header,22h)
OPEN (Detail,22h)
OPEN (Product,22h)
SET (Cus:AcctKey)
OPEN (ViewOrder)
  LOOP                      !Process records Loop
  LOOP                      !Loop to avoid "deadly embrace"
    HOLD (ViewOrder,1)      !Arm Hold on view, primary record only,try for 1 second
    NEXT (ViewOrder)        !Get and hold the record
    IF ERRORCODE() = 43 !If someone else has it
      CYCLE                  ! try again
    ELSE
      BREAK                  !Break if not held
    END
  END
  IF ERRORCODE() THEN BREAK END !Check for end of file
  !Process the records
  RELEASE (ViewOrder)       !release Primary held record
END
CLOSE (ViewOrder)

```

**See Also:**

RELEASE

NEXT

PREVIOUS

WATCH

GET

REGET

## HOWMANY (return dimensions)

**HOWMANY**( *label* ,*element*)

---

**HOWMANY** Returns the number of dimensions for a designated element.

*label* The label of a GROUP, QUEUE or RECORD.

*element* A LONG constant or variable that identifies the ordinal position of the target element to examine.

**HOWMANY** returns the number of dimensions the n'th field of a GROUP, QUEUE or RECORD. A multi-dimensioned field has its dimensions flattened.

**HOWMANY** will return zero (0) if you ask for the dimensions of a field within a dimensioned GROUP. To access the number of dimensions of such a field, you must first use GETGROUP to get one element of the dimensioned group.

**Return Data Type:** LONG

**Example:**

```
NestGroup  GROUP
subGroup   GROUP,DIM(2,2)
var1       LONG,DIM(3,3)
           END
           END
gr &GROUP
```

```
MyGroup  GROUP
var1     LONG,DIM(3,3)
var2     LONG,DIM(100)
var3     LONG,DIM(2,3,4)
           END
```

```
CODE
HOWMANY(MyGroup, 1)    !Returns 9
HOWMANY(MyGroup, 2)    !Returns 100
HOWMANY(MyGroup, 3)    !Returns 24
HOWMANY(NestGroup, 1)  !Returns 4
HOWMANY(NestGroup, 2)  !Returns 0
IF ISGROUP(NestGroup, 1)
  gr &= GETGROUP(NestGroup, 1, 1)
  HOWMANY(gr, 1)       !Returns 9
END
```

**See Also:**

ISGROUP

GETGROUP

WHAT

WHERE

WHO

## IDLE (arm periodic procedure)

`IDLE([procedure] [,separation])`

---

<b>IDLE</b>	Arms a <i>procedure</i> that periodically executes.
<i>procedure</i>	The label of a PROCEDURE. The <i>procedure</i> may not take any parameters.
<i>separation</i>	An integer that specifies the minimum wait time (in seconds) between calls to the <i>procedure</i> . A <i>separation</i> of 0 specifies continuous calls. If <i>separation</i> is omitted, the default value is 1 second.

An **IDLE** procedure is active while ASK or ACCEPT are waiting for user input. Only one IDLE procedure may be active at a time. Naming a new IDLE *procedure* overrides the previous one. An IDLE statement with no parameters disarms the IDLE process.

The IDLE *procedure* executes on thread one (1)--the same thread as the APPLICATION frame in an MDI application. Therefore, any WINDOW structure in an IDLE *procedure* must not have the MDI attribute. Since opening a non-MDI window in the same thread as the APPLICATION frame creates an application modal window, it would be more usual for an IDLE *procedure* not to have a WINDOW structure at all.

An IDLE *procedure* is usually prototyped in the PROGRAM's MAP. If prototyped in a MEMBER MAP, the IDLE statements which activate and de-activate it must be contained in a procedure within the same MEMBER module.

### Example:

```
IDLE (ShoTime,10)      !Call shotime every 10 seconds
IDLE (CheckNet)        !Check network activity every 1 second
IDLE                   !Disarm idle procedure
```

### See Also:

ASK

ACCEPT

PROCEDURE

MAP

MDI

## IMAGE (draw a graphic image)

**IMAGE**( *x* , *y* , [ *width* ] , [ *height* ] , *filename* [,*attributelist*])

---

<b>IMAGE</b>	Places a graphic image on the current window or report.
<i>X</i>	An integer expression that specifies the horizontal position of the starting point.
<i>Y</i>	An integer expression that specifies the vertical position of the starting point.
<i>Width</i>	An integer expression that specifies the width. This may be a negative number. If omitted, defaults to the width of the graphic as it is stored.
<i>Height</i>	An integer expression that specifies the height. This may be a negative number. If omitted, defaults to the height of the graphic as it is stored.
<i>filename</i>	A string constant or variable containing the name of the file to display.
<i>attributelist</i>	A string constant, variable, or EQUATE containing an optional type of output document and its associated attributes. Only valid when the target is a REPORT. See EXTEND

The **IMAGE** procedure places a graphic image on the current window or report at the position and size specified by its *x*, *y*, *width*, and *height* parameters. This may be a bitmap (.BMP), icon (.ICO), PaintBrush (.PCX), Graphic Interchange Format (.GIF), JPEG (.JPG), or Windows metafile (.WMF). This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !window controls
END

CODE
OPEN(MDIChild)
IMAGE(100,50,100,50,'LOGO.BMP')    !Draw graphic image
```

### See Also:

Current Target  
SETPENCOLOR  
SETPENWIDTH  
SETPENSTYLE

## INLIST (return entry in list)

**INLIST**(*searchstring*,*liststring*,*liststring* [,*liststring*...])

**INLIST** Returns item in a list.

*searchstring* A constant, variable, or expression that contains the value for which to search. If the value is numeric, it is converted to a string before comparisons are made.

*liststring* The label of a variable or constant value to compare against the *searchstring*. If the value is numeric, it is converted to a string before comparisons are made. There may be up to 25 *liststring* parameters, and there must be at least two.

The **INLIST** procedure compares the contents of the *searchstring* against the values contained in each *liststring* parameter. If a matching value is found, the procedure returns the number of the first *liststring* parameter containing the matching value (relative to the first *liststring* parameter). If the *searchstring* is not found in any *liststring* parameter, **INLIST** returns zero.

**Return Data Type:** LONG

### Example:

```
INLIST('D','A','B','C','D','E') !returns 4
INLIST('B','A','B','C','D','E') !returns 2
```

```
EXECUTE INLIST(Emp:Status,'Fulltime','Parttime','Retired','Consultant')
  Scr:Message = 'All Benefits'           !Full timer
  Scr:Message = 'Holidays Only'         !Part timer
  Scr:Message = 'Medical/Dental Only'   !Retired
  Scr:Message = 'No Benefits'           !Consultant
END
```

### See Also:

CHOOSE

## INSTANCE (return variable's thread instance address)

**INSTANCE**(*variable*,*threadno*)

Returns an unsigned integer value that references the address of the variable instance.

---

<b>INSTANCE</b>	Returns the address of a variable or entity's thread instance.
<i>variable</i>	Label of a variable, field, FILE, KEY or QUEUE or reference variable.
<i>threadno</i>	A numeric constant, variable, or expression that can be evaluated as a SIGNED integer.

The **INSTANCE** procedure evaluates the condition of the *variable* parameter and its thread number referenced by the *threadno* parameter and returns the following results:

If the value of *threadno* is not zero(0), and the thread referenced by *threadno* is not started (or an instance of *variable* is not allocated for the thread referenced by *threadno*), **INSTANCE** returns zero(0). Otherwise, **INSTANCE** returns the address of the *variable* instance allocated for the active thread referenced by *threadno*.

The *variable* parameter must be either an instance of a threaded variable or entity allocated for the current thread, or a reference variable pointing to a memory location whose address has been obtained by the call to **INSTANCE**(*variable*, 0). Otherwise, the **INSTANCE** function returns an address of the passed variable.

If the *threadno* parameter is set to zero(0), **INSTANCE** returns the address of the *variable* that is assigned by the program loader. This is also known as the variables' *thread independent ID*.

**INSTANCE** can be used instead of the ADDRESS( ) statement when ADDRESS( ) is not valid or available (e.g. FILE and QUEUE structures). ADDRESS(QUEUE) is a legal call, but it returns the address of the queue's internal buffer. On the other hand, **INSTANCE**(QUEUE,THREAD()) returns the address of the queue's internal structure.

For example, given the following QUEUE declarations:

```
SomeQueue QUEUE
```

```
...
```

```
END
```

```
QueueRef &QUEUE
```

The following assignment is correct:

```
QueueRef &= INSTANCE (SomeQueue, Somethread)
```

while the assignment shown below is not correct:

```
QueueRef &= ADDRESS (SomeQueue)
```

and sets the QueueRef variable to the wrong value.

**INSTANCE** is also valuable when you need the thread independent ID of the variable.

**Return Data Type:** LONG

**Example:**

```
addressvar = INSTANCE(SalesFile,THREAD())
!return address of SalesFile entity on active thread

addressvar = INSTANCE(GLO:LoginID, 0)
!get the thread independent ID of a global threaded variable
```

**Expanded Example:**

```
PROGRAM

MAP
PROC1()
END

ThreadClass CLASS,TYPE
A STRING(10)
END

NoThreadClass CLASS,TYPE
TC &ThreadClass
Init PROCEDURE(ThreadClass TC)
GetA PROCEDURE(),STRING
SetA PROCEDURE(STRING A)
END

MyClass NoThreadClass
MyThreadClass ThreadClass,THREAD
!If MyThreadClass was not threaded, the value of "A" will be the same for each
!thread, and access to it should be synchronized

AppFrame APPLICATION('Application'),AT(,505,318),|
FONT('MS Sans Serif',8,,FONT:regular),|
CENTER,ICON('WAFRAME.ICO'),STATUS(-1,80,120,45),SYSTEM,MAX,RESIZE
END

CODE
MyClass.Init(MyThreadClass)
OPEN(AppFrame)
START(PROC1)
START(PROC1)
ACCEPT
END

PROC1 PROCEDURE()
LOC:SETVAL STRING(10)
LOC:GETVAL STRING(10)
Window WINDOW('Win'),AT(,119,100),|
FONT('MS Sans Serif',8,,FONT:regular),IMM,GRAY,AUTO,MDI
BUTTON('Set Value'),AT(5,6,41,14),USE(?SET)
ENTRY(@s10),AT(53,7,60,10),USE(LOC:SETVAL)
BUTTON('Get Value'),AT(5,25,41,14),USE(?GET)
ENTRY(@s10),AT(53,28,60,10),USE(LOC:GETVAL)
BUTTON('&Close'),AT(35,50,46,14),USE(?Close),LEFT,STD(STD:Close)
PROMPT('Each window is getting/setting the value of its own' &|
' instance of the ThreadClass'),AT(5,67,107,31),USE(?Description)
END
```

```
CODE
OPEN(Window)
0{PROP:TEXT}=0{PROP:TEXT}&'-'&THREAD()
LOC:SETVAL = THREAD()
MyClass.SETA(LOC:SETVAL)
ACCEPT
CASE EVENT()
OF EVENT:ACCEPTED
CASE ACCEPTED()
OF ?GET
LOC:GETVAL=MyClass.GETA()
DISPLAY()
OF ?SET
MyClass.SETA(LOC:SETVAL)
END
END
END

NoThreadClass.Init      PROCEDURE(ThreadClass TC)
CODE
!Storing the "Thread independent ID" for the class
SELF.TC &= INSTANCE(TC,0)

NoThreadClass.GetA      PROCEDURE()
LTC &ThreadClass
CODE
! SELF.TC contain the "Thread independent ID" for the threaded class
LTC &= INSTANCE(SELF.TC,THREAD())
! LTC is a reference to the instance for the current thread
RETURN LTC.A

NoThreadClass.SetA      PROCEDURE(STRING A)
LTC &ThreadClass
CODE
! SELF.TC contains the "Thread independent ID" for the threaded class
LTC &= INSTANCE(SELF.TC,THREAD())
! LTC is a reference to the instance for the current thread
LTC.A = A
```

See Also: THREAD



## INSTRING (return substring position)

**INSTRING**(*substring*,*string* [,*step*] [,*start*])

Returns an unsigned integer value from zero to the length of the search string.

<b>INSTRING</b>	Searches for a substring in a string.
<i>substring</i>	A string constant, variable, or expression that contains the string for which to search. You should CLIP a variable <i>substring</i> so INSTRING will not look for a match that contains the trailing spaces in the variable.
<i>string</i>	A string constant, or the label of the STRING, CSTRING, or PSTRING variable to be searched.
<i>step</i>	A numeric constant, variable, or expression which specifies the step length of the search. A <i>step</i> of 1 will search for the <i>substring</i> beginning at every character in the <i>string</i> , a <i>step</i> of 2 starts at every other character, and so on. A negative <i>step</i> value (-1) will search from right to left within the <i>string</i> . If <i>step</i> is omitted, the step length defaults to the length of the <i>substring</i> .
<i>start</i>	A numeric constant, variable, or expression which specifies where to begin the search of the <i>string</i> . If omitted, the search starts at the first character position.  <b>ClarionWin32</b> The first character position is one (1)  <b>Clarion#</b> The first character position is zero (0)

### Remarks:

The **INSTRING** procedure *steps* through a *string*, searching for the occurrence of a *substring*. If the *substring* is found, the procedure returns the *step* number on which the *substring* was found.

### ClarionWin32

If the *substring* is not found in the *string*, **INSTRING** returns zero.

### Clarion#

In Clarion# indexing starts with 0, so if the substring is not found then -1 is returned.

**INSTRING** starts to search for *substring* from the *start* position in the *string* and moves forward with *step* until the *substring* is found, or the unchecked tail of the *string* is less than length of the *substring*. In the latter case, **INSTRING** returns zero.

If the *substring* is found, the result is equal to the number of *steps* from the origin of the *string* to the found position. If the value of *step* is not equal to 1, the result is rounded up to the whole number of steps as follows:

$\text{INT} ((\text{found position} - 1) / \text{step}) + 1$

The only negative *step* value allowed is -1, and the *substring* must be 1 character long in this case. In other words, a negative *step* is not allowed with any *substring* greater than 1 character.

**Return Data Type:**        UNSIGNED

**Clarion Win32 Example:**

```
INSTRING('DEF', 'ABCDEFGHIJ', 1, 1) !returns 4
INSTRING('DEF', 'ABCDEFGHIJ', 1, 2) !returns 4
INSTRING('DEF', 'ABCDEFGHIJ', 1, 3) !returns 4
INSTRING('DEF', 'ABCDEFGHIJ', 1, 4) !returns 4
INSTRING('DEF', 'ABCDEFGHIJ', 1, 5) !returns 0

INSTRING('DEF', 'ABCDEFGHIJ', 2, 1) !returns 0
INSTRING('DEF', 'ABCDEFGHIJ', 2, 2) !returns 2
INSTRING('DEF', 'ABCDEFGHIJ', 3, 1) !returns 2

!Extract extension from file spec:
Extension = SUB(FileSpec, INSTRING('.', FileSpec) + 1, 3)

IF INSTRING(CLIP(Search), Cus:Notes, 1, 1) !If search variable found
  Scr:Message = 'Found' !display message
END
```

**Clarion# Example:**

```
ns     STRING

CODE

ns = 'abcdefghijklmnopqrstuvwxyz'

! but these functions return one (1) as the first "STEP"
INSTRING('a', ns, 1, 0)     ! we start search at 0 position and it returns STEP 1
INLIST('a', 'a', 'b', 'c') ! returns 1
```

**See Also:**

SUB

STRING

CSTRING

PSTRING

String Slicing

INLIST

## INT (truncate fraction)

`INT(expression)`

---

**INT**                Return integer.

*expression*        A numeric constant, variable, or expression.

The **INT** procedure returns the integer portion of a numeric expression. No rounding is performed, and the sign remains unchanged.

**Return Data Type:**    REAL or DECIMAL

**Example:**

```
!INT(8.5)        returns 8
!INT(-5.9)       returns -5
```

```
x = INT(y)        !Return integer portion of y variable contents
```

**See Also:**

BCD Operations and Procedures

ROUND

## ISALPHA (return alphabetic character)

ISALPHA( *string* )

---

**ISALPHA** Returns whether the *string* passed to it contains an alphabetic character.

*string* The label of the character string to test. If the *string* contains more than one character, only the first character is tested.

The ISALPHA procedure returns TRUE if the *string* passed to it is alphabetic (an upper or lower case letter) and false otherwise. This is independent of the language and collation sequence. This procedure requires that CLACASE has been set in the application's environment file or through the LOCALE statement.

**Return Data Type:** LONG

**Example:**

```
SomeString STRING(1)
CODE
SomeString = 'A'           !ISALPHA returns true
IF ISALPHA(SomeString)
  X# = MESSAGE('Alpha string')
END
SomeString = '1'           !ISALPHA returns false
IF ISALPHA(SomeString)
  X# = MESSAGE('Alpha string')
ELSE
  X# = MESSAGE('Not Alpha string')
END
```

**See Also:**

ISUPPER

ISLOWER

LOCALE

Environment Files

## ISGROUP (return GROUP type or not)

**ISGROUP**( *label*, *element* )

**ISGROUP** Returns true if the *element* is a GROUP data type.

*label* The label of a GROUP or QUEUE.

*element* An integer expression specifying the ordinal position of a field in the GROUP or QUEUE.

The **ISGROUP** statement returns true if the *element* of a GROUP or QUEUE is a GROUP data type.

**Return Data Type:** SIGNED

### Example:

```
MyGroup  GROUP
F1        LONG          !Field number 1
F2        SHORT         !Field number 2
F3        STRING(30)    !Field number 3
InGroup   GROUP         !Field number 4
F1        LONG          !Field number 5
F2        SHORT         !Field number 6
F3        STRING(30)    !Field number 7
          END
          END

Flag  LONG
CODE
Flag = ISGROUP(MyGroup,1) !returns FALSE

Flag = ISGROUP(MyGroup,4) !returns TRUE
```

### See Also:

HOWMANY  
GETGROUP  
WHAT  
WHERE  
WHO

## ISLOWER (return lower case character)

**ISLOWER**( *string* )

---

**ISLOWER** Returns whether the *string* passed to it contains a lower case alphabetic character.

*string* The label of the string to test. If the *string* contains more than one character, only the first character is tested.

The ISLOWER procedure returns TRUE if the *string* passed to it is a lower case letter and false otherwise. This is independent of the language and collation sequence. This procedure requires that CLACASE has been set in the application's environment file or through the LOCALE statement.

**Return Data Type:** LONG

**Example:**

```
SomeString STRING(1)
CODE
SomeString = 'a'           !ISLOWER returns true
IF ISLOWER(SomeString)
  X# = MESSAGE('Lower case string')
END
SomeString = 'A'           !ISLOWER returns false
IF ISLOWER(SomeString)
  X# = MESSAGE('Lower case string')
ELSE
  X# = MESSAGE('Not lower case string')
END
```

**See Also:**

ISUPPER

ISALPHA

LOCALE

Environment Files

## ISSTRING (return field string type or not)

**ISSTRING**( *field* )

**ISSTRING** Returns true if the *field* is a GROUP, STRING, CSTRING, or PSTRING data type.

*field* The label of a field.

The **ISSTRING** statement returns true if the *field* is a GROUP, STRING, CSTRING, or PSTRING data type.

**Return Data Type:** SIGNED

### Example:

```
MyGroup  GROUP
F1        LONG          !Field number 1
F2        SHORT         !Field number 2
F3        STRING(30)    !Field number 3
InGroup   GROUP         !Field number 3
F1        LONG          !Field number 4
F2        SHORT         !Field number 5
F3        STRING(30)    !Field number 6
          END
          END

Flag  LONG
CODE
Flag = ISSTRING(MyGroup.F1)  !returns FALSE

Flag = ISSTRING(MyGroup.F3)  !returns TRUE
```

### See Also:

WHAT

WHERE

## ISUPPER (return upper case character)

ISUPPER( *string* )

---

**ISUPPER** Returns whether the *string* passed to it contains an upper case alphabetic character.

*string* The label of the string to test. If the *string* contains more than one character, only the first character is tested.

The ISUPPER procedure returns TRUE if the *string* passed to it is an upper case letter and false otherwise. This is independent of the language and collation sequence. This procedure requires that CLACASE has been set in the application's environment file or through the LOCALE statement.

**Return Data Type:** LONG

### Example:

```
SomeString STRING(1)
CODE
SomeString = 'A'           !ISUPPER returns true
IF ISUPPER(SomeString)
  X#= MESSAGE('Upper case string')
END
SomeString = 'a'           !ISUPPER returns false
IF ISUPPER(SomeString)
  X#= MESSAGE('Upper case string')
ELSE
  X#= MESSAGE('Not upper case string')
END
```

### See Also:

ISLOWER

ISALPHA

LOCALE

Environment Files



## KEYBOARD (return keystroke waiting)

**KEYBOARD()**

---

The **KEYBOARD** procedure returns the keycode of the first keystroke in the keyboard buffer. It is used to determine if there are keystrokes waiting to be processed by an ASK or ACCEPT statement.

**Return Data Type:**    UNSIGNED

**Example:**

```
LOOP UNTIL KEYBOARD()           !Wait for any key
  ASK
  IF KEYCODE() = EscKey THEN BREAK END  !On esc key, break the loop
END
```

**See Also:**

ASK

ACCEPT

KEYCODE

Keycode Equate Labels

## KEYCHAR (return ASCII code)

**KEYCHAR()**

---

The **KEYCHAR** procedure returns the ASCII value of the last key pressed at the time the event occurred.

**Return Data Type:**    UNSIGNED

**Example:**

```
ACCEPT                                !Wait for an event
CASE KEYCHAR()                       !Process the last keystroke
OF VAL('A') TO VAL('Z') ! upper case?
  DO ProcessUpper
OF VAL('a') TO VAL('z') ! lower case?
  DO ProcessLower
END
END
```

**See Also:**

SETKEYCHAR

ASK

ACCEPT

SELECT

VAL

CHR

## KEYCODE (return last keycode)

**KEYCODE()**

---

The **KEYCODE** procedure returns the keycode of the last key pressed at the time the event occurred, or the last keycode value set by the SETKEYCODE procedure. The current list of key codes can be found in the KEYCODES.CLW source file.

**Return Data Type:**    UNSIGNED

**Example:**

```
ACCEPT                !Loop on the display
CASE KEYCODE()        !Process the keystroke
  OF UpKey             !up arrow
    DO GetRecordUp     !get a record
  OF DownKey           !down arrow
    DO GetRecordDn     !get a record
  END
END
```

**See Also:**

ASK

ACCEPT

KEYBOARD

SETKEYCODE

KEYSTATE

Keycode Equate Labels

Keycode Equates List

## KEYSTATE (return keyboard status)

### KEYSTATE()

The **KEYSTATE** procedure returns a bitmap containing the status of the SHIFT, CTRL, ALT, any extended key, CAPS LOCK, NUM LOCK, SCROLL LOCK, and INSERT keys for the last KEYCODE procedure return value. The bitmap is contained in the high-order byte of the returned SHORT.

x . . . . .	insert key	(8000h)
. x . . . . .	scroll lock	(4000h)
. . x . . . .	num lock	(2000h)
. . . x . . .	caps lock	(1000h)
. . . . x . .	extended	(0800h)
. . . . . x .	alt	(0400h)
. . . . . . x	ctrl	(0200h)
. . . . . . . x	shift	(0100h)

Return Data Type:   UNSIGNED

#### Example:

```
ACCEPT                                !Loop on the display
CASE KEYCODE ()                      !Process the keystroke
OF EnterKey                          !User pressed Enter
  IF BAND (KEYSTATE (), 0800h)      !Detect enter on numeric keypad
    PRESSKEY (TabKey)              !press tab for the user
  END
END
END
END
```

#### See Also:

KEYCODE

BAND

Keycode Equates List

## LASTFIELD (return last window control)



**LASTFIELD ( )**

---

The **LASTFIELD** procedure returns the highest field number in the currently active window (or REPORT) as specified by SETTARGET. This does not include any controls in a TOOLBAR or MENUBAR.

**Return Data Type:** SIGNED

**Example:**

```
DISABLE (FIRSTFIELD ( ) ,LASTFIELD ( ) )      !Dim all control fields
```

**See Also:**

FIRSTFIELD

## LEFT (return left justified string)

**LEFT**(*string* [,*length*])

---

**LEFT**            Left justifies a string.

*string*            A string constant, variable, or expression.

*length*            A numeric constant, variable, or expression for the length of the return string. If omitted, *length* defaults to the length of the *string*.

The **LEFT** procedure returns a left justified string. Leading spaces are removed from the *string*. Spaces are padded on the right to return a string of the "length" specified. To remove trailing spaces use CLIP(LEFT())

**Return Data Type:**    STRING

**Examples:**

```
LEFT(' ABC') returns 'ABC '
!*****
CompanyName = LEFT(CompanyName)    !Left justify the company name
!*****
IF FILEDIALOG('Pick file',FileName) THEN
    IF LEFT(FileName,2)='\\' THEN
        STOP('\\UNC paths are not supported!')
    ELSIF UPPER(LEFT(FileName,11))='C:\WINDOWS\' THEN
        STOP('Do not select Windows folder!')
    END
END
!*****
MESSAGE('Sub Total $' & CLIP(LEFT(FORMAT(Inv:PmtTotal,@n-15.2))) & ' plus...')
!*****
IF LEFT(CardNo,1) = '4' THEN
    CardType = 'VISA'
ELSIF LEFT(CardNo,2) >= '50' AND LEFT(CardNo,2) <= '55'
    CardType = 'MC'
ELSIF LEFT(CardNo,4) = '6011'
    CardType = 'DISC'
ELSIF LEFT(CardNo,2) = '34' OR LEFT(CardNo,2) = '37'
    CardType = 'AMEX'
ELSE
    Message('Unknown card type ' & LEFT(CardNo,4))
    RETURN
END
```

**See Also:** RIGHT, CENTER, CLIP, SUB

## LEN (return length of string)

**LEN**(*string*)

**LEN** Returns length of a string.

*string* A string constant, variable, or expression.

The **LEN** procedure returns the length of a *string*. If the *string* parameter is the label of a STRING variable, the procedure will return the declared length of the variable. If the *string* parameter is the label of a CSTRING or PSTRING variable, the procedure will return the length of the contents of the variable. Numeric variables are automatically converted to STRING intermediate values.

**Return Data Type:** UNSIGNED

### Example:

```
IF LEN(CLIP(Title) & ' ' & CLIP(First) & ' ' & CLIP>Last)) > 30 !If full name won't fit
  Rpt:Name = CLIP(Title) & ' ' & SUB(First,1,1) & '. ' & Last    !use first initial
ELSE
  Rpt:Name = CLIP(Title) & ' ' & CLIP(First) & ' ' & CLIP>Last)    !else use full name
END

Rpt:Title = CENTER(Cus:Name,LEN(Rpt:Title))                !Center the name in the title
```

## LINE (draw a straight line)

**LINE**( *x* , *y* , *width* , *height* [, *attributelist*])

---

<b>LINE</b>	Draws a straight line on the current window or report.
<b>X</b>	An integer expression specifying the horizontal position of the starting point.
<b>Y</b>	An integer expression specifying the vertical position of the starting point.
<b>Width</b>	An integer expression specifying the width. This may be a negative number.
<b>Height</b>	An integer expression specifying the height. This may be a negative number.
<b>attributelist</b>	A string constant, variable, or EQUATE containing an optional type of output document and its associated attributes. Only valid when the target is a REPORT. See EXTEND

The **LINE** procedure places a straight line on the current window or report. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

The starting position, slope, and length of the line are specified by *x*, *y*, *width*, and *height* parameters. The *x* and *y* parameters specify the starting point of the line. The *width* and *height* parameters specify the horizontal and vertical distance to the end point of the line. If these are both positive numbers, the line slopes to the right and down from its starting point. If the *width* parameter is negative, the line slopes left; if the *height* parameter is negative, the line slopes left. If either the *width* or *height* parameter is zero, the line is horizontal or vertical.

<u>Width</u>	<u>Height</u>	<u>Result</u>
positive	positive	right and down from start point
negative	positive	left and down from start point
positive	negative	right and up from start point
negative	negative	left and up from start point
zero	positive	vertical, down from start point
zero	negative	vertical, up from start point
positive	zero	horizontal, right from start point
negative	zero	horizontal, left from start point

The line color is the current pen color set by SETPENCOLOR; the default color is the Windows system color for window text. The width is the current width set by SETPENWIDTH; the default width is one pixel. The line's style is the current pen style set by SETPENSTYLE; the default style is a solid line.

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !window controls
END

CODE
OPEN(MDIChild)
LINE(100,50,100,50)    !Draw line
```

**See Also:** Current Target, SETPENCOLOR, SETPENWIDTH, SETPENSTYLE



## LOCALE (load environment file)

```
LOCALE(  | file | )

        | setting, value |
```

**LOCALE** Allows the user to load a specific environment file (.ENV) at run-time and also to set individual environment settings.

*file* A string constant or variable containing the name (including extension) of the environment file (.ENV) to load, or the keyword WINDOWS. This may be a fully-qualified DOS pathname.

*setting* A string constant or variable containing the name of the environment variable to set. Valid choices are listed under the *Environment Files* section.

*value* A string constant or variable containing the environment variable setting.

The **LOCALE** procedure allows the user to load a specific environment file (.ENV) at run-time and also to set individual environment settings. This allows an application to load another file to override the default *appname*.ENV file, or to specify individual environment file settings when no environment file exists.

The WINDOWS keyword as the *file* parameter specifies use of Windows' default values for CLACOLSEQ, CLACASE and CLAAMP. When specifying individual *settings*, the *value* parameter does not require double quotes around each individual item in the *value* string, unlike the syntax required in an .ENV file.

### Errors Posted:

02      File Not Found  
05      Access Denied

### Example:

```
LOCALE('MY.ENV')           !Load an environment file
LOCALE('WINDOWS')          !Set default CLACOLSEQ, CLACASE and CLAAMP
LOCALE('CLABUTTON', 'OK, &Si, &No, &Abortar, &Ignora, &Volveratratar, Cancelar, &Ayuda')
                           !Set CLABUTTON to Spanish
LOCALE('CLACOLSEQ', |
'AAAEaääääääBbCCcçDdEEëëëëëFfGgHhIiIiIiJjKkLlMmNnÑñOöoöoöPpQqRrSsTtUüüüüüVvWwXxYyZzÿ')
                           !Set the collating sequence
LOCALE('CLACASE', 'AAÆÇEÑÖÜ, ääæçéñöü') !Set upper/lower case pairs
LOCALE('CLAMSG2', 'No File Found')        !Set ERROR() message for ERRORCODE()=2
```

### See Also:

Environment Files  
OEM

## LOCK (exclusive file access)

**LOCK**(*file* [,*seconds*])

---

**LOCK**                Locks a data file.

*file*                 The label of a FILE opened for shared access.

*seconds*             A numeric constant or variable which specifies the maximum wait time in seconds.

The **LOCK** statement locks a *file* against access by other workstations in a multi-user environment. Generally, this excludes other users from writing to or reading from the *file*. The file driver may or may not treat separate execution threads within a single program as another workstation or not.

**LOCK**(*file*)                Attempts to lock the *file* until it is successful. If it is already locked by another workstation, **LOCK** will wait until the other workstation unlocks it.

**LOCK**(*file*,*seconds*)       Posts the "File Is Already Locked" error after unsuccessfully trying to lock the file for the specified number of *seconds*.

The most common problem to avoid when locking files is referred to as "deadly embrace." This condition occurs when two workstations attempt to lock the same set of files in two different orders and both are using the **LOCK**(*file*) form of **LOCK**. One workstation has already locked a file that the other is trying to **LOCK**, and vice versa. This problem may be avoided by using the **LOCK**(*file*,*seconds*) form of **LOCK**, and always locking files in the same order.

### Errors Posted:

32            File Is Already Locked

### Example:

```
LOOP                    !Loop to avoid "deadly embrace"
  LOCK(Master,1)        !Lock the master file, try 1 second
  IF ERRORCODE() = 32 !If someone else has it
    CYCLE                !try again
  END
  LOCK(Detail,1)        !Lock the detail file, try 1 second
  IF ERRORCODE() = 32 !If someone else has it
    UNLOCK(Master)       !unlock the locked file
    CYCLE                !try again
  END
  BREAK                 !Break loop when both files are locked
END
```

See Also: UNLOCK, HOLD, LOGOUT

## LOCKTHREAD (re-lock the current execution thread)

### LOCKTHREAD

---

The **LOCKTHREAD** statement re-locks the current execution thread that has been unlocked with the **UNLOCKTHREAD** statement.

The **THREADLOCKED()** procedure determines whether the thread has been unlocked or not.

#### Example:

```
UNLOCKTHREAD           !Unlock the thread
MyLibraryCodeWithMessageLoop  !Call the code that has its own message loop
LOCKTHREAD             !Re-lock the thread
```

#### See Also:

ACCEPT

UNLOCKTHREAD

THREADLOCKED

## LOG10 (return base 10 logarithm)

**LOG10**(*expression*)

---

**LOG10** Returns base 10 logarithm.

*expression* A numeric constant, variable, or expression. If the value of the *expression* is zero or less, the return value will be zero. The base 10 logarithm is undefined for values less than or equal to zero.

The **LOG10** (pronounced "log ten") procedure returns the base 10 logarithm of a numeric *expression*. The base 10 logarithm of a value is the power to which 10 must be raised to equal that value.

**Return Data Type:** REAL

**Example:**

```
!LOG10(10)    returns 1
!LOG10(1)     returns 0
```

```
LogStore = LOG10(Var)           !Store the log 10 of var
```

**See Also:**

LOGE

## LOG10 (return base 10 logarithm)

**LOG10**(*expression*)

---

**LOG10** Returns base 10 logarithm.

*expression* A numeric constant, variable, or expression. If the value of the *expression* is zero or less, the return value will be zero. The base 10 logarithm is undefined for values less than or equal to zero.

The **LOG10** (pronounced "log ten") procedure returns the base 10 logarithm of a numeric *expression*. The base 10 logarithm of a value is the power to which 10 must be raised to equal that value.

**Return Data Type:** REAL

**Example:**

```
!LOG10(10)    returns 1
!LOG10(1)     returns 0
```

```
LogStore = LOG10(Var)           !Store the log 10 of var
```

**See Also:**

LOGE

## LOGE (return natural logarithm)

**LOGE**(*expression*)

---

**LOGE** Returns the natural logarithm.

*expression* A numeric constant, variable, or expression. If the value of the *expression* is less than zero, the return value is zero. The natural logarithm is undefined for values less than zero.

The **LOGE** (pronounced "log-e") procedure returns the natural logarithm of a numeric *expression*. The natural logarithm of a value is the power to which **e** must be raised to equal that value. The value of **e** used internally by the Clarion library for these calculations is 2.71828182846.

**Return Data Type:** REAL

**Example:**

```
!LOGE(2.71828182846)  returns 1
!LOGE(1)              returns 0
```

```
LogVal = LOGE(Val)    !Get the natural log of Val
```

**See Also:**

LOG10

## LONGPATH (return long filename)

**LONGPATH**( [ *shortfilename* ] )

---

**LONGPATH** Returns the fully-qualified long filename for a given short filename.

*shortfilename* A string constant, variable, or expression that specifies the DOS standard filename to convert. This may include the complete path. If omitted, **LONGPATH** returns the current drive and directory in long name form.

The **LONGPATH** procedure returns the long filename for a given *short* filename. The file named in the *shortfilename* parameter must already exist on disk. **LONGPATH** can now be used in expressions evaluated by the **EVALUATE** statements in runtime applications and in the templates.

**Return Data Type:** STRING

**Example:**

```
MyLongFile STRING(260)
CODE
MyLongFile = LONGPATH('c:\progra~1\mytext~1.txt')
!returns: c:\program files\my text file.txt
```

**See Also:**

SHORTPATH

PATH

DIRECTORY

FILEDIALOG

## LOWER (return lower case)

**LOWER**(*string*)

---

**LOWER**       Converts a string to all lower case.

*string*        A string constant, variable, or expression for the *string* to be converted.

The **LOWER** procedure returns a string with all letters converted to lower case.

**Return Data Type:**    STRING

**Example:**

```
!LOWER('ABC') returns 'abc'
```

```
Name = SUB(Name,1,1) & LOWER(SUB(Name,2,19))  
!Make the rest of the name lower case
```

**See Also:**

UPPER

ISUPPER

ISLOWER



## MATCH (compare matching values)

**MATCH**( *first*, *second* [, *mode* ] )

**MATCH** Returns true or false based on a comparison of the first two parameters passed.

*first* A string containing data to compare against the *second* parameter. String constants must be enclosed in single quotes.

*second* A string containing data to compare against the first parameter. For Wild and Regular modes *second* must contain the pattern or expression to match. String constants must be enclosed in single quotes.

*mode* An integer constant or equate which specifies the method of comparison. If omitted, a wild card comparison is the default.

The **MATCH** procedure returns true or false as to whether the *first* and *second* parameters match according to the comparison *mode* specified. The following *mode* value EQUATES are listed in EQUATES.CLW:

Match:Simple	A straight-forward equivalence comparison ( <i>first</i> = <i>second</i> ), which is most useful when combined with Match:NoCase
Match:Wild (default)	A wild card match with the <i>second</i> parameter containing the pattern that can contain asterisk (*) to match 0 or more of any character, and question mark (?) to match any single character.
Match:Regular	A regular expression match where the <i>second</i> parameter contains the regular expression. Repeated usage with the same regular expression value is optimized (to avoid recompiling the expression).
Match:Soundex	A standard soundex comparison of the two strings, returning true if they have the same soundex value.
Match:NoCase	Add to the <i>mode</i> for a case insensitive match (except Soundex).

### Regular Expression Operators

Regular expressions are used to describe patterns in text. The following characters are regular expression operators (or metacharacters) used to increase the power and versatility of regular expressions.

^	Caret matches the beginning of the string or the beginning of a line within the string. For example: ^@chapter matches the "@chapter" at the beginning of a string.
---	---

\$	Dollar sign is similar to the caret, but it matches only at the end of a string or the end of a line within the string. For example: <code>p\$</code> matches a record that ends with a p.
.	Period (.) matches any single character except a new line. For example: <code>.P</code> matches any single character followed by a P in a string. Using concatenation we can make regular expressions like 'U.A', which matches any three-character sequence that begins with 'U' and ends with 'A'.
[...]	This is called a character set. It matches any one of the characters that are enclosed in the square brackets. For example: <code>[mvx]</code> matches any one of the characters M, V, or X in a string. Ranges of characters are indicated by using a hyphen between the beginning and ending characters, and enclosing the whole thing in brackets. For example: <code>[0-9]</code> matches any digit. To match '-', write it as '---', which is a range containing only '-'. You may also give '-' as the first or last character in the set. To match '^', put it anywhere except as the first character of a set. To match a ']', make it the first character in the set. For example: <code>[^a^]</code> matches either ']', 'd' or '^'.
[^ ...]	This is a complemented character set. The first character after the [ must be a ^. It matches any characters except those in the square brackets (or newline). For example: <code>[^0-9]</code> matches any character that is not a digit.
	Vertical bar is the alternation operator and it is used to specify alternatives. For example: <code>^P [0-9]</code> matches any string that matches either ^P or [0-9]. This means it matches any string that contains a digit or starts with P. The alternation applies to the largest possible regexps on either side. No spaces are allowed between strings and the alternation operator.
{...}	Brackets are used for grouping in regular expressions as in arithmetic. They can be used to concatenate regular expressions containing the alternation operator,  .
*	Asterisk means that the preceding regular expression is to be repeated as many times as possible to find a match. For example: <code>ph*</code> applies the * symbol to the preceding h and looks for matches to one p followed by any number of h's. This will also match just p if no h's are present. The * repeats the smallest possible preceding expression (use parentheses if you wish to repeat a larger expression). It finds as many repetitions as possible. For example: <code>(c[ad][ad]*r x)</code> matches a string of the form (car x), (cdr x), (cadr x), and so on.
+	Plus sign is similar to *, but the preceding expression must be matched at least once. This means that: <code>wh+y</code> would match "why" and "whhy" but not "wy," whereas <code>wh*y</code> would match all three of these strings. This is a simpler way of writing the last * example: <code>(c[ad]+r x)</code>
?	Question mark is similar to *, but the preceding expression can be matched once or not at all. For example: <code>fe?a</code> will match fed and fd, but nothing else.
\	Backslash is used to suppress the special meaning of a character when matching. For example: <code>\\$</code> matches the character \$.

In regular expressions, the \*, +, and ? operators have the highest precedence, followed by concatenation, and finally by |.

**Note:**

There is now extended support for the MATCH function when used with the FILTER attribute of any VIEW structure that accesses SQL and ODBC back ends. For more detailed information, see the Use of MATCH with PROP:Filter and SQL Databases help topic.

**Return Data Type:** LONG

**Example:**

```
A STRING('Richard')
B STRING('RICHARD')
C STRING('R*')
D STRING('[A-D]')
ListHave1    STRING('IN,OH,KY,TN,PA')
ListHave2    STRING('WI,MN,IA,SD,ND')
StatesWanted  STRING('NJ|NY|PA|DE')
RV           BYTE !Return Value
X            BYTE
Y            BYTE
EmployeeName  STRING('Tom Thumb')
EMailAddr    STRING('bob@softvelocity.com')

CODE
RV = MATCH(A,B,Match:Simple+Match:NoCase)    !Returns true -
case insensitive match
RV = MATCH(A,B,Match:Soundex)                !Returns true -
same soundex values
RV = MATCH(A,C)                              !Returns true - wildcard match

RV=MATCH('Fireworks on the fourth', '{{4|four}th', Match:Regular+Match:NoCase)
!returns True
RV=MATCH('July 4th fireworks', '{{4|four}th', Match:Regular+Match:NoCase)
!returns True

X = STRPOS(ListHave1,StatesWanted,Match:Regular+Match:NoCase)    ! X = 1
Y = STRPOS(ListHave2,StatesWanted,Match:Regular+Match:NoCase)    ! Y = 0

IF MATCH(EmployeeName,'^Th?om{as|my}?{ }+', Match:Regular+Match:NoCase)
  Message('Welcome Tom Thom Thomas or Tommy')
END

!Regular expression for testing an email address as valid.

!1. The name portion can contain the characters: A-Z 0-9 -._
!2. Then must have an @
!3. Then repeating groups containing: A-Z 0-9 -._
!4. A period and 2, 3, 4 letters

RV = MATCH(UPPER(CLIP(eMailAddr)),|
'^[-A-Z0-9._]+@{[-A-Z0-9._]+}[A-Z][A-Z][A-Z]?[A-Z]?$', Match:Regular)
```

**See Also:**

STRPOS

## MAXIMUM (return maximum subscript value)

**MAXIMUM**(*variable*,*subscript*)

---

**MAXIMUM** Returns maximum subscript value.

*variable* The label of a variable declared with a DIM attribute.

*subscript* A numeric constant for the subscript number. The *subscript* identifies which array dimension is passed to the procedure. In Clarion Win32, subscript is 1-based. In Clarion# for .NET applications, subscript is zero (0) based.

The **MAXIMUM** procedure returns the maximum subscript value for an explicitly dimensioned variable. MAXIMUM does not operate on the implicit array dimension of STRING, CSTRING, or PSTRING variables. This is usually used to determine the size of an array passed as a parameter to a procedure or procedure.

**Return Data Type:** LONG

### Clarion Win32 Example:

```
Array BYTE,DIM(10,12)      !Define a two-dimensional array

!For the above Array:    MAXIMUM(Array,1) returns 10
!                        MAXIMUM(Array,2) returns 12

CODE
LOOP X# = 1 TO MAXIMUM(Array,1)    !Loop until end of 1st dimension
  LOOP Y# = 1 TO MAXIMUM(Array,2)  !Loop until end of 2nd dimension
    Array[X#,Y#] = 27              !Initialize each element to default
  END
END
```

### Clarion# Example:

```
array BYTE,DIM(10,12)  !first dimension is 10 elements

CODE
!the dimension starts at zero
MAXIMUM(array,0)       ! so this returns 10 (zero is first dimension)
```

### See Also:

DIM

Prototype Parameter Lists (Passing Arrays)

## MESSAGE (return message box response)

**MESSAGE**( *text* [,*caption*] [,*icon*] [,*buttons*] [,*default*] [,*style*] )

---

<b>MESSAGE</b>	Displays a message dialog box and returns the button the user pressed.
<i>text</i>	A string constant or variable containing the text to display in the message box. A vertical bar ( ) in the text indicates a line break for multi-line messages. Including '<9>' in the text inserts a tab for text alignment.
<i>caption</i>	The dialog box title. If omitted, the dialog has no title.
<i>icon</i>	A string constant or variable naming the .ICO file to display, or an EQUATE for one of Windows' standard icons (these EQUATES are listed in EQUATES.CLW). If omitted, no icon is displayed on the dialog box.
<i>buttons</i>	Either an integer expression which indicates which Windows standard buttons (may indicate multiple buttons) to place on the dialog box, or a string expression containing a vertical bar ( ) delimited list of the text for up to 8 buttons. If omitted, the dialog displays an Ok button.
<i>default</i>	An integer constant, variable, EQUATE, or expression which indicates the default button on the dialog box. If omitted, the first button is the default.
<i>style</i>	The <i>style</i> parameter is a bitmap integer constant, variable, EQUATE, or expression that specifies the type of modal behavior, and whether or not the text of the message can be copied to the Windows Clipboard.

The actual values for the *style* parameter are:

<u>Dec</u>	<u>Bin</u>	<u>Type</u>
<b>Modal Type:</b>		
0	0b	Application Modal
1	1b	System Modal
<b>Copy Text:</b>		
0	00b	message text is displayed as a static text without copy capability
2	10b	message text is displayed as a read only multi-line edit control with the possibility to select all or any part of the text and copy it to the clipboard

The **MESSAGE** procedure displays a Windows-standard message box, typically requiring only a Yes or No response, or no specific response at all. You can specify the font for MESSAGE by setting SYSTEM{PROP:FONT}.

The EQUATES.CLW file contains symbolic constants for the *icon*, *buttons*, and *default* parameters. The following list is all the EQUATES available for use in the *buttons* and *default* parameters for use when the *buttons* parameter is not a string:

BUTTON:OK  
 BUTTON:YES  
 BUTTON:NO  
 BUTTON:ABORT  
 BUTTON:RETRY

BUTTON:IGNORE  
BUTTON:CANCEL  
BUTTON:HELP

When *buttons* is a string, the *default* must be an integer in the range of 1 to the number of buttons defined in the *buttons* text (a maximum of 8).

The MESSAGE procedure returns the number of the button the user presses to exit the dialog box. The button number returned is the constant value that each of these EQUATEs represents (when the *buttons* parameter is an integer), and an integer in the range of 1 to the number of buttons defined in the *buttons* text (up to 8) when *buttons* contains string text.

The following list shows the most common EQUATEs used in the *icon* parameter (there are more listed in EQUATES.CLW):

ICON:None  
ICON:Application  
ICON:Hand  
ICON:Question  
ICON:Exclamation  
ICON:Asterisk  
ICON:Pick  
ICON:Clarion

The *style* parameter determines whether the message window is Application Modal or System Modal, and whether or not the message text can be copied to the Windows Clipboard. An Application Modal window must be closed before the user is allowed to do anything else in the application, but does not prevent the user from switching to another Windows application. A System Modal window must be closed before the user is allowed to do anything else in Windows.

The following list shows the EQUATEs used in the *style* parameter:

MSGMODE:SYSMODAL  
MSGMODE:CANCOPY

**Return Data Type:**     UNSIGNED

**Example:**

```
!A ? icon with Yes and No buttons, the default button is No:
CASE MESSAGE('Quit?', 'Editor', ICON:Question, BUTTON:Yes+BUTTON:No, BUTTON:No, 1)
OF BUTTON:No
    !the window is System Modal, no copy ability
    CYCLE
OF BUTTON:Yes
    MESSAGE('Goodbye|So Long|Sayonara') !A 3-line message with only an Ok button.
    RETURN
END

!Yes, No, and Maybe buttons, default is Maybe, Application Modal, with copy ability
CASE MESSAGE('Quit?', 'Editor', ICON:Question, '&Yes|&No|&Maybe', 3, 2)
OF 1
    !Yes button
    RETURN
OF 2
    !No button
    CYCLE
OF 3
    !Maybe button
    MESSAGE('You have a 50-50 chance of staying or going')
    IF CLOCK() % 2
        !Is the current time an odd or even hundredth of a second?
        RETURN
    ELSE
        CYCLE
    END;END
```

## MONTH (return month of date)

**MONTH**(*date*)

---

**MONTH** Returns month in year.

*date* A numeric constant, variable, expression, or the label of a STRING, CSTRING, or PSTRING variable declared with a date picture token. The *date* must be a standard date. A variable declared with a date picture token is automatically converted to a standard date intermediate value.

The **MONTH** procedure returns the month of the year (1 to 12) for a given standard date.

**Return Data Type:** LONG

**Example:**

```
PayMonth = MONTH(DueDate)    !Get the month from the date
```

**See Also:**

Standard Date

DAY

YEAR

TODAY

DATE

## MOUSEY (return mouse vertical position)

**MOUSEY()**

---

The **MOUSEY** procedure returns a numeric value corresponding to the current vertical position of the mouse cursor at the time of the event. The position is relative to the origin of that window.

The default return value is in dialog units, unless modified by the PROP:Pixels property. If the PROP:Pixels property is set to TRUE (1), the return value of MOUSEY is expressed in pixels.

**Return Data Type:**     SIGNED

**Example:**

```
SaveMouseY = MOUSEY ()     !Save mouse position
```

**See Also:**

MOUSEX



## NAME (return file name)

**NAME**(*label*)

---

**NAME**            Returns name of a file.

*label*            The label of a FILE declaration.

The **NAME** procedure returns a string containing the operating system device name for the structure identified by the *label*. For FILE structures, if the file is OPEN, the complete DOS file specification (drive, path, name, and extension) is returned. If the FILE is closed, the contents of the NAME attribute on the FILE are returned. If there is no NAME attribute, the FILE label is returned.

**Return Data Type:**    STRING

**Example:**

```
OpenFile = NAME(Customer)    Save the name of the open file
```

**See Also:**

EXISTS

## NEXT (read next record in sequence)

**NEXT**( *entity* )

---

**NEXT** Reads the next record in sequence from a FILE or VIEW.

*entity* The label of a FILE or VIEW declaration.

**NEXT** reads the next record in sequence from a FILE or VIEW. The SET (or RESET) statement determines the sequence in which records are read. The first NEXT following a SET reads the record at the position specified by the SET statement. Subsequent NEXT statements read subsequent records in that sequence. The sequence is not affected by any GET, REGET, ADD, PUT, or DELETE. Executing NEXT without a preceding SET, or attempting to read past the end of file posts the "Record Not Available" error.

### FILE Usage

---

NEXT reads the next record in sequence from the data FILE and places it in the RECORD structure data buffer.

### VIEW Usage

---

NEXT reads the next record(s) in sequence from a VIEW and places the appropriate fields in the VIEW structure component files' data buffer(s). If the VIEW contains JOIN structures, NEXT retrieves the appropriate next set of related records.

Either the last SET statement issued on the VIEW's primary file before the OPEN(view) statement, or the SET(view) statement issued after the OPEN(view) determines the sequence in which records are read.

#### Errors Posted:

- 33 Record Not Available
- 37 File Not Open
- 43 Record Is Already Held
- 90 Driver Specific Error (returned by FILEERRORCODE)

**Example:**

```

ViewOrder VIEW(Customer)                                !Declare VIEW structure
    PROJECT (Cus:AcctNumber,Cus:Name)
    JOIN (Hea:AcctKey,Cus:AcctNumber)                    !Join Header file
        PROJECT (Hea:OrderNumber)
        JOIN (Dt1:OrderKey,Hea:OrderNumber)              !Join Detail file
            PROJECT (Det:Item,Det:Quantity)
        END
    END
END

CODE
OPEN (Customer,22h)
SET (Cus:NameKey)                                       !Beginning of file in keyed sequence
LOOP                                                    !Read all records through end of file
    NEXT (Customer)                                     !read a record sequentially
    IF ERRORCODE () THEN BREAK.                         !break on end of file
    DO PostTrans                                       !call transaction posting routine
END

OPEN ((Header,22h)
OPEN (Detail,22h)
OPEN (Product,22h)
SET (Cus:AcctKey)
OPEN (ViewOrder)
    LOOP                                                !Read all records through end of primary file
        NEXT (ViewOrder)                               !read a record sequentially
        IF ERRORCODE () THEN BREAK.                   !break on end of file
        DO PostTrans                                   !call transaction posting routine
    END
END                                                    !End loop

```

**See Also:**

SET  
 RESET  
 PREVIOUS  
 EOF  
 HOLD  
 WATCH

## NOMEMO (read file record without reading memo)

**NOMEMO**(*file*)

---

**NOMEMO**      Arms "memoless" record retrieval.

*file*            The label of a FILE.

The **NOMEMO** statement arms "memoless" record retrieval for the next GET, REGET, NEXT, or PREVIOUS statement encountered. The following GET, REGET, NEXT, or PREVIOUS gets the record but does not get any associated MEMO or BLOB field(s) for the record. Generally, this speeds up access to the record when the contents of the MEMO or BLOB field(s) are not needed by the procedure.

**Example:**

```
SET (Master)
LOOP
  NOMEMO (Master)           !Arm "memoless" access
  NEXT (Master)             !Get record without memo
  IF ERRORCODE () THEN BREAK.
  Queue = Mst:Record        !Fill memory queue
  ADD (Queue)
  IF ERRORCODE () THEN STOP (ERROR ()) .
END
DISPLAY (?ListBox)         !Display the queue
```

**See Also:**

GET

NEXT

PREVIOUS

MEMO

## NOTIFICATION (receive information from sender thread)

**NOTIFICATION**(*notifycode*, <*thread*>, <*parameter*> )

---

**NOTIFICATION**    Receives information from a sender thread.

*notifycode*        An UNSIGNED variable that receives a notify code value passed by the sender with a NOTIFY statement.

*thread*            An optional SIGNED variable that receives the number of the sender's thread parameter.

*parameter*        A LONG variable that receives the parameter passed by the sender with a NOTIFY statement.

The **NOTIFICATION** function is used by a receiving thread. It receives the notification code, thread number, and parameter passed by the sending thread's NOTIFY statement.

**NOTIFICATION** returns FALSE (0) if the EVENT() function returns an event other than EVENT:Notify. If EVENT:Notify is posted, **NOTIFICATION** returns TRUE. Because calls to NOTIFY and **NOTIFICATION** are asynchronous, the sender thread can be closed already when receiver thread accepts the EVENT:Notify event.

NOTIFY and NOTIFICATION are a functional replacement for the SETTARGET(*,thread*) statement. They can also be used for safe transfer information between threads.

The code between SETTARGET(*,thread*) and a subsequent SETTARGET is executing in the context of the specified *thread* but also as a part of the current thread. Hence, two threads can execute the code in the same context. Also, related DLLs can associate their thread dependent data with the Thread ID of the current thread. These aspects make using SETTARGET(*,thread*) potentially dangerous in the new threading model.

The purpose of NOTIFY and NOTIFICATION is to provide a way to send a notification with parameters from one thread to another. The receiver thread can then execute the request in the correct context.

**Return Data Type:**    BYTE

**Example:**

```

CASE EVENT()
  OF EVENT:Accepted
    CASE ACCEPTED()
      OF ?Start
        START (T1)
      OF ?Load
        CALL ('DLL.DLL', 'EntryPoint', 1)
      ELSE
        Q.Feq = ACCEPTED()
        GET (Q, Q.Feq)
        IF ERRORCODE() = 0 AND Q.Op <> 0
          DM &= Q.ID + 0
          DM.ExecuteMenu (Q.Op)
        END
      END
  OF EVENT:Notify
    IF NOTIFICATION (NCode,, NParam) !NOTIFY has sent a Notify Event. Get Code and Parameter
      DM &= NParam + 0 !Assign passed parameter to reference var

      CASE Ncode !Test the Notify Code
        OF NOTIFY:Load !Execute appropriate action
          DM.CreateMenu (Q)
        OF NOTIFY:Unload
          DO DestroyMenu
          UNLOAD ('DLL.DLL') !Execute appropriate action
        END
      END
    END
  END
END

```

**See Also:**

NOTIFY

## NOTIFY (send safe information to a receiver thread)

**NOTIFY**( *notifycode*, <*thread*>, <*parameter*> )

---

<b>NOTIFY</b>	Sends an event and optional parameter to a receiving thread.
<i>notifycode</i>	An unsigned integer value that indicates the notification or request code.
<i>thread</i>	A signed integer that identifies the number of the receiver thread; if omitted or equal to 0, the current thread is the receiver.
<i>parameter</i>	An optional LONG value that is used as a parameter of the notification or request

The **NOTIFY** statement is called on the sender side. It generates the EVENT:Notify event and places it at the front of the event queue of receiver's thread top window. Generally, the EVENT:Notify event is a special event that can transfer up to 2 additional parameters (*thread* and *parameter*) to the receiver.

Execution of the sender thread continues immediately. It does not wait for any response from the receiver.

NOTIFY and NOTIFICATION are a functional replacement for the SETTARGET(*thread*) statement. They can also be used for safe transfer information between threads.

The code between SETTARGET(*thread*) and a subsequent SETTARGET is executing in the context of the specified *thread* but also as a part of the current thread. Hence, two threads can execute the code in the same context. Also, related DLLs can associate their thread dependent data with the Thread ID of the current thread. These aspects make using SETTARGET(*thread*) potentially dangerous in the new threading model.

The purpose of NOTIFY and NOTIFICATION is to provide a way to send a notification with parameters from one thread to another. The receiver thread can then execute the request in the correct context.

### Example:

```
DynMenu.Construct  PROCEDURE ()
  CODE
  SELF.NofWindows = 0
  NOTIFY (NOTIFY:Load, 1, ADDRESS (SELF.IDynMenu)) !Send Notify event to primary thread
  RETURN

! -----

DynMenu.Destruct  PROCEDURE()
  CODE
  NOTIFY (NOTIFY:Unload, 1, ADDRESS (SELF.IDynMenu))
  RETURN
```

See Also: **NOTIFICATION** , **SETTARGET**

## NULL (return null file field)



**NULL**(*field*)  
**NULL**(*file*, *field*)

---

<b>NULL</b>	Determines null "value" of a <i>field</i> .
<i>field</i>	The label (including prefix) of a field in a FILE structure. This may be a GROUP or RECORD structure.
<i>file</i>	The label of a FILE.

The **NULL** procedure returns a non-zero value (true) if the *field* is null, and zero (false) if the *field* contains any known value (including blank or zero). If the *field* is a GROUP or RECORD structure, all component fields of the GROUP or RECORD must be null for NULL to return true. Support for null "values" in a FILE is entirely dependent upon the file driver.

You can now pass a file as the first parameter to **NULL**. This allows you to pass references to fields (see the example below).

**Return Data Type:** LONG

### Example:

```
Customer FILE, DRIVER('MSSQL'), PRE(Cus)  !Declare customer file layout
AcctKey   KEY(Cus:AcctNumber)
Record    RECORD
AcctNumber LONG
OrderNumber LONG
Name      STRING(20)
Addr      STRING(20)
CSZ       STRING(35)
          END
          END

Header FILE, DRIVER('MSSQL'), PRE(Hea)  !Declare header file layout
AcctKey   KEY(Hea:AcctNumber)
Record    RECORD
AcctNumber LONG
OrderNumber LONG
ShipToName STRING(20)
ShipToAddr STRING(20)
ShipToCSZ STRING(35)
          END
          END

CODE
OPEN(Header)
OPEN(Customer)
SET(Hea:AcctKey)
LOOP
  NEXT(Header)
  IF ERRORCODE() THEN BREAK.
```



```
IF NULL(Hea:ShipToName)           !Check for null ship-to address
  Cus:AcctNumber = Hea:AcctNumber
  GET(Customer,Cus:AcctKey)       !Get Customer record
  IF ERRORCODE()
    CLEAR(Cus:Record)
  END
  Hea:ShipToName = Cus:Name       ! and assign customer address
  Hea:ShipToAddr = Cus:Addr      ! as the ship-to address
  Hea:ShipToCSZ  = Cus:CSZ
END
PUT(Header)                      !Put Header record back
END

!Example Two - Use of file parameter
SwapNullState PROCEDURE(File F, *? var)
CODE
  IF NULL(f, var)
    SETNONULL(f, var)
  ELSE
    SETNULL(f, var)
  END
```

**See Also:**

SETNULL

SETNULLS

SETNONULL

GETNULLS

## NUMERIC (return numeric string)

**NUMERIC**(*string*)

---

**NUMERIC**      Validates all numeric string.

*string*          A string constant, variable, or expression.

The **NUMERIC** procedure returns the value 1 (true) if the *string* only contains a valid numeric value. It returns zero (false) if the *string* contains any non-numeric characters. Valid numeric characters are the digits 0 through 9, the letter "E" (see below), a leading minus sign, and a decimal point. DEFORMAT is used to return unformatted numbers from a formatted string.

A valid number may also be a REAL and hence the format of strings representing correct numerics can be one of the following:

```
[<sign><number>[. [<number>]] [e [<sign><number>]]
[<sign>].<number>[e [<sign><number>]]
```

where:

<sign> - either minus (-) or plus (+) character

<number> - definitive (non-empty) sequence of decimal digits

e - either "e" or "E" character

**Return Data Type:**      UNSIGNED

**Example:**

```
!NUMERIC('1234.56')    returns 1
!NUMERIC('1,234.56')   returns 0
!NUMERIC('-1234.56')   returns 1
!NUMERIC('1234.56-')   returns 0
```

```
IF NOT NUMERIC(PartNumber)    !If part number is not numeric
DO ChkValidPart               !check for valid part number
END                            !End if
```

**See Also:**

DEFORMAT

## OMITTED (return omitted parameters)

**OMITTED** (*position*)

(*name*)

---

**OMITTED** Tests for unpassed parameters.

*position* An integer constant or variable which specifies the ordinal parameter position to test.

*name* The name of a procedure parameter.

The **OMITTED** procedure tests whether a parameter of a PROCEDURE was actually passed. The return value is one (true) if the parameter in the specified *position* was omitted. The return value is zero (false) if the parameter was passed. Any *position* past the last parameter passed is considered omitted.

For the purpose of the OMITTED procedure, a parameter may only be omitted if its data type is enclosed in angle brackets ( < > ) in the PROCEDURE prototype . Although parameters prototyped with default values may be omitted from the procedure call, the default value is actually passed, and the OMITTED procedure therefore returns false (0) for those parameters.

All CLASS methods have an implicit first parameter which is always passed--the CLASS name. This means that OMITTED(1) will always return false for a CLASS method. Any actual parameters passed to the method are numbered beginning with two (2). Therefore, to test whether two actual parameters to a CLASS method are passed means you must test *positions* two (2) and three (3).

The name of a procedure parameter can now be used in the call to the OMITTED() function. The OMITTED function now checks that its parameter is an identifier that matches the name of any procedure parameter it is called from. Otherwise, it treats a passed value as an expression that returns a parameter ordinal number. The identifier passed to OMITTED is taken as is, i.e., if the identifier is an EQUATE that names a label that happens to match the name of some procedure parameter, the compiler does not use the equated label, but uses the EQUATE as the literal procedure parameter.

**Return Data Type:** LONG

**Example:**

```

MAP
SomeProc  PROCEDURE (STRING,<LONG>,<STRING>)           !Procedure prototype
END
MyClass  CLASS
MyMethod  PROCEDURE (STRING Field1,<LONG Date>,<STRING Field3>) !Method prototype
        END

CODE
SomeProc(Field1,,Field3) !For this statement:
                        !OMITTED(1) returns 0, OMITTED(2) returns 1
                        !OMITTED(3) returns 0, OMITTED(4) returns 1
SomeProc PROCEDURE (Field1,Date,Field3)
CODE
IF OMITTED (2)           !If date parameter was omitted
    Date = TODAY()       !substitute the system date
END
MyClass.MyMethod  PROCEDURE (STRING Field1,<LONG Date>,<STRING Field3>)
CODE
IF OMITTED (3)           !If date parameter was omitted
    Date = TODAY()       !substitute the system date
END
*****Example of using OMITTED with a Procedure parameter:
PROGRAM

MAP
    PP (LONG) ,LONG,TYPE
END

T      CLASS
F      PROCEDURE (<LONG>,<QUEUE>,<FILE>,<KEY>,<BLOB>,<T>, |
        <WINDOW>,<?>,<PP>) ,LONG,PROC
END

CODE
T.F()

T.F PROCEDURE (<LONG L>,<QUEUE Q>,<FILE F>,<KEY K>,<BLOB B>,<T TT>, |
        <WINDOW W>,<? A>,<PP P>)

Res  LONG,AUTO

CODE

Res  = 0
Res += OMITTED (SELF)
Res += OMITTED (L)
Res += OMITTED (Q)
Res += OMITTED (F)
Res += OMITTED (K)
Res += OMITTED (B)
Res += OMITTED (TT)
Res += OMITTED (W)
Res += OMITTED (A)
Res += OMITTED (P)
RETURN Res

```

**See Also:**

Prototype Parameter Lists (Passing Arrays)

## OPEN (open a data structure)

**OPEN**( *entity* [, *access mode* / *owner* ] )

---

<b>OPEN</b>	Opens a FILE, VIEW, APPLICATION, WINDOW, or REPORT structure for processing.
<i>entity</i>	The label of a FILE, VIEW, APPLICATION, WINDOW, or REPORT structure.
<i>access mode</i>	A numeric constant, variable, or expression which determines the level of access granted to both the user opening the FILE <i>entity</i> , and other users in a multi-user system. If omitted, the default value is 22h (Read/Write + Deny Write). Valid only when the <i>entity</i> parameter names a FILE structure.
<i>owner</i>	The label of the APPLICATION or WINDOW structure which "owns" the window <i>entity</i> being opened. Normally, this parameter would be an &WINDOW reference variable. Valid only when the <i>entity</i> parameter names an APPLICATION or WINDOW structure.

The **OPEN** statement opens a FILE, VIEW, APPLICATION, WINDOW, or REPORT structure for processing.

### FILE Usage

---

The OPEN statement opens a FILE structure for processing and sets the *access mode*. Support for various *access modes* are file driver dependent. All files must be explicitly opened before the records may be accessed.

The *access mode* is a bitmap which tells the operating system what access to grant the user opening the file and what access to deny to others using the file.

The actual values for each access level are:

<u>Dec</u>	<u>Hex</u>	<u>Access</u>
------------	------------	---------------

**User Access:**

0	0h	Read Only
1	1h	Write Only
2	2h	Read/Write

**Other's Access:**

0	0h	Any Access (FCB compatibility mode)
16	10h	Deny All
32	20h	Deny Write
48	30h	Deny Read
64	40h	Deny None

## VIEW Usage

---

The OPEN statement opens a VIEW structure for processing. A VIEW must be explicitly opened before it may be accessed. The files used in the VIEW must already be open.

Before the OPEN(*view*) statement, you may issue a SET statement to the VIEW structure's primary file to setup sequential processing for the VIEW. You cannot issue a SET statement to the primary file while the VIEW is OPEN--you must CLOSE(*view*), then issue the SET, and then OPEN(*view*) again. SET(*view*) may be issued while the VIEW is open to setup sequential processing using the ORDER attribute.

## Window Usage

---

OPEN activates an APPLICATION or WINDOW for processing. However, nothing is displayed until a DISPLAY statement or the ACCEPT loop is encountered. This allows an opportunity to execute pre-display code to customize the display.

A *window* with an *owner* always appears on top of its *owner*, and is automatically hidden if the *owner* is minimized or hidden. If the *owner* is closed, all owned windows are also automatically closed. MDI windows are implicitly owned by the frame window. Non-MDI windows do not have an *owner* by default.

## REPORT Usage

---

OPEN activates a REPORT structure. You must explicitly OPEN a REPORT before any of the structures may be printed.

### Errors Posted:

02	File Not Found
03	Path Not Found
04	Too Many Open Files
05	Access Denied
32	File Is Already Locked
36	Invalid Data File
38	Invalid Key File
45	Invalid File Name
46	Key Files Must Be Rebuilt
47	Invalid File Declaration
52	File Already Open
57	Invalid Memo File
73	Memo File is Missing
75	Invalid Field Type Descriptor
79	Unsupported Data Type In File
88	Invalid Key Length
90	File System Error
92	Build In Progress

**Example:**

```

ReadOnly    EQUATE (0)                                !Access mode equates
WriteOnly   EQUATE (1)
ReadWrite   EQUATE (2)
DenyAll    EQUATE (10h)
DenyWrite  EQUATE (20h)
DenyRead   EQUATE (30h)
DenyNone   EQUATE (40h)

Header  FILE,DRIVER('Clarion'),PRE(Hea)                !Declare header file layout
AcctKey  KEY(Hea:AcctNumber)
OrderKey KEY(Hea:OrderNumber)
Record   RECORD
AcctNumber LONG
OrderNumber LONG
ShipToName STRING(20)
ShipToAddr STRING(20)
        END
        END

Detail  FILE,DRIVER('Clarion'),PRE(Dtl)                !Declare detail file layout
OrderKey KEY(Dtl:OrderNumber)
Record   RECORD
OrderNumber LONG
Item      LONG
Quantity  SHORT
        END
        END

ViewOrder VIEW(Header),ORDER('+Hea:OrderNumber') !Declare VIEW structure
        PROJECT(Hea:OrderNumber)
        JOIN(Dtl:OrderKey,Hea:OrderNumber)           !Join Detail file
        PROJECT(Det:Item,Det:Quantity)
        END
        END

CODE
OPEN (Names,ReadWrite+DenyNone)                       !Open fully shared access
OPEN (Header)
OPEN (Detail)
SET(Hea:AcctKey)                                       !Set to primary file
OPEN (ViewOrder)                                     !then Open view
SET(ViewOrder)                                       !or SET(view) after opening
                                                    !to use ORDER attribute
OPEN (CustRpt)                                       !Open a report

Win1Proc PROCEDURE
Win1 WINDOW,ALRT(F10Key)
        END
CODE
OPEN (Win1)                                           !Open the window
GlobalWindowReference &= Win1                       !Assign window reference to a
                                                    !global &WINDOW

ACCEPT
        IF EVENT() = EVENT:AlertKey
                START(Win2Proc)
        END
END

Win2Proc PROCEDURE

```

Win2 WINDOW

END

CODE

OPEN (Win2,GlobalWindowReference)

!Open Win2, "owned" by Win1

ACCEPT

END

**See Also:**

SHARE

CLOSE

SET

EXISTS

FILE

VIEW

APPLICATION

WINDOW

REPORT

ACCEPT

DISPLAY

CLOSE



## PACK (remove deleted records)

**PACK**(*file*)

**PACK**                Removes deleted records from a data file and rebuilds its keys.

*file*                The label of a FILE declaration.

The **PACK** statement removes deleted records from a data file and rebuilds its keys. The resulting data files are as compact as possible. PACK requires at least twice the disk space that the file, keys, and memos occupy to perform the process. New files are created from the old, and the old files are deleted only after the process is complete. PACK requires exclusive access to the file. Therefore, the file must be opened with *access mode* set to 12h (Read/Write Deny All) or 22h (Read/Write Deny Write).

PACK will generate events to the currently open window if you assign a value (an integer from 1 to 100) to PROP:ProgressEvents for the affected FILE before you issue the PACK. The larger the value you assign to PROP:ProgressEvents, the more events are generated and the slower the PACK will progress. These events allow you to indicate to the user the progress of the PACK. This can keep end-users informed that PACK is still working while building large files (so they don't re-boot thinking the machine has locked up).

It is not valid to make any calls to the *file* being built except to query its properties, call NAME(*file*), or CLOSE(*file*) (which aborts the process and is not recommended). Issuing a CYCLE statement in response to any of the events generated (except EVENT:BuildDone) cancels the operation. During the PACK operation, *file*{PROP:Completed} returns the percentage completed of the re-build and you can use *file*{PROP:CurrentKey} to get a key reference then either *key*{PROP:Name} or *key*{PROP:Label} to return the name of the current key being built.

### Errors Posted:

63 Exclusive Access Required

### Events Generated:

EVENT:BuildFile    PACK(*file*) is rebuilding the data portion of the *file*.

EVENT:BuildKey    PACK(*file*) is rebuilding the keys in the *file*.

EVENT:BuildDone    The PACK is complete.

### Example:

```
OPEN(Trans,12h)    !Open the file in exclusive mode
PACK(Trans)        ! and pack it
```

### See Also:

OPEN

SHARE

BUILD

PROP:ProgressEvents

PROP:Completed

## PATH (return current directory)

**PATH()**

---

**PATH** returns a string containing the current drive and directory. This is equivalent to the SHORTPATH procedure.

**PATH** can be used in expressions evaluated by the EVALUATE statements in runtime applications and in the templates.

**Return Data Type:**   STRING

**Example:**

```
IF PATH() = 'C:\'                !If in the root
  MESSAGE('You are in the Root Directory')  !display message
ELSIF PATH() = 'C:\INVOICE'        !In program directory
  MESSAGE('You are in the INVOICE Directory') !display message
END
```

**See Also:**

SETPATH

SHORTPATH

LONGPATH

DIRECTORY

## PEEK (read memory address)

**PEEK**(*address,destination*)

**PEEK** Reads data from a memory address.

*Address* A numeric constant, variable, or expression (evaluated to a LONG) that specifies a memory address. This parameter should always use the ADDRESS procedure, to ensure the correct address is used.

*destination* The label of a variable to receive the contents of the memory location.

The **PEEK** statement reads the memory address specified by *address* and copies the data found there into the *destination* variable. PEEK reads as many bytes as are required to fill the *destination* variable.

It is easily possible to create a General Protection Fault (GPF) if you PEEK at an incorrect address, so great care should be taken when using PEEK. There are usually Windows API procedures that will do whatever you require of PEEK and these should be used in preference to PEEK.

### Example:

```
MemAddress      LONG
Dest1           BYTE
Dest2           SHORT
Dest3           REAL
KeyboardFlag    BYTE
```

```
CODE
  PEEK (ADDRESS (MemAddress) ,Dest1)      !Read 1 byte
  PEEK (ADDRESS (MemAddress) ,Dest2)      !Read 2 bytes
  PEEK (ADDRESS (MemAddress) ,Dest3)      !Read 8 bytes
```

### See Also:

POKE

ADDRESS

## PENCOLOR (return line draw color)

**PENCOLOR()**

The **PENCOLOR** procedure returns the current pen color set by SETPENCOLOR. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

**Return Data Type:** LONG

**Example:**

```
Proc1    PROCEDURE
MDIChild1 WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
        !window controls
        END

CODE
OPEN(MDIChild1)
SETPENCOLOR(000000FFh)      !Set blue pen color
Proc2                                !Call another procedure

Proc2    PROCEDURE
MDIChild2 WINDOW('Child Two'),AT(0,0,320,200),MDI,MAX,HVSCROLL
        !window controls
        END

ColorNow    LONG
CODE
ColorNow = PENCOLOR()      !Get current pen color
OPEN(MDIChild2)
SETPENCOLOR(ColorNow)      !Set same pen color
SETPENSTYLE(PEN:dash)      !Set dashes for line style
SETPENWIDTH(2)             !Set two dialog unit thickness
BOX(100,50,100,50,00FF0000h) !Red box with thick blue dashed border
```

**See Also:**

SETPENCOLOR

## PENSTYLE (return line draw style)

### PENSTYLE( )

The **PENSTYLE** procedure returns the current line draw style set by SETPENSTYLE. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

EQUATE statements for the pen styles are contained in the EQUATES.CLW file. The following list is a representative sample of these (see EQUATES.CLW for the complete list):

PEN:solid	Solid line
PEN:dash	Dashed line
PEN:dot	Dotted line
PEN:dashdot	Mixed dashes and dots

**Return Data Type:** SIGNED

**Example:**

```

Proc1  PROCEDURE
MDIChild1 WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !window controls
END

CODE
OPEN(MDIChild1)
SETPENCOLOR(000000FFh)    !Set blue pen color
SETPENSTYLE(PEN:dash)    !Set dashes for line style
Proc2                    !Call another procedure

Proc2  PROCEDURE
MDIChild2 WINDOW('Child Two'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !window controls
END

ColorNow LONG
StyleNow LONG
CODE
ColorNow = PENCOLOR()    !Get current pen color
StyleNow = PENSTYLE()    !Get current pen style
OPEN(MDIChild2)
SETPENCOLOR(ColorNow)    !Set same pen color
SETPENSTYLE(StyleNow)    !Set same pen style
SETPENWIDTH(2)           !Set two dialog unit thickness
BOX(100,50,100,50,00FF0000h) !Red box with thick blue dashed border

```

**See Also:**

SETPENSTYLE

## PENWIDTH (return line draw thickness)

**PENWIDTH( )**

The **PENWIDTH** procedure returns the current line draw thickness set by SETPENWIDTH. The return value is in dialog units (unless overridden by the THOUS, MM, or POINTS attributes on a REPORT).

**Return Data Type:** SIGNED

**Example:**

```
Proc1  PROCEDURE
MDIChild1 WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
        !window controls
        END

CODE
OPEN(MDIChild1)
SETPENCOLOR(000000FFh)           !Set blue pen color
SETPENSTYLE(PEN:dash)           !Set dashes for line style
SETPENWIDTH(2)                  !Set two dialog unit thickness
Proc2                          !Call another procedure

Proc2  PROCEDURE
MDIChild2 WINDOW('Child Two'),AT(0,0,320,200),MDI,MAX,HVSCROLL
        !window controls
        END

ColorNow LONG
StyleNow LONG
WidthNow LONG
CODE
ColorNow = PENCOLOR()           !Get current pen color
StyleNow = PENSTYLE()           !Get current pen style
WidthNow = PENWIDTH()           !Get current pen width
OPEN(MDIChild2)
SETPENCOLOR(ColorNow)           !Set same pen color
SETPENSTYLE(StyleNow)           !Set same pen style
SETPENWIDTH(WidthNow)           !Set same pen width
BOX(100,50,100,50,00FF0000h)   !Red box with thick blue dashed border
```

**See Also:**

SETPENWIDTH

## PIE (draw a pie chart)

**PIE**( *x* ,*y* ,*width* ,*height* ,*slices* ,*colors* [,*depth*] [,*wholevalue*] [,*startangle*] [,*attributelist*])

---

<b>PIE</b>	Draws a pie chart on the current window or report.
<i>X</i>	An integer expression that specifies the horizontal position of the starting point.
<i>Y</i>	An integer expression that specifies the vertical position of the starting point.
<i>Width</i>	An integer expression that specifies the width.
<i>Height</i>	An integer expression that specifies the height.
<i>Slices</i>	A SIGNED array of values that specify the relative size of each slice of the pie.
<i>Colors</i>	A LONG array that specifies the fill color for each slice.
<i>Depth</i>	An integer expression that specifies the depth of the three-dimensional pie chart. If omitted, the chart is two-dimensional.
<i>wholevalue</i>	A numeric constant or variable that specifies the total value required to create a complete pie chart. If omitted, the sum of the <i>slices</i> array is used.
<i>startangle</i>	A numeric constant or variable that specifies the starting point of the first slice of the pie, measured as a fraction of the <i>wholevalue</i> . If omitted (or zero), the first slice starts at the twelve o'clock position.
<i>attributelist</i>	A string constant, variable, or EQUATE containing an optional type of output document and its associated attributes. Only valid when the target is a REPORT. See EXTEND

The **PIE** procedure creates a pie chart on the current window or report. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

The pie (an ellipse) is drawn inside a "bounding box" defined by the *x*, *y*, *width*, and *height* parameters. The *x* and *y* parameters specify the starting point, and the *width* and *height* parameters specify the horizontal and vertical size of the "bounding box."

The slices of the pie are created clockwise from the *startangle* parameter as a fraction of the *wholevalue*. Supplying a *wholevalue* parameter that is greater than the sum of all the *slices* array elements creates a pie chart with a piece missing.

The color of the lines is the current pen color set by SETPENCOLOR; the default color is the Windows system color for window text. The width of the lines is the current width set by SETPENWIDTH; the default width is one pixel. The line style is the current pen style set by SETPENSTYLE; the default style is a solid line.

**Example:**

PROGRAM

MAP

END

Window WINDOW('Child One'),AT(0,0,320,200),HVSCROLL,SYSTEM,MAX

END

SliceSize SIGNED,DIM(4)

SliceColor LONG,DIM(4)

CODE

SliceSize[1] = 90

SliceColor[1] = 0 !Black

SliceSize[2] = 90

SliceColor[2] = 00FF0000h !Red

SliceSize[3] = 90

SliceColor[3] = 0000FF00h !Green

SliceSize[4] = 90

SliceColor[4] = 000000FFh !Blue

OPEN(Window)

PIE(100,50,100,50,SliceSize,SliceColor,20)

!Draw pie chart containing

!four equal slices, starting at 12 o'clock

!drawn counter-clockwise - Black, Red, Green, and Blue

ACCEPT

END

**See Also:**

Current Target

SETPENCOLOR

SETPENWIDTH

SETPENSTYLE



## POINTER (return last queue entry position)

**POINTER**( *queue* )

**POINTER** Returns the entry number of the last entry accessed in a QUEUE.

*queue* The label of a QUEUE structure, or the label of a passed QUEUE parameter.

The **POINTER** procedure returns a LONG integer specifying the entry number of the last QUEUE entry accessed by ADD, GET, or PUT.

The value of **POINTER** is only valid if the ADD, GET, or PUT operation is successful.

**Return Data Type:** LONG

**Example:**

```
Que:Name = 'Jones'           !Initialize key field in sorted queue
GET (NameQue,Que:Name)       !Get the entry, if available
IF ~ERRORCODE ()             !If successful
  ADD (SecondQue,POINTER (NameQue)) !add the entry to second queue.
END
```

**See Also:**

GET

PUT

ADD

## POKE (write to memory address)

**POKE**(*address*,*source*)

---

**POKE**                Writes data to a memory address.

*address*             A numeric constant, variable, or expression (evaluated to a LONG) which specifies a memory address. This parameter should always use the ADDRESS procedure, to ensure the correct protected mode address is used.

*source*              The label of a variable.

The **POKE** statement writes the contents of the *source* variable to the memory address at *address*. POKE writes as many bytes as are in the *source* variable.

It is easily possible to create a General Protection Fault (GPF) if you POKE to an incorrect address, so great care should be taken when using POKE. There are usually Windows API functions that will do whatever you require of POKE and these should be used in preference to POKE.

### Example:

```
MAddress            LONG
Source1             BYTE
Source2             SHORT
Source3             REAL
KeyboardFlag        BYTE
```

```
CODE
POKE (ADDRESS (MAddress) , Source1)    !Write 1 byte to the memory location
POKE (ADDRESS (MAddress) , Source2)    !Write 2 bytes to the memory location
POKE (ADDRESS (MAddress) , Source3)    !Write 8 bytes to the memory location

KeyboardFlag = BOR (KeyboardFlag, 40h)    !turn on caps lock
POKE (ADDRESS (00400017h) , KeyboardFlag)    !and put it back
```

### See Also:

PEEK

ADDRESS

## POLYGON (draw a multi-sided figure)

**POLYGON**( *array* [,*fill*] [,*attributelist*])

**POLYGON**      Draws a multi-sided figure on the current window or report.

*Array*            An array of SIGNED integers that specify the x and y coordinates of each "corner point" of the polygon.

*Fill*             A LONG integer constant, constant EQUATE, or variable containing the red, green, and blue components that create the color in the three low-order bytes (bytes 0, 1, and 2) or an EQUATE for a standard Windows color value.

*attributelist*    A string constant, variable, or EQUATE containing an optional type of output document and its associated attributes. Only valid when the target is a REPORT. See EXTEND

The **POLYGON** procedure places a multi-sided figure on the current window or report. The polygon is always closed. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

The *array* parameter contains the x and y coordinates of each "corner point" of the polygon. The polygon will have as many corner points as the total number of array elements divided by two. For each corner point in turn, its x coordinate is taken from the odd-numbered array element and the y coordinate from the immediately following even-numbered element.

The border color is the current pen color set by SETPENCOLOR; the default color is the Windows system color for window text. The border width is the current width set by SETPENWIDTH; the default width is one pixel. The line's style is the current pen style set by SETPENSTYLE; the default style is a solid line.

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !window controls
END
Corners SIGNED,DIM(8)

CODE
Corners[1] = 0           !1st x position
Corners[2] = 90          !1st y position
Corners[3] = 90          !2nd x position
Corners[4] = 190         !2nd y position
Corners[5] = 100         !3rd x position
Corners[6] = 200         !3rd y position
Corners[7] = 50          !4th x position
Corners[8] = 60          !4th y position
OPEN(MDIChild)
POLYGON(Corners,000000FFh) !Blue filled four-sided polygon
```

**See Also:** Current Target, SETPENCOLOR, SETPENWIDTH, SETPENSTYLE

## POPUP (return popup menu selection)



**POPUP**( *selections* [, *x*] [, *y*] [, *position*] )

---

<b>POPUP</b>	Returns an integer indicating the user's choice from the menu.
<i>selections</i>	A string constant, variable, or expression containing the text for the menu choices.
<i>x</i>	An integer constant, variable, or expression that specifies the horizontal position of the menu's top left corner. If omitted, the menu appears at the current cursor position.
<i>y</i>	An integer constant, variable, or expression that specifies the vertical position of the menu's top left corner. If omitted, the menu appears at the current cursor position.
<i>position</i>	A BYTE value that if set to 1 specifies that the popup coordinates (2nd and 3rd parameters) are treated as relative to the upper left corner of the active window's client area. If set to 0 (the default), they are screen coordinates.

The **POPUP** procedure returns an integer indicating the user's choice from the popup menu that appears when the procedure is invoked. If the user clicks outside the menu or presses ESC (indicating no choice), POPUP returns zero.

Within the *selections* string, each choice in the popup menu must be delimited by a vertical bar (|) character. The following rules apply:

- A set of vertical bars containing only a hyphen (|-|) defines a separator between groups of menu choices.
- A menu choice immediately preceded by a tilde (~) is disabled (it appears dimmed out in the popup menu).
- A menu choice immediately preceded by a plus sign (+) appears with a check mark to its left in the popup menu.
- A menu choice immediately preceded by a minus sign (-) appears without a check mark to its left in the popup menu.
- A menu choice immediately followed by a set of choices contained within curly braces (|SubMenu{{SubChoice 1|SubChoice 2}}|) defines a sub-menu within the popup menu (the two beginning curly braces are required by the compiler to differentiate your sub-menu from a string repeat count).
- You may use the ASCII tab character (<9>) in your *selection* string to right-align text.
- You may specify an icon for the menu item by preceding the menu choice with square brackets enclosing PROP:Icon & ' (MyIco.ICO) ]MenuChoice'

```
POPUP('[' & PROP:Icon & ' (MyIco.ICO) ]MenuChoice')
```

Each menu selection is numbered in ascending sequence according to its position within the *selections* string, beginning with one (1). Separators and selections that call a sub-menu are not included in the numbering sequence (which makes an EXECUTE structure the most efficient code structure to use with this procedure). When the user **CLICKS** or presses **ENTER** on a choice, the procedure terminates, returning the position number of the selected menu item.

**Return Data Type:** SIGNED

**Example:**

```

PopupString = 'First|+Second|Sub menu{{One|Two}}|-|Third|~Disabled|' & |
              '[' & PROP:Icon & ' (MyIco.ICO)]Last Menu Choice'
ToggleChecked = 1
ACCEPT
CASE EVENT()
OF EVENT:AlertKey
  IF KEYCODE() = MouseRight
    EXECUTE POPUP(PopupString)
      FirstProc      !Call proc for selection 1
    BEGIN           !Code to execute for toggle selection 2
      IF ToggleChecked = 1 !Check toggle state
        SecondProc(Off)   !Call proc to turn off something
        PopupString[7] = '-' !Reset string so the check mark does not appear
        ToggleChecked = 0 !Set toggle flag
      ELSE
        SecondProc(On)    !Call proc to turn off something
        PopupString[7] = '+' !Reset string so the check mark does appear
        ToggleChecked = 1 !Set toggle flag
      END
    END             !End Code to execute for toggle selection 2
    OneProc         !Call proc for selection 3
    TwoProc         !Call proc for selection 4
    ThirdProc       !Call proc for selection 5
    DisabledProc    !Selection 6 is dimmed so it cannot run this proc
    IconProc        !Selection 7 displays an icon in the menu
  END
END
END
END

```

!The example below demonstrates the use of an API to get popup positioning !coordinates, and alert the Mouse Menu key along with the Mouse Right key

PROGRAM

INCLUDE('keycodes.clw')

RECT GROUP,TYPE

Left SIGNED

Top SIGNED

Right SIGNED

Bottom SIGNED

END

MAP

MODULE('Win32Api')

GetWindowRect(UNSIGNED hWnd, \*RECT lpRect),BOOL,PASCAL,RAW,PROC

END

END

W WINDOW('GetWindowRect'),AT(,156,110),ALRT(93),ALRT(MouseRight),SYSTEM,GR  
Y

BUTTON('GetWindowRect'),AT(23,21,75,14),USE(?GetWindowRectButton)  
END

rcCtrl LIKE(RECT)

hWndControl LONG,AUTO

CODE

OPEN(W)

hWndControl = ?GetWindowRectButton{PROP:Handle}

ACCEPT

IF FIELD() = ?GetWindowRectButton

IF EVENT() = EVENT:Accepted

!Get the rect of the button control in screen coordinates

GetWindowRect(hWndControl, rcCtrl)

x# = POPUP('1|2|3', rcCtrl.Left, rcCtrl.Bottom)

END

END

IF KeyCode()=93 !Hit right mouse menu key, position the Popup based on that

GetWindowRect(hWndControl, rcCtrl)

x# = POPUP('Moe|Larry|Curly', rcCtrl.Left, rcCtrl.Bottom)

ELSIF KeyCode()=MouseRight

x# = POPUP('Moe|Larry|Curly')

END

END

## POSITION (return record sequence position)

**POSITION**( *sequence* )

**POSITION** Identifies a record's unique position in a FILE or VIEW or QUEUE.

*sequence* The label of a VIEW, FILE, KEY, or INDEX or QUEUE declaration.

**POSITION** returns a STRING which identifies a record's unique position within the *sequence*. **POSITION** returns the position of the last record accessed in the file or VIEW. The **POSITION** procedure is used with **RESET** to temporarily suspend and resume sequential processing.

### FILE usage

The value contained in the returned STRING and the length of that STRING are dependent on the file driver. As a general rule, for file systems that have record numbers, the size of the STRING returned by **POSITION**(file) is 4 bytes. The return string from **POSITION**(key) is 4 bytes plus the sum of the sizes of the fields in the key. For file systems that do not have record numbers, the size of the STRING returned by **POSITION**(file) is generally the sum of the sizes of the fields in the Primary Key (the first KEY on the FILE that does not have the DUP or OPT attribute). The return string from **POSITION**(key) is the sum of the sizes of the fields in the Primary Key plus the sum of the sizes of the fields in the key.

### VIEW usage

The return string for **POSITION**(view) contains all the information required by the underlying file system to reset to the one specific position within the record set currently in the VIEW. It also contains the file system's **POSITION** return value for the primary file key and all secondary file linking keys. This allows **POSITION**(view) to accurately define a position for all related records in the VIEW.

### QUEUE usage

**POSITION**(queue) returns a pointer to the first queue record with a matching key value (for current active sort order). If an exact match is not found, a pointer to the next entry greater to one given in the current queue buffer is returned. If all entries in the queue have a lower key, **RECORDS**(queue)+1 is returned.

#### Errors Posted:

- 35 Record Not Found
- 30 Entry Not Found (QUEUE specific)

#### Return Data Types:

- LONG for **POSITION**(QUEUE)
- STRING all others

**Example of (POSITION(VIEW)):**

```
ViewO VIEW(Customer)  !Declare VIEW structure
  PROJECT(Cus:AcctNumber,Cus:Name)
  JOIN(Hea:AcctKey,Cus:AcctNumber) !Join Header file
  PROJECT(Hea:OrderNumber)
  JOIN(Dtl:OrderKey,Hea:OrderNumber) !Join Detail file
  PROJECT(Det:Item,Det:Quantity)
  JOIN(Pro:ItemKey,Dtl:Item) !Join Product file
  PROJECT(Pro:Description,Pro:Price)
  END
END
END
END
RecordQue QUEUE,PRE(Que)
AcctNumber LIKE(Cus:AcctNumber)
Name       LIKE(Cus:Name)
OrderNumber LIKE(Hea:OrderNumber)
Item       LIKE(Det:Item)
Quantity   LIKE(Det:Quantity)
Description LIKE(Pro:Description)
Price      LIKE(Pro:Price)
          END
SavPosition STRING(260)
CODE
OPEN(Customer,22h)
OPEN(Header,22h)
OPEN(Detail,22h)
OPEN(Product,22h)
SET(Cus:AcctKey)
OPEN(ViewOrder)
LOOP
  NEXT(ViewOrder)
  IF ERRORCODE()
    DO DisplayQue
    BREAK
  END
  RecordQue := Cus:Record
  RecordQue := Hea:Record
  RecordQue := Dtl:Record
  RecordQue := Pro:Record
  ADD(RecordQue)
  ASSERT(~ERRORCODE())
  IF RECORDS(RecordQue) = 20
    DO DisplayQue
  END
END
END

DisplayQue ROUTINE
  SavPosition = POSITION(ViewOrder) !Save record position
  DO ProcessQue
  FREE(RecordQue)
  RESET(ViewOrder,SavPosition)
  NEXT(ViewOrder)
```

!Top of file in keyed sequence  
!Read all records in file  
!read a record sequentially  
!Display the queue  
!Move record into queue  
!Move record into queue  
!Move record into queue  
!Move record into queue  
!and add it  
!20 records in queue?  
!Display the queue  
!Display the queue  
!and free it  
!Reset the record pointer  
!and get the record again



**Example (POSITION(Queue)):**

```
TaxQ   QUEUE
LowPay   DECIMAL(9,2)
HighPay  DECIMAL(9,2)
TaxAmount DECIMAL(9,2)
PlusPercent DECIMAL(5,2)
END
```

```
Bracket   LONG,AUTO `
```

```
CODE
SORT(TaxQ, TaxQ.HighPay)           !Set sort order
TaxQ.HighPay = PayCheck.GrossPay !Initialize QUEUE key field
Bracket = POSITION(TaxQ)             !Find pay bracket
!If Queue was not SORTed, an ERRORCODE 30 will be posted here.
IF Bracket > RECORDS(TaxQ)          !If value exceeds number of records
  Bracket = RECORDS(TaxQ)           !in QUEUE, set to highest value in QUEUE
END
GET(TaxQ, Bracket)                  !read QUEUE entry
Paycheck.Tax = TaxAmount+ |         !calculation based on QUEUE entry
(Paycheck.Gross-TaxQ.LowPay)*TaxQ.PlusPercent
```

**See Also:**

RESET

REGET

## POST (post user-defined event)

**POST**( *event* [,*control*] [,*thread*] [,*position*] )

---

**POST** Posts an event.

*event* An integer constant, variable, expression, or EQUATE containing an event number. A value in the range 400h to 0FFFh is a User-defined event.

*control* An integer constant, EQUATE, variable, or expression containing the field number of the control affected by the event. If omitted, the event is field-independent.

*thread* An integer constant, EQUATE, variable, or expression containing the execution thread number whose ACCEPT loop is to process the event. If omitted, the event is posted to the current thread.

*position* An integer constant, EQUATE, variable, or expression containing either zero (0) or one (1). If one (1), the *event* message is placed at the front of the event message queue. If omitted or zero (0), the *event* message is placed at the end of the event message queue.

**POST** posts an event to the currently active ACCEPT loop of the specified *thread*. This may be a User-defined event, or any other event. User-defined event numbers can be defined as any integer between 400h and 0FFFh. Any *event* posted with a *control* specified is a field-specific event, while those without are field-independent events.

POSTing an event causes the ACCEPT loop to fire but does not cause the event to "happen." For example, POST(EVENT:Selected,?MyControl) executes any code in EVENT:Selected for ?MyControl but does not cause ?MyControl to gain focus.

### Example:

```
Win1 WINDOW('Tools'),AT(156,46,32,28),TOOLBOX
      BUTTON('Date'),AT(0,0,,),USE(?Button1)
      BUTTON('Time'),AT(0,14,,),USE(?Button2)
END
CODE
OPEN(Win1)
ACCEPT
  IF EVENT() = EVENT:User          !Detect user-defined event
    BREAK
  END
  CASE ACCEPTED()
  OF ?Button1
    POST(EVENT:User,,UseToolsThread) !Post field-independent event to other thread
  OF ?Button2
    POST(EVENT:User)                !Post field-independent event to this thread
  END
END
CLOSE(Win1)
```

**See Also:** ACCEPT, EVENT, Modal Events

## PRAGMA (control pragma settings from source)

**PRAGMA**(*string*)

**PRAGMA** Send to the project system a statement from your generated source code

*string* A string constant, variable, or expression, of the format '*project(string)*', '*compile(string)*', or '*link(string)*'.

`PRAGMA('project(string)')`

Supports the use of the project system's statements in Clarion source code, and adds the statement to the project dynamically. The string parameter defines the proper project syntax.

Any valid pragma statement (e.g., CALL, DATA, DEFINE, etc.) can be used.

`PRAGMA('compile(string)')`

Equivalent to `PRAGMA('project(#compile string)')`

`PRAGMA('link(string)')`

Equivalent to `PRAGMA('project(#pragma link(string))')`

**PRAGMA** supports the use of the project system's pragma statement in Clarion source code, and adds the pragma to the project dynamically. The *string* parameter defines the proper project syntax.

Generally, the **PRAGMA** setting is in effect until the end of the source module where it was used. If the **PRAGMA** statement was used in the data section of a program's main module, it is working for all of the non-generic MEMBER source modules of the program.

### Examples:

```

PROGRAM
MAP
    INCLUDE ('MYUTIL.INC')
END
PRAGMA('project(#compile MYUTIL.CLW)')
PRAGMA('project(#pragma link(C%V%DOS%X%L%.LIB))')

F FILE,DRIVER('DOS'),CREATE,NAME('Test.!!')
Record RECORD
    BYTE,DIM(1000)
END

END

CODE
CREATE (F)
```

In the previous example, the project **pragma** forces the system to compile MYUTIL.CLW, and automatically adds the correct DOS driver library to the link list.

```
PROGRAM
MAP
  INCLUDE ( 'MYUTIL. INC' )
END
PRAGMA ( 'compile (MYUTIL.CLW) ' )
PRAGMA ( 'link (C%V%DOS%X%%L%.LIB) ' )

F      FILE, DRIVER ( 'DOS' ) , CREATE, NAME ( 'Test. !' )
Record RECORD
  BYTE, DIM (1000)
  END
END

CODE
CREATE (F)
```

The above example is identical in function to the first example.

## PRESS (put characters in the buffer)

**PRESS**(*string*)

---

**PRESS**            Places characters in the keyboard input buffer.

*string*            A string constant, variable, or expression.

**PRESS** places characters in the Windows keyboard input buffer. The entire *string* is placed in the buffer. Once placed in the keyboard buffer, the *string* is processed just as if the user had typed in the data.

**Example:**

```
IF LocalRequest = AddRecord            !On the way into a memo on adding a record
  TempString = FORMAT(TODAY(),@D1) & ' ' & FORMAT(CLOCK(),@T4)
  PRESS(TempString)                    !Pre-load first line of memo with date and time
END
```

**See Also:**

PRESSKEY

## PRESSKEY (put a keystroke in the buffer)

**PRESSKEY**(*keycode*)

---

**PRESSKEY**     Places one keystroke in the keyboard input buffer.

*keycode*        An integer constant or keycode EQUATE label.

**PRESSKEY** places one keystroke in the Windows keyboard input buffer. Once placed in the keyboard buffer, the *keycode* is processed just as if the user had pressed the key. ALIAS does not transform a **PRESSKEY** *keycode*.

**Example:**

```
IF Action = 'Add'           !On the way into a memo control on an add record
  Cus:MemoControl = FORMAT(TODAY(),@D1) & ' ' & FORMAT(CLOCK(),@T4)
                           !Pre-load first line of memo with date and time
  PRESSKEY(EnterKey)       !and position user on second line
END
```

**See Also:**

PRESS

## PREVIOUS (read previous view record in sequence)

**PREVIOUS**( *entity* )

---

**PREVIOUS** Reads the previous record in sequence.

*entity* The label of a FILE or VIEW declaration.

**PREVIOUS** reads the previous record(s) in sequence from a FILE or VIEW. The SET (or RESET) statement determines the sequence in which records are read. Executing **PREVIOUS** without a preceding SET, or attempting to read past the beginning of a file posts the "Record Not Available" error.

### FILE Usage

---

**PREVIOUS** reads the previous record in sequence from a data file and places it in the RECORD structure data buffer. The first **PREVIOUS** following a SET reads the record at the position specified by the SET statement. Subsequent **PREVIOUS** statements read subsequent records in reverse sequence. The sequence is not affected by any GET, REGET, ADD, PUT, or DELETE.

### VIEW Usage

---

**PREVIOUS** reads the previous record(s) in sequence from a VIEW and places the appropriate fields in the VIEW structure component files' data buffer(s). If the VIEW contains JOIN structures, **PREVIOUS** retrieves the appropriate previous set of related records.

Either the SET statement issued on the VIEW's primary file before the OPEN(view) statement, or the SET(view) statement issued after the OPEN(view) determines the sequence in which records are read. The first **PREVIOUS(view)** reads the record at the position specified by the SET statement. Subsequent **PREVIOUS** statements read subsequent records in that sequence. The sequence is not affected by PUT or DELETE statements.

#### Errors Posted:

- 33 Record Not Available
- 37 File Not Open
- 43 Record Is Already Held

**Example:**

```
ViewOrder VIEW(Header)
    PROJECT (Hea:OrderNumber)
    JOIN (Dtl:OrderKey,Hea:OrderNumber)    !Join Detail file
    PROJECT (Det:Item,Det:Quantity)
    JOIN (Pro:ItemKey,Dtl:Item)             !Join Product file
    PROJECT (Pro:Description,Pro:Price)
    END
END
END

CODE
OPEN ((Header,22h)
OPEN (Detail,22h)
OPEN (Product,22h)
SET (Cus:AcctKey)
OPEN (ViewOrder)
    LOOP                                !Read all records through beginning of primary file
    PREVIOUS (ViewOrder)                !read a record sequentially
    IF ERRORCODE() THEN BREAK END        !break on end of file
    DO PostTrans                         !call transaction posting routine
END                                      !End loop
```

**See Also:**

SET  
 RESET  
 NEXT  
 BOF  
 HOLD  
 WATCH  
 REGET  
 ADD  
 PUT  
 DELETE



## PRINT (print a report structure)

```
PRINT    (| structure | )

          | report ,number |
```

---

<b>PRINT</b>	Prints a report DETAIL structure.
<i>structure</i>	The label of a DETAIL structure.
<i>report</i>	The label of a REPORT structure.
<i>number</i>	The number or EQUATE label of a report DETAIL structure to print (only valid with a <i>report</i> parameter).

The **PRINT** statement prints a DETAIL report structure to the Windows default printer or the destination specified by the user in the Windows Print... dialog. PRINT automatically activates group breaks and page overflow as needed. You must explicitly OPEN a REPORT before any of the structures may be printed.

You cannot use the PRINT statement to explicitly print a HEADER or FOOTER section.

### Example:

```
MEMBER ()

MAP
  BuildRpt
END

BuildRpt PROCEDURE

CustRpt  REPORT, PRE (RPT)
Top      DETAIL, USE (?Top)    !Page header
        !structure elements
        END
CustDetail DETAIL, USE (?Detail)    !Line item detail
        !structure elements
        END
        END

CODE
OPEN (CustRpt)
!initialize any report variables here
PRINT (RPT:CustDetail)          !Print order detail line
PRINT (CustRpt, ?Top)           !Print the Top DETAIL only
CLOSE (CustRpt)
```

**See Also:** Page Overflow, BREAK, DETAIL, PROP:FlushPreview, OPEN

## PRINTERDIALOG (return chosen printer)

**PRINTERDIALOG**( [*title*] [,*flag*] )

---

**PRINTERDIALOG** Displays the Windows standard printer choice dialog box to allow the user to select or configure a printer.

*title* A string constant or variable containing the title to place on the file choice dialog. If omitted, a default *title* is supplied by Windows.

*flag* A numeric constant or variable which displays a target Print dialog based on the flag's value:

0 = *Choose Printer* dialog

1 = *Print Setup* dialog

2 = *Page Setup* dialog

The **PRINTERDIALOG** procedure displays the Windows standard printer choice dialog box, Print Setup dialog, or Page Setup dialog based on the *flag* value and returns the printer chosen by the user in the PRINTER "built-in" variable in the internal library. This sets the default printer used for the next REPORT opened.

PRINTERDIALOG returns zero (0) if the user pressed the Cancel button, or one (1) if the user pressed the Ok button on the dialog.

**Return Data Type:** SIGNED

**Example:**

```
CustRpt REPORT,AT(1000,1000,6500,9000),THOUS,Font('Arial',12),PRE(Rpt)
      !Report structures and controls
      END
```

```
CODE
IF NOT PRINTERDIALOG('Choose Printer')
  RETURN      !Abort if user pressed Cancel
END
OPEN(CustRpt)
```

## POPERRORS (return error information)

**POPERRORS()**

**POPERRORS** Returns the last error information saved by **PUSHERRORS()**

The **POPERRORS** procedure restores the last error information that was saved by **PUSHERRORS**. This includes **ERRORCODE()**, **ERROR()**, **FILEERRORCODE()**, **FILEERROR()**, **ERRORFILE()**, the C library *errno* variable, and the current Windows error code returned by the **GetLastError()** API function. To read these errors, you need to use the appropriate support statements.

**POPERRORS** is especially useful for programmer's that use the **GetLastError()** API function. **POPERRORS** restores the Windows error code that had been saved by **PUSHERRORS**. **GetLastError()** will return the same error code after **POPERRORS** that it would have returned just prior to **PUSHERRORS**.

**PUSHERRORS** and **POPERRORS** works using the LIFO (last in, first out) stack convention. The maximum depth of the stack is dependent on available memory.

Because **ERRORCODE()**, **ERROR()**, etc. are thread dependent, **PUSHERRORS** and **POPERRORS** statements that are called from different threads are independent of each other, and allocate a different memory stack for each thread.

### Example:

```

PROGRAM

MAP
  InitialErrors()
END

TESTFILE      FILE, DRIVER('DOS')
              RECORD
f1             BYTE
              END
              END

CODE
!file processing and initialization here
OPEN(testfile)  !forcing an error
PUSHERRORS()

!additional code here

InitialErrors
```

InitialErrors	PROCEDURE
ERRORCODEVAR	LONG
ERRORVAR	CSTRING(255)
FILEERRORCODEVAR	LONG
FILEERRORVAR	CSTRING(255)
ERRORFILEVAR	CSTRING(255)

```
Window WINDOW('Error Report'),AT(,,362,128),FONT('MS Sans Serif',8,,FONT:regular,CHARSET:ANSI),SYSTEM, |
    GRAY
    PROMPT('ERRORCODE:'),AT(9,10),USE(?Prompt1)
    STRING(@N_4),AT(97,10,43,10),USE(ERRORCODEVAR)
    PROMPT('ERROR:'),AT(9,25),USE(?Prompt2)
    STRING(@s40),AT(96,25),USE(ERRORVAR)
    PROMPT('FILEERRORCODE:'),AT(9,40),USE(?Prompt3)
    STRING(@N_4),AT(95,40),USE(FILEERRORCODEVAR)
    PROMPT('FILEERROR:'),AT(9,55),USE(?Prompt4)
    STRING(@s40),AT(95,55),USE(FILEERRORVAR)
    PROMPT('ERRORFILE:'),AT(9,70),USE(?Prompt5)
    STRING(@s40),AT(95,71),USE(ERRORFILEVAR)
END
```

```
CODE
POPERRORS()
ERRORCODEVAR = ERRORCODE()      !will return 2
ERRORVAR      = ERROR()          !will return "File Not Found"
FILEERRORCODEVAR = FILEERRORCODE()
FILEERRORVAR    = FILEERRORCODE()
ERRORFILEVAR    = ERRORFILE()    !will return "TESTFILE"
OPEN(WINDOW)
ACCEPT
DISPLAY
END
```

**See Also:**

PUSHERRORS

## PUSHERRORS (write error information)

**PUSHERRORS()**

**PUSHERRORS** Writes the last error information to an internal memory stack.

The **PUSHERRORS** procedure writes the current error states of the current thread's `ERRORCODE()`, `ERROR()`, `FILEERRORCODE()`, `FILEERROR()`, `ERRORFILE()`, the C library *errno* variable, and the current Windows error code returned by the `GetLastError()` API function.

`POPERRORS` is used to restore the error states originally saved by **PUSHERRORS**. The main purpose of these functions is to save errors states and then check them later, after performing some additional code that can potentially change them.

**PUSHERRORS** and `POPERRORS` works using the LIFO (last in, first out) stack convention. The maximum depth of the stack is dependent on available memory. Because `ERRORCODE()`, `ERROR()`, etc. are thread dependent, **PUSHERRORS** and `POPERRORS` statements that are called from different threads are independent of each other, and allocate a different memory stack for each thread.

**Example:**

```

PROGRAM

MAP
    InitialErrors()
END

TESTFILE    FILE, DRIVER('DOS')
            RECORD
f1          BYTE
            END
            END

CODE
!file processing and initialization here
OPEN(testfile)    !forcing an error
PUSHERRORS()

!additional code here

InitialErrors

InitialErrors    PROCEDURE

ERRORCODEVAR    LONG
ERRORVAR        CSTRING(255)
FILEERRORCODEVAR    LONG
FILEERRORVAR    CSTRING(255)
ERRORFILEVAR    CSTRING(255)

```

```

Window WINDOW('Error Report'),AT(,,362,128),FONT('MS Sans Serif',8,,FONT:regular,CHARSET:ANSI),SYSTEM, |
    GRAY
    PROMPT('ERRORCODE:'),AT(9,10),USE(?Prompt1)
    STRING(@N_4),AT(97,10,43,10),USE(ERRORCODEVAR)
    PROMPT('ERROR:'),AT(9,25),USE(?Prompt2)
    STRING(@s40),AT(96,25),USE(ERRORVAR)
    PROMPT('FILEERRORCODE:'),AT(9,40),USE(?Prompt3)
    STRING(@N_4),AT(95,40),USE(FILEERRORCODEVAR)
    PROMPT('FILEERROR:'),AT(9,55),USE(?Prompt4)
    STRING(@s40),AT(95,55),USE(FILEERRORVAR)
    PROMPT('ERRORFILE:'),AT(9,70),USE(?Prompt5)
    STRING(@s40),AT(95,71),USE(ERRORFILEVAR)
END

```

```

CODE
POPERRORS()
ERRORCODEVAR      = ERRORCODE()      !will return 2
ERRORVAR           = ERROR()          !will return "File Not Found"
FILEERRORCODEVAR  = FILEERRORCODE()
FILEERRORVAR       = FILEERRORCODE()
ERRORFILEVAR       = ERRORFILE()      !will return "TESTFILE"
OPEN(WINDOW)
    ACCEPT
    DISPLAY
END

```

**See Also:**

POPERRORS

## PUT (re-write record)

```

PUT  (| file [, filepointer [, length ] ] | )
      | queue , [[+]key,..., [-]key]|
      | queue , name|
      | queue , function|
      | view|

```

---

<b>PUT</b>	Writes a record back to a FILE, QUEUE, or VIEW.
<i>file</i>	The label of a FILE declaration.
<i>filepointer</i>	A numeric constant, variable, or expression for the value returned by the POINTER( <i>file</i> ) procedure.
<i>length</i>	An integer constant, variable, or expression containing the number of bytes to write to the <i>file</i> . This must be greater than zero and not greater than the RECORD length. If omitted or out of range, the RECORD length is used.
<i>queue</i>	The label of a QUEUE structure.
<b>+ -</b>	The leading plus or minus sign specifies the <i>key</i> is sorted in ascending or descending sequence.
<i>key</i>	The label of a field declared within the QUEUE structure. If the QUEUE has a PRE attribute, the <i>key</i> must include the prefix.
<i>name</i>	A string constant, variable, or expression containing the NAME attribute of QUEUE fields, separated by commas, and optional leading + or - signs for each attribute. This parameter is case sensitive.
<i>function</i>	The label of the function containing two parameters of a *GROUP or named GROUP passed by address, and having a SIGNED return value. Both parameters must use the same parameter type, and cannot be omitted. The RAW, C and PASCAL attributes are not permitted in the prototype declaration. See Additional Queue Considerations.
<i>view</i>	The label of a VIEW declaration.

The **PUT** statement re-writes a previously accessed record in a FILE, QUEUE, or VIEW.

## FILE Usage

---

The **PUT** statement writes the current values in the RECORD structure data buffer to a previously accessed record in the *file*. If the record was held, it is automatically released.

<code>PUT(<i>file</i>)</code>	Writes back the last record accessed with NEXT, PREVIOUS, GET, or ADD. If the values in the key variables were changed, the KEYS are updated.
<code>PUT(<i>file,filepointer</i>)</code>	Writes the record to the <i>filepointer</i> location in the <i>file</i> and the KEYS are updated.
<code>PUT(<i>file,filepointer,length</i>)</code>	Writes <i>length</i> bytes to the <i>filepointer</i> location in the <i>file</i> and the KEYS are updated.

If a record was not accessed with NEXT, PREVIOUS, GET, REGET, ADD, or was deleted, the "Record Not Available" error is posted. PUT also posts the "Creates Duplicate Key" error. If any error is posted, the record is not written to the file.

## QUEUE Usage

---

**PUT** writes the contents of the data buffer back to the QUEUE (after a successful GET or ADD) to the position returned by the POINTER procedure. If no previous GET or ADD was executed, the "Entry Not Found" error is posted.

<code>PUT(<i>queue</i>)</code>	Writes the data buffer back to the same relative position within the QUEUE of the last successful GET or ADD.
<code>PUT(<i>queue,key</i>)</code>	Writes an entry to a sorted memory queue after a successful GET or ADD, maintaining the sort order if any <i>key</i> fields have changed value. Multiple <i>key</i> parameters may be used (up to 16), separated by commas, with optional leading plus or minus signs to indicate ascending or descending sequence. The entry is inserted immediately after all other entries with matching <i>key</i> values.
<code>PUT(<i>queue,name</i>)</code>	Writes an entry to a sorted memory queue after a successful GET or ADD, maintaining the sort order if any <i>key</i> fields have changed value. The <i>name</i> string must contain the NAME attributes of the fields, separated by commas, with optional leading plus or minus signs to indicate ascending or descending sequence. The entry is inserted immediately after all other entries with matching field values.
<code>PUT(<i>queue,function</i>)</code>	Using PUT by FUNCTION will write from a positional value returned by the function. If the function returns zero (0) the queue record of the first parameter is treated as equal to the second. In this case, no record is written, since the values are equal. If the function returns a negative value, the PUT of the record passed as a first parameter is treated as having less value than record passed as second parameter and is written accordingly. If the function returns a positive value, the PUT of the record passed as a first parameter is treated as having a greater value than record passed as second parameter and is written accordingly.



## VIEW Usage

---

The **PUT** statement writes the current values in the VIEW structure's primary file's data buffer to a previously accessed primary file record in the *view*. If the record was held, it is automatically released. PUT writes to the last record accessed with the REGET, NEXT, or PREVIOUS statements. If the values in the key variables were changed, then the KEYS are updated.

PUT only writes to the primary file in the VIEW because the VIEW structure performs both relational Project and Join operations at the same time. Therefore, it is possible to create a VIEW structure that, if all its component files were updated, would violate the Referential Integrity rules set for the database. The common solution to this problem in SQL-based database products is to write only to the Primary file. Therefore, Clarion has adopted this same industry standard solution.

If a record was not accessed with REGET, NEXT, or PREVIOUS statements, or was deleted, then the "Record Not Available" error is posted. PUT also posts the "Creates Duplicate Key" error. If any error is posted, then the record is not written to disk.

### Errors Posted:

- |    |                                   |
|----|-----------------------------------|
| 05 | Access Denied                     |
| 08 | Insufficient Memory               |
| 30 | Entry Not Found                   |
| 33 | Record Not Available              |
| 40 | Creates Duplicate Key             |
| 75 | Invalid Field Type Descriptor     |
| 89 | Record Changed By Another Station |

**Example:**

```
ViewOrder  VIEW(Header)
            JOIN(Dtl:OrderKey,Hea:OrderNumber) !Join Detail file
            PROJECT(Det:Item,Det:Quantity)
            END
            END

NameQue  QUEUE,PRE(Que)
Name     STRING(20),NAME('FirstField')
Zip      DECIMAL(5,0),NAME('SecondField')
            END

CODE
OPEN(Header,22h)
OPEN(Detail,22h)
SET(Cus:AcctKey)
OPEN(ViewOrder)
LOOP
    PREVIOUS(ViewOrder)      !Read all records in reverse order
    ! read a record sequentially
    IF ERRORCODE() THEN BREAK. ! break at beginning of file
    DO LastInFirstOut         !Call last in first out routine
    PUT(ViewOrder)            !Write transaction record back to the file
    IF ERRORCODE() THEN STOP(ERROR()) END
END
    !End loop

DO BuildQue                  !Call routine to build the queue

Que:Name = 'Jones'          !Initialize key field
GET(NameQue,Que:Name)       !Get the matching record
IF ERRORCODE() THEN STOP(ERROR()) END
Que:Zip = 12345              !Change the zip
PUT(NameQue)                 !Write the changes to the queue
IF ERRORCODE() THEN STOP(ERROR()) END
Que:Name = 'Jones'          !Initialize key field
GET(NameQue,Que:Name)       !Get the matching record
IF ERRORCODE() THEN STOP(ERROR()) END
Que:Name = 'Smith'          !Change key field
PUT(NameQue,Que:Name)       !Write changes to the queue
IF ERRORCODE() THEN STOP(ERROR()) END
Que:Name = 'Smith'          !Initialize key field
GET(NameQue,'FirstField')   !Get the matching record
IF ERRORCODE() THEN STOP(ERROR()) END
Que:Name = 'Jones'          !Change key field
PUT(NameQue,'FirstField')   !Write changes to the queue
IF ERRORCODE() THEN STOP(ERROR()) END
```

**See Also:**

NEXT  
PREVIOUS  
GET  
ADD  
WATCH  
HOLD  
RELEASE  
SORT

## PUTINI (set INI file entry)

**PUTINI**( *section* [,*entry*] [,*value*] [,*file*] )

---

<b>PUTINI</b>	Sets the value for an INI file entry.
<i>section</i>	A string constant or variable containing the name of the portion of the INI file which contains the <i>entry</i> .
<i>entry</i>	A string constant or variable containing the name of the specific entry to set. If this parameter is omitted, the entire <i>section</i> , including all entries within the section, is deleted.
<i>value</i>	A string constant or variable containing the setting to place in the <i>entry</i> (up to 1023 characters). An empty string (") leaves the <i>entry</i> empty. If omitted, the <i>entry</i> is deleted.
<i>file</i>	A string constant or variable containing the name of the INI file to search. A file name without a full path (e.g. 'Autolog.ini') looks for the file in the Windows directory. To look for the file in the current directory enter a dot path (e.g. '.\Autolog.ini'). If the file doesn't exist, a new .INI file is created. If omitted, PUTINI places the <i>entry</i> in the WIN.INI file.

The **PUTINI** procedure places the *value* into an *entry* in a Windows-standard .INI file (maximum size of the file is 64K). A Windows-standard .INI file is an ASCII text file with the following format:

```
[some section name]
entry=value
next entry=another value
```

For example, WIN.INI contains entries such as:

```
[windows]
spooler=yes
load=nwpopup.exe
[intl]
sLanguage=enu
sCountry=United States
iCountry=1
```

The PUTINI procedure searches the specified *file* for the *entry* within the *section* you specify. It replaces the current entry value with the *value* you specify. If necessary, the *section* and *entry* are created.

### Example:

```
CODE
PUTINI('MyApp', 'SomeSetting', 'Initialized')    !Place setting in WIN.INI
PUTINI('MyApp', 'ASetting', '2', 'MYAPP.INI')    !Place setting in MYAPP.INI
```

### See Also:

GETINI

## PUTREG (write value to Windows registry)

**PUTREG**(*root*, *keyname*, *valuename* [, *value*] [, *valuetype*] )

---

<b>PUTREG</b>	Writes a string value into the system registry.				
<i>root</i>	A LONG integer constant, variable or expression that specifies the root section of the registry to which to write the value. Valid values for this are defined in <b>equates.clw</b> and are as follows:  <b>REG_CLASSES_ROOT</b>  <b>REG_CURRENT_USER</b>  <b>REG_LOCAL_MACHINE</b>  <b>REG_USERS</b>  <b>REG_PERFORMANCE_DATA</b>  <b>REG_CURRENT_CONFIG</b>  <b>REG_DYN_DATA</b>				
<i>keyname</i>	A STRING constant, variable or expression that contains the key name of the key whose value is to be written. This may contain a path separated by backslash '\ characters. The <i>keyname</i> cannot contain a leading backslash.				
<i>valuename</i>	A STRING constant, variable or expression that contains the name of the value to be written.				
<i>value</i>	A STRING constant, variable or expression that contains the value to be written to the registry in the position given. If omitted, an empty string is written to the registry.				
<i>valuetype</i>	A LONG integer constant, variable or expression that specifies the how to store passed value. If omitted, the default value is REG_SZ (see below).  Supported types (expressed as EQUATES):  <table><tr><td><b>REG_NONE</b></td><td>value is ignored</td></tr><tr><td><b>REG_SZ</b></td><td>value is stored as a null terminated UNICODE string (default)</td></tr></table>	<b>REG_NONE</b>	value is ignored	<b>REG_SZ</b>	value is stored as a null terminated UNICODE string (default)
<b>REG_NONE</b>	value is ignored				
<b>REG_SZ</b>	value is stored as a null terminated UNICODE string (default)				

<b>REG_EXPAND_SZ</b>	value is stored as a null terminated UNICODE string that can contain unexpanded environment variables.
<b>REG_MULTI_SZ</b>	value is stored as an array of null terminated UNICODE strings. Strings in the array (i.e. in value parameter) are separated with '<0>' characters. GETREG appends 2 '<0>' characters at the end of array if they are not given.
<b>REG_DWORD</b>	value is stored as a 32 bit number, lower bytes stored first, e.g. value equal to 12345678h is stored as '<78h,56h,34h,12h>'
<b>REG_DWORD_LITTLE_ENDIAN</b>	the same as REG_DWORD
<b>REG_DWORD_BIG_ENDIAN</b>	value is stored as a 32 bit number with backward order of bytes, e.g. value equal to 12345678h is stored as '<12h,34h,56h,78h>'
<b>REG_QWORD</b>	value is a 64 bit number, lower bytes are stored first
<b>REG_QWORD_LITTLE_ENDIAN</b>	the same as REG_QWORD
<b>REG_BINARY</b>	value string is a binary data of any form

The PUTREG procedure places the value into a valuenam that exists in the Windows registry. The key and value will be created if it does not exist. If the write to the registry is successful, PUTREG returns 0. If the write to the registry is unsuccessful, the result is a non-zero value.

### **Vista and Clarion Built-in Registry Functions**

On Vista, a (non-elevated) app can READ the registry key HKLM (local machine) with no problems, but as far as writing to the Registry it needs to use HKCU (current user).

If you code sign your executable and run with elevated privileges then you can write to HKLM

**Return Data Type:** LONG

**Example:**

```
PROGRAM

MAP.

INCLUDE('EQUATES')
CurrentPath CSTRING(100)
ColorScheme CSTRING(100)

CODE
!Set the root directory of Clarion 6 install
CurrentPath = 'C:\Clarion7'
IF PUTREG(REG_LOCAL_MACHINE,'SOFTWARE\SoftVelocity\Clarion7','root',CurrentPath)
    MESSAGE('Unable to set the root directory') !post error if non-zero value returned
END
!writes the current user's color scheme to the registry
ColorScheme = 'Windows Standard'
IF PUTREG(REG_CURRENT_USER,'Control Panel\Current','Color Schemes',ColorScheme)
    MESSAGE('Unable to set the color scheme') !post error if non-zero value returned
END
```

**See Also:**

GETREG, DELETEREG

## QUOTE (replace string special characters)

**QUOTE**( *string* , *flag* )

**QUOTE**            Expands (or unpacks) *string* data

*string*            A string constant or variable containing the properties to parse.

*flag*            An unsigned integer that controls the method of unpacking.

The way that **QUOTE** processes the *string* is based on the *flag* parameter.

If the *flag* parameter is set to 0 (default), the **QUOTE** procedure returns the string contained in the symbol with all single quotes ('), un-paired left angle brackets (<), and un-paired left curly braces ({} "doubled up" to prevent compiler errors. Non-printable characters are replaced with <*n*> sequences, where *n* is a character code. 10 or more repeated characters are replaced with a *a*{*n*} sequence, where *a* is a character and *n* is the number of times that the character is repeated.

If the *flag* parameter is set to 1, **QUOTE** unpacks {} and <> sequences if the sequence inside the {} or <> is numeric and doubles all single quotes (').

This allows the user to enter string constants containing apostrophes, and filter expressions containing less than signs (<) without requiring that they enter two of each.

**Return Data Type:**    STRING

**Example:**

```
stringvar1  STRING('<250>')
stringvar2  STRING('<display text>')
stringvar3  STRING(30)
```

CODE

```
MESSAGE(QUOTE(stringvar1,0))  !returns accented u
MESSAGE(QUOTE(stringvar1,1))  !returns accented u

MESSAGE(QUOTE(stringvar2,0))  !returns '<<display text>'
MESSAGE(QUOTE(stringvar2,1))  !returns '<display text>'

stringvar3 = 'label{{PROP:text} = value'

MESSAGE(QUOTE(stringvar3,0))  !returns 'label{{PROP:text} = value'
MESSAGE(QUOTE(stringvar3,1))  !returns 'label{PROP:text} = value'
```

**See Also:**

UNQUOTE

## RANDOM (return random number)

**RANDOM**(*low,high*)

---

**RANDOM** Returns random integer.

*low* A numeric constant, variable, or expression for the lower boundary of the range.

*high* A numeric constant, variable, or expression for the upper boundary of the range.

The **RANDOM** procedure returns a random integer between the *low* and *high* values, inclusively. The *low* and *high* parameters may be any numeric expression, but only their integer portion is used for the inclusive range.

**Return Data Type:** LONG

**Example:**

```
Num                BYTE,DIM(49)
LottoNbr           BYTE,DIM(6)
CODE
CLEAR (Num)
CLEAR (LottoNbr)
LOOP X# = 1 TO 6
  LottoNbr[X#] = RANDOM(1,49)    !Pick numbers for Lotto
  IF NOT Num[LottoNbr[X#]]
    Num[LottoNbr[X#]] = 1
  ELSE
    X# -= 1
  END
END
END
```



## RECORDS (return number of rows in data set)

**RECORDS**( *entity* )

---

**RECORDS**      Returns the number of records.

*entity*              The label of a QUEUE, VIEW, FILE, KEY, or INDEX declaration.

The **RECORDS** procedure returns a LONG integer containing the number of entries in the *entity*.

### **FILE Usage**

---

The RECORDS procedure returns the number of records in a FILE, KEY, or INDEX. Since the OPT attribute of a KEY or INDEX excludes "null" entries, RECORDS may return a smaller number for the KEY or INDEX than the FILE.

### **QUEUE Usage**

---

The RECORDS procedure returns a LONG integer containing the number of entries in the QUEUE.

### **VIEW Usage**

---

The RECORDS procedure returns a LONG integer containing the number of rows in the VIEW's return data set, if no KEY fields are used in the VIEW's ORDER attribute.

For non-SQL file systems, if a KEY field is used in the VIEW's ORDER attribute, then RECORDS returns negative one (-1). RECORDS can only return a valid value in the cases where the VIEW engine must build its own index of all the records in the return data set. For those non-SQL VIEWS which do use a KEY field in the ORDER attribute, Clarion's VIEW engine optimizations make use of that KEY (allowing for faster overall processing), so no index is built and the number of records in the return data set is therefore not known.

**Return Data Type:**    LONG

**Example:**

SomeProc PROCEDURE(LocationQueue Location) !receives named QUEUE structure

```
Customer FILE,DIRECT('Clarion'),PRE(Cus)
AcctKey   KEY(Cus:AcctNumber)
NameKey   KEY(Cus:Name)
Record    RECORD
AcctNumber LONG
Name      STRING(20)
Addr      STRING(20)
CSZ       STRING(60)
          END
          END
```

```
Header FILE,DIRECT('Clarion'),PRE(Hea)
AcctKey KEY(Hea:AcctNumber)
OrderKey KEY(Hea:OrderNumber)
Record RECORD
AcctNumber LONG
OrderNumber LONG
OrderAmount DECIMAL(11,2)
          END
          END
```

```
ViewOrder VIEW(Customer),ORDER('Cus:Name,-Hea:OrderAmount') !ORDER without KEY fields
          PROJECT(Cus:AcctNumber,Cus:Name)
          JOIN(Hea:AcctKey,Cus:AcctNumber)
          PROJECT(Hea:OrderNumber)
          PROJECT(Hea:OrderAmount)
          END
          END
```

```
SaveCount LONG
SaveNameCount LONG
```

```
CODE
OPEN(Customer)
OPEN(Header)
SaveCount = RECORDS(Customer) !Save the record count
SaveNameCount = RECORDS(Cus:NameKey) !Number of records with names filled in
OPEN(ViewOrder)
MESSAGE("Records in VIEW = ' & RECORDS(ViewOrder)")

Entries# = RECORDS(Location) !Determine number of entries in passed QUEUE
LOOP I# = 1 TO Entries# !Loop through QUEUE
  GET(Location,I#) !getting each entry
  ASSERT(NOT ERRORCODE())
  DO SomeProcess !process the entry
END
```

**See Also:**

QUEUE

ADD

KEY

INDEX

OPT

## REGISTER (register event handler)

**REGISTER**( *event*, *handler*, *object* [, *window*] [, *control*] )

**REGISTER** Registers an event handling procedure.

<i>event</i>	An integer constant, variable, expression, or EQUATE containing an event number. A value in the range 400h to 0FFFh is a User-defined event.
<i>handler</i>	A LONG variable, or expression containing the return value from ADDRESS for the PROCEDURE to handle the <i>event</i> .
<i>object</i>	A LONG integer constant, variable, or expression containing any 32-bit unique value to identify the specific <i>handler</i> . This is generally the return value of ADDRESS(SELF) when the <i>handler</i> is a CLASS method.
<i>window</i>	The label of the WINDOW or REPORT whose <i>event</i> to handle. If omitted, the current target WINDOW or REPORT is assumed.
<i>control</i>	An integer constant, EQUATE, variable, or expression containing the field number of the specific control whose <i>event</i> to handle. If omitted, the <i>event</i> is handled for every control on the <i>window</i> .

### Note:

Can also be prototyped as **REGISTEREVENT**.

**REGISTER** registers an event *handler* PROCEDURE called internally by the currently active ACCEPT loop of the specified *window* whenever the specified *event* occurs. This may be a User-defined event, or any other event. User-defined event numbers can be defined as any integer between 400h and 0FFFh.

You may REGISTER multiple *handlers* for the same *event* if you choose--the *handlers* are called by ACCEPT in reverse order of their registration (the last one registered executes first). You may explicitly call UNREGISTER to remove the registration of any specific *handler*. The Clarion runtime library automatically unregisters all registered *event handlers* (for the WINDOW passed as the 4<sup>th</sup> parameter) as a part of the window's closing (when the outer most ACCEPT loop that is running in the window terminates its execution), so explicitly calling UNREGISTER is not required unless your program's logic requires it.

Anytime the *event* occurs, the *handler* procedure is called internally by the events processor running from within the ACCEPT statement. The value returned by the *handler* determines whether or not ACCEPT cycles for any additional *event* processing.

The handler procedure MUST have 1 parameter: when the *handler* is called the runtime library is passing the *object* value (the 3rd parameter in the call to REGISTER) as its parameter.

The *handler* PROCEDURE must not take any parameters and must return a BYTE containing one of the following EQUATED values (these EQUATES are defined in the ABERROR.INC file):

Level:Benign	Calls any other <i>handlers</i> and the ACCEPT loop, if available.
Level:Notify	Doesn't call other <i>handlers</i> or the ACCEPT loop. This is like executing CYCLE when processing the event in an ACCEPT loop.
Level:Fatal	Doesn't call other <i>handlers</i> or the ACCEPT loop. This is like executing BREAK when processing the event in an ACCEPT loop.

**Example:**

```
WindowResizeClass.Init PROCEDURE
CODE
REGISTER(EVENT:Sized,ADDRESS(SELF.TakeResize),ADDRESS(SELF))
!Other code follows

WindowResizeClass.TakeResize PROCEDURE
ReturnValue BYTE
CODE
ReturnValue = Level:Benign
RETURN(ReturnValue)
```

**See Also:**

UNREGISTER

ACCEPT

EVENT

## REGET (re-get record)

**REGET**( *sequence*, *string* )

---

<b>REGET</b>	Regets a specific record.
<i>sequence</i>	The label of a VIEW, FILE, KEY, or INDEX declaration.
<i>string</i>	The string returned by the POSITION procedure.

The **REGET** re-reads a previously accessed record.

### FILE Usage

---

REGET reads the record identified by the *string* returned by the POSITION procedure. The value contained in the *string* returned by the POSITION procedure, and its length, are dependent on the file driver.

### VIEW Usage

---

REGET reads the VIEW record identified by the *string* returned by the POSITION(view) procedure. The value contained in the *string* returned by the POSITION procedure, and its length, are file driver dependent. If the VIEW contains JOIN structures, REGET retrieves the appropriate set of related records.

REGET re-loads all the VIEW component files' record buffers with complete records. It does not perform the relational "Project" operation. REGET(view) is explicitly designed to reset the record buffers to the appropriate records immediately prior to a CLOSE(view) statement. However, the processing sequence of the files must be reset with a SET or RESET statement.

#### Errors Posted:

- 35     Record Not Found
- 37     File Not Open
- 43     Record Is Already Held
- 78     Invalid number of parameters (*string* parameter is too small)

#### Example:

```
ViewOrder VIEW(Customer)  !Declare VIEW structure
    PROJECT (Cus:AcctNumber,Cus:Name)
    JOIN(Hea:AcctKey,Cus:AcctNumber) !Join Header file
    PROJECT (Hea:OrderNumber)
    JOIN(Dtl:OrderKey,Hea:OrderNumber) !Join Detail file
    PROJECT (Det:Item,Det:Quantity)
    JOIN(Pro:ItemKey,Dtl:Item) !Join Product file
    PROJECT (Pro:Description,Pro:Price)
    END
    END
    END
    END
```

```

RecordQue  QUEUE,PRE (Que)
AcctNumber  LIKE (Cus:AcctNumber)
Name        LIKE (Cus:Name)
OrderNumber LIKE (Hea:OrderNumber)
Item        LIKE (Det:Item)
Quantity    LIKE (Det:Quantity)
Description LIKE (Pro:Description)
Price       LIKE (Pro:Price)
SavPosition STRING (260)
            END

CODE
OPEN (Customer,22h)
OPEN ( (Header,22h)
OPEN (Detail,22h)
OPEN (Product,22h)
SET (Cus:AcctKey)
  OPEN (ViewOrder)
LOOP                                !Read all records in file
  NEXT (ViewOrder)                  !read a record sequentially
  IF ERRORCODE ()
    DO DisplayQue
    BREAK
  END
  RecordQue :=: Cus:Record          !Move record into queue
  RecordQue :=: Hea:Record          !Move record into queue
  RecordQue :=: Dtl:Record          !Move record into queue
  RecordQue :=: Pro:Record          !Move record into queue
  SavPosition = POSITION (ViewOrder) !Save record position
  ADD (RecordQue)                   !and add it
  ASSERT (NOT ERRORCODE ())
END
ACCEPT
CASE ACCEPTED ()
OF ?ListBox
  GET (RecordQue,CHOICE ())
  REGEX (ViewOrder,Que:SavPosition) !Reset the record buffers
  CLOSE (ViewOrder)                 !and get the record again
  FREE (RecordQue)
  UpdateProc                         !Call Update Procedure
  BREAK
END
END

```

**See Also:**

POSITION  
 SET  
 RESET  
 WATCH  
 GET  
 NEXT  
 PREVIOUS

## RELEASE (release a held record)

RELEASE( *entity* )

**RELEASE** Releases the held record(s).

*entity* The label of a FILE or VIEW declaration.

The **RELEASE** statement releases a record previously held by the HOLD procedure. It will not release a record held by another user in a multi-user environment. If the record is not held, or is held by another user, RELEASE is ignored.

**Example:**

```
ViewOrder VIEW(Customer) !Declare VIEW structure
    PROJECT (Cus:AcctNumber,Cus:Name)
    JOIN (Hea:AcctKey,Cus:AcctNumber) !Join Header file
    PROJECT (Hea:OrderNumber)
    JOIN (Dtl:OrderKey,Hea:OrderNumber) !Join Detail file
    PROJECT (Det:Item,Det:Quantity)
    JOIN (Pro:ItemKey,Dtl:Item) !Join Product file
    PROJECT (Pro:Description,Pro:Price)
    END
    END
    END
    END
CODE
OPEN (Customer,22h)
OPEN (Header,22h)
OPEN (Detail,22h)
OPEN (Product,22h)
SET (Cus:AcctKey)
OPEN (ViewOrder)
LOOP                                !Process records Loop
    LOOP                            !Loop to avoid "deadly embrace"
        HOLD (ViewOrder,1)         !Arm Hold on view, try for 1 second
        NEXT (ViewOrder)           !Get and hold the record
        IF ERRORCODE() = 43        !If someone else has it
            CYCLE                   !and try again
        ELSE
            BREAK                   !Break if not held
        END
    END
    IF ERRORCODE() THEN BREAK END !Check for end of file
    !Process the records
    RELEASE (ViewOrder)            !release held records
END
```

**See Also:**

HOLD

PUT

## REMOVE (erase a file)

**REMOVE**(*file*)

---

**REMOVE**        Deletes a FILE.

*file*             The label of the FILE to be removed, or a string constant or variable containing the filename of the file to erase.

The **REMOVE** statement erases a file specification from the operating system directory in the same manner as the DOS "Delete" command. The *file* must be closed, or the "File Already Open" error is posted. If any error is posted, the file is not removed.

Since some file drivers use multiple physical disk files for one logical FILE structure, the default filename and extension assumptions are dependent on the file driver. If any error is posted, the file is not deleted.

**REMOVE** cannot be used to delete a Directory, even an empty one. To delete a directory use the CLib function **RmDir**, or the Windows API **RemoveDirectory()** for empty directories and **SHFileOperation** to delete files also and recurse subdirectories.

### Errors Posted:

02	File Not Found
03	The system cannot find the path specified.
05	Access Denied
52	File Already Open

### Example:

```
REMOVE (OldFile)           !Delete the old file
REMOVE ('Changes.dat')     !Delete the changes file
```

### See Also:

CLOSE



## RENAME (change file directory name)

**RENAME**(*file*,*new file*)

**RENAME**      Renames a FILE.

*file*            The label of a FILE to rename, or a string constant or variable containing a file specification.

*new file*       A string constant or variable containing a file specification. If the file specification does not contain a drive and path, the current drive and directory are assumed. If only the path is specified, the filename and extension of the original *file* are used for the *new file*. Files cannot be renamed to a new drive.

The **RENAME** statement changes the *file* specification to the specification for the *new file* in the directory. The *file* to rename must be closed, or the "File Already Open" error is posted. If the file specification of the *new file* is identical to the original *file*, the RENAME statement is ignored. If any error is posted, the file is not renamed.

Since some file drivers use multiple physical disk files for one logical FILE structure, the default filename and extension assumptions are dependent on the file driver.

### Errors Posted:

02      File Not Found  
03      Path Not Found  
05      Access Denied  
52      File Already Open

### Example:

```
RENAME (Text, 'text.bak')           !Make it the backup
RENAME (Master, '\newdir')         !Move it to another directory
RENAME ('C:\AUTOEXEC.BAT', 'C:\AUTOEXEC.SAV') !Make it the backup
```

### See Also:

CLOSE

# RESET (reset record sequence position)

```
RESET ( | view, string| )  
  
      | view, file|  
  
      | sequence, string|
```

---

<b>RESET</b>	Resets sequential processing to a specific record.
<i>view</i>	The label of a VIEW.
<i>string</i>	The string returned by the POSITION procedure.
<i>file</i>	The label of a component file of the VIEW.
<i>sequence</i>	The label of a FILE, KEY, or INDEX declaration.

**RESET** resets sequential processing to a specific record.

## VIEW Usage

---

RESET restores the VIEW to a previously read position in the return record set.

RESET( <i>view</i> , <i>string</i> )	Resets to the record identified by the <i>string</i> that was returned by the POSITION procedure. Once RESET has restored the record pointer, either NEXT or PREVIOUS will read that record.
RESET( <i>view</i> , <i>file</i> )	Resets to the record identified by the current contents of the <i>file</i> 's record buffer. This is used when the order of the VIEW is specified using PROP:Order and is equivalent to a RESET( <i>view</i> , <i>string</i> ).

The value contained in the *position* string (a value returned by the POSITION procedure) and its length, are file driver dependent. RESET is usually used in conjunction with POSITION to temporarily suspend and resume sequential VIEW processing.

## FILE Usage

RESET restores the record pointer to the record identified by the *string* returned by the POSITION procedure. Once RESET has restored the record pointer, either NEXT or PREVIOUS will read that record.

The value contained in the *string* returned by the POSITION procedure, and its length, are dependent on the file driver. RESET is used in conjunction with POSITION to temporarily suspend and resume sequential file processing.

### Errors Posted:

- 33      Record Not Available
- 37      File Not Open
- 78      Invalid number of parameters (*string* parameter is too small)

### Example:

```
ViewOrder VIEW(Customer)  !Declare VIEW structure
    PROJECT (Cus:AcctNumber,Cus:Name)
    JOIN (Hea:AcctKey,Cus:AcctNumber) !Join Header file
    PROJECT (Hea:OrderNumber)
    JOIN (Dtl:OrderKey,Hea:OrderNumber) !Join Detail file
    PROJECT (Det:Item,Det:Quantity)
    JOIN (Pro:ItemKey,Dtl:Item) !Join Product file
    PROJECT (Pro:Description,Pro:Price)
    END
    END
    END
    END

RecordQue  QUEUE,PRE (Que)
AcctNumber  LIKE (Cus:AcctNumber)
Name        LIKE (Cus:Name)
OrderNumber LIKE (Hea:OrderNumber)
Item        LIKE (Det:Item)
Quantity    LIKE (Det:Quantity)
Description LIKE (Pro:Description)
Price       LIKE (Pro:Price)
    END

SavPosition STRING(260)
CODE
OPEN (Customer,22h)
OPEN (Header,22h)
OPEN (Detail,22h)
OPEN (Product,22h)
SET (Cus:AcctKey)
OPEN (ViewOrder)           !Top of file in keyed sequence
LOOP                       !Read all records in file
    NEXT (ViewOrder)       ! read a record sequentially
    IF ERRORCODE ()
        DO DisplayQue
        BREAK
    END
    RecordQue :=: Cus:Record !Move record into queue
    RecordQue :=: Hea:Record !Move record into queue
    RecordQue :=: Dtl:Record !Move record into queue
```

```
RecordQue :=: Pro:Record    !Move record into queue
ADD (RecordQue)             ! and add it
ASSERT (NOT ERRORCODE ())
IF RECORDS (RecordQue) = 20 !20 records in queue?
DO DisplayQue               !Display the queue
END
END                           !End loop

DisplayQue ROUTINE
  SavPosition = POSITION (ViewOrder)    !Save record position
DO ProcessQue                          !Display the queue
FREE (RecordQue)                      !and free it
RESET (ViewOrder, SavPosition)        !Reset the record pointer
NEXT (ViewOrder)                     !and get the record again
```

**See Also:**

POSITION

SET

NEXT

PREVIOUS

REGET

## RESTORESTATE (restore state of data file)

**RESTORESTATE**(*file*, *savedstate*, <*restoreflag*>)

**RESTORESTATE** Restores a file's *savedstate* state including the record buffer, file pointer, file sequencing order, and the error state of the system.

*file* The label of a FILE declaration.

*savedstate* A LONG numeric variable which represents the value returned by the GETSTATE procedure.

*restoreflag* A BYTE value that sets whether or not the file's record buffer is to be restored. The default value is FALSE (0), which indicates that the file buffer is not restored.

**RESTORESTATE** restores a file's state including the file pointer, file sequencing order, and the current error state of the system. By default, **RESTORESTATE** does not restore the file's record buffer. Setting the *restoreflag* to TRUE will restore the state of the file's record buffer.

RESTORESTATE does not change the data stored in a file. If data is added to a file after GETSTATE and before RESTORESTATE, the new record(s) will remain in the data file after the RESTORESTATE.

### Example:

```
MyFunction PROCEDURE(FILE MyFile)
```

```
CurState LONG
```

```
CODE
```

```
! File will be in the same state on exit of this procedure as it was on entry
CurState = GETSTATE(MyFile)      !save current state of file
SET(MyFile)                       !ready to access file
NEXT(MyFile)                      !read a record
CLEAR(MyFile)                    !clear record buffer
RESTORESTATE(MyFile, CurState, 1) !restore file and buffer to initial state
FREESTATE(MyFile, CurState)       !release resources
```

### See Also:

FREESTATE

GETSTATE

## RESUME (resume thread execution)



**RESUME**(*threadno*)

---

**RESUME**      Resume thread execution.

*threadno*      A numeric constant, variable, or expression that can be evaluated as a SIGNED integer.

The RESUME procedure restores a thread that has been suspended with the SUSPEND statement. If the threadno parameter is a number of a thread that was previously suspended by the call to SUSPEND, its suspending count is decremented. If the suspending count becomes equal to zero(0), execution of the thread continues from the point where it has been suspended. Therefore, the number of calls to RESUME must be equal to the number of calls to SUSPEND for the thread execution to resume.

RESUME can also be used to activate a new thread immediately. Normally, a procedure does not allocate memory for thread variables until the ACCEPT event handler is executed. RESUME can be used to activate a new thread directly upon procedure entry.

**Example:**

```
RESUME(ThreadNumVariable)    !attempt to resume thread execution
RESUME(START(MyThreadProc)) !start a new thread immediately
```

**See Also:**      SUSPEND

                 Launching a thread - a look behind the scenes

## ROLLBACK (terminate unsuccessful transaction)

### ROLLBACK

The **ROLLBACK** statement terminates an active transaction. Execution of a ROLLBACK statement assumes that the transaction was unsuccessful and the database must be restored to the state it was in before the transaction began.

ROLLBACK informs the file driver involved in the transaction that the temporary files containing the information necessary to restore the database to its previous state must be used to restore the database. The file driver then performs the actions necessary to its file system to roll back the transaction.

#### Errors Posted:

65     Unable to ROLLBACK Transaction

91     No Logout Active

#### Example:

```

LOGOUT(1,OrderHeader,OrderDetail)      !Begin Transaction
DO ErrHandler                          !always check for errors
ADD(OrderHeader)                        !Add Parent record
DO ErrHandler                          !always check for errors
LOOP X# = 1 TO RECORDS(DetailQue)      !Process stored detail records
  GET(DetailQue,X#)                    !Get one from the QUEUE
  DO ErrHandler                        !always check for errors
  Det:Record = DetailQue                !Assign to record buffer
  ADD(OrderDetail)                      !and add it to the file
  DO ErrHandler                        !always check for errors
END
COMMIT                                 !Terminate successful transaction
ASSERT(~ERRORCODE())

ErrHandler ROUTINE                      !Error routine
IF NOT ERRORCODE() THEN EXIT.           !Bail out if no error
ROLLBACK                               !Rollback the aborted transaction
ASSERT(~ERRORCODE())
BEEP                                   !Alert the user
MESSAGE('Transaction Error - ' & ERROR())
RETURN                                 !and get out

```

#### See Also:

LOGOUT

COMMIT

## ROUND (return rounded number)

**ROUND**(*expression,order*)

---

**ROUND**            Returns rounded value.

*expression*        A numeric constant, variable, or expression.

*order*                A numeric expression with a value equal to a power of ten, such as 1, 10, 100, 0.1, 0.001, etc. If the value is not an even power of ten, the next lowest power is used; 0.55 will use 0.1 and 155 will use 100.

The **ROUND** procedure returns the value of an *expression* rounded to a power of ten. If the *order* is a LONG or DECIMAL Base Type, then rounding is performed as a BCD operation. Note that if you want to round a real number larger than  $1^{30}$ , you should use `ROUND(num,1.0e0)`, and not `ROUND(num,1)`. The **ROUND** procedure is very efficient ("cheap") as a BCD operation and should be used to compare REALs to DECIMALs at decimal width.

**Return Data Type:**    DECIMAL or REAL

**Example:**

```
!ROUND(5163,100)        returns 5200
!ROUND(657.50,1)        returns 658
!ROUND(51.63594,.01) returns 51.64
```

```
Commission = ROUND(Price / Rate,.01)    !Round the commission to the nearest cent
```

**See Also:**

BCD Operations and Procedures



## RUN (execute command)

**RUN**( *command* [, *waitflag* ] )

---

<b>RUN</b>	Executes a <i>command</i> as if it were entered on the DOS command line.
<i>command</i>	A string constant or variable containing the command to execute. This may include a full path and command line parameters.
<i>waitflag</i>	An integer constant, variable, or EQUATE indicating whether RUN should launch the <i>command</i> and wait for its termination, or immediately return after launching. If omitted or zero (0), control immediately returns to the statement following the RUN. If one (1), control returns to the statement following the RUN only after the <i>command</i> has completed its execution.

The **RUN** statement executes a *command* to execute a DOS or Windows program. If the *command* parameter is a STRING variable, you must first use CLIP to remove trailing spaces (not necessary if the *command* is a CSTRING variable). Internally, RUN uses the appropriate API call to execute the *command*.

When the *command* executes, the new program is loaded as the ontop and active program. Execution control in the launching program returns immediately to the statement following RUN and the launching program continues executing as a background application if the *waitflag* is set to zero (0). The user can return to the launching program by either terminating the launched program, or switching back to it through the Windows Task List. Execution control in the launching program returns to the statement following RUN only after the *command* has terminated its execution if the *waitflag* is set to one (1).

If the *command* does not contain a path to the program, the following search sequence is followed:

1. The DOS current directory
2. The Windows directory
3. The Windows system directory
4. Each directory in the DOS PATH
5. Each directory mapped in a network

The successful execution of the *command* may be verified with the RUNCODE procedure, which returns the DOS exit code of the *command*. If unsuccessful, RUN posts the error to the ERROR and ERRORCODE procedures.

The RUN statement now supports Vista UAC to open documents of registered types. If RUN is called for a document (not an EXE), additional parameters in passed string are ignored.

**Errors Posted:** RUN may post any possible error

**Example:**

```
ProgNameC  CSTRING(100)
ProgNameS  STRING(100)
```

```
CODE
RUN('notepad.exe readme.txt')      !Run Notepad, automatically loading readme.txt file

RUN(ProgNameC)                     !Run the command in the ProgNameC CSTRING variable

RUN(CLIP(ProgNameS))               !Run the command in the ProgNameS STRING variable

RUN('command.com /c MyBat.bat',1) !Run the command and wait for it to complete

RUN('viewme.jpg',TRUE)             !Run command open registered document type
```

**See Also:**

RUNCODE

HALT

ERROR

ERRORCODE

## RUNCODE (return program exit code)

**RUNCODE()**

The **RUNCODE** procedure returns the exit code passed to the operating system from the command executed by the RUN statement. This is the exit code passed by the HALT statement in Clarion programs and is the same as the DOS ERRORLEVEL. RUNCODE returns a LONG integer which may be any value that is returned to DOS as an exit code by the child program.

The child program may only supply a BYTE value as an exit code, therefore negative values are not possible as exit codes. This fact allows RUNCODE to reserve these values to handle situations in which an exit code is not available:

```

0 normal termination
-1 program terminated with Ctrl-C
-2 program terminated with Critical error
-3 TSR exit
-4 program did not run (check ERROR())

```

**Return Data Type:** LONG

**Example:**

```

RUN('Nextprog.exe')           !Run next program
IF RUNCODE() = -4
  IF ERROR() = 'Not Enough Memory' !If program didn't run for lack of memory
    MESSAGE('Insufficient memory') !display a message
    RETURN                        !and terminate the procedure
  ELSE
    STOP(ERROR())                !terminate program
  END
END

```

**See Also:**

RUN

HALT

## SELECT (select next control to process)



**SELECT**( [*control*] [,*position*] [,*endposition*] )

---

**SELECT** Sets the next control to receive input focus.

*control* A field number or field equate label of the next control to process. If omitted, the SELECT statement initiates AcceptAll mode.

*position* Specifies a position within the *control* to place the cursor. For an ENTRY or TEXT, SPIN, or COMBO control this is a character position, or a beginning character position for a marked block. For an OPTION structure, this is the selection number within the OPTION. For a LIST control, this is the QUEUE entry number. This parameter can also be specified using property syntax by PROP:Selected or PROP:SelStart.

*endposition* Specifies an ending character position within an ENTRY, TEXT, SPIN, or COMBO *control*. The character position specified by *position* and *endposition* are marked as a block, available for cut and paste operations. This parameter can also be specified using property syntax by PROP:SelEnd.

**SELECT** overrides the normal TAB key sequence control selection order of an APPLICATION or WINDOW. Its action affects the next ACCEPT statement that executes. The *control* parameter determines which control the ACCEPT loop will process next. If *control* specifies a control which cannot receive focus because a DISABLE or HIDE statement has been issued, focus goes to the next control following it in the window's source code that can receive focus. If *control* specifies a control on a TAB which does not have focus, the TAB is brought to the front before the control receives focus.

**SELECT** with *position* and *endposition* parameters specifies a marked block in the *control* which is available for cut and paste operations. You can use the SELECT statement to force navigation to a specific tab by specifying the TAB control's position number within the sheet as the second parameter: SELECT(?Sheet,TabNumber).

**SELECT** with no parameters initiates AcceptAll mode (also called non-stop mode). This is a field edit mode in which each control in the window is processed in Field Equate sequence by generating EVENT:Accepted for each. This allows data entry validation code to execute for all controls, including those that the user has not touched.

AcceptAll mode terminates when any of the following conditions is met:

- A SELECT(?) statement selects the same control for the user to edit. This code usually indicates the value it contains is invalid and the user must re-enter data.
- The Window{PROP:AcceptAll} property is set to zero (0). This property contains one (1) when AcceptAll mode is active. Assigning values to this property can also be used to initiate and terminate AcceptAll mode.
- A control with the REQ attribute is blank or zero. AcceptAll mode terminates with the control highlighted for user entry, without processing any more fields in the Field Equate key sequence.

When all controls have been processed, PROP:AcceptAll is zero and EVENT:Completed is posted to the window.

**Example:**

```
Screen WINDOW,PRE(Scr)
    ENTRY(@N3),USE(Ctl:Code)
    ENTRY(@S30),USE(Ctl:Name)
    LIST,USE(Ctl:Type),From(TypeQue),Drop(5)
    BUTTON('OK'),USE(?OkButton),KEY(EnterKey)
    BUTTON('Cancel'),USE(?CanxButton),KEY(EscKey)
END

CODE
OPEN(Screen)
SELECT(?Ctl:Code)                !Start with Ctl:Code
ACCEPT
CASE SELECTED()
OF ?Ctl:Type
    GET(TypeQue,Ctl:Type)        !Find type in List
    SELECT(?Ctl:Type,POINTER(TypeQue) !Select list to element
END
CASE ACCEPTED()
OF ?Ctl:Code
    IF Ctl:Code > 150             !If data entered is invalid
        BEEP                     !alert the user and
        SELECT(?)                !make them re-enter the data
    END
OF ?Ctl:Name
    SELECT(?Ctl:Name,1,5)        !Mark first five characters as a block
OF ?OkButton
    SELECT                       !Initiate AcceptAll mode
END
IF EVENT() = EVENT:Completed
    BREAK                       !AcceptAll mode terminated
END
END
```

**See Also:**

ACCEPT

PROP:AcceptAll

## SELECTED (return control that has received focus)



### SELECTED( )

---

The **SELECTED** procedure returns the field number of the control receiving input focus when an EVENT:Selected event occurs. SELECTED returns zero (0) for all other events.

Positive field numbers are assigned by the compiler to all WINDOW controls, in the order their declarations occur in the WINDOW structure. Negative field numbers are assigned to all APPLICATION controls. In executable code statements, field numbers are usually represented by field equate labels--the label of the USE variable preceded by a question mark (?FieldName).

**Return Data Type:** SIGNED

**Example:**

```
CASE SELECTED( )           !Process pre-edit code
OF ?Cus:Company             !Pre-load field value
OF ?Cus:CustType            !Pre-load field value
END
```

**See Also:**

ACCEPT

SELECT

## SEND (send message to file driver)

**SEND**(*file,message*)

**SEND**               Sends a message to the file driver.

*file*                The label of a FILE declaration. The FILE's DRIVER attribute identifies the file driver to receive the *message*.

*message*            A string constant or variable containing the information to supply to the file driver.

The **SEND** procedure allows the program to pass any driver-specific information to a file driver during program execution. Valid *messages* are dependent upon the file driver in use. Documentation of all valid SEND *messages* for a given file driver are listed in the file driver's documentation.

**Return Data Type:**   STRING

**Example:**

```
FileCheck = SEND (ClarionFile, 'RECOVER=120') !Arm recovery process for a Clarion data file
```

You can also use the Clarion SEND procedure to send an SQL command to a backend database. This is provided for backward compatibility with early versions of Clarion. We recommend using property syntax to send SQL statements to the backend database.

```
SEND (SQLFile, 'SELECT field1,field2 FROM table1'      |
      & 'WHERE field1 > (SELECT max(field1)'          |
      & 'FROM table2')                                ! Returns a result set you
                                                    ! get one row at a time
                                                    ! using NEXT(SQLFile)
```

```
SEND (SQLFile, 'CALL GetRowsBetween(2,8)')           !Call stored procedure
```

```
SEND (SQLFile, 'CREATE INDEX ON table1(field1 DESC)') !No result set
```

## SET (initiate sequential file processing)

```
| file|  
SET  ( | file, key| )  
      | file, filepointer|  
      | key|  
      | key, key|  
      | key, keypointer|  
      | key, key, filepointer|  
      | view |  
      | view , number |
```

---

<b>SET</b>	Initializes sequential processing of a FILE or VIEW.
<i>file</i>	The label of a FILE declaration. This parameter specifies processing in the physical order in which records occur in the data file.
<i>key</i>	The label of a KEY or INDEX declaration. When used in the first parameter position, <i>key</i> specifies processing in the sort sequence of the KEY or INDEX.
<i>filepointer</i>	A numeric constant, variable, or expression for the value returned by the POINTER( <i>file</i> ) procedure.
<i>keypointer</i>	A numeric constant, variable, or expression for the value returned by the POINTER( <i>key</i> ) procedure.
<i>View</i>	The label of a VIEW.
<i>Number</i>	An integer constant, variable or expression that specifies the start position based on the first <i>number</i> of components of the ORDER attribute. If omitted, all ORDER attribute components are used.

**SET** initializes sequential processing for a FILE or VIEW. SET does not get a record, but only sets up processing order and starting point for the following NEXT or PREVIOUS statements.

### FILE Usage

---

SET initializes sequential processing of a data file. The first parameter determines the order in which records are processed. The second and third parameters determine the starting point within the file. If the second and third parameters are omitted, processing begins at the beginning (or end) of the file.



SET( <i>file</i> )	Specifies physical record order processing and positions to the beginning (SET...NEXT) or end (SET...PREVIOUS) of the file.
SET( <i>file,key</i> )	Specifies physical record order processing and positions to the first record which contains values matching the values in the component fields of the <i>key</i> . NOTE: This form is rarely used and is only useful if the file has been physically sorted in the <i>key</i> order. A common mistake is to use this form when SET( <i>key,key</i> ) is the actual form desired.
SET( <i>file,filepointer</i> )	Specifies physical record order processing and positions to the <i>filepointer</i> record within the <i>file</i> .
SET( <i>key</i> )	Specifies keyed sequence processing and positions to the beginning (SET...NEXT) or end (SET...PREVIOUS) of the file in that sequence.
SET( <i>key,key</i> )	Specifies keyed sequence processing and positions to the first or last record which contains values matching the values in the component fields of the <i>key</i> . Both <i>key</i> parameters must be the same.
SET( <i>key,keypointer</i> )	Specifies keyed sequence processing and positions to the <i>keypointer</i> record within the <i>key</i> .
SET( <i>key,key,filepointer</i> )	Specifies keyed sequence processing and positions to a record which contains values matching the values in the component fields of the <i>key</i> at the exact record number specified by <i>filepointer</i> . Both <i>key</i> parameters must be the same.

When *key* is the second parameter, processing begins at the first or last record containing values matching the values in all the component fields of the specified KEY or INDEX. If an exact match is found, NEXT will read the first matching record while PREVIOUS will read the last matching record. If no exact match is found, the record with the next greater value is read by NEXT, the record with next lesser value is read by PREVIOUS.

The values for *filepointer* and *keypointer* are dependent on the file driver. They could be a record number, the relative byte position within the file, or some other kind of "seek position" within the file. These parameters are used to begin processing at a specific record within the file.

For all file drivers, an attempt to SET past the end of the file will set the EOF procedure to true, and an attempt to SET before the beginning of the file will set the BOF procedure to true.

## VIEW Usage

---

SET sets sequential processing for the VIEW to the beginning or end of the set of records specified by the FILTER attribute, sorted by the ORDER attribute. The optional *number* parameter limits the SET to assume that the values in the first specified *number* of expressions in the ORDER attribute are fixed. The VIEW must be OPEN before the SET.

**Example:**

```
ViewOrder  VIEW(Customer),FILTER('Hea:OrderTotal >= 500') |,ORDER('-Hea:OrderDate,Cus:Name')
            PROJECT(Cus:AcctNumber,Cus:Name)
            JOIN(Hea:AcctKey,Cus:AcctNumber)      !Join Header file
            PROJECT(Hea:OrderNumber,Hea:OrderTotal,Hea:OrderDate)
            JOIN(Dtl:OrderKey,Hea:OrderNumber)    !Join Detail file
            PROJECT(Det:Item,Det:Quantity)
            JOIN(Pro:ItemKey,Dtl:Item)           !Join Product file
            PROJECT(Pro:Description,Pro:Price)
            END
            END
            END
            END
CODE
DO OpenAllFiles

!Physical file order, beginning of file
SET(Customer)

Cus:Name = 'Smith'
!Physical file order, first record where Name = 'Smith'
SET(Customer,Cus:NameKey)

SavePtr = POINTER(Customer)
!Physical file order, physical record number = SavePtr
SET(Customer,SavePtr)

!NameKey order, beginning of file (relative to the key)
SET(Cus:NameKey)

SavePtr = POINTER(Cus:NameKey)
!NameKey order, key-relative record number = SavePtr
SET(Cus:NameKey,SavePtr)

Cus:Name = 'Smith'
!NameKey order, first record where Name = 'Smith'
SET(Cus:NameKey,Cus:NameKey)

Cus:Name = 'Smith'
SavePtr = POINTER(Customer)
!NameKey order, Name = 'Smith' and rec number = SavePtr
SET(Cus:NameKey,Cus:NameKey,SavePtr)

OPEN(ViewOrder)
SET(ViewOrder)                                !Top of record set in ORDER sequence
LOOP                                           !Read all records in file
    NEXT(ViewOrder)                           !read a record sequentially
    IF ERRORCODE() THEN BREAK END
    !Process the order
    END
END
Hea:OrderDate = TODAY()-1                     !Assign yesterday's date
SET(ViewOrder,1)                             !and process just yesterday's orders
LOOP                                           !Read all records in file
    NEXT(ViewOrder)                           !read a record sequentially
    IF ERRORCODE() THEN BREAK.
    !Process the order
    END
END
```

## SET3DLOOK (set 3D window look)



**SET3DLOOK**( *switch* )

**SET3DLOOK** Toggles three-dimensional look and feel.

*switch* An integer constant switching the 3D look off (0) and on (1).

The **SET3DLOOK** procedure sets up the program to display a three-dimensional look and feel. The default program setting is 3D enabled. On a WINDOW, the GRAY attribute causes the controls to display with a three-dimensional appearance. Controls in the TOOLBAR are always displayed with the three-dimensional look, unless disabled by SET3DLOOK. When three-dimensional look is disabled by SET3DLOOK, the GRAY attribute has no effect.

SET3DLOOK(0) turns off the three-dimensional look and feel. SET3DLOOK(1) turns on the three-dimensional look and feel. Values other than zero or one are reserved for future use.

**Example:**

```

MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS,HVSCROLL,RESIZE
MENUBAR
  MENU('&File'),USE(?FileMenu)
  ITEM('&Open...'),USE(?OpenFile)
  ITEM('&Close'),USE(?CloseFile),DISABLE
  ITEM('Turn off 3D Look'),USE(?Toggle3D),CHECK
  ITEM('E&xit'),USE(?MainExit)
END
END
END
CODE
OPEN(MainWin)
ACCEPT
CASE ACCEPTED()
OF ?Toggle3D
  IF MainWin$?Toggle3D{PROP:text} = 'Turn off 3D Look'      !If on
    SET3DLOOK(0)                                           !Turn off
    MainWin$?Toggle3D{PROP:text} = 'Turn on 3D Look'      !and change text
  ELSE
    SET3DLOOK(1)                                           !Else
    MainWin$?Toggle3D{PROP:text} = 'Turn off 3D Look'      !Turn on
    MainWin$?Toggle3D{PROP:text} = 'Turn off 3D Look'      ! and change text
  END
OF ?OpenFile
  START(OpenFileProc)
OF ?MainExit
  BREAK
END
END
CLOSE(MainWin)

```

## SETCLIPBOARD (set windows clipboard contents)

SETCLIPBOARD( *string* )

---

**SETCLIPBOARD** Puts information in the Windows clipboard.

*string* A string constant or variable containing the information to place in the Windows clipboard. This should not contain any embedded null characters (ASCII 0). This is placed in the CF\_TEXT format, only.

The **SETCLIPBOARD** procedure places the contents of the *string* into the Windows clipboard, overwriting any previous contents.

**Example:**

```
Que1 QUEUE
    STRING(30)
    END
Que2 QUEUE
    STRING(30)
    END
WinOne WINDOW,AT(0,0,160,400)
    LIST,AT(120,0,20,20),USE(?List1),FROM(Que1),DRAGID('List1')
        !Allows drags, but not drops
    LIST,AT(120,120,20,20),USE(?List2),FROM(Que2),DROPID('List1')
        !Allows drops from List1, but no drags
    END
CODE
OPEN(WinOne)
ACCEPT
CASE EVENT()
OF EVENT:Drag
    IF DRAGID()
        SETCLIPBOARD(Que1)
    END
    !When a drag event is attempted
    !check for success
    !and setup info to pass
OF EVENT:Drop
    Que2 = CLIPBOARD()
    ADD(Que2)
    !When drop event is successful
    !get dropped info
    !and add it to the queue
END
END
```

**See Also:**

CLIPBOARD

PROP:ClipBits

## SETCLOCK (set system time)

**SETCLOCK**(*time*)

---

**SETCLOCK**    Sets the DOS system clock.

*time*            A numeric constant, variable, or expression for a standard time (expressed as hundredths of a second since midnight, plus one).

The **SETCLOCK** statement sets the operating system time of day.

**Example:**

```
SETCLOCK(1)            !Set clock to midnight
SETCLOCK(6001)        !Set clock to one minute past midnight
```

**See Also:**

Standard Time

CLOCK

## SETCOMMAND (set command line parameters)

**SETCOMMAND**(*commandline*)

---

**SETCOMMAND** Internally sets command line parameters.

*commandline*      A string constant, variable, or expression containing the new command line parameters.

**SETCOMMAND** allows the program to internally specify command line parameters that may be read by the COMMAND procedure. SETCOMMAND overwrites any previous command line flag of the same value. To turn off a leading slash flag, append an equal sign (=) to it in the *commandline*.

SETCOMMAND may not be used to set system level switches which must be specified when the program is loaded. The temporary files directory switch (CLATMP=) may be set with SETCOMMAND.

**Example:**

```
SETCOMMAND(' /N')      !Add /N parameter
SETCOMMAND(' /N=')     !Turn off /N parameter
```

**See Also:**

COMMAND

## SETCURSOR (set temporary mouse cursor)

**SETCURSOR**( *cursor* )

**SETCURSOR** Specifies a temporary mouse cursor to display.

*cursor* An EQUATE naming a Windows-standard mouse cursor, or a string constant naming a cursor resource linked into the project--the name of a .CUR file with a leading tilde ('~Mycur.CUR'). If omitted, turns off the temporary cursor.

The **SETCURSOR** statement specifies a temporary mouse *cursor* to display until a SETCURSOR statement without a *cursor* parameter turns it off. This cursor overrides all CURSOR attributes. When SETCURSOR without a *cursor* parameter is encountered, all CURSOR attributes once again take effect. SETCURSOR is generally used to display the hourglass while your program is doing some "behind the scenes" work that the user should not break into.

EQUATE statements for the Windows-standard mouse cursors are contained in the EQUATES.CLW file. The following list is a representative sample of these (see EQUATES.CLW for the complete list):

CURSOR:None	No mouse cursor
CURSOR:Arrow	Normal windows arrow cursor
CURSOR:IBeam	Capital "I" like a steel I-beam
CURSOR:Wait	Hourglass
CURSOR:Cross	Large plus sign
CURSOR:UpArrow	Vertical arrow
CURSOR:Size	Four-headed arrow
CURSOR:Icon	Box within a box
CURSOR:SizeNWSE	Double-headed arrow slanting left
CURSOR:SizeNESW	Double-headed arrow slanting right
CURSOR:SizeWE	Double-headed horizontal arrow
CURSOR:SizeNS	Double-headed vertical arrow

**Example:**

```
MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS,HVSCROLL
    MENUBAR
        ITEM('Batch Update'),USE(?Batch)
    END
END

CODE
OPEN(MainWin)
ACCEPT
CASE ACCEPTED()
OF ?Batch
    SETCURSOR(CURSOR:Wait)    !Turn on hourglass mouse cursor
    BatchUpdate              !and call the batch update procedure
    SETCURSOR                !then turn off hourglass
END
END
```



## SETDROPID (set DROPID return string)



**SETDROPID**( *string* )

**SETDROPID** Sets the DROPID procedure's return value.

*string* A string constant or variable containing the value the DROPID procedure will return.

The **SETDROPID** procedure sets the DROPID procedure's return value. This allows the DROPID procedure to pass the data in a drag-and-drop operation. When drag-and-drop operations are performed between separate Clarion applications, this is the mechanism to use to pass the data.

### Example:

```

Que1 QUEUE
    STRING(30)
END
Que2 QUEUE
    STRING(30)
END

WinOne WINDOW,AT(0,0,160,400)
    LIST,AT(120,0,20,20),USE(?List1),FROM(Que1),DRAGID('List1')
        !Allows drags, but not drops
    LIST,AT(120,120,20,20),USE(?List2),FROM(Que2),DROPID('List1')
        !Allows drops from List1 or the Windows File Manager,
        !but no drags
END

CODE
OPEN(WinOne)
ACCEPT
CASE EVENT()
OF EVENT:Drag      !When a drag event is attempted
    IF DRAGID()     !check for success
        SETDROPID(Que1) !and setup info to pass
    END
OF EVENT:Drop      !When drop event is successful
    Que2 = DROPID() !get dropped info, from List1 or File Manager
    ADD(Que2)       !and add it to the queue
END
END

```

### See Also:

DRAGID

DROPID

## SETFONT (specify font)

```
SETFONT( control , [ typeface ] , [ size ] , [ color ] , [ style ] , [ charset ] )  
SETFONT( window , [ typeface ] , [ size ] , [ color ] , [ style ] , [ charset ] )
```

---

<b>SETFONT</b>	Dynamically sets the display font for a control or window.
<i>control</i>	A field number or field equate label for the control to affect. If <i>control</i> is zero (0), it specifies the WINDOW.
<i>window</i>	Label of a WINDOW, APPLICATION or REPORT structure, or a value of the reference variable of the type &WINDOW, or a procedure parameter of the type WINDOW, or a built-in TARGET variable.
<i>typeface</i>	A string constant or variable containing the name of the font. If omitted, the system font is used.
<i>size</i>	An integer constant or variable containing the size (in points) of the font. If omitted, the system default font size is used.
<i>color</i>	A LONG integer constant or variable containing the red, green, and blue values for the color of the font in the low-order three bytes, or an EQUATE for a standard Windows color value. If omitted, black is used.
<i>style</i>	An integer constant, constant expression, EQUATE, or variable specifying the strike weight and style of the font. If omitted, the weight is normal.
<i>charset</i>	A LONG integer variable specifying the character set value.

**SETFONT** dynamically specifies the display font for the *control*, overriding any FONT attribute. If the *control* parameter is zero (0), SETFONT specifies the default font for the window. However, this does not affect existing controls—only controls CREATED after SETFONT executes are affected.

SETFONT allows you to specify all parameters of a font change at once, instead of one at a time as runtime property assignment allows. This has the advantage of implementing all changes at once, whereas runtime property assignment would change each individually, displaying each separate change as it occurs.

The *typeface* may name any font registered in the Windows system. The EQUATES.CLW file contains EQUATE values for standard *style* values. A *style* on the range zero (0) to one thousand (1000) specifies the strike weight of the font. You may also add values that indicate italic, underline, or strikeout text. The following EQUATES are in EQUATES.CLW:

FONT:thin	EQUATE (100)
FONT:regular	EQUATE (400)
FONT:bold	EQUATE (700)
FONT:italic	EQUATE (01000H)

FONT:underline        EQUATE (02000H)

FONT:strikeout       EQUATE (04000H)

When *window* is used as the first parameter, it allows you to change the window or report font both before *and* after opening them. If this form of SETFONT is called before a window or report opening, the FONT attribute in the window or report declaration is ignored COMPLETELY. Calling SETFONT before a window or report is opened needs to provide all of required aspects of the designated font, because all font settings in the window or report declaration are ignored rather than merged with the values given in the call to SETFONT.

Calling the SETFONT function with the *window* parameter after a window or report is opened is equivalent to the SETFONT(0,...) form with the *control* as the first parameter, with the exception that the opened window or report cannot be the current target. In addition a window or report that is not opened can not be the value of the built-in TARGET variable. So, the call

### SETFONT (TARGET, ...)

is changing the font settings of the active window in the current thread. If there are no active windows in the current thread, it is implicitly applied to the MDI frame window (if it exists), or simply ignored otherwise.

#### Example:

```
SETFONT(1, 'Arial', 14, , FONT:thin+FONT:Italic)        ! 14 pt. Arial black thin italic
SETFONT(QuickWindow, 'Arial', 14, , FONT:thin+FONT:Italic) ! 14 pt. Arial black thin italic
                                                          ! for the entire window
```

#### See Also:

GETFONT , FONTDIALOG, FONTDIALOGA , FONT(set default font)

## SETKEYCHAR (specify ASCII code)

**SETKEYCHAR**(*keychar*)

---

**SETKEYCHAR** Sets the ASCII character returned by the KEYCHAR procedure.

*keychar*            An integer constant, variable, or expression containing the ASCII value of the character to set.

**SETKEYCHAR** sets the internal ASCII character returned by the KEYCHAR procedure. The character is not put into the keyboard buffer.

**Example:**

```
SETKEYCHAR(VAL('A'))        !Set up the keychar procedure to return 'A'
```

**See Also:**

KEYCHAR

## SETKEYCODE (specify keycode)

**SETKEYCODE**(*keycode*)

---

**SETKEYCODE** Sets the keycode returned by the KEYCODE procedure.

*keycode*            An integer constant or keycode EQUATE label.

**SETKEYCODE** sets the internal keycode returned by the KEYCODE procedure. The keycode is not put into the keyboard buffer.

**Example:**

```
SETKEYCODE(0800h)        !Set up the keycode procedure to return 0800h
```

**See Also:**

KEYCODE

Keycode Equate Labels

Keycode Equates List

## SETLAYOUT (set window orientation)



**SETLAYOUT**( *window* , *layout* )

---

**SETLAYOUT** Dynamically sets the window or report orientation.

*window*            Label of a WINDOW, APPLICATION or REPORT structure, or a value of the reference variable of the type &WINDOW, or a procedure parameter of the type WINDOW, or a built-in TARGET variable.

*layout*            A BYTE value or variable that specifies the *window* orientation. Zero (0) sets a left-to-right layout and one (1) sets a right-to-left layout.

**SETLAYOUT** is valid for WINDOWS and REPORTs only. It allows you to change the window or report layout both before *and* after opening them.

SETLAYOUT is equivalent to `window{PROP:Layout}=n` but is a little more efficient. Windows or reports that are not opened cannot be used as a value of the built-in TARGET variable. So, the call:

SETLAYOUT (TARGET, n)

will ONLY change the layout of the active opened *window* in the current thread. If there are no active *windows* in the current thread ,it is implicitly applied to the MDI frame window (if it exists), or simply ignored otherwise.

**Example:**

```
SETLAYOUT (QuickWindow,1)            !Set up right-to-left orientation
```

**See Also:**

LAYOUT

## SETNULL (set file field null)



**SETNULL**(*field*)  
**SETNULL**(*file*, *field*)

---

**SETNULL**      Assigns null "value" to a *field*.

*field*            The label (including prefix) of a field in a FILE structure. This may be a GROUP or RECORD structure.

*file*             The label of a FILE.

The **SETNULL** statement assigns a null "value" to a *field* in a FILE structure. If the *field* is a GROUP or RECORD structure, all component fields are set to null. Support for null "values" in a FILE is entirely dependent upon the file driver. The file must be opened before this statement is applied.

You can now pass a file as the first parameter to **SETNULL**. This allows you to pass references to fields (see the example below).

**Example:**

```
Customer FILE, DRIVER('Clarion'), PRE(Cus) !Declare customer file layout
AcctKey   KEY(Cus:AcctNumber)
Record    RECORD
AcctNumber LONG
OrderNumber LONG
Name      STRING(20)
Addr      STRING(20)
CSZ       STRING(35)
          END
          END

Header    FILE, DRIVER('Clarion'), PRE(Hea) !Declare header file layout
AcctKey   KEY(Hea:AcctNumber)
OrderKey  KEY(Hea:OrderNumber)
Record    RECORD
AcctNumber LONG
OrderNumber LONG
ShipToName STRING(20)
ShipToAddr STRING(20)
ShipToCSZ STRING(35)
          END
          END

CODE
OPEN(Header)
OPEN(Customer)
SET(Hea:AcctKey)
LOOP
  NEXT(Header)
  IF ERRORCODE()
    BREAK
  END
  Cus:AcctNumber = Hea:AcctNumber
  GET(Customer, Cus:AcctKey) !Get Customer record
  IF ERRORCODE()
    CLEAR(Cus:Record)
  END
  IF NOT NULL(Hea:ShipToName) AND Hea:ShipToName = Cus:Name !Check ship-to address
    SETNULL(Hea:ShipToName) !and assign null "values"
    SETNULL(Hea:ShipToAddr) ! to ship-to address
    SETNULL(Hea:ShipToCSZ)
  END
  PUT(Header) !Put Header record back
END

!Example Two - Use of file parameter
SwapNullState PROCEDURE(File F, ANY var)
CODE
  IF NULL(f, var)
    SETNONNULL(f, var)
  ELSE
    SETNULL(f, var)
  END
```

**See Also:** NULL, SETNONNULL, GETNULLS, SETNULLS



## SETNULLS(set the null state of columns)



**SETNULLS**(*table*, *null-value*)

**SETNULLS** Set NULL state of columns in a table.

*table* The label of a FILE.

*null-value* Null "value" to assign to the table.

**SETNULLS** sets the NULL state of every column in the table based on the contents of the passed string. The passed string must be obtained from a prior call to GETNULLS. This function is valid on all SQL table types.

### Errors Posted:

75 Invalid Column Type Descriptor – Indicating that the passed string was too small.

80 Function Not Supported

### Example:

```
StorageString STRING(255)
Rec           STRING(2048)

CODE
StorageString = GETNULLS(table)  !Get NULL state of table
Rec = table.record              !Save record buffer
! Do Table Processing
Table.Record = Rec              !Restore record buffer
SETNULLS(table, StorageString)  !Set NULL state of table columns
```

### See Also:

GETNULLS

NULL

SETNONULL

## SETPATH (change current drive and directory)

**SETPATH**(*path*)

---

**SETPATH**      Changes the current drive and directory.

*path*            A string constant or the label of a STRING, CSTRING, or PSTRING variable containing a new drive and/or directory specification.

**SETPATH** changes the current drive and directory. If the *drive and path* entry is invalid, the "Path Not Found" error is posted, and the current directory is not changed.

If the drive letter and colon are omitted from the *path*, the current drive is assumed. If only a drive letter and colon are in the *path*, SETPATH changes to the current directory of that drive.

**Errors Posted:**

03    Path Not Found

**Example:**

```
SETPATH('C:\LEDGER')      !Change to the ledger directory
SETPATH(UserPath)        !Change to the user's directory
```

**See Also:**

PATH

SHORTPATH

LONGPATH

DIRECTORY

FILEDIALOG

## SETPENCOLOR (set line draw color)

**SETPENCOLOR**( *color* )

**SETPENCOLOR** Sets the current pen color.

*Color* A LONG integer constant, constant EQUATE, or variable containing the red, green, and blue components that create the color in the three low-order bytes (bytes 0, 1, and 2) or an EQUATE for a standard Windows color value. If omitted, the Windows system color for window text is set.

The **SETPENCOLOR** procedure sets the current pen color for use by all graphics procedures. The default color is the Windows system color for window text. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

Every window has its own current pen color. Therefore, to consistently use the same pen (which does not use the default color setting) across multiple windows, the SETPENCOLOR statement should be issued for each window.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !window controls
END

CODE
OPEN(MDIChild)
SETPENCOLOR(000000FFh)      !Set blue pen color
ROUNDBOX(100,50,100,50,00FF0000h) !Red round-cornered box with blue border
```

**See Also:**

PENCOLOR

## SETPENWIDTH (set line draw thickness)

**SETPENWIDTH**( [*width*] )

---

**SETPENWIDTH** Sets the current pen width.

*Width* An integer expression that specifies the pen's thickness, measured in dialog units (unless overridden by the THOUS, MM, or POINTS attribute on a REPORT). If omitted, the default (one pixel) is set.

The **SETPENWIDTH** procedure sets the current line draw thickness for use by all graphics procedures. The default is one pixel, which may be set with a *width* of zero (0). This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

Every window has its own current pen width. Therefore, to consistently use the same pen (which does not use the default width setting) across multiple windows, the SETPENWIDTH statement should be issued for each window.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !window controls
END

CODE
OPEN(MDIChild)
SETPENCOLOR(000000FFh)      !Set blue pen color
SETPENSTYLE(PEN:dash)       !Set dashes for line style
SETPENWIDTH(2)              !Set two dialog unit thickness
BOX(100,50,100,50,00FF0000h) !Red box with thick blue dashed border
```

**See Also:**

PENWIDTH

## SETPOSITION (specify new control position)



```
SETPOSITION([ control [, x ] [, y ] [, width ] [, height ] )
            | target |
```

**SETPOSITION** Dynamically specifies the position and size of an APPLICATION, WINDOW, REPORT, or control.

<i>control</i>	A field number or field equate label for the control to affect. If <i>control</i> is zero (0), it specifies the window.
<i>target</i>	The label of an APPLICATION, WINDOW, or REPORT structure, or a reference to any of those structures.
<i>x</i>	An integer constant, expression, or variable that specifies the horizontal position of the top left corner. If omitted, the <i>x</i> position is not changed.
<i>y</i>	An integer constant, expression, or variable that specifies the vertical position of the top left corner. If omitted, the <i>y</i> position is not changed.
<i>width</i>	An integer constant, expression, or variable that specifies the width. If omitted, the <i>width</i> is not changed.
<i>height</i>	An integer constant, expression, or variable that specifies the height. If omitted, the <i>height</i> is not changed.

**SETPOSITION** dynamically specifies the position and size of an APPLICATION, WINDOW, REPORT, or control. If any parameter is omitted, the value is not changed. The *window* parameter is used to set the position and/or dimensions of a window that currently is not on top or has focus.

The values contained in the *x*, *y*, *width*, and *height* parameters are measured in dialog units. Dialog units are defined as one-quarter the average character width by one-eighth the average character height. The size of a dialog unit is dependent upon the size of the default font for the window. This measurement is based on the font specified in the FONT attribute of the window, or the system default font specified by Windows.

Using SETPOSITION produces a "smoother" control appearance change than using property expressions to change the AT attribute's parameter values. This is because SETPOSITION changes all four parameters at once. Property expressions must change one parameter at a time. Since each individual parameter change would be immediately visible on screen, this would cause the control to appear to "jump."

### Example:

```
CREATE (?Code4Entry,CREATE:entry,?Ctl:Code) !Create a control
?Code4Entry{PROP:use} = 'Code4Entry'        !Set USE variable
?Code4Entry{PROP:text} = '@s10'              !Set entry picture
GETPOSITION (?Ctl:Code,X,Y,Width,Height)     !Get Ctl:Code position
SETPOSITION (?Code4Entry,X+Width+40,Y)       !Set x 40 past Ctl:Code
UNHIDE (?Code4Entry)                         !Display the new control
```

## SETTARGET (set current window or report)



```
SETTARGET ( [ target ] )  
  
          | , thread |  
  
          | target , band |
```

---

**SETTARGET** Sets the current window (or report) for drawing graphics and other window-interaction statements.

*target* The label of an APPLICATION, WINDOW, or REPORT structure, or a reference to any of those structures. The execution *thread* is always deduced from the *target* and any specified *thread* parameter is ignored. If omitted, the last window opened and not yet closed in the specified *thread* is used.

*thread* The number of the execution thread whose topmost procedure contains the window to set as the *target*. If omitted, the execution *thread* is deduced from the *target*.

*band* The control number or field equate label of the REPORT band (or IMAGE control in a window *target*) to draw graphics primitives to (ARC, CHORD, etc.).

**SETTARGET** sets the current *target* for runtime property assignment, and the CREATE, SETPOSITION, GETPOSITION, SETFONT, GETFONT, DISABLE, HIDE, CONTENTS, DISPLAY, ERASE, and UPDATE statements. Using these statements with SETTARGET allows you to manipulate the window display in the topmost window of any execution thread. SETTARGET also specifies the *target* structure for drawing with the graphics primitives procedures (ARC, CHORD, etc.).

SETTARGET sets the "built-in" variable TARGET (also set when a window opens), which may be used in any statement which requires the label of the current window or report. SETTARGET does not change procedures, and does not change which ACCEPT loop receives the events generated by Windows. SETTARGET without any parameters resets to the procedure and execution thread with the currently active ACCEPT loop.

A REPORT structure is never the default TARGET. Therefore, SETTARGET must be used before using the graphics primitives procedures to draw graphics on a REPORT. To draw graphics to a specific band in the REPORT (or onto an IMAGE in a window), you must specify the *band* as the second parameter.

SETTARGET	Resets TARGET to the topmost window in the execution thread with the currently active ACCEPT loop.
-----------	--

SETTARGET( <i>target</i> )	Sets TARGET to the specified window or report. The execution <i>thread</i> is deduced from the <i>target</i> .
SETTARGET( <i>target,thread</i> )	Sets TARGET to the specified window or report. The execution <i>thread</i> is deduced from the <i>target</i> parameter and any specified <i>thread</i> parameter is ignored.
SETTARGET( , <i>thread</i> )	Sets TARGET to the topmost window in the specified execution <i>thread</i> .
SETTARGET( <i>target,band</i> )	Sets TARGET to the specified <i>target</i> window or report, and draws graphics primitives to the specified <i>band</i> (report band or IMAGE control).

**Example:**

```

Report  REPORT
        HEADER,USE (?PageHeader)
        END
Detail  DETAIL
        END
        END
CODE
OPEN(Report)
SETTARGET(Report,?PageHeader)  !Make the report the current target
TARGET{PROP:Landscape} = 1    !and turn on landscape mode
ARC(100,50,100,50,0,900)      !Draw 90 degree arc from 3 to 12 o'clock, as
                              !the top-right quadrant of ellipse
                              !to the page HEADER band

SETTARGET                      !Reset to top window

```

**See Also:**    **START** , **THREAD NOTIFY**

## SHORTPATH (return short filename)

**SHORTPATH**( [ *longfilename* ] )

---

**SHORTPATH** Returns the fully-qualified short filename for a given long filename.

*longfilename* A string constant, variable, or expression that specifies the long filename to convert. This may include the complete path. If omitted, **SHORTPATH** returns the current drive and directory in short name form.

The **SHORTPATH** procedure returns the DOS standard short filename for a given *longfilename*. The file named as the parameter must exist on disk. **SHORTPATH** can now be used in expressions evaluated by the **EVALUATE** statements in runtime applications and in the templates.

**Note:**

If the 8.3 Name Creation on NTFS Partitions is disabled, **SHORTPATH** and **PATH** are equivalent.

**Return Data Type:** STRING

**Example:**

```
MyFile STRING(64)
CODE
MyFile = SHORTPATH('c:\program files\my text file.txt') !c:\progra~1\mytext~1.txt
```

**See Also:**

SETPATH

LONGPATH

PATH

DIRECTORY

FILEDIALOG



## SHOW (write to screen)



**SHOW**( *x* , *y* , *string* )

---

<b>SHOW</b>	Writes a <i>string</i> to the current window or report.
<i>x</i>	An integer expression that specifies the horizontal position of the starting point, in dialog units.
<i>y</i>	An integer expression that specifies the vertical position of the starting point, in dialog units.
<i>string</i>	A string constant, variable, or expression containing the formatted text to place on the current window or report.

**SHOW** writes the *string* text to the current window or report. The font used is the current font for the window or report.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !window controls
END

CODE
OPEN(MDIChild)
DISPLAY
SHOW(100,100,FORMAT(TODAY(),@D3))      !Display the date
SHOW(20,20,'Press Any Key to Continue') !Display a message
```

**See Also:**

Current Target

## SHUTDOWN (arm termination procedure)

**SHUTDOWN**(*[procedure]*)

---

**SHUTDOWN**    Arms a procedure which is called when the program terminates.

*procedure*        The label of a PROCEDURE. If omitted, the **SHUTDOWN** process is disarmed.

The **SHUTDOWN** statement arms a *procedure* which is called when the program terminates. The shutdown *procedure* is called by normal program termination or by an abnormal-end/run-time halt. It may not be able to execute for an abnormal-end/run-time halt, depending upon the state of the system resources at the time of the crash. It is not called if the computer is rebooted or the program is terminated due to power failure. The same effect as SHUTDOWN can be more safely achieved by simply calling a procedure to execute on EVENT:CloseDown for the application frame.

**Example:**

```
SHUTDOWN(CloseSys)            !Arm CloseSys as the shutdown procedure
```

**See Also:**

HALT

RETURN

## SIN (return sine)

**SIN**(*radians*)

**SIN** Returns sine.

*radians* A numeric constant, variable or expression for the angle expressed in radians.  $\pi$  is a constant which represents the ratio of the circumference and radius of a circle. There are  $2\pi$  radians (or 360 degrees) in a circle.

The **SIN** procedure returns the trigonometric sine of an angle measured in *radians*. The sine is the ratio of the length of the angle's opposite side divided by the length of the hypotenuse.

**Return Data Type:** REAL

**Example:**

```
PI           EQUATE (3.1415926535898)      !The value of PI
Rad2Deg      EQUATE (57.295779513082)      !Number of degrees in a radian
Deg2Rad      EQUATE (0.0174532925199)      !Number of radians in a degree
CODE
Angle = 45 * Deg2Rad                      !Translate 45 degrees to Radians
SineAngle = SIN(Angle)                    !Get the sine of 45 degree angle
```

**See Also:**

TAN

ATAN

ASIN

COS

ACOS

## SORT (sort queue entries)

```
SORT( queue,      | [+]key,...,[-]key )  
                        | name  
                        | function
```

---

**SORT** Reorders entries in a QUEUE.

*queue* The label of a QUEUE structure, or the label of a passed QUEUE parameter.

**+ -** The leading plus or minus sign specifies the *key* will be sorted in ascending or descending sequence.

*key* The label of a field declared within the QUEUE structure. If the QUEUE has a PRE attribute, the *key* must include the prefix. This may not be a reference variable.

*name* A string constant, variable, or expression containing the NAME attribute of QUEUE fields, separated by commas, and optional leading + or - signs for each attribute. This parameter is case sensitive and may not contain any reference variables.

*function* The label of the function containing two parameters of a \*GROUP or named GROUP passed by address, and having a SIGNED return value. Both parameters must use the same parameter type, and cannot be omitted. The RAW, C and PASCAL attributes are not permitted in the prototype declaration. See Additional Queue Considerations.

**SORT** reorders the entries in a QUEUE. QUEUE entries with identical key values maintain their relative position.

SORT(*queue*,*key*) Reorders the QUEUE in the sequence specified by the *key*. Multiple *key* parameters may be used (up to 16), separated by commas, with optional leading plus or minus signs to indicate ascending or descending sequence.

SORT(*queue*,*name*) Reorders the QUEUE in the sequence specified by the *name* string. The *name* string must contain the NAME attributes of the fields, separated by commas, with leading plus or minus signs to indicate ascending or descending sequence.

### Errors Posted:

08 Insufficient Memory

75 Invalid Field Type Descriptor

**Example:**

```

Location  QUEUE,PRE(Loc)
Name      STRING(20),NAME('FirstField')
City      STRING(10),NAME('SecondField')
State     STRING(2)
Zip       DECIMAL(5,0)
          END

CODE
  SORT(Location,Loc:State,Loc:City,Loc:Zip)      !Sort by zip in city in state
  SORT(Location,+Loc:State,-Loc:Zip)             !Sort descending by zip in state
  SORT(Location,'FirstField,-SecondField')      !Sort descending by city in name
  *****
!Example of using SORT with a FUNCTION as a parameter
PROGRAM
MAP
  CaseInsensitive(*GROUP A, *GROUP B),SIGNED
end

Q        QUEUE
Val      STRING(5)
          END

Window WINDOW('Test Sort'),AT(,,116,224),FONT('MS SansSerif',8,,FONT:regular),I
MM,SYSTEM,GRAY,AUTO
  BUTTON('Sort Case Sensitive'),AT(8,3,95,14),USE(?SortCase),LEFT,DEFAULT
  BUTTON('Sort Case INSensitive'),AT(8,20,95,14),USE(?SortNoCase),LEFT
  LIST,AT(6,37,101,179),USE(?List1),FORMAT('7L(2)|M~Val~@s5@'),FROM(Q)
  END

CODE
Q.Val = 'aaaaa'; Add(Q)
Q.Val = 'AAAAA'; Add(Q)
Q.Val = 'ddddd'; Add(Q)
Q.Val = 'DDDDD'; Add(Q)
Q.Val = 'EEEEEE'; Add(Q)
Q.Val = 'EEEEEE'; Add(Q)
Q.Val = 'qqqqq'; Add(Q)
Q.Val = 'QQQQQ'; Add(Q)
Q.Val = 'zzzzz'; Add(Q)
Q.Val = 'ZZZZZ'; Add(Q)
Q.Val = 'ggggg'; Add(Q)
Q.Val = 'GGGGG'; Add(Q)

OPEN(Window)
ACCEPT
  CASE ACCEPTED()
    OF ?SortCase ; SORT(Q, Q.Val)
    OF ?SortNoCase ; SORT(Q, CaseInsensitive)
  END
END

CaseInsensitive PROCEDURE(*GROUP A, *GROUP B)!,SIGNED

CODE
IF UPPER(A) = UPPER(B) THEN RETURN 0
ELIF UPPER(A) > UPPER(B) THEN RETURN 1
ELSE RETURN -1
END

```

See Also: ADD, GET, PUT

## SQL (use SQL code)

**SQL**(*sql expression*)

---

**SQL** Specifies a proper SQL expression to be used to affect the records in a VIEW.

*sql expression* A string expression containing valid SQL code.

**SQL** specifies a valid SQL statement which is applied to a FILTER, ORDER, JOIN, PROP:FILTER, PROP:ORDER, or PROP:JOINEXPRESSION surrounding it. Anything specified in the *sql expression* is treated as pure SQL code.

**Tip**

With the SQL statement, you can now use native SQL code as filter criteria from within the IDE template interface. Example: In the Record Filter prompt, enter SQL('your SQL filter code').

When you are using the SQL statement with a view you need to be aware of how the SELECT statement is generated. By default, the view engine puts an SQL alias on each file in a VIEW. The SQL driver generates an SQL statement which uses an Alias of "A" for the first file in the View, "B" for the second etc. If you wish to use SQL, your filter has to be compatible with the previously generated SQL statement – i.e., you need use A/B/etc as the file prefixes. If necessary, you can use PROP:Alias to change this behavior. Using the default configuration the following SQL() commands in a filter are illegal, and must be aliased prior to opening the VIEW:

```
SQL(dbo.Employees.EmployeeID > 0)
```

```
! Illegal - a period is not a valid character in an alias label
```

```
SQL(Employees.EmployeeID > 0)
```

```
! Use Employee{PROP:Alias} = '' or Employee{PROP:Alias} = 'Employees' prior to opening VIEW
```

```
SQL(Emp2:EmployeeID > 0) !This is not a valid SQL statement
```

Using the defaults and assuming EmployeeID is a field of the first table in the view, then these statements are legal

```
SQL(A.EmployeeID > 0)
```

```
SQL(EmployeeID > 0)
```

**Examples:**

```

OrdFile      FILE,DRIVER('ODBC'),PRE(Ord)
PrimaryKey   KEY(Ord:OrdID),PRIMARY
Record       RECORD
OrdID        LONG
Customer     LONG
PurchaseDate DATE
Info         CSTRING(61)
            END
            END

```

```

MyView VIEW(AFile), FILTER('Ord:PurchaseDate = TODAY() AND ' & |
    'SQL(A.Info LIKE "%Must deliver today%")'), ORDER('SQL(A.Customer)')
END

```

```

MyView{PROP:Filter} =
    'SQL(A.Customer IN (SELECT CustID FROM Customers WHERE BadCustomer = 0))'

```

```

!ABC template generated code:  SQL(ProductID > 5) entered on Record Filter line
BRW1.SetFilter('(SQL(ProductID > 5))')

```

!For the Clarion template chain, the generated code is:

```
BRW1::View:Browse{Prop:Filter} = 'SQL(ProductID > 5)'
```

!It is also valid to mix SQL and Clarion references on the Record Filter line

```
! SQL(SupplierID > 7)  AND  SQL(ProductID > 5)
```

!or

```
! Pro:SupplierID > 7  AND  SQL(ProductID > 5)  -  or these can be flipped as
```

```
! SQL(ProductID > 5) AND Pro:SupplierID > 7
```

## SQLCALLBACK (register or unregister a SQLCallbackInterface)



**SQLCALLBACK**(*entity*, *SQLCallbackInterface*, [*flag*])

---

**SQLCALLBACK**      Register or unregister a SQLCallbackInterface.

*entity*              The label of a FILE or VIEW.

*SQLCallbackInterface*    The label of the interface that implements the SQLCallbackInterface.  
The method of the SQLCallbackInterface (ExecutingCode) is called just before the SQL statement is passed to the SQL server for execution.

*flag*                An integer constant, variable, EQUATE, or expression that indicates whether or not to unregister an interface associated with a FILE or VIEW. A value of one (1 or TRUE) unregisters the interface. If omitted, the interface is registered with the *entity*.

The **SQLCallback** method registers a callback interface with the specified entity. The methods of the registered interface are called whenever a file operation is done. Multiple interfaces can be registered with an entity.

To unregister an interface, set the *flag* to TRUE. Any registered interfaces must be unregistered before the object that implements the interface is removed.

**Implementation:** This function is only supported by the SQL drivers.



**Example:**

PROGRAM

```

MAP
END
INCLUDE ('FILECB.INC'), ONCE

```

**!Data file**

```

People      FILE, DRIVER('TOPSPEED'), PRE(PEO), CREATE, BINDABLE, THREAD
KeyId       KEY(PEO:Id), NOCASE, OPT
KeyLastName KEY(PEO:LastName), DUP, NOCASE
Record      RECORD, PRE()
Id          LONG
FirstName   STRING(30)
LastName    STRING(30)
Gender      LONG
            END
            END

```

**!DataFile**

```

SQLFile     FILE, DRIVER('MSSQL'), OWNER('(local)', clarion, sa, ;'), NAME('sptesttable')
Record      RECORD
Id          LONG
            END
            END

```

**!LogFile**

```

LogFile     FILE, DRIVER('BASIC', '/ALWAYSQUOTE=OFF /COMMA=1,1'), CREATE, NAME('logfile.txt')
Record      RECORD
Operation   STRING(200)
            END
            END

```

**!FileCallback implementation**

```

FCB CLASS, IMPLEMENTS(FileCallBackInterface), IMPLEMENTS(SQLCallBackInterface)
END

```

CODE

CALLBACK(People, FCB.FileCallBackInterface)	!Register Interface
SQLCALLBACK(SQLFile, FCB.SQLCallBackInterface)	!Register Interface
CREATE(Logfile)	!Create log file
OPEN(Logfile)	!Open log file
OPEN(People)	!Open data file
SET(PEO:KeyId, PEO:KeyID)	!Set and
LOOP	!loop thru
NEXT(People)	!data until
IF ERRORCODE() THEN BREAK END	!end of file
END	
CLOSE(People)	!Close data file
SQLFile{PROP:SQL} = 'CREATE TABLE sptesttable (c INT)'	!Create SQL table
OPEN(SQLFile)	!Open SQL table
SQLFile.Id=5	
ADD(SQLFile)	!Update SQL table
SQLFile.Id=7	
ADD(SQLFile)	!Update SQL table
SQLFile.Id=8	
ADD(SQLFile)	!Update SQL table
CLOSE(SQLFile)	!Close SQL table
CALLBACK(People, FCB.FileCallBackInterface, TRUE)	!Unregister Interface
SQLCALLBACK(SQLFile, FCB.SQLCallBackInterface, TRUE)	!Unregister Interface

!This method is called prior to each operation of the data file. The log file is updated !with the file operation that is being executed.

FCB.FileCallBackInterface.FunctionCalled |

PROCEDURE(SIGNED opCode, \*Params Parameters, \*CSTRING ErrCode, \*CSTRING ErrMsg)

p LIKE(Params)

CODE

```
p = Parameters
CASE opCode
OF DriverOp:ADD
  logFile.Operation = 'ADD(f)'
OF DriverOp:APPEND
  logFile.Operation = 'APPEND(f)'
OF DriverOp:CLOSE
  logFile.Operation = 'CLOSE(f)'
OF DriverOp:COPY
  logFile.Operation = 'COPY(f, ''&CLIP(Parameters.Text)&'')'
OF DriverOp:CREATE
  logFile.Operation = 'CREATE(f)'
OF DriverOp:DELETE
  logFile.Operation = 'DELETE(f)'
OF DriverOp:NEXT
  logFile.Operation = 'NEXT(f)'
OF DriverOp:OPEN
  logFile.Operation = 'OPEN(f, '&Parameters.openMode&')'
OF DriverOp:PUT
  logFile.Operation = 'PUT(f)'
OF DriverOp:SETkeykey
  logFile.Operation = 'SET(k,k)'
END
ADD(logFile)
RETURN TRUE
```

!This method is called after each operation to the data file. This simply returns a TRUE !according to the rules of the FileCallBackInterface.

FCB.FileCallBackInterface.FunctionDone |

PROCEDURE(SIGNED opCode, Params Parameters, \*CSTRING ErrCode, \*CSTRING ErrMsg)

CODE

RETURN TRUE

!This method is called just before the SQL statement is passed to the SQL server for !execution

FCB.SQLCallBackInterface.ExecutingCode |

PROCEDURE(CONST \*CSTRING inStr, \*BYTE Err, \*CSTRING ErrCode, \*CSTRING ErrMsg)

CODE

Err = FALSE

RETURN inStrPUT\_re\_write\_record

## SQRT (return square root)

**SQRT**(*expression*)

---

**SQRT** Returns square root.

*expression* A numeric constant, variable, or expression. If the value of the expression is less than zero, the return value is zero.

The **SQRT** procedure returns the square root of the *expression*. If *X* represents any positive real number, the square root of *X* is a number that, when multiplied by itself, produces a product equal to *X*.

**Return Data Type:** REAL

**Example:**

```
Length = SQRT(X^2 + Y^2) !Find the distance from 0,0 to x,y (pythagorean theorem)
```

## START (return new execution thread)



**START**(*procedure* [, *stack*] [, *passed value*])

---


<b>START</b>	Begins a new execution thread.
<i>procedure</i>	The label of the first PROCEDURE to call on the new execution thread. This may not be an overloaded procedure.
<i>stack</i>	An integer constant or variable containing the size of the stack to allocate to the new execution thread. If omitted, the default stack is 20,000 bytes.
<i>passed value</i>	A string constant, variable, or expression containing the value to pass as a parameter to the <i>procedure</i> . There may be up to three <i>passed values</i> listed.

The **START** procedure begins a new execution thread, calling the *procedure* and returning the number assigned to the new thread. The returned thread number is used by procedures and built-in procedures whose action may be performed on any execution thread (e.g., SETTARGET). *The maximum number of simultaneously available execution threads in a single application is theoretically unlimited.* However, the word "unlimited" means that limits are applied not by the Clarion Runtime Library, but by the Operating System's environment settings, i.e., limited to the amount of virtual memory available for the process, or limited number of threads in the system, or limited number of windows (including controls) that can be opened simultaneously in the process, etc.

Code execution in the launching thread immediately continues with the next statement following the START and continues until an ACCEPT statement executes. Once the launching thread executes ACCEPT, the launched *procedure* begins executing its code in its new thread, retaining control until it executes an ACCEPT.

The *procedure* may be prototyped to receive up to three STRING or GROUP parameters (passed by value) which may not be omitted. The values to pass to the *procedure* are listed as the *passed values* parameters to the START statement, and not in a parameter list attached to the *procedure* within the START statement. The procedure may not be an overloaded procedure.

The first execution thread in any program is the main program code, which is always numbered one (1). Therefore, the lowest value START can return is two (2), when the first START procedure is executed in a program. START may return zero (0), which indicates failure to open the thread. This can occur by running out of memory, or by starting a thread when the system is modal.



The *stack* parameter has no meaning in the Clarion# environment and is ignored if present.

In Clarion#, the START function has the following form that supports the use of an arbitrary numbers of parameters:

**START**( *procedure*, *stack*, **PARAMS** *array*[ ] *arrayname*)

See PARAMS in the Clarion.NET documentation for more information.

Return Data Type: SIGNED

Example:

```
MAP
NewProc1  PROCEDURE
NewProc2  PROCEDURE (STRING)
NewProc3  PROCEDURE (STRING,STRING)
NewProc4  PROCEDURE (STRING,STRING,STRING)
END

MainWin APPLICATION('My Application'),SYSTEM,MAX,ICON('MyIcon.ICO'),STATUS |
,HVSCROLL,RESIZE
  MENUBAR
    MENU('&File'),USE(?FileMenu)
    ITEM('Selection &1...'),USE(?MenuSelection1)
    ITEM('Selection &2...'),USE(?MenuSelection2)
    ITEM('Selection &3...'),USE(?MenuSelection3)
    ITEM('Selection &4...'),USE(?MenuSelection4)
    ITEM('E&xit'),USE(?Exit)
  END
END
END

SaveThread1  LONG                !Declare thread number save variables
SaveThread2  LONG
SaveThread3  LONG
SaveThread4  LONG
GroupName    GROUP
F1           STRING(30)
F2           LONG
            END

CODE
OPEN(MainWin)                !Open the APPLICATION
ACCEPT
CASE ACCEPTED()
OF ?MenuSelection1
  !Start thread with 35K stack
  SaveThread1 = START(NewProc1,35000)
OF ?MenuSelection2
  !Start thread, passing 1 parm
  SaveThread2 = START(NewProc2,35000,GroupName)
OF ?MenuSelection3
  !Start thread, passing 2 parms
  SaveThread3 = START(NewProc3,35000,'X','21')
OF ?MenuSelection4
  !Start a new thread
  SaveThread4 = START(NewProc4,35000,'X','21',GroupName)
OF ?Exit
  RETURN
END
END

NewProc2  PROCEDURE(MyGroup)
LocalGroup  GROUP(GroupName)    !Declare local group same as passed group
            END

CODE
LocalGroup = MyGroup            !Get the passed data
```

See Also: ACCEPT, THREAD, SETTARGET, POST,

## STATUS (return file or window/report status)

**STATUS** (| *file* |  
| *window* |

---

**STATUS** Returns the passed file, window or report status.

*file* The label of a FILE statement.

*window* The label of a WINDOW, APPLICATION, or REPORT structure, or valid built-in variables TARGET, PRINTER, or SYSTEM.

The **STATUS** procedure returns zero (0) if the *file* is not open, and the *file's access mode* if it is open. If the *access mode* is actually zero (Read Only / Any Access), 40h (Read Only / Deny None) is returned (see OPEN).

**STATUS** can also be used to check the state of a WINDOW or REPORT structure. If the passed WINDOW or REPORT exists and is opened, **STATUS** returns zero (0). If the passed WINDOW or REPORT exists but either has not been opened or has been closed, **STATUS** returns one (1). If the passed parameter is not a valid WINDOW or REPORT structure, **STATUS** returns two (2).

To simplify testing of results returned from calls to **STATUS**(WINDOW), the following declarations have been added to EQUATES.CLW:

```
WINDOW:OK           EQUATE (0)
WINDOW:NotOpened    EQUATE (1)
WINDOW:BadWindow    EQUATE (2)
```

Built-in variables TARGET, PRINTER and SYSTEM can be passed as parameters to calls to STATUS(WINDOW). The function always returns WINDOW:OK if the actual parameter is PRINTER or SYSTEM.

**Return Data Type:** LONG

**Example:**

```

IF STATUS(DataFile) % 16 = 0      !Opened Read-Only?
    RETURN                      !get out
ELSE                             !Otherwise
    EXECUTE DiskAction          !Write record to disk
    ADD(DataFile)
    PUT(DataFile)
    DELETE(DataFile)
END
END

CASE STATUS(PassedLabel)         !Check parameter passed
OF WINDOW:OK                    !if window is good, and opened
    CYCLE                      !continue
OF WINDOW:NotOpened             !if window is good, but not opened
    OPEN(PassedLabel)          !open it
OF WINDOW:BadWindow             !bad window?
    MESSAGE('Invalid Window','Note:') !exit procedure
    RETURN
END

```

**See Also:**

OPEN

EXISTS

## STOP (suspend program execution)

**STOP**( [ *message* ] )

---

**STOP**                Suspends program execution and displays a message window.

*message*            An optional string expression (up to 64K) which displays in the error window.

**STOP** suspends program execution and displays a message window. It offers the user the option of continuing the program or exiting. When exiting, it closes all files and frees the allocated memory.

**Example:**

```
PswdScreen WINDOW
    STRING(' Please Enter the Password '),AT(5,5)
    ENTRY(@10),AT(20,5),USE(Password),PASSWORD
END

CODE
OPEN(PswdScreen)                !Open the password screen
ACCEPT                          !and get user input
CASE ACCEPTED
OF ?Password)
    IF Password <> 'PayMe$moRe'    !Correct password?
        STOP('Incorrect Password Entered -- Access Denied -- Retry?')
        X# += 1
    IF X# > 3                      !Let them try 3 times
        HALT(0,'Incorrect password') !then throw them out
    END
END
END
END
END
```

**See Also:**

HALT



## STREAM (enable operating system buffering)

**STREAM**(*file*)

**STREAM**        Disables automatic FILE flushing.

*file*            The label of a FILE.

Some file systems flush the operating system's buffers on each disk write keeping the file "logically closed" (for example, the Clarion and TopSpeed file drivers do this by default). The **STREAM** statement disables this automatic flushing operation. A STREAM operation is terminated by closing the file, which automatically flushes the buffers, or by issuing a FLUSH statement.

STREAM and FLUSH are inherently single-user, batch process type of statements, although you can use them in networked environments. In some file systems, STREAM and FLUSH are simply ignored when the file is opened for shared access while in others they execute but it is possible to create a "deadlock" situation between workstations for multiple file updates. LOGOUT accomplishes a similar purpose in multi-user environments and is much safer.

Support for this statement is dependent upon the file system and is described in its file driver's documentation.

### Example:

```

STREAM(History)            !Use DOS buffering
SET(Current)              !Set to top of current file
LOOP
  NEXT(Current)
  IF ERRORCODE() THEN BREAK END
  His:Record = Cur:Record
  ADD(History)
END
FLUSH(History)            !End streaming, flush buffers

```

### See Also:

FLUSH

LOGOUT

BUFFER

## STRPOS (return matching value position)

**STRPOS**( *first*, *second* [, *mode* ] )

<b>STRPOS</b>	Returns the starting position of a substring based on all parameters passed.
<i>first</i>	A string containing data to compare against the <i>second</i> parameter.
<i>second</i>	A string containing a regular expression to match the <i>first</i> parameter.
<i>mode</i>	An integer constant or equate which specifies if the comparison method is case sensitive. If FALSE (0), the method is case sensitive. If TRUE (1), the method is not case sensitive. The default value is case sensitive.

The **STRPOS** procedure returns the starting position where the first and second parameters match according to the comparison mode specified. The following mode value EQUATE, listed in EQUATES.CLW, is supported by STRPOS:

### Match:Regular

A match with the *first* parameter where the *second* parameter contains the regular expression. Repeated usage with the same regular expression value is optimized (to avoid re-compiling the expression).

### Regular Expression Operators

Regular expressions are used to describe patterns in text. The following characters are regular expression operators (or metacharacters) used to increase the power and versatility of regular expressions.

- ^**      C caret matches the beginning of the string. For example: `^@chapter` matches the "`@chapter`" at the beginning of a string.
- \$**      Dollar sign is similar to the caret, but it matches only at the end of a string. For example: `p$` matches a record that ends with a p.
- .**      Period matches any single character except a new line. For example: `.P` matches any single character followed by a P in a string. Using concatenation we can make regular expressions like ``U.A'`, which matches any three-character sequence that begins with ``U'` and ends with ``A'`.
- [...]**    This is called a character set. It matches any one of the characters that are enclosed in the square brackets. For example: `[mvx]` matches any one of the characters M, V, or X in a string. Ranges of characters are indicated by using a hyphen between the beginning and ending characters, and enclosing the whole thing in brackets. For example: `[0-9]` matches any digit. To match ``-'`, write it as ``---'`, which is a range containing only ``-'`. You may also give ``-'` as the first or last character in the set. To match ``^'`, put it anywhere except as the first character of a set. To match a ``j'`, make it the first character in the set. For example: `[j^d]` matches either ``j'`, ``d'` or ``^'`.

- [^ ...]** This is a complemented character set. The first character after the `[` must be a `^`. It matches any characters except those in the square brackets (or new line). For example: `[^0-9]` matches any character that is not a digit.
- |** Vertical bar is the alternation operator and it is used to specify alternatives. For example: `^P|[0-9]` matches any string that matches either `^P` or `[0-9]`. This means it matches any string that contains a digit or starts with P. The alternation applies to the largest possible regular expressions on either side.
- {...}** Parentheses are used for grouping in regular expressions as in arithmetic. They can be used to concatenate regular expressions containing the alternation operator, `|`.
- \*** Asterisk means that the preceding regular expression is to be repeated as many times as possible to find a match. For example: `ph*` applies the `*` symbol to the preceding `h` and looks for matches to one `p` followed by any number of `h`'s. This will also match just `p` if no `h`'s are present. The `*` repeats the smallest possible preceding expression (use parentheses if you wish to repeat a larger expression). It finds as many repetitions as possible. For example: `(c[ad][ad]*r x)` matches a string of the form `(car x)`, `(cdr x)`, `(cadr x)`, and so on.
- +** Plus sign is similar to `*`, but the preceding expression must be matched at least once. This means that: `wh+y` would match "why" and "whhy" but not "wy," whereas `wh*y` would match all three of these strings. This is a simpler way of writing the last `*` example: `(c[ad]+r x)`
- ?** Question mark is similar to `*`, but the preceding expression can be matched once or not at all. For example: `fe?a` will match `fed` and `fd`, but nothing else.
- \** Backslash is used to suppress the special meaning of a character when matching. For example: `\$` matches the character `$`.

In regular expressions, the `*`, `+`, and `?` operators have the highest precedence, followed by concatenation, and finally by `|`.

**Return Data Type:** LONG

#### Example:

```
ListHave1  STRING('IN,OH,KY,TN,PA')
ListHave2  STRING('WI,MN,IA,SD,ND')
StatesWanted STRING('NJ|NY|PA|DE')
CODE
X = STRPOS(ListHave1,StatesWanted,True)      !X = 13
Y = STRPOS(ListHave2,StatesWanted,True)      !Y = 0

X = STRPOS('Fireworks on the fourth', '{{4|Four}th', True) !X = 18
X = STRPOS('Fireworks on the fourth', '{{4|Four}th', False) !X = 0 Case sensitive
X = STRPOS('July 4th fireworks', '{{4|four}th', True)      !X = 6
```

**See Also:** MATCH

## SUB (return substring of string)

**SUB**(*string*,*position*,*length*)

---

**SUB** Returns a portion of a string.

*string* A string constant, variable or expression.

*position* A integer constant, variable, or expression. If positive, it points to a character position relative to the beginning of the *string*. If negative, it points to the character position relative to the end of the *string* (i.e., a *position* value of -3 points to a position 3 characters from the end of the *string*). If position is omitted or zero, the default in Clarion Win32 is 1.

In Clarion#, *position* uses a zero-based index. A value of zero (0) points to character position 1, 1 points to 2, etc.

*length* A numeric constant, variable, or expression of number of characters to return.

The **SUB** procedure parses out a sub-string from a *string* by returning *length* characters from the *string*, starting at *position*.

The SUB procedure is similar to the "string slicing" operation on STRING, CSTRING, and PSTRING variables. SUB is less flexible and efficient than string slicing, but SUB is "safer" because it ensures that the operation does not overflow the bounds of the *string*.

"String slicing" is more flexible than SUB because it may be used on both the destination and source sides of an assignment statement, while the SUB procedure can only be used as the source. It is more efficient because it takes less memory than individual character assignments or the SUB procedure (however, no bounds checking occurs).

To take a "slice" of a string, the beginning and ending character numbers are separated by a colon (:) and placed in the implicit array dimension position within the square brackets ([]) of the string. The position numbers may be integer constants, variables, or expressions. If variables are used, there must be at least one blank space between the variable name and the colon separating the beginning and ending number (to prevent PREFIX confusion).

**Return Data Type:** STRING

**Example:**

```
!SUB('ABCDEFGHI',1,1) returns 'A'
!SUB('ABCDEFGHI',-1,1) returns 'I'
!SUB('ABCDEFGHI',4,3) returns 'DEF'

!Get the file extension using SUB procedure
Extension = SUB(FileName,INSTRING('.',FileName,1,1)+1,3)

!The same operation using string slicing
Extension = FileName[(INSTRING('.',FileName,1,1)+1) : (INSTRING('.',FileName,1,1)+3)]

!*****

IF FILEDIALOG('Pick file',FileName)
```

```
IF SUB(FileName,1,2)='\\' THEN
    STOP('\\UNC paths are not supported!')
ELSIF UPPER(SUB(FileName,1,11))='C:\WINDOWS\' THEN
    STOP('Do not select Windows folder!')
END
END

IF FILEDIALOG('Pick file',FileName)
    CASE UPPER(SUB(CLIP(FileName),-4,4))  !Note CLIP(), else get trailing spaces
    OF '.TPS' ; DO TPS_File
    OF '.DBF' ; DO DBase_File
    OF '.CSV' ; DO Text_File
    ELSE
        Message('Unknown file type ' & RIGHT(FileName,4))
    END
END
END
```

**See Also:**

LEFT  
RIGHT  
INSTRING  
STRING  
CSTRING  
PSTRING  
String Slicing

## SUSPEND (suspend thread execution)

**SUSPEND**(*threadno*, *quietmode*)

---

**SUSPEND**      Suspend thread execution.

*threadno*      A numeric constant, variable, or expression that can be evaluated as a SIGNED integer.

*quietmode*      A numeric constant, variable, or expression that can be evaluated as a SIGNED integer.

The **SUSPEND** function suspends a thread specified by the *threadno* parameter. If the *threadno* parameter is a number of an active thread, its execution is suspended and a suspending counter is incremented. Each additional **SUSPEND** statement issued to the same active thread will increment the suspending counter by one. Therefore, a thread that has been suspended with a given number of **SUSPEND** statements can only resume thread execution when an equal number of RESUME statements has been executed.

The *quietmode* parameter controls the built-in messaging support provided by **SUSPEND**. If the *quietmode* parameter is set to TRUE (1), SUSPEND will not display a message if it has detected that the thread it is about to suspend is not safe. If the *quietmode* parameter is set to FALSE (0), a message will be displayed if the impending thread suspension is not safe.

SUSPEND returns TRUE (1) if a thread has been suspended and returns FALSE (0) if the thread could not be suspended.

Care should be taken with MDI programs using **SUSPEND**, as improper use can cause program lockups. All MDI child windows have an MDI client window as a parent, and the MDI client window can send rather than post messages to its child windows.

For example, calling the inter-thread SendMessage modal function (Windows API call) causes the calling thread (the MDI client window) to suspend activity until the called thread (the MDI Child window) returns from the call. If the called thread is suspended, we would have a program lockup.

Suspending a thread that is not already active is ignored.

**Return Data Type:**    SIGNED

**Example:**

```
!suspend thread execution number stored in variable
!Disable built-in messaging, use the one on next line
IF NOT SUSPEND(ThreadNumVariable,1)
    MESSAGE('Thread could not be suspended')
END
```

**See Also:**

RESUME

## TAN (return tangent)

**TAN**(*radians*)

**TAN** Returns tangent.

*radians* A numeric constant, variable or expression for the angle in radians.  $\pi$  is a constant which represents the ratio of the circumference and radius of a circle. There are  $2\pi$  radians (or 360 degrees) in a circle.

The **TAN** procedure returns the trigonometric tangent of an angle measured in *radians*. The tangent is the ratio of the angle's opposite side divided by its adjacent side.

**Return Data Type:** REAL

**Example:**

```
PI           EQUATE (3.1415926535898)      !The value of PI
Rad2Deg      EQUATE (57.295779513082)      !Number of degrees in a radian
Deg2Rad      EQUATE (0.0174532925199)      !Number of radians in a degree
CODE
Angle = 45 * Deg2Rad                      !Translate 45 degrees to Radians
TangentAngle = TAN(Angle)                 !Get the tangent of 45 degree angle
```

**See Also:**

ATAN

SIN

ASIN

COS

ACOS

## THREADLOCKED (returns current execution thread locked state)

THREADLOCKED()

---

The **THREADLOCKED** procedure returns the current execution thread's locked/unlocked state. It returns zero (0) if the thread is unlocked and one (1) if the thread is locked.

**Return Data Type:** SIGNED

**Example:**

<code>X# = THREADLOCKED()</code>	<code>!Returns 1</code>
<code>UNLOCKTHREAD</code>	<code>!Unlock the thread</code>
<code>X# = THREADLOCKED()</code>	<code>!Returns 0</code>
<code>MyLibraryCodeWithMessageLoop</code>	<code>!Call the code that has its own message loop</code>
<code>LOCKTHREAD</code>	<code>!Re-lock the thread</code>

**See Also:**

ACCEPT

LOCKTHREAD

UNLOCKTHREAD



## TIE(associate a string value to an ASTRING)

**TIE**([*stringtoken*] [,*index*] [,*value*])

**TIE** Associates a string value to an ASTRING.

*stringtoken* A string constant or the label of a previously declared ASTRING token.

*index* A numeric constant or variable defining the index value of an ASTRING. The index value may be any LONG value greater than zero.

*value* A numeric constant or variable. The value may be any LONG value greater than zero.

The **TIE** statement associates a *value* to a particular *stringtoken* and *index*. A unique index may be allocated at runtime by either omitting the index or setting it to zero. If the index is allocated at runtime, TIE will return the generated index number.

**Return Data Type:** LONG

**Example:**

```
PROGRAM
MAP
END

INCLUDE ('EQUATES.CLW')
COLOR    EQUATE(1)
SIDES    EQUATE(2)

AS1      ASTRING

CODE
AS1 = 'SHAPE'                !Declare ASTRING string token
TIE ('SHAPE',COLOR,COLOR:RED) !Associate COLOR:RED to COLOR for ASTRING SHAPE
TIE (AS1,SIDES,3)           !Associate 3 to SIDES for ASTRING SHAPE
IF TIED('SHAPE',SIDES) = 3 AND | !If the value associated to SIDES = 3
    TIED(AS1,COLOR) = COLOR:RED !and the value associated with COLOR=COLOR:RED
    MESSAGE('Shape is a red triangle')
END
```

**See Also:**

TIED

UNTIE

## TIED(retrieves a value associated with an ASTRING)

**TIED**(*stringtoken*, *index*)

---

**TIED**               Retrieves a string value that was previously associated to an ASTRING token.

*stringtoken*       A string constant or the label of a previously declared ASTRING token.

*index*             A numeric constant or variable defining the index value of an ASTRING. The index value may be any LONG value greater than zero.

The **TIED** statement retrieves the value that was previously associated to a particular ASTRING *stringtoken* and *index*. If a value is not TIED then 0 will be returned.

**Return Data Type:**   LONG

**Example:**

```
PROGRAM
MAP
END

INCLUDE ('EQUATES.CLW')
COLOR   EQUATE(1)
SIDES   EQUATE(2)

AS1      ASTRING

CODE
AS1 = 'SHAPE'
TIE('SHAPE',COLOR,COLOR:RED)
TIE(AS1,SIDES,3)
IF TIED('SHAPE',SIDES) = 3
  AND TIED(AS1,COLOR) = COLOR:RED
  MESSAGE('Shape is a red triangle')
END
```

**See Also:**

TIE

UNTIE

## TODAY (return system date)

TODAY()

---

The **TODAY** procedure returns the operating system date as a standard date. The range of possible dates is from January 1, 1801 (standard date 4) to December 31, 2099 (standard date 109,211).

**Return Data Type:** LONG

**Example:**

```
OrderDate = TODAY()    !Set the order date to system date
```

**See Also:**

Standard Date

DAY

MONTH

YEAR

SETTODAY

DATE

## TYPE (write string to screen)

**TYPE**(*string*)

---

**TYPE**                Writes a *string* to the current window or report.

*String*              A string constant, variable, or expression.

**TYPE** writes a *string* to the current window or report. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

The *string* appears on the window or report at the current cursor position, if there's room, if not, it appears on the next line. The font used is the current font for the window or report. The SHOW statement may be used to position the cursor before output from TYPE.

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    !window controls
END
CODE
OPEN(MDIChild)
DISPLAY
TYPE(Cus:Notes)      !Type the notes field
```

**See Also:**

Current Target

## UNFIXFORMAT (unfix a dynamic file)

**UNFIXFORMAT**( *file* )

---

**UNFIXFORMAT**      Change state of a dynamic file to unfixed

*file*                      The label of a FILE structure, which must be a reference variable.

**UNFIXFORMAT** changes a dynamic file that has previously been fixed into an unfixed state, thus allowing you to further change the format.

**UNFIXFORMAT** will set ERRORCODE to NoDriverSupport if you pass a file that was not created with NEW(file)

If you pass a file that was not created using NEW(file), **UNFIXFORMAT** posts the following error codes that can be trapped by the ERRORCODE function:

Errorcode	Equate	Reason
80	<i>NoDriverSupport</i>	File passed that was not created with NEW( <i>file</i> )
47	<i>InvalidFileErr</i>	Structure is invalid

If error code 47 is posted, the FILEERRORCODE statement can be used to return extended information. See the ErrorCode 47 Extended information topic for more information.

**See Also:** FIXFORMAT , FILEERRORCODE

## UNHIDE (show hidden control)

**UNHIDE**( [ *first control* ] [, *last control* ] )

---

**UNHIDE**            Displays previously hidden controls.

*first control*        Field number or field equate label of a control, or the first control in a range of controls. If omitted, defaults to zero (0).

*last control*        Field number or field equate label of the last control in a range of controls.

The **UNHIDE** statement reactivates a control or range of controls, that were hidden by the HIDE statement. Once un-hidden, the control is again visible on screen. This procedure is valid in Clarion Win32 Windows, and also for REPORT structures in both Clarion Win32 and Clarion#.

**Example:**

```
CODE
OPEN (Screen)
HIDE (?Control2)           !Control2 is hidden
IF Ctl:Password = 'Supervisor'
  UNHIDE (?Control2)       !Unhide Control2
END
```

**See Also:**

HIDE

ENABLE

DISABLE

## UNLOAD (remove a CALLED DLL from memory)

**UNLOAD**( *file* )

**UNLOAD** Unloads a Windows standard .DLL previously loaded by CALL.

*file* A string constant, variable, or expression containing the name (including extension) of the .DLL to unload. This may include a full path.

The **UNLOAD** procedure unloads a .DLL *file* left loaded by the CALL procedure.

### Example:

```
Win1 WINDOW
  BUTTON('Load DLL'),USE(?DLLButton)
END

CODE
OPEN(Win1)
ACCEPT
CASE EVENT()
OF EVENT:Accepted
  IF ACCEPTED() = ?DLLButton
    !Call procedure in CUSTOM.DLL and leave DLL resident:
    X# = CALL('CUSTOM.DLL','EntryPoint',1)
    IF X# THEN STOP(X#) END !Check for successful execution
  END
OF EVENT:CloseWindow
  UNLOAD('CUSTOM.DLL') !Unload the CUSTOM.DLL
END
END
!Process
```

### See Also:

CALL

## UNLOCK (unlock a locked data file)

**UNLOCK**(*file*)

---

**UNLOCK**        Unlocks a previously locked data file.

*file*            The label of a FILE declaration.

The **UNLOCK** statement unlocks a previously LOCKed data file. It will not unlock a file locked by another user. If the *file* is not locked, or is locked by another user, UNLOCK is ignored. UNLOCK posts no errors.

**Example:**

```
LOOP                    !Loop to avoid "deadly embrace"
  LOCK(Master,1)        !Lock the master file, try for 1 second
  IF ERRORCODE() = 32 !If someone else has it
    CYCLE                !try again
  END
  LOCK(Detail,1)        !Lock the detail file, try for 1 second
  IF ERRORCODE() = 32 !If someone else has it
    UNLOCK(Master)       !unlock the locked file
    CYCLE                !try again
  END
  BREAK                 !Break loop when both files are locked
END
```

**See Also:**

LOCK



## UNLOCKTHREAD (unlock the current execution thread)

### UNLOCKTHREAD

The **UNLOCKTHREAD** statement allows a Clarion program to call 3rd-party code or API procedures that contain their own message loop (like Clarion's ACCEPT loop).

Normally, ACCEPT loops in a Clarion program execute in turn (even in 32-bit programs) so that problems do not arise due to simultaneous access to data. Thread-switching only occurs at an ACCEPT statement, and thus only one thread can execute Clarion code at a time. However, if the currently executing thread calls an external procedure (including API functions) that (for example) opens a window and processes messages until the window closes, then other threads must be allowed to execute (co-operatively) to process their own messages. You do this by calling UNLOCKTHREAD before the external procedure, then LOCKTHREAD after it returns.

Because UNLOCKTHREAD may allow other threads to pre-empt the currently executing thread, it is important that you make **NO** calls to the Clarion runtime library between UNLOCKTHREAD and its corresponding LOCKTHREAD. This means you must not call any Clarion language procedure. You also must not perform any operations involving a STRING, CSTRING, PSTRING, DECIMAL, or PDECIMAL data types. The one exception is that you may pass a STRING, CSTRING, or PSTRING variable as a RAW parameter to an external (non-Clarion) procedure.

**Failure to observe this restriction may result in data on another thread becoming corrupted, or other generally unpredictable misbehavior.**

The THREADLOCKED() procedure determines whether the thread has been unlocked or not.

**Example:**

```
UNLOCKTHREAD          !Unlock the thread
MyLibraryCodeWithMessageLoop  !Call the code that has its own message loop
LOCKTHREAD            !Re-lock the thread
```

**See Also:**

ACCEPT

LOCKTHREAD

THREADLOCKED

## UNQUOTE (remove string special characters)

**UNQUOTE**( *value* )

---

**UNQUOTE** Contracts the *value*'s string data, "singling up" doubled single quotes ("), and all doubled un-paired left angle brackets (<<) and left curly braces ({{).

*value* A string constant or variable containing the properties to parse.

The **UNQUOTE** procedure returns the string contained in the *value* with all doubled single quotes ("), doubled un-paired left angle brackets (<<), and un-paired left curly braces ({{) "singled up" (returned to single instances instead of double instances of each character).

**Return Data Type:** STRING

**Example:**

```
stringvar1  STRING('<250>')
stringvar2  STRING('<<display text>')
stringvar3  STRING(30)
```

```
CODE
stringvar3 = 'label{{PROP:text} = value'
```

```
MESSAGE(UNQUOTE(stringvar1))  !returns accented u
MESSAGE(UNQUOTE(stringvar2))  !returns '<display text>'
MESSAGE(UNQUOTE(stringvar3))  !returns 'label{PROP:text} = value'
```

**See Also:**

QUOTE

## UNREGISTER (unregister event handler)

**UNREGISTER**( [*event*] [, *handler*] [, *object*] [, *window*] [, *control*] )

**UNREGISTER** Unregisters an event handling procedure.

<i>event</i>	An integer constant, variable, expression, or EQUATE containing an event number. A value in the range 400h to 0FFFh is a User-defined event. If omitted, all <i>events</i> are unregistered.
<i>handler</i>	A LONG variable, or expression containing the return value from ADDRESS for the PROCEDURE to handle the <i>event</i> . If omitted, all <i>handlers</i> are unregistered.
<i>object</i>	A LONG integer constant, variable, or expression containing any 32-bit unique value to identify the specific <i>handler</i> . This is generally the return value of ADDRESS(SELF) when the <i>handler</i> is a CLASS method.
<i>window</i>	The label of the WINDOW or REPORT whose <i>event</i> to handle. If omitted, the current target WINDOW or REPORT is assumed.
<i>control</i>	An integer constant, EQUATE, variable, or expression containing the field number of the specific control whose <i>event</i> to handle. If omitted, the <i>event</i> is handled for every control on the <i>window</i> .

**UNREGISTER** prevents a previously REGISTERed event *handler* PROCEDURE from being called to handle its *event*.

### Note:

Can also be prototyped as **UNREGISTEREVENT**.

### Example:

```
WindowResizeClass.Kill PROCEDURE
CODE
UNREGISTER(EVENT:Sized,ADDRESS(SELF.TakeResize),ADDRESS(SELF))
!Other code follows

WindowResizeClass.TakeResize PROCEDURE
ReturnValue BYTE
CODE
ReturnValue = Level:Benign
RETURN(ReturnValue)
```

### See Also:

REGISTER  
ACCEPT  
EVENT

## UNTIE(disassociate a string value from an ASTRING)

**UNTIE**([*stringtoken*],[*index*])

---

**UNTIE**            Removes a value previously TIED for an ASTRING.

*stringtoken*        The label of a previously declared ASTRING token. If omitted, all previously declared ASTRINGs are used.

*index*              A numeric constant or variable defining the index value of a previously declared ASTRING. The index value may be any LONG value greater than zero. If omitted, all indexes are used.

The **UNTIE** statement disassociates a string value that was previously associated to a particular ASTRING *stringtoken* and *index*.

**Example:**

```
PROGRAM
MAP
END

INCLUDE ('EQUATES.CLW')
COLOR   EQUATE(1)
SIDES   EQUATE(2)

AS1      ASTRING

CODE
AS1 = 'SHAPE'           !Declare ASTRING string token
TIE('SHAPE',COLOR,COLOR:RED) !Associate COLOR:RED to COLOR for ASTRING SHAPE
TIE(AS1,SIDES,3)        !Associate 3 to SIDES for ASTRING SHAPE
(some code here)
UNTIE(AS1, SIDES)
```

**See Also:**

TIE

TIED

## UPDATE (write from screen to USE variables)

**UPDATE( [first control] [,last control] )**

**UPDATE** Writes the contents of a control to its USE variable.

*first control* Field number or field equate label of a control, or the first control in a range of controls.

*last control* Field number or field equate label of the last control in a range of controls.

**UPDATE** writes the contents of a screen control to its USE variable. This takes the value displayed on screen and places it in the variable specified by the control's USE attribute.

USE variables are updated automatically by ACCEPT as each control is accepted. However, certain events (such as an ALERTed key press) do not automatically update USE variables. This is the purpose of the UPDATE statement.

UPDATE	Updates all controls on the screen.
--------	-------------------------------------

UPDATE( <i>first control</i> )	Updates a specific USE variable from its associated screen control.
--------------------------------	---

UPDATE( <i>first control</i> , <i>last control</i> )	Updates the USE variables of an inclusive range of screen controls.
--	---

**Example:**

UPDATE (?)	!Update the currently selected control
UPDATE	!Update all controls on the screen
UPDATE (?Address)	!Update the address control
UPDATE (3,7)	!Update controls 3 through 7
UPDATE (?Name,?Zip)	!Update controls from name through zip
UPDATE (?City,?City+2)	!Update city and 2 controls following

**See Also:**

## Field Equate Labels

## DISPLAY

CHANGE

## UPPER (return upper case)

**UPPER**(*string*)

---

**UPPER** Returns all upper case string.

*string* A string constant, variable, or expression for the *string* to be converted.

The **UPPER** procedure returns a string with all letters converted to upper case.

**Return Data Type:** STRING

**Example:**

```
!UPPER('abc') returns 'ABC'
```

```
Name = UPPER(Name)    !Make the name upper case
```

**See Also:**

LOWER

ISUPPER

ISLOWER

## VAL (return ASCII value)

**VAL**(*character*)

---

**VAL**                Returns ASCII code.

*character*        A one-byte string containing an ANSI character.

The **VAL** procedure returns the ASCII code of a *character*.

**Return Data Type:**    LONG

**Example:**

```
!VAL('A')    returns 65
!VAL('z')    returns 122
```

```
CharVal = VAL(StrChar)        !Get the ASCII value of the string character
```

**See Also:**

CHR

## WATCH (automatic concurrency check)

**WATCH**( *entity* )

---

**WATCH**            Arms automatic optimistic concurrency checking.

*entity*            The label of a FILE or VIEW declaration.

The **WATCH** statement arms automatic optimistic concurrency checking by the file driver for a following GET, REGET, NEXT, or PREVIOUS statement in a multi-user environment. The WATCH terminates when the WATCHed record is PUT back to the *entity*, or another GET, NEXT, PREVIOUS, or REGET statement executes on the same *entity* without first executing another WATCH statement.

Generally, the file driver retains a copy of the retrieved record on the GET, NEXT, PREVIOUS, or REGET when it successfully gets the record. When the retrieved record is PUT to the *file*, the record on disk is compared to the original record retrieved. Error 89 (Record Changed By Another Station) is posted by the PUT statement if the record has been changed by another user.

You can now specify which fields are to be used to WATCH if a record has changed. By default *all* fields are used. However, if you have a specific field (or set of fields) that are always changed when a record is changed (e.g., a record last changed a timestamp field), then you can set the **external name** of the field to:

<FieldName> | WATCH

and then *only* fields with the WATCH switch in them will be used to check if a record has changed.

### Example:

```
SET(Itm:InvoiceKey)           !Start at beginning of Items file
LOOP                          !Process all records
  WATCH(Items)               !Arm concurrency check
  NEXT(Items)                 !Get a record
  IF ERRORCODE() THEN BREAK.
  DO ItemProcess              !process the item
  PUT(Items)                  !and put it back
  IF ERRORCODE() = RecordChangedErr !If changed by another station
    PREVIOUS(Items)          !Setup to re-process the changed record
  ELSE
    STOP(ERROR())            !Stop on any other error
  END
END
```

### See Also:

NEXT

PREVIOUS

GET

REGET

HOLD



## WHAT (return field from group)

**WHAT**( *group*, *number* [,*dimension*] )

**WHAT** Returns a specified field from a *group* structure.

*group* The label of a GROUP, RECORD, CLASS, or QUEUE declaration.

*number* An integer expression specifying the ordinal position of a field in the *group*.

*dimension* An optional dimension element number, if applicable.

The **WHAT** statement returns the *number* specified field from a *group* structure. Generally, this would be assigned to an ANY variable. If the number specified field is a dimensioned field, then WHAT returns a reference to the *dimension* element of the *number* field.

If the field with an ordinal position equal to the passed second parameter is defined as an ANY type or has the DIM attribute, the returned value can only be used in "reference equality" (&=) operations. Any attempt to access the field will cause a run-time error.

**Return Data Type:** ANY

**Example:**

```
MyGroup  GROUP
F1        LONG(3)           !Field number 1
F2        SHORT             !Field number 2
F3        STRING(30)        !Field number 3
InGroup   GROUP             !Field number 4
F1        LONG              !Field number 5
F2        SHORT(2)          !Field number 6
F3        STRING(30),DIM(2) !Field number 7
F4        LONG,DIM(3,3)     !Field number 8
F5        ANY
          END
          END
```

**CurrentField** ANY

```
CODE
CurrentField &= WHAT(MyGroup,1) !Returns contents of MyGroup.F1 (3)
CurrentField &= WHAT(MyGroup,6) !Returns contents of MyGroup.Ingroup.F2 (2)
CurrentField &= WHAT(MyGroup,7) !Returns contents of MyGroup.Ingroup.F3[1]
  IF CurrentField &= RefVar      !LEGAL
    CurrentField = 2             !INVALID - posts a runtime error
  END
CurrentField &= WHAT(MyGroup,8,3) !Returns contents of MyGroup.Ingroup.F4[1,3]
CurrentField &= WHAT(MyGroup,8,5) !Returns contents of MyGroup.Ingroup.F4[2,2]

!For String Comparison, the returned field must be moved into a work field:
CurrentField &= WHAT(MyGroup,8,7) !Returns contents of MyGroup.Ingroup.F4[3,1]
IF CurrentField = 'xyz'
  !do something
END
```

**See Also:** ANY, WHERE, WHO, GETGROUP, GROUP, HOWMANY, ISSTRING, ISGROUP, RECORD, CLASS, QUEUE

## WHERE (return field position in group)

**WHERE**( *group*, *field* )

---

**WHERE** Returns a *field's* ordinal position within a GROUP, RECORD, CLASS, or QUEUE structure.

*group* The label of a GROUP, RECORD, CLASS, or QUEUE declaration.

*field* The label of a field in the *group* declaration.

The **WHERE** statement returns the ordinal position of a specified *field* in a *group* structure.

**Return Data Type:** SIGNED

**Example:**

```
MyGroup  GROUP
F1        LONG           !Field number 1
F2        SHORT          !Field number 2
F3        STRING(30)     !Field number 3
InGroup   GROUP          !Field number 4
F1        LONG           !Field number 5
F2        SHORT          !Field number 6
F3        STRING(30)     !Field number 7
          END
          END
```

CurrentField LONG

```
CODE
CurrentField = WHERE(MyGroup,MyGroup.F1)           !WHERE returns 1

CurrentField = WHERE(MyGroup,MyGroup.Ingroup.F2)   !WHERE returns 6

CurrentField = WHERE(MyGroup.Ingroup,MyGroup.Ingroup.F2) !WHERE returns 2
```

**See Also:**

WHAT

WHO

GETGROUP

GROUP

HOWMANY

ISGROUP

ISSTRING

RECORD

CLASS

QUEUE

## WHO (return field name from group)

**WHO**( *group*, *number* )

**WHO** Returns a string containing the name of a specified field from a *group* structure.

*group* The label of a GROUP, RECORD, CLASS, or QUEUE declaration with the BINDABLE attribute.

*number* An integer expression specifying the ordinal position of a field in the *group*.

The **WHO** statement returns a string containing the name of the *number* specified field from a *group* structure.

**Return Data Type:** STRING

**Example:**

```
MyGroup GROUP
F1      LONG                !Field number 1
F2      SHORT              !Field number 2
F3      STRING(30)         !Field number 3
InGroup GROUP             !Field number 4
F4      LONG               !Field number 5
F5      SHORT              !Field number 6
F6      STRING(30),NAME('CustomName') !Field number 7
      END
      END
```

CurrentField STRING(30)

```
CODE
CurrentField = WHO(MyGroup,1)    !Returns "F1"
CurrentField = WHO(MyGroup,6)    !Returns "F5"
CurrentField = WHO(MyGroup,7)    !Returns "CustomName"
```

**See Also:**

WHAT

WHERE

GETGROUP

GROUP

HOWMANY

ISGROUP

RECORD

CLASS

QUEUE

BINDABLE

## YEAR (return year of date)

**YEAR**(*date*)

---

**YEAR** Returns the year.

*date* A numeric constant, variable, expression, or the label of a string variable declared with a date picture, containing a standard date. A variable declared with a date picture is automatically converted to a standard date intermediate value.

The **YEAR** procedure returns a four digit number for the year of a standard *date* (1801 to 9999).

**Return Data Type:** LONG

**Example:**

```
IF YEAR>LastOrd) < YEAR(TODAY())    !If last order date not from this year
  DO StartNewYear                    !start new year to date totals
END
```

**See Also:**

Standard Date

DAY

MONTH

TODAY

DATE

## Appendix A - DDE, OLE, and OCX

### Dynamic Data Exchange- DDE Overview

Dynamic Data Exchange (DDE) is a very powerful Windows tool that allows a user to access data from another separately executing Windows application. This allows the user to work with the data in its native format (in the originating application), while ensuring that the application in which the data is used always has the most current values.

DDE is based upon establishing "conversations" (links) between two concurrently executing Windows applications. One of the applications acts as the DDE server to provide the data, and the other is the DDE client that receives the data. A single application may be both a DDE client and server, getting data from other applications and providing data to other applications. Multiple DDE "conversations" can occur concurrently between any given DDE server and client.

#### **To be a DDE server, a Clarion application must:**

- Open at least one window, since all DDE servers must be associated with a window (and its ACCEPT loop).
- Register with Windows as a DDE server, using the DDESERVER procedure.
- Provide the requested data to the client, using the DDEWRITE statement.
- When DDE is no longer required, terminate the link by using the DDECLOSE statement. You can also allow it to terminate when the user closes the server application or the window that started the link.

#### **To be a DDE client, a Clarion application must:**

- Open at least one window, since all DDE events must be processed with a window's ACCEPT loop.
- Open a link to a DDE server as its client, using the DDECLIENT procedure.
- Ask the server for data, using the DDEREAD statement, or ask the server for a service using the DDEEXECUTE statement.
- When DDE is no longer required, terminate the link by using the DDECLOSE statement. You can also allow it to terminate automatically when the user closes the client window or application.

The DDE procedures are prototyped in the DDE.CLW file, which you must INCLUDE in your program's MAP structure. The DDE process posts DDE-specific field-independent events to the ACCEPT loop of the window that opened the link between applications as a server or client.

## DDE Events

The DDE process is governed by several field-independent events specific to DDE. These events are posted to the ACCEPT loop of the window that opened the link between applications, either as a server or client.

The following events are posted only to a Clarion server application:

EVENT:DDErequest	A client has requested a data item.
EVENT:DDEadvise	A client has requested continuous updates of a data item.
EVENT:DDEexecute	A client has executed a DDEEXECUTE statement.
EVENT:DDEpoke	A client has sent unsolicited data

The following events are posted only to a Clarion client application:

EVENT:DDEdata	A server has supplied an updated data item.
EVENT:DDEclosed	A server has terminated the DDE link.

When one of these DDE events occur there are several procedures that tell you what posted the event:

- DDECHANNEL() returns the handle of the DDE server or client.
- DDEITEM() returns the item or command string passed to the server by the DDEREAD or DDEEXECUTE statements.
- DDEVALUE returns a string containing the data sent to the Clarion DDE server by the DDEPOKE statement, or the command to execute from a DDEEXECUTE statement.
- DDEAPP() returns the name of the application.
- DDETOPIC() returns the name of the topic.

When a Clarion program creates a DDE server, external clients can link to this server and request data. Each data request is accompanied by a string (in some specific format which the server program knows) indicating the required data item. If the Clarion server already knows the value for a given item, it supplies it to the client automatically without generating any events. If it doesn't, an EVENT:DDErequest or EVENT:DDEadvise event is posted to the server window's ACCEPT loop.

When a Clarion program creates a DDE client, it can link to external servers which can provide data. When the server first provides the value for a given item, it supplies it to the client automatically without generating any events. If the client has established a "hot" link with the server, an EVENT:DDEdata event is posted to the client window's ACCEPT loop whenever the server posts a new value for the data item.

## DDEACKNOWLEDGE (send acknowledgement from DDE server)

**DDEACKNOWLEDGE**( *response* )

**DDEACKNOWLEDGE** Sends acknowledgement of the current DDEPOKE or DDEEXECUTE statement sent to the DDE server.

*Response* An integer constant, variable, or expression containing zero (0) or one (1) to indicate negative or positive acknowledgement.

The **DDEACKNOWLEDGE** procedure allows a DDE server program to immediately acknowledge unsolicited data sent from DDEPOKE, or commands sent from DDEEXECUTE. This allows the client application to immediately continue its processing. Although a CYCLE statement after EVENT:DDEpoke or EVENT:DDEexecute also signals positive acknowledgement to the client, DDEACKNOWLEDGE allows you to send negative acknowledgement.

### Example:

```
!The client application's code contains:
WinOne WINDOW,AT(0,0,160,400)
    END
SomeServer LONG
DDEChannel LONG
CODE
OPEN(WinOne)
DDEChannel = DDECLIENT('MyServer','System') !Open a channel to MyServer app
DDEEXECUTE(DDEChannel,'[ShowList]')          !Tell it to do something
```

```
!The server application's code contains:
WinOne WINDOW,AT(0,0,160,400)
    END
DDEChannel LONG
CODE
OPEN(WinOne)
DDEChannel = DDESERVER('MyServer','System') !Open channel
ACCEPT
CASE EVENT()
OF EVENT:DDEExecute
CASE DDEVALUE()
OF 'ShowList'
    DDEACKNOWLEDGE(1)
    DO ShowList
ELSE
    DDEACKNOWLEDGE(0)
END
END
END
END
```

!Check the requested action

!Send positive acknowledgement

!and take the action

!If requested action is unknown

!Send negative acknowledgement

### See Also:

DDEPOKE

DDEEXECUTE

## DDEAPP (return server application)

### DDEAPP()

The **DDEAPP** procedure returns a string containing the application name in the DDE channel that has just posted a DDE event. This is usually the same as the first parameter to the DDESERVER or DDECLIENT procedure when the DDE channel is established.

**Return Data Type:** STRING

**Example:**

```
ClientApp STRING(20)
WinOne WINDOW,AT(0,0,160,400)
        STRING(@S20),AT(5,5,90,20),USE(ClientApp)
END

TimeServer LONG
DateServer LONG
FormatTime STRING(5)
FormatDate STRING(8)

CODE
OPEN(WinOne)
TimeServer = DDESERVER('SomeApp','Time')      !Open as server
DateServer = DDESERVER('SomeApp','Date')      !Open as server
ACCEPT
CASE EVENT()
OF EVENT:DDErequest
CASE DDECHANNEL()
OF TimeServer
ClientApp = DDEAPP()                          !Get client's name
DISPLAY                                       !and display on screen
FormatTime = FORMAT(CLOCK(),@T1)
DDEWRITE(TimeServer,DDE:manual,'Time',FormatTime)
OF DateServer
ClientApp = DDEAPP()                          !Get client's name
DISPLAY                                       !and display on screen
FormatDate = FORMAT(TODAY(),@D1)
DDEWRITE(DateServer,DDE:manual,'Date',FormatDate)
END
END
END
```

**See Also:**

DDECLIENT

DDESERVER



## DDECHANNEL (return DDE channel number)

**DDECHANNEL()**

The **DDECHANNEL** procedure returns a LONG integer containing the channel number of the DDE client or server application that has just posted a DDE event. This is the same value returned by the DDESERVER or DDECLIENT procedure when the DDE channel is established.

**Return Data Type:** LONG

**Example:**

```
WinOne WINDOW,AT(0,0,160,400)
    END
TimeServer LONG
DateServer LONG
FormatTime STRING(5)
FormatDate STRING(8)
CODE
OPEN(WinOne)
TimeServer = DDESERVER('SomeApp','Time')      !Open as server
DateServer = DDESERVER('SomeApp','Date')      !Open as server
ACCEPT
CASE EVENT()
OF EVENT:DDErequest
    CASE DDECHANNEL()                          !Check which channel
    OF TimeServer
        FormatTime = FORMAT(CLOCK(),@T1)
        DDEWRITE(TimeServer,DDE:manual,'Time',FormatTime)
    OF DateServer
        FormatDate = FORMAT(TODAY(),@D1)
        DDEWRITE(DateServer,DDE:manual,'Date',FormatDate)
    END
END
END
END
```

**See Also:**

DDECLIENT

DDESERVER

## DDECLIENT (return DDE client channel)

**DDECLIENT**( [ *application* ] [, *topic* ] )

---

**DDECLIENT** Returns a new DDE client channel number.

*application* A string constant or variable containing the name of the server application to link to. Usually, this is the name of the application. If omitted, the first DDE server application available is used.

*topic* A string constant or variable containing the name of the application-specific topic. If omitted, the first topic available in the *application* is used.

The **DDECLIENT** procedure returns a new DDE client channel number for the *application* and *topic*. If the *application* is not currently executing, DDECLIENT returns zero (0).

Typically, when opening a DDE channel as the client, the *application* is the name of the server application. The *topic* is a string that the *application* has either registered with Windows as a valid *topic* for the *application*, or represents some value that tells the *application* what data to provide. You can use the DDEQUERY procedure to determine the *applications* and *topics* currently registered with Windows.

**Return Data Type:** LONG

**Example:**

```
DDEReadVal REAL
WinOne WINDOW, AT(0,0,160,400)
    ENTRY (@s20) , USE (DDEReadVal)
END
ExcelServer LONG
CODE
OPEN(WinOne)

!Open as client to Excel spreadsheet:
ExcelServer = DDECLIENT('Excel', 'MySheet.XLS')

IF NOT ExcelServer                !If the server is not running
    MESSAGE('Please start Excel')    !alert the user to start it
    RETURN                          !and try again
END
DDEREAD(ExcelServer, DDE:auto, 'R5C5', DDEReadVal)
ACCEPT
CASE EVENT()
OF EVENT:DDEdata                  !As changed data comes from Excel
    PassedData(DDEReadVal)        !process the new data
END
END
```

**See Also:**

DDEQUERY

DDEWRITE

DDESERVER

## DDECLOSE (terminate DDE server link)

**DDECLOSE**( *channel* )

---

**DDECLOSE**     Closes an open DDE channel.

*channel*             The label of the LONG integer variable containing the channel number--the value returned by the DDESERVER or DDECLIENT procedure.

The **DDECLOSE** procedure allows a DDE client program to terminate the specified *channel*. A *channel* is automatically terminated when the window which opened the *channel* is closed.

**Errors Posted:**

- 601     Invalid DDE Channel
- 602     DDE Channel Not Open
- 605     Time Out

**Example:**

```
WinOne  WINDOW,AT(0,0,160,400)
        END
SomeServer LONG
CODE
OPEN(WinOne)
SomeServer = DDECLIENT('SomeApp','MyTopic') !Open as client
ACCEPT
END
DDECLOSE(SomeServer)
```

**See Also:**

DDECLIENT  
DDESERVER

## DDEEXECUTE (send command to DDE server)

**DDEEXECUTE**( *channel*, *command* )

---

**DDEEXECUTE** Sends a command string to an open DDE client channel.

*channel* A LONG integer constant or variable containing the client channel--the value returned by the DDECLIENT procedure.

*command* A string constant or variable containing the application-specific command for the server to execute.

The **DDEEXECUTE** procedure allows a DDE client program to communicate a *command* to the server. The *command* must be in a format the server application can recognize and act on. The server does not need to be a Clarion program. By convention, the entire *command* string is normally contained within square brackets ( [ ] ).

A Clarion DDE server can use the DDEVALUE() procedure to determine what *command* the client has sent. The CYCLE statement after an EVENT:DDEexecute signals positive acknowledgement to the client that sent the *command*. DDEACKNOWLEDGE can send either positive or negative acknowledgement.

### Errors Posted:

601	Invalid DDE Channel
602	DDE Channel Not Open
603	DDEEXECUTE Failed
605	Time Out

### Events Generated:

EVENT:DDEexecute A client has sent a command.

### Example:

```
!The client application's code contains:
WinOne WINDOW,AT(0,0,160,400)
    END
SomeServer LONG
DDEChannel LONG
CODE
    OPEN(WinOne)

!Open a channel to Windows Program Manager:
DDEChannel = DDECLIENT('PROGMAN','PROGMAN')

!Create a new program group:
DDEEXECUTE(DDEChannel,['CreateGroup(Clarion Applications)'])

!Display it:
DDEEXECUTE(DDEChannel,['ShowGroup(1)'])

!Create new item in the group using second icon in progman.exe
DDEEXECUTE(DDEChannel,['AddItem(MYAPP.EXE,My Program,PROGMAN.EXE,2)'])
```

**See Also:** DDEACKNOWLEDGE, DDEVALUE

## DDEITEM (return server item)

DDEITEM()

The **DDEITEM** procedure returns a string containing the name of the item for the current DDE event. This is the item requested by a DDEREAD, or the data item supplied by DDEPOKE.

**Return Data Type:** STRING

**Example:**

```
WinOne WINDOW,AT(0,0,160,400)
      END

Server      LONG
FormatTime  STRING(5)
FormatDate  STRING(8)

CODE
OPEN(WinOne)
Server = DDESERVER('SomeApp','Clock')  !Open as server for my topic
ACCEPT
CASE EVENT()
OF EVENT:DDErequest
CASE DDEITEM()
OF 'Time'
FormatTime = FORMAT(CLOCK(),@T1)
DDEWRITE(Server,DDE:manual,'Time',FormatTime)
OF 'Date'
FormatDate = FORMAT(TODAY(),@D1)
DDEWRITE(Server,DDE:manual,'Date',FormatDate)
END
OF EVENT:DDEadvise
CASE DDEITEM()
OF 'Time'
FormatTime = FORMAT(CLOCK(),@T1)
DDEWRITE(Server,1,'Time',FormatTime)
OF 'Date'
FormatDate = FORMAT(TODAY(),@D1)
DDEWRITE(Server,60,'Date',FormatDate)
END
END
END
```

**See Also:**

DDEREAD

DDEEXECUTE

DDEPOKE

## DDEPOKE (send unsolicited data to DDE server)

**DDEPOKE**( *channel*, *item*, *value* )

---

**DDEPOKE**      Sends unsolicited data through an open DDE client channel to a DDE server.

*channel*          A LONG integer constant or variable containing the client channel--the value returned by the DDECLIENT procedure.

*item*            A string constant or variable containing the application-specific item to receive the unsolicited data.

*value*           A string constant or variable containing the data to place in the *item*.

The **DDEPOKE** procedure allows a DDE client program to communicate unsolicited data to the server. The *item* and *value* parameters must be in a format the server application can recognize and act on. The server does not need to be a Clarion program.

A Clarion DDE server can use the DDEITEM() and DDEVALUE() procedures to determine what the client has sent. The CYCLE statement after an EVENT:DDEpoke signals positive acknowledgement to the client that sent the unsolicited data. DDEACKNOWLEDGE can send either positive or negative acknowledgement.

### Errors Posted:

- 601      Invalid DDE Channel
- 602      DDE Channel Not Open
- 604      DDEPOKE Failed
- 605      Time Out

### Events Generated:

EVENT:DDEpoke    A client has sent unsolicited data

**Example:**

```

WinOne WINDOW,AT(0,0,160,400)

      END
DDEChannel LONG
CODE
OPEN(WinOne)
DDEChannel = DDECLIENT('Excel','System')           !Open channel to Excel
DDEEXECUTE(DDEChannel,'[NEW(1)]')                   !Create a new spreadsheet
DDEEXECUTE(DDEChannel,'[Save.As("DDE_CHART.XLS")]') !Save it as DDE_CHART.XLS
DDECLOSE(DDEChannel)                                !Close conversation
DDEChannel = DDECLIENT('Excel','DDE_CHART.XLS')     !Open channel to new chart
DDEPOKE(DDEChannel,'R1C2','Widgets')                !Send it data
DDEPOKE(DDEChannel,'R1C3','Gadgets')
DDEPOKE(DDEChannel,'R2C1','East')
DDEPOKE(DDEChannel,'R3C1','West')
DDEPOKE(DDEChannel,'R2C2','450')
DDEPOKE(DDEChannel,'R3C2','275')
DDEPOKE(DDEChannel,'R2C3','340')
DDEPOKE(DDEChannel,'R3C3','390')
DDEEXECUTE(DDEChannel,'[SELECT("R1C1:R3C2")]')      !Highlight the data
DDEEXECUTE(DDEChannel,'[NEW(2,2)]')                  !and create a new chart
      !Send some more commands here to format the chart and work with it
DDECLOSE(DDEChannel)                                !Close channel when done

```

**See Also:**

DDEACKNOWLEDGE

DDEITEM

DDEVALUE

## DDEQUERY (return registered DDE servers)

DDEQUERY( [ *application* ] [, *topic* ] )

---

**DDEQUERY** Returns currently executing DDE servers.

*application* A string constant or variable containing the name of the application to query. For most applications, this is the name of the application. If omitted, all registered *applications* registered with the specified *topic* are returned.

*topic* A string constant or variable containing the name of the application-specific topic to query. If omitted, all *topics* for the *application* are returned.

The **DDEQUERY** procedure returns a string containing the names of the currently available DDE server *applications* and their *topics*.

If the *topic* parameter is omitted, all *topics* for the specified *application* are returned. If the *application* parameter is omitted, all registered *applications* registered with the specified *topic* are returned. If both parameters are omitted, DDEQUERY returns all currently available DDE servers.

The format of the data in the return string is *application:topic* and it can contain multiple *application* and *topic* pairs delimited by commas (for example, 'Excel:MySheet.XLS,ClarionApp:DataFile.DAT').

**Return Data Type:** STRING

**Example:**

```
!This example code does not handle DDEADVISE
WinOne WINDOW,AT(0,0,160,400)
    END
SomeServer LONG
ServerString STRING(200)
CODE
OPEN(WinOne)
LOOP
    ServerString = DDEQUERY()                !Return all registered servers
    IF NOT INSTRING('SomeApp:MyTopic',ServerString,1,1)
        MESSAGE('Open SomeApp, Please')
    ELSE
        BREAK
    END
END
SomeServer = DDECLIENT('SomeApp','MyTopic') !Open as client
ACCEPT
END
DDECLOSE(SomeServer)
```



## DDEREAD (get data from DDE server)

**DDEREAD**( *channel*, *mode*, *item* [, *variable* ] )

**DDEREAD** Gets data from a previously opened DDE client channel.

*channel* A LONG integer constant or variable containing the client channel--the value returned by the DDECLIENT procedure.

*mode* An EQUATE defining the type of data link: DDE:auto, DDE>manual, or DDE:remove (defined in EQUATES.CLW).

*item* A string constant or variable containing the application-specific name of the data item to retrieve.

*variable* The name of the variable to receive the retrieved data. If omitted and *mode* is DDE:remove, all links to the *item* are canceled.

The **DDEREAD** procedure allows a DDE client program to read data from the *channel* into the *variable*. The type of update is determined by the *mode* parameter. The *item* parameter supplies some string value to the server application that tells it what specific data item is being requested. The format and structure of the *item* string is dependent upon the server application.

If the *mode* is DDE:auto, the *variable* is continually updated by the server (a "hot" link). An EVENT:DDEdata is generated each time the *variable* is updated by the server.

If the *mode* is DDE>manual, the *variable* is updated once and no event is generated. Another DDEREAD request must be sent to the server to check for any changed value (a "cold" link).

If the *mode* is DDE:remove, a previous "hot" link to the *variable* is terminated. If the *mode* is DDE:remove and *variable* is omitted, all previous "hot" links to the *item* are terminated, no matter what *variables* were linked. This means the client must send another DDEREAD request to the server to check for any changed value.

### Errors Posted:

601 Invalid DDE Channel

602 DDE Channel Not Open

605 Time Out

### Events Generated:

These events are posted to the client application:

EVENT:DDEdata A server has supplied an updated data item for a hot link.

EVENT:DDEclosed A server has terminated the DDE link.

**Example:**

```
WinOne WINDOW,AT(0,0,160,400)
      END
```

```
ExcelServer LONG(0)
DDEReadVal REAL
```

```
CODE
OPEN(WinOne)
!Open as client to Excel spreadsheet
ExcelServer = DDECLIENT('Excel','MySheet.XLS')
IF NOT ExcelServer          !If the server is not running
  MESSAGE('Please start Excel') !alert the user to start it
  CLOSE(WinOne)
  RETURN
END

!Request continual update from server:
DDEREAD(ExcelServer,DDE:auto,'R5C5',DDEReadVal)
ACCEPT
CASE EVENT()
  OF EVENT:DDEdata          !As changed data comes from Excel
    PassedData(DDEReadVal)  ! call proc to process the new data
  END
END
```

**See Also:**

DDEQUERY

DDEWRITE

DDESERVER

## DDESERVER (return DDE server channel)

**DDESERVER**( [ *application* ] [, *topic* ] )

**DDESERVER** Returns a new DDE server channel number.

*application* A string constant or variable containing the name of the application. Usually, this is the name of the application. If omitted, the filename of the application (without extension) is used.

*topic* A string constant or variable containing the name of the application-specific topic. If omitted, the *application* will respond to any data request.

The **DDESERVER** procedure returns a new DDE server channel number for the *application* and *topic*. The channel number specifies a *topic* for which the *application* will provide data. This allows a single Clarion *application* to register as a DDE server for multiple *topics*.

**Return Data Type:** LONG

**Example:**

```

DDERetVal  STRING(20)
WinOne     WINDOW,AT(0,0,160,400)
           ENTRY(@s20),USE(DDERetVal)
           END
MyServer   LONG

CODE
OPEN(WinOne)
MyServer = DDESERVER('MyApp','DataEntered')  !Open as server
ACCEPT
CASE EVENT()
OF EVENT:DDErequest           !As server for data requested once
  DDEWRITE(MyServer,DDE:manual,'DataEntered',DDERetVal) !Provide data once
OF EVENT:DDEadvise            !As server for constant update request
  DDEWRITE(MyServer,15,'DataEntered',DDERetVal)
                                !Check for change every 15 seconds
                                !and provide data whenever changed

END
END

```

**See Also:**

DDECLIENT

DDEWRITE

## DDETOPIC (return server topic)

**DDETOPIC()**

The **DDETOPIC** procedure returns a string containing the topic name for the DDE channel that has just posted a DDE event.

**Return Data Type:**   STRING

**Example:**

```
WinOne WINDOW,AT(0,0,160,400)
    END

TimeServer LONG
DateServer LONG
FormatTime STRING(5)
FormatDate STRING(8)

CODE
OPEN(WinOne)
TimeServer = DDESERVER('SomeApp')      !Open as server
ACCEPT
CASE EVENT()
OF EVENT:DDErequest
CASE DDETOPIC()                        !Get requested topic
OF 'Time'
    FormatTime = FORMAT(CLOCK(),@T1)
    DDEWRITE(TimeServer,DDE:manual,'Time',FormatTime)
OF 'Date'
    FormatDate = FORMAT(TODAY(),@D1)
    DDEWRITE(DateServer,DDE:manual,'Date',FormatDate)
END
END
END
```

**See Also:**

DDEREAD

DDECLIENT

DDESERVER

## DDEVALUE (return data value sent to server)

DDEVALUE()

The **DDEVALUE** procedure returns a string containing the data sent to a Clarion DDE server by the DDEPOKE statement, or the command to execute from a DDEEXECUTE statement.

**Return Data Type:** STRING

**Example:**

```
WinOne WINDOW,AT(0,0,160,400)
      END
TimeServer LONG

TimeStamp FILE,DRIVER(ASCII),PRE(Tim)
Record      RECORD
FormatTime  STRING(5)
FormatDate  STRING(8)
Message     STRING(50)
      END
      END

CODE
OPEN(WinOne)
TimeServer = DDESERVER('TimeStamp')      !Open as server
ACCEPT
CASE EVENT()
OF EVENT:DDEpoke
OPEN(TimeStamp)
Tim:FormatTime = FORMAT(CLOCK(),@T1)
Tim:FormatDate = FORMAT(TODAY(),@D1)
Tim:Message = DDEVALUE()                  !Get data
ADD(TimeStamp)
CLOSE(TimeStamp)
CYCLE                                     !Ensure acknowledgement
END
END
```

**See Also:**

DDEPOKE

DDEEXECUTE

## DDEWRITE (provide data to DDE client)

**DDEWRITE**( *channel*, *mode*, *item* [, *variable* ] )

---

**DDEWRITE**     Provide data to an open DDE server channel.

<i>channel</i>	A LONG integer constant or variable containing the server channel--the value returned by the DDESERVER procedure.
<i>mode</i>	An integer constant or variable containing the interval (in seconds) to poll for changes to the <i>variable</i> , or an EQUATE defining the type of data link: DDE:auto, DDE>manual, or DDE:remove (defined in EQUATES.CLW).
<i>item</i>	A string constant or variable containing the application-specific name of the data item to provide.
<i>variable</i>	The name of the variable providing the data. If omitted and <i>mode</i> is DDE:remove, all links to the <i>item</i> are canceled.

The **DDEWRITE** procedure allows a DDE server program to provide the *variable*'s data to the client. The *item* parameter supplies a string value that identifies the specific data item being provided. The format and structure of the *item* string is dependent upon the *server* application. The type of update performed is determined by the *mode* parameter.

If the *mode* is DDE:auto, the client program receives the current value of the variable and the internal libraries continue to provide that value whenever the client (or any other client) asks for it again. If the client requested a "hot" link, any changes to the *variable* should be tracked by the Clarion program so it can issue a new DDEWRITE statement to update the client with the new value.

If the *mode* is DDE>manual, the *variable* is updated only once. If the client requested a "hot" link, any changes to the *variable* should be tracked by the Clarion program so it can issue a new DDEWRITE statement to update the client with the new value. PROP:DDETimeOut can be used to set or get the time out value for the DDE connection (default is five seconds).

If the *mode* is a positive integer, the internal libraries check the value of the *variable* whenever the specified number of seconds has passed. If the value has changed, the client is automatically updated with the new value by the internal libraries (without the need for any further Clarion code). This can incur significant overhead, depending upon the data, and so should be used only when necessary.

If the *mode* is DDE:remove, any previous "hot" link to the *variable* is terminated. If the *mode* is DDE:remove and *variable* is omitted, all previous "hot" links to the *item* are terminated, no matter what *variables* were linked. This means the client must send another DDEREAD request to the server to check for any changed value.

### Errors Posted:

- 601     Invalid DDE Channel
- 602     DDE Channel Not Open
- 605     Time Out

**Events Generated:**

EVENT:DDErequest    A client has requested a data item (a "cold" link).

EVENT:DDEadvise    A client has requested continuous updates of a data item (a "hot" link).

**Example:**

```

DDERetVal  STRING(20)
WinOne     WINDOW,AT(0,0,160,400)
           ENTRY(@s20),USE(DDERetVal)
           END
MyServer    LONG
CODE
OPEN(WinOne)
MyServer = DDESERVER('MyApp','DataEntered')    !Open as server
ACCEPT
CASE EVENT()
OF EVENT:DDErequest                                !As server for data requested once
  DDEWRITE(MyServer,DDE:manual,'DataEntered',DDERetVal)  !Provide data once
OF EVENT:DDEadvise                                !As server for constant update request
  DDEWRITE(MyServer,15,'DataEntered',DDERetVal)
                                           !Check for change every 15 seconds
                                           !and provide data whenever changed

END
END

```

**See Also:**

DDEQUERY

DDEREAD

DDESERVER

# Object Linking and Embedding

## OLE Overview

Object Linking and Embedding (OLE) allows "objects" from one application to be linked or embedded into a "document" (data structure) of another application. The application that creates and maintains the object is an OLE Server application, while the application that contains the object is an OLE Controller application (sometimes referred to as an OLE Client application). OLE "objects" are data structures appropriate to the OLE Server application (such as a chart from a spreadsheet, or an image from a paint or drawing application). The object is placed in a "container window" in the Controller application. In Clarion for Windows, "container windows" are OLE controls.

Clarion's implementation of OLE allows a Clarion for Windows application to serve as an OLE Controller application, linking or embedding objects from any OLE Server application. Clarion also supports OLE Automation, which gives an OLE Controller application dynamic control of the OLE Server application, using the OLE Server's macro language.

### **Object Linking**

Object Linking generally means the OLE Controller application stores "pointer" information to the object, whether that object is the entire data structure (like a spreadsheet file) or a component of the data structure (like a range of cells in a spreadsheet). When an Object is linked into the OLE Controller application the OLE Controller application contains only the information necessary to reference the linked data. This can be stored in either a BLOB or an OLE Compound Storage file.

### **Object Embedding**

Object Embedding generally means the OLE Controller application stores the entire object, independently of the OLE Server application. An Object embedded into the OLE Controller application does not exist as a separate data file which the OLE Server application may access. The OLE Controller application completely contains the active object, which can be stored in either a BLOB or an OLE Compound Storage file.

### **Maintaining the OLE Object**

Any object in the OLE Controller application, whether linked or embedded, is maintained by the OLE Server application which created it, not the OLE Controller application. This means that when the user wants to change the object, the OLE Controller application activates the OLE Server application to make the changes. There are two ways to activate an OLE Server: "in-place activation" and "open-mode."

#### **In-place activation**

In-place activation means the user seems to stay in the OLE Controller application, but the OLE Server's menus and toolbar merge into the OLE Controller's menus and toolbar and the OLE Server is the currently executing application. The Object being edited has a "hash-mark" border to indicate that it is in edit-mode.

If the OLE Server application has one or more toolbars then the toolbars will appear either as pop-up toolbars or as toolbars attached to one of the edges of the frame, or a combination of both. This can appear to "push down" the controls on your window, so take care designing your window.

#### **Open-mode activation**

Open-mode activation means the user is switched into the OLE Server application executing in a separate window. The Object being edited is in the Server application and ready to edit, while the Object in the OLE Controller application has "hash-marks" completely covering it to indicate a separate window is editing the object.



## OLE Container Properties

### **Contents:**

Attribute Properties  
 Undeclared Properties  
 Example Program  
 Interface Properties  
 Clarion OLE/OCX library and object hierarchies

There are a number of properties associated with an OLE container control that deal only with OLE objects (not .OCX controls).

### **Attribute Properties**

PROP:Create	The CREATE attribute (blank if none). (WRITE ONLY)
PROP:Open	The OPEN attribute (blank if none). (WRITE ONLY)
PROP:Document	The DOCUMENT attribute (blank if none). (WRITE ONLY)
PROP:Link	The LINK attribute (blank if none). (WRITE ONLY)
PROP:Clip	The CLIP attribute. A toggle attribute. Assigning a null string (") or zero turns it off, and '1' or 1 turns it on. (WRITE ONLY)
PROP:Stretch	The STRETCH attribute. A toggle attribute. Assigning a null string (") or zero turns it off, and '1' or 1 turns it on. (WRITE ONLY)
PROP:Autosize	The AUTOSIZE attribute. A toggle attribute. Assigning a null string (") or zero turns it off, and '1' or 1 turns it on. (WRITE ONLY)
PROP:Zoom	The ZOOM attribute. A toggle attribute. Assigning a null string (") or zero turns it off, and '1' or 1 turns it on. (WRITE ONLY)
PROP:Compatibility	The COMPATIBILITY attribute (blank if none). (WRITE ONLY)

### **Undeclared Properties**

PROP:Blob	Convert an object to and from a blob. (READ/WRITE)		
PROP:SaveAs	Saves the object to an OLE Compound Storage file. (WRITE ONLY) The syntax for placing the object in the file is ' <i>filename\!component</i> ' For example: <pre>?controlx{PROP:SaveAs} = 'myfile\!objectx'</pre>		
PROP:DoVerb	Executes an OLE doverb command from the following set of commands (WRITE ONLY): <table> <tr> <td>DOVERB:Primary (0)</td><td>Calls the object's primary action. The object, not the container, determines this action. If the object supports in-place activation, the primary verb usually activates the object in-place.</td></tr> </table>	DOVERB:Primary (0)	Calls the object's primary action. The object, not the container, determines this action. If the object supports in-place activation, the primary verb usually activates the object in-place.
DOVERB:Primary (0)	Calls the object's primary action. The object, not the container, determines this action. If the object supports in-place activation, the primary verb usually activates the object in-place.		

DOVERB:Show (-1)	Tells the object to show itself for editing or viewing. Called to display newly inserted objects for initial editing and to show link sources. This is usually an alias for some other object-defined action.
DOVERB:Open (-2)	Tells the object to open itself for editing in a separate window from its container (this includes objects that support in-place activation). If the object does not support in-place activation, this has the same action as DOVERB:Show.
DOVERB:Hide (-3)	Tells the object to remove its user interface. This applies only to objects activated in-place.
DOVERB:UIActivate (-4)	Activates the object in place, along with its full set of user-interface tools, including menus, toolbars, and its name in the title bar of the container window.
DOVERB:InPlaceActivate (-5)	Activates the object in-place without displaying the tools (menus and toolbars) that end-users need to change the behavior or appearance of the object.
DOVERB:DiscardUndoState (-6)	Tells the object to discard any undo state that it may be maintaining without deactivating the object.
DOVERB:Properties (-7)	Invokes the modal system property browser for the object to allow the user to set its properties.
PROP:Deactivate	Deactivates an in-place active OLE object. (READ/WRITE/EXECUTE)
PROP:Update	Tells the OLE object to update itself. (READ/WRITE/EXECUTE)
PROP:CanPaste	Can you paste the object in the clipboard? (READ ONLY)
PROP:Paste	Pastes an object from the clipboard to an OLE container control. (READ/WRITE/EXECUTE)
PROP:CanPasteLink	Can the object in the clipboard be pasted as a link? (READ ONLY)
PROP:PasteLink	Pastes and links an object from the clipboard to an OLE container control. (READ/WRITE/EXECUTE)
PROP:Copy	Copies an object in an OLE container control to the clipboard. (READ/WRITE/EXECUTE)
PROP:ReportException	Report OLE exceptions (for debug). (WRITE ONLY)
PROP:OLE	Is there an OCX or OLE object in the container? (READ ONLY)
PROP:Language	The number for the language used for OLE Automation or OCX Method. The number for US English is 0409H, and other language numbers can be computed from the data in the WINNT.H file in the MS Windows SDK. (READ/WRITE)

**Example Program:**

```

PROGRAM
MAP
    INCLUDE('OCX.CLW')
SelectOleServer  PROCEDURE(OleQ PickQ),STRING
END
    INCLUDE 'XL.CLW'           !Constants that Excel uses
    INCLUDE 'ERRORS.CLW'       !Include errorcode constants
SaveLinks  FILE,DRIVER('TopSpeed'),PRE(SAV),CREATE
Object     BLOB
Record     RECORD
LinkType   STRING(1)          !F = File, B = BLOB
LinkFile   STRING(64)         !OLE Compound Storage file name and object
END
END

i          LONG               !Loop counters
j          LONG
ResultQ    QUEUE              !Queue to hold return from OLEDIRECTORY
Name       CSTRING(64)
CLSID      CSTRING(64)
ProgID     CSTRING(64)
END
MainWin    WINDOW('OLE Demo'),AT(,350,200),STATUS(-1,-1),SYSTEM,GRAY,RESIZE,MAX,TIMER(1)
MENUBAR
    MENU('&File')
        ITEM('&exit'),USE(?exit)
    END
    MENU('&Objects')
        ITEM('Create Object'),USE(?CreateObject)
        ITEM('Paste Object'),USE(?PasteObject)
        ITEM('PasteLink Object'),USE(?PasteLinkObject)
        ITEM('Save Object to BLOB'),USE(?SaveObjectBlob),DISABLE
        ITEM('Save Object to OLE File'),USE(?SaveObjectFile),DISABLE
        ITEM('Retrieve Saved Object'),USE(?GetObject),DISABLE
    END
    MENU('&Activate')
        ITEM('&Spreadsheet'),USE(?ActiveExcel)
        ITEM('&Any OLE Object'),USE(?ActiveOLE),DISABLE
    END
END
OLE,AT(5,10,160,100),COLOR(0808000H),USE(?ExcelObject)
MENUBAR
    MENU('&Clarion App')
        ITEM('&Deactivate Excel'),USE(?DeactExcel)
    END
END
OLE,AT(170,10,160,100),USE(?AnyOLEObject),AUTOSIZE
MENUBAR
    MENU('&Clarion App')
        ITEM('&Deactivate Object'),USE(?DeactOLE)
    END
END
END
END
END
CODE
OPEN(SaveLinks)

```

```
IF ERRORCODE()                                !Check for error on Open
  IF ERRORCODE() = NoFileErr                   !if the file doesn't exist
    CREATE(SaveLinks)                         !then create it
    IF ERRORCODE() THEN HALT(,ERROR()) END
    OPEN(SaveLinks)                           !then open it for use
    IF ERRORCODE() THEN HALT(,ERROR()) END
  ELSE
    HALT(,ERROR())
  END
END
OPEN(MainWin)
?ExcelObject{PROP:Create} = 'Excel.Sheet.5'   !Create an Excel spreadsheet object
DO BuildSheetData                             !populate it with some random data
IF RECORDS(SaveLinks)                         !Check for existing saved record
  SET(SaveLinks)                              !and get it
  NEXT(SaveLinks)
  POST(EVENT:Accepted,?GetObject)             !and display it
  DO MenuEnable
ELSE
  ADD(SaveLinks)                             !or add blank record
END
IF ERRORCODE() THEN HALT(,ERROR()) END
ACCEPT
CASE EVENT()
  OF EVENT:CloseWindow
    ?ExcelObject{PROP:Deactivate}             !Deactivate the OLE Server applications
    ?AnyOLEObject{PROP:Deactivate}
  OF EVENT:Timer
    IF CLIPBOARD()
      IF ?AnyOLEObject{PROP:CanPaste}         !Can Paste object from the clipboard?
        IF ?PasteObject{PROP:Disable}
          ENABLE(?PasteObject)
        END
      ELSIF NOT ?PasteObject{PROP:Disable}
        DISABLE(?PasteObject)
      END
      IF ?AnyOLEObject{PROP:CanPasteLink}      !Can PasteLink object from clipboard?
        IF ?PasteLinkObject{PROP:Disable}
          ENABLE(?PasteLinkObject)
        END
      ELSIF NOT ?PasteLinkObject{PROP:Disable}
        DISABLE(?PasteLinkObject)
      END
    END
  OF EVENT:Accepted
    CASE FIELD()
      OF ?Exit
        POST(EVENT:CloseWindow)
      OF ?CreateObject
        OLEDIRECTORY(ResultQ,0)               !Get a list of installed OLE Servers
        ?AnyOLEObject{PROP:Create} = SelectOleServer(ResultQ) !Let the user pick one
        ?AnyOLEObject{PROP:DoVerb} = 0        !Activate OLE Server in its default mode
        DO MenuEnable
      OF ?PasteObject
        ?AnyOLEObject{PROP:Paste}             !Paste the object
        SETCLIPBOARD('Paste Completed')       !Assign non-object text to clipboard
        DO MenuEnable
      OF ?PasteLinkObject
        ?AnyOLEObject{PROP:PasteLink}         !PasteLink the object
        SETCLIPBOARD('PasteLink Completed')   !Assign non-object text to clipboard
```

```

DO MenuEnable
OF ?SaveObjectBlob                                !Save object to BLOB
  SAV:Object{PROP:Handle} = ?AnyOLEObject{PROP:Blob}
  SAV:LinkType = 'B'
  PUT(SaveLinks)
  IF ERRORCODE() THEN STOP(ERROR()) END
OF ?SaveObjectFile                                !Save to OLE Compound Storage file
  ?AnyOLEObject{PROP:SaveAs} = 'TEST1.OLE\!Object'
  SAV:LinkFile = 'TEST1.OLE\!Object'
  SAV:LinkType = 'F'
  PUT(SaveLinks)
  IF ERRORCODE() THEN STOP(ERROR()) END
OF ?GetObject
  IF SAV:LinkType = 'F'                            !Saved to OLE Compound Storage file?
    ?AnyOLEObject{PROP:Open} = SAV:LinkFile
  ELSIF SAV:LinkType = 'B'                          !Saved to BLOB?
    ?AnyOLEObject{PROP:Blob} = SAV:Object{PROP:Handle}
  END
  DISPLAY
OF ?ActiveExcel
  ?ExcelObject{PROP:DoVerb} = 0                    !In-place activate Excel
OF ?ActiveOLE
  ?AnyOLEObject{PROP:DoVerb} = 0                  !Activate OLE Server in its default mode
OF ?DeactExcel
  ?ExcelObject{PROP:Deactivate}                   !Return to the Clarion application
OF ?DeactOLE
  ?AnyOLEObject{PROP:Deactivate}                   !Return to the Clarion application
END !CASE FIELD()
END !CASE EVENT0()
END !ACCEPT

BuildSheetData  ROUTINE                          !Use OLE Automation to build spreadsheet
?ExcelObject{PROP:ReportException} = TRUE        !Excel will report any errors
?ExcelObject{'Application.Calculation'} = xlManual !turn off auto recalc
LOOP i = 1 TO 3                                  !Fill Sheet with some values
  LOOP j = 1 TO 3
    ?ExcelObject{'Cells(' & i & ',' & j & ').Value'} = Random(100,900)
  END
  ?ExcelObject{'Cells(4,' & i & ').Value'} = 'Sum'
  ?ExcelObject{'Cells(5,' & i & ').FormulaR1C1'} = '=SUM(R[-4]C:R[-2]C)'
  ?ExcelObject{'Cells(6,' & i & ').Value'} = 'Average'
  ?ExcelObject{'Cells(7,' & i & ').FormulaR1C1'} = '=AVERAGE(R[-6]C:R[-4]C)'
END
!turn auto recalc back on
?ExcelObject{'Application.Calculation'} = xlAutomatic
DISPLAY

MenuEnable  ROUTINE                              !Enable menu items
  ENABLE(?ActiveOLE)
  ENABLE(?SaveObjectBlob,?GetObject)

SelectOleServer PROCEDURE(OleQ PickQ)
window WINDOW('Choose OLE Server'),AT(,,122,159),CENTER,SYSTEM,GRAY
  LIST,AT(11,8,100,120),USE(?List),HVSCROLL, |
  FORMAT('146L~Name~@s64@135L~CLSID~@s64@20L~ProgID~@s64@',FROM(PickQ)
  BUTTON('Select'),AT(42,134),USE(?Select)
END

CODE
OPEN(window)

```

```
SELECT(?List,1)
ACCEPT
CASE ACCEPTED()
OF ?Select
  GET(PickQ,CHOICE(?List))
  IF ERRORCODE() THEN STOP(ERROR()) END
  POST(EVENT:CloseWindow)
END
END
RETURN(PickQ.ProgID)
```

## **Interface Properties**

PROP:Object Gets the Dispatch interface for the object. (READ ONLY)

In VB the toolbar and tree control use the image-list control to show icons in the tree control and on the buttons on the toolbar. To associate an image control with a toolbar, use the following code:

```
?toolbar{'ImageList'} = ?imagelist{prop:object}
```

PROP:SelectInterface Selects the interface to use with the object. (WRITE ONLY)

```
?x{PROP:SelectInterface} = 'x.y'
?x{'z(1)'} = 1
?x{'z(2)'} = 2
```

has the same meaning as

```
?x{'x.y.z(1)'} = 1
?x{'x.y.z(2)'} = 2
```

PROP:AddRef Increments the reference count for an interface. (WRITE ONLY)

PROP:Release Decrements the reference count for an interface. (WRITE ONLY)

## **Clarion OLE/OCX library and object hierarchies:**

At the time of the design and implementation of the Clarion OLE library, the lack of access to secondary objects created by a primary object (example from excel: ExcelUse{'Application.Charts.Add'}), was not considered a problem as there were other ways of accessing the object(ExcelUse {'Application.Charts(Chart1).ChartWizard(' &?ex{'Range(A5:C5)'}&','&xl3DPie&',7,1,0,0,2,,,')})

At the time there was only one known instance where this was not the case. This is probably still true today as the OLE standard states that an object implement a collection, must also implement a method for accessing the objects by indexing.

Due to the special case mentioned above, when an object was created by one control and passed onto an other object as a parameter, a method which would be more or less transparent to the user, was implemented.

Calling a method which returns an IDispatchInterface is converted into a special representation (a '' followed by a number of digits). This special representation is recognized in a couple of places in the OLE library.

The place that you will find most useful is, when the special representation is in the place where an interface could occur in the property syntax it will replace any previous interface in the access of the properties or methods of the object. For example:

```
x=y{'charts.add()'}  
y{x&'p(7)')}
```

where y is an ole object and x is a cstring. This is an example of a method returning an interface and later this interface is used to access a method p with the parameter 7.

In this context a further complication arises from the reference counting used in OLE. Which means that if the object are used more than once it must have it's reference count increased before use.

```
x=y{'charts.add()'}  
y{PROP:AddRef}=x  
y{x&'p(7)'}  
y{x&'p(7)'} ;last use of x
```

## OLEDIRECTORY (get list of installed OLE/OCX)

**OLEDIRECTORY**( *list* , *flag* [, *bits* ] )

---

**OLEDIRECTORY** Gets a list of all installed OLE servers or OCX controls.

*list* The label of the QUEUE structure to receive the list.

*flag* An integer constant or variable that determines whether to get a list of OLE servers (*flag* = 0) or OCX controls (*flag* = 1).

*bits* An integer constant or variable that determines whether to get a list of 16-bit or 32-bit OCX controls. If one (1), it returns 16-bit OCX controls. If two (2), it returns 32-bit OCX controls. If three (3), it returns both 16-bit and 32-bit OCX controls. If omitted or zero, 16-bit programs return 16-bit OCX controls and 32-bit programs return 32-bit OCX controls.

*Note: With 16-bit support deprecated in this release, the 32-bit mode should be used exclusively.*

**OLEDIRECTORY** gets a list of all installed OLE servers or OCX controls and places it in the *list* QUEUE. The *list* QUEUE must be declared with the same structure as the OleQ QUEUE declaration in EQUATES.CLW:

```
OleQ    QUEUE,TYPE
Name    CSTRING(64)    !Name of the OLE Server application
CLSID   CSTRING(64)    !Unique identifier for the operating system
ProgID  CSTRING(64)    !Registry name, such as: Excel.Sheet.5
END
```

### Example:

```
ResultQ QUEUE (OleQ) .           !Declare ResultQ the same as OleQ QUEUE in EQUATES.CLW
CODE
OLEDIRECTORY(ResultQ,0)          !Get list of installed OLE Servers & put it in ResultQ
                                !then let the user pick one:
?OleControl{PROP:Create} = SelectOleServer(ResultQ)
```

!User's OLE Server choice procedure:

SelectOleServer PROCEDURE(OleQ PickQ)

```
window WINDOW('Choose OLE Server'),AT(,,122,159),CENTER,SYSTEM,GRAY
LIST,AT(11,8,100,120),USE(?List),HVSCROLL, |
    FORMAT('146L~Name~@s64@135L~CLSID~@s64@20L~ProgID~@s64@'),FROM(PickQ)
BUTTON('Select'),AT(42,134),USE(?Select)
END
```

```
CODE
OPEN(window)
SELECT(?List,1)
ACCEPT
CASE ACCEPTED()
OF ?Select
GET(PickQ,CHOICE(?List))
IF ERRORCODE() THEN STOP(ERROR()) END
POST(EVENT:CloseWindow)
END
END
RETURN(PickQ.ProgID)
```



## OLE custom control Overview

OLE custom controls commonly have the .OCX file extension. Therefore, they are commonly referred to as .OCX controls. .OCX controls are similar to .VBX controls in that they are self-contained and designed to perform a specific task when used in a program. However, .OCX controls do not have the limitations that .VBX controls have, since .OCX controls are built to Microsoft's OLE 2 specification, which was designed with cross-language compatibility in mind (to languages other than just Visual Basic).

## .OCX Control Properties

<u>Name</u>	<u>Description</u>
PROP:Create	The CREATE attribute (blank if none). (WRITE ONLY)
PROP:DesignMode	Is the .OCX control in the container in design-mode (does it have a size border around it)? (WRITE ONLY)
PROP:Ctrl	Is this an .OCX control? (READ ONLY)
PROP:GrabHandles	Makes the .OCX control show grab handles. (WRITE ONLY)
PROP:OLE	Is there an OCX or OLE object in the container? (READ ONLY)
PROP:IsRadio	Is this an OCX radio button? (READ ONLY)
PROP:LastEventName	Gets the name of the last event sent to an .OCX control. (READ ONLY)
PROP:SaveAs	<p>Saves the object to an OLE Compound Storage file. (WRITE ONLY)</p> <p>The syntax for placing the object in the file is <i>'filename\!component'</i> For example:</p> <pre>?controlx{PROP:SaveAs} = 'myfile\!objectx'</pre>
PROP:ReportException	Report OLE exceptions (for debug). (WRITE ONLY)
PROP:DoVerb	Executes an OLE doverb command from the following set of commands (WRITE ONLY):
DOVERB:Primary (0)	Calls the object's primary action. The object, not the container, determines this action. If the object supports in-place activation, the primary verb usually activates the object in-place.
DOVERB:Show (-1)	Tells the object to show itself for editing or viewing. Called to display newly inserted objects for initial editing and to show link sources. This is usually an alias for some

	other object-defined action.
DOVERB:Open (-2)	Tells the object to open itself for editing in a separate window from its container (this includes objects that support in-place activation). If the object does not support in-place activation, this has the same action as DOVERB:Show.
DOVERB:Hide (-3)	Tells the object to remove its user interface. This applies only to objects activated in-place.
DOVERB:UIActivate (-4)	Activates the object in-place, along with its full set of user-interface tools, including menus, toolbars, and its name in the title bar of the container window.
DOVERB:InPlaceActivate (-5)	Activates the object in-place without displaying tools (menus and toolbars) that end-users need to change the behavior or appearance of the object.
DOVERB:DiscardUndoState (-6)	Tells the object to discard any undo state that it may be maintaining without deactivating the object.
DOVERB:Properties (-7)	Invokes the modal system property browser for the object to allow the user to set its properties.
PROP:Language	The number for the language used for OLE Automation or OCX Method. The number for US English is 0409H, and other language numbers can be computed from the data in the WINNT.H file in the MS Windows SDK. (READ/WRITE)

## .OCX Control Properties

<u>Name</u>	<u>Description</u>
PROP:Create	The CREATE attribute (blank if none). (WRITE ONLY)
PROP:DesignMode	Is the .OCX control in the container in design-mode (does it have a size border around it)? (WRITE ONLY)
PROP:Ctrl	Is this an .OCX control? (READ ONLY)
PROP:GrabHandles	Makes the .OCX control show grab handles. (WRITE ONLY)
PROP:OLE	Is there an OCX or OLE object in the container? (READ ONLY)
PROP:IsRadio	Is this an OCX radio button? (READ ONLY)
PROP:LastEventName	Gets the name of the last event sent to an .OCX control. (READ ONLY)
PROP:SaveAs	<p>Saves the object to an OLE Compound Storage file. (WRITE ONLY)</p> <p>The syntax for placing the object in the file is <i>'filename\!component'</i> For example:</p> <pre>?controlx{PROP:SaveAs} = 'myfile\!objectx'</pre>
PROP:ReportException	Report OLE exceptions (for debug). (WRITE ONLY)
PROP:DoVerb	Executes an OLE doverb command from the following set of commands (WRITE ONLY):
DOVERB:Primary (0)	Calls the object's primary action. The object, not the container, determines this action. If the object supports in-place activation, the primary verb usually activates the object in-place.
DOVERB:Show (-1)	Tells the object to show itself for editing or viewing. Called to display newly inserted objects for initial editing and to show link sources. This is usually an alias for some other object-defined action.
DOVERB:Open (-2)	Tells the object to open itself for editing in a separate window from its container (this includes objects that support in-place activation). If the object does not support in-place activation, this has the same action as DOVERB:Show.
DOVERB:Hide (-3)	Tells the object to remove its user interface. This applies only to objects activated in-

	place.
DOVERB:UIActivate (-4)	Activates the object in-place, along with its full set of user-interface tools, including menus, toolbars, and its name in the title bar of the container window.
DOVERB:InPlaceActivate (-5)	Activates the object in-place without displaying tools (menus and toolbars) that end-users need to change the behavior or appearance of the object.
DOVERB:DiscardUndoState (-6)	Tells the object to discard any undo state that it may be maintaining without deactivating the object.
DOVERB:Properties (-7)	Invokes the modal system property browser for the object to allow the user to set its properties.
PROP:Language	The number for the language used for OLE Automation or OCX Method. The number for US English is 0409H, and other language numbers can be computed from the data in the WINNT.H file in the MS Windows SDK. (READ/WRITE)

## Calling OLE Object Methods

Both OLE Automation to an OLE Server application and OCX/ActiveX objects publish methods (procedures) that you can call to have the object perform specified actions. Since OCXs are the OLE successors to VBX controls, most OCX vendors provide their example code using Visual Basic (VB) syntax. Those that can be used in C++ programs usually also have C++ code examples.

Translating these examples to the relevant Clarion code usually requires some knowledge of VB or C++. This section demonstrates the most common types of method calls in VB examples and how they translate to Clarion.

## Method Syntax Overview

To call any OLE/OCX method, you use Clarion's Property Syntax. You specify the control to which the method or property belongs as the field equate label of the OLE control, then write the method call in a string constant inside the curly braces ({}).

The example code supplied with most OLE controls uses the VB/C++ "dot property" syntax to specify the name of the control and the method to call or the property to set. For example, the following VB code:

```
ControlName.AboutBox
```

translates to Clarion as:

```
?Ole{ 'AboutBox' }
```

This code displays the "About" dialog for the *ControlName* control. You might also see this example's VB code as:

```
Form1.ControlName.AboutBox
```

This form simply specifies the dialog containing the *ControlName* object. The Clarion translation for this is still the same.

The OLE/OCX object is always referenced in Clarion code by the field equate label of the Clarion OLE control, no matter what the name of the control is in VB, because the object's registered name is specified in the CREATE or OPEN attribute of the OLE control. Therefore, the Clarion runtime library only needs to know the field equate label to know exactly which object is being referenced.

### **Translating VB's "With" Syntax**

Many OLE/OCX code examples use the VB *With ... End With* structure to associate multiple property assignments and/or method calls with a single object. In this case, the object is named in the *With* statement and all the property assignments and method calls within the structure begin with the dot separator, then the name of the property to set or method to call. For example, the following VB code:

```
With Form1.VtChart1
    'displays a 3d chart with 8 columns and 8 rows data
    .chartType = VtChChartType3dBar
    .columnCount = 8
    .rowCount = 8
    For column = 1 To 8
        For row = 1 To 8
            .column = column
            .row = row
            .Data = row * 10
        Next row
    Next column
    'use the chart as the backdrop of the legend
    .ShowLegend = True
End With
```

translates to Clarion as:

```
!displays a 3d chart with 8 columns and 8 rows data
?Ole{'chartType'} = VtChChartType3dBar
?Ole{'columnCount'} = 8
?Ole{'rowCount'} = 8
LOOP column# = 1 TO 8
    LOOP row# = 1 TO 8
        ?Ole{'column'} = column#
        ?Ole{'row'} = row#
        ?Ole{'Data'} = row# * 10
    END
END
!use the chart as the backdrop of the legend
?Ole{'ShowLegend'} = True
```

Since Clarion has no direct equivalent to the VB *With ... End With* structure, you just explicitly name the OLE control's field equate label on each property assignment or method call. The single quote (') in VB code indicates a comment.

VB allows nesting these *With ... End With* structures, so you may need to "travel" back to find the object's name. This example demonstrates nested VB *With* structures:

```
With MyObject
    .Height = 100
    .Caption = "Hello World"
    With .Font
        .Color = Red
        .Bold = True
    End With
End With
' Same as MyObject.Height = 100.
' Same as MyObject.Caption = "Hello World".
' Same as MyObject.Font.Color = Red.
' Same as MyObject.Font.Bold = True.
```

which translates to Clarion as:

```
?Ole{'Height'} = 100
?Ole{'Caption'} = 'Hello World'
?Ole{'Font.Color'} = Red
?Ole{'Font.Bold'} = True
! MyObject.Height = 100
! MyObject.Caption = "Hello World"
! MyObject.Font.Color = Red
! MyObject.Font.Bold = True
```

## Parameter Passing to OLE/OCX Methods

Just as in Clarion, there are two ways to pass parameters in VB: by value, or by address (by reference). The VB keywords *ByVal* and *ByRef* specify these two methods in VB code. These terms mean the same thing in VB as in Clarion—passing a parameter by value passes a copy of the contents of the variable, while passing a parameter by reference (VB's default) passes the address of the variable itself so the receiving method can modify its contents.

### Using Parentheses

VB syntax can either use parentheses surrounding the parameter list or not. If the VB method does not return a value, or you don't care about the returned value, the parameters are passed in VB without parentheses, like this:

```
VtChart1.InsertColumns 6,3
```

If you do want the returned value, then the parameters are passed in VB within parentheses, like this:

```
ReturnValue = VtChart1.InsertColumns (6,3)
```

In Clarion syntax, parameters are always passed within parentheses. Therefore, these two examples translate to:

```
?Ole{'InsertColumns(6,3)'}
ReturnValue = ?Ole{'InsertColumns(6,3)'}
```

### Passing Parameters By Value

Value parameters are passed to OLE/OCX objects as strings (except Boolean parameters). Since OLE/OCX objects are supposed to cast their input to the correct data types using a VARIANT mechanism (similar to Clarion's data type conversion), this allows the most compatibility with the least work. Any string which requires a double quote mark (") needs to include two ("").

Value parameters may be passed to OLE/OCX object methods as constants or variables. The examples above pass parameters as constants. You may not have blank spaces in the constant unless the parameter is contained in double quotes (for example, "Value with blanks").

There are two ways to pass a Clarion variable to an OLE/OCX method by value: concatenated into the string constant that calls the method, or by using BIND on the variable name and placing the name of the variable directly in the string constant that calls the method. For example, to rewrite the above example passing the variable values in a concatenated string:

```
ColumnNumber = 6
NumberOfColumns = 3
?Ole{'InsertColumns(' & ColumnNumber & ',' & NumberOfColumns & ')'}
!Same as ?Ole{'InsertColumns(6,3)'}
```

The second way to pass variables by value is to BIND them and name them in the string constant, like this:

```
BIND('ColumnNumber',ColumnNumber)
BIND('NumberOfColumns',NumberOfColumns)
?Ole{'InsertColumns(ColumnNumber,NumberOfColumns)'}
!Same as ?Ole{'InsertColumns(6,3)'}
```

This method makes the code more easily readable, but you must first BIND the variables to pass.

### **Passing Parameters By Address (Reference)**

Parameters passed by address may be passed to OLE/OCX object methods only as named variables in the constant string. Therefore, you must use BIND on the variable name and place the name of the variable directly in the string constant that calls the method with an ampersand prepended to the variable name to signal that the variable is being passed by reference. For example, to re-write the above example to pass the variables by address:

```
ColumnNumber = 6
NumberOfColumns = 3
BIND('ColumnNumber',ColumnNumber)
BIND('NumberOfColumns',NumberOfColumns)
?Ole{ 'InsertColumns(&ColumnNumber,&NumberOfColumns)' }
```

Parameters passed by address are passed to OLE/OCX objects as the data type of the bound variable (except Boolean parameters). The variables are actually passed as temporary string variables which the Clarion library automatically dereferences so that any modifications to the passed variable by the OLE/OCX method are carried back to the original variable passed.

### **Boolean Parameters**

Boolean parameters (1/0 or True/False) are passed either by value or by address. When passing by value, you may either pass a constant (a 1 or 0, or the words TRUE or FALSE), like this:

```
?Ole{ 'ODBCConnect(&DataSource,1,&RetVal)' }
?Ole{ 'ODBCConnect(&DataSource,TRUE,&RetVal)' }
```

or pass a variable name (after BINDing it) within a "bool()" call, like this:

```
BoolParm = 1
BIND('BoolParm',BoolParm)
?Ole{ 'ODBCConnect(&DataSource,bool(BoolParm),&RetVal)' }
```

Bool() is a construct that tells the property expression parser to pass it as a Boolean value. Bool() is only valid within an OLE/OCX method call string.

To pass by reference, simply prepend an ampersand to the variable name within the bool() construct, like this:

```
BIND('BoolParm',BoolParm)
?Ole{ 'ODBCConnect(&DataSource,bool(&BoolParm),&RetVal)' }
```



## **Named Parameters**

In VB, there are two ways to pass parameters: positionally, or as "named arguments." Positional parameters imply that you must either pass a parameter or place a comma place-holder for any omitted parameters in the method call. Since some methods can receive a large number of parameters, this can result in a long string of comma place-holders when you simply want to pass one or two parameters to the method. VB solves this problem by allowing programmers to "name" the parameters, which allows the programmer calling the method to only pass the few parameters they choose to without regard to their position or order within the parameter list.

Named parameters are not universally supported in VB, so the OLE/OCX vendor needs to have written their methods specifically to support them. The OLE/OCX help file should state whether named parameters are supported, or you can use VB's Object Browser to determine whether they are supported and the parameter names to use.

The VB syntax for named parameters uses `:=` to assign the value to the parameter's name. For example, for the following VB statement:

```
OpenIt(Name:=, [Exclusive]:=, [ReadOnly]:=, [Connect]:=)
```

you can call the method in VB using positional parameters, like this:

```
Db = OpenIt("MyFile",False,False,"ODBC;UID=Fred")
```

which translates to Clarion (using positional parameters) as:

```
Db = ?Ole{ 'OpenIt("MyFile",False,False,"ODBC;UID=Fred") ' }
```

You can call the same method in VB using named parameters, like this (the underscore character is VB's line continuation character):

```
Db = OpenIt(Name:="MyFile",Exclusive:=False,ReadOnly:=False, _ Connect:="ODBC;UID=Fred")
```

which translates to Clarion as:

```
Db = ?Ole{ 'OpenIt(Name="MyFile",Exclusive=False,ReadOnly=False, ' & |  
'Connect="ODBC;UID=Fred") ' }
```

or you can pass the parameters in VB in a different order:

```
Db = OpenIt(Connect:="ODBC;UID=Fred", _  
Name:="MyFile", _  
ReadOnly:=False, _  
Exclusive:=False)
```

which translates to Clarion as:

```
Db = ?Ole{ 'OpenIt(Connect="ODBC;UID=Fred",Name="MyFile",' & |  
'Exclusive=False,ReadOnly=False') ' }
```

## OCX Library Procedures

### OCXREGISTERPROPEDIT (install property edit callback)

**OCXREGISTERPROPEDIT**( *control* , *procedure* )

---

**OCXREGISTERPROPEDIT**    Installs a property edit callback function.

*Control*                      An integer expression containing the field number or field equate label of the OLE control to affect.

*Procedure*                    The label of the property edit callback function for the *control*.

**OCXREGISTERPROPEDIT** installs a property edit callback *procedure* for the *control*. The callback function *procedure* controls property edits to the *control* by allowing or disallowing them.

**Example:**

```
OCXREGISTERPROPEDIT (?OleControl, CallbackFunc)
```

**See Also:**

Callback Functions

## OCXREGISTERPROPCHANGE (install property change callback)

**OCXREGISTERPROPCHANGE**( *control* , *procedure* )

---

**OCXREGISTERPROPCHANGE**    Installs a property change callback procedure.

*control*                                      An integer expression containing the field number or field equate label of the OLE control to affect.

*procedure*                                      The label of the property change callback procedure for the *control*.

**OCXREGISTERPROPCHANGE** installs a property change callback *procedure* for the *control*. The callback *procedure* is called when a property of the *control* has been changed.

**Example:**

```
OCXREGISTERPROPCHANGE (?OleControl, CallbackProc)
```

**See Also:**

Callback Functions

## OCXREGISTEREVENTPROC (install event processing callback)

**OCXREGISTEREVENTPROC**( *control* , *procedure* )

---

**OCXREGISTEREVENTPROC**    Installs an OCX event callback procedure.

*control*                      An integer expression containing the field number or field equate label of the OLE control to affect.

*procedure*                    The label of the event processing callback procedure for the *control*.

**OCXREGISTEREVENTPROC** installs an OCX event callback *procedure* for the *control*. The callback *procedure* is called when any event is posted by the operating system for the *control*.

**Example:**

```
OCXREGISTEREVENTPROC (?OleControl,CallbackProc)
```

**See Also:**

Callback Functions

## OCXUNREGISTERPROPEDIT (un-install property edit callback)

**OCXUNREGISTERPROPEDIT**( *control* )

---

**OCXUNREGISTERPROPEDIT** Un-installs a property edit callback procedure.

*control*                                      An integer expression containing the field number or field equate label of the OLE control to affect.

**OCXUNREGISTERPROPEDIT** un-installs a property edit callback *procedure* for the *control*.

**Example:**

```
OCXUNREGISTERPROPEDIT (?OleControl)
```

**See Also:**

Callback Functions

## OCXUNREGISTERPROPCHANGE (un-install property change callback)

**OCXUNREGISTERPROPCHANGE**( *control* )

---

**OCXUNREGISTERPROPCHANGE** Un-installs a property change callback procedure.

*Control* An integer expression containing the field number or field equate label of the OLE control to affect.

**OCXUNREGISTERPROPCHANGE** un-installs a property change callback *procedure* for the *control*.

**Example:**

```
OCXUNREGISTERPROPCHANGE (?OleControl)
```

**See Also:**

Callback Functions

## OCXUNREGISTEREVENTPROC (un-install event process callback)

**OCXUNREGISTEREVENTPROC**( *control* )

**OCXUNREGISTEREVENTPROC** Un-installs an OCX event callback procedure.

*control* An integer expression containing the field number or field equate label of the OLE control to affect.

**OCXUNREGISTEREVENTPROC** un-installs an OCX event callback *procedure* for the *control*.

**Example:**

```
OCXUNREGISTEREVENTPROC (?OleControl)
```

**See Also:**

Callback Functions

## OCXGETPARAMCOUNT (return number of parameters for current event)

**OCXGETPARAMCOUNT**( *reference* )

---

**OCXGETPARAMCOUNT** Returns the number of parameters associated with the current OCX event.

*Reference* The label of the first parameter of the event processing callback procedure.

**OCXGETPARAMCOUNT** returns the number of parameters associated with the current .OCX event. This procedure is only valid when the .OCX event processing callback function is active.

**Return Data Type:** USHORT

**Example:**

```
OEvent PROCEDURE (Reference, OleControl, CurrentEvent) !Event processing callback proc
Count LONG
Res CSTRING(200)
Parm CSTRING(30)
CODE
IF CurrentEvent <> OCXEVENT:MouseMove !Eliminate mouse move events
  Res = 'Control ' & OleControl & ' Event ' & OleControl{PROP:LastEventName} & ':'
  LOOP Count = 1 TO OCXGETPARAMCOUNT (Reference) !Cycle through all parameters
    Parm = OCXGETPARAM (Reference, Count) !getting each parameter name
    Res = CLIP (Res) & ' ' & Parm !and concatenate them together
  END
  GlobalQue = Res !Assign to a global QUEUE
  ADD (GlobalQue) !add the entry for later display
END !of all the OCX events and their
RETURN (True) !parameters
```

**See Also:**

Callback Functions

OCXGETPARAM



## OCXGETPARAM (return current event parameter string)

**OCXGETPARAM**( *reference* ,*number* )

**OCXGETPARAM** Returns the value of a parameter associated with the current OCX event.

*reference*                      The label of the first parameter of the event processing callback procedure.

*number*                        The number of the parameter to retrieve.

**OCXGETPARAM** returns the value of the *number* parameter associated with the current .OCX event. This procedure is only valid when the .OCX event processing callback function is active.

**Return Data Type:**    STRING

**Example:**

```
OEvent  PROCEDURE (Reference,OleControl,CurrentEvent)  !Event processing callback proc
Count  LONG
Res     CSTRING(200)
Parm    CSTRING(30)
CODE
IF CurrentEvent <> OCXEVENT:MouseMove                !Eliminate mouse move events
  Res = 'Control ' & OleControl & ' Event ' & OleControl{PROP:LastEventName} & ':'
  LOOP Count = 1 TO OCXGETPARAMCOUNT(Reference)    !Cycle through all parameters
    Parm = OCXGETPARAM(Reference,Count)              !getting each parameter name
    Res = CLIP(Res) & ' ' & Parm                      !and concatenate them together
  END
  GlobalQue = Res                                     !Assign to a global QUEUE
  ADD(GlobalQue)                                     !add the entry for later display
END                                                    !of all the OCX events and their
RETURN(True)                                          !parameters
```

**See Also:**

Callback Functions

OCXSETPARAM

OCXGETPARAMCOUNT

## OCXSETPARAM (set current event parameter string)

**OCXSETPARAM**( *reference* , *number* , *value* )

---

**OCXSETPARAM** Sets the value of a parameter associated with the current OCX event.

*reference*                The label of the first parameter of the event processing callback procedure.

*number*                The number of the parameter to set.

*value*                A string constant or variable containing the value to set.

**OCXSETPARAM** sets the value of the *number* parameter associated with the current event. This is only allowed on parameters that are passed by address (see the OCX control's documentation for valid parameters to set). If the modification is not allowed it will be ignored. This procedure is only valid when the .OCX event processing callback function is active.

### Example:

```
OEvent  PROCEDURE (Reference,OleControl,CurrentEvent)  !Event processing callback proc
Count  LONG
Res     CSTRING(200)
Parm    CSTRING(30)
CODE
IF CurrentEvent <> OCXEVENT:MouseMove                !Eliminate mouse move events
  Res = 'Control ' & OleControl & ' Event ' & OleControl{PROP:LastEventName} & ':'
  LOOP Count = 1 TO OCXGETPARAMCOUNT(Reference)      !Cycle through all parameters
    Parm = OCXGETPARAM(Reference,Count)                !getting each parameter name
    Res = CLIP(Res) & ' ' & Parm                        !and concatenate them together
    OCXSETPARAM(Reference,1,'1')                       !Change the parameter's value
  END
  GlobalQue = Res                                     !Assign to a global QUEUE
  ADD(GlobalQue)                                       !add the entry for later display
END                                                    !of all the OCX events and their
RETURN(True)                                          !parameters
```

### See Also:

Callback Functions

OCXGETPARAM

## OCXLOADIMAGE (return an image object)

**OCXLOADIMAGE**( *name* )

---

**OCXLOADIMAGE** Returns an image object.

*name*                      A string expression containing the name of the file or resource to load.

**OCXLOADIMAGE** returns an image object. This image object can be assigned to any control that uses an image object (such as a VB imagelist control).

**Return Data Type:**    STRING

**Example:**

```
!Add an image to an ImageList control:  
?imagelist{ 'ListImages.Add(,, ' & OCXLOADIMAGE('CLOCK.BMP') & ' ' ) }
```



## Appendix B - Events

### Modal Events



The following Events must always be treated as "modal":

- EVENT:LoseFocus
- EVENT:GainFocus
- EVENT:Dragging
- EVENT:Contracting
- EVENT:Expanding
- EVENT:PreAlertKey
- EVENT:TabChanging
- EVENT:Move
- EVENT:Size
- EVENT:Restore
- EVENT:Maximize
- EVENT:Iconize
- EVENT:Sized
- EVENT:Selected
- EVENT:Selecting

Also, if a list box has the IMM attribute

- EVENT:ScrollUp
- EVENT:ScrollDown
- EVENT:PageUp
- EVENT:PageDown
- EVENT:ScrollTop
- EVENT:ScrollBottom
- EVENT:ScrollTrack
- EVENT:ScrollDrag

When we refer to an event as "modal", it means that until the event is completed the runtime library can't continue its normal work. The main rule for writing code that responds to these events is that the event must be completed within a "finite" period of time.

This means that the code you write for handling "modal" events should not invoke dialogs, include inner ACCEPT loops, call Message Boxes, or anything similar that would prevent the ACCEPT loop from completing the processing of the event. When your program needs to do something like this upon processing one of these events, a custom event should be posted to the front of the event queue. For example:

```
CASE EVENT()  
...  
OF EVENT:GainFocus  
    POST(MyGainFocus,,, TRUE) !Post a user defined event to handle GainFocus action  
...  
OF MyGainFocus  
    <perform actions for gaining focus>  
...  
END
```

## Field-Independent Events



A **Field-independent** event does not relate to any one control but requires some program action (for example, to close a window, quit the program, or change execution threads). Most of these events cause the system to become modal for the period during which they are processing, since they require a response before the program may continue.

EVENT:AlertKey	EVENT:BuildDone
EVENT:BuildFile	EVENT:BuildKey
EVENT:CloseDown	EVENT:CloseWindow
EVENT:Completed	DDE Events
EVENT:Docked	EVENT:Undocked
EVENT:GainFocus	EVENT:Iconize
EVENT:Iconized	EVENT:LoseFocus
EVENT:Maximize	EVENT:Maximized
EVENT:Move	EVENT:Moved
EVENT:OpenWindow	EVENT:PreAlertKey
EVENT:Restore	EVENT:Restored
EVENT:Size	EVENT:Sized
EVENT:Timer	

## EVENT:AlertKey



The user pressed an ALRT attribute (or ALERT statement) hot key for an ALRT attribute on the window. This is the event on which you perform the action the user has requested by pressing the alert key.

## EVENT:BuildDone



The BUILD or PACK statement has completed re-building the keys. This is the event on which you perform any build cleanup code. If the user cancelled the BUILD, ERRORCODE 93 is set.

## EVENT:BuildFile



The BUILD or PACK statement is re-building the file. This is the event on which you inform your user of the progress of the build.

## EVENT:BuildKey



The BUILD or PACK statement is re-building the key. This is the event on which you inform your user of the progress of the build.

## EVENT:CloseDown



The application is closing. POSTing this event closes the application. This is the event on which you perform any application cleanup code.

When the Application frame is closing it receives an EVENT:CloseWindow first, then it sends an Event:CloseDown to all child windows. During that event if a child window does an ACCEPT loop CYCLE then the Application frame does not close. When the frame is closing the child windows only receive the EVENT:CloseDown and do not receive an Event:CloseWindow. The Application frame only receives the Event:CloseWindow and not the EVENT:CloseDown.



**Note:**

The IDE, and any programs generated by Clarion, do not automatically shut down when you shut down the Operating System. This allows the user to complete any critical processes or updates and prevents possible data corruption. If you need to shut down applications when the operating system shuts down, you will need to subclass the appropriate window messages in your target application.

**See Also:** ACCEPT, APPLICATION, EVENT:CloseWindow.

## EVENT:CloseWindow



The window is closing. POSTing this event closes the window. This is the event on which you perform any window cleanup code. Performing an ACCEPT loop CYCLE prevents the Window from closing.

A child window may also be closed by an EVENT:CloseDown sent by the frame when it has received an Event:CloseWindow, in that case no EVENT:CloseWindow occurs before the child window closes.

An Event:CloseWindow can result from a number of actions by the user:

- Pressing the Close X on the Top-Right of the Window
- Selecting Close from the System Menu
- Pressing Escape or Ctrl+F4
- Pressing Ctrl+F4 closes a Child Window
- Pressing Alt+F4 posts Event:CloseWindow to the Application Frame

Rather than trapping any of these individual actions it is best to trap the Event:CloseWindow event.

Performing a BREAK within the ACCEPT LOOP ends the loop immediately and does not send any events. Performing a BREAK in the Frame is generally a bad idea.

**See Also:** ACCEPT, WINDOW, EVENT:CloseDown.

## EVENT:Completed



AcceptAll (non-stop) mode has finished processing all the window's controls. This is the event on which you have executed all data entry validation code for the controls in the window and can safely write to disk.

## DDE Events



### **EVENT:DDEadvise**

A client has requested continuous updates of a data item from this Clarion DDE server application. This is the event on which you execute DDEWRITE to provide the data to the client every time it changes.

### **EVENT:DDEclosed**

A DDE server has terminated the DDE link to this Clarion client application.

### **EVENT:DDEdata**

A DDE server has supplied an updated data item to this Clarion client application.

### **EVENT:DDEexecute**

A client has sent a command to this Clarion DDE server application (if the client is another Clarion application, it has executed a DDEEXECUTE statement). This is the event on which you determine the action the client has requested and perform it, then execute a CYCLE statement to signal positive acknowledgement to the client that sent the command.

### **EVENT:DDEpoke**

A client has sent unsolicited data to this Clarion DDE server application. This is the event on which you determine what the client has sent and where to place it, then execute a CYCLE statement to signal positive acknowledgement to the client that sent the data.

### **EVENT:DDErequest**

A client has requested a data item from this Clarion DDE server application. This is the event on which you execute DDEWRITE to provide the data to the client once.

## EVENT:Docked



A dockable toolbox window has been docked or its docked position has been changed.

## EVENT:Undocked



A dockable toolbox window has been undocked.

## EVENT:GainFocus



The window is gaining input focus from another thread. This is the event on which you restore any data you saved in EVENT:LoseFocus. The system is modal during this event.

EVENT:GainFocus is not generated until EVENT:LoseFocus is processed (if focus was on another window of the same program).

## EVENT:Iconize



The user is minimizing a window with the IMM attribute. If a CYCLE statement is encountered in the code to process this event, the EVENT:Iconized is not generated and the action is aborted. This is the event on which you can prevent users from minimizing a window. The system is modal during this event.

## EVENT:Iconized



The user has minimized a window with the IMM attribute. This is the event on which you readjust anything that is screen-size-dependent.

## EVENT:LoseFocus



The window is losing input focus to another thread. This is the event on which you save any data that could be at risk of being changed by another thread. The system is modal during this event.

## EVENT:Maximize



The user is maximizing a window with the IMM attribute. If a CYCLE statement is encountered in the code to process this event, EVENT:Maximized is not generated and the action is aborted. This is the event on which you can prevent users from maximizing a window. The system is modal during this event.

## EVENT:Maximized



The user has maximized a window with the IMM attribute. This is the event on which you readjust anything that is screen-size-dependent.

## EVENT:Move



The user is moving a window with the IMM attribute. If a CYCLE statement is encountered in the code to process this event, EVENT:Moved is not generated and the action is aborted. This is the event on which you can prevent users from moving a window. The system is modal during this event.

## EVENT:Moved



The user has moved a window with the IMM attribute. This is the event on which you readjust anything that is screen-position-dependent.

## EVENT:NestedLoop



Posted on entry to a nested ACCEPT loop.

## EVENT:Notify



A NOTIFY statement has been executed. This event is used by the receiver thread to detect that a NOTIFY has been sent.

## EVENT:OpenWindow



The window is opening. This is the event on which you perform any window initialization code.

## EVENT:PreAlertKey



The user pressed an ALRT attribute (or ALERT statement) hot key for an ALRT attribute on the window. If a CYCLE statement executes in the code to process this event, the normal library action for the keystroke executes before EVENT:AlertKey generates. This event allows you to specify whether the normal library action for the keystroke executes or not, in addition to the code you place in EVENT:AlertKey. The system is modal during this event.

## EVENT:Restore



The user is restoring the previous size of a window with the IMM attribute. If a CYCLE statement is encountered in the code to process this event, EVENT:Restored is not generated and the action is aborted. This is the event on which you can prevent users from restoring a window. The system is modal during this event.

## EVENT:Restored



The user has restored the previous size of a window with the IMM attribute. This is the event on which you readjust anything that is screen-size-dependent.

## EVENT:Resume

### Note:

Due to the change in the thread model in Clarion 6, this event is no longer available for use in Clarion 6.

The window still has input focus and is regaining control from an EVENT:Suspend. The system is modal during this event.

## EVENT:Size



The user is resizing a window with the IMM attribute. If a CYCLE statement is encountered in the code to process this event, EVENT:Sized is not generated and the action is aborted. This is the event on which you can prevent users from resizing a window. The system is modal during this event.

## EVENT:Sized



The user has resized a window with the IMM attribute. This is the event on which you readjust anything that is screen-size-dependent.

## EVENT:Suspend

### Note:

Due to the change in the thread model in Clarion 6, this event is no longer available for use in Clarion 6.

The window still has input focus but is giving control to another thread to process timer events. The system is modal during this event.

## EVENT:Timer



The TIMER attribute has triggered. This is the event on which you perform any timed actions, such as clock display, or background record processing for reports or batch processes.

## Field-Specific Events

### EVENT:Accepted



The user has entered data or made a selection then pressed TAB or CLICKED the mouse to move on to another control. This is the event on which you should perform any data input validation code.

**See Also:** PROP:Touched

### EVENT:AlertKey



The user pressed an ALRT attribute hot key for an ALRT attribute on the control. This is the event on which you perform the action the user has requested by pressing the alert key.

### EVENT:ColumnResize



On a LIST control with an M in the FORMAT attribute string, the user has resized a column.

### EVENT:Contracted



On a LIST control with T in the FORMAT attribute string, the user has clicked on a tree expansion box.

List boxes with a Tree modifier (T) have a *Level* field (a LONG) following the tree column. On initial display, if this Level is negative, the branch is contracted. (Note: if the line has no children and a negative level, it will show a [+] when it should not, so do not arbitrarily make every level negative, only do so for parent levels.)

As the user clicks the [+] [-] icons the tree is expanded and contracted. This does *not* change the Level sign but does post "expanded" and "contracted" events. On this event, you can manually update the level sign and save the contracted state of the tree.

To determine what row is currently selected, query the PROPLIST:MouseDownRow list box property.



**Example:**

```

OF EVENT:Expanded
  GET(PriorQ, 0 + ?List:PriorQ{PROPLIST:MouseDownRow} ) !Row clicked on [+] sign
  !since PROP's are strings and GET is overloaded with (Q,String) you
  !must convert to number with 0+proplist:xxx (or other ways)
  !CHOICE(?List:PriorQ) will not work since the record is not
  !selected when clicking on the [+]
  IF ~ERRORCODE()
    PriorQ:Level=ABS(PriorQ:Level)          !Expanded, so make Level Positive
    PUT(PriorQ)
  END

OF EVENT:Contracted
  GET(PriorQ, 0 + ?List:PriorQ{PROPLIST:MouseDownRow} ) !Row clicked on [-] sign
  IF ~ERRORCODE()
    PriorQ:Level = -ABS(PriorQ:Level)      !Contracted, make Level Negative
    PUT(PriorQ)
  END

```

You can also expand/contract parents by double clicking on a row. You can tell the difference by examining ?List:PriorQ{PROPLIST:MouseDownZone}=LISTZONE:ExpandBox or alerting the MouseLeft2 keycode.

**EVENT:Contracting**

On a LIST control with T in the FORMAT attribute string, the user has clicked on a tree contraction box. If a CYCLE statement is encountered in the code to process this event, the EVENT:Contracted is not generated and the contraction is aborted. The system is modal during this event.

**EVENT:Drag**

The user began a valid drag operation and released the mouse button. This event is posted to the control from which the user is dragging. This is the event on which you set the program to pass the dragged data to the drop target.

**See Also:** DRAGID, SETDROPID

## EVENT:Dragging



The user is dragging the mouse from a control with the DRAGID attribute and the mouse cursor is over a valid potential drop target. This event is posted to the control from which the user is dragging. This is the event on which you can change the mouse cursor to indicate a valid drop target.

**See Also:** SETCURSOR

## EVENT:Drop



The user released the mouse button over a valid drop target. This event is posted to the drop target control. This is the event on which you receive the dragged data.

**See Also:** DROPID

## EVENT:DroppedDown



On a LIST or COMBO control with the DROP attribute, the list has dropped. This is the event on which you can hide other controls that the droplist covers to prevent "screen clutter" from distracting the user.

## EVENT:DroppingDown



On a LIST or COMBO control with the DROP attribute, the user pressed the down arrow button. This is the event on which you get the records when "demand-loading" the list.

## EVENT:Expanded



On a LIST control with T in the FORMAT attribute string, the user has clicked on a tree expansion box.

List boxes with a Tree modifier (T) have a *Level* field (a LONG) following the tree column. On initial display, if this Level is negative, the branch is contracted. (Note: if the line has no children and a negative level, it will show a [+] when it should not, so do not arbitrarily make every level negative, only do so for parent levels.)

As the user clicks the [+] [-] icons the tree is expanded and contracted. This does *not* change the Level sign but does post "expanded" and "contracted" events. On this event, you can manually update the level sign and save the contracted state of the tree.

To determine what row is currently selected, query the PROPLIST:MouseDownRow list box property.

### Example:

```

OF EVENT:Expanded
  GET(PriorQ, 0 + ?List:PriorQ{PROPLIST:MouseDownRow} ) !Row clicked on [+] sign
  !since PROP's are strings and GET is overloaded with (Q,String) you
  !must convert to number with 0+proplist:xxx (or other ways)
  !CHOICE(?List:PriorQ) will not work since the record is not
  !selected when clicking on the [+]
  IF ~ERRORCODE()
    PriorQ:Level=ABS(PriorQ:Level)           !Expanded, so make Level Positive
    PUT(PriorQ)
  END

OF EVENT:Contracted
  GET(PriorQ, 0 + ?List:PriorQ{PROPLIST:MouseDownRow} ) !Row clicked on [-] sign
  IF ~ERRORCODE()
    PriorQ:Level = -ABS(PriorQ:Level)       !Contracted, make Level Negative
    PUT(PriorQ)
  END

```

You can also expand/contract parents by double clicking on a row. You can tell the difference by examining ?List:PriorQ{PROPLIST:MouseDownZone}=LISTZONE:ExpandBox or alerting the MouseLeft2 keycode.

## EVENT:Expanding



On a LIST control with T in the FORMAT attribute string, the user has clicked on a tree expansion box. If a CYCLE statement is encountered in the code to process this event, the EVENT:Expanded is not generated and the expansion is aborted. The system is modal during this event.

## EVENT:Locate



On a LIST control with the VCR attribute, the user pressed the locator (?) VCR button. This is the event on which you can unhide the locator entry control, if it is kept hidden.

## Mouse Events



### **EVENT:MouseDown**

On a REGION with the IMM attribute, a synonym for EVENT:Accepted (for code readability, only).

### **EVENT:MouseIn**

On a REGION with the IMM attribute, the mouse cursor has entered the region.

### **EVENT:MouseMove**

On a REGION with the IMM attribute, the mouse cursor has moved within the region.

### **EVENT:MouseOut**

On a REGION with the IMM attribute, the mouse cursor has left the region.

### **EVENT:MouseUp**

On a REGION with the IMM attribute, the mouse button has been released.

## EVENT:NewSelection



In a LIST, COMBO, SHEET, or SPIN control, this event generates when the current selection has changed. In an ENTRY control with the IMM attribute, this event generates whenever the contents of the control changes or the cursor moves. This is the event on which you perform any "housekeeping" to synchronize other controls with the currently highlighted record in the list, or determine that the user has entered all allowable data in the ENTRY.

## EVENT:PageDown



On a LIST or COMBO control with the IMM attribute, the user pressed PGDN. This is the event on which you get the next page of records when "page-loading" the list.

## EVENT:PageUp



On a LIST or COMBO control with the IMM attribute, the user pressed PGUP. This is the event on which you get the previous page of records when "page-loading" the list.

## EVENT:PreAlertKey (Field Specific)



The user pressed an ALRT attribute hot key for an ALRT attribute on the control. If a CYCLE statement is encountered in the code to process this event, the normal library action for the keystroke executes before EVENT:AlertKey generates. This event allows you to specify whether the normal library action for the keystroke executes or not, in addition to the code you place in EVENT:AlertKey. The system is modal during this event.

## EVENT:Rejected



The user has entered an invalid value for the entry picture, or an out-of-range number on a SPIN control. The REJECTCODE procedure returns the reason the user's input has been rejected and you can use the PROP:ScreenText property to get the user's input from the screen. This is the event on which you alert the user to the exact problem with their input.

## EVENT:ScrollBottom



On a LIST or COMBO control with the IMM attribute, the user pressed CTRL+PGDN. This is the event on which you get the last page of records when "page-loading" the list.

## EVENT:ScrollDown



On a LIST or COMBO control with the IMM attribute, the user has attempted to move the highlight bar down in the LIST. This is the event on which you get the next record when "page-loading" the list or just move the highlight bar when getting another record isn't needed.

## EVENT:ScrollDrag



On a LIST or COMBO control with the IMM attribute, the user has moved the scroll bar's "thumb" and has just released the mouse button. This is the event on which you dynamically scroll the displayed records based on the current value of PROP:VScrollPos.

## EVENT:ScrollTop



On a LIST or COMBO control with the IMM attribute, the user pressed CTRL+PGUP. This is the event on which you get the first page of records when "page-loading" the list.

## EVENT:ScrollTrack



On a LIST or COMBO control with the IMM attribute, the user is currently moving the scroll bar's "thumb." This is an event on which you can dynamically scroll the displayed records based on the current value of PROP:VScrollPos.

## EVENT:ScrollUp



On a LIST or COMBO control with the IMM attribute, the user has attempted to move the highlight bar up in the LIST. This is the event on which you get the previous record when "page-loading" the list or just move the highlight bar when getting another record isn't needed.

## EVENT:Selected



The control has received input focus. This is the event on which you should perform any data initialization code.

## EVENT:Selecting



This modal event is executed before placing EVENT:Selected in the window's event queue. If the ACCEPT is handling EVENT:Selecting and the CYCLE statement is encountered in the code executed for this event, EVENT:Selected is not generated. The Field Equate Label of the field to be selected can be obtained here using the FIELD() function.

EVENT:Selecting is *not* executed before the generation of EVENT:Selected if a menu item with the IMM attribute is selected, because EVENT:Selected is modal in this case.

Setting the initial focus to a control has been moved from the OPEN(Window) statement to the DISPLAY statement(which is also implicitly called from ACCEPT). Therefore, if there are no explicit DISPLAY statements between OPEN and ACCEPT, EVENT:Selecting will be posted prior to the first EVENT:Selected event.

If there is any DISPLAY statement called before ACCEPT, the first EVENT:Selected event is posted without any prior EVENT:Selecting event, because the ACCEPT loop has not been reached.

## EVENT:TabChanging



On a SHEET control, focus is about to pass to another tab. This is the event on which you perform any necessary "housekeeping" code for the tab you're leaving.





## App C - Runtime Properties

### PROP:AcceptAll

Property of a WINDOW which returns one (1) if AcceptAll mode is active and zero (0) if it is not, and may also be used to toggle AcceptAll (non-stop) mode. SELECT with no parameters usually initiates AcceptAll mode. This is a field edit mode in which each control in the window is processed by generating EVENT:Accepted for each. This allows data entry validation code to execute for all controls, including those that the user has not touched. AcceptAll mode immediately terminates when any of the following conditions is met:

```
SELECT(?)
Window{PROP:AcceptAll} = 0
A REQ control is left blank or zero.
```

The SELECT(?) statement selects the same control for the user to edit. This code usually indicates the value it contains is invalid and the user must re-enter data. The Window{PROP:AcceptAll} = 0 statement toggles AcceptAll mode off. Assigning values to this property can be used to initiate and terminate AcceptAll mode. When a control with the REQ attribute is left blank or zero, AcceptAll mode terminates with the control highlighted for user entry, without processing any more fields in the TAB key sequence. EVENT:Completed is posted to the window when all controls have been successfully processed.

Controls with a USE *variable* get EVENT:Accepted, but not those with a USE *field equate*.

#### Example:

```
Window WINDOW,PRE(Scr)
    ENTRY(@N3),USE(Ctl:Code)
    ENTRY(@S30),USE(Ctl:Name),REQ
    BUTTON('OK'),USE(?OkButton),KEY(EnterKey)
    BUTTON('Cancel'),USE(?CanxButton),KEY(EscKey)
END

CODE
OPEN(Window)
ACCEPT
    IF EVENT() = EVENT:Completed THEN BREAK.    ! AcceptAll mode terminated
    CASE ACCEPTED()
    OF ?Ctl:Code
        IF Ctl:Code > 150                        !If data entered is invalid
            BEEP                                  ! alert the user and
            SELECT(?)                             ! make them re-enter the data
        END
    OF ?OkButton
        Window{PROP:AcceptAll} = 1              !Initiate AcceptAll mode
    END
END
!Terminate ACCEPT and CASE ACCEPTED
```

**See Also:** SELECT

## PROP:Active

WINDOW or SYSTEM property. If the target is a WINDOW, PROP:Active returns 1 if the window is the active window, blank if not. Set to 1 to make the top window of a thread the active window.

If the SYSTEM variation is used, SYSTEM{Prop:Active} returns the number of active thread.

### Example:

```
CODE
OPEN(Window)
X# = START(AnotherThread)      ! Start another thread
ACCEPT
CASE EVENT()
OF EVENT:LoseFocus             ! When this window is losing focus
IF Y# <> X#                     ! check for the first focus change
Window{PROP:Active} = 1       ! and return focus to this thread
Y# = X#                       ! then flag first focus change completed
END
END
END

AnyActiveThread PROCEDURE      !lets any calling procedure know what thread
ActiveThread LONG,AUTO         !is active.
CODE
ActiveThread = SYSTEM{PROP:Active}
RETURN CHOOSE(ActiveThread = THREAD(), 0, ActiveThread)
```

## PROP:AlwaysDrop

When set to zero, the drop portion of a COMBO or LIST control with the DROP attribute only drops down when the user clicks on the dropdown icon, and when the user presses the down arrow key the displayed entries rotate without dropping down the list. When set to anything other than zero, the drop portion drops down either on the down arrow key or click on the dropdown icon.

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
COMBO(@S20),AT(0,0,20,220),USE(MyCombo),FROM(Que),DROP(5)
END

CODE
OPEN(MDIChild)
?MyCombo{PROP:AlwaysDrop} = 0 !Set windows-like drop behavior
```

## PROP:AppInstance

Returns the instance handle (HInstance) of the .EXE file for use in low-level API calls which require it. This is only used with the SYSTEM built-in variable. (READ-ONLY)

### Example:

```
PROGRAM
HInstance LONG
CODE
OPEN(AppFrame)
HInstance = SYSTEM{PROP:AppInstance} !Get .EXE instance handle for later use
ACCEPT
END
```

## PROP:AssertHook

A property of the SYSTEM built-in variable that sets the override procedure for the ASSERT internal Clarion procedure. Equivalent to {PROP:LibHook,8}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the ASSERT procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the ASSERT procedure (STRING filename, UNSIGNED LineNumber). (WRITE-ONLY)

See PROP:AssertHook2 for example source.

## PROP:AssertHook2

A property of the SYSTEM built-in variable that sets the override procedure for the ASSERT internal Clarion procedure. Equivalent to {PROP:LibHook,13}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the ASSERT procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the ASSERT procedure (UNSIGNED LineNumber, STRING filename, STRING message). (WRITE-ONLY)

**See Also:** ASSERT

**Example:**

```
PROGRAM
  MAP
  AssertMy1  PROCEDURE (STRING filename, UNSIGNED LineNumber)
  AssertMy2  PROCEDURE (UNSIGNED LineNumber, STRING filename, STRING message)
  END

  PRAGMA('define(zero_divide => on'))

  CODE

  SYSTEM{prop:asserthook} = ADDRESS (AssertMy1)
  SYSTEM{prop:asserthook2} = ADDRESS (AssertMy2)

  assert(0)
  assert(0, 'i am a message')

  AssertMy1  PROCEDURE (STRING filename, UNSIGNED LineNumber)
  CODE
  AssertMy2 (LineNumber, FileName, '')

  AssertMy2  PROCEDURE (UNSIGNED LineNumber, STRING filename, STRING message)
  1 long
  CODE
  SYSTEM{prop:asserthook} = 0  !Stop recursive calls into assert handler
  SYSTEM{prop:asserthook2} = 0  !Stop recursive calls into assert handler

  IF MESSAGE('Assert 1|filename=' & CLIP(filename) & '|line=' & LineNumber & |
    '|Message=' & CLIP(message) & '|Do you want me to GPF?', |
    'ASSERT', ICON:Exclamation, BUTTON:Yes + BUTTON:No)
    1 = 1 / 1  ! Causes a divide by zero GPF
  END
```

## PROP:AutoPaper

Sets and returns the state of the automatic best-fit paper selection feature of the report engine. The default value is feature-enabled. This is only used with the SYSTEM built-in variable.

**Example:**

```
PROGRAM
CODE
OPEN(AppFrame)
SYSTEM{PROP:AutoPaper} = '' !Turn off best-fit paper selection
ACCEPT
END
```

## PROP:BreakVar

Sets the variable for a BREAK structure within a REPORT.

**Example:**

```
Report  REPORT,AT(1000,2000,6000,7000),PRE(RPT),FONT('Arial',10,,FONT:regular),
THOUS
Break1  BREAK(ORD:CustNumber),USE(?Break1)
Break2  BREAK(DTL:OrderNumber),USE(?Break2)
        HEADER,AT(,,2167)
        END
detail  DETAIL,AT(,,,385)
        END
        FOOTER,PAGEAFTER(-1)
        END
        END
        FOOTER,PAGEAFTER(-1),AT(,,,1385)
        END
        END
        FOOTER,AT(1000,9000,6000,1000)
        END
END

CODE
OPEN(Report)
Report$?Break1{PROP:BreakVar} = ORD:CustName !Change the break variable for B
reak1
```

## PROP:Buffer

Property of a window which allows you to select off-display background re-paints. This can dramatically reduce screen flicker in some situation (such as animated GIF images), but incurs a potentially large memory overhead.

The default value is zero (0) which draws directly to the screen. This is fastest and incurs no memory overhead, but may create flicker in some cases.

Assigning one (1) allocates a permanent memory buffer for the window. This is quite fast, but incurs the most memory overhead.

Assigning two (2) reallocates a memory buffer for the window each time a re-paint is required. This is slower, but incurs the least memory overhead while still reducing flicker.

### Example:

```
WinView WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    END
CODE
OPEN(WinView)
WinView{PROP:Buffer} = 1    !Permanent redraw buffer for the window
```

## PROP:CharSet

The *charset* parameter may name any *character set* registered in the Windows system. For a report, the printer driver must support the specified *character set*. The EQUATES.CLW file contains EQUATE values for standard *character set* values.

This is a SYSTEM property that can be used to set the Character Set property at the system level (i.e., SYSTEM{PROP:CharSet} = CHARSET:GREEK).

CHARSET:ANSI	EQUATE(0)
CHARSET:DEFAULT	EQUATE(1)
CHARSET:SYMBOL	EQUATE(2)
CHARSET:MAC	EQUATE(77)
CHARSET:SHIFTJIS	EQUATE(128)
CHARSET:HANGEUL	EQUATE(129)
CHARSET:JOHAB	EQUATE(130)
CHARSET:GB2312	EQUATE(134)
CHARSET:CHINESEBIG5	EQUATE(136)
CHARSET:GREEK	EQUATE(161)
CHARSET:TURKISH	EQUATE(162)
CHARSET:HEBREW	EQUATE(177)
CHARSET:ARABIC	EQUATE(178)
CHARSET:BALTIC	EQUATE(186)
CHARSET:CYRILLIC	EQUATE(204)
CHARSET:THAI	EQUATE(222)
CHARSET:EASTEUROPE	EQUATE(238)
CHARSET:OEM	EQUATE(255)

This property is not to be confused with PROP:FontCharSet, specifying the character set for a specific FONT (PROP:FontCharSet) or (PROP:Font,5). This provides support for international character sets. If omitted, the default character set for the FONT is used.

**See Also:** FONT

## PROP:Checked

Returns the current display state of a CHECK control--checked (1) or un-checked ("). (READ ONLY). PROP:Checked can also be used with menu items that have the CHECK attribute applied.

### Example:

```
WinView WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    CHECK('Check Me'),AT(20,0,20,20),USE(CheckVar)
END

CODE
OPEN(WinView)
IF ?CheckVar{PROP:Checked} = TRUE  !Is it checked?
    !Do something
END
ACCEPT
END
```

## PROP:Child and PROP:ChildIndex

**PROP:Child** is an array property which returns the control number (e.g., Field Equate number) of a child control in a parent control structure (such as a SHEET, TAB, OPTION, or GROUP). (READ ONLY) The element number (array index into the property) is the ordinal position of the control in the parent structure. Returns null string (") if the element number is out of range. *?Sheet{Prop:Child,Choice(?Sheet)}* is equivalent to using *?Sheet{Prop:ChoiceFEQ}*.

**PROP:ChildIndex** is an integer property which returns the ordinal position of all the child controls in a parent control structure (such as a SHEET, TAB, OPTION, or GROUP). (READ ONLY) The element number is the control number of the control in the parent structure. Returns a null string (") if the element number is out of range.

**PROP:ChildIndex** is normally used with the child control Field Equate Label. Use the **PROP:Parent** property to determine the parent control's Field Equate Label.

### Example:

```
Chld    PROCEDURE
optvar1 string(32)
Label   STRING('Test')

WinView    WINDOW('Child One'),SYSTEM,MAX,AT(0,0,141,106),MDI,|
FONT('Microsoft Sans Serif',10,,,CHARSET:DEFAULT),HVSCROLL
    STRING('String1'), AT(2,2), USE(Label)
    OPTION('Option 1'), AT(0,17,103,41), USE(OptVar1), KEY(F10Key), HLP('Option1Help')
    RADIO('Radio 1'), AT(0,17,42,20), USE(?R1)
    RADIO('Radio 2'), AT(2,37,40,20), USE(?R2)
END

END

CODE
OPEN(WinView)
LOOP X# = 1 TO 99
    Y# = ?OptVar1{PROP:Child,X#}
    IF NOT Y#
        BREAK
    END
    EXECUTE X#
    Z# = ?R1{PROP:ChildIndex}
```





## PROP:ChoiceFeq

Returns or sets the field number of the currently selected TAB in a SHEET, or RADIO in an OPTION structure.

### Example:

```
WinView WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    OPTION('Option 1'),USE(OptVar1),KEY(F10Key),HLP('Option1Help')
        RADIO('Radio 1'),AT(0,0,20,20),USE(?R1)
        RADIO('Radio 2'),AT(20,0,20,20),USE(?R2)
    END
END
```

```
CODE
OPEN(WinView)
?OptVar1{PROP:ChoiceFeq} = ?R1  !Select radio one
ACCEPT
END
```

### See Also:

PROP:NumTabs

PROP:Child

PROP:ChildIndex

PROP:Parent

## PROP:ClientHandle

WINDOW property which returns the client window handle (the area of the window that contains the controls) for use with low-level Windows API calls that require it. (READ-ONLY)

**Example:**

```
WinView WINDOW('View'), AT(0,0,320,200), MDI, MAX, HVSCROLL
    END
MessageText    CSTRING('You cannot exit the program from this window ')
MessageCaption CSTRING('No EVENT:CloseDown Allowed ')
TextAddr       LONG
CaptionAddr     LONG
RetVal         SHORT
CODE
    OPEN(WinView)
    ACCEPT
    CASE EVENT()
    OF EVENT:CloseDown
        TextAddr = ADDRESS(MessageText)
        CaptionAddr = ADDRESS(MessageCaption)
        RetVal = MessageBox(WinView{PROP:ClientHandle}, TextAddr, CaptionAddr, MB_OK)
                                !Windows API call using a window handle
    CYCLE                !Disallow program closedown from this window
    END
END
|*****
|
|hDC = GetDC(Window{PROP:ClientHandle})
|DO DrawStuff
|ReleaseDC(Window{PROP:ClientHandle}, hDC)
```

**See Also:** PROP:Handle

## PROP:ClientHeight

APPLICATION or WINDOW property which returns the height of the client area for use with low-level Windows API calls that require it. (READ-ONLY).

## PROP:ClientWidth

APPLICATION or WINDOW property which returns the width of the client area for use with low-level Windows API calls that require it. (READ-ONLY)

## PROP:ClientWndProc

WINDOW property which sets or gets the client window (not including title or status areas) messaging procedure for use with low-level Windows API calls that require it. Generally used with sub-classing to track all Windows messages.

### Example:

```

PROGRAM
MAP
  Main
SubClassFunc(UNSIGNED hWnd,SIGNED wMsg,UNSIGNED wParam,LONG lParam),LONG,PASCAL
  MODULE('win32')                                !Windows Library
    CallWindowProc(LONG,UNSIGNED,SIGNED,UNSIGNED,LONG),LONG,PASCAL,NAME('CallWindowProcA')
  END
END
SavedProc LONG
PT      GROUP,PRE(PT)
X        SHORT
Y        SHORT
      END
CODE
  Main
Main      PROCEDURE
WinView WINDOW('View'),AT(0,0,320,200),HVSCROLL,MAX,TIMER(1)
  STRING('X Pos'),AT(1,1,,),USE(?String1)
  STRING(@n3),AT(24,1,,),USE(PT:X)
  STRING('Y Pos'),AT(44,1,,),USE(?String2)
  STRING(@n3),AT(68,1,,),USE(PT:Y)
  BUTTON('Close'),AT(240,180,60,20),USE(?Close)
END

```

```
CODE
OPEN (WinView)
SavedProc = WinView{PROP:ClientWndProc}           !Save this procedure
WinView{PROP:ClientWndProc} = ADDRESS(SubClassFunc) !Change to subclass procedure
ACCEPT
  CASE ACCEPTED()
  OF ?Close
    BREAK
  END
END
SubClassFunc    PROCEDURE (hWnd,wMsg,wParam,lParam)    !Sub class procedure
WM_MOUSEMOVE    EQUATE (0200H)                        ! to track mouse movement in
CODE                                                    ! client area of window
CASE wMsg
OF WM_MOUSEMOVE
  PT:X = MOUSEX()
  PT:Y = MOUSEY()
END
RETURN(CallWindowProc(SavedProc,hWnd,wMsg,wParam,lParam))
                                                    !Pass control back to
                                                    ! saved procedure
```

## PROP:ClientX

APPLICATION or WINDOW property which returns the horizontal position of the top left corner of the client area. (READ-ONLY)

## PROP:ClientY

APPLICATION or WINDOW property which returns the vertical position of the top left corner of the client area. (READ-ONLY)

## PROP:ClipBits

Property of an IMAGE control that allows bitmap images to be moved into (but not out of) the Windows clipboard when set to one (1). Only .BMP, .PCX, or .GIF image types can be stored as a bitmap (.BMP) image in the Clipboard.

**Example:**

```
WinView WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    IMAGE(),AT(0,0,,),USE(?Image)
    BUTTON('Save Picture'),AT(80,180,60,20),USE(?SavePic)
    BUTTON('New Picture'),AT(160,180,60,20),USE(?NewPic)
END

FileName  STRING(64)                !Filename variable

CODE
OPEN(WinView)
DISABLE(?LastPic)
IF NOT FILEDIALOG('Choose File to View',FileName,'BitMap|*.BMP|PCX|*.PCX',0)
    RETURN                        !Return if no file chosen
END
?Image{PROP:Text} = FileName
ACCEPT
CASE ACCEPTED()
OF ?NewPic
    IF NOT FILEDIALOG('Choose File to View',FileName,'BitMap|*.BMP|PCX|*.PCX',0)
        BREAK                    !Return if no file chosen
    END
    ?Image{PROP:Text} = FileName
OF ?SavePic
    ?Image{PROP:ClipBits} = 1      !Put image into Clipboard

ENABLE(?LastPic)                  ! activate Last Picture button

END
END
```

## PROP:CloseReportHook

A property of the SYSTEM built-in variable that sets the override procedure for the CLOSE(Report) internal Clarion procedure. Equivalent to {PROP:LibHook,22}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the default CLOSE procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the CLOSE procedure found in the BUILTINS.CLW. (WRITE-ONLY)

## PROP:CloseWindowHook

A property of the SYSTEM built-in variable that sets the override procedure for the CLOSE(Window) internal Clarion procedure. Equivalent to {PROP:LibHook,20}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the default CLOSE procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the CLOSE procedure found in the BUILTINS.CLW. (WRITE-ONLY)

## PROP:ColorDialogHook

A property of the SYSTEM built-in variable that sets the override procedure for the COLORDIALOG internal Clarion procedure. Equivalent to {PROP:LibHook,1}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the COLORDIALOG procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the COLORDIALOG procedure found in the BUILTINS.CLW. (WRITE-ONLY)

## PROP:ColorHighByte

A property of the SYSTEM built-in variable that sets the high byte of the RGB DWORD using

```
SYSTEM{PROP:ColorHighByte} = n.
```

Setting the value of *n* to 0 turns on color dithering in the 256 color mode. Setting it to 2 (the default) causes the system to only use solid colors.

## PROP:CustomColor

A read/write SYSTEM property that can be used to save custom colors added by a user between program sessions.

### Syntax:

```
color = SYSTEM {PROP:CustomColor, n}  
SYSTEM {PROP:CustomColor, n} = color
```

*n* must be an integer value between 1-16.

This property returns the RGB value of *n*-th entry of the Custom Colors list contained in the standard Color dialog. If the *n*-th entry is not set, the returned value is 0FFFFFFh (white color).

Setting this property sets *n*-th entry of the Custom Colors list of the standard Color dialog to specified RGB value.

## PROP:DDEMode

A property of the SYSTEM built-in variable that allows you to set normal DDE event behavior (0, the default) whereby all DDE events are sent to the window that opened the DDE channel, or one (1), which causes all DDE events to be sent to the top window of the current thread.

**Example:**

```
DDERetVal  STRING(20)
WinOne  WINDOW,AT(0,0,160,400)
        ENTRY(@s20),USE(DDERetVal)
        END
MyServer  LONG
CODE
OPEN(WinOne)
SYSTEM{PROP:DDEMode} = 1           !Send events to top window of current thread
MyServer = DDESERVER('MyApp','DataEntered') !Open as server
ACCEPT
END
```

## PROP:DDETimeOut

A property of the SYSTEM built-in variable that allows you to set and get the DDE timeout used for all DDE commands. This value is in hundredths of seconds and the default value is 500.

**Example:**

```
DDERetVal  STRING(20)
WinOne  WINDOW,AT(0,0,160,400)
        ENTRY(@s20),USE(DDERetVal)
        END
MyServer  LONG
CODE
OPEN(WinOne)
SYSTEM{PROP:DDETimeOut} = 12000    !Set time out to two minutes
MyServer = DDESERVER('MyApp','DataEntered') !Open as server
ACCEPT
CASE EVENT()
OF EVENT:DDErequest                !Data requested once
  DDEWRITE(MyServer,DDE:manual,'DataEntered',DDERetVal)
                                !Provide data once
END
END
```

## PROP:DeferMove

A property of the SYSTEM built-in variable that defers the resizing and/or movement of controls until the end of the ACCEPT loop or SYSTEM{PROP:DeferMove} is reset to zero (0). This disables the immediate effect of all assignments to position and size properties, enabling the library to perform all moves at once (which eliminates temporarily overlapping controls). The absolute value of the number assigned to SYSTEM{PROP:DeferMove} defines the number of deferred moves for which space is pre-allocated (automatically expanded when necessary, but less efficient and may fail). Assigning a positive number automatically resets PROP:DeferMove to zero at the next ACCEPT, while a negative number leaves it set until explicitly reset to zero (0).

In multi-threaded applications, the setting of SYSTEM{PROP:DeferMove} to a non-zero value initiates the deferred move for the current thread only.

**Note:**

PROP:DeferMove is ignored if PROP:LazyDisplay is set to zero (0).

**Example:**

```
WinView WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    IMAGE(),AT(0,0,,),USE(?Image)
    BUTTON('New Picture'),AT(160,180,60,20),USE(?NewPic)
    BUTTON('Close'),AT(80,180,60,20),USE(?Close)
END
FileName      STRING(64)                !Filename variable
ImageWidth    SHORT
ImageHeight    SHORT
CODE
OPEN(WinView)
DISABLE(?LastPic)
IF NOT FILEDIALOG('Choose File to View',FileName,'BitMap|*.BMP|PCX|*.PCX',0)
    RETURN                                !Return if no file chosen
END
?Image{PROP:Text} = FileName
ACCEPT
CASE ACCEPTED()
OF ?NewPic
    IF NOT FILEDIALOG('Choose File to View',FileName,'BitMap|*.BMP|PCX|*.PCX',0)
        BREAK                            !Return if no file chosen
    END
    ?Image{PROP:Text} = FileName
    SYSTEM{PROP:DeferMove} = 4             !Defer move and resize
    ImageWidth = ?Image{PROP:Width}       !1 move
    ImageHeight = ?Image{PROP:Height}     !2 moves
    IF ImageWidth > 320
        ?Image{PROP:Width} = 320
        ?Image{PROP:XPos} = 0
    ELSE
        ?Image{PROP:XPos} = (320 - ImageWidth) / 2    !Center horizontally
    END
    IF ImageHeight > 180
        ?Image{PROP:Height} = 180
        ?Image{PROP:YPos} = 0
    ELSE
        ?Image{PROP:YPos} = (180 - ImageHeight) / 2    !Center vertically
    END
OF ?Close
    BREAK
END
END                                     !Moves and resizing happens at the end of the ACCEPT loop
```



## PROP:Edit

LIST control property which specifies the field equate label of the control to perform edit-in-place for a LIST box column. This is an array whose element number indicates the column number to edit. When non-zero, the control is unhidden and moved/resized over the current row in the column indicated to allow the user to input data. Assign zero to re-hide the data entry control.

**Example:**

```
Q    QUEUE
f1   STRING(15)
f2   STRING(15)
      END
Win1 WINDOW('List Edit In Place'),AT(0,1,308,172),SYSTEM
      LIST,AT(6,6,120,90),USE(?List),COLUMN,FORMAT('60L@s15@60L@s15@'), |
      FROM(Q),ALRT(EnterKey)
      END
?EditEntry EQUATE(100)
CODE
OPEN(Win1)
CREATE(?EditEntry,CREATE:Entry)
SELECT(?List,1)
ACCEPT
CASE FIELD()
OF ?List
CASE EVENT()
OF EVENT:AlertKey
IF KEYCODE() = EnterKey
SETKEYCODE(MouseLeft2)
POST(EVENT:Accepted,?List)
END
OF EVENT:NewSelection
IF ?List{PROP:edit,?List{PROP:column}}
GET(Q,CHOICE())
END
OF EVENT:Accepted
IF KEYCODE() = MouseLeft2
GET(Q,CHOICE())
?EditEntry{PROP:text} = ?List{PROPLIST:picture,?List{PROP:column}}
CASE ?List{PROP:column}
OF 1
?EditEntry{PROP:use} = Q.F1
OF 2
?EditEntry{PROP:use} = Q.F2
END
?List{PROP:edit,?List{PROP:column}} = ?EditEntry
. .
OF ?EditEntry
CASE EVENT()
OF EVENT:Selected
?EditEntry{PROP:Touched} = 1
OF EVENT:Accepted
PUT(Q)
?List{PROP:edit,?List{PROP:column}} = 0
. . .
```

## PROP:Enabled

Returns an empty string if the control is not enabled either because it itself has been disabled, or because it is a member of a "parent" control (OPTION, GROUP, MENU, SHEET, or TAB) that has been disabled. (READ-ONLY)

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
SHEET,AT(0,0,320,175),USE(SelectedTab)
TAB('Tab One'),USE(?TabOne)
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P1)
    ENTRY(@S8),AT(100,140,32,20),USE(E1)
    PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P2)
    ENTRY(@S8),AT(100,240,32,20),USE(E2)
END
TAB('Tab Two'),USE(?TabTwo)
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P3)
    ENTRY(@S8),AT(100,140,32,20),USE(E3)
    PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P4)
    ENTRY(@S8),AT(100,240,32,20),USE(E4)
END
END
BUTTON('Ok'),AT(100,180,20,20),USE(?Ok)
BUTTON('Cancel'),AT(200,180,20,20),USE(?Cancel)
END

CODE
OPEN(MDIChild)
ACCEPT
CASE EVENT()
OF EVENT:Completed
    BREAK
END
CASE FIELD()
OF ?Ok
    CASE EVENT()
    OF EVENT:Accepted
        SELECT
    END
OF ?E3
    CASE EVENT()
    OF EVENT:Accepted
        IF ?E3{PROP:Enabled} AND MDIChild{PROP:AcceptAll}
            !Check for visibility during AcceptAll mode
            E3 = UPPER(E3) !Convert the data entered to Upper case
            DISPLAY(?E3) ! and display the upper cased data
        END
    END
OF ?Cancel
    CASE EVENT()
    OF EVENT:Accepted
        BREAK
    END
END
END
```

## PROP:EventsWaiting

WINDOW property which returns whether the window has any further events waiting to be processed. Generally only used by Internet Connect to know when to format an HTML page. (READ-ONLY)

### Example:

```
IF TARGET{PROP:EventsWaiting}      !Check for waiting events
    !Do something
END
```

## PROP:ExeVersion

A property of the SYSTEM built-in variable that returns the version number of an EXE created by Clarion for Windows. This is the version number of Clarion for Windows which compiled the EXE file, even if the runtime library .DLL is from a newer release (see PROP:LibVersion). This first appeared in Clarion for Windows release 1501, so PROP:ExeVersion returns blank for releases prior to 1501. (READ-ONLY)

### Example:

```
MESSAGE('Compiled in CW release ' & SYSTEM{PROP:ExeVersion})
```

## PROP:FatalErrorHook

A property of the SYSTEM built-in variable that sets the override procedure for the internal Clarion procedure. Equivalent to {PROP:LibHook,9}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the internal procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the internal procedure's (STRING message,UNSIGNED ErrorNumber). (WRITE-ONLY)

## PROP:FileDialogHook

A property of the SYSTEM built-in variable that sets the override procedure for the FILEDIALOG internal Clarion procedure. Equivalent to {PROP:LibHook,2}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the FILEDIALOG procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the FILEDIALOG procedure found in the BUILTINS.CLW. (WRITE-ONLY)

## PROP:FlushPageNumFunc

A property of a REPORT that sets the callback function called during the flushing of previewed pages. This callback function returns the number of the next page to be flushed. The callback function must be a PROCEDURE that takes a single LONG parameter and returns a LONG.

To turn this on, the ADDRESS of your callback function must be assigned to PROP:FlushPageNumFunc. To turn it off, assign zero (0) to it.

When the report engine flushes report pages to a printer as a result of the execution of Report{PROP:FlushPreview}, the callback function is called to retrieve the number of the next page to be printed. The parameter passed to the callback function is the number of the last printed page, or 0 before printing of the first page. If the callback function returns a value out of the range of pages in the report, the report engine stops printing and removes all records from the preview queue.

The PROP:FlushPageNumFunc can return the same page number multiple times prior to the closing of the report. Once the report is closed the report engine removes the created metafiles.

### Example:

```
MAP
  PageNum (LONG), LONG
END

CODE
OPEN (Report)
!Report processing code here
Report{PROP:FlushPageNumFunc} = ADDRESS (PageNum)
Report{PROP:FlushPreview} = TRUE
Report{PROP:FlushPageNumFunc} = 0

PageNum PROCEDURE (LONG LastPage)
CODE
IF LastPage = 0
  RETURN 1
ELSE
  RETURN LastPage + 2 ! Print odd pages only
END
```

## PROP:FlushPreview

Flushes the REPORT structure's PREVIEW attribute metafiles to the printer (0 = off, else on, always 0 at report open).

Example:

```
SomeReport PROCEDURE
WMFQueue QUEUE                                !Queue to contain .WMF filenames
    STRING(64)
END
NextEntry BYTE(1)                             !Queue entry counter variable

Report    REPORT,PREVIEW(WMFQueue)           !Report with PREVIEW attribute
DetailOne DETAIL
    !Report controls
    END
    END

ViewReport WINDOW('View Report'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    IMAGE(),AT(0,0,320,180),USE(?ImageField)
    BUTTON('View Next Page'),AT(0,180,60,20),USE(?NextPage),DEFAULT
    BUTTON('Print Report'),AT(80,180,60,20),USE(?PrintReport)
    BUTTON('Exit Without Printing'),AT(160,180,60,20),USE(?ExitReport)
    END

CODE
OPEN(Report)
SET(SomeFile)                                !Code to generate the report
LOOP
    NEXT(SomeFile)
    IF ERRORCODE() THEN BREAK.
    PRINT(DetailOne)
END
ENDPAGE(Report)
OPEN(ViewReport)                            !Open report preview window
GET(WMFQueue,NextEntry)                     !Get first queue entry
?ImageField{PROP:text} = WMFQueue           !Load first report page
ACCEPT
CASE ACCEPTED()
OF ?NextPage
    NextEntry += 1                           !Increment entry counter
    IF NextEntry > RECORDS(WMFQueue)         !Check for end of report
        CYCLE
    END
    GET(WMFQueue,NextEntry)                   !Get next queue entry
    ?ImageField{PROP:text} = WMFQueue         !Load next report page
    DISPLAY                                  ! and display it
OF ?PrintReport
    Report{PROP:FlushPreview} = 1             !Flush files to printer
    BREAK                                    ! and exit procedure
OF ?ExitReport
    BREAK                                    !Exit procedure
    END
END
CLOSE(Report)
CLOSE(Window)
RETURN                                       ! Return to caller, automatically
                                           ! freeing the queue and automatically
```

`! deleting all the temporary .WMF files`

## PROP:Follows

Changes the tab order to specify the position within the parent that the control will occupy. The control follows the control number you specify in the tab order. This must specify an existing control within the parent (window, option, group, menu, report, detail, etc.). Setting PROP:Follows to a REGION control will be ignored, as REGIONS are not in the Windows tab order. (WRITE-ONLY)

### Example:

```
WinView    WINDOW('View Report'),AT(0,0,320,200),MDI,MAX,HVSCROLL
           BUTTON('View Next Page'),AT(0,180,60,20),USE(?NextPage),DEFAULT
           BUTTON('Print Report'),AT(80,180,60,20),USE(?PrintReport)
           BUTTON('Exit Without Printing'),AT(160,180,60,20),USE(?ExitReport)
           END
CODE
OPEN(WinView)
           !Print Report button normally follows View button
?PrintReport{PROP:Follows} = ?ExitReport
           !Now Print Report button follows Exit button in the tab order
ACCEPT
END
```

**See Also:** Prop:NextField

## PROP:FontDialogHook

A property of the SYSTEM built-in variable that sets the override procedure for the FONTDIALOG internal Clarion procedure. Equivalent to {PROP:LibHook,3}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the FONTDIALOGA procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the FONTDIALOGA procedure found in the BUILTINS.CLW. (WRITE-ONLY)

## PROP:HaltHook

A property of the SYSTEM built-in variable that sets the override procedure for the HALT internal Clarion procedure. Equivalent to {PROP:LibHook,5}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the HALT procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the HALT procedure found in the BUILTINS.CLW. (WRITE-ONLY)

## PROP:Handle

Returns the window or control handle for use with low-level Windows API calls that require it. It is also used when assigning the handle of one BLOB to another.

### Example:

```
WinView    WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL
           END

MessageText  CSTRING('You cannot exit the program from this window ')
MessageCaption CSTRING('No EVENT:CloseDown Allowed ')

TextAddress   LONG
CaptionAddress LONG
RetVal        SHORT

CODE
OPEN(WinView)
ACCEPT
CASE EVENT()
OF EVENT:CloseDown
    TextAddress = ADDRESS(MessageText)
    CaptionAddress = ADDRESS(MessageCaption)
    RetVal = MessageBox(WinView{PROP:Handle},TextAddress,CaptionAddress,MB_OK)
                                !Windows API call using a window handle
CYCLE                        !Disallow program closedown from this window
END
END
```



```

!*****

!Make Window Always on Top

SetWindowPos(Window{PROP:Handle},HWND_TOPMOST,0,0,0,0,SWP_NOMOVE + SWP_NOSIZE)
!*****

!Remove MIN Button on window with ICON()

Sty = GetWindowLong(Window{prop:handle}, GWL_STYLE)
SetWindowLong(Window{prop:handle}, GWL_STYLE, BAND(Sty,BXOR(-
1,WS_MINIMIZEBOX)))

!*****

BlobPtr = GlobalLock(Pre:Blob{PROP:Handle})
DO WorkOnBlob
GlobalUnlock(Pre:Blob{PROP:Handle})

```

**See Also:** PROP: ClientHandle

## PROP:HeaderHeight

Returns the height of the header in a LIST or COMBO control. The height is measured in dialog units (unless PROP:Pixels is active). (READ-ONLY)

**Example:**

```
MDIChild WINDOW('Child One'), AT(0,0,320,200), MDI, MAX, HVSCROLL
    LIST, AT(0,0,220,220), USE(?L1), FROM(Que), IMM, FORMAT('60L~Header Text~')
END
CODE
OPEN(MDIChild)
X# = ?L1{PROP:HeaderHeight}      'Get height of header in dialog units
```

## PROP:HscrollPos

Returns the position of the horizontal scroll bar's "thumb" (from 0 to 255) on a window, IMAGE, TEXT, LIST or COMBO with the HSCROLL attribute. Setting this causes the control or window's contents to scroll horizontally.

**Example:**

```
Que      QUEUE
F1       STRING(50)
F2       STRING(50)
F3       STRING(50)
END
WinView  WINDOW('View'), AT(, , 340, 200), SYSTEM, CENTER
    LIST, AT(20,0,300,200), USE(?List), FROM(Que), IMM, HVSCROLL |
        FORMAT('80L#1#80L#2#80L#3#')
END
CODE
OPEN(WinView)
DO BuildListQue
ACCEPT
CASE FIELD()
OF ?List
CASE EVENT()
OF EVENT:ScrollDrag
CASE (?List{PROP:HscrollPos} % 200) + 1
OF 1
?List{PROP:Format} = '80L#1#80L#2#80L#3#'
OF 2
?List{PROP:Format} = '80L#2#80L#3#80L#1#'
OF 3
?List{PROP:Format} = '80L#3#80L#1#80L#2#'
END
DISPLAY
. . .
FREE(Que)
BuildListQue ROUTINE
LOOP 15 TIMES
Que.F1 = 'F1F1F1F1'
Que.F2 = 'F2F2F2F2'
Que.F3 = 'F3F3F3F3'
ADD(Que)
END
```

## PROP:IconList

An array that sets or returns the icons displayed in a LIST formatted to display icons (usually a tree control). If the name of the icon file to assign has a number in square brackets appended to its end, this indicates the file contains multiple icons and the number specifies which to assign (zero-based). If the name of the icon file has a tilde (~) prepended to it (~IconFile.ICO), this indicates the file has been linked into the project as a resource and is not on disk.

**Example:**

```

PROGRAM

MAP
RandomAlphaData  PROCEDURE(*STRING Field)
END
TreeDemo  QUEUE,PRE() !Data list box FROM queue
FName     STRING(20)
ColorNFG  LONG         !Normal Foreground color for FName
ColorNBG  LONG         !Normal Background color for FName
ColorSFG  LONG         !Selected Foreground color for FName
ColorSBG  LONG         !Selected Background color for FName
IconField LONG         !Icon number for FName
TreeLevel LONG         !Tree Level
LName     STRING(20)
Init      STRING(4)
END

Win  WINDOW('List Box'),AT(0,0,374,314),FONT('Tahoma',8,,FONT:regular,CHARSET:ANSI),|
    SYSTEM,GRAY,DOUBLE
    LIST,AT(3,4,369,306),USE(?Show),HVSCROLL,COLOR(,COLOR:Black,0E7E7E7H),|
    FORMAT('121L(2)|M*IT~First Name~149L(2)|M~Last Name~16C(2)|M~Initials~'),|
    FROM(TreeDemo),GRID(0E7E7E7H)
END
x    long
CODE
LOOP x = 1 to 20
    RandomAlphaData(FName)
    ColorNFG = COLOR:Black           !Assign FNAME's colors
    ColorNBG = 0F0FFFFH
    ColorSFG = COLOR:White
    ColorSBG = COLOR:Silver
    IconField = ((x-1) % 4) + 1      !Assign icon number
    TreeLevel = ((x-1) % 4) + 1      !Assign tree level
    RandomAlphaData(LName)
    RandomAlphaData(Init)
    ADD(TreeDemo)
END
OPEN(Win)
?Show{prop:lineheight} = 10
?Show{PROP:iconlist,1} = ICON:VCRback      !Icon 1 = <
?Show{PROP:iconlist,2} = ICON:VCRrewind    !Icon 2 = <<
?Show{PROP:iconlist,3} = 'VCRdown.ico'     !Icon 3 = > not linked into project
?Show{PROP:iconlist,4} = '~VCRnext.ico'    !Icon 4 = >>linked into project
ACCEPT
END

RandomAlphaData PROCEDURE(*STRING Field)
CODE
y# = RANDOM(1,SIZE(Field))           !Random fill size
LOOP x# = 1 to y#                     !Fill each character with
    Field[x#] = CHR(RANDOM(97,122))    !a random lower case letter
END

```

## PROP:ImageBits

Property of an IMAGE control that allows bitmap images displayed in the control to be moved into and out of memo fields. Any image displayed in the control can be stored. PROP:ImageBlob performs the same type of function for a BLOB.

### Example:

```
WinView  WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL
         IMAGE(),AT(0,0,,),USE(?Image)
         BUTTON('Save Picture'),AT(80,180,60,20),USE(?SavePic)
         BUTTON('New Picture'),AT(160,180,60,20),USE(?NewPic)
         BUTTON('Last Picture'),AT(240,180,60,20),USE(?LastPic)
END

SomeFile  FILE,DRIVER('Clarion'),PRE(Fil)      !A file with a memo field
MyMemo    MEMO(65520),BINARY
Rec       RECORD
F1        LONG
. .

FileName  STRING(64)                          !Filename variable

CODE
OPEN(SomeFile)
OPEN(WinView)
DISABLE(?LastPic)
IF NOT FILEDIALOG('Choose File to View',FileName,'BitMap|*.BMP|PCX|*.PCX',0)
  RETURN                                     !Return if no file chosen
END
?Image{PROP:Text} = FileName
ACCEPT
CASE ACCEPTED()
OF ?NewPic
  IF NOT FILEDIALOG('Choose File to View',FileName,'BitMap|*.BMP|PCX|*.PCX',0)
    BREAK                                   !Return if no file chosen
  END
  ?Image{PROP:Text} = FileName
OF ?SavePic
  Fil:MyMemo = ?Image{PROP:ImageBits}      !Put image into memo
  ADD(SomeFile)                            ! and save it to the file on disk
  ENABLE(?LastPic)                        ! activate Last Picture button
OF ?LastPic
  ?Image{PROP:ImageBits} = Fil:MyMemo      !Put last saved memo into image
END
END
```

## **PROP:ImageBlob**

Property of an IMAGE control that allows bitmap images displayed in the control to be moved into and out of BLOB fields. Any image displayed in the control can be stored. PROP:ImageBits performs the same type of function for a MEMO. Most images are stored in a bitmap format by default (except PCX and GIF), unless PROP:PrintMode is set to store the native format.

### **See Also:**

How to Store and Display a Graphic Image with a Memo or Blob Data Type

## **PROP:ImageInstance**

A SYSTEM property that returns the HINSTANCE of the active EXE/DLL for use with linked-in image files.

Regarding icon/cursor resources: the runtime library looks for them not only in the executable that contains the value of PROP:ImageInstance, but also in the EXE or DLL where the current active window thread was loaded from.

## **PROP:InitAStringHook**

A property of the SYSTEM built-in variable that allows a procedure to be set up to automatically initialize the TIE values the first time an ASTRING representing a particular value is assigned. Equivalent to {PROP:LibHook,14}. Assign the ADDRESS of the InitAString procedure, and the runtime library will call this procedure when an ASTRING variable is first assigned. Assign zero and the runtime library will stop calling the InitAString procedure. (WRITE-ONLY)

## **PROP:Interface**

A property of a TEXT control used to get an interface to the RTF control's host interface.

## PROP:InToolbar

A toggle attribute which returns whether the control is in a TOOLBAR structure. (READ-ONLY)

**Example:**

```
WinView WINDOW('View'),AT(0,0,,),MDI,MAX,HVSCROLL,SYSTEM,RESIZE
    TOOLBAR
        BUTTON('Save Picture'),AT(80,180,60,20),USE(?SavePic)
    END
    LIST,AT(6,6,120,90),USE(?List),FORMAT('120L'),FROM(Q),IMM
END

CODE
OPEN(WinView)
IF ?SavePic{PROP:InToolbar} = TRUE
    !DO Something
END
ACCEPT
END
```

## PROP:IPRequestCount

**IPRequestCount** is a read/write property used exclusively by the SoftVelocity IP Driver that sets the number of requests to be sent to the server in a single MRP (Multiple Request Packet). The server will then execute the specified number of statements, and return the results in an MRP packet to the client. If this property is set to -1, the current packet is immediately sent. If this property is set to zero, the current packet is reset, and nothing is sent to the server.

This property can also be used to determine how many records were actually read.

**Syntax:**

***entity{PROP:IPRequestCount} = number***

*Entity*            the label of a FILE or VIEW

*number*           the number of requests to be sent to the server in a single MRP. The maximum value is 1,000,000.

**Example:**

```
myfile{PROP:IPRequestCount} = 20            ! create packet with 20 requests
NEXT(myfile)                                ! send packet to server with 20 NEXTs
nRecNum = myfile{PROP:IPRequestCount}      ! get number of records in MRP packet
```

## PROP:Items

Returns or sets the number of entries visible in a LIST or COMBO control.

**Example:**

```

Que      QUEUE
        STRING(30)
        END

WinView  WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL,SYSTEM
        LIST,AT(6,6,120,90),USE(?List),FORMAT('120L'),FROM(Q),IMM
        END

CODE
OPEN(WinView)
SET(SomeFile)
LOOP ?List(PROP:Items) TIMES  !Fill display queue to limit of displayable item
s
    NEXT(SomeFile)
    Que = Fil:Record
    ADD(Que)
END
ACCEPT
END

```

## PROP:LazyDisplay

SYSTEM property which disables (when set to 1) or enables (when set to 0, the default) the feature where all window re-painting is completely done before processing continues with the next statement following a DISPLAY. Setting PROP:LazyDisplay = 1 creates seemingly faster video processing, since the re-paints occur at the end of the ACCEPT loop if there are no other messages pending. This can improve the performance of some applications, but can also have a negative impact on appearance.

**Example:**

```

WinView  APPLICATION('MyApp'),AT(0,0,320,200),MAX,HVSCROLL,SYSTEM
        END

CODE
OPEN(WinView)
SYSTEM{PROP:LazyDisplay} = 1  !Disable extra paint message display
                             ! throughout entire application
ACCEPT
END

```

## PROP:LFNSupport

**NOTE: This property has been deprecated in this release.**

A property of the SYSTEM built-in variable in 16-bit programs that returns one (1) if the operating system supports long filenames, and an empty string (") if it does not. 32-bit operating systems all support long filenames. (READ-ONLY)

**Example:**

```
IF SYSTEM{PROP:LFNSupport} = TRUE
  MESSAGE('Long Filenames are supported')
ELSE
  MESSAGE('Long Filenames are NOT supported')
END
```

## PROP:LibHook

An array property of the SYSTEM built-in variable that sets override procedures for several internal Clarion procedures. For each of these procedures, you assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the Clarion library procedure. The overriding procedure's prototype must be exactly the same as the internal Clarion procedure as declared in Builtins.Clw. These properties were implemented to facilitate Internet Connect. (WRITE-ONLY)

{PROP:Libhook, 1}	PROP:ColorDialogHook
{PROP:Libhook, 2}	PROP:FileDialogHook
{PROP:Libhook, 3}	PROP:FontDialogHook
{PROP:Libhook, 4}	PROP:PrinterDialogHook
{PROP:Libhook, 5}	PROP:HaltHook
{PROP:Libhook, 6}	PROP:MessageHook
{PROP:Libhook, 7}	PROP:StopHook
{PROP:Libhook, 8}	PROP:AssertHook
{PROP:Libhook, 9}	PROP:FatalErrorHook
{PROP:Libhook, 12}	PROP:SystemPropHook
{PROP:Libhook, 13}	PROP:AssertHook2
{PROP:Libhook, 14}	PROP:InitAStringHook
{PROP:Libhook, 15}	PROP:UnlockThreadHook
{PROP:Libhook, 16}	PROP:LockThreadHook
{PROP:Libhook, 17}	PROP:ThreadLockedHook
{PROP:Libhook, 18}	PROP:FileDialogAHook
{PROP:Libhook, 19}	PROP:OpenWindowHook
{PROP:Libhook, 20}	PROP:CloseWindowHook
{PROP:Libhook, 21}	PROP:OpenReportHook
{PROP:Libhook, 22}	PROP:CloseReportHook



## PROP:LibVersion

A property of the SYSTEM built-in variable that returns the version number of the Clarion for Windows runtime library .DLL currently loaded for the EXE currently executing. This is separate from the version number of Clarion for Windows which compiled the EXE file (see PROP:ExeVersion). This first appeared in Clarion for Windows release 1501, so PROP:ExeVersion returns blank for releases prior to 1501. (READ-ONLY)

**Example:**

```
MESSAGE('Runtime DLL from release ' & SYSTEM{PROP:LibVersion})
```

## PROP:Line and PROP:LineCount

PROP:Line is an array whose elements each contain one line of the text in a TEXT control. (READ ONLY)

PROP:LineCount returns the number of lines of text in a TEXT control, or the total number of records in the listbox source. It can be useful if source of records is not a queue. If source is a queue, returned value is equal to RECORDS(queue). (READ ONLY)

### Example:

```
LineCount SHORT
MemoLine STRING(80)

CustRpt  REPORT,AT(1000,1000,6500,9000),THOUS
Detail1  DETAIL,AT(0,0,6500,6000)
        TEXT,AT(0,0,6500,6000),USE(Fil:MemoField)
        END
Detail2  DETAIL,AT(0,0,6500,125)
        STRING(@s80),AT(0,0,6500,125),USE(MemoLine)
        END
        END

CODE
OPEN(File)
SET(File)
OPEN(CustRpt)
LOOP
    NEXT(File)
    LineCount = CustRpt$?Fil:MemoField{PROP:LineCount}
    LOOP X# = 1 TO LineCount
        MemoLine = CustRpt$?Fil:MemoField{PROP:Line,X#}
        PRINT(Detail2)
    END
END
END
```

## PROP:LineHeight

Sets or returns the height of the rows in a LIST or COMBO control. The height is measured in dialog units (unless PROP:Pixels is active). For a TEXT control, it returns the character cell height of the control's font (the distance from the top of one line of text to the top of the next) in whatever measurement unit is currently in use. READ-ONLY for a TEXT control.

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    LIST,AT(0,0,220,220),USE(?L1),FROM(Que),IMM
END

CODE
OPEN(MDIChild)
?L1{PROP:LineHeight} = 8           !Set height to 8 dialog units
```

## PROP:MaxHeight

PROP:MaxHeight sets or returns the maximum height of a resizable window.

Regarding REPORT structures, this property can also be used to set or get the maximum value of a target report band's dimensions.

### Example:

```
WinView WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL,SYSTEM,RESIZE,|
    LIST,AT(6,6,120,90),USE(?List),FORMAT('120L'),FROM(Q),IMM
END

CODE
OPEN(WinView)
WinView{PROP:MaxHeight} = 200      !Set boundaries beyond which the user cannot
WinView{PROP:MaxWidth} = 320       ! resize the window
WinView{PROP:MinHeight} = 90
WinView{PROP:MinWidth} = 120
ACCEPT
END
```

## PROP:MaxWidth

PROP:MaxWidth sets or returns the maximum width of a resizable window.

Regarding REPORT structures, this property can also be used to set or get the maximum value of a target report band's dimensions.

### Example:

```
WinView WINDOW('View') ,AT(0,0,320,200) ,MDI ,MAX ,HVSCROLL ,SYSTEM ,RESIZE , |
    LIST ,AT(6,6,120,90) ,USE(?List) ,FORMAT('120L') ,FROM(Q) ,IMM
END

CODE
OPEN(WinView)
WinView{PROP:MaxHeight} = 200      !Set boundaries beyond which the user cannot
WinView{PROP:MaxWidth} = 320      ! resize the window
WinView{PROP:MinHeight} = 90
WinView{PROP:MinWidth} = 120
ACCEPT
END
```

## PROP:MenuBar

A WINDOW property used to return the Field Equate Label of a window's menubar.

This property is READ ONLY.

### Example:

```
MenubarFEQ = MyWindowLabel{PROP:Menubar}  !get Menubar's FEQ
```

## PROP:MessageHook

A property of the SYSTEM built-in variable that sets the override procedure for the MESSAGE internal Clarion procedure. Equivalent to {PROP:LibHook,6}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the MESSAGE procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the MESSAGE procedure found in the BUILTINS.CLW file. (WRITE-ONLY)

## PROP:MinHeight

PROP:MinHeight sets or returns the minimum height of a resizable window.

Regarding REPORT structures, this property can also be used to set or get the minimum value of a target report band's dimensions.

### Example:

```
WinView WINDOW('View') ,AT(0,0,320,200) ,MDI ,MAX ,HVSCROLL ,SYSTEM ,RESIZE ,|
    LIST ,AT(6,6,120,90) ,USE(?List) ,FORMAT('120L') ,FROM(Q) ,IMM
END

CODE
OPEN(WinView)
WinView{PROP:MaxHeight} = 200      !Set boundaries beyond which the user cannot
WinView{PROP:MaxWidth} = 320      ! resize the window
WinView{PROP:MinHeight} = 90
WinView{PROP:MinWidth} = 120
ACCEPT
END
```

## PROP:MinWidth

PROP:MinWidth sets or returns the minimum width of a resizable window. Also sets the minimum width of TAB controls in a SHEET.

Regarding REPORT structures, this property can also be used to set or get the minimum value of a target report band's dimensions.

### Example:

```
WinView WINDOW('View') ,AT(0,0,320,200) ,MDI ,MAX ,HVSCROLL ,SYSTEM ,RESIZE |
LIST ,AT(6,6,120,90) ,USE(?List) ,FORMAT('120L') ,FROM(Q) ,IMM
END

CODE
OPEN(WinView)
WinView{PROP:MaxHeight} = 200      !Set boundaries beyond which the user cannot
WinView{PROP:MaxWidth} = 320      ! resize the window
WinView{PROP:MinHeight} = 90
WinView{PROP:MinWidth} = 120
ACCEPT
END
```

## PROP:NextField

An array property which returns the next control number in sequence of a window or report. (READ-ONLY) The control number returned is the control following the array element numbered control. The order in which PROP:NextField returns field numbers is undefined. PROP:NextField returns zero when the array element number is the last control in its list. This property easily allows you to loop through all the controls in a window or report, whether those controls have USE attributes or not.

### Example:

```
WinView WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    IMAGE(),AT(0,0,,),USE(?Image)
    BUTTON('Save Picture'),AT(80,180,60,20),USE(?SavePic)
    BUTTON('New Picture'),AT(160,180,60,20),USE(?NewPic)
    BUTTON('Last Picture'),AT(240,180,60,20),USE(?LastPic)
END
ThisField SHORT(0)
CODE
OPEN(WinView)
LOOP
    ThisField = WinView{PROP:NextField,ThisField} !Process every control
    IF ThisField
        ThisField{PROP:FontName} = 'Arial' !Changing the font
        ThisField{PROP:FontSize} = 10
    ELSE
        BREAK !Break when done
    . .
ACCEPT
END
```

**See Also:** Prop:Follows

## PROP:NextPageNo

A property which sets or returns the next page number in a report.

When returning the NextPageNo property, consider that the page number may not yet have been determined by the print engine. It has many "page-based printing" features (e.g. WITHPRIOR/WITHNEXT) that may cause it to cache printed details and delay page break determination. To be sure that the page number you get is the final one after all cached details use the ENDPAGE statement.

The next page number may also be reset using the PAGEBEFORE or PAGEAFTER attributes on a DETAIL structure.

### Example:

```
CustRpt  REPORT, AT (1000,1000,6500,9000), THOUS
          HEADER
          STRING (@n3), USE (?Page), PAGENO
          END
Detail   DETAIL, AT (0,0,6500,1000)
          STRING, AT (10,10), USE (Fil:Field)
          END
          END

CODE
OPEN (File)
SET (File)
OPEN (CustRpt)
LOOP
  NEXT (File)
  IF Fil:KeyField <> Sav:KeyField      !Detect group break
    Sav:KeyField = Fil:KeyField      !Detect group break
    ENDPAGE                          !Force page break
    CustRpt{PROP:NextPageNo} = 1     !Every group starts on page one
  END
  PRINT (Detail)
END
CLOSE (CustRpt)
CLOSE (File)
```

### See Also:

REPORT, ENDPAGE, PAGEBEFORE, PAGEAFTER

## PROP:NextTabStop and PROP:PrevTabStop

PROP:NextTabStop returns the next control (field equate label) that can have input focus and be reached by pressing the Tab key.

PROP:PrevTabStop returns the previous control (field equate label) that can have input focus and be reached by pressing ShiftTab key

Example:

```
NextControlFEQ = window{PROP:NextTabStop} !get next control to TAB to
PrevControlFEQ = window{PROP:PrevTabStop} !Get next control to shift-tab to
Window{PROP:NextTabStop} = ?List      !Set the next control to tab to
```

## PROP:NoFrame

PROP:NoFrame is valid for any target control (BUTTON, CHECK, RADIO) containing an image.

If PROP:NoFrame is set to TRUE, the runtime library does not draw the focus rectangle for the target control even if it indeed has focus.

This property is useful for controls with an image occupying the full control area to avoid image distortion.

PROP:NoFrame has no effect if the target control does not have an image.

Example:

```
?Button {PROP:Icon} = 'Animated.GIF'
?Button {PROP:NoFrame} = TRUE
```

The default value for this property is FALSE. This property can only be set at runtime.



## PROP:NoHeight and PROP:NoWidth

PROP:NoHeight is a toggle attribute which returns whether the window or control was set to default its height (had an omitted height parameter in its AT attribute). Setting this property to TRUE is equivalent to resetting the control to its default height as determined by the library (which you cannot do using PROP:Height).

PROP:NoWidth is a toggle attribute which returns whether the window or control was set to default its width (had an omitted width parameter in its AT attribute). Setting this property to TRUE is equivalent to resetting the control to its default width as determined by the library (which you cannot do using PROP:Width).

### Example:

```
WinView WINDOW('View'),AT(0,0,,),MDI,MAX,HVSCROLL,SYSTEM,RESIZE
        LIST,AT(6,6,120,90),USE(?List),FORMAT('120L'),FROM(Q),IMM
        END
```

```
CODE
OPEN(WinView)
IF WinView{PROP:NoHeight} = TRUE
    WinView{PROP:Height} = 200          !Set height
END
IF WinView{PROP:NoWidth} = TRUE
    WinView{PROP:Width} = 320          !Set width
END
ACCEPT
END
```

## PROP:NoTips

Disables (when set to 1) or re-enables (when set to 0) tooltip display (TIP attribute) for the SYSTEM, window, or control.

### Example:

```
WinView APPLICATION('MyApp'),AT(0,0,320,200),MAX,HVSCROLL,SYSTEM
        END
CODE
OPEN(WinView)
SYSTEM{PROP:NoTips} = 1 !Disable TIP display throughout entire application
ACCEPT
END
```

**See Also:** TIP, TipsFont, TipDelay/TipDisplay

## PROP:NumTabs

PROP:NumTabs returns the number of TABs in a SHEET. (READ-ONLY)

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
SHEET,AT(0,0,320,175),USE(SelectedTab)
TAB('Tab One'),USE(?TabOne)
    OPTION('Option 1'),USE(OptVar1),KEY(F10Key),HLP('Option1Help')
    RADIO('Radio 1'),AT(20,0,20,20),USE(?R1)
    RADIO('Radio 2'),AT(40,0,20,20),USE(?R2)
END
OPTION('Option 2'),USE(OptVar2),MSG('Option 2')
RADIO('Radio 3'),AT(60,0,20,20),USE(?R3)
RADIO('Radio 4'),AT(80,0,20,20),USE(?R4)
END
END
TAB('Tab Two'),USE(?TabTwo)
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P1)
    ENTRY(@S8),AT(100,140,32,20),USE(E1)
    PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P2)
    ENTRY(@S8),AT(100,240,32,20),USE(E2)
END
TAB('Tab Three'),USE(?TabThree)
    OPTION('Option 3'),USE(OptVar3)
    RADIO('Radio 1'),AT(20,0,20,20),USE(?R5)
    RADIO('Radio 2'),AT(40,0,20,20),USE(?R6)
END
OPTION('Option 4'),USE(OptVar4)
RADIO('Radio 3'),AT(60,0,20,20),USE(?R7)
RADIO('Radio 4'),AT(80,0,20,20),USE(?R8)
END
END
TAB('Tab Four'),USE(?TabFour)
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P3)
    ENTRY(@S8),AT(100,140,32,20),USE(E3)
    PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P4)
    ENTRY(@S8),AT(100,240,32,20),USE(E4)
END
END
BUTTON('Ok'),AT(100,180,20,20),USE(?Ok)
BUTTON('Cancel'),AT(200,180,20,20),USE(?Cancel)
END
CODE
OPEN(MDIChild)
MESSAGE('Number of TABs: ' & ?SelectedTab{PROP:NumTabs})
MESSAGE('Number of rows of TABs: ' & ?SelectedTab{PROP:TabRows})
ACCEPT
END
```

**See Also:**

PROP:Child

PROP:ChildIndex

PROP:ChoiceFEQ

PROP:Parent

## **PROP:OpenReportHook**

A property of the SYSTEM built-in variable that sets the override procedure for the OPEN(Report) internal Clarion procedure. Equivalent to {PROP:LibHook,21}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the default OPEN procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the OPEN procedure found in the BUILTINS.CLW. (WRITE-ONLY)

## PROP:OpenWindowHook

A property of the SYSTEM built-in variable that sets the override procedure for the OPEN(Window) internal Clarion procedure. Equivalent to {PROP:LibHook,19}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the default OPEN procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the OPEN procedure found in the BUILTINS.CLW. (WRITE-ONLY)

## PROP:Parent

Returns the parent control for a control within a structure (such as an OPTION, SHEET or GROUP control structure, or a DETAIL, TOOLBAR, or MENUBAR structure). It can also be used to name a control (e.g., IMAGE) as a parent container for other controls.

### Example 1:

```
WinView WINDOW('MyApp'),AT(0,0,320,200),MAX,HVSCROLL,SYSTEM
    END
OptionSelected STRING(6)
?OptionControl EQUATE(100)    !A field equate number for CREATE to use
?Radio1         EQUATE(101)    !A field equate number for CREATE to use
?Radio2         EQUATE(102)    !A field equate number for CREATE to use
CODE
OPEN(WinView)
CREATE(?OptionControl,CREATE:option)           !Create the OPTION control
?OptionControl{PROP:use} = OptionSelected
?OptionControl{PROP:Text} = 'Pick one'
?OptionControl{PROP:Boxed} = TRUE
SETPOSITION(?OptionControl,10,10)
CREATE(?Radio1,CREATE:radio,?OptionControl)    !Create a RADIO control
?Radio1{PROP:Text} = 'First'
SETPOSITION(?Radio1,12,20)
!Create another with same parent:
CREATE(?Radio2,CREATE:radio,?Radio1{PROP:Parent})
?Radio2{PROP:Text} = 'Second'
SETPOSITION(?Radio2,12,30)
UNHIDE(?OptionControl,?Radio2)                !Display the new controls
ACCEPT
END
```

**Example 2:**

```

!-----
WinParent WINDOW('Caption'),AT(0,0,320,200),SYSTEM,GRAY,MDI
    SHEET,AT(x,x,x,x),USE(?Sheet)
    TAB('Tab 1'),USE(?Tab1)
    PROMPT('Prompt1:'),AT(x,x,x,x),USE(?Prompt1)
    ENTRY(@s20),AT(x,x,x,x),USE(Loc.Var)
    END
    END
    BUTTON('Close'),AT(x,x,x,x),USE(?Close)
    END

!      ?Sheet{Prop:Parent}    Belongs to WinParent
!      ?Tab1{Prop:Parent}    Belongs to ?Sheet
!      ?Prompt1{Prop:Parent} Belongs to ?Tab1
!      ?Loc:Var{Prop:Parent} Belongs to ?Tab1
!      ?Close{Prop:Parent}   Belongs to WinParent

```

**Example 3:**

```

!name a control as a parent container for other controls
CASE x{Prop:Type}
  OF Create:Button
    X{Prop:Parent}=?ImageHorizontal
    X{Prop:Ypos}=0
    X{Prop:Xpos}=ButtonXpos
    X{Prop:Scroll}=True
    ButtonXPos+=50
  OF Create:Prompt
    X{Prop:Parent}=?ImageStatic
    X{Prop:Xpos}=PromptXpos    !controls are mirrored to the image
    X{Prop:Scroll}=True
    X{Prop:Follows}=LastControl
    LastControl=X
  OF Create:Entry OROF Create:Text
    X{Prop:Parent}=?ImageStatic
    X{Prop:Xpos}=Xpos          !controls are mirrored to the image
    X{Prop:Scroll}=True
    X{Prop:Follows}=Lastcontrol
    LastControl=X
END

```

**See Also:**

PROP:NumTabs

PROP:Child

PROP:ChildIndex

PROP:ChoiceFEQ

## PROP:Pixels

WINDOW property which toggles screen measurement between dialog units (DLUs) and pixels (not available for reports). After setting this property, all screen positioning (such as GETPOSITION, SETPOSITION, MOUSEX, MOUSEY, PROP:Xpos, PROP:Ypos, PROP:Width, and PROP:Height) return and require co-ordinates in pixels rather than DLUs.

### Example:

```
WinView    WINDOW('MyApp') , AT(0,0,320,200) , MAX, HVSCROLL, SYSTEM
           END
CODE
OPEN(WinView)
WinView{PROP:Pixels} = 1  !Change measurement to pixels
ACCEPT
!all screen positioning statements now return pixels
END
```

## PROP:Places

An array that returns the number of decimal places declared for the specified DECIMAL or PDECIMAL field.

**See Also:** FILE Structure Properties

## PROP:PrinterDialogHook

A property of the SYSTEM built-in variable that sets the override procedure for the PRINTERDIALOG internal Clarion procedure. Equivalent to {PROP:LibHook,4}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the PRINTERDIALOG procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the PRINTERDIALOG procedure found in the BUILTINS.CLW file. (WRITE-ONLY)

## PROP:PrintMode

PROP:PrintMode is a property of a specific IMAGE control (or SYSTEM for all) that specifies how the PROP:ImageBlob property assignment stores images in the BLOB.

A value of 1 indicates that decoded (DIB or BMP) image information is only required to be stored.

A value of 2 indicates that undecoded (native) image information is only required to be stored.

When set to 3, both the original (undecoded) data and the decoded DIB data are available, allowing PROP:ImageBlob to store the image in its native format (such as JPG) in the BLOB, in addition to the decoded DIB data.

### Example:

```
WinView  WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL
         IMAGE(),AT(0,0,,),USE(?Image)
         BUTTON('Save Picture'),AT(80,180,60,20),USE(?SavePic)
         BUTTON('New Picture'),AT(160,180,60,20),USE(?NewPic)
         BUTTON('Last Picture'),AT(240,180,60,20),USE(?LastPic)
         END

SomeFile  FILE,DRIVER('TopSpeed'),PRE(Fil)      !A file with a memo field
MyBlob    BLOB,BINARY
Rec        RECORD
Fl         LONG
          END
          END

FileName  STRING(64)                          !Filename variable

CODE
OPEN(SomeFile); OPEN(WinView)
DISABLE(?LastPic)
IF NOT FILEDIALOG('File to View',FileName,'Images|*.BMP;*.PCX;*.JPG;*.WMF',0)
  RETURN                                     !Return if no file chosen
END
?Image{PROP:PrintMode} = 3                  !Setup to store native and DIB formats
?Image{PROP:Text} = FileName
ACCEPT
CASE ACCEPTED()
OF ?NewPic
  IF NOT FILEDIALOG('File to View',FileName,'Images|*.BMP;*.PCX;*.JPG;*.WMF',0)
    BREAK
  END
  ?Image{PROP:Text} = FileName
OF ?SavePic
  Fil:MyBlob{PROP:Handle} = ?Image{PROP:ImageBlob}  !Put image into BLOB
  ADD(SomeFile)                                     !and save it to the file on disk
  ENABLE(?LastPic)                                  !activate Last Picture button
OF ?LastPic
  ?Image{PROP:ImageBlob} = Fil:MyBlob{PROP:Handle}  !Put last saved BLOB into image
END
END
```

## PROP:Progress

You can directly update the display of a PROGRESS control by assigning a value (which must be within the range defined by the RANGE attribute) to the control's PROP:progress property.

**Example:**

```
BackgroundProcess PROCEDURE      !Background processing batch process

Win  WINDOW('Batch Processing...'),AT(,,400,400),TIMER(1),MDI,CENTER
      PROGRESS,AT(100,140,200,20),USE(?ProgressBar),RANGE(0,200)
      BUTTON('Cancel'),AT(190,300,20,20),STD(STD:Close)
      END

CODE
OPEN(Win)
OPEN(File)
?ProgressBar{PROP:rangehigh} = RECORDS(File)
SET(File)                  !Set up a batch process
ACCEPT
CASE EVENT()
OF EVENT:CloseWindow
  BREAK
OF EVENT:Timer              !Process records when timer allows it
  ProgressVariable += 3      !Auto-updates 1st progress bar
  LOOP 3 TIMES
  NEXT(File)
  IF ERRORCODE() THEN BREAK.
  ?ProgressBar{PROP:progress} = ?ProgressBar{PROP:progress} + 1
                                !Manually update progress bar
  !Perform some batch processing code
  . . .
CLOSE(File)
```

## PROP:PropVScroll

This property is used to determine how the vertical scroll bar's "thumb." is displayed.

If set to 1 and the number of records in the list box source (normally a queue) is greater than number of list box visible rows, the thickness of the "thumb" is dependent on the ratio of number of visible rows to the total number of records.

If set to 0, or the number of records is not greater than number of rows (i.e., page loaded browses), the "thumb" has a square shape.

This property is applicable for LIST and COMBO controls and for SYSTEM. New LIST and COMBO controls inherit the current value of this property from the SYSTEM setting.



## PROP:RejectCode

ENTRY, TEXT, COMBO, or SPIN control property which returns the last value REJECTCODE value set in EVENT:Rejected. PROP:RejectCode is persistent, while the REJECTCODE procedure only returns a valid value during EVENT:Rejected.

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P1)
    ENTRY(@N8),AT(100,140,32,20),USE(E1)
    BUTTON('Ok'),AT(100,180,20,20),USE(?Ok)
    BUTTON('Cancel'),AT(200,180,20,20),USE(?Cancel)
END

CODE
OPEN(MDIChild)
ACCEPT
CASE EVENT()
OF EVENT:Completed
    BREAK
END
CASE FIELD()
OF ?Ok
    CASE EVENT()
    OF EVENT:Accepted
        SELECT
    END
OF ?E1
    CASE EVENT()
    OF EVENT:Accepted
        IF ?E1{PROP:RejectCode} <> 0    !Check for rejected entry
            SELECT(?)                ! and make the user re-enter
            CYCLE                    ! immediately
        END
    END
OF ?Cancel
    CASE EVENT()
    OF EVENT:Accepted
        BREAK
    END
END
END
```

See Also: REJECTCODE

## PROP:ScreenText



Returns the text displayed on screen in the specified control.

### Example:

```
WinView    WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL
           SPIN(@n3),AT(0,0,320,180),USE(Fil:Field),RANGE(0,255)
           END

CODE
OPEN(WinView)
ACCEPT
CASE FIELD()
OF ?Fil:Field
CASE EVENT()
OF EVENT:Rejected
MESSAGE(?Fil:Field{PROP:ScreenText} & ' is not in the range 0-255')
SELECT(?)
CYCLE
END
END
END
```

### See Also:

CONTENTS

CHANGE

## PROP:SelStart (or PROP:Selected) and PROP:SelEnd

**PROP:SelStart** (also named **PROP:Selected**) sets or retrieves the beginning (inclusive) character to mark as a block in an **ENTRY** or **TEXT** control. It positions the data entry cursor left of the character, and sets **PROP:SelEnd** to zero (0) to indicate no block is marked. It also identifies the currently highlighted entry in a **LIST** or **COMBO** control (usually coded as **PROP:Selected** for this purpose). For **COMBO** controls, **PROP:Selected** should be applied to the **PROP:ListFeq** of the **COMBO**, and not to the combo **FEQ** directly.

**PROP:SelEnd** sets or retrieves the ending (inclusive) character to mark as a block in an **ENTRY** or **TEXT** control. A value of -1 is a special value that indicates that the selection goes to the end of the target control's text.

### Example:

```
WinView WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    ENTRY(@S30),AT(0,0,320,180),USE(Fil:Field),ALRT(F10Key)
    LIST,AT(6,6,120,90),USE(?List),FORMAT('120L'),FROM(Q),IMM
END

CODE
OPEN(WinView)
ACCEPT
CASE ACCEPTED()
OF ?List
    GET(Q,?List{PROP:Selected})      !Get highlighted entry from queue
OF ?Fil:Field
    SETCLIPBOARD(Fil:Field{?Fil:Field{PROP:SelStart} : ?Fil:Field{PROP:SelEnd}})
    !Place highlighted string slice in Windows' clipboard
END
END
```

```
!Example using a COMBO control in an EIP configuration
CASE EVENT()
    ! Trap the event
OF EVENT:NewSelection
    ! If the event is a new selection
    ! And it's a key we want...
IF KEYCODE() <> UpKey AND KEYCODE() <> DownKey AND |
    KEYCODE() <> PgDnKey AND KEYCODE() <> PgUpKey
UPDATE(SELF.FEQ)
Loc:Offset = SELF.FEQ{PROP:SelStart} -
1    ! Figure out where the cursor is
                                !in the item field
    ! Put the entered code into a local variable:
Loc:ItemCode = SUB(ItemList.Q.SON:ItemCode,1,Loc:Offset)
    ! Loop through the local item queue:
LOOP Loc:LqRecordCount = 1 to RECORDS(LQ:Queue)
    GET(LQ:Queue, Loc:LqRecordCount)
    IF LEFT(LQ:ItemCode,LEN(CLIP(Loc:ItemCode))) = CLIP(Loc:ItemCode)
        IF Loc:LqRecordCount > 1
            Loc:LQ:Position = Loc:LqRecordCount -
1    ! The record we want is the one
                                ! before the one we're on.
        ELSE
            Loc:LQ:Position = 1
                                ! Otherwise it's the first..
        END
    END
    ! Position to the LIST COMBO control:
    (SELF.FEQ{PROP:ListFeq}){PROP:Selected}=Loc:LQ:Position
    CHANGE(SELF.FEQ, LQ:ItemCode)
    ! Change the queue to reflect it
    BREAK
END
END
END
END
```

## PROP:Size

Returns or sets the size of a BLOB field. Before assigning data to the BLOB using the string slicing technique, if the BLOB does not yet contain any data you must set its size using PROP:Size. Before assigning additional data that will increase the amount of data in the BLOB (using the string slicing technique), you must reset its size using PROP:Size.

### Example:

```
Names      FILE,DRIVER('TopSpeed')
NbrKey     KEY(Names:Number)
Notes      BLOB           !Can be larger than 64K
Rec        RECORD
Name       STRING(20)
Number     SHORT
           END
           END

BlobSize   LONG
BlobBuffer1 STRING(65520),STATIC !Maximum size string
BlobBuffer2 STRING(65520),STATIC !Maximum size string

WinView    WINDOW('View BLOB Contents'),AT(0,0,320,200),SYSTEM
           TEXT,AT(0,0,320,180),USE(BlobBuffer1),VSCROLL
           TEXT,AT(0,190,320,180),USE(BlobBuffer2),VSCROLL,HIDE
           END

CODE
OPEN(Names)
SET(Names)
NEXT(Names)
OPEN(WinView)
BlobSize = Names.Notes{PROP:Size}    !Get size of BLOB contents
IF BlobSize > 65520
  BlobBuffer1 = Names.Notes[0 : 65519]
  BlobBuffer2 = Names.Notes[65520 : BlobSize - 1]
  WinView{PROP:Height} = 400
  UNHIDE(?BlobBuffer2)
ELSE
  BlobBuffer1 = Names.Notes[0 : BlobSize - 1]
END
ACCEPT
END
```

### See Also:

SIZE  
FILE Structure Properties

## PROP:SnapHeight and PROP:SnapWidth

PROP:SnapHeight sets the snap height of any window or dockable toolbox when it is resized. When a toolbox is repositioned from vertical docking to horizontal docking, it is resized and adjusted according to the PROP:SnapHeight and PROP:SnapWidth values.

PROP:SnapWidth sets the snap width of any window or dockable toolbox when it is resized. When a toolbox is repositioned from vertical docking to horizontal docking, it is resized and adjusted according to the PROP:SnapHeight and PROP:SnapWidth values.

### See Also:

DOCK, DOCKED, TOOLBOX

### Example:

```

PROGRAM
MAP
    main

    p1 (STRING)
END

CODE
main

main PROCEDURE

window APPLICATION('SnapWidth & SnapHeight'),AT(,,262,243),STATUS,MAX,RESIZE

    END
CODE
OPEN(window)
window{PROP:StatusText} = 'Drag the toolbar to any edge'
ACCEPT
    IF EVENT()=Event:OpenWindow
        START(p1,,system{PROP:target})

    END
END

p1 PROCEDURE(w)
win &WINDOW
width    SIGNED
height   SIGNED
window WINDOW,AT(50,50,100,20),SYSTEM,TOOLBOX,GRAY,RESIZE,MDI,IMM
        BUTTON,AT(80,2,15,15),USE(?Button4),ICON(ICON:Cut),FLAT
        BUTTON,AT(31,2,15,15),USE(?Button2),ICON(ICON:Copy),FLAT
        BUTTON,AT(55,2,15,15),USE(?Button3),ICON(ICON:Paste),FLAT
    END

!*****
! Using SnapWidth and SnapHeight, sets up "n" possible sizes for a TOOLBOX. I
n this |
! example, when the toolbox is docked to the left or right, it takes on the Ta
ll size
! When Top or Botton, it takes the Wide size.

!*****

```

```
CODE
win &= (w)
OPEN(window, win)
WINDOW{PROP:docked} = Dock:Float
window{PROP:dock} = DOCK:ALL

window{PROP:snapwidth, 1} = 20    ! Vertical size i.e., when made tall
window{PROP:snapheight, 1} = 150

window{PROP:snapwidth, 2} = 100   ! Horizontal size i.e., when made wide
window{PROP:snapheight, 2} = 20

window{PROP:snapwidth, 3} = 50    ! square
window{PROP:snapheight, 3} = 50

ACCEPT

IF EVENT() = EVENT:sized
! handle repositioning of buttons here
IF window{PROP:Width} = 20    ! is it tall?
    ?Button4{PROP:xpos} = 2
    ?Button4{PROP:ypos} = 53
    ?Button2{PROP:xpos} = 2
    ?Button2{PROP:ypos} = 19
    ?Button3{PROP:xpos} = 2
    ?Button3{PROP:ypos} = 36
ELIF window{PROP:Width} = 100 ! Is it wide?
    ?Button4{PROP:xpos} = 70
    ?Button4{PROP:ypos} = 2
    ?Button2{PROP:xpos} = 50
    ?Button2{PROP:ypos} = 2
    ?Button3{PROP:xpos} = 30
    ?Button3{PROP:ypos} = 2
ELSE                                     !it must be square
    ?Button4{PROP:xpos} = 27
    ?Button4{PROP:ypos} = 27
    ?Button2{PROP:xpos} = 27
    ?Button2{PROP:ypos} = 10
    ?Button3{PROP:xpos} = 5
    ?Button3{PROP:ypos} = 27
END
END
END
```

## PROP:StatusFont

A SYSTEM or WINDOW property that reads and writes the font settings for status bars. This property is used in conjunction with PROP:FontName, PROP:FontSize, PROP:FontColor, and PROP:FontStyle. The status bar uses the default character set (a value of the SYSTEM{PROP:CharSet}).

### Example:

```
! Tahoma is set as a default status bar font
SYSTEM{PROP:FontName + PROP:StatusFont} = 'Tahoma'
! When this window is active, Tahoma 10 is used for status bar
Window{PROP:FontSize + PROP:StatusFont} = 10
```

## PROP:StopHook

A property of the SYSTEM built-in variable that sets the override procedure for the STOP internal Clarion procedure. Equivalent to {PROP:LibHook,7}. Assign the ADDRESS of the overriding procedure, and the runtime library will call the overriding procedure instead of the STOP procedure. Assign zero and the runtime library will once again call its internal procedure. The overriding procedure's prototype must be exactly the same as the STOP procedure found in the BUILTINS.CLW file. (WRITE-ONLY)

## PROP:SystemPropHook

A property of the SYSTEM built-in variable that allows you to trap when SYSTEM{property} is being called. Equivalent to {PROP:LibHook,12}. You need to pass the address of a procedure which has a prototype of

PROCEDURE(SIGNED *Property*, BYTE *DoingSet*, BYTE *\*Done*, STRING *Value*), STRING

*Property* is the equated value between the property brackets {}.

*DoingSet* is set to TRUE (1) if **SYSTEM{property} = 'value'** is being called, or FALSE (0) if **'value = SYSTEM{property}'** is being called.

*Done* is set to TRUE if you do not want the system to process the property.

*Value* is set to what the property is being set to. This is only set when *DoingSet* is TRUE.

The procedure must return a string. This string is only used when *DoingSet* is FALSE and *Done* is set to TRUE. In this case it is what *value* gets set to in the line **'value = SYSTEM{property}'**.

## PROP:TabBarColor

```
FrameWindow{PROP:TabBarColor, index} = color  
color = FrameWindow{PROP:TabBarColor, n}
```

PROP:TabBarColor is used to set the background color for the MDI tab created for target MDI Child windows.

*FrameWindow* is the label of the Parent APPLICATION structure

*Index* must be an integer number from 1-8. An index value of 1 sets or gets the background color of the Tab Bar (the default value is the COLOR\_3DFACE system color). Other index values (2-8) are used for tab colors used on the tabs of subsequent MDI child windows.

This property is valid for MDI frame windows only. PROP:TabBarVisible must be set to TRUE for the frame; otherwise the PROP:TabBarColor property has no effect. Setting PROP:TabBarVisible to FALSE clears all previously set colors. The PROP:TabStyle must also be set to TabStyle:Colored.

### Example:

```
AppFrame{PROP:TabBarLocation} = MDITabLocation:Top  
AppFrame{PROP:TabBarStyle} = TabStyle:Default  
AppFrame{PROP:TabBarVisible} = True  
AppFrame{PROP:TabBarColor,1} = Color:Blue  
AppFrame{PROP:TabBarColor,2} = Color:Green  
AppFrame{PROP:TabBarColor,3} = Color:Red  
AppFrame{PROP:TabBarColor,4} = Color:Yellow  
AppFrame{PROP:TabBarColor,5} = Color:Aqua  
AppFrame{PROP:TabBarColor,6} = Color:Fuchsia  
AppFrame{PROP:TabBarColor,7} = Color:Teal  
AppFrame{PROP:TabBarColor,8} = Color:Purple
```

**See Also:** PROP:TabBarVisible



## **PROP:TabBarLocation**

**PROP:TabBarLocation** specifies the location of the MDI tab bar.

0 indicates to position the tab bar at the top of the frame window, and 1 indicates to position the tab bar at the bottom of the frame window.

## **PROP:TabBarStyle**

**PROP:TabBarStyle** specifies the visual style of the tab bar.

- |   |  |
|---|--|
| 1 | "black and white" in Office 2003 style |
| 2 | colored in Office 2003 style           |
| 3 | squared tab                            |
| 4 | boxed tab                              |

## **PROP:TabBarVisible**

**PROP:TabBarVisible** turns on/off visibility of the tab bar. The property is Boolean (TRUE/FALSE)

## PROP:TabRows

PROP:TabRows returns the number of rows of TABs in a SHEET. (READ-ONLY)

**See Also:** PROP:NumTabs

**Example:**

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
SHEET,AT(0,0,320,175),USE(SelectedTab)
TAB('Tab One'),USE(?TabOne)
    OPTION('Option 1'),USE(OptVar1),KEY(F10Key),HLP('Option1Help')
    RADIO('Radio 1'),AT(20,0,20,20),USE(?R1)
    RADIO('Radio 2'),AT(40,0,20,20),USE(?R2)
END
OPTION('Option 2'),USE(OptVar2),MSG('Option 2')
RADIO('Radio 3'),AT(60,0,20,20),USE(?R3)
RADIO('Radio 4'),AT(80,0,20,20),USE(?R4)
END
END
TAB('Tab Two'),USE(?TabTwo)
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P1)
    ENTRY(@S8),AT(100,140,32,20),USE(E1)
    PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P2)
    ENTRY(@S8),AT(100,240,32,20),USE(E2)
END
TAB('Tab Three'),USE(?TabThree)
    OPTION('Option 3'),USE(OptVar3)
    RADIO('Radio 1'),AT(20,0,20,20),USE(?R5)
    RADIO('Radio 2'),AT(40,0,20,20),USE(?R6)
END
OPTION('Option 4'),USE(OptVar4)
RADIO('Radio 3'),AT(60,0,20,20),USE(?R7)
RADIO('Radio 4'),AT(80,0,20,20),USE(?R8)
END
END
TAB('Tab Four'),USE(?TabFour)
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P3)
    ENTRY(@S8),AT(100,140,32,20),USE(E3)
    PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P4)
    ENTRY(@S8),AT(100,240,32,20),USE(E4)
END
END
BUTTON('Ok'),AT(100,180,20,20),USE(?Ok)
BUTTON('Cancel'),AT(200,180,20,20),USE(?Cancel)
END
CODE
OPEN(MDIChild)
MESSAGE('Number of TABs: ' & ?SelectedTab{PROP:NumTabs})
MESSAGE('Number of rows of TABs: ' & ?SelectedTab{PROP:TabRows})
ACCEPT
END
```

## PROP:TabSheetStyle

PROP:TabSheetStyle specifies the visual style of the target sheet/tab control.

0	"black and white" in Office 2003 style
1	colored in Office 2003 style
2	squared tab
3	boxed tab

## PROP:Target

A property of the SYSTEM built-in variable that is used to manipulate the current target. This property can be used to read or set the current target. It is equivalent to SETTARGET(target).

## PROP:TempImage

Property of an IMAGE control which returns the filename it creates for an image. For internal use in the Internet Connect templates, only.

## PROP:TempImagePath

SYSTEM property which sets or returns the path containing the temporary image files set by PROP:PrintMode or PROP:TempImage. Equivalent to {PROP:TempPath,2}. For internal use in the Internet Connect templates only.

## PROP:TempImageStatus

Property of an IMAGE control which returns whether or not PROP:TempImage created a new file or overwrote an existing file. For internal use in the Internet Connect templates, only.

## PROP:TempNameFunc

Property of a REPORT which allows you to create your own names for the metafiles generated for the PREVIEW attribute by writing a callback function to supply the metafile name for each page of the report. The callback function must be a PROCEDURE which takes a single SIGNED parameter and returns a STRING.

To turn this on, you must assign the ADDRESS of your callback function to PROP:TempNameFunc. To turn it off, you must assign zero (0).

The report engine, when it is about to write a page of the report to disk, calls your procedure, passing it the page number, and uses the return value from your procedure as the name of the metafile (both on disk and in the PREVIEW attribute's QUEUE). The callback function must create the file to ensure that the name is available.

When using PROP:TempNameFunc, PROP:FlushPreview writes the metafiles to the printer but does not automatically delete them (you must clean them up yourself, whenever your program is finished using them).

**Example:**

```
MEMBER('MyApp')
MAP
PageNames PROCEDURE(SIGNED),STRING      !Callback function prototype
END

MyReport PROCEDURE
MyQueue QUEUE                          !Preview queue
    STRING(64)
END
Report REPORT,PREVIEW(MyQueue)          !ReportDeclaration
END
CODE
OPEN(Report)
Report{PROP:TempNameFunc} = ADDRESS(PageNames) !Assign ADDRESS to property so
the
                                ! report engine calls PageNames to
                                ! get the name to use for each page
!Report processing code goes here
Report{PROP:TempNameFunc} = 0          !Assign zero to property to turn off
Report{PROP:FlushPreview} = TRUE       !Send the report to the printer
                                ! and the .WMF files are still on disk

PageNames PROCEDURE(PageNumber)        !Callback function for page names
NameVar STRING(260),STATIC
PageFile FILE,DRIVER('DOS'),NAME(NameVar),CREATE
Rec RECORD
Fl LONG
. .
CODE
NameVar = PATH() & '\PAGE' & FORMAT(PageNumber,@n04) & '.WMF'
CREATE(PageFile)
RETURN(NameVar)
```

## PROP:TempPagePath

SYSTEM property which sets or returns the path containing the temporary files for the page images. Equivalent to {PROP:TempPath,1}. For internal use in the Internet Connect templates, only.

## PROP:TempPath

Array SYSTEM property which sets or returns the path containing the temporary files for the page images or the path containing the temporary image files set by PROP:PrintMode. For internal use in the Internet Connect templates, only.

## PROP:ThemeActive

Returns a Boolean value (TRUE) if a Windows theme is currently active. This is usually a SYSTEM, READONLY property, but can also be used to test a specific control.

### Example:

```
IF SYSTEM{PROP:ThemeActive} = TRUE    !If a theme is active
!get new font size and set for target controls
  Do ProcessNewFontSize
END

!or:
IF ?Button{PROP:ThemeActive} = TRUE    !If a theme on a button is active
!get new font size and set for target control
  ProcessNewFontSize(?Button)
END
```

## PROP:Thread

Returns the thread number of a window. This is not necessarily the currently executing thread, if you've used SETTARGET to set the TARGET built-in variable. (READ-ONLY)

### Example:

```
WinView WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL,SYSTEM
  END
ToolboxThread BYTE
CODE
OPEN(WinView)
ToolboxThread = ToolboxWin{PROP:Thread}    !Get window thread number
ACCEPT
END
```

## PROP:Threading

Property of the SYSTEM built-in variable which, when set to zero (0), disables all MDI behavior and turns the application into an SDI application.

### Example:

```
PROGRAM
!Data declarations
CODE
IF SomeCondition = TRUE
  SYSTEM{PROP:Threading} = 0    !Set to SDI behavior
END
```

## PROP:TipDelay and PROP:TipDisplay

**PROP:TipDelay** sets the time delay before tooltip display (TIP attribute) for the SYSTEM.

**PROP:TipDisplay** sets the duration of tooltip display (TIP attribute) for the SYSTEM.

**Example:**

```
WinView  APPLICATION('MyApp'), AT(0,0,320,200), MAX, HVSCROLL, SYSTEM
        END

CODE
SYSTEM{PROP:TipDelay} = 50      !Delay TIP display for 1/2 second
SYSTEM{PROP:TipDisplay} = 500  !TIP display for 5 seconds
!It is always a best practice to set the SYSTEM properties
! before opening Frame
OPEN(WinView)
ACCEPT
END
```

**See Also:** TIP, TipsFont, NoTips

## PROP:TipsFont

A property of the SYSTEM built-in variable that reads and writes the font settings for tooltips. This property is used in conjunction with PROP:FontName, PROP:FontSize, PROP:FontColor, and PROP:FontStyle. Tooltips use the default character set (a value of the SYSTEM{PROP:CharSet}).

**Example:**

```
SYSTEM {PROP:FontName + PROP:TipsFont} !set/get font's typeface
SYSTEM {PROP:FontSize + PROP:TipsFont} !set/get font's size
SYSTEM {PROP:FontColor + PROP:TipsFont} !set/get font's color
SYSTEM {PROP:FontStyle + PROP:TipsFont} !set/get font's style
```

**See Also:** TIP, NoTips, TipDelay/TipDisplay

## PROP:ToolBar

A WINDOW property used to return the Field Equate Label of a window's toolbar.

This property is READ ONLY.

**Example:**

```
ToolBarFEQ = MyWindowLabel{PROP:ToolBar} !get toolbar's FEQ
```

## PROP:Touched

When non-zero, indicates the data in the ENTRY, TEXT, SPIN, or COMBO control with input focus has been changed by the user since the last EVENT:Accepted. This is automatically reset to zero each time the control generates an EVENT:Accepted. Setting this property (in EVENT:Selected) allows you to ensure that EVENT:Accepted generates to force data validation code to execute, overriding Windows' standard behavior--simply pressing TAB to navigate to another control does not automatically generate EVENT:Accepted.

PROP:Touched can also be interrogated to determine if the content of a BLOB has changed since it was retrieved from disk.

### Example:

```
WinView WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL
    ENTRY(@S30),AT(0,0,320,180),USE(Fil:Field)
    BUTTON('Ok'),AT(100,180,20,20),USE(?Ok)
    BUTTON('Cancel'),AT(200,180,20,20),USE(?Cancel)
END
SaveCancelPos LONG,DIM(4)
CODE
OPEN(WinView)
SaveCancelPos[1] = ?Cancel{PROP:Xpos}          !Save Cancel button area
SaveCancelPos[2] = ?Cancel{PROP:Xpos}+?Cancel{PROP:Width}
SaveCancelPos[3] = ?Cancel{PROP:Ypos}
SaveCancelPos[4] = ?Cancel{PROP:Ypos}+?Cancel{PROP:Height}
ACCEPT
CASE FIELD()
OF ?Fil:Field
CASE EVENT()
OF EVENT:Selected
    ?Fil:Field{PROP:Touched} = 1          !Force EVENT:Accepted to generate
OF EVENT:Accepted
    IF KEYCODE() = MouseLeft AND |          !Detect user clicking on Cancel
        INRANGE(MOUSEX(),SaveCancelPos[1],SaveCancelPos[2]) AND |
        INRANGE(MOUSEY(),SaveCancelPos[3],SaveCancelPos[4])
        CYCLE          !User clicked on Cancel
    ELSE
        !Process the data, whether entered by the user or in the field at the start
    END
OF ?Ok
CASE EVENT()
OF EVENT:Accepted
    !Write the data to disk
END
OF ?Cancel
CASE EVENT()
OF EVENT:Accepted
    !Do not write the data to disk
END
END
END
```

## PROP:Type

Contains the type of control. Values are the CREATE:xxxx equates (listed in EQUATES.CLW). (READ-ONLY)

**Note:**

PROP:Type has a different usage when used with FILE structures. [Jump here to review this.](#)

**Example:**

```
MyField  STRING(1)
?MyField EQUATE(100)

WinView  WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL
        END
CODE
OPEN(WinView)
IF UserChoice = 'CheckField'
    CREATE(?MyField,CREATE:Check)
ELSE
    CREATE(?MyField,CREATE:Entry)
END
?MyField{PROP:Use} = MyField
SETPOSITION(?MyField,10,10)
IF ?MyField{PROP:Type} = CREATE:Check      !Check control type
    ?MyField{PROP:TrueValue} = 'T'
    ?MyField{PROP:FalseValue} = 'F'
END
ACCEPT
END
```



## PROP:UpsideDown

This property toggles both the UP and DOWN attributes at once to display inverted TAB control text in a SHEET structure.

### Example:

```
WinView WINDOW('View'),AT(0,0,320,200),MDI,MAX,HVSCROLL
      SHEET,AT(0,0,320,175),USE(SelectedTab),RIGHT,DOWN !Tabs right reading do
wn
      TAB('Tab One'),USE(?TabOne)
        PROMPT('Enter Data:'),AT(100,100,20,20),USE(?P1)
        ENTRY(@S8),AT(100,140,32,20),USE(E1)
        PROMPT('Enter More Data:'),AT(100,200,20,20),USE(?P2)
        ENTRY(@S8),AT(100,240,32,20),USE(E2)
      END
      PROMPT('Enter Data:'),AT(100,100,20,20),USE(?P3)
      ENTRY(@S8),AT(100,140,32,20),USE(E3)
      PROMPT('Enter More Data:'),AT(100,200,20,20),USE(?P4)
      ENTRY(@S8),AT(100,240,32,20),USE(E4)
    END
  END
  BUTTON('Ok'),AT(100,180,20,20),USE(?Ok)
  BUTTON('Cancel'),AT(200,180,20,20),USE(?Cancel)
END
CODE
OPEN(WinView)
?SelectedTab{PROP:BELOW} = TRUE !Set tabs to display at bottom of sheet
?SelectedTab{PROP:UpsideDown} = TRUE !Invert the text displayed on the tabs
ACCEPT
END
```

## PROP:UseAddress

Returns the address of an ANY typed variable that refers to the USE variable of a control. This property is Read/Write, but the returned value can be used only in the right side of another property assignment to PROP:UseAddress (or, for comparison of values returned for 2 PROP:UseAddress properties).

### Example:

```
Loc:Any ANY
FEQ2      ANY

Window WINDOW('Caption'),AT(, ,260,100),GRAY
    ENTRY(@s20),AT(57,23,60,10),USE(Loc:Any)
    ENTRY(@s20),AT(57,50,60,10),USE(FEQ2)
END
X          LONG
CODE
OPEN(Window)
ACCEPT
    X = ?Loc:Any{PROP:UseAddress}
    ?Feq2{PROP:UseAddress} = X
    BREAK
END
```

## PROP:Visible

Returns an empty string if the control is not visible because either because it has been hidden, or it is a member of a "parent" control (OPTION, GROUP, MENU, SHEET, or TAB) that is hidden, or is on a TAB control page that is not currently selected. (READ-ONLY)

### Example:

```
MDIChild WINDOW('Child One'),AT(0,0,320,200),MDI,MAX,HVSCROLL
SHEET,AT(0,0,320,175),USE(SelectedTab)
TAB('Tab One'),USE(?TabOne)
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P1)
    ENTRY(@S8),AT(100,140,32,20),USE(E1)
    PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P2)
    ENTRY(@S8),AT(100,240,32,20),USE(E2)
END
TAB('Tab Two'),USE(?TabTwo)
    PROMPT('Enter Data: '),AT(100,100,20,20),USE(?P3)
    ENTRY(@S8),AT(100,140,32,20),USE(E3)
    PROMPT('Enter More Data: '),AT(100,200,20,20),USE(?P4)
    ENTRY(@S8),AT(100,240,32,20),USE(E4)
END
END
BUTTON('Ok'),AT(100,180,20,20),USE(?Ok)
BUTTON('Cancel'),AT(200,180,20,20),USE(?Cancel)
END

CODE
OPEN(MDIChild)
ACCEPT
CASE EVENT()
OF EVENT:Completed
    BREAK
END
CASE FIELD()
OF ?Ok
    CASE EVENT()
    OF EVENT:Accepted
        SELECT
    END
OF ?E3
    CASE EVENT()
    OF EVENT:Accepted
        E3 = UPPER(E3)           !Convert the data entered to Upper case
        IF ?E3{PROP:Visible} AND MDIChild{PROP:AcceptAll}
            !Check for visibility during AcceptAll mode
            DISPLAY(?E3)        ! and display the upper cased data
        END
    END
OF ?Cancel
    CASE EVENT()
    OF EVENT:Accepted
        BREAK
    END
END
END
```

## PROP:VLBproc and PROP:VLBval

PROP:VLBProc sets the source procedure for a "Virtual List Box" LIST or COMBO control without a FROM attribute. This procedure provides the control with the data to display.

The procedure's prototype must take three parameters:

```
VLBProc PROCEDURE (LONG, LONG, SHORT), STRING
```

where the first LONG is either SELF (indicating the procedure is a method of a CLASS) or the value set for PROP:VLBval. The second LONG passes the row number of the virtual list box to affect. There are three "special" values for this parameter, -1 asks for the number of records to display in the list, -2 asks for the number of fields in the nominal Queue (data and color/tree/icon fields) to display in the list, and -3 asks if there are any changes to display. The SHORT parameter specifies the column number of the virtual list box to affect.

PROP:VLBVal sets the source object for a "Virtual List Box" LIST or COMBO control without a FROM attribute. This can be any 32-bit unique value to identify the specific list box, but is generally the return value of ADDRESS(SELF) when the PROP:VLBProc procedure is a CLASS method.

**Example:**

```
PROGRAM
MAP
    Main
END

StripedListQ  QUEUE, TYPE
S              STRING (20)
END

StripedList  CLASS, TYPE
Init          PROCEDURE (WINDOW w, SIGNED feq, StripedListQ Q)
VLBproc       PROCEDURE (LONG row, SHORT column), STRING, PRIVATE
               !Required first parameter is implicit in a CLASS method
Q             &StripedListQ, PRIVATE
ochanges      LONG, PRIVATE
END

CODE
Main

StripedList.Init  PROCEDURE (WINDOW w, SIGNED feq, StripedListQ Q)

CODE
SELF.Q &= Q
SELF.ochanges = CHANGES (Q)

w $ feq{PROP:VLBval} = ADDRESS (SELF)      !Must assign this first
w $ feq{PROP:VLBproc} = ADDRESS (SELF.VLBproc)  ! then this

StripedList.VLBproc PROCEDURE (LONG row, SHORT col)  !Required first parameter is implied
nchanges LONG

CODE
CASE row
OF -1              ! How many rows?
    RETURN RECORDS (SELF.Q)
OF -2              ! How many columns?
    RETURN 5       ! 1 data, four color fields in the "nominal Q"
OF -3              ! Has it changed
```

```

    nchanges = CHANGES(SELF.Q)
    IF nchanges <> SELF.ochanges THEN
        SELF.ochanges = nchanges
        RETURN 1
    ELSE
        RETURN 0
    END
ELSE
    GET(SELF.Q, row)
    CASE col
    OF 1
        !Data field
        RETURN WHAT(SELF.Q,1)
    OF 3
        !Background color field
        RETURN CHOOSE(BAND(row,1), COLOR:none, 0c00000H)
    ELSE
        !All other fields
        RETURN COLOR:None
    ! Use default color
    END
END
END

Main PROCEDURE
window WINDOW('Caption'),AT(,,153,103),GRAY,SYSTEM
    LIST,AT(33,12,80,80),USE(?List1),FORMAT('20L*')
    END
Q    QUEUE(StripedListQ)
    END
SL    StripedList
i    SIGNED
CODE
LOOP i = 1 TO 20
    Q.s = 'Line ' & i
    ADD(Q)
END
OPEN(window)
SL.Init(window, ?list1, Q)
ACCEPT
END

```

## **PROP:Vscroll**

This Read/Write property mimics the VSCROLL attribute. If the value is set to zero ( 0 ), the vertical scrollbar will not be displayed, even if the number of records in the list is more than the number of visible rows.

When you place VSCROLL on a LIST with the IMM attribute, the vertical scroll bar is always present, even when the list is not full. When the user clicks on the scroll bar, events are generated, but the list contents do not move (executable code should perform this task). You can interrogate the PROP:VscrollPos property to determine the scroll thumb's position in the range 0 (top) to 100 (bottom).

## PROP:VscrollPos

Returns the position of the vertical scroll bar's "thumb." Valid values are from 0 to 255 on a window, IMAGE, or TEXT control with the VSCROLL attribute.

Valid values are from 0 to 100 on a LIST, or COMBO control with the VSCROLL attribute (when the IMM attribute is set on). If the IMM attribute is omitted, the values range from 0 to the number of items available for display in the LIST or COMBO (as specified by the FROM() attribute) minus one. If FROM(Queue) is specified, then the range is 0 to RECORDS(Queue) - 1. If FROM('list'), then the range is 0 to the number of items in 'list' - 1. For example, if FROM('Mr.|Mrs.|Ms.|Dr.'), Then the range is 0 to 3, because 4 is the number of items in the list.

The value of PROP:VScrollPos with IMM off specifies the exact number of items in the list or QUEUE that *precede* the first item displayed. For example, if row 5 of a QUEUE is the first item displayed, then the value of PROP:VScrollPos is 4.

Setting this property causes the control or window's contents to be scrolled vertically (unless the IMM attribute is on the LIST or COMBO, then only the "thumb" moves).

### Example:

```

Que  QUEUE
      STRING(50)
      END
WinView WINDOW('View'),AT(0,0,320,200),MDI,SYSTEM
      LIST,AT(0,0,320,200),USE(?List),FROM(Que),IMM,VSCROLL
      END

CODE
OPEN(WinView)
Fil:KeyField = 'A' ; DO BuildListQue
ACCEPT
CASE FIELD()
OF ?List
CASE EVENT()
OF EVENT:ScrollDrag
EXECUTE INT(?List{PROP:VscrollPos}/10) + 1
  Fil:KeyField = 'A'
  Fil:KeyField = 'C'
  Fil:KeyField = 'E'
  Fil:KeyField = 'G'
  Fil:KeyField = 'K'
  Fil:KeyField = 'M'
  Fil:KeyField = 'P'
  Fil:KeyField = 'S'
  Fil:KeyField = 'V'
  Fil:KeyField = 'Y'
END
DO BuildListQue
END
END
FREE(Que)

BuildListQue ROUTINE
FREE(Queue)
SET(Fil:SomeKey,Fil:SomeKey)           !Set to selected key field
LOOP ?List{PROP:Items} TIMES           !Process number of recs visible in list
  NEXT(SomeFile) ; IF ERRORCODE() THEN BREAK. !Break at end of file
  Que = Fil:KeyField                   !Assign field to display to QUEUE
  ADD(Que)                             ! and add it to the QUEUE
END

```

## PROP:Watched

Property of a FILE that returns whether the current record is being WATCHed. Returns 1 if the record is watched and an empty string (") if not. (READ ONLY)

**Example:**

```
FileName STRING(256)
Customer FILE,DRIVER('Clarion')
Record RECORD
Name STRING(20)

. .

CODE
OPEN(Customer)
SET(Customer)
LOOP
    WATCH(Customer)
    NEXT(Customer)
    IF ERRORCODE() THEN BREAK.
    IF Customer{PROP:Watched} <> ''
        MESSAGE('Record watched')
    END
END
END
```

## PROP:WheelScroll

A read/write property valid for list and combo box controls. Used to adjust the control sensitivity to mouse wheel scrolling. If property is set to a value less than 1, the property defaults to 1. The lower the value of the property results in more lines scrolled per wheel "click". Default value is 40 (approximately 3 rows per wheel "click" for standard mouse driver settings).



## PROP:WindowsVersion

Returns the string that describes Windows version running the program.

The runtime library returns the following information:

Windows/Win32 <version> [<category> | <edition>] [ServicePack] Build Number

Currently, values up to the *ServicePack* can be one of the following strings:

Windows 95  
Windows 95 OSR2  
Windows 98  
Windows 98 SE  
Windows Me  
Windows NT 3.5 WorkStation  
Windows NT 4 WorkStation  
Windows 2000 Professional  
Windows XP Home Edition  
Windows XP Professional  
Windows XP Tablet PC Edition  
Windows XP Media Center Edition  
Windows NT 3.5 Server  
Windows NT 3.5 Advanced Server  
Windows NT 4 Server  
Windows NT 4 Server, Enterprise Edition  
Windows 2000 Advanced Server  
Windows 2000 Small Business Server  
Windows 2000 Datacenter Server  
Windows Server 2003 Standard Edition  
Windows Server 2003 Datacenter Edition  
Windows Server 2003 Enterprise Edition  
Windows Server 2003 Web Edition  
Windows Vista Professional Build xxxx

The Service Pack value is present only if applicable

Read only. Available for SYSTEM only.

### Example:

```
GLO:WindowsVersion = SYSTEM{PROP:WindowsVersion}
```

## PROP:WndProc

Sets or gets the window's (not the client area) or a specific control's messaging procedure for use with low-level Windows API calls that require it. Generally used in sub-classing to track all Windows messages.

### Example:

```
PROGRAM

MAP

Main          PROCEDURE

SubClassFunc1  PROCEDURE (UNSIGNED, UNSIGNED, UNSIGNED, LONG), LONG, PASCAL
SubClassFunc2  PROCEDURE (UNSIGNED, UNSIGNED, UNSIGNED, LONG), LONG, PASCAL
MODULE (')
!SoftVelocity Win Library
CallWindowProc
PROCEDURE (LONG, UNSIGNED, SIGNED, UNSIGNED, LONG), LONG, PASCAL, NAME ('CallWindowProcA')
END
END

SavedProc1    LONG
SavedProc2    LONG
WM_MOUSEMOVE  EQUATE (0200H)

PT            GROUP
X             SIGNED
Y             SIGNED
END

CODE
Main

Main          PROCEDURE

WinView WINDOW ('View'), AT (0, 0, 320, 200), HVSCROLL, MAX, TIMER (1), STATUS
STRING ('X Pos'), AT (1, 1, ,), USE (?String1)
STRING (@n3), AT (24, 1, ,), USE (PT:X)
STRING ('Y Pos'), AT (44, 1, ,), USE (?String2)
STRING (@n3), AT (68, 1, ,), USE (PT:Y)
BUTTON ('Close'), AT (240, 180, 60, 20), USE (?Close)
END

CODE
```

```

OPEN(WinView)

SavedProc1 = WinView{PROP:WndProc}           !Save this procedure
WinView{PROP:WndProc} = ADDRESS(SubClassFunc1) !Name subclass procedure

SavedProc2 = WinView{PROP:ClientWndProc}     !Save this procedure
WinView{PROP:ClientWndProc} = ADDRESS(SubClassFunc2) !Name subclass procedure

ACCEPT
CASE ACCEPTED()
OF ?Close
  BREAK
END
END

SubClassFunc1    PROCEDURE(hWnd,wMsg,wParam,lParam)    !Sub class procedure
CODE                                                     ! to track mouse movement in
IF wMsg = WM_MOUSEMOVE                                ! window's status bar (only)
  PT.X = MOUSEX() ; PT.Y = MOUSEY()                   !Assign mouse position
END
RETURN(CallWindowProc(SavedProc1,hWnd,wMsg,wParam,lParam))!Pass control to SavedProc1

SubClassFunc2    PROCEDURE(hWnd,wMsg,wParam,lParam)    !Sub class procedure
CODE                                                     ! to track mouse movement in
IF wMsg = WM_MOUSEMOVE                                ! window's client area
  PT.X = MOUSEX() ; PT.Y = MOUSEY()                   !Assign mouse position
END
RETURN(CallWindowProc(SavedProc2,hWnd,wMsg,wParam,lParam))!Pass control to SavedProc2

```

## PROP:Xorigin and PROP:YOrigin

### ( how much a window or control has been scrolled)

Attributes of a SHEET, IMAGE, or LIST control (which have horizontal and/or vertical scrollbar(s)) that sets or retrieves how much the control has been scrolled. XORIGIN (**PROP:Xorigin**) specifies how much the control has scrolled in the X direction. YORIGIN (**PROP:Yorigin**) specifies how much the control has scrolled in the Y direction. As the example shows below, these properties are also valid on a WINDOW.

This property returns the value that CHOICE( ) would return for the first visible row of a referenced list box. This property allows you to calculate the current position of the highlighted row, (e.g. CHOICE(?List) - ?List{PROP:YOrigin} + 1)

You can also set this property using the following syntax:

```
?List {PROP:YOrigin} = n
```

where  $n$  is the topmost visible row to scroll the list box to. The runtime library will then adjust the given value to show as many rows as possible. For example, if

$n + (?List\{PROP:Items\} - 1) > ?List\{PROP:LineCount\}$ ,  $n$  is changed to  $?List\{PROP:LineCount\} - (?List\{PROP:Items\} - 1)$

If  $n \leq 0$ ,  $n$  is changed to 1.

#### Example

```
PROGRAM
MAP
END
S STRING(20)
Window WINDOW('Caption'),AT(,,400,250),FONT('MS Sans Serif',8,,FONT:regular)|
,IMM,VSCROLL, STATUS,SYSTEM,GRAY,CENTER
ENTRY(@S20),AT(10,100),USE(S,,?S1),SCROLL
ENTRY(@S20),AT(10,500),USE(S,,?S2),SCROLL
ENTRY(@S20),AT(10,900),USE(S,,?S3),SCROLL
END
```

y1        UNSIGNED

y2        UNSIGNED

Wy1       UNSIGNED

Wy2       UNSIGNED

Control SIGNED

```
CODE
OPEN(Window)
ACCEPT
CASE EVENT()
OF EVENT:Selected
Control = SELECTED()
```

```
IF Control
  y1 = Control {PROP:yPos}
  y2 = y1 + Control {PROP:Height}
  Wy1 = 0{PROP:YOrigin}                                !read Yorigin
  Wy2 = Wy1 + 0 {PROP:ClientHeight}
  IF y1 < Wy1
    0{PROP:YOrigin} = CHOOSE (y1 < 20, 0, y1 - 20)
  ELSIF y2 > Wy2
    0{PROP:YOrigin} = Wy1 + y2 - Wy2 + 20              !set Yorigin
  END
END
END
END
CLOSE(Window)
```

**See Also:** PROP:LineCount

## Runtime VIEW and FILE Properties

### File Structure Properties

PROP:Blob – FILE property  
PROP:Completed – FILE property  
PROP:ConnectionString – FILE property  
PROP:CurrentKey – FILE property  
PROP:Details – FILE property  
PROP:DriverLogoutAlias – FILE property  
PROP:DuplicateKey  
PROP:FetchSize – FILE or VIEW property  
PROP:Field – VIEW property  
PROP:Fields - FILE and VIEW property  
PROP:FieldsFile – VIEW property  
PROP:File – VIEW property  
PROP:Files – VIEW property  
PROP:FlushLog – FILE property  
PROP:Held – FILE property  
PROP:Log – FILE property  
PROP:Logout – FILE property  
PROP:LogoutIsolationLevel – FILE property  
PROP:MaxStatements – FILE property  
PROP:Profile – FILE property  
PROP:ProgressEvents – FILE property  
PROP:Record – FILE property  
PROP:SQLDriver – FILE property  
PROP:StmtAttr – FILE property  
PROP:SupportsOp – FILE property  
PROP:SupportsType – FILE property  
PROP:Text – FILE (MEMO)property  
PROP:Value – FILE property  
PROP:Watched – FILE property

## PROP:Completed

PROP:Completed is a property of a FILE that returns the percentage completed of the re-build during a BUILD or PACK operation for which PROP:ProgressEvents has been turned on. Returns zero (0) if the file driver does not know how much of the BUILD or PACK has been done (READ ONLY).

## PROP:ConnectionString

Property of a FILE using the ODBC driver that returns the connection string (normally stored in the file's OWNER attribute) that would allow a complete connection. If the OWNER attribute contains only a data source name, a login screen appears to ask for the rest of the required details before the connection is made. This login window appears every time you log on. With this property, the developer can enter information in the login screen once, then set the OWNER attribute to the return value from PROP:ConnectionString, eliminating the login.

### Example:

```
OwnerString  STRING(20)
Customer  FILE,DRIIVER('ODBC'),OWNER(OwnerString)
Record      RECORD
Name        STRING(20)
.
.
CODE
OwnerString = 'DataSourceName'
OPEN(Customer)
OwnerString = Customer{PROP:ConnectionString}      !Get full connect string
MESSAGE(OwnerString)                               !Display it for future use
```

## PROP:CurrentKey

Property of a FILE that returns a reference to the current KEY or INDEX being used for sequential processing, or the current key being built during a BUILD or PACK operation (READ ONLY). Valid only as the source side of a reference assignment statement or in a logical expression comparing the return result to NULL. Returns NULL if the file is being processed in record order.

### Example:

```
KeyRef &KEY
Customer  FILE,DRIIVER('Clarion'), PRE(Cus)
NameKey   KEY(Cus:Name),DUP
Record     RECORD
Name      STRING(20)
.
.
CODE
OPEN(Customer)
SET(Customer)
KeyRef &= Customer{PROP:CurrentKey}      !Returns NULL
IF Customer{PROP:CurrentKey} &= NULL     !Compare to NULL
  MESSAGE('SET to record order')
END
SET(Cus:NameKey)
KeyRef &= Customer{PROP:CurrentKey}      !Returns reference to Cus:NameKey
```

## PROP:DataPath

A read/write SYSTEM property that can be used to set the default directory for data files.

All files with unqualified file names (e.g., those files with no NAME attribute or a NAME with only a relative path) will be looked for in the directory specified by SYSTEM{PROP:DataPath}.

SYSTEM{PROP:DataPath} defaults to the directory the application starts in. This will save developers from having to do startup code like the following:

```
GETINI(datadirectory)
file1name = datadirectory & 'file1'
file2name = datadirectory & 'file2'
file3name = datadirectory & 'file3'
```

## PROP:Details

Property of a FILE that toggles turning Record Buffer logging on or off. file{PROP:Details}=1 turns Record Buffer logging on and file{PROP:Details}=0 turns Record Buffer logging off.

**See Also:**

PROP:Profile

PROP:Log

## PROP:DriverLogoutAlias

Property of a FILE that returns whether the file driver allows the LOGOUT statement to name both a file and an alias for the file in the same statement (READ ONLY).

**Example:**

```
IF Customer{PROP:DriverLogoutAlias} = '' !Test for alias allowed in LOGOUT
  MESSAGE('Driver does not allow files and their aliases in LOGOUT')
END
```



## PROP:DuplicateKey

Read-Only property of a FILE that returns the key that caused the last duplicate key error. It is cleared only when a subsequent ADD or PUT is attempted.

It is very common that you want to know which key causes a duplicate key error after you do a PUT or an ADD. At present you do this by looping through all keys that a file has and testing for DUPLICATE for each key until you find one. This is inefficient and requires a fair amount of code. Generally, the file drivers already know which key you are looking for, so why not ask the driver for the key. You can now do this using PROP:DuplicateKey.

### Example:

```

PROGRAM

MAP
END

f FILE, DRIVER('Clarion'), CREATE, PRE(f)
pk KEY(f:fld1)
RECORD
fld1 LONG
END
END

k &KEY
CODE
CREATE(f)
OPEN(f)
f.fld1 = 1
ADD(f)
f.fld1 = 2
ADD(f)
k &= f{PROP:DuplicateKey} ! k is NULL at this stage because no duplicate has occurred
f.fld1 = 1
PUT(f)
k &= f{PROP:DuplicateKey} ! k will be set to f:pk as the PUT caused a
                        ! duplicate key error

SET(pk)
GET(pk)
f.fld1 = 7
k &= f{PROP:DuplicateKey} ! k will be still be set at this stage
PUT(f)
k &= f{PROP:DuplicateKey} ! k will be NULL now

```

## PROP:FetchSize

Property of a FILE or VIEW which sets or gets the *pagesize* parameter for the last BUFFER statement executed.

Example:

```
CODE
OPEN(MyFile)
BUFFER(MyFile,10,5,2,300)  !10 records per page, 5 pages behind and 2 read-
ahead,
                        ! with a 5 minute timeout
MyFile{PROP:FetchSize} = 1 !Change fetch rate to one record at a time
```

## PROP:Field

Property of a VIEW which returns the field number in a file for the specified field number in a VIEW. (READ ONLY)

You can also use PROP:Field to retrieve the component of a designated key.

Example:

```
KFile  &FILE
Record &GROUP
CODE
    KFile &= key{PROP:File}
    MESSAGE(KFile{PROP:Label, key{PROP:Field, 1}}) !Returns label of first key component
```

## PROP:FieldsFile

Property of a VIEW which returns a reference to the file that contains the specified field number in a VIEW. (READ ONLY)

Example:

```
Header  FILE,DRIVER('TopSpeed'),PRE(Hea)
OrderKey KEY(Hea:AcctNumber, Hea:OrderNumber)
Record  RECORD
AcctNumber  LONG
OrderNumber LONG
OrderDate   LONG
. .

Detail  FILE,DRIVER('TopSpeed'),PRE(Det)
OrderKey KEY(Det:AcctNumber,Det:OrderNumber)
Record  RECORD
AcctNumber  LONG
OrderNumber LONG
ItemNumber  LONG
. .

AView  VIEW(Header)
      PROJECT(Hea:AcctNumber,Hea:OrderNumber,Hea:OrderDate)
      JOIN(Det:OrderKey,Hea:AcctNumber,Hea:OrderNumber)
. .

!AView{PROP:Field,1} Returns 1 which represents Hea:AcctNumber
!AView{PROP:Field,2} Returns 2 which represents Hea:OrderNumber
!AView{PROP:Field,3} Returns 3 which represents Hea:OrderDate
!AView{PROP:Field,4} Returns 1 which represents Det:AcctNumber
!AView{PROP:Field,5} Returns 2 which represents Det:OrderNumber
!AView{PROP:Field,6} Returns 3 which represents Det:ItemNumber

!AView{PROP:FieldsFile,2} Returns a reference to the Header File
!AView{PROP:FieldsFile,5} Returns a reference to the Detail File
```

## PROP:File

An array property of a VIEW. Each array element returns a reference to the numbered file in the VIEW. This reference can be used as the source side of a reference assignment statement. The files are numbered within the VIEW starting with 1 (the primary file in the VIEW) and continuing for each JOIN, as they appear within the VIEW structure. (READ ONLY)

PROP:File can now also be used to return the key's file name from a KEY.

Example:

```
GetFileInfoFromKey  PROCEDURE(*KEY key)
KFile  &FILE
Record &GROUP
CODE
  KFile &= key{PROP:File}
  MESSAGE(KFile{PROP:Label, key{PROP:Field, 1}}) !Returns label of first key component
```

## PROP:Files

Property of a VIEW which returns the total number of files in the VIEW. This is equivalent to the total number of JOIN structures, plus one (the primary file named in the VIEW statement itself). (READ ONLY)

view{PROP:files, *N*}

Returns the number of JOINS (including sub-joins) that there are for a file. *N* is the order of the file nested in the VIEW. If *n* is 0, the total number of files in the VIEW is returned. This property is useful to detect how many files are children of a target JOIN.

### Example 1:

```
AVIEW VIEW(BaseFile)                                !File 1
  JOIN(ParentFile, 'BaseFile.parentID = ParentFile.ID') !File 2
  JOIN(GrandParent.PrimaryKey, ParentFile.GrandParentID) !File 3
  END
END
JOIN(OtherParent.PrimaryKey, BaseFile.OtherParentID) !File 4
END
END
! AView{PROP:Files} returns 4
! AView{PROP:File,1} returns a reference to BaseFile
! AView{PROP:File,2} returns a reference to Parent
! AView{PROP:File,3} returns a reference to GrandParent
! AView{PROP:File,4} returns a reference to OtherParent

FilesQ QUEUE
FileRef &FILE
  END
CODE
LOOP X# = 1 TO AView{PROP:Files}      !Loop 4 times
  FilesQ.FileRef &= AView{PROP:File,X#} !Reference assign each file in the VIEW
  ADD(FilesQ)                        ! and add it to the queue
  ASSERT(~ERRORCODE())               !Assume no errors
  CLEAR(FilesQ)                      !Clear the queue for the next assignment
END
```

### Example 2:

```
v VIEW(PFile), ORDER('PFile:String1'), FILTER('PFile:ID = 3')
  PROJECT(PFile:ID, PFile:String1)
  JOIN(Child1:Keyname, PFile:ID)      !File Child1 has 4 fields
  JOIN(Child2:Keyname, Child1:ID)     !File Child2 has 4 fields
  JOIN(Child3, 'Child3:LinkField = Child2:ID')
  PROJECT(Child3:String2)
  END
END
JOIN(Child2Child1:KeyName, Child1:ID) !File Child2Child1 has 4 fields
END
END
END

v{PROP:Files, 0} will return 5
v{PROP:Files, 1} will return 4
v{PROP:Files, 2} will return 3
v{PROP:Files, 3} will return 1
v{PROP:Files, 4} will return 0
v{PROP:Files, 5} will return 0
```

See Also: JOIN

## PROP:FileSize

*file*{PROP:FileSize}

*file*     The label of the file, or a property that references a file label.

---

PROP:FileSize returns the number of bytes in the file. BYTES() returns the file size until the first record access, then it returns the size of the last read record. PROP:FileSize can be used to return the full file size after the first GET/NEXT/ADD statement.

### Example:

```
ProcessClass.Reset  PROCEDURE
CODE
SELF.RecordsProcessed = 0
IF ~SELF.StepMgr &= NULL
    SELF.SetProgressLimits
ELSIF ~SELF.RecordsToProcess
    SELF.Primary.Me.UseFile
    SELF.RecordsToProcess = RECORDS(SELF.Primary.Me.File)
    IF ~SELF.RecordsToProcess    ! Records not supported
        SELF.FileSize = SELF.Primary.Me.File{PROP:FileSize}
    END
END
END
SELF.ChildRead = 0
PARENT.Reset
```

## PROP:FlushLog

*file**label*{PROP:FlushLog} = 0|1

or

Flush=1|0 (in the WIN.INI)

Property of a FILE that will disable the default caching of the file logging feature.

By default, the file drivers will cache logging information so that a complete line is written to the log file at one time. This makes the log file easy to read when you have multiple threads running, but has the disadvantage that some information can be lost if a crash occurs.

If you want to make sure that no information is lost during a log run, and don't mind having some mixed up logging information when multiple threads are running, then you can force the file driver to flush the log file whenever there is something to write by adding

```
file{PROP:FlushLog} = TRUE
```

or by adding the line

```
Flush=1
```

to the driver section of WIN.INI. You can use the trace utility to do this for you.

```
file{PROP:FlushLog} = FALSE
```

will turn off flushing.

## PROP:GlobalHelp

SYSTEM property which, when on, specifies disabling automatic .HLP file closing when the window which opened the .HLP file is closed. This makes the .HLP file stay open until the user closes it.

### Example:

```
SYSTEM{PROP:GlobalHelp} = TRUE      !Disable automatic HLP file close
```

## PROP:Held

Property of a FILE that returns whether the current record is held. Returns 1 if the record is held and an empty string ("") if not. (READ ONLY)

### Example:

```
FileName STRING(256)
Customer FILE,DRIVER('Clarion')
Record    RECORD
Name      STRING(20)
          END
          END
CODE
OPEN(Customer)
SET(Customer)
LOOP
  HOLD(Customer,1)
  NEXT(Customer)
  IF ERRORCODE() THEN BREAK END
  IF Customer{PROP:Held} <> ''
    MESSAGE('Record Held')
  END
END
RELEASE(Customer)
```

## PROP:Log

Property of a FILE that writes a string to the current profile output file (assigned to PROP:Profile). This string is placed on its own line in the file. (WRITE ONLY)

### Example:

```
FileName STRING(256)
Customer  FILE,DRIVER('TopSpeed')
Record    RECORD
Name      STRING(20)
          END
          END

CODE
Customer{PROP:Profile} = 'CustLog.TXT'
!statement above turns profiling on, output file:CustLog.TXT
OPEN(Customer)
Filename = Customer{PROP:Profile} !Get name of current log file

Customer{PROP:Log} = CLIP(Filename) & ' ' & |
                    FORMAT(TODAY(),@D2) & ' ' & |
                    FORMAT(CLOCK(),@T1)
!Write a line of text to the log file

SET(Customer)
LOOP
  NEXT(Customer)          !All file I/O action is logged out to
  IF ERRORCODE() THEN BREAK. ! the CustLog.TXT file
END
Customer{PROP:Profile} = '' !Turn profiling off
```



## PROP:Logout

Property of a FILE that assigns or returns the priority level of the referenced FILE within a transaction. PROP:Logout may be used to build the list of files in the transaction before issuing the LOGOUT(*seconds*) statement to begin the transaction. By using PROP:Logout, you can add more files to the transaction than the limited number of parameters the LOGOUT statement will allow. If the LOGOUT statement lists any files at all, all files previously set for the transaction by PROP:Logout are removed from the transaction and only the files listed in the LOGOUT statement are logged out.

The priority level indicates the order in which the file is logged out in the transaction, with lower numbers being logged out before the higher numbers. If two files have the same priority level, they are logged out in the order in which they were added to the logout list. Assigning a positive priority level adds the FILE to the transaction, assigning a negative priority level removes the FILE from the transaction, and assigning zero (0) has no effect. Querying PROP:Logout returns the priority level assigned to the file, and zero (0) if the file is not a part of the transaction.

Attempting to use PROP:Logout to add a file to the transaction which uses a different file driver will result in ERRORCODE 48, "Unable to log transaction."

### Example:

```
Customer FILE,DRIVER('TopSpeed')
Record   RECORD
CustNumber LONG
Name     STRING(20)
        END
        END

Orders  FILE,DRIVER('TopSpeed')
Record  RECORD
CustNumber LONG
OrderNumber LONG
OrderDate LONG
        END
        END

Items   FILE,DRIVER('TopSpeed')
Record  RECORD
OrderNumber LONG
ItemNumber LONG
        END
        END

CODE
Customer{PROP:Logout} = 1 !Add Customer file to list and set priority to 1
Items{PROP:Logout} = 2    !Add Items file to logout list and set priority to 2
Orders{PROP:Logout} = 1   !Add Orders file to logout list and set priority to 1

X# = Items{PROP:Logout}    !Return Items file priority level (X# = 2)
Customer{PROP:Logout} = -1 !Remove Customer file from logout list
LOGOUT(1)                  !Begin transaction and
                           ! logout files in this order: Orders, Items
                           ! AND clear the logout list
X# = Items{PROP:Logout}    !Returns 0 LOGOUT statement cleared the logout list.
Items{PROP:Logout} = 1     !Add Items to list (now there is one table in list)

COMMIT                     !Terminate the transaction
Orders{PROP:Logout}=1      !Add Orders as well (now there are 2 tables on the list)
LOGOUT(1)                  !Logout Items and Orders tables, and clear the list
COMMIT                     !Terminate the transaction
```

## PROP:LogoutIsolationLevel

Property of a FILE that controls what isolation level is used within a transaction frame. This property is valid on all SQL based drivers (except Oracle). The default value is 8.

PROP:LogoutIsolationLevel uses the ODBC isolation level standard. This may not be the same as the isolation levels documented on the target driver's native back end. For example, with Sybase's ASA, the documented isolation levels are 0, 1, 2 and 3 and they correspond to

ODBC level	Sybase Level
1	0
2	1
4	2
8	3
16	N/A

## PROP:MaxStatements

Property of a FILE that allows you to find out how many statements can be active before a new connection to the database is raised. This property can also set the maximum number of statements before another connection is raised. This property is valid on all SQL file types except Oracle.

## PROP:Profile

Property of a FILE that toggles logging out (profiling) all file I/O calls and errors returned by the file driver to a specified text file. Assigning a filename to PROP:Profile initiates profiling, while assigning an empty string ("") turns off profiling. Querying this property returns the name of the current logfile, and an empty string ("") if profiling is turned off.

### Example:

```
filelabel{PROP:Profile} = 'tracelog.txt' !turn on logging
filelabel{PROP:Profile} = '' !turn OFF logging
```

## PROP:ProgressEvents

PROP:ProgressEvents is a property of a FILE that generates events to the currently open window during a BUILD or PACK operation (WRITE ONLY). This property is driver-dependent, and currently only supported for Clarion and Topspeed files.

Assigning a value of zero (0) turns off event generation for the next BUILD or PACK statement executed, while assigning any other value (valid range--1 to 100) turns on event generation. Out of range assignments are treated as follows: a negative number is treated as one (1), and any value greater than one hundred (100) is treated as one hundred (100). The larger the value assigned, the more events are generated and the slower the BUILD or PACK will progress.

Events generated are: EVENT:BuildFile, EVENT:BuildKey, and EVENT:BuildDone. It is not valid to make any calls to the FILE being built except to query its properties, call NAME(*file*), or CLOSE(*file*) (which aborts the process and is not recommended). Issuing a CYCLE statement in response to any of the events generated (except EVENT:BuildDone) cancels the operation.

PROP:CurrentKey may be used to get a reference to the current key being built, then PROP:Label may be used to retrieve the key's label for display to the user.

PROP:Completed is a property of a FILE that returns the percentage completed of the re-build during a BUILD or PACK operation for which PROP:ProgressEvents has been turned on. Returns zero (0) if the file driver does not know how much of the BUILD or PACK has been done. (READ ONLY)

### Example:

```
PROGRAM

MAP
    CheckError(), bool
END

Window WINDOW('Event:BuildDone Example'), AT(, , 209, 76), |
    FONT('MS SansSerif', 8, , FONT:regular, CHARSET:ANSI), |
    CENTER, SYSTEM, GRAY, DOUBLE
    BUTTON('Create file'), AT(3, 5, 57, 22), USE(?Button:CreateFile)
    BUTTON('Build File (With Events)'), AT(71, 7, 84, 22), USE(?Button:Build)
END

MyTPS    FILE, DRIVER('TOPSPEED'), CREATE, RECLAIM, NAME('MyTPS.tps'), PRE(MYT)
PK_IDKey  KEY(MYT:ID), PRIMARY
K_DescKey KEY(MYT:Description), DUP, NOCASE
Record    RECORD
ID         LONG
Description CSTRING(256)
END
END

COUNT    LONG, AUTO
CODE
    OPEN(Window)
    ACCEPT
    CASE EVENT()
    OF Event:Accepted
        CASE FIELD()
        OF ?Button:CreateFile
            ?Button:CreateFile{Prop:Disable} = TRUE
            CREATE(MyTPS)
            IF CheckError()
                POST(Event:CloseWindow)
            CYCLE
        END
```

```
OPEN(MyTPS)
IF CheckError()
    POST(Event:CloseWindow)
    CYCLE
END
STREAM(MyTPS)
LOOP Count = 1 to 100
    CLEAR(MyTPS)
    MYT:ID = Count
    MYT:Description = 'Desc#: ' & Count
    APPEND(MyTPS)
    IF CheckError() THEN BREAK.
END
FLUSH(MyTPS)
IF MESSAGE('Do you want to create a duplicate record?', 'Create duplicate',|
    Icon:Question, Button:Yes + Button:No,Button:Yes) = Button:Yes
    CLEAR(MyTPS)
    MYT:ID = 1
    MYT:Description = 'Desc#: ' & 1
    APPEND(MyTPS)
END
CLOSE(MyTPS)
?Button:CreateFile{Prop:Disable} = FALSE
OF ?Button:Build
?Button:Build{Prop:Disable} = TRUE
MyTPS{Prop:ProgressEvents} = 100
SEND(MyTPS, 'FULLBUILD=on')
BUILD(MyTPS)
IF CheckError() THEN POST(Event:CloseWindow).
END
OF Event:BuildFile OROF Event:BuildKey
OF Event:BuildDone
    IF CheckError()
        MESSAGE('BUILD FAILED !', 'BUILD', Icon:Hand)
    ELSE
        MESSAGE('BUILD OK', 'BUILD', Icon:Asterisk)
    END
    ?Button:Build{Prop:Disable} = FALSE
END
END

!-----
CheckError      FUNCTION()
CODE
IF ERRORCODE()
    MESSAGE(ERROR(), 'CheckError: ' & ERRORCODE(), Icon:Hand)
    RETURN TRUE
END
RETURN FALSE
```

## PROP:Record

Property of a FILE that returns a group reference to the file's record buffer. (READ ONLY)

**Example:**

```
Rec &GROUP
Customer FILE,DIVER('TopSpeed')
Record RECORD
Name STRING(20)
. .
CODE
Rec &= Customer{PROP:Record}
```

## PROP:SQLDriver

A property of a FILE that returns '1' if the file driver accepts SQL, otherwise it returns an empty string ("). (READ ONLY)

**Example:**

```
Customer FILE,DIVER('Clarion'),PRE(CUS)
Record RECORD
Name STRING(20)
. .
SQLFlag BYTE
CODE
IF Customer{PROP:SQLDriver} THEN SQLFlag = TRUE.
```

## PROP:StmtAttr

Property of a FILE that allows you to read or set the ODBC Statement Attribute. This is equivalent to calling the ODBC API functions *SQLSetStmtOption* or *SQLGetStmtOption*. This property is valid on all SQL file types except Oracle.

**Example:**

```
Customer{PROP:StmtAttr,7} = 3 ! Sets concurrency to row version checking
```

## PROP:SupportsOp

Property of a FILE that returns whether the specified function is supported by the file driver. Returns 1 if the operation is supported and 0 if it is not. Valid functions supported by this property are the DriverOp:xxxx found in EQUATES.CLW. (READ ONLY)

## PROP:SupportsType

Property of a FILE that returns whether the specified data type is supported by the file driver. Returns 1 if the data type is supported and 0 if it is not. Valid data types supported by this property are the DataType:xxxx found in EQUATES.CLW. (READ ONLY)

### Example:

```
Customer FILE,DRIVER('Clarion')
Record    RECORD
Id        LONG
.
Supported BYTE
CODE
Supported = Customer{PROP:SupportsType,DriverOp:CREATE} ! Returns 1
Supported = Customer{PROP:SupportsType,DriverOp:NULL}  ! Returns 0
Supported = Customer{PROP:SupportsType,DataType:LONG}  ! Returns 1
Supported = Customer{PROP:SupportsType,DataType:DATE}  ! Returns 0
```

## PROP:Text (MEMO/BLOB Property)

An array property of a FILE that sets or returns the specified MEMO or BLOB field's data. MEMO and BLOB controls are negatively numbered, therefore the array element number must be a negative value. MEMO and BLOB declarations begin with -1 and decrement by 1 for each subsequent MEMO and BLOB, in the order in which they appear within the FILE structure.

### Example:

```
MemoText STRING(2000)
Customer FILE,DRIVER('Clarion'),PRE(CUS)
Notes    MEMO(2000)
Record   RECORD
Name     STRING(20)
.
CODE
OPEN(Customer)
SET(Customer)
NEXT(Customer)
ASSERT(~ERRORCODE())
Memotext = Customer{PROP:Text,-1}
```

## PROP:Value

An array property of a FILE that sets or returns the data contained in a specified MEMO or BLOB column (use the WHAT procedure for any other type of column). The array element for PROP:Value is a simple negative number which indicates the MEMO or BLOB. MEMO and BLOB fields are numbered negatively. MEMO and BLOB declarations begin with -1 and decrement by 1 for each subsequent MEMO and BLOB, in the order in which they appear within the FILE structure.

### Example:

```
Text      STRING(2000)
MoreText  STRING(64000)
Number    LONG
Customer  FILE,DRIER('TopSpeed'),PRE(CUS)
Notes     MEMO(2000)
BigText   BLOB
Record    RECORD
Number     LONG,DIM(20)
Name      STRING(20)
          END
          END

CODE
OPEN(Customer)
SET(Customer)
NEXT(Customer)
ASSERT(~ERRORCODE())
Text = Customer{PROP:Value,-1}      !Get CUS:Notes contents
MoreText = Customer{PROP:Value,-2}  !Get CUS:BigText contents
```

See Also:    **PROP:Memos, PROP:Blobs**

## PROP:Watched

Property of a FILE that returns whether the current record is being WATCHed. Returns 1 if the record is watched and an empty string (") if not. (READ ONLY)

### Example:

```
FileName STRING(256)
Customer FILE,DIRECT('Clarion')
Record RECORD
Name STRING(20)

. .
CODE
OPEN(Customer)
SET(Customer)
LOOP
  WATCH(Customer)
  NEXT(Customer)
  IF ERRORCODE() THEN BREAK.
  IF Customer{PROP:Watched} <> ''
    MESSAGE('Record watched')
  END
END
END
```



## App D - Error Codes

### XML ErrorCodes

At the time of this release, here are possible errors that can be returned by the `GetLastError` function, used when processing XML parsing operations. For more detailed information, refer to the *Clarion XML Support* PDF.

<u>Error Level</u>	<u>Description</u>
0	NoError
1	XMLReadFail
2	XMLWriteFail
3	DuplicateName
4	IllegalName
5	CreateDOMFail
6	EOF (End of File)
7	InvalidArgument
8	IllegalFunctionCall
9	NotSupported
10	InternalError
11	FieldNotFound
12	CommonError
13	IllegalParameter
14	ImportFail
15	NotSuccessful
16	IllegalFormat
17	IllegalType
18	IllegalSize
19	NoSuchField
20	EOS (End of Schema)
21	SchemaNotSupported
22	InconsistentSchema
23	CheckFail
24	AddRecordFailed
25	InvalidNodeName
26	NoCurrentNode
27	CdataNotSupported
28	Base64NotSupported

## Extended ERRORCODE 47 Errors

When an ERRORCODE value of 47 is returned ('Invalid File Declaration'), you can use the FILEERRORCODE statement to check for more information.

FILEERRORCODE returns a string in the following format

```
"obj : index : property : errorcode"
```

*obj* is one of SYSTEM, FILE, FIELD, MEMO/BLOB, KEY, or COMPONENT

*index* the ordinal of the object in the parent (1 based).

*property* the name of the property that is invalid

*errorcode* the format *Snumber* or *Dnumber*

Below is a table of extended error codes, with their corresponding CLAMSG number, default error message, and notes

*Dnumber* indicates a **driver specific** error code

*Snumber* indicates a **general** error code

Below is a table of *Snumber* error codes, with their corresponding CLAMSG number, default error message and notes

Object	ErrorCode	CLAMSG number	Error Message	Notes
SYSTEM	S00001	100000I	Internal Error: Property cannot be set	You should never see this. It indicates a bug in the runtime library.
	S00002	1000002	Dynamic File Support Not Found	You are trying to change the driver of a static file without having the Dynamic File Driver support library present.  This error code is returned by file{PROP:Driver} = 'value'.
FILE	S0000I	110000I	No File Driver Specified	
	S00002	1100002	File Driver could not be loaded	The system could not load the file driver DLL. Probably because it is not on the path
	S00003	1100003	The DLL is not a valid file driver	This normally indicates a corrupt file driver

	S00004	1100004	File Driver not defined	<p>The value specified in file{PROP:Driver} does not match any know driver. If you have a third party file driver you may need to add an entry to the list of drivers stored in the windows registry at</p> <p>"HKEY_LOCAL_MACHINE\Software\SoftVelocity\AnyDriver\C70"</p>
	S00005	1100005	The record structure is greater than 4,194,304 bytes in size	
FIELD	S00001	1200001	Not a Valid Clarion Label	
	S00002	1200002	Duplicate Label	
	S00003	1200003	No Type Specified	
	S00004	1200004	Type requires a size and no size specified	
	S00005	1200005	The Group has more fields than has been defined	You have not defined enough fields in the file to fill the group based on the file{PROP:Fields, n} value set for this group
	S00006	1200006	More Decimal Places than specified size	
	S00007	1200007	Size is too big	
	S00008	1200008	Field Count not specified for a GROUP field	
	S00009	1200009	Field must be over a field defined before the field	
	S00010	1200010	The Group is greater than 4,194,304 bytes in size	
	S00011	1200011	The Field is greater than 4,190,208 bytes in size	

	S000I2	12000I2	Field is larger than the field that it is over
	S000I3	12000I3	Invalid Picture
	S000I4	12000I4	Field cannot be over a field inside another GROUP
KEY	S0000I	130000I	Not a Valid Clarion Label
	S00002	1300002	Duplicate Label
	S00003	1300003	Type set to 'KEY', but no fields specified
	S00004	1300004	Key is defined as PRIMARY and DUP
COMPONENT	S0000I	140000I	Component number is greater than the number of fields in the file structure
	S00002	1400002	Component is a dimensioned field
MEMO/BL OB	S0000I	130000I	Not a Valid Clarion Label
	S00002	1300002	Duplicate Label
	S00003	1500003	No Size Specified for a MEMO

Below is a table of *Dnumber* error codes, with their corresponding CLAMSG number, default error message

<b>Object</b>	<b>ErrorCode</b>	<b>CLAMSG number</b>	<b>Error Message</b>
FILE	D00001	2100001	Component does not match physical file structure
FIELD	D00001	2200001	Component does not match physical file structure
	D00002	2200002	No Name or Label Specified
	D00003	2200003	Data type not supported
	D00004	2200004	Number of dimensions is greater than that supported by the file driver
	D00005	2200005	Field is larger than the maximum supported by the file driver
KEY	D00001	2300001	Component does not match physical file structure
	D00002	2300002	No Name or Label Specified
	D00003	2300003	Too Many Keys defined
COMPONENT	D00001	2400001	Component does not match physical file structure
	D00002	2400002	Driver does not support Descending Key Components
	D00003	2400003	Driver does not support mixed Ascending and Descending Key Components
MEMO/BLOB	D00001	2500001	Component does not match physical file structure
	D00002	2500002	No Name or Label Specified
	D00003	2500003	Too Many Memos defined
	D00004	2500004	Memo is larger than the maximum size supported by the file driver
	D00005	2500005	Driver does not support BLOBs

D00006	2500006	Driver does not support MEMOs
D00007	2500007	Driver does not support BINARY memos or blobs

Below is an error code specific to the ODBC driver, with corresponding CLAMSG number, and default error message.

Object	ErrorCode	CLAMSG number	Error Message
FIELD	D03101	2203101	You are using an unsigned data type with an ODBC 1.0 backend

Below is an error code specific to the Oracle driver, with corresponding CLAMSG number, and default error message.

Object	ErrorCode	CLAMSG number	Error Message
MEMO/BLOB	D03201	253201	BLOB fields are not supported on Oracle v7 or earlier

Below is an error code specific to the TopSpeed driver, with corresponding CLAMSG number, and default error message and notes.

Object	ErrorCode	CLAMSG number	Error Message	Notes
FILE	D00102	2100102	You are attempting to open a newer TopSpeed file format than the driver supports	At present this error code can never occur. This error code may occur in the future if the TopSpeed file format changes and you attempt to open a new format file with the current driver

## Run Time Errors

### Trappable Run Time Errors

The following errors can be trapped in code with the `ERRORCODE` and `ERROR` procedures. Each error has a code number (returned by the `ERRORCODE` procedure) and an associated text message (returned by the `ERROR` procedure) indicating what the problem is.

**2      File Not Found**

The requested file does not exist in the specified directory.

**3      Path Not Found**

The directory name specified as part of the path does not exist.

**4      Too Many Open Files**

The total number of file handles available has been used. Check the `FILES=` setting in the `CONFIG.SYS` file, or the user's or network's simultaneous open files setting in a network environment.

**5      Access Denied**

The file has already been opened by another user for exclusive access, has been left in a locked state, or you do not have network rights to open the file. This error can also occur when no disk space is available.

**7      Memory Corrupted**

Some unknown memory corruption has occurred.

**8      Insufficient Memory**

There is not enough unallocated memory left to perform the operation. Closing other applications may free up enough memory.

**15     Invalid Drive**

An attempt to read a non-existent disk drive has failed.

**27     Invalid Table Declaration**

An attempt to open a table that has an invalid table structure has failed. This is normally found when a Dynamic File has been created incorrectly. Also seen in IP Driver based applications.

**30     Entry Not Found**

A `GET` to `QUEUE` has failed. For `GET(Q,key)`, the matching *key* value was not found, and for `GET(Q,pointer)`, the *pointer* is out of range.

**32 File Is Already Locked**

An attempt to LOCK a file has failed because another user has already locked it.

**33 Record Not Available**

Usually an attempt to read past the end or beginning of file with NEXT or PREVIOUS. May also be posted by PUT or DELETE when no record was read before the attempted PUT or DELETE.

**35 Record Not Found**

For a GET(File,key), the matching *key* field value was not found.

**36 Invalid Data File**

Some unknown data file corruption has occurred, or the OWNER attribute does not match the password used to encrypt the file.

**37 File Not Open**

An attempt to perform some operation that requires the file be already open has failed because the file is not open.

**38 Invalid Key File**

Some unknown key file corruption has occurred.

**40 Creates Duplicate Key**

An attempt to ADD or PUT a record with key field values that duplicate another existing record in the file has been made to a file with a key that does not allow duplicate entries.

**43 Record Is Already Held**

An attempt to HOLD a record has failed because another user has already held it.

**45 Invalid Filename**

The filename does not meet the definition of a valid DOS filename.

**46 Key File Must Be Rebuilt**

Some unknown key corruption has occurred that requires the BUILD statement to rebuild the key.

**47 Invalid Record Declaration**

The data file on disk does not match the file's declaration in the .EXE, usually because you have changed the file's definition in the Data Dictionary and have not yet converted the existing data file to the new format. See How do I handle an Error 47



**48      Unable To Log Transaction**

A transaction logout or pre-image file cannot be written to disk. This usually occurs because no disk space is available, or the user does not have the proper network rights.

**52      File Already Open**

An attempt to OPEN a file that has already been opened by this user.

**54      No Create Attribute**

An attempt to execute the CREATE procedure on a file whose declaration does not include the CREATE attribute.

**55      File Must Be Shared**

An attempt to open a file for exclusive access that must be shared. (Legacy error, no longer used)

**56      LOGOUT Already Active**

An attempt to issue a second LOGOUT statement while a transaction is already in progress.

**57      Invalid Memo File**

Some unknown memo file corruption has occurred. For Clarion data files, this could come from a corrupt .MEM file "signature" or pointers to the memo file in the data file that are "out of sync" (usually due to copying files from one location to another and copying the wrong .MEM file).

**63      Exclusive Access Required**

An attempt to perform a BUILD(file), BUILD(key), EMPTY(file) or PACK(file) was made when the file had not been opened with exclusive access.

**64      Sharing Violation**

An attempt to perform some action on a file which requires that the file be opened for shared access.

**65      Unable To ROLLBACK Transaction**

An attempt to ROLLBACK a transaction has failed for some unknown reason.

**73      Memo File Missing**

An attempt to OPEN a file that has been declared with a MEMO field and the file containing that memo data does not exist.

**75 Invalid Field Type Descriptor**

Either the type descriptor is corrupt, you have used a *name* that does not exist in GET(Q,*name*), or the file definition is not valid for the file driver. For example, trying to define a LONG field in an xBase file without a matching MEMO field.

**76 Invalid Index String**

The index *string* passed to BUILD(DynIndex,*string*) was invalid.

**77 Unable To Access Index**

An attempt to retrieve records using a dynamic index failed because the dynamic index could not be found.

**78 Invalid Number Of Parameters**

You did not pass the correct number of parameters to a procedure called in an EVALUATE statement. Note: As of Clarion Version 6.2 (9047), the SQL Drivers now add more information to the trace log file, explaining why the ERRORCODE 78 was generated.

**79 Unsupported Data Type In File**

The file driver has detected a field in the file declared with a data type that is not supported by the file system the driver is designed to access.

**80 Unsupported File Driver Function**

The file driver has detected a file access statement that is not supported. This is frequently an unsupported form (different parameters) of a statement that is supported.

**81 Unknown Error Posted**

The file driver has detected some error from the backend file system that it cannot get further information about.

**88 Invalid Key Length**

An attempt to CREATE a Clarion file driver KEY or INDEX with more than 245 characters. Other file drivers can also return this error when their file system key length limits are exceeded.

**89 Record Changed By Another Station**

The WATCH statement has detected a record on disk that does not match the original version of the record about to be updated in a network situation.

**90 File Driver Error**

The file driver has detected some other error reported by the file system. You can use the FILEERRORCODE and FILEERROR procedures to determine exactly what native error the file system is reporting.

**91 No Logout Active**

The COMMIT or ROLLBACK statement has been issued outside of a transaction frame (no LOGOUT statement has been executed).

**92 BUILD in Progress**

A BUILD statement has been issued and PROP:ProgressEvents has been set to generate events. The statement generating this error is not appropriate to execute during a BUILD process.

**93 BUILD Cancelled**

The user cancelled the BUILD. This error is set when EVENT:BuildDone is posted.

**94 Record Limit Exceeded**

The target file has exceeded the record limit. This value is file driver dependant, and can be returned during any attempt to modify a file where the record limit is exceeded.

**97 Stream Error**

Used during RTF processing.

**100 Trigger Error**

This error is set whenever a registered file callback method returns FALSE. See CALLBACK

**601 Invalid DDE Channel****602 DDE Channel Not Open****603 DDEEXECUTE Failed****604 DDEPOKE Failed****605 Time Out****1010 Illegal Expression**

The EVALUATE procedure has detected an error in the syntax of the expression it is attempting to evaluate.

**1011      Variable Not Found**

The EVALUATE procedure has not found a variable used in the expression it is attempting to evaluate. You must first BIND all variables used in the expression for them to be visible to EVALUATE.

**1015      Invalid Parameter in Built-In**

The EVALUATE procedure has found a missing or invalid variable in a built-in function that used in the expression it is attempting to evaluate.

## Compiler Errors

The compiler generates an error message at exactly the point in the source code where it determines that something has gone wrong. Therefore, the problem is always either right at that point, or somewhere in the code preceding that point. For most error messages, the problem exists right at the point at which it is detected, but some error messages are typically generated by problems that far precede their detection by the compiler, making some "detective work" necessary, along with an understanding of what the compiler is trying to tell you in the error message itself.

Deciphering compiler error messages to determine exactly what syntax error needs to be corrected can be a bit of an arcane science. The major reason for this is that a single (relatively minor) error can create a "cascade effect;" a long list of error messages that all have one root cause. This is typically the case in the situation where there are a very large number of compiler errors reported in the same source module. To handle this, you should correct just the first error reported then re-compile to see how many errors are left (quite often, none). If you have just a couple of errors reported that are widely separated in the source code, it is likely that each is a discrete error and you should correct them all before re-compiling.

## Specific Errors

The following error messages occur when the compiler has detected a specific syntax problem and is attempting to alert you to exactly what the problem is so that you may correct it.

Some of the following error messages contain a "%V" token. The compiler substitutes an explicit label indicating what problem is occurring for this token when it generates the error message, which should help point to the cause of the error.

### **! introduces a comment**

This is a common C programmer's error. If you type `IF A != 1 THEN` you get this warning.

### **Actual value parameter cannot be array**

The passed parameter must not be an array.

### **ADDRESS parameter ambiguous**

`ADDRESS(MyLabel)` where *MyLabel* is the label of both a procedure and a data item.

### **All fields must be declared before JOINS**

All `PROJECT` statements for the file must precede any `JOIN` statements in the `VIEW` structure.

### **Ambiguous label**

The field qualification syntax has come up with more than one solution for the label you have supplied.

For example:

```
G    GROUP
S:T  SHORT  !Referenced as G:S:T
      END
G:S  GROUP
T    SHORT  !Referenced as G:S:T
      END
CODE
G:S:T = 7    !Which are you talking about?
```

### **Array too big**

Arrays are limited to 64K in 16 bit.

### **Attribute parameter must be QUEUE, QUEUE field or constant string**

The parameter must be the label of a previously declared `QUEUE` structure, a field within a `QUEUE` structure, or a string constant.

### **Attribute requires more parameters**

You must pass all required parameters to an attribute that takes parameters.

### **Attribute string must be constant**

The parameter must be a string constant, not the label of a variable.

### **Attribute variable must be global**

The parameter must be a variable declared in the `PROGRAM` module as global data.

**Attribute variable must have string type**

The parameter must be a variable declared as a STRING, CSTRING, or PSTRING.

**BREAK structure must enclose DETAIL**

There must be at least one DETAIL structure within nested BREAK structures (at the lowest level).

**Calling function as procedure**

A Warning that a PROCEDURE which returns a value and does not have the PROC attribute is being called as a PROCEDURE without a return value would be and the return value will be lost.

**Cannot call procedure as function**

You cannot call a PROCEDURE which does not return a value as the source of an assignment statement or as a parameter.

**Cannot declare KEY in a VIEW**

A KEY declaration is not valid in a VIEW structure.

**Cannot EXIT from here**

Only a ROUTINE may contain the EXIT statement.

**Cannot GOTO into ROUTINE**

The target of GOTO must be the label of an executable code statement within the same procedure or ROUTINE, and may not be the label of a ROUTINE.

**Cannot have default parameter here**

You may only have a default value on non-omittable integer data type parameters passed by value.

**Cannot have initial values with OVER**

A variable declaration with the OVER attribute may not also have an initial value parameter.

**Cannot have statement here**

This happens if the compiler thinks you have tried to define a code label inside the global data section.

**Cannot initialize variable reference**

A reference variable cannot have an initial value.

**Cannot return CSTRING from CLARION function**

CSTRING is not a valid return data type for a PROCEDURE written in Clarion (only for functions written in other languages).

**Cannot RETURN value from procedure**

Only a PROCEDURE prototyped to return a value may contain the RETURN statement with a return value parameter.

### **CLARION function cannot use RAW or NAME**

These attributes are not appropriate for a PROCEDURE written in Clarion (only for functions written in other languages).

### **DECIMAL has too many places**

A DECIMAL or PDECIMAL declaration may only have a maximum of 30 places to the right of the decimal, and the decimal portion must be less than the total length.

### **DECIMAL too long**

A DECIMAL or PDECIMAL declaration may have a maximum length of 31 digits.

### **Declaration not valid in FILE structure**

This data declaration may not be contained within a FILE structure.

### **Declaration too big**

The compiler has detected a PSTRING > 255 or MEMO > 64K in 16 bit, etc.

### **DLL attribute requires EXTERNAL attribute**

The DLL attribute further defines the EXTERNAL attribute and is necessary in 32-bit programs.

### **Dynamic INDEX must be empty**

An attempt to use the 2 parameter form of BUILD on a KEY or INDEX declared with component fields.

### **Embedded OVER must name field in same structure**

The parameter to the OVER attribute must be the label of a previously declared variable in the same structure.

### **ENCRYPT attribute requires OWNER**

The ENCRYPT attribute and OWNER attribute function together.

### **Entity-parameter cannot be an array**

You cannot pass an array of entity parameters (FILE, QUEUE, etc.).

### **Expected: %V**

This is one of the most common errors. The compiler was expecting to find something (one of the items in the list substituted for the %V token) as the next code to compile, but instead found the code at the point in the source that the error is generated.

### **Expression cannot be picture**

You have attempted to use an EQUATE label to a picture token in a place where a picture token is not valid.

### **Expression cannot have conditional type**

An expression is not a numeric value. For example, MyValue = A > B is invalid.

### **Expression must be constant**

Variables are not valid in this expression.



**Field equate label not defined: %V**

The named field equate label has not been previously declared.

**Field not found**

Using field qualification syntax to reference a field that is not in the parent item. For example, referencing MyGroup.SomeField where SomeField is not in the MyGroup declaration.

**Field not found in parent FILE**

A JOIN statement must declare all the linking fields between the parent and child files.

**Field requires (more) subscripts**

This is referencing an array with multiple dimensions, and you must supply an index into each dimension.

**FILE must have DRIVER attribute**

The DRIVER attribute is required to declare the file system for which the data file is formatted.

**FILE must have RECORD structure**

It is invalid to declare a FILE which does not contain a RECORD structure.

**FILES must have same DRIVER attribute**

All files named in a LOGOUT statement must use the same file system.

**Function did not return a result**

A warning that the implementation of the PROCEDURE prototyped to return a value did not return a result.

**Function result is not of correct type**

The RETURN statement must return a value consistent with the return data type prototyped in the MAP structure.

**Group too big**

GROUPs are limited to 64K in 16 bit.

**Ignoring EQUATE redefinition: %V**

A Warning that the named equate is being ignored. This is really a label-redefined error except that the definition is not thrown away.

**Illegal array assignment**

An assignment to an array must reference a single element, not the entire array.

**Illegal character**

A non-valid lexical token. For example, an ASCII 255 in your source.

**Illegal data type: %V**

The named data type is inappropriate for the structure in which it is placed.

### **Illegal key component**

A KEY has any type of illegal component.

### **Illegal nesting of window controls**

Window controls other than RADIO have been placed within an OPTION structure, or controls other than TAB have been placed directly within a SHEET structure.

### **Illegal parameter for LIKE**

An illegal parameter to a LIKE declaration. For example, LIKE(7).

### **Illegal parameter type for STRING**

An illegal parameter to a STRING declaration. For example, STRING(MyVar) where MyVar is the label of a variable and not an EQUATE.

### **Illegal reference assignment**

A reference variable may only be assigned another reference variable of the same type, or the label of a variable of the type it references.

### **Illegal return type or attribute**

The prototype contains an invalid data type as the return data type (such as \*CSTRING).

### **Illegal target for DO**

The target of DO must be the label of a ROUTINE.

### **Illegal target for GOTO**

The target of GOTO must be the label of an executable code statement within the same procedure or ROUTINE, and may not be the label of a ROUTINE.

### **INCLUDE invalid, expected: %V**

The INCLUDE statement's parameter must be a well formed Clarion string. In particular, type conversion is not valid, so INCLUDE('MyFile'&MyValue) is invalid.

### **INCLUDE misplaced**

INCLUDE has to follow a line-break, or a semi-colon (possibly followed by white space).

### **INCLUDE nested too deep**

You can only nest INCLUDEs 3 deep. In other words you can INCLUDE a file that INCLUDEs a file that INCLUDEs a file, but the last file must not INCLUDE anything.

### **Incompatible assignment types**

An attempt to assign between incompatible data types.

### **Incorrect procedure profile**

An attempt to pass a procedure with the wrong prototype as a procedure-parameter.

### **Indices must be constant**

An attempt has been made to have a USE variable that is an array element with variable indices.

**Indistinguishable new prototype: %V**

A prototype that the compiler cannot uniquely distinguish from a previous prototype using the rules for procedure overloading .

**Integer expression expected**

The expression must evaluate to an integer.

**Invalid BREAK statement**

A BREAK that attempts to break to a non-LOOP label or is outside a LOOP or ACCEPT structure.

**Invalid CYCLE statement**

A CYCLE that attempts to cycle to a non-LOOP label or is outside a LOOP or ACCEPT structure.

**Invalid data declaration attribute**

An attribute that is inappropriate on the data declaration.

**Invalid data type for value parameter**

The data type prototyped in the MAP may not be passed by value and must be passed by address. For example, to pass a CSTRING parameter to a Clarion procedure, it may only be prototyped as \*CSTRING.

**Invalid FILE attribute**

An attribute that is inappropriate on a FILE declaration.

**Invalid first parameter of ADD**

The statement's first parameter is not appropriate.

**Invalid first parameter of FREE**

The statement's first parameter is not appropriate.

**Invalid first parameter of NEXT**

The statement's first parameter is not appropriate.

**Invalid first parameter of PUT**

The statement's first parameter is not appropriate.

**Invalid GROUP/QUEUE/RECORD attribute**

An attribute that is inappropriate on a GROUP, QUEUE, or RECORD declaration.

**Invalid KEY/INDEX attribute**

An attribute that is inappropriate on a KEY or INDEX declaration.

**Invalid label**

A label that contains characters other than letters, numbers, underscore (`_`), or colon (`:`), or does not start with a letter or underscore.

**Invalid LOOP variable**

An attempt to use an illegal data type (DATE, TIME, STRING, etc.) as a LOOP variable.

### **Invalid MEMBER statement**

The parameter to the MEMBER statement is not a string constant or does not reference the PROGRAM module for the current project.

### **Invalid method invocation syntax**

An attempt to use the {} syntax for method invocation on a BLOB or FILE.

### **Invalid number**

A number is required, for example inside the repeat character notation ({} ) in a string constant.

### **Invalid OMIT expression**

The parameter to the OMIT statement is invalid.

### **Invalid parameters for attribute**

You must pass valid parameters to an attribute that takes them.

### **Invalid picture token**

A picture token that contains inappropriate characters.

### **Invalid printer control token**

A PRINT statement containing a printer control token.

### **Invalid QUEUE/RECORD attribute**

An attribute that is inappropriate on a QUEUE or RECORD declaration.

### **Invalid SIZE parameter**

SIZE(Junk+SomeMoreJunk)

### **Invalid string (misused <...> or {...} )**

A string constant contains a single beginning bracket (< or {) without a matching terminating bracket (> or }). These characters must have two together (<< or {{) if intended to be part of the string.

### **Invalid structure as first parameter**

The statement's first parameter is not appropriate.

### **Invalid structure within property syntax**

A structure that is inappropriate in a property assignment statement.

### **Invalid USE attribute parameter**

The parameter is not appropriate for a USE attribute.

### **Invalid use of PRIVATE data**

Attempt to access a PRIVATE data member outside the CLASS module.

### **Invalid use of PRIVATE procedure**

Attempt to call a PRIVATE method outside the CLASS module.

**Invalid variable data parameter type**

When passing parameters by address, you must pass the same data type as prototyped in the MAP structure.

**Invalid WINDOW control**

A control that is inappropriate in a WINDOW structure.

**ISL error: %V**

Contact Technical Support and provide all details of the error message.

**KEY must have components**

You cannot declare a KEY without naming the component fields that establish the KEY's sort order.

**Label duplicated, second used: %V**

The named field equate label is used multiple times within the same module and only the last encountered is used in the list of equate labels that may be used within the executable code. Correctable with the third parameter to the USE attribute.

**Label in prototype not defined: %V**

Using a prototype where one of the data types has not yet been defined.

**Label not defined: %V**

The named label has not been previously declared.

**Mis-placed string slice operator**

A string slice that is not the last array index. For example, MyStringArray[3:4,5].

**Missing procedure definition: %V**

The named procedure is not prototyped in a MAP structure.

**Missing virtual function**

Compiler bug.

**Must be dimensioned variable**

This must be an array.

**Must be field of a FILE or VIEW**

Must be a field that is a member of a FILE or VIEW structure. For example NULL(LocalVariable) with give this error.

**Must be FILE or KEY**

The parameter to JOIN is not a FILE or KEY label.

**Must be reference variable**

You can only DISPOSE of a reference variable.

**Must be variable**

This must be the label of a previously declared variable.

**Must have constant string parameter**

The parameter must be a string constant, not the label of a variable.

**Must RETURN value from function**

A PROCEDURE prototyped to return a value must contain the RETURN statement with a return value parameter.

**Must specify DECIMAL size**

A DECIMAL or PDECIMAL declaration must declare the maximum number of digits it stores.

**Must specify identifier**

An identifier was required but not supplied.

**Must specify print-structure**

A PRINT statement may only print a structure in a REPORT.

**No matching prototype available**

Attempt to define a procedure for which there is no matching prototype in a MAP or CLASS.

**Not valid inside structure**

A data type is inappropriate for the structure in which it is placed.

**OMIT cannot be nested**

You are in an OMIT (or COMPILE) that is *not* omitting code and the compiler encounters another OMIT.

**OMIT misplaced**

OMIT has to follow a line-break, or a semi-colon (possibly followed by white space).

**OMIT not terminated: %V**

The referenced OMIT parameter was not found before the end of the source module.

**Order is MENUBAR, TOOLBAR, Controls**

The MENUBAR structure must come before the TOOLBAR, and the TOOLBAR structure must come before the controls in a WINDOW or APPLICATION.

**OVER must name variable**

The parameter to the OVER attribute must be the label of a previously declared variable.

**OVER must not be larger than target variable**

The parameter to the OVER attribute must be the label of a previously declared variable that is greater than or equal to the size of the variable being declared OVER it.

**OVER not allowed with STATIC or THREAD**

A variable declaration with the OVER attribute may not also have the STATIC or THREAD attribute (these must be on the initial declaration).

**Parameter cannot be omitted**

The procedure call must pass all parameters that have not been prototyped as omissible parameters.

**Parameter kind does not match**

When passing parameters by address, you must pass the same data type as prototyped in the MAP structure.

**Parameter must be picture**

This must be a display picture token.

**Parameter must be procedure label**

This must be the label of a procedure.

**Parameter must be report DETAIL label**

A PRINT statement may only print a DETAIL structure in a REPORT.

**Parameters must have labels**

Attempt to define a procedure without using labels on parameters.

**Parameter type label ambiguous (CODE or DATA)**

You may have a PROCEDURE and data declaration with the same name, but then you cannot use that name in a procedure prototype.

**PROCEDURE cannot have return type**

If you declare a prototype without a return data type in the MAP, you must create it as a PROCEDURE.

**Procedure doesn't belong to module: %V**

An attempt to define a procedure that has a prototype that says it belongs in another module.

**Procedure in parent CLASS has VIRTUAL mismatch**

Virtual methods require the VIRTUAL attribute on the prototypes in both the parent and derived CLASSES.

**Prototype is: %V**

Attempt to define a procedure with the wrong prototype.

**QUEUE/RECORD not valid in GROUP**

A GROUP structure may not contain a QUEUE or RECORD structure.

**Redefining system intrinsic: %V**

A Warning that the named procedure (part of your source code) has the same name as a Clarion run time library procedure and that your procedure will be called instead of the built-in library's.

**Routine label duplicated**

The label of a ROUTINE statement has been previously used on another statement.

**Routine not defined: %V**

The named ROUTINE does not exist.

**SECTION duplicated: %V**

The named SECTION exists twice in the INCLUDE file.

**SECTION not found: %V**

The named SECTION does not exist in the INCLUDE file.

**Statement label duplicated**

Two lines of executable source code have the same label.

**Statement must have label**

The statement (such as a ROUTINE or PROCEDURE statement) must have a label.

**String not terminated**

A string constant without a terminating single quote (').

**Subscript out of range**

An attempt to reference an array element beyond the valid number of elements dimensioned in the data declaration.

**Too few indices**

This is referencing an array with multiple dimensions, and you must supply an index into each dimension.

**Too few parameters**

The procedure call must pass all parameters that have not been prototyped as omissible parameters.

**Too many indices**

This is referencing an array and you are supplying too many indexes into the dimensions.

**Too many parameters**

The procedure call may not pass more parameters than have been prototyped.

**Unable to verify validity of OVER attribute**

A Warning that you are declaring a variable OVER a passed parameter and the data types may not match at run time.

**Unknown attribute: %V**

The named attribute is not part of the Clarion language.

**Unknown function label**

The PROCEDURE has not been previously prototyped in a MAP structure.



**Unknown identifier**

The label has not been previously declared.

**Unknown identifier: %V**

The named identifier has not been previously declared.

**Unknown key component: %V**

The named key component does not exist within the FILE structure.

**Unknown procedure label**

The PROCEDURE has not been previously prototyped in a MAP structure.

**UNTIL/WHILE illegal here**

Attempt to use UNTIL or WHILE to terminate a LOOP structure that is already terminated.

**Value-parameter cannot be an array**

You cannot pass an array as a value-parameter.

**Value requires (more) subscripts**

This is referencing an array with multiple dimensions, and you must supply an index into each dimension.

**Variable expected**                      This must be the label of a previously declared variable.

**Variable-size must be constant**

The variable declaration must contain a constant expression for its size parameter.

**VIRTUAL illegal outside of CLASS structure**

You can only use the VIRTUAL attribute on prototypes in a CLASS structure, not in a MAP.

**Wrong number of parameters**

The procedure call must pass all parameters that have not been prototyped as omissible parameters.

**Wrong number of subscripts**

An attempt to access a multi-dimensioned array without providing an element number for each dimension.

For example:

```
MyShort SHORT,DIM(8,2)  !Two-dimensional array
CODE
MyValue = MyShort[7]    !Wrong number of subscripts error
```

## Unknown errors

These are errors that should never happen and are only to give the compiler writer a clue as to what is wrong. Report the problem immediately to SoftVelocity together with the source file that generated the error.

- Inconsistent scanner initialization
- Unknown operator
- Unknown expression type
- Unknown expression kind
- Unknown variable context
- Unknown parameter kind
- Unknown assignment operator
- Unknown variable type
- Unknown case type
- Unknown equate type
- Unknown string kind
- Unknown picture type
- Unknown descriptor type
- Unknown initializer type
- Unknown designator kind
- Unknown structure field
- Unknown formal entity
- Type descriptor not static
- Unknown clear type
- Unknown simple formal type
- Out of attribute space
- Unknown label/routine
- Unknown special identifier
- Value not static
- Unknown static label
- Unknown screen structure kind
- Corrupt pragma string
- Old symbol non-NIL
- Not implemented yet
- String not CCST

## App E - Legacy Statements

### BOF (return beginning of file)     {bmc C6H0007.BMP}

**BOF**(*file*)

**BOF**                      Flags the beginning of the FILE during sequential processing.

*file*                      The label of a FILE declaration.

The **BOF** procedure returns a non-zero value (true) when the first record in relative file sequence has been read by PREVIOUS or passed by SKIP. Otherwise, the return value is zero (false).

The BOF procedure is not supported by all file drivers, and can be very inefficient even if supported (check the driver documentation). Therefore, for efficiency and guaranteed file system support it is not recommended to use this procedure. Instead, check the ERRORCODE() procedure after each disk read to detect an attempt to read past the beginning of the file.

The BOF procedure was most often used as an UNTIL condition evaluated at the top of a LOOP, so BOF returns true after the last record has been read and processed in reverse order (using PREVIOUS).

**Return Data Type:**    LONG

#### Example:

*!Not recommended, but still supported for backward compatibility:*

```
SET(Trn:DateKey)           !End/Beginning of file in keyed sequence
LOOP UNTIL BOF(Trans)      !Process file backwards
  PREVIOUS(Trans)          ! read a record sequentially
  IF ERRORCODE() THEN STOP(ERROR()).
  DO LastInFirstOut        ! call last in first out routine
END
```

*!Recommended as most efficient code for use with all file drivers:*

```
SET(Trn:DateKey)           !End/Beginning of file in keyed sequence
LOOP                       !Process file backwards
  PREVIOUS(Trans)          ! read a record sequentially
  IF ERRORCODE() THEN BREAK. !Break loop at attempt to read past beginning
  DO LastInFirstOut        ! call last in first out routine
END
```

#### See Also:

ERRORCODE

## EOF (return end of file)

**EOF**(*file*)

---

**EOF**                Flags the end of the FILE during sequential processing.

*file*                The label of a FILE declaration.

The **EOF** procedure returns a non-zero value (true) when the last record in relative file sequence has been read by NEXT or passed by SKIP. Otherwise, the return value is zero (false).

The EOF procedure is not supported by all file drivers, and can be very inefficient even if supported (check the driver documentation). Therefore, for efficiency and guaranteed file system support it is not recommended to use this procedure. Instead, check the ERRORCODE() procedure after each disk read to detect an attempt to read past the end of the file.

The EOF procedure was most often used as an UNTIL condition at the top of a LOOP, so EOF returns true after the last record has been read and processed.

**Return Data Type:**    LONG

**Example:**

```
!Not recommended, and still available for backward compatibility:
SET(Trn:DateKey)                !Beginning of file in keyed sequence
LOOP UNTIL EOF(Trans)            !Process all records
  NEXT(Trans)                    ! read a record sequentially
  IF ERRORCODE() THEN STOP(ERROR()).
  DO LastInFirstOut              ! call last in first out routine
END
```

```
!Recommended for use with all file drivers:
SET(Trn:DateKey)                !Beginning of file in keyed sequence
LOOP                              !Process all records
  NEXT(Trans)                    ! read a record sequentially
  IF ERRORCODE() THEN BREAK.    !Break loop on attempt to read past end of file
  DO LastInFirstOut              ! call last in first out routine
END
```

**See Also:**

ERRORCODE

## FUNCTION (define a function)

*label*    **FUNCTION** [(*parameter list*)]

*local data*

**CODE**

*statements*

**RETURN**(*value*)

**FUNCTION** is a statement which once defined a PROCEDURE prototyped to return a value (referred to as a function in some other programming languages). The FUNCTION keyword has been replaced by the PROCEDURE statement and is now a synonym for PROCEDURE in all cases.

### Example:

```

PROGRAM
MAP
FullName FUNCTION (STRING Last, STRING First, <STRING Init>), STRING
                                     !Function prototype with parameters
DayString FUNCTION, STRING          !Function prototype without parameters
END
TodayString STRING(3)
CODE
TodayString = DayString()           !Function call without parameters
                                     ! the () is required for a function

FullName FUNCTION (STRING Last, STRING First, STRING Init)      !Full name function
CODE                                                            !Begin executable code section
IF OMITTED(3) OR Init =                                         !If no middle initial
    RETURN(CLIP(First) &    & Last)    ! return full name
ELSE                                                            !Otherwise
    RETURN(CLIP(First) &    & Init & . & Last)    ! return full name
END

DayString FUNCTION                                     !Day string function
ReturnString STRING(9), AUTO                                  !Uninitialized local stack variable
CODE                                                        !Begin executable code section
RETURN (CHOOSE (TODAY () %7) +1, Sun, Mon, Tue, Wed, Thu, Fri, Sat))

```

### See Also:

PROCEDURE

## POINTER (return relative record position)

```
POINTER ( | file | )  
        | key |
```

---

**POINTER** Returns relative record position.

*file* The label of a FILE declaration. This specifies physical record order within the file.

*key* The label of a KEY or INDEX declaration. This specifies the entry order within the KEY or INDEX file.

**POINTER** returns the relative record position within the data file (in *file* sequence), or the relative record position within the KEY or INDEX file (in *key* sequence) of the last record accessed.

The value returned by the **POINTER** procedure is dependent on the file driver. It may be a record number, the relative byte position within the file, or some other kind of seek position within the file.

The **POINTER** procedure is not supported by all file drivers. Therefore it should be used only when you know the file system supports it and you will not be changing file systems in the future. The preferred method of record positioning that is designed to work across all file systems is the **POSITION** procedure with **RESET** and **REGET**.

**Return Data Type:** LONG

**Example:**

```
SavePtr# = POINTER(Customer)    !Save file pointer
```

**See Also:**

**POSITION**

## SHARE (open data file for shared access)

**SHARE**(*file* [,*access mode*])

**SHARE** Opens a FILE structure for processing.

*file* The label of a FILE declaration.

*access mode* A numeric constant, variable, or expression which determines the level of access granted to both the user opening the file, and other users in a multi-user system. If omitted, the default value is 42h (Read/Write, Deny None).

The **SHARE** statement opens a FILE structure for processing and sets the *access mode*. The SHARE statement is exactly the same as the OPEN statement, with the exception of the default value of *access mode*.

The *access mode* is a bitmap which tells the operating system what access to grant the user opening the file and what access to deny to others using the file.

The actual values for each access level are:

	<u>Dec.</u>	<u>Hex.</u>	<u>Access</u>
User Access:	0	0h	Read Only
	1	1h	Write Only
	2	2h	Read/Write
Others Access:	0	0h	Any Access (FCB compatibility mode)
	16	10h	Deny All
	32	20h	Deny Write
	48	30h	Deny Read
	64	40h	Deny None

**Errors Posted:** The same set of errors that may be posted by OPEN

**Example:**

```

ReadOnly    EQUATE (0)                !Access mode equates
WriteOnly   EQUATE (1)
ReadWrite   EQUATE (2)
DenyAll     EQUATE (10h)
DenyWrite   EQUATE (20h)
DenyRead    EQUATE (30h)
DenyNone    EQUATE (40h)
CODE
  SHARE (Master,ReadOnly+DenyWrite)    !Open read only mode

```

**See Also:**

OPEN





# Index

! Comments .....	13	ACCEPTED (return control just completed) .....	548
# added after a label .....	119	Access Mode .....	731
\$ - dollar sign syntax .....	500	ACOS .....	549
\$ added after a label .....	119	ACOS (return arccosine) .....	549
* .....	36	ACTIVE .....	936
* parameter .....	13	ADD .....	550
. - Period .....	13	ADD (add an entry) .....	550
.DLL .....	206	Addition operator .....	492
.ENV .....	175, 703	ADDRESS .....	554
.INI .....	668, 769	ADDRESS (return memory address) .....	554
GETINI .....	668	AGE .....	555
PUTINI .....	769	AGE (return age from base date) .....	555
.OCX Control Properties .....	895	Alarm (BEEP) .....	566
:=		ALERT .....	556
Deep Assignment .....	515	ALERT (set event generation key) .....	556
? - Used in Procedure Parameters .....	36	AlertKey .....	918
? (field equate labels) .....	13, 256	Algebraic Order of Operation .....	491
? debug .....	13	ALIAS .....	558
@ token .....	13	ALIAS (set alternate keycode) .....	558
@@ .....	13	ALL .....	559
line continuation .....	13	ALL (return repeated characters) .....	559
~ file .....	13	allocate heap memory .....	126
755 Error .....	1037	Allocation .....	123
ABCDIIMode .....	201	memory	
ABOVE .....	424	Dynamic .....	123
ABS .....	547	Static .....	123
ABS (return absolute value) .....	547	ALLTRIM .....	593
ABSOLUTE .....	352	ALONE .....	353
ABSOLUTE (set fixed-position printing) .....	352	ALONE - print without page header or form .....	353
ACCEPT .....	529	Alphanumeric .....	98, 103, 105
ACCEPT (the event processor) .....	529	CSTRING .....	103
AcceptAll .....	935	PSTRING .....	105
AcceptAll mode .....	794	STRING .....	98
Accepted .....	926	ALRT .....	354
ACCEPTED .....	548		

ALRT (set window.....)	354	ASK.....	562
AlwaysDrop.....	936	ASK (get one keystroke).....	562
AND.....	494	ASSERT.....	61
ANGLE.....	356	ASSERT (set assumption for debugging). 61	
ANGLE (set control display or print angle) .....	356	AssertHook.....	937
ANSITOOEM.....	604	AssertHook2.....	937
ANY.....	114	Assignment Statements.....	517
ANY (any simple data type).....	114	CLEAR.....	519, 592
APPEND.....	560	Deep.....	515
APPEND (add a new file record).....	560	Operating.....	514
AppInstance.....	936	Reference.....	517
APPLICATION.....	237	Simple.....	513
APPLICATION (declare an MDI frame window).....	237	ASTRING.....	100
Application modal.....	242	ASTRING (atomic string).....	100
Application Modal Windows.....	433, 435	AT.....	357
Application windows.....	254	AT (set position and size).....	357
ARC.....	561	ATAN.....	564
ARC (draw an arc of an ellipse).....	561	ATAN (arctangent).....	564
Arithmetic Operators.....	492, 497	ATAN (return arctangent).....	564
Addition.....	492	Attribute Equates.....	349
Division.....	492	Attribute Property Equates.....	349
Exponentiation.....	492	AUTO.....	195, 360
Modulus.....	492	AUTO - variable attribute.....	195
Multiplication.....	492	AUTO (set USE variable automatic re- display).....	360
Subtraction.....	492	automatic constructor.....	146
Arithmetic overflow.....	132, 520	Automatic Conversion of Data Types.....	520
Array.....	199	automatic destructor.....	146
DIM.....	199	AutoPaper.....	938
subscript.....	491, 503	AUTOSIZE.....	361
array elements.....	256	AUTOSIZE (set OLE object resizing).....	361
field equate labels.....	256	AVE.....	362
arrays - variable size.....	125	AVE (set report total average).....	362
ASCII Character Codes.....	496	B (blank when zero).....	132
ASIN.....	563	BackColor - PROPLIST.....	403
ASIN (arcsine).....	563	BackColor - PROPSTYLE.....	401
ASIN (return arcsine).....	563	Background.....	371

background color .....	371	BIND (declare runtime expression string variable) .....	504
BackSelected - PROPLIST .....	403	BINDABLE .....	197
BackSelected - PROPSTYLE .....	401	BINDABLE (set runtime expression string variables) .....	197
BAND .....	565	BINDEXPRESSION .....	506
BAND (Bitwise AND) .....	565	Bit manipulation	
BAND (return bitwise AND) .....	565	BXOR .....	574
BarFrame - PROPLIST .....	403	Bit Manipulation .....	565, 568, 570
BarFrame - PROPSTYLE .....	401	bitmap images in memo fields .....	962
Base 10 logarithm .....	706	BLANK .....	567
Base Data Types .....	521	BLANK (erase graphics) .....	567
Base numbers .....	495	Blank when zero .....	132
Binary .....	495	BLOB .....	163
Decimal .....	495	BLOB (declare a variable-length field) ....	163
Hexadecimal .....	495	BLOB Properties .....	1028, 1029
Octal .....	495	BOF .....	1057
Base Types .....	521	BOF (return beginning of file) .....	1057
BCD .....	522	Boolean operators .....	494
BCD Conversion .....	522	BOR .....	568
BCD Operations and Procedures .....	522	BOR (Bitwise OR) .....	568
BEEP .....	566	BOR (return bitwise OR) .....	568
BEEP (sound tone on speaker) .....	566	BOX .....	277, 569
BEGIN .....	62, 533	BOX (declare a box control) .....	277
BEGIN (define code structure) .....	62	BOX (draw a rectangle) .....	569
BELOW .....	424	BOXED .....	364
BEVEL .....	363	BOXED (set controls group border) .....	364
BEVEL (set 3-D effect border) .....	363	BREAK .....	265, 539
BFLOAT4 .....	90	BREAK (declare group break structure) .	265
BFLOAT4 (four-byte signed floating point)	90	BREAK (immediately leave loop) .....	539
BFLOAT8 .....	92	BreakVar .....	938
BFLOAT8 (eight-byte signed floating point)	92	BSHIFT .....	570
Binary .....	495	BSHIFT (Bitwise SHIFT) .....	570
Numeric constant .....	495	BSHIFT (return shifted bits) .....	570
BINARY .....	196	Btrieve .....	103, 105
BINARY (memo contains binary data) ....	196	DATE .....	109
Binary Coded Decimal (BCD) .....	522	LSTRING .....	105
BIND .....	504	TIME .....	111

ZSTRING .....	103	CENTERED .....	367
BUFFER .....	570, 939	CENTERED (set centered image) .....	367
BUFFER (set record paging) .....	570	CHAIN .....	584
BUILD .....	571	CHAIN (execute another program) .....	584
BUILD (build keys and indexes) .....	571	CHANGE .....	585
BuildDone .....	918	CHANGE (change control field value) ....	585
BuildKey .....	918	CHANGES .....	586
Built-in variables		CHANGES (return changed queue) .....	586
PRINTER .....	760	Chapter Organization .....	1
TARGET .....	820	Character String .....	98, 103, 105
Built-in Variables .....	500	CSTRING .....	103
BUTTON .....	279	PSTRING .....	105
BUTTON (declare a pushbutton control) ..	279	STRING .....	98
BXOR (Bitwise eXclusive OR) .....	574	CharSet .....	940
BXOR (return bitwise exclusive OR) .....	574	CharSet - PROPSTYLE .....	401
BY .....	537	CHECK .....	282, 368
BYTE .....	75	CHECK (declare a checkbox control) ....	282
BYTE (one-byte unsigned integer) .....	75	CHECK (set on/off ITEM) .....	368
BYTES .....	575	Checked .....	941
BYTES (return size in bytes) .....	575	Child .....	941
C .....	46	ChildIndex .....	941
CALL .....	577	CHOICE .....	587
CALL (call procedure from a DLL) .....	577	CHOICE (return relative item position) ...	587
Callback .....	897	ChoiceFEQ .....	943
CALLBACK .....	578	CHOOSE .....	588
CALLBACK - register or unregister a FileCallBackInterface .....	578	CHOOSE (return chosen value) .....	588
CAP .....	365	CHORD .....	590
UPR (set case) .....	365	CHORD (draw a section of an ellipse) ....	590
CASE .....	531	CHR .....	591
CASE (selective execution structure) .....	531	CHR (return character from ASCII) .....	591
Case insensitive key .....	220	CLAAMP .....	175
Case insensitive report break .....	438	CLABUTTON .....	175
Casting .....	120	CLACASE .....	175
CENTER .....	366, 425, 583	CLACHARSET .....	175
CENTER (return centered string) .....	583	CLACOLSEQ .....	175
CENTER (set centered window position) ..	366	CLADIGRAPH .....	175
		CLAMON .....	175

CLAMONTH.....	175	CNT (set total count).....	370
CLAMSG.....	175	CODE.....	26
Clarion Keycodes.....	6	CODE (begin executable statements) .....	26
Clarion standard date .....	4	collating sequence .....	160, 161, 826
Clarion standard time .....	5	INDEX .....	160
CLASS .....	146	KEY .....	161
LINK.....	217	SORT (QUEUE).....	826
MODULE .....	218	COLOR .....	371
CLASS (object declaration) .....	146	COLOR (set color) .....	371
CLASS Variables .....	229, 230	COLORIALOG.....	600
PRIVATE .....	229	COLORIALOG (return chosen color) ...	600
PROTECTED.....	230	ColorDialogHook.....	948
CLEAR.....	519, 592	colorized list box fields .....	393
CLEAR (clear a variable).....	519, 592	colors in list boxes.....	306
clear the reference .....	517	Column.....	373
NULL.....	517	COLUMN (set list box highlight bar) .....	373
ClientHandle .....	944	ColumnResize.....	926
ClientHeight .....	945	COMBO .....	285
ClientWidth .....	945	COMBO (declare an entry/list control)....	285
ClientWndProc.....	945	COMMAND .....	601
CLIP.....	369, 593	COMMAND (return command line).....	601
CLIP (return string without trailing spaces) .....	593	Command line.....	601, 804
CLIP (set OLE object clipping) .....	369	COMMAND .....	601
ClipBits.....	947	SETCOMMAND .....	804
CLIPBOARD .....	594	Comments ! symbol .....	13
CLIPBOARD (return windows clipboard contents) .....	594	COMMIT .....	602
CLOCK .....	595	COMMIT (terminate successful transaction) .....	602
CLOCK (return system time) .....	595	Commit boundaries.....	708
CLONE .....	596	Comparison Operators .....	494
CLONE(duplicate existing control) .....	596	COMPATIBILITY.....	374
CLOSE.....	598	COMPATIBILITY (set OLE control compatibility) .....	374
CLOSE (close a data structure).....	598	Compatible_Modulus .....	492
CloseReportHook .....	947	COMPILE.....	63
CloseWindow .....	919	COMPILE (specify source to compile).....	63
CloseWindowHook .....	947	Compiler Directives.....	60
CNT .....	370	Compiler Error Messages .....	1043

Compiler Errors.....	1043	COPY .....	606
Completed .....	919, 1013	COPY (copy a file) .....	606
Concatenation.....	497	Corrupt pragma string .....	1056
Concatenation Operator .....	493	COS .....	607
concurrency checking language statements .....	862	COS (cosine of angle) .....	607
Conditional Operators.....	494	CREATE .....	198, 375, 608, 609
ConnectionString .....	1013	CREATE (allow data file creation) .....	198
CONST .....	36	CREATE (create an empty data file) .....	608
Constants.....	495	CREATE (create OLE control object) .....	375
Numeric Constants .....	495	CREATE (return new control created)....	609
String Constant.....	496	Credit (CR) pictures .....	132
constructor .....	146	credit pictures.....	132
container control .....	314	CSTRING.....	103
container windows .....	886	CSTRING (fixed-length null terminated string) .....	103
CONTENTS .....	603	Currency Pictures .....	132
CONTENTS (return contents of USE variable) .....	603	Current Target.....	259
Contracted .....	926	CurrentKey.....	1013
Contracting .....	927	CURSOR .....	376
Control Fields.....	255	CURSOR (set mouse cursor type) .....	376
Control menu .....	469	CustomColor property.....	948
Control Numbering.....	256	CYCLE .....	540
Control Structures.....	531	CYCLE (go to top of loop).....	540
Conventions and Symbols.....	3	DATA .....	27
Conversion.....	614	DATA (begin routine local data section) ...	27
date		Data Declaration Sections .....	124
DEFORMAT .....	614	Data Type Conversion .....	522
Conversion of Data Types .....	520	Data Type Conversion Rules.....	520
convert ANSI strings to ASCII .....	604	Data Types.....	86, 88, 90, 92, 98, 103, 105
convert ASCII strings to ANSI .....	605	ANY .....	114
CONVERTANSITOOEM .....	604	BFLOAT4 .....	90
CONVERTANSITOOEM (convert ANSI strings to ASCII).....	604	BFLOAT8 .....	92
CONVERTOEMTOANSI .....	605	BYTE.....	75
CONVERTOEMTOANSI (convert ASCII strings to ANSI).....	605	CSTRING.....	103
Cooperative multi-tasking .....	866	DATE .....	109
		DECIMAL .....	94
		GROUP .....	143

LIKE .....	117	DDECLOSE .....	873
LONG .....	80	DDECLOSE (terminate DDE server link) .....	873
PDECIMAL .....	96	DDEclosed .....	920
PSTRING .....	105	DDEdata .....	920
REAL .....	88	DDEexecute .....	920
SHORT .....	76	DDEEXECUTE .....	874
SIGNED .....	84	DDEEXECUTE (send command to DDE server) .....	874
SREAL .....	86	DDEITEM .....	875
STRING .....	98	DDEITEM (return server item) .....	875
TIME .....	111	DDEMode .....	949
ULONG .....	82	DDEpoke .....	920
UNSIGNED .....	85	DDEPOKE .....	876
USHORT .....	78	DDEPOKE (send unsolicited data to DDE server) .....	876
Date		DDEQUERY .....	878
Standard Date .....	4	DDEQUERY (return registered DDE servers) .....	878
DATE .....	109, 612	DDERead .....	879
DATE (four-byte date) .....	109	DDERead (get data from DDE server) ..	879
DATE (return standard date) .....	612	DDErequest .....	920
Date conversion .....	614	DDESERVER .....	881
DEFORMAT .....	614	DDESERVER (return DDE server channel) .....	881
Date Pictures .....	136	DDETimeOut .....	949
DAY .....	613	DDETOPIC .....	882
DAY (return day of month) .....	613	DDETOPIC (return server topic) .....	882
Day of the week .....	4	DDEVALUE .....	883
DDE .....	867, 920	DDEVALUE (return data value sent to server) .....	883
DDE Events .....	868, 920	DDEWRITE .....	884
DDE Overview .....	867	DDEWRITE (provide data to DDE client) ..	884
DDEACKNOWLEDGE .....	869	de-allocate heap memory .....	129
DDEACKNOWLEDGE (send acknowledgement from DDE server) .....	869	Debit (DB) pictures .....	132
DDEadvise .....	920	debit pictures .....	132
DDEAPP .....	870	Debug ? symbol .....	13
DDEAPP (return server application) .....	870	DEBUGHOOK .....	613
DDECHANNEL .....	871	Decimal .....	495
DDECHANNEL (return DDE channel number) .....	871	Numeric Constant .....	495
DDECLIENT .....	872		
DDECLIENT (return DDE client channel) ..	872		

DECIMAL.....	94, 425	DISPLAY .....	623
DECIMAL (signed packed decimal).....	94	DISPLAY (write USE variables to screen) .....	623
Decimal Arithmetic.....	522	DISPOSE .....	129
Declaration and Statement Labels .....	8	DISPOSE (de-allocate heap memory)....	129
Deep Assignment .....	515	Division operator .....	492
Deep Assignment Statements .....	515	DLL .....	201, 206
DEFAULT .....	377	DLL (set procedure defined externally in .DLL) .....	48
DEFAULT (set enter key button) .....	377	DLL (set variable defined externally in .DLL) .....	201
DeferMove .....	949	dll_mode .....	201
DEFORMAT.....	614	DO.....	542
DEFORMAT (return unformatted numbers from string).....	614	DO (call a ROUTINE) .....	542
DELAY .....	378	DOCK.....	380
DELAY (set repeat button delay).....	378	DOCK (set dockable toolbox window) ....	380
DELETE (delete a record) .....	615	Docked.....	921
Delete a file (REMOVE).....	782	DOCKED.....	381
DELETEREG .....	617	DOCKED (set dockable toolbox window docked at open) .....	381
DERIVED (prevent function overloading) ..	47	DOCUMENT .....	382
Derived CLASSes (Inheritance) .....	146	DOCUMENT (create OLE control object from file).....	382
Destination variable .....	513, 514, 515, 517	Document windows.....	254
DESTROY .....	618	Documentation Conventions and Symbols. 3	
DESTROY (remove a control).....	618	Dollar sign .....	132
destructor.....	146	dollar sign syntax .....	500
DETAIL .....	266	Dot Syntax .....	10
DETAIL (report detail line structure) .....	266	DOUBLE .....	383
Details - Record Buffer logging.....	1014	NOFRAME, RESIZE (set window border) .....	383
Dialog boxes .....	254	Double-precision real .....	88, 92
dialog units.....	242, 357, 393, 424, 445, 464	DOWN.....	479
DIM .....	199	Drag .....	927
DIM (set array dimensions) .....	199	Dragging .....	928
DIRECTORY.....	619	DRAGID .....	384, 624
DIRECTORY (get file directory).....	619	DRAGID (return matching drag-and-drop signature).....	624
directory existence.....	638	DRAGID (set drag-and-drop host signatures) .....	384
DISABLE.....	379, 622		
DISABLE (dim a control) .....	622		
DISABLE (set control dimmed at open) ..	379		
Dispatch interface .....	887		



DRIVER .....	203	ENCRYPT (encrypt data file).....	205
DRIVER (specify data file type).....	203	END .....	30
DriverLogoutAlias .....	1014	END (terminate a structure).....	30
DriverOp .....	578	ENDPAGE .....	631
Drop .....	928	ENDPAGE (force page overflow) .....	631
DROP .....	385	Entity Parameters .....	36
DROP (set list box behavior) .....	385	ENTRY .....	292
DROPID .....	386, 625	ENTRY (declare a data entry control).....	292
DROPID (return drag-and-drop string) ....	625	ENV .....	175
DROPID (set drag-and-drop target signatures) .....	386	ENV file .....	703
DroppedDown .....	928	Environment Files .....	175
DroppingDown .....	928	EOF .....	1058
DUP .....	204	EOF (return end of file) .....	1058
DUP (allow duplicate KEY entries) .....	204	EQUATE .....	65
DUPLICATE .....	627	EQUATE (assign label) .....	65
DUPLICATE (check for duplicate key entries) .....	627	ERASE .....	633
Dynamic Data .....	123	ERASE (clear screen control and USE variables) .....	633
Dynamic Data Exchange .....	867	ERROR .....	634
Dynamic File Driver Support .....	651, 851	ERROR (return error message) .....	634
dynamic INDEX .....	160	Error Information .....	761
Dynamic index		Error messages	
BUILD .....	571	Compiler .....	1043
Edit .....	951	Run time .....	1037
Editing data .....	140	Error Messages .....	1043
ELLIPSE .....	290, 628	ERRORCODE .....	635
ELLIPSE (declare an ellipse control) .....	290	ERRORCODE (return error code number) .....	635
ELLIPSE (draw an ellipse) .....	628	ERRORFILE .....	636
ELSE .....	531, 533, 535	ERRORFILE (return error filename) .....	636
ELSIF .....	535	ERRORLEVEL .....	675, 793
EMPTY .....	629	EVALUATE .....	507
EMPTY (empty a data file) .....	629	EVALUATE (return runtime expression string result) .....	507
ENABLE .....	630	Evaluations .....	494
ENABLE (re-activate dimmed control) .....	630	logical .....	494
Enabled .....	952	Event .....	920, 922
Encapsulation .....	146	DDEadvise .....	920
ENCRYPT .....	205		

DDEclosed.....	920	MouseUp.....	930
DDEdata.....	920	Move.....	417, 922
DDEexecute.....	920	Moved.....	417, 922
DDEPoke.....	920	NewSelection.....	931
DDERequest.....	920	Notify.....	922
NestedLoop.....	922	OpenWindow.....	923
EVENT.....	637, 922, 930, 933	PageDown.....	931
Accepted.....	926	PageUp.....	931
AlertKey.....	918, 926	PreAlertKey.....	924, 931
BuildDone.....	918	Rejected.....	777, 931
BuildFile.....	918	Restore.....	417, 924
BuildKey.....	918	Restored.....	417, 924
CloseDown.....	918	Resume.....	924
CloseWindow.....	919	ScrollBottom.....	932
ColumnResize.....	926	ScrollDown.....	932
Completed.....	919	ScrollDrag.....	932
Contracted.....	926	ScrollTop.....	932
Contracting.....	927	ScrollTrack.....	932
Docked.....	921	ScrollUp.....	932
Drag.....	927	Selected.....	933
Dragging.....	928	Selecting.....	933
Drop.....	928	Size.....	417, 924
DroppedDown.....	928	Sized.....	417, 925
DroppingDown.....	928	Suspend.....	925
Expanded.....	928	TabChanging.....	933
Expanding.....	929	Timer.....	925
GainFocus.....	921	Undocked.....	921
Iconize.....	417, 921	EVENT (return event number).....	637
Iconized.....	417, 921	Event processor.....	529
Locate.....	929	Events - Modal.....	915
LoseFocus.....	921	Events - User Defined.....	752
Maximize.....	417, 922	EventsWaiting.....	953
Maximized.....	417, 922	Exclude null key entries.....	222
MouseDown.....	930	Exclusive Access.....	731
MouseIn.....	930	EXECUTE.....	533
MouseMove.....	930	BEGIN.....	533
MouseOut.....	930		

EXECUTE (statement execution structure) .....	533	file access .....	731
ExeVersion .....	953	file directory .....	619
EXISTS .....	638	file existence .....	638
Exists - PROPLIST .....	403	File Size .....	1019
EXISTS (return file existence) .....	638	file STATUS .....	836
EXIT .....	543	FILE Structure Properties .....	168
EXIT (leave a ROUTINE) .....	543	FileCallbackInterface .....	578
Expanded .....	928	FILEDIALOG .....	640
Expanding .....	929	FILEDIALOG (return chosen file) .....	640
Exponentiation operator .....	492	FILEDIALOGA .....	644
Expression Evaluation .....	491	FileDialogHook .....	953
Expression Strings .....	503	FILEERROR .....	648
Expressions .....	491	FILEERROR (return file driver error message) .....	648
Evaluation Precedence .....	491	FILEERRORCODE .....	649
Logical Expressions .....	499	FILEERRORCODE (return file driver error code number) .....	649
Numeric Expressions .....	497	files .....	1018
Runtime .....	503	FILES with the EXTERNAL attribute .....	206
String Expressions .....	498	FILL .....	388
EXTEND .....	387	FILL (set fill color) .....	388
Extended ERRORCODE 47 Errors .....	1032	FillColor .....	371
EXTERNAL .....	206	FILTER .....	208
EXTERNAL (set defined externally) .....	206	FILTER (set view filter expression) .....	208
FatalErrorHook .....	953	FIRST .....	389
FetchSize .....	1016	LAST (set MENU or ITEM position) .....	389
FIELD .....	639, 1016	FIRSTFIELD .....	650
FIELD (return control with focus) .....	639	FIRSTFIELD (return first window control) .....	650
Field Completion Keys .....	354, 556	FIXFORMAT .....	651
ALERT .....	556	FLAT .....	389
ALRT .....	354	FLAT (set flat buttons) .....	389
Field Equate Labels .....	256	Floating Point .....	86, 88, 90, 92
Field Qualification .....	10	Double Precision .....	88, 92
Field-independent events .....	917	Single Precision .....	86, 90
Fields (controls) .....	255	floating tabs .....	440
FieldsFile .....	1017	FLUSH .....	652
FILE .....	157, 1017	FLUSH (flush buffers) .....	652
FILE (declare a data file structure) .....	157	FlushPageNumFunc .....	954

FlushPreview .....	955	FREESTATE (free resources) .....	661
FOCUS .....	653	FROM .....	407
FOCUS (return control with focus) .....	653	FROM (set listbox data source) .....	407
folder existence.....	638	Full .....	409
Follows.....	957	FULL (set full-screen) .....	409
FONT .....	390	FUNCTION (define a function) .....	1059
FONT (set default font).....	390	GainFocus.....	921
FontColor - PROPSTYLE .....	401	GET .....	662
FONTDIALOG .....	654	GET (read a record or entry) .....	662
FONTDIALOG (return chosen font).....	654	GETFONT .....	666
FONTDIALOGA.....	656	GETFONT (get font information) .....	666
FONTDIALOGA (return chosen font and character set).....	656	GETGROUP .....	667
FontDialogHook .....	958	GETINI .....	668
FontName - PROPSTYLE .....	401	GETINI (return INI file entry).....	668
FontSize - PROPSTYLE.....	401	GETNULLS(get the NULL state of a table) .....	669
FontStyle - PROPSTYLE.....	401	GETPOSITION .....	670
FOOTER.....	268	GETPOSITION (get control position).....	670
FOOTER (page or group footer structure) .....	268	GETREG.....	672
Foreground color .....	371	GETSTATE .....	674
FORM .....	270	GETSTATE (return current state of data file) .....	674
FORM (page layout structure).....	270	Global.....	123
FORMAT.....	393, 658	Local, Static, and Dynamic .....	123
FORMAT (return formatted numbers into a picture).....	658	Global data.....	124
FORMAT (set LIST or COMBO layout) ...	393	Global menu.....	248
FORMAT() List Box Mouse Click Properties .....	405	Global tools .....	251
FORMAT() Other List Box Properties.....	403	GlobalHelp .....	1021
FORMAT() Runtime Properties .....	398	GOTO .....	544
FORMAT() Style Properties.....	401	GOTO (go to a label) .....	544
formatting.....	131	Graphics Coordinates .....	260
forward reference.....	120	GRAY .....	410
FORWARDKEY (pass keystrokes to control .....	659	GRAY (set 3-D look background) .....	410
FREE .....	660	GRID .....	411
FREE (delete all entries) .....	660	GRID (set list grid-line display color) .....	411
FREESTATE.....	661	GROUP .....	143, 296
		GROUP (compound data structure) .....	143
		GROUP (declare a group of controls).....	296

HALT .....	675	IMAGE (declare a graphic image control)	299
HALT (exit program) .....	675	IMAGE (draw a graphic image) .....	682
HaltHook .....	958	ImageBits .....	962
handle .....	944, 958	ImageBlob .....	963
HEADER .....	271	IMM .....	417
HEADER (page or group header structure) .....	271	IMM (set immediate event notification) ...	417
HeaderHeight .....	960	IMPLEMENTS .....	211
Held .....	1021	IMPLEMENTS Inheritance .....	213
HELP (help window access) .....	676	IMPLEMENTS(add methods to a CLASS) .....	211
Hexadecimal (numeric constant) .....	495	Implicit String Arrays .....	107
HIDE .....	411, 677	Implicit String Arrays and String Slicing ..	107
HIDE (blank a control) .....	677	Implicit Variables .....	119
HIDE (set control hidden) .....	411	LONG .....	119
HLP .....	412	REAL .....	119
HLP (set on-line help identifier) .....	412	STRING(32) .....	119
HOLD .....	678	INCLUDE .....	65
HOLD (exclusive record access) .....	678	INCLUDE (compile code in another file) ...	65
HOWMANY .....	680	INCOMPLETE .....	682
HSCROLL .....	413	INCOMPLETE (return empty REQ control) .....	682
VSCROLL, HVSCROLL (set scroll bars) .....	413	Inconsistent scanner initialization .....	1056
HScrollPos .....	960	INDEX .....	160
HVSCROLL .....	413	INDEX (declare static file access index) ..	160
ICON .....	414	Inheritance .....	146
ICON (set icon) .....	414	INI .....	668, 769
Iconize .....	921	GETINI .....	668
ICONIZE .....	416	PUTINI .....	769
ICONIZE (set window open as icon) .....	416	InitAStringHook .....	963
Iconized .....	921	INLIST .....	683
IconList .....	961	INLIST (return entry in list) .....	683
icons in list boxes .....	306, 393	INNER .....	216
icons in list fields .....	393	INNER (set inner join operation) .....	216
IDLE .....	681	inner join .....	216
IDLE (arm periodic procedure) .....	681	In-place activation .....	886
IF .....	535	Input Focus .....	255
IF (conditional execution structure) .....	535	INRANGE .....	683
IMAGE .....	299, 682	INRANGE (check number within range) ..	683

INS .....	419	KEYBOARD (return keystroke waiting) ..	695
OVR (set typing mode) .....	419	Keyboard Functions .....	695
INSTANCE .....	684	Keyboard Procedures .....	558
Instantiation .....	146	KEYCHAR .....	696
INSTRING .....	687	KEYCHAR (return ASCII code) .....	696
INSTRING (return substring position) .....	687	KEYCODE .....	697
INT .....	689	KEYCODE (return last keycode) .....	697
INT (integer function) .....	689	Keycode EQUATE Labels .....	6
INT (truncate fraction) .....	689	Keycodes .....	6
INTERFACE .....	155	KEYCODES.EQU .....	6
INTERFACE (class behavior definition) ..	155	Key-in Pictures .....	140
Intermediate value .....	491, 492	Key-in Template Pictures .....	140
Internationalization .....	175	KEYSTATE .....	698
InToolbar .....	964	KEYSTATE (return keyboard status) .....	698
Introduction .....	1	KEYWORD (short description of intended use) .....	4
IPRequestCount .....	964	label .....	8
ISALPHA .....	690	LANDSCAPE .....	422
ISALPHA (return alphabetic character) ..	690	LANDSCAPE (set page orientation) .....	422
ISGROUP .....	691	LAST .....	389
ISLOWER .....	692	LASTFIELD .....	699
ISLOWER (return lower case character) ..	692	LASTFIELD (return last window control) ..	699
ISSTRING .....	693	LAYOUT .....	423, 812
ISSTRING (return field string type or not) ..	693	LazyDisplay .....	965
ISUPPER .....	694	Leading zeroes .....	132
ISUPPER (return upper case character) ..	694	LEFT .....	424, 425, 700
ITEM .....	301	RIGHT, ABOVE, BELOW (set TAB position) ..	424
ITEM (declare a menu item) .....	301	RIGHT, CENTER, DECIMAL (set justification) .....	425
ITEMIZE .....	66	LEFT (return left justified string) .....	700
ITEMIZE (enumeration data structure) .....	66	LEN .....	701
ITEMS .....	965	LEN (return length of string) .....	701
Join .....	182, 420	LFNSupport .....	966
JOIN (declare a .....	182	LibHook .....	966
JOIN (set joined TAB scroll buttons) .....	420	LibVersion .....	967
KEY .....	161, 421	LIKE .....	117
KEY (declare dynamic file access index) ..	161	LIKE (inherited data type) .....	117
KEY (set execution keycode) .....	421		
KEYBOARD .....	695		

LINE .....	304, 702, 968	LOGOUT (begin transaction) .....	708
LINE (declare a line control) .....	304	LogoutIsolationLevel .....	1024
LINE (draw a straight line) .....	702	LONG .....	80
LINE declaration .....	304	LONG (four-byte signed integer) .....	80
LineCount .....	968	long filename support .....	966
LineHeight .....	969	Long to Short filename conversion .....	822
LINEWIDTH .....	427	SHORTPATH .....	822
LINEWIDTH (set line thickness) .....	427	LONGPATH .....	709
link .....	427	LONGPATH (return long filename) .....	709
LINK .....	217	LOOP .....	537
LINK (create OLE control link to object from file) .....	427	LOOP (iteration structure) .....	537
LINK (specify CLASS link into project) ....	217	LoseFocus .....	921
LIST .....	306	LOWER .....	710
LIST (declare a window list control) .....	306	LOWER (return lower case) .....	710
List Row Height .....	969	Maintaining INI Files .....	668
Local data .....	124	MAP .....	20
Local Derived Methods .....	146	MAP (declare PROCEDURE prototypes) .	20
Local menu .....	248	MARK .....	428
Local tools .....	251	MARK (set multiple selection mode) .....	428
LOCALE .....	703	MASK .....	429
LOCALE (load environment file) .....	703	control-level .....	429
Locate .....	929	MASK (set pattern editing data entry) .....	429
LOCK .....	704	Match .....	711
LOCK (exclusive file access) .....	704	NoCase .....	711
LOCKTHREAD .....	705	RegExpr .....	711
LOCKTHREAD (re-lock the current execution thread) .....	705	Simple .....	711
Log .....	1022	Soundex .....	711
LOG10 .....	706	Wild .....	711
LOG10 (return base 10 logarithm) .....	706	MATCH - compare matching values .....	711
Logarithm .....	706, 707	MAX .....	430
LOGE .....	707	MAX (set maximize control or total maximum) .....	430
LOGE (return natural logarithm) .....	707	MaxHeight .....	969
Logical Evaluations .....	494	Maximize .....	922
Logical Expressions .....	499	MAXIMIZE .....	432
Logical Operators .....	494	MAXIMIZE (set window open maximized) .....	432
LOGOUT .....	708, 1023	Maximized .....	922

MAXIMUM .....	714	MinWidth .....	971
MAXIMUM (return maximum subscript value) .....	714	Mixed data types.....	143
MaxStatements.....	1024	MM .....	471
MaxWidth.....	970	REPORT attribute .....	471
MDI .....	433	modal .....	242, 435
MDI (set MDI child window).....	433	MODAL (set system modal window).....	435
MDI application window .....	254	Modal Events .....	915
MDI child windows .....	254	Modal Windows.....	433, 435
MDI frame window .....	237	Modeless Windows .....	433, 435
MDI program.....	254	MODULE.....	22, 218
MEMBER .....	18	MODULE (specify CLASS member source file) .....	218
MEMBER (identify member source file) ....	18	MODULE (specify MEMBER source file) .	22
Memo		Module data .....	124
BINARY .....	196	Modulus Division.....	492
MEMO .....	162	Modulus operator .....	492
MEMO (declare a text field).....	162	MONTH .....	717
MEMO Properties .....	1028, 1029	MONTH (return month of date).....	717
Memory Allocation .....	123	Mouse Events .....	930
Dynamic.....	123	Mouse Properties - List Box.....	405
Static.....	123	MouseDown .....	930
memory QUEUE .....	185	MouseIn .....	930
Memory redeclaration (OVER) .....	225	MouseMove .....	930
MENU .....	311	MouseOut .....	930
MENU (declare a menu box) .....	311	MouseUp.....	930
MENUBAR.....	248	MOUSEX .....	717
MENUBAR (declare a pulldown menu) ...	248	MOUSEY .....	718
MESSAGE .....	715	Move .....	417, 922
MESSAGE (return message box response) .....	715	Moved .....	922
MessageHook.....	970	MSG .....	436
Method Syntax Overview.....	899	MSG (set status bar message).....	436
Methods .....	146	Multi-Monitor Support .....	366
VIRTUAL.....	146	Multiple Document Interface (MDI) .....	254
methods (PROCEDURES).....	146	Multiplication operator.....	492
MIN .....	434	Multi-threading .....	705, 834, 845, 846, 855
MIN (set total minimum) .....	434	LOCKTHREAD .....	705
MinHeight.....	971	START .....	834



THREAD .....	845	NOSHEET (set.....)	440
THREADLOCKED .....	846	NOT .....	494
UNLOCKTHREAD .....	855	Not implemented yet .....	1056
Name .....	219	NOTIFICATION.....	723
NAME .....	719	NOTIFY .....	725
NAME (return file name).....	719	Notify EVENT .....	922
NAME (set external name) .....	219	NoTips.....	975
NAME (set prototype's external name).....	48	NoWidth .....	975
Name Mangling and C++ Compatibility .....	59	Null .....	167
named group.....	120	NULL.....	517, 669, 726, 812, 813, 815
named GROUPs and QUEUEs .....	120	NULL (return null file field) .....	726
Natural logarithm .....	707	Null Data Processing .....	167
NestedLoop .....	922	Null String .....	496
NEW .....	126	number of entries visible in a LISTor COMBO .....	965
NEW (allocate heap memory) .....	126	NUMERIC .....	728
NewSelection.....	931	NUMERIC (return numeric string).....	728
NEXT .....	720	Numeric and Currency Pictures.....	132
NEXT (read next record in sequence).....	720	Numeric Constants .....	495
NextField.....	972	Numeric Expressions .....	497
NextPageNo .....	973	Numeric Pictures.....	132
NextTabStop.....	974	NumTabs .....	976
NOBAR .....	437	Object declaration.....	146
NOBAR (set no highlight bar).....	437	CLASS .....	146
NOCASE.....	220, 438	Object Linking and Embedding.....	886
NOCASE (case insensitive KEY or INDEX) .....	220	Object Properties (Encapsulation).....	146
NOCASE (case insensitive report BREAK) .....	438	Octal (numeric constant).....	495
NOFRAME.....	383	OCX Callback functions.....	897
NoHeight.....	975	OCX Events .....	897
NOMEMO .....	722	OCX Properties.....	897
NOMEMO (read file record without reading memo).....	722	OCXGETPARAM.....	911
NOMERGE .....	439	OCXGETPARAM (return current event parameter string).....	911
NOMERGE (set merging behavior) .....	439	OCXGETPARAMCOUNT .....	910
Nonstop mode .....	794	OCXGETPARAMCOUNT (return number of parameters for current event) .....	910
Non-Trappable Run Time Errors .....	1037	OCXLOADIMAGE.....	913
NOSHEET .....	440		

OCXLOADIMAGE (return an image object) .....	913	OLEDIRECTORY (get list of installed OLE/OCX) .....	894
OCXREGISTEREVENTPROC .....	906	OMIT .....	67
OCXREGISTEREVENTPROC (install event processing callback) .....	906	OMIT (specify source not to be compiled) ..	67
OCXREGISTERPROPCHANGE .....	905	OMITTED .....	729
OCXREGISTERPROPCHANGE (install property change callback) .....	905	OMITTED (return omitted parameters)...	729
OCXREGISTERPROPEdit .....	904	ONCE .....	69
OCXREGISTERPROPEdit (install property edit callback) .....	904	ONCE (prevent duplicate included data) ..	69
OCXSETPARAM .....	912	OPEN .....	441, 731
OCXSETPARAM (set current event parameter string) .....	912	OPEN (open a data structure) .....	731
OCXUNREGISTEREVENTPROC .....	909	OPEN (open OLE control object from file) .....	441
OCXUNREGISTEREVENTPROC (un-install event process callback) .....	909	Open-mode activation .....	886
OCXUNREGISTERPROPCHANGE .....	908	OpenReportHook .....	977
OCXUNREGISTERPROPCHANGE (un-install prop change callback) .....	908	OpenWindow .....	923
OCXUNREGISTERPROPEdit .....	907	OpenWindowHook .....	978
OCXUNREGISTERPROPEdit (un-install property edit callback) .....	907	Operating Assignment Statements .....	514
OEM .....	221	Operating Assignments .....	514
OEM (set international string support) .....	221	Operator Precedence .....	491
OEMTOANSI .....	605	Operators .....	494
OF .....	531	Conditional Operators .....	494
Old symbol non-NIL .....	1056	Logical Operators .....	494
OLE .....	314, 886	OPT .....	222
container windows .....	886	OPT (exclude null KEY or INDEX entries) .....	222
OLE (declare a window OLE or .OCX container control) .....	314	OPTION .....	318
OLE Automation .....	886	OPTION (declare a set of RADIO controls) .....	318
OLE Container Properties .....	887	OR .....	494
OLE Controller application .....	886	ORDER .....	223
OLE custom control OverView .....	895	ORDER (set view sort order expression) ..	223
OLE Overview .....	886	OROF .....	531
OLE Server application .....	886	Out of attribute space .....	1056
OLEDIRECTORY .....	894	outline control .....	393
		OVER .....	225
		OVER (set shared memory location) .....	225
		Overflow .....	132, 520
		arithmetic .....	132, 520

Overview .....	491	PATH .....	736
OVR .....	419	PATH (return current directory) .....	736
OWNER .....	226	Pattern Pictures .....	139
OWNER (declare password for data encryption) .....	226	PDECIMAL.....	96
PACK .....	735	PDECIMAL (signed packed decimal) .....	96
PACK (remove deleted records).....	735	PEEK .....	737
Packed Decimal.....	94, 96	PEEK (read memory address).....	737
PAGE .....	441	PENCOLOR.....	738
PAGE (set page total reset).....	441	PENCOLOR (return line draw color).....	738
Page Overflow .....	264	PENSTYLE .....	739
PAGEAFTER .....	442	PENSTYLE (return line draw style) .....	739
PAGEAFTER (set page break after) .....	442	PENWIDTH.....	740
Page-based printing .....	261	PENWIDTH (return line draw thickness) .....	740
PAGEBEFORE .....	443	Picture - PROPSTYLE .....	401
PAGEBEFORE (set page break first).....	443	Picture Tokens .....	131
PageDown .....	931	Pictures .....	132
PAGENO .....	444	Date .....	136
PAGENO (set page number print).....	444	Key-in .....	140
PageUp.....	931	Numeric and Currency .....	132
PALETTE.....	444	Pattern .....	139
PALETTE (set number of hardware colors) .....	444	Scientific Notation .....	134
PANEL .....	322	String.....	135
PANEL (declare a panel control).....	322	Time .....	138
PAPER.....	445	PIE .....	741
PAPER (set report paper size) .....	445	PIE (draw a pie chart) .....	741
Parameter Passing to OLE/OCX Methods .....	901	Pixels .....	980
Parameters .....	498	POINTER .....	743, 1060
expression used as.....	491, 503	POINTER (return last queue entry position) .....	743
PARENT .....	146, 155, 978	POINTER (return relative record position) .....	1060
PASCAL.....	46	POINTS.....	471
passed by address .....	36	REPORT attribute .....	471
passed by value.....	36	POKE .....	744
Passing Arrays.....	36	POKE (write to memory address).....	744
PASSWORD.....	446	POLYGON .....	745
PASSWORD (set data non-display).....	446	POLYGON (draw a multi-sided figure) ...	745
		Polymorphism .....	146

POPBIND.....	509	HEADER.....	271
POPBIND (restore runtime expression string name space).....	509	PRINTER.....	500, 760
POPERERRORS.....	761	built-in variable.....	500
POPUP.....	746	Printer Control Properties.....	273
POPUP (return popup menu selection)...	746	PRINTERDIALOG.....	760
POSITION.....	749	PRINTERDIALOG (return chosen printer) .....	760
POSITION (return record sequence position) .....	749	PrinterDialogHook.....	980
POST.....	752	PrintMode.....	981
POST (post user-defined event).....	752	PRIVATE.....	229
PRAGMA.....	753	PRIVATE (set procedure private to a CLASS or module).....	49
PRAGMA control pragma settings from source.....	753	PRIVATE (set variable private to a CLASS module).....	229
PRE.....	227	PROC (set function called as procedure without warnings).....	50
PRE (set label prefix).....	227	PROCEDURE.....	23
PreAlertKey.....	924, 931	PROCEDURE (define a procedure).....	23
PRESS.....	755	PROCEDURE Calls.....	32
PRESS (put characters in the buffer).....	755	Procedure Overloading.....	56
PRESSKEY.....	756	Procedure Parameters.....	36
PRESSKEY (put a keystroke in the buffer) .....	756	PROCEDURE Return Types.....	44
PREVIEW.....	447	Profile.....	1024
PREVIEW (set report output to metafiles) .....	447	PROGRAM.....	15
PREVIOUS.....	757	PROGRAM (declare a program).....	15
PREVIOUS (read previous view record in sequence).....	757	PROGRESS.....	325, 982
PrevTabStop.....	974	PROGRESS (declare a progress control) .....	325
PRIMARY.....	228	PROJECT.....	181
PRIMARY (set relational primary key).....	228	PROJECT (set view fields).....	181
Primary Key.....	228	PROMPT.....	323
PRINT.....	759	PROMPT (declare a prompt control).....	323
PRINT (print a report structure).....	759	PROP.....	251, 351, 362, 370, 387, 423, 430, 432, 434, 462, 468, 471, 472, 575, 936, 940, 947, 948, 964, 970, 974, 977, 978, 980, 982, 989, 990, 991, 993, 996, 1015, 1019
Print structure.....	265, 266, 268, 270, 271	ABOVE.....	424
BREAK.....	265	AboveSize.....	424
DETAIL.....	266	ABSOLUTE.....	352
FOOTER.....	268	AcceptAll.....	935
FORM.....	270		

ACTIVE.....	936	CHECK .....	368
AddRef.....	887	Checked.....	941
ALONE.....	353	Child .....	941
ALRT.....	354	ChildIndex .....	941
AlwaysDrop.....	936	ChoiceFeq.....	943
ANGLE.....	356	ClientHandle .....	944
AppInstance.....	936	ClientHeight .....	945
Ascending .....	168	ClientWidth.....	945
AssertHook .....	937, 966	ClientWndProc .....	945
AssertHook2 .....	937, 966	ClientX .....	946
AT .....	357	ClientY .....	946
AUTO.....	360	CLIP .....	369, 887
AutoPaper.....	938	ClipBits.....	947
AUTOSIZE.....	361, 887	CloseReportHook.....	947
AVE.....	362	CloseWindowHook.....	947
Background.....	371	CNT.....	370
BELOW.....	424	COLOR .....	371
BelowSize .....	424	ColorDialogHook.....	948, 966
BEVEL .....	363	ColorHighByte.....	948
BevelInner.....	363	COLUMN .....	373
BevelOuter.....	363	COMPATIBILITY.....	374, 887
BevelStyle.....	363	Completed.....	1013
BINARY .....	168, 196	Components.....	168
Blob.....	168, 887	ConnectString .....	1013
Blobs.....	168	Copy.....	887
BOXED .....	364	Create .....	168, 198, 375, 887, 895
BreakVar.....	938	CreateFromFile .....	887
BrokenTabs .....	413	CreateLinkToFile.....	887
Buffer .....	939	Ctrl .....	895
ButtonFeq .....	480	CurrentKey.....	1013
CanPaste .....	887	CURSOR .....	376
CanPasteLink .....	887	CustomColor .....	948
CAP .....	365	DataPath .....	1014
CENTER.....	366, 425	DDEMode .....	949
CENTERED .....	367	DDETimeOut.....	949
CenterOffset .....	425	Deactivate .....	887
CharSet.....	940	DECIMAL .....	425

DecimalOffset .....	425	FileDialogHook.....	953, 966
DEFAULT .....	377	FileDriver.....	168
DeferMove .....	949	Files .....	1018
DELAY .....	378	FileSize .....	575, 1019
DesignMode.....	895	FILL.....	388
Details.....	1014	FillColor.....	371
Dim .....	168	FILTER.....	208
DISABLE.....	379	FIRST.....	389
DOCK .....	380	FLAT .....	389
DOCKED .....	381	FlushLog .....	1020
DOCUMENT .....	382	FlushPageNumFunc.....	954
DOUBLE .....	383	FlushPreview .....	955
DoVerb.....	887, 895	Follows.....	957
Down.....	479	FONT .....	390
DRAGID.....	384	FontCharSet.....	390, 940
Driver .....	168, 203	FontColor .....	390
DriverLogoutAlias .....	1014	FontDialogHook .....	958, 966
DriverString.....	168, 203	FontName .....	390
DROP .....	385	FontSize.....	390
DROPID.....	386	FontStyle.....	390
DropWidth.....	385	FORMAT .....	393
DUP .....	168, 204	FROM .....	407
DuplicateKey.....	1015	FULL .....	409
Edit.....	951	GlobalHelp .....	1021
Enabled.....	952	GrabHandles.....	895
Encrypt.....	168, 205	GRAY .....	410
EventsWaiting.....	953	HaltHook .....	958, 966
ExeVersion .....	953	Handle.....	958
EXTEND .....	387	HeaderHeight.....	960
FalseValue.....	483	Height.....	357
FatalErrorHook .....	953, 966	Held.....	1021
Feq.....	480	HIDE .....	411
FetchSize.....	570, 1016	HLP .....	412
FIELD.....	168, 1016	HSCROLL .....	413
Fields .....	168	HscrollPos.....	960
FieldsFile .....	1017	ICON .....	414
File .....	1017	ICONIZE .....	416

IconList .....	961	Logout .....	1023
ImageBits .....	962	LogoutIsolationLevel .....	1024
ImageBlob .....	963	MARK .....	428
ImageInstance .....	963	MASK .....	429
IMM .....	417	Max .....	248, 430
InitAStringHook .....	963, 966	MaxHeight .....	969
INNER .....	216	MAXIMIZE .....	432
INS .....	419	MaxStatements .....	1024
Interface .....	963	MaxWidth .....	970
InToolbar .....	964	MDI .....	433
IPRequestCount .....	964	Memos .....	168
IsRadio .....	895	MenuBar .....	970
Items .....	965	MessageHook .....	966, 970
JOIN .....	420	MIN .....	434
JoinExpression .....	182	MinHeight .....	971
Key .....	168, 421	MinWidth .....	971
Keys .....	168	MM .....	471
Label .....	168	MODAL .....	435
LANDSCAPE .....	422	MSG .....	436
Language .....	887, 895	Name .....	168, 219
LAST .....	389	NextField .....	972
LastEventName .....	895	NextPageNo .....	973
LAYOUT .....	423	NextTabStop .....	974
LazyDisplay .....	965	NOBAR .....	437
LEFT .....	424, 425	NoCase .....	168, 220
LeftOffset .....	424, 425	NOFRAME .....	383, 974
LFNSupport .....	966	NoHeight .....	975
LibHook .....	966	NOMERGE .....	439
LibVersion .....	967	NOSHEET .....	440
Line .....	968	NoTips .....	975
LineCount .....	968	NoWidth .....	975
LineHeight .....	969	NumTabs .....	976
LINEWIDTH .....	427	Object .....	887
LINK .....	427	OEM .....	221
ListFeq .....	480	OLE .....	887, 895
LockThreadHook .....	966	OPEN .....	441, 887
Log .....	1022	OpenReportHook .....	977

OpenWindowHook.....	978	REPEAT.....	451
OPT.....	168, 222	ReportException.....	887, 895
ORDER.....	223	REQ.....	452
Over.....	168	RESET.....	453
OVR.....	419	RESIZE.....	383, 454
Owner.....	168, 226	RIGHT.....	424, 425, 455
PAGE.....	441	RightOffset.....	425
PAGEAFTER.....	442	ROUND.....	456
PageAfterNum.....	442	SaveAs.....	887, 895
PAGEBEFORE.....	443	ScreenText.....	984
PageBeforeNum.....	443	SCROLL.....	458
PAGENO.....	444	Selected.....	985
PALETTE.....	444	SelectedColor.....	371
Parent.....	978	SelectedFillColor.....	371
PASSWORD.....	446	SelectInterface.....	887
Paste.....	887	SelEnd.....	985
PasteLink.....	887	SelStart.....	985
Pixels.....	980	SINGLE.....	460
Places.....	168, 980	Size.....	168, 986
POINTS.....	471	SKIP.....	461
PREVIEW.....	447	Smooth.....	462
PrevTabStop.....	974	SnapHeight.....	987
Primary.....	168, 228	SnapWidth.....	987
PrinterDialogHook.....	966, 980	SPREAD.....	463
PrintMode.....	981	SQLDriver.....	1027
Profile.....	1024	SQLJoinExpression.....	182
Progress.....	982	SQLOrder.....	223
ProgressEvents.....	1025	STATUS.....	464
PropVScroll.....	982	StatusFont.....	989
RANGE.....	449	StatusText.....	464
RangeHigh.....	449	STD.....	465
RangeLow.....	449	STEP.....	466
READONLY.....	450	StmtAttr.....	1027
Reclaim.....	168, 231	StopHook.....	966, 989
Record.....	1027	STRETCH.....	467, 887
RejectCode.....	983	SUM.....	468
Release.....	887	SupportsOp.....	1027



SupportsType .....	1028	Update .....	887
SYSTEM .....	469	UPR .....	365
SystemPropHook .....	966, 989	UpsideDown .....	479, 999
TabBarColor .....	990	USE .....	480
TabBarLocation .....	991	UseAddress .....	1000
TabBarStyle .....	991	VALUE .....	483, 1029
TabBarVisible .....	991	VCR .....	485
TabRows .....	992	VcrFeq .....	485
TabSheetStyle .....	993	Visible .....	1001
TALLY .....	470	VLBproc .....	1002
Target .....	993	VLBval .....	1002
TempImage .....	993	VSCROLL .....	413, 1004
TempImagePath .....	993	VscrollPos .....	1005
TempImageStatus .....	993	WALLPAPER .....	486
TempNameFunc .....	993	Watched .....	1006, 1030
TempPagePath .....	994	WheelScroll .....	1006
TempPath .....	994	Width .....	357
Text .....	351, 1028	WindowsVersion .....	1007
ThemeActive .....	995	WITHNEXT .....	487
THOUS .....	471	WITHPRIOR .....	488
Thread .....	168, 234, 995	WIZARD .....	489
Threading .....	995	WndProc .....	1008
ThreadLockedHook .....	966	XOrigin .....	1010
TILED .....	472	Xpos .....	357
TIMER .....	473	YOrigin .....	1010
TIP .....	474	Ypos .....	357
TipDelay .....	996	Zoom .....	887
TipDisplay .....	996	PROP Text with Windows and Controls .	351
TipsFont .....	996	Properties .....	146, 995
TOOLBAR .....	251, 996	Object .....	146
TOOLBOX .....	476	thread number .....	995
Touched .....	997	Property Access Syntax .....	500
TRN .....	478	Property Equates .....	349
TrueValue .....	483	Property Expressions .....	500
Type .....	168, 998	PROPLIST .....	393, 403, 405
UnlockThreadHook .....	966	BackColor .....	403
UP .....	479	BackSelected .....	403

BarFrame.....	403	MouseUpField.....	405
CellStyle.....	393	MouseUpRow.....	405
Center.....	393	MouseUpZone.....	405
CenterOffset.....	393	Picture.....	393
Color.....	393	Resize.....	393
ColStyle.....	393	Right.....	393
Decimal.....	393	RightBorder.....	393
DecimalOffset.....	393	RightOffset.....	393
DefaultTip.....	393	Scroll.....	393
Exists.....	403	Style.....	403
FieldNo.....	393	TextColor.....	403
Fixed.....	393	TextSelected.....	403
Format.....	393	Tip.....	393
GRID.....	411	Tree.....	393
Group.....	393	TreeBoxes.....	393
GroupNo.....	393	TreeIndent.....	393
Header.....	393	TreeLines.....	393
HeaderCenter.....	393	TreeOffset.....	393
HeaderCenterOffset.....	393	TreeRoot.....	393
HeaderDecimal.....	393	Underline.....	393
HeaderDecimalOffset.....	393	Width.....	393
HeaderLeft.....	393	PROPPRINT.....	273
HeaderLeftOffset.....	393	Collate.....	273
HeaderRight.....	393	Color.....	273
HeaderRightOffset.....	393	Context.....	273
Icon.....	393	Copies.....	273
IconTrn.....	393	Device.....	273
LastOnLine.....	393	DevMode.....	273
Left.....	393	Driver.....	273
LeftOffset.....	393	Duplex.....	273
Locator.....	393	Extend.....	273
MouseDownField.....	405	FontMode.....	273
MouseDownRow.....	405	FromMin.....	273
MouseDownZone.....	405	FromPage.....	273
MouseMoveField.....	405	Paper.....	273, 445
MouseMoveRow.....	405	PaperBin.....	273
MouseMoveZone.....	405	PaperHeight.....	273, 445

PaperWidth .....	273, 445	PUTINI (set INI file entry).....	769
Percent .....	273	PUTREG .....	770
Port .....	273	QUEUE .....	185, 188
PrintToFile .....	273	ADD .....	550
PrintToName.....	273	CHANGES .....	586
Resolution.....	273	POINTER .....	743
SupportCollate .....	273	Processing .....	188
SupportCopies .....	273	QUEUE (declare a memory QUEUE structure).....	185
ToMax.....	273	QUOTE .....	773
ToPage .....	273	quotes added after a label .....	119
Yresolution.....	273	RADIO.....	327
PROPSTYLE .....	401	RADIO (declare a radio button control) ..	327
BackColor .....	401	RANDOM.....	774
BackSelected.....	401	RANDOM (return random number).....	774
BarStyle .....	401	RANGE .....	449
CharSet.....	401	RANGE (set range limits) .....	449
FontColor .....	401	Range validation .....	683
FontName .....	401	RangeHigh.....	449
FontSize.....	401	RangeLow.....	449
FontStyle.....	401	RAW (pass address only) .....	52
Picture.....	401	READONLY .....	450
TextColor .....	401	READONLY (set display-only).....	450
TextSelected.....	401	REAL.....	88
PROTECTED.....	230	REAL (eight-byte signed floating point) ....	88
PROTECTED (set procedure private to a CLASS or derived CLASS).....	51	RECLAIM .....	231
PROTECTED (set variable private to a CLASS or derived CLASS).....	230	RECLAIM (reuse deleted record space). 231	
Prototype Parameter Lists .....	36	RECORD .....	166, 1027
PSTRING.....	105	RECORD (declare record structure).....	166
PSTRING (embedded length-byte string)105		RECORDS .....	775
PUSHBIND .....	510	RECORDS (return number of rows in data set) .....	775
PUSHBIND (save runtime expression string name space).....	510	Recursive .....	124
PUSHERRORS .....	763	FUNCTION .....	124
PUT.....	765	PROCEDURE .....	124
PUT (re-write record).....	765	Redeclares (OVER) .....	225
PUTINI.....	769	Reference Assignment Statements .....	517
		Reference Assignments.....	517

Reference Variables .....	120	RESET .....	784
REGET .....	779	RESET (reset record sequence position) .....	784
REGET (re-get record) .....	779	RESET (set total reset) .....	453
REGION .....	330	RESIZE .....	383, 417, 454
REGION (declare a window region control) .....	330	RESIZE (set variable height TEXT control) .....	454
regular expression match .....	711	Restore .....	924
REJECTCODE .....	777, 983	Restored .....	924
REJECTCODE (return reject code number) .....	777	RESTORESTATE .....	787
Rejected .....	931	RESTORESTATE (restore state of data file) .....	787
RELEASE .....	781	RESUME .....	788
RELEASE (release a held record) .....	781	RETURN .....	545
Remainder (Modulus division) .....	492	RETURN (return to caller) .....	545
REMOVE .....	782	return file existence .....	638
REMOVE (erase a file) .....	782	Rewrite (PUT) .....	765
RENAME .....	783	RIGHT .....	424, 425, 455, 788
RENAME (change file directory name) .....	783	RIGHT (return right justified string) .....	788
REPEAT .....	451	RIGHT (set MENU position) .....	455
REPEAT (set repeat button rate) .....	451	ROLLBACK .....	789
Repeat count notation .....	496	ROLLBACK (terminate unsuccessful transaction) .....	789
Repeated characters .....	559	ROUND .....	456, 790
REPLACE .....	53	ROUND (return rounded number) .....	790
REPLACE (set replacement constructor or destructor) .....	53	ROUND (set round-cornered BOX) .....	456
REPORT .....	261	ROUNDBOX .....	790
REPORT (declare a report structure) .....	261	ROUNDBOX (draw a box with round corners) .....	790
Report Measurement Units .....	471	ROUTINE .....	28, 543
Report totals .....	362, 370, 430, 434, 468	DO .....	542
AVE .....	362	EXIT .....	543
CNT .....	370	Row Height - LIST or COMBO .....	969
MAX .....	430	RTF .....	457
MIN .....	434	RTF Support .....	457
SUM .....	468	Rules for Procedure Overloading .....	57
REQ .....	452	RUN .....	791
REQ (set required entry) .....	452	RUN (execute command) .....	791
Reserved Words .....	12	Run Time Errors .....	1037
Reset .....	453		

RUNCODE.....	793	SET .....	798
RUNCODE (return program exit code)....	793	SET (initiate sequential file processing) .	798
Runtime Expression .....	503	SET3DLOOK .....	801
Runtime Expression Evaluation.....	503	SET3DLOOK (set 3D window look).....	801
Runtime Property Assignment.....	349, 500	SETCLIPBOARD .....	802
Property Access Syntax .....	500	SETCLIPBOARD (set windows clipboard contents) .....	802
Property Equates .....	349	SETCLOCK.....	803
Scientific Notation Pictures.....	134	SETCLOCK (set system time) .....	803
scope .....	123	SETCOMMAND .....	804
Screen Fields (controls).....	255	SETCOMMAND (set command line parameters).....	804
ScreenText .....	984	SETCURSOR .....	805
SCROLL .....	458	SETCURSOR (set temporary mouse cursor) .....	805
SCROLL (set scrolling control).....	458	SETDROPID .....	807
ScrollBottom .....	932	SETDROPID (set DROPID return string)	807
ScrollDown.....	932	SETFONT .....	808
ScrollDrag .....	932	SETFONT (specify font) .....	808
ScrollTop.....	932	SETKEYCHAR.....	810
ScrollTrack.....	932	SETKEYCHAR (specify ASCII code).....	810
ScrollUp .....	932	SETKEYCODE .....	811
SECTION.....	70	SETKEYCODE (specify keycode) .....	811
SECTION (specify source code section)...	70	SETLAYOUT.....	812
SELECT .....	794	SETNONULL .....	812
SELECT (select next control to process)	794	SETNONULL (set file field non-null) .....	812
Selected.....	933	SETNULL .....	813
SELECTED .....	796, 985	SETNULL (set file field null).....	813
SELECTED (return control that has received focus) .....	796	SETNULLS .....	815
SelectedColor .....	371	SETNULLS(set the null state of columns) .....	815
SelectedFillColor.....	371	SETPATH .....	816
Selecting .....	933	SETPATH (change current drive and directory) .....	816
SelEnd .....	985	SETPENCOLOR.....	817
SELF .....	146	SETPENCOLOR (set line draw color) ....	817
SelStart.....	985	SETPENSTYLE .....	817
SEND .....	797	SETPENSTYLE (set line draw style).....	817
SEND (send message to file driver) .....	797	SETPENWIDTH.....	818
SEPARATOR.....	459		
SEPARATOR (set separator line ITEM)..	459		

SETPENWIDTH (set line draw thickness) .....	818	SIZE .....	71, 986
SETPOSITION.....	819	SIZE (memory size in bytes).....	71
SETPOSITION (specify new control position) .....	819	Size of a File .....	1019
SETTARGET .....	500, 820	Size Window .....	924
SETTARGET (set current window or report) .....	820	Sized .....	925
SETTODAY .....	822	SKIP .....	461, 825
SETTODAY (set system date).....	822	SKIP (bypass records in sequence) .....	825
SHARE .....	1061	SKIP (set Tab key skip or conditional print control) .....	461
SHARE (open data file for shared access) .....	1061	SMOOTH .....	462
SHEET .....	332	SnapHeight .....	987
SHEET (declare a group of TAB controls) .....	332	SnapWidth .....	987
SHORT .....	76	SORT .....	826
SHORT (two-byte signed integer) .....	76	SORT (QUEUE).....	826
Short to Long filename conversion .....	709	SORT (sort queue entries).....	826
LONGPATH .....	709	sort order.....	160, 161
SHORTPATH.....	822	INDEX .....	160
SHORTPATH (return short filename).....	822	KEY .....	161
SHOW.....	823	VIEW .....	223
SHOW (write to screen).....	823	Sound (BEEP).....	566
SHUTDOWN.....	824	soundex .....	711
SHUTDOWN (arm termination procedure) .....	824	Source variable .....	513
SIGNED .....	84	Special Characters.....	13
SIGNED (16/32-bit signed integer).....	84	used in string constants .....	496
Simple Assignment Data Type Conversion .....	523	Specific Errors.....	1044
Simple Assignment Statements.....	513	SPIN.....	336
Simple Assignments .....	513	SPIN (declare a spinning list control).....	336
SIN .....	825	SPREAD .....	463
SIN (return sine) .....	825	SPREAD (set evenly spaced TAB controls) .....	463
SINGLE.....	460	SQL .....	828
SINGLE (set TEXT for single line entry).....	460	SQL (use SQL code) .....	828
Single Document Interface (SDI).....	254	SQLCALLBACK (register or unregister a SQLCallBackInterface .....	830
Single-precision real .....	86, 90	SQLDriver .....	1027
		SQRT .....	833
		SQRT (return square root).....	833
		SREAL .....	86

SREAL (four-byte signed floating point) ....	86	Style - PROPLIST .....	403
Standard Date.....	4	SUB.....	842
Standard Time .....	5	SUB (return substring of string) .....	842
START .....	834	Subscript .....	199
START (return new execution thread).....	834	Array .....	199
Statement Execution Sequence .....	31	MAXIMUM.....	714
Statement Format.....	7	Subtraction operator .....	492
STATIC .....	232	SUM .....	468
STATIC (set allocate static memory).....	232	SUM (set total) .....	468
Static Data .....	123	SupportsOp .....	1027
STATUS.....	464, 836	SupportsType.....	1028
STATUS (return file status) .....	836	SUSPEND.....	844
STATUS (set status bar) .....	464	Switch To .....	469
StatusFont .....	989	SYSTEM .....	469, 500
STD.....	465	built-in variable.....	500
STD (set standard behavior) .....	465	SYSTEM (set system menu) .....	469
STEP .....	466	System date .....	849
STEP (set SPIN increment).....	466	TODAY.....	849
StmtAttr.....	1027	System Date .....	822
STOP .....	838	SETTODAY.....	822
STOP (suspend program execution).....	838	System menu .....	469
StopHook .....	989	System modal .....	242, 435
STREAM.....	839	System Time .....	595, 803
STREAM (enable operating system buffering).....	839	CLOCK.....	595
STRETCH.....	467	SETCLOCK.....	803
STRETCH (set OLE object stretching)....	467	TAB .....	344
STRING .....	98, 340	TAB (declare a page of a SHEET control) .....	344
STRING (declare a string control) .....	340	TabChanging .....	933
STRING (fixed-length string) .....	98	TabRows.....	992
String Constants .....	496	TALLY .....	470
String Expressions.....	498	TALLY (set total calculation times) .....	470
String not CCST.....	1056	TAN.....	845
String Pictures .....	135	TAN (tangent of angle) .....	845
String Slicing.....	107	TARGET .....	500, 993
STRPOS .....	840	built-in variable.....	500
Structure Termination .....	9	TARGET, built-in variable .....	820

TemplImage.....	993	TILED (set tiled image) .....	472
TemplImagePath .....	993	Time	
TemplImageStatus .....	993	Standard Time .....	5
TempNameFunc.....	993	TIME .....	111
TempPagePath.....	994	TIME (four-byte time).....	111
TempPath .....	994	Time Pictures .....	138
Termination.....	543, 545, 675	Timer .....	925
FUNCTION .....	545	TIMER.....	473
HALT .....	675	TIMER (set periodic event) .....	473
PROCEDURE.....	545	TIMES .....	537
PROGRAM .....	545	TIP .....	474
ROUTINE.....	543	TIP (set .....	474
TEXT .....	346, 1028	TipDelay .....	996
TEXT (declare a multi-line text control) ...	346	TipDisplay .....	996
TextColor - PROPLIST .....	403	TipsFont .....	996
TextColor - PROPSTYLE .....	401	TO .....	531, 537
TextSelected - PROPLIST.....	403	TODAY.....	849
TextSelected - PROPSTYLE.....	401	TODAY (return system date) .....	849
THEN .....	535	TOGETHER.....	475
THOUS .....	471	TOOLBAR.....	251
MM, POINTS (set report coordinate measure).....	471	TOOLBAR (declare a tool bar) .....	251
REPORT attribute.....	471	TOOLBOX.....	476
THREAD .....	234, 845, 995	TOOLBOX (set toolbox window behavior) .....	476
THREAD (return current execution thread) .....	845	Totals .....	362, 370, 430, 434, 468
THREAD (set thread-specific memory allocation) .....	234	AVE .....	362
thread number .....	995	CNT .....	370
threading.....	788, 995	MAX .....	430
THREADLOCKED .....	846	MIN .....	434
THREADLOCKED (returns current execution thread locked state).....	846	SUM .....	468
TIE(associate a string value to an ASTRING).....	847	Touched .....	997
TIED(retrieves a value associated with an ASTRING.....	848	Transaction Processing .....	602, 708, 789
TILED.....	472	COMMIT .....	602
IMAGE attribute .....	472	LOGOUT.....	708
		ROLLBACK.....	789
		Tree control.....	393
		tree controls in list boxes .....	306



TRN .....	478	Unknown picture type .....	1056
TRN (set transparent control) .....	478	Unknown screen structure kind .....	1056
Truncation .....	520	Unknown simple formal type .....	1056
Data Type Conversion Rules .....	520	Unknown special identifier .....	1056
two-column drop menu .....	248	Unknown static label .....	1056
TYPE .....	236, 850, 998	Unknown string kind .....	1056
TYPE (specify PROCEDURE type definition) .....	54	Unknown structure field .....	1056
TYPE (type definition) .....	236	Unknown variable context .....	1056
TYPE (write string to screen) .....	850	Unknown variable type .....	1056
Type Conversion .....	520, 522	UNLOAD .....	853
Type Conversion and Intermediate Results .....	522	UNLOAD (remove a CALLED DLL from memory) .....	853
type definition .....	236	UNLOCK .....	854
Type descriptor not static .....	1056	UNLOCK (unlock a locked data file) .....	854
ULONG .....	82	UNLOCKTHREAD .....	855
ULONG (four-byte unsigned integer) .....	82	UNLOCKTHREAD (unlock the current execution thread) .....	855
UNBIND .....	511	UNQUOTE .....	856
UNBIND (free runtime expression string variable) .....	511	UNQUOTE language statement .....	856
UNFIXFORMAT .....	851	UNREGISTER .....	857
UNHIDE .....	852	UNREGISTER (unregister event handler) .....	857
UNHIDE (show hidden control) .....	852	UNREGISTEREVENT .....	857
UNICODE .....	175	UNSIGNED .....	85
Unknown assignment operator .....	1056	UNSIGNED (16/32-bit unsigned integer) ..	85
Unknown case type .....	1056	UNTIE(disassociate a string value from an ASTRING) .....	858
Unknown clear type .....	1056	UNTIL .....	537
Unknown descriptor type .....	1056	UP .....	479
Unknown designator kind .....	1056	DOWN (set TAB text orientation) .....	479
Unknown equate type .....	1056	UPDATE .....	859
Unknown errors .....	1056	UPDATE (write from screen to USE variables) .....	859
Unknown expression kind .....	1056	UPPER .....	860
Unknown expression type .....	1056	UPPER (return upper case) .....	860
Unknown formal entity .....	1056	UPR .....	365
Unknown initializer type .....	1056	UpsideDown .....	999
Unknown label/routine .....	1056	use .....	480
Unknown operator .....	1056		
Unknown parameter kind .....	1056		

USE (set field equate label or control update variable).....	480	TIME .....	111
UseAddress .....	1000	ULONG .....	82
User Defined Events.....	752	UNSIGNED .....	85
USHORT.....	78	USHORT .....	78
USHORT (two-byte unsigned integer).....	78	VARIANT .....	114
VAL .....	861	VB to Clarion Syntax.....	899
VAL (return ASCII value).....	861	VCR .....	485
valid Clarion label .....	8	VCR (set VCR control).....	485
VALUE .....	483, 1029	VERTICAL .....	484
VALUE (set RADIO or CHECK control USE variable assignment) .....	483	VERTICAL set vertical progress bar display .....	484
Value not static .....	1056	VIEW .....	178
Value Parameters.....	36	VIEW - sorting.....	223
Variable Parameters .....	36	VIEW (declare a.....	178
Variable size arrays .....	125	VIRTUAL (set virtual method).....	55
Variable Size Declarations .....	125	VIRTUAL Methods.....	146
Variables.. 86, 88, 90, 92, 98, 103, 105, 229, 230		Visible .....	1001
ANY .....	114	VLBproc .....	1002
BFLOAT4.....	90	VLBval.....	1002
BFLOAT8.....	92	VSCROLL .....	413
BYTE .....	75	VscrollPos .....	1005
CSTRING.....	103	WALLPAPER .....	486
DATE .....	109	WALLPAPER (set background image)...	486
DECIMAL.....	94	WATCH .....	862
GROUP.....	143	WATCH (automatic concurrency check). 862	
Implicit.....	119	Watched.....	1006, 1030
LONG.....	80	WHAT .....	863
PDECIMAL .....	96	WHAT (return field from group) .....	863
PRIVATE .....	229	WheelScroll.....	1006
PROTECTED.....	230	WHERE.....	864
PSTRING.....	105	WHERE (return field position in group)...	864
REAL .....	88	WHILE.....	537
SHORT .....	76	WHO .....	865
SIGNED .....	84	WHO (return field name from group) .....	865
SREAL .....	86	wild card match .....	711
STRING .....	98	WINDOW .....	242
		MDI child window .....	242

---

non-MDI window .....	242	WIZARD .....	489
WINDOW (declare a dialog window) .....	242	WIZARD (set .....	489
Window Controls and Input Focus .....	255	WndProc .....	1008
Window Functions .....	548	WSLSTG 755 .....	1037
Window Overview .....	254	XML ErrorCodes .....	1031
Window Procedures .....	585	XOR .....	494
Windows Standard Dialog Functions .....	600	YEAR .....	866
WindowsVersion .....	1007	YEAR (return year of date) .....	866
WITHNEXT .....	487	YIELD .....	866
WITHNEXT (set widow elimination) .....	487	YIELD (allow event processing) .....	866
WITHPRIOR .....	488	ZOOM .....	490
WITHPRIOR (set orphan elimination) .....	488	ZOOM (set OLE object zooming) .....	490