

# Space Game Client/Server PC Setup

For Server setup, skip #4 and #5  
For Client setup, skip #11

## 1) Setup Offline Account

- No password is necessary (leave blank)

## 2) Update Windows 10 to most current version

- We should try to have the same OS version (x.x.x.x.x) build on each unit

## 3) Automate Account Login:

- Search Windows for **Regedit** (registry editor) and open
- Navigate to *HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\WindowsNT \Current Version\Winlogon*
- Double click *AutoAdminLogon*
- Modify "Value Data": 1

## 4) Disable Edge Swiping:

- Search Windows for **Local Group Policy Editor** and open
- Navigate to *Computer Configuration/Administrative Templates/Windows Components/Edge UI* → **Disable**

## 5) Display Settings:

- Search Windows for **Display Settings** and open
- Rotation Lock*: **On**
- Display Orientation*: **Landscape**

## 6) Sleep/Power Settings:

- Search Windows for **Power & Sleep** and open
- On Battery Power, Turn Off After*: **Never**
- When Plugged In, Turn Off After*: **Never**
- On Battery Power, PC Goes to Sleep After*: **Never**
- When Plugged In, PC Goes to Sleep After*: **Never**

## 7) Install Wu10man:

- Navigate to <https://github.com/WereDev/Wu10Man/releases>
- Download installer and install
- Turn off all Windows updating options (x3)

## 8) Install Space Game Client/Server Application:

- Navigate to <https://github.com/AdenInteractive/bam-kazam-space-game> and download the repository (*code* → *download .zip*) ... or ...
- Utilize the site's Space Game USB backup drive
- Copy the *Client\_#* or *Server* folder onto the desktop (*bam-kazam-space-game-main* → *Builds*)

### 9) Create Batch Script for Automated App Launch:

- Right click the bottom left Windows icon
- Select *Run*, and enter *shell:startup*
- Within the folder, create a new text file and insert the following lines:  
    cd C:\Users\"Account Name\"\\\"Client # or Server\"  
    timeout /t 60  
    Bam Kazam Space Game
- Click "Save As" and set "Save As" type to "All Files"
- Set and save the file name to "ClientLaunch.bat" or "ServerLaunch.bat"

### 10) Set Windows Restart Time within Task Scheduler

- Search Windows for **Task Scheduler** and open
- Within the *Actions* window, select *Create Basic Task*
- Within the pop-up window, enter "Restart Computer" and push *Next*
- Ensure that *Daily* is selected, then push *Next*
- Ensure that the task "Starts" today, and set the time to 7:00 AM (or other)
- Ensure that the task recurs every "1" days, then push *Next*
- Ensure that *Start a Program* is selected, then push *Next*
- Enter the following:  
    *Program/script:* C:\Windows\System32\shutdown.exe  
    *Add arguments:* /r
- Push *Next*, then push *Finish*

### 11) Configure Bios

- Power-on or Restart the computer
- During the boot process, press F2 (or other) to enter BIOS
- Navigate to Power Management → AC Recovery
- Select **ON**, Press **ESC**, the select **Save and Exit**
- Note: This process might slightly differ from one PC to another

### 12) Set IP Addresses

- Search Windows for **Network Connections** and open
- Server* → double-click *Ethernet*; *Client* → double-click *Wi-Fi*
- Select *Internet Protocol Version 4* and push *Properties*
- After selecting both "Use the following..." buttons, input these items:
  - IP address:* 192.168.50.xxx (xxx = appropriate client/server octet)
  - Subnet mask:* 255.255.255.0
  - Default gateway:* 192.168.50.1
  - Preferred DNS server:* 192.168.50.1
- Press OK to confirm these changes, and then press OK on the next window

### 13)Install the Arduino IDE

- Navigate to <https://www.arduino.cc/en/software> and download/install the IDE software
- Refer to the README file within the *Arduino Scripts* folder for further directions

### 14)Configure XML Files

- Refer to the *Space Game Client Server XML* document for details