

# Not1MM User Manual

Mike Bridak K6GTE

October 2025

# Contents

<b>1</b>	<b>Not1MM</b>	<b>1</b>
1.1	Not1MM. What is it . . . . .	1
1.2	The Why . . . . .	1
1.3	Target Environment . . . . .	1
1.4	Current State, or Code Maturity . . . . .	1
<b>2</b>	<b>List of Should be Working Contests</b>	<b>2</b>
2.1	Other not so Supported Contests . . . . .	2
<b>3</b>	<b>Installation</b>	<b>3</b>
3.1	Prerequisites . . . . .	3
3.2	The Easy and Fast way to install or run the latest version . . . . .	3
<b>4</b>	<b>After the Install</b>	<b>4</b>
4.1	You May or May Not Get a Warning Message Like . . . . .	4
4.2	Or this Fan Favorite . . . . .	4
4.3	Update Your CTY and SCP Files . . . . .	4
<b>5</b>	<b>Various Data File Locations</b>	<b>5</b>
5.1	Data . . . . .	5
5.2	Config . . . . .	5
<b>6</b>	<b>The Database</b>	<b>5</b>
6.1	Why . . . . .	5
6.2	The First One is Free . . . . .	5
6.3	Why Limit Yourself . . . . .	5
6.4	Revisiting an Old Friend . . . . .	5
<b>7</b>	<b>Station Settings Dialog</b>	<b>6</b>
7.1	Changing Station Information . . . . .	6
<b>8</b>	<b>Selecting a Contest</b>	<b>6</b>
8.1	Selecting a New Contest . . . . .	6
8.2	Selecting an Existing Contest as the Current Contest . . . . .	7
8.3	Editing Existing Contest Parameters . . . . .	7
<b>9</b>	<b>Configuration Settings</b>	<b>8</b>
9.1	Lookup . . . . .	8
9.2	Soundcard . . . . .	8
9.3	CAT Control . . . . .	8
9.4	CW Keyer Interface . . . . .	8
9.5	Cluster . . . . .	9
9.6	N1MM Packets . . . . .	9
9.7	Bands . . . . .	10
9.8	Options . . . . .	11
<b>10</b>	<b>Logging Digital Contacts</b>	<b>12</b>
<b>11</b>	<b>Operating Multi Multi</b>	<b>13</b>
11.1	Network Settings for Multi Multi . . . . .	13
11.2	Contest Settings for Multi Multi . . . . .	14

<b>12 Sending CW</b>	<b>15</b>
12.1 Sending CW Macros . . . . .	15
12.2 Auto CQ . . . . .	15
12.2.1 Setting the delay . . . . .	15
12.3 Sending CW Free Form . . . . .	15
<b>13 Editing Macro Keys</b>	<b>16</b>
13.1 Macro Substitutions . . . . .	16
13.2 Macro Use with Voice . . . . .	16
13.2.1 Voice macro wave files . . . . .	16
13.2.2 Macro control of radio functions . . . . .	17
<b>14 cty.dat and QRZ for Distance and Bearing</b>	<b>18</b>
<b>15 Other Uses for the Call Field</b>	<b>18</b>
<b>16 The Windows</b>	<b>19</b>
16.1 The Main Window . . . . .	19
16.1.1 Keyboard Commands . . . . .	20
16.2 The Log Window . . . . .	20
16.2.1 Editing a Contact . . . . .	21
16.3 The Bandmap Window . . . . .	23
16.4 The Check Partial Window . . . . .	25
16.5 The Rate Window . . . . .	26
16.6 The DXCC window . . . . .	26
16.7 The Zone window . . . . .	26
16.8 The Rotator Window (Work In Progress) . . . . .	26
16.9 The Remote VFO Window . . . . .	28
<b>17 Cabrillo</b>	<b>29</b>
<b>18 ADIF</b>	<b>29</b>
<b>19 Recalculate Mults</b>	<b>29</b>
<b>20 ESM</b>	<b>30</b>
20.1 Run States . . . . .	31
20.1.1 CQ . . . . .	31
20.1.2 Call Entered Send His Call and the Exchange . . . . .	31
20.1.3 Empty Exchange Field Send AGN Till You Get It . . . . .	31
20.1.4 Exchange Field Filled, Send TU QRZ and Logs it . . . . .	32
20.2 S&P States . . . . .	32
20.2.1 With His Call Entered, Send Your Call . . . . .	32
20.2.2 If No Exchange Entered Send AGN . . . . .	32
20.2.3 With Exchange Entered, Send Your Exchange and Log it . . . . .	33
<b>21 Call History Files</b>	<b>34</b>
<b>22 Creating your own Call History files</b>	<b>35</b>
<b>23 Contest Specific Notes</b>	<b>37</b>
23.1 ARRL Sweekstakes . . . . .	37
23.1.1 The Exchange Parser . . . . .	37
23.1.2 The Exchange . . . . .	37
23.2 RAEM . . . . .	37
23.3 RandomGram . . . . .	37

23.4 UKEI DX . . . . .	37
23.5 CWO Open Contest . . . . .	38

# 1 Not1MM

The worlds number 1 unfinished contest logger. \*According to my daughter Corinna.

Not1MM's interface is a blatant rip-off of N1MM. It is NOT N1MM and any problem you have with this software should in no way reflect on their software.

## 1.1 Not1MM. What is it

Not1MM attempts to be a usable amateur radio, or HAM, contest logger. It's written in Python 3.10+, and uses Qt6 framework for the graphical interface and SQLite for the database.

## 1.2 The Why

**Currently, this exists for my own personal enjoyment.** I recently retired after 35+ years working for 'The Phone Company', GTE Verizon Frontier. And being a Gentleman of Leisure, I needed something to do in my free time. I am a casual tester and could not find any contesting software for Linux that I wanted to use. There is **Tucnak**, available at [HTTP://tucnak.nagano.cz/](http://tucnak.nagano.cz/) which is very robust and mature. It just wasn't for me.

## 1.3 Target Environment

The primary target for this application is Linux. It may be able to run on other platforms, BSD and Windows. But I don't have a way, or desire, to directly support them. I've recently purchased an M4 Mac Mini, So I'll probably put more effort into that platform as well.

## 1.4 Current State, or Code Maturity

Not1MM is, at times, fairly stable. Recently, it would seem that I'm desperately trying to change that. The current focus of development is adding support for Multi Multi contest operations. It is something that I have no practical experience in. So you can expect the same quality of code fit and finish.

## 2 List of Should be Working Contests

- General Logging
- 10 10 Fall CW
- 10 10 Spring CW
- 10 10 Summer Phone
- 10 10 Winter Phone
- ARI 40 80
- ARI DX
- ARRL 10M
- ARRL 160M
- ARRL DX CW, SSB
- ARRL Field Day
- ARRL RTTY Roundup
- ARRL Sweepstakes
- ARRL VHF
- CQ 160
- CQ WPX
- CQ World Wide
- CWOps CWT, CWO
- DARC Xmas
- DARC VHF
- EA Majistad CW
- EA Majistad SSB
- EA RTTY
- ES FIELD DAY HF
- ES OPEN HF
- Estonian LL Cup
- Helvetia
- IARU Field day
- IARU HF
- ICWC MST
- Japan International DX
- K1USN Slow Speed Test
- Labre RS Digi
- LZ DX
- NAQP
- Phone Weekly Test
- RAEM
- RAC Canada Day
- RandomGram
- REF CW, SSB
- SAC CW, SSB
- SPDX
- Stew Perry Top band
- UK/EI DX
- Weekly RTTY
- Work All Germany
- Winter Field Day

### 2.1 Other not so Supported Contests

Of note, state QSO parties. I haven't worked any yet. And no one has submitted a PR adding one... So there you go. In the near future I'll probably add California, guess where I live, and the 4 states QSO party.

## 3 Installation

This section will hopefully get you started with installing Not1MM.

### 3.1 Prerequisites

Not1MM requires:

- Python 3.10+
- PyQt6
- libportaudio2
- libxcb-cursor0 (maybe... Depends on the distro)
- libxslt-devel (maybe... Depends on the distro)
- libxml2-devel (maybe... Depends on the distro)

You should install these through your distribution's package manager before continuing.

### 3.2 The Easy and Fast way to install or run the latest version

Step 1. Visit <https://docs.astral.sh/uv/> and install uv.

In short you run this in your terminal:

```
curl -LsSf https://astral.sh/uv/install.sh | sh
```

Step 2. Tell it to run not1mm:

```
uvx not1mm@latest
```

or install it:

```
uv tool install not1mm@latest
```

That's it... It will go out, fetch the latest version of not1mm, setup a python virtual environment, get all the needed python libraries, cache everything and run not1mm. The first time takes a minute, but each time after, it's lightning quick and it will automatically check for updates and run the latest version.

But wait... There's more. If your distro is old and you're stuck with an older version of python... Say 3.10. And you want to see what all the cool kids are using. But you don't want to corrupt your broke ol' system by downloading the newest Python version. No problem. You can tell uv to run not1mm with any version of Python you'd like. Let's say 3.14.

```
uvx --python 3.14 not1mm@latest
```

It'll download Python 3.14 into your virtual environment and run not1mm. Let's say I was an idiot and pushed a new version and didn't fully test it. This happens a-lot... We test in production. Or lets say you just want to see the pain that was back in 2023. No problem. Just tell it which version of not1mm you'd like to run.

```
uvx --python 3.10 not1mm==23.5.19
```

Pow! Enjoy the pain...

## 4 After the Install

You can now open a new terminal and type 'not1mm'. On it's first run, it may or may not install a lovely non AI generated icon, which you can later click on to launch the application.

### 4.1 You May or May Not Get a Warning Message Like

WARNING: The script not1mm is installed in '/home/mbridak/.local/bin', which is not on PATH. Consider adding this directory to PATH or, if you prefer to suppress this warning, use --no-warn-script-location.

If you do, log out and back in or reboot.

### 4.2 Or this Fan Favorite

Warning: Ignoring XDG\SESSION\TYPE=wayland on Gnome.  
Use QT\_QPA\_PLATFORM=wayland to run on Wayland anyway.  
qt.qpa.plugin: Could not load the Qt platform plugin "xcb" even though it was found. This application failed to start because no Qt platform plugin could be initialized.  
Reinstalling the application may fix this problem.

You can use your package manager to load **libxcb-cursor0**.  
If that is not an option, you can export an environment variable and launch the app like this:

```
mbridak@vm:~$ export QT_QPA_PLATFORM=wayland; not1mm
```

For a more permanent solution, you can place the line:

```
export QT_QPA_PLATFORM=wayland
```

in your home directories .bashrc file. Then after logging out and back in you should be able to launch it normally.

### 4.3 Update Your CTY and SCP Files

Before operating in a contest, you might want to update the CTY and SCP files. You can do this by choosing **FILE » Update CTY** and **FILE » Update MASTER.SCP**



## 5 Various Data File Locations

### 5.1 Data

If your system has an ‘XDG\_DATA\_HOME’ environment variable set, the database and CW macro files can be found there. Otherwise they will be found at ‘yourhome/.local/share/not1mm’

### 5.2 Config

Configuration file(s) can be found at the location defined by

XDG\_CONFIG\_HOME

Otherwise they will be found at

yourhome/.config/not1mm

## 6 The Database

### 6.1 Why

The database holds... wait for it... data... I know shocker right. A database can hold one or many contest logs. It also holds the station information, everything shown in the Station Settings dialog. You can have one database for the rest of your life. Filled with hundreds of contests you’ve logged. Or, you can create a new database to hold just one contest. You do You Boo.

### 6.2 The First One is Free

On the initial running, a database is created for you called ‘ham.db’. This, and all future databases, are located in the data directory mentioned above.

### 6.3 Why Limit Yourself

You can create a new database by selecting **File » New Database** from the main window, and give it a snazzy name. Why limit yourself. Hell, create one every day for all I care. You can manage your own digital disaster.

### 6.4 Revisiting an Old Friend

You can select a previously created databases for use by selecting **File » Open Database**.

## 7 Station Settings Dialog

After initial run of the program or creating a new database you will need to fill out the Station Settings dialog that will pop up.

The screenshot shows a 'Settings' dialog box with the following fields and values:

Call	K6GTE		
Name	Michael Bridak		
Address	2854 W Bridgeport Ave.		
Address			
City	Anaheim	State	CA
		Zip	92804
Country	United States		
Grid Square	Dm13at	CQ Zone	3
		ITU Zone	6
License	General	Latitude	33.8125
		Longitude	-117.9583
Station TX/RX		Power	
Antenna		Ant. Height	a.s.l.
ARRL Section	ORG		
Rover QTH			
Club	Americal Radio Relay League		
Email address	michael.bridak@gmail.com		

Buttons: Cancel, OK

You can fill it out if you want to. You can leave our friends behind 'Cause your friends don't fill, and if they don't fill. Well, they're no friends of mine.

You can fill. You can fill. Everyone look at your keys. *You had to be around in the 80's*

### 7.1 Changing Station Information

Station information can be changed any time by going to **File » Station Settings** and editing the information.

## 8 Selecting a Contest

### 8.1 Selecting a New Contest

Select **File » New Contest**

**New Contest**

Select Contest Type for New Log

Log Type: CQ WPX CW

Start UTC: 2023-05-27 00:00:00

Operator: SINGLE-OP

Band: ALL

Power: LOW

Mode: CW

Overlay: N/A

Station: FIXED

Assisted: ASSISTED

Transmitter: ONE

Sent Exchange: # ☐ Exclude RST

Operators: K6GTE

Soapbox

Cancel OK

## 8.2 Selecting an Existing Contest as the Current Contest

Select **File » Open Contest**

**Choose a Contest**

Contest Name	Contest Start
cq_wpx_cw	2023-05-27 00:00:00
cq_wpx_ssb	2023-03-25 00:00:00

Cancel OK


## 8.3 Editing Existing Contest Parameters

You can edit the parameters of a previously defined contest by selecting it as the current contest. Then select **File » Edit Current Contest**. Click ‘OK’ to save the new values and reload the contest. ‘Cancel’ to keep the existing parameters.

## 9 Configuration Settings

To setup your CAT control, CW keyer, Callsign lookups, select **File » Configuration Settings**

The tabs for groups and N1MM are disabled and are for future expansion.



### 9.1 Lookup

For callsign lookup, Two services are supported. QRZ and HamQTH. They require a username and password, Enter it here.

### 9.2 Soundcard

Choose the sound output device for the voice keyer.


### 9.3 CAT Control

Under the 'CAT' TAB, you can choose either 'rigctlld' normally with an IP of '127.0.0.1' and a port of '4532'. Or 'flrig', IP normally of '127.0.0.1' and a port of '12345'. 'None' is always an option, but is it really? There's an onscreen icon for CAT status. Green good, Red bad, Grey neither.

### 9.4 CW Keyer Interface

Under the 'CW' TAB, There are three options. 'cwdaemon', which normally uses IP '127.0.0.1' port '6789'. 'pywinkeyer' which normally uses IP '127.0.0.1' port '8000' and 'CAT' which if your radio supports it, sends Morse characters via rigctlld.

## 9.5 Cluster



Under the 'Cluster' TAB you can change the default AR Cluster server, port and filter settings used for the bandmap window.

## 9.6 N1MM Packets

Work has started on N1MM UDP packets. So far just RadioInfo, contactinfo, contactreplace and contact-delete.

Configuration Settings

Lookup Sound CAT CW Cluster Group **N1MM** Bands

☒ Send N1MM packets

Station Name: 20M CW Tent Operator Name: Bernie

Radio: ☒ 127.0.0.1:12060

Contact: ☒ 127.0.0.1:12060

Lookup: ☐ 127.0.0.1:12060

Score: ☐ 127.0.0.1:12060

When entering IP and Ports, enter them with a colon ':' between them. You can enter multiple pairs on the same line if separated by a space ' '.

## 9.7 Bands

You can define which bands appear in the main window. Those with checkmarks will appear. Those without will not.

Configuration Settings

Lookup Sound CAT CW Cluster Group N1MM **Bands**

<input type="checkbox"/> 160M	<input checked="" type="checkbox"/> 6M
<input type="checkbox"/> 80M	<input checked="" type="checkbox"/> 2M
<input type="checkbox"/> 40M	<input checked="" type="checkbox"/> 1.25M
<input type="checkbox"/> 20M	<input checked="" type="checkbox"/> 70cm
<input type="checkbox"/> 15M	<input checked="" type="checkbox"/> 33cm
<input type="checkbox"/> 10M	<input checked="" type="checkbox"/> 23cm

## 9.8 Options

On the Options TAB you can:

- Select to use Enter Sends Message (ESM), and configure it's function keys.
- Select whether or not to use Call History info.
- Select whether or not to send XML score info to online scoreboards.
- Select whether or not to clear input fields when you QSY while in S&P mode.

The screenshot shows a software window titled "Configuration Settings" with a dark theme. It has several tabs: "Lookup", "Sound", "CAT", "CW", "Cluster", "N1MM", "Bands", and "Options" (which is selected and highlighted with a blue border). The "Options" tab contains the following settings:

- ☒ Enable ESM
- ☒ Use Call History
- ☒ Use RTC score reporting
- CQ: F1 (dropdown)
- His Call: F2 (dropdown)
- Exchange: F3 (dropdown)
- AGN: F9 (dropdown)
- My Call: F5 (dropdown)
- QRZ: F4 (dropdown)
- QS0 B4: DISABLED (dropdown)
- URL: <https://hamscore.com/postxml/> (dropdown)
- Keyer: k6gte (text field)
- Score posting interval (minutes): 2 (text field)

At the bottom of the dialog are two buttons: "Save" (with a floppy disk icon) and "Cancel" (with a close icon).


Three realtime score boards are supported:

- Real Time Contest Server at [hamscore.com](https://hamscore.com)
- Contest Online ScoreBoard at [contestonlinescore.com](https://contestonlinescore.com)
- iveScore at [contest.run](https://contest.run)

## 10 Logging Digital Contacts

Not1MM listens for WSJT-X UDP traffic on the Multicast address 224.0.0.1:2237. No setup is needed to be done on Not1MM's side. That's good because I'm lazy.

Not1MM watches for fldigi qso's by watching for UDP traffic from fldigi on 127.0.0.1:9876.




The F1-F12 function keys are sent to fldigi via XMLRPC. Fldigi will be placed into TX mode, the message will be sent and a ^r will be tacked onto the end to place it back into RX mode.

Unlike WSJT, fldigi needs to be setup for this to work. The XMLRPC interface needs to be active. And in fldigi's config dialog, go to **CONTESTS » General » CONTEST** and select Generic Contest. Make sure the Text Capture Order field says CALL EXCHANGE.



## 11 Operating Multi Multi

Work is underway on Multi Multi contest operations. There is a companion project **renfield** <https://github.com/mbridak/renfield> that will be needed for this. The idea is to have a separate slave server running, preferably, on another computer that's on the same network as the contesting PC's. This server will handle all the database CRUD operations. It will also handle the functions of handing out serial numbers and checking of a contact is a dupe. In the end, generating a Cabrillo file.




This is a very lightweight terminal application and can be easily hosted on a Raspberry Pi or similar device. In a pinch it can be run along side Not1MM on one of the contesting machines. Tho I'd think twice about that.

You could even use this while operating alone as an automated backup. So in case your logging computer should fail, you'd have a copy of the contest log.

### 11.1 Network Settings for Multi Multi

In the configuration dialog under the group tab, select Connect to server.



One computer needs to be the master station. The master station will tell the renfield server what contest is being run.

## 11.2 Contest Settings for Multi Multi

For the settings of the contest, if the Operator is set to "MULTI-OP" and the Transmitter category is not "ONE" or "SWL" Not1MM will ask the renfield server for serial numbers and dupe checks.

Log Type	HELVETIA
Start UTC	2025-09-28 00:00:00
Operator	MULTI-OP
Band	ALL
Power	LOW
Mode	CW
Overlay	N/A
Station	FIXED
Assisted	ASSISTED
Transmitter	UNLIMITED
Sent Exchange	#
	Exclude RST


## 12 Sending CW

### 12.1 Sending CW Macros

Other than sending CW by hand, you can also send predefined CW text messages by pressing F1 - F12. See next section on Editing macro keys.

### 12.2 Auto CQ

If you press 'SHIFT-F1' The Auto CQ mode will be activated, you will be placed in a Run state and the F1 macro will be resent after each Auto CQ Delay interval has passed. An indicator will appear to the upper left of the F1 macro key as a visual reminder that your Auto CQ is active. With it to the right, you will see a small progress bar giving you a visual indication as to when F1 will fire next.



#### 12.2.1 Setting the delay

The delay can be changed by going to the 'Options' TAB in the Configuration dialog. If you are in S&P mode when you enable Auto CQ, you will be automatically switched into RUN mode. To properly set the delay you should time how long your F1 macro takes to key, then add how many seconds of pause you would like. This is your delay value.

### 12.3 Sending CW Free Form

If you need to send something freeform, you can press **CTRL-SHIFT-K**, this will expose an entry field at the bottom of the window which you can type directly into. When you're done you can either press **CTRL-SHIFT-K** again, or press the Enter Key to close the field.

## 13 Editing Macro Keys

To edit the macros, choose **File » Edit Macros**. This will open your systems registered text editor with current macros loaded. When your done just save the file and close the editor. The file loaded to edit, CW, SSB or RTTY, will be determined by your current operating mode and contest. Each contest gets it's own copy of the macros.

After editing and saving the macro file. You can force the logger to reload the macro file by toggeling between 'Run' and 'S&P' states.

### 13.1 Macro Substitutions

You can include a limited set of substitution instructions.

Macro	Substitution
{MYCALL}	Sends the station call.
{HISCALL}	Send what's in the callsign field.
{SNT}	Sends 5nn (cw) or 599 (ssb)
{SENTNR}	Sends whats in the SentNR field.
{EXCH}	Sends what's in the Sent Exchange field when contest is defined.
{PREVNR}	Sends the previous serial number.
{OTHER1}	Sends whats in the SentNR/Name field without altering it.
{OTHER2}	Sends whats in the Comment field without altering it.
{LOGIT}	Log the contact after macro pressed.
{TX}	Switch to transmit mode (PTT ON) - NOTE: the 'Sends' macros perform their own PTT ON/OFF
{RX}	Switch to receive mode (PTT OFF).
{TX/RX}	Toggle between transmit/receive (PTT) mode.
{MARK}	Mark the current call in the bandmap.
{SPOT}	Spot the current call to the cluster.
{RUN}	Change to Run mode.
{SANDP}	Change to S&P mode.
{WIPE}	Wipe input fields.
#	Sends serial number.
{VOICE1} - {VOICE10}	Uses rigctlD to send voice macros stored in the radio.
RI:	Send Rig specific codes. See Macro control of radio functions.
^M	in a RTTY macro will be replaced with a newline character.

### 13.2 Macro Use with Voice

#### VOICE1 - VOICE10

If you use rigctlD and your radio supports it you can use the macros VOICE1, VOICE2 etc to send the voice messages stored in your radio.

#### 13.2.1 Voice macro wave files

The macros when used with voice, will also accept filenames of WAV files to play, excluding the file extension. The filename must be enclosed by brackets. For example '[CQ]' will play 'cq.wav', '[again]' will play 'again.wav'. The wav files are stored in the operators personal data directory. The filenames must be in lowercase. See **Various data file locations** above for the location of your data files. For me, the macro '[cq]' will play

```
/home/mbridak/.local/share/not1mm/K6GTE/cq.wav
```

**The current wav files in place are not the ones you will want to use. They sound like an idiot.** You can use something like Audacity to record new wav files in your own voice.

Aside from the '[filename]' wav files, there are also NATO phonetic wav files for each letter and number. So if your macro key holds 'HISCALL SNT SENTNR' and you have entered K5TUX in callsign field during CQ WW SSB while in CQ Zone 3. You'll here Kilo 5 Tango Uniform X-ray, 5 9 9, 3. Hopefully not in an idiots voice.

### **13.2.2 Macro control of radio functions**


Macros can also be used to send CAT/CI-V control codes to your radio. To make use of this feature, start your command with the letters "RI" and a colon, followed by the command you would like to send. If your command is ASCII text (for example, for Yaesu radios), just enter the text after "RI:". For binary codes, enter hexadecimal values separated by spaces.

For example, to enable the auto-notch filter on a Yaesu FT-710, your command would be "RI:BC01;". To do the same on an Icom 7300, your command would be something like "RI:FE FE 94 E0 16 41 01 FD". Please refer to your radio's manual or online sources to determine the commands you need.

Please note that CAT/CI-V command macros are only available if you are using either FLRig or rigctld (HamLib) for rig control.


## 14 ctz.dat and QRZ for Distance and Bearing

When a callsign is entered, a look up is first done in a ctz.dat file to determine the country of origin, geographic center, cq zone and ITU region. Great circle calculations are done to determine the heading and distance from your gridsquare to the geographic center. This information then displayed at the bottom left.



Regional Hdg 176° LP 356° / distance 9937mi 15993km  
G: EU/England cq:14 itu:27

After this, a request is made to QRZ for the gridsquare of the callsign. If there is a response the information is recalculated and displayed. You'll know this has happened, since the gridsquare will replace the word "Regional".



I091vI Hdg 178° LP 358° / distance 9848mi 15850km  
G: EU/England cq:14 itu:27

## 15 Other Uses for the Call Field


You must press the SPACE bar after entering any of the below.

- **Frequency** You can enter a frequency in kilohertz. This will change the band you're logging on. If you have CAT control, this will change the frequency of the radio as well.
- **CW, SSB, RTTY** You can set the mode logged. If you have CAT control this will also change the mode on the radio.
- **OPON** Change the operator currently logging.

You must press the SPACE bar after entering any of the above.

## 16 The Windows

### 16.1 The Main Window



### 16.1.1 Keyboard Commands

Key	Result
Esc	Stops cwdaemon from sending Morse.
PgUp	Increases the cw sending speed.
PgDown	Decreases the cw sending speed.
Arrow-Up	Jump to the next spot above the current VFO cursor in the bandmap window (CAT Required).
Arrow-Down	Jump to the next spot below the current VFO cursor in the bandmap window (CAT Required).
TAB	Move cursor to the right one field.
Shift-Tab	Move cursor left One field.
SPACE	When in the callsign field, will move the input to the first field needed for the exchange.
Enter	Submits the fields to the log. Unless ESM is enabled.
F1-F12	Send (CW/RTTY/Voice) macros.
CTRL-S	Spot Callsign to the cluster.
CTRL-M	Mark Callsign to the bandmap window to work later.
CTRL-G	Tune to a spot matching partial text in the callsign entry field (CAT Required).
CTRL-SHIFT-K	Open CW text input field.
CTRL-=	Log the contact without sending the ESM macros.
CTRL-W	Clears the input fields of any text.
ALT-B	Toggles the BandMap window.
ALT-C	Toggles the Check Partial window.
ALT-L	Toggles the QSO Log window.
ALT-R	Toggles the Rate window.
ALT-S	Toggles the Statistics window.
ALT-V	Toggles the VFO window.

## 16.2 The Log Window

### Window » Log Window

The Log display gets updated automatically when a contact is entered. The top half is a list of all contacts.



Log Display											x	
YYYY-MM-DD HH:MM:SS	Call	Freq	Snt	Rcv	M1	ZN	M2	PFX	PTS			
2023-03-17 13:39:03	K5TUX	14032.25	599	599	4		K5	0				
2023-03-17 14:14:23	W1AW	14032.25	599	599	5		W1	0				
2023-03-17 14:37:00	C0FEE	14032.25	599	599	0		C0	0				
2023-03-17 16:47:09	W1AW	14032.25	599	599	5		W1	0				
2023-03-17 16:56:55	W2AW	14032.25	599	599	5		W2	0				
YYYY-MM-DD HH:MM:SS	Call	Freq	Snt	Rcv	M1	ZN	M2	PFX	PTS			
2023-03-10 20:10:38	K6GTE	14230.2	59	59	3		K6	0				
2023-03-15 14:23:45	K6GTE	14062.0	59	59	3		K6	0				

The bottom half of the log displays contacts sorted by what's currently in the call entry field. The columns displayed in the log window are dependent on what contests is currently active.

### 16.2.1 Editing a Contact

W	14032.25	599	5
Call	Freq	Snt	
W	14062.0		5

You can double click a cell in the log window and edit its contents. You can also Right-Click on a cell to bring up the edit dialog.

Edit Contact

Call

G0UPL

TimeStamp

2023-03-23 18:50:23

Rx

14250.0

Tx Freq

14250.0

Mode

USB

Contest

CQ-WPX-SSB

RST Sent

59

RST RCV

59

Country

G

Station Call

K6GTE

Name

QTH

Comment

Nr

143

Nr Sent

2

Points

3

Power

0

Zone

14

Section

Mult

☒

Band

14

Check

0

Prec

Mult

☐

WPX

G0

Exchange

Run 1/2

Mult

☐

Radio

Grid

Op

K6GTE

Misc

Rover QTH

Delete

Cancel

OK


You can not directly edit the multiplier status of a contact. Instead, see the next section on recalculating mults. If you change the callsign make sure the WPX field is still valid.

## 16.3 The Bandmap Window


### Window » Bandmap

Put your callsign in the top and press the connect button.

The bandmap window is, as with everything, a work in progress. The bandmap now follows the VFO.



VFO indicator now displays as a small triangle in the frequency tick marks. A small blue rectangle shows the reported receiver bandwidth if one is reported.



Clicked on spots now tune the radio and set the callsign field.

Previously worked calls are shown in red.

Callsigns that were marked with CTRL-M to work later are displayed in a Yellow-ish color.

In between the spots call and time is now a little icon to visually tell you what kind of spot it is.



○ CW

◉ FT\*

◐ RTTY

△ Beacons

@ Everything else

Secondary Icons:

[P] POTA


[S] SOTA

## 16.4 The Check Partial Window

### Window » Check Partial Window

As you enter a callsign, the Check Window will show probable matches to calls either in the MASTER.SCP file, your local log or the recent telnet spots. The MASTER.SCP column will show results for strings of 3 or more matching characters from the start of the call string. The local log and telnet columns will show matches of any length that appear anywhere in the string.

Clicking on any of these items will change the callsign field.




The screenshot shows a window titled "CheckWindow" with a standard macOS-style title bar (minimize, maximize, close buttons). The window contains a table with three columns: "Log", "Master", and "Telnet". The "Log" column contains the text "LW2D0". The "Master" column contains a list of call signs: "LW2DH", "LW2DHD", "LW2DJM", "LW2DLY", "LW2D0", "LW2D0D", "LW2DX", "LW2EDM", "LW2EIY", "LW2EKY", and "LW2HAB". The "Telnet" column contains the text "LW2D0".

Log	Master	Telnet
LW2D0	LW2DH	LW2D0
	LW2DHD	
	LW2DJM	
	LW2DLY	
	LW2D0	
	LW2D0D	
	LW2DX	
	LW2EDM	
	LW2EIY	
	LW2EKY	
	LW2HAB	

## 16.5 The Rate Window

### Window » Rate Window

This window contains QSO rates and counts.




The RateWindow interface displays the following data:

All bands - All modes	
Last Hour:	9.85 Q/h
10 Last QSO:	10.85 Q/h
100 Last QSO:	--- Q/h
Since 19:00:00z:	2 QSO
<hr/>	
Run QSO:	9
S&P QSO:	5
Hour Run QSO:	1
Hour S&P QSO:	1

## 16.6 The DXCC window

### Window » DXCC

This window shows you a grid of DXCC entities you've aquired and on what bands. There is a checkbox to enable this table to be automatically scrolled to the DXCC entity if the call in the callsign entry field if it exists in the table.



The DXCC Tracker window displays the following table:

DXCC	160m	80m	40m	20m	15m	10m	Total
K	0	0	12	25	13	0	50
VE	0	0	2	6	3	0	11
KH6	0	0	0	1	2	3	6
JA	0	0	0	5	1	0	6
XE	0	0	0	2	0	0	2
PY	0	0	0	0	1	1	2
KP4	0	0	1	1	0	0	2

## 16.7 The Zone window


### Window » Zone

This window does what the DXCC window does, but for zones. In addition to the Scroll to checkbox, there are a couple radio buttons to tell it what zone to scroll to CQ Zones or ITU Zones. Make sure they match the contest your running.


## 16.8 The Rotator Window (Work In Progress)

### Window » Rotator


The Rotator window is a work in progress. The Rotator window relies on the functionality of the rotctld daemon. It connects to rotctld on address 127.0.0.1 and port 4533. You can change this if needed in the configuration dialog under the rotator tab. If started and there is no connection, you will see this:



Once there is a connection to rotctld, the current azimuth of the antenna is obtained and you will see a direction needle appear:



Once a call is entered and the bearing to contact is calculated you will see another needle appear:



At this time you can click on the 'Move' button to point your antenna at the contact. A list of other buttons follows below.

**Move:** Rotates the antenna at the target.

**Stop:** Stops the current movement.

**Park:** Parks the antenna.

**N,S,W,E:** Points the antenna to one of the 4 cardinal directions.

You can also move the rotator by clicking in the globe where you want the antenna to point.

## 16.9 The Remote VFO Window

You can control the VFO on a remote rig by following the directions listed in the link below. It is a small hardware project with a BOM of under \$20, and consisting of two parts.

1. Making the VFO

[https://github.com/mbridak/not1mm/blob/master/usb\\\_vfo\\\_knob/vfo.md](https://github.com/mbridak/not1mm/blob/master/usb\_vfo\_knob/vfo.md)

2. Then... **Window » VFO**





## 17 Cabrillo

Click on **File » Generate Cabrillo**

The file will be placed in your home directory. The name will be in the format of:

```
'StationCall'_'ContestName'_'CurrentDate'_'CurrentTime'.log
```

So for me, it would look like:

```
K6GTE\_CANADA-DAY\_2023-09-04\_07-47-05.log
```

## 18 ADIF

**File » Generate ADIF**

Boom... ADIF


```
'StationCall'_'ContestName'_'Date'_'Time'.adi
```

## 19 Recalculate Mults

After editing a contact and before generating a Cabrillo file. There is a Misc menu option that will recalculate the multipliers incase an edit had caused a change.

## 20 ESM

I caved and started working on ESM or Enter Sends Message. To test it out you can go to **FILE » Configuration Settings**



The screenshot shows the 'Configuration Settings' dialog box with the 'Options' tab selected. The 'Enable ESM' checkbox is checked. Below it, several function keys are mapped to specific actions: CQ (F1), His Call (F2), Exchange (F3), AGN (F9), My Call (F5), QRZ (F4), and QS0 B4 (DISABLED). To the right, the 'Use Call History' checkbox is also checked, and 'Use RTC score reporting' is checked. The URL for score reporting is set to 'https://hamscore.com/postxml/'. Below this, the call sign 'k6gte' is entered. A visual representation of the function keys shows that F1 through F5 and F9 are highlighted in green, while F4 and the disabled key are not. The 'Score posting interval (minutes)' is set to 2. At the bottom, there are 'Save' and 'Cancel' buttons.


Function	Key
Enable ESM	<input checked="" type="checkbox"/>
Use Call History	<input checked="" type="checkbox"/>
Use RTC score reporting	<input checked="" type="checkbox"/>
Score reporting URL	https://hamscore.com/postxml/
Call Sign	k6gte
Score posting interval (minutes)	2

Check the mark to Enable ESM and tell it which function keys do what. The keys will need to have the same function in both Run and S&P modes. The function keys will highlight green depending on the state of the input fields. The green keys will be sent if you press the Enter key. You should use the Space bar to move to another field.


The contact will be automatically logged once all the needed info is collected and the QRZ (for Run) or Exchange (for S&P) is sent.

## 20.1 Run States


### 20.1.1 CQ




### 20.1.2 Call Entered Send His Call and the Exchange



### 20.1.3 Empty Exchange Field Send AGN Till You Get It




#### 20.1.4 Exchange Field Filled, Send TU QRZ and Logs it




## 20.2 S&P States


### 20.2.1 With His Call Entered, Send Your Call



### 20.2.2 If No Exchange Entered Send AGN




### 20.2.3 With Exchange Entered, Send Your Exchange and Log it



## 21 Call History Files

To use Call History files, go to **FILE » Configuration Settings**.



The screenshot shows the 'Configuration Settings' dialog box with the 'Options' tab selected. The 'Enable ESM' checkbox is checked. The 'Use Call History' checkbox is also checked. Below it, the 'Use RTC score reporting' checkbox is checked. The 'CQ' field is set to 'F1', 'His Call' to 'F2', 'Exchange' to 'F3', 'AGN' to 'F9', 'My Call' to 'F5', 'QRZ' to 'F4', and 'QS0 B4' to 'DISABLED'. The 'URL' field is set to 'https://hamscore.com/postxml/'. The 'k6gte' field is empty. The 'Score posting interval (minutes)' is set to '2'. The 'Save' and 'Cancel' buttons are at the bottom.

Field	Value
Enable ESM	<input checked="" type="checkbox"/>
Use Call History	<input checked="" type="checkbox"/>
Use RTC score reporting	<input checked="" type="checkbox"/>
CQ	F1
His Call	F2
Exchange	F3
AGN	F9
My Call	F5
QRZ	F4
QS0 B4	DISABLED
URL	https://hamscore.com/postxml/
k6gte	
Score posting interval (minutes)	2

Place a check in the 'Use Call History' box. Call history files are very specific to the contest you are working. Example files can be obtained from <https://n1mmwp.hamdocs.com/mmfiles/categories/callhistory/> website. They have a searchbox so you can find the contest you are looking for. If you are feeling masocistic, you can craft your own. The general makeup of the file is a header defining the fields to be used, followed by lines of comma separated data.


## 22 Creating your own Call History files

You can use **adif2callhistory** at <https://github.com/mbridak/adif2callhistory> to generate your own call history file from your ADIF files. An example file excerpt looks like:

```
!!Order!!,Call,Name,State,UserText,
#
# 0-This is helping file, LOG what is sent.
# 1-Last Edit,2024-08-18
# 2-Send any corrections direct to ve2fk@arrl.net
# 3-Updated from the log of Marsh/KA5M
# 4-Thanks Bjorn SM7IUN for his help.
# 5-Thanks
# NAQPCW
# NAQPRTTY
# NAQPSSB
# SPRINTCW
# SPRINTLADD
# SPRINTNS
# SPRINTRTTY
# SPRINTSSB
AAOAC,DAVE,MN,Example UserText
AAOAI,STEVE,IA,
AAOAO,TOM,MN,
AAOAW,DOUG,MN,
AAOBA,,TN,
AAOBR,,CO,
AAOBW,,MO,
```

The first line is the field definition header. The lines starting with a '#' are comments. Some of the comments are other contests that this file also works with. This is followed by the actual data. If the matched call has 'UserText' information, that user text is populated to the bottom left of the logging window.

So if one were to go to **FILE » LOAD CALL HISTORY FILE** and choose a downloaded call history file for NAQP and typed in the call AA0AC while operating in the NAQP, after pressing space, one would see:



Where the Name and State would auto-populate and the UserText info appears in the bottom left.




## 23 Contest Specific Notes

I found it might be beneficial to have a section devoted to wierd quirky things about operating a specific contests.

### 23.1 ARRL Sweekstakes

#### 23.1.1 The Exchange Parser

This was a pain in the tukus. There are so many elements to the exchange, and one input field aside from the callsign field. So I had to write sort of a 'parser'. The parser moves over your input string following some basic rules and is re-evaluated with each keypress and the parsed result will be displayed in the label over the field. The exchange looks like '124 A K6GTE 17 ORG', a Serial number, Precidence, Callsign, Year Licenced and Section. even though the callsign is given as part of the exchange, the callsign does not have to be entered and is pulled from the callsign field. If the exchange was entered as '124 A 17 ORG' you would see:



You can enter the serial number and precidence, or the year and section as pairs. For instance '124A 17ORG'. This would ensure the values get parsed correctly.

You do not have to go back to correct typing. You can just tack the correct items to the end of the field and the older values will get overwritten. So if you entered '124A 17ORG Q', the precidence will change from A to Q. If you need to change the serial number you must append the precidence to it, '125A'.

If the callsign was entered wrong in the callsign field, you can put the correct callsign some where in the exchange. As long as it shows up in the parsed label above correctly your good.

The best thing you can do is play around with it to see how it behaves.

#### 23.1.2 The Exchange

In the 'Sent Exchange' field of the New Contest dialog put in the Precidence, Call, Check and Section. Example: 'A K6GTE 17 ORG'.

For the Run Exchange macro I'd put 'HISCALL SENTNR EXCH'.

### 23.2 RAEM

In the New/Edit Contest dialog, in the exchange field put just your Lat and Lon. for me 33N117W. And in the exchange macro put '# EXCH'.

### 23.3 RandomGram

This plugin was submitted by @alduhoo. It reads a rg.txt file if it exists in the user's home directory to populate the next group in the sent exchange field.

### 23.4 UKEI DX

For the Run exchange macro I'd put 'SNT # EXCH'

## **23.5 CWO Open Contest**

Note: when completing the "Recd Number and Name" field, place a space between the received serial number and the name of the other operator. eg. "123 Fred". (Advance on spacebar is disabled for this field.)