

Tested in Ubuntu 24.04.

Qemu

Install:

```
$ sudo apt install qemu-system-misc u-boot-qemu
```

List 32-bits supported boards:

```
$ qemu-system-riscv32 --machine help
```

List 64-bits supported boards:

```
$ qemu-system-riscv64 --machine help
```

Download the Ubuntu preinstalled server image:

```
$ wget --continue https://cdimage.ubuntu.com/releases/24.04/release/ubuntu-24.04.1-preinstalled-server-riscv64.img.xz
```

Decompress the image:

```
$ xz --decompress --keep ubuntu-24.04.1-preinstalled-server-riscv64.img.xz
```

Resize the image:

```
$ qemu-img resize -f raw ubuntu-24.04.1-preinstalled-server-riscv64.img +5G
```

Run on the generic virtual platform virt

:

```
$ qemu-system-riscv64 \ -machine virt \ -nographic \ -m 2048 \ -smp 4 \ -kernel /usr/lib/u-boot/qemu-riscv64_smode/u-boot.elf \ -device virtio-net-device,netdev=eth0 \ -netdev user,id=eth0 \ -device virtio-rng-pci \ -drive file=ubuntu-24.04.1-preinstalled-server-riscv64.img,format=raw,if=virtio
```

Log in with user and password ubuntu

.

References

- [RISC-V System emulator — QEMU documentation](#)
- [Running 64- and 32-bit RISC-V Linux on QEMU — RISC-V - Getting Started Guide](#)
- [RISC-V/QEMU - Ubuntu Wiki](#)