

Configuring

[Configuring](#) / [Configuring document processing features](#) / [Working with sample AFP files](#) / [Editing AFP files](#) / [Modifying or deleting AFP Editor definitions](#)
/ Modifying text strings

Modifying text strings

You can modify a string of text that was created with AFP Editor. You cannot modify text in the AFP file itself.

⬇ Note:

- In RICOH Visual Workbench you can display measurement units in inches or millimeters. To change the measurement unit, click [View ⇒ Units](#).

To modify a text string:

1. In RICOH Visual Workbench, open a sample AFP file and the control file that contains the definitions for text strings.
2. Click **Mode ⇒ AFP Editor**.
3. Click **Tools ⇒ Modify Definitions**.
4. Do one of these:
 - Select the text definition that you want to modify and then click **Modify**.
 - Double-click the text definition that you want to modify.
You see the Modify Text String window.
5. **Optional:** On the **Text** tab, type a new name for the text area in the **Text definition name** field, change data in the **Text string data** section, or change the color in the **Color** drop-down list.
To edit the text string, select a line of data and use **Up** or **Down** to change the order of the line or **Remove** to delete the line. You can also add new values. Remember to add blank characters between words if you need to. For example, to change the text string from "Page 1 of 10" to "Page 1 for John Doe":
 1. Press and hold the CTRL key, and then select **of** and **Page Count**.
 2. Click **Remove**.
 3. Type **for** in the **Text** field and click **Add**.
 4. Select a customer index tag from the **Index tag** drop-down list and click **Add**.
You see the edited text string value in the field below the data fields.
6. **Optional:** On the **Font** tab, select one of these:

Core Fonts

From the drop-down lists, select the character set and code page, and, if the font is an outline font, the point size in the Font Information section.

External Fonts

Type a character set and code page pair, a coded font name, or all three. For double-byte character set (DBCS) fonts, use the coded font name only.

⬇ Note:

- If you enter a code page that is part of a DBCS-coded font, you see an error message that suggests you use the coded font name instead.

You see the **Character Set Description** and **Font Resource** fields change for the font you selected. **Font Resource** is "Outline" for core fonts and "Raster" for external fonts.

⬇ Note:

- On your workstation, if the font size does not exist for the color you selected, your display defaults to 12 black, even though the final AFP file will have the correct font and color.
- If the character names do not match between a character set and code page, the job goes into an error state in RICOH ProcessDirector and the printer issues an error. To correct the error, change the character set and code page to a valid pair and process the job again.

7. **Optional:** On the **Position** tab, change the origin (top-left corner), size, and orientation of the text area. Specify the origin and size in inches or millimeters. Decimal values (such as 2.5) are allowed.

⬇ Note:

- If you rotated the AFP file using the **Rotate by 90°** option on the **View** menu, measure the X and Y positions from the top-left corner of the logical page in the unrotated view.

8. Click **OK**.

You see the edited text in the AFP file.

Parent topic: [Modifying or deleting AFP Editor definitions](#)