

## Configuring

[Configuring](#) / [Preparing for job submission](#) / [Preparing to submit batch jobs](#) / [Batching methods](#) / Pages

### Pages

When the batching method is **Pages**, the hot folder or SFTP input device submits one or more PDF files as a group, based on the number of pages in the files that are received by the input device. This method is only valid for PDF files.

The hot folder or SFTP input device examines PDF files as they arrive and determines how many pages they contain. The hot folder or SFTP input device maintains a count of the total number of PDF pages currently in the input device. When the total number of PDF pages matches or exceeds the value set for the **Number of pages to batch** property, the hot folder or SFTP input device submits a group of files.

The PDF file that makes the total number of pages exceed the value set for the **Number of pages to batch** property is only included in the group if the **Exceed pages to batch** property is set to **Yes**. If the **Exceed pages to batch** property is set to **No**, this PDF file remains in the hot folder or SFTP input device as the first set of pages for the next batch.

If a single file contains more pages than the value set for the **Number of pages to batch** property and the **Exceed pages to batch** property is set to **Yes**, the file is submitted for printing, either as a batch with the rest of the PDF files that are waiting to print or as a batch that contains only one file. However, if the **Exceed pages to batch** property is set to **No**, the file cannot be submitted. Processing for the hot folder or SFTP input device stops until that input file is deleted, the value of the **Number of pages to batch** property is increased to at least the number of pages in the file, or the **Exceed pages to batch** property is changed to **Yes** so the file can be submitted.

#### ⬇ Note:

- The **Pages** batching method does not support encrypted or password-protected PDF files. If an encrypted or password-protected PDF file is submitted to a hot folder or SFTP input device that uses the **Pages** batching method, RICOH ProcessDirector issues an error message because it cannot open the file to count the number of pages.

When you use the **Pages** batching method, set these input device properties as indicated:

- **Workflow:** ParentNoPrint
- **Child workflow:** The workflow that is appropriate for the print files in the job.
- **Submit step:** SubmitInputFiles
- **Create .zip file:** If this property is set to **Yes**, all input files that match the value set in the **Data patterns** property are combined as a ZIP file and submitted as a single job. If this value is set to **No**, all input files are submitted as child jobs.
- **Number of pages to batch:** the number of pages that the hot folder or SFTP input device waits to receive before submitting the files as a single group.
- **Exceed pages to batch:** If this property is set to **Yes**, a PDF file that contains enough pages to make the total number of pages in the hot folder or SFTP input device exceed the value set for **Number of pages to batch** property will be submitted with the rest of the files. If this property is set to **No**, this file will remain in the hot folder or SFTP input device as the first set of pages for the next batch.
- **Data patterns:** a pattern that matches PDF file names, such as `.*pdf$` or `.*PDF$`.

Parent topic: [Batching methods](#)