

Managing objects

[Managing system objects](#) / [RICOH ProcessDirector servers](#) / Updating a primary computer host name or IP address

Updating a primary computer host name or IP address

When the host name or IP address of a primary computer changes, you must update RICOH ProcessDirector to recognize the change.

Change the host name or IP address before you update RICOH ProcessDirector.

To update RICOH ProcessDirector:

1. Log in to the primary computer as the root user.

2. Start a command prompt.

3. Enter this command. For *oldhostname*, use the old host name without the domain name:

```
/opt/infoprint/ippd/bin/changeHostname.pl oldhostname
```

The changeHostname utility shuts down RICOH ProcessDirector and updates the files listed here. The path name might be different if you used an install location that is not the default.

- /aiw/aiwl/config/servers.cfg
- /aiw/aiwl/config/communication.cfg
- /home/aiwinst/sqllib/db2nodes.cfg

Then it restarts RICOH ProcessDirector.

Parent topic: [RICOH ProcessDirector servers](#)