

CONFIGURING DHCP SERVER ON CISCO ROUTER IN PACKET TRACER



HANDS-ON LAB

Prepared by: Eng. Joshua IRADUKUNDA

Table of Contents


1. Introduction	1
2. Network Topology Example	1
3. DHCP Configuration Steps on a Cisco Router	2
4. Verifying DHCP Configuration On Router.....	3
5. Common Issues and Troubleshooting.....	5
Summary	6

1. Introduction

Dynamic Host Configuration Protocol (DHCP) is a network management protocol used to automatically assign IP addresses, subnet masks, default gateways, and other network parameters to devices (clients) on a network. This eliminates the need for manual configuration of IP addresses on each device.

In Cisco Packet Tracer, a router can be configured as a DHCP server to provide IP addressing services to PCs and other hosts connected to its interfaces.

2. Network Topology Example



Router: Acts as DHCP Server.

Switch: Connects multiple end devices.

End Devices (PCs/Laptops): DHCP clients that will receive IP addresses dynamically.

3. DHCP Configuration Steps on a Cisco Router

Step 1: Access Router CLI

Open the router in Packet Tracer → Go to CLI tab.

Step 2: Enter Global Configuration Mode

```
Router> enable
Router# configure terminal
```

Step 3: Exclude IP Addresses

Before creating a DHCP pool, you should exclude the IP addresses that should not be assigned to clients (e.g., the router's own interface or reserved addresses).

```
Router(config)# ip dhcp excluded-address 192.168.1.1 192.168.1.10
```

This excludes addresses 192.168.1.1 through 192.168.1.10 from the DHCP pool.

Step 4: Create a DHCP Pool

```
Router(config)# ip dhcp pool LAN-POOL
Router(dhcp-config)# network 192.168.1.0 255.255.255.0
Router(dhcp-config)# default-router 192.168.1.1
Router(dhcp-config)# dns-server 8.8.8.8
Router(dhcp-config)# domain-name example.local
```

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp excluded-address 192.168.1.1 192.168.1.10
Router(config)#ip dhcp pool LAN-POOL
Router(dhcp-config)#network 192.168.1.0 255.255.255.0
Router(dhcp-config)#default-router 192.168.1.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#domain-name example.local
```

Explanation of Commands:

network: Defines the network range and mask for DHCP.

default-router: Specifies the gateway clients will use (usually router's IP).

dns-server: Sets the DNS server (can use public servers like 8.8.8.8).

domain-name: Assigns a domain name to the clients.

Step 5: Configure Router Interface

Router(config)#	interface fastethernet 0/0
Router(config-if)#	ip address 192.168.1.1 255.255.255.0
Router(config-if)#	no shutdown

```
Router(config)#interface fastethernet 0/0
Router(config-if)#ip address 192.168.1.1 255.255.255.0
Router(config-if)#no shutdown
```

4. Verifying DHCP Configuration On Router

Use the following show commands:

```
Router# show running-config

Router# show ip dhcp pool

Router# show ip dhcp binding
```

Explanation:

show running-config → Displays current DHCP configuration.

```
Router#show running-config
```

```
!
ip dhcp excluded-address 192.168.1.1 192.168.1.10
!
ip dhcp pool LAN-POOL
network 192.168.1.0 255.255.255.0
default-router 192.168.1.1
dns-server 8.8.8.8
domain-name example.local
!
```

show ip dhcp pool → Shows details of the created DHCP pool, including total addresses.

```
Router#show ip dhcp pool

Pool LAN-POOL :
Utilization mark (high/low)      : 100 / 0
Subnet size (first/next)         : 0 / 0
Total addresses                   : 254
Leased addresses                  : 3
Excluded addresses                : 1
Pending event                     : none

1 subnet is currently in the pool
Current index    IP address range    Leased/Excluded/Total
192.168.1.1     192.168.1.1 - 192.168.1.254    3 / 1 / 254
```

show ip dhcp binding → Shows IP addresses leased to clients.


```
Router#show ip dhcp binding
IP address      Client-ID/      Lease expiration      Type
                Hardware address
192.168.1.11    00D0.970D.EAC7   --                     Automatic
192.168.1.12    00D0.BC4B.B136   --                     Automatic
192.168.1.13    00D0.58C7.C6BD   --                     Automatic
```

On Client PC

Open the PC Desktop → IP Configuration.


Select DHCP.

The PC should automatically receive an IP address, subnet mask, gateway, and DNS.



Verify by using the command prompt:

ipconfig or ipconfig /all



5. Common Issues and Troubleshooting

Clients not receiving IP → Ensure router interface is up (no shutdown).

Wrong default gateway → Verify correct IP in default-router command.

Overlapping pools → Avoid configuring multiple DHCP pools for the same network.

Excluded addresses missing → Confirm with show running-config.

Summary

- DHCP automates IP address assignment.
- Cisco router in Packet Tracer can act as a DHCP server.
- Key steps include excluding addresses, creating a DHCP pool, and verifying.
- Always check with show commands to confirm functionality.

End.