

[FOS] Room Indicator setting

- Overview
 - Objectives
 - Requirements
 - Expected users
- Description
 - Room Indicator List
 - View indicator details (same design as edit mode)
 - Room Indicator Creation screen
 - Room assigning flow
 - Single assigning
 - Multiple assigning

Overview

Objectives

This screen is used to register specific `room indicator` that can be accessed from the Room management page

Requirements

Feature ID	
F_FO_13_4	ルーム管理で使用するルームインジケータの設定を行う。 Set the room indicator used for room management


Expected users

Same with Room Setting. See `Room setting` in `Role and permission matrix` of [User Authorization - ユーザー認可管理](#)

Description

Room Indicator List

From the sidebar, select フロント設定 > ルームインジケータ (Front settings > Room Indicator)



Room indicator initial screen shows the components below

- Create room indicator button
- List of existing room indicators
 - Select one or many check boxes to see delete button




View indicator details (same design as edit mode)

When a room indicator is clicked, it will always open a screen with room indicator details in edit mode with following components:

- Top bar
 - Indicator name: support all types of characters but no more than 12 characters. Indicator names are unique within a hotel.
 - Indicator type: This is a toggle button between rooms and facilities. It's set to Rooms by default.
 - Display size: Showing the size of the grid below with 3 options
 - 6x10: Default
 - 10x15
 - 15x20
 - However, regardless of the selected displayed size, the actual size in pixels remains the same: 1269x2115 (i.e. each box could be smaller or bigger depending of selected displayed size)

- Button to select multiple boxes: Click this will select all unassigned boxes
- Button to assign multiple rooms: Only available after selected multiple boxes
- A grid with size indicated in top bar:
 - Each box in the grid can be assigned with a room
 - Boxes with assigned rooms will show: (see the assigning flow in next section)
 - Room name
 - Room type abbreviation (ex: S for Single, D for Double)
 - Delete button: Used to unassign room
- Bottom bar
 - Save button: Save the room indicator and return to room indicator list
 - Cancel button: Discard change and return to room indicator list



Room indicator details in edit mode

When Save button is clicked, it should show an alert

✓ Changes have been saved successfully!

変更は正常に保存されました！

If error and indicator name is duplicated,

✗ Indicator name should be unique. Please try again.

インジケータ名は表内で一意である必要があります。もう一度設定してください。

Room Indicator Creation screen

This screen has the same UI design and behavior as Room indicator detail screen.




Empty Registration Screen

Room assigning flow


Single assigning

Each box in room indicator's grid has 3 states: Unassigned (default), Assigning, and Assigned

- To assign a room into an unassigned box, hover and click the box to open room name dropdown.
- Selected room is assigned to the box and no longer displayed in the room name dropdown.
- Assigned box can be unassigned by clicking on Delete button



Unassigned state



Assigned state



- Click the button 複数のボックスを選択 (Select multiple boxes) in the setting panel to select all unassigned boxes
- Selected boxes will be highlighted
- A Room name list will be dropped down from below the Select multiple boxes button.
 - User can select multiple rooms from this room list dropdown
 - Selected rooms are assigned to highlighted boxes (unassigned boxes) in the order of left to right and top to bottom.
 - Assigned boxes will turn to dark cyan



Click on インジケーターを作成 (Create Indicator button) at the bottom the page. The indicator grid will be saved as below or click on Cancel to discard current Indicator page and return to indicator list screen.

ホーム / ルームインジケータ / インジケータの詳細

インジケータの詳細

インジケータ名: インジケータ0

部屋

設備

表示サイズ: 6 x 10

複数のボックスを選択

部屋を選択

ボックスをホバーしてクリックすると部屋が追加できます

		101 S 🗑	102 S 🗑		
			201 D 🗑	202 D 🗑	
	301 S 🗑				

山田 花子

クーポン

ダッシュボード

PMS

宿泊予約

Pricing

設備管理

ゲスト

部屋管理

帳票

総務作業

フロント設定

BO設定

If room indicator is saved, it will show on the indicator list screen