



# **Creating a Connector in AWS from Cloud Manager**

## **Cloud Manager**

Ben Cammett, Julia  
September 01, 2021

This PDF was generated from [https://docs.netapp.com/us-en/occm/task\\_creating\\_connectors\\_aws.html](https://docs.netapp.com/us-en/occm/task_creating_connectors_aws.html) on September 09, 2021. Always check docs.netapp.com for the latest.

# Table of Contents

- Creating a Connector in AWS from Cloud Manager..... 1
  - Setting up AWS permissions to create a Connector ..... 1
  - Creating a Connector in AWS ..... 1

# Creating a Connector in AWS from Cloud Manager

An Account Admin needs to deploy a *Connector* before you can use most Cloud Manager features. [Learn when a Connector is required](#). The Connector enables Cloud Manager to manage resources and processes within your public cloud environment.

This page describes how to create a Connector in AWS directly from Cloud Manager. You also have the option to [create the Connector from the AWS Marketplace](#), or to [download the software and install it on your own host](#).

These steps must be completed by a user who has the Account Admin role. A Workspace Admin can't create a Connector.



When you create your first Cloud Volumes ONTAP working environment, Cloud Manager will prompt you to create a Connector if you don't have one yet.

## Setting up AWS permissions to create a Connector

Before you can deploy a Connector from Cloud Manager, you need to ensure that your AWS account has the correct permissions.

### Steps

1. Download the Connector IAM policy from the following location:

[NetApp Cloud Manager: AWS, Azure, and GCP Policies](#)



For IAM user permissions for Amazon FSx for ONTAP, see [Create an FSx for ONTAP working environment](#).

2. From the AWS IAM console, create your own policy by copying and pasting the text from the Connector IAM policy.
3. Attach the policy that you created in the previous step to the IAM user who will create the Connector from Cloud Manager.

### Result

The AWS user now has the permissions required to create the Connector from Cloud Manager. You'll need to specify AWS access keys for this user when you're prompted by Cloud Manager.

## Creating a Connector in AWS

Cloud Manager enables you to create a Connector in AWS directly from its user interface.

### What you'll need


- An AWS access key and secret key for an IAM user who has the [required permissions](#) to create a Connector.
- A VPC, subnet, and keypair in your AWS region of choice.
- If you don't want Cloud Manager to automatically create an IAM role for the Connector, then you'll need to

create your own [using this policy](#).

These permissions are for the Connector instance. It's a different set of permissions than what's provided in the first bullet above.

## Steps

1. If you're creating your first Working Environment, click **Add Working Environment** and follow the prompts. Otherwise, click the **Connector** drop-down and select **Add Connector**.



2. Choose **Amazon Web Services** as your cloud provider and click **Continue**.

Remember that the Connector must have a network connection to the type of working environment that you're creating and the services that you're planning to enable.

[Learn more about networking requirements for the Connector](#).

3. Follow the steps in the wizard to create the Connector:
  - **Get Ready:** Review what you'll need.
  - **AWS Credentials:** Specify the AWS access key and secret key that meet permissions requirements and then select your region.
  - **Details:** Enter a name for the instance, specify tags, and choose whether you want Cloud Manager to create a new role that has the required permissions, or if you want to select an existing role that you set up with [the required permissions](#).
  - **Network:** Specify a VPC, subnet, and key pair for the instance, choose whether to enable a public IP address, and optionally specify a proxy configuration.
  - **Security Group:** Choose whether to create a new security group or whether to select an existing security group that allows inbound HTTP, HTTPS, and SSH access.



There's no incoming traffic to the Connector, unless you initiate it. HTTP and HTTPS provide access to the [local UI](#), which you'll use in rare circumstances. SSH is only needed if you need to connect to the host for troubleshooting.

- **Review:** Review your selections to verify that your set up is correct.
4. Click **Add**.

The instance should be ready in about 7 minutes. You should stay on the page until the process is complete.

**After you finish**

You need to associate a Connector with workspaces so Workspace Admins can use those Connectors to create Cloud Volumes ONTAP systems. If you only have Account Admins, then associating the Connector with workspaces isn't required. Account Admins have the ability to access all workspaces in Cloud Manager by default. [Learn more](#).

## Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

## Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.