



Chapter 4

NIOS Client DOS APIs

Global Variables	30
UINT8 DosSwitcherActive	30
UINT8 DosWinDebFlag	30
UINT8 DosWinDebKernelFlag	30
UINT8 DosWinStandardMode	30
UINT8 DosWinFlag	31
UINT32 DosVmIdToVmCbTable[MAX_NUM_VM]	31
DosAllocV86Callback	32
DosAMapFlat	34
DosBeginNestExec	35
DosBeginNestExecWithCrs	36
DosBeginReentrantExec	37
DosBeginUseDos	38
DosCancelDosAvailEvent	39
DosCall	40
DosCallC	41
DosCallUseCurrSDA	42
DosCallWhenV86IntReturns	43
DosCallWithDTA	45
DosClose	47
DosCMapFlat	48
DosConvGetInfo	49
DosConvMemAlloc	50
DosConvMemFree	53
DosCreate	54
DosDelete	56
DosDeRegisterUserCmd	57
DosDeRegisterV86Int2F	58
DosDoesFileExist	59
DosEndNestExec	60
DosEndNestExecWithCrs	61
DosEndReentrantExec	62
DosEndUseDos	63
DosEnumerateUserCmds	64
DosExecuteFarRet	65

DosExecuteIRet	66
DosExecutePop	67
DosExecutePush	68
DosExecuteV86FarCall	69
DosExecuteV86Int	70
DosFlush	71
DosFastExecuteFarRet	72
DosFastExecutePop	73
DosFastExecutePush	74
DosFreeV86Callback	75
DosGetCurrVmHandle	76
DosGetExeContext	77
DosGetFileSize	78
DosGetNextVmHandle	79
DosHookExceptionInterrupt	80
DosHookPMInterrupt	82
DosHookV86Interrupt	84
DosIsDosBusy	86
DosOpen	87
DosRead	88
DosRegisterUserCmd	90
DosRegisterV86Int2F	92
DosRename	94
DosScheduleDosAvailEvent	95
DosSearchForFile	97
DosSeek	98
DosSharedBufAlloc	100
DosSharedBufFree	102
DosSharedBufGetInfo	103
DosUnHookExceptionInterrupt	104
DosUnHookPMInterrupt	105
DosUnHookV86Interrupt	106
DosVid16DeregisterGuiCB	107
DosVid16RegisterGuiCB	109
DosVidCallWhenPopupOk	111
DosVidCheckKey	112
DosVidCursorSet	113
DosVidEmptyTypeAhead	114
DosVidGetKey	115
DosVidGetPopupInfo	116
DosVidIsPopupOk	117
DosVidPopup	119
DosVidPopupExt	121
DosVidRestoreScreen	124
DosVidSaveScreen	125
DosVidSoundBell	127
DosVidStdOut	128
DosVidWriteToPopup	129
DosWrite	131
Win16GetProcAddress	133

WinCallWhenPMIntReturns	134
WinHookPMInt21	136
WinUnHookPMInt21	138

Global Variables

UINT8 DosSwitcherActive

`#include <tasksw.h>`

Global variable set to a non-zero value when a DOS task switcher is active in the system. Possible values are:

- 0 No Task Switcher Active
- 1 Task Switcher Is Active

UINT8 DosWinDebFlag

`#include <dosvmm.h>`

Global variable set to a non-zero value if MS Windows is active and a debugger compatible with MS Windows is loaded.

UINT8 DosWinDebKernelFlag

`#include <dosvmm.h>`

Global variable set to a non-zero value if Windows is active and the debug version of the Windows VMM is loaded.

UINT8 DosWinStandardMode

`#include <tasksw.h>`

Global variable set to a value of 1 if standard-mode Windows is active. The value is zero otherwise.

UINT8 DosWinFlag

```
#include <dosvmm.h>
```

Global variable set to a nonzero value when enhanced-mode MS Windows is active. Possible values are:

```
DOSWINFLAG_DOS_ONLY      equ 0 ; Only DOS is active
DOSWINFLAG_WIN_31x       equ 1 ; Windows v3.1x is active
DOSWINFLAG_WIN_4x        equ 2 ; Windows v4.x is active
```

UINT32 DosVmIdToVmCbTable[MAX_NUM_VM]

```
#include <dosvmm.h>
```

Global table that can be used to translate a VM ID into its associated VM Control Block value.

Since an NLM should not save a VM's control block address long term, it must instead save the VM's Id. This table assists in translating the VM Id into the VM's control block.

0xFFFFFFFF is returned for entries that are *not* in use.

DosAllocV86Callback

Description

DosAllocV86Callback allocates to the caller a V86 callback address. This seg:off address can be used by V86 code to make requests to Ring-0 modules.

Syntax

```
#include <dosvmm.h>

UINT32
DosAllocV86Callback
    (modHandle    moduleHandle,
     UINT32       referenceData,
     void         (*handler)(void));
```

Parameters

moduleHandle Caller's module handle.

referenceData Value passed to callback handler when the V86 callback is invoked.

handler Pointer to Ring-0 procedure that is invoked when the allocated V86 callback is called. **The handler must execute (simulate) a V86 retf instruction before returning from its handler.**

Entry and exit conditions for this handler are:

On entry:

- ebx -> VM CB
- ebp -> CRS
- edx reference data
- CLD has been executed
- Interrupts are disabled in DOS only
- Interrupts are enabled if MS Windows is active

On return:

- CLD preserved
- All registers can be destroyed
- Interrupts in any state

Returns

!0 V86 Seg:Off address

0 All V86 callback resources are in use

Remarks The value passed in *referenceData* can be anything the caller desires, or can be ignored if not needed.

See Also DosFreeV86Callback
 DosExecuteFarRet
 DosFastExecuteFarRet

DosAMapFlat

Description	DosAMapFlat converts a <i>selector:offset</i> to its flat linear address.
Assumes	<i>eax</i> High word = Selector Low word = Offset
Returns	<i>eax</i> Linear address All other registers are preserved
Remarks	The selector can be either an LDT or a GDT. Passed-in LDT selectors must exist in the active LDT.
See Also	DosCMapFlat

DosBeginNestExec

Description	This function allocates a new <i>ClientRegStruc</i> from the current stack and initializes it for nested execution.
Assumes	Interrupt state undefined
Returns	<i>ebp</i> Pointer to CRS to use during nested execution <i>eax</i> Destroyed All other registers preserved Interrupts same as entered
Remarks	<p>This function is callable at interrupt time if MS Windows is NOT running. V86 code is NOT callable at interrupt time under Windows.</p> <p>This service is designed to be called from assembly code. Use DosBeginNestExecWithCrs if calling from 'C' code.</p> <p>NLMs that wish to call code in V86 mode usually use the DosExecuteV86FarCall or DosExecuteV86Int services. These services require the NLM to enter a nested execution block prior to calling them.</p> <p>The caller must not make any assumptions about where the returned CRS is actually located.</p> <p>Note: The caller must explicitly set the interrupt enable flag to the desired value in the new <i>CrsEFlags</i> field prior to invoking V86 code, since the new <i>CrsEFlags</i> are inherited from the active <i>CrsEFlags</i> at the time this function is invoked.</p>
See Also	DosEndNestExec DosBeginNestExecWithCrs DosEndNestExecWithCrs

DosBeginNestExecWithCrs

Description	This function initializes the passed-in CRS and prepares the system for nested V86 execution.
Syntax	<pre>#include <dosvmm.h> CRS *DosBeginNestExecWithCrs(CRS *saveCrsBuf);</pre>
Parameters	<i>saveCrsBuf</i> Pointer to a CRS structure used to preserve the current CRS information. The caller should not interpret any information in this structure after invoking this service.
Returns	Pointer to CRS to use during nested execution. All register values except CrsSS,CrsSP are undefined in this structure.
Remarks	<p>This function is callable at interrupt time if MS Windows isn't running.</p> <p>The returned CRS pointer may be different than the passed in CRS structure; therefore the caller must use the returned value when setting up the registers for V86 execution.</p> <p>If the caller needs the original CRS register values during the nested execution block, it should preserve the active CRS register values into a work buffer prior to invoking this service.</p>
See Also	DosEndNestExecWithCrs DosBeginNestExec DosEndNestExec

DosBeginReentrantExec

Description	Used in special cases where an NLM needs to invoke a service that normally isn't callable at hardware interrupt time.
Syntax	<pre>#include <dosvmm.h> UNIT32 DosBeginReentrantExec(void);</pre>
Parameters	None
Returns	Previous reentrancy level.
Remarks	Although this service will allow a foreground only function to be called, it may causes corruption or other problems since the routine being called may be reentered.
See Also	DosEndReentrantExec

DosBeginUseDos

Description	This function hooks Control-C, Control-Break, and Interrupt 24h vectors in the current VM with handlers that effectively cause these interrupts to be ignored.	
Syntax	<pre>#include <dosvmm.h> void DosBeginUseDos(UINT32 *savedVectInfo);</pre>	
Parameters	<i>savedVectInfo</i>	Pointer to an array of three UINT32's that will be used to save the current INT 1Bh, INT 23h, and INT 24h vector information. The caller must pass this same buffer to DosEndUseDos when finished with the execution block.
Returns	Nothing Interrupts same as entered	
Remarks	DosBeginUseDos is usually used to bracket code that will be calling DOS using DosExecuteV86Int for which the caller wants to protect itself from abort conditions. Users of the DosCall, DosCallC, and/or DosCallUseCurrSDA services do not need to use this function.	
See Also	DosEndUseDos	

DosCancelDosAvailEvent

Description Cancels a "DOS available event" that was previously scheduled using *DosScheduleDosAvailEvent*.

Syntax

```
#include <dosvmm.h>

UINT32
DosCancelDosAvailEvent(
    FEB    *eventBlock);
```

Parameters

eventBlock Pointer to a FEBStruc that was passed to *DosScheduleDosAvailEvent*

Returns

0 Event was cancelled successfully
 !0 Event is NOT currently scheduled

Remarks

See Also

DosCall

Description	DosCall executes the specified DOS function.
Assumes	<code>ebp</code> Points to CRS with regs set appropriate for DOS function Interrupts in any state
Returns	Carry flag equal to CRS carry flag <code>ebp</code> Points to CRS All registers preserved Interrupts same as entered
Remarks	<p>Generally it is easier to use this function than executing the Int 21h using the DosExecuteV86Int function, since this function takes care of many of the issues related to calling DOS from an NLM, such as setting up NIOS's PSP, failing critical errors, and disabling Control-Break.</p> <p>This function cannot be used if DOS is busy, unless the caller has preserved DOS's data areas prior to invoking this function. Because DOS is never busy inside an NLM's initialization and unload function, this function can be used without restriction in these two cases.</p> <p>The caller must set up a nested execution ClientRegStruc prior to calling this function. Also, the caller must set the CRS register values appropriately for the DOS call that will be invoked.</p> <p>This function yields control.</p>
See Also	DosCallC DosCallUseCurrSDA

DosCallC

Description	"C" wrapper for the DosCall service.
Syntax	<pre>#include <dosvmm.h> UINT32 DosCallC(void);</pre>
Returns	<p>0 Carry flag is 0 (DOS function successful)</p> <p>!0 Carry flag is 1 (DOS function failed)</p> <p>Interrupts same as entered</p>
Remarks	<p>Executes the specified DOS function. Generally it is easier to use this function than executing the Int 21h using the DosExecuteV86Int function, since this function takes care of many of the issues related to calling DOS from an NLM, such as setting up NIOS's PSP, failing critical errors, and disabling Control-Break.</p> <p>This function cannot be used if DOS is busy unless the caller has preserved DOS's data areas prior to invoking this function. Because DOS is never busy inside of an NLM's initialization and unload functions, this function, in the context of a DosScheduleDosAvailEvent, can be used without restrictions in these two cases.</p> <p>The caller must set up a nested execution <i>ClientRegStruc</i> prior to calling this function. Also, the caller must set the CRS register values appropriate for the DOS call that will be invoked.</p> <p>This function yields control.</p>
See Also	<p>DosCall</p> <p>DosCallUseCurrSDA</p> <p>DosCallWithDTA</p>

DosCallUseCurrSDA

Description	Executes the specified DOS function.
Syntax	<pre>#include <dosvmm.h> UINT32 DosCallUseCurrSDA(void);</pre>
Returns	<p>0 Carry flag is 0 (DOS function successful) !0 Carry flag is 1 (DOS function failed) Interrupts same as entered</p>
Remarks	<p>This function is the same as DosCallC except that the current DOS Swappable Data Area (SDA) information is used instead of swapping NIOS's SDA information in.</p> <p>Generally it is easier to use this function than to execute the Int 21h using the DosExecuteV86Int function, since this function takes care of many of the issues related to calling DOS from an NLM, such as failing critical errors, and disabling Control-Break.</p> <p>This function cannot be used if DOS is busy unless the caller has preserved DOS's data areas prior to invoking this function. DOS is never busy inside of an NLM's initialization and unload functions; therefore this function can be used without restrictions in these two cases.</p> <p>The caller must set up a nested execution ClientRegStruc prior to calling this function. In addition the caller must set the CRS register values appropriate for the DOS call that will be invoked.</p> <p>This function yields control.</p>
See Also	<p>DosCall DosCallC</p>

DosCallWhenV86IntReturns

Description This service can be used in an NLM's V86 interrupt handler to obtain control on the back end of a current V86 interrupt.

Assumes *edx* Reference data
 Interrupts in any state
esi Points to callback handler. Called as follows:

On entry:
 ebx -> VM CB
 edx Reference data
 ebp -> CRS
 Interrupts are disabled if DOS only case
 Interrupts are enabled if MS Windows is active
 CLD has been executed

On return:
 CLD preserved
 Interrupt state undefined
 All registers can be destroyed

Returns Z flag cleared
 Interrupt state preserved.
 All registers preserved.
 Nothing.

Remarks This function is callable at interrupt time if MS Windows isn't running.

An NLM that uses this service must first call this service, then return from its V86 interrupt handler signalling that the interrupt was NOT consumed. This service is designed so that the NLM's interrupt handler can simply jump to this service and this service will return back from the handler with the Z flag cleared.

This service places a callback address on the current V86 stack such that when the V86 interrupt handling code ired's out of the interrupt, NLM handlers that have used this service will receive control. This occurs in a LIFO manner, thus preserving the ordering that should occur when multiple NLMs hook the back end of the same V86 interrupt.

When the handler is invoked, the current CrsCS, CrsIP, and CrsFlags will hold the current ired information. If the handler needs to modify the return flags it should do so by modifying the CrsFlags field.

See Also

DosCallWithDTA

Description	Makes DOS functions calls that use the Disk Transfer Area.	
Syntax	<pre>#include<dosvmm.h> UINT32 DosCallWithDTA(UINT8 *nlmDTA);</pre>	
Parameters	<i>nlmDTA</i>	Pointer to 128-byte DTA buffer that will be used as the active DTA prior to invoking the DOS function and will receive a copy of the DTA information after the DOS function completes.
Returns	Zero Non-zero	Carry flag is zero (DOS function successful). Carry flag is one (DOS function failed)
	Interrupts same as at entry.	
Remarks	<p>Examples of DOS functions calls that use the DTA are: DOS find first and DOS find next.</p> <p>Executes the specified DOS function. Generally it is easier to use this function than executing the Int 21h using the DosExecuteV86Int function since this function takes care of many of the issues related to calling DOS from an NLM, such as setting up Nios's PSP, failing critical errors, and disabling Control-Break, etc.</p> <p>This function cannot be used if DOS is busy unless the caller has preserved DOS's data areas prior to invoking this function. DOS is never busy inside of an NLM's initialization and unload functions, and in the context of a DosScheduleDosAvailEvent therefore this function can be used without restrictions in these cases.</p> <p>The caller must setup a nested execution <i>ClientRegStruc</i> prior to calling this function. In addition the caller must set the CRS register values appropriate for the DOS call that will be invoked.</p> <p>This function yields control.</p>	

See Also

DosCall
DosCallC

DosClose

Description	Closes the specified file.
Syntax	<pre>#include <dosvmm.h> UINT32 DosClose(modHandle module, UINT32 fileHandle);</pre>
Parameters	<p><i>module</i> Caller's module handle</p> <p><i>fileHandle</i> Handle of file to close</p>
Returns	<p>0 Close was successful</p> <p>0xFFFFFFFF Invalid file handle</p>
Remarks	DOS must be in a callable state. Generally this function can be used inside of an NLM's initialization function as well as during an event scheduled using the DosScheduleDosAvailEvent service.
See Also	<p>DosCreate</p> <p>DosOpen</p> <p>DosDelete</p> <p>DosRead</p> <p>DosWrite</p> <p>DosSeek</p> <p>DosRename</p> <p>DosGetFileSize</p> <p>DosDoesFileExist</p> <p>DosSearchForFile</p>

DosCMapFlat

Description	DosCMapFlat converts a <i>selector:offset</i> to its flat linear address.
Syntax	<pre>#include <dosvmm.h> void *DosCMapFlat(UINT32 SelOff);</pre>
Parameters	<i>SelOff</i> High word has selector Low word has offset
Returns	Linear address
Remarks	The selector can be either an LDT or a GDT. Passed-in LDT selectors must exist in the active LDT.
See Also	DosAMapFlat

DosConvGetInfo

Description Returns the size of the largest block of conventional memory that can be currently allocated using DosConvMemAlloc.

Syntax

```
#include <dosvmm.h>

UINT32
DosConvGetInfo(
    void);
```

Returns Number of bytes in largest free conventional memory block

Remarks

See Also DosConvMemAlloc

DosConvMemAlloc

Description Attempts to allocate a block of memory from conventional memory that is globally accessible in all VMs.

Syntax

```
#include <dosvmm.h>

UINT32
DosConvMemAlloc(
    modHandle    module,
    UINT32       options,
    UINT32       size,
    UINT32       *lowAddress,
    void         **linAddress );
```

Parameters	<p><i>module</i> Caller's module handle.</p> <p><i>options</i> Reserved for future use, must be 0.</p> <p><i>size</i> Number of bytes to allocate. This value is rounded up to the next highest multiple of 16 (paragraph) value.</p> <p><i>lowAddress</i> Set on return to the allocated memory below 1 megabyte address. This value is always on a paragraph boundary. For example, if the allocated memory was at D000:0000 (seg:off) then *lowAddress would be set to 000D0000h.</p> <p style="padding-left: 100px;">This address should not be used by an NLM to read from and/or write to the conventional memory block since there are certain times in a Windows environment where this linear address is not valid, instead always use the *linAddress value to access the memory from protected mode.</p> <p><i>linAddress</i> Set on return to a linear address which can be used to read from and/or write to the allocated conventional memory block.</p>
Returns	<p>zero Allocation successful.</p> <p>non-zero Allocation FAILED.</p>

Remarks

In a DOS-only configuration, **DosConvMemAlloc** attempts the following strategies:

- (1) Allocate best fit, UMB.
- (2) Allocate DOS memory block using first fit. This allocates the block at the lowest possible address in the 640K address space.

There are situations where conventional memory cannot be allocated. In the DOS-only case, this service will fail if inadequate free UMB memory is available and/or inadequate conventional memory below 640K is available.

In a Windows environment, this function allocates conventional memory from the NIOS global V86 memory region. By default, NIOS allocates 8K for this pool, but that can be changed by specifying a different value for the **GLOBAL V86 WIN PAGES** parameter in the NetWare configuration database.

Note that this pool of memory is only available during the Windows session and becomes invalid once Windows is exited. If, at Windows' exit, conventional memory is still allocated from this pool, NIOS will auto free it before exiting back to DOS.

In this case, an NLM should schedule a DOS available event by using **DosScheduleDosAvailEvent** during the Windows "WIN SYS CRIT EXIT" event. When your DOS available event handler is invoked, use **DosConvMemAlloc** to allocate a new block of memory.

Conventional memory allocated prior to Windows loading is available inside of Windows and after Windows is exited.

In the MS Windows environment, **DosConvMemAlloc** fails if all of the NIOS-reserved global V86 memory region is already allocated, or there is insufficient memory in this pool to satisfy the request.

This function yields.

See Also

DosConvMemFree
DosConvGetInfo

DosConvMemFree

Description **DosConvMemFree** frees a block of conventional memory that was previously allocated using the **DosConvMemAlloc** service. This function yields.

Syntax #include <dosvmm.h>

 UINT32
 DosConvMemFree(
 modHandle module,
 UINT32 lowAddress);

Parameters *module* Caller's module handle

lowAddress Below 1 megabyte address returned from
 DosConvMemAlloc.

Returns 0 Invalid *lowAddress* parameter
 !0 Memory was freed

Remarks

See Also DosConvMemAlloc

DosCreate

Description	Creates the specified file.	
<hr/>		
Syntax	<pre>#include <dosvmm.h> UINT32 DosCreate (modHandle module, UINT8 *filePath, UINT32 createAttributes);</pre>	
Parameters	<i>module</i>	Caller's module handle
	<i>filePath</i>	ASCIIZ string containing the full or partial path of the file to be created
	<i>createAttributes</i>	Attribute flags for the file: CREATE_NORMAL CREATE_HIDDEN CREATE_SYSTEM CREATE_HIDDEN_SYSTEM
Returns	file handle If create was successful 0xFFFFFFFF Invalid path, root directory full, existing file is read-only, or insufficient access rights	
<hr/>		
Remarks	If the file already exists, NiosCreate will truncate the file to zero length. DOS must be in a callable state. Generally this function can be inside of an NLM's initialization function as well as during an event scheduled using the DosScheduleDosAvailEvent service.	

See Also

DosClose
DosOpen
DosDelete
DosRead
DosWrite
DosSeek
DosRename
DosGetFileSize
DosDoesFileExist
DosSearchForFile

DosDelete

Description	Deletes the specified file.
Syntax	<pre>#include <dosvmm.h> UINT32 DosDelete(UINT8 *filePath);</pre>
Parameters	<i>filePath</i> ASCIIZ string full or partial path of the file to be deleted
Returns	<div>0 Delete was successful</div> <div>0xFFFFFFFF Invalid path, file does not exist, file is read-only, or insufficient access rights</div>
Remarks	DOS must be in a callable state. Generally this function can be inside of an NLM's initialization function as well as during an event scheduled using the DosScheduleDosAvailEvent service.
See Also	DosClose DosOpen DosCreate DosRead DosWrite DosSeek DosRename DosGetFileSize DosDoesFileExist DosSearchForFile

DosDeRegisterUserCmd

Description Deregisters a previously installed custom DOS command processor command.

Syntax

```
#include <cmdcom.h>

UINT32
DosDeRegisterUserCmd(
    modHandle      moduleHandle,
    struct UserCmdStruc *userCmdInfo);
```

Parameters

moduleHandle Caller's module handle

userCmdInfo Pointer to UserCmd structure

Returns

0 Command successfully deregistered

0xFFFFFFFF Specified command was not registered

Remarks

See Also

CMDCOM.H
CMDCOM.INC
DosRegisterUserCmd
DosEnumerateUserCmds

DosDeRegisterV86Int2F

Description **DosDeRegisterV86Int2F** removes a previously registered Interrupt 2Fh handler.

Syntax

```
#include <dosvmm.h>

UINT32
DosDeRegisterV86Int2F
(modHandle      moduleHandle,
 struct Int2FInfoStruc *int2FInfo);
```

Parameters

<i>moduleHandle</i>	Caller's module handle
<i>int2FInfo</i>	Pointer to <i>Int2FInfoStruc</i> that was used to originally register the handler

Returns

0	Handler was deregistered successfully
0xFFFFFFFF	Handler was not registered

Remarks

See Also DosRegisterV86Int2F

DosDoesFileExist

Description	Determines if the specified [path\] file exists.
Syntax	<pre>#include <dosvmm.h> UINT8 DosDoesFileExist(UINT8 *filename);</pre>
Parameters	<i>filename</i> Specifies the file to look for. Cannot contain wildcards.
Returns	0 File does NOT exist !0 File does exist
Remarks	DOS must be in a callable state. Generally this function can be inside of an NLM's initialization function as well as during an event scheduled using the DosScheduleDosAvailEvent service.
See Also	DosClose DosOpen DosCreate DosGetFileSize DosRead DosDelete DosSeek DosWrite DosSearchForFile

DosEndNestExec

Description **DosEndNestExec** is callable at interrupt time if MS Windows isn't running. This function ends a previously started nested execution. The passed-in CRS is deallocated and the previous CRS is restored.

Assumes *ebp* Points to CRS
Interrupt state undefined

Returns *ebp* destroyed
All other registers preserved
Interrupts same as entered

Remarks The ESP value coming into this routine must have the same value as when the DosBeginNestExec function returned.

Note: Do NOT access the nested execution CRS registers after this function has been called.

See Also DosBeginNestExec
DosBeginNestExecWithCrs
DosEndNestExecWithCrs

DosEndNestExecWithCrs

Description	This function ends a previously started nested execution entered using the DosBeginNestExecWithCrs service. Ownership of the CRS structure provided to start the nested block is returned to the NLM when this service is invoked.
Syntax	<pre>#include <dosvmm.h> CRS *DosEndNestExecWithCrs(CRS *saveCrsBuf);</pre>
Parameters	<i>saveCrsBuf</i> Pointer to CRS structure that was used during the call to DosBeginNestExec to preserve the current CRS
Returns	Pointer to previous CRS
Remarks	<p>This function is callable at interrupt time if MS Windows isn't running. V86 code is NOT callable at interrupt time under MS Windows.</p> <p>Note: Do NOT access the nested execution CRS registers after this function has been called.</p>
See Also	DosBeginNestExecWithCrs DosBeginNestExec DosEndNestExec

DosEndReentrantExec

Description	Ends a reentrant execution block.		
Syntax	<pre>#include <dosvmm.h> void DosEndReentrantExec(UINT32 prevCount);</pre>		
Parameters	<table> <tr> <td><i>prevCount</i></td><td>Value for restoring the internal interrupt nesting level obtained from a previous call.</td></tr> </table>	<i>prevCount</i>	Value for restoring the internal interrupt nesting level obtained from a previous call.
<i>prevCount</i>	Value for restoring the internal interrupt nesting level obtained from a previous call.		
Returns	Nothing		
Remarks	<p>The internal interrupt nesting level is restored to <i>prevCount</i> which should be the value obtained from a previous call to DosBeginReentrantExec.</p>		
See Also	DosBeginReentrantExec		

DosEndUseDos

Description This function restores the Control-C, Control-Break, and Interrupt 24h vectors in the current VM with the previous vectors that were preserved using **DosBeginUseDos**.

Syntax

```
#include <dostvmm.h>

void
DosEndUseDos(
    UINT32    *savedVectInfo);
```

Parameters

<i>savedVectInfo</i>	Pointer to an array of 3 UINT32's that holds the previously saved INT 1Bh, INT 23h, and INT 24h vectors from a call to DosBeginUseDos
----------------------	--

Returns

Nothing
Interrupts same as entered

Remarks

See Also

DosBeginUseDos

DosEnumerateUserCmds

Description	Allows the caller to determine which DOS custom commands have been registered with NIOS.
Syntax	<pre>#include <cmdcom.h> UINT32 DosEnumerateUserCmds(struct UserCmdStruc *userCmdInfo);</pre>
Parameters	<i>userCmdInfo</i> Pointer to a UserCmdStruc structure that will be filled with next registered command structure
Returns	0 Next command successfully found 0xFFFFFFFF No more registered commands
Remarks	<p>Note that the UCText buffer must be provided by the user of this function and will be a copy of the actual command text.</p> <p>The passed-in UserCmdStruc structure's UCText field must point to a 10-byte buffer which will receive a copy of command's text.</p> <p>To start the search, UCOwner must be set to NULL. Subsequent calls to this function use the previously returned text in the UCText buffer and the previous value in the UCOwner field to locate the next registered command.</p>
See Also	CMDCOM.H CMDCOM.INC DosRegisterUserCmd DosDeRegisterUserCmd

DosExecuteFarRet

Description Use **DosExecuteFarRet** to execute (simulate) a V86 retf instruction.

Assumes *ebp* Points to CRS

Returns

- ebp.CrsSP* increased by four
- ebp.CrsCS* set to seg value on stack
- ebp.CrsIP* set to off value on stack
- eax, edx* destroyed
- All other registers preserved

Remarks An in-line version of this function is available using the macro **DosFastExecuteFarRet**.

See Also

DosExecuteIRet

Description	DosExecuteIRet executes (simulates) a V86 iret instruction.
Assumes	<i>ebp</i> Points to CRS
Returns	<div> <div>ebp.CrsSP</div> <div>increased by six</div> <div>ebp.CrsCS</div> <div>set to seg value on stack</div> <div>ebp.CrsIP</div> <div>set to off value on stack</div> <div>ebp.CrsEFlags</div> <div>set to flags on stack</div> <div>eax, edx</div> <div>destroyed</div> <div>All other registers preserved</div> </div>
Remarks	NLMs should not perform a simulated V86 IRET manually. Always use this function for proper operation under MS Windows.
See Also	

DosExecutePop

Description Use **DosExecutePop** to execute (simulate) a V86 pop instruction.

Assumes *ebp* Points to CRS

Returns

ax	Value popped from stack
ebp.CrsSP	increased by two
edx	destroyed
All other registers preserved	

Remarks An in-line version of this function is available using the macro **DosFastExecutePop**.

See Also

DosExecutePush

Description Use **DosExecutePush** to execute a V86 push instruction.

Assumes *ax* Value to push
ebp Points to CRS

Returns *ebp.CrsSP* decreased by two
crs.Stack has *ax* value
All registers preserved

Remarks An in-line version of this function is available using the macro **DosFastExecutePush**.

See Also

DosExecuteV86FarCall

Description	DosExecuteV86FarCall switches to real mode and executes a far call to a specified procedure.
Assumes	<i>eax</i> seg:off of V86 routine to call <i>ebp</i> Points to CRS Interrupt state undefined
Returns	<i>ebp</i> Pointer to CRS All other pm registers destroyed Interrupt state preserved
Remarks	This function is callable at interrupt time if MS Windows isn't running. If called from the foreground, this function yields to any waiting foreground events. The caller must call DosBeginNestExec or DosBeginNestExecWithCrs before invoking this function.
See Also	DosBeginNestExec DosBeginNestExecWithCRS

DosExecuteV86Int

Description	DosExecuteV86Int switches to real mode and executes a specified interrupt.
Assumes	<i>ebp</i> Points to CRS <i>al</i> Interrupt to execute Interrupt state undefined
Returns	<i>ebp</i> Pointer to CRS All other pm registers destroyed Interrupts state preserved
Remarks	<p>This function is callable at interrupt time if MS Windows isn't running.</p> <p>If called from the foreground, this function yields to any waiting foreground events.</p> <p>The caller must call DosBeginNestExec or DosBeginNestExecWithCRS before invoking this function.</p>
See Also	DosBeginNestExec DosBeginNestExecWithCrs

DosFlush

Description	Flushes all disk buffers using DOS function 0Dh.
Syntax	void DosFlush(void);
Parameters	None
Returns	Nothing
Remarks	<p>Note: Certain disk cache programs will not flush write behind data unless the target data files have been closed.</p> <p>DOS must be in a callable state. Generally this function can be used inside of an NLM's initialization function as well as during an event scheduled using the DosScheduleDosAvailEvent service.</p> <p>This function yields.</p>
See Also	DosCreate, DosOpen, DosClose, DosDelete, DosRead, DosWrite, DosSeek, DosRename, DosGetFileSize, DosDoesFileExist, DosSearchForFile

DosFastExecuteFarRet

Description **DosFastExecuteFarRet** executes (simulates) a V86 retf instruction.

Assumes #include dosvmm.inc

ebp Pointer to CRS

Returns *ebp.CrsSP* increased by four
ebp.CrsCS set to seg value on stack
ebp.CrsIP set to off value on stack
eax, edx destroyed
All other registers preserved

Remarks A non-inline version of this macro is available using the function **DosExecuteFarRet**.

See Also

DosFastExecutePop

Description Use the **DosFastExecutePop** macro to execute (simulate) a V86 pop instruction.

Assumes `#include dosvmm.inc`

ebp Points to CRS

Returns `ax` Value popped from stack
`ebp.CrsSP` increased by two
`edx` destroyed
All other registers preserved

Remarks A non-inline version of this macro is available using the function **DosExecutePop**.

See Also

DosFastExecutePush

Description Use the **DosFastExecutePush** macro to execute (simulate) a V86 push instruction.

Assumes `#include dosvmm.inc`

ax Value to push
ebp Pointer to crs

Returns *ebp.CrsSP* decreased by two
crs.Stack has *ax* value
All registers preserved

Remarks A non-inline version of this macro is available using the function **DosExecutePush**.

See Also

DosFreeV86Callback

Description **DosFreeV86Callback** deallocates a previously allocated V86 callback handler.

Syntax #include <dosvmm.h>

 UINT32
 DosFreeV86Callback(
 modHandle moduleHandle,
 UINT32 v86CallbackAddress);

Parameters *moduleHandle* Caller's module handle

v86CallbackAddress Seg:Off to free

Returns !0 Callback does not exist
 0 Callback was successfully freed

Remarks

See Also

DosGetCurrVmHandle

Description	DosGetCurrVmHandle returns a pointer to the currently executing VM's control block.
Assumes	#include <dostvmm.inc>
Returns	EBX -> VM control block All other registers preserved Interrupt state preserved
Remarks	<p>Note that NLMs should not save the VM CB pointer value and use it later in a different thread of execution, since its value can change when the user enters and/or exits the MS Windows environment. An NLM should use the VM ID (VMCBVmId) for this purpose.</p> <p>This function is callable at interrupt time in DOS and MS Windows environments.</p>
See Also	DosGetNextVmHandle

DosGetExeContext

Description	DosGetExeContext returns whether the caller can invoke non-interrupt-time callable APIs in the current execution context.
Syntax	<pre>#include <dosvmm.h> UINT32 DosGetExeContext(void);</pre>
Parameters	None All registers are preserved except <code>eax</code>
Returns	0 Execution is foreground !0 Execution is in the context of a hardware interrupt
Remarks	This function is callable at interrupt time in DOS and MS Windows environments.
See Also	<code>NiosScheduleForegroundEvent</code> found in <i>NetWare Client NIOS Dictionary</i>

DosGetFileSize

Description	Returns the length of the specified file.				
Syntax	<pre>#include <dosvmm.h> UINT32 DosGetFileSize(UINT32 fileHandle);</pre>				
Parameters	<table> <tr> <td><i>fileHandle</i></td><td>Handle of file for which to return size.</td></tr> </table>	<i>fileHandle</i>	Handle of file for which to return size.		
<i>fileHandle</i>	Handle of file for which to return size.				
Returns	<table> <tr> <td>Size of file</td><td></td></tr> <tr> <td>0xFFFFFFFF</td><td>Error</td></tr> </table>	Size of file		0xFFFFFFFF	Error
Size of file					
0xFFFFFFFF	Error				
Remarks	<p>The current seek position is preserved.</p> <p>DOS must be in a callable state. Generally this function can be inside of an NLM's initialization function as well as during as event scheduled using the DosScheduleDosAvailEvent service.</p>				
See Also	<p> DosClose DosOpen DosCreate DosRead DosWrite DosDelete DosSeek DosDoesFileExist DosSearchForFile </p>				

DosGetNextVmHandle

Description	DosGetNextVmHandle returns a pointer to the next active VM control block. It is callable at interrupt time in DOS and MS Windows environments.
Assumes	<i>EBX</i> Pointer to previous VM control block
Returns	<i>EBX</i> Pointer to VM control block All other registers preserved Interrupt state preserved
Remarks	<p>The list of VM's control blocks is circular; therefore the caller must check for end of list by comparing the returned value against the starting VM control block value to know when the last VM control block has been returned.</p> <p>Note that NLMs should not save the VM CB pointer value and use it later in a different thread of execution since its value can change when the user enters and/or exits the MS Windows environment. An NLM should use the VM ID (VMCBVId) for this purpose.</p>
See Also	DosGetCurrVmHandle

DosHookExceptionInterrupt

Description	DosHookExceptionInterrupt hooks the specified protected-mode interrupt (0,2,4-31).
Syntax	<pre>#include <dosvmm.h> UINT32 DosHookExceptionInterrupt(modHandle moduleHandle, UINT32 intToHook, UINT32 referenceData, void (*intHandler)(void));</pre>
Parameters	<p><i>moduleHandle</i> Caller's module handle.</p> <p><i>intToHook</i> Interrupt to hook (0,2,4-31).</p> <p><i>referenceData</i> Value passed to intHandler. This value can be anything the caller desires, or can be ignored if not needed.</p> <p><i>intHandler</i> Pointer to routine that is called when the specified interrupt occurs.</p> <p>The entry and exit conditions are:</p> <p>On entry:</p> <ul style="list-style-type: none"> edx referenceData Interrupts are disabled CLD has been executed ebp -> stack frame Stack frame <ul style="list-style-type: none"> EFlags CS EIP Error Code (if present) pushad regs

On return:

Z flag set if interrupt was serviced
else pass int to next handler
CLD preserved
Interrupts are disabled
All registers can be destroyed

Returns

0	Interrupt was hooked successfully
0xFFFFFFFF	Not enough free memory to hook the interrupt
0xFFFFFFFFE	Invalid intToHook value
0xFFFFFFFFD	Service not supported by NIOS environment

Remarks

The *intHandler* is only invoked when the specified exception is invoked while in protected mode and executing in NIOS. Exceptions generated in real mode are not seen by the caller's *intHandler*.

Callers that wish to hook one of the other processor interrupts (1,3,32-255) should do so by using either **DosHookPMInterrupt** or **DosHookV86Interrupt**.

See Also

DosHookPMInterrupt

Description **DosHookPMInterrupt** hooks the specified protected-mode interrupt (1,3,32-255).

Syntax

```
#include <dostmm.h>

UINT32
DosHookPMInterrupt(
    modHandle    moduleHandle,
    UINT32       intToHook,
    UINT32       referenceData,
    void         (*intHandler)( void));
```

Parameters

moduleHandle Caller's module handle.

intToHook Interrupt to hook (1,3,32-255).

referenceData Value passed to intHandler. This value can be anything the caller desires, or can be ignored if not needed.

intHandler Pointer to routine that is called when the specified interrupt occurs. The entry and exit conditions are:

On entry:
 edx referenceData
 Interrupts are disabled
 CLD has been executed
 ebp -> stack frame
 Stack frame
 EFlags
 CS
 EIP
 pushad regs

On return:
 Z flag set if interrupt was serviced
 else pass int to next handler
 CLD preserved
 Interrupts are disabled
 All registers can be destroyed

Returns

0	Interrupt was hooked successfully
0xFFFFFFFF	Not enough free memory to hook the interrupt
0xFFFFFFFFE	Invalid intToHook value
0xFFFFFFFFD	Service not supported by NIOS environment

Remarks

If an interrupt is not serviced by a protected-mode handler it is passed on to the real-mode interrupt handlers. The *intHandler* is only invoked when the specified interrupt is invoked while in protected mode and executing in NIOS. Interrupts generated in real mode are not seen by the caller's *intHandler*.

Note that this function only hooks the interrupt in the context of the DOS NIOS IDT. Therefore, if the interrupt occurs in real mode or while Windows is active, the specified handler will *not* be invoked.

Callers who wish to hook one of the processor exception interrupts (0,2,4-31) should do so by using **DosHookExceptionInterrupt**.

Callers who wish to hook an interrupt regardless of the mode (real or protected) in which the interrupt occurred should use **DosHookV86Interrupt**.

See Also

DosHookV86Interrupt

Description **DosHookV86Interrupt** hooks the specified V86 interrupt (0-255).

Syntax

```
#include <dosvmm.h>

UINT32
DosHookV86Interrupt(
    modHandle    moduleHandle,
    UINT32       intToHook,
    UINT32       referenceData,
    void          (*intHandler)( void));
```

Parameters

moduleHandle Caller's module handle.

intToHook Interrupt to hook (0-255).

referenceData Value passed to intHandler. This value can be anything the caller desires, or can be ignored if not needed.

intHandler Pointer to routine that is called when the specified interrupt occurs.

The handler's entry and exit conditions are:

On entry:

ebx -> VM CB

edx referenceData

ebp -> CRS

Interrupts are disabled in DOS-only case

Interrupts are enabled if MS Windows is active

CLD has been executed

On return:

Z flag set if interrupt was serviced

else int is passed to next handler

CLD preserved

Interrupt state undefined

All registers can be destroyed

Returns	0	Interrupt was hooked successfully.
	0xFFFFFFFF	Not enough internal resources to complete the operation.
	0xFFFFFFFFE	Invalid intToHook value.
	0xFFFFFFFFD	2Fh specified as intToHook which is invalid.
	0xFFFFFFFFC	V86 interrupt was not hooked prior to MS Windows loading. The calling NLM cannot be loaded when MS Windows is active. The hook operation will be scheduled and executed when MS Windows is exited for Win 3.x.

Remarks

Use this service instead of **DosHookPMInterrupt** if the caller is interested in getting called whenever the specified interrupt is invoked--whether it be from protected mode or real mode--since the **DosHookPMInterrupt** service only calls the *intHandler* when the interrupt is invoked while in protected mode.

Note: Interrupt 2Fh should not be hooked using this API; instead use the **DosRegisterV86Int2F** function.

NLMs that need to pass a V86 interrupt down the chain and then receive control on the back end of the interrupt can use **DosCallWhenV86IntReturns** inside of their interrupt handler function.

When the handler is invoked, the current CrsCS, CrsIP, and CrsFlags will hold the current iret information. If the handler needs to modify the return flags it should do so by modifying the CrsFlags field.

See Also

DosUnHookV86Interrupt
 DosCallWhenV86IntReturns

DosIsDosBusy

Description	Determines whether DOS is in a callable state.
Syntax	<pre>#include <dosvmm.h> UINT32 DosIsDosBusy(void);</pre>
Parameters	None
Returns	0 DOS is NOT busy !0 DOS is busy
Remarks	<p>This service considers DOS to be callable if the InDOS and Critical Error flags are zero. (In an MS Windows environment, this information pertains to the currently running VM.)</p> <p>DOS is always callable inside an NLM's initialization and unload procedures, since initialization and unload always execute in a DOS foreground context.</p> <p>If this service determines that DOS is NOT callable, an NLM should use DosScheduleDosAvailEvent to schedule a callback that will be invoked when the current DOS function is finished or whenever an INT 28h (Idle Interrupt) is generated with the InDOS flag set to 1.</p>

See Also

DosOpen

Description Opens the specified file.

Syntax

```
#include <dosvmm.h>

UINT32
DosOpen(
    modHandle    module,
    UINT8        *pathSpec,
    UINT32        openAttributes);
```

Parameters

<i>module</i>	Caller's module handle
<i>pathSpec</i>	Pointer to ASCII string describing the [path\]name of file to open
<i>openAttributes</i>	Defined in DOSVMM.H and DOSVMM.INC

Returns

File handle
0xFFFFFFFF Error opening file

Remarks DOS must be in a callable state. Generally this function can be inside of an NLM's initialization function as well as during an event scheduled using the **DosScheduleDosAvailEvent** service.

See Also

- DosCreate
- DosClose
- DosDelete
- DosRead
- DosWrite
- DosSeek
- DosRename
- DosGetFileSize
- DosDoesFileExist
- DosSearchForFile

DosRead

Description Reads data from the specified file.

Syntax #include <dosvmm.h>

```
UINT32
DosRead(
    UINT32    fileHandle,
    UINT32    readOffset,
    void      *readBuf,
    UINT32    readSize);
```

Parameters

<i>fileHandle</i>	Handle of file to read from (returned by DosOpen or DosCreate). The file must have been opened for reading.
-------------------	--

<i>readOffset</i>	Offset from start of file to read from. 0xFFFFFFFF if read occurs at current position.
-------------------	--

<i>readBuf</i>	Pointer to buffer to hold read data.
----------------	--------------------------------------

<i>readSize</i>	Number of bytes to read (0 - 0xFFFFFFFFC).
-----------------	--

Returns

Number of bytes read
0xFFFFFFFF Seek failed
0xFFFFFFFFE I/O error during read
0xFFFFFFFFD Function failure

Remarks DOS must be in a callable state. Generally this function can be inside of an NLM's initialization function as well as during an event scheduled using the **DosScheduleDosAvailEvent** service.

See Also

DosClose
DosOpen
DosCreate
DosGetFileSize
DosWrite
DosDelete
DosSeek
DosDoesFileExist
DosSearchForFile

DosRegisterUserCmd

Description This function installs a new DOS command, allowing custom commands to be added to the list of resident commands available in the active command processor (such as COMMAND.COM).

Syntax

```
#include <cmdcom.h>

UINT32
DosRegisterUserCmd(
    modHandle          moduleHandle,
    struct UserCmdStruc *userCmdInfo,
    UINT32              options);
```

Parameters

moduleHandle Caller's module handle.

userCmdInfo Pointer to UserCmd structure. The memory for this structure is owned by NIOS until the command is deregistered. The caller must set the UHandler and UCText fields. UCOwner will be set by this function.

options Reserved for future use. Must be set to zero.

Returns 0 Command installed successfully

Remarks When the user enters the registered command, the specified callback is invoked to allow processing of the command. The handler is invoked as follows:

```
UINT32 (userCmdInfo->UHandler)(
    struct UserCmdStruc *userCmdInfo,
    UINT8               *cmdLine,
    UINT32               argCount,
    UINT8               *argVector[])
```

userCmdInfo Pointer to UserCmdStruc used to register the command.

cmdLine Pointer to len-preceded string containing any parameters entered after the command. This string is not NULL terminated. Typically, the handler should ignore this parameter, instead making use of the parsed parameter information found in the next two parameters.

argCount Count of parsed parameters found after the command. This value will be zero if no parameters were specified.

argVectors Pointer to array of pointers to ASCIIz string parameters. *argCount* defines the number of entries in this array.

Each entry will be stripped of leading and trailing white space unless the information is found inside quotes. No upper/lower case conversions are performed. Any leading '-' character will be converted to the '/' character to allow the user to use either switch character.

Note that the buffers used to hold the individual parameters can be modified by the UCHandler (e.g., case conversions) as long as the handler does not access past the end of the string.

Returns: Command completion code. The low-order byte of this value is passed back as the ERRORLEVEL.

See Also

CMDCOM.H
CMDCOM.INC
DosDeRegisterUserCmd
DosEnumerateUserCmds

DosRegisterV86Int2F

Description Installs a handler for the specified Int 2Fh AH value. The handler is invoked when an Interrupt 2Fh is executed in real mode with AH equal to the value in the I2FAhValue field of the passed-in structure.

Syntax

```
#include <dostvmm.h>

void
DosRegisterV86Int2F(
    modHandle      moduleHandle,
    struct Int2FInfoStruc *int2FInfo);
```

Parameters

moduleHandle Caller's module handle.

int2FInfo Pointer to **Int2FInfoStruc** with the I2FHandler and I2FAhValue fields set. The entry and exit conditions for the I2FHandler are:

On entry:

- ebx -> VM CB
- ecx 0 if interrupt was seen with a hook in the V86 vector table.
- !0 if interrupt was seen from a Windows protected mode V86 hook procedure.
- edx -> referenceData
- ebp -> CRS

Interrupts are disabled in DOS case only
 Interrupts are enabled if MS Windows is active
 CLD has been executed

On return:

- Z flag set if interrupt was serviced
- else int is passed to next handler
- CLD preserved
- Interrupt state undefined
- All registers can be destroyed

Returns Nothing

Remarks The memory for the int2FInfo structure is owned by NIOS until the handler is deregistered using the **DosDeRegisterV86Int2F** function.

This function should be used in place of hooking the V86 Int 2F interrupt vector directly to allow for more efficient Int 2F processing.

When the handler is invoked, the current CrsCS, CrsIP, and CrsFlags will hold the current iret information. If the handler needs to modify the return flags it should do so by modifying the CrsFlags field.

See Also

DosDeRegisterV86Int2F

DosRename

Description	Renames the specified file.
Syntax	<pre>#include <dosvmm.h> UINT32 DosRename(UINT8 *currentFilePath, UINT8 *newFilePath);</pre>
Parameters	<i>filePath</i> ASCIIZ string containing full or partial path of the file to be renamed
Returns	0 If rename was successful 0xFFFFFFFF Invalid path, file does not exist, new file already exists, new file on different disk, root directory full, or insufficient access rights
Remarks	<p>This function will move the file to a different directory if the <i>newFilePath</i> is different and is on the same disk as <i>currentFilePath</i>.</p> <p>DOS must be in a callable state. Generally this function can be inside of an NLM's initialization function as well as during an event scheduled using the DosScheduleDosAvailEvent service.</p>
See Also	DosClose DosOpen DosCreate DosRead DosWrite DosSeek DosDelete DosGetFileSize DosDoesFileExist DosSearchForFile

DosScheduleDosAvailEvent

Description This function schedules an event that will be called when the currently executing DOS function has finished or when DOS issues interrupt 28h (idle interrupt) with the InDOS flag set to one.

Syntax

```
#include <dostmm.h>

UINT32
DosScheduleDosAvailEvent(
    FEB    *eventBlock);
```

Parameters

eventBlock Pointer to a FEBStruc with the FEBESR field set to point to a valid procedure that will be invoked when DOS is in a callable state. The FEB structure passed to this function is owned by NIOS until either the event completes or it is canceled.

Returns

All registers can be destroyed
Interrupts in any state

Remarks

If DOS is not busy when this function is called, the FEBESR is invoked immediately. In an MS Windows environment, the event can be serviced in a different VM than the VM that was active when this service was called.

Note that the FEBESR handler cannot call DOS functions below 0Dh or functions 3Fh,40h with a file handle which references a CON device since this causes stack reentrancy inside of DOS when the FEBESR wakes up because of a DOS INT 28h (Idle interrupt).

If the event handler needs to invoke BIOS or other non-reentrant functions, it must verify that the desired function is not busy (that is, would be reentered). When the FEBESR is invoked, this service guarantees that the video (Int 10h), disk (Int 13h), mouse (Int 15h), and keyboard (Int 16h) BIOS services are NOT busy. No guarantees are made for other BIOS services.

When the defined FEBESR is invoked, a nested ClientRegStruc is already set up for the NLM to use; therefore the NLM does not need to call DosBeginNestExec, etc., before issuing DOS calls.

The FEBESR is invoked as follows:

```

assumes:  For "C" ESRs: void (*FEBESR)(
                                FEB *eventBlock,
                                CRS *crs)
          For "asm" ESRs:
                                esi -> eventBlock
                                ebp -> Nested ClientRegStruc
          CLD has been executed
          Interrupts are enabled
    
```

Returns

```

0   DOS was not busy, event completed before this function returned
    to the caller
!0  DOS was busy, event was scheduled
    
```

See Also

```

DosCancelDosAvailEvent
DosIsDosBusy
DosCall
DosCallC
    
```

DosSearchForFile

Description	Searches the PATH environmental variable for the specified file. The current directory is tried first.
Syntax	<pre>#include <dosvmm.h> UINT8 DosSearchForFile(UINT8 *filename);</pre>
Parameters	<i>filename</i> Searches for the specified file. The current directory is tried first, then the NIOS System directory, then the PATH. This cannot contain wildcards. If successful, this buffer is used to hold the path and filename of the found file. This buffer must be large enough to hold the worst-case path\filename.
Returns	zero File could NOT be found non-zero File was found (filename holds result)
Remarks	DOS must be in a callable state. Generally this function can be inside of an NLM's initialization function as well as during an event scheduled using the DosScheduleDosAvailEvent service. This function assumes that DOS is in a callable state. This function yields.
See Also	DosClose DosOpen DosCreate DosGetFileSize DosRead DosDelete DosSeek DosWrite DosDoesFileExist

DosSeek

Description **NiosSeek** moves the file's read/write file pointer to the specified position.

Syntax

```
#include <dosvmm.h>

UINT32
DosSeek(
    UINT32    fileHandle,
    UINT32    seekType,
    UINT32    seekOffset);
```

Parameters

<i>fileHandle</i>	Handle of file in which to move pointer
<i>seekType</i>	One of the following: SEEK_SET Move <i>seekOffset</i> from beginning SEEK_CURRENT Move <i>seekOffset</i> from current position SEEK_END Move <i>seekOffset</i> from end
<i>seekOffset</i>	Number of bytes to move pointer from specified starting location (<i>seekType</i>)

Returns

New pointer position
0xFFFFFFFF Seek failed

Remarks

DOS must be in a callable state. Generally this function can be inside of an NLM's initialization function as well as during an event scheduled using the **DosScheduleDosAvailEvent** service.

See Also

DosClose
DosOpen
DosCreate
DosRead
DosWrite
DosDelete
DosGetFileSize
DosDoesFileExist
DosSearchForFile

DosSharedBufAlloc

Description **DosSharedBufAlloc** must be called before using the NIOS shared DOS buffer. This function is callable at interrupt time.

Syntax `#include <dosvmm.h>`

`UINT32`
 `DosSharedBufAlloc(`
 `modHandle module);`

Parameters *module* Caller's module handle

Returns 0 Allocation was successful.
 !0 Error allocating buffer. Not enough free memory available to
 preserve buffer contents.

Interrupt state preserved and not changed.

Remarks This function is callable at interrupt time in a DOS-only environment. If called during interrupt time in a DOS-only environment, the caller must check to see if the buffer contents need preservation by checking the return code from **DosSharedBufGetInfo**. If it does, then the caller must preserve the contents and restore the contents before calling **DosSharedBufFree**.

This buffer can be used by anyone in the system needing temporary global DOS memory. The shared buffer must be allocated and freed in the same execution thread.

This function uses a semaphore to ensure only one access to the shared buffer at a time. If an attempt is made to allocate the buffer reentrantly in the context of the same VM, then the buffer contents will be preserved prior to returning. In this case the contents will be restored when the caller invokes **DosSharedBufFree**.

The fact that the buffer contents may be swapped out in the background could preclude its use in some situations, in which case a private DOS buffer must be allocated by the module.

The size and location of the shared buffer can be determined using **DosSharedBufGetInfo**.

See Also

DosSharedBufFree
DosSharedBufGetInfo
DosGetExeContext

DosSharedBufFree

Description **DosSharedBufFree** must be called after using the NIOS shared DOS buffer.

Syntax

```
#include <doshmm.h>

void
DosSharedBufFree(
    modHandle    module);
```

Parameters *module* Caller's module handle

Returns Nothing
Interrupt state preserved and not changed

Remarks

If the buffer's contents had to be preserved, the contents will be restored by this function before returning.

If the buffer was allocated during interrupt context and the buffer was already in use, the caller must restore the contents itself prior to invoking this function.

This function is callable at interrupt time in a DOS-only environment.

See Also DosSharedBufAlloc

DosSharedBufGetInfo

Description	DosSharedBufGetInfo returns information about the shared DOS buffer maintained by NIOS.	
Syntax	<pre>#include <dosvmm.h> UINT32 DosSharedBufGetInfo(SDBInfo *sdbiStruc);</pre>	
Parameters	<i>sdbiStruc</i>	Pointer to buffer set on return with a copy of the current shared DOS buffer information
Returns	zero non-zero	Buffer is unallocated. Buffer is currently allocated. Use of DosSharedBufAlloc will cause the current contents to be preserved if current execution context is not interrupt time.
Interrupt state preserved and not changed.		
Remarks	<p>NIOS manages a shareable conventional memory block (< 1 Meg) that can be allocated and used by NLMs. If an NLM only needs a block of conventional memory for a short period of time, it can use this service instead of allocating a block for itself, thus reducing overall conventional memory usage.</p> <p>This function is callable at interrupt time in a DOS-only environment.</p> <p>The minimum size of the Shared DOS buffer is 512 bytes. The actual size is returned in the <i>SDBSize</i> field of the returned <i>SDBInfo</i> structure.</p>	
See Also	DosSharedBufAlloc DosSharedBufFree DosGetExeContext	

DosUnHookExceptionInterrupt

Description Unhooks the caller from the specified exception interrupt chain.

Syntax

```
#include <dostvmm.h>

UINT32
DosUnHookExceptionInterrupt(
    modHandle    moduleHandle,
    UINT32       intToUnHook,
    void         (*intHandler)( void));
```

Parameters

<i>moduleHandle</i>	Caller's module handle
<i>intToUnHook</i>	Interrupt to unhook from (0,2,4-31)
<i>intHandler</i>	Pointer to caller's interrupt handler routine

Returns

0	Caller was unhooked successfully
0xFFFFFFFF	Caller was not hooking the interrupt
0xFFFFFFFFE	Invalid intToUnHook value
0xFFFFFFFFD	Service not supported by NIOS environment

Remarks

See Also

DosUnHookPMInterrupt

Description Unhooks the caller from the specified interrupt chain.

Syntax

```
#include <dosvmm.h>

UINT32
DosUnHookPMInterrupt(
    modHandle    moduleHandle,
    UINT32       intToUnHook,
    void          (*intHandler)( void));
```

Parameters

<i>moduleHandle</i>	Caller's module handle
<i>intToUnHook</i>	Interrupt to unhook from (32-255)
<i>intHandler</i>	Pointer to caller's interrupt handler routine

Returns

0	Caller was unhooked successfully
0xFFFFFFFF	Caller was not hooking the interrupt
0xFFFFFFFFE	Invalid intToUnHook value
0xFFFFFFFFD	Service not supported by NIOS environment

Remarks

See Also

DosUnHookV86Interrupt

Description Unhooks the caller from the specified V86 interrupt chain.

Syntax

```
#include <dosvmm.h>

UINT32
DosUnHookV86Interrupt(
    modHandle    moduleHandle,
    UINT32       intToUnHook,
    void         (*intHandler)(void));
```

Parameters

<i>moduleHandle</i>	Caller's module handle
<i>intToUnHook</i>	Interrupt to unhook from (0-255)
<i>intHandler</i>	Pointer to caller's interrupt handler routine

Returns

0	Caller was unhooked successfully
0xFFFFFFFF	Caller was not hooking the interrupt
0xFFFFFFFFE	Invalid intToUnHook value

Remarks

See Also

DosVid16DeregisterGuiCB

Description Cancels a previously registered GUI callback given the function.

Syntax

```

UINT32
DosVid16DeregisterGuiCB (
    UINT32      funcNum,
    UINT32      (far *callback) );
    
```

Parameters

funcNum Index to function list as follows:

- 0 = UINT32 NiosVidMessageBox (
 - UINT8 far *title,
 - UINT8 far *prompt,
 - UINT32 buttons);
- 1 = UINT32 NiosVidInputDialogBox (
 - UINT8 far *title,
 - UINT8 far *prompt,
 - UINT8 far *input,
 - UINT32 length);
- 2 = void far *NiosVidCreateDialogBox (
 - UINT8 far *title,
 - UINT8 far *prompt0;
- 3 = UINT32 NiosVidDestroyDialogBox (
 - void far *handle);
- 4 = UINT32 NiosVidUpdateDialogBox (
 - void far *handle,
 - UINT8 far *prompt,
 - UINT8 far *title);

callback Pointer to function address

Returns

- 0 Successful
- 0xFFFFFFFF Invalid parameters

Remarks

See Also DosVid16RegisterGuiCB

DosVid16RegisterGuiCB

Description Sets the address of the current GUI callback as defined by *funcNum*.

Syntax

```

UINT32
DosVid16RegisterGuiCB (
    UINT32      funcNum,
    UINT32      (far *callback) );
    
```

Parameters

funcNum Index to function list as follows:

- 0 = UINT32 NiosVidMessageBox (
 - UINT8 far *title,
 - UINT8 far *prompt,
 - UINT32 buttons);
- 1 = UINT32 NiosVidInputDialogBox (
 - UINT8 far *title,
 - UINT8 far *prompt,
 - UINT8 far *input,
 - UINT32 length);
- 2 = void far *NiosVidCreateDialogBox (
 - UINT8 far *title,
 - UINT8 far *prompt0;
- 3 = UINT32 NiosVidDestroyDialogBox (
 - void far *handle);
- 4 = UINT32 NiosVidUpdateDialogBox (
 - void far *handle,
 - UINT8 far *prompt,
 - UINT8 far *title);

callback Pointer to function address

Returns

- 0 Successful
- 0xFFFFFFFF Invalid function or registry full

Remarks

See Also DosVid16DeregisterGuiCB

DosVidCallWhenPopupOk

Description Schedules an event that will fire when the system is capable of displaying a popup message.

Syntax

```
#include <dosvmm.h>

UINT32
DosVidCallWhenPopupOk(
    FEB    *eventBlock);
```

Parameters *eventBlock* Pointer to FEBStruc with the FEBESR field set

Returns

zero	Event completed before this function returned
non-zero	Event was scheduled

Remarks When the callback is invoked the current VM will be the focus VM and execution will be in the foreground sufficient for using the **DosVid** popup/keyboard services.

While scheduled, the *eventBlock.FEBStatus* field will be set to a non-zero value. When invoked, the *FEBStatus* field will be zero.

This function is callable at interrupt time in all environments.

See Also

DosVidCheckKey

Description Determines if a key is waiting in the keyboard buffer; if there is, it is returned.

Syntax

```
#include <dosvmm.h>

UINT16
DosVidCheckKey(
    void);
```

Parameters None

Returns 0xFFFF No key available
 else
 Lower byte contains ASCII code or other translation
 Upper byte contains scan code or special character ID

Remarks

The key is removed from the keyboard input queue.

Returned Scan/ASCII codes are compatible with BIOS Int 16h, functions 10h/11h. The key is NOT displayed by this service.

Keyboard BIOS must be callable.

This service is intended to be used only in the context of a popup.

See Also

DosVidGetKey
 DosVidEmptyTypeAhead

DosVidCursorSet

Description	This service positions the cursor to the specified x,y coordinate in the specified popup.
Syntax	<pre>#include <dosvmm.h> UINT32 DosVidCursorSet (PopupHandle popupHandle, UINT8 newX, UINT8 newY);</pre>
Parameters	<p><i>popupHandle</i> Specifies a handle returned from a previous call to DosVidSaveScreen or DosVidPopup</p> <p><i>newX</i> Logical column within the specified popup where cursor should be positioned</p> <p><i>newY</i> Logical row within the specified popup where cursor should be positioned</p>
Returns	<p>0 Cursor successfully positioned</p> <p>0xFFFFFFFF Invalid popupHandle parameter</p>
Remarks	The cursor can be disabled by setting <i>newX</i> and <i>newY</i> to 0xFF.
See Also	

DosVidEmptyTypeAhead

Description	Empties the keyboard typeahead buffer.
Syntax	<pre>void DosVidEmptyTypeAhead(void);</pre>
Parameters	None
Returns	Nothing
Remarks	<p>Keyboard BIOS must be callable.</p> <p>This service is intended to be used only in the context of a popup.</p>
See Also	

DosVidGetKey

Description Waits for a key press and returns the key value. While waiting this function relinquishes control by calling **NiosPoll**.

Syntax #include <dosvmm.h>

 UINT16
 DosVidGetKey(
 void);

Parameters None

Returns Lower byte contains ASCII code or other translation
 Upper byte contain scan code or special character ID

Remarks Returned Scan/ASCII codes are compatible with BIOS Int 16h, functions 10h/11h.

 Keyboard BIOS must be callable.

 This service is intended to be used only in the context of a popup.

See Also DosVidCheckKey
 DosVidEmptyTypeAhead

DosVidGetPopupInfo

Description Obtains miscellaneous information about an active popup created using either the **DosVidSaveScreen** or **DosVidPopup** service. This information can be used to determine how to write text into the popup.

Syntax

```
#include <dosvmm.h>

UINT32
DosVidGetPopupInfo(
    PopupHandle  popupHandle,
    PopupInfo    *popInfo );
```

Parameters

popupHandle Handle of popup about which to return info. This handle must be a valid handle returned by **DosVidSaveScreen** or **DosVidPopup**.

popInfo Pointer to PopupInfo structure which, on return, will be filled with information about the specified popup.

Returns

0	Function successful
0xFFFFFFFF	Invalid popupHandle parameter

Remarks

See Also

DosVidIsPopupOk

Description Determines if it is possible to display a popup message in the current context.

Syntax

```
#include <dostmm.h>

SINT32
DosVidIsPopupOk(
    void);
```

Parameters None

Returns

```
>=0    Popup ok
<=0    Popup NOT ok
```

Possible Values - Popup Ok

MS Windows message mode should be used except for DVOK_FULL_DOS_BOX_AVAIL.

DVOK_SYSTEM_VM	Focus VM is system VM
DVOK_WINDOWED_DOS_BOX	Focus VM is windowed DOS box
DVOK_FULL_DOS_BOX_AVAIL	Focus VM is full screen DOS box
DVOK_FULL_DOS_BOX_BUSY	Focus VM is full screen DOS box, video/keyboard BIOS is available
DVOK_FULL_DOS_BOX_GRP	Focus VM is full screen DOS box inside of Windows, video BIOS is busy

Possible Values - Popup NOT Ok

DVOK_WIN_NOT_FOCUS_VM	Windows active, focus VM is not current VM
DVOK_WIN_AT_HARD_INT	Windows active, at hardware interrupt time

DVOK_DOS_BAD_GRP_MODE	DOS only, unsupported graphics mode
DVOK_DOS_BIOS_BUSY	DOS only, video BIOS is busy

Remarks

See Also

DosVidPopup

Description Displays a popup message on the screen with the specified title, subtitle, prompt, and message text.

Syntax

```
#include <dosvmm.h>

void
*DosVidPopup(
    UINT8    *titleStr,
    UINT8    *subtitleStr,
    UINT8    *promptStr,
    UINT8    *msg);
```

Parameters

<i>titleStr</i>	Title of popup. This should be a short message. If this parameter is NULL, no title message will be displayed.
<i>subtitleStr</i>	Subtitle of popup. This should be a short message. If this parameter is NULL, no subtitle message will be displayed.
<i>promptStr</i>	Prompt message. This describes some type of user action. If NULL, no prompt will be displayed.
<i>msg</i>	Main popup text. This is a message describing something to the user.

Returns

zero	Error creating popup
non-zero	Popup handle

Remarks Control is given back to the caller once the popup is displayed. The caller must use the **DosVidRestoreScreen** service to remove the popup message and restore the previous screen contents.

Note that the size of the popup is dynamically calculated. The actual size is based on the length of the passed-in msg string along with the lengths of the title and prompt strings.

See Also

- DosVidRestoreScreen
- DosVidPopupExt
- DosVidWriteToPopup

DosVidGetPopupInfo

DosVidPopupExt

Description Displays a popup on the screen with the specified title, subtitle, prompt, and message text.

Syntax

```
#include <dosvmm.h>

UINT32
DosVidPopupExt(
    PopupHandle    popupHandle,
    UINT8          *titleStr,
    UINT8          *subtitleStr,
    UINT8          *promptStr,
    UINT8          *msg,
    UINT8          extraLines,
    UINT8          minColumns,
    UINT8          minRows,
    UINT8          popupStartColumn,
    UINT8          popupStartRow);
```

Parameters	<i>popupHandle</i>	Specifies a handle returned from a previous call to DosVidSaveScreen .
	<i>titleStr</i>	Title of popup. This should be a short message. If this parameter is NULL, no title message will be displayed.
	<i>subtitleStr</i>	Subtitle of popup. This should be a short message. If this parameter is NULL, no subtitle message will be displayed.
	<i>promptStr</i>	Prompt message. This describes some type of user action, such as which keys do what. If NULL, no prompt will be displayed.
	<i>msg</i>	Main popup text. This is a message describing something to the user.
	<i>extraLines</i>	Number of extra empty lines that should be built after the msg string. This allows the caller to dynamically add text to the bottom of the popup using the DosVidWriteToPopup service. If zero, no extra lines will be output.

<i>minColumns</i>	Minimum number of user space columns in the popup. If set to zero, the number of columns is dynamically calculated based on the contents of the passed-in string parameters.
<i>minRows</i>	Minimum number of user space rows in the popup. If set to zero, the number of rows is dynamically calculated based on the contents of the passed-in string parameters.
<i>popupStartColumn</i>	Specifies the X coordinate of where the popup will begin on the screen. If set to 0xFF, the popup will be horizontally centered on the screen.
<i>popupStartRow</i>	Specifies the Y coordinate of where the popup will begin on the screen. If set to 0xFF, the popup will be vertically centered on the screen.

Returns

0	Popup successfully created
0xFFFFFFFF	<i>popupStartColumn</i> is out of bounds
0xFFFFFFFFE	<i>popupStartRow</i> is out of bounds
0xFFFFFFFFD	<i>minColumns</i> is out of bounds
0xFFFFFFFFC	<i>minRows</i> is out of bounds
0xFFFFFFFFB	Not enough free memory to process popup
0xFFFFFFFFA	Invalid <i>popupHandle</i> parameter

Remarks

Control is given back to the caller once the popup is displayed. The caller must use the **DosVidRestoreScreen** service to remove the popup message and restore the previous screen contents.

This function should be used instead of **DosVidPopup** when more control over the popup's format is needed.

Note: This service requires a *popupHandle* as an input parameter; therefore, the caller must invoke **DosVidSaveScreen** prior to using this service.

See Also

DosVidPopup
 DosVidSaveScreen
 DosVidRestoreScreen
 DosVidWriteToPopup
 DosVidGetPopupInfo

DosVidRestoreScreen

Description	Restores the contents of a portion of the screen previously preserved using the DosVidSaveScreen or DosVidPopup functions.
Syntax	<pre>#include <dosvmm.h> void DosVidRestoreScreen(PopupHandle popupHandle);</pre>
Parameters	<i>popupHandle</i> Handle of popup returned from DosVidSaveScreen
Returns	0 Screen successfully restored, popupHandle freed 0xFFFFFFFF Invalid popupHandle parameter
Remarks	This function also restores the cursor to the settings present at the time DosVidSaveScreen was called.
See Also	DosVidSaveScreen

DosVidSaveScreen

Description	Saves the contents of the specified rectangular portion of the screen (including current cursor information) to a dynamically allocated buffer.								
Syntax	<pre>#include <dosvmm.h> UINT32 DosVidSaveScreen(PopupHandle *popupHandle);</pre>								
Parameters	<i>popupHandle</i> Pointer to a pointer which will be set on return to a handle describing the specified saved video region. This handle is used to restore the window contents.								
Returns	<table> <tr> <td>0</td><td>Function was successful</td></tr> <tr> <td>0xFFFFFFFF</td><td>Unable to allocate save buffer</td></tr> <tr> <td>0xFFFFFFFFE</td><td>Bad video mode</td></tr> <tr> <td>0xFFFFFFFFD</td><td>Bad parameters</td></tr> </table>	0	Function was successful	0xFFFFFFFF	Unable to allocate save buffer	0xFFFFFFFFE	Bad video mode	0xFFFFFFFFD	Bad parameters
0	Function was successful								
0xFFFFFFFF	Unable to allocate save buffer								
0xFFFFFFFFE	Bad video mode								
0xFFFFFFFFD	Bad parameters								
Remarks	<p>This function disables the cursor until DosVidRestoreScreen is called. This function is provided for NLMs that need to access the display directly when the DosVidPopup service does not provide enough functionality.</p> <p>Before using this service, the caller must verify that a popup is possible by using either the DosVidIsPopupOk or DosVidCallWhenPopupOk services.</p> <p>Use of this function allows the caller to gain direct control of where text is placed on the screen. Using the returned <i>popupHandle</i>, the caller can use the DosVidWriteToPopup and/or DosVidPopupExt services to place text anywhere on the screen.</p>								

See Also

DosVidRestoreScreen
DosVidPopup
DosVidIsPopupOK
DosVidCallWhenPopupOk
DosVidWriteToPopup
DosVidGetPopupInfo

DosVidSoundBell

Description	Rings the bell once.
Syntax	<pre>#include <dosvmm.h> void DosVidSoundBell(void);</pre>
Parameters	None
Returns	Nothing
Remarks	This is a synchronous call. In other words, it does not return until the bell is finished. This function enables interrupts and yields by calling NiosPoll .
See Also	

DosVidStdOut

Description	Displays the specified prefix and message using DOS STDOUT.
Syntax	<pre>#include <dosvmm.h> void DosVidStdOut(UINT8 *prefix, UINT8 *msg);</pre>
Parameters	<p><i>prefix</i> Pointer to message prefix string. If NULL, no prefix will be displayed.</p> <p><i>msg</i> Pointer to message string to display.</p>
Returns	Nothing
Remarks	DOS must be callable. This function displays the strings using the STDOUT file handle for the currently active Program Segment Prefix (PSP). This function yields.
See Also	

DosVidWriteToPopup

Description Writes the specified string contents to the specified (column, row) position inside the popup specified by *popupHandle*. The output will be truncated if the string exceeds the popup dimensions.

Syntax

```
#include <dostvmm.h>

UINT32
DosVidWriteToPopup(
    PopupHandle    popupHandle,
    UINT32         column,
    UINT32         row,
    UINT8          attribute,
    UINT32         len,
    UINT8          *str);
```

Parameters

popupHandle Handle of popup returned from a previous call to either **DosVidSaveScreen** or **DosVidPopup**

column Logical x position where string should be written to (for example, value of 0 is the left-hand corner of the popup)

row Logical y position where string should be written to (for instance, value of 0 is the first row of the popup)

attribute Standard color display attribute describing the background and foreground attributes to use when writing out string

len Number of bytes in string

Returns	0	String output successfully.
	0xFFFFFFFF	Invalid column and/or row parameters.
	0xFFFFFFFFE	String was output; however, it exceeded the popup size and was truncated.
	0xFFFFFFFFD	Invalid popup handle.

Remarks

See Also

- DosVidSaveScreen
- DosVidPopup
- DosVidGetPopupInfo

DosWrite

Description Writes to the specified file.

Syntax

```
#include <dosvmm.h>

UINT32
DosWrite(
    UINT32    fileHandle,
    UINT32    writeOffset,
    void      *writeBuf,
    UINT32    writeSize);
```

Parameters

<i>fileHandle</i>	Handle of file to write to (returned by DosOpen). The file must have been opened for writing.
<i>writeOffset</i>	Offset from start of file to write to: 0xFFFFFFFF if write should occur at current position.
<i>writeBuf</i>	Pointer to buffer holding data to write.
<i>writeSize</i>	Number of bytes to write (0 - 0xFFFFFFFFC).

Returns

Number of bytes written	
0xFFFFFFFF	Seek failed
0xFFFFFFFFE	I/O error during write
0xFFFFFFFFD	Function failure

Remarks DOS must be in a callable state. Generally this function can be inside of an NLM's initialization function as well as during an event scheduled using the **DosScheduleDosAvailEvent** service.

See Also

DosClose
DosOpen
DosCreate
DosGetFileSize
DosRead
DosDelete
DosSeek
DosDoesFileExist
DosSearchForFile

Win16GetProcAddress

Description	Resolves the sel:off of an exported 16-bit Windows procedure.	
Syntax	#include <nlmapi.h>	
	<pre>UINT32 Win16GetProcAddress(UINT8 *modName, UINT8 *procName, UINT32 *procSelOff);</pre>	
Parameters	<i>modName</i>	Name of module, DLL, or application that exports the procName.
	<i>procName</i>	Pointer to ASCIIZ procedure name to resolve. If the upper 16-bits of this value is zero, the low order 16-bits are interpreted as an ordinal value.
	<i>procSelOff</i>	UINT32 set on return to the sel:off of the resolved Windows function if this service returns successfully.
Returns	Zero	Procedure successfully resolved.
	0xFFFFFFFF	Unresolved procName.
	0xFFFFFFFFE	Service not currently available. There is a window during MS Windows initialization that this service isn't available. An NLM can watch for the "WIN16 GETPROCADDR AVAIL" event to know when this service is available.
	0xFFFFFFFFD	Current execution context isn't the system VM, or the system VM isn't executing in protected mode.
Remarks	This function calls the Windows function GetProcAddress to service the request.	

WinCallWhenPMIntReturns

Description	Used in an NLM's PM interrupt handler to obtain control on the back end of a current PM interrupt.
Assumes	<p><i>edx</i> Reference data Interrupt in any state. <i>esi</i> Points to callback handler. Called as follows:</p> <p>On entry: <i>ebx</i> Points to VM CB <i>edx</i> Reference data <i>ebp</i> Points to CRS Interrupts are enabled. CLD has been executed.</p> <p>On return: CLD preserved Interrupts are enabled. All registers can be destroyed.</p>
Returns	<p>Z flag cleared. Interrupt state preserved. All registers can be destroyed.</p>
Remarks	<p>This function is callable only in the context of a protected mode (PM) interrupt under Windows Enhanced mode.</p> <p>An NLM that uses this service must first call this service then return from its PM interrupt handler signalling that the interrupt was NOT consumed. This service is designed so that the NLM's interrupt handler can simply jump to this service and this service will return back from the handler with the Z flag cleared.</p> <p>This service places a PM callback address on the current PM stack such that when the PM interrupt handling code iret's out of the interrupt, NLM handlers that have used this service will receive control. This occurs in a LIFO manner thus preserving the ordering that should occur when multiple NLMs hook the backend of the same PM interrupt.</p> <p>When the handler is invoked, the current CrsCS, CrsIP and CrsFlags will hold the current iret information. If the handler needs to modify the return flags it should do so by modifying the CrsFlags field.</p>

WinHookPMInt21

Description Displays the specified prefix and message using DOS STDOUT.

Syntax

```
#include <dostvmm.h>

UINT32
WinHookPMInt21 (
    modHandle    moduleHandle,
    UINT32       referenceData,
    UINT32       (*handler)(
        VmCb      *vm,
        UINT32     referenceData,
        CRS        *crs));
```

Parameters

moduleHandle Callers module handle.

referenceData Data to be passed to the handler.

handler Pointer to int 21h handler to install.

Parameters:

vm Current vm handle.

referenceData Data specified during registration.

crs Pointer to client registers.

Returns:

Zero to consume the interrupt.

Non-zero to chain the interrupt.

Returns

0 on success.

0xFFFFFFFF if out of memory.

Remarks

This function can be called when Windows is not active; however, the hook only becomes active after the NE_WIN_SYS_VM_INIT NESL event. The hook becomes inactive once Windows destroys its PM int 21 chain, but it will reactivate the next time Windows loads (after the NE_WIN_SYS_VM_INIT event).

Every call to WinHookPMInt21 must be matched with a corresponding call to WinUnHookPMInt21.

NLMs that need to pass a PM Int 21h interrupt on down the chain and then receive control on the back end of the interrupt can use the WinCallWhenPMIntReturns service inside of their interrupt handler function to obtain this type of functionality.

This function is not available at interrupt time.

See Also

WinUnHookPMInt21
WinCallWhenPMIntReturns

WinUnHookPMInt21

Description Displays the specified prefix and message using DOS STDOUT.

Syntax

```
#include <dosvmm.h>

UINT32
WinUnHookPMInt21 (
    modHandle    moduleHandle,
    UINT32       (*handler)(
        VmCb      *vm,
        UINT32     referenceData,
        CRS        *crs));
```

Parameters

moduleHandle Callers module handle.

handler Pointer to int 21h handler to uninstall.

Parameters:

vm Current vm handle.

referenceData Data specified during registration.

crs Pointer to client registers.

Returns:

Zero to consume the interrupt.

Non-zero to chain the interrupt.

Returns

0 on success.

0xFFFFFFFF if handler is not registered by moduleHandle..

Remarks

See Also

WinHookPMInt21

WinCallWhenPMIntReturns