








Emacs support for Erlang ⚠️

Description	Keystroke	Function	Note
Support for the Erlang Programming Language	 Emacs provides support for Erlang and Erlang Tools via the <code>erlang-mode</code> external package and some other packages.  PEL activates Erlang support via the customize user option variable <code>pel-use-erlang</code> . It must be set to <code>t</code> to activate support for Erlang.  Further customization is available via several user options. <ul style="list-style-type: none">PEL customization for Erlang: use the command below: <code>pel-cfg-pkg-erlang</code>.<ul style="list-style-type: none"><code>pel-erlang-rootdir</code>:<code>pel-erlang-exec-path</code>:<code>pel-erlang-shell-prevent-echo</code>: set to <code>t</code> to prevent the Erlang shell from echoing every command.		
Customize PEL Erlang Support (See also: Σ Customize)	<ul style="list-style-type: none"><code><f11> <f1></code> <code>SPC e</code><code><f12> <f1></code>	<code>(pel-cfg-pkg-erlang &optional OTHER-WINDOW)</code>	Customize PEL Erlang support. <ul style="list-style-type: none">If <code>OTHER-WINDOW</code> is non-nil (use <code>C-u</code>), display in another window.The <code><f12> <f1></code> binding is available when point is in a buffer visiting a Erlang file.
Editing Erlang Code			
Electric Key in Erlang Source code	The following keys have “ <i>electric</i> ” behaviour and perform special editing tasks to help edit Erlang source code.		
Electric comma	,	<code>(erlang-electric-comma &optional ARG)</code>	Insert a comma character and possibly a new indented line. <ul style="list-style-type: none">The variable ‘<code>erlang-electric-comma-criteria</code>’ states a criterion, when fulfilled a newline is inserted and the next line is indented.Behaves just like the normal comma when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.
Electric semicolon	;	<code>(erlang-electric-semicolon &optional ARG)</code>	Insert a semicolon character and possibly a prototype for the next line. <ul style="list-style-type: none">The variable ‘<code>erlang-electric-semicolon-criteria</code>’ states a criterion, when fulfilled a newline is inserted, the next line is indented and a prototype for the next line is inserted. Normally the prototype consists of " <code>-></code>". Should the semicolon end the clause a new clause header is generated.The variable ‘<code>erlang-electric-semicolon-insert-blank-lines</code>’ controls the number of blank lines inserted between the current line and new function header.Behaves just like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.
Electric > (for the end of arrow)	>	<code>(erlang-electric-gt &optional ARG)</code>	Insert a greater-than sign, and optionally insert a new line and indent.
Erlang Comments	Erlang uses the <code>%</code> character to identify line comments. It uses the following conventions: <ul style="list-style-type: none"><code>%</code> - Single percent characters for comments located toward the end of a line of code<code>%%</code> - Two percent characters are used for comments starting at indentation level.<code>%%%</code> - Three percent characters are used to describe modules and are always placed in the first column		
Comment/un-comment Note: <code>M-;</code> works much better than <code>C-c C-c</code> and <code>C-c C-u</code>	<code>M-;</code>	<code>(comment-dwim ARG)</code>	Comment line or region with <code>%</code> or <code>%%</code> style comments depending on the location in the buffer. <ul style="list-style-type: none">When no marked region and no comment:<ul style="list-style-type: none">On empty line: insert <code>%%</code> comment starter at the proper indentation level.On line with code: insert <code>%</code> comment starter after the code for an end-of-line commentWith marked un-commented region:<ul style="list-style-type: none">Comment region (each line is commented)With marked commented region:<ul style="list-style-type: none">removes the comment.Call the comment command you want (Do What I Mean).<ul style="list-style-type: none">If the region is active and ‘<code>transient-mark-mode</code>’ is on, call ‘<code>comment-region</code>’ (unless it only consists of comments, in which case it calls ‘<code>uncomment-region</code>’). Else, if the current line is empty, call ‘<code>comment-insert-comment-function</code>’ if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call ‘<code>comment-kill</code>’. Else, call ‘<code>comment-indent</code>’.
	<code>C-c C-c</code>	<code>(comment-region BEG END &optional ARG)</code>	Comment or uncomment each line in the region. <ul style="list-style-type: none">With just <code>C-u</code> prefix arg, uncomment each line in region <code>BEG .. END</code>.Numeric prefix ARG means use ARG comment characters.If ARG is negative, delete that many comment characters instead.The strings used as comment starts are built from ‘<code>comment-start</code>’ and ‘<code>comment-padding</code>’; the strings used as comment ends are built from ‘<code>comment-end</code>’ and ‘<code>comment-padding</code>’.By default, the ‘<code>comment-start</code>’ markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with ‘<code>comment-style</code>’.
Un-comment region	<code>C-c C-u</code>	<code>(uncomment-region BEG END &optional ARG)</code>	Uncomment each line in the <code>BEG .. END</code> region. The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.
Indentation	All syntactic indentation control for D is controlled by the <code>CC-Mode</code> logic and provided commands listed below. <ul style="list-style-type: none">Rigid indentation commands are also available and listed at the end of this list. They are also listed in the Σ Indentation table.		
Indent current line or region (See also: Σ Indentation)	<code><tab></code>	<code>(c-indent-line-or-region &optional ARG REGION)</code>	Indent active region, current line, or block starting on this line. Behaviour depends on syntactic-indentation mode (enabled by default but can be toggled on/off with the <code><f12> M-i</code> key): <ul style="list-style-type: none">With syntactic-indentation on (the default):<ul style="list-style-type: none">In Transient Mark mode, when the region is active, reindent the region.Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line.Otherwise reindent just the current line.👉 This might seem strange for new Emacs users, but it ends up being very useful. You can type <code><tab></code> anywhere in the line to adjust the indentation of the current line or everything in the marked area if a block is marked.With syntactic-indentation off:<ul style="list-style-type: none"><code><tab></code> always indent current line by one level<code>C-u - <tab></code> or <code>M- <tab></code> always un-indent current line by one levelIndenting marked region is done without syntax knowledge and at the same level as previous line.👉 If you want to indent rigidly you can use:<ul style="list-style-type: none">(<code>pel-indent-rigidly &optional N</code>) (bound to <code>C-x <tab></code> and to <code><f11> <tab><tab></code>) to indent the line or region rigidly.(<code>tab-to-tab-stop</code>), bound to <code>M-i</code> to insert spaces to the next tab stop column.
Indent lines of list after point (See also: Σ Indentation)	<code>C-M-q</code>	<code>(prog-indent-sexp &optional DEFUN)</code>	Indent the expression after point. When interactively called with prefix, indent the enclosing defun instead.
Indent current function or class	<code>C-c C-q</code>	<code>(erlang-indent-function)</code>	Indent current Erlang function.

Description	Keystroke	Function	Note
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region. <ul style="list-style-type: none"> A numeric prefix argument specifies a column: indent each line to that column. With no prefix argument, the command chooses one of these methods and indents all the lines with it: <ol style="list-style-type: none"> If ‘fill-prefix’ is non-nil, insert ‘fill-prefix’ at the beginning of each line in the region that does not already begin with it. If ‘indent-region-function’ is non-nil, call that function to indent the region. Indent each line via ‘indent-according-to-mode’. 🍌 When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.
Navigation in Erlang code (See also: ∑ Navigation)	The emacs-mode provides commands to navigate across Erlang source code. Most commands are specialization of the normal navigation commands which are described in the table ∑ Navigation, along with the other commands that are also available. The list below describe the specialized commands only. See the others inside ∑ Navigation, like the navigation by blocks.		
Go to beginning of statement	M-a	(backward-sentence &optional ARG)	Go backward to the beginning of an Erlang clause. <ul style="list-style-type: none"> With a numerical argument repeat that many times.
Go to the end of statement	M-e	(forward-sentence &optional ARG)	Go forward to the end of an Erlang clause. <ul style="list-style-type: none"> With a numerical argument repeat that many times.
Go to beginning of current function or top-level function	C-M-a	(c-beginning-of-defun &optional ARG)	Move backward to the beginning of an Erlang function. <ul style="list-style-type: none"> Every top level declaration that contains a brace paren block is considered to be a defun. With a positive argument, move backward that many defuns. A negative argument -N means move forward to the Nth following beginning.
Goto end of current function or top-level function	C-M-e	(c-end-of-defun &optional ARG)	Move forward to the end of an Erlang function. <ul style="list-style-type: none"> With argument, do it that many times. Negative argument -N means move back to Nth preceding end.
Backward to beginning of defun	<ul style="list-style-type: none"> C-M-a C-M-<home> <f6> p 	(beginning-of-defun &optional ARG)	Move backward to the beginning of an Erlang clause. <ul style="list-style-type: none"> With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun. ➡ Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M-<home>). However <f6> p handles Shift-marking fine in terminal mode.
Forward to end of defun	<ul style="list-style-type: none"> C-M-e C-M-<end> 	(end-of-defun &optional ARG)	Move forward to end of Erlang function. <ul style="list-style-type: none"> With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun. ➡ Shift marking is available in graphics mode, not in terminal mode (both keys).
Forward to start of next defun	<f6> n	(pel-beginning-of-next-defun ARG)	Move forward to the beginning of the next Erlang clause. ➡ Shift marking is available.
Highlighting blocks	The following commands can be used to activate or toggle useful modes to highlight blocks of (), {}, and []. <ul style="list-style-type: none"> show-paren-mode, which highlights the parens that matches the one before or after point. rainbow-delimiters mode, where matching nested parens are highlighted with the same colour. 		
Toggle show-paren mode on/off (see also: ∑ Highlight)	<ul style="list-style-type: none"> <f12> M-9 <M-f12> M-9 <f11> b h ((show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode). <ul style="list-style-type: none"> With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise. Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in ‘show-paren-style’ after ‘show-paren-delay’ seconds of Emacs idle time.
Enable/Disable coloured highlight of nested blocks (), {}, [] (see also: ∑ Highlight)	<ul style="list-style-type: none"> <f12> M-r <M-f12> M-r <f11> b h R 	(rainbow-delimiters-mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth. <ul style="list-style-type: none"> Customize the depth and colours with M-x customize-group rainbow-delimiters 📦 Requires: rainbow-delimiters.el 📖 PEL activates this when the pel-use-rainbow-delimiters customize variable is set to t.
Using Flymake to perform dynamic syntax checking	Flymake performs these checks while the user is editing. <div>  Flymake is activated for Erlang source code when pel-use-erlang-flymake user option is set to t. </div> <div>  Flymake has several customizable variables, which some listed here: </div> The following customization variables determine the exact circumstances whereupon Flymake decides to initiate a check of the buffer: <ul style="list-style-type: none"> flymake-start-on-flymake-mode : t to start checking when flymake-mode is started. nil to prevent check. flymake-no-changes-timeout : time to wait after last change to start checking. Default = 0.5 seconds. flymake-start-syntax-check-on-newline : t to check after insertion or removal of newline char from buffer. nil to prevent check. The following variable control navigation to next or previous error: <ul style="list-style-type: none"> flymake-wrap-around : If non-nil, moving to errors wraps around buffer boundaries. flymake-diagnostic-types-alist : Alist ((KEY . PROPS)*) of properties of Flymake diagnostic types. See Emacs documentation for more info. The M-n and M-p keys are mapped to flymake commands only when flymake-mode is turned on.		
Toggle Flymake mode on/off	<f12> F	(flymake-mode &optional ARG)	Toggle Flymake mode on or off. <ul style="list-style-type: none"> With a prefix argument ARG, enable Flymake mode if ARG is positive, and disable it otherwise. Flymake is an Emacs minor mode for on-the-fly syntax checking. Flymake collects diagnostic information from multiple sources, called backends, and visually annotates the buffer with the results.
Go to next flymake diagnostic	M-n	(flymake-goto-next-error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic. <ul style="list-style-type: none"> With a prefix arg, skip any diagnostics with a severity less than ‘:warning’. Display the error message in the echo line.
Go to previous flymake diagnostic	M-p	(flymake-goto-prev-error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic. <ul style="list-style-type: none"> With a prefix arg, skip any diagnostics with a severity less than ‘:warning’. Display the error message in the echo line.
Erlang Shell	On some systems the Erlang shell annoyingly echoes each typed command. If this is the case for your system, PEL provides a fix: <div>   To prevent the Erlang shell to echo every command, set the pel-erlang-shell-prevent-echo user option to t. After doing that execute pel-init or restart Emacs. </div>		
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.
Start Erlang Shell	<f11> x r	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer. <ul style="list-style-type: none"> The variable ‘erlang-shell-function’ decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started. C-c C-z starts the Erlang Shell from the Erlang Mode. <f11> x r starts it anytime, as long as it was installed. 📖 Under PEL this command is available only when the pel-use-erlang customize variable is set to t.
Compiling Erlang Code	The following commands are used to compile Erlang source code files to .beam files located in the same directory as the source code. Detected errors are listed in the “erlang” shell opened to compile the files. The buffer shows the location of error and the error description. The following commands are used to navigate to the next or previous detected error.		
Compile code	C-c C-k	(erlang-compile)	Compile Erlang module in current buffer. <ul style="list-style-type: none"> If buffer visiting file was modified and not saved, prompts the user to save it first. Opens and “erlang” shell, in which the Erlang compile is done with a eshell c() command. <ul style="list-style-type: none"> The buffer lists the errors. Hitting <RET> on the error file/line move point to that line in the Erlang file buffer. The <RET> key is bound to (compile-goto-error &optional EVENT) It’s also possible to use the next-error and previous error.

Description	Keystroke	Function	Note
Display compilation output	C-c C-l	(erlang-compile-display)	Display compilation output. <ul style="list-style-type: none"> Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.
Move to next compilation error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.
Move to previous compilation error	C-c C-p	(edts-code-previous-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.
	C-c C-a	(erlang-align-arrows START END)	Align arrows ("->") in function clauses from START to END. <ul style="list-style-type: none"> When called interactively, aligns arrows after function clauses inside the region. With a prefix argument, aligns all arrows, not just those in function clauses. Example: <pre> sum(L) -> sum(L, 0). sum([H T], Sum) -> sum(T, Sum + H); sum([], Sum) -> Sum. </pre> becomes: <pre> sum(L) -> sum(L, 0). sum([H T], Sum) -> sum(T, Sum + H); sum([], Sum) -> Sum. </pre>
Move to next compile error	<ul style="list-style-type: none"> C-x ` M-g n M-g M-n 	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; <ul style="list-style-type: none"> negative means move back to previous error messages. Just C-u as a prefix means reparse the error message buffer and start at the first error.
Move to previous compile error	<ul style="list-style-type: none"> M-g p M-g M-p 	(previous-error &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative).
Erlang Shell Command History	The following commands can be used to retrieve previously issued Erlang shell commands at the shell prompt. Note that the shell history is saved inside a file the is restored when opening a new shell: therefore commands from previously opened Erlang shells are also available.		
Next shell command	M-n	(comint-next-input ARG)	Cycle forwards through Erlang shell input history.
Previous shell command	M-p	(comint-previous-input ARG)	Cycle backwards through Erlang shell input history, saving input.
Using Man inside Emacs and support Erlang Man pages (See also: Σ Help/Info, Σ Shells)	Emacs provide 2 main commands to display man pages inside buffers. <ul style="list-style-type: none"> Both of these are much more powerful than the usual man reader available on the shell allowing navigation across man pages and opening hyperlinks. The man command uses the system man utility, while woman is a complete implementation. It has some formatting limitations compared to man but it's very useful in systems where man is not available. <p>To see Erlang man pages: On most systems the Man pages for Erlang are not available to the man utility and therefore not available for man inside Emacs. There are several ways this can be remedied:</p> <ul style="list-style-type: none"> One is to set the MANPATH environment variable to include the directory where these files are located. Then man can be used outside and inside Emacs to access Erlang's man pages. For example the following lines can be stored inside a shell script to do this: <pre> MANPATH=`manpath`:/usr/local/Cellar/erlang/22.3.4/lib/erlang/man export MANPATH </pre> Another way is to customize the Emacs Man-switches user option variable to something that includes the same directory. This will add the capability of Emacs man to fin the Erlang's man pages without modifying the capabilities of the parent shell. For example, if we want to use the same directory as the above example we need to set the Man-switches which is normally set to nil to the following value: <pre> "-M`manpath`:/usr/local/Cellar/erlang/22.3.4/lib/erlang/man" </pre> <p>The second alternative can be used to add other directories for the man pages of other programming languages while leaving the ability to have several shells that have their own value of MANPATH. That might be very useful for someone that uses different versions of Erlang in a system and needs access to the man pages of different versions of Erlang. It becomes possible to run different shells inside Emacs with each having its own value of MANPATH and therefore providing the man pages from different locations. It is also possible to place all of these directories inside the Man-switches or MANPATH and buses man's ability to view several pages for the same topic.</p>		
Open a man page inside an Emacs buffer	<ul style="list-style-type: none"> <f11> ? m ⌘-M 	(man MAN-ARGS)	Using man pages inside emacs is even better than using it from the shell because: <ul style="list-style-type: none"> the links are active and can be followed. When the man page describes a directory or file, emacs will open the file or the directory (in direct mode) when pressing <RET> over the link. You can navigate easily between sections (n/p will move to the next/previous section) You can use any of the searches. You can use any of the options to the man command at the prompt, like the -a option to access all man pages of the same name. Then use M-n and M-p to move from one to the other page, inside the same buffer. See all keys available in mode description (Use '<f1> m' or '<f11> ? k m') to do so.
Open a man page without external man process: woman	<f11> ? w	(woman &optional TOPIC RE-CACHE)	Open a man page file in Emacs using the woman mode, completely implemented in Emacs Lisp (and therefore without using the external 'man' process). That can be very useful under environments where man is not available (such as basic Windows).
Edit Erlang Code			
Create additional clause	C-c C-j	(erlang-generate-new-clause)	Create additional Erlang clause header. <ul style="list-style-type: none"> Parses the source file for the name of the current Erlang function. Create the header containing the name, a pair of parentheses, and an arrow. The space between the function name and the first parenthesis is preserved. The point is placed between the parentheses.
Indent Erlang function	C-c C-q	(erlang-indent-function)	Indent current Erlang function. This also works with a simple tab.
Clone clause arguments	C-c C-y	(erlang-clone-arguments)	Insert, at the point, the argument list of the previous clause. <ul style="list-style-type: none"> The mark is set at the beginning of the inserted text, the point at the end.
Move to beginning of clause	<ul style="list-style-type: none"> C-c M-a <F12> a 	(erlang-beginning-of-clause &optional ARG)	Move backward to previous start of clause. <ul style="list-style-type: none"> With argument, do this that many times.
Move to end of clause	<ul style="list-style-type: none"> C-c M-e <F12> e 	(erlang-end-of-clause &optional ARG)	Move to the end of the current clause. <ul style="list-style-type: none"> With argument, do this that many times.
Mark current clause	C-c M-h	(erlang-mark-clause)	Put mark at end of clause, point at beginning.
Show syntactic information	C-c C-s	(erlang-show-syntactic-information)	Show syntactic information for current line. <ul style="list-style-type: none"> Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.
Tempo Template Tag Insertion	C-c C-M-i	(tempo-complete-tag &optional SILENT)	Look for a tag and expand it. <ul style="list-style-type: none"> All the tags in the tag lists in 'tempo-local-tags' (this includes 'tempo-tags') are searched for a match for the text before the point. The way the string to match for is determined can be altered with the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all. If a single match is found, the corresponding template is expanded in place of the matching string. If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal. If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed.
Jump to previous tempo mark	C-c M-b	(tempo-backward-mark)	Jump to the previous mark in 'tempo-back-mark-list'.

