


Case Conversions

Operation	Keystroke	Function	Note
Upper/Lower/ Capital(Title) Case	<p>Emacs has 3 types of case conversion commands: to upper case, to lower case and to capital case (also called title case) where the first letter of a word is upper case and all the other letters are lower case.</p> <ul style="list-style-type: none">The main commands operate on words a concept that Emacs control via its syntax tables. What constitutes a word may be modified by changing the text mode, using the superword-mode or the subword-mode. The commands also operate on the letter where point (the cursor) is located. You need to position point at the beginning of the word to apply the conversion to all letters of the word.You can apply the word-related commands to several words, before and after point, using command prefixes.Emacs also provide commands that operate on a marked region. <p>➡ The PEL package provides more functionality with less key bindings. Plain Emacs uses M-l, C-x C-l, M-u, C-x C-u, and M-c for the case conversion operations. The PEL package uses only M-c, M-C and M-T key bindings which operate on the current word like the original commands, but also operate on the region if it is visible. They also operate on the complete word at point, regardless of point's position within the word if a 0 numerical argument is specified. The M-c and M-C commands capitalize word(s) when you use them to convert to the same case of the “criteria” character(s). This way if text is in lower case, you can capitalize each word using M-c and if text is in uppercase you can capitalize the word(s) with M-C. You can then perform all conversions with M-c and M-C, no other key is really required.</p> <p>➡ Note that M-T and M-C require the use of the Shift key. It's OK since the original commands break the region marking done with Shift pressed during navigation anyway. PEL frees the unused M-l, M-u, C-x C-l and C-x C-u for other bindings.</p> <p>➡✂ Also note that PEL uses M-u for undo, instead of up-casing.</p>		
Lowercase word(s) or all words in marked region ★ PEL Enhanced Key ★	<ul style="list-style-type: none">M-c<f11> t l	(pel-downcase-word-or-region &optional N)	<p>Downcase word(s) or all words in marked region.</p> <ul style="list-style-type: none">If no region marked, with:<ul style="list-style-type: none">no argument: downcase current word (from current position).N = 0: downcase current word (from start of current word)N > 0: downcase current word, N-1 following words and move forward.N < 0: downcase current word and N-1 previous words.For non-zero N, the conversion starts at point, not at the beginning of the word (unless point is at beginning of word).If region is marked: downcase all words in region.Note:<ul style="list-style-type: none">If "criteria" character is already a lower-case letter, the function capitalizes the word(s) instead. The "criteria" character is the first (or last) letter character at point of after (before) point depending of N's sign.This allows to use the key binding to downcase or capitalize a word.Uses: <i>downcase-word</i> <p>👉✂ This differs from the original Emacs binding for M-c.</p> <p>👉 Use the prefix numerical argument to control the text conversion. For example:</p> <ul style="list-style-type: none">M-2 M-c Convert current word and next word to lower case (or capitalized if the first word is already lower-case)M-- M-c Convert last word to lower case (or to capitalized if that word is already lower case).M-0 M-c Converts the complete current word to lower case (or to capitalized if it's already lower-case), regardless of point position within the word.M-c Converts the text starting at point to the end of current word to lower case (or capitalized if it's already lower-case).
Uppercase word(s) or all words in marked region ★ PEL Enhanced Key ★	<ul style="list-style-type: none">M-C<f11> t u	(pel-upcase-word-or-region &optional N)	<p>Upcase word(s) or all words in marked region.</p> <ul style="list-style-type: none">If no region marked, with:<ul style="list-style-type: none">no argument: upcase current word (from current position).N = 0: upcase current word (from start of current word)N > 0: upcase current word, N-1 following words and move forward.N < 0: upcase current word and N-1 previous words.For non-zero N, the conversion starts at point, not at the beginning of the word (unless point is at beginning of word).If region is marked: upcase all words in region.Note:<ul style="list-style-type: none">If 2 "criteria" characters are already upper-case letters, the function capitalizes the word(s) instead. The two "criteria" characters are the first (or last) two letter characters at point of after (before) point depending of N's sign.This allows to use the key binding to downcase or capitalize a word.Uses: <i>upcase-word</i> <p>👉 Press the Shift key (with M-c) to execute this command.</p> <p>👉 Use the prefix numerical argument to control the text conversion. For example:</p> <ul style="list-style-type: none">M-2 M-C Convert current word and next word to upper case (or capitalized if the first word is already upper-case)M-- M-C Convert last word to upper case (or to capitalized if that word is already upper case).M-0 M-C Converts the complete current word to upper case (or to capitalized if it's already upper-case), regardless of point position within the word.M-C Converts the text starting at point to the end of current word to upper case (or capitalized if it's already upper-case).
Title-case word(s) or all words in marked region ★ PEL Enhanced Key ★ ⚠ The M-T binding might be reassigned for other functionality in the future since the operation can be achieved via M-c or M-C.	<ul style="list-style-type: none">M-T<f11> t c	(pel-capitalize-word-or-region &optional N)	<p>Capitalize N word(s) or all words in marked region.</p> <ul style="list-style-type: none">If no region marked, with:<ul style="list-style-type: none">no argument: capitalize current word (from current position).N = 0: capitalize current word (from start of current word)N > 0: capitalize current word, N-1 following words and move forward.N < 0: capitalize current word and N-1 previous words.For non-zero N, the conversion starts at point, not at the beginning of the word (unless point is at beginning of word). Uses: <i>capitalize-word</i>.If region is marked:<ul style="list-style-type: none">if no prefix (N is nil): convert first letter of each word to upper/title case and convert all other word letters to lower case, using 'capitalize-region'.if N <0: convert first letter of each word to upper/title case but leave the rest unchanged. Uses <i>upcase-initials-region</i>. <p>👉 Press the Shift key (with M-t) to execute this command.</p>
Non-Required or modified keys	⚠ The following bindings exists in basic Emacs, but are either not required or have been re-assigned when PEL is used. These keys can be used for other operations. At the moment PEL rebinds some of them when respective packages are activated through customization.		
Uppercase word ✂ PEL uses this for undo.	M-u	(upcase-word ARG)	<p>Convert to upper case from point to end of word, moving over.</p> <ul style="list-style-type: none">If point is in the middle of a word, the part of that word before point is ignored when moving forward.With negative argument, convert previous words but do not move.
Upcase-region	C-x C-u	(upcase-region BEG END &optional REGION-NONCONTIGUOUS-P)	<p>Convert the region to upper case.</p>
Lowercase word ✂ PEL uses this for listing auto-completion menu.	M-l	(downcase-word ARG)	<p>Convert to lower case from point to end of word, moving over.</p> <ul style="list-style-type: none">If point is in the middle of a word, the part of that word before point is ignored when moving forward.With negative argument, convert previous words but do not move.

Operation	Keystroke	Function	Note
<u>Lowercase-region</u>	C-x C-1	(downcase-region BEG END &optional REGION-NONCONTIGUOUS-P)	Convert the region to lower case.
<u>Capitalize word</u>  PEL rebinds this key, see above.	M-c	(capitalize-word ARG)	Capitalize from point to the end of word, moving over. <ul style="list-style-type: none"> • With numerical argument ARG, capitalize the next ARG-1 words as well. • This gives the word(s) a first character in upper case and the rest lower case. • If point is in the middle of a word, the part of that word before point is ignored when moving forward. • With negative argument, capitalize previous words but do not move.