

# Basic Assembly Programming

Azlan Mukhtar  
CYSECA Solutions Sdn Bhd

- **x86 Basic Architecture**

- Introduction
- Endianness
- Registers and Flags
- Memory Addressing
- Stacks
- Signed number representations

- **Assembly Programming**

- Data movement
- Arithmetic operation
- Control structure
- Bitwise operation
- Data/Array manipulations
- Assembler

# Introduction to x86

---

- Started with 8086 in 1978
- Continued with 8088, 80186, 80286, 386, 486, Pentium, 686... Intel Core
- CISC architecture
- 32-bit is called x86-32 or IA-32
- 64-bit is called x86-64, AMD64, Intel 64

# Intel 80386

---

- Introduced in 1986
- Has a 32-bit word length
- Has eight general-purpose registers
- Supports paging and virtual memory
- Addresses up to 4GiB of memory
- Base for current x86 32 bit architecture

# Byte Order/Endianness

---

- Little Endian
  - On memory: 78 56 34 12
  - Actual value: 0x12345678
- Big Endian
  - On Memory: 12 34 56 78
  - Actual value: 0x12345678

# String Styles

---

- ASCIIZ – C-style

H	e	l	l	o	
48	65	6C	6C	6F	00

- Null-terminated Unicode

H		e		l		l		o			
48	00	65	00	6C	00	6C	00	6F	00	00	00

- Pascal

	H	e	l	l	o
05	48	65	6C	6C	6F

- Delphi

				H	e	l	l	o
05	00	00	00	48	65	6C	6C	6F

# Data Register Layout

---


## General-Purpose Registers

31	16	15	8	7	0	16-bit	32-bit
	AH		AL			AX	EAX
	BH		BL			BX	EBX
	CH		CL			CX	ECX
	DH		DL			DX	EDX
	BP						EBP
	SI						ESI
	DI						EDI
	SP						ESP

# Register Layout - Example

---

- EAX = 12345678h
- AX = 5678h
- AH = 56h
- AL = 78h



\* h is for hexadecimal notation

---



# Data Registers

Register	Description	Usage
AL / AH / AX/ EAX	Accumulator Register	Arithmetic operations
BL / BH / BX / EBX	Base register	General data storage, index
CL / CH / CX / ECX	Counter register	Loop constructs
DL / DH / DX / EDX	Data register	Arithmetic

# Data Register - Example

---

- Accumulator
- `ADD EAX, EBX ; add the value in EBX and EAX, and store the  
; result into EAX`
- `SUB EAX, EBX ; substitute the value in EBX from EAX, and  
; store the result into EAX`
- `IMUL EAX, EBX ; multiply EAX and EBX, and store the result  
; into EAX`
- More about this later

# Address Registers

Register	Description	Usage
IP / EIP	Instruction Pointer	Program execution counter
SP / ESP	Stack Pointer	ESP will hold an offset to top of stacks memory location
BP / EBP	Base Pointer	Stack frame
SI / ESI	Source Index	String operation
DI / EDI	Destination Index	String operation

# Segment Registers

Register	Description	Usage
CS	Code Segment	Program code
DS	Data Segment	Program data
SS	Stack Segment	Stack
ES / FS /GS	Other Segments	Other uses

# Segment Registers

---


- However, modern Operating System such as Windows, Mac OS X, Linux are using protected mode flat model and segment registers are less relevant. CS, DS, SS, and ES are pointing to the same location, which is 0 offset.
- Windows NT is utilizing FS register to store Process Environment Block and Thread Information Block (TIB)
  - [https://en.wikipedia.org/wiki/Process\\_Environment\\_Block](https://en.wikipedia.org/wiki/Process_Environment_Block)
  - [http://en.wikipedia.org/wiki/Win32\\_Thread\\_Information\\_Block](http://en.wikipedia.org/wiki/Win32_Thread_Information_Block)

# EFLAGS Register (bit 0 – 15)

S	Status Flag
C	Control Flag
X	System Flag

15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
0	NT	IOPL		OF	DF	IF	TF	SF	ZF	0	AF	0	PF	1	CF

X	Nested Task
X	IO Privilege Level
S	Overflow Flag
C	Direction Flag
X	Interrupt Enable Flag
X	Trap Flag
S	Sign Flag
S	Zero Flag
S	Auxiliary Carry Flag
S	Parity Flag
S	Carry Flag



# EFLAGS Register (bit 16 – 31)

S	Status Flag
C	Control Flag
X	System Flag

31	30	29	28	27	26	25	24	23	22	21	20	19	18	17	16
0	0	0	0	0	0	0	0	0	0	ID	VIP	VIF	AC	VM	RF

X	ID Flag
X	Virtual Interrupt Pending
X	Virtual Interrupt Flag
X	Alignment Check
X	Virtual 8086 Mode
X	Resume Flag

# EFLAGS Register – Status Flags

---

- ZF - Zero flag - Set if the result is zero; cleared otherwise.
- SF - Sign flag - Set equal to the most-significant bit of the result, which is the sign bit of a signed integer. (0 indicates a positive value and 1 indicates a negative value.)
- CF - Carry flag - Set if an arithmetic operation generates a carry or a borrow out of the most significant bit of the result; cleared otherwise. This flag indicates an overflow condition for unsigned-integer arithmetic. It is also used in multiple-precision arithmetic.
- OF - Overflow flag - Set if the integer result is too large a positive number or too small a negative number (excluding the sign-bit) to fit in the destination operand; cleared otherwise. This flag indicates an overflow condition for signed-integer (two's complement) arithmetic.
- AF - Adjust flag - Set if an arithmetic operation generates a carry or a borrow out of bit 3 of the result; cleared otherwise. This flag is used in binary-coded decimal (BCD) arithmetic. (Rarely Used)
- PF - Parity flag - Set if the least-significant byte of the result contains an even number of 1 bits; cleared otherwise. (Rarely Used)



# EFLAGS Registers – DF FLAG

---

- The direction flag (DF, located in bit 10 of the EFLAGS register) controls string instructions (MOVS, CMPS, SCAS, LODS, and STOS). Setting the DF flag causes the string instructions to auto-decrement (to process strings from high addresses to low addresses). Clearing the DF flag causes the string instructions to auto-increment (process strings from low addresses to high addresses).
- The STD and CLD instructions set and clear the DF flag, respectively.

# EFLAGS Register – Flags Changing Instructions

---

- Instruction that affecting flags
  - ADD/SUB – Modifies Flags: AF CF OF PF SF ZF
  - CMP- Modifies Flags: AF CF OF PF SF ZF
  - TEST - Modifies Flags: CF OF PF SF ZF (AF undefined)
  - CLD/STD – Modifies Flags: DF

# Signed number representations

## – Two's Complement

---

- 8 bit [two's complement](#)

Binary Value	Hex Value	Two's Complement	Unsigned
00000000	0x00	0	0
00000001	0x01	1	1
...	...	...	..
01111110	0x7E	126	126
01111111	0x7F	127	127
10000000	0x80	-128	128
10000001	0x81	-127	129
10000010	0x82	-126	130
...	...	...	...
11111110	0xFE	-2	254
11111111	0xFF	-1	255

# Two's Complement – How to convert

---

- Method one

Steps	Example 1	Example 2
1. Starting from the right, find the first '1'	010100 <b>1</b>	0101 <b>1</b> 00
2. Invert all of the bits to the left of that one	<b>1101011</b> 1	<b>1010</b> 100

- Method two

Steps	0000000 <b>1</b>
1. Invert all the bits through the number	11111110
2. Add one	1111111 <b>1</b>

- Method three

- Use x86 instruction for Two's Complement Negation, NEG
- Example – NEG EAX

# Two's Complement - examples

---

Example 1:

```
mov al, 0x05
```

```
add al, 0xFE    ; 0xFE = -2 or 0xFE = 254
```

⇒ al = 3

Example 2:

```
mov al, 0x02
```

```
add al, 0xFA    ; 0xFA = -6 or 0xFA = 250
```

⇒ al = 0xFC ; 0xFC = -4 or 0xFC = 252

# Basic x86 Assembly instructions

---

- Data Transfers
- Arithmetic
- Logic
- Jumps
- Misc

# Reading the x86 Manual (RTxM)

---

## MOVZX - Move with Zero-Extend

0F B6 / r	MOVZX r16,r/m8	Move byte to word with zero-extension
0F B6 / r	MOVZX r32,r/m8	Move byte to doubleword, zero-extension
0F B7 / r	MOVZX r32,r/m16	Move word to doubleword, zero-extension

### Description

Copies the contents of the source operand (register or memory location) to the destination operand (register) and zero extends the value to 16 or 32 bits. The size of the converted value depends on the operand-size attribute.

Operands	Bytes	Clocks
reg, reg	3	3 NP
reg, mem	3+d(0,1,2,4)	3 NP
(Note: destination reg is 16 or 32-bits; source is 8 or 16 bits)		
Flags Affected None.		

# Reading the x86 Manual – cont.

---

r Any general register

r8 One of the byte general-purpose registers AL, CL, DL, BL, AH, CH, DH, or BH.

r16 One of the word general-purpose registers AX, CX, DX, BX, SP, BP, SI, or DI.

r32 One of the doubleword general-purpose registers EAX, ECX, EDX, EBX, ESP, EBP, ESI, or EDI.

m A 16- or 32-bit operand in memory.

m8 A byte operand in memory, usually expressed as a variable or array name, but pointed to by the DS:(E)SI or ES:(E)DI registers. This nomenclature is used only with the string instructions and the XLAT instruction.

m16 A word operand in memory, usually expressed as a variable or array name, but pointed to by the DS:(E)SI or ES:(E)DI registers. This nomenclature is used only with the string instructions.

....

And so on, please refer the [docs](#), Volume 2, Chapter 3.1 - Interpreting The Instruction Reference Pages

---



# Data Transfer Instructions

---

- MOV - Move data between general-purpose registers; move data between memory and general purpose or segment registers; move immediates to general-purpose registers
- MOVSX - Move and sign extend
- MOVZX - Move and zero extend
- PUSH - Push onto stack
- POP - Pop off of stack
- XCHG - Exchange
- BSWAP - Byte swap - converts between 32 bit little endian and big endian values
- PUSHA/PUSHAD - Push general-purpose registers onto stack
- POPA/POPAD - Pop general-purpose registers from stack
- CWD/CDQ - Convert word to doubleword/Convert doubleword to quadword
- CBW/CWDE - Convert byte to word/Convert word to doubleword in EAX register

# Binary Arithmetic Instructions

---

- ADD - Integer add
- ADC - Add with carry
- SUB - Subtract
- SBB - Subtract with borrow
- IMUL - Signed multiply
- MUL - Unsigned multiply
- IDIV - Signed divide
- DIV - Unsigned divide
- INC - Increment
- DEC - Decrement
- CMP - Compare – (Similar to SUB but the result is not stored (discarded) and the flags are changed)
- NEG - Negate

# Logical Instructions

---

- AND - Perform bitwise logical AND
- OR - Perform bitwise logical OR
- XOR - Perform bitwise logical exclusive OR
- NOT - Perform bitwise logical NOT

# Shift and Rotate Instructions

---

- SAR - Shift arithmetic right
- SHR - Shift logical right
- SAL/SHL - Shift arithmetic left/Shift logical left
- SHRD - Shift right double
- SHLD - Shift left double
- ROR - Rotate right
- ROL - Rotate left
- RCR - Rotate through carry right
- RCL - Rotate through carry left

# Control Transfer Instructions

---

- JMP - Jump
- JE/JZ - Jump if equal/Jump if zero
- JNE/JNZ - Jump if not equal/Jump if not zero
- JA/JNBE - Jump if above/Jump if not below or equal
- JAE/JNB - Jump if above or equal/Jump if not below
- JB/JNAE - Jump if below/Jump if not above or equal
- JBE/JNA - Jump if below or equal/Jump if not above
- JG/JNLE - Jump if greater/Jump if not less or equal
- JGE/JNL - Jump if greater or equal/Jump if not less
- JL/JNGE - Jump if less/Jump if not greater or equal
- JLE/JNG - Jump if less or equal/Jump if not greater
- JC - Jump if carry

# Control Transfer Instructions - continue

---

- JNC - Jump if not carry
- JO - Jump if overflow
- JNO - Jump if not overflow
- JS - Jump if sign (negative)
- JNS - Jump if not sign (non-negative)
- JPO/JNP - Jump if parity odd/Jump if not parity
- JPE/JP - Jump if parity even/Jump if parity
- JCXZ/JECXZ - Jump register CX zero/Jump register ECX zero
- LOOP - Loop with ECX counter
- LOOPZ/LOOPE - Loop with ECX and zero/Loop with ECX and equal
- LOOPNZ/LOOPNE - Loop with ECX and not zero/Loop with ECX and not equal

# Control Transfer Instructions - continue

---

- CALL Call procedure
- RET Return
- IRET Return from interrupt
- INT Software interrupt
- ENTER High-level procedure entry
- LEAVE High-level procedure exit

# String Instructions

---

- MOVS/MOVS<sub>B</sub> Move string/Move byte string
- MOVS/MOVS<sub>W</sub> Move string/Move word string
- MOVS/MOVS<sub>D</sub> Move string/Move doubleword string
- CMPS/CMPS<sub>B</sub> Compare string/Compare byte string
- CMPS/CMPS<sub>W</sub> Compare string/Compare word string
- CMPS/CMPS<sub>D</sub> Compare string/Compare doubleword string
- SCAS/SCAS<sub>B</sub> Scan string/Scan byte string
- SCAS/SCAS<sub>W</sub> Scan string/Scan word string
- SCAS/SCAS<sub>D</sub> Scan string/Scan doubleword string



# String Instructions - Continue

---

- LODS/LODSB Load string/Load byte string
- LODS/LODSW Load string/Load word string
- LODS/LODSD Load string/Load doubleword string
- STOS/STOSB Store string/Store byte string
- STOS/STOSW Store string/Store word string
- STOS/STOSD Store string/Store doubleword string
- REP Repeat while ECX not zero
- REPE/REPZ Repeat while equal/Repeat while zero
- REPNE/REPNZ Repeat while not equal/Repeat while not zero

# Miscellaneous Instructions

---

- LEA Load effective address
- NOP No operation

# Examples of Mnemonics

mnemonic argument1, argument2, argument3	
MOV EAX, 1	Move 1 to EAX
ADD EDX, 5	Add 5 to EDX
SUB EBX, 2	Subtract 2 from EBX
AND ECX, 0	Bit-wise AND 0 to ECX
XOR EDX, 4	Bit-wise eXclusive OR 4 to EDX
SHL ECX, 6	Shift ECX left by six
ROR EBX, 3	Bit-wise rotate EBX right by 3
INC ECX	Increment ECX

# Addressing Memory

---

- `mov eax, [ebx]`  
; Move the 4 bytes in memory at the address contained in EBX into EAX
- `mov [var], ebx`  
; Move the contents of EBX into the 4 bytes at memory address var.  
(Note, var is a 32-bit constant).
- `mov eax, [esi-4]`  
; Move 4 bytes at memory address ESI + (-4) into EAX
- `mov [esi+eax], cl`  
; Move the contents of CL into the byte at address ESI+EAX
- `mov edx, [esi+4*ebx]`  
; Move the 4 bytes of data at address ESI+4\*EBX into EDX
- **If we replace mov with lea, then we will get the address, example:**  
`lea edx, [esi+4*ebx]`

# Addressing Memory – With Size Directive

---

- `mov BYTE PTR [ebx], 2`  
; Move 2 into the single byte at the address stored in EBX.
- `mov WORD PTR [ebx], 2`  
; Move the 16-bit integer representation of 2 into the 2 bytes starting at the address in EBX.
- `mov DWORD PTR [ebx], 2`  
; Move the 32-bit integer representation of 2 into the 4 bytes starting at the address in EBX.

# Microsoft Macro Assembler

---

- Why MASM
  - Free (comes with Visual C++ Express/Community)
  - Can use Visual Studio IDE for Coding and Debugging

# Microsoft Macro Assembler (MASM)

```
.386
.model flat, stdcall
option casemap :none    ; case sensitive

include \masm32\include\windows.inc
include \masm32\include\user32.inc
include \masm32\include\kernel32.inc

includelib \masm32\lib\user32.lib
includelib \masm32\lib\kernel32.lib

.data
szTitle db 'Win32', 0
szMessage db 'Hello World', 0

.code
start:
push 0                ; uType = MB_OK
push offset szTitle   ; LPCSTR lpCaption
push offset szMessage ; LPCSTR lpText
push 0                ; hWnd = HWND_DESKTOP
call MessageBoxA
push 0
call ExitProcess

end start
```

# Netwide Assembler (NASM) - Alternative

```
; Assemble: nasm -f win32 hello_nasm.asm
; Link: link hello_nasm.obj user32.lib /entry:main
; (using Visual C++'s linker)

extern _MessageBoxA@16

segment .text
global _main

_main:
    push dword 0      ; uType = MB_OK
    push szTitle      ; LPCSTR lpCaption
    push szMessage     ; LPCSTR lpText
    push dword 0      ; hWnd = HWND_DESKTOP
    call _MessageBoxA@16
    ret

segment .data
szMessage: db 'Hello World',0
szTitle: db 'Program Title',0
```



# FASM – Arithmetic – Alternative

```
format PE Console 4.0
entry start

include 'win32a.inc'

section '.text' code readable executable
start:
xor    eax, eax
add    eax, 8
mov    ecx, 2
sub    eax, ecx
mul    ecx
push   eax
push   szResult
call   [printf]
add    esp, 8
ret

section '.data' data readable writeable
szResult    db "The result is: %d",10,0

section '.idata' import data readable
library msvcrt,'msvcrt.dll'

import msvcrt,\
printf,'printf'
```

# References

---

## **Intel® 64 and IA-32 Architectures Software Developer Manuals**

<http://www.intel.com/content/www/us/en/processors/architectures-software-developer-manuals.html>

## **80x86 Instruction Set cheatsheet**

<http://www.jegerlehner.ch/intel/>

## **x86 Assembly**

[http://en.wikibooks.org/wiki/X86\\_Assembly](http://en.wikibooks.org/wiki/X86_Assembly)

[http://en.wikibooks.org/wiki/X86\\_Disassembly](http://en.wikibooks.org/wiki/X86_Disassembly)

<http://www.cs.virginia.edu/~evans/cs216/guides/x86.html>