

Accessibility issues with the 'Mark-the-words' H5P content type when working with the ChromeVox screen reader.

- **Issue:** No way to move quickly to the beginning or end of the list.
- **Fixed:** Now the user can use the 'Home' and 'End' buttons to move quickly to the start and end of the list of words respectively. In addition, hidden instructions were added to indicate the new keyboard navigation shortcuts.

- **Issue:** When the user selects a word with the 'spacebar' key (to mark it), it doesn't tell the user they selected (i.e. marked) the word.
- **Fixed:** Now it says "Clicked button".

- **Issue:** When reading word-by-word, it doesn't indicate if a word was marked or not.
- **Fixed:** Now it says "Button pressed".

- **Issue:** When reading word-by-word, it says the word and then the word "button".
- **Suggested fix:**
 - By default, don't set the role of the words in the list to "button". Then, when the user selects a word, add the role "button" so that later ARIA can read that the button was marked. On the other hand, if a selected word is unselected, remove the role "button".
 - In addition, indicate when the list of words starts and ends with the hidden text "Begin list" and "End list", respectively.
 - Include hidden instructions that indicate that for this content type the keywords "Begin list" and "End list".

- **Issue:** After clicking the 'Check' and/or the "Check solution" buttons to check whether or not the marked words were correct or to see the words that should have been marked, there is no way for users to go back (with the keyboard) to read the list of words word-by-word. It follows then that the user can't go back to check which words were correctly or incorrectly marked and, in general, to see the solution. (Note: If you **click** on the marked words, it doesn't tell you if they were correct/wrong.)
- **Suggested fix:** Allow users to navigate through the list of words with the keyboard.