

ASTSConnectivity API

**Application Programming Interface
for connecting external systems to the
Moscow Exchange ASTS Trading & Clearing
System**

(MTESRL v. 4.2)


TABLE OF CONTENTS

| | |
|--|----|
| INTRODUCTION | 3 |
| MTESRL LIBRARY | 3 |
| HARDWARE AND SOFTWARE REQUIREMENTS..... | 3 |
| WORK SCENARIO..... | 4 |
| CONNECTION TO THE SERVER | 4 |
| CONNECTING TO ASTSBridge | 4 |
| SELECTING THE LIST OF BOARDS..... | 7 |
| OBTAINING SYSTEM AND SERVICE INFORMATION..... | 8 |
| BRIDGE SERVER DETAILS | 8 |
| BRIDGE CLIENT LIBRARY VERSION..... | 9 |
| OBTAINING CONNECTION STATUS..... | 10 |
| OBTAINING CONNECTION STATISTICS..... | 10 |
| OBTAINING INFORMATION OBJECTS DESCRIPTION | 11 |
| WORKING WITH INFORMATION OBJECTS | 13 |
| TRANSACTIONS EXECUTION..... | 13 |
| WORKING WITH TABLES..... | 16 |
| Opening a table..... | 17 |
| Request for update | 17 |
| Closing the table | 18 |
| Example..... | 19 |
| Notes on Working with Tables | 20 |
| MEMORY USE OPTIMIZATION..... | 21 |
| RECOVERY AFTER FAILURES AT ASTSBRIDGE SERVER | 21 |
| BACKING UP BRIDGE INTERNAL STRUCTURE | 21 |
| BRIDGE INTERNAL STRUCTURE RECOVERY | 23 |
| EXAMPLE OF RECOVERY AFTER THE FAILURE | 26 |
| SELECTIVE OPENING OF TABLES FROM THE SNAPSHOT..... | 26 |
| CLOSING CONNECTION SESSION | 28 |
| ERROR MESSAGES | 29 |
| ERROR CODES..... | 29 |
| APPENDIX 1. BUFFER FORMAT OF THE MTESTRUCTURE, MTESTRUCTURE2 AND MTESTRUCTUREEX FUNCTIONS | 31 |
| APPENDIX 2. BUFFER FORMAT OF THE MTEOPENTABLE FUNCTION..... | 34 |
| APPENDIX 3. BUFFER FORMAT OF THE MTEREFRESH FUNCTION | 35 |
| APPENDIX 4. BASIC TYPES | 35 |
| APPENDIX 5. FORMAT OF THE FLOAT, FIXED, DATE, TIME, FLOATPOINT FIELD TYPES | 36 |

INTRODUCTION

ASTSConnectivity API should be used to connect any types of external systems to the Moscow Exchange ASTS Trading & Clearing System. These could be: brokerage systems, market data vending systems, risk-management systems, technical analysis applications, etc.

System architecture is shown on following diagram:



This document details creation of client applications using ASTSConnectivity API. All the required functions are included into MTESrI library.

MTESRL LIBRARY

MTESrI library provides bidirectional connection to the ASTS Trading & Clearing System (TS) and contains functions for both receiving data from TS (general market data such as trades, quotes, financial instruments as well as company specific trading information) and executing transactions (order entry and withdrawal). Library supports all the Moscow Exchange markets powered by the ASTS platform: Equity & Bond ("Main Market" sector), FX, Derivatives, Government Securities and Commodity Markets.

HARDWARE AND SOFTWARE REQUIREMENTS

MTESrI library is compatible with the following operating systems:

- Windows 2000/XP/Vista/7 or Windows Server 2003/2008, 32 or 64 bit (mtesrl[64].dll);
- Linux OS family, both 32 or 64 bit (libmtesrl.so). Note: The cdecl calling convention is used.

There are two versions of MTESRL library which differ in way of connection to TS:

- Connection to the trading system through ASTSBridge (using TCP/IP protocol) or TEServer (outdated, RS-232);
- Direct connection to the trading system. This version of library can only be used at the co-location facility.

Minimal hardware requirements for MTESRL:

- CPU: Intel Core 1.4GHz or higher;
- RAM – 1GB or more;
- HDD with 10 GB free space for logging;
- Ethernet network card (for ASTSBridge) and RS-232 serial port (only for TEServer version of the Bridge).

WORK SCENARIO

The typical work scenario is as follows:

1. Connect to the server.
2. Download the information object metadata (types, tables and transactions).
3. Open and refresh tables. Send transactions.
4. Save snapshots (optional).
5. Close the connection.

There are interface modules for library as well as Delphi and MS VC 6 samples in the Demo subdirectory of installation folder.

CONNECTION TO THE SERVER

CONNECTING TO ASTSBridge

MTEConnect function is used to connect to the Trading System through the ASTSBridge Server. This function should be called before proceeding to any other library functions.

C++

```
int32 WINAPI MTEConnect(char *Params, char *ErrorMsg);
```

Pascal

```
function MTEConnect(Params, ErrorMsg: LPSTR): Integer; stdcall;
```

Arguments:

Params

Connection parameters. This is a pointer to an ASCIIZ-string, which contains the list of parameters separated with the “end of line” and “carriage return” symbols (0x0D, 0x0A) with the following syntax:

```
Parameter1=Value1
Parameter2=Value2
...
ParameterN=ValueN
```

Denominations of parameters and their possible values depend on the method of connection of a specific library to the trading system. The following parameters are available for the MTESRL library:

Connecting to ASTSBridge

| | |
|----------------------|--|
| HOST | List of comma-separated IP addresses with ports; for example: “194.186.240.85:20006,194.186.240.73:20006”. |
| PREFERREDHOST | Preferred host address. If not defined, server with the least traffic from the “HOST” list is used. |
| SERVER | Server ID, for example: “EQ_TEST”. |
| USERID | User ID in the Trading System. |
| PASSWORD | User password in the Trading System. |
| INTERFACE | Trading System interface ID that user is going to work with. For |

| | |
|--------------------|---|
| | example, "IFCBroker15A". |
| BOARDS | List of boards that user is going to work with; for example: "EQBR,EQNO,EQNL,PSEQ" (this is an optional parameter, if not defined, all boards are available). |
| COMPRESSION | Compression of transmitted data: "0" – no compression (fast on wide network channels); "1" – ZLIB compression (medium compression); "2" – compress large network packets with BZIP (maximum compression). Level 2 is used by default. |

Encryption and digital signature "Validata" configuration

Validata.ProfileName - cryptographic "Validata" library profile name (optional; if not defined then neither digital signature nor encryption will be used); the old PROFILENAME parameter is still supported; it's also possible to specify the name "My" – in this case application will prompt for a profile;

Validata.BasePath and **Validata.LdapPath** - another method to initialize Validata. It could be useful when Validata has been installed with another user's system account – for example, when the client application is started as a service. In such situation there will be no profile name in user's registry branch and the ProfileName could not be used. Values for these parameters should be taken from the appropriate user's branch in the system registry:

Validata.BasePath is stored in

HKEY_CURRENT_USER\Software\MDPREI\mpki\Profiles\0\BasePath

Validata.LdapPath is stored in

HKEY_CURRENT_USER\Software\MDPREI\mpki\store\2\name

Validata.InitFlags a set of Validata initialization flags:

- 1 - Do not update the list of recalled certificates at initialization;
- 2 - Show expiring objects during initialization;
- 4 - Do not use network directories;
- 8 - Do not unload digital key at shutdown.

Connecting via «embedded» bridge at colocation facility

| | |
|----------------------|---|
| SERVER | Trading system Server Name, e.g., «GATEWAY». |
| SERVICE | Trading system Service Name, e.g., «gateway». |
| BROADCAST | Broadcast address for the server search to access the trading system, e.g., «195.1.1.255,195.1.2.255». |
| PREFBROADCAST | Preferred broadcast server address. |
| USERID | Client user ID in Trading System. |
| PASSWORD | User password in Trading System. |
| INTERFACE | ID of the bridge interface, which user is going to work with. |
| BOARDS | List of boards that the user is going to work with; for example: "EQBR,EQNO,EQNL,PSEQ" (this is the optional parameter; if not defined, all boards are available). |
| CACHEFOLDER | Directory for caching interface description, downloaded from trading system. If this parameter is not defined, caching is not performed, and interface is downloaded from Trading System at each connection. |
| LOGLEVEL | Level of TSMR internal logging: "0" – logging is disabled (default value); "1" – "30" – logging level. |
| COMPRESSION | TSMR compression: "0" – no compression; "1" – compression is enabled (default value). |
| IPSRCORDER | List of IP addresses of network interfaces that are allowed to connect to Trading System. The order of IP addresses in the list defines the priority. If RestrictList=0, connection attempts from all other addresses |

| | |
|---------------------|--|
| | are allowed, but with a lower priority. If RestrictList=1, only attempts from specified addresses are available, e.g. "192.168.126.1, 192.168.56.1". |
| RESTRICTLIST | <p>"0" – searching for gateways is allowed from all available network interfaces (default value);</p> <p>"1" – searching for gateways is allowed only from interfaces, listed in IpSrcOrder attribute.</p> |

Note: to disable data compression in colocation mode create (or edit) TSMR.INI file and add CompressionMode=0 parameter to the [TSMR] section.

Also, in all of the cases the following parameters are supported:

| | |
|--------------------|--|
| TIMEOUT | Server (i.e. trading system) request execution timeout. For mtesrl.dll – in milliseconds, for embedded-mtesrl.dll ("embedded" Bridge) – in seconds. Default value is 30 seconds. If reply from server is not received within specified time, the reconnection procedure will be initiated. If connection interrupt is registered before the timeout expire – reconnection procedure will begin earlier. |
| LOGGING | <p>String in the format "N,M", where first digit "N" – API MTESRL calls logging level.</p> <p>"0" – no logging (do not create log-file);</p> <p>"1" – log errors only;</p> <p>"2" – log library function calls;</p> <p>"3" – log contents of table;</p> <p>"4" – log contents of table and field numbers;</p> <p>"5" – log TSMR protocol messages (only for colocation version).</p> <p>Second digit "M" – connection statistics logging level. Statistics is stored in a separate file formatted «mtesrl-YYYYMMDD-<userid>-stats.log».</p> <p>"0" – do not collect statistics;</p> <p>"1" – collect statistics on query execution time and the trading system response size;</p> <p>"2" – Collect statistics and requests distribution on requests to the tables.</p> <p>Default value for logging is 2,2.</p> <p>For a complete logging disabling, use "LOGGING=0,0"</p> <p>Log files are kept for 7 calendar days. All the older logs are deleted when the MTEConnect function is called.</p> |
| RETRIES | Number of attempts to reconnect after the loss of connection with ASTSBridge Server (10 by default); |
| CONNECTTIME | Maximum reconnect time in ms. Default is 1 minute (60000). Any value between 5 and 300 sec. can be specified. Reconnection lasts not more than [RETRIES] attempts and no longer than [CONNECTTIME] ms, depending on which event comes first. This value is approximate and may differ from a real one for several seconds. |
| LOGFOLDER | A folder to store the log files. By default, library folder is used. |
| FEEDBACK | Free formatted text string, describing the client system, connected to the bridge. For example, «FondAnalytic v3.5.456, e-mail: admin@fondru.ru». |
| LANGUAGE | Specify the language for messages issued by the Bridge and MTESRL client library. To change the language use transaction CHANGE_LANGUAGE. Possible values are "Russian" and "English". |

ErrorMsg

A pointer to a buffer of at least 256 bytes to store error description, in case an error occurs.

Returned value:

If connection is successful, the function returns a descriptor of the established connection (value that is greater or equal to MTE_OK). The received connection descriptor is used during execution of all MTExxxx functions.

If error occurs, one of the MTE_xxxx error codes is returned and error description is placed to ErrorMsg argument.

Example:

Connect through the COM1 port at the baud rate of 115200 baud.

C++

```
int32 Idx;
char ErrorMsg[255];
...
Idx = MTEConnect("PORT=COM1\rBAUDRATE=115200", ErrorMsg);
if( Idx < MTE_OK )
{
    fprintf(stderr, "Error while establishing the connection: %s",
    ErrorMsg);
    exit(1);
}
else
    fprintf(stdout, "Connection established.");
```

Pascal

```
Idx: Integer;
ErrorMsg: TMTEErrorMsg;
...
Idx := MTEConnect('PORT=COM1'#13#10'BAUDRATE=115200', @ErrorMsg);
if Idx < MTE_OK then
begin
    Writeln(Error while establishing the connection: ' + ErrorMsg);
    Halt;
end
else
    Writeln('Connection established.');
```

SELECTING THE LIST OF BOARDS

Usually, the list of boards is defined in "BOARDS=" parameter, when calling MTEConnect function. But also can be selected later, using MTESelectBoards. It's allowed to use only one method of these two for selecting boards. After calling MTESelectBoards, close all the tables and open them again, because all the tables content depends on selected boards.

C++

```
int32 WINAPI MTESelectBoards(int32 Idx, char * BoardsList,
                             char *result);
```

Pascal

```
function MTESelectBoards(Id: Integer; BoardList: LPSTR;
                          ResultMsg: LPSTR): Integer; stdcall;
```

Аргументы:

Idx

A descriptor of connection, for which, the data should be received.

BoardList

A pointer to the string, containing a list of boards' identifiers, separated by comma. For example, "EQBR,EQNE,RPMA".

ResultMsg

A pointer to a buffer of at least 256 bytes to store the text string with transaction result in case of successful execution.

Returned value:

If the transaction has been processed by the trading system, it returns the following:

MTE_OK – boards selected;

MTE_TRANSREJECTED - request has been processed, but rejected by the trading system (an invalid board specified, no rights to perform, etc.);

MTE_TSMR - fatal error occurred, when executing the query (the loss of connection with the trading system, etc.).

A text string with query result is placed into *ResultMsg* argument.

If error occurs, one of the MTE_xxxx error codes is returned. In this case a value of *ResultMsg* is not defined.

OBTAINING SYSTEM AND SERVICE INFORMATION

BRIDGE SERVER DETAILS

To get additional details about the server side of ASTSBridge, use `MTEGetServInfo` function.

C++

```
int32 WINAPI MTEGetServInfo(int32 Idx, char ** ServInfo, int *Len);
```

Pascal

```
function MTEGetServInfo(Idx: Integer; var ServInfo: LPSTR;  
    var Len: Integer): Integer; stdcall;
```

Arguments:

Idx

A descriptor of connection, for which, the data should be received.

ServInfo

A pointer to a buffer to store returned values.

Len

A pointer to a variable to store the length of returned data.

Returned value:

If successful, MTE_OK is returned and *ServInfo* points to a buffer of the following structure:

| Field | Data type (IBM PC) | Length, bytes | Description |
|--------------------|--------------------|---------------|--|
| Connected_To_Micex | INTEGER | 4 | Connection status. Possible values: 0 – not connected; 1 - connected to production environment; 2 - connected to test environment. |
| Session_Id | INTEGER | 4 | Current trading session internal ID. Changes each session. |
| MICEX_Sever_Name | CHAR | 33 | Access server logical name. For example, GATEWAY, FOND_GATEWAY, etc. Can be used to identify a market and type of the system (test or production). |
| Version_Major | CHAR | 1 | ASTSBridge major version number. |
| Version_Minor | CHAR | 1 | ASTSBridge minor version number. |
| Version_Build | CHAR | 1 | ASTSBridge build number. This and two previous fields identify the version as Major.Minor.Build. |
| Beta_version | CHAR | 1 | ASTSBridge beta version flag. If not 0, then, this is |

| | | | |
|----------------|------------------------------|----------|--|
| | | | beta version with a corresponding number. |
| Debug_flag | CHAR | 1 | ASTSBridge debug version flag. If not 0, then this is a debug version. |
| Test_flag | CHAR | 1 | ASTSBridge test release flag. If not 0 then, this is a test version. |
| Start_Time | INTEGER | 4 | Session start time (defined in the Bridge INI file). Specified as HHMMSS. <u>Note:</u> Must be an integer value. |
| Stop_Time_Min | INTEGER | 4 | Bridge shutdown time (defined in the Bridge INI file). Specified as HHMMSS. <u>Note:</u> Must be an integer value. |
| Stop_Time_Max | INTEGER | 4 | Equals to Stop_Time_Min. |
| Next_Event | INTEGER | 4 | Next expected event in the server schedule. Possible values: 0 – waiting for a new trading session startup; 1 – waiting for a current trading session end. |
| Event_Date | INTEGER | 4 | Date of an expected event as DDMMYYYY. <u>Note:</u> Must be an integer value. |
| BoardsSelected | ASCIIZ string | variable | Comma separated list of selected trading boards. |
| UserID | CHAR, null terminated string | 13 | User ID used by the server for current connection. |
| SystemId | CHAR | 1 | Trading system type: “P” – equities & bonds or government securities; “C” – FX market; “F” – derivatives market. |
| ServerIp | ASCIIZ string | variable | Gateway IP, e.g., «195.1.3.51». |

If error occurs, one of the MTE_xxxx error codes is returned.

BRIDGE CLIENT LIBRARY VERSION

MTEGetVersion function is used to get the client library version number.

C++

```
char * WINAPI MTEGetVersion();
```

Pascal

```
function MTEGetVersion: LPSTR; stdcall;
```

Arguments:

none

Returned value:

A pointer to an ASCIIZ string containing a text description of client library version. For example: “MTESrl library 3.8.93”.

OBTAINING CONNECTION STATUS

To obtain the current status of connection to ASTSBridge server, `MTEConnectionStatus` function should be used.

C++

```
int32 WINAPI MTEConnectionStatus(int32 Idx);
```

Pascal

```
function MTEConnectionStatus(Idx: Integer): Integer; stdcall;
```

Arguments:

Idx

A descriptor of connection, for which, the data should be received.

Returned value:

One of the following `MTE_XXX` codes:

| | |
|---------------------------------|-------------------------------------|
| <code>MTE_OK</code> | Connection established. |
| <code>MTE_INVALIDCONNECT</code> | Invalid connection descriptor. |
| <code>MTE_SRVUNAVAIL</code> | ASTSBridge server is not available. |
| <code>MTE_TEUNAVAIL</code> | Trading system is not available. |

OBTAINING CONNECTION STATISTICS

To obtain a statistical data on the connection (connection flags, amount of transferred data, etc.) `MTEConnectionStats` function can be used.

C++

```
int32 WINAPI MTEConnectionStats(int32 Idx, MTEConnStats * Stats);
```

Pascal++

```
function MTEConnectionStats(Idx: Integer; var Stats: TMTEConnStats):  
    Integer; stdcall;
```

Idx

A descriptor of connection, for which, the data should be received.

Returned value:

In case of success function returns MTE_OK and fills the Stats structure by statistical data on the connection. Stats structure has the following format:

| | | |
|------------------|----------|---|
| Size | int32 | Input field, must be filled <code>sizeof(Stats)</code> . |
| Properties | uint32 | Connection flags, combination of values ZLIB_COMPRESSED, FLAG_ENCRYPTED, FLAG_SIGNING_ON. |
| SentPackets | uint32 | A number of packets, sent to ASTSBridge server. |
| RecvPackets | uint32 | A number of packets, received from ASTSBridge server. |
| SentBytes | uint32 | A number of bytes, sent to ASTSBridge server, considering compression. |
| RecvBytes | uint32 | A number of bytes, received from ASTSBridge server, considering compression. |
| ServerIpAddress | uint32 | ASTSBridge server IP-address. |
| ReconnectCount | uint32 | A number of reconnections to ASTSBridge server. |
| SentUncompressed | uint32 | A number of bytes, sent to ASTSBridge server, not taking compression into account. |
| RecvUncompressed | uint32 | A number of bytes, received from ASTSBridge server, not taking compression into account. |
| ServerName | char[64] | ASTSBridge server identifier. |
| TsmrPacketSize | uint32 | A size of packet of TSMR protocol, bytes (only for colocation version). |
| TsmrSent | uint32 | A number of bytes, sent to TS via TSMR protocol (only for colocation version). |
| TsmrRecv | uint32 | A number of bytes, received from TS via TSMR protocol (only for colocation version). |

If error occurs, one of the MTE_XXXX error codes is returned.

OBTAINING INFORMATION OBJECTS DESCRIPTION

Information objects description contains a list of tables, transactions, their fields and some additional objects, available to the client. MTEStructure, MTEStructure2 and MTEStructureEx functions are used to get the description. MTEStructure2 and MTEStructureEx functions return an expanded set of trading system objects characteristics (see Appendix 1).

MTEStructureEx completely covers all the capabilities of two other functions: MTEStructure call is similar to MTEStructureEx call with *Version=0* attribute, MTEStructure2 call is similar to MTEStructureEx call with *Version=2* attribute.

C++

```
int32 WINAPI MTEStructure(int32 Idx, TMTEMsg **Msg);
int32 WINAPI MTEStructure2(int32 Idx, TMTEMsg **Msg);
int32 WINAPI MTEStructureEx(int32 Idx, int32 Version, TMTEMsg **Msg);
```

Pascal

```
function MTEStructure(Idx: Integer; var Msg: PMTEMsg): Integer; stdcall;
function MTEStructure2(Idx: Integer; var Msg: PMTEMsg): Integer; stdcall;
function MTEStructureEx(Idx: Integer; Version: Integer; var Msg:
    PMTEMsg): Integer; stdcall;
```

Arguments:*Idx*

A descriptor of connection, for which, the data should be received.

Version

[Only for *MTEStructureEx*]. The needed version of information objects description. Possible values are in range from 0 to 3. The higher the value is, the more detailed description will be received.

Msg

An address of a variable (of the type “a pointer to a *TMTEMsg*”) to store a pointer to the buffer, containing information objects description. Memory for this buffer is allocated by the library. Buffer format for *MTEStructure* and *MTEStructure2* functions is described in Appendix 1. *TMTEMsg* structure is defined as follows:

C++

```
typedef struct TMTEMSG_TAG
{
    long DataLen; // The length of the data to follow
    // char Data[DataLen]; // commented - pseudo field
} TMTEMSG;
// data of the [DataLen] length directly follows the data of this
// structure.
```

Pascal

```
PMTEMsg = ^TMTEMsg;
TMTEMsg = record
    DataLen: Integer; // The length of the data to follow
    Data: record end; // Variable length data
end;
```

Returned value:

In case of success, function returns *MTE_OK* and places a buffer with the description to *Msg* argument.

If error occurs, one of the *MTE_xxxx* error codes is returned. If *MTE_TSMR* error code is returned, then the data field of *Msg* structure contains the error message of *[DataLen]* length.

Example:

Get the description of available information objects for the *Idx* session.

C++

```
int32 Idx;
char ErrorMessage[255];
TMTEMsg *Msg;
char *Data;
int32 err;
...
Idx = MTEConnect("PORT=COM1\rBAUDRATE=115200", ErrorMessage);
If (Idx < MTE_OK) {
    fprintf(stderr, " Connection error: %s: %s", ErrorMessage);
    exit(1);
} else
    fprintf(stdout, "Connection established.");

if ((err = MTEStructure(Idx, &Msg)) != MTE_OK ) {
    if (Err == MTE_TSMR) {
        Data = (char *) (Msg + 1);
        fprintf(stderr, "Error: %s\n", Data );
    } else
        fprintf(stderr, "Error: %s\n", MTEErrorMsg(Err));
} else
```

```

    fprintf("Information objects description has been
received.\n");
Data = (char *) (Msg + 1); // Actual data

```

Pascal

```

Idx: Integer;           // Initiated by the MTEConnect
Err: Integer;
Msg: PMTEMsg;
S: string;
Data: PAnsiChar;
...
Err := MTEStructure(Idx, Msg);
if Err <> MTE_OK then
    if Err = MTE_TSMR then begin
        SetString(S, @Msg.Data, Msg.DataLen);
        Writeln('Error: ' + S);
    end else
        Writeln('Error: ' + MTEErrorMsg(Err))
else
    Writeln(Information objects description has been received.);
Data := @Msg.Data;      // Actual data

```

The structure of information objects, returned by this function, can be obtained as a HTML-file using TETServer.exe command: Session | Export metadata.

WORKING WITH INFORMATION OBJECTS

Working with information objects includes working with tables and transactions execution.

TRANSACTIONS EXECUTION

All the active operations (i.e. transactions), such as order entry, withdrawal, etc. are executed with MTEExecTrans, MTEExecTransIP and MTEExecTransEx functions.

C++

```

int32 WINAPI MTEExecTrans(int32 Idx, char *TransName, char *Params,
                           char *ResultMsg);
int32 WINAPI MTEExecTransIP(int32 Idx, char *TransName, char *Params,
                             char *ResultMsg, int32 ClientIP);

```

Pascal

```

function MTEExecTrans(Idx: Integer; TransName, Params,
                      ResultMsg: LPSTR): Integer; stdcall;
function MTEExecTrans(Idx: Integer; TransName, Params,
                      ResultMsg: LPSTR; ClientIP: Integer): Integer; stdcall;

```

Arguments:

Idx

A descriptor of connection, on which, the transaction is being executed.

TransName

A pointer to an ASCIIZ string containing the name of transaction. Available names can be obtained with MTEStructure, MTEStructure2 or MTEStructureEx functions.

Params

A pointer to an ASCIIZ string containing the transaction parameters. The length of the string and its value must match the description of transaction input fields (obtained with MTEStructure, MTEStructure2 or MTEStructureEx functions). All fields have to be submitted as text, according to the following trading system formatting:

| | |
|-------------|---|
| Char | Blank spaces are appended to correspond to the string length, defined in the field description. For example, for a Char(12) field the string "ROOT" has to be |
|-------------|---|

| | |
|----------------|---|
| | presented as "ROOT " . |
| Integer | Zeros are added to the left side to reach the required length. For example, the value 127 of the Integer(10) type has to be presented as "0000000127". |
| Fixed | Two symbols after the decimal point are kept, the decimal point itself is deleted, and zeros are added to the left side to reach the required length. For example, value 927.4 of the Fixed(8) type has to be transformed into "00092740" string. |
| Float | N symbols after the decimal point are kept, the decimal point itself is deleted, zeros are added to the left side to reach the required length. The value of N depends on the price precision of a given financial instrument. For example, value 26.75 of the Float(9) type for the instrument with N=4, has to be presented as "000267500". |
| Date | Specified as YYYYMMDD. For example, 24 August 1999 has to be presented as "19990824". |
| Time | Specified as HHMMSS. For example, 16:27:39 is to be presented as "162739". |

ClientIp

(For MTEExecTransIP function) IP-address of the client, on whose behalf, the transaction is performed. To be used in interfaces for technical centers and regional exchanges.

ResultMsg

A pointer to a buffer of at least 256 bytes to store a text string containing the result of transaction execution, in case of success.

Returned value:

If transaction has been processed by the trading system, then, one of the following codes is returned:

MTE_OK – transaction executed;
MTE_TRANSREJECTED – the transaction has been received, but rejected by the trading system (incorrect arguments, no rights to execute transactions, etc.);
MTE_TSMR - fatal error during the transaction execution (connection to the trading system is lost, etc.).

A text string with the result of the transaction processing is stored in *ResultMsg* argument.

If error occurs, one of the MTE_xxxx error codes is returned. In this case a value of *ResultMsg* is not defined.

Example:

Let the description of an object (received with MTEStructure) contains "Enter an order" transaction with the following fields:

```
ORDER // Transaction name
BuySell: Char(1) // "B" - buy, "S" - sell
SecCode: Char(17) // Security code
Price: Float(9) // Price
Quantity: Integer(10) // Number of lots
```

The following code is used to submit an order to buy 14 items of the "0CURRUSD000000TOD" at the price of 26.15 (for this security, the price precision is 4 symbols after the decimal point):

C++

```
int32 Idx; // Initiated by MTEConnect
int32 Err;
char *ResultMsg;
...
Err = MTEExecTrans(Idx, "ORDER",
"0CURRUSD000000TOD0002615000000000014", ResultMsg);
if( Err == MTE_OK )
    fprintf(stdout, "Transaction executed: %s\n", ResultMsg);
else if( Err == MTE_TSMR )
    fprintf(stdout, "Transaction IS NOT executed: %s\n", ResultMsg);
else fprintf(stderr, "Error: %s\n", MTEErrorMsg(Err));
```

Pascal

```
Idx: Integer;           // Initiated by MTEConnect
Err: Integer;
ResultMsg: TErrorMsg;
...
Err := TExecTrans(IdX, 'ORDER',
  'B0CURRUSD000000TOD0002615000000000014', @ResultMsg);
case Err of
  MTE_OK: Writeln('Transaction executed: ' + ResultMsg);
  MTE_TSMR, MTE_TRANSREJECTED: Writeln('Transaction IS NOT
executed: ' + ResultMsg);
  else Writeln('Error: ' + MTEErrorMsg(Err));
end;
```

Note: all transactions or table data requests are sent sequentially within one connection. It means that a transaction or a table data request can be sent to the trading system only after the reply to the previous one is received. To avoid any related delays it is recommended:

- To use separate connections to perform transactions and to request table data.
- To use load balancer to distribute transactions between connections in case of high transaction volume.

New transactions supported by the trading system can return multiple replies or string, longer than 255 symbols. For that kind of transactions, it's recommended to use `MTEExecTransEx` function, which returns an array of replies and text messages of unlimited length:

C++

```
int32 WINAPI MTEExecTransEx(int32 Idx, char *TransName, char *Params,
  int32 ClientIp, TMTEExecTransResult *Reply);
```

Pascal

```
function MTEExecTransEx(IdX: Integer; TransName, Params: LPSTR;
  ClientIp: Integer; var Reply: TMTEExecTransResult): Integer; stdcall;
```

Arguments:

Idx

A descriptor of connection, on which, the transaction is being executed.

TransName

A pointer to an ASCIIZ string containing the name of transaction. Possible names can be obtained by calling `MTEStructure`, `MTEStructure2` or `MTEStructureEx` functions.

Params

A pointer to an ASCIIZ string containing the transaction parameters. The length of the string and its value must match the description of transaction input fields, obtained by calling `MTEStructure`/`MTEStructure2` or `MTEStructureEx` functions. All fields have to be submitted as text, with the proper formatting (see. `MTEExecTrans`).

ClientIp

IP-address of the client, on whose behalf, the transaction is performed. To be used in interfaces for technical centers and regional exchanges.

Reply

A pointer to a text string, in which, the transaction execution result and trading system reply are stored. `TMTEExecTransResult` structure is defined as:

C++

```
typedef struct TransResult {
    // a number of entries in "replies" field
    uint32_t replyCount;
    // a pointer to an array of TMTETransReply entries
    MteTransReply* replies;
} MteTransResult;

typedef struct TransReply {
    int32_t errCode; // Returned code (see. Returned values)
    int32_t msgCode; // A number of message in Trading System
    (which is indicated by brackets in the text)
    char* msgText; // Trading System text message
    int32_t paramCount; // A number of parameters in the reply
    MteTransParam* params; // An array of parameters in the
reply
} MteTransReply;
```

Pascal

```
TMTEExecTransResult = record
    // a number of entries in "Replies" field
    ReplyCount: Longword;
    // a pointer to an array of TMTETransReply entries
    Replies: PMTETransReplies;
end;

// single reply of the Trading System
TMTETransReply = record
    ErrCode: TMTEResult; // Returned code (see. Returned values)
    MsgCode: Integer; // A number of message in Trading System
    (which is indicated by brackets in the text)
    MsgText: PAnsiChar; // Trading System text message
    ParamCount: Integer; // A number of parameters in the reply
    Params: PMTETransParams; // An array of parameters in the
reply
end;
```

Most of transactions return only one single reply, so ReplyCount value is "1" and Replies contains 1 entry. An example of transaction, which returns more than one reply: ORDER2 (entry of the two-way order) on MICEX Derivatives Market. Currently, the reply of trading system don't contain any additional parameters, so the ParamCount value is always "0", and Params = nil.

Returned value:

If the transaction has been processed by trading system, the following is returned:

MTE_OK – transaction successfully executed;
MTE_TRANSREJECTED – the transaction has been processed, but rejected by the trading server (invalid board specified, no rights to perform, etc.);
MTE_TSMR - fatal error occurred, when processing the transaction (the loss of connection with the trading system, etc.).

WORKING WITH TABLES

Working with tables includes the following steps:

1. Opening a table
2. Periodically requesting for updates
3. Closing the table

OPENING A TABLE

To start working with a table, first it's necessary to call `MTEOpenTable` function. This function opens a table and returns the content of the table partially or at once..

C++

```
int32 WINAPI MTEOpenTable(int32 Idx, char *TableName, char *Params,
                        int32 Complete, TMTEMsg **Msg);
```

Pascal

```
function MTEOpenTable(Idx: Integer; TableName, Params: LPSTR;
                    Complete: BOOL; var Msg: PMTEMsg): Integer; stdcall;
```

Arguments:

Idx

A descriptor of connection, obtained by `MTEConnect`.

TableName

A pointer to an ASCIIZ string containing the name of the table. Available names can be obtained with `MTEStructure`, `MTEStructure2` or `MTEStructureEx` functions.

Params

A pointer to an ASCIIZ string containing the parameters of the table. The length of the string and its value must match the description of table input fields, received with `MTEStructure`, `MTEStructure2` or `MTEStructureEx`. All fields have to be submitted as a text with the proper formatting (see `MTEExecTrans`).

Complete

Flag to request either all the table data at once or only a part of it:

- TRUE** Return all the table data. Function will query the trading system as many times as needed to obtain all the data. In case of big table size (e.g. `TRADES` or `SETTLECODES`) it may take a long time. If the content is not needed all at once, then in order to decrease execution time, the `FALSE` value should be used.
- FALSE** Depending on the table type, the function returns only a part of the data or nothing at all. Function will query the trading system one time, maximum. The remaining data will be considered as an update and should be read during the update request cycle, initiated with `MTEAddTable`/`MTERefresh`.

Msg

An address of a variable (of the type "a pointer to a `TMTEMsg`"), to store a pointer to the buffer, containing the data of opened table. Buffer format is described in Appendix 2.

Returned value:

If successful, a descriptor of an open table is returned (value that is greater or equal to `MTE_OK`). Received descriptor can be used when calling `MTEAddTable` function.

If error occurs, one of the `MTE_xxxx` error codes is returned. If `MTE_TSMR` error code is returned, then "Data" field of the `Msg` structure contain error message with a length of `[DataLen]` symbols.

REQUEST FOR UPDATE

Request for a table content update is performed in a batch mode, i.e. requests to update several open tables are processed simultaneously. A set of tables to be refreshed is formed by calling `MTEAddTable` function for every table. Then all the updates can be received with `MTERefresh` function. Execution of other library functions (except `MTEErrorMsg`) is not allowed between those two functions.

`MTEAddTable` function adds a table to the update queue (changes that occurred since the last request).

C++

```
int32 WINAPI MTEAddTable(int32 Idx, int32 HTable, int32 Ref);
```

Pascal

```
function MTEAddTable(Idx, HTable, Ref: Integer): Integer; stdcall;
```

Arguments:

Idx

Connection descriptor received with MTEConnect.

HTable

Table descriptor received with MTEOpenTable.

Ref

Optional parameter to store arbitrary data. Usually used to match the data with a table in a buffer, received with MTERefresh.

Returned value:

One of the MTE_XXXX error codes.

MTERefresh function performs the batch table updates (the request is formed with the MTEAddTable)

C++

```
int32 WINAPI MTERefresh(int32 Idx, TMTEMsg **Msg);
```

Pascal

```
function MTERefresh(Idx: Integer; var Msg: PMTEMsg): Integer; stdcall;
```

Arguments:

Idx

Connection descriptor obtained by calling MTEConnect.

Msg

An address of a variable (of the type “a pointer to a TMTEMsg”) to store the received updates. The buffer format is described in appendix 3.

Returned value:

If successful then MTE_OK is returned and pointer to the update is saved into Msg argument

If error occurs, one of the MTE_XXXX error codes is returned. If MTE_TSMR error code is returned, then the Data field of the Msg structure will contain the error message and have the DataLen length of string.

CLOSING THE TABLE

Upon the end of work with a table it should be closed with MTECloseTable. The table descriptor cannot be used after this function execution.

C++

```
int32 WINAPI MTECloseTable(int32 Idx, int32 HTable);
```

Pascal

```
function MTECloseTable(Idx, HTable: Integer): Integer; stdcall;
```

Arguments:

Idx

Connection descriptor received with MTEConnect.

HTable

A descriptor of the closing table, received with MTEOpenTable.

Returned value:

One of MTE_XXXX error codes.

EXAMPLE

Let the structure of input fields (received with MTEStructure) of SECURITIES and TRADES tables, is as follows:

```
SECURITIES           // Table name (Securities)
  Market: Char(4)     // Market code
  Board: Char(4)      // Trading board (mode) code

TRADES               // "TRADES" table has no input fields
```

The following code shows how to work with tables. Tables are opened, their content is periodically updated and then the tables are closed.

C++

```
int32 Idx; // Initiated by MTEConnect
TMTEMsg *Msg;
char *Data;
int32 HSecurs, Htrades;
...

HSecurs = MTEOpenTable(Idx, "SECURITIES", "CURR    ", 1 /*True*/,
&Msg);
Data = (char *) (Msg + 1);
...
// Processing the received data
...
HTrades = MTEOpenTable(Idx, "TRADES", "", 0/*False*/, Msg);
Data = (char *) (Msg + 1);
...
// Processing the received data
...

do
{
  MTEAddTable(Idx, HSecurs, 0);
  MTEAddTable(Idx, HTrades, 1);
  MTERefresh(Idx, &Msg);
  Data = (char *) (Msg + 1);
  ...
  // Processing the updates
  ...
}while( !Terminated );

MTECloseTable(Idx, HSecurs);
MTECloseTable(Idx, HTrades);
```

Pascal

```
Idx: Integer;           // Initiated by MTEConnect
Msg: PMTEMsg;
HSecurs, HTrades: Integer;
Data: PAnsiChar;
...

HSecurs := MTEOpenTable(Idx, 'SECURITIES', 'CURR    ', True,
Msg);
...
// Processing the received data
...
```

```

HTrades := MTEOpenTable(Idx, 'TRADES', '', False, Msg);
...
// Processing the received data
...

repeat
    MTEAddTable(Idx, HSecurs, 0);
    MTEAddTable(Idx, HTrades, 1);
    MTERefresh(Idx, Msg);
    Data := @Msg.Data;
    ...
    // Processing the updates
    ...
until Terminated;

MTECloseTable(Idx, HSecurs);
MTECloseTable(Idx, HTrades);

```

NOTES ON WORKING WITH TABLES

Note 1. Follow these steps to avoid disconnections on timeout: 1. do not to set too small (less than 60 seconds) values for the DisconnectIfIdleFor parameter in ASTSBridge configuration file; 2. maintain active connection (heartbeat) by regular (approximately every 30 seconds) requests – for example, to update TESYSTIME table.

Note 2. Most of the tables can be opened and closed anytime and as many times as needed during the connection session with a server. Any number of table copies can be opened. However, due to certain limitations of a trading system, some of the tables can be opened only once during the session. These tables are: ORDERS, TRADES, NEGDEALS, ALL_TRADES. If such table is closed and then opened again, then initial content of the table will not be received again – only content updates will come.

Consequently, it is recommended to open such tables only once during the connection session and close them only at the end of the session.

Note 3. For tables having the "tfClearOnUpdate – Clear on update" flag (except for the ORDERBOOK table) the following updates processing order is defined: when a table is to be cleared, then the RowsNumber is set to 1, i.e. only a single string with DataLength=0 is returned (see Appendix 2).

There are two types of requests for orderbook (quotations) for the ORDERBOOK table:

1. To get information on one security, the request has to have non-empty values of “Board” and “Security” fields;
2. To get orderbook (quotations) for all available securities with one request, fields “Board” and “Security” have to be filled-in with spaces.

For the first type, when the orderbook table has to be cleared as the result of request, a table with a single row is received that contains the following values: NumberOfFields=2 and DataLength=(length of “Board” field + length of “Security” field). This string contains only the “Board” and “Security” fields. For the second type, the reply on request can contain several such strings (which contain only the values of “Board” and “Security” fields) – for given financial instruments this will mean the deletion of orderbook (quotation) values.

Note that during the first request for all securities (i.e. at opening time), strings with initial zero values of orderbook can be received. This is explained by the Trading system data transfer mechanism: the status of these instruments has changed, so the Trading system only sends updates of the orderbook fields, which are not reflected in clients’ systems. That is why all the updated orderbooks are transmitted even if they are empty. The consequent requests will return data only on the orderbooks that have changed.

Also note that TEClient.exe only shows data from the last request for updates, i.e. only those of the orderbooks that have changed.

Note 4. The maximum refresh interval is governed by a document "Requirments for external systems and their interfacing with ASTS Trading system". To avoid any delays at peak times, it’s possible to use the

adaptive refresh model: if the received data buffer is greater than 30 Kbytes, then ask for another update immediately. If the buffer is less than 30 Kbytes then send the next request with standard interval (in 1 second, for example).

MEMORY USE OPTIMIZATION

All the functions of MTESRL library that return pointers to data buffer (pointer to the PMTEMsg structure; for example, MTEStructure, MTERefresh) use the same memory region as the reception buffer (this is for one connection; with multiple connections multiple memory areas are used). Let's call these functions "informational functions".

If informational function call returns data buffer that is larger than allocated, then the reallocation of a larger block of memory will occur. Thus the maximum size of allocated memory equals to the largest block of data received. All the allocated memory is released when connection is closed with MTEDisconnect.

It is also possible to free the memory allocated for the buffer at any time, without closing the connection. MTEFreeBuffer function is used for this purpose. This function should be called only after all the received data has been processed. It should be kept in mind that before the next call of any of the informational functions, memory should be allocated again. Frequent use of MTEFreeBuffer can negatively influence the performance.

C++

```
int32 WINAPI MTEFreeBuffer(int32_t conno);
```

Pascal

```
function MTEFreeBuffer(Idx: Integer): Integer; stdcall;
```

Arguments:

Idx

A descriptor of connection, that should be dropped, received with MTEConnect.

Returned value:

One of the MTE_XXXX error codes.

RECOVERY AFTER FAILURES AT ASTSBRIDGE SERVER

During operation, external system or ASTSBRIDGE sometimes needs to be restarted in case of a critical error. In that case, it is necessary to restore the system as soon as possible. In such situations, it is recommended to use the following technology: external system makes a backup of loaded tables and state of internal structures in files with a certain periodicity; in case of failure, data from the saved files is used to restore last saved state of the external system.

MTESRL library allows to initiate the data transfer from ASTSBRIDGE Server, not only from the beginning of a trading session, but from a certain point as well. To do so, the snapshot of opened tables status should be made beforehand. Afterwards (if, for example, the connection to ASTSBRIDGE Server has been lost) it will be possible to recover the status of open tables and continue getting data.

BACKING UP BRIDGE INTERNAL STRUCTURE

Backing up the state of the Bridge internal structures is performed after requesting and processing tables' updates. This operation can be performed after each request for changes or after certain number of them. As a rule, along with saving of bridge internal structures, the current state of all tables of the external system is backed up. This ensures complete preservation of the current state of the whole system, consisting of an external system and ASTSBRIDGE. A detailed scenario of operation in this case is shown below:

To obtain a current state of tables opened on the server, use MTEGetSnapshot function.

C++

```
int32 WINAPI MTEGetSnapshot( int32 Idx, char ** Snapshot, int *Len);
```

Pascal

```
function MTEGetSnapshot(Idx: Integer; var Snapshot: LPSTR;
                        var Len: Integer): Integer; stdcall;
```

Arguments:

Idx

Descriptor of connection, for which, the snapshot of opened tables should be received.

Snapshot

Address of the variable where pointer to the snapshot will be placed in case of success.

Len

Address of the variable, where the snapshot (i.e. buffer at which the *Snapshot* points) length will be placed in case of success.

Returned value:

In case of success the function returns MTE_OK.

If error occurs, one of the error MTE_xxxx codes is returned. If MTE_TSMR error code is returned, then the *Snapshot* will point to the error message and the *Len* will contain the length of this message.

The snapshot of tables, loaded on the server side, can be considered just as a buffer with some binary data. Its content does not have any meaning for the client.

The following code assumes that external system has connected to ASTSBridge, received a data structure, opened tables and moved to the cycle of getting tables updates:

C++

```
int32 Idx;          // Initiated by MTEConnect
TMTEMsg *Msg;
char *DataPtr;
int32 *TablesIdx; // array of indexes received with MTEOpenTable
int32 i, NumTables; // number of the updated tables
char *SnapshotBuf; // pointer to the buffer for the emergency
int32 SnapshotLen; // length of the buffer for the emergency saving
...
do
{
    for( i = 0; i < NumTables; i++ )
        MTEAddTable(Idx, TablesIdx[i], i);
    MTERefresh(Idx, &Msg);
    DataPtr = (char *) (Msg + 1);
    ...
    // Processing the updates
    ...
    // Receive of the buffer for the Bridge internal structure
    MTEGetSnapshot(Idx, &SnapshotBuf, &SnapshotLen);
    // saving the buffer to the file
    ...
    // saving the status
    ...
}while( !Terminated );
```

Pascal

```
Idx: Integer;           // Initiated by MTEConnect
Msg: PMTEMsg;
DataPtr: PChar;
TablesIdx: array of Integer; // of indexes received with
MTEOpenTable
i, NumTables: Integer; // number of the updated tables
SnapshotBuf: PChar;    // pointer to the buffer for the
emergency
SnapshotLen: Integer;  // length of the buffer for the emergency
saving
...
repeat
  for i := 0 to NumTables - 1 do
    MTEAddTable(Idx, TablesIdx[i], i);
  MTERefresh(Idx, Msg);
  DataPtr = @Msg.Data;
  ...
  // Processing the updates
  ...
  // Receive of the buffer for the Bridge internal structure
  MTEGetSnapshot(Idx, SnapshotBuf, SnapshotLen);
  // saving the buffer to the file
  ...
  // saving the status
  ...
until Terminated;
```

BRIDGE INTERNAL STRUCTURE RECOVERY

To get the list of opened tables, contained in a given snapshot, use `MTEGetTablesFromSnapshot` function. This function can be called both before and after `MTESetSnapshot`.

C++

```
int32 WINAPI MTEGetTablesFromSnapshot( int32 Idx, char * Snapshot,
int Len, MTESnapTable **SnapTables);
```

Pascal

```
function MTEGetTablesFromSnapshot(Idx: Integer; Snapshot: LPSTR;
Len: Integer, var SnapTables: PMTESnapTables): Integer; stdcall;
```

Arguments:

Idx

Connection descriptor, obtained by `MTEConnect` function.

Snapshot

A pointer to a buffer, where the snapshot, taken by `MTEGetSnapshot`, is stored.

Len

Buffer length.

SnapTables

An address of a variable containing a pointer to `MTESnapTable` structure, where, in case of success, a pointer to a buffer of opened tables will be placed. A memory for this buffer is allocated by a library. In case of repeated calls to this function, the same buffer is used, so, result should be saved by external system. The buffer has following format:

C++

```
typedef struct SnapTable {
    int32 Htable;    // Descriptor of the opened table
```

```

    char* TableName    // A pointer to an ASCIIZ-string,
    containing table name.
    char* Params;      // A pointer to an ASCIIZ-string,
    containing the parameters, used when opening the table.
} MteSnapTable;

```

Pascal

```

TMTESnapTable = record
    HTable: Integer;      // A table descriptor
    TableName: PAnsiChar; // char, Zero-byte terminated, Table
    Name
    Params: PAnsiChar;    // char, Zero-byte terminated,
    Parameters provided on open table
end;

PMTESnapTables = ^TMTESnapTables;
TMTESnapTables = array [0..999999] of TMTESnapTable;

```

Returned value:

In case of negative value, return code is interpreted as MTE_xxxx error code.

In case of success, function returns non-negative value, equal to the number of opened tables, and a pointer to a formed array of tables structures `MTESnapTable` through `SnapTables` parameter.

Internal structures recovery is performed when restarting Bridge or external system after failures, to restore the system to the moment of last snapshot. This operation should be performed only within the current trading session (see. `MTEGetSnapshot`). As a result, all opened tables and their descriptors will be restored. So, previously used descriptors can be used again right after recovery. `MTESetSnapshot` function can be used to restore Bridge last saved state.

C++

```

int32 WINAPI MTESetSnapshot( int32 Idx, char * Snapshot, int Len,
                             char *ResultMsg);

```

Pascal

```

function MTESetSnapshot(Idx: Integer; Snapshot: LPSTR; Len: Integer;
                        ErrorMessage: LPSTR): Integer; stdcall;

```

Arguments:

Idx

A descriptor of connection, for which, the last state is restored.

Snapshot

A pointer to the buffer, which stores previously taken “snapshot”.

Len

The length of the buffer, pointed by a snapshot.

ErrorMsg

A pointer to at least 256 bytes buffer, to store a text string containing the result of restoring.

Returned value:

If function was successfully processed by the trading system, the following will be returned:

MTE_OK – restoring complete;

MTE_TSMR - trading system is unable to restore the state.

A text string containing result, returned by trading system, will be placed to *ErrorMsg* argument.

If error occurs, one of the MTE_xxxx error codes is returned. *ErrorMsg* field value is not defined.

The following code assumes that external system has backed up own and Bridge’s state before the failure. Complete restart of the system, including Bridge server, is performed (acts similar when restarting only external system or just ASTSBridge server). System has connected to Bridge server and obtained data structure description:

C++

```
int32 Idx;           // Initialized MTEConnect call
TMTEMsg *Msg;
char *DataPtr;
int32 *TablesIdx;    // array of indexes of opened tables
int32 i, NumTables;  // a number of updated tables
char *SnapshotBuf;   // a pointer to a data buffer that will
                     // be used when restoring the state of Bridge server
int32 SnapshotLen;   // buffer length
...
// Recovery of the external system from the stored data
// At the same time NumTables values and index array of open tables
...
// Loading of the saved buffer from the file,
// which was backed up after last MTEGetSnapshot call,
// (initialization and loading SnapshotBuf buffer)
...
//Restoring the internal structures last state
MTESetSnapshot(Idx, SnapshotBuf, SnapshotLen);
//start of the normal operation cycle of the external system
do
{
    for( i = 0; i < NumTables; i++ )
        MTEAddTable(Idx, TablesIdx[i], i);
    MTERefresh(Idx, &Msg);
    DataPtr = (char *) (Msg + 1);
    ...
    // Processing the updates
    ...
}while( !Terminated );
```

Pascal

```
Idx: Integer;           // Initialized MTEConnect call
Msg: PMTEMsg;
DataPtr: PChar;
TablesIdx: array of Integer; // array of indexes of opened tables
i, NumTables: Integer; // a number of updated tables
SnapshotBuf: PChar;     // a pointer to a data buffer that will
                        // be used when restoring the state of Bridge server
SnapshotLen: Int32;     // buffer length
...
// Recovery of the external system from the stored data
// At the same time NumTables values and index array of open tables
...
// Loading of the saved buffer from the file,
// which was backed up after last MTEGetSnapshot call,
// (initialization and loading SnapshotBuf buffer)
...
// Restoring the internal structures last state
MTESetSnapshot(Idx, SnapshotBuf, SnapshotLen);
// start of the normal operation cycle of the external system
repeat
    for i := 0 to NumTables - 1 do
        MTEAddTable(Idx, TablesIdx[i], i);
        MTERefresh(Idx, Msg);
        DataPtr = @Msg.Data;
        ...
        // Processing the updates
        ...
until Terminated;
```

EXAMPLE OF RECOVERY AFTER THE FAILURE

Suppose that we have:

1. Established the connection with ASTSBridge Server with `MTEConnect`.
2. Opened several tables by calling `MTEOpenTable` and saved their descriptors in variables named `hTable1`, `hTable2`, ..., `hTableN`.
3. Executed some transactions, requested updates of informational tables, periodically saved the snapshots with `MTEGetSnapshot`.
4. Now suppose that at certain point the connection with ASTSBridge Server has been lost. The recovery procedure will be as follows.
5. Reconnect to the Bridge Server with `MTEConnect`;
6. Call `MTESetSnapshot` with the last saved snapshot
7. Now we can use previously defined table handles `hTable1`, `hTable2`, ..., `hTableN`. There is no need to call `MTEOpenTable` again. All the following `MTERefresh` calls will return tables updates, accumulated after saving Snapshot.

If the data, received before the connection loss, have been saved, Get / Set Snapshot mechanism can significantly reduce the time of reception of all tables' updates after the reconnection.

SELECTIVE OPENING OF TABLES FROM THE SNAPSHOT

There is also an alternative way to restore the system after failure. Instead of saving and loading complete state of all tables, it's possible to restore only certain large tables (e.g. "ORDERS", "TRADES"), and open other tables in the usual way – with `MTEOpenTable` function. This way eliminates the need for storage a list of open tables along with their descriptors. It's enough to retain only the snapshot, and then open the tables, using the `MTEOpenTableAtSnapshot` function. The data from tables, opened this way, will not come from scratch but from the moment when an appropriate snapshot was taken. There is no need to call `MTESetSnapshot` in that scenario.

C++

```
int32 WINAPI MTEOpenTableAtSnapshot (int32 Idx, char* TableName,
    char* Params, char* Snapshot, int SnapshotLen, TMTEMsg **Msg);
```

Pascal

```
function MTEOpenTableAtSnapshot (Idx: Integer;
    TableName, Params, Snapshot: PAnsiChar;
    SnapshotLen: Integer; var Msg: PMTEMsg): Integer; stdcall;
```

Arguments:

Idx

A descriptor of connection, obtained by calling `MTEConnect`.

TableName

A pointer to ASCIIZ string containing a table name. Possible names can be obtained by calling `MTEStructure`, `MTEStructure2` or `MTEStructureEx` functions.

Params

A pointer to ASCIIZ string containing parameters of the table. The length of the string and its value must match the description of table input fields, received with `MTEStructure` or `MTEStructure2` or `MTEStructureEx`. All fields have to be submitted as a text with trading system formatting.

Snapshot

A pointer to a buffer containing a snapshot. The requested table with the specified parameters should be included in this snapshot, otherwise the function returns an `MTE_TSMR` error. If null

pointer is passed in this parameter, the function behaves like a call to `MTEOpenTable` with `Complete = FALSE` option.

SnapshotLen

A length of the buffer containing the snapshot.

Msg

Address of variable (of type "pointer to `TMTEMsg`"), which, if successful, will store a pointer to a buffer containing a portion of updates for an open table. The buffer format is described in Appendix 2.

Returned value:

In case of success, function returns descriptor of the opened table (value greater or equal `MTE_OK`). Obtained descriptor is used when calling `MTEAddTable` function.

If error occurs, one of the `MTE_XXXX` error codes is returned. If the returned error code is `MTE_TSMR`, the `Data` field of `Msg` structure contains error message of `DataLen` characters length.

The following code shows selective opening of «Orders» table from the snapshot:

```
C++
int32 Idx;           // Initialized by calling MTEConnect
TMTEMsg *Msg;
char *DataPtr;
char *Snapshot;
int32 Len;
int32 HSecurs, HTrades;
...
HSecurs = MTEOpenTable(Id, "SECURITIES", "EQBR", 1 /*True*/,
    &Msg);
// Processing the received data
...
HTrades = MTEOpenTable(Id, "TRADES", "", 0 /*False*/, &Msg);
// Processing the received data
...
// Fail occurred!. Saving the snapshot and closing the tables
MTEGetSnapshot(Id, &Snapshot, &Len);
MTECloseTable(Id, HSecurs);
MTECloseTable(Id, HTrades);
...
// Recovery starts. Loading the snapshot and opening the tables
HSecurs = MTEOpenTable(Id, "SECURITIES", "EQBR", 1 /*True*/, &Msg);
// SECURITIES table is opened from scratch, processing the data
...
HTrades = MTEOpenTableAtSnapshot(Id, "TRADES", "", Snapshot,
    Len, &Msg);
// TRADES table is opened from the snapshot, processing the data
...
do {
    MTEAddTable(Id, HSecurs, 0);
    MTEAddTable(Id, HTrades, 1);
    MTERefresh(Id, &Msg);
    DataPtr = (char *) (Msg + 1);
    // Processing the updates
    ...
} while (!Terminated);

MTECloseTable(Id, HSecurs);
MTECloseTable(Id, HTrades);
```

Pascal

```

Idx: Integer;           // Initialized by calling MTEConnect
Msg: PMTEMsg;
HSecurs, HTrades: Integer;
Snapshot: PAnsiChar;
Len: Integer;
Data: PAnsiChar;
...
HSecurs := MTEOpenTable(Idx, 'SECURITIES', 'EQBR', True, Msg);
// Processing the received data
...
HTrades := MTEOpenTable(Idx, 'TRADES', '', False, Msg);
// Processing the received data
...
// Fail occurs here. Saving the snapshot and closing the tables
MTEGetSnapshot(Idx, Snapshot, Len);
MTECloseTable(Idx, HSecurs);
MTECloseTable(Idx, HTrades);
...
// Recovery starts. Loading the snapshots and opening the tables
HSecurs := MTEOpenTable(Idx, 'SECURITIES', 'EQBR', True, Msg);
// SECURITIES table is opened from scratch, processing the data
...
HTrades := MTEOpenTableAtSnapshot(Idx, 'TRADES', '', Snapshot,
Len, Msg);
// TRADES table is opened from the snapshot, processing the data
...
repeat
    MTEAddTable(Idx, HSecurs, 0);
    MTEAddTable(Idx, HTrades, 1);
    MTERefresh(Idx, Msg);
    Data := @Msg.Data;
    // Processing the updates
    ...
until Terminated;

MTECloseTable(Idx, HSecurs);
MTECloseTable(Idx, HTrades);

```

CLOSING CONNECTION SESSION

Upon the end of work on the market, the client has to execute the `MTEDisconnect` function.

C++

```
int32 WINAPI MTEDisconnect(int32 Idx);
```

Pascal

```
function MTEDisconnect(Idx: Integer): Integer; stdcall;
```

Arguments:

Idx

Connection handle received with `MTEConnect`, that has to be closed.

Returned value:

One of the `MTE_XXXX` error codes.

Example:

Close the connection with `Idx` descriptor.

C++

```
int32 Idx; // Initiated by MTEConnect
int32 Err;
...
Err = MTEDisconnect(Idx);
if (Err != MTE_OK)
    fprintf(stderr, "Error: %s\n", MTEErrorMsg(Err));
else
    fprintf(stdout, "Session has ended\n");
```

Pascal

```
Idx: Integer; // Initiated by MTEConnect
Err: Integer;
...
Err := MTEDisconnect(Idx);
if Err <> MTE_OK then Writeln(MTEErrorMsg(Err))
else Writeln('Session has ended');
```

ERROR MESSAGES

All the library functions support MTE_xxxx error codes. MTEErrorMsg or MTEErrorMsgEx functions can be used to get the error code text description

C++

```
char * WINAPI MTEErrorMsg(int32 ErrorCode);
char * WINAPI MTEErrorMsgEx(int32 ErrorCode, char *Language);
```

Pascal

```
function MTEErrorMsg(ErrCode: Integer): LPSTR; stdcall;
function MTEErrorMsgEx(ErrCode: Integer; Language: PAnsiChar): LPSTR;
    stdcall;
```

Arguments:

ErrorCode

One of the MTE_xxxx error codes.

Language

Appropriate language to use in error messages. Possible values are: "English", "Russian", "Ukrainian". If invalid language is specified, English will be used instead. MTEErrorMsg function always returns messages in English.

Returned value:

Pointer to an ASCIIZ-string that contains text description of an error.

ERROR CODES

| ID | Code | Description |
|--------------------|------|--|
| MTE_OK | 0 | No errors. |
| MTE_CONFIG | -1 | Configuration error: cannot open COM-port (for TESServer version), trying to connect to the wrong server, no services specified on a server, wrong parameter values in configuration file. |
| MTE_SRVUNAVAIL | -2 | Server is not available. ASTSBridge Server is not running, Trading system is not available or connection is disrupted. |
| MTE_LOGERROR | -3 | Could not create log file when calling MTEConnect. |
| MTE_INVALIDCONNECT | -4 | Invalid connection handle was given. MTEConnect has not been called or MTEDisconnect function has already been called. |
| MTE_NOTCONNECTED | -5 | Connection with a given descriptor has been lost due to an error (and not as the result of MTEDisconnect function). |

| | | |
|--------------------|-----|---|
| | | Error on ASTSBridge Server, Trading System has been shut down or connection is disrupted. |
| MTE_WRITE | -6 | Error writing to port. Error on ASTSBridge Server or port connection is disrupted. |
| MTE_READ | -7 | Error reading from port. Error on ASTSBridge Server or port connection is disrupted. |
| MTE_TSMR | -8 | Error related to the protocol of interaction with the Trading system, or trading system is not available. |
| MTE_NOMEMORY | -9 | Not enough memory to perform the operation. |
| MTE_ZLIB | -10 | Error in compression/decompression of transmitted data. |
| MTE_PKTINPROGRESS | -11 | MTEAddTable function has been called without the following call of MTERefresh. Other functions can not be called while the request package is being prepared. |
| MTE_PKTNOTSTARTED | -12 | MTERefresh function has been called without the prior call of MTEAddTable. The update request package has to be prepared first. |
| MTE_FATALERROR | -13 | An unexpected fatal error has occurred. |
| MTE_INVALIDHANDLE | -14 | Invalid table descriptor. Either the descriptor hasn't been received with MTEOpenTable or a table has already been closed with MTECloseTable. |
| MTE_DSROFF | -15 | Serial port connection has been disrupted (no DSR signal). Probably the serial cable is damaged or the serial port is closed at one of the connecting sides. |
| MTE_UNKNOWN | -16 | Unexpected error occurred when executing a function. |
| MTE_BADPTR | -17 | Invalid pointer argument has been passed to a one of MTExxxx() function. |
| MTE_TRANSREJECTED | -18 | Trading system has processed the request and returned an error code. Transaction has been rejected. |
| MTE_TEUNAVAIL | -19 | Trading system is temporary unavailable. The server attempts to recover the connection with the Trading system, or waits for a trading session. |
| MTE_NOTLOGGEDIN | -20 | Client attempts to execute a request after the server has established a new connection session with the trading session. Client re-connection required. |
| MTE_WRONGVERSION | -21 | Current version of client library is not supported by server. |
| MTE_LOGON | -30 | Wrong login data (USERID, PASSWORD, etc.) provided. |
| MTE_TOOSLOWCONNECT | -31 | Too slow connection channel does not allow to finalize connection/reconnection procedure correctly. |
| MTE_CRYPTO_ERROR | -32 | Encryption/decryption error when creating/verifying the digital signature. |
| MTE_THREAD_ERROR | -33 | The client is trying to use one connection in two threads. For example, trying to call an MTExxxx() function while the previously executed MTExxxx() function has not finished its operation yet. |
| MTE_NOTIMPLEMENTED | -34 | The requested function is not supported by this version of client library. |
| MTE_ABANDONED | -35 | Returned by MTEDisconnect function (called in another thread), in case of working thread has been stopped by calling TerminateThread. |

APPENDIX 1. BUFFER FORMAT OF THE MTESTRUCTURE, MTESTRUCTURE2 AND MTESTRUCTUREEX FUNCTIONS

The Data field of the TMTEMsg structure, pointer to which is returned by the MTEStructure function, has the following format (for the description of basic types e.g. String, Integer, etc, see Appendix 4; in case of MTEStructure each String field is preceded with 4 bytes that indicate the length of the following string). Fields and values, passed only in MTEStructure2 function (similar to MTEStructureEx with *Version=2* attribute) are marked with red:

| Field | type |
|----------------------|---|
| TInterface: | |
| InterfaceName | String |
| InterfaceTitle | String |
| InterfaceDescription | String // only MTEStructureEx with Version>=2 |
| EnumeratedTypes | TEnumTypes |
| Tables | TTables |
| Transactions | TTransactions |

The description of information objects consists of three blocks: enumerated types, tables and transactions.

| | |
|-------------------|-----------|
| TEnumTypes: | |
| NumberOfTypes | Integer |
| Type ₁ | TEnumType |
| Type ₂ | TEnumType |
| ... | |
| Type _N | TEnumType |

| | |
|------------------------|---|
| TEnumType: | |
| Name | String |
| Title | String |
| Description | String // only MTEStructureEx with Version>=2 |
| Size | Integer |
| Type | TEnumKind |
| NumberOfConstants | Integer |
| Constant ₁ | TEnumConst |
| Constant ₂ | TEnumConst |
| ... | |
| Contstant _N | TEnumConst |

| | | |
|------------------------------|--------|--------------------------------------|
| TEnumConst for MTEStructure: | | |
| String | string | // formatted «Value=LongDescription» |

| | |
|--|--------|
| TEnumConst for MTEStructureEx with Version>=2: | |
| Value | string |
| LongDescription | string |
| ShortDescription | string |

| | |
|-------------|---------|
| TEnumKind: | Integer |
| ekCheck = 0 | |
| ekGroup = 1 | |
| ekCombo = 2 | |

Enumerated types are used to describe available values of table fields and transactions. A type description looks similar to the following:

| | |
|---------------------|--------------------------------------|
| 'TCurrency' | // Name |
| 'Currency' | // Description |
| 4 | // Size |
| ekCombo | // Preferred representation - "Type" |
| 3 | // Number of constants |
| 'RUR =Roubles' | // Constant 1 |
| 'USD =U.S. Dollars' | // Constant 2 |
| 'DEM =Marks' | // Constant 3 |

"Size" field (=4) indicates the size of available values for the fields of this type.

"Type" field (=ekCombo) assigns the preferred way of field representation that is used during the creation of a form for parameters entry. For example, the ekCombo field type can be presented as a list of values. Available values are illustrated below:



For MTEStructure constants consist of two parts – acceptable value (always with the length of "Length") and description of this value. Two parts are separated by the equals sign (=).

For MTEStructure2 and MTEStructureEx with Version>=2 constants value and their description are passed in separate fields.

```

TTables:
    NumberOfTables      Integer
    Table1             TTable
    Table2             TTable
    ...
    TableN             TTable

TTable:
    Name                String
    Title               String
    Description          String          // only MTEStructureEx with Version>=2
    SystemIndex         Integer        // only MTEStructureEx with Version>=2
    Attributes           TTableFlags
    InputFields          TFields
    OutputFields         TFields

TTableFlags:           Integer
    tfUpdateable        = 1
    tfClearOnUpdate     = 2
    tfOrderbook         = 4            // only MTEStructureEx with Version>=2

```

The list of table input fields is used when forming a parameter string for MTEOpenTable function.

The list of output parameters allows to parse buffers, returned by MTEOpenTable and MTERefresh functions.

"SystemIndex" field contains a number of subsystem of ASTS Trading system, which processes current request. Updates packet, formed by MTEAddTable calls, may contain only queries with the same "SystemIndex". Currently, for all markets, except for Derivatives market, the index is 0, and all the tables can be updated with a single MTERefresh call. There are two subsystems in the derivatives market: Trading system and Risk Management system – so all requests for update should be divided into two packets according to the "SystemIndex".

Table attributes can be combined (i.e. the value will be equal to 3) and have the following values:

tfUpdateable - the table is updateable. Functions MTEAddTable/MTERefresh can be used to get updates;

tfClearOnUpdate - the old table contents should be cleared before each update with MTEAddTable/MTERefresh functions.

tfClearOrderbook – the table has a orderbook (quotebook) format and should be appropriately processed (see. [Working with tables -> Notes](#)).


```

TFields:
    NumberOfFields      Integer
    Field1              TField
    Field2              TField
    ...
    FieldN              TField

TField:
    Name                String
    Title               String
    Description          String          // only MTEStructureEx with Version>=2
    Size                Integer
    Type                TFieldType
    NumbDecimalPlaces   Integer          // only MTEStructureEx with Version>=2
    Attributes          TFieldFlags
    EnumeratedType      String
    DefaultValue        String

TFieldType:              Integer
    ftChar              = 0
    ftInteger           = 1
    ftFixed             = 2
    ftFloat             = 3
    ftDate              = 4
    ftTime              = 5
    ftFloatPoint        = 6          // only MTEStructureEx with Version>=3

TFieldFlags:              Integer
    ffKey               = 0x01
    ffSecCode           = 0x02
    ffNotNull           = 0x04
    ffVarBlock          = 0x08          // only MTEStructureEx with Version>=2

```

Field attributes (TFieldFlags) can be combined and have the following values:

| | |
|-------------------|---|
| <i>ffKey</i> | Key field. Table rows with the same key field values should be merged in one string. |
| <i>ffSecCode</i> | This field contains security ID. It's recommended to consider this flag when automating the procedure of counting decimal places in fields of type <i>FLOAT</i> . |
| <i>ffNotNull</i> | Cannot be null. |
| <i>ffVarBlock</i> | This field may be repeated several times. |

Note. "DefaultValue" field is available only as input field.

"Size" defines the lengths of a field in characters.

"NumbDecimalPlaces" specifies the number of decimal places for fields of type ftFixed.

"EnumeratedType" can contain either name of an enumerated type to which a field refers or an empty string.

"Default Value" can be used when creating a form for parameters entry.

All fields are represented in trading system text format (see MTEExecTrans).

```

TTransactions:
    NuOfTransactions    Integer
    Transaction1        TTransaction
    Transaction2        TTransaction
    ...
    TransactionN        TTransaction

TTransaction:
    Name                String
    Title               String
    Description          String          // only MTEStructureEx with Version>=2
    SystemIndex         Integer          // only MTEStructureEx with Version>=2
    InputFields         TFields

```

The list of transaction input fields is used when forming a parameter string for the `MTEExecTrans` function.

APPENDIX 2. BUFFER FORMAT OF THE MTEOPENTABLE FUNCTION

The Data field of the `TMTEMsg` structure (pointer to `TMTEMsg` is returned by `MTEOpenTable` function) contains rows of a requested table and has the following format (for the description of the basic types e.g. `String`, `Integer`, etc, see Appendix 4):

| field | type |
|------------------------------|----------------------|
| <code>TMTETable:</code> | |
| <code>Ref</code> | <code>Integer</code> |
| <code>NuOfRows</code> | <code>Integer</code> |
| <code>Row₁</code> | <code>TMTERow</code> |
| <code>Row₂</code> | <code>TMTERow</code> |
| <code>...</code> | |
| <code>Row_N</code> | <code>TMTERow</code> |

"Ref" field is used when requesting updates for several tables simultaneously with `MTEAddTable`/`MTERefresh` functions. It contains the value of a third parameter passed to `MTEAddTable`(`Idx`, `Htable`, `Ref`) function. By value of this field, it's possible to determine which table (`Htable` descriptor) the received `TMTETable` structure corresponds to. The "Ref" field value is set to "0" in the buffer returned by the `MTEOpenTable`.

| | |
|-----------------------------|-----------------------------------|
| <code>TMTERow:</code> | |
| <code>NumberOfFields</code> | <code>Byte</code> |
| <code>DataLength</code> | <code>Integer</code> |
| <code>FieldNumber</code> | <code>Byte[NumberOfFields]</code> |
| <code>FieldData</code> | <code>Byte[DataLength]</code> |

Table rows have variable length and can contain different number of fields.

"NumberOfFields" field contains the number of table fields, present in a given string. If the value is 0 then strings contains all the fields of the table (see. `MTEStructure`).

"DataLength" field contains the total length of table fields, present in a given string.

"FieldsNumber" field has a variable length. Its size equals to the value of "NumberOfFields" field. This field contains numbers of fields (one byte per number), present in a given string. The number of field corresponds to the number of an output field in the description of information objects (see `MTEStructure`). If "NumberOfFields" is 0 then "FieldsNumber" is not available and all the fields' numbers should be taken sequentially: 0, 1, 2, 3 ... N.

"FieldsData" field (size equals to the size of "DataLength", in bytes) contains set of table fields values. The number of fields is defined by "NumberOfFields" and their total length – by "DataLength". Length and type of each field are defined in the description of an information object (see `MTEStructure`). All fields are represented in trading system text format (see `MTEExecTrans`).

Example:

Let the description of information objects, received with `MTEStructure`, defines the "Trades" table with the following input fields:

```
TRADES // "Trades"
TradeNum: Integer(12) // Number of a trade
TradeTime: Char(6) // Time of a trade
BuySell: Char(1) // "B" - buy, "S" - sell
SecCode: Char(17) // financial instrument code
Price: Float(9) // price
Qty: Integer(10) // quantity of lots
```

The function is invoked:

```
MTEOpenTable (Idx, 'TRADES', '', True, Msg);
```

As the result, Msg.Data field contains the following data:

```
{
    0x00000000,          // "Ref" field
    0x00000002,          // Two rows received
    0x04,                // First row has 4 fields
    0x00000030,          // Data length is 48 bytes
    #0#3#4#5,           // Numbers of fields 0, 3, 4, 5:
    // these are "TradeNum","SecCode","Price","Qty" fields from description
    '0000001205670CURRUSD000000TOD00025790000000000037'
    // Fields values: 120567, "0CURRUSD000000TOD", 25.79, 37
    0x02,                // Second row contains 2 fields
    0x17,                // Data length is 23 bytes
    #1#3,                // Numbers of fields 1, 3:
    // these are "TradeTime" abd "SecCode" fields from description
    '1029530CURRUSD000000TOM'
    // Fields values: "10:29:53" and "0CURRUSD000000TOM"
}
```

APPENDIX 3. BUFFER FORMAT OF THE MTEREFRESH FUNCTION

The Data field of the TMTEMsg structure (pointer to TMTEMsg is returned by MTEOpenRefresh function) contains several tables from the trading system and has the following format (for the description of the basic types e.g. String, Integer, etc, see Appendix 4):

| field | type |
|--------------------|-----------|
| TMTETables: | |
| NuOfTables | Integer |
| Table ₁ | TMTETable |
| Table ₂ | TMTETable |
| ... | |
| Table _N | TMTETable |

So the buffer can contains several tables. The format of this buffer is described in appendix 2.

APPENDIX 4. BASIC TYPES

MTESRL library uses the following structures to represent basic types:

Byte

One byte.

Integer

Four bytes in a format of x86 CPU (the little-endian byte goes first).

String

Structure as follows:

```
StringLength: Integer
StringText: Byte[StringLength]
```

Byte[N]

Byte array of the length of N.

APPENDIX 5. FORMAT OF THE FLOAT, FIXED, DATE, TIME, FLOATPOINT FIELD TYPES

Float

Values of fields of Float type (real numbers) are transmitted in text format without a decimal point. The number of digits after the decimal point in Float-type fields for a specific security is defined by the “DECIMALS” field of “SECURITIES” table.

The Float-type fields must contain [DECIMALS] number of digits after the decimal point. For example, the number 465.39 for a security with DECIMALS =4 must be represented as “4653900”. The value of “46539” would have been processed by the trading system as 4.6539.

Fixed

The Fixed-type fields are also passed as text strings without a decimal point. By default, fields of this type have two digits after the decimal point. However, when using MTEStructure2 and MTEStructureEx with *Version* ≥ 2 (see Appendix 1), the exact number of decimal places is passed.

Date

The Date-type fields are strings with DDMMYYYY format.

Date

The Time-type fields are strings with HHMMSS format.

FloatPoint

Values of fields of FloatPoint type (real numbers) are transmitted in a text format with the decimal point and should be supplemented to the required value with zeros on the left. This type is available when obtaining information objects structure with MTEStructureEx function with *Version* ≥ 3 attribute (see. Appendix 1). In case of using MTEStructure and MTEStructure2 the type is transmitted as a string (ftChar). Decimal point position is not strictly regulated. Decimal point and, if needed, sign of the number (positive or negative), are considered at length calculation. For example: FloatPoint(9): "001.45712", FloatPoint(16): "-0000012071000.5".