

Performance Monitoring Statistics for the SGW

DESCRIPTION

Copyright

© Ericsson AB 2013. All rights reserved. No part of this document may be reproduced in any form without the written permission of the copyright owner.

Disclaimer

The contents of this document are subject to revision without notice due to continued progress in methodology, design and manufacturing. Ericsson shall have no liability for any error or damage of any kind resulting from the use of this document.

Trademark List

All trademarks mentioned herein are the property of their respective owners. These are shown in the document Trademark Information.



Contents

1	Introduction	1
1.1	Scope	1
1.2	Reading Instructions	1
2	Counters and Gauges Information for the SGW	2
2.1	sgwNumberOfUes	2
2.2	sgwNumberOfSessions	4
2.3	sgwGtpTunnelMgmtTowardsMmeSgsn	5
2.4	sgwGtpTunnelMgmtTowardsPgw	24
2.5	sgwGtpPathMgmtTowardsMmeSgsn	38
2.6	sgwGtpPathMgmtTowardsPgw	41
2.7	sgwGtpOverloadProtection	45
2.8	sgwUplinkTraffic	46
2.9	sgwDownlinkTraffic	51
2.10	sgwEbm	57
2.11	sgwGtpErrorStats	58
2.12	offlineCharging	59
2.13	highAvailability	61
2.14	handover	63





1 Introduction

This document presents the counter groups, counters, and gauges of the SGW for GSM, WCDMA Systems, and LTE radio network access.

1.1 Scope

This document gives descriptions of the different counter groups, counters, and gauges of the SGW.

The values for performance monitoring objects are retrieved using the CLI or an Extensible Markup Language (XML) document.

For more information on counters and gauges, see *Operation and Maintenance Description*.

For more information about retrieving performance monitoring statistics using an XML document, see *Performance Management Interface Description*.

1.2 Reading Instructions

All the counter groups, counters, and gauges of the SGW are presented in Section 2 on page 2.

Under each counter group description, there is a counter list including all the counters that belong to this counter group. By clicking the object in the counter list, the user is directed to a description of the object. By clicking the group in the object description, the user is directed back to the counter list.

Each object is described with the following attributes:

Measurement Name	The descriptive name of the object
Description	An explanation of the measurement operation
Group	The counter group name that the counter belongs to
Type	The measurement type, either CC (Cumulative Counter) or GAUGE
Sub Type	The sub measurement type, always defined as SUM
Output Unit	A description of expected result value(s) (for example, a single integer value)



Size	The bit size of the value of the object
Status	The status of the object (USED, DEPRECATED, OBSOLETE, or PRELIMINARY)
Increments	The condition that causes the object to be incremented
Decrements	The condition that causes the object to be decremented
CLI	The CLI command that is executed to show the value of the object
Name in CLI Output	The presentation of the object in CLI output

2 Counters and Gauges Information for the SGW

2.1 sgwNumberOfUes

This counter group includes following counters:

sgwNbrOf Ues	sgwNbrOfConnectedUe s	nbrOfSuspendedUes
-----------------	--------------------------	-------------------

2.1.1 sgwNbrOfUes

Measurement Name	sgwNbrOfUes
Description	The total number of users in the SGW.
Group	sgwNumberOfUes
Type	GAUGE
Sub Type	SUM
Output Unit	integer
Size	32
Status	USED
Increments	When the first PDN connection for a UE is established in the SGW.



Decrements	When the last PDN connection for a UE is deleted from the SGW.
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-nbr-of-ues

2.1.2 **sgwNbrOfConnectedUes**

Measurement Name	sgwNbrOfConnectedUes
Description	The total number of connected users.
Group	sgwNumberOfUes
Type	GAUGE
Sub Type	SUM
Output Unit	integer
Size	32
Status	USED
Increments	When a user has downlink tunnel established in the SGW at initial attach for RAT type EUTRAN, and upon IRAT handover from non-EUTRAN to EUTRAN access.
Decrements	When a user is detached or deleted while a downlink tunnel is established, when a downlink tunnel is removed for RAT type EUTRAN, or upon IRAT handover from EUTRAN to non-EUTRAN access.
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-nbr-of-connected-ues

2.1.3 **nbrOfSuspendedUes**

Measurement Name	nbrOfSuspendedUes
Description	The total number of suspended users in the SGW.
Group	sgwNumberOfUes
Type	GAUGE
Sub Type	SUM
Output Unit	integer
Size	32
Status	USED



Increments	When the first PDN connection is suspended for a UE in the SGW.
Decrements	When the last PDN connection is resumed for a UE in the SGW.
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	nbr-of-suspended-ues

2.2 sgwNumberOfSessions

This counter group includes following counters:

sgwNbrOfPdnConnections	sgwNbrOfBearers	sgwNbrOf3gdtPdnConnections
------------------------	-----------------	----------------------------

2.2.1 sgwNbrOfPdnConnections

Measurement Name	sgwNbrOfPdnConnections
Description	The total number of PDN connections currently handled by the SGW.
Group	sgwNumberOfSessions
Type	GAUGE
Sub Type	SUM
Output Unit	integer
Size	32
Status	USED
Increments	When a PDN connection is established.
Decrements	When an PDN connection is disconnected.
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-nbr-of-pdn-connections

2.2.2 sgwNbrOfBearers

Measurement Name	sgwNbrOfBearers
Description	The total number of bearers currently handled by the SGW.
Group	sgwNumberOfSessions



Type	GAUGE
Sub Type	SUM
Output Unit	integer
Size	32
Status	USED
Increments	When a bearer is created.
Decrements	When a bearer is deleted.
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-nbr-of-bearers

2.2.3 **sgwNbrOf3gdtPdnConnections**

Measurement Name	sgwNbrOf3gdtPdnConnections
Description	The total number of PDN connections currently handled by the SGW and direct tunnel is established between RNC and SGW.
Group	sgwNumberOfSessions
Type	GAUGE
Sub Type	SUM
Output Unit	integer
Size	32
Status	USED
Increments	When a PDN connection is established with direct tunnel applied between RNC and SGW.
Decrements	When a PDN connection with 3G direct tunnel is disconnected, or when a PDN connection with 3G direct tunnel is modified and direct tunnel is not applied, or when a PDN connection with 3G direct tunnel is modified and whether direct tunnel is applied or not is not known.
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-nbr-of-3gdt-pdn-connections

2.3 **sgwGtpTunnelMgmtTowardsMmeSgsn**

This counter group includes following counters:



sgwCreateSessionReqReceived	sgwCreateSessionRespAccSent	sgwCreateSessionRespRejSent
sgwModifyBearerReqReceived	sgwModifyBearerRespAccSent	sgwModifyBearerRespRejSent
sgwDeleteSessionReqReceived	sgwDeleteSessionRespAccSent	sgwDeleteSessionRespRejSent
sgwDeleteBearerReqSent	sgwDeleteBearerRespAccReceived	sgwDeleteBearerRespRejReceived
sgwDIDataNotificationSent	sgwDIDataNotificationAckAccReceived	sgwDIDataNotificationAckRejReceived
sgwDIDataNotificationFailureIndReceived	sgwReleaseAccessBearersReqReceived	sgwReleaseAccessBearersRespAccSent
sgwReleaseAccessBearersRespRejSent	sgwUpdateBearerReqSent	sgwUpdateBearerRespAccReceived
sgwUpdateBearerRespRejReceived	sgwCreateIndirectDataFwdTunnelReqReceived	sgwCreateIndirectDataFwdTunnelRespAccSent
sgwCreateIndirectDataFwdTunnelRespRejSent	sgwCreateBearerRespRejReceived	sgwCreateBearerRespAccReceived
sgwCreateBearerReqSent	sgwDeleteBearerFailureIndSent	sgwDeleteBearerCmdReceived
sgwModifyBearerCmdReceived	sgwBearerResourceCmdReceived	sgwBearerResourceFailureIndSent
sgwModifyBearerFailureIndSent	suspendNotificationReceived	resumeNotificationReceived



2.3.1 **sgwCreateSessionReqReceived**

Measurement Name	sgwCreateSessionReqReceived
Description	The total number of GTPv2-C Create Session Request messages received by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Session Request message is received by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-session-req-received

2.3.2 **sgwCreateSessionRespAccSent**

Measurement Name	sgwCreateSessionRespAccSent
Description	The total number of GTPv2-C Create Session Response messages sent by the SGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Session Response message is sent by the SGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-session-resp-acc-sent



2.3.3 **sgwCreateSessionRespRejSent**

Measurement Name	sgwCreateSessionRespRejSent
Description	The total number of GTPv2-C Create Session Response messages sent by the SGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Session Response message is sent by the SGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-session-resp-rej-sent

2.3.4 **sgwModifyBearerReqReceived**

Measurement Name	sgwModifyBearerReqReceived
Description	The total number of GTPv2-C Modify Bearer Request messages received by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Modify Bearer Request message is received by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-modify-bearer-req-received



2.3.5 **sgwModifyBearerRespAccSent**

Measurement Name	sgwModifyBearerRespAccSent
Description	The total number of GTPv2-C Modify Bearer Response messages sent by the SGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Modify Bearer Response message is sent by the SGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-modify-bearer-resp-acc-sent

2.3.6 **sgwModifyBearerRespRejSent**

Measurement Name	sgwModifyBearerRespRejSent
Description	The total number of GTPv2-C Modify Bearer Response messages sent by the SGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Modify Bearer Response message is sent by the SGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-modify-bearer-resp-rej-sent



2.3.7 **sgwDeleteSessionReqReceived**

Measurement Name	sgwDeleteSessionReqReceived
Description	The total number of GTPv2-C Delete Session Request messages received by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Session Request message is received by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-session-req-received

2.3.8 **sgwDeleteSessionRespAccSent**

Measurement Name	sgwDeleteSessionRespAccSent
Description	The total number of GTPv2-C Delete Session Response messages sent by the SGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Session Response message is sent by the SGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-session-resp-acc-sent



2.3.9 **sgwDeleteSessionRespRejSent**

Measurement Name	sgwDeleteSessionRespRejSent
Description	The total number of GTPv2-C Delete Session Response messages sent by the SGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Session Response message is sent by the SGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-session-resp-rej-sent

2.3.10 **sgwDeleteBearerReqSent**

Measurement Name	sgwDeleteBearerReqSent
Description	The total number of GTPv2-C Delete Bearer Request messages sent by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Bearer Request message is sent by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-bearer-req-sent



2.3.11 **sgwDeleteBearerRespAccReceived**

Measurement Name	sgwDeleteBearerRespAccReceived
Description	The total number of GTPv2-C Delete Bearer Response messages sent by the SGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Bearer Response message is sent by the SGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-bearer-resp-acc-received

2.3.12 **sgwDeleteBearerRespRejReceived**

Measurement Name	sgwDeleteBearerRespRejReceived
Description	The total number of GTPv2-C Delete Bearer Response messages sent by the SGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Bearer Response message is sent by the SGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-bearer-resp-rej-received



2.3.13 **sgwDIDataNotificationSent**

Measurement Name	sgwDIDataNotificationSent
Description	The total number of GTPv2-C Downlink Data Notification messages sent by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Downlink Data Notification message is sent by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-dl-data-notification-sent

2.3.14 **sgwDIDataNotificationAckAccReceived**

Measurement Name	sgwDIDataNotificationAckAccReceived
Description	The total number of GTPv2-C Downlink Data Notification Acknowledgement messages received by the SGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Downlink Data Notification Acknowledge message is received by the SGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-dl-data-notification-ack-acc-received



2.3.15 **sgwDIDataNotificationAckRejReceived**

Measurement Name	sgwDIDataNotificationAckRejReceived
Description	The total number of GTPv2-C Downlink Data Notification Acknowledgement messages received by the SGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Downlink Data Notification Acknowledge message is received by the SGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-dl-data-notification-ack-rej-received

2.3.16 **sgwDIDataNotificationFailureIndReceived**

Measurement Name	sgwDIDataNotificationFailureIndReceived
Description	The total number of GTPv2-C Downlink Data Notification Failure Indication messages received by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Downlink Data Notification Failure Indication message is received by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-dl-data-notification-failure-ind-received



2.3.17 **sgwReleaseAccessBearersReqReceived**

Measurement Name	sgwReleaseAccessBearersReqReceived
Description	The total number of GTPv2-C Release Access Bearers Request messages received by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Release Access Bearers Request message is received by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-release-access-bearers-req-received

2.3.18 **sgwReleaseAccessBearersRespAccSent**

Measurement Name	sgwReleaseAccessBearersRespAccSent
Description	The total number of GTPv2-C Release Access Bearers Response messages sent by the SGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Release Access Bearers Response message is sent by the SGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-release-access-bearers-resp-acc-sent



2.3.19 **sgwReleaseAccessBearersRespRejSent**

Measurement Name	sgwReleaseAccessBearersRespRejSent
Description	The total number of GTPv2-C Release Access Bearers Response messages sent by the SGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Release Access Bearers Response message is sent by the SGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-release-access-bearers-resp-rej-sent

2.3.20 **sgwUpdateBearerReqSent**

Measurement Name	sgwUpdateBearerReqSent
Description	The total number of GTPv2-C Update Bearer Request messages sent by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Update Bearer Request message is sent by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-update-bearer-req-sent



2.3.21 **sgwUpdateBearerRespAccReceived**

Measurement Name	sgwUpdateBearerRespAccReceived
Description	The total number of GTPv2-C Update Bearer Response messages received by the SGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Update Bearer Response message is received by the SGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-update-bearer-resp-acc-received

2.3.22 **sgwUpdateBearerRespRejReceived**

Measurement Name	sgwUpdateBearerRespRejReceived
Description	The total number of GTPv2-C Update Bearer Response messages received by the SGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Update Bearer Response message is received by the SGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-update-bearer-resp-rej-received



2.3.23 **sgwCreateIndirectDataFwdTunnelReqReceived**

Measurement Name	sgwCreateIndirectDataFwdTunnelReqReceived
Description	The total number of GTPv2-C Create Indirect Data Forwarding Tunnel Request messages received by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Indirect Data Forwarding Tunnel Request message is received by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-indirect-data-fwd-tunnel-req-received

2.3.24 **sgwCreateIndirectDataFwdTunnelRespAccSent**

Measurement Name	sgwCreateIndirectDataFwdTunnelRespAccSent
Description	The total number of GTPv2-C Create Indirect Data Forwarding Tunnel Response messages sent by the SGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Indirect Data Forwarding Tunnel Response message is sent by the SGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-indirect-data-fwd-tunnel-resp-acc-sent

**2.3.25****sgwCreateIndirectDataFwdTunnelRespRejSent**

Measurement Name	sgwCreateIndirectDataFwdTunnelRespRejSent
Description	The total number of GTPv2-C Create Indirect Data Forwarding Tunnel Response messages sent by the SGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Indirect Data Forwarding Tunnel Response message is sent by the SGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-indirect-data-fwd-tunnel-resp-rej-sent

2.3.26**sgwCreateBearerRespRejReceived**

Measurement Name	sgwCreateBearerRespRejReceived
Description	The total number of GTPv2-C Create Bearer Response messages received by the SGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Bearer Response message is received by the SGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-bearer-resp-rej-received



2.3.27 **sgwCreateBearerRespAccReceived**

Measurement Name	sgwCreateBearerRespAccReceived
Description	The total number of GTPv2-C Create Bearer Response messages received by the SGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Bearer Response message is received by the SGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-bearer-resp-acc-received

2.3.28 **sgwCreateBearerReqSent**

Measurement Name	sgwCreateBearerReqSent
Description	The total number of GTPv2-C Create Bearer Request messages sent by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Bearer Request message is sent by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-bearer-req-sent



2.3.29 **sgwDeleteBearerFailureIndSent**

Measurement Name	sgwDeleteBearerFailureIndSent
Description	The total number of GTPv2-C Delete Bearer Failure Indication messages sent by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Bearer Failure Indication message is sent by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-bearer-failure-ind-sent

2.3.30 **sgwDeleteBearerCmdReceived**

Measurement Name	sgwDeleteBearerCmdReceived
Description	The total number of GTPv2-C Delete Bearer Command messages received by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Bearer Command message is received by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-bearer-cmd-received



2.3.31 **sgwModifyBearerCmdReceived**

Measurement Name	sgwModifyBearerCmdReceived
Description	The total number of GTPv2-C Modify Bearer Command messages received by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Modify Bearer Command message is received by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-modify-bearer-cmd-received

2.3.32 **sgwBearerResourceCmdReceived**

Measurement Name	sgwBearerResourceCmdReceived
Description	The total number of GTPv2-C Bearer Resource Command messages received by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Bearer Resource Command message is received by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-bearer-resource-cmd-received



2.3.33 **sgwBearerResourceFailureIndSent**

Measurement Name	sgwBearerResourceFailureIndSent
Description	The total number of GTPv2-C Bearer Resource Failure Indication messages sent by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Bearer Resource Failure Indication message is sent by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-bearer-resource-failure-ind-sent

2.3.34 **sgwModifyBearerFailureIndSent**

Measurement Name	sgwModifyBearerFailureIndSent
Description	The total number of GTPv2-C Modify Bearer Failure Indication messages sent by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Modify Bearer Failure Indication message is sent by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-modify-bearer-failure-ind-sent



2.3.35 **suspendNotificationReceived**

Measurement Name	suspendNotificationReceived
Description	The total number of GTPv2-C Suspend Notification messages received by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Suspend Notification message is received by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	suspend-notification-received

2.3.36 **resumeNotificationReceived**

Measurement Name	resumeNotificationReceived
Description	The total number of GTPv2-C Resume Notification messages received by the SGW.
Group	sgwGtpTunnelMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Resume Notification message is received by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	resume-notification-received

2.4 **sgwGtpTunnelMgmtTowardsPgw**

This counter group includes following counters:



sgwCreateSessionReqSent	sgwCreateSessionRespAccReceived	sgwCreateSessionRespRejReceived
sgwModifyBearerReqSent	sgwModifyBearerRespAccReceived	sgwModifyBearerRespRejReceived
sgwDeleteSessionReqSent	sgwDeleteSessionRespAccReceived	sgwDeleteSessionRespRejReceived
sgwDeleteBearerReqReceived	sgwDeleteBearerRespAccSent	sgwDeleteBearerRespRejSent
sgwUpdateBearerReqReceived	sgwUpdateBearerRespAccSent	sgwUpdateBearerRespRejSent
sgwCreateBearerReqReceived	sgwCreateBearerRespAccSent	sgwCreateBearerRespRejSent
sgwModifyBearerCmdSent	sgwModifyBearerFailureIndReceived	sgwDeleteBearerCmdSent
sgwDeleteBearerFailureIndReceived	sgwBearerResourceCmdSent	sgwBearerResourceFailureIndReceived
resumeNotificationSent	suspendNotificationSent	

2.4.1 **sgwCreateSessionReqSent**

Measurement Name	sgwCreateSessionReqSent
Description	The total number of GTPv2-C Create Session Request messages sent to the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Create Session Request message is sent to the PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-session-req-sent

2.4.2 **sgwCreateSessionRespAccReceived**

Measurement Name	sgwCreateSessionRespAccReceived
Description	The total number of GTPv2-C Create Session Response messages received from the PGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Session Response message is received from the PGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-session-resp-acc-received

2.4.3 **sgwCreateSessionRespRejReceived**

Measurement Name	sgwCreateSessionRespRejReceived
Description	The total number of GTPv2-C Create Session Response messages received from the PGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Create Session Response message is received from the PGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-session-resp-rej-received

2.4.4 **sgwModifyBearerReqSent**

Measurement Name	sgwModifyBearerReqSent
Description	The total number of GTPv2-C Modify Bearer Request messages sent to the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Modify Bearer Request message is sent to the PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-modify-bearer-req-sent

2.4.5 **sgwModifyBearerRespAccReceived**

Measurement Name	sgwModifyBearerRespAccReceived
Description	The total number of GTPv2-C Modify Bearer Response messages received from the PGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Modify Bearer Response message is received from the PGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-modify-bearer-resp-acc-received

2.4.6 **sgwModifyBearerRespRejReceived**

Measurement Name	sgwModifyBearerRespRejReceived
Description	The total number of GTPv2-C Modify Bearer Response messages received from the PGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Modify Bearer Response message is received from the PGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-modify-bearer-resp-rej-received

2.4.7 **sgwDeleteSessionReqSent**

Measurement Name	sgwDeleteSessionReqSent
Description	The total number of GTPv2-C Delete Session Request messages sent to the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Delete Session Request message is sent to the PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-session-req-sent

2.4.8 **sgwDeleteSessionRespAccReceived**

Measurement Name	sgwDeleteSessionRespAccReceived
Description	The total number of GTPv2-C Delete Session Response messages received from the PGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Session Response message is received from the PGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-session-resp-acc-received

2.4.9 **sgwDeleteSessionRespRejReceived**

Measurement Name	sgwDeleteSessionRespRejReceived
Description	The total number of GTPv2-C Delete Session Response messages received from the PGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Delete Session Response message is received from the PGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-session-resp-rej-received

2.4.10 **sgwDeleteBearerReqReceived**

Measurement Name	sgwDeleteBearerReqReceived
Description	The total number of GTPv2-C Delete Bearer Request messages received from the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Bearer Request message is received from the PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-bearer-req-received

2.4.11 **sgwDeleteBearerRespAccSent**

Measurement Name	sgwDeleteBearerRespAccSent
Description	The total number of GTPv2-C Delete Bearer Response messages sent to the PGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Delete Bearer Response message is sent to the PGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-bearer-resp-acc-sent

2.4.12 **sgwDeleteBearerRespRejSent**

Measurement Name	sgwDeleteBearerRespRejSent
Description	The total number of GTPv2-C Delete Bearer Response messages sent to the PGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Bearer Response message is sent to the PGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-bearer-resp-rej-sent

2.4.13 **sgwUpdateBearerReqReceived**

Measurement Name	sgwUpdateBearerReqReceived
Description	The total number of GTPv2-C Update Bearer Request messages received from PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Update Bearer Request message is received from the PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-update-bearer-req-received

2.4.14 **sgwUpdateBearerRespAccSent**

Measurement Name	sgwUpdateBearerRespAccSent
Description	The total number of GTPv2-C Update Bearer Response messages sent to the PGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Update Bearer Response message is sent to the PGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-update-bearer-resp-acc-sent

2.4.15 **sgwUpdateBearerRespRejSent**

Measurement Name	sgwUpdateBearerRespRejSent
Description	The total number of GTPv2-C Update Bearer Response messages sent to the PGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Update Bearer Response message is sent to the PGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-update-bearer-resp-rej-sent

2.4.16 **sgwCreateBearerReqReceived**

Measurement Name	sgwCreateBearerReqReceived
Description	The total number of GTPv2-C Create Bearer Request messages received from the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Bearer Request message is received from the PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-bearer-req-received

2.4.17 **sgwCreateBearerRespAccSent**

Measurement Name	sgwCreateBearerRespAccSent
Description	The total number of GTPv2-C Create Bearer Response messages sent to the PGW with an acceptance response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Create Bearer Response message is sent to the PGW with an acceptance response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-bearer-resp-acc-sent

2.4.18 **sgwCreateBearerRespRejSent**

Measurement Name	sgwCreateBearerRespRejSent
Description	The total number of GTPv2-C Create Bearer Response messages sent to the PGW with a rejection response cause value.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Bearer Response message is sent to the PGW with a rejection response cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-create-bearer-resp-rej-sent

2.4.19 **sgwModifyBearerCmdSent**

Measurement Name	sgwModifyBearerCmdSent
Description	The total number of GTPv2-C Modify Bearer Command messages sent to the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Modify Bearer Command message is sent to the PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-modify-bearer-cmd-sent

2.4.20 **sgwModifyBearerFailureIndReceived**

Measurement Name	sgwModifyBearerFailureIndReceived
Description	The total number of GTPv2-C Modify Bearer Failure Indication messages received from the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Modify Bearer Failure Indication message is received from the PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-modify-bearer-failure-ind-received

2.4.21 **sgwDeleteBearerCmdSent**

Measurement Name	sgwDeleteBearerCmdSent
Description	The total number of GTPv2-C Delete Bearer Command messages sent to the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Bearer Command message is sent to the PGW.



Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-bearer-cmd-sent

2.4.22 **sgwDeleteBearerFailureIndReceived**

Measurement Name	sgwDeleteBearerFailureIndReceived
Description	The total number of GTPv2-C Delete Bearer Failure Indication messages received from the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Delete Bearer Failure Indication message is received from the PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-delete-bearer-failure-ind-received

2.4.23 **sgwBearerResourceCmdSent**

Measurement Name	sgwBearerResourceCmdSent
Description	The total number of GTPv2-C Bearer Resource Command messages sent to the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Bearer Resource Command message is sent to the PGW.
Decrements	N/A



CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-bearer-resource-cmd-sent

2.4.24 **sgwBearerResourceFailureIndReceived**

Measurement Name	sgwBearerResourceFailureIndReceived
Description	The total number of GTPv2-C Bearer Resource Failure Indication messages received from the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Bearer Resource Failure Indication message is received from PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-bearer-resource-failure-ind-received

2.4.25 **resumeNotificationSent**

Measurement Name	resumeNotificationSent
Description	The total number of GTPv2-C Resume Notification messages sent to the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Resume Notification message is sent to the PGW.
Decrements	N/A



CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	resume-notification-sent

2.4.26 suspendNotificationSent

Measurement Name	suspendNotificationSent
Description	The total number of GTPv2-C Suspend Notification messages sent to the PGW.
Group	sgwGtpTunnelMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Suspend Notification message is sent to the PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	suspend-notification-sent

2.5 sgwGtpPathMgmtTowardsMmeSgsn

This counter group includes following counters:

sgwMmeSgsnEchoReqSent	sgwMmeSgsnEchoRespAccReceived	sgwMmeSgsnEchoRespRejReceived
sgwMmeSgsnEchoReqReceived	sgwMmeSgsnEchoRespAccSent	sgwMmeSgsnEchoRespRejSent

2.5.1 sgwMmeSgsnEchoReqSent

Measurement Name	sgwMmeSgsnEchoReqSent
Description	The total number of GTPv2-C Echo Request messages sent to the S4-SGSN or the MME.
Group	sgwGtpPathMgmtTowardsMmeSgsn



Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Echo Request message is sent to the S4-SGSN or the MME.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-mme-sgsn-echo-req-sent

2.5.2 **sgwMmeSgsnEchoRespAccReceived**

Measurement Name	sgwMmeSgsnEchoRespAccReceived
Description	The total number of GTPv2-C Echo Response messages received from the S4-SGSN or the MME with no cause value included.
Group	sgwGtpPathMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Echo Response message is received from the S4-SGSN or the MME with no cause value included.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-mme-sgsn-echo-resp-acc-received

2.5.3 **sgwMmeSgsnEchoRespRejReceived**

Measurement Name	sgwMmeSgsnEchoRespRejReceived
Description	The total number of GTPv2-C Echo Response messages received from the S4-SGSN or the MME with a rejection cause value.
Group	sgwGtpPathMgmtTowardsMmeSgsn



Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Echo Response message is received from the S4-SGSN or the MME with a rejection cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-mme-sgsn-echo-resp-rej-received

2.5.4 **sgwMmeSgsnEchoReqReceived**

Measurement Name	sgwMmeSgsnEchoReqReceived
Description	The total number of GTPv2-C Echo Request messages received from the S4-SGSN or the MME.
Group	sgwGtpPathMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Echo Request message is received from the S4-SGSN or the MME.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-mme-sgsn-echo-req-received

2.5.5 **sgwMmeSgsnEchoRespAccSent**

Measurement Name	sgwMmeSgsnEchoRespAccSent
Description	The total number of GTPv2-C Echo Response messages sent to the S4-SGSN or the MME with no cause value included.
Group	sgwGtpPathMgmtTowardsMmeSgsn



Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Echo Response message is sent to the S4-SGSN or the MME with no cause value included.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-mme-sgsn-echo-resp-acc-sent

2.5.6 **sgwMmeSgsnEchoRespRejSent**

Measurement Name	sgwMmeSgsnEchoRespRejSent
Description	The total number of GTPv2-C Echo Response messages sent to the S4-SGSN or the MME with a rejection cause value.
Group	sgwGtpPathMgmtTowardsMmeSgsn
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Echo Response message with a rejection cause is sent to the S4-SGSN or the MME.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-mme-sgsn-echo-resp-rej-sent

2.6 **sgwGtpPathMgmtTowardsPgw**

This counter group includes following counters:



sgwPgwEchoReqSent	sgwPgwEchoRespAccReceived	sgwPgwEchoRespRejReceived
sgwPgwEchoReqReceived	sgwPgwEchoRespAccSent	sgwPgwEchoRespRejSent

2.6.1

sgwPgwEchoReqSent

Measurement Name	sgwPgwEchoReqSent
Description	The total number of GTPv2-C Echo Request messages sent to the PGW.
Group	sgwGtpPathMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Echo Request message is sent to the PGW
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-pgw-echo-req-sent

2.6.2

sgwPgwEchoRespAccReceived

Measurement Name	sgwPgwEchoRespAccReceived
Description	The total number of GTPv2-C Echo Response messages received from the PGW with no cause value included.
Group	sgwGtpPathMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Echo Response message is received from the PGW with no cause value included.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-pgw-echo-resp-acc-received

2.6.3 **sgwPgwEchoRespRejReceived**

Measurement Name	sgwPgwEchoRespRejReceived
Description	The total number of GTPv2-C Echo Response messages received from the PGW with a rejection cause value.
Group	sgwGtpPathMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Echo Response message is received from the PGW with a rejection cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-pgw-echo-resp-rej-received

2.6.4 **sgwPgwEchoReqReceived**

Measurement Name	sgwPgwEchoReqReceived
Description	The total number of GTPv2-C Echo Request messages received from the PGW.
Group	sgwGtpPathMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Echo Request message is received from the PGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-pgw-echo-req-received

2.6.5 **sgwPgwEchoRespAccSent**

Measurement Name	sgwPgwEchoRespAccSent
Description	The total number of GTPv2-C Echo Response messages sent to the PGW with no cause value included.
Group	sgwGtpPathMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Echo Response message is sent to the PGW with no cause value included.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-pgw-echo-resp-acc-sent

2.6.6 **sgwPgwEchoRespRejSent**

Measurement Name	sgwPgwEchoRespRejSent
Description	The total number of GTPv2-C Echo Response messages sent to the PGW with a rejection cause value.
Group	sgwGtpPathMgmtTowardsPgw
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a GTPv2-C Echo Response message is sent to the PGW with a rejection cause value.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-pgw-echo-resp-rej-sent

2.7 sgwGtpOverloadProtection

This counter group includes following counters:

sgwGtpMessageDrops	sgwGtpCreateMessageDrops
--------------------	--------------------------

2.7.1 sgwGtpMessageDrops

Measurement Name	sgwGtpMessageDrops
Description	The total number of GTPv2-C Tunneling Management Messages that have been dropped by the node due to overload situations. When an overload situation occurs this counter is incremented and the message is dropped before the relevant message counter is incremented.
Group	sgwGtpOverloadProtection
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Tunneling Management Message has been dropped by the node due to an overload situation.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-gtp-message-drops



2.7.2 sgwGtpCreateMessageDrops

Measurement Name	sgwGtpCreateMessageDrops
Description	The total number of GTPv2-C Create Messages that have been dropped by the node due to overload situations. When an overload situation occurs this counter is incremented and the message is dropped before the create message counter is incremented.
Group	sgwGtpOverloadProtection
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C create Message has been dropped by the node due to an overload situation.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-gtp-create-message-drops

2.8 sgwUplinkTraffic

This counter group includes following counters:

sgwUplinkDroppedPackets	sgwUplinkDroppedBytes	gtpIncDataPktS1uS4S12
gtpIncDataByteS1uS4S12	gtpOutDataPktS5S8	gtpOutDataByteS5S8
gtpDroppedIncDataPktS1uS4S12	gtpDroppedOutDataPktS5S8	

2.8.1 sgwUplinkDroppedPackets

Measurement Name	sgwUplinkDroppedPackets
Description	The total number of uplink packets dropped by the SGW.



Group	sgwUplinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an uplink packet is dropped by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-uplink-dropped-packets

2.8.2 **sgwUplinkDroppedBytes**

Measurement Name	sgwUplinkDroppedBytes
Description	The total number of uplink bytes dropped by the SGW.
Group	sgwUplinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an uplink user plane packet is dropped by the SGW the bytes are counted.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-uplink-dropped-bytes

2.8.3 **gtplncDataPktS1uS4S12**

Measurement Name	gtplncDataPktS1uS4S12
Description	The total number of incoming user plane packets handled by the GTP stack on one of the S1, S4 or S12 interfaces.
Group	sgwUplinkTraffic
Type	CC



Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an incoming user plane packet received on one of the S1, S4 or S12 interfaces has been handled by the GTP stack.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-inc-data-pkt-s1us4s12

2.8.4 **gtpIncDataByteS1uS4S12**

Measurement Name	gtpIncDataByteS1uS4S12
Description	The total number of incoming user plane Bytes handled by the GTP stack on one of the S1, S4 or S12 interfaces. The bytes in the G-PDU is counted without the GTP header.
Group	sgwUplinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an incoming user plane packet received on one of the S1, S4 or S12 interfaces has been handled by the GTP stack, the Bytes are counted.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-inc-data-byte-s1us4s12

2.8.5 **gtpOutDataPktS5S8**

Measurement Name	gtpOutDataPktS5S8
Description	The total number of outgoing user plane packets handled by the GTP stack on the S5 or the S8 interfaces.



Group	sgwUplinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an outgoing user plane packet sent on the S5 or the S8 interfaces has been handled by the GTP stack.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-out-data-pkt-s5s8

2.8.6

gtpOutDataByteS5S8

Measurement Name	gtpOutDataByteS5S8
Description	The total number of outgoing user plane Bytes handled by the GTP stack on the S5 or the S8 interfaces. The bytes in the G-PDU is counted without the GTP header.
Group	sgwUplinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an outgoing user plane packet sent on the S5 or the S8 interfaces has been handled by the GTP stack, the Bytes are counted.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-out-data-byte-s5s8



2.8.7 **gtpDroppedIncDataPktS1uS4S12**

Measurement Name	gtpDroppedIncDataPktS1uS4S12
Description	The total number of incoming user plane packets dropped by the GTP stack on one of the S1, S4 or S12 interfaces.
Group	sgwUplinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an incoming user plane packet received on one of the S1, S4 or S12 interfaces is dropped by the GTP stack.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-dropped-inc-data-pkt-s1us4s12

2.8.8 **gtpDroppedOutDataPktS5S8**

Measurement Name	gtpDroppedOutDataPktS5S8
Description	The total number of outgoing user plane packets dropped by the GTP stack on the S5 or S8 interfaces.
Group	sgwUplinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an outgoing user plane packet sent on the S5 or the S8 interfaces is dropped by the GTP stack.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-dropped-out-data-pkt-s5s8



2.9 sgwDownlinkTraffic

This counter group includes following counters:

sgwDownlinkDroppedPackets	sgwDownlinkDroppedBytes	sgwDroppedPacketsBufferOverflow
sgwDroppedBytesBufferOverflow	droppedBytesSuspend	droppedPacketsSuspend
gtpIncDataPktS5S8	gtpIncDataByteS5S8	gtpOutDataPktS1uS4S12
gtpOutDataByteS1uS4S12	gtpDroppedIncDataPktS5S8	gtpDroppedOutDataPktS1uS4S12

2.9.1 sgwDownlinkDroppedPackets

Measurement Name	sgwDownlinkDroppedPackets
Description	The total number of downlink packets dropped by the SGW.
Group	sgwDownlinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a downlink user plane packet is dropped by the SGW.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-downlink-dropped-packets

2.9.2 sgwDownlinkDroppedBytes

Measurement Name	sgwDownlinkDroppedBytes
Description	The total number of downlink bytes dropped by the SGW.



Group	sgwDownlinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a downlink user plane packet is dropped by the SGW the bytes are counted.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-downlink-dropped-bytes

2.9.3 **sgwDroppedPacketsBufferOverflow**

Measurement Name	sgwDroppedPacketsBufferOverflow
Description	The total number of downlink packets dropped by the SGW due to overflow of the buffer.
Group	sgwDownlinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a downlink user plane packet is dropped by the SGW due to buffer overflow.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-dropped-packets-buffer-overflow

2.9.4 **sgwDroppedBytesBufferOverflow**

Measurement Name	sgwDroppedBytesBufferOverflow
Description	The total number of downlink bytes dropped by the SGW due to overflow of the buffer.
Group	sgwDownlinkTraffic
Type	CC



Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a downlink user plane packet is dropped by the SGW due to buffer overflow, the bytes are counted.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-dropped-bytes-buffer-overflow

2.9.5 **droppedBytesSuspend**

Measurement Name	droppedBytesSuspend
Description	The total number of downlink bytes dropped by the SGW due to suspension.
Group	sgwDownlinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a downlink user plane packet is dropped by the SGW due to UE suspension, the bytes are counted.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	dropped-bytes-suspend

2.9.6 **droppedPacketsSuspend**

Measurement Name	droppedPacketsSuspend
Description	The total number of downlink packets dropped by the SGW due to suspension.
Group	sgwDownlinkTraffic
Type	CC



Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a downlink user plane packet is dropped by the SGW due to UE suspension.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	dropped-packets-suspend

2.9.7 **gtplncDataPktS5S8**

Measurement Name	gtplncDataPktS5S8
Description	The total number of incoming user plane packets handled by the GTP stack on the S5 or the S8 interfaces.
Group	sgwDownlinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an incoming user plane packet received on the S5 or the S8 interfaces has been handled by the GTP stack.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-inc-data-pkt-s5s8

2.9.8 **gtplncDataByteS5S8**

Measurement Name	gtplncDataByteS5S8
Description	The total number of incoming user plane Bytes handled by the GTP stack on the S5 or the S8 interfaces. The bytes in the G-PDU is counted without the GTP header.
Group	sgwDownlinkTraffic



Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an incoming user plane packet received on the S5 or the S8 interfaces has been handled by the GTP stack, the Bytes are counted.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-inc-data-byte-s5s8

2.9.9 **gtpOutDataPktS1uS4S12**

Measurement Name	gtpOutDataPktS1uS4S12
Description	The total number of outgoing user plane packets handled by the GTP stack on one of the S1, S4 or S12 interfaces.
Group	sgwDownlinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an outgoing user plane packet sent on one of the S1, S4 or S12 interfaces has been handled by the GTP stack.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-out-data-pkt-s1us4s12



2.9.10 gtpOutDataByteS1uS4S12

Measurement Name	gtpOutDataByteS1uS4S12
Description	The total number of outgoing user plane Bytes handled by the GTP stack on one of the S1, S4 or S12 interfaces. The bytes in the G-PDU is counted without the GTP header.
Group	sgwDownlinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an outgoing user plane packet sent on one of the S1, S4 or S12 interfaces has been handled by the GTP stack, the Bytes are counted.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-out-data-byte-s1us4s12

2.9.11 gtpDroppedIncDataPktS5S8

Measurement Name	gtpDroppedIncDataPktS5S8
Description	The total number of incoming user plane packets dropped by the GTP stack on the S5 or S8 interfaces.
Group	sgwDownlinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an incoming user plane packet received on the S5 or the S8 interfaces is dropped by the GTP stack.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-dropped-inc-data-pkt-s5s8



2.9.12 gtpDroppedOutDataPktS1uS4S12

Measurement Name	gtpDroppedOutDataPktS1uS4S12
Description	The total number of outgoing user plane packets dropped by the GTP stack on one of the S1, S4 or S12 interfaces.
Group	sgwDownlinkTraffic
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an outgoing user plane packet sent on one of the S1, S4 or S12 interfaces is dropped by the GTP stack.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	gtp-dropped-out-data-pkt-s1us4s12

2.10 sgwEbm

This counter group includes following counters:

sgwEbmEv sgwEbmBytes
ents

2.10.1 sgwEbmEvents

Measurement Name	sgwEbmEvents
Description	The total number of sgw events transmitted over the ebm streaming interface.
Group	sgwEbm
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED



Increments	When a Sgw Ebm event is transmitted over the ebm streaming interface, the number of events is counted.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-ebm-events

2.10.2 **sgwEbmBytes**

Measurement Name	sgwEbmBytes
Description	The total number of sgw event bytes transmitted over the ebm streaming interface.
Group	sgwEbm
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a Sgw Ebm event is transmitted over the ebm streaming interface the bytes are counted.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-ebm-bytes

2.11 **sgwGtpErrorStats**

This counter group includes following counters:

sgwGtpErr
orResourc
esUnavaila
ble

2.11.1 **sgwGtpErrorResourcesUnavailable**

Measurement Name	sgwGtpErrorResourcesUnavailable
Description	The number of GTP resources unavailable errors sent by the SGW.



Group	sgwGtpErrorStats
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C message is rejected with the cause No Resources Available.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	sgw-gtp-error-no-resources

2.12 offlineCharging

This counter group includes following counters:

rfAcctReq WrittenTo Disk	rfAcctReqSent	rfAcctAnswerRejRec
rfAcctAnswerAccRec		

2.12.1 rfAcctReqWrittenToDisk

Measurement Name	rfAcctReqWrittenToDisk
Description	The total number of Accounting Requests written to disk by the SGW.
Group	offlineCharging
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an Accounting Request message is written to disk by the SGW.
Decrements	N/A



CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	rf-acct-req-written-to-disk

2.12.2 **rfAcctReqSent**

Measurement Name	rfAcctReqSent
Description	The total number of Accounting Requests sent by the SGW over the Rf interface.
Group	offlineCharging
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an Accounting Request message is sent by the SGW over the Rf interface.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	rf-acct-req-sent

2.12.3 **rfAcctAnswerRejRec**

Measurement Name	rfAcctAnswerRejRec
Description	The total number of Accounting Answers received by the SGW over the Rf interface without result code DIAMETER_SUCCESS, or with syntax errors.
Group	offlineCharging
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an Accounting Answer message is received by the SGW over the Rf interface without result code DIAMETER_SUCCESS, or with syntax errors.
Decrements	N/A



CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	rf-acct-answer-rej-rec

2.12.4 **rfAcctAnswerAccRec**

Measurement Name	rfAcctAnswerAccRec
Description	The total number of Accounting Answers received by the SGW over the Rf interface with result code DIAMETER_SUCCESS.
Group	offlineCharging
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When an Accounting Answer message is received by the SGW over the Rf interface with result code DIAMETER_SUCCESS.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	rf-acct-answer-acc-rec

2.13 **highAvailability**

This counter group includes following counters:

icrCreateSessionSyncSent	icrCreateSessionSyncReceived	icrDeleteSessionSyncSent
icrDeleteSessionSyncReceived		

2.13.1 **icrCreateSessionSyncSent**

Measurement Name	icrCreateSessionSyncSent
Description	The total number of create session synchronization messages sent over the ICR synchronization channel.



Group	highAvailability
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a create session synchronization message is sent over the ICR synchronization channel
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	icr-create-session-sync-sent

2.13.2 **icrCreateSessionSyncReceived**

Measurement Name	icrCreateSessionSyncReceived
Description	The total number of create session synchronization messages received over the ICR synchronization channel.
Group	highAvailability
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a create session synchronization message is received over the ICR synchronization channel
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	icr-create-session-sync-received

2.13.3 **icrDeleteSessionSyncSent**

Measurement Name	icrDeleteSessionSyncSent
Description	The total number of delete session synchronization messages sent over the ICR synchronization channel.



Group	highAvailability
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a delete session synchronization message is sent over the ICR synchronization channel
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	icr-delete-session-sync-sent

2.13.4 **icrDeleteSessionSyncReceived**

Measurement Name	icrDeleteSessionSyncReceived
Description	The total number of delete session synchronization messages received over the ICR synchronization channel.
Group	highAvailability
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a delete session synchronization message is received over the ICR synchronization channel
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	icr-delete-session-sync-received

2.14 handover

This counter group includes following counters:

attemptedPdnHoFromNon3gpp	completedPdnHoFromNon3gpp
---------------------------	---------------------------



2.14.1 attemptedPdnHoFromNon3gpp

Measurement Name	attemptedPdnHoFromNon3gpp
Description	Total number of PDN Connection IRAT handover attempts from non-3GPP to 3GPP.
Group	handover
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Create Session Request message with the Handover Indicator flag set is received.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	attempted-pdn-ho-from-non-3gpp

2.14.2 completedPdnHoFromNon3gpp

Measurement Name	completedPdnHoFromNon3gpp
Description	Total number of successful PDN Connection IRAT handover procedures from non-3GPP to 3GPP.
Group	handover
Type	CC
Sub Type	SUM
Output Unit	integer
Size	64
Status	USED
Increments	When a GTPv2-C Modify Bearer Response message with an acceptance response cause value is sent as a result of a successful PDN Connection IRAT handover procedure from non-3GPP to 3GPP.
Decrements	N/A
CLI	ManagedElement=1,Epg=1,Sgw=1,statistics
Name in CLI Output	completed-pdn-ho-from-non-3gpp