

How to enable docker remote API on docker host ?

1. Navigate to `/lib/systemd/system` in your terminal and open `docker.service` file
`vi /lib/systemd/system/docker.service`
2. Find the line which starts with `ExecStart` and adds `-H=tcp://0.0.0.0:2375` to make it look like
`ExecStart=/usr/bin/dockerd -H=fd:// -H=tcp://0.0.0.0:2375`
3. Save the Modified File
4. Reload the docker daemon
`systemctl daemon-reload`
5. Restart the container
`sudo service docker restart`
6. Test if it is working by using this command, if everything is fine below command should return a JSON
`curl http://localhost:2375/images/json`
7. To test remotely, use the PC name or IP address of Docker Host