

# NSX Command Line Interface Reference

NSX 6.1 for vSphere

This document supports the version of each product listed and supports all subsequent versions until the document is replaced by a new edition. To check for more recent editions of this document, see <http://www.vmware.com/support/pubs>.

EN-001589-00

**vmware®**

You can find the most up-to-date technical documentation on the VMware Web site at:

<http://www.vmware.com/support/>

The VMware Web site also provides the latest product updates.

If you have comments about this documentation, submit your feedback to:

[docfeedback@vmware.com](mailto:docfeedback@vmware.com)

Copyright © 2012 - 2014 VMware, Inc. All rights reserved. This product is protected by U.S. and international copyright and intellectual property laws. VMware products are covered by one or more patents listed at <http://www.vmware.com/go/patents>.

VMware is a registered trademark or trademark of VMware, Inc. in the United States and/or other jurisdictions. All other marks and names mentioned herein may be trademarks of their respective companies.

**VMware, Inc.**  
3401 Hillview Ave.  
Palo Alto, CA 94304  
[www.vmware.com](http://www.vmware.com)

# Contents

About This Book	9
<b>1 Introduction to the NSX CLI</b>	<b>11</b>
CLI Command Modes	11
Logging In and Out of the CLI	12
Syntax Notation Used in this Document	12
Moving Around in the CLI	12
Getting Help within the CLI	13
<b>2 Securing CLI User Accounts</b>	<b>15</b>
CLI User Account Management	15
Hardening the CLI of an NSX Virtual Appliance	15
Change the admin User Account Password	15
Change the CLI Privileged Mode Password	16
Add a CLI User Account	16
Delete the admin User Account from the CLI	17
<b>3 NSX CLI Commands</b>	<b>19</b>
NSX Manager Commands	19
configure terminal	19
database erase	19
disable	20
enable	20
enable password	20
exit	21
export tech-support scp	21
hostname	21
interface	22
ip address	22
ip route	23
list	23
ping	23
reset	24
quit	24
reboot	24
set clock	25
setup	25
show arp	25
show clock	26
show ethernet	26
show filesystem	26
show manager log	27
show manager log last	27
show slots	28
show tech-support	28
shutdown	28
ssh	29
terminal length	29

- terminal no length 29
- traceroute 30
- user 30
- write 30
- write erase 31
- write memory 31
- NSX Edge Commands 31
  - clear nat counters 31
  - clear arp WORD 32
  - clear service dhcp lease 32
  - clear service ipsec sa 32
  - debug packet capture 32
  - debug packet display interface 32
  - dnslookup *serverName* 33
  - dnslookup *serverName* | *address* 33
  - debug crashdump 33
  - debug packet display interface 33
  - export tech-support scp 34
  - ping 34
  - ping interface addr 35
  - show arp 35
  - show clock 35
  - show configuration 36
  - show configuration dhcp 36
  - show configuration dns 37
  - show configuration firewall 38
  - show configuration global 39
  - show configuration highavailability 40
  - show configuration interface 41
  - show configuration ipsec 43
  - show configuration ipset 44
  - show configuration l2vpn 44
  - show configuration loadbalancer 45
  - show configuration loadbalancer monitor 47
  - Example 47
  - show configuration loadbalancer pool *poolName* 48
  - Example 48
  - show configuration loadbalancer rule *ruleName* 49
  - show configuration loadbalancer virtual *virtualServerName* 49
  - Example 49
  - show configuration nat 49
  - show configuration ospf 51
  - show configuration static\_routing 52
  - show configuration syslog 52
  - show configuration sslvpn-plus 53
  - show fips 53
  - show firewall 53
  - show firewall flows 53
  - show firewall flows top *number* 53
  - show firewall flows top *number* sort-by pkts 54
  - show firewall flows top *number* sort-by bytes 54
  - show firewall rule-id *ID* 54
  - show firewall rule-id *ID* flows 54
  - show firewall rule-id *ID* flows top *number* 54
  - show firewall rule-id *ID* flows top *number* sort-by pkts 55
  - show firewall rule-id *ID* flows top *number* sort-by-bytes 55
  - show flowtable 55

show flowtable rule-id <i>ID</i>	55
show flowtable rule-id <i>ID</i> top <i>number</i>	55
show flowtable rule-id <i>ID</i> top <i>number</i> sort-by pkts	55
show flowtable rule-id <i>ID</i> top <i>number</i> sort-by bytes	56
show flowtable top <i>number</i>	56
show flowtable top <i>number</i> sort-by pkts	56
show flowtable top <i>number</i> sort-by bytes	56
show hostname	56
show interface	57
show interface <i>name</i>	57
show ip bgp	57
show ip bgp neighbors	57
show ip forwarding	58
show ip ospf	58
show ip ospf database	59
show ip ospf database adv-router	59
show ip ospf database asbr-summary	60
show ip ospf database external	60
show ip ospf database network	60
show ip ospf database nssa-external	61
show ip ospf database opaque-area	61
show ip ospf database router	61
show ip ospf database summary	61
show ip ospf interface	62
show ip ospf ne	62
show ip ospf statistics	62
show ip route	63
show ip route ospf	63
show ip route bgp	64
show ip route A.B.C.D/M	64
show log	64
show log follow	65
show log last	65
show log reverse	65
show nat	66
show process	66
show route	66
show service	66
show service l2vpn (on server)	67
show service l2vpn (on client)	67
show service l2vpn bridge	67
show service l2vpn trunk-table	68
show service l2vpn conversion table	68
show service monitor	69
show service monitor service	69
show service dhcp	70
show service dns	70
show service ipsec	71
show service ipsec cacerts	71
show service ipsec certs	71
show service ipsec crls	71
show service ipsec pubkeys	72
show service ipsec sa	72
show service ipsec sp	72
show service highavailability	72
show service highavailability link	72
show service highavailability connection-sync	73

```

show service loadbalancer 73
show service loadbalancer monitor monitorName 73
show service loadbalancer pool poolName 73
show service loadbalancer session 74
show service loadbalancer table 74
show service loadbalancer virtual serverName 74
show service network connections 74
show service sslvpn-plus 75
show service sslvpn-plus stats 75
show service sslvpn-plus sessions 75
show service sslvpn-plus tunnels 75
show system load 75
show system network-stats 76
show system cpu 76
show system log size 76
show system memory 76
show system storage 77
show system uptime 77
show tech-support 77
show version 77
traceroute 77

NSX Controller Commands 78
restart controller 78
set control-cluster core log-level value 78
show control-cluster core 78
show control-cluster logical-routers 79
show control-cluster logical-routers bridge-mac logicalRouterID_and/or_bridgeID 80
show control-cluster logical-routers bridges logicalRouterID_and_bridgeID 80
show control-cluster logical-routers instance logicalRouterID 80
show control-cluster logical-routers interface logicalRouterID_and_logicalRouterName 80
show control-cluster logical-routers interface-summary logicalRouterID 81
show control-cluster logical-routers routes routerID 81
show control-cluster logical-routers routes routerID_and_IPaddress_and_prefixLength 81
show control-cluster logical-routers stats 81
show control-cluster logical-routers vdr-stats logicalRouterID 81
show control-cluster startup-nodes 82
show control-cluster status 82
show network interface 82

ESXi CLI Commands 83
esxcli network vswitch dvs vmware vxlan config stats get 83
esxcli network vswitch dvs vmware vxlan config stats set 83
esxcli network vswitch dvs vmware vxlan get 83
esxcli network vswitch dvs vmware vxlan list --vds-name value 83
esxcli network vswitch dvs vmware vxlan network list --vds-name value vxlan-id value 84
esxcli network vswitch dvs vmware vxlan network arp list --vds-name value --vxlan-id value 84
esxcli network vswitch dvs vmware vxlan network arp reset --vds-name value --vxlan-id value 84
esxcli network vswitch dvs vmware vxlan network mac list --vds-name value --vxlan-id value 84
esxcli network vswitch dvs vmware vxlan network mac reset --vxlan-id value --vdsport-id value 85
esxcli network vswitch dvs vmware vxlan network port list --vds-name value --vdsport-id value
--vxlan-id value 85
esxcli network vswitch dvs vmware vxlan network port stats list --vds-name value --vdsport-id value
--vxlan-id value 85
esxcli network vswitch dvs vmware vxlan network stats list --vdsd-name value --vxlan-id value 85
esxcli network vswitch dvs vmware vxlan network stats reset --vxlan-id value --vdsport-id value 86
esxcli network vswitch dvs vmware vxlan network vtep list --vds-name value --vxlan-id value
--segment-id value --vtep-ip value 86

```

esxcli network vswitch dvs vmware vxlan vmknic list --vds-name <i>value</i> --endpoint-id <i>value</i> --vmknic-name <i>value</i> --vmknic-ip <i>value</i>	87
esxcli network vswitch dvs vmware vxlan vmknic multicastgroup list --vds-name <i>value</i> --vmknic-id <i>value</i> --vmknic-name <i>value</i> --vmknic-ip <i>value</i>	87
esxcli network vswitch dvs vmware vxlan stats list --vds-name <i>value</i> --endpoint-id <i>value</i> --vmknic-name <i>value</i> --vmknic-ip <i>value</i>	87
esxcli network vswitch dvs vmware vxlan stats reset --vds-name <i>value</i>	88
DVFilter Commands	88
summarize-dvfilter	88
Deprecated Commands	89
Index	93





# About This Book

---

The *NSX Command Line Interface Reference* describes how to use the NSX for vSphere Command Line Interface (CLI) and includes examples and command overviews.

## Intended Audience

This guide is intended for anyone who wants to install or use NSX in a VMware vCenter environment. The information in this guide is written for experienced system administrators who are familiar with virtual machine technology and virtual datacenter operations. This guide assumes familiarity with VMware Infrastructure 4.x, including VMware ESX, vCenter Server, and the vSphere Client.

## VMware Technical Publications Glossary

VMware Technical Publications provides a glossary of terms that might be unfamiliar to you. For definitions of terms as they are used in VMware technical documentation go to <http://www.vmware.com/support/pubs>.

## Document Feedback

VMware welcomes your suggestions for improving our documentation. If you have comments, send your feedback to [docfeedback@vmware.com](mailto:docfeedback@vmware.com).

## NSX Documentation

The following documents comprise the NSX documentation set:

- *NSX Administration Guide*
- *NSX Installation and Upgrade Guide*
- *NSX API Programming Guide*



# Introduction to the NSX CLI

---

IT organizations have gained significant benefits as a direct result of server virtualization. Server consolidation reduced physical complexity, increased operational efficiency and the ability to dynamically re-purpose underlying resources to quickly and optimally meet the needs of increasingly dynamic business applications.

VMware's Software Defined Data Center (SDDC) architecture is now extending virtualization technologies across the entire physical data center infrastructure. VMware NSX®, the network virtualization platform, is a key product in the SDDC architecture. With NSX, virtualization delivers for networking what it has already delivered for compute and storage. In much the same way that server virtualization programmatically creates, snapshots, deletes and restores software-based virtual machines (VMs), NSX network virtualization programmatically creates, snapshots, deletes, and restores software-based virtual networks. The result is a completely transformative approach to networking that not only enables data center managers to achieve orders of magnitude better agility and economics, but also allows for a vastly simplified operational model for the underlying physical network. With the ability to be deployed on any IP network, including both existing traditional networking models and next-generation fabric architectures from any vendor, NSX is a completely non-disruptive solution. In fact, with NSX, the physical network infrastructure you already have is all you need to deploy a software-defined data center.

To use the NSX virtual appliance CLI, you must have console access to an NSX virtual appliance. Each NSX virtual appliance contains a command line interface (CLI). The viewable modes in the NSX CLI can differ based on the assigned role and rights of a user. If you are unable to access an interface mode or issue a particular command, consult your NSX administrator.

---

**NOTE** User account management in the CLI is separate from user account management in the NSX Manager user interface.

---

This chapter includes the following topics:

- [“CLI Command Modes”](#) on page 11
- [“Logging In and Out of the CLI”](#) on page 12
- [“Syntax Notation Used in this Document”](#) on page 12
- [“Moving Around in the CLI”](#) on page 12
- [“”](#) on page 13

## CLI Command Modes

The commands available to you at any given time depend on the mode you are currently in.

---

**NOTE** NSX Edge virtual machines have Basic mode only.

---

- **Basic.** Basic mode is a read-only mode. To have access to all commands, you must enter Privileged mode.

- **Privileged.** Privileged mode commands allow support-level options such as debugging and system diagnostics. To save configuration changes you have made in Privileged mode, you must run the write memory command. Otherwise, the changes are lost upon reboot.
- **Configuration.** Configuration mode commands allow you to change the current configuration of utilities on an NSX virtual appliance. You can access Configuration mode from Privileged mode. From Configuration mode, you can enter Interface configuration mode.
- **Interface Configuration.** Interface Configuration mode commands allow you to change the configuration of virtual machine interfaces. For example, you can change the IP address and IP route for the management port of the NSX Manager.

## Logging In and Out of the CLI

Before you can run CLI commands, you must initiate a console session to an NSX virtual appliance. To open a console session within the vSphere Client, select the NSX virtual appliance from the inventory panel and click the **Console** tab. You can log in to the CLI by using the default user name admin and the password you specified while installing NSX Manager.

You can also use SSH to access the CLI. If you did not enable SSH while installing NSX Manager, you can use the ssh command to enable and disable the SSH service on an NSX virtual appliance. See “ssh” on page 29.

To log out, type exit from either Basic or Privileged mode.

## Syntax Notation Used in this Document

Run commands at the prompt as shown. Do not type the ( ), < >, or [ ] symbols.

command A.B.C.D (option1 | option2) <0-512> [WORD]

- Required numerical ranges are enclosed in angle brackets.
- Required text is presented in all capital letters.
- Multiple, required keywords or options are enclosed in parentheses and separated by a pipe character.
- An optional keyword or value is enclosed in square brackets.

## Moving Around in the CLI

The following commands move the pointer around on the command line.

Keystrokes	Description
CTRL+A	Moves the pointer to beginning of the line.
CTRL+B or the left arrow key	Moves the pointer back one character.
CTRL+C	Ends any operation that continues to propagate, such as a ping.
CTRL+D	Deletes the character at the pointer.
CTRL+E	Moves the pointer to end of the line.
CTRL+F or the right arrow key	Moves the pointer forward one character.
CTRL+K	Deletes all characters from the pointer to the end of the line.
CTRL+N or the down arrow key	Displays more recent commands in the history buffer after recalling commands with CTRL+P (or the up arrow key). Repeat to recall other recently run commands.
CTRL+P or the up arrow key	Recalls commands in the history, starting with the most recent completed command. Repeat to recall successively older commands.
CTRL+U	Deletes all characters from the pointer to beginning of the line.

Keystrokes	Description
CTRL+W	Deletes the word to the left of pointer.
ENTER	Scrolls down one line.
ESC+B	Moves the pointer back one word.
ESC+D	Deletes all characters from the pointer to the end of the word.
ESC+F	Moves the pointer forward one word.
SPACE	Scrolls down one screen.

## Getting Help within the CLI

The CLI contains the following commands to assist you.

Command	Description
?	Moves the pointer to the beginning of the line.
sho?	Displays a list of commands that begin with a particular character string.
exp+TAB	Completes a partial command name.
show ?	Lists the associated keywords of a command.
show log ?	Lists the associated arguments of a keyword.
list	Displays the verbose options of all commands for the current mode.



# Securing CLI User Accounts

---

Each NSX virtual appliance comes with a default user account and password.

---

**NOTE** User account management in the CLI is separate from user account management in the NSX Manager user interface.

---

This chapter includes the following topics:

- [“CLI User Account Management”](#) on page 15
- [“Hardening the CLI of an NSX Virtual Appliance”](#) on page 15
- [“Add a CLI User Account”](#) on page 16
- [“Delete the admin User Account from the CLI”](#) on page 17

## CLI User Account Management

You must manage CLI user accounts separately on each NSX virtual appliance. By default, you use the admin user account to log in to the CLI of each NSX virtual appliance.

The Privileged mode password is managed separately from the admin user account password. The default Privileged mode password is the same for each CLI user account.

---

**IMPORTANT** Each NSX virtual appliance has a built-in CLI user account (nobody) for system use. Do not delete or modify this account. If this account is deleted or modified, the virtual machine will not work.

---

You can create new CLI user accounts. Each created user account has administrator-level access to the CLI.

## Hardening the CLI of an NSX Virtual Appliance

To harden access to the CLI of an NSX virtual appliance, you must change the admin user account and Privileged mode passwords after initial login.

### Change the admin User Account Password

#### To change the admin user account password

- 1 Log in to the vSphere Client and select an NSX virtual appliance from the inventory.
- 2 Click the **Console** tab to open a CLI session.
- 3 Log in to the CLI and switch to Privileged mode.  

```
manager> enable
password:
manager#
```
- 4 Switch to Configuration mode.

- ```
manager# configure terminal
```
- 5 Change the admin account password.  

```
manager(config)# cli password PASSWORD
```

where PASSWORD is replaced with the new password you want to use.
  - 6 Save the configuration.  

```
manager(config)# write memory
Building Configuration...
Configuration saved.
[OK]
```

## Change the CLI Privileged Mode Password

You can change the Privileged mode password to secure access to the configuration options of the CLI.

### To change the Privileged mode password

- 1 Log in to the vSphere Client and select an NSX virtual appliance from the inventory.
- 2 Click the **Console** tab to open a CLI session.
- 3 Log in to the CLI and switch to Privileged mode.  

```
manager> enable
password:
manager#
```
- 4 Switch to Configuration mode.  

```
manager# configure terminal
```
- 5 Change the Privileged mode password.  

```
manager(config)# enable password PASSWORD
```
- 6 Save the configuration.  

```
manager(config)# write memory
Building Configuration...
Configuration saved.
[OK]
```
- 7 Run the exit command twice to log out of the CLI.  

```
manager(config)# exit
manager# exit
```
- 8 Log in to the CLI and switch to Privileged mode by using the new password.  

```
manager> enable
password:
manager#
```

## Add a CLI User Account

You can add CLI user accounts for each NSX virtual appliance.

### To add a CLI user account

- 1 Log in to the vSphere Client and select an NSX virtual appliance from the inventory.
- 2 Click the **Console** tab to open a CLI session.
- 3 Log in by using the admin account.  

```
manager login: admin
password:
manager>
```



- 4 Switch to Privileged mode.

```
manager> enable
password:
manager#
```

- 5 Switch to Configuration mode.

```
manager# configure terminal
```

- 6 Add a user account.

```
manager(config)# user abc password plaintext PASSWORD
```

where abc is replaced with the username and PASSWORD is replaced with the desired password.

- 7 Save the configuration.

```
manager(config)# write memory
Building Configuration...
Configuration saved.
[OK]
```

- 8 Exit the CLI.

```
manager(config)# exit
manager# exit
```

## Delete the admin User Account from the CLI

Do not delete the admin user account until you add a user account to replace the admin account. This prevents you from being locked out of the CLI.

### To delete the admin user account

- 1 Log in to the vSphere Client and select an NSX virtual appliance from the inventory.

- 2 Click the **Console** tab to open a CLI session.

- 3 Log in by using a user account other than admin.

- 4 Switch to Privileged mode.

```
manager> enable
password:
manager#
```

- 5 Switch to Configuration mode.

```
manager# configure terminal
```

- 6 Delete the admin user account.

```
manager(config)# no user admin
```

- 7 Save the configuration.

```
manager(config)# write memory
Building Configuration...
Configuration saved.
[OK]
```

- 8 Run the exit command twice to log out of the CLI.

```
manager(config)# exit
manager# exit
```



# NSX CLI Commands

---

The chapter includes the following topics:

- [“NSX Manager Commands”](#) on page 19
- [“NSX Edge Commands”](#) on page 31
- [“NSX Controller Commands”](#) on page 78
- [“ESXi CLI Commands”](#) on page 83
- [“DVFilter Commands”](#) on page 88
- [“Deprecated Commands”](#) on page 89

## NSX Manager Commands

This section describes NSX Manager CLI commands.

### configure terminal

Switches to Configuration mode from Privileged mode.

#### Synopsis

configure terminal

#### CLI Mode

Privileged

#### Example

```
vShield# configure terminal
vShield(config)#
```

#### Related Commands

[interface](#)

### database erase

Erases the NSX Manager database, resetting the database to factory defaults. This command clears all configuration data from the NSX Manager user interface. The NSX Manager CLI configuration is not affected by this command.

#### Synopsis

database erase

**CLI Mode**

Privileged

**Example**

```
manager# database erase
```

**disable**

Switches to Basic mode from Privileged mode.

**Synopsis**

```
disable
```

**CLI Mode**

Basic

**Example**

```
vShield# disable
vShield>
```

**Related Commands**[enable](#)**enable**

Switches to Privileged mode from Basic mode.

**Synopsis**

```
enable
```

**CLI Mode**

Basic

**Example**

```
vShield> enable
password:
vShield#
```

**Related Commands**[disable](#)**enable password**

Changes the Privileged mode password. You should change the Privileged mode password for each NSX virtual machine. CLI user passwords and the Privileged mode password are managed separately. The Privileged mode password is the same for each CLI user account.

**Synopsis**

```
enable password PASSWORD
```

| Option   | Description                                       |
|----------|---------------------------------------------------|
| PASSWORD | Password to use. The default password is default. |

**CLI Mode**

Configuration

**Example**

```
vShield# configure terminal
vShield(config)# enable password abcd123
```

**Related Commands**

[enable](#)

**exit**

Exits from the current mode and switches to the previous mode, or exits the CLI session if run from Privileged or Basic mode.

**Synopsis**

```
exit
```

**CLI Mode**

Basic, Privileged, Configuration, and Interface Configuration

**Example**

```
vShield(config-if)# exit
vShield(config)# exit
vShield#
```

**Related Commands**

[quit](#)

**export tech-support scp**

Exports the system diagnostics to a specific location via Secure Copy Protocol (SCP). You can also export system diagnostics for an NSX virtual machine from the NSX Manager user interface.

**Synopsis**

```
export tech-support scp URL
```

| Option | Description                                                                                                              |
|--------|--------------------------------------------------------------------------------------------------------------------------|
| URL    | Enter the username and complete path of the destination. Standard scp /ssh syntax is used for username and machine name. |

**CLI Mode**

Basic and Privileged

**Example**

```
vShield# export tech-support scp user123@host123:file123
```

**hostname**

Changes the host name of the machine, which is used as the CLI prompt. The default prompt name for the NSX Manager is `manager`.

**Synopsis**

```
hostname WORD
```

| Option | Description         |
|--------|---------------------|
| WORD   | Prompt name to use. |

**CLI Mode**

Configuration

**Example**

```
vShield(config)# hostname vs123
vs123(config)#
```

**interface**

Switches to Interface Configuration mode for the specified interface.

To delete the configuration of an interface, use `no` before the command.

**Synopsis**

```
[no] interface mgmt
```

| Option | Description                                    |
|--------|------------------------------------------------|
| mgmt   | The management port on an NSX virtual machine. |

**CLI Mode**

Configuration

**Example**

```
vShield# configure terminal
vShield(config)# interface mgmt
vShield(config-if)#
```

or

```
vShield(config)# no interface mgmt
```

**ip address**

Assigns an IP address to an interface. On the NSX virtual machines, you can assign an IP address to the management interface only.

To remove an IP address from an interface, use `no` before the command.

**Synopsis**

```
[no] ip address A.B.C.D/M
```

| Option  | Description         |
|---------|---------------------|
| A.B.C.D | IP address to use.  |
| M       | Subnet mask to use. |

**CLI Mode**

Interface Configuration

**Example**

```
vShield(config)# interface mgmt
vShield(config-if)# ip address 192.168.110.200/24
```

or

```
vShield(config)# interface mgmt
vShield(config-if)# no ip address 192.168.110.200/24
```

## ip route

Adds a static route.

To delete an IP route, use `no` before the command.

### Synopsis

[no] ip route A.B.C.D/M W.X.Y.Z

| Option  | Description                    |
|---------|--------------------------------|
| A.B.C.D | IP address to use.             |
| M       | Subnet mask to use.            |
| W.X.Y.Z | IP address of network gateway. |

### CLI Mode

Configuration

### Example

```
vShield# configure terminal
vShield(config)# ip route 0.0.0.0/0 192.168.1.1

or

vShield(config)# no ip route 0.0.0.0/0 192.168.1.1
```

## list

Lists all in-mode commands.

### Synopsis

list

### CLI Mode

Basic, Privileged, Configuration, Interface Configuration

### Examples

```
NSXMgr> list
enable
exit
list
ping WORD
...
```

## ping

Pings a destination by its hostname or IP address.

### Synopsis

ping (HOSTNAME | A.B.C.D)

| Option             | Description                                      |
|--------------------|--------------------------------------------------|
| HOSTNAME   A.B.C.D | The hostname or IP address of the target system. |

### CLI Mode

Basic, Privileged

**Usage Guidelines**

Enter CTRL+C to end ping replies.

**Example**

```
vShield# ping 192.168.1.1
```

**reset**

Resets the terminal settings to remove the current screen output and return a clean prompt.

**Synopsis**

```
reset
```

**CLI Mode**

Basic, Privileged, Configuration

**Example**

```
manager# reset
```

**Related Commands**

[terminal length](#)

[terminal no length](#)

**quit**

Quits Interface Configuration mode and switches to Configuration mode, or quits the CLI session if run from Privileged or Basic mode.

**Synopsis**

```
quit
```

**CLI Mode**

Basic, Privileged, and Interface Configuration

**Example**

```
vShield(config-if)# quit  
vShield(config)#
```

**Related Commands**

[exit](#)

**reboot**

Reboots an NSX virtual appliance.

**Synopsis**

```
reboot
```

**CLI Mode**

Privileged

**Related Commands**

```
shutdown
```



## set clock

Sets the date and time if not using an NTP server.

### Synopsis

set clock HH:MM:SS MM DD YYYY

| Option   | Description           |
|----------|-----------------------|
| HH:MM:SS | Hours:minutes:seconds |
| MM       | Month                 |
| DD       | Day                   |
| YYYY     | Year                  |

### CLI Mode

Privileged

### Example

```
vShield# show clock
Mon Apr 7 05:26:49 UTC 2014
```

### Related Commands

[show clock](#)

## setup

Opens the CLI initialization wizard for NSX virtual machine installation. You configure multiple settings by using this command. You run the setup command during NSX Manager installation. Press ENTER to accept a default value.

### Synopsis

setup

### CLI Mode

Basic

### Example

```
manager(config)# setup
Default settings are in square brackets '['].
Hostname [manager]:
IP Address (A.B.C.D or A.B.C.D/MASK): 192.168.0.253
Default gateway (A.B.C.D): 192.168.0.1
Old configuration will be lost, and system needs to be rebooted
Do you want to save new configuration (y/[n]): y
Please log out and log back in again.
```

## show arp

Shows the contents of the ARP cache.

### Synopsis

show arp

### CLI Mode

Basic, Privileged

**Example**

```
vShield# show arp
IP address    HW type  Flags  HW address    Mask  Device
192.0.2.130   0x1      0x6    00:00:00:00:81 *    virteth1
192.168.110.1 0x1      0x2    00:0F:90:D5:36:C1 *    mgmt
```

**show clock**

Shows the current time and date of the virtual machine. If you use an NTP server for time synchronization, the time is based on Coordinated Universal Time (UTC).

**Synopsis**

```
show clock
```

**CLI Mode**

Basic, Privileged

**Example**

```
vShield# show clock
Wed Feb  9 13:04:50 UTC 2005
```

**Related Commands**

[set clock](#)

**show ethernet**

Shows Ethernet information for virtual machine interfaces.

**Synopsis**

```
show ethernet
```

**CLI Mode**

Basic, Privileged

**Example**

```
vShield# show ethernet
Settings for mgmt:
  Supported ports: [ TP ]
  Supported link modes: 10baseT/Half 10baseT/Full
                        100baseT/Half 100baseT/Full
                        1000baseT/Full
  Supports auto-negotiation: Yes
  Advertised link modes: 10baseT/Half 10baseT/Full
                        100baseT/Half 100baseT/Full
                        1000baseT/Full
  Advertised auto-negotiation: Yes
  Speed: 100Mb/s
  Duplex: Full
```

**show filesystem**

Shows the hard disk drive capacity for an NSX virtual machine. NSX Manager has two disk drives.

**Synopsis**

```
show filesystem
```

**CLI Mode**

Basic, Privileged

**Example**

```
vShield# show filesystem
Filesystem      Size  Used Avail Use% Mounted on
/dev/hda3        4.9G  730M   3.9G  16% /
/dev/hda6        985M   17M   919M   2% /tmp
/dev/hda7        24G   1.7G   21G   8% /common
```

**show manager log**

Shows the system log of the NSX Manager.

**Synopsis**

show manager log [follow | reverse]

| Option        | Description                                                        |
|---------------|--------------------------------------------------------------------|
| follow        | Update the displayed log every 5 seconds.                          |
| reverse       | Show the log in reverse chronological order.                       |
| size          | Display manager log size.                                          |
| last <i>n</i> | Display the last <i>n</i> number of events in the NSX Manager log. |

**CLI Mode**

Basic, Privileged

**Example**

```
vShield# show manager log
SEM Debug Nov 15, 2005 02:46:23 PM PropertyUtils Prefix:applicationDir

SEM Debug Nov 15, 2005 02:46:23 PM PropertyUtils Props Read:[]
SEM Info Nov 15, 2005 02:46:23 PM RefreshDb UpdateVersionNumbers info does not exist

SEM Debug Nov 15, 2005 02:46:23 PM RefreshDb Applications: []
SEM Info Nov 15, 2005 02:46:23 PM RefreshDb Compiler version pairs found: []
```

**Related Commands**

[show manager log last](#)

**show manager log last**

Shows the last *n* number of events in the NSX Manager log.

**Synopsis**

show manager log last NUM

| Option | Description                  |
|--------|------------------------------|
| NUM    | Number of events to display. |

**CLI Mode**

Basic, Privileged

**Example**

```
manager# show manager log last 10
```

**Related Commands**

[show network interface](#)

## show slots

Shows the software images on the slots of an NSX virtual machine. Boot indicates the image that is used to boot the virtual machine.

### Synopsis

show slots

### CLI Mode

Basic, Privileged

### Example

```
manager# show slots
Recovery: System Recovery v0.3.2
Slot 1: 13Aug09-09.49PDT
Slot 2: * 16Aug09-23.52PDT (Boot)
```

## show tech-support

Shows the system diagnostic log that can be sent to technical support by running the export tech-support scp command.

### Synopsis

show tech-support

### CLI Mode

Basic, Privileged

### Example

```
vShield# show tech-support
```

## shutdown

In Privileged mode, the shutdown command powers off the virtual machine. In Interface Configuration mode, the shutdown command disables the interface.

To enable a disabled interface, use no before the command.

### Synopsis

[no] shutdown

### CLI Mode

Privileged, Interface Configuration

### Example

```
vShield# shutdown

or

vShield(config)# interface mgmt
vShield(config-if)# shutdown
vShield(config-if)# no shutdown
```

### Related Commands

[reboot](#)

The feature commands help you monitor NSX Edge states and statistics.

## ssh

Starts or stops the SSH service on an NSX virtual appliance.

### Synopsis

ssh (start | stop)

### CLI Mode

Privileged

### Example

manager# ssh start

or

manager# ssh stop

## terminal length

Sets the number of rows to display at a time in the CLI terminal.

### Synopsis

terminal length <0-512>

| Option | Description                                                                           |
|--------|---------------------------------------------------------------------------------------|
| 0-512  | Enter the number of rows to display. If length is 0, no display control is performed. |

### CLI Mode

Privileged

### Example

manager# terminal length 50

### Related Commands

[terminal length](#)

[terminal no length](#)

## terminal no length

Negates the terminal length command.

### Synopsis

terminal no length

### CLI Mode

Privileged

### Example

manager# terminal no length

### Related Commands

[terminal length](#)

[terminal length](#)

## traceroute

Traces the route to a destination.

### Synopsis

traceroute (HOSTNAME | A.B.C.D)

| Option             | Description                                      |
|--------------------|--------------------------------------------------|
| HOSTNAME   A.B.C.D | The hostname or IP address of the target system. |

### CLI Mode

Basic, Privileged

### Example

```
vShield# traceroute 10.16.67.118
traceroute to 10.16.67.118 (10.16.67.118), 30 hops max, 40 byte packets
 1 10.115.219.253 (10.115.219.253) 128.808 ms 74.876 ms 74.554 ms
 2 10.17.248.51 (10.17.248.51) 0.873 ms 0.934 ms 0.814 ms
 3 10.16.101.150 (10.16.101.150) 0.890 ms 0.913 ms 0.713 ms
 4 10.16.67.118 (10.16.67.118) 1.120 ms 1.054 ms 1.273 ms
```

## user

Adds a CLI user account. The user admin is the default user account. The CLI admin account and password are separate from the vShield Manager user interface admin account and password.

---

**IMPORTANT** Each vShield virtual machine has two built-in CLI user accounts for system use: nobody and vs\_comm. Do not delete or modify these accounts. If these accounts are deleted or modified, the virtual machine will not work.

---

To remove a CLI user account, use no before the command.

### Synopsis

[no] user USERNAME password (hash | plaintext) PASSWORD

| Option    | Description                                                                                                                       |
|-----------|-----------------------------------------------------------------------------------------------------------------------------------|
| USERNAME  | Login name of the user.                                                                                                           |
| hash      | Masks the password by using the MD5 hash. You can view and copy the provided MD5 hash by running the show running-config command. |
| plaintext | Keeps the password unmasked.                                                                                                      |
| PASSWORD  | Password to use.                                                                                                                  |

### CLI Mode

Configuration

### Example

```
vShield(config)# user newuser1 password plaintext abcd1234
```

or

```
vShield(config) no user newuser1
```

## write

Writes the running configuration to memory. This command performs the same operation as the write memory command.

**Synopsis**

write

**CLI Mode**

Privileged

**Example**

manager# write

**Related Commands**

[write memory](#)

**write erase**

Resets the CLI configuration to factory default settings.

**Synopsis**

write erase

**CLI Mode**

Privileged

**Example**

manager# write erase

**write memory**

Writes the current configuration to memory. This command is identical to the write command.

**Synopsis**

write memory

**CLI Mode**

Privileged, Configuration, and Interface Configuration

**Example**

manager# write memory

**Related Commands**

[write](#)

**NSX Edge Commands**

This section describes NSX Edge CLI commands.

**clear nat counters**

Resets NAT counters to zeros.

**Synopsis**

clear nat counters

**CLI Mode**

Privileged, Configuration, and Interface Configuration

## clear arp WORD

Deletes an ARP entry from the ARP table, which is associated with the specified IP address.

### Synopsis

clear arp WORD

### CLI Mode

Privileged

## clear service dhcp lease

Removes DHCP lease information from the DHCP service.

### Synopsis

clear service dhcp lease

### CLI Mode

Privileged

## clear service ipsec sa

Deletes the SA (Security Association) associated with the specified peer name.

### Synopsis

clear service ipsec sa WORD

### CLI Mode

Privileged

## debug packet capture

Captures all packets processed by an NSX Edge, similar to a tcpdump. Enabling this command can slow NSX Edge performance. Packet debug capture is disabled by default. To disable packet capture, use no before the command.

### Synopsis

[no] debug packet capture (intif| extif) [EXPRESSION]

intif | extif            The specific NSX Edge interface from which to capture packets.

EXPRESSION            A tcpdump-formatted string. You must use an underscore between words in the expression.

### CLI Mode

Privileged

## debug packet display interface

Displays all packets captured by an NSX Edge interface, similar to a tcpdump. Enabling this command can impact NSX Edge performance. To disable the display of packets, use no before the command.

### Synopsis

[no] debug packet display interface (intif | extif) [EXPRESSION]



|               |                                                                                         |
|---------------|-----------------------------------------------------------------------------------------|
| intif   extif | The specific NSX Edge interface from which to display packets.                          |
| EXPRESSION    | A tcpdump-formatted string. You must use an underscore between words in the expression. |

**CLI Mode**

Privileged

**dnslookup serverName**

Makes DNS lookup query to the specified DNS server.

**Synopsis**

```
dnslookup ABC
```

**CLI Mode**

Basic

**dnslookup serverName / address**

Makes DNS lookup query for the specified host or IP address.

**Synopsis**

```
dnslookup server name_or_address
```

**CLI Mode**

Basic

**debug crashdump**

Activates crash dump support and triggers a reboot. After the reboot, NSX Edge runs with crashkernel support active. When a kernel panic occurs, NSX Edge boots the crash kernel and stores the kernel dump to the file system. Edge then reboots again back into the standard kernel, with crashdump still enabled.

To view the kernel dump file, use `debug show files`.

To copy the kernel dump file, use `debug copy [ftp/scp] ....`

To delete the kernel dump file, use `debug remove [<filename>|all]`.

When crashdump is enabled, the available NSX Edge memory is reduced by 64MB. To disable crashdump support, type `no debug crashdump`.

The debug crashdump command is not supported for the 64 bit X-Large NSX Edge.

**Synopsis**

```
debug crashdump
```

**CLI Mode**

Privileged

**debug packet display interface**

Displays all packets captured by an NSX Edge interface, similar to a tcpdump. Enabling this command can impact NSX Edge performance.

To disable the display of packets, use `no` before the command.

**Synopsis**

[no] debug packet display interface mgmt [EXPRESSION]

| Option     | Description                                                                             |
|------------|-----------------------------------------------------------------------------------------|
| mgmt       | The specific interface from which to capture packets.                                   |
| EXPRESSION | A tcpdump-formatted string. You must use an underscore between words in the expression. |

**NSX Edge**

[no] debug packet display interface (intif | extif) [EXPRESSION]

| Option        | Description                                                                             |
|---------------|-----------------------------------------------------------------------------------------|
| intif   extif | The specific NSX Edge interface from which to capture packets.                          |
| EXPRESSION    | A tcpdump-formatted string. You must use an underscore between words in the expression. |

**CLI Mode**

Privileged

**Example**

```
vShield# debug packet display interface mgmt host_10.10.11.11_and_port_80
```

**export tech-support scp**

Exports the system diagnostics to a specific location via Secure Copy Protocol (SCP). You can also export system diagnostics for an NSX virtual machine from the NSX Manager user interface.

**Synopsis**

export tech-support scp URL

| Option | Description                                 |
|--------|---------------------------------------------|
| URL    | Enter the complete path of the destination. |

**CLI Mode**

Basic and Privileged

**Example**

```
vShield# export tech-support scp user123@host123:file123
```

**ping**

Pings a destination by its hostname or IP address.

**Synopsis**

ping (HOSTNAME | A.B.C.D)

| Option             | Description                                      |
|--------------------|--------------------------------------------------|
| HOSTNAME   A.B.C.D | The hostname or IP address of the target system. |

**CLI Mode**

Basic, Privileged

**Usage Guidelines**

Enter CTRL+C to end ping replies.

**Example**

```
vShield# ping 192.168.1.1
```

**ping interface addr**

Pings an external destination from the internal address of a virtual machine protected by an NSX Edge.

**Synopsis**

```
ping interface addr (SOURCE_HOSTNAME | A.B.C.D) (DEST_HOSTNAME | A.B.C.D)
```

| Option                    | Description                                                                        |
|---------------------------|------------------------------------------------------------------------------------|
| SOURCE_HOSTNAME   A.B.C.D | The hostname or internal IP address of a virtual machine protected by an NSX Edge. |
| DEST_HOSTNAME   A.B.C.D   | The hostname or IP address of the destination.                                     |

**CLI Mode**

Basic, Privileged

**Usage Guidelines**

This command is useful for debugging IPSec-related issues.

Enter CTRL+C to end ping replies.

**Example**

```
vshieldEdge# ping interface addr 192.168.1.1 69.147.76.15
```

**show arp**

Shows the Address Resolution Protocol (ARP) settings for the NSX Edge.

**Synopsis**

```
show arp
```

**CLI Mode**

Basic

**Example**

```
vShield Edge ARP Cache:
IP Address      Interface  MAC Address  State
10.115.172.1    vNic_0    00:00:0c:07:ac:01  DELAY
10.115.172.161  vNic_0    00:0c:29:ee:40:b9  STALE
```

**show clock**

Shows the current time and date of the virtual machine. If you use an NTP server for time synchronization, the time is based on Coordinated Universal Time (UTC).

**Synopsis**

```
show clock
```

**CLI Mode**

Basic, Privileged

**Example**

```
vShield# show clock
```

Wed Feb 9 13:04:50 UTC 2005

**Related Commands**[set clock](#)**show configuration**

Shows either the current global configuration or the configuration for a specified service on an NSX Edge.

**Synopsis**

```
show configuration (dhcp | firewall | ipsec | loadbalancer | nat | syslog | loadbalancer)
```

| Option       | Description                                   |
|--------------|-----------------------------------------------|
| dhcp         | Show the current DHCP configuration.          |
| firewall     | Show the current firewall configuration.      |
| ipsec        | Show the current VPN configuration.           |
| l2vpn        | Show the current L2 VPN configuration         |
| loadbalancer | Show the current Load Balancer configuration. |
| nat          | Show the current NAT configuration.           |
| syslog       | Show the current syslog configuration.        |

Usage for each option is shown in the command descriptions below.

**CLI Mode**

Basic

**Example**

```
vShieldEdge# show configuration dhcp
```

**show configuration dhcp**

Shows NSX Edge IP address pooling and one-to-one static IP address allocation.

**Synopsis**

```
show configuration dhcp
```

**CLI Mode**

Basic

**Example**

```
vShield-edge-2-0> show configuration dhcp
```

```
-----
vShield Edge DHCP Config:
```

```
{
  "dhcp": {
    "relay": null,
    "logging": {
      "enable": false,
      "logLevel": "info"
    },
  },
  "enable": true,
  "bindings": {
    "vNic_1": {
      "staticBindings": [],
      "ipPools": [
        {
```

```

        "subnetMask" : "255.255.255.0",
        "maxLeaseTime" : "86400",
        "endIp" : "11.1.1.100",
        "primaryNameServer" : null,
        "defaultGateway" : "11.1.1.1",
        "defaultLeaseTime" : "86400",
        "domainName" : null,
        "secondaryNameServer" : null,
        "startIp" : "11.1.1.2"
    }
}
}
}
}
}

```

## show configuration dns

Shows external DNS servers.

### Synopsis

```
show configuration dns
```

### CLI Mode

Basic

### Example

```
vShield-edge-2-0> show configuration dns
```

---

vShield Edge DNS Config:

```

{
  "dns" : {
    "views" : [
      {
        "recursion" : true,
        "enableForwarding" : true,
        "name" : "vsm-default-view",
        "zones" : null,
        "forwarders" : [
          "10.112.0.1",
          "10.112.0.2"
        ],
        "matchInterfaces" : [
          "any"
        ],
        "matchClients" : [
          "any"
        ]
      }
    ],
    "logging" : {
      "enable" : false,
      "logLevel" : "info"
    },
    "enable" : true,
    "listenOn" : [
      "10.115.172.18",
      "11.1.1.1"
    ],
    "cacheSize" : 16,
    "zones" : null,
    "forwarders" : [
      "10.112.0.1",
      "10.112.0.2"
    ]
  }
}

```

```

    ]
  }
}

```

## show configuration firewall

Shows NSX Edge firewall configuration.

### Synopsis

show configuration firewall

### CLI Mode

Basic

### Example

vShield-edge-2-0> show configuration firewall

---

```

vShield Edge Firewall Config:
{
  "firewall" : {
    "globalConfig" : {
      "ipGenericTimeout" : 120,
      "icmp6Timeout" : 10,
      "tcpPickOngoingConnections" : false,
      "tcpAllowOutOfWindowPackets" : false,
      "tcpTimeoutEstablished" : 3600,
      "disableFirewall" : false,
      "dropInvalidTraffic" : true,
      "tcpTimeoutClose" : 30,
      "icmpTimeout" : 10,
      "udpTimeout" : 60,
      "tcpTimeoutOpen" : 30,
      "tcpSendResetForClosedVsePorts" : true,
      "logInvalidTraffic" : false
    },
    "rules" : [
      {
        "source" : [
          "vse"
        ],
        "dstIface" : [],
        "destination" : [
          "any"
        ],
        "matchTranslated" : false,
        "sourcePort" : [],
        "description" : "firewall",
        "service" : [
          "any:any:any"
        ],
        "srcIface" : [],
        "logging" : {
          "enable" : false,
          "logLevel" : null
        },
        "action" : "accept",
        "id" : 131074
      },
      {
        "source" : [
          "vnic-index-1"
        ],
        "dstIface" : [],
        "destination" : [

```

```

        "vse"
    ],
    "matchTranslated" : false,
    "sourcePort" : [],
    "description" : "dhcp",
    "service" : [
        "17:67:any"
    ],
    "srcIface" : [],
    "logging" : {
        "enable" : false,
        "logLevel" : null
    },
    "action" : "accept",
    "id" : 131075
},
{
    "source" : [
        "any"
    ],
    "dstIface" : [],
    "destination" : [
        "10.115.172.18"
    ],
    "matchTranslated" : false,
    "sourcePort" : [],
    "description" : "sslvpn",
    "service" : [
        "6:443:any"
    ],
    "srcIface" : [],
    "logging" : {
        "enable" : false,
        "logLevel" : null
    },
    "action" : "accept",
    "id" : 131076
},
{
    "source" : [
        "any"
    ],
    "dstIface" : [],
    "destination" : [
        "any"
    ],
    "matchTranslated" : false,
    "sourcePort" : [],
    "description" : "default rule for ingress traffic",
    "service" : [
        "any:any:any"
    ],
    "srcIface" : [],
    "logging" : {
        "enable" : false,
        "logLevel" : null
    },
    "action" : "accept",
    "id" : 131073
}
]
}
}

```

## show configuration global

Shows configuration for all NSX Edge services.

**Synopsis**

```
show configuration global
```

**CLI Mode**

Basic

**Example**

```
vShield-edge-2-0> show configuration global
```

```
-----
vShield Edge Global Config:
```

```
{
  "global" : {
    "edgeAssistId" : 0,
    "enableTcpLoose" : false,
    "hostname" : "vShield-edge-2-0",
    "hypervisorAssist" : false,
    "size" : "compact",
    "fips" : {
      "enable" : false
    },
    "enableAesni" : true,
    "tenantId" : "default",
    "haIndex" : "0",
    "distributedRouter" : false
  }
}
```

**show configuration highavailability**

Shows high availability configuration for the NSX Edge.

**Synopsis**

```
show configuration highavailability
```

**CLI Mode**

Basic

**Example**

```
vShield-edge-2-0> show configuration highavailability
```

```
-----
vShield Edge High Availability Config:
```

```
{
  "highAvailability" : {
    "enable" : false,
    "heartbeatInterval" : 0,
    "logging" : null,
    "interface" : null,
    "heartbeatDeadTime" : 0,
    "security" : {
      "psk" : "****",
      "enable" : false,
      "encryptionAlgorithm" : null,
      "authenticationSignature" : {
        "type" : "sha1",
        "key" : "962215d5d6a49a1ae738f5c99087cb2efd87fd65"
      }
    },
    "nodes" : [],
    "heartbeatWarnTime" : 0,
    "heartbeatInitDead" : 0
  }
}
```



## show configuration interface

Shows interfaces configured for the NSX Edge.

### Synopsis

show configuration interface

### CLI Mode

Basic

### Example

vShield-edge-2-0> show configuration interface

```
-----
vShield Edge Interface Config:
{
  "interfaceConfig" : {
    "vNic_0" : {
      "status" : "up",
      "name" : "uplink",
      "sendRedirects" : false,
      "index" : 0,
      "enableProxyArp" : false,
      "lifName" : null,
      "mac" : "00:50:56:a2:57:f9",
      "subnets" : [
        {
          "primary" : "10.115.172.18",
          "address" : [
            "10.115.172.18"
          ],
          "subnet" : "10.115.172.0/24"
        }
      ],
      "mtu" : 1500
    },
    "vNic_9" : {
      "status" : "down",
      "name" : "vnic9",
      "sendRedirects" : true,
      "index" : 9,
      "enableProxyArp" : false,
      "lifName" : null,
      "mac" : "00:50:56:a2:73:98",
      "subnets" : [],
      "mtu" : 1500
    },
    "vNic_4" : {
      "status" : "down",
      "name" : "vnic4",
      "sendRedirects" : true,
      "index" : 4,
      "enableProxyArp" : false,
      "lifName" : null,
      "mac" : "00:50:56:a2:76:06",
      "subnets" : [],
      "mtu" : 1500
    },
    "vNic_7" : {
      "status" : "down",
      "name" : "vnic7",
      "sendRedirects" : true,
      "index" : 7,
      "enableProxyArp" : false,
      "lifName" : null,
      "mac" : "00:50:56:a2:58:c5",
      "subnets" : [],
    }
  }
}
```

```

    "mtu" : 1500
  },
  "vNic_3" : {
    "status" : "down",
    "name" : "vnic3",
    "sendRedirects" : true,
    "index" : 3,
    "enableProxyArp" : false,
    "lifName" : null,
    "mac" : "00:50:56:a2:f8:e0",
    "subnets" : [],
    "mtu" : 1500
  },
  "vNic_5" : {
    "status" : "down",
    "name" : "vnic5",
    "sendRedirects" : true,
    "index" : 5,
    "enableProxyArp" : false,
    "lifName" : null,
    "mac" : "00:50:56:a2:ce:f7",
    "subnets" : [],
    "mtu" : 1500
  },
  "vNic_8" : {
    "status" : "down",
    "name" : "vnic8",
    "sendRedirects" : true,
    "index" : 8,
    "enableProxyArp" : false,
    "lifName" : null,
    "mac" : "00:50:56:a2:6e:07",
    "subnets" : [],
    "mtu" : 1500
  },
  "vNic_2" : {
    "status" : "down",
    "name" : "vnic2",
    "sendRedirects" : true,
    "index" : 2,
    "enableProxyArp" : false,
    "lifName" : null,
    "mac" : "00:50:56:a2:2b:ec",
    "subnets" : [],
    "mtu" : 1500
  },
  "vNic_6" : {
    "status" : "down",
    "name" : "vnic6",
    "sendRedirects" : true,
    "index" : 6,
    "enableProxyArp" : false,
    "lifName" : null,
    "mac" : "00:50:56:a2:38:33",
    "subnets" : [],
    "mtu" : 1500
  },
  "vNic_1" : {
    "status" : "up",
    "name" : "int",
    "sendRedirects" : false,
    "index" : 1,
    "enableProxyArp" : false,
    "lifName" : null,
    "mac" : "00:50:56:a2:75:f0",
    "subnets" : [
      {
        "primary" : "11.1.1.1",

```

```

        "address" : [
            "11.1.1.1"
        ],
        "subnet" : "11.1.1.0/24"
    }
],
"mtu" : 1500
}
}
}

```

## show configuration ipsec

Shows certificate configuration for IPsec VPN.

### Synopsis

```
show configuration ipsec
```

### CLI Mode

Basic

### Example

```
vShield-edge-2-0> show configuration ipsec
```

---

vShield Edge IPsec VPN Config:

```

{
  "ipsec" : {
    "sites" : [
      {
        "certificate" : null,
        "encryptionAlgorithm" : "aes",
        "enabled" : true,
        "mtu" : null,
        "psk" : "*****",
        "extension" : null,
        "peerSubnets" : [
          "192.168.2.0/24"
        ],
        "peerIp" : "10.115.172.19",
        "name" : "IPsec",
        "description" : null,
        "localSubnets" : [
          "11.1.1.0/24"
        ],
        "dhGroup" : "dh2",
        "peerId" : "10.115.172.19",
        "enablePfs" : true,
        "localIp" : "10.115.172.18",
        "authenticationMode" : "psk",
        "localId" : "10.115.172.18"
      }
    ],
    "enable" : true,
    "logging" : {
      "enable" : false,
      "logLevel" : "info"
    },
    "global" : {
      "extension" : null,
      "crlCertificates" : [],
      "serviceCertificate" : null,
      "pskForDynamicIp" : null,
      "id" : null,
      "caCertificates" : []
    }
  }
}

```

```
}
}
```

## show configuration ipset

Shows IP address groups defined at the NSX Edge scope.

### Synopsis

```
show configuration ipset
```

### CLI Mode

Basic

### Example

```
vShield-edge-2-0> show configuration ipset
```

```
-----
vShield Edge IpSet Config:
```

```
{
  "ipSet" : []
}
```

## show configuration l2vpn

Shows L2 VPN configuration.

### Synopsis

```
show configuration l2vpn
```

### CLI Mode

Basic

### Example

```
vShield-edge-2-0> show configuration l2vpn
```

```
-----
{
  "l2vpn" : {
    "ciphers" : [
      "AES256-SHA"
    ],
    "listenerPort" : 443,
    "clientVnicIndex" : null,
    "filters" : [],
    "serverPort" : null,
    "caCertificate" : null,
    "encryptionAlgorithm" : null,
    "listenerIp" : "10.110.18.190",
    "peerSites" : [
      {
        "vseVnicNames" : [
          "vNic_10",
          "vNic_11",
          "vNic_12",
          "vNic_13",
          "vNic_14",
          "vNic_15",
          "vNic_16",
          "vNic_17",
          "vNic_18",
          "vNic_19"
        ],
        "name" : "site1",
        "filters" : [],

```

```

    "l2vpnUser" : {
      "password" : "****",
      "userId" : "user1"
    }
  },
  {
    "vseVnicNames" : [
      "vNic_20",
      "vNic_21",
      "vNic_22",
      "vNic_23",
      "vNic_24",
      "vNic_25",
      "vNic_26",
      "vNic_27",
      "vNic_28",
      "vNic_29"
    ],
    "name" : "site2",
    "filters" : [],
    "l2vpnUser" : {
      "password" : "****",
      "userId" : "user2"
    }
  } ],
  "clientProxySetting" : null,
  "enable" : true,
  "trunkedVnicIndexes" : [
    1
  ],
  "serverVnicIndex" : null,
  "l2vpnUsers" : [],
  "serverAddress" : null,
  "logging" : {
    "enable" : true,
    "logLevel" : "info"
  },
  "vseVnicNames" : null,
  "serverCertificate" : null
}
}

```

## show configuration loadbalancer

Shows external, or public, IP address mapped to internal servers for load balancing. Note that there are a number of specialized show configuration loadbalancer sub-commands explained after this one.

### Synopsis

```
show configuration loadbalancer
```

### CLI Mode

Basic

### Example

```
vShield-edge-2-0> show configuration loadbalancer
```

```
-----
vShield Edge Loadbalancer Config:
```

```

{
  "monitorService" : {
    "logging" : {
      "enable" : false,
      "logLevel" : "info"
    },
    "enable" : true,
    "healthMonitors" : [

```

```

    {
      "extension" : null,
      "send" : null,
      "expected" : null,
      "maxRetries" : 3,
      "name" : "default_tcp_monitor",
      "interval" : 5,
      "receive" : null,
      "timeout" : 15,
      "url" : null,
      "type" : "tcp",
      "method" : null
    },
    {
      "extension" : null,
      "send" : null,
      "expected" : null,
      "maxRetries" : 3,
      "name" : "default_http_monitor",
      "interval" : 5,
      "receive" : null,
      "timeout" : 15,
      "url" : "/",
      "type" : "http",
      "method" : "GET"
    },
    {
      "extension" : null,
      "send" : null,
      "expected" : null,
      "maxRetries" : 3,
      "name" : "default_https_monitor",
      "interval" : 5,
      "receive" : null,
      "timeout" : 15,
      "url" : "/",
      "type" : "https",
      "method" : "GET"
    }
  ],
  "loadBalancer" : {
    "logging" : {
      "enable" : false,
      "logLevel" : "info"
    },
    "enable" : true,
    "vips" : [
      {
        "maxConn" : 0,
        "rateLimit" : 0,
        "applicationRules" : null,
        "mode" : "http",
        "name" : "VSIP",
        "accelerationEnabled" : false,
        "redirection" : null,
        "serverSsl" : null,
        "serverSslEnabled" : false,
        "insertXForwardedFor" : false,
        "sessionPersistence" : null,
        "ipAddresses" : [
          "[10.115.172.18]:80"
        ],
        "defaultPool" : null,
        "clientSsl" : null
      }
    ],
    "applicationRules" : null,

```

```

"objectSet" : null,
"accelerationEnabled" : false,
"pools" : [
{
  "members" : [
    {
      "maxConn" : 0,
      "minConn" : 0,
      "name" : "http-Server",
      "objectId" : null,
      "ipAddress" : "11.1.1.2",
      "port" : 80,
      "weight" : 1,
      "monitorPort" : 80,
      "healthMonitors" : [
        "default_http_monitor"
      ],
      "condition" : "enabled"
    }
  ],
  "algorithm" : "round-robin",
  "transparent" : {
    "enable" : false
  },
  "name" : "http-pool"
}
]
}
}

```

## show configuration loadbalancer monitor

Shows monitor details.

### Synopsis

show configuration loadbalancer monitor

### CLI Mode

Basic

### Example

```
vShield-edge-2-0> show configuration loadbalancer monitor
```

```
-----
vShield Edge Loadbalancer Config:
```

```

{
  "healthMonitors" : [
    {
      "extension" : null,
      "send" : null,
      "expected" : null,
      "maxRetries" : 3,
      "name" : "default_tcp_monitor",
      "interval" : 5,
      "receive" : null,
      "timeout" : 15,
      "url" : null,
      "type" : "tcp",
      "method" : null
    },
    {
      "extension" : null,
      "send" : null,
      "expected" : null,
      "maxRetries" : 3,
      "name" : "default_http_monitor",

```

```

        "interval" : 5,
        "receive" : null,
        "timeout" : 15,
        "url" : "/",
        "type" : "http",
        "method" : "GET"
    },
    {
        "extension" : null,
        "send" : null,
        "expected" : null,
        "maxRetries" : 3,
        "name" : "default_https_monitor",
        "interval" : 5,
        "receive" : null,
        "timeout" : 15,
        "url" : "/",
        "type" : "https",
        "method" : "GET"
    }
]
}

```

## show configuration loadbalancer pool *poolName*

Shows pool details.

### Synopsis

show configuration loadbalancer pool poolname

### CLI Mode

Basic

### Example

```
vShield-edge-2-0> show configuration loadbalancer pool
```

```
-----
vShield Edge Loadbalancer Config:
```

```

{
  "pools" : [
    {
      "members" : [
        {
          "maxConn" : 0,
          "minConn" : 0,
          "name" : "http-Server",
          "objectId" : null,
          "ipAddress" : "11.1.1.2",
          "port" : 80,
          "weight" : 1,
          "monitorPort" : 80,
          "healthMonitors" : [
            "default_http_monitor"
          ],
          "condition" : "enabled"
        }
      ],
      "algorithm" : "round-robin",
      "transparent" : {
        "enable" : false
      },
      "name" : "http-pool"
    }
  ]
}

```



**show configuration loadbalancer rule *ruleName***

Shows rule details.

**Synopsis**

show configuration loadbalancer rule *ruleName*

**CLI Mode**

Basic

**show configuration loadbalancer virtual *virtualServerName***

Shows virtual server details.

**Synopsis**

show configuration loadbalancer virtual *virtualServerName*

**CLI Mode**

Basic

**Example**

```
vShield-edge-2-0> show configuration loadbalancer virtual
```

```
-----
vShield Edge Loadbalancer Config:
```

```
{
  "vips" : [
    {
      "maxConn" : 0,
      "rateLimit" : 0,
      "applicationRules" : null,
      "mode" : "http",
      "name" : "VSIP",
      "accelerationEnabled" : false,
      "redirection" : null,
      "serverSsl" : null,
      "serverSslEnabled" : false,
      "insertXForwardedFor" : false,
      "sessionPersistence" : null,
      "ipAddresses" : [
        "[10.115.172.18]:80"
      ],
      "defaultPool" : null,
      "clientSsl" : null
    }
  ]
}
```

**show configuration nat**

Shows NAT rules defined for the NSX Edge.

**Synopsis**

show configuration nat

**CLI Mode**

Basic

**Example**

```
vShield-edge-2-0> show configuration nat
```

```
-----
vShield Edge NAT Config:
```

```

{
  "dnat" : [
    {
      "protocol" : "17",
      "internalIp" : "10.115.172.18",
      "externalPort" : "500",
      "comments" : "ipsec",
      "ruleId" : 200706,
      "icmpType" : null,
      "internalPort" : "500",
      "logging" : {
        "enable" : false,
        "logLevel" : null
      },
      "interface" : "vNic_0",
      "externalIp" : "10.115.172.18"
    },
    {
      "protocol" : "17",
      "internalIp" : "10.115.172.18",
      "externalPort" : "4500",
      "comments" : "ipsec",
      "ruleId" : 200707,
      "icmpType" : null,
      "internalPort" : "4500",
      "logging" : {
        "enable" : false,
        "logLevel" : null
      },
      "interface" : "vNic_0",
      "externalIp" : "10.115.172.18"
    },
    {
      "protocol" : "50",
      "internalIp" : "10.115.172.18",
      "externalPort" : "any",
      "comments" : "ipsec",
      "ruleId" : 200708,
      "icmpType" : null,
      "internalPort" : "any",
      "logging" : {
        "enable" : false,
        "logLevel" : null
      },
      "interface" : "vNic_0",
      "externalIp" : "10.115.172.18"
    },
    {
      "protocol" : "51",
      "internalIp" : "10.115.172.18",
      "externalPort" : "any",
      "comments" : "ipsec",
      "ruleId" : 200709,
      "icmpType" : null,
      "internalPort" : "any",
      "logging" : {
        "enable" : false,
        "logLevel" : null
      },
      "interface" : "vNic_0",
      "externalIp" : "10.115.172.18"
    },
    {
      "protocol" : "6",
      "internalIp" : "10.115.172.18",
      "externalPort" : "443",
      "comments" : "sslvpn",
      "ruleId" : 196609,

```

```

    "icmpType" : null,
    "internalPort" : "443",
    "logging" : {
      "enable" : false,
      "logLevel" : null
    },
    "interface" : "vNic_0",
    "externalIp" : "10.115.172.18"
  },
  {
    "protocol" : "6",
    "internalIp" : "10.115.172.18",
    "externalPort" : "80",
    "comments" : "loadBalancer",
    "ruleId" : 200710,
    "icmpType" : null,
    "internalPort" : "80",
    "logging" : {
      "enable" : false,
      "logLevel" : null
    },
    "interface" : "vNic_0",
    "externalIp" : "10.115.172.18"
  }
],
"snat" : []
}

```

## show configuration ospf

Shows OSPF configuration.

### Synopsis

show configuration ospf

### CLI Mode

Basic

### Example

vShield-edge-1-0> sh configuration ospf  
vShield Edge OSPF Routing Protocol Config:

```

{
  "ospf" : {
    "defaultOriginate" : false,
    "forwardingAddress" : null,
    "gracefulRestart" : true,
    "interfaces" : [
      {
        "cost" : 1,
        "priority" : 128,
        "areaId" : 51,
        "mtuIgnore" : false,
        "vnic" : "vNic_1",
        "deadInterval" : 40,
        "helloInterval" : 10
      },
      {
        "cost" : 1,
        "priority" : 128,
        "areaId" : 0,
        "mtuIgnore" : false,
        "vnic" : "vNic_2",
        "deadInterval" : 40,
        "helloInterval" : 10
      }
    ]
  }
}

```

```

    ],
    "redistribute" : {
      "rules" : [
        {
          "fromOSPF" : false,
          "fromBGP" : false,
          "fromISIS" : false,
          "fromStatic" : true,
          "fromConnected" : false,
          "action" : "permit",
          "id" : 0,
          "prefix" : null
        }
      ],
      "enabled" : true
    },
    "protocolAddress" : null,
    "areas" : [
      {
        "areaId" : 51,
        "authenticationType" : "none",
        "authenticationSecret" : null,
        "type" : "nssa"
      },
      {
        "areaId" : 0,
        "authenticationType" : "none",
        "authenticationSecret" : null,
        "type" : "normal"
      },
      {
        "areaId" : 1,
        "authenticationType" : "none",
        "authenticationSecret" : null,
        "type" : "normal"
      }
    ],
    "enabled" : true
  }
}

```

## show configuration static\_routing

Shows the static routes defined for the NSX Edge data packets.

### Synopsis

```
show configuration static_routing
```

### CLI Mode

Basic

## show configuration syslog

Shows remote syslog servers defined for the NSX Edge.

### Synopsis

```
show configuration syslog
```

### CLI Mode

Basic

### Example

```
vShield-edge-2-0> show configuration syslog
```

---

vShield Edge Syslog Config:

```
{
  "syslog" : {
    "protocol" : "tcp",
    "destinationHost" : [
      "11.1.1.100",
      "11.1.1.2"
    ]
  }
}
```

## show configuration sslvpn-plus

Shows the SSL VPN configuration.

### Synopsis

show configuration sslvpn-plus

### CLI Mode

Basic

## show fips

Indicates whether fips (Federal Information Processing Standard) is enabled for the specified NSX Edge.

### Synopsis

show fips

### CLI Mode

Basic

## show firewall

Displays firewall packet counters along with firewall rules that specify what to do with a packet that matches.

### Synopsis

show firewall

### CLI Mode

Basic

## show firewall flows

Displays the firewall packet counters along with packet flows.

### Synopsis

show firewall flows

### CLI Mode

Basic

## show firewall flows top *number*

Displays firewall packet counters along with top N number of packet flows.

**Synopsis**

show firewall flows top 10

**CLI Mode**

Basic

**show firewall flows top *number* sort-by pkts**

Displays firewall packet counters along with top N number of packet flows sorted by packet numbers.

**Synopsis**

show firewall flows top 10 sort-by-pkts

**CLI Mode**

Basic

**show firewall flows top *number* sort-by bytes**

Displays firewall packet counters along with top N number of packet flows sorted by byte numbers.

**Synopsis**

show firewall flows top 10 sort-by-bytes

**CLI Mode**

Basic

**show firewall rule-id *ID***

Displays firewall packet counters filtered by rule-id.

**Synopsis**

show firewall rule-id 25

**CLI Mode**

Basic

**show firewall rule-id *ID* flows**

Displays firewall packet counters filtered by rule-id.

**Synopsis**

show firewall rule-id 25 flows

**CLI Mode**

Basic

**show firewall rule-id *ID* flows top *number***

Displays firewall packet counters filtered by rule-id along with top N number of packet flows.

**Synopsis**

show firewall rule-id 25 flows top 10

**CLI Mode**

Basic

**show firewall rule-id *ID* flows top *number* sort-by pkts**

Displays firewall packet counters filtered by rule-id along with top N number of packet flows sorted by packet numbers.

**Synopsis**

show firewall rule-id 25 flows top 10 sort-by-pkts

**CLI Mode**

Basic

**show firewall rule-id *ID* flows top *number* sort-by-bytes**

Displays firewall packet counters filtered by rule-id along with top N number of packet flows sorted by byte numbers.

**Synopsis**

show firewall rule-id 25 flows top 10 sort-by-bytes

**CLI Mode**

Basic

**show flowtable**

Displays packet flows in a table.

**Synopsis**

show flowtable

**CLI Mode**

Basic

**show flowtable rule-id *ID***

Displays packet flows matched by rule-id.

**Synopsis**

show flowtable rule-id 25

**CLI Mode**

Basic

**show flowtable rule-id *ID* top *number***

Displays the top N number of packet flows matched by rule-id.

**Synopsis**

show flowtable rule-id 25 top 30

**CLI Mode**

Basic

**show flowtable rule-id *ID* top *number* sort-by pkts**

Displays the top N number of packet flows matched by rule-id sorted by packet numbers.

**Synopsis**

show flowtable rule-id 25 top 30 sort-by pkts

**CLI Mode**

Basic

**show flowtable rule-id *ID* top *number* sort-by bytes**

Displays top N number of packet flows matched by rule-id sorted by byte numbers.

**Synopsis**

show flowtable rule-id 25 top 30 sort-by bytes

**CLI Mode**

Basic

**show flowtable top *number***

Displays top N number of packet flows.

**Synopsis**

show flowtable top 10

**CLI Mode**

Basic

**show flowtable top *number* sort-by pkts**

Displays top N number of packet flows sorted by packet numbers.

**Synopsis**

show flowtable top 10 sort-by pkts

**CLI Mode**

Basic

**show flowtable top *number* sort-by bytes**

Displays top N number of packet flows sorted by byte numbers.

**Synopsis**

show flowtable top 10 sort-by bytes

**CLI Mode**

Basic

**show hostname**

Shows the current hostname for an NSX Edge.

**Synopsis**

show hostname

**CLI Mode**

Basic, Privileged



**Example**

```
vshieldEdge# show hostname
```

**show interface**

Displays interface information like IP addresses.

**Synopsis**

```
show interface
```

**CLI Mode**

Basic

**show interface *name***

Displays interface information for the specified interface.

**Synopsis**

```
show interface TEST
```

**CLI Mode**

Basic

**show ip bgp**

Shows entries in the Border Gateway Protocol (BGP) routing table.

**Synopsis**

```
show ip bgp
```

**CLI Mode**

Basic, Privileged

**Example**

Status codes: s - suppressed, d - damped, > - best, i - internal

Origin codes: i - IGP, e - EGP, ? - incomplete

| Network         | Next Hop   | Metric | LocPrf | Weight | Origin |
|-----------------|------------|--------|--------|--------|--------|
| > 50.50.50.0/24 | 0.0.0.0    | 0      | 100    | 32768  | i      |
| > 60.60.60.0/24 | 50.50.50.3 | 0      | 100    | 32768  | i      |
| 80.80.80.0/24   | 20.20.20.1 | 0      | 100    | 60     | ?      |
| > 80.80.80.0/24 | 70.70.70.1 | 0      | 100    | 60     | ?      |
| > 90.90.90.0/24 | 50.50.50.3 | 0      | 100    | 32768  | i      |

**show ip bgp neighbors**

Shows BGP neighbors.

**Synopsis**

```
show ip bgp neighbors
```

**CLI Mode**

Basic, Privileged

**Example**

BGP neighbor is 20.20.20.1, remote AS 200,

BGP state = Established, up

Hold time is 180, Keep alive interval is 60 seconds

```

Neighbor capabilities:
  Route refresh: advertised and received
  Address family IPv4 Unicast:advertised and received
  Graceful restart Capability:advertised and received
  Restart remain time: 0
Received 3034 messages, Sent 3033 messages
Default minimum time between advertisement runs is 30 seconds
For Address family IPv4 Unicast:advertised and received
  Index 1 Identifier 0x9ac9f52c
  Route refresh request:received 0 sent 0
  Prefixes received 1 sent 3 advertised 3
Connections established 2, dropped 57
Local host: 20.20.20.113, Local port: 43886
Remote host: 20.20.20.1, Remote port: 179
BGP neighbor is 70.70.70.1, remote AS 200,
BGP state = Established, up
Hold time is 180, Keep alive interval is 60 seconds
Neighbor capabilities:
  Route refresh: advertised and received
  Address family IPv4 Unicast:advertised and received
  Graceful restart Capability:advertised and received
  Restart remain time: 0
Received 3085 messages, Sent 3075 messages
Default minimum time between advertisement runs is 30 seconds
For Address family IPv4 Unicast:advertised and received
  Index 2 Identifier 0x9ac9f52c
  Route refresh request:received 0 sent 0
  Prefixes received 1 sent 3 advertised 3
Connections established 1, dropped 9
Local host: 70.70.70.113, Local port: 179
Remote host: 70.70.70.1, Remote port: 26563

```

## show ip forwarding

Shows forwarding table entries.

### Synopsis

```
show ip forwarding
```

### CLI Mode

Basic, Privileged

### Example

Codes: C - connected, R - remote,  
> - selected route, \* - FIB route

```

R>* 0.0.0.0/0 via 10.24.31.253, vNic_3
C>* 10.24.28.0/22 is directly connected, vNic_3
C>* 20.20.20.0/24 is directly connected, vNic_2
C>* 50.50.50.0/24 is directly connected, vNic_0
R>* 60.60.60.0/24 via 50.50.50.3, vNic_0
C>* 70.70.70.0/24 is directly connected, vNic_1
R>* 80.80.80.0/24 via 70.70.70.1, vNic_2
R>* 90.90.90.0/24 via 50.50.50.3, vNic_0

```

## show ip ospf

Shows information about Open Shortest Path First (OSPF) routing process.

### Synopsis

```
show ip ospf
```

**CLI Mode**

Basic, Privileged

**Example**

```

OSPF routing process with Router ID 50.50.50.113
Supports opaque LSA
SPF schedule delay: 5 secs, Hold time between two SPF's: 10 secs
Minimum LSA interval: 5 secs, Minimum LSA arrival: 1 secs
Number of external LSA: 4, Checksum Sum: 0X119C0
Number of opaque AS LSA: 0, Checksum Sum: 0
Area BACKBONE(0)
  SPF algorithm executed 292 times
  Number of area border routers reachable within area: 0
  Number of LSA: 9, Checksum Sum: 0X32360
  Number of router LSA: 3, Checksum Sum: 0XE766
  Number of network LSA: 1, Checksum Sum: 0X5808
  Number of summary network LSA: 0, Checksum Sum: 0
  Number of summary ASB LSA: 0, Checksum Sum: 0
  Number of external NSSA LSA: 0, Checksum Sum: 0
  Number of opaque LSA: 5, Checksum Sum: 0X1E3F2
Area 0.0.0.51
  It is a NSSA area
  SPF algorithm executed 292 times
  Number of area border routers reachable within area: 0
  Number of LSA: 3, Checksum Sum: 0X203EE
  Number of router LSA: 0, Checksum Sum: 0
  Number of network LSA: 0, Checksum Sum: 0
  Number of summary network LSA: 0, Checksum Sum: 0
  Number of summary ASB LSA: 0, Checksum Sum: 0
  Number of external NSSA LSA: 1, Checksum Sum: 0X8BF5
  Number of opaque LSA: 2, Checksum Sum: 0X177F9

```

**show ip ospf database**

Shows IPv4 OSPF database.

**Synopsis**

show ip ospf database

**CLI Mode**

Basic, Privileged

**Example**

```

adv-router    Filtered by advertising router.
asbr-summary  Show asbr-summary (type 4) LSAs.
external      Show external (type 5) LSAs.
network       Show network (type 2) LSAs.
nssa-external Show nssa-external (type 7) LSAs.
opaque-area   Show opaque-area (type 10) LSAs.
router        Show router (type 1) LSAs.
summary       Show summary (type 3) LSAs.

```

**show ip ospf database adv-router**

Filters OSPF results by advertising router.

**Synopsis**

show ip ospf database adv-router

**CLI Mode**

Basic, Privileged

**Example**

```

Router Link States (Area 0.0.0.0)
Link ID      ADV Router  Age      Seq Num      Checksum
50.50.50.113 50.50.50.113 866      0x80000068   0x00009039
Network Link States (Area 0.0.0.0)
Link ID      ADV Router  Age      Seq Num      Checksum
50.50.50.113 50.50.50.113 866      0x80000067   0x00005808
Opaque Area Link States (Area 0.0.0.0)
Link ID      ADV Router  Age      Seq Num      Checksum
1.0.0.1      50.50.50.113 737      0x8000005a   0x000003a6
1.0.0.2      50.50.50.113 692      0x8000005a   0x000029ab
Type-7 AS External Link States (Area 0.0.0.51)
Link ID      ADV Router  Age      Seq Num      Checksum
80.80.80.0   50.50.50.113 1317     0x80000059   0x00008bf5
Opaque Area Link States (Area 0.0.0.51)
Link ID      ADV Router  Age      Seq Num      Checksum
1.0.0.1      50.50.50.113 737      0x8000005a   0x0000a8fa
1.0.0.2      50.50.50.113 692      0x8000005a   0x0000ceff
AS External Link States
Link ID      ADV Router  Age      Seq Num      Checksum
80.80.80.0   50.50.50.113 1317     0x80000059   0x000089f7

```

**show ip ospf database asbr-summary**

Shows asbr-summary (type 4) LSAs.

**Synopsis**

```
show ip ospf database asbr-summary
```

**CLI Mode**

Basic, Privileged

**show ip ospf database external**

Shows external (type 5) LSAs.

**Synopsis**

```
show ip ospf database external
```

**CLI Mode**

Basic, Privileged

**Example**

```

AS External Link States
Link ID      ADV Router  Age      Seq Num      Checksum
60.60.60.0   60.60.60.3 183      0x8000005b   0x00004130
80.80.80.0   50.50.50.41 475      0x80000059   0x00003b8e
80.80.80.0   50.50.50.113 1279     0x80000059   0x000089f7
90.90.90.0   60.60.60.3 1769     0x80000054   0x0000130b

```

**show ip ospf database network**

Shows network (type 2) LSAs.

**Synopsis**

```
show ip ospf database network
```

**CLI Mode**

Basic, Privileged

**Example**

```
Network Link States (Area 0.0.0.0)
Link ID      ADV Router    Age      Seq Num      Checksum
50.50.50.113 50.50.50.113    832      0x80000067   0x00005808
```

**show ip ospf database nssa-external**

Shows nssa-external (type 7) LSAs.

**Synopsis**

```
show ip ospf database nssa-external
```

**CLI Mode**

Basic, Privileged

**Example**

```
Type-7 AS External Link States (Area 0.0.0.51)
Link ID      ADV Router    Age      Seq Num      Checksum
80.80.80.0   50.50.50.113 1286     0x80000059   0x00008bf5
```

**show ip ospf database opaque-area**

Shows opaque-area (type 10) LSAs.

**Synopsis**

```
show ip ospf database opaque-area
```

**CLI Mode**

Basic, Privileged

**Example**

```
Type-7 AS External Link States (Area 0.0.0.51)
Link ID      ADV Router    Age      Seq Num      Checksum
80.80.80.0   50.50.50.113 1286     0x80000059   0x00008bf5
```

**show ip ospf database router**

Shows router (type 1) LSAs.

**Synopsis**

```
show ip ospf database router
```

**CLI Mode**

Basic, Privileged

**Example**

```
Router Link States (Area 0.0.0.0)
Link ID      ADV Router    Age      Seq Num      Checksum
50.50.50.41   50.50.50.41   841      0x8000006b   0x00001b84
50.50.50.113 50.50.50.113 841      0x80000068   0x00009039
60.60.60.3    60.60.60.3   146      0x8000005b   0x00003ba9
```

**show ip ospf database summary**

Shows summary (type 3) LSAs.

**Synopsis**

show ip ospf database summary

**CLI Mode**

Basic, Privileged

**Example**

```
Router Link States (Area 0.0.0.0)
Link ID      ADV Router   Age      Seq Num   Checksum
50.50.50.41  50.50.50.41   841     0x8000006b 0x00001b84
50.50.50.113 50.50.50.113  841     0x80000068 0x00009039
60.60.60.3   60.60.60.3   146     0x8000005b 0x00003ba9
```

**show ip ospf interface**

Shows IPv4 OSPF interface.

**Synopsis**

show ip ospf interface

**CLI Mode**

Basic, Privileged

**Example**

```
vNic_0 is activated
Internet Address 50.50.50.113, Network Mask 255.255.255.0, Area 0.0.0.0
Transmit Delay is 1 sec, Network Type BROADCAST, State DR, Priority 128
Designated Router's Interface Address 50.50.50.113
Backup Designated Router's Interface Address 50.50.50.4
Timer intervals configured, Hello 10, Dead 40, Retransmit 5
```

**show ip ospf ne**

Shows IP addresses of OSPF neighbors.

**Synopsis**

show ip ospf ne

**CLI Mode**

Basic, Privileged

**Example**

| Neighbor ID | Priority | Address     | Dead Time | State        |
|-------------|----------|-------------|-----------|--------------|
| 60.60.60.3  | 128      | 50.50.50.4  | 34        | Full/BDR     |
| 50.50.50.41 | 128      | 50.50.50.41 | 36        | Full/DROTHER |

**show ip ospf statistics**

Shows IPv4 OSPF statistics.

**Synopsis**

show ip ospf statistics

**CLI Mode**

Basic, Privileged

**Example**

```

Area 0.0.0.0: SPF algorithm executed 292 times
Area 0.0.0.51: SPF algorithm executed 292 times
vShield-edge-6-0> sh ip ospf database
      Router Link States (Area 0.0.0.0)
Link ID      ADV Router   Age      Seq Num      Checksum
50.50.50.41  50.50.50.41   822      0x8000006b   0x00001b84
50.50.50.113 50.50.50.113  822      0x80000068   0x00009039
60.60.60.3   60.60.60.3   127      0x8000005b   0x00003ba9
Network Link States (Area 0.0.0.0)
Link ID      ADV Router   Age      Seq Num      Checksum
50.50.50.113 50.50.50.113  822      0x80000067   0x00005808
Opaque Area Link States (Area 0.0.0.0)
Link ID      ADV Router   Age      Seq Num      Checksum
1.0.0.1      50.50.50.41  154      0x8000005a   0x0000ff76
1.0.0.1      50.50.50.113 693      0x8000005a   0x000003a6
1.0.0.1      60.60.60.3   237      0x8000005a   0x0000671f
1.0.0.2      50.50.50.41  827      0x80000063   0x0000500c
1.0.0.2      50.50.50.113 648      0x8000005a   0x000029ab
Type-7 AS External Link States (Area 0.0.0.51)
Link ID      ADV Router   Age      Seq Num      Checksum
80.80.80.0   50.50.50.113 1273     0x80000059   0x00008bf5
Opaque Area Link States (Area 0.0.0.51)
Link ID      ADV Router   Age      Seq Num      Checksum
1.0.0.1      50.50.50.113 693      0x8000005a   0x0000a8fa
1.0.0.2      50.50.50.113 648      0x8000005a   0x0000ceff
AS External Link States
Link ID      ADV Router   Age      Seq Num      Checksum
60.60.60.0   60.60.60.3   177      0x8000005b   0x00004130
80.80.80.0   50.50.50.41  469      0x80000059   0x00003b8e
80.80.80.0   50.50.50.113 1273     0x80000059   0x000089f7
90.90.90.0   60.60.60.3   1763     0x80000054   0x0000130b

```

**show ip route**

Shows all routes in the routing information base (RiB).

**Synopsis**

show ip route [A.B.C.D/M]

| Option  | Description         |
|---------|---------------------|
| A.B.C.D | IP address to use.  |
| M       | Subnet mask to use. |

**CLI Mode**

Basic, Privileged

**Example**

```

vShield# show ip route
Codes: K - kernel route, C - connected, S - static,
       > - selected route, * - FIB route
S>* 0.0.0.0/0 [1/0] via 192.168.110.1, mgmt
C>* 192.168.110.0/24 is directly connected, mgmt

```

**Related Commands**

[ip route](#)

**show ip route ospf**

Shows routes in routing information base (RiB) learnt through OSPF protocol.

**Synopsis**

```
show ip route ospf
```

**CLI Mode**

Basic, Privileged

**Example**

Codes: O - OSPF derived, i - IS-IS derived, B - BGP derived,  
 C - connected, S - static, L1 - IS-IS level-1, L2 - IS-IS level-2,  
 IA - OSPF inter area, E1 - OSPF external type 1, E2 - OSPF external type 2  
 O E2 60.60.60.0/24 [110/1] via 50.50.50.3  
 O E2 90.90.90.0/24 [110/1] via 50.50.50.3

**show ip route bgp**

Shows routes in routing information base (RiB) learnt through the BGP protocol.

**Synopsis**

```
show ip route bgp
```

**CLI Mode**

Basic, Privileged

**Example**

Codes: O - OSPF derived, i - IS-IS derived, B - BGP derived,  
 C - connected, S - static, L1 - IS-IS level-1, L2 - IS-IS level-2,  
 IA - OSPF inter area, E1 - OSPF external type 1, E2 - OSPF external type 2  
 B 80.80.80.0/24 [20/0] via 20.20.20.1  
 B 80.80.80.0/24 [20/0] via 70.70.70.1

**show ip route A.B.C.D/M**

Displays a route entry matched by the specified prefix.

**Synopsis**

```
show ip route A.B.C.D
```

**CLI Mode**

Privileged, Configuration, and Interface Configuration

**show log**

Shows the system log.

**Synopsis**

```
show log [follow | reverse]
```

| Option  | Description                                  |
|---------|----------------------------------------------|
| follow  | Update the displayed log every 5 seconds.    |
| reverse | Show the log in reverse chronological order. |

**CLI Mode**

Basic, Privileged



**Example**

```
vShield# show log
Aug 7 17:32:37 vShield_118 syslog-ng[27397]: Configuration reload request received, reloading configuration;
Aug 7 17:32:37 vShield_118 udev[21427]: removing device node '/dev/vcs12'
Aug 7 17:32:37 vShield_118 udev[21429]: removing device node '/dev/vcsa12'
Aug 7 17:32:37 vShield_118 udev[21432]: creating device node '/dev/vcs12'
Aug 7 17:32:37 vShield_118 udev[21433]: creating device node '/dev/vcsa12'
Aug 7 17:33:37 vShield_118 ntpdate[21445]: adjust time server 10.115.216.84 offset 0.011031 sec
Aug 7 17:34:37 vShield_118 ntpdate[21466]: adjust time server 10.115.216.84 offset 0.002739 sec
Aug 7 17:35:37 vShield_118 ntpdate[21483]: adjust time server 10.115.216.84 offset 0.010884 sec
...
```

**Related Commands**

[show log last](#)

**show log follow**

Displays the log as it gets log contents.

**Synopsis**

show log follow

**CLI Mode**

Basic

**show log last**

Shows last *n* lines of the log.

**Synopsis**

show log last NUM

| Option | Description                    |
|--------|--------------------------------|
| NUM    | Number of log lines to display |

**CLI Mode**

Basic, Privileged

**Example**

```
vShield# show log last 2
Feb 9 12:30:55 localhost ntpdate[24503]: adjust time server 192.168.110.199 off
set -0.000406 sec
Feb 9 12:31:54 localhost ntpdate[24580]: adjust time server 192.168.110.199 off
set -0.000487 sec
```

**Related Commands**

[show log](#)

**show log reverse**

Displays the log in reverse chronological order.

**Synopsis**

show log reverse

**CLI Mode**

Basic

## show nat

Displays NAT packet counters along with the NAT rules that specify how to translate network addresses for a packet that matches.

### Synopsis

show nat

### CLI Mode

Basic

## show process

Shows information related to NSX Edge processes.

### Synopsis

show process (list | monitor)

| Option  | Description                                           |
|---------|-------------------------------------------------------|
| list    | List all currently running processes on the NSX Edge. |
| monitor | Continuously monitor the list of processes.           |

### CLI Mode

Basic, Privileged

### Example

vShieldEdge# show process list

## show route

Shows the current routes configured on an NSX Edge.

### Synopsis

show route

### CLI Mode

Basic, Privileged

### Example

vShieldEdge# show route

## show service

Shows the status of the specified NSX Edge service.

### Synopsis

show service (dhcp | ipsec | lb)

| Option | Description                                   |
|--------|-----------------------------------------------|
| dhcp   | Show the status of the DHCP service.          |
| ipsec  | Show the status of the VPN service.           |
| lb     | Show the status of the Load Balancer service. |

**CLI Mode**

Basic

**Example**

```
vShieldEdge# show service dhcp
```

**show service l2vpn (on server)**

Shows the L2 VPN server status and tunnel information along with the encryption algorithm that is being used in the communication.

**Synopsis**

```
show service l2vpn
```

**CLI Mode**

Basic, Privileged

**Example**

```
vShield-edge-1-0> show service l2vpn
L2 VPN is running
-----
L2 VPN type: Server
Tunnel information: 1 ABC na 1 1402561453 AES128-SHA
```

**show service l2vpn (on client)**

Shows the L2 VPN client status.

**Synopsis**

```
show service l2vpn
```

**CLI Mode**

Basic, Privileged

**Example**

```
vShield-edge-1-0> show service l2vpn
L2 VPN is running
-----
L2 VPN type: Client
Tunnel status: up
Total bytes sent: 582
Total bytes received: 408
```

**show service l2vpn bridge**

Shows the L2 VPN bridge configuration. You can run this command on both the client and the server.

**Synopsis**

```
show service l2vpn bridge
```

**CLI Mode**

Basic, Privileged

**Example**

```
vShield-edge-1-0> show service l2vpn bridge
```

| bridge name | bridge id         | STP enabled | interfaces   |
|-------------|-------------------|-------------|--------------|
| br-sub      | 8000.005056b86b46 | no          | vn1c1<br>na1 |

List of learned MAC addresses for L2 VPN bridge br-sub

| port no | mac addrr         | is local? | vlan id | ageing timer |
|---------|-------------------|-----------|---------|--------------|
| 1       | 00:50:56:b8:6b:46 | yes       | 0       | );00         |
| 2       | c2:2b:0e:8b:b3:ba | yes       | 0       | 0:00         |

## show service l2vpn trunk-table

Lists the interfaces of the Edge and shows the trunk interfaces. You can run this command on both the client and the server.

### Synopsis

show service l2vpn trunk-table

### CLI Mode

Basic, Privileged

### Example

vShield-edge-1-0> show service l2vpn trunk-table

| ifindex | iface  | trunk flag |
|---------|--------|------------|
| 01      | lo     | 0          |
| 02      | VDR    | 0          |
| 03      | vNIC_0 | 0          |
| 04      | vNIC_4 | 0          |
| ...     | ...    | ...        |
| ...     | ...    | ...        |
| 06      | vNIC_1 | 1          |

## show service l2vpn conversion table

Lists the tunnel ID to which the network is mapped. Also indicates whether the network is VLAN or VXLAN.

### Synopsis

show service l2vpn trunk-table

### CLI Mode

Basic, Privileged

### Example

vShield-edge-1-0> show service l2vpn trunk-table

| TunnelId | VLAN/VNI | Type |
|----------|----------|------|
| 10       | 100      | VLAN |

## show service monitor

Shows the running status of health monitor service.

### Synopsis

show service monitor

### CLI Mode

Basic, Privileged

### Example

```
vShield-edge-1-0> show service monitor
Network Monitor Service Status:
Network Monitor : running
PID : 18578
Total Services : 7
Monitored Services Status:
Services in OK/WARNING/UNKNOWN/CRITICAL : 1 / 0 / 0 / 6
Services Scheduled : 7
Services Checked : 7
Service Checks Last 1/5/15 min : 45 / 45 / 45
Total Service State Change : 0.000 / 0.000 / 0.000 %
```

## show service monitor service

Shows the running status of health monitor instances.

### Synopsis

show service monitor service

### CLI Mode

Basic, Privileged

### Example

```
vShield-edge-1-0> show service monitor service
Network Monitor: Monitored Services Statistics:
MONITOR default_tcp_monitor
| TOTAL SERVICES MONITORED: 5
+-->SERVICE [0]
+-->SERVICE METADATA INFORMATION:
| MONITOR: default_tcp_monitor
| POOL: iis-pool
| MEMBER: m1
| HOST ADDRESS: 10.117.5.62
| CHECK EXECUTION TIME (s): 15.033
| CHECK LATENCY (s): 0.627
| CHECK ATTEMPTS (CUR/MAX): 1/1
| CHECK RESULT: CRITICAL - Socket timeout after 15 seconds
+-->SERVICE [1]
+-->SERVICE METADATA INFORMATION:
| MONITOR: default_tcp_monitor
| POOL: tcp-pool-shared-l4-l7
| MEMBER: 192.168.1.100
| HOST ADDRESS: 192.168.1.100
| CHECK EXECUTION TIME (s): 3.036
| CHECK LATENCY (s): 0.652
| CHECK ATTEMPTS (CUR/MAX): 1/1
| CHECK RESULT: No route to host
+-->SERVICE [2]
+-->SERVICE METADATA INFORMATION:
| MONITOR: default_tcp_monitor
| POOL: tcp-pool
| MEMBER: m1
```

```

| HOST ADDRESS: 192.168.1.100
| CHECK EXECUTION TIME (s): 2.036
| CHECK LATENCY (s): 0.653
| CHECK ATTEMPTS (CUR/MAX): 1/1
| CHECK RESULT: No route to host
+-->SERVICE [3]
+-->SERVICE METADATA INFORMATION:
| MONITOR: default_tcp_monitor
| POOL: tcp-pool
| MEMBER: m2
| HOST ADDRESS: 192.168.1.40
| CHECK EXECUTION TIME (s): 0.015
| CHECK LATENCY (s): 0.654
| CHECK ATTEMPTS (CUR/MAX): 1/1
| CHECK RESULT: Connection refused
+-->SERVICE [4]
+-->SERVICE METADATA INFORMATION:
| MONITOR: default_tcp_monitor
| POOL: tcp-pool
| MEMBER: m3
| HOST ADDRESS: 192.168.1.50
| CHECK EXECUTION TIME (s): 0.035
| CHECK LATENCY (s): 0.652
| CHECK ATTEMPTS (CUR/MAX): 1/1
| CHECK RESULT: Connection refused
MONITOR HC-WEB
| TOTAL SERVICES MONITORED: 2
+-->SERVICE [0]
+-->SERVICE METADATA INFORMATION:
| MONITOR: HC-WEB
| POOL: http-pool
| MEMBER: m1
| HOST ADDRESS: 192.168.1.100
| CHECK EXECUTION TIME (s): 3.037
| CHECK LATENCY (s): 0.652
| CHECK ATTEMPTS (CUR/MAX): 1/1
| CHECK RESULT: No route to host
+-->SERVICE [1]
+-->SERVICE METADATA INFORMATION:
| MONITOR: HC-WEB
| POOL: http-pool
| MEMBER: m2
| HOST ADDRESS: 192.168.1.40
| CHECK EXECUTION TIME (s): 0.009
| CHECK LATENCY (s): 0.654
| CHECK ATTEMPTS (CUR/MAX): 1/1
| CHECK RESULT: HTTP OK: Status line output matched "HTTP/1.1 200 OK" - 329 bytes in 0.002 second response time

```

## show service dhcp

Displays whether the DHCP service is running.

### Synopsis

```
show service dhcp
```

### CLI Mode

Basic

## show service dns

Displays whether the DNS service is running.

### Synopsis

```
show service dns
```

**CLI Mode**

Basic

**show service ipsec**

Shows the VPN service details. For an explanation of the various sub-modes of this command, see the sections that follow this one.

**Synopsis**

```
show service ipsec (cacerts | certs | ctrl | pubkeys | sa | sp | status)
```

| Option  | Description                                          |
|---------|------------------------------------------------------|
| cacerts | Show the CA certificates.                            |
| certs   | Show the Edge certificates                           |
| ctrls   | Show the CRLs revoke certificates.                   |
| pubkeys | Show the public keys.                                |
| sa      | Show the Ssecurity Association Database (SAD) entry. |
| sp      | Show the Ssecurity Policy Database (SPD) entry.      |
| status  | Show the status of the ipsec server.                 |

**CLI Mode**

Basic

**Example**

```
vShieldEdge# show service ipsec status
```

**show service ipsec cacerts**

Displays IPSEC CA certificates.

**Synopsis**

```
show service ipsec cacerts
```

**CLI Mode**

Privileged, Configuration, and Interface Configuration

**show service ipsec certs**

Displays IPSEC certificates.

**Synopsis**

```
show service ipsec certs
```

**CLI Mode**

Basic

**show service ipsec crls**

Displays Certificate Revocation Lists (CRL).

**Synopsis**

```
show service ipsec crls
```

**CLI Mode**

Basic

**show service ipsec pubkeys**

Displays all installed public keys that are either received from peers or loaded locally.

**Synopsis**

```
show service ipsec pubkeys
```

**CLI Mode**

Basic

**show service ipsec sa**

Displays the security association database, which contains a set of security information that describes a particular kind of secure connection between one device and another.

**Synopsis**

```
show service ipsec sa
```

**CLI Mode**

Basic

**show service ipsec sp**

Displays the security policy database, which contains a set of rules that are programmed into the IPSec implementation that tells it how to process different packets received by the device.

**Synopsis**

```
show service ipsec sp
```

**CLI Mode**

Basic

**show service highavailability**

Displays high availability (HA) service information such as HA status and Healthcheck status, etc.

**Synopsis**

```
show service highavailability
```

**CLI Mode**

Basic

**show service highavailability link**

Displays HA link information such as IP addresses for peer links and local links.

**Synopsis**

```
show service highavailability link
```

**CLI Mode**

Basic



## show service highavailability connection-sync

Displays HA connection sync-up status information. For example, statistics about current active connections of both local and peer device.

### Synopsis

```
show service highavailability connection-sync
```

### CLI Mode

Basic

## show service loadbalancer

Display overall current loadbalancer engine state.

### Synopsis

```
show service loadbalancer
```

### CLI Mode

Basic

## show service loadbalancer monitor *monitorName*

Displays health of specified monitor.

### Synopsis

```
show service loadbalancer monitor monitorName
```

### CLI Mode

Basic

### Example

```
vShield-edge-2-0> show service loadbalancer monitor
```

```
-----  
Loadbalancer HealthMonitor Statistics:
```

| POOL      | MEMBER      | HEALTH STATUS                 |
|-----------|-------------|-------------------------------|
| http-pool | http-Server | default_http_monitor:CRITICAL |

## show service loadbalancer pool *poolName*

Displays pool member state.

### Synopsis

```
show service loadbalancer pool name
```

### CLI Mode

Basic

### Example

```
vShield-edge-2-0> show service loadbalancer pool
```

```
-----  
Loadbalancer Pool Statistics:
```

```
POOL http-pool  
| LB METHOD round-robin  
| LB PROTOCOL L7  
| Transparent disabled
```

```
| SESSION (cur, max, limit, total) = (0, 0, 1, 0)
| BYTES in = (0), out = (0)
+-->POOL MEMBER: http-pool/http-Server, STATUS: DOWN
| | STATUS = DOWN, MONITOR STATUS = default_http_monitor:CRITICAL
| | SESSION (cur, max, limit, total) = (0, 0, , 0)
| | BYTES in = (0), out = (0)
```

## show service loadbalancer session

Displays concurrent sessions for both L4 and L7 load balancer engines.

### Synopsis

```
show service loadbalancer session
```

### CLI Mode

Basic

## show service loadbalancer table

Displays session persistence table entries.

### Synopsis

```
show service loadbalancer table
```

### CLI Mode

Basic

## show service loadbalancer virtual *serverName*

Displays virtual server details.

### Synopsis

```
show service loadbalancer virtual serverName
```

### CLI Mode

Basic

### Example

```
vShield-edge-2-0> show service loadbalancer virtual
```

```
-----
Loadbalancer VirtualServer Statistics:
```

```
VIRTUAL VSIP
| ADDRESS [10.115.172.18]:80
| SESSION (cur, max, limit, total) = (0, 0, 1024, 0)
| RATE (cur, max, limit) = (0, 0, 0)
| BYTES in = (0), out = (0)
```

## show service network connections

Displays service network connection information. For example, TCP and UDP service information.

### Synopsis

```
show service network connections
```

### CLI Mode

Basic

**show service sslvpn-plus**

Displays SSL VPN-Plus service information.

**Synopsis**

show service sslvpn-plus

**CLI Mode**

Basic

**show service sslvpn-plus stats**

Displays SSL VPN-Plus statistic information.

**Synopsis**

show service sslvpn-plus stats

**CLI Mode**

Basic

**show service sslvpn-plus sessions**

Displays SSL VPN-Plus active sessions.

**Synopsis**

show service sslvpn-plus sessions

**CLI Mode**

Basic

**show service sslvpn-plus tunnels**

Displays SSL VPN-Plus tunnel information.

**Synopsis**

show service sslvpn-plus tunnels

**CLI Mode**

Basic

**show system load**

Shows the average processing load on an NSX Edge.

**Synopsis**

show system load

**CLI Mode**

Basic, Privileged

**Example**

```
vShield# show system mem
MemTotal:  2072204 kB
MemFree:   1667248 kB
Buffers:   83120 kB
```

## show system network-stats

Displays network statistics. For example, statistics for IP, ICMP, TCP and UDP, etc.

### Synopsis

```
show system network-stats
```

### CLI Mode

Basic

## show system cpu

Shows the system cpu details.

### Synopsis

```
show system cpu
```

### CLI Mode

Basic

### Example

```
vShield# show system cpu
```

### Related Commands

[show system memory](#)

[show system uptime](#)

## show system log size

Shows the total size of the system log files.

### Synopsis

```
show system log size
```

### CLI Mode

Basic

### Example

```
vShield# show system log size  
1M
```

## show system memory

Shows the summary of memory utilization.

### Synopsis

```
show system memory
```

### CLI Mode

Basic, Privileged

### Example

```
vShield# show system mem  
MemTotal: 2072204 kB  
MemFree: 1667248 kB  
Buffers: 83120 kB
```

## show system storage

Shows the disk usage details for an NSX Edge.

### Synopsis

show system storage

### CLI Mode

Basic, Privileged

### Example

vShield# show system storage

## show system uptime

Shows the length of time the NSX virtual machine has been operational since last reboot.

### Synopsis

show system uptime

### CLI Mode

Basic, Privileged

### Example

vShield# show system uptime  
0 day(s), 8 hour(s), 50 minute(s), 26 second(s)

## show tech-support

Displays system information for tech-support. It shows all the information contained in tech-support tarball file.

### Synopsis

show tech-support

### CLI Mode

Basic

## show version

Shows the software version currently running on the virtual machine.

### Synopsis

show version

### CLI Mode

Basic, Privileged

### Example

vShield# show version

## traceroute

Traces the route to a destination.

**Synopsis**

```
traceroute (HOSTNAME | A.B.C.D)
```

| Option             | Description                                      |
|--------------------|--------------------------------------------------|
| HOSTNAME   A.B.C.D | The hostname or IP address of the target system. |

**CLI Mode**

Basic, Privileged

**Example**

```
vShield# traceroute 10.16.67.118
traceroute to 10.16.67.118 (10.16.67.118), 30 hops max, 40 byte packets
 1 10.115.219.253 (10.115.219.253) 128.808 ms 74.876 ms 74.554 ms
 2 10.17.248.51 (10.17.248.51) 0.873 ms 0.934 ms 0.814 ms
 3 10.16.101.150 (10.16.101.150) 0.890 ms 0.913 ms 0.713 ms
 4 10.16.67.118 (10.16.67.118) 1.120 ms 1.054 ms 1.273 ms
```

## NSX Controller Commands

This section describes controller commands. Log in as the controller admin to use the controller CLI commands.

### restart controller

Restarts a controller. You must restart only one controller in a cluster at a time.

**Synopsis**

```
restart controller
```

### set control-cluster core log-level *value*

Sets log level for the controller cluster. Possible values are:

- error
- warn
- info
- debug
- trace

**Synopsis**

```
set control-cluster core log-level value
```

**Example**

```
nsx-controller # set control-cluster core error
```

### show control-cluster core

Lists all available properties, the required parameters, and their descriptions for the controller framework.

**Synopsis**

```
show control-cluster core
```

**show control-cluster core stats**

Displays controller statistics.

**Synopsis**

```
show control-cluster core stats
```

**Example**

```
nvp-controller # show control-cluster core stats
messages.received      40
messages.received.dropped  0
messages.transmitted    22
messages.transmit.dropped  0
messages.processing.dropped 0
connections.up          2
connections.down        0
connections.timeout     0
connections.active      2
connections.sharding.subscribed 0
```

**show control-cluster core connection-stats *ipAddress***

Displays statistics for the specified controller.

**Synopsis**

```
show control-cluster core connection-stats 11.11.111.11
```

**Example**

```
nvp-controller # show control-cluster core connection-stats 10.24.106.158
messages.received      22
messages.received.dropped 0
messages.transmitted    10
messages.transmit.dropped 0
```

**show control-cluster core connection *ipAddress***

Displays status of specified connection.

**Synopsis**

```
show control-cluster core log-level 11.11.111.11
```

**Example**

```
nvp-controller # show control-cluster core connection 11.11.111.11
Host-IP    Port ID
10.24.106.158 53540 3
```

**show control-cluster core log-level**

Displays log level for the specified controller.

**Synopsis**

```
show control-cluster core log-level
```

**Example**

```
nvp-controller # show control-cluster core log-level
Log level: INFO
```

**show control-cluster logical-routers**

Lists all available properties, the required parameters, and their descriptions for logical routers.

**Synopsis**

```
show control-cluster logical-routers
```

## show control-cluster logical-routers bridge-mac *logicalRouterID\_and/or\_bridgeID*

Displays bridge mac records for a bridge of a logical router. *logical\_router\_ID* and/or *bridge\_ID* can be all.

### Synopsis

show control-cluster logical-routers bridge-mac *logicalRouterID\_and\_bridgeID*

### Example

```
nvp-controller # show control-cluster logical-routers bridge-mac 1 all
LR-Id   Bridge-Id  Mac              Vlan-Id Vxlan-Id Port-Id Source
1       1001      01:00:00:01:00:00 0       65535   1       vxlan
```

## show control-cluster logical-routers bridges *logicalRouterID\_and\_bridgeID*

Displays bridge instance information for a logical router. *logical\_router\_id* and/or *bridge-id* can be all.

### Synopsis

show control-cluster logical-routers bridges *logicalRouterID\_and\_bridgeID*

### Example

```
nvp-controller # show control-cluster logical-routers bridges 1 all
LR-Id   Bridge-Id  Host           Active
1       1001      10.24.106.158 true
```

## show control-cluster logical-routers instance *logicalRouterID*

Displays logical router information. *logicalRouterID* can be all.

### Synopsis

show control-cluster logical-routers instance *logicalRouterID*

### Example

```
nvp-controller # show control-cluster logical-routers instance 1
LR-Id LR-Name  Hosts[]           Edge-Connection Service-Controller
1     perftest  10.24.106.158      10.24.105.58
```

## show control-cluster logical-routers interface *logicalRouterID\_and\_logicalRouterName*

Displays interface details for logical router specified by ID and name.

### Synopsis

show control-cluster logical-routers interface *logicalRouterID\_and\_logicalRouterName*

### Example

```
nvp-controller # show control-cluster logical-routers interface 1 lif0
Interface-Name: lif0
Logical-Router-Id: 1
Id:             0
Type:           vlan
IP:             10.0.0.0/24
DVS-UUID:       64767331-0000-0000-0000-000000000000
Mac:            00:00:00:00:00:00
Mtu:            1500
Multicast-IP:
Designated-IP:  10.24.106.158
Is-Sedimented:  false
Bridge-Id:
```



Bridge-Name:

## show control-cluster logical-routers interface-summary *logicalRouterID*

Displays interface summary for specified logical router.

### Synopsis

show control-cluster logical-routers interface-summary *logicalRoute\_ID*

### Example

```
nvp-controller # show control-cluster logical-routers interface-summary 1
Interface      Type  Id      IP[]
lif0           vlan  0      10.0.0.0/24
lif1           vlan  1      10.0.1.0/24
```

## show control-cluster logical-routers routes *routerID*

Displays static route for router specified by ID. *routerID* can be all.

### Synopsis

show control-cluster logical-routers routes *routerID*

### Example

```
nvp-controller # show control-cluster logical-routers routes 1
LR-Id  Destination  Next-Hop
1      70.70.70.0/24  10.0.1.2
1      80.80.80.0/24  10.0.0.2
```

## show control-cluster logical-routers routes *routerID\_and\_IPaddress\_and\_prefixLength*

Displays static route for router specified by ID, IP address, and prefix length. *router\_ID* can be all.

### Synopsis

show control-cluster logical-routers routes *routerID\_and\_IPaddress\_and\_prefixLength*

### Example

```
nvp-controller # show control-cluster logical-routers route 1 70.70.70.0 24
LR-Id  Destination  Next-Hop
1      70.70.70.0/24  10.0.1.2
```

## show control-cluster logical-routers stats

Displays statistics of all logical routers on this controller.

### Synopsis

show control-cluster logical-routers stats

### Example

```
nvp-controller # show control-cluster logical-routers stats
messages.query      0
messages.update     4
messages.flush      0
messages.notification 0
```

## show control-cluster logical-routers vdr-stats *logicalRouterID*

Displays statistics of the specified logical router.

**Synopsis**

```
show control-cluster logical-routers vdr-stats logicalRouterID
```

**Example**

```
nvp-controller # show control-cluster logical-routers vdr-stats 1
host.reports.received    1
host.reports.dropped    0
edge.routes.received    2
edge.routes.dropped    0
bridge.reports.received  1
bridge.reports.dropped  0
bridge.macs.received    1
bridge.macs.dropped    0
route.queries.received  0
interface.queries.received 0
mac.queries.received    0
clear.routes.received    0
clear.macs.received    0
errdecode.messages.dropped 0
memfull.messages.dropped 0
errserver.messages.dropped 0
notifications.error      0
```

**show control-cluster startup-nodes**

Shows the IP addresses of active controllers in the cluster.

**Synopsis**

```
show control-cluster startup-nodes
```

**Example**

```
nvp-controller # show control-cluster startup-nodes
10.24.105.59
```

**show control-cluster status**

Shows control-cluster status. The example below shows that the controller status is normal. All controllers in the cluster should have the same cluster ID as the first controller.

**Synopsis**

```
show control-cluster status
```

**Example**

```
nvp-controller # show control-cluster status
Type Status Since
-----
Join status: Join complete 08/15 00:39:57
Majority status: Connected to cluster majority 08/15 00:39:33
Restart status: This controller can be safely restarted 08/15 00:40:03
Cluster ID: 2105ad76-0449-47ef-9f99-83e7ddd14cd0
Node UUID: 2105ad76-0449-47ef-9f99-83e7ddd14cd0
Role Configured status Active status
-----
api_provider enabled activated
persistence_server enabled activated
switch_manager enabled activated
logical_manager enabled activated
directory_server enabled activated
```

**show network interface**

Shows the IP address of the controller.

**Synopsis**

show network interface

**CLI Mode**

Basic, Privileged

## ESXi CLI Commands

This section describes the ESXi CLI commands for NSX vSphere. For additional ESX CLI commands, see *vSphere Command-Line Interface Documentation*.

### esxcli network vswitch dvs vmware vxlan config stats get

Shows statistics.

**Synopsis**

esxcli network vswitch dvs vmware vxlan config stats get

**Example**

```
# esxcli network vswitch dvs vmware vxlan config stats get
Level: 1
```

### esxcli network vswitch dvs vmware vxlan config stats set

Enable statistics. Adding level=0 disables statistics.

**Synopsis**

esxcli network vswitch dvs vmware vxlan config stats set

### esxcli network vswitch dvs vmware vxlan get

Shows VXLAN global states on the system.

**Synopsis**

esxcli network vswitch dvs vmware vxlan get

**Example**

```
# esxcli network vswitch dvs vmware vxlan get
Controlplane Out Of Sync: No
UDPport: 8472
```

### esxcli network vswitch dvs vmware vxlan list --vds-name *value*

Shows VXLAN switches information for the specified vDS.

**Synopsis**

esxcli network vswitch dvs vmware vxlan list

**Example**

```
# esxcli network vswitch dvs vmware vxlan list
```

| VDS ID                                          | VDS Name | MTU  | Segment ID  | Gateway IP    | Gateway MAC       | Network Count | Vmknics Count |
|-------------------------------------------------|----------|------|-------------|---------------|-------------------|---------------|---------------|
| 35 fe 34 50 d4 59 27 de-e7 9f c0 3d c8 c7 a0 84 | dvSwitch | 1600 | 192.168.0.0 | 192.168.0.254 | 00:00:0c:00:11:22 | 1             | 1             |

## esxcli network vswitch dvs vmware vxlan network list --vds-name *value* vxlan-id *value*

Shows VXLAN network information with specified vDS.

### Synopsis

esxcli network vswitch dvs vmware vxlan network list --vds-name *value* [--vxlan-id *value*]

### Example

```
# esxcli network vswitch dvs vmware vxlan network list --vds-name dvSwitch
```

| VXLAN ID | Multicast IP              | Control Plane                        | Controller    | Connection | Port Count | MAC Entry Count | ARP Entry Count |
|----------|---------------------------|--------------------------------------|---------------|------------|------------|-----------------|-----------------|
| 5000     | N/A (headend replication) | Enabled (multicast proxy, ARP proxy) | 192.168.100.1 | (up)       | 1          | 11              | 1               |

## esxcli network vswitch dvs vmware vxlan network arp list --vds-name *value* --vxlan-id *value*

Retrieves VXLAN network ARP table for specified vDS.

### Synopsis

esxcli network vswitch dvs vmware vxlan network arp list --vds-name *value* --vxlan-id *value* --vdsport-id *value*

### Example

```
# esxcli network vswitch dvs vmware vxlan network arplist --vds-name dvSwitch --vxlan-id 5000 --vdsport-id=101
```

| IP            | MAC               | Flags    |
|---------------|-------------------|----------|
| 192.168.200.1 | 00:50:56:00:11:22 | 00000000 |

## esxcli network vswitch dvs vmware vxlan network arp reset -vds-name *value* --vxlan-id *value*

Resets VXLAN network ARP table for specified vDS.

### Synopsis

esxcli network vswitch dvs vmware vxlan network are reset -vds-name *value* --vxlan-id *value* --vdsport-id *value*

## esxcli network vswitch dvs vmware vxlan network mac list --vds-name *value* --vxlan-id *value*

Retrieves VXLAN network MAC table for specified vDS.

### Synopsis

esxcli network vswitch dvs vmware vxlan network mac ABC 500

### Example

```
# esxcli network vswitch dvs vmware vxlan network mac --vds-name dvSwitch --vxlan-id 5000
```

| Inner MAC         | Outer MAC         | Outer IP    | Flags    |
|-------------------|-------------------|-------------|----------|
| 00:50:56:00:11:23 | 00:50:56:01:23:45 | 192.168.0.2 | 00000000 |

## **esxcli network vswitch dvs vmware vxlan network mac reset --vxlan-id *value* --vdsport-id *value***

Resets VXLAN network MAC table for specified vDS.

### **Synopsis**

esxcli network vswitch dvs vmware vxlan network mac reset -vxlan-id=*value* --vdsport-id=*value*

## **esxcli network vswitch dvs vmware vxlan network port list --vds-name *value* --vdsport-id *value* --vxlan-id *value***

Shows VXLAN port information with specified network.

### **Synopsis**

esxcli network vswitch dvs vmware vxlan network port list --vds-name *value* --vxlan-id *value* [--vdsport-id *value*]

### **Example**

```
# esxcli network vswitch dvs vmware vxlan network port list --vds-name dvSwitch --vxlan-id 5000
```

| Switch Port ID | VDS Port ID | VMKNIC ID |
|----------------|-------------|-----------|
| 67108869       | 101         | 0         |

## **esxcli network vswitch dvs vmware vxlan network port stats list --vds-name *value* --vdsport-id *value* --vxlan-id *value***

Shows VXLAN port statistics information with specified network.

### **Synopsis**

esxcli network vswitch dvs vmware vxlan network port stats list --vds-name *value* --vxlan-id *value* --vdsport-id *value*

### **Example**

```
# esxcli network vswitch dvs vmware vxlan network port stats list --vds-name dvSwitch --vxlan-id 5000 --vdsport-id=101
```

| Name     | Value |
|----------|-------|
| tx.total | 0     |
| rx.total | 0     |

## **esxcli network vswitch dvs vmware vxlan network stats list --vdsd-name *value* --vxlan-id *value***

Shows VXLAN network statistics.

### **Synopsis**

esxcli network vswitch dvs vmware vxlan network stats list --vds-name *value* --vxlan-id *value*

### **Example**

```
# esxcli network vswitch dvs vmware vxlan network stats list --vds-name dvSwitch --vxlan-id 5000
```

| Name           | Value |
|----------------|-------|
| tx.total       | 0     |
| tx.nonUnicast  | 0     |
| tx.crossRouter | 0     |
| tx.drop.total  | 0     |

| Name                 | Value |
|----------------------|-------|
| rx.total             | 0     |
| rx.mcastEncap        | 0     |
| rx.crossRouter       | 0     |
| rx.drop.wrongDest    | 0     |
| rx.drop.invalidEncap | 0     |
| rx.drop.total        | 0     |
| mac.lookup.found     | 0     |
| mac.lookup.flood     | 0     |
| mac.lookup.full      | 0     |
| mac.update.learn     | 0     |
| mac.update.extend    | 0     |
| mac.update.full      | 0     |
| mac.age              | 0     |
| mac.renew            | 0     |
| arp.lookup.found     | 0     |
| arp.lookup.unknown   | 0     |
| arp.lookup.full      | 0     |
| arp.lookup.wait      | 0     |
| arp.lookup.timeout   | 0     |
| arp.update.update    | 0     |
| arp.update.unknown   | 0     |
| arp.update.notFound  | 0     |
| arp.age              | 0     |
| arp.renew            | 0     |

### **esxcli network vswitch dvs vmware vxlan network stats reset --vxlan-id *value* --vdsport-id *value***

Resets VXLAN network statistics.

#### **Synopsis**

esxcli network vswitch dvs vmware vxlan network stats reset -vxlan-id *value* --vdsport-id *value*

### **esxcli network vswitch dvs vmware vxlan network vtep list --vds-name *value* --vxlan-id *value* --segment-id *value* --vtep-ip *value***

Retrieves VXLAN network VTEP table for specified vDS. To retrieve VTEP information for a specific segment or VTEP IP address, specify the segmentID or vtepIP parameter.

#### **Synopsis**

esxcli network vswitch dvs vmware vxlan network mac --vds-name *value* --vxlan-id *value* [--segment-id *value* --vtep-ip *value*]

#### **Example**

```
# esxcli network vswitch dvs vmware vxlan network mac --vds-name dvSwitch --vxlan-id 5000
```

| IP          | Segment ID  | Is MTEP |
|-------------|-------------|---------|
| 192.168.0.2 | 192.168.0.0 | False   |

### **esxcli network vswitch dvs vmware vxlan vmknic list --vds-name *value* --endpoint-id *value* --vmknic-name *value* --vmknic-ip *value***

Retrieves VXLAN vmknic multicast group information. To retrieve multicast group information for a specific vmknic, specify the vmknic ID, IP, or name using the appropriate parameter.

#### **Synopsis**

esxcli network vswitch dvs vmware vxlan vmknic list --vds-name *value* [--endpoint-id *value* --vmknic-name *value* --vmknic-ip *value*]

#### **Example**

```
# esxcli network vswitch dvs vmware vxlan vmknic list --vds-name dvSwitch
```

| Vmknic Name | Switch Port ID | VDS PortID | Endpoint ID | VLAN ID | IP          | Netmask       | IP Acquire Timeout | Multicast Group Count | Segment ID  |
|-------------|----------------|------------|-------------|---------|-------------|---------------|--------------------|-----------------------|-------------|
| vmk2        | 67108868       | 100        | 0           | 0       | 192.168.0.1 | 255.255.255.0 | 34960              | 0                     | 192.168.0.0 |

### **esxcli network vswitch dvs vmware vxlan vmknic multicastgroup list --vds-name *value* --vmknic-id *value* --vmknic-name *value* --vmknic-ip *value***

Retrieves VXLAN network VTEP table for specified vDS. To retrieve VTEP information for a specific segment or VTEP IP address, specify the segmentID or vtepIP parameter.

#### **Synopsis**

esxcli network vswitch dvs vmware vxlan vmknic multicastgroup list --vds-name *value* [--vmknic-id *value* --vmknic-name *value* --vmknic-ip *value*]

#### **Example**

```
# esxcli network vswitch dvs vmware vxlan network mac --vds-name dvSwitch --vmknic-name vmk2
```

| Vmknic Name | Vmknic ID | VXLAN IP    | Multicast IP | Joined | Port Count |
|-------------|-----------|-------------|--------------|--------|------------|
| vmk2        | 0         | 192.168.0.1 | 239.0.0.1    | YES    | 1          |

### **esxcli network vswitch dvs vmware vxlan stats list --vds-name *value* --endpoint-id *value* --vmknic-name *value* --vmknic-ip *value***

Retrieves VXLAN vmknic statistics. To retrieve statistics for a specific vmknic, specify the Endpoint ID, IP, or name using the appropriate parameter.

#### **Synopsis**

esxcli network vswitch dvs vmware vxlan stats list --vds-name *value* [--endpoint-id *value* --vmknic-name *value* --vmknic-ip *value*]

#### **Example**

```
# esxcli network vswitch dvs vmware vxlan stats list --vds-name dvSwitch
```

| Name           | Value |
|----------------|-------|
| tx.passThrough | 0     |
| tx.vxlanTotal  | 0     |
| tx.clone       | 0     |
| tx.tso         | 0     |

| Name                   | Value |
|------------------------|-------|
| tx.csum                | 0     |
| tx.drop.invalidFrame   | 0     |
| tx.drop.guestTag       | 0     |
| tx.drop.noResource     | 0     |
| tx.drop.invalidState   | 0     |
| rx.passThrough         | 0     |
| rx.vxlanTotal          | 0     |
| rx.clone               | 0     |
| rx.drop.invalidFrame   | 0     |
| rx.drop.notExist       | 0     |
| rx.drop.noResource     | 0     |
| forward.pass           | 0     |
| forward.reject         | 0     |
| forward.rpf            | 0     |
| arpProxy.reply.total   | 0     |
| arpProxy.reply.fail    | 0     |
| arpProxy.request.total | 0     |
| arpProxy.request.fail  | 0     |
| mcastProxy.tx.total    | 0     |
| mcastProxy.tx.fail     | 0     |
| mcastProxy.rx.total    | 0     |
| mcastProxy.rx.fail     | 0     |

## esxcli network vswitch dvs vmware vxlan stats reset --vds-name *value*

Resets VXLAN vDS statistics.

### Synopsis

esxcli network vswitch dvs vmware vxlan stats reset -vds-name *value*

## DVFilter Commands

To use the DVFilter command, log in to the host CLI terminal as root with the password that you specified while installing NSX Manager.

### summarize-dvfilter

Displays fast-path and slow-path agents of the DVFilters that are deployed on the host.

### Synopsis

summarize-dvfilter

### Example

```
# summarize-dvfilter
Fastpaths:
agent: dvfilter-faulter, refCount: 1, rev: 0x1010000, apiRev: 0x1010000, module: dvfilter
agent: dvfg-igmp, refCount: 1, rev: 0x1010000, apiRev: 0x1010000, module: dvfg-igmp
agent: dvfilter-generic-vmware, refCount: 1, rev: 0x1010000, apiRev: 0x1010000, module: dvfilter-generic-fastpath
```



agent: vmware-sfw, refCount: 1, rev: 0x1010000, apiRev: 0x1010000, module: vsip  
 agent: dvfilter-generic-vmware-swsec, refCount: 2, rev: 0x1010000, apiRev: 0x1010000, module: dvfilter-switch-security

Slowpaths:

Filters:  
 world 1000672395 vmm0:pro-vm vcUuid:'50 07 6c 09 c9 18 c5 9a-bb 78 37 70 e0 52 bd b6'  
 port 67108869 pro-vm.eth1  
 vNic slot 0  
 name: nic-1000672395-eth1-dvfilter-generic-vmware-swsec.0  
 agentName: dvfilter-generic-vmware-swsec  
 state: IOChain Attached  
 vmState: Detached  
 failurePolicy: failOpen  
 slowPathID: none  
 filter source: Alternate Opaque Channel

## Deprecated Commands

The following table lists deprecated commands.

**Table 3-1.** Deprecated Commands

| Command                                |
|----------------------------------------|
| cli ssh allow                          |
| clear firewall counters                |
| clear vmwall rules                     |
| clear vty                              |
| close support-tunnel                   |
| copy http URL slot (1 2)               |
| copy http URL temp                     |
| copy scp URL slot (1 2)                |
| copy scp URL temp                      |
| debug copy                             |
| debug export snapshot                  |
| debug import snapshot                  |
| debug service                          |
| debug service flow src                 |
| debug show files                       |
| debug snapshot list                    |
| debug snapshot remove                  |
| debug snapshot restore                 |
| default web-manager password           |
| duplex auto                            |
| duplex (half full) speed (10 100 1000) |
| http server                            |
| ip name server                         |
| ip policy-address                      |
| link-detect                            |
| linkwatch interval <5-60>              |
| manager key                            |

**Table 3-1.** Deprecated Commands

| Command                            |
|------------------------------------|
| mode policy-based-forwarding       |
| ntp server                         |
| open support-tunnel                |
| set support key                    |
| show alerts                        |
| show debug log                     |
| show dv-support                    |
| show hardware                      |
| show gateway rules                 |
| show interface                     |
| shop ip addr                       |
| show iptables                      |
| show kernel message                |
| show kernel message last           |
| show log alerts                    |
| show log events                    |
| show service helpers               |
| show service statistics            |
| show services                      |
| show session-manager counters      |
| show session-manager sessions      |
| show stacktrace                    |
| show startup-config                |
| show raid                          |
| show raid detail                   |
| show realms                        |
| copy running-config startup-config |
| show running-config                |
| show syslog                        |
| show system events                 |
| show system network_connections    |
| show syslog                        |
| show vmwall log                    |
| show vmwall rules                  |
| ssh end                            |
| syslog                             |
| telnet                             |
| vm validation                      |
| vm validation log                  |
| vmwall log suppression             |
| web-manager                        |





# Index

## B

basic mode of CLI **11**

## C

clear arp WORD **32**

clear nat counters **31**

clear service ipsec sa WORD **32**

CLI

configuration mode **12**

help **13**

interface mode **12**

logging in **12**

modes **11, 12**

privileged mode **12**

syntax **12**

command syntax **12**

commands,ESXi **83**

commands,NSX Controller **78**

commands,NSX Edge **31**

commands,NSX Manager **19, 89**

configuration mode of CLI **12**

## D

database erase **19**

debug crashdump **33**

debug packet capture **32**

debug packet display interface **32, 33**

disable **20**

dnslookup server **33**

dnslookup server name\_or\_address **33**

## E

enable **20**

enable password **20**

esxcli network vswitch dvs vmware vxlan config stats  
get **83**

esxcli network vswitch dvs vmware vxlan config stats  
set **83**

esxcli network vswitch dvs vmware vxlan list get **83**

esxcli network vswitch dvs vmware vxlan list --vds-  
name value **83**

esxcli network vswitch dvs vmware vxlan network  
arp list --vds-name value --vxlan-id  
value **84**

esxcli network vswitch dvs vmware vxlan network  
arp reset -vds-name value --vxlan-id  
value **84**

esxcli network vswitch dvs vmware vxlan network list  
--vds-name value vxlan-id value **84**

esxcli network vswitch dvs vmware vxlan network  
mac list --vds-name value --vxlan-id  
value **84**

esxcli network vswitch dvs vmware vxlan network  
mac reset --vxlan-id value --vdsport-id  
value **85**

esxcli network vswitch dvs vmware vxlan network  
port list --vds-name value --vdsport-id value  
--vxlan-id value **85**

esxcli network vswitch dvs vmware vxlan network  
port stats list --vds-name value --vdsport-id  
value --vxlan-id value **85**

esxcli network vswitch dvs vmware vxlan network  
stats list --vdsd-name value --vxlan-id  
value **85**

esxcli network vswitch dvs vmware vxlan network  
stats reset --vxlan-id value --vdsport-id  
value **86**

esxcli network vswitch dvs vmware vxlan network  
vtep list --vds-name value --vxlan-id value -  
-segment-id value --vtep-ip value **86**

esxcli network vswitch dvs vmware vxlan stats list --  
vds-name value --endpoint-id value --  
vmknic-name value --vmknic-ip value **87**

esxcli network vswitch dvs vmware vxlan stats reset  
--vds-name value **88**

esxcli network vswitch dvs vmware vxlan vmknic list  
--vds-name value --endpoint-id value --  
vmknic-name value --vmknic-ip value **87**

esxcli network vswitch dvs vmware vxlan vmknic  
multicastgroup list --vds-name value --  
vmknic-id value --vmknic-name value --  
vmknic-ip value **87**

ESXi CLI Commands **83**

exit **21**

export tech-support scp **21, 34**

## H

help

CLI **13**

hostname **21**

## I

interface **22**

interface mode of CLI **12**

ip address **22**

ip route **23**

**L**

list **24**  
 login  
     CLI **12**

**P**

ping **23, 34**  
 ping interface addr **28, 35**  
 privileged mode of CLI **12**

**Q**

quit **24**

**R**

reboot **24**  
 reset **29**  
 restart controller **78**

**S**

set clock **25**  
 set control-cluster core log-level **78**  
 setup **29**  
 show arp **25, 35**  
 show clock **26, 35**  
 show configuration **36**  
 show configuration dhcp **36**  
 show configuration dns **37**  
 show configuration firewall **38**  
 show configuration global **39**  
 show configuration highavailability **40**  
 show configuration interface **41**  
 show configuration ipsec **43**  
 show configuration ipset **44**  
 show configuration loadbalancer **45**  
 show configuration loadbalancer monitor **47**  
 show configuration loadbalancer pool **48**  
 show configuration loadbalancer rule **49**  
 show configuration loadbalancer virtual **49**  
 show configuration nat **49**  
 show configuration ospf **51**  
 show configuration sslvpn-plus **53**  
 show configuration static\_routing **52**  
 show configuration syslog **52**  
 show control-cluster core **78**  
 show control-cluster logical-routers **79**  
 show control-cluster logical-routers bridge-mac  
     logicalRouterID\_and/or\_bridgeID **80**  
 show control-cluster logical-routers bridges  
     logicalRouterID\_and\_bridgeID **80**  
 show control-cluster logical-routers instance  
     logicalRouterID **80**  
 show control-cluster logical-routers interface  
     logicalRouterID\_and\_logicalRouterName  
     **80**

show control-cluster logical-routers interface-  
     summary logicalRouterID **81**  
 show control-cluster logical-routers routes  
     routerID **81**  
 show control-cluster logical-routers routes  
     routerID\_and\_IPAddress\_and\_prefixLength  
     **81**  
 show control-cluster logical-routers stats **81**  
 show control-cluster logical-routers vdr-stats  
     logicalRouterID **81**  
 show control-cluster startup-nodes **82**  
 show control-cluster status **82**  
 show ethernet **26**  
 show filesystem **26**  
 show fips **53**  
 show firewall **53**  
 show firewall flows **53**  
 show firewall flows top number **53**  
 show firewall flows top number sort-by bytes **54**  
 show firewall flows top number sort-by pkts **54**  
 show firewall rule-id ID **54**  
 show firewall rule-id ID flows **54**  
 show firewall rule-id ID flows top number **54**  
 show firewall rule-id ID flows top number sort-by  
     pkts **55**  
 show firewall rule-id ID flows top number sort-by-  
     bytes **55**  
 show flowtable **55**  
 show flowtable rule-id ID **55**  
 show flowtable rule-id ID top number **55**  
 show flowtable rule-id ID top number sort-by  
     bytes **56**  
 show flowtable rule-id ID top number sort-by pkts **55**  
 show flowtable top number **56**  
 show flowtable top number sort-by bytes **56**  
 show flowtable top number sort-by pkts **56**  
 show hostname **56**  
 show interface **57**  
 show interface name **57**  
 show ip bgp **57**  
 show ip bgp neighbors **57**  
 show ip forwarding **58**  
 show ip ospf **58**  
 show ip ospf database **59**  
 show ip ospf database adv-router **59**  
 show ip ospf database asbr-summary **60**  
 show ip ospf database external **60**  
 show ip ospf database network **60**  
 show ip ospf database nssa-external **61**  
 show ip ospf database opaque-area **61**  
 show ip ospf database router **61**  
 show ip ospf database summary **61**  
 show ip ospf interface **62**  
 show ip ospf ne **62**

show ip ospf statistics **62**  
 show ip route **63**  
 show ip route A.B.C.D/M **64**  
 show ip route bgp **64**  
 show ip route ospf **63**  
 show log **64**  
 show log last **65**  
 show log reverse **65**  
 show manager log **82**  
 show manager log last **27**  
 show nat **66**  
 show network interface **82**  
 show process **66**  
 show route **66**  
 show service **66**  
 show service dhcp **70**  
 show service dns **70**  
 show service highavailability **72**  
 show service highavailability connection-sync **73**  
 show service highavailability link **72**  
 show service ipsec **71**  
 show service ipsec certs **71**  
 show service ipsec crls **71**  
 show service ipsec pubkeys **72**  
 show service ipsec sa **72**  
 show service ipsec sp **72**  
 show service loadbalancer **73**  
 show service loadbalancer monitor monitorName **73**  
 show service loadbalancer pool poolName **73**  
 show service loadbalancer session **74**  
 show service loadbalancer table **74**  
 show service loadbalancer virtual serverName **74**  
 show service monitor **69**  
 show service monitor service **69**  
 show service network connections **74**  
 show service sslvpn-plus **75**  
 show service sslvpn-plus sessions **75**  
 show service sslvpn-plus stats **75**  
 show service sslvpn-plus tunnels **75**  
 show session-manager counters **28**  
 show slots **28**  
 show system cpu **76**  
 show system load **75, 76**  
 show system memory **76**  
 show system network-stats **76**  
 show system storage **77**  
 show system uptime **77**  
 show tech support **28**  
 show tech-support **77**  
 show version **77**  
 shutdown **28**  
 summarize-dvfilter **88**

syntax for CLI commands **12**

## T

terminal length **29**  
 terminal no length **29**  
 traceroute **30, 77**

## U

user **30**

## W

write **30**  
 write erase **31**  
 write memory **31**

