

SETTING UP VPN

Homepage: <https://drv.tw/~sj6219@hotmail.com/od/Doc4Code/>


Email: sj6219@hotmail.com

2012/12/09

내용


윈도우 서버 SSTP 설정	2
원격 액세스 역할 추가	2
액세스 권한 허용	11
라우터(공유기) 설정	13
SSTP 설정	14
self-signed certificate 파일(.PFX) 생성	14
IIS 관리자	14
라우팅 및 원격 액세스 관리자	16
Command Shell	17
윈도우 클라이언트 SSTP 설정	17
SSTP Certificate 등록	23
Iptime 공유기 서버 L2TP 설정	25
Windows Client L2TP Setup	26
Android Client L2TP Setup	28

윈도우 서버 SSTP 설정




원격 액세스 역할 추가


관리도구 > 서버관리자 > Manage > Add Roles and Features



Remote Access




DirectAccess and VPN



Restart the destination server automatically if required > on


관리도구 > 라우팅 및 원격 액세스



서버 선택

동작 메뉴 > 라우팅 및 원격 액세스 구성 및 사용

Routing and Remote Access Server Setup Wizard



Welcome to the Routing and Remote Access Server Setup Wizard

This wizard helps you set up your server so that you can connect to other networks and allow connections from remote clients.

To continue, click Next.

< Back

Next >

Cancel

Routing and Remote Access Server Setup Wizard

Configuration

You can enable any of the following combinations of services, or you can customize this server.

☐ Remote access (dial-up or VPN)

Allow remote clients to connect to this server through either a dial-up connection or a secure virtual private network (VPN) Internet connection.

☐ Network address translation (NAT)

Allow internal clients to connect to the Internet using one public IP address.

☐ Virtual private network (VPN) access and NAT

Allow remote clients to connect to this server through the Internet and local clients to connect to the Internet using a single public IP address.

☐ Secure connection between two private networks

Connect this network to a remote network, such as a branch office.

☒ Custom configuration

Select any combination of the features available in Routing and Remote Access.

[For more information](#)

< Back

Next >

Cancel

Routing and Remote Access Server Setup Wizard

Custom Configuration

When this wizard closes, you can configure the selected services in the Routing and Remote Access console.

Select the services that you want to enable on this server.

☒ VPN access

☐ Dial-up access

☐ Demand-dial connections (used for branch office routing)

☐ NAT

☐ LAN routing

[For more information.](#)

< Back

Next >

Cancel

Routing and Remote Access Server Setup Wizard

Completing the Routing and Remote Access Server Setup Wizard

You have successfully completed the Routing and Remote Access Server Setup wizard.

Summary of selections:

VPN access


After you close this wizard, configure the selected services in the Routing and Remote Access console.

To close this wizard, click Finish.

< Back

Finish

Cancel



서버 선택

동작 메뉴 > 속성 > IPv4

SJ6219 (local) Properties ? X

General Security **IPv4** IPv6 IKEv2 PPP Logging

☒ Enable IPv4 Forwarding

IPv4 address assignment

This server can assign IPv4 addresses by using:

☐ Dynamic Host Configuration Protocol (DHCP)

☒ Static address pool

From	To	Number	IP Address...	Mask

☒ Enable broadcast name resolution


Use the following adapter to obtain DHCP, DNS, and WINS addresses for dial-up clients.

Adapter: Allow RAS to select adapter ▼

[For more information](#)

고정 주소 풀

추가



Dialog box titled "Edit IPv4 Address Range".

Instructions: Type a starting IP address and either an ending IP address or the number of addresses in the range.

Fields:


- Start IP address: 192 . 168 . 99 . 201
- End IP address: 192 . 168 . 99 . 210
- Number of addresses: 10

Buttons: OK, Cancel

기존 서버 망의 주소 영역을 지정할 수도 있는데, 다른 DHCP 서버의 주소 영역과 겹치지 않도록 주의해야 한다.


액세스 권한 허용

관리도구 > 컴퓨터 관리



사용자 선택

동작 메뉴 > 속성 > Dial-in



전화접속 로그인 > 네트워크 액세스 권한 > 액세스 허용

라우터(공유기) 설정

PPTP : TCP 1723, IP 47(GRE)

L2TP over IPSEC: UDP 1701, UDP 500, UDP 4500, IP 50(ESP)

SSTP: TCP 443(HTTPS)

IKEv2: UDP1701, UDP 500, UDP 4500, IP 50(ESP)

SSTP 를 사용하므로 TCP 443 만 port forwarding 하면 된다.

SSTP 설정

SELF-SIGNED CERTIFICATE 파일(.PFX) 생성


Visual Studio Command Prompt

```
> makecert -r -pe -sv sj6219.pvk -n "CN=sj6219.cloudapp.net" sj6219.cer
```

암호 공백


```
> pvk2pfx -pvk sj6219.pvk -spc sj6219.cer -pfx sj6219.pfx
```

IIS 관리자




서버 선택 > Server Certificates


Actions > Open Feature



Actions > Import...



동작 메뉴 > 속성 > Security



SSL Certificate Binding > Certificate

Action> All Task> Restart


COMMAND SHELL

> netsh http show ssl



SSL Certificate bindings 에 내용이 제대로 들어가 있는지 확인

윈도우 클라이언트 SSTP 설정

제어판 > 네트워크 및 공유센터



새 연결 또는 네트워크 설정



회사에 연결

연결할 인터넷 주소를 입력하십시오.

네트워크 관리자가 이 주소를 제공할 수 있습니다.

인터넷 주소(I):


sj6219.cloudapp.net

대상 이름(E):

cloud

☐ 스마트 카드 사용(S)

☒ 내 자격 증명 기억(R)

 ☒ 다른 사람이 이 연결을 사용하도록 허용(A)


이 옵션은 이 컴퓨터에 액세스하는 모든 사용자가 이 연결을 사용하도록 허용합니다.

만들기(C)


취소

제어판 > 네트워크 및 공유센터 > 어댑터 설정 변경


속성 > 네트워킹



속성




고급



원격 네트워크에 기본 게이트웨이 사용 > 안 함


보안




VPN 종류 > SSTP

SSTP CERTIFICATE 등록

.CER (또는 .PFX) 파일 실행



저장소 위치 > 로컬 컴퓨터



인증서 저장소 > 신뢰할 수 있는 루트 인증 기관

IPTIME 공유기 서버 L2TP 설정

Iptime > Advanced Setup > Utility > VPN Setup

VPN Setup

PPTP Server ☐ Start ☒ Stop Use Encryption(MPPE) ☐

L2TP Server ☒ Start ☐ Stop PSK ☐ View

VPN Account

Account	IP Address	Status	Discon	Del
sjpark	192.168.111.9	Connected(L2TP)	<input type="checkbox"/>	<input type="checkbox"/>

Add VPN Account

Account sjpark

Password ☐ View

IP Address 192 . 168 . 111 . 9

Max number of VPN user is 10.

WINDOWS CLIENT L2TP SETUP

All Settings > Network & Internet > VPN > VPN Connections > Add VPN

Edit VPN connection

These changes will take effect the next time you connect.

Connection name

Server name or address

VPN type


Pre-shared key

Type of sign-in info

User name (optional)

Password (optional)

Controls > Network and Sharing Center > Change Adapter Settings > iptime > Properties >
Internet Protocol Version 4 > Properties > Advanced >
Use default gateway on remote network : off



ANDROID CLIENT L2TP SETUP

Android 설정 > 연결 > 기타 연결 설정 > VPN > 추가

VPN 네트워크 편집

이름

Iptime

종류

L2TP/IPSec PSK ▾

서버 주소

tower6219.iptime.org

L2TP 비밀 키

사용 안 함



IPSec 식별자

사용 안 함

IPsec 사전 공유 키

.....

☐ 고급 옵션 표시

사용자 이름

sjpark

비밀번호

.....

☐ VPN 항상 켜기

VPN 항상 켜기 설정은 숫자로 된 DNS 서버 주소만 사용할 수 있습니다.

[삭제](#)

[취소](#)

[저장](#)