


Topology Diagram



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	Fa0/0	172.30.1.1	255.255.255.0	N/A
	Fa0/1	172.30.2.1	255.255.255.0	N/A
	S0/0/0	209.165.200.230	255.255.255.252	N/A
R2	Fa0/0	10.1.0.1	255.255.0.0	N/A
	S0/0/0	209.165.200.229	255.255.255.252	N/A
	S0/0/1	209.165.200.233	255.255.255.252	N/A
R3	Fa0/0	172.30.100.1	255.255.255.0	N/A
	S0/0/1	209.165.200.234	255.255.255.252	N/A
	Lo0	172.30.110.1	255.255.255.0	N/A
	Lo1	172.30.200.17	255.255.255.240	N/A
	Lo2	172.30.200.33	255.255.255.240	N/A
PC1	NIC	172.30.1.10	255.255.255.0	172.30.2.1
PC2	NIC	172.30.2.10	255.255.255.0	172.30.1.1
PC3	NIC	10.1.0.10	255.255.0.0	10.1.0.1
PC4	NIC	172.30.100.10	255.255.255.0	172.30.100.1

## Learning Objectives

Upon completion of this lab, you will be able to:

- Cable a network according to the Topology Diagram.
- Load provided scripts onto the routers.
- Examine the current status of the network.
- Configure RIPv2 on all routers.
- Examine the automatic summarization of routes.
- Examine routing updates with `debug ip rip`.
- Disable automatic summarization.
- Examine the routing tables.
- Verify network connectivity.
- Document the RIPv2 configuration.


## Scenario

The network shown in the Topology Diagram contains a discontinuous network, 172.30.0.0. This network has been subnetted using VLSM. The 172.30.0.0 subnets are physically and logically divided by at least one other classful or major network, in this case the two serial networks 209.165.200.228/30 and 209.165.200.232/30. This can be an issue when the routing protocol used does not include enough information to distinguish the individual subnets. RIPv2 is a classless routing protocol that can be used to provide subnet mask information in the routing updates. This will allow VLSM subnet information to be propagated throughout the network.

### Task 1: Cable, Erase, and Reload the Routers.

#### Step 1: Cable a network.

Cable a network that is similar to the one in the Topology Diagram.



Cisco Packet Tracer

File Edit Options View Tools Extensions Help

Logical Physical x: 623, y: 443 [Root] 12:16:00

IP Address	IPv6 Address	MAC Address
172.30.100.1/24	<not set>	0030.F2A6.5B01
<not set>	<not set>	0030.F2A6.5B02
<not set>	<not set>	<not set>
209.165.200.234/30	<not set>	<not set>
172.30.110.1/24	<not set>	000A.F378.6428
172.30.200.17/28	<not set>	0001.6342.95A8
172.30.200.33/28	<not set>	000D.BD98.0888
<not set>	<not set>	0005.5EA4.3A31

Home City, Corporate Office, Main Wiring Closet


Time: 01:11:21


Realtime Simulation

Automatically Choose Connection Type

## Step 2: Clear the configuration on each router.

Clear the configuration on each of routers using the **erase startup-config** command and then **reload** the routers. Answer **no** if asked to save changes.





Physical Config CLI Attributes

## IOS Command Line Interface

```
Router#
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
Router#
%SYS-5-CONFIG_I: Configured from console by console
erase startup-config
Erasing the nvram filesystem will remove all configuration files!
Continue? [confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
Router#reload
System configuration has been modified. Save? [yes/no]:no
Proceed with reload? [confirm]
System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fcl)
Initializing memory for ECC
..
C1841 processor with 524288 Kbytes of main memory
Main memory is configured to 64 bit mode with ECC enabled

Readonly ROMMON initialized


Self decompressing the image :
#####
```

Ctrl+F6 to exit CLI focus

Copy

Paste





## Task 2: Load Routers with the Supplied Scripts.

### Step 1: Load the following script onto R1.

```
!  
hostname R1
```

```
!  
!  
!  
interface FastEthernet0/0  
ip address 172.30.1.1 255.255.255.0  
duplex auto  
speed auto  
no shutdown  
!  
interface FastEthernet0/1  
ip address 172.30.2.1 255.255.255.0  
duplex auto  
speed auto  
no shutdown  
!  
interface Serial0/0/0  
ip address 209.165.200.230 255.255.255.252  
clock rate 64000  
no shutdown  
!  
router rip  
passive-interface FastEthernet0/0  
passive-interface FastEthernet0/1  
network 172.30.0.0  
network 209.165.200.0  
!  
line con 0  
line vty 0 4  
login  
!  
end
```



```
Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R1
R1(config)#interface FastEthernet0/0
R1(config-if)#ip address 172.30.1.1 255.255.255.0
R1(config-if)#duplex auto
R1(config-if)#speed auto
R1(config-if)# no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
exit
R1(config)#interface FastEthernet0/1
R1(config-if)#ip address 172.30.2.1 255.255.255.0
R1(config-if)# duplex auto
R1(config-if)# speed auto
R1(config-if)# no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
quit
^
% Invalid input detected at '^' marker.

R1(config-if)#quit
^
% Invalid input detected at '^' marker.

R1(config-if)#exit
R1(config)#interface Serial0/0/0
R1(config-if)#ip address 209.165.200.230 255.255.255.252
R1(config-if)# clock rate 64000
This command applies only to DCE interfaces
R1(config-if)# no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
R1(config-if)#exit
R1(config)#router rip
R1(config-router)#passive-interface FastEthernet0/0
R1(config-router)# passive-interface FastEthernet0/1
R1(config-router)# network 172.30.0.0
R1(config-router)# network 209.165.200.0
R1(config-router)#exit
R1(config)#line con 0
R1(config-line)#line vty 0 4
R1(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
```

Ctrl+F6 to exit CLI focus

```
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
R1(config-if)#exit
R1(config)#router rip
R1(config-router)#passive-interface FastEthernet0/0
R1(config-router)# passive-interface FastEthernet0/1
R1(config-router)# network 172.30.0.0
R1(config-router)# network 209.165.200.0
R1(config-router)#exit
R1(config)#line con 0
R1(config-line)#line vty 0 4
R1(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R1(config-line)#password password
R1(config-line)#login
R1(config-line)#end
R1#
%SYS-5-CONFIG_I: Configured from console by console
```

Ctrl+F6 to exit CLI focus

☐ Top

## Step 2: Load the following script onto R2.

```
hostname R2
!
!
!
interface FastEthernet0/0
ip address 10.1.0.1 255.255.0.0
duplex auto
speed auto
no shutdown
!
interface Serial0/0/0
ip address 209.165.200.229 255.255.255.252
no shutdown
!
interface Serial0/0/1
ip address 209.165.200.233 255.255.255.252
clock rate 64000
no shutdown
!
router rip
passive-interface FastEthernet0/0
network 10.0.0.0
network 209.165.200.0
!
line con 0
line vty 0 4
login
!
End
```

```

Router>
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R2
R2(config)#interface FastEthernet0/0
R2(config-if)#ip address 10.1.0.1 255.255.0.0
R2(config-if)# duplex auto
R2(config-if)# speed auto
R2(config-if)# no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
exit
R2(config)#interface Serial0/0/0
R2(config-if)#ip address 209.165.200.229 255.255.255.252
R2(config-if)# no shutdown

R2(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
exit
R2(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up

R2(config)#interface Serial0/0/0
R2(config-if)#ip address 209.165.200.229 255.255.255.252
R2(config-if)# no shutdown
R2(config-if)#exit
R2(config)#interface Serial0/0/1
R2(config-if)#ip address 209.165.200.233 255.255.255.252
R2(config-if)# clock rate 64000
R2(config-if)# no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
R2(config-if)#exit
R2(config)#router rip
R2(config-router)#passive-interface FastEthernet0/0
R2(config-router)# network 10.0.0.0
R2(config-router)# network 209.165.200.0
R2(config-router)#exit
R2(config)#line con 0
R2(config-line)#line vty 0 4
R2(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R2(config-line)#password password
R2(config-line)#login
R2(config-line)#end
R2#
%SYS-5-CONFIG_I: Configured from console by console

```

Ctrl+F6 to exit CLI focus

☐ Top


### Step 3: Load the following script onto R3.

```
hostname R3
```

```

!
!
!
interface FastEthernet0/0
ip address 172.30.100.1 255.255.255.0
duplex auto
speed auto
no shutdown
!
interface Serial0/0/1
ip address 209.165.200.234 255.255.255.252
no shutdown
!
interface Loopback0
ip address 172.30.110.1 255.255.255.0
!
interface Loopback1
ip address 172.30.200.17 255.255.255.240
!
interface Loopback2
ip address 172.30.200.33 255.255.255.240
!
router rip
passive-interface FastEthernet0/0
network 172.30.0.0
network 209.165.200.0
!
line con 0
line vty 0 4
login
!
End

```



Physical Config CLI Attributes

```

Router>
Router>
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R3
R3(config)#interface FastEthernet0/0
R3(config-if)#ip address 172.30.100.1 255.255.255.0
R3(config-if)# duplex auto
R3(config-if)# speed auto
R3(config-if)# no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
exit
R3(config)#interface Serial0/0/1
R3(config-if)#ip address 209.165.200.234 255.255.255.252
R3(config-if)# no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
exit
R3(config)#interface Loopback0
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to up

```



```
R3(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
exit
R3(config)#interface Serial0/0/1
R3(config-if)#ip address 209.165.200.234 255.255.255.252
R3(config-if)# no shutdown

R3(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
exit
R3(config)#interface Loopback0
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to up

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up
ip address 172.30.110.1 255.255.255.0
R3(config-if)#exit
R3(config)#interface Loopback1

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback1, changed state to up
ip address 172.30.200.17 255.255.255.240
R3(config-if)#exit
R3(config)#interface Loopback2

R3(config-if)#
%LINK-5-CHANGED: Interface Loopback2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback2, changed state to up
ip address 172.30.200.33 255.255.255.240
R3(config-if)#exit
R3(config)#router rip
R3(config-router)#passive-interface FastEthernet0/0
R3(config-router)# network 172.30.0.0
R3(config-router)# network 209.165.200.0
R3(config-router)#exit
R3(config)#line con 0
R3(config-line)#line vty 0 4
R3(config-line)#login
% Login disabled on line 194, until 'password' is set
% Login disabled on line 195, until 'password' is set
% Login disabled on line 196, until 'password' is set
% Login disabled on line 197, until 'password' is set
% Login disabled on line 198, until 'password' is set
R3(config-line)#password password
R3(config-line)#login
R3(config-line)#end
```

Ctrl+F6 to exit CLI focus

☐ Top

### Task 3: Examine the Current Status of the Network.

#### Step 1: Verify that both serial links are up.

The two serial links can quickly be verified using the `show ip interface brief` command on R2.

```
R2#show ip interface brief
```

Router2

PhysicalConfigCLIAttributes

IOS Command Line Interface

```
% Invalid input detected at '^' marker.

R2 (config) #quit
^
% Invalid input detected at '^' marker.

R2 (config) #
R2 #
%SYS-5-CONFIG_I: Configured from console by console

R2 #show ip interface brief
Interface                IP-Address      OK? Method Status
Protocol
FastEthernet0/0          10.1.0.1        YES manual up
up
FastEthernet0/1          unassigned      YES NVRAM
administratively down down
Serial0/0/0              209.165.200.229 YES manual up
up
Serial0/0/1              209.165.200.233 YES manual up
up
Vlan1                    unassigned      YES NVRAM
administratively down down
R2 #
```

Ctrl+F6 to exit CLI focus

CopyPaste

☐ Top


## Step 2: Check the connectivity from R2 to the hosts on the R1 and R3 LANs.

Note: For the 1841 router, you will need to disable IP CEF to obtain the correct output from the `ping` command. Although a discussion of IP CEF is beyond the scope of this course, you may disable IP CEF by using the following command in global configuration mode:

```
R2 (config) #no ip cef
```



From the R2 router, how many ICMP messages are successful when pinging PC1?



```
Router2
Physical Config CLI Attributes
IOS Command Line Interface
up
Vlan1 unassigned YES NVRAM
administratively down down
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#no ip cef
R2(config)#exit
^
% Invalid input detected at '^' marker.
R2(config)#exit
R2#
%SYS-5-CONFIG_I: Configured from console by console
ping 172.30.1.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.30.1.10, timeout is 2
seconds:
.U!..!
Success rate is 40 percent (2/5), round-trip min/avg/max = 1/6/11
ms


R2#
R2#
R2#
```

Ctrl+F6 to exit CLI focus

Copy Paste

Hence 2 packets were received

From the R2 router, how many ICMP messages are successful when pinging PC4?



```
Router2
Physical Config CLI Attributes
IOS Command Line Interface
R2(config)#exit
R2#
%SYS-5-CONFIG_I: Configured from console by console
ping 172.30.1.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.30.1.10, timeout is 2
seconds:
.U!..!
Success rate is 40 percent (2/5), round-trip min/avg/max = 1/6/11
ms

R2#
R2#
R2#ping 172.30.100.10

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.30.100.10, timeout is 2
seconds:
.U!..!
Success rate is 40 percent (2/5), round-trip min/avg/max = 1/3/5
ms

R2#
```

Ctrl+F6 to exit CLI focus


Copy Paste

☐ Top

Hence 2 packets were received

### Step 3: Check the connectivity between the PCs.

From the PC1, is it possible to ping PC2?



```
PC1
Physical Config Desktop Programming Attributes
Command Prompt

Packet Tracer PC Command Line 1.0
C:\>ping 172.30.2.10

Pinging 172.30.2.10 with 32 bytes of data:

Request timed out.
Reply from 172.30.2.10: bytes=32 time<1ms TTL=127
Reply from 172.30.2.10: bytes=32 time<1ms TTL=127
Reply from 172.30.2.10: bytes=32 time<1ms TTL=127


Ping statistics for 172.30.2.10:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>
```

What is the success rate?

75 % as 1 packet is loss

From the PC1, is it possible to ping PC3?



```
C:\>ping 10.1.0.10

Pinging 10.1.0.10 with 32 bytes of data:

Request timed out.
Reply from 10.1.0.10: bytes=32 time=2ms TTL=126
Request timed out.
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126

Ping statistics for 10.1.0.10:
    Packets: Sent = 4, Received = 2, Lost = 2 (50% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 2ms, Average = 1ms

C:\>
```

What is the success rate?

50 % as 2 packet is loss

From the PC1, is it possible to ping PC4?

```
C:\>ping 172.30.100.10

Pinging 172.30.100.10 with 32 bytes of data:


Reply from 172.30.1.1: Destination host unreachable.
Reply from 172.30.1.1: Destination host unreachable.
Reply from 172.30.1.1: Destination host unreachable.
Reply from 172.30.1.1: Destination host unreachable.

Ping statistics for 172.30.100.10:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
|
C:\>
```

What is the success rate?

0 %

From the PC4, is it possible to ping PC2?

The image shows a screenshot of a Packet Tracer interface. At the top, there's a tab bar with 'Physical', 'Config', 'Desktop' (selected), 'Programming', and 'Attributes'. Below the tabs, a 'Command Prompt' window is open. The text in the Command Prompt is as follows:

```
Packet Tracer PC Command Line 1.0
C:\>ping 172.30.2.10

Pinging 172.30.2.10 with 32 bytes of data:

Reply from 172.30.100.1: Destination host unreachable.
Request timed out.
Reply from 172.30.100.1: Destination host unreachable.
Reply from 172.30.100.1: Destination host unreachable.

Ping statistics for 172.30.2.10:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
```

What is the success rate?

0 %

```

C:\>ping 10.1.0.10

Pinging 10.1.0.10 with 32 bytes of data:

Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Request timed out.
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Request timed out.

Ping statistics for 10.1.0.10:
    Packets: Sent = 4, Received = 2, Lost = 2 (50% loss)
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 1ms, Average = 1ms

```

From the PC4, is it possible to ping PC3?

What is the success rate?

50 %

#### Step 4: View the routing table on R2.

Both the R1 and R3 are advertising routes to the 172.30.0.0/16 network; therefore, there are two entries for this network in the R2 routing table. The R2 routing table only shows the major classful network address of 172.30.0.0—it does not show any of the subnets for this network that are used on the LANs attached to R1 and R3. Because the routing metric is the same for both entries, the router alternates the routes that are used when forwarding packets that are destined for the 172.30.0.0/16 network.

R2#show ip route

```

R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

 10.0.0.0/16 is subnetted, 1 subnets
C       10.1.0.0 is directly connected, FastEthernet0/0
R       172.30.0.0/16 [120/1] via 209.165.200.230, 00:00:21, Serial0/0/0
           [120/1] via 209.165.200.234, 00:00:15, Serial0/0/1
 209.165.200.0/30 is subnetted, 2 subnets
C       209.165.200.228 is directly connected, Serial0/0/0
C       209.165.200.232 is directly connected, Serial0/0/1

R2#

```

Ctrl+F6 to exit CLI focus

### Step 5: Examine the routing table on the R1 router.

Both R1 and R3 are configured with interfaces on a discontinuous network, 172.30.0.0. The 172.30.0.0 subnets are physically and logically divided by at least one other classful or major network—in this case, the two serial networks 209.165.200.228/30 and 209.165.200.232/30. Classful routing protocols like RIPv1 summarize networks at major network boundaries. Both R1 and R3 will be summarizing 172.30.0.0/24 subnets to 172.30.0.0/16. Because the route to 172.30.0.0/16 is directly connected, and because R1 does not have any specific routes for the 172.30.0.0 subnets on R3, packets destined for the R3 LANs will not be forwarded properly.

```
R1#show ip route
```

```
R1>
R1>en
R1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

R    10.0.0.0/8 [120/1] via 209.165.200.229, 00:00:13, Serial0/0/0
    172.30.0.0/24 is subnetted, 2 subnets
C      172.30.1.0 is directly connected, FastEthernet0/0
C      172.30.2.0 is directly connected, FastEthernet0/1
    209.165.200.0/30 is subnetted, 2 subnets
C      209.165.200.228 is directly connected, Serial0/0/0
R      209.165.200.232 [120/1] via 209.165.200.229, 00:00:13, Serial0/0/0

R1#
```

Ctrl+F6 to exit CLI focus

☐ Top

### Step 6: Examine the routing table on the R3 router.

R3 only shows its own subnets for 172.30.0.0 network: 172.30.100/24, 172.30.110/24, 172.30.200.16/28, and 172.30.200.32/28. R3 does not have any routes for the 172.30.0.0 subnets on R1.

```
R3#show ip route
```



```

R3>
R3>en
R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

R    10.0.0.0/8 [120/1] via 209.165.200.233, 00:00:20, Serial0/0/1
    172.30.0.0/16 is variably subnetted, 4 subnets, 2 masks
C    172.30.100.0/24 is directly connected, FastEthernet0/0
C    172.30.110.0/24 is directly connected, Loopback0
C    172.30.200.16/28 is directly connected, Loopback1
C    172.30.200.32/28 is directly connected, Loopback2
    209.165.200.0/30 is subnetted, 2 subnets
R    209.165.200.228 [120/1] via 209.165.200.233, 00:00:20, Serial0/0/1
C    209.165.200.232 is directly connected, Serial0/0/1

R3#

```

Ctrl+F6 to exit CLI focus

☐ Top

### Step 7: Examine the RIPv1 packets that are being received by R2.

Use the `debug ip rip` command to display RIP routing updates.

R2 is receiving the route 172.30.0.0, with 1 hop, from both R1 and R3. Because these are equal cost metrics, both routes are added to the R2 routing table. Because RIPv1 is a classful routing protocol, no subnet mask information is sent in the update.

R2#`debug ip rip`

R2 is sending only the routes for the 10.0.0.0 LAN and the two serial connections to R1 and R3. R1 and R3 are not receiving any information about the 172.30.0.0 subnet routes.

When you are finished, turn off the debugging. R2#`undebug all`

```

R2>
R2>
R2>en
R2#debug ip rip
RIP protocol debugging is on
R2#undebug all
All possible debugging has been turned off
R2#

```

Ctrl+F6 to exit CLI focus



## Task 4: Configure RIP Version 2.

**Step 1: Use the `version 2` command to enable RIP version 2 on each of the routers.**

```
R2(config)#router rip
R2(config-router)#version 2
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#router rip
R2(config-router)#version 2
R2(config-router)#
```

```
R1(config)#router rip
R1(config-router)#version 2
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#router rip
R1(config-router)#version 2
R1(config-router)#
```

```
R3(config)#router rip
R3(config-router)#version 2
R3#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#router rip
R3(config-router)#versio 2
R3(config-router)#version 2
R3(config-router)#
```

RIPv2 messages include the subnet mask in a field in the routing updates. This allows subnets and their masks to be included in the routing updates. However, by default RIPv2 summarizes networks at major network boundaries, just like RIPv1, except that the subnet mask is included in the update.

**Step 2: Verify that RIPv2 is running on the routers.**

The `debug ip rip`, `show ip protocols`, and `show run` commands can all be used to confirm that RIPv2 is running. The output of the `show ip protocols` command for R1 is shown below.

```
R1# show ip protocols
```

```
R1#
R1#show ip protocols
Routing Protocol is "rip"
Sending updates every 30 seconds, next due in 18 seconds
Invalid after 180 seconds, hold down 180, flushed after 240
Outgoing update filter list for all interfaces is not set
Incoming update filter list for all interfaces is not set
Redistributing: rip
Default version control: send version 2, receive 2
  Interface          Send Recv Triggered RIP Key-chain
  Serial0/0/0         2    2
Automatic network summarization is in effect
Maximum path: 4
Routing for Networks:
  172.30.0.0
  209.165.200.0
Passive Interface(s):
  FastEthernet0/0
  FastEthernet0/1
Routing Information Sources:
  Gateway         Distance      Last Update
  209.165.200.229    120          00:00:08
Distance: (default is 120)
```

## Task 5: Examine the Automatic Summarization of Routes.

The LANs connected to R1 and R3 are still composed of discontinuous networks. R2 still shows two equal cost paths to the 172.30.0.0/16 network in the routing table. R2 still shows only the major classful network address of 172.30.0.0 and does not show any of the subnets for this network.

R2#**show ip route**

```
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/16 is subnetted, 1 subnets
C    10.1.0.0 is directly connected, FastEthernet0/0
R    172.30.0.0/16 [120/1] via 209.165.200.230, 00:00:19, Serial0/0/0
      [120/1] via 209.165.200.234, 00:00:16, Serial0/0/1
209.165.200.0/30 is subnetted, 2 subnets
C    209.165.200.228 is directly connected, Serial0/0/0
C    209.165.200.232 is directly connected, Serial0/0/1

R2#
```

R1 still shows only its own subnets for the 172.30.0.0 network. R1 still does not have any routes for the 172.30.0.0 subnets on R3.

R1#**show ip route**

```
R1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

R    10.0.0.0/8 [120/1] via 209.165.200.229, 00:00:01, Serial0/0/0
172.30.0.0/24 is subnetted, 2 subnets
C    172.30.1.0 is directly connected, FastEthernet0/0
C    172.30.2.0 is directly connected, FastEthernet0/1
209.165.200.0/30 is subnetted, 2 subnets
C    209.165.200.228 is directly connected, Serial0/0/0
R    209.165.200.232 [120/1] via 209.165.200.229, 00:00:01, Serial0/0/0

R1#
```

R3 still only shows its own subnets for the 172.30.0.0 network. R3 still does not have any routes for the 172.30.0.0 subnets on R1.

R3#**show ip route**

```

R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

R    10.0.0.0/8 [120/1] via 209.165.200.233, 00:00:22, Serial0/0/1
    172.30.0.0/16 is variably subnetted, 4 subnets, 2 masks
C    172.30.100.0/24 is directly connected, FastEthernet0/0
C    172.30.110.0/24 is directly connected, Loopback0
C    172.30.200.16/28 is directly connected, Loopback1
C    172.30.200.32/28 is directly connected, Loopback2
    209.165.200.0/30 is subnetted, 2 subnets
R    209.165.200.228 [120/1] via 209.165.200.233, 00:00:22, Serial0/0/1
C    209.165.200.232 is directly connected, Serial0/0/1

R3#

```

Use the output of the **debug ip rip** command to answer the following questions:  
 What entries are included in the RIP updates sent out from R3?

```

R3>
R3>enable
R3#debug ip rip
RIP protocol debugging is on
R3#RIP: sending v2 update to 224.0.0.9 via Loopback0
(172.30.110.1)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
    172.30.100.0/24 via 0.0.0.0, metric 1, tag 0
    172.30.200.16/28 via 0.0.0.0, metric 1, tag 0
    172.30.200.32/28 via 0.0.0.0, metric 1, tag 0
    209.165.200.0/24 via 0.0.0.0, metric 1, tag 0
RIP: sending v2 update to 224.0.0.9 via Loopback1
(172.30.200.17)
RIP: build update entries
    10.0.0.0/8 via 0.0.0.0, metric 2, tag 0
    172.30.100.0/24 via 0.0.0.0, metric 1, tag 0

```


Ctrl+F6 to exit CLI focus

Copy

Paste

10.0.0.0/8  
 172.30.100.0/24  
 172.30.110.0/24  
 172.30.200.16/28  
 209.165.200.0/24

On R2, what routes are in the RIP updates that are received from R3?



The screenshot shows the CLI of Router2. The 'CLI' tab is selected. The output shows the RIP protocol debugging is enabled. It displays a received v2 update from 209.165.200.230 on Serial0/0/0 for the 172.30.0.0/16 network. It also shows the router sending a v2 update to 224.0.0.9 via Serial0/0/0 for the same network. The build update entries section shows the 10.0.0.0/8 and 209.165.200.232/30 networks being summarized.

```
Router2
Physical Config CLI Attributes
IOS Command Line Interface
changed state to up

R2>
R2>
R2>enable
R2#debug ip rip
RIP protocol debugging is on
R2#RIP: received v2 update from 209.165.200.230 on Serial0/0/0
      172.30.0.0/16 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.229)
RIP: build update entries
      10.0.0.0/8 via 0.0.0.0, metric 1, tag 0
      209.165.200.232/30 via 0.0.0.0, metric 1, tag 0
```


**172.30.0.0/16**

R3 is not sending any of the 172.30.0.0 subnets—only the summarized route of 172.30.0.0/16, including the subnet mask. This is why R2 and R1 are not seeing the 172.30.0.0 subnets on R3.

### Task 6: Disable Automatic Summarization.

The **no auto-summary** command is used to turn off automatic summarization in RIPv2. Disable auto summarization on all routers. The routers will no longer summarize routes at major network boundaries.

```
R2(config)#router rip
R2(config-router)#no auto-summary
```



The screenshot shows the CLI of Router2. The output shows the router debugging is turned off. The configuration mode is entered, and the **no auto-summary** command is entered under the **router rip** configuration.

```
R2#
R2#undebg all
All possible debugging has been turned off
R2#en
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#router rip
R2(config-router)#no auto-summary
R2(config-router)#
```

Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top

```
R1(config)#router rip
R1(config-router)#no auto-summary
```



```
R1>
R1>
R1>
R1>
R1>enable
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#router rip
R1(config-router)#no auto-summary
R1(config-router)#
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

```
R3(config)#router rip
R3(config-router)#no auto-summary
```

```
R3>
R3>
R3>
R3>
R3>enable
R3#undebg all
All possible debugging has been turned off
R3#
R3#
R3#
R3#en
R3#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R3(config)#router rip
R3(config-router)#no auto-summary
R3(config-router)#
```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

The **show ip route** and **ping** commands can be used to verify that automatic summarization is off.

### Task 7: Examine the Routing Tables.

The LANs connected to R1 and R3 should now be included in all three routing tables.

```
R2#show ip route
```

```

R2#
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

```

Gateway of last resort is not set

```

      10.0.0.0/16 is subnetted, 1 subnets
C       10.1.0.0 is directly connected, FastEthernet0/0
      172.30.0.0/16 is variably subnetted, 7 subnets, 3 masks
R       172.30.0.0/16 [120/1] via 209.165.200.230, 00:02:09, Serial0/0/0
          [120/1] via 209.165.200.234, 00:02:03, Serial0/0/1
R       172.30.1.0/24 [120/1] via 209.165.200.230, 00:00:23, Serial0/0/0
R       172.30.2.0/24 [120/1] via 209.165.200.230, 00:00:23, Serial0/0/0
R       172.30.100.0/24 [120/1] via 209.165.200.234, 00:00:12, Serial0/0/1
R       172.30.110.0/24 [120/1] via 209.165.200.234, 00:00:12, Serial0/0/1
R       172.30.200.16/28 [120/1] via 209.165.200.234, 00:00:12, Serial0/0/1
R       172.30.200.32/28 [120/1] via 209.165.200.234, 00:00:12, Serial0/0/1
      209.165.200.0/30 is subnetted, 2 subnets
--More--

```

Ctrl+F6 to exit CLI focus

☐ Top

R1#show ip route

```

R1#
R1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

```

Gateway of last resort is not set

```

      10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
R       10.0.0.0/8 is possibly down, routing via 209.165.200.229, Serial0/0/0
R       10.1.0.0/16 [120/1] via 209.165.200.229, 00:00:12, Serial0/0/0
      172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
C       172.30.1.0/24 is directly connected, FastEthernet0/0
C       172.30.2.0/24 is directly connected, FastEthernet0/1
R       172.30.100.0/24 [120/2] via 209.165.200.229, 00:00:12, Serial0/0/0
R       172.30.110.0/24 [120/2] via 209.165.200.229, 00:00:12, Serial0/0/0
R       172.30.200.16/28 [120/2] via 209.165.200.229, 00:00:12, Serial0/0/0
R       172.30.200.32/28 [120/2] via 209.165.200.229, 00:00:12, Serial0/0/0
      209.165.200.0/30 is subnetted, 2 subnets
C       209.165.200.228 is directly connected, Serial0/0/0
--More--

```

Ctrl+F6 to exit CLI focus

☐ Top

R3#show ip route



```

R3#
R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
R    10.0.0.0/8 is possibly down, routing via 209.165.200.233, Serial0/0/1
R    10.1.0.0/16 [120/1] via 209.165.200.233, 00:00:18, Serial0/0/1
172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
R    172.30.1.0/24 [120/2] via 209.165.200.233, 00:00:18, Serial0/0/1
R    172.30.2.0/24 [120/2] via 209.165.200.233, 00:00:18, Serial0/0/1
C    172.30.100.0/24 is directly connected, FastEthernet0/0
C    172.30.110.0/24 is directly connected, Loopback0
C    172.30.200.16/28 is directly connected, Loopback1
C    172.30.200.32/28 is directly connected, Loopback2
209.165.200.0/30 is subnetted, 2 subnets
R    209.165.200.228 [120/1] via 209.165.200.233, 00:00:18, Serial0/0/1
--More--

```

Ctrl+F6 to exit CLI focus

☐ Top

Use the output of the `debug ip rip` command to answer the following questions:

What entries are included in the RIP updates sent out from R1?

```

R1#debug ip rip
RIP protocol debugging is on
R1#RIP: received v2 update from 209.165.200.229 on Serial0/0/0
    10.1.0.0/16 via 0.0.0.0 in 1 hops
    172.30.100.0/24 via 0.0.0.0 in 2 hops
    172.30.110.0/24 via 0.0.0.0 in 2 hops
    172.30.200.16/28 via 0.0.0.0 in 2 hops
    172.30.200.32/28 via 0.0.0.0 in 2 hops
    209.165.200.232/30 via 0.0.0.0 in 1 hops
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0
(209.165.200.230)
RIP: build update entries
    172.30.1.0/24 via 0.0.0.0, metric 1, tag 0
    172.30.2.0/24 via 0.0.0.0, metric 1, tag 0

```

Ctrl+F6 to exit CLI focus

Copy

Paste

☐ Top

**172.30.1.0/24**

**172.30.2.0/24**

On R2, what routes are in the RIP updates that are received from R1?

```
R2#  
R2#  
R2#debug ip rip  
RIP protocol debugging is on  
R2#RIP: received v2 update from 209.165.200.234 on Serial0/0/1  
    172.30.100.0/24 via 0.0.0.0 in 1 hops  
    172.30.110.0/24 via 0.0.0.0 in 1 hops  
    172.30.200.16/28 via 0.0.0.0 in 1 hops  
    172.30.200.32/28 via 0.0.0.0 in 1 hops  
RIP: received v2 update from 209.165.200.230 on Serial0/0/0  
    172.30.1.0/24 via 0.0.0.0 in 1 hops  
    172.30.2.0/24 via 0.0.0.0 in 1 hops  
RIP: sending v2 update to 224.0.0.9 via Serial0/0/0  
(209.165.200.229)
```

**172.30.1.0/24**

**172.30.2.0/24**

Are the subnet masks now included in the routing updates?

**Yes**

### **Task 8: Verify Network Connectivity.**

#### **Step 1: Check connectivity between R2 router and PCs.**

From R2, how many ICMP messages are successful when pinging PC1?


---

From R2, how many ICMP messages are successful when pinging PC4?

```
Type escape sequence to abort.  
Sending 5, 100-byte ICMP Echos to 172.30.100.10, timeout is 2  
seconds:  
.!!!!  
Success rate is 80 percent (4/5), round-trip min/avg/max = 1/1/2  
ms
```

#### **Step 2: Check the connectivity between the PCs.**

From PC1, is it possible to ping PC2?



PC1

Physical Config **Desktop** Programming Attributes

Command Prompt

```
Packet Tracer PC Command Line 1.0
C:\>ping 172.30.1.10

Pinging 172.30.1.10 with 32 bytes of data:


Reply from 172.30.1.10: bytes=32 time=3ms TTL=128
Reply from 172.30.1.10: bytes=32 time=3ms TTL=128
Reply from 172.30.1.10: bytes=32 time<1ms TTL=128
Reply from 172.30.1.10: bytes=32 time=2ms TTL=128

Ping statistics for 172.30.1.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 3ms, Average = 2ms
```

What is the success rate?

**100 %**

From PC1, is it possible to ping PC3?



```
C:\>ping 10.1.0.10

Pinging 10.1.0.10 with 32 bytes of data:

Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Reply from 10.1.0.10: bytes=32 time=4ms TTL=126
Reply from 10.1.0.10: bytes=32 time=14ms TTL=126

Ping statistics for 10.1.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 14ms, Average = 5ms

C:\>
```

What is the success rate?

**100 %**

From PC1, is it possible to ping PC4?

```
C:\>ping 172.30.100.10
```

```
Pinging 172.30.100.10 with 32 bytes of data:
```

```
Reply from 172.30.100.10: bytes=32 time=3ms TTL=125
```

```
Reply from 172.30.100.10: bytes=32 time=2ms TTL=125
```

```
Reply from 172.30.100.10: bytes=32 time=2ms TTL=125
```

```
Reply from 172.30.100.10: bytes=32 time=2ms TTL=125
```

```
Ping statistics for 172.30.100.10:
```

```
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
```

```
Approximate round trip times in milli-seconds:
```

```
    Minimum = 2ms, Maximum = 3ms, Average = 2ms
```

```
C:\>|
```

☐ Top

What is the success rate?

**100 %**

From PC4, is it possible to ping PC2?

 PC4

Physical Config Desktop Programming Attributes

Command Prompt

```
Packet Tracer PC Command Line 1.0
```

```
C:\>ping 172.30.1.10
```

```
Pinging 172.30.1.10 with 32 bytes of data:
```

```
Reply from 172.30.1.10: bytes=32 time=4ms TTL=125
```

```
Reply from 172.30.1.10: bytes=32 time=2ms TTL=125
```

```
Reply from 172.30.1.10: bytes=32 time=2ms TTL=125
```

```
Reply from 172.30.1.10: bytes=32 time=2ms TTL=125
```

```
Ping statistics for 172.30.1.10:
```

```
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
```

```
Approximate round trip times in milli-seconds:
```

```
    Minimum = 2ms, Maximum = 4ms, Average = 2ms
```

What is the success rate?

**100 %**



From PC4, is it possible to ping PC3?

```
C:\>ping 10.1.0.10

Pinging 10.1.0.10 with 32 bytes of data:

Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Reply from 10.1.0.10: bytes=32 time=3ms TTL=126
Reply from 10.1.0.10: bytes=32 time=1ms TTL=126
Reply from 10.1.0.10: bytes=32 time=2ms TTL=126

Ping statistics for 10.1.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 3ms, Average = 1ms
```

What is the success rate?

**100 %**

### Task 9: Documentation

On each router, capture the following command output to a text (.txt) file and save for future reference.

- **show running-config**
- **show ip route**
- **show ip interface brief**
- **show ip protocols**

If you need to review the procedures for capturing command output, refer to Lab 1.5.1.

R1:

- **show running-config**

```
R1#show running-config
Building configuration...
```

```
Current configuration : 886 bytes
!
version 12.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R1
!
!
!
!
!
!
!
no ip cef
no ipv6 cef
!
```

!

- **show ip route**

```
R1#sh ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
```

Gateway of last resort is not set

```
10.0.0.0/16 is subnetted, 1 subnets
R 10.1.0.0 [120/1] via 209.165.200.229, 00:00:05, Serial0/0/0
172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks
C 172.30.1.0/24 is directly connected, FastEthernet0/0
C 172.30.2.0/24 is directly connected, FastEthernet0/1
R 172.30.100.0/24 [120/2] via 209.165.200.229, 00:00:05, Serial0/0/0
R 172.30.110.0/24 [120/2] via 209.165.200.229, 00:00:05, Serial0/0/0
R 172.30.200.16/28 [120/2] via 209.165.200.229, 00:00:05, Serial0/0/0
R 172.30.200.32/28 [120/2] via 209.165.200.229, 00:00:05, Serial0/0/0
209.165.200.0/30 is subnetted, 2 subnets
C 209.165.200.228 is directly connected, Serial0/0/0
R 209.165.200.232 [120/1] via 209.165.200.229, 00:00:05, Serial0/0/0
--More--
```

- **show ip interface brief**

```
R1#show ip interface brief
Interface IP-Address OK? Method Status Protocol
FastEthernet0/0 172.30.1.1 YES manual up up
FastEthernet0/1 172.30.2.1 YES manual up up
Serial0/0/0 209.165.200.230 YES manual up up
Serial0/0/1 unassigned YES NVRAM administratively down down
Vlan1 unassigned YES unset administratively down down
```

- **show ip protocols**

```
R1#sh ip protocols
Routing Protocol is "rip"
Sending updates every 30 seconds, next due in 20 seconds
Invalid after 180 seconds, hold down 180, flushed after 240
Outgoing update filter list for all interfaces is not set
Incoming update filter list for all interfaces is not set
Redistributing: rip
Default version control: send version 2, receive 2
Interface Send Recv Triggered RIP Key-chain
Serial0/0/0 2 2
Automatic network summarization is not in effect
Maximum path: 4
Routing for Networks:
  172.30.0.0
  209.165.200.0
Passive Interface(s):
  FastEthernet0/0
  FastEthernet0/1
Routing Information Sources:
  Gateway Distance Last Update
  209.165.200.229 120 00:00:20
```



Distance: (default is 120)

**R2:**

- **show running-config**

R2#show running-config

Building configuration...

Current configuration : 870 bytes

!

version 12.4

no service timestamps log datetime msec

no service timestamps debug datetime msec

no service password-encryption

!

hostname R2

!

!

!

!

!

!

!

!

no ip cef

no ipv6 cef

!

!

- **show ip route**

R2#sh ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

\* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/16 is subnetted, 1 subnets

C 10.1.0.0 is directly connected, FastEthernet0/0

172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks

R 172.30.1.0/24 [120/1] via 209.165.200.230, 00:00:22, Serial0/0/0

R 172.30.2.0/24 [120/1] via 209.165.200.230, 00:00:22, Serial0/0/0

R 172.30.100.0/24 [120/1] via 209.165.200.234, 00:00:11, Serial0/0/1

R 172.30.110.0/24 [120/1] via 209.165.200.234, 00:00:11, Serial0/0/1

R 172.30.200.16/28 [120/1] via 209.165.200.234, 00:00:11, Serial0/0/1

R 172.30.200.32/28 [120/1] via 209.165.200.234, 00:00:11, Serial0/0/1

209.165.200.0/30 is subnetted, 2 subnets

C 209.165.200.228 is directly connected, Serial0/0/0

C 209.165.200.232 is directly connected, Serial0/0/1

--More--

- **show ip interface brief**

R2#show ip interface brief

Interface IP-Address OK? Method Status Protocol

FastEthernet0/0 10.1.0.1 YES manual up up

FastEthernet0/1 unassigned YES NVRAM administratively down down

```
Serial0/0/0 209.165.200.229 YES manual up up
Serial0/0/1 209.165.200.233 YES manual up up
Vlan1 unassigned YES unset administratively down down
```

- **show ip protocols**

```
R2#sh ip protocols
Routing Protocol is "rip"
Sending updates every 30 seconds, next due in 28 seconds
Invalid after 180 seconds, hold down 180, flushed after 240
Outgoing update filter list for all interfaces is not set
Incoming update filter list for all interfaces is not set
Redistributing: rip
Default version control: send version 2, receive 2
Interface Send Recv Triggered RIP Key-chain
Serial0/0/0 2 2
Serial0/0/1 2 2
Automatic network summarization is not in effect
Maximum path: 4
Routing for Networks:
    10.0.0.0
    209.165.200.0
Passive Interface(s):
    FastEthernet0/0
Routing Information Sources:
    Gateway Distance Last Update
    209.165.200.230 120 00:00:07
    209.165.200.234 120 00:00:26
Distance: (default is 120)
```

### **R3:**

- **show running-config**

```
R3#show running-config
Building configuration...

Current configuration : 1030 bytes
!
version 12.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R3
!
!
!
!
!
!
!
no ip cef
no ipv6 cef
!
!
```

- **show ip route**

```
R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
```

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area  
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2  
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP  
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area  
\* - candidate default, U - per-user static route, o - ODR  
P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/16 is subnetted, 1 subnets  
R 10.1.0.0 [120/1] via 209.165.200.233, 00:00:20, Serial0/0/1  
172.30.0.0/16 is variably subnetted, 6 subnets, 2 masks  
R 172.30.1.0/24 [120/2] via 209.165.200.233, 00:00:20, Serial0/0/1  
R 172.30.2.0/24 [120/2] via 209.165.200.233, 00:00:20, Serial0/0/1  
C 172.30.100.0/24 is directly connected, FastEthernet0/0  
C 172.30.110.0/24 is directly connected, Loopback0  
C 172.30.200.16/28 is directly connected, Loopback1  
C 172.30.200.32/28 is directly connected, Loopback2  
209.165.200.0/30 is subnetted, 2 subnets  
R 209.165.200.228 [120/1] via 209.165.200.233, 00:00:20, Serial0/0/1  
C 209.165.200.232 is directly connected, Serial0/0/1  
--More--

• **show ip interface brief**

R3#show ip interface brief  
Interface IP-Address OK? Method Status Protocol  
FastEthernet0/0 172.30.100.1 YES manual up up  
FastEthernet0/1 unassigned YES NVRAM administratively down down  
Serial0/0/0 unassigned YES NVRAM administratively down down  
Serial0/0/1 209.165.200.234 YES manual up up  
Loopback0 172.30.110.1 YES manual up up  
Loopback1 172.30.200.17 YES manual up up  
Loopback2 172.30.200.33 YES manual up up  
Vlan1 unassigned YES unset administratively down down


• **show ip protocols**

R3#sh ip protocols  
Routing Protocol is "rip"  
Sending updates every 30 seconds, next due in 15 seconds  
Invalid after 180 seconds, hold down 180, flushed after 240  
Outgoing update filter list for all interfaces is not set  
Incoming update filter list for all interfaces is not set  
Redistributing: rip  
Default version control: send version 2, receive 2  
Interface Send Recv Triggered RIP Key-chain  
Loopback0 2 2  
Loopback1 2 2  
Loopback2 2 2  
Serial0/0/1 2 2  
Automatic network summarization is not in effect  
Maximum path: 4  
Routing for Networks:  
172.30.0.0  
209.165.200.0  
Passive Interface(s):  
FastEthernet0/0  
Routing Information Sources:  
Gateway Distance Last Update  
209.165.200.233 120 00:00:10  
--More--

## Task 10: Clean Up

Erase the configurations and reload the routers. Disconnect and store the cabling. For PC hosts that are normally connected to other networks (such as the school LAN or to the Internet), reconnect the appropriate cabling and restore the TCP/IP settings.

**R1:**



The screenshot shows the R1 router's CLI interface. The window has tabs for Physical, Config, CLI (selected), and Attributes. The CLI window displays the following text:

```
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0,
changed state to up


R1>enable
R1#erase startup-config
Erasing the nvram filesystem will remove all configuration files!
Continue? [confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
R1#reload
Proceed with reload? [confirm]
System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fcl)
Initializing memory for ECC
..
C1841 processor with 524288 Kbytes of main memory
Main memory is configured to 64 bit mode with ECC enabled

Readonly ROMMON initialized

Self decompressing the image :
#####
```

At the bottom of the CLI window, there is a prompt "Ctrl+F6 to exit CLI focus" and two buttons: "Copy" and "Paste". Below the CLI window, there is a "Top" button.

R2:

 R2

Physical Config CLI Attributes

IOS Command Line Interface

```
http://www.cisco.com/wwl/export/crypto/tool/stqrg.html

If you require further assistance please contact us by sending
email to
export@cisco.com.

Cisco 1841 (revision 5.0) with 114688K/16384K bytes of memory.
Processor board ID FTX0947218E
M860 processor: part number 0, mask 49
2 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
191K bytes of NVRAM.
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M),
Version 12.4(15)T1, RELEASE SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/
no]:
```


Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top



### R3:

 R3

Physical Config CLI Attributes

IOS Command Line Interface

```
%LINK-3-UPDOWN: Interface Serial0/0/1, changed state to down

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1,
changed state to down

R3>enable
R3#erase startup-config
Erasing the nvram filesystem will remove all configuration files!
Continue? [confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
R3#reload
Proceed with reload? [confirm]
System Bootstrap, Version 12.3(8r)T8, RELEASE SOFTWARE (fcl)
Initializing memory for ECC
..
C1841 processor with 524288 Kbytes of main memory
Main memory is configured to 64 bit mode with ECC enabled

Readonly ROMMON initialized

Self decompressing the image :
#####
```

Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top