

## Enabling Hive Metastore High Availability



1. Go to the Hive service.
2. If you have a secure cluster, enable the Hive token store. Non-secure clusters can skip this step. If more than one role group applies to this configuration, edit the value for the appropriate role group.
  - a. Click the **Configuration** tab.
  - b. Select **Scope > Hive Metastore Server**.
  - c. Select **Category > Advanced**.
  - d. Locate the **Hive Metastore Delegation Token Store** property or search for it by typing its name in the Search box.
  - e. Select `org.apache.hadoop.hive.thrift.DBTokenStore`.
  - f. Click **Save Changes** to commit the changes.
3. Click the **Instances** tab.
4. Click **Add Role Instances**.
5. Click the text field under **Hive Metastore Server**.
6. Check the box by the host on which to run the additional metastore and click **OK**.
7. Click **Continue** and click **Finish**.
8. Check the box by the new **Hive Metastore Server** role.
9. Select **Actions for Selected > Start**, and click **Start** to confirm.
10. Click **Close** and click to display the stale configurations page.
11. Click **Restart Stale Services** and click **Restart Now**.
12. Click **Finish** after the cluster finishes restarting.