

# PBblas/ trsm

---

[Go Up](#)

## IMPORTS

PBblas | PBblas.Types | std.BLAS | PBblas.internal | PBblas.internal.Types |  
PBblas.internal.MatDims | PBblas.internal.Converted | std.system.Thorlib |

## DESCRIPTIONS

### FUNCTION trsm

<code>DATASET(Layout_Cell)</code>	<code>trsm</code>
<pre>(Side s, Triangle tri, BOOLEAN transposeA, Diagonal diag, value_t alpha, DATASET(Layout_Cell) A_in, DATASET(Layout_Cell) B_in)</pre>	

Partitioned block parallel triangular matrix solver. Solves for X using:  $AX = B$  or  $XA = B$  A is a square triangular matrix, X and B have the same dimensions. A may be an upper triangular matrix ( $UX = B$  or  $XU = B$ ), or a lower triangular matrix ( $LX = B$  or  $XL = B$ ). Allows optional transposing and scaling of A. Partially based upon an approach discussed by MJ DAYDE, IS DUFF, AP CERFACS. A Parallel Block implementation of Level-3 BLAS for MIMD Vector Processors ACM Tran. Mathematical Software, Vol 20, No 2, June 1994 pp 178-193 and other papers about PB-BLAS by Choi and Dongarra This module supports the "Myriad" style interface, allowing many independent problems to be worked on at once. Corresponding A and B matrixes are related by a common work-item identifier (wi\_id) within each cell of the matrix. The returned X matrix will contain cells for the same set of work-items as specified for the A and B matrices.

**PARAMETER** `s` Types.Side enumeration indicating whether we are solving  $AX = B$  or  $XA = B$

**PARAMETER** tri Types.Triangle enumeration indicating whether we are solving an Upper or Lower triangle.

**PARAMETER** transposeA Boolean indicating whether or not to transpose the A matrix before solving

**PARAMETER** diag Types.Diagonal enumeration indicating whether A is a unit matrix or not. This is primarily used after factoring matrixes using getrf (LU factorization). That module produces a factored matrix stored within the same space as the original matrix. Since the diagonal is used by both factors, by convention, the Lower triangle has a unit matrix (diagonal all 1's) while the Upper triangle uses the diagonal cells. Setting this to UnitTri, causes the contents of the diagonal to be ignored, and assumed to be 1. NotUnitTri should be used for most other cases.

**PARAMETER** alpha Multiplier to scale A

**PARAMETER** A\_in The A matrix in Layout\_Cell format

**PARAMETER** B\_in The B matrix in Layout\_Cell format

**RETURN** X solution matrix in Layout\_Cell format

**SEE** Types.Layout\_Cell

**SEE** Types.Triangle

**SEE** Types.Side