

# Spring Cloud Server

manages all the application  
related configuration  
properties

# Creating Spring Cloud Configuration Server

```
<dependency>
```

```
    <groupId>org.springframework.cloud</groupId>
```

```
    <artifactId>spring-cloud-config-server</artifactId>
```

```
</dependency>
```

- Gradle users can add the below dependency in your build.gradle file.

```
compile('org.springframework.cloud:spring-cloud-config-server')
```

# Creating Spring Cloud Configuration Server

- Add the **@EnableConfigServer** annotation in your main Spring Boot application class file. The **@EnableConfigServer** annotation makes your Spring Boot application act as a Configuration Server

@SpringBootApplication

**@EnableConfigServer**

```
public class ConfigserverApplication {  
    public static void main(String[] args) {  
        SpringApplication.run(ConfigserverApplication.class, args);  
    }  
}
```

# application.properties

- Add the below configuration to your properties file and replace the application.properties file into bootstrap.properties file. Observe the code given below –

`server.port = 8888`

`spring.cloud.config.server.native.searchLocations=file:///C:/  
configprop/`

`SPRING_PROFILES_ACTIVE=native`

- Configuration Server runs on the Tomcat port 8888 and application configuration properties are loaded from native search locations.

# config-client.properties

- in **file:///C:/configprop/**, place your client application - **application.properties** file. For example, your client application name is **config-client**, then rename your **application.properties** file as **config-client.properties** and place the properties file on the path **file:///C:/configprop/**.
- The code for config-client properties file is given below –  
welcome.message = Welcome to Spring cloud config server

```
// 20171208120841
// http://localhost:8888/config-client/default/master
{
  "name": "config-client",
  "profiles": [
    "default"
  ],
  "label": "master",
  "version": null,
  "state": null,
  "propertySources": [
    {
      "name": "file:///C:/configprop/config-client.properties",
      "source": {
        "welcome.message": "Welcome to Spring cloud config server"
      }
    }
  ]
}
```

# Cloud Configuration Client

- Some applications may need configuration properties that may need a change and developers may need to take them down or restart the application to perform this.
- However, this might lead to downtime in production and the need of restarting the application.
- Spring Cloud Configuration Server lets developers to load the new configuration properties without restarting the application and without any downtime.

# Cloud Configuration Client

```
<dependency>
```

```
  <groupId>org.springframework.cloud</groupId>
```

```
  <artifactId>spring-cloud-starter-config</artifactId>
```

```
</dependency>
```

- Gradle users can add the following dependency into the build.gradle file.

```
compile('org.springframework.cloud:spring-cloud-starter-config')
```



# Cloud Configuration Client

- Add the **@RefreshScope** annotation to your main Spring Boot application. The **@RefreshScope** annotation is used to load the configuration properties value from the Config server.

@SpringBootApplication

**@RefreshScope**

```
public class ConfigclientApplication {  
    public static void main(String[] args) {  
        SpringApplication.run(ConfigclientApplication.class, args);  
    }  
}
```

# Cloud Configuration Client

- Add the config server URL in your application.properties file and provide your application name.
- Note – `http://localhost:8888` config server should be run before starting the config client application.

`spring.application.name = config-client`

`spring.cloud.config.uri = http://localhost:8888`

# Cloud Configuration Client

```
@RestController  
public class ConfigclientApplication {  
    @Value("${welcome.message}")  
    String welcomeText;  
    @RequestMapping(value = "/")  
    public String welcomeText() {  
        return welcomeText;  
    }  
}
```

# Cloud Configuration Client

```
2017-12-08 12:41:57.682 INFO 1104 --- [
```

```
main] c.c.c.ConfigServicePropertySourceLocator :
```

```
Fetching config from server at: http://localhost:8888
```

- Now hit the URL, **http://localhost:8080/** welcome message is loaded from the Configuration server.
- Now, go and change the property value on the Configuration server and hit the actuator Endpoint POST URL **http://localhost:8080/refresh** and see the new configuration property value in the URL **http://localhost:8080/**




