

z/OS  
2.5

*SDSF Operation and Customization*



**Note**

Before using this information and the product it supports, read the information in [“Notices” on page 521.](#)

This edition applies to Version 2 Release 5 of z/OS® (5650-ZOS) and to all subsequent releases and modifications until otherwise indicated in new editions.

Last updated: 2023-07-14

© **Copyright International Business Machines Corporation 1997, 2023.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

© **Rocket Software, Inc. 2017, 2023.**

---

# Contents

<b>Figures.....</b>	<b>xiii</b>
<b>Tables.....</b>	<b>xv</b>
<b>About this document.....</b>	<b>xxiii</b>
<b>z/OS information.....</b>	<b>xxv</b>
<b>How to send your comments to IBM.....</b>	<b>xxvii</b>
If you have a technical problem.....	xxvii
<b>Summary of changes.....</b>	<b>xxix</b>
Summary of changes for SDSF 2.5.....	xxix
<b>Chapter 1. Exploiting new functions.....</b>	<b>1</b>
Exploiting the Address Space Diagnostics panel (AD).....	1
Exploiting the CF Data Sets panel (CFD).....	1
Exploiting the Common Storage Subpools panel (CS).....	2
Exploiting the Common Storage Subpool Details panel (CSI).....	2
Exploiting the Link List sets panel (LLS).....	2
Exploiting the Memory contents panel (MEM).....	3
Exploiting the PC Routines panel (PC).....	3
Exploiting the Private Storage Subpool panel (USI).....	3
Exploiting the System Parameters panel (SYSP).....	3
Exploiting the SVC routines and ESR panel (SVC).....	4
<b>Chapter 2. Using ISFPARMS for customization.....</b>	<b>5</b>
ISFPARMS overview.....	5
ISFPARMS format alternatives.....	5
Converting ISFPARMS assembler macros to statements.....	6
Reverting to the ISFPARMS defined with assembler macros.....	7
NOPARM fallback.....	7
Samples.....	7
Auditing ISFPARMS.....	7
Diagnosing security.....	7
Rules for coding ISFPARMS.....	8
Statements.....	8
Assembler macros.....	9
Conditional processing.....	10
WHEN Statement.....	10
System symbols.....	12
Global initialization parameters (OPTIONS or ISFPMAC).....	12
Example of the OPTIONS statement and ISFPMAC macro.....	12
OPTIONS or ISFPMAC reference.....	13
Server connection (CONNECT).....	16
Example of the CONNECT statement.....	16
CONNECT statement.....	16
Group authorization parameters (GROUP or ISFGRP).....	17
Using SAF to control group membership.....	17

Group function.....	18
Group function parameters reference.....	18
Variable field lists (FLD or ISFFLD).....	47
Example of the FLD statement and ISFFLD macro.....	48
FLD and ISFFLD syntax.....	48
Name tables (NTBL or ISFNTBL).....	53
Examples of the NTBL statement and ISFNTBL macro.....	54
NTBL and ISFNTBL syntax.....	54
Usage notes.....	54
Customized properties (PROPLIST).....	54
Example of the PROPLIST and associated statements.....	55
PROPLIST syntax.....	55
Code page (TRTAB/TRDEF or ISFTR).....	68
Examples of the TRTAB statement and ISFTR macro.....	68
TRTAB and ISFTR syntax.....	69
Coding a translate table.....	71

### **Chapter 3. Using the SDSF server..... 73**

Configuring server security.....	73
Defining the input.....	74
Starting the server.....	74
Starting the SDSFAUX server.....	74
Processing the statements.....	74
Accessing the server.....	74
Logging.....	75
Security.....	75
Server operator commands.....	75
Start the SDSF server.....	75
Start Aux.....	78
Change server options.....	79
Display Exit.....	81
Display Help.....	81
Display JES.....	82
Display Services.....	82
Display Systems.....	83
Display Task.....	83
Display User.....	84
Display information about server communications.....	84
Refresh ISFPARMS.....	85
Refresh JES.....	86
Refresh SYS.....	86
Set Sample.....	87
Set Trace.....	88
Start communications.....	88
Stop communications.....	89
Stop the SDSF server.....	89
Stop Aux.....	90
Switch Log.....	90
Switch Trace.....	91

### **Chapter 4. Columns on the SDSF panels..... 93**

Action Help panel (ACTH).....	93
Address Space Diagnostics panel (AD).....	94
Address Space Memory panel (AS).....	94
Authorized Program Facility panel (APF).....	96
CF Connections panel (CFC).....	97
CF Data Sets panel (CFD).....	98

CF Structure panel (CFS).....	99
Columns Help panel (COLH).....	100
Command Help panel (CMDH).....	101
Common Storage Subpools panel (CS) .....	102
Common Storage Subpool Details panel (CSI).....	103
Common Storage Remaining panel (CSR) .....	103
Device Activity panel (DEV) .....	104
Display Active Users panel (DA).....	105
Dynamic Exits panel (DYNX).....	109
Enclaves panel (ENC).....	110
Enqueue panel (ENQ).....	111
Extended Console panel (EMCS) .....	113
File Systems panel (FS) .....	114
Generic Tracker panel (GT) .....	115
Health Check History panel (CKH).....	116
Health Checker panel (CK).....	116
Held Output panel (H).....	118
Initiator panel (INIT).....	121
Input Queue panel (I).....	123
JES Checkpoint panel (CKPT).....	126
JESInfo panel (JRI).....	127
JESInfo by Job panel (JRJ).....	128
JES Subsystem panel (JES).....	129
JESPLEX panel (JP).....	130
Job Class Members panel (JCM).....	130
Job Class panel (JC).....	131
Job Common Storage panel (JCS).....	133
Job Data Set panel (JDS).....	134
Job Delay panel (JY).....	138
Job Dependency panel (JP).....	139
Job Device panel (JD).....	140
Job DDName panel (JDDN).....	142
Job Group panel (JG).....	143
Job Memory panel (JM).....	143
Job Memory Objects panel (JMO).....	144
Job Module panel (JC) .....	145
Job Step panel (JS).....	146
Job Tasks panel (JT) .....	148
Job 0 (J0).....	149
Lines panel (LI).....	150
Link List sets panel (LLS).....	152
Link List panel (LNK).....	153
Link Pack Area panel (LPA).....	154
Link Pack Directory panel (LPD).....	154
Multi-Access Spool panel (MAS) and JESPLEX (JP) panel.....	155
Memory contents panel (MEM) .....	157
Network Activity panel (NA) .....	158
Network Connections (NC) .....	159
Network Servers (NS).....	161
Nodes panel (NO).....	162
OMVS options panel (BPXO).....	164
Output Queue panel (O).....	165
Page panel (PAG).....	168
PARMLIB panel (PARM).....	169
PC Routines panel (PC).....	170
Printer panel (PR).....	170
Private Storage Subpool panel (USI).....	175
Proclib panel (PROC).....	176

Processes panel (PS).....	177
Punch panel (PUN).....	178
Reader panel (RDR).....	181
Resource panel (RES).....	183
Resource Monitor panel (RM).....	183
Resource Monitor Alerts panel (RMA).....	184
Scheduling Environment panel (SE).....	185
Spool Offload panel (SO).....	185
Spool Volumes panel (SP).....	188
Search panel (SRCH).....	190
Search Help panel (SEARCH).....	191
SMS Groups panel (SMSG) .....	192
SMS Volumes panel (SMSV) .....	193
Status panel (ST).....	193
Subsystem panel (SSI).....	198
SVC routines and ESR panel (SVC).....	199
System Symbols panel (SYM).....	200
System panel (SYS).....	201
System Parameters panel (SYSP).....	203
System Requests panel (SR).....	204
Virtual Storage Map panel (VMAP) .....	205
WLM Policy panel (WLM).....	205
WLM Report Class panel (REPC).....	206
WLM Resource Group panel (RGRP).....	207
WLM Service Classes panel (SRVC).....	208
WLM Workload panel (WKLD).....	209
XCF Members and Groups panel (XCFM).....	210
 <b>Chapter 5. Using SAF for security.....</b>	 <b>213</b>
Relationship of SAF and ISFPARMS.....	213
Changing authorization dynamically.....	213
Auditing access attempts.....	213
Diagnosing security.....	214
SAF concepts for SDSF resources.....	214
Protecting SDSF function.....	215
 <b>Chapter 6. SDSF and RACF.....</b>	 <b>219</b>
Security administration.....	219
Brief summary of RACF commands.....	219
Delegation of RACF administrative authority.....	220
SDSF resource group class.....	220
Establishing SAF security with RACF.....	221
RACF authorization checking.....	221
Considerations for broad access.....	221
Using RACLIST and REFRESH.....	221
Using RACLIST and REFRESH with the SDSF class.....	222
Using RACLIST and REFRESH with the OPERCMDS class.....	222
Using conditional access.....	222
Sample RACF commands.....	223
Multilevel Security.....	223
 <b>Chapter 7. Protecting SDSF functions.....</b>	 <b>225</b>
Access requirements for SDSF users.....	225
Action characters.....	225
Protecting the objects of action characters.....	225
Protecting the generated MVS and JES commands.....	226
Protecting action characters as separate resources .....	227

Setting up generic profiles.....	228
Examples of protecting action characters.....	228
Tables of action characters.....	229
Authorized program facility data sets.....	260
Protecting authorized program facility data sets.....	260
Example of protecting authorized program facility data sets.....	260
Authorized SDSF commands.....	261
Protecting SDSF commands.....	261
Setting up generic profiles.....	264
Examples of protecting commands.....	264
Address spaces.....	265
Protecting address spaces.....	265
Example of address spaces.....	265
Coupling facility (CF) connections.....	265
Protecting CF connections.....	265
Example of CF connections.....	266
Coupling facility (CF) data sets.....	266
Protecting CF data sets.....	266
Example of CF data sets.....	266
Coupling facility (CF) structures.....	266
Protecting CF structures.....	266
Example of CF structures.....	266
Checks on the CK and CKH panels.....	267
Protecting checks.....	267
Example of protecting checks.....	267
Destination names.....	268
Protecting destination names.....	268
Initializing destinations.....	268
Example of protecting destination names.....	269
Destination operator authority.....	269
Protecting operator authority by destination.....	269
Device activity information.....	270
Protecting device activity.....	270
Example of protecting device information.....	270
Dynamic exit information.....	271
Protecting dynamic exits.....	271
Example of protecting dynamic exits.....	271
EMCS consoles information.....	271
Protecting EMCS consoles.....	271
Example of protecting EMCS consoles.....	272
Enclaves.....	272
Protecting enclaves.....	272
Example of protecting enclaves.....	272
Enqueue information.....	272
Protecting Enqueue Information.....	272
Example of protecting enqueue information.....	273
File system information.....	273
Protecting file systems.....	273
Example of protecting file systems.....	273
Generic tracker events.....	273
Protecting generic tracker events.....	273
Example of protecting generic tracker events.....	274
Initiators.....	274
Protecting initiators.....	274
Example of protecting initiators.....	274
JES2 resources on the RM panel.....	274
Protecting JES2 resources.....	275
Example of protecting JES2 resources.....	276

JES subsystems.....	276
Protecting JES subsystems.....	276
Example of protecting JES subsystems.....	276
Job classes.....	276
Protecting job classes.....	276
Example of protecting job classes.....	277
Job class members.....	277
Protecting job class members.....	277
Example of protecting job class members.....	277
Job devices.....	277
Protecting job devices.....	277
Example of protecting job devices.....	277
Jobs, job groups, output groups, and SYSIN/SYSOUT data sets.....	278
Protecting jobs, job groups, output groups, and SYSIN/SYSOUT data sets.....	278
Permitting other users to view your data.....	279
Providing function comparable to NOTIFY authority.....	279
Examples of protecting jobs and output groups.....	280
JESInfo resources.....	281
Protecting JESInfo resources.....	281
Example of protecting JESInfo resources.....	281
JESInfo by job resources.....	281
Protecting JESInfo by job resources.....	282
Example of protecting JESInfo by job resources.....	282
Lines.....	282
Protecting lines.....	282
Example of protecting lines.....	282
Link list sets.....	283
Protecting link list sets.....	283
Example of protecting link list sets.....	283
Link list data sets.....	283
Protecting link list data sets.....	283
Example of protecting link list data sets.....	283
MAS and JESPLEX members.....	283
Protecting MAS and JESPLEX members.....	284
Example of protecting MAS members.....	284
Membership in groups.....	284
Controlling membership in groups.....	284
Example of protecting membership in a group in ISFPARMS.....	284
Memory contents.....	285
Protecting memory contents.....	285
Example of protecting memory contents.....	285
MVS and JES commands on the command line.....	285
Protecting the slash command.....	285
Slash command and User Log.....	286
Example of protecting the slash command.....	286
Network activity.....	286
Protecting network activity.....	286
Example of protecting network activity.....	286
Network connections.....	287
Protecting network connections.....	287
Example of protecting network connections.....	287
Network servers.....	287
Protecting network servers.....	287
Example of protecting network servers.....	288
Nodes.....	288
Protecting nodes.....	288
Example of protecting nodes.....	289
OMVS options.....	289



Protecting OMVS options.....	289
Example of protecting OMVS options.....	289
OPERLOG.....	289
Protecting the log stream.....	289
Overtimeable fields.....	290
Protecting the overtimeable field.....	290
Protecting the objects of overtimeable fields.....	290
Protecting the generated MVS and JES commands.....	291
Generic profiles.....	291
Examples of protecting overtimeable fields.....	292
Tables of overtimeable fields.....	293
Page data sets.....	332
Protecting page data sets.....	332
Example of protecting page data sets.....	332
PARMLIB data sets.....	332
Protecting PARM data sets.....	332
Example of protecting PARM data sets.....	333
Printers.....	333
Protecting printers.....	333
Permitting access only while using SDSF.....	334
Examples of protecting printers.....	334
Processes (z/OS UNIX System Services).....	334
Protecting processes.....	334
Example of protecting processes.....	334
Proclibs.....	335
Protecting proclibs.....	335
Example of protecting proclibs.....	335
Punches.....	335
Protecting punches.....	335
Permitting access only while using SDSF.....	336
Example of protecting punches.....	336
Readers.....	336
Protecting readers.....	336
Example of protecting readers.....	336
Resource monitor alerts.....	337
Protecting resource monitor alerts.....	337
Example of protecting resource monitor alerts.....	337
Resources defined to WLM.....	337
Protecting WLM resources.....	337
Example of protecting resources.....	337
Scheduling environments.....	338
Protecting scheduling environments.....	338
Example of protecting scheduling environments.....	338
SDSF server.....	338
Protecting the SDSF server.....	338
Examples of protecting the SDSF server.....	339
SMS storage groups.....	339
Protecting SMS storage groups.....	339
Example of protecting SMS storage groups.....	339
SMS volumes.....	340
Protecting SMS volumes.....	340
Example of protecting SMS volumes.....	340
Spool offloaders.....	340
Protecting spool offloaders.....	340
Example of protecting spool offloaders.....	341
Spool volumes.....	341
Protecting spool volumes.....	341
Example of protecting spool volumes.....	342

Subsystems.....	342
Protecting subsystems.....	342
Example of protecting subsystems.....	342
System parameters.....	342
Protecting subsystem parameters.....	342
Example of protecting subsystem parameters.....	342
SYSLOG.....	342
Protecting the logical log.....	343
System Symbol information.....	343
Protecting system symbol information.....	343
Example of protecting system symbol information.....	343
System information.....	343
Protecting system information.....	343
Example of protecting system information.....	345
System requests.....	345
Protecting system requests.....	345
Example of protecting system requests.....	345
User log (ULOG).....	345
Protecting the ULOG.....	345
Examples of protecting ULOG.....	346
XCF groups and members.....	346
Protecting XCF groups and members.....	346
Example of protecting XCF groups and members.....	346

## **Chapter 8. Using installation exit routines..... 349**

Installation exit routines.....	349
Using the ISFUSER module.....	349
Installation exit points.....	350
SAF considerations for exit points.....	350
Initialization exit point.....	350
SDSF termination exit point.....	353
Pre-SAF exit point.....	353

## **Chapter 9. Installation and configuration considerations..... 355**

JES3 considerations.....	355
Getting started running SDSF in the JES3 environment.....	355
JES2 considerations.....	356
DESTDEF considerations.....	356
SDSF with a secondary JES2 subsystem.....	356
SDSF considerations.....	356
Issuing MVS and JES commands.....	356
Console for issuing MVS and JES commands.....	356
Storing MVS and JES commands.....	357
RMF considerations.....	358
ISPF considerations.....	359
Scrollable main menu and fallback.....	360
ISFISP entry point.....	361
Specifying that SDSF should process JES2.....	362
z/OSMF considerations.....	362
Using the SDSF classic interface.....	365

## **Chapter 10. SDSF messages and codes.....367**

Displaying message help.....	367
User authorization.....	367
SDSF messages.....	367
Messages with HSF message numbers.....	413
Messages with ISF message numbers.....	420

Messages for IBM Health Checker for z/OS.....	483
SDSF user abend codes.....	493
<b>Appendix A. SDSF problem management.....</b>	<b>497</b>
Observing and identifying a problem.....	497
Gathering information about a problem.....	497
Dumps.....	497
Trace.....	497
Module information.....	497
SDSF problem index.....	498
The SDSF server fails to start.....	498
Problems with the Repeat-Find PF keys (PF5 and PF17).....	499
Problems with the LOG and RETRIEVE commands.....	499
Users are experiencing authorization problems.....	499
SDSF has abended.....	500
Documentation is incorrect.....	500
An SDSF message is incorrect.....	500
Data on an SDSF panel is garbled or incorrect.....	500
RMF exit is not installed.....	500
<b>Appendix B. SDSF resource names for SAF security.....</b>	<b>503</b>
<b>Appendix C. Accessibility.....</b>	<b>519</b>
<b>Notices.....</b>	<b>521</b>
Terms and conditions for product documentation.....	522
IBM Online Privacy Statement.....	523
Policy for unsupported hardware.....	523
Minimum supported hardware.....	523
Programming interface information.....	524
<b>Index.....</b>	<b>525</b>



---

# Figures

1. Start Aux Options — Syntax.....	79
2. Change Server Options — Syntax.....	80
3. Display Exit Options — Syntax.....	81
4. Display Help Options — Syntax.....	82
5. Display JES Options — Syntax.....	82
6. Display Services — Syntax.....	83
7. Display Systems Options — Syntax.....	83
8. Display Task Options — Syntax.....	84
9. Display User Options — Syntax.....	84
10. Display Information About Server Communications — Syntax.....	85
11. Refresh ISFPARMS — Syntax.....	85
12. Refresh JES — Syntax.....	86
13. Refresh SYS — Syntax.....	87
14. Set Sample Options — Syntax.....	87
15. Set Trace Options — Syntax.....	88
16. Start Communications — Syntax.....	89
17. Stop Communications — Syntax.....	89
18. STOP the SDSF Server — Syntax.....	89
19. Stop Aux Options — Syntax.....	90
20. Switch Log Options — Syntax.....	90
21. Switch Trace Options — Syntax.....	91



---

# Tables

1. Exploitation tasks for the AD panel.....	1
2. Exploitation tasks for the CFD panel.....	1
3. Exploitation tasks for the CS panel.....	2
4. Exploitation tasks for the CSI panel.....	2
5. Exploitation tasks for the LLS panel.....	2
6. Exploitation tasks for the MEM panel.....	3
7. Exploitation tasks for the PC panel.....	3
8. Exploitation tasks for the USI panel.....	3
9. Exploitation tasks for the SYSP panel.....	4
10. Exploitation tasks for the SVC panel.....	4
11. Summary of ISFPARMS Statements and Macros.....	6
12. Special DDNames for SECTRACE.....	8
13. Field List Parameters.....	49
14. Properties to Specify with the PROPERTY Statement.....	55
15. Columns on the ACTH Panel.....	93
16. Columns on the AD Panel .....	94
17. Columns on the AS Panel .....	95
18. Columns on the APF Panel .....	97
19. Columns on the CFC Panel .....	98
20. Columns on the CFD Panel .....	99
21. Columns on the CFS Panel .....	99
22. Columns on the COLH Panel.....	100
23. Columns on the CMDH Panel.....	101

24. Columns on the CS Panel .....	102
25. Columns on the CSI Panel .....	103
26. Columns on the CSR Panel .....	104
27. Columns on the DEV Panel .....	105
28. Columns on the DA Panel.....	105
29. Columns on the DYNX Panel .....	109
30. Columns on the ENC Panel.....	110
31. Columns on the ENQ Panel.....	112
32. Columns on the EMCS Panel.....	113
33. Columns on the FS Panel .....	114
34. Columns on the GT Panel .....	115
35. Columns on the CKH Panel.....	116
36. Columns on the CK Panel.....	117
37. Columns on the H Panel .....	119
38. Columns on the INIT Panel .....	121
39. Columns on the I Panel .....	123
40. Columns on the CKPT Panel .....	127
41. Columns on the JESInfo Panel.....	128
42. Columns on the JESInfo by Job Panel.....	129
43. Columns on the JES Subsystem Panel .....	129
44. Columns on the JCM Panel.....	130
45. Columns on the JC Panel.....	131
46. Columns on the JCS Panel .....	133
47. Columns on the JDS Panel .....	134
48. Columns on the JY Panel .....	138



49. Columns on the Job Dependency Panel .....	139
50. Columns on the JD Panel .....	140
51. Columns on the JDDN Panel .....	142
52. Columns on the JG Panel .....	143
53. Columns on the JM Panel .....	144
54. Columns on the JMO Panel.....	144
55. Columns on the Job Module Panel .....	145
56. Columns on the JS Panel .....	146
57. Columns on the JT Panel .....	148
58. Columns on the JO Panel.....	149
59. Columns on the LI Panel .....	150
60. Columns on the LLS Panel .....	152
61. Columns on the LNK Panel .....	153
62. Columns on the LPA Panel .....	154
63. Columns on the Link Pack Directory Panel.....	155
64. Columns on the MAS and JP Panel .....	155
65. Columns on the MEM Panel .....	157
66. Columns on the NA Panel .....	158
67. Columns on the NC Panel.....	159
68. Columns on the NS Panel.....	161
69. Columns on the NO Panel.....	162
70. Columns on the OMVS Panel.....	165
71. Columns on the O Panel .....	165
72. Columns on the PAG Panel .....	168
73. Columns on the PARM Panel .....	169

74. Columns on the PC Panel .....	170
75. Columns on the PR Panel .....	171
76. Columns on the USI Panel .....	176
77. Columns on the PROC Panel .....	176
78. Columns on the PS Panel.....	177
79. Columns on the PUN Panel .....	178
80. Columns on the RDR Panel .....	181
81. Columns on the RES Panel.....	183
82. Columns on the RM Panel .....	183
83. Columns on the RMA Panel .....	184
84. Columns on the SE Panel.....	185
85. Columns on the SO Panel.....	185
86. Columns on the SP Panel .....	189
87. Columns on the SRCH Panel.....	191
88. Columns on the SEARCH Panel.....	191
89. Columns on the SMSG Panel .....	192
90. Columns on the SMSV Panel .....	193
91. Columns on the ST Panel .....	194
92. Columns on the SSI Panel .....	198
93. Columns on the SVC Panel .....	199
94. Columns on the System Symbols Panel.....	200
95. Columns on the SYS Panel .....	201
96. Columns on the SYSP Panel .....	203
97. Columns on the SR Panel.....	204
98. Columns on the VMAP Panel .....	205

99. Columns on the WLM Policy Panel.....	206
100. Columns on the WLM Report Class Panel.....	206
101. Columns on the WLM Resource Group Panel.....	207
102. Columns on the WLM Service Classes Panel.....	208
103. Columns on the WLM Workload Panel.....	209
104. Columns on the XCF Members and Groups Panel.....	210
105. SDSF Classes and Resources.....	215
106. SDSF Resources That Protect Action Characters.....	227
107. Generic Profiles for Commands Generated by Actions Characters.....	228
108. Action Characters.....	229
109. Action Characters by OPERCMDS Resource Name.....	250
110. OPERCMDS Resources That Protect Issuing Action Characters for JES2 Resources.....	260
111. SAF Resources for Authorized Program Facility Data Sets.....	260
112. SDSF Class Resource Names and SDSF Commands.....	261
113. SAF Resources for Address Spaces.....	265
114. SAF Resources for CF Connections.....	265
115. SAF Resources for CF Data Sets.....	266
116. SAF Resources for CF Structures.....	266
117. Authority Required to Checks for Actions and Overtypes.....	267
118. Authority Required to the Log Stream Used for Check History.....	267
119. Authority Required for Destination Names.....	268
120. Authority Required for Destination Operator Authority.....	269
121. SAF Resources for Device Activity.....	270
122. SAF Resources for Dynamic Exits.....	271
123. SAF Resources for EMCS Consoles.....	271

124. SAF Resources for Enclaves.....	272
125. SAF Resources for Enqueue Information.....	272
126. SAF Resources for File Systems.....	273
127. SAF Resources for Generic Tracker Events.....	273
128. Authority Required to Initiator Resource for Actions and Overtypes.....	274
129. Authority Required to JES2 Resources for Actions and Overtypes.....	275
130. SAF Resources for JES subsystems.....	276
131. Authority Required to Job Class Resource for Actions and Overtypes.....	276
132. SAF Resources for Job Class Members.....	277
133. SAF Resources for Job Devices.....	277
134. SAF Resources for JESInfo Resources.....	281
135. SAF Resources for JESInfo by Job Resources.....	282
136. Authority Required to Lines Resources for Actions and Overtypes.....	282
137. SAF Resources for Link List Sets.....	283
138. SAF Resources for Link List Data Sets.....	283
139. Authority Required to MAS or JESPLEX Members for Actions and Overtypes.....	284
140. Authority Required for membership in an ISFPARMS group.....	284
141. Authority Required to MEM for Actions and Overtypes.....	285
142. Authority Required for the Slash Command.....	285
143. SAF Resources for Network Activity.....	286
144. Authority Required to Network Connection Resources for Actions and Overtypes.....	287
145. Authority Required to Network Servers Resources for Actions and Overtypes.....	288
146. Authority Required to Nodes Resources for Actions and Overtypes.....	288
147. SAF Resources for OMVS Options.....	289
148. Authority Required for Accessing the Log Stream.....	289

149. Generic Profiles for Overtypable Fields.....	291
150. Overtypable Fields.....	293
151. Actions with Overtypes on the PR and PUN Panels in a JES3 Environment.....	315
152. Overtypable Fields Sorted by OPERCMDS Resource Name.....	316
153. OPERCMDS Resources That Protect Overtyping JES2 Resources.....	331
154. SAF Resources for Page Data Sets.....	332
155. SAF Resources for PARM Data Sets.....	333
156. Authority Required to Printer Resources for Actions and Overtypes.....	333
157. Authority Required to z/OS UNIX Processes for Actions and Overtypes.....	334
158. SAF Resources for Proclibs.....	335
159. Authority Required to Punch Resources for Actions and Overtypes.....	335
160. Authority Required to Reader Resources for Actions and Overtypes.....	336
161. SAF Resources for Resource Monitor Alerts.....	337
162. Authority Required to SAF Resources for WLM Resources.....	337
163. Authority Required to Scheduling Environment Resource for Actions.....	338
164. Authority Required to Server Functions.....	338
165. SAF Resources for SMS Storage Groups.....	339
166. SAF Resources for SMS Volumes.....	340
167. Authority Required to Offloader Resources for Actions and Overtypes.....	340
168. Authority Required to Spool Volume Resources for Actions and Overtypes.....	341
169. SAF Resources for Subsystems.....	342
170. SAF Resources for Subsystem Parameters.....	342
171. Authority Required for Accessing the Logical Log.....	343
172. SAF Resources for System Symbol Information.....	343
173. SAF Resources for System Information.....	344

174. Authority Required to System Request Resource for Action Characters.....	345
175. Resource that Protects the Extended Console.....	346
176. SAF Resources for XCF Groups and Members.....	346
177. Required Resource Access for RMF-based Panels.....	359
178. Resources in the ZMFAPLA Class.....	363
179. z/OSMF Views and Corresponding z/OS SDSF Commands.....	364
180. SDSF Abend Codes.....	493
181. Security Classes, Resource Names, and What They Protect.....	503
182. SDSF Class Resource Names and Overtypable Fields.....	508

## About this document

---

This document is for use with z/OS System Display and Search Facility (SDSF). It is intended primarily for system programmers and operators, and assumes you are familiar with the z/OS operating system, including JES. This document contains information about migration, customization, security, operation, maintenance and problem determination, including explanations of SDSF messages.

This document also describes how to use SDSF's application services to write REXX execs or Java™ programs that exploit SDSF function. It includes a quick introduction to SDSF function and terminology for people who are not already experienced users of SDSF but want to exploit SDSF's application services.

Complete information about using SDSF, such as commands, action characters and messages, is provided in the online help for z/OS SDSF. In addition, introductory information is available on the Internet at <http://www.ibm.com/systems/z/os/zos/features/sdsf/>.





## z/OS information

---

This information explains how z/OS references information in other documents and on the web.

When possible, this information uses cross document links that go directly to the topic in reference using shortened versions of the document title. For complete titles and order numbers of the documents for all products that are part of z/OS, see *z/OS Information Roadmap*.

To find the complete z/OS library, go to [IBM Documentation \(www.ibm.com/docs/en/zos\)](http://www.ibm.com/docs/en/zos).



## How to send your comments to IBM

---

We invite you to submit comments about the z/OS product documentation. Your valuable feedback helps to ensure accurate and high-quality information.

**Important:** If your comment regards a technical question or problem, see instead [“If you have a technical problem”](#) on page xxvii.

Submit your feedback by using the appropriate method for your type of comment or question:

### **Feedback on z/OS function**

If your comment or question is about z/OS itself, submit a request through the [IBM RFE Community](#) ([www.ibm.com/developerworks/rfe/](http://www.ibm.com/developerworks/rfe/)).

### **Feedback on IBM® Documentation function**

If your comment or question is about the IBM Documentation functionality, for example search capabilities or how to arrange the browser view, send a detailed email to IBM Documentation Support at [ibmdoc@us.ibm.com](mailto:ibmdoc@us.ibm.com).

### **Feedback on the z/OS product documentation and content**

If your comment is about the information that is provided in the z/OS product documentation library, send a detailed email to [mhvrfs@us.ibm.com](mailto:mhvrfs@us.ibm.com). We welcome any feedback that you have, including comments on the clarity, accuracy, or completeness of the information.

To help us better process your submission, include the following information:

- Your name, company/university/institution name, and email address
- The following deliverable title and order number: z/OS SDSF Operation and Customization, SA23-2274-50
- The section title of the specific information to which your comment relates
- The text of your comment.

When you send comments to IBM, you grant IBM a nonexclusive authority to use or distribute the comments in any way appropriate without incurring any obligation to you.

IBM or any other organizations use the personal information that you supply to contact you only about the issues that you submit.

## If you have a technical problem

---

If you have a technical problem or question, do not use the feedback methods that are provided for sending documentation comments. Instead, take one or more of the following actions:

- Go to the [IBM Support Portal](#) ([support.ibm.com](http://support.ibm.com)).
- Contact your IBM service representative.
- Call IBM technical support.



## Summary of changes

---

This information includes terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations for the current edition are indicated by a vertical line to the left of the change.

**Note:** IBM z/OS policy for the integration of service information into the z/OS product documentation library is documented on the z/OS Internet Library under [IBM z/OS Product Documentation Update Policy \(www-01.ibm.com/servers/resourcelink/svc00100.nsf/pages/ibm-zos-doc-update-policy?OpenDocument\)](http://www-01.ibm.com/servers/resourcelink/svc00100.nsf/pages/ibm-zos-doc-update-policy?OpenDocument).

## Summary of changes for SDSF 2.5

---

The following content is new, changed, or no longer included in SDSF 2.5.

### New

The following content is new.

#### July 2023 refresh

- Additional information for protecting resources for the Job Step (JS) panel was added to [“Protecting jobs, job groups, output groups, and SYSIN/SYSOUT data sets”](#) on page 278.

#### June 2023 refresh

- The z/OSMF Security Configuration Assistant component of z/OSMF can be used to verify that security is properly configured for SAF resources that are used by SDSF. To use this functionality, SDSF APAR PH53477 must be applied. For more information, see the topic [“z/OSMF considerations”](#) on page 362.
- The REUSASID startup parameter was added to the SDSF server START command. The topic [“Format”](#) on page 75 in the section [“Start the SDSF server”](#) on page 75 was updated.
- Message ISFH1027E was added in [“Messages for IBM Health Checker for z/OS”](#) on page 483.

### Changed

The following content has changed.

#### June 2023 refresh

- The width of the DATE column on the SR panel was increased from 8 to 10. See the topic [“System Requests panel \(SR\)”](#) on page 204.
- Corrections were made to the topics [“Exploiting the Common Storage Subpools panel \(CS\)”](#) on page 2, [“Address Space Diagnostics panel \(AD\)”](#) on page 94, and [“Protecting action characters as separate resources”](#) on page 227.
- Because SDSFAUX is responsible for data collection, it should be placed into a higher priority WLM service class. The topic [Chapter 3, “Using the SDSF server,”](#) on page 73 was updated.
- Installation exit return code descriptions were changed for SAF security. The topic [“Return codes”](#) on page 354 was updated.
- Messages ISFH1018R and ISFH1026R were updated in [“Messages for IBM Health Checker for z/OS”](#) on page 483.

### Deleted

The following content has been deleted.

#### June 2023 refresh

- The custom property Panel.DA.DynamiczAAPCols is not supported. It was removed from the topic [“PROPLIST syntax” on page 55](#) and the corresponding UPROFLG1.UPRO1DYZ field for a user exit was removed from the topic [“Initialization exit point” on page 350](#).
- Resource ISFLPA.*datasetname* for LPA data sets is not checked by SDSF and was removed from tables of checked resources. The topics [“SAF classes and resources for SDSF function” on page 215](#) and Appendix B, [“SDSF resource names for SAF security,” on page 503](#) were modified.

# Chapter 1. Exploiting new functions

Migration information is in [z/OS Upgrade Workflow](#). This topic contains information about exploiting new functions in this release. It describes changes to the security and customization of SDSF and is intended for system programmers. Information about using the new functions can be found in the What's New topic of SDSF's online help.

## Exploiting new functions for SDSF 2.5 as updated September, 2021

Before implementing the new functions in SDSF 2.5, the SDSF server must be started. For information, see [Chapter 3, "Using the SDSF server,"](#) on page 73.

- ["Exploiting the Address Space Diagnostics panel \(AD\)"](#) on page 1
- ["Exploiting the CF Data Sets panel \(CFD\)"](#) on page 1
- ["Exploiting the Common Storage Subpools panel \(CS\)"](#) on page 2
- ["Exploiting the Common Storage Subpool Details panel \(CSI\)"](#) on page 2
- ["Exploiting the Link List sets panel \(LLS\)"](#) on page 2
- ["Exploiting the Memory contents panel \(MEM\)"](#) on page 3
- ["Exploiting the PC Routines panel \(PC\)"](#) on page 3
- ["Exploiting the Private Storage Subpool panel \(USI\)"](#) on page 3
- ["Exploiting the System Parameters panel \(SYSP\)"](#) on page 3
- ["Exploiting the SVC routines and ESR panel \(SVC\)"](#) on page 4

## Exploiting the Address Space Diagnostics panel (AD)

The Address Space Diagnostics (AD) panel shows identification information about each address space and the memory addresses of important control blocks.

*Table 1. Exploitation tasks for the AD panel*

Task	Reference Information
<b>Control use of the AD command with the ISFCMD.ODSP.AD.sysname resource.</b>	<a href="#">"Protecting SDSF commands" on page 261</a>
<b>Control use of the action characters using SAF.</b>	<a href="#">"Action characters" on page 225</a> and <a href="#">"Protecting action characters as separate resources " on page 227</a>
<b>Optionally, customize columns on the panel using the ADFLDS parameter and FLD statement in ISFPRMxx.</b>	<a href="#">"FLD and ISFFLD syntax" on page 48</a>

## Exploiting the CF Data Sets panel (CFD)

The CF Data Sets (CFD) panel allows authorized users to display coupling facility data sets defined to the sysplex.

*Table 2. Exploitation tasks for the CFD panel*

Task	Reference Information
<b>Control use of the CFD command with the ISFCMD.ODSP.COUPLED.SYSNAME resource.</b>	<a href="#">"Protecting SDSF commands" on page 261</a>

Table 2. Exploitation tasks for the CFD panel (continued)

Task	Reference Information
<b>Control use of the action characters using SAF.</b>	<a href="#">“Action characters” on page 225</a>
<b>Optionally, customize columns on the panel using the CFDFLDS parameter and FLD statement in ISFPRMxx.</b>	<a href="#">“FLD and ISFFLD syntax” on page 48</a>

## Exploiting the Common Storage Subpools panel (CS)

The Common Storage Subpools (CS) panel allows authorized users to view common storage summary usage by subpool and key.

Table 3. Exploitation tasks for the CS panel

Task	Reference Information
<b>Control use of the CS command with the ISFCMD.ODSP.CS.sysname resource.</b>	<a href="#">“Protecting SDSF commands” on page 261</a>
<b>Control use of the action characters using SAF.</b>	<a href="#">“Action characters” on page 225</a>
<b>Optionally, customize columns on the panel using the CSFLDS parameter and FLD statement in ISFPRMxx.</b>	<a href="#">“FLD and ISFFLD syntax” on page 48</a>

## Exploiting the Common Storage Subpool Details panel (CSI)

The Common Storage Subpool Details (CSI) is a secondary panel that allows authorized users to view common storage details for a selected subpool and key.

Table 4. Exploitation tasks for the CSI panel

Task	Reference Information
<b>Control use of the action characters using SAF.</b>	<a href="#">“Action characters” on page 225</a>
<b>Optionally, customize columns on the panel using the CSIFLDS parameter and FLD statement in ISFPRMxx.</b>	<a href="#">“FLD and ISFFLD syntax” on page 48</a>

## Exploiting the Link List sets panel (LLS)

The LLS panel displays link list sets that are defined in the sysplex.

Table 5. Exploitation tasks for the LLS panel

Task	Reference Information
<b>Control use of the LLS command with the ISFCMD.ODSP.LLS.sysname resource.</b>	<a href="#">“Protecting SDSF commands” on page 261</a>
<b>Control use of the action characters using SAF.</b>	<a href="#">“Action characters” on page 225</a>
<b>Optionally, customize columns on the panel using the LLSFLDS parameter and FLD statement in ISFPRMxx.</b>	<a href="#">“FLD and ISFFLD syntax” on page 48</a>



## Exploiting the Memory contents panel (MEM)

The Memory contents (MEM) panel allows authorized users to browse the memory contents for any address space within the sysplex, including common storage and 64-bit memory objects.

*Table 6. Exploitation tasks for the MEM panel*

Task	Reference Information
<b>Control use of the MEM command with the ISFCMD.ODSP.MEM.sysname and ISFJOB.STORAGE.owner.jobname.sysname resources.</b>	<a href="#">“Protecting SDSF commands” on page 261</a>
<b>Optionally, customize columns on the panel using the MEMFLDS parameter and FLD statement in ISFPRMxx.</b>	<a href="#">“FLD and ISFFLD syntax” on page 48</a>

## Exploiting the PC Routines panel (PC)

The PC Routines (PC) panel displays the currently defined system linkage indexes (LX) PC routines.

*Table 7. Exploitation tasks for the PC panel*

Task	Reference Information
<b>Control use of the PC command with the ISFCMD.ODSP.PC.sysname resource.</b>	<a href="#">“Protecting SDSF commands” on page 261</a>
<b>Optionally, customize columns on the panel using the PCFLDS parameter and FLD statement in ISFPRMxx.</b>	<a href="#">“FLD and ISFFLD syntax” on page 48</a>

## Exploiting the Private Storage Subpool panel (USI)

The Private Storage Subpool (USI) is a secondary panel that allows authorized users to view private storage details for a selected subpool and key.

*Table 8. Exploitation tasks for the USI panel*

Task	Reference Information
<b>Control use of the USI panel with the ISFCMD.ODSP.USI.sysname and ISFJOB.STORAGE.owner.jobname.sysname resources</b>	<a href="#">“Protecting action characters as separate resources” on page 227</a>
<b>Optionally, customize columns on the panel using the USIFLDS parameter and FLD statement in ISFPRMxx.</b>	<a href="#">“FLD and ISFFLD syntax” on page 48</a>

## Exploiting the System Parameters panel (SYSP)

The SYSP panel shows the parameters that are used when the system is IPLed, including IEASYSxx PARMLIB statements and their sources.

Table 9. Exploitation tasks for the SYSP panel

Task	Reference Information
Control use of the SYSP command with the ISFCMD.ODSP.PARMLIB.sysname resource.	<a href="#">“Protecting SDSF commands” on page 261</a>
Control use of the action characters using SAF.	<a href="#">“Action characters” on page 225</a>
Optionally, customize columns on the panel using the SYSPFLDS parameter and FLD statement in ISFPRMxx.	<a href="#">“FLD and ISFFLD syntax” on page 48</a>

## Exploiting the SVC routines and ESR panel (SVC)

The SVC panel shows the SVC (supervisor call instructions) as well as the ESR (extended service routines) table entries.

Table 10. Exploitation tasks for the SVC panel

Task	Reference Information
Control use of the SVC command with the ISFCMD.ODSP.SVC.sysname resource.	<a href="#">“Protecting SDSF commands” on page 261</a>
Optionally, customize columns on the panel using the SVCFLDS parameter and FLD statement in ISFPRMxx.	<a href="#">“FLD and ISFFLD syntax” on page 48</a>

## Chapter 2. Using ISFPARMS for customization

This topic describes SDSF's internal parameters, ISFPARMS, and explains how to use ISFPARMS to customize SDSF.

**Important:** SDSF does not support security via the ISFPARMS mechanism. All users of SDSF 2.5 must use the Security Authorization Facility (SAF) with an External Security Manager (ESM) such as RACF, ACF2, or TSS. For information about migrating from using SDSF security with ISFPARMS (ISFPRMxx or ISFPARMS with assembler macros) to RACF security, refer to [z/OS SDSF Security Migration Guide](#).

**Note:** SDSF provides a utility for converting ISFPARMS assembler macros to ISFPRMxx statements. See [“Converting ISFPARMS assembler macros to statements”](#) on page 6.

### ISFPARMS overview

ISFPARMS defines global and group options and the format of the panels. The options include things like the name of the JES subsystem to process, what generic and wildcard characters to allow in SDSF commands, and whether to display the action bar on SDSF panels. The format of the panels includes the order and titles of the columns.

As of SDSF 2.5, all SDSF security functions are provided through SAF. The ISFPARMS keywords that are related to SAF are obsolete and are ignored. For more information, see [Chapter 5, “Using SAF for security,”](#) on page 213.

### ISFPARMS format alternatives

SDSF provides two alternatives for ISFPARMS:

- The ISFPRMxx member of PARMLIB. This is the **recommended format**. The statements in ISFPRMxx are easier to define and are more dynamic than the assembler macros: they can be updated without reassembling or link-editing. For a JES3 environment, you must use the ISFPRMxx member.

The statements in ISFPRMxx are processed by the SDSF server, which is controlled by MVS operator commands. The server and associated commands are described in detail in [Chapter 3, “Using the SDSF server,”](#) on page 73.

- Assembler macros that you define, assemble, and then link into the SDSF load library. This is the original format for defining ISFPARMS, and it continues to be supported for compatibility in the JES2 environment. However, some functions, such as conditional processing are not available using this format, and it is not supported in the JES3 environment. If you are using the assembler macro-based ISFPARMS, it is strongly recommended the you convert them to the ISFPRMxx format. You can use the ISFACP utility as described in [“Converting ISFPARMS assembler macros to statements”](#) on page 6 to assist in the conversion.

For simplicity, this information refers to both the assembler macro ISFPARMS and PARMLIB member ISFPRMxx as ISFPARMS.

In some cases, SDSF may revert from processing ISFPRMxx to the ISFPARMS defined with assembler macros. This is described in [“Reverting to the ISFPARMS defined with assembler macros”](#) on page 7.

To assist you in defining your ISFPARMS, SDSF provides sample ISFPRMxx members as well as a sample ISFPARMS defined with assembler macros. You can modify the appropriate sample to meet the needs of your installation.

The statements and corresponding assembler macros that make up ISFPARMS are summarized in [Table 11 on page 6](#).

Table 11. Summary of ISFPARMS Statements and Macros

Statement	Assembler Macro	Required	Description	Refer to
<b>OPTIONS</b>	ISFPMAC	Assembler only	Specifies global SDSF initialization parameters.	<a href="#">“Global initialization parameters (OPTIONS or ISFPMAC)” on page 12</a>
<b>CONNECT</b>	Not available	No	Defines server connection properties, SDSFAUX options, and the XCF application server name.	<a href="#">“CONNECT statement” on page 16</a>
<b>GROUP</b>	ISFGRP	ISFPRMxx only	Defines a group of users and their attributes.	<a href="#">“Group authorization parameters (GROUP or ISFGRP)” on page 17</a>
<b>FLD + FLDENT</b>	ISFFLD	No	Customizes the fields shown on an SDSF primary or alternate panel for members of a group. Associated with an ISFGRP macro or GROUP statement.	<a href="#">“Variable field lists (FLD or ISFFLD)” on page 47</a>
<b>NTBL + NTBLENT</b>	ISFNTBL	No	Defines include/exclude lists of jobs associated with a group. Associated with an ISFGRP macro or GROUP statement.	<a href="#">“Name tables (NTBL or ISFNTBL)” on page 53</a>
<b>PROPLIST + PROPERTY</b>	Not available	No	Specifies a property to customize. Provides an alternative to a user exit routine. Associated with a GROUP statement.	<a href="#">“Customized properties (PROPLIST)” on page 54</a>
<b>TRTAB + TRDEF</b>	ISFTR	Assembler only	Specifies the code page that SDSF uses for members of the group. Associated with an ISFGRP macro or GROUP statement.	<a href="#">“Code page (TRTAB/ TRDEF or ISFTR)” on page 68</a>
<b>WHEN</b>	Not available	No	Provides conditional processing of statements	<a href="#">“Conditional processing” on page 10</a>

## Converting ISFPARMS assembler macros to statements



**Attention:** If you are using the assembler macro-based ISFPARMS, it is strongly recommended that you convert them to the ISFPRMxx format. You can use the ISFACP utility as described in the following topics to assist in the conversion.

If you already have defined ISFPARMS with the assembler macros, you can use a conversion utility provided by SDSF to convert them to the statement format used in ISFPRMxx. The utility displays a panel on which you type the names of the input data set (ISFPARMS assembler macros) and output data set (statements), as well as the assembler macro library you use when assembling SDSF. You invoke the utility by typing the ISFACP command on the ISPF command line.

The syntax of the ISFACP command is shown below:

```
ISFACP — TRACE= — rexx-trace-option
```

Because the macros in ISFPARMS can be coded in different ways, the conversion may not be exact. You may need to make corrections to the generated statements.

The conversion utility processes only SDSF macros. For the utility to resolve macro labels to names, the labels must be on the same line as the macros. The conversion utility will attempt to add the labels if it recognizes common coding conventions, such as a label defined with a DS 0H, DS 0F, or EQU \* immediately preceding an SDSF macro.

## Reverting to the ISFPARMS defined with assembler macros

---

The user is connected to the SDSF server during SDSF initialization, and uses the server to process the ISFPARMS defined with statements.

To control when SDSF reverts to the ISFPARMS in assembler macro format, you can define SAF profiles for the SERVER.NOPARM resource in the SDSF class. This resource is checked when no ISFPARMS statements are in effect. If the user has READ access to the profile (or if SAF returns an indeterminate response), SDSF reverts to the ISFPARMS in assembler macro format. If the user does not have access to the profile, SDSF does not revert to the assembler macros and the user is not authorized to SDSF.

## NOPARM fallback

NOPARM fallback occurs when ISFPRMxx is not in effect, or the SDSF server has been started in NOPARM mode. If the user is authorized to the SERVER.NOPARM resource, fallback occurs to ISFPARMS assembler macros. If the user is not authorized, access to SDSF is denied.

A generic tracker event is created for this condition to alert you that fallback is occurring. See [z/OS MVS Diagnosis: Tools and Service Aids](#) for information on generic tracker events.

**Note:** In a subsequent release, the SDSF server will be required and ISFPRMxx must be active. Accessing SDSF through fallback will not be permitted.

You can use the “Generic Tracker panel (GT) ” on page 115 to view the generic tracker event. The generic tracker event for this condition includes the following fields:

- **OWNER** is IBMSDSF
- **EVENTDESC** is: *SDSF NOPARM FALLBACK: ISFPRMXX NOT ACTIVE*
- **PROGRAM** is the SDSF module that detected the event
- **EVENTDATA** is set to zeros

## Samples

---

SDSF supplies the following samples in the ISF.SISFJCL dataset:

- ISFPRM00, which is an ISFPARMS in statement format that matches SDSF's sample ISFPARMS in assembler macro format
- ISFPRM01, which is the same as ISFPRM00 with the addition of field lists for the tabular displays.

A sample ISFPARMS module in assembler macro format for the JES2 environment is provided in member ISFPARMS of the data set ISF.SISFSRC. The ISFPARMS sample provides security with ISFPARMS parameters only. .

## Auditing ISFPARMS

---

When you use the statement format of ISFPARMS, SDSF provides an audit trail of all statements that have been processed. The statements and any associated error messages are written to the SDSFLOG ddname allocated in the SDSF address space.

## Diagnosing security

---

SDSF's security trace function helps you understand and diagnose SDSF security using SAF. In response to the actions that you take, such as issuing commands or overtyping columns, it issues messages that

describe the associated SAF resources. You control security trace with commands, REXX variable or Java methods.

- With the **SET SECTRACE** command, you turn security tracing on and specify how the associated messages are handled.
  - **SET SECTRACE ON** causes the trace messages to be sent to the ULOG.
  - **SET SECTRACE WTP** causes the messages to be issued as write-to-programmer messages. Use this if security prevents you from accessing SDSF or the user log.
- With the **SECTRACE** option on the **SDSF** command, you can turn security tracing on as soon as you access SDSF.
- When SDSF SECTRACE is active, SDSFAUX SECTRACE is also activated. SDSFAUX uses SECTRACE to record the results of security calls for diagnosis.
- With the ISFSECTRACE REXX special variable, you can control security tracing from a REXX exec.
- With ISFRequestSettings methods addISFSecTrace and removeISFSecTrace, you can control security tracing from a Java program.

## Using the SECTRACE special ddnames

SDSF checks for the presence of the special ddnames shown in Table 12 on page 8. If the ddname is allocated, SECTRACE is enabled. This simplifies getting a SECTRACE, particularly in the SDSF/REXX environment because there is no need to modify a script to set the ISFSECTRACE special variable. In the z/OSMF ISPF classic interface, SECTRACE is automatically enabled when early trace is enabled.

Table 12. Special DDNames for SECTRACE	
DDName	Description
ISFSECTR	Equivalent to SECTRACE(ON). SECTRACE messages are written to the ULOG or ISFMSG2 variables.
ISFSECTW	Equivalent to SECTRACE(WTP). SECTRACE messages are written as write-to-programmer (WTP) and ULOG. WTP messages are returned to the TSO user PROFILE WTPMSG is in effect. WTP messages are also written to the job log and syslog.

For example, the following TSO commands allocate and free the special ddname. Allocate the ddname before accessing SDSF.

```
alloc fi(isfsectw) dummy reus
free fi(isfsectw)
```

For more information about the commands, refer to the online help. You could use the SEARCH command, for example, SEARCH SET SECTRACE. For more information about the REXX special variable and Java, refer to [z/OS SDSF User's Guide](#).

## Rules for coding ISFPARMS

This section describes the rules for syntax and implementation of ISFPARMS.

### Statements

Enter statements as card images in a data set that you create with any editor. The data set is identified to the SDSF server through the server startup JCL.

The ISFPARMS statements use a *keyword(value)* format. For example, a GROUP statement might look like this:

```
GROUP NAME (ISFPROG) ,  
CONFIRM (ON)
```

The complete set of rules for specifying ISFPARMS statements follows.

## General rules for coding statements

- A statement is 80 characters long. Use columns 1 through 71 for the statement; columns 72 through 80 are ignored.
- A statement can span any number of lines. To indicate that the statement continues on the next line, use a trailing comma.
- Enclose comments in a */\*\*/* pair, for example, */\* comment \*/*. You can include comments anywhere in a record that a blank is valid. A comment cannot span lines; it must be closed on the line on which it begins.
- When you use a trailing comma to continue a statement, the only thing that can follow the comma on that line is a comment.
- Completely blank lines (in columns 1 through 71) are ignored; you can intersperse them freely with statements.

## Rules for statement types, keywords, and values

The exact syntax of each of the statements is defined in the remainder of this topic. However, the following general rules apply to the statements and their keywords:

- Parameters must be separated from one another by a comma or a blank. Any number of blanks may appear between keywords, values, and commas, and parentheses.
- Each statement must have at least one keyword on the same line.
- Values are translated to uppercase. If the value contains embedded blanks or is case-sensitive, enclose it in single quotes.
- Parameters can be in any order in a statement.
- Statements can appear in any order; however, FLDENT statements must appear after an FLD statement and NTBLENT statements must appear after an NTBL statement.
- To specify a value of blanks, enclose one or more blanks in single quotation marks, for example, ' '.
- Unquoted blank characters inside keyword values are implicitly treated as comma separators and could appear as commas in SDSF syntax error messages.

## Duplicate statements

In general, when SDSF encounters a duplicate statement, it uses the values from the last statement. However, duplicate FLDENT and NTBLENT statements are processed multiple times. For example, a duplicate field appears twice in the list.

## Assembler macros

Code the ISFPARMS module according to standard MVS assembler language rules. The macros use a *keyword=value* format. In addition,

- The ISFPMAC macro must be the first macro in ISFPARMS, and only one ISFPMAC macro may be coded.
- The ISFGRP macros must be coded second, after the ISFPMAC macro and before any ISFNTBL, ISFFLD, and ISFTR macros.
- At least one ISFTR macro must be included.

After coding the ISFPARMS module, assemble and link-edit it. ISFPARMS must be reentrant. You can use the SMP/E procedure described in [Chapter 9, “Installation and configuration considerations,”](#) on page 355.

## Conditional processing

To facilitate using a common ISFPARMS for multiple systems, SDSF provides support for:

- A WHEN statement that allows you to identify statements that apply to a particular system
- System symbols in the ISFPARMS statements.

Conditional processing is available only with the statement format of ISFPARMS. It is not available with the assembler format of ISFPARMS.

Note that, even with conditional processing, if you want to use a common ISFPARMS with different levels of SDSF, you must ensure that the ISFPARMS does not include support (such as new keywords or values) that was introduced in the higher level of SDSF unless SDSF toleration APARs are applied.

### WHEN Statement

The WHEN statement can be used to conditionally process an entire ISFPARMS statement (OPTIONS, GROUP, and so on). The WHEN statement specifies one or more conditions which are compared to the current environment. All of the conditions must be true for the statements that follow to be processed.

In processing a WHEN statement, SDSF checks each of the values against the current system. If all values match the current system, the statements that follow the WHEN statement are processed until the next WHEN is encountered, or until the end of the file is reached. If any of the values do not match the current system, the statements that follow the WHEN statement are checked for syntax but not processed, until the next WHEN is encountered.

The WHEN statement cannot be used to conditionally process a single parameter within a statement. For example, use WHEN to conditionally process an entire OPTIONS statement with all of its parameters, not to conditionally process just the TIMEOUT parameter of OPTIONS. This means that if even a few parameters in a statement vary between systems, multiple versions of the statement may be required. (System symbols, described in [“System symbols”](#) on page 12, can be used to replace the value for a single parameter.)

Messages logged by the server indicate which initialization statements are being processed.

WHEN and all of its parameters are optional. WHEN with no parameters causes the statements that follow (until the next WHEN) to be selected; this can be used to end a preceding WHEN.

The parameters are in the format *keyword(value)*. The value for *value* can be any text string, including standard pattern matching characters:

- \*, which represents any string of characters
- %, which represents any single character.

The SYMBOL keyword lets you specify an expression for the value.

### WHEN parameters

The parameters that describe the processing conditions are described below.

Parameter	Description
<b>LPARNAME</b> ( <i>lpar-name</i> )	Name of the LPAR
<b>SYSNAME</b> ( <i>system-name</i> )	Name of the system
<b>SYSPLEX</b> ( <i>sysplex-name</i> )	Name of the sysplex
<b>HWNAME</b> ( <i>processor-name</i> )	Name of the CPC



Parameter	Description
<b>VMUSERID</b> ( <i>vm-userid</i> )	User ID of a VM system under which MVS is running
<b>SERVER</b> ( <i>sdsf-server-name</i> )	Name of the SDSF server
<b>SYMBOL</b> ( <i>expression</i> )	Evaluate an expression using one or more symbols

#### **LPARNAME** (*lpar-name*)

Names a logical partition that is defined to a processor, which is one of the following: the partition name specified on the 'add partition' panel in HCD, or the partition name specified on the resource or chpid statement that is input to the I/O configuration program (IOCP). The maximum length is 8 characters. Specify a value of ' ' (one or more blanks enclosed by single quotation marks) to indicate a processor that is not initialized in lpar mode.

#### **SYSNAME** (*system-name*)

Specifies the name assigned to an MVS system. The maximum length is 8 characters.

#### **SYSPLEX** (*sysplex-name*)

Names the sysplex this MVS system is in. The maximum length is 8 characters.

#### **HWNAME** (*processor-name*)

Names the central processor complex (CPC) as defined to HCD. The maximum length is 8 characters. Note: specify a value of ' ' (one or more blanks enclosed by single quotation marks) to indicate a processor with no name.

#### **VMUSERID** (*vm-userid*)

Specifies the user ID of a VM system under which MVS is running as a guest. The maximum length is 8 characters. Specify a value of ' ' (one or more blanks enclosed by single quotation marks) to indicate a system not running as a guest under VM.

#### **SERVER** (*sdsf-server-name*)

Names the SDSF server processing the statements.

#### **SYMBOL** (*expression*)

Checks for a value for any system static symbol. These are defined in the IEASYMxx parmlib member. The maximum length is 128 characters.

The format is WHEN SYMBOL(*x* | *^*=*y*,...) where the operands *x* and *y* can be either strings or symbols. The comparison is either equal or not equal. A symbol is expressed as &*name*. The operands can be specified in either order (for example, &SYSNAME=SYS1 or SYS1=&SYSNAME). If an operand does not evaluate to a symbol, the string is checked as is.

**Note:** Pattern matching operations (using \* and % ) are not supported for the SYMBOL keyword.

For the "equal" condition, the strings must match in length and content. Strings are case sensitive. To specify a "not equal" condition, use *^*=, */*= or *\*=.

You can specify any number of conditions, separated by a comma; all must be true for the statement to be accepted.

You can combine the SYMBOL keyword with any other WHEN keyword; all keywords must evaluate to true to be accepted.

If more than one SYMBOL keyword is present, the last one replaces any prior ones regardless of the previous conditions that were processed (that is, conditions cannot be replaced individually).

### Examples of the WHEN statement

#### 1. WHEN SYMBOL(&SYSNAME ^=SY1)

This is accepted when the value of symbol SYSNAME is not equal to SY1. Note that this will also be accepted if SYSNAME is not a defined symbol, as the character string &SYSNAME is not equal to the string SY1.

#### 2. WHEN SYMBOL(&SYSNAME=SY1, &SYSPLEX=PLEX1)

This is accepted when the value of symbol SYSNAME is equal to SY1, and the value of symbol SYSPLEX is equal to PLEX1.

#### 3. WHEN SYMBOL(&SYSPLEX=PLEX1) SYSNAME(SY1)

This example shows a WHEN with two conditions, one of which uses a symbol. This WHEN is accepted when the value of the symbol SYSPLEX is PLEX1 and the sysname is SY1.

## System symbols

Statements can include system symbols for keyword values. Symbols in ISFPARMS are identified by an initial ampersand (&). They also have an ending period, though the period is required only if omitting it would cause ambiguity. It is required if the character that follows is a period.

System symbols are not supported in the assembler macro format of ISFPARMS.

For example, the MENUS data set name may vary by system. A system symbol can be used to substitute the data set name when ISFPARMS is processed. To define the MENUS data set, you might use:

```
MENUS(&SYSPFX. . ISF .SISFPLIB)
```

where &SYSPFX is a symbol for the system name. When ISFPARMS is processed, the system name is substituted for &SYSPFX, resulting in a MENUS data set name that is correct for the system. Note that in this example, the ending period for &SYSPFX. is required, so that the period used to separate data set qualifiers is preserved. The server initialization log will show the actual value used when the statement was processed.

## Global initialization parameters (OPTIONS or ISFPMAC)

The OPTIONS statement or ISFPMAC macro specifies the global initialization parameters for SDSF.

In ISFPARMS assembler macros, ISFPMAC must be the first macro, and there can be only one ISFPMAC macro.

### Example of the OPTIONS statement and ISFPMAC macro

OPTIONS Statement	ISFPMAC Macro
<pre> 1  OPTIONS SYSOUT(A), 2      LINECNT(55), 3      FINDLIM(100000), SCRSIZE(3440), 4      SCHARS('*%'), DCHAR('?')</pre>	<pre> 1  ISFPMAC SYSOUT=A, 2      LINECNT=55, 3      FINDLIM=100000, SCRSIZE=3440, 4      SCHARS=*, DCHAR=?</pre>

On line **1**, the SYSOUT parameter specifies the default SYSOUT class for the SDSF PRINT command.

On line **2**, the LINECNT parameter specifies 55 lines per page of printed output when using the PRINT command to print portions of the system log or output data sets.

On line **3**, the FINDLIM parameter specifies that the FIND command will search up to 100,000 lines on a single pass before displaying the number of lines searched. In the above example, the SCRSIZE parameter specifies that the maximum screen size on which SDSF will be used is 3440 characters.

On line **4**, the SCHARS parameter specifies the search character used for PREFIX and OWNER pattern matching. The DCHAR parameter specifies the display query character.

## OPTIONS or ISFPMAC reference

The parameters that can be coded in the OPTIONS statement or ISFPMAC macro are show below. Defaults are underlined.

OPTIONS	ISFPMAC	Description
ADMSYMBL ( <i>symbol-sets-dsn</i> )	ADMSYMBL= <i>symbol-sets-dsn</i>	GDDM symbols
CSRSEARCH ( <u>LOOKAT</u>   <i>ISPF-member-name</i> )	Not available	Program to run when the cursor is placed on a word in an SDSF screen and the assigned PF key is pressed
DCHAR ( <u>'?</u> ')   ( <i>'query-char'</i> )	DCHAR= <u>?</u>   <i>query-char</i>	Query character
DSI ( <u>NO</u> )   (YES)	DSI= <u>NO</u>   YES	This option is obsolete.
FINDLIM ( <u>5000</u> )   ( <i>lines-searched</i> )	FINDLIM= <u>5000</u>   <i>lines-searched</i>	Lines searched by FIND
JESNAME ( <i>user-JES2-name</i> )   ( <i>JES2-name</i> )	JESNAME= <i>user-JES2-name</i>   <i>JES2-name</i>	Name of the JES2 subsystem that is processed
JES3NAME ( <i>user-JES3-name</i> )   ( <i>JES3-name</i> )	Not available	Name of the JES3 subsystem that is processed
LINECNT ( <u>55</u> )   ( <i>lines</i> )	LINECNT= <u>55</u>   <i>lines-per-page</i>	Lines per page
LOGLIM ( <u>0</u> )   ( <i>hours-searched</i> )	LOGLIM= <u>0</u>   <i>hours-searched</i>	Hours of OPERLOG data filtered
SCHARS ( <u>'*%'</u> )   ( <i>'search-characters'</i> )	SCHARS= <u>*%</u>   <i>search-characters</i>	Pattern matching characters
SCRSIZE ( <u>1920</u> )   ( <i>screen-size</i> )	SCRSIZE= <u>1920</u>   <i>screen-size</i>	Screen size
SYSOUT ( <u>A</u> )   ( <i>class</i> )	SYSOUT= <u>A</u>   <i>class</i>	Default print class
TIMEOUT ( <u>5</u> )   ( <i>seconds</i> )	TIMEOUT= <u>5</u>   <i>seconds</i>	Default timeout interval (JES2 only)
TRCLASS ( <u>A</u> )   ( <i>class</i> )	TRCLASS= <u>A</u>   <i>class</i>	Default trace SYSOUT class
UNALLOC ( <u>NO</u> )   (YES)	UNALLOC= <u>NO</u>   YES	Free files at termination

OPTIONS	ISFPMAC
ADMSYMBL ( <i>symbol-sets-data-set-name</i> )	ADMSYMBL= <i>symbol-sets-data-set-name</i>

Defines a default GDDM symbol sets data set to be used when displaying page-mode data with the V action character.

*symbol-sets-data-set-name* is the name of a cataloged data set for the GDDM symbol sets. This data set will be dynamically allocated by SDSF only if the ADMSYMBL ddname is not already allocated.

There is no default for ADMSYMBL. If you don't specify this keyword, SDSF will not allocate a symbol sets data set.

OPTIONS	ISFPMAC
CSRSEARCH ( <u>LOOKAT</u>   <i>ISPF-member-name</i> )	Not available

Specifies the name of an ISPF command to be invoked when you place the cursor on a word in an SDSF screen and press the assigned PF key. It is recommended that you redefine key PF6 for this purpose. The specified command is invoked and is passed a runtime parameter of the word value from the screen cursor position.

With this option, you can override the SDSF default and supply your own (or an ISV) ISPF command to act on the word identified at the cursor position.

The default is LOOKAT. The value must be 1 to 8 characters and must be a valid ISPF member name.

OPTIONS	ISFPMAC
DCHAR ('?')   (' <i>query-char</i> ')	DCHAR= ?   <i>query-char</i>

Defines the query character for use with commands, to display their current values. The character you specify must be different from the SCHARS value. Also, be sure to tell your users what the new query character is. The default is ?. When using statements, enclose the query character in quotation marks.

OPTIONS	ISFPMAC
DSI (NO)   (YES)	DSI= <u>NO</u>   YES

**Note:** This option is obsolete as of z/OS V2R3.

**YES**

specifies that dynamically allocated data sets are to be enqueued upon by SDSF for the user when they are allocated.

**NO**

is the default and specifies that dynamically allocated data sets are not to be enqueued upon (for data set reservation) by SDSF for the user when they are allocated.

OPTIONS	ISFPMAC
DUMPHLQ ( <u>userid</u> )	Not available

OPTIONS	ISFPMAC
FINDLIM ( <u>5000</u> )   ( <i>lines-searched</i> )	FINDLIM= <u>5000</u>   <i>lines-searched</i>

Specifies the maximum number of lines the FIND command will search on a single pass before displaying the number of lines searched. When running under ISPF, the FINDLIM value is saved and restored across sessions if the user is authorized to issue the command. See the online help for a description of the FIND command. Valid values are 1000 to 9999999.

OPTIONS	ISFPMAC
JESNAME ( <i>user-JES-name</i> )   ( <i>JES-name</i> )	JESNAME= <i>user-JES-name</i>   <i>JES-name</i>

Indicates the name of the JES2 subsystem. The name can be 1 to 4 characters. The default is the JES system the user is currently running under.

For information on specifying this parameter when SDSF is installed to run with a secondary JES2 subsystem, see [“SDSF with a secondary JES2 subsystem” on page 356](#). This applies to JES2 only; for JES3, use the JES3NAME parameter.

OPTIONS	ISFPMAC
JES3NAME (*)   ( <i>JES-name</i> )	not available

Indicates the name of the JES3 subsystem. The name can be 1 to 4 characters. The default is \*, which requests the JES system the user is currently running under.

OPTIONS	ISFPMAC
LINECNT ( <u>55</u> )   ( <i>lines</i> )	LINECNT= <u>55</u>   <i>lines-per-page</i>

Specifies the number of lines per page of printed output when using the PRINT command to print portions of the SYSLOG or OPERLOG. Valid values are 10 to 9999999.

OPTIONS	ISFPMAC
LOGLIM ( <u>0</u> )   ( <i>hours-searched</i> )	LOGLIM= <u>0</u>   ( <i>hours-searched</i> )

Specifies the maximum amount of OPERLOG data, in hours, that SDSF will search on a single pass for OPERLOG records that meet filter criteria. If LOGLIM is omitted, the value is set to 0, which indicates no maximum.

Valid values are 0-999.

SDSF searches the OPERLOG data until it finds enough records to fill the screen, or until it reaches the limit, whichever comes first.

Users can override *hours* with the LOGLIM command. Under ISPF, the LOGLIM value is saved across sessions.

OPTIONS	ISFPMAC
SCHARS ('*%')   (' <i>search-characters</i> ')	SCHARS=*%   <i>search-characters</i>

Specifies the generic and placeholder characters. These characters are used wherever pattern matching is supported.

The values for *search-characters* are of the form *ab*, where *a* is the generic character and *b* is the placeholder character. The values cannot be alphabetic, numeric, or national characters; they cannot be @, #, \$, &;, the ISPF end-of-line character, the current query character, blank, or equal to each other. In addition, using :, ( or ) may interfere with using system symbols with filtering. The defaults are \* and %.

When you use statements, enclose the characters in quotation marks.

OPTIONS	ISFPMAC
SCRSIZE ( <u>1920</u> )   ( <i>screen-size</i> )	SCRSIZE= <u>1920</u>   <i>screen-size</i>

Specifies the maximum size, in characters, of the largest terminal screen on which SDSF will be used. Valid values are 1920 to 99999.

OPTIONS	ISFPMAC
SYSOUT ( <u>A</u> )   ( <i>class</i> )	SYSOUT= <u>A</u>   <i>class</i>

Specifies the default SYSOUT class for the SDSF PRINT command.

OPTIONS	ISFPMAC
TIMEOUT ( <u>5</u> )   ( <i>seconds</i> )	TIMEOUT= <u>5</u>   <i>seconds</i>

Specifies the default timeout interval, in seconds, for awaiting sysplex data. A value of 0 means that SDSF should not wait, that is, sysplex data is not available on those panels. This parameter is allowed in the assembler ISFPMAC macro, but the sysplex support requires the statement format of ISFPARMS. Valid values are 0 to 9999.

If this parameter is omitted, 5 seconds is used.

OPTIONS	ISFPMAC
TRCLASS ( <u>A</u> )   ( <i>class</i> )	TRCLASS= <u>A</u>   <i>class</i>

Specifies the default sysout class used by SDSF when dynamically allocating a trace file.

OPTIONS	ISFPMAC
UNALLOC ( <u>NO</u> )   (YES)	UNALLOC= <u>NO</u>   YES

#### YES

indicates that when an SDSF session is terminated, all dynamically allocated data sets are to be freed.

#### NO

is the default and indicates that SDSF will not free dynamically allocated data sets. They will be available if the user should begin another SDSF session before logging off.

## Server connection (CONNECT)

The CONNECT statement defines the server connection, including the XCF application server name and the action to be taken on SAF indeterminate results. It can also request that XCF not be used to provide sysplex data.

CONNECT can be placed anywhere in the ISFPARMS statements.

### Example of the CONNECT statement

```
CONNECT
      ,AUXSAF(NOFAILRC4)
```

This statement indicates that SDSF and SDSFAUX verify requests should not fail (authorized) when SAF returns an indeterminate result (return code 04).

### CONNECT statement

The following table shows the parameters that you code on a CONNECT statement.

Parameter	Description
<b>AUXPROC(<i>SDSFAUX-procedure-name</i>)</b>	Specifies the SDSFAUX procedure name.
<b>AUXNAME(<i>SDSFAUX-jobname</i>)</b>	Specifies the SDSFAUX job name.
<b>AUXSAF(FAILRC4   NOFAILRC4)</b>	Specifies the action to be taken by the SDSF and SDSFAUX address spaces when a SAF authentication request results in a return code 04 (indeterminate response).
<b>MAXSESSIONS(<i>max-concurrent-sessions</i>)</b>	Specifies the maximum number of concurrent sessions.
<b>XCFSRVNM(<i>server-name</i> SAME NONE)</b>	Defines the XCF application server name, or requests that XCF should not be used to provide sysplex data

The parameters are described in detail below.

#### **AUXPROC(*SDSFAUX-procedure-name*)**

##### ***SDSFAUX-procedure-name***

indicates the procedure name for starting SDSFAUX. The default is SDSFAUX.

#### **AUXNAME(*SDSFAUX-job-name*)**

##### ***SDSFAUX-job-name***

indicates the job name to use when starting the SDSFAUX address space. The default is SDSFAUX.

## AUXSAF(**FAILRC4**|**NOFAILRC4**)

### **FAILRC4**

indicates that SDSF and SDSFAUX verify requests should fail (not authorized) when SAF returns an indeterminate result (return code 04). This is the default.

### **NOFAILRC4**

indicates that SDSF and SDSFAUX verify requests should not fail (authorized) when SAF returns an indeterminate result (return code 04).

## MAXSESSIONS(*max-concurrent-sessions*)

### *max-concurrent-sessions*

specifies the maximum number of concurrent SDSF sessions per address space. Any attempt to start an SDSF session after this limit is reached results in a connection failure to the SDSF server. Valid values are 2 - 64. The default value is 32.

## XCFSRVNM(**SAME**|*server-name*|**NONE**)

### **SAME**

indicates that the XCF application server name is derived from the SDSF server name. This is the default.

When you use SAME, all SDSF servers that are to participate in sysplex requests must have the same name. (The server name is either the job name or the started task ID.)

### *server-name*

specifies the customizable portion of the XCF application server name, ISFSRVR.*server-name*. *server-name* can be up to 8 characters, and can consist of alphabetic characters, numeric characters and the national characters @, #, or \$.

When you use *server-name*, the names of the SDSF servers that are to participate in sysplex requests do not need to be the same.

### **NONE**

indicates that the server should not identify itself to XCF and so will not respond to sysplex requests through XCF. A value of NONE for a remote system requests that this remote system not be included in the sysplex-wide data.

## Group authorization parameters (**GROUP** or **ISFGRP**)

A GROUP statement defines:

- A group of users
- Customization values, such as columns on SDSF panels, and date format

**Note:** Field lists for panels added in this release cannot be specified using the ISFGRP macro. Field lists for those panels can only be specified through ISFPRMxx.

## Using SAF to control group membership

You can define membership in the groups in ISFPARMS with SAF.

SDSF scans ISFPARMS from the beginning and assigns users to the first group for which they are qualified. This means that the order of the group definitions is important: Arrange them from most selective to least selective.

A user must be assigned to a group in order to use SDSF. Users can display the name of the group to which they belong with the WHO command. When a user tries to access SDSF but is not assigned to any group, SDSF issues message ISF024I. For more information, see [“Access requirements for SDSF users” on page 225](#).

When using SAF to define who belongs to an ISFPARMS group, you:

1. Assign a name to each group, as follows:

- With a GROUP statement, using the NAME parameter.
  - With an ISFGRP macro, using the macro label. The label must start in column 1 and be 1-8 characters. It must conform to standard assembler language programming conventions and be unique within ISFPARMS.
2. Define SAF profiles `GROUP.group-name.server-name`, in the SDSF class, and permit users to them as appropriate. For more information, see [“Membership in groups” on page 284](#).

SDSF works through the groups in ISFPARMS, checking for READ access to the SAF resource `GROUP.group-name.server-name` in the SDSF class. If the user is authorized to the group through the SAF profile, then the user is assigned to the group, regardless of whether he may be authorized to groups that occur later in ISFPARMS. If the user is not authorized to the group through the SAF profile, SDSF goes on to the next group.

If you do not assign a name to a group, SDSF generates one: ISF plus the index value of the group, in the format `ISFnnnnn`. However, because this name will change when you add or subtract groups from ISFPARMS, it is not suitable for use with SAF. To avoid conflicts with the SDSF-generated names, you should *not* assign names in the format `ISFnnnnn`.

The ISFPARMS and statements shipped with SDSF use the following names:

- ISFSPROG for group 1
- ISFOPER for group 2
- ISFUSER for group 3

## Group function

SAF is used to map a user to a group. Once a user is mapped to a group, various default options can be associated with the group.

## Group function parameters reference

All parameters apply in the JES2 environment; those parameters that apply in the JES3 environment are indicated in the table.

**Note:** You cannot specify field lists for new panels added in this release by using the ISFPARMS ISFGRP macro. All new configuration options are supported through ISFPRMxx. In addition, alternate field lists are no longer implemented: new panels support only a primary field list.

GROUP	ISFGRP	Description
<b>ACTION (NONE)   (ALL)   (routing-code-list)</b>	ACTION= <u>NONE</u>   ALL   (routing-code-list)	Display of outstanding WTORs in LOG
<b>ACTIONBAR (YES)   (NO)</b>	ACTIONBAR= <u>YES</u>   NO	Display of the action bar
<b>ADFLDS(FLD-name)</b>		Primary field list for AD
<b>APFFLDS (FLD-name)</b>	APFFLDS= <i>ISFFLD-label</i>	Primary field list for APF
<b>APFFLD2 (FLD-name)</b>	APFFLD2= <i>ISFFLD-label</i>	Alternate field list for APF
<b>APPC (ON)   (OFF)</b>	APPC= <u>ON</u>   OFF	Display of APPC transaction sysout (JES2 only)
<b>ASFLDS (FLD-name)</b>	ASFLDS= <i>ISFFLD-label</i>	Primary field list for AS
<b>ASFLD2 (FLD-name)</b>	ASFLD2= <i>ISFFLD-label</i>	Alternate field list for AS
<b>AUPDT (2)   (interval)</b>	AUPDT= <u>2</u>   <i>interval</i>	Minimum auto update interval
<b>BROWSE (S   SB   SE   NONE)</b>	BROWSE=S   SB   SE   <u>NONE</u>	Default browse action character



GROUP	ISFGRP	Description
<b>CDEFLDS (FLD-name)</b>		Primary field list for job module panel
<b>CFCFLDS (FLD-name)</b>		Primary field list for CFC
<b>CFDFLDS (FLD-name)</b>		Primary field list for CFD
<b>CFSFLDS (FLD-name)</b>		Primary field list for CFS
<b>CKFLDS (FLD-name)</b>	CKFLDS= <i>ISFFLD-label</i>	Primary field list for CK
<b>CKFLD2 (FLD-name)</b>	CKFLD2= <i>ISFFLD-label</i>	Alternate field list for CK
<b>CKHFLDS (FLD-name)</b>	CKHFLDS= <i>ISFFLD-label</i>	Primary field list for CKH
<b>CKHFLD2 (FLD-name)</b>	CKHFLD2= <i>ISFFLD-label</i>	Alternate field list for CKH
<b>CKPTFLDS (FLD-name)</b>		Primary field list for CKPT
<b>CMDAUTH (auth-list)</b>	CMDAUTH=( <i>auth-list</i> )	Action characters, overtypes, / commands
<b>CMDLEV (0)   (level)</b>	CMDLEV= <u>0</u>   <i>level</i>	Command authorization level (JES2 only)
<b>CONFIRM (ON)   (OFF)   (ALWAYS)</b>	CONFIRM= <u>ON</u>   OFF   ALWAYS	Confirmation of action characters
<b>CPUFMT(LONG)   (SHORT)</b>	CPUFMT= <u>LONG</u>   SHORT	Format of CPU on DA title line
<b>CSIFLDS (FLD-name)</b>		Primary field list for CS
<b>CSRFLDS (FLD-name)</b>		Primary field list for CSR
<b>CTITLE (ASIS)   (UPPER)</b>	CTITLE= <u>ASIS</u>   UPPER	Case of text, such as column titles
<b>CURSOR (ON)   (OFF)   TOP</b>	CURSOR= <u>ON</u>   OFF   TOP	Cursor placement
<b>CUSTOM(<i>proplist-name</i>)</b>	Not supported	Customization of properties
<b>DADFLT (types-and-pos)</b>	DADFLT=( <i>types-and-pos</i> )	Types of jobs on DA
<b>DATE (MMDDYYYY)   (DDMMYYYY)   (YYYYMMDD)</b>	DATE= <u>MMDDYYYY</u>   DDMMYYYY   YYYYMMDD	Date format
<b>DATESEP (/)   (-)   (.)</b>	DATESEP= <u>/</u>   -   .	Date separator
<b>DEST (NTBL-name)</b>	DEST= <i>ISFNTBL-label</i>	Destinations
<b>DEVFLDS (FLD-name)</b>		Primary field list for DEV
<b>DFIELDS (FLD-name)</b>	DFIELDS= <i>ISFFLD-label</i>	Primary field list for DA
<b>DFIELD2 (FLD-name)</b>	DFIELD2= <i>ISFFLD-label</i>	Alternate field list for DA
<b>DISPLAY (OFF)   (ON)</b>	DISPLAY=OFF   ON	Display of current values
<b>DSPAUTH (auth-list)</b>	DSPAUTH=( <i>auth-list</i> )	Types of jobs the group can browse
<b>DYNXFLDS (FLD-name)</b>	DYNXFLDS= <i>ISFFLD-label</i>	Primary field list for DYNX
<b>DYNXFLD2 (FLD-name)</b>	DYNXFLD2= <i>ISFFLD-label</i>	Alternate field list for DYNX
<b>EMCSFLDS (FLD-name)</b>		Primary field list for EMCS
<b>EMCSAUTH (MASTER   ALL)</b>	EMCSAUTH= <u>MASTER</u>   ALL	Authority used with the EMCS console

GROUP	ISGRP	Description
<b>EMCSREQ (YES   NO)</b>	EMCSREQ=YES   <u>NO</u>	EMCS required for system commands
<b>ENCFLDS (FLD-name)</b>	ENCFLDS=ISFFLD-label	Primary field list for ENC
<b>ENCFLD2 (FLD-name)</b>	ENCFLD2=ISFFLD-label	Alternate field list for ENC
<b>ENQFLDS (FLD-name)</b>	ENQFLDS=ISFFLD-label	Primary field list for ENQ
<b>ENQFLD2 (FLD-name)</b>	ENQFLD2=ISFFLD-label	Alternate field list for ENQ
<b>FSFLDS (FLD-name)</b>		Primary field list for FS
<b>GPLEN (prefix-length)</b>	GPLEN=prefix-length	Length of the group prefix
<b>GPREF (group-prefix)</b>	GPREF=group-prefix	Group prefix string
<b>GQEFLDS (group-prefix)</b>		Primary field list for GQE (action character JCS)
<b>GTFLDS (FLD-name)</b>		Primary field list for GT
<b>HFIELDS (FLD-name)</b>	HFIELDS=ISFFLD-label	Primary field list for H
<b>HFIELD2 (FLD-name)</b>	HFIELD2=ISFFLD-label	Alternate field list for H
<b>ICMD (NTBL-name)</b>	ICMD=ISFNTBL-label	Jobs to be included with CMDAUTH
<b>IDEST (NTBL-name)</b>	IDEST=ISFNTBL-label	Initial list of destinations
<b>IDSP (NTBL-name)</b>	IDSP=ISFNTBL-label	Jobs to be included with DSPAUTH
<b>IDSPD (NTBL-name)</b>	IDSPD=ISFNTBL-statement	Jobs for which messages can be displayed
<b>IFIELDS (FLD-name)</b>	IFIELDS=ISFFLD-label	Primary field list for I
<b>IFIELD2 (FLD-name)</b>	IFIELD2=ISFFLD-label	Alternate field list for I
<b>ILOGCOL (1)   (position)</b>	ILOGCOL= <u>1</u>   position	Starting column for LOG
<b>INPUT (OFF)   (ON)</b>	INPUT= <u>OFF</u>   ON	SYSIN data sets shown with browse
<b>INTFLDS (FLD-name)</b>	INTFLDS=ISFFLD-label	Primary field list for INIT
<b>INTFLD2 (FLD-name)</b>	INTFLD2=ISFFLD-label	Alternate field list for INIT
<b>ISTATUS (NTBL-name)</b>	ISTATUS=ISFNTBL-name	Jobs included on DA, H, I, O, PS and ST
<b>ISYS (LOCAL)   (NONE)</b>	ISYS= <u>LOCAL</u>   NONE	Systems shown on sysplex panels
<b>JCFLDS (FLD-name)</b>	JCFLDS=ISFFLD-label	Primary field list for JC
<b>JCFLD2 (FLD-name)</b>	JCFLD2=ISFFLD-label	Alternate field list for JC
<b>JDDFLDS (FLD-name)</b>	JDDFLDS=ISFFLD-label	Primary field list for JD
<b>JDDFLD2 (FLD-name)</b>	JDDFLD2=ISFFLD-label	Alternate field list for JD
<b>JDDNFLDS (FLD-name)</b>	JDDNFLDS=ISFFLD-label	Primary field list for JDDN
<b>JDMFLDS (FLD-name)</b>	JDMFLDS=ISFFLD-label	Primary field list for JM
<b>JDMFLD2 (FLD-name)</b>	JDMFLD2=ISFFLD-label	Alternate field list for JM

GROUP	ISFGRP	Description
<b>JDPFLDS (FLD-name)</b>	JDPFLDS= <i>ISFFLD-label</i>	Primary field list for Job Dependency
<b>JDPFLD2 (FLD-name)</b>	JDPFLD2= <i>ISFFLD-label</i>	Alternate field list for Job Dependency
<b>JDSFLDS (FLD-name)</b>	JDSFLDS= <i>ISFFLD-label</i>	Primary field list for JDS
<b>JDSFLD2 (FLD-name)</b>	JDSFLD2= <i>ISFFLD-label</i>	Alternate field list for JDS
<b>JDYFLDS (FLD-name)</b>	JDYFLDS= <i>ISFFLD-label</i>	Primary field list for JY
<b>JDYFLD2 (FLD-name)</b>	JDYFLD2= <i>ISFFLD-label</i>	Alternate field list for JY
<b>JESFLDS (FLD-name)</b>		Primary field list for JES
<b>JGFLDS (FLD-name)</b>	JGFLDS= <i>ISFFLD-label</i>	Primary field list for JG
<b>JGFLD2 (FLD-name)</b>	JGFLD2= <i>ISFFLD-label</i>	Alternate field list for JG
<b>JMOFLDS (FLD-name)</b>		Primary field list for JMO
<b>JRIFLDS (FLD-name)</b>		Primary field list for JRI
<b>JRJFLDS (FLD-name)</b>		Primary field list for JRJ
<b>JSFLDS (FLD-name)</b>	JSFLDS= <i>ISFFLD-label</i>	Primary field list for JS
<b>JSFLD2 (FLD-name)</b>	JSFLD2= <i>ISFFLD-label</i>	Alternate field list for JS
<b>JOFLDS (FLD-name)</b>	JOFLDS= <i>ISFFLD-label</i>	Primary field list for JO (JES3 only)
<b>JOFLD2 (FLD-name)</b>	JOFLD2= <i>ISFFLD-label</i>	Alternate field list for JO (JES3 only)
<b>LINEFLDS (FLD-name)</b>	LINEFLDS= <i>ISFFLD-name</i>	Primary field list for LI
<b>LINEFLD2 (FLD-name)</b>	LINEFLD2= <i>ISFFLD-name</i>	Alternate field list for LI
<b>LNKFLDS (FLD-name)</b>	LNKFLDS= <i>ISFFLD-name</i>	Primary field list for LNK
<b>LNKFLD2 (FLD-name)</b>	LNKFLD2= <i>ISFFLD-name</i>	Alternate field list for LNK
<b>LOG (OPERACT)   (OPERLOG)   (SYSLOG)</b>	LOG= <u>OPERACT</u>   OPERLOG   SYSLOG	Default Log panel
<b>LPAFLDS (FLD-name)</b>	LPAFLDS= <i>ISFFLD-name</i>	Primary field list for LPA
<b>LPAFLD2 (FLD-name)</b>	LPAFLD2= <i>ISFFLD-name</i>	Alternate field list for LPA
<b>LPDFLDS (FLD-name)</b>		Primary field list for LPD
<b>MASFLDS (FLD-name)</b>	MASFLDS= <i>ISFFLD-name</i>	Primary field list for MAS and JP
<b>MASFLD2 (FLD-name)</b>	MASFLD2= <i>ISFFLD-name</i>	Alternate field list for MAS and JP
<b>MEMFLDS(FLD-name)</b>		Primary field list for MEM
<b>NAFLDS (FLD-name)</b>		Primary field list for NA
<b>NCFLDS(FLD-name)</b>	NCFLDS= <i>ISFFLD-name</i>	Primary field list for NC
<b>NCFLD2(FLD-name)</b>	NCFLD2S= <i>ISFFLD-name</i>	Alternate field list for NC
<b>NODEFLDS (FLD-name)</b>	NODEFLDS= <i>ISFFLD-name</i>	Primary field list for NO
<b>NSFLDS (FLD-name)</b>	NSFLDS= <i>ISFFLD-name</i>	Primary field list for NS
<b>NSFLD2 (FLD-name)</b>	NSFLD2= <i>ISFFLD-name</i>	Alternate field list for NS

GROUP	ISFGRP	Description
<b>NODEFLD2 (FLD-name)</b>	NODEFLD2= <i>ISFFLD-name</i>	Alternate field list for NO
<b>OFIELDS (FLD-name)</b>	OFIELDS= <i>ISFFLD-name</i>	Primary field list for O
<b>OFLD2 (FLD-name)</b>	OFLD2= <i>ISFFLD-name</i>	Alternate field list for O
<b>OMVSFLDS (FLD-name)</b>		Primary field list for OMVS
<b>OWNER (NONE)   (USERID)</b>	OWNER= <u>NONE</u>   USERID	Default for OWNER
<b>PAGFLDS (FLD-name)</b>	PAGFLDS= <i>ISFFLD-name</i>	Primary field list for PAG
<b>PAGFLD2 (FLD-name)</b>	PAGFLD2= <i>ISFFLD-name</i>	Alternate field list for PAG
<b>PARMFLDS (FLD-name)</b>	PARMFLDS= <i>ISFFLD-name</i>	Primary field list for PARM
<b>PARMFLD2 (FLD-name)</b>	PARMFLD2= <i>ISFFLD-name</i>	Alternate field list for PARM
<b>PCFLDS(FLD-name)</b>		Primary field list for PC
<b>PREFIX (NONE)   (USERID)   (GROUP)</b>	PREFIX= <u>NONE</u>   USERID   GROUP	Default for PREFIX
<b>PROCFLDS (FLD-name)</b>	PROCFLDS= <i>ISFFLD-label</i>	Primary field list for PROC
<b>PROCFLD2 (FLD-name)</b>	PROCFLD2= <i>ISFFLD-label</i>	Alternate field list for PROC
<b>PRTFLDS (FLD-name)</b>	PRTFLDS= <i>ISFFLD-label</i>	Primary field list for PR
<b>PRTFLD2 (FLD-name)</b>	PRTFLD2= <i>ISFFLD-label</i>	Alternate field list for PR
<b>PSFLDS (FLD-name)</b>	PSFLDS= <i>ISFFLD-label</i>	Primary field list for PS
<b>PSFLD2 (FLD-name)</b>	PSFLD2= <i>ISFFLD-label</i>	Alternate field list for PS
<b>PUNFLDS (FLD-name)</b>	PUNFLDS= <i>ISFFLD-label</i>	Primary field list for PUN
<b>PUNFLD2 (FLD-name)</b>	PUNFLD2= <i>ISFFLD-label</i>	Alternate field list for PUN
<b>RDRFLDS (FLD-name)</b>	RDRFLDS= <i>ISFFLD-label</i>	Primary field list for RDR
<b>RDRFLD2 (FLD-name)</b>	RDRFLD2= <i>ISFFLD-label</i>	Alternate field list for RDR
<b>REPCFLDS (FLD-name)</b>		Primary field list for REPC
<b>RGRPFLDS (FLD-name)</b>		Primary field list for RGRP
<b>RESFLDS (FLD-name)</b>	RESFLDS= <i>ISFFLD-label</i>	Primary field list for RES
<b>RESFLD2 (FLD-name)</b>	RESFLD2= <i>ISFFLD-label</i>	Alternate field list for RES
<b>RMAFLDS (FLD-name)</b>		Primary field list for RMA
<b>RMFLDS (FLD-name)</b>	RMFLDS= <i>ISFFLD-label</i>	Primary field list for RM (JES2 only)
<b>RMFLD2 (FLD-name)</b>	RMFLD2= <i>ISFFLD-label</i>	Alternate field list for RM (JES2 only)
<b>RSYS (LOCAL   NONE)</b>	RSYS=LOCAL   <u>NONE</u>	WTORs shown on Log
<b>SEFLDS (FLD-name)</b>	SEFLDS= <i>ISFFLD-label</i>	Primary field list for SE
<b>SEFLD2 (FLD-name)</b>	SEFLD2= <i>ISFFLD-label</i>	Alternate field list for SE
<b>SMSGFLDS (FLD-name)</b>		Primary field list for SMSG
<b>SMSVFLDS (FLD-name)</b>		Primary field list for SMSV
<b>SOFLDS (FLD-name)</b>	SOFLDS= <i>ISFFLD-label</i>	Primary field list for SO (JES2 only)

GROUP	ISFGRP	Description
<b>SOFLD2 (FLD-name)</b>	SOFLD2= <i>ISFFLD-label</i>	Alternate field list for SO (JES2 only)
<b>SPFLDS (FLD-name)</b>	SPFLDS= <i>ISFFLD-label</i>	Primary field list for SP
<b>SPFLD2 (FLD-name)</b>	SPFLD2= <i>ISFFLD-label</i>	Alternate field list for SP
<b>SRCHFLDS (FLD-name)</b>	SRCHFLDS= <i>ISFFLD-name</i>	Primary field list for SRCH
<b>SRCHFLD2 (FLD-name)</b>	SRCHFLD2= <i>ISFFLD-name</i>	Alternate field list for SRCH
<b>SRFLDS (FLD-name)</b>	SRFLDS= <i>ISFFLD-label</i>	Primary field list for SR
<b>SRFLD2 (FLD-name)</b>	SRFLD2= <i>ISFFLD-label</i>	Alternate field list for SR
<b>SRVCFLDS (FLD-name)</b>		Primary field list for SRVC
<b>SSIFLDS (FLD-name)</b>		Primary field list for SSI
<b>STFLDS (FLD-name)</b>	STFLDS= <i>ISFFLD-label</i>	Primary field list for ST
<b>STFLD2 (FLD-name)</b>	STFLD2= <i>ISFFLD-label</i>	Alternate field list for ST
<b>SVCFLDS (FLD-name)</b>		Primary field list for SVC
<b>SYMFLDS (FLD-name)</b>	SYMFLDS= <i>ISFFLD-label</i>	Primary field list for SYM
<b>SYMFLD2 (FLD-name)</b>	SYMFLD2= <i>ISFFLD-label</i>	Alternate field list for SYM
<b>SYSFLDS (FLD-name)</b>	SYSFLDS= <i>ISFFLD-name</i>	Primary field list for SYS
<b>SYSFLD2 (FLD-name)</b>	SYSFLD2= <i>ISFFLD-name</i>	Alternate field list for SYS
<b>SYSID (system-id)</b>	SYSID= <i>system-id</i>	System ID for LOG in a JES2 environment (JES2 only)
<b>SYSID3 (system-id)</b>	Not supported	System ID for LOG in a JES3 environment
<b>SYSPFLDS (FLD-name)</b>		Primary field list for SYSP
<b>TCBFLDS (FLD-name)</b>		Primary field list for job tasks panel
<b>UPCTAB (TRTAB2)   (TRTAB-name)</b>	UPCTAB= <u>TRTAB2</u>   <i>TRTAB-name</i>	Upper case translation table
<b>USIFLDS(FLD-name)</b>		Primary field list for USI
<b>VALTAB (TRTAB)   (TRTAB-name)</b>	VALTAB= <u>TRTAB</u>   <i>TRTAB-name</i>	Valid character translation table
<b>VIO (SYSALLDA)   (unit-name)</b>	VIO= <u>SYSALLDA</u>   <i>unit-name</i>	VIO unit name for viewing page-mode output
<b>VMAPFLDS (FLD-name)</b>		Primary field list for VMAP
<b>WKLDFLDS (FLD-name)</b>		Primary field list for WKLD
<b>WLMFLDS(FLD-name)</b>		Primary field list for WLM
<b>XCFMFLDS (FLD-name)</b>		Primary field list for XCFM
<b>XCMD (NTBL-name)</b>	XCMD= <i>ISFNTBL-label</i>	Jobs to be excluded when processing CMDAUTH
<b>XDSP (NTBL-name)</b>	XDSP= <i>ISFNTBL-label</i>	Jobs to be excluded when processing DSPAUTH
<b>XDSPD (NTBL-name)</b>	XDSPD= <i>ISFNTBL-label</i>	Jobs to be excluded for which messages can be displayed

GROUP	ISFGRP	Description
<b>XSTATUS (NTBL-name)</b>	XSTATUS=ISFNTBL-label	Jobs excluded from DA, H, I, O, PS and ST
<b>GROUP</b>	<b>ISFGRP</b>	
ACTION (NONE)   (ALL)   (routing-code-list)	ACTION=NONE   ALL   (routing-code-list)	

Specifies routing codes that determine which write-to-operator-with-reply (WTOR) messages should be displayed at the bottom of the SYSLOG panel for members of this group.

#### ALL

specifies that WTOR messages for MCS routing codes 1 through 28 are to be displayed.

#### NONE

specifies that no WTOR messages are to be displayed. This is the default.

#### (routing-code-list)

specifies that WTOR messages for specific routing codes are to be displayed. If you specify more than one option in your routing code list, enclose the list in parentheses and separate each option with a comma. The list can be made up of one or more of the following options:

- One or more decimal routing codes. The possible routing codes are 1 through 28.
- MVS, which enables the 12 routing codes used by MVS-JES. The routing codes used by MVS-JES are 1 through 12.
- USER, which enables the routing codes reserved for customer use. The routing codes reserved for customer use are 13 through 28.
- ALL or NONE, if you are using statements. ALL and NONE are described above. If included in the list, they are added to other items in the list.

The setting of the ACTION parameter can be changed by an authorized user through the use of the ACTION command.

<b>GROUP</b>	<b>ISFGRP</b>
ACTIONBAR (YES)   (NO)	ACTIONBAR=YES   NO

Sets an initial value for the display of the action bar.

#### YES

indicates that the action bar is displayed.

#### NO

indicates that the action bar is not displayed.

If the ACTIONBAR parameter is omitted, the initial setting is to display the action bar.

Users can override the ACTIONBAR setting with the Set Screen Characteristics pop-up.

<b>GROUP</b>	<b>ISFGRP</b>
ADFLDS (FLD-statement-name)	

Names an FLD statement that defines the primary field list for the AD panel. If this parameter is omitted, the default primary field list is used.

<b>GROUP</b>	<b>ISFGRP</b>
APFFLDS (FLD-statement-name)	APFFLDS=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the APF panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
APFFLD2 ( <i>FLD-statement-name</i> )	APFFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **Alternate** variable field list for the APF panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
APPC ( <u>ON</u> )   (OFF)	APPC= <u>ON</u>   OFF

Controls whether a group member will see APPC transactions on the H and O panels. (Applies to JES2 only.)

**ON**

indicates that APPC transactions are displayed.

**OFF**

indicates that APPC transactions are not displayed.

If the APPC parameter is omitted, APPC transactions are displayed. Users can override the APPC setting with the APPC command or pull-down choice.

GROUP	ISFGRP
ASFLDS ( <i>FLD-statement-name</i> )	ASFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the AS panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
ASFLD2 ( <i>FLD-statement-name</i> )	ASFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **Alternate** variable field list for the AS panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
AUPDT ( <u>2</u> )   ( <i>interval</i> )	AUPDT= <u>2</u>   <i>interval</i>

Specifies the minimum automatic update interval, in seconds, that can be specified by members of this group. *interval* is a number from 0 to 255. The default is 2. A value of 0 indicates that the members of this group are not allowed to use the automatic update facility.

GROUP	ISFGRP
BROWSE (S   SB   SE   NONE)	BROWSE=S   SB   SE   NONE

Specifies the default browse action character, which is invoked when a user selects a row on a panel by placing the cursor in the NP column and pressing Enter. This applies to all panels that support browse.

**S**

is SDSF browse.

**SB**

is ISPF browse.

**SE**

is ISPF edit.

**NONE**

specifies that there should be no default browse action character. This is also the case if this parameter is omitted.

GROUP	ISFGRP
CDEFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the job module panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
CFCFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the CFC panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
CFDFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the CFD panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
CFSFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the CFS panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
CKFLDS ( <i>FLD-statement-name</i> )	CKFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the CK panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
CKFLD2 ( <i>FLD-statement-name</i> )	CKFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the CK panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
CKHFLDS ( <i>FLD-statement-name</i> )	CKHFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the CKH panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
CKHFLD2 ( <i>FLD-statement-name</i> )	CKHFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the CKH panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
CKPTFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the JES checkpoint panel. If this parameter is omitted, the default primary variable field list is used.



GROUP	ISFGRP
CMDAUTH ( <i>authorization-list</i> )	

As of SDSF 2.5, all authorization is performed using SAF. CMDAUTH can be used with the MSG option only. For compatibility, other options in the *authorization-list* are accepted, but ignored.

(*authorization-list*) specifies CMDAUTH values. If the list contains more than one value, the values must be separated by a comma.

#### MSG

issues a security WTO message whenever a member of this group issues a command (the WTO message is always issued when an SDSF user attempts to issue a system command for which the user is not authorized). The WTO message is also issued for all SSI requests.

The following options are obsolete and are provided for reference only:

- ALL (JES2 only)
- DEST (JES2 only)
- DISPLAY (JES2 only)
- GROUP (JES2 only)
- INIT (JES2 only)
- NOTIFY (JES2 only)
- USERID (JES2 only)

GROUP	ISFGRP
CMDLEV ( <u>0</u> )   ( <i>level</i> )	CMDLEV= <u>0</u>   <i>level</i>

As of SDSF 2.5, all authorization is performed using SAF. CMDLEV is obsolete. For compatibility, the parameter and its options are accepted, but ignored.

GROUP	ISFGRP
CONFIRM ( <u>ON</u> )   (OFF)   (ALWAYS)	CONFIRM= <u>ON</u>   OFF   ALWAYS

Specifies whether SDSF requests confirmation of destructive action characters (such as cancel or purge).

#### ON

indicates that the action characters will require confirmation.

If CONFIRM is omitted, the value is ON.

#### OFF

indicates that the action characters will not require confirmation.

#### ALWAYS

indicates that the action characters will require confirmation, and that users cannot turn off confirmation with the SET CONFIRM OFF command.

GROUP	ISFGRP
CPUFMT ( <u>LONG</u> )   (SHORT)	CPUFMT= <u>LONG</u>   SHORT

Specifies whether SDSF displays the MVS, LPAR and IBM zEnterprise Application Assist Processor (zAAP) views of CPU busy on the title line of the DA panel, or only the MVS view. The LPAR and zAAP views require RMF.

**LONG**

indicates that all values are displayed. The LPAR view is shown only when in LPAR mode. The zAAP view is shown only when a zAAP is defined and the system is in LPAR-mode.

**SHORT**

indicates that only the MVS view is shown.

The MVS view (the first value on the title line) is a better indicator of a CPU bottleneck. The LPAR view (the second value, if present) takes into account several states related to PR/SM. The zAAP view (the third value, if present) shows usage of the IBM zEnterprise Application Assist Processor .

GROUP	ISFGRP
CSRFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the CSR panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
CTITLE ( <u>ASIS</u> )   (UPPER)	CTITLE= <u>ASIS</u>   UPPER

Specifies how the case of text is displayed, specifically:

- Column titles on SDSF panels
- Text on the primary option menu
- Text on the print pop-ups
- Column titles on pop-ups
- Text displayed by SET ACTION
- Column titles displayed by SET DISPLAY
- Pop-ups when SDSF is running under TSO

Note that the case of column titles has no effect on commands that accept column titles as parameters, such as LOCATE or SORT.

**ASIS**

preserves the case. It is the default.

**UPPER**

folds text to uppercase. Column titles are folded to uppercase regardless of how they are defined in field lists in ISFPARMS.

GROUP	ISFGRP
CURSOR ( <u>ON</u> )   (OFF)   (TOP)	CURSOR= <u>ON</u>   OFF   TOP

Specifies how SDSF should control placement of the cursor on tabular panels.

**ON**

causes the cursor to return to the NP column for the last row you worked with. If the row is not on the screen, because it would require a scroll or because system or user activity caused it to be removed from the display, the cursor is returned to the command line.

If CURSOR is omitted, the value is ON.

**OFF**

causes the cursor to return to the command line.

**TOP**

causes the last row you worked with to be scrolled to the top of the screen. The cursor returns to the command line.

GROUP	ISFGRP
CUSTOM ( <i>proplist-name</i> )	Not supported

Names a PROPLIST statement that customizes certain SDSF properties. For information about the PROPLIST statement, see “Customized properties (PROPLIST)” on page 54.

GROUP	ISFGRP
DADFLT ( <i>types-and-positions</i> )	DADFLT=( <i>types-and-positions</i> )

Indicates the default address space types and positions to be shown on the DA panel when members of this group enter a DA command without any parameters. If the list contains more than one item, separate the items with a comma.

If this parameter is not coded with at least one value for address space position (IN, OUT, TRANS, READY) and at least one value for address space type (STC, INIT, TSU, JOB), then no address spaces are displayed when the DA command is entered with no parameters.

The possible values for the parameter follow. When RMF is installed, SDSF uses RMF as the source of data for the panel.

#### IN

Displays swapped-in address spaces

#### OUT

Displays swapped-out address spaces

#### TRANS

Displays address spaces that are in transition

#### READY

Displays address spaces that are ready for execution

#### STC

Displays started tasks

#### INIT

Displays initiators

#### TSU

Displays TSO users

#### JOB

Displays batch jobs

GROUP	ISFGRP
DATE ( <u>MMDD</u> YYYY)   (DD <u>MM</u> YYYY)   (YYYY <u>MMDD</u> )	DATE= <u>MMDD</u> YYYY   D <u>MM</u> YYYY   YYYY <u>MMDD</u>

Sets a date format for this group: *month day year*, *day month year*, or *year month day*. SDSF uses this format when displaying dates on tabular panels and on the title line of the log panels. Commands that accept dates (LOCATE, PRINT, and FILTER) use this format.

If DATE is omitted, SDSF uses MMDDYYYY.

Users can override the date format with the SET DATE command or pop-up.

Specify the separator to be used between month, day, and year with the DATESEP parameter.

GROUP	ISFGRP
DATESEP (/)   (-)   (.)	DATESEP= <u>/</u>   -   .

Sets a date separator for this group: slash (/), dash (-), or period (.). SDSF uses this separator between the month, day, and year when displaying dates on tabular panels and on the title line of the log panels. Commands with dates as parameters (LOCATE, PRINT, and FILTER) accept this separator.

If DATESEP is omitted, SDSF uses the slash (/).

Users can override the date separator with the SET DATE command or pop-up.

GROUP	ISFGRP
DEST ( <i>NTBL-statement-name</i> )	DEST= <i>ISFNTBL-macro-label</i>

As of SDSF 2.5, all authorization is performed using SAF. DEST is obsolete. For compatibility, the parameter and its options are accepted, but ignored.

GROUP	ISFGRP
DEVFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the DEV panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
DFIELDS ( <i>FLD-statement-name</i> )	DFIELDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the DA panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
DFIELD2 ( <i>FLD-statement-name</i> )	DFIELD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the DA panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
DISPLAY ( <u>OFF</u> )   (ON)	DISPLAY= <u>OFF</u>   ON

Specifies whether SDSF is to display the current values for DEST, OWNER, PREFIX, SORT, and FILTER on the SDSF tabular panels. The default is OFF.

Users can query and override the setting with the SET DISPLAY command or pull-down choice.

GROUP	ISFGRP
DSPAUTH ( <i>authorization-list</i> )	DSPAUTH=( <i>authorization-list</i> )

As of SDSF 2.5, all authorization is performed using SAF. DSPAUTH is obsolete. For compatibility, the parameter and its options in the *authorization-list* are accepted, but ignored.

GROUP	ISFGRP
DYNXFLDS ( <i>FLD-statement-name</i> )	DYNXFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the DYNX panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
DYNXFLD2 ( <i>FLD-statement-name</i> )	DYNXFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **Alternate** variable field list for the DYNX panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
EMCS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the EMCS panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
EMCSAUTH ( <u>MASTER</u>   ALL)	EMCSAUTH= <u>MASTER</u>   ALL

Indicates the authority that will be used when activating the EMCS console. For a description of SDSF's use of the console, see [“Issuing MVS and JES commands”](#) on page 356.

**MASTER**

specifies MASTER authority. This is the default.

**ALL**

specifies SYS,IO,CONS authority. Note that profiles in the OPERCMDS class can be used to permit SDSF users to commands that require MASTER authority when EMCSAUTH=ALL is specified in ISFPARMS.

GROUP	ISFGRP
EMCSREQ (YES   <u>NO</u> )	EMCSREQ=YES   <u>NO</u>

Controls whether SDSF must use the EMCS console for system commands. For a description of SDSF's use of the console, see [“Issuing MVS and JES commands”](#) on page 356.

**YES**

specifies that SDSF must use the EMCS console.

**NO**

specifies that the EMCS console is not required. SDSF will use console ID 0 (INTERNAL) to issue commands when an EMCS console is not active. This is the default.

GROUP	ISFGRP
ENCFLDS ( <i>FLD-statement-name</i> )	ENCFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the ENC panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
ENCFLD2 ( <i>FLD-statement-name</i> )	ENCFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the ENC panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
ENQFLDS ( <i>FLD-statement-name</i> )	ENQFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the ENQ panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
ENQFLD2 ( <i>FLD-statement-name</i> )	ENQFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the ENQ panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
GPLEN ( <i>prefix-length</i> )	GPLEN= <i>prefix-length</i>

Defines a prefix for a group.

To create the prefix, SDSF takes as many characters as are specified by *group-prefix-length* from the members' TSO user IDs. *Group-prefix-length* can be 1 to 8.

For example, if you have operator IDs defined as OPER1, OPER2, and OPER3, you might put the operators in a group with a group membership parameter and set GPLEN to 4 to define a group prefix of OPER for that group.

You can code either GPLEN or GPREF, but not both. GPREF is described below. GPLEN works in conjunction with a value of GROUP for the PREFIX parameter.

GROUP	ISFGRP
GPREF ( <i>group-prefix</i> )	GPREF= <i>group-prefix</i>

Specifies a prefix for an authorization group. The group prefix can be 1 to 8 characters and can include the generic and placeholder characters (\* and % by default).

**Note:** The generic search character must be appended to the group prefix in order for it to be treated like a prefix.

You can code either GPLEN or GPREF, but not both. GPREF works in conjunction with GROUP for the PREFIX parameter.

GROUP	ISFGRP
GTFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the GT panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
HFIELD5 ( <i>FLD-statement-name</i> )	HFIELD5= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the H panel. If this parameter is omitted, the default primary variable field list is used. (Applies to JES2 only.)

GROUP	ISFGRP
HFIELD2 ( <i>FLD-statement-name</i> )	HFIELD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the H panel. If this parameter is omitted, the default alternate variable field list is used. (Applies to JES2 only.)

GROUP	ISFGRP
ICMD ( <i>NTBL-statement-name</i> )	ICMD= <i>ISFNTBL-macro-label</i>

As of SDSF 2.5, all authorization is performed using SAF. ICMD is obsolete. For compatibility, the parameter and its options are accepted, but ignored.

GROUP	ISFGRP
IDEST ( <i>NTBL-statement-name</i> )	IDEST= <i>ISFNTBL-macro-label</i>

Names an ISFNTBL macro or NTBL statement that determines which jobs SDSF displays at session initialization to members of the group. This parameter does not affect the Display Active Users panel. See also the ISTATUS and XSTATUS parameters.

If the IDEST parameter is coded for a group, the SDSF panels are initialized with only those jobs having destination names listed in the NTBL macro or NTBL statement. The ISFNTBL macro or NTBL statement can contain from 1 to 4 valid destination names. Any of the names in this list that are invalid (not defined to the active JES subsystem), or to which the user is not authorized through SAF, are not used as initial destinations.

If the IDEST parameter is not coded, the SDSF panels are initialized with jobs for all destinations, unless a member is not authorized to a destination name through the SAF security scheme.

The members can use the DEST command to display jobs and outputs for *all* destinations, regardless of the user ID on the node.

GROUP	ISFGRP
IDSP ( <i>NTBL-statement-name</i> )	IDSP= <i>ISFNTBL-macro-label</i>

As of SDSF 2.5, all authorization is performed using SAF. IDSP is obsolete. For compatibility, the parameter and its options are accepted, but ignored.

GROUP	ISFGRP
IDSPD ( <i>NTBL-statement-name</i> )	IDSPD= <i>ISFNTBL-statement-name</i>

As of SDSF 2.5, all authorization is performed using SAF. IDSPD is obsolete. For compatibility, the parameter and its options are accepted, but ignored.

GROUP	ISFGRP
IFIELDS ( <i>FLD-statement-name</i> )	IFIELDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the I panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
IFIELD2 ( <i>FLD-statement-name</i> )	IFIELD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the I panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
ILOGCOL ( <u>1</u> )   ( <i>position</i> )	ILOGCOL= <u>1</u>   <i>position</i>

Indicates which position (or column) of the SYSLOG or OPERLOG will be the first position displayed on the panel. *position-number* can be any number from 1 through 255.

This parameter is ignored if the screen on which the SYSLOG or OPERLOG is displayed can display the entire width of the SYSLOG/OPERLOG. Also, if the value for *position-number* is so high that less than a full screen of data is displayed on the SYSLOG or OPERLOG panel, SDSF adjusts the starting position number to display a full screen of data. For example, if the width of the screen on which the SYSLOG is displayed is 80 characters, SDSF adjusts the value of *position-number* to ensure that 80 characters of data are displayed.

GROUP	ISFGRP
INPUT ( <u>OFF</u> )   (ON)	INPUT= <u>OFF</u>   ON

Sets an initial value to control whether SYSIN data sets are displayed when users browse a job.

**OFF**

specifies that SYSIN data sets should not be displayed.

**ON**

specifies that SYSIN data sets should be displayed.

If INPUT is omitted, OFF is used.

Authorized users can override the INPUT value with the INPUT command or the associated pull-down choice.

GROUP	ISFGRP
INTFLDS ( <i>FLD-statement-name</i> )	INTFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Initiator panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
INTFLD2 ( <i>FLD-statement-name</i> )	INTFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines **alternate** variable field list for the INIT panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
ISTATUS ( <i>NTBL-statement-name</i> )	ISTATUS= <i>ISFNTBL-statement-name</i>

Indicates that jobs whose job names are in the list created by the specified ISFNTBL macro or NTBL statement are to always be displayed on the DA, H, I, O, PS and ST panels unless specifically excluded by the XSTATUS parameter.

There is an exception for the Held Output Queue. When the user enters the H command with no parameter, jobs in the ISTATUS list always appear, except when the user has PREFIX=\*. In this case, jobs that don't match the user's user ID don't appear, even if they are on the ISTATUS list.

GROUP	ISFGRP
ISYS ( <u>LOCAL</u> )   (NONE)	ISYS= <u>LOCAL</u>   NONE

Sets an initial value to limit the data, based on a system, that a group member will see on the sysplex panels. (Applies to JES2 only.)

**LOCAL**

indicates that the panels will show data for the system the user is logged on to.

**NONE**

indicates that data on the panels is not limited by system, that is, all systems in the sysplex will be shown.

If ISYS is omitted, LOCAL is used.

Authorized users can override the ISYS value with the SYSNAME command or pull-down choice.

GROUP	ISFGRP
JCFLDS ( <i>FLD-statement-name</i> )	JCFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Job Class panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JCFLD2 ( <i>FLD-statement-name</i> )	JCFLD2= <i>ISFFLD-macro-label</i>



Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Job Class panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
JDDFLDS ( <i>FLD-statement-name</i> )	JDDFLDS=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Job Device panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JDDFLD2 ( <i>FLD-statement-name</i> )	JDDFLD2=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Job Device panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JDDNFLDS ( <i>FLD-statement-name</i> )	

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the JDDN panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JDMFLDS ( <i>FLD-statement-name</i> )	JDMFLDS=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Job Memory panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JDMFLD2 ( <i>FLD-statement-name</i> )	JDMFLD2=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Job Memory panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JDPFLDS ( <i>FLD-statement-name</i> )	JDPFLDS=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Job Dependency panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JDPFLD2 ( <i>FLD-statement-name</i> )	JDPFLD2=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Job Dependency panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JDSFLDS ( <i>FLD-statement-name</i> )	JDSFLDS=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Job Data Set panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JDSFLD2 ( <i>FLD-statement-name</i> )	JDSFLD2=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Job Data Set panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
JDYFLDS ( <i>FLD-statement-name</i> )	JDYFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Job Delay panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JDYFLD2 ( <i>FLD-statement-name</i> )	JDYFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Job Delay panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JESFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the JES panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JGFLDS ( <i>FLD-statement-name</i> )	JGFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Job Group panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JGFLD2 ( <i>FLD-statement-name</i> )	JGFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Job Group panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JMOFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the JMO panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JRIFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the JRI panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JRJFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the JRJ panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JSFLDS ( <i>FLD-statement-name</i> )	JSFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Job Step panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JSFLD2 ( <i>FLD-statement-name</i> )	JSFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Job Step panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
JOFLDS ( <i>FLD-statement-name</i> )	JOFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Job 0 panel. If this parameter is omitted, the default primary variable field list is used. (JES3 only)

GROUP	ISFGRP
JOFLD2 ( <i>FLD-statement-name</i> )	JOFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Job 0 panel. If this parameter is omitted, the default alternate variable field list is used. (JES3 only)

GROUP	ISFGRP
LINEFLDS ( <i>FLD-statement-name</i> )	LINEFLDS= <i>ISFFLD-statement-name</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the LI panel. If this parameter is omitted, the default primary variable field list is displayed. (Applies to JES2 only.)

GROUP	ISFGRP
LINEFLD2 ( <i>FLD-statement-name</i> )	LINEFLD2= <i>ISFFLD-statement-name</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the LI panel. If this parameter is omitted, the default alternate variable field list is displayed. (Applies to JES2 only.)

GROUP	ISFGRP
LNKFLDS ( <i>FLD-statement-name</i> )	LNKFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the LNK panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
LNKFLD2 ( <i>FLD-statement-name</i> )	LNKFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the LNK panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
LOG (OPERACT)   (OPERLOG)   (SYSLOG)	LOG= <u>OPERACT</u>   OPERLOG   SYSLOG

Names the default Log panel. The default Log panel is displayed when the LOG command is entered with no parameters, or the Log choice of the Display pull-down is selected.

GROUP	ISFGRP
LPAFLDS ( <i>FLD-statement-name</i> )	LPAFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the LPA panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
LPAFLD2 ( <i>FLD-statement-name</i> )	LPAFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the LPA panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
LPDFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the LPD panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
MASFLDS ( <i>FLD-statement-name</i> )	MASFLDS= <i>ISFFLD-statement-name</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the MAS (JES2) and JP (JES3) panels. If this parameter is omitted, the default primary variable field list is displayed.

GROUP	ISFGRP
MASFLD2 ( <i>FLD-statement-name</i> )	MASFLD2= <i>ISFFLD-statement-name</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the MAS (JES2) and JP (JES3) panels. If this parameter is omitted, the default alternate variable field list is displayed.

GROUP	ISFGRP
MEMFLDS( <i>FLD-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the MEM panel. If this parameter is omitted, the default alternate primary field list is displayed.

GROUP	ISFGRP
NAFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the NA panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
NCFLDS ( <i>FLD-statement-name</i> )	NCFLDS= <i>ISFFLD-statement-name</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the NC panel. If this parameter is omitted, the default primary variable field list is displayed.

GROUP	ISFGRP
NCFLD2 ( <i>FLD-statement-name</i> )	NCFLD2= <i>ISFFLD-statement-name</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the NC panel. If this parameter is omitted, the default alternate variable field list is displayed.

GROUP	ISFGRP
NODEFLDS ( <i>FLD-statement-name</i> )	NODEFLDS= <i>ISFFLD-statement-name</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the NODES panel. If this parameter is omitted, the default primary variable field list is displayed.

GROUP	ISFGRP
NODEFLD2 ( <i>FLD-statement-name</i> )	NODEFLD2=ISFFLD-statement-name

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the NODES panel. If this parameter is omitted, the default alternate variable field list is displayed.

GROUP	ISFGRP
NSFLDS ( <i>FLD-statement-name</i> )	NSFLDS=ISFFLD-statement-name

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the NS panel. If this parameter is omitted, the default primary variable field list is displayed.

GROUP	ISFGRP
NSFLD2 ( <i>FLD-statement-name</i> )	NSFLD2=ISFFLD-statement-name

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the NS panel. If this parameter is omitted, the default alternate variable field list is displayed.

GROUP	ISFGRP
OFIELDS ( <i>FLD-statement-name</i> )	OFIELDS=ISFFLD-statement-name

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Output Queue panel. If this parameter is omitted, the default primary variable field list is used. (Applies to JES2 only.)

GROUP	ISFGRP
OFIELD2 ( <i>FLD-statement-name</i> )	OFIELD2=ISFFLD-statement-name

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Output Queue panel. If this parameter is omitted, the default alternate variable field list is used. (Applies to JES2 only.)

GROUP	ISFGRP
OMVSFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the OMVS panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
OWNER (NONE)   (USERID)	OWNER=NONE   USERID

Limits the jobs that a group member will see on the DA, H, I, O, PS and ST panels.

It provides a default for the OWNER command.

#### USERID

indicates that only those jobs whose owner is the member's user ID are displayed.

#### NONE

is the default. Jobs displayed are not limited by owner.

Users who are authorized to issue the OWNER command (which can be protected only through SAF security) can override the OWNER parameter with the OWNER command or pull-down choice, or the SELECT command.

GROUP	ISFGRP
PAGFLDS ( <i>FLD-statement-name</i> )	PAGFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the PAG panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
PAGFLD2 ( <i>FLD-statement-name</i> )	PAGFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the PAG panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
PARMFLDS ( <i>FLD-statement-name</i> )	PARMFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the PARM panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
PARMFLD2 ( <i>FLD-statement-name</i> )	PARMFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the PARM panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
PCFLDS( <i>FLD-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the PC panel. If this parameter is omitted, the default alternate primary field list is displayed.

GROUP	ISFGRP
PREFIX ( <u>NONE</u> )   (USERID)   (GROUP)	PREFIX= <u>NONE</u>   USERID   GROUP

Limits the jobs that a group member will see on the DA, H, I, O, PS and ST panels.

The possible values for the PREFIX parameter are:

#### USERID

indicates that only those jobs whose name begins with the member's user ID are displayed, unless this parameter is overridden by the ISTATUS parameter.

#### GROUP

indicates that only those jobs whose name begins with the group's prefix are displayed, unless overridden by the ISTATUS parameter.

**Note:** PREFIX=GROUP works in conjunction with GPLEN and GPREF.

#### NONE

is the default. All jobs are displayed. Only those jobs whose names begin with the member's user ID are displayed on the Held Output panel.

On the O panel, users will see netmail when their current PREFIX matches a job's netmail ID. The netmail ID is displayed as part of the DEST field. See also the ISTATUS and XSTATUS parameters.

Users who are authorized to issue the PREFIX command can override the PREFIX parameter with the PREFIX command or pull-down choice, or the SELECT command.

GROUP	ISFGRP
PROCFLDS ( <i>FLD-statement-name</i> )	PROCFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the PROC panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
PROCFLD2 ( <i>FLD-statement-name</i> )	PROCFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **Alternate** variable field list for the PROC panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
PRTFLDS ( <i>FLD-statement-name</i> )	PRTFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Printer panel. If this parameter is omitted, the default primary variable field list is used. (Applies to JES2 only.)

GROUP	ISFGRP
PRTFLD2 ( <i>FLD-statement-name</i> )	PRTFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Printer panel. If this parameter is omitted, the default alternate variable field list is used. (Applies to JES2 only.)

GROUP	ISFGRP
PSFLDS ( <i>FLD-statement-name</i> )	PSFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Process panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
PSFLD2 ( <i>FLD-statement-name</i> )	PSFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Process panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
PUNFLDS ( <i>FLD-statement-name</i> )	PUNFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro that defines the **primary** field list for the Punch panel. If this parameter is omitted, the default primary variable field list is displayed.

GROUP	ISFGRP
PUNFLD2 ( <i>FLD-statement-name</i> )	PUNFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro that defines the **alternate** field list for the Punch panel. If this parameter is omitted, the default alternate variable field list is displayed.

GROUP	ISFGRP
RDRFLDS ( <i>FLD-statement-name</i> )	RDRFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro that defines the **primary** field list for the Reader panel. If this parameter is omitted, the default primary variable field list is displayed.

GROUP	ISFGRP
RDRFLD2 ( <i>FLD-statement-name</i> )	RDRFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro that defines the **alternate** field list for the Reader panel. If this parameter is omitted, the default alternate variable field list is displayed.

GROUP	ISFGRP
REPCFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the REPC panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
RESFLDS ( <i>FLD-statement-name</i> )	RESFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Resource panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
RESFLD2 ( <i>FLD-statement-name</i> )	RESFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Resource panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
RGRPFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the RGRP panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
RMAFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the RMA panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
RMFLDS ( <i>FLD-statement-name</i> )	RMFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the RM panel. If this parameter is omitted, the default primary variable field list is used.(Applies to JES2 only.)

GROUP	ISFGRP
RMFLD2 ( <i>FLD-statement-name</i> )	RMFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the RM panel. If this parameter is omitted, the default alternate variable field list is used.(Applies to JES2 only.)



GROUP	ISFGRP
RSYS (LOCAL)   (NONE)	RSYS=LOCAL   NONE

Sets an initial value to limit WTORs, based on system, that a group member will see on the Log panels.

**LOCAL**

indicates that only WTORs issued by the system the user is logged on to are displayed.

**NONE**

indicates that WTORs are not limited by system, that is, all WTORs for all systems are shown.

If RSYS is omitted, NONE is used.

GROUP	ISFGRP
SEFLDS ( <i>FLD-statement-name</i> )	SEFLDS=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Scheduling Environment panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
SEFLD2 ( <i>FLD-statement-name</i> )	SEFLD2=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Scheduling Environment panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
SOFLDS ( <i>FLD-statement-name</i> )	SOFLDS=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Spool Offload panel. If this parameter is omitted, the default primary variable field list is used.(Applies to JES2 only.)

GROUP	ISFGRP
SMSGFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the SMSG panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
SMSVFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the SMSV panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
SOFLD2 ( <i>FLD-statement-name</i> )	SOFLD2=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Spool Offload panel. If this parameter is omitted, the default alternate variable field list is used.(Applies to JES2 only.)

GROUP	ISFGRP
SPFLDS ( <i>FLD-statement-name</i> )	SPFLDS=ISFFLD-macro-label

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Spool Volumes panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
SPFLD2 ( <i>FLD-statement-name</i> )	SPFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Spool Volumes panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
SRCHFLDS ( <i>FLD-statement-name</i> )	SRCHFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the SRCH panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
SRCHFLD2 ( <i>FLD-statement-name</i> )	SRCHFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the SRCH panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
SRFLDS ( <i>FLD-statement-name</i> )	SRFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the System Requests panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
SRFLD2 ( <i>FLD-statement-name</i> )	SRFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the System Requests panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
SRVCFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the SRVC panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
SSIFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the SSI panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
STFLDS ( <i>FLD-statement-name</i> )	STFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the Status panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
STFLD2 ( <i>FLD-statement-name</i> )	STFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the Status panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
SVCFLDS( <i>FLD-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the SVC panel. If this parameter is omitted, the default alternate primary field list is displayed.

GROUP	ISFGRP
SYMFLDS ( <i>FLD-statement-name</i> )	SYMFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the SYM panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
SYMFLD2 ( <i>FLD-statement-name</i> )	SYMFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the SYM panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
SYSFLDS ( <i>FLD-statement-name</i> )	SYSFLDS= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **primary** variable field list for the SYS panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
SYSFLD2 ( <i>FLD-statement-name</i> )	SYSFLD2= <i>ISFFLD-macro-label</i>

Names an ISFFLD macro or FLD statement that defines the **alternate** variable field list for the SYS panel. If this parameter is omitted, the default alternate variable field list is used.

GROUP	ISFGRP
SYSID ( <i>system-id</i> )	SYSID= <i>system-id</i>

Indicates the default system ID of the system log which a member of this group displays on the SYSLOG panel in a JES2 environment.. If this parameter is omitted, the default is the current system log. This parameter is useful in a JES2 multi-access spool environment. The setting of SYSID can be changed by the user through use of the SYSID command if the user is authorized to use it, through the AUTH parameter. (Applies to JES2 only.)

GROUP	ISFGRP
SYSID3 ( <i>system-id</i> )	SYSID3= <i>system-id</i>

Indicates the default system ID of the system log which a member of this group displays on the SYSLOG panel in a JES3 environment. If this parameter is omitted, the default is the current system log. The setting of SYSID3 can be changed by the user through use of the SYSID command if the user is authorized to use it, through the AUTH parameter. (Applies to JES3 only.)

GROUP	ISFGRP
SYSPFLDS( <i>FLD-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the SYSP panel. If this parameter is omitted, the default alternate primary field list is displayed.

GROUP	ISFGRP
TCBFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the job tasks panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
UPCTAB ( <u>TRTAB2</u> )   ( <i>TRTAB-statement-name</i> )	UPCTAB= <u>TRTAB2</u>   <i>TRTAB-statement-name</i>

Assigns a name to the translation table that converts lowercase characters to uppercase. Use this parameter to request a code page other than the default code page for a group of users.

This parameter works with an ISFTR macro, TRTAB statement, or TRDEF statement. SDSF looks for:

- An ISFTR macro or TRTAB statement with the character string *TR-statement-name* in the UPCTAB parameter.
- A TRDEF statement with the character string *TR-statement-name* in the NAME parameter. Use TRDEF to define your own translation table.

*TR-statement-name* can be any character string that is a valid label for your assembler. The default is TRTAB2.

If you are using statements and omit UPCTAB, the code page defaults to **SDSF**. For more information, see [“Code page \(TRTAB/TRDEF or ISFTR\)”](#) on page 68.

GROUP	ISFGRP
VALTAB ( <u>TRTAB</u> )   ( <i>TRTAB-statement-name</i> )	VALTAB= <u>TRTAB</u>   <i>TRTAB-statement-name</i>

Assigns a name to the translation table that checks for valid characters. Use this parameter to request a code page other than the default code page for a group of users.

This parameter works with an ISFTR macro, TRTAB statement, or TRDEF statement. SDSF looks for:

- An ISFTR macro or TRTAB statement with the character string *TR-statement-name* in the VALTAB parameter.
- A TRDEF statement with the character string *TR-statement-name* in the NAME parameter. Use TRDEF to define your own translation table.

*TR-statement-name* can be any character string that is a valid label for your assembler. The default is TRTAB.

If you are using statements, and omit VALTAB, the code page defaults to **SDSF**. For more information, see [“Code page \(TRTAB/TRDEF or ISFTR\)”](#) on page 68.

GROUP	ISFGRP
VIO ( <u>SYSALLDA</u> )   ( <i>unit-name</i> )	VIO= <u>SYSALLDA</u>   <i>unit-name</i>

Specifies the unit name to be used for a temporary file when viewing page-mode output. (Applies to JES2 only.) If VIO is not specified, SDSF uses the default, SYSALLDA. Specification of a unit name that refers to a VIO device is strongly recommended for performance and security reasons.

GROUP	ISFGRP
VMAPFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the VMAP panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
WKLDFLDS ( <i>FLD-statement-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the WKLD panel. If this parameter is omitted, the default primary variable field list is used.

GROUP	ISFGRP
WLMFLDS( <i>FLD-name</i> )	

Names an FLD statement that defines the **primary** variable field list for the WLM panel. If this parameter is omitted, the default alternate primary field list is displayed.

GROUP	ISFGRP
XCMD ( <i>NTBL-statement-name</i> )	XCMD=ISFNTBL-macro-label

As of SDSF 2.5, all authorization is performed using SAF. XCMD is obsolete. For compatibility, the parameter and its options are accepted, but ignored.

GROUP	ISFGRP
XDSP ( <i>NTBL-statement-name</i> )	XDSP=ISFNTBL-macro-label

As of SDSF 2.5, all authorization is performed using SAF. XDSP is obsolete. For compatibility, the parameter and its options are accepted, but ignored.

GROUP	ISFGRP
XDSPD ( <i>NTBL-statement-name</i> )	XDSPD=ISFNTBL-macro-label

As of SDSF 2.5, all authorization is performed using SAF. XDSPD is obsolete. For compatibility, the parameter and its options are accepted, but ignored.

GROUP	ISFGRP
XSTATUS ( <i>NTBL-statement-name</i> )	XSTATUS=ISFNTBL-macro-label

Indicates that jobs whose names are in the list created by the specified ISFNTBL macro or NTBL statement will be excluded from all SDSF panels for members of this group. This parameter overrides all other parameters that control which jobs are displayed, including ISTATUS.

## Variable field lists (FLD or ISFFLD)

An FLD statement along with FLDENT statements, or an ISFFLD macro, defines the fields that are displayed on an SDSF panel. It is associated with the field list for a particular panel by an ISGRP macro or GROUP statement.

In ISFPARMS assembler macros, the ISFFLD macros must come after the ISFGRP macros. When you use statements, the statements can be in any order.

You can define a **primary** and **alternate** variable field list for each SDSF panel. The primary field list contains those fields that are shown upon entry into a panel. The alternate field list contains fields that can be displayed by use of the ? command.

For using SDSF interactively, it is important to locate otypeable fields on the panel so that the entire field is visible on one screen. An otypeable field can be otyped only when the entire field is visible.

The fields that are available on a panel can also be affected by the JES level. The ARRANGE command allows users to change the order and widths of the fields in each field list.

You can include the ISFEND column in ISFPRMxx. Because the ISFEND column title and width cannot be changed, the TITLE and WIDTH parameters of the FLDENT statement are ignored and message ISF870W is issued. When ISFEND is not included in the field list, SDSF automatically adds it to the end of the list.

The ISFEND column is not supported on the ISFFLD macro when coded in ISFPARMS. Hidden column support is not available for those panels with installation-defined field lists in ISFPARMS. You receive the error message “column not found” when referencing the .END column for these field lists.

With SDSF's support for REXX, users can develop REXX execs that have dependencies on specific columns. You should be aware when removing columns from a field list that this may impact REXX execs.

## Example of the FLD statement and ISFFLD macro

FLD and FLDENT Statements	ISFFLD Macro
<pre> <b>1</b> GROUP IFIELDS(DFLD) <b>2</b> FLD NAME(DFLD) TYPE(IN)     FLDENT COLUMN(JNUM),TITLE(' JOBNUM'),WIDTH(7) <b>3</b> FLDENT COLUMN(JPRIO),TITLE(PRTY),WIDTH(4) </pre>	<pre> <b>1</b> ISFGRP IFIELDS=DFLD <b>2</b> DFLD ISFFLD JNUM,' JOBNUM',7, <b>3</b> JPRIO,'PRTY',4, <b>4</b> TYPE=IN </pre>

On line **1** of the example, the IFIELDS parameter refers to an ISFFLD macro (with the macro label) or FLD statement (with the NAME parameter).

The ISFFLD macro and FLD statement begin on the line marked with **2**. Each defines a column for the JES job number, with a title of ' JOBNUM' and a width of 7 characters; and a column for the JES input queue priority, with a title of PRTY and width of 4 characters (line **3**). The TYPE parameter identifies the panel as the IN or Input Queue panel (line **4** in the ISFGRP macro, line **3** of the FLD example).

## FLD and ISFFLD syntax

### FLD and FLDENT statements

```

FLD NAME(FLD-statement-name),TYPE(panel-ID)
    FLDENT COLUMN(column),TITLE(title),WIDTH(width)

```

### ISFFLD macro

```

label ISFFLD column,title,width,...,TYPE=panel-ID

```

#### *label* or *FLD-statement-name*

names the ISFFLD macro or FLD statement referenced by a group. The name can be alphabetic, numeric, or national characters (@, #, \$) and must begin with an alphabetic character.

#### *column*

is a 2-to-8-character name, as defined by SDSF, for a column on an SDSF panel that displays tabular information. [Chapter 4, “Columns on the SDSF panels,” on page 93](#) includes tables of the columns for each panel.

You will achieve better SDSF performance if the primary field list contains only those fields that SDSF can obtain from in-storage control blocks. These are marked as having *immediate* access in the tables in [Chapter 4, “Columns on the SDSF panels,” on page 93](#). Those fields that require an I/O operation to the spool data set (*delayed* access) should be in the alternate field list.

#### *title*

is the title that appears on a panel for the column defined by *column*.

When you define a title using mixed case, enclose it in single quotation marks to ensure that it is displayed in mixed case. The case of the column titles does not affect commands that use titles as parameters, such as SORT and FILTER. The CTITLE parameter of the GROUP statement can be used to fold all column titles to uppercase.

If the title contains blanks, you **must** enclose it in single quotation marks. Similarly, users entering commands with column titles as parameters will be required to enclose those titles within quotation marks. For this reason, you may want to avoid coding titles that contain blanks.

A title must not be more than 18 characters long.

#### **width**

is the width of the column on the panel. The width must be at least as long as the title. Use D to get the SDSF default length.

When displaying numeric values that are too large for the column width, SDSF scales them using these abbreviations: T (thousands), M (millions), B (billions), KB (kilobytes), MB (megabytes), GB (gigabytes), TB (terabytes) and PB (petabytes).

#### **panel-ID**

is one of the values listed in column 1 of [Table 13 on page 49](#), corresponding to the SDSF tabular panel for which this variable field list was designed.

[Table 13 on page 49](#) shows for each SDSF panel the *panel-ID* value that can be used in the FLD and ISFFLD syntax, the ISFGRP and GROUP parameters that name the primary and alternate field lists, and where to find a complete list of fields.

*Table 13. Field List Parameters*

<b>panel-ID parameter value</b>	<b>Panel</b>	<b>ISFGRP or GROUP Parameter</b>	<b>Reference for Field List</b>
<b>AD</b>	AD (Address Space panel)	ADFLDS(GROUP only)	<a href="#">“Address Space Diagnostics panel (AD)” on page 94</a>
<b>APF</b>	APF (Authorized Program Facility panel)	APFFLDS, APFFLD2	<a href="#">“Authorized Program Facility panel (APF)” on page 96</a>
<b>AS</b>	AS (Address Space panel)	ASFLDS, ASFLD2	<a href="#">“Address Space Memory panel (AS)” on page 94</a>
<b>CDE</b>	CDE (Job Module panel)	CDEFLDS (GROUP only)	<a href="#">“Job Module panel (JC)” on page 145</a>
<b>CFC</b>	CFC (CF Connections panel)	CFCFLDS (GROUP only)	<a href="#">“CF Connections panel (CFC)” on page 97</a>
<b>CFD</b>	CFD (CF Data Sets panel)	CFDFLDS (GROUP only)	<a href="#">“CF Data Sets panel (CFD)” on page 98</a>
<b>CFS</b>	CFS (CF Structure panel)	CFSFLDS (GROUP only)	<a href="#">“CF Structure panel (CFS)” on page 99</a>
<b>CK</b>	CK	CKFLDS, CKFLD2	<a href="#">“Health Checker panel (CK)” on page 116</a>
<b>CKH</b>	CKH (Health Checker panel)	CKHFLDS, CKHFLD2	<a href="#">“Health Check History panel (CKH)” on page 116</a>
<b>CKPT</b>	CKPT (JES Checkpoint panel)	CKPTFLDS (GROUP only)	<a href="#">“JES Checkpoint panel (CKPT)” on page 126</a>

Table 13. Field List Parameters (continued)

<b>panel-ID parameter value</b>	<b>Panel</b>	<b>ISFGRP or GROUP Parameter</b>	<b>Reference for Field List</b>
<b>CS</b>	CS (Common Storage Subpools panel)	CSFLDS (GROUP only)	<a href="#">“Common Storage Subpools panel (CS)” on page 102</a>
<b>CSI</b>	CSI (Common Storage Subpool Details panel)	CSIFLDS (GROUP only)	<a href="#">“Common Storage Subpool Details panel (CSI)” on page 103</a>
<b>CSR</b>	CSR (Common Storage Remaining panel)	CSRFLDS (GROUP only)	<a href="#">“Common Storage Remaining panel (CSR)” on page 103</a>
<b>DA</b>	DA (Display Active Users panel)	DFIELDS, DFIELD2	<a href="#">“Display Active Users panel (DA)” on page 105</a>
<b>DEV</b>	DEV (Device Activity panel)	DEVFLDS (GROUP only)	<a href="#">“Device Activity panel (DEV)” on page 104</a>
<b>DYNX</b>	DYNX (Dynamic Exits panel)	DYNXFLDS, DYNXFLD2	<a href="#">“Dynamic Exits panel (DYNX)” on page 109</a>
<b>EMCS</b>	EMCS (Extended Console panel)	EMCSFLDS (GROUP only)	<a href="#">“Extended Console panel (EMCS)” on page 113</a>
<b>ENC</b>	ENC (Enclaves panel)	ENCFLDS, ENCFLD2	<a href="#">“Enclaves panel (ENC)” on page 110</a>
<b>ENQ</b>	ENQ (Enqueue panel)	ENQFLDS, ENQFLD2	<a href="#">“Enqueue panel (ENQ)” on page 111</a>
<b>FS</b>	FS (File Systems panel)	FSFLDS (GROUP only)	<a href="#">“File Systems panel (FS)” on page 114</a>
<b>GQE</b>	GQE (Job Common Storage panel)	GQEFLDS (GROUP only)	<a href="#">“Job Common Storage panel (JCS)” on page 133</a>
<b>GT</b>	GT (Generic Tracker panel)	GTFLDS (GROUP only)	<a href="#">“Generic Tracker panel (GT)” on page 115</a>
<b>HOLD</b>	H (Held Output panel)	HFIELDS, HFIELD2	<a href="#">“Held Output panel (H)” on page 118</a>
<b>IN</b>	I (Input Queue panel)	IFIELDS, IFIELD2	<a href="#">“Input Queue panel (I)” on page 123</a>
<b>INT</b>	INIT (Initiator panel)	INTFLDS, INTFLD2	<a href="#">“Initiator panel (INIT)” on page 121</a>
<b>JC</b>	JC (Job Class panel)	JCFLDS, JCFLD2	<a href="#">“Job Class panel (JC)” on page 131</a>
<b>JCM</b>	JCM (Job Class Members field)	JCMFLDS (GROUP only)	<a href="#">“Job Class Members panel (JCM)” on page 130</a>
<b>JDD</b>	JD (Job Device panel)	JDDFLDS, JDDFLD2	<a href="#">“Job Device panel (JD)” on page 140</a>
<b>JDDN</b>	JDDN (Job DDName panel)	JDDNFLDS (GROUP only)	<a href="#">“Job DDName panel (JDDN)” on page 142</a>



Table 13. Field List Parameters (continued)

<b>panel-ID parameter value</b>	<b>Panel</b>	<b>ISFGRP or GROUP Parameter</b>	<b>Reference for Field List</b>
<b>JDP</b>	JDP (Job Dependency)	JDPFLDS, JDPFLD2	<a href="#">“Job Dependency panel (JP)” on page 139</a>
<b>JDS</b>	JDS (Job Data Set panel)	JDSFLDS, JDSFLD2	<a href="#">“Job Data Set panel (JDS)” on page 134</a>
<b>JES</b>	JES (JES Subsystem panel)	JESFLDS (GROUP only)	<a href="#">“JES Subsystem panel (JES)” on page 129</a>
<b>JG</b>	JG (Job Group panel)	JGFLDS, JGFLD2	<a href="#">“Job Group panel (JG)” on page 143</a>
<b>JDM</b>	JM (Job Memory panel)	JDMFLDS, JDMFLD2	<a href="#">“Job Memory panel (JM)” on page 143</a>
<b>JMO</b>	JMO (Job Memory Objects panel)	JMOFLDS (GROUP only)	<a href="#">“Job Memory Objects panel (JMO)” on page 144</a>
<b>JRI</b>	JRI (JESInfo panel)	JRIFLDS (GROUP only)	<a href="#">“JESInfo panel (JRI)” on page 127</a>
<b>JRJ</b>	JRJ (JESInfo by Job panel)	JRJFLDS (GROUP only)	<a href="#">“JESInfo by Job panel (JRJ)” on page 128</a>
<b>JS</b>	JS (Job Step panel)	JSFLDS, JSFLD2	<a href="#">“Job Step panel (JS)” on page 146</a>
<b>TCB</b>	TCB (Job Tasks panel)	TCBFLDS (GROUP only)	<a href="#">“Job Tasks panel (JT)” on page 148</a>
<b>JDY</b>	JY (Job Delay panel)	JDYFLDS, JDYFLD2	<a href="#">“Job Delay panel (JY)” on page 138</a>
<b>JO</b>	JO (Job 0 panel)	JOFLDS, JOFLD2	<a href="#">“Job 0 (JO)” on page 149</a>
<b>LINE</b>	LI (Lines panel)	LINEFLDS, LINEFLD2	<a href="#">“Lines panel (LI)” on page 150</a>
<b>LLS</b>	LLS (Link List sets panel)	LLSFLDS (GROUP only)	<a href="#">“Link List sets panel (LLS)” on page 152</a>
<b>LNK</b>	LNK (Link List panel)	LNKFLDS, LNKFLD2	<a href="#">“Link List panel (LNK)” on page 153</a>
<b>LPA</b>	LPA (Link Pack Area panel)	LPAFLDS, LPAFLD2	<a href="#">“Link Pack Area panel (LPA)” on page 154</a>
<b>LPD</b>	LPD (Link Pack Directory panel)	LPDFLDS (GROUP only)	<a href="#">“Link Pack Directory panel (LPD)” on page 154</a>
<b>MAS</b>	MAS (Multi-Access Spool panel) and JP (JESPLEX panel)	MASFLDS, MASFLD2	<a href="#">“Multi-Access Spool panel (MAS) and JESPLEX (JP) panel” on page 155</a> and <a href="#">“JESPLEX panel (JP)” on page 130</a>
<b>MEM</b>	MEM (Memory contents panel)	MEMFLDS (GROUP only)	<a href="#">“Memory contents panel (MEM)” on page 157</a>
<b>NA</b>	NA (Network Activity panel)	NAFLDS (GROUP only)	<a href="#">“Network Activity panel (NA)” on page 158</a>

Table 13. Field List Parameters (continued)

<b>panel-ID parameter value</b>	<b>Panel</b>	<b>ISFGRP or GROUP Parameter</b>	<b>Reference for Field List</b>
<b>NC</b>	NC (Network Connections panel)	NCFLDS, NCFLD2	<a href="#">“Network Connections (NC)” on page 159</a>
<b>NODE</b>	NO (Nodes panel)	NODEFLDS, NODEFLD2	<a href="#">“Nodes panel (NO)” on page 162</a>
<b>NS</b>	NS (Network Servers panel)	NSFLDS, NSFLD2	<a href="#">“Network Servers (NS)” on page 161</a>
<b>OUT</b>	O (Output Queue panel)	OFLDS, OFIELD2	<a href="#">“Output Queue panel (O)” on page 165</a>
<b>BPXO</b>	OMVS (OMVS options panel)	OMVSFLDS (GROUP only)	<a href="#">“OMVS options panel (BPXO)” on page 164</a>
<b>PAG</b>	PAG (Page panel)	PAGFLDS, PAGFLD2	<a href="#">“Page panel (PAG)” on page 168</a>
<b>PARM</b>	PARM (PARMLIB panel)	PARMFLDS, PARMFLD2	<a href="#">“PARMLIB panel (PARM)” on page 169</a>
<b>PC</b>	PC (PC Routines panel)	PCFLDS (GROUP only)	<a href="#">“PC Routines panel (PC)” on page 170</a>
<b>PROC</b>	PROC (Proclib panel)	PROCFLDS, PROCFLD2	<a href="#">“Proclib panel (PROC)” on page 176</a>
<b>PS</b>	PS (Processes panel)	PSFLDS, PSFLD2	<a href="#">“Processes panel (PS)” on page 177</a>
<b>PUN</b>	PUN (Punch panel)	PUNFLDS, PUNFLD2	<a href="#">“Punch panel (PUN)” on page 178</a>
<b>RDR</b>	RDR (Reader panel)	RDRFLDS, RDRFLD2	<a href="#">“Reader panel (RDR)” on page 181</a>
<b>REPC</b>	REPC (WLM Report Class panel)	REPCFLDS (GROUP only)	<a href="#">“WLM Report Class panel (REPC)” on page 206</a>
<b>RES</b>	RES (Resource panel)	RESFLDS, RESFLD2	<a href="#">“Resource panel (RES)” on page 183</a>
<b>RGRP</b>	RGRP (WLM Resource Group panel)	RGRPFLDS (GROUP only)	<a href="#">“WLM Resource Group panel (RGRP)” on page 207</a>
<b>RM</b>	RM (Resource Monitor panel)	RMFLDS, RMFLD2	<a href="#">“Resource Monitor panel (RM)” on page 183</a>
<b>RMA</b>	RMA (Resource Monitor alerts panel)	RMAFLDS (GROUP only)	<a href="#">“Resource Monitor Alerts panel (RMA)” on page 184</a>
<b>SE</b>	SE (Scheduling environment panel)	SEFLDS, SEFLD2	<a href="#">“Scheduling Environment panel (SE)” on page 185</a>
<b>SMSG</b>	SMSG (SMS Groups panel)	SMSGFLDS (GROUP only)	<a href="#">“SMS Groups panel (SMSG)” on page 192</a>

Table 13. Field List Parameters (continued)

<b>panel-ID parameter value</b>	<b>Panel</b>	<b>ISFGRP or GROUP Parameter</b>	<b>Reference for Field List</b>
<b>SMSV</b>	SMSV (SMS Volumes panel)	SMSVFLDS (GROUP only)	<a href="#">“SMS Volumes panel (SMSV)” on page 193</a>
<b>SO</b>	SO (Spool Offload panel)	SOFLDS, SOFLD2	<a href="#">“Spool Offload panel (SO)” on page 185</a>
<b>SP</b>	SP (Spool Volumes panel)	SPFLDS, SPFLD2	<a href="#">“Spool Volumes panel (SP)” on page 188</a>
<b>SR</b>	SR (System Requests panel)	SRFLDS, SRFLD2	<a href="#">“System Requests panel (SR)” on page 204</a>
<b>SRCH</b>	SRCH (Search panel)	SRCHFLDS, SRCHFLD2	<a href="#">“Search panel (SRCH)” on page 190</a>
<b>SRVC</b>	SRVC (WLM Service Classes panel)	SRVCFLDS (GROUP only)	<a href="#">“WLM Service Classes panel (SRVC)” on page 208</a>
<b>STAT</b>	ST (Status panel)	STFLDS, STFLD2	<a href="#">“Status panel (ST)” on page 193</a>
<b>SVC</b>	SVC (SVC routines and ESR panel)	SVCFLDS (GROUP only)	<a href="#">“SVC routines and ESR panel (SVC)” on page 199</a>
<b>SYM</b>	SYM (System Symbols panel)	SYMFLDS, SYMFLD2	<a href="#">“System Symbols panel (SYM)” on page 200</a>
<b>SYS</b>	SYS (System panel)	SYSFLDS, SYSFLD2	<a href="#">“System panel (SYS)” on page 201</a>
<b>SYSP</b>	SYSP (System Parameters panel)	SYSPFLDS (GROUP only)	<a href="#">“System Parameters panel (SYSP)” on page 203</a>
<b>USI</b>	USI (Private Storage Subpools panel)	USIFLDS (GROUP only)	<a href="#">“Private Storage Subpool panel (USI)” on page 175</a>
<b>VMAP</b>	VMAP (Virtual Storage Map panel)	VMAPFLDS (GROUP only)	<a href="#">“Virtual Storage Map panel (VMAP)” on page 205</a>
<b>WKLD</b>	WKLD (WLM Workload panel)	WKLDFLDS (GROUP only)	<a href="#">“WLM Workload panel (WKLD)” on page 209</a>
<b>XCFM</b>	XCFM (XCF Members and Groups panel)	XCFMFLDS (GROUP only)	<a href="#">“XCF Members and Groups panel (XCFM)” on page 210</a>

## Name tables (NTBL or ISFNTBL)

An NTBL statement along with NTBLENT statements, or an ISFNTBL macro, works in conjunction with an ISFGRP macro or GROUP statement in placing an SDSF user into a group, or in determining which SDSF functions are available to a member of a group.

In ISFPARMS assembler macros, the ISFNTBL macros must follow the ISFGRP macros.

## Examples of the NTBL statement and ISFNTBL macro

NTBL and NTBLENT Statements	ISFNTBL Macro
<pre>1 GROUP XSTATUS(EXCLUDE) 2 NTBL NAME(EXCLUDE)   NTBLENT STRING(RSCS)</pre>	<pre>1 ISFGRP XSTATUS=EXCLUDE 2 EXCLUDE ISFNTBL RSCS,1</pre>

On line **1**, the XSTATUS parameter works with the ISFNTBL macro, or the combination of NTBL and NTBLENT statements, beginning on line **2**, to exclude from the SDSF panels any job whose name begins with the characters *RSCS*. The OFFSET parameter is omitted and defaults to 1.

For more examples, see samples ISFPRM00 and ISFPRM01 in ISF.SISFJCL.

## NTBL and ISFNTBL syntax

### NTBL and NTBLENT Statements

NTBL NAME(*NTBL-statement-name*) TYPE(DEST)  
NTBLENT STRING(*string*) OFFSET(*beginning-column-of-string*)

### ISFNTBL Macro

*label* ISFNTBL *string*, *beginning-column-of-string*,... [,TYPE=DEST]

#### ***label or NTBL-statement-name***

names the ISFNTBL macro or NTBL statement. The name must be 2-8 alphabetic, numeric, or national characters (@, #, \$) and must begin with an alphabetic character.

#### ***string***

is a character string.

If a character string contains blanks, it must be enclosed in single quotation marks.

#### ***beginning-column-of-string***

is the beginning column number of the character string. In the NTBLENT statement, OFFSET(*beginning-column-of-string*) is optional. If it is omitted, *beginning-column-of-string* defaults to 1.

#### **TYPE**

is an optional parameter. The value of DEST indicates that this definition contains enhanced destination names. If you are using these longer destination names, you must specify the TYPE parameter, with a value of DEST.

## Usage notes

If you code name tables for destination names, you may want to put the installation-defined destination names last. Installation-defined names may be most likely to cause an error, and when SDSF encounters an error during initialization, it continues initialization with the destination names that were processed successfully before the error.

## Customized properties (PROPLIST)

A PROPLIST statement, along with PROPERTY statements, defines customized values for certain SDSF properties. It provides an alternative to writing user exit routines to customize those properties. A user exit routine that customizes the same property as a PROPERTY statement overrides the value on the PROPERTY statement.

The PROPLIST statement is associated with a group of users through the CUSTOM parameter on the GROUP statement.

The PROPLIST statement has no equivalent in ISFPARMS assembler macros.

## Example of the PROPLIST and associated statements

```
1 GROUP NAME(DEPTA)
2   CUSTOM(USERPROP)
  .
  .
3 PROPLIST NAME(USERPROP)
  4   PROPERTY NAME(Security.Browse.LogNOFAIL) VALUE(TRUE)
```

On line **2** of the example, the CUSTOM parameter refers to a PROPLIST statement with the NAME parameter.

The PROPLIST statement with the appropriate name begins on the line marked with **3**. It consists of one PROPERTY statement, on the line marked with **4**, which specifies the Security.Browse.LogNOFAIL property.

## PROPLIST syntax

### PROPLIST and PROPERTY statements

```
PROPLIST NAME(proplist-statement-name),
  PROPERTY NAME(property-name) VALUE(value)
```

#### ***proplist-statement-name***

names the PROPLIST statement referenced by the CUSTOM parameter in a GROUP statement. The name can be 1 to 8 alphabetic, numeric, or national characters (@, #, \$) and must begin with an alphabetic or national character.

#### ***property-name***

names the property. The properties are described in [Table 14 on page 55](#).

#### ***value***

specifies the setting for the property.

[Table 14 on page 55](#) shows the properties that you can specify with the PROPERTY statement, and the corresponding flag that you could set in a user exit routine to achieve the same result. The user exit overrides the PROPERTY statement.

Table 14. Properties to Specify with the PROPERTY Statement

Name	Values	Description	Corresponding Field for User Exit
<b>Browse.Alloc.MaxDS</b>	10 - 400	Controls the number of data sets open at one time for browse. The default is 400.	UPRDSAL
<b>Browse.CoreBuf.NoSwap</b>	TRUE or FALSE	Affects the browsing of job data sets. A value of TRUE requests that SDSF not attempt to gather data not yet written to spool if the job is swapped out. This is ignored for systems other than the one you are logged onto. FALSE is the default.	UPRSFLG3.UPRS3SWP

Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Browse.Suppress.DupDS</b>	TRUE or FALSE	Controls whether duplicate SYSOUT data sets are included when you browse or print a job. A value of TRUE requests that duplicate SYSOUT data sets not be included. FALSE is the default.	UPROFLG3.UPRO3NOD
<b>Comm.Release.Mode</b>	1 or 2	Sets the mode that SDSF uses for communication to provide sysplex-wide data on SDSF panels.  A value of 2 sets the communication mode to Z13, which requests that SDSF use the sysplex support that was introduced in z/OS V1R13 SDSF. SDSF uses XCF for communications and does not use the server group. Systems that you wish to be included must be at least z/OS V1R13. This is the default.	UPRCMODE
<b>Command.FILTER.SymbolsDisabled</b>	TRUE or FALSE	Controls the use of system symbols with filtering. If the value is TRUE, any symbols in a string are not resolved. If the value is FALSE, symbols are resolved. FALSE is the default.	UPRS6FSY
<b>Command.HOLD.AddGenChar</b>	TRUE or FALSE	Affects the job name parameter on the H command. If the value is TRUE, SDSF appends a generic pattern-matching character to the job name specified with the H command, unless the job name already ends with a generic character or is already the maximum length (8 characters). For example, the command H GREER would result in H GREER*. FALSE is the default.	UPROFLG1.UPRO1GHO
<b>Command.INIT.DefaultJESManaged</b>	TRUE or FALSE	Controls the rows that are shown on the initiator panel by default. If the value is TRUE, only JES-managed initiators are shown by default. FALSE is the default.	UPROFLG2.UPRO2IDJ

Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Command.PREFIX.AddGenChar</b>	TRUE or FALSE	Affects the PREFIX command. If the value is TRUE, SDSF appends a generic pattern-matching character to the prefix specified with the PREFIX command, unless the prefix already ends with a generic character or is already the maximum length (8 characters). For example, the command PREFIX JONES would result in a prefix of JONES*. FALSE is the default.	UPROFLG1.UPRO1GPF
<b>Command.SLASH.CommandLimit</b>	20 - 2000	Sets the number of system commands entered with the / command that SDSF stores. When the number is exceeded, the oldest command is removed from the list. The default is 1,000. System commands are stored only when using SDSF under ISPF.	UPRCMDLM
<b>Command.SLASH.Name</b>	/, ( or )	Specifies a single character to use when issuing system commands through SDSF (usually referred to as the slash command). You would use this character with all forms of the slash command, including I/ and W/. Enclose the character in single quotation marks, for example VALUE(' '). The default is /.  This also affects the character used with the REXX ISFEXEC command. The REXX ISFSLASH command is preferred, as it does not require the character to be coded with the command.	UPRSLCMD UPRSLCIC UPRSLCWC
<b>Command.SLASH.NoDynamicPanels</b>	TRUE or FALSE	Controls whether the size of the System Command Extension pop-up varies with the screen size of the emulator session. If the value is TRUE, the size of the pop-up does not vary. If the value is FALSE, the size of the pop-up varies. FALSE is the default.	UPROFLG4.UPRO4CDP

Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Command.STAT.AddGenChar</b>	TRUE or FALSE	Affects the job name parameter on the ST command. If the value is TRUE, SDSF appends a generic pattern-matching character to the job name specified with the ST command, unless the job name already ends with a generic character or is already the maximum length (8 characters). For example, the command ST GREER would result in ST GREER*. FALSE is the default.	UPROFLG1.UPRO1GST
<b>Console.EMCS.ConModChars</b>	String of up to 32 characters consisting of A-Z, 0-9, @, #, \$.	Names the list of suffixes to use when modifying the console name when the console activation fails due to the console being in use. The default is \$#@12345.	UPXCONSF
<b>Console.EMCS.DataSpaceSize</b>	1 - 2048	Controls the size of the dataspace used when the EMCS console is activated. The data space size controls the number of messages that may be queued to the console prior to them being retrieved. The value indicates the size in megabytes. 2048 is the default.	UPRCONSZ
<b>Console.EMCS.NoConMod</b>	TRUE or FALSE (the default)	Disables modification of the console name when console activation fails due to the console being in use. A value of TRUE disables the function and a value of FALSE enables it. FALSE is the default.	UPROFLG2.UPRO2NMD
<b>Console.EMCS.UlogAuthReq</b>	TRUE or FALSE (the default)	Controls activation of the extended console based on authorization to ISFCMD.ODSP.ULOG.jesx. When the value is TRUE, an extended console will be activated only if the user has READ access to ISFCMD.ODSP.ULOG.jesx in the SDSF class. When the value is FALSE, access to ISFCMD.ODSP.ULOG.jesx will not be checked when activating an EMCS console. FALSE is the default.	UPROFLG6.UPRO6UCN



Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Log.Operlog.ViewAll</b>	TRUE or FALSE	Controls the lines shown on the OPERLOG panel. If the value is TRUE, the OPERLOG panel includes data from the inactive portion of the log stream. FALSE is the default.	UPROFLG2.UPRO2OVW
<b>Panel.All.JESplexScope</b>	TRUE or FALSE	Controls the scope of the AD, APF, AS, CK, CKPT, CSR, DA, DEV, DYNX, ENC, ENQ, FS, GT, JES, LLS, LNK, LPA, LPD, PAG, MEM, NA, OMVS, PARM, PC, PS, SMSG, SMSV, SSI, SVC, SYM, SYS, SYSP, and VMAP panels. If the value is TRUE, the scope of the panels is JESplex-wide. If the value is FALSE, the scope of the panels is sysplex-wide. FALSE is the default.	UPROFLG3.UPRO3JPC, UPROFLG3.UPRO3JPD, UPROFLG3.UPRO3JPE, UPROFLG3.UPRO3JPP, UPROFLG4.UPRO4JAP, UPROFLG4.UPRO4JLN, UPROFLG4.UPRO4JLP, UPROFLG4.UPRO4JPA, UPROFLG4.UPRO4JPM, UPROFLG4.UPRO4JSM, UPROFLG4.UPRO4JSY, UPROFLG5.UPRO5JEN, UPROFLG5.UPRO5JAS, UPROFLG5.UPRO5JDY, UPROFLG5.UPRO5JFS, UPROFLG5.UPRO5JSG, UPROFLG5.UPRO5JSV, UPROFLG5.UPRO5JSS, UPROFLG5.UPRO5JVM, UPROFLG7.UPRO7JCS, UPROFLG7.UPRO7JGT, UPROFLG7.UPRO7JNA, UPROFLG7.UPRO7JDV, UPROFLG7.UPRO7JOM, UPROFLG7.UPRO7JLD, UPROFLG7.UPRO7JLS, UPROFLG8.UPRO8JAD, UPROFLG8.UPRO8JME, UPROFLG8.UPRO8JPC, UPROFLG8.UPRO8JSP, UPROFLG8.UPRO8JSV
<b>Panel.AD.JESplexScope</b>	TRUE or FALSE	Controls scope of the AD panel. If the value is TRUE, the scope of the AD panel is JESplex-wide. If the value is FALSE, the scope of the AD panel is sysplex-wide. FALSE is the default.	UPROFLG8.UPRO8JAD
<b>Panel.APF.JESplexScope</b>	TRUE or FALSE	Controls scope of the APF panel. If the value is TRUE, the scope of the APF panel is JESplex-wide. If the value is FALSE, the scope of the APF panel is sysplex-wide. FALSE is the default.	UPROFLG4.UPRO4JAP

Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Panel.AS.JESplexScope</b>	TRUE or FALSE	Controls scope of the AS panel. If the value is TRUE, the scope of the AS panel is JESplex-wide. If the value is FALSE, the scope of the AS panel is sysplex-wide. FALSE is the default.	UPROFLG5.UPRO5JAS
<b>Panel.CK.JESplexScope</b>	TRUE or FALSE	Controls the scope of the CK panel. If the value is TRUE, the scope of the CK panel is JESplex-wide. If the value is FALSE, the scope of the CK panel is sysplex-wide. FALSE is the default.	UPROFLG3.UPRO3JPC
<b>Panel.CKH.DefaultCKLim</b>	1–999999	Sets the default maximum number of instances for a check for IBM Health Checker for z/OS that will be read from the logstream for the CKH panel. Users can override this with the SET CKLIM command. The default is 10.	UPRCKLIM
<b>Panel.CSR.JESplexScope</b>	TRUE or FALSE	Controls the scope of the CSR panel. If the value is TRUE, the scope of the CSR panel is JESplex-wide. If the value is FALSE, the scope of the CSR panel is sysplex-wide. FALSE is the default.	UPROFLG7.UPRO7JCS
<b>Panel.DA.CPUPctBasedLPAR</b>	TRUE or FALSE	Affects normalization of the CPU% column on the DA panel. If the value is TRUE, the CPU% column is normalized using the LPAR value for CPU busy for the system. If the value is FALSE, the CPU% column is normalized with the MVS value for CPU busy for the system. The LPAR value takes into account several states related to PR/SM. The LPAR value requires RMF. If the LPAR value is not available, SDSF uses the MVS value to normalize the CPU% column. FALSE is the default.	UPRSFLG6.UPRS6DNL

Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Panel.DA.JESPLexScope</b>	TRUE or FALSE	Controls the scope of the DA panel. If the value is TRUE, the scope of the DA panel is JESPLex-wide. If the value is FALSE, the scope of the DA panel is sysplex-wide. FALSE is the default.	UPROFLG3.UPRO3JPD
<b>Panel.DA.ShowTitleSIO</b>	TRUE or FALSE	Affects the contents of the title line on the DA panel. If the value is TRUE, the system SIO rate is included, but the system zAAP use is not. If the value is FALSE, the SIO rate is omitted, and the system zAAP use is shown if a zAAP is defined on the local system. FALSE is the default.	UPRSFLG5.UPRS5DSI
<b>Panel.DEV.JESPLexScope</b>	TRUE or FALSE	Controls the scope of the DEV panel. If the value is TRUE, the scope of the DEV panel is JESPLex-wide. If the value is FALSE, the scope of the DEV panel is sysplex-wide. FALSE is the default.	UPROFLG7.UPRO7JDV
<b>Panel.DYNX.JESPLexScope</b>	TRUE or FALSE	Controls scope of the DYNX panel. If the value is TRUE, the scope of the DYNX panel is JESPLex-wide. If the value is FALSE, the scope of the DYNX panel is sysplex-wide. FALSE is the default.	UPROFLG5.UPRO5JDY
<b>Panel.ENC.JESPLexScope</b>	TRUE or FALSE	Controls the scope of the ENC panel. If the value is TRUE, the scope of the ENC panel is JESPLex-wide. If the value is FALSE, the scope of the ENC panel is sysplex-wide. FALSE is the default.	UPROFLG3.UPRO3JPE
<b>Panel.ENQ.JESPLexScope</b>	TRUE or FALSE	Controls scope of the ENQ panel. If the value is TRUE, the scope of the ENQ panel is JESPLex-wide. If the value is FALSE, the scope of the ENQ panel is sysplex-wide. FALSE is the default.	UPROFLG5.UPRO5JEN

Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Panel.FS.JESplexScope</b>	TRUE or FALSE	Controls the scope of the FS panel. If the value is TRUE, the scope of the FS panel is JESplex-wide. If the value is FALSE, the scope of the FS panel is sysplex-wide. FALSE is the default.	UPROFLG5.UPRO5JFS
<b>Panel.GT.JESplexScope</b>	TRUE or FALSE	Controls the scope of the GT panel. If the value is TRUE, the scope of the GT panel is JESplex-wide. If the value is FALSE, the scope of the GT panel is sysplex-wide. FALSE is the default.	UPROFLG7.UPRO7JGT
<b>Panel.INIT.UseInitNum</b>	TRUE or FALSE	Controls use of initiator number or names when generating commands. If the value is TRUE, the initiator number is used. If the value is FALSE, the initiator name is used. FALSE is the default.	UPROFLG6.UPRO6INN
<b>Panel.JES.JESplexScope</b>	True or FALSE	Controls scope of the JES panel. If the value is TRUE, the scope of the JES panel is JESplex-wide. If the value is FALSE, the scope of the JES panel is sysplex-wide. FALSE is the default.	UPROFLG7.UPRO7JJE
<b>Panel.LLS.JESplexScope</b>	TRUE or FALSE	Controls scope of the LLS panel. If the value is TRUE, the scope of the LLS panel is JESplex-wide. If the value is FALSE, the scope of the LLS panel is sysplex-wide. FALSE is the default.	UPROFLG7.UPRO7JLS
<b>Panel.LNK.JESplexScope</b>	TRUE or FALSE	Controls scope of the LNK panel. If the value is TRUE, the scope of the LNK panel is JESplex-wide. If the value is FALSE, the scope of the LNK panel is sysplex-wide. FALSE is the default.	UPROFLG4.UPRO4JLN
<b>Panel.LPA.JESplexScope</b>	TRUE or FALSE	Controls scope of the LPA panel. If the value is TRUE, the scope of the LPA panel is JESplex-wide. If the value is FALSE, the scope of the LPA panel is sysplex-wide. FALSE is the default.	UPROFLG4.UPRO4JLP

Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Panel.LPD.JESplexScope</b>	TRUE or FALSE	Controls scope of the LPD panel. If the value is TRUE, the scope of the LPD panel is JESplex-wide. If the value is FALSE, the scope of the LPD panel is sysplex-wide. FALSE is the default.	UPROFLG7.UPRO7JLD
<b>Panel.Main.DisableTable</b>	TRUE or FALSE	Controls the format of the main menu. If the value is TRUE, the non-scrollable main panel is shown. If the value is FALSE, the main panel is shown in scrollable format. FALSE is the default.	UPROFLG7.UPRO7JCS
<b>Panel.MEM.JESplexScope</b>	TRUE or FALSE	Controls the scope of the MEM panel. If the value is TRUE, the scope of the MEM panel is JESplex-wide. If the value is FALSE, the scope of the MEM panel is sysplex-wide. FALSE is the default.	UPROFLG8.UPRO8JME
<b>Panel.NA.JESplexScope</b>	TRUE or FALSE	Controls the scope of the NA panel. If the value is TRUE, the scope of the NA panel is JESplex-wide. If the value is FALSE, the scope of the NA panel is sysplex-wide. FALSE is the default.	UPROFLG6.UPRO6NMT
<b>Panel.OMVS.JESplexScope</b>	TRUE or FALSE	Controls scope of the OMVS panel. If the value is TRUE, the scope of the OMVS panel is JESplex-wide. If the value is FALSE, the scope of the OMVS panel is sysplex-wide. FALSE is the default.	UPROFLG7.UPRO7JOM
<b>Panel.PAG.JESplexScope</b>	TRUE or FALSE	Controls scope of the PAG panel. If the value is TRUE, the scope of the PAG panel is JESplex-wide. If the value is FALSE, the scope of the PAG panel is sysplex-wide. FALSE is the default.	UPROFLG4.UPRO4JPA
<b>Panel.PARM.JESplexScope</b>	TRUE or FALSE	Controls scope of the PARM panel. If the value is TRUE, the scope of the PARM panel is JESplex-wide. If the value is FALSE, the scope of the PARM panel is sysplex-wide. FALSE is the default.	UPROFLG4.UPRO4JPM

Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Panel.PC.JESplexScope</b>	TRUE or FALSE	Controls scope of the PC panel. If the value is TRUE, the scope of the PC panel is JESplex-wide. If the value is FALSE, the scope of the PC panel is sysplex-wide. FALSE is the default.	UPROFLG8.UPRO8JPC
<b>Panel.PR.DevNameAlwaysShort</b>	TRUE or FALSE	Controls how device names are formatted on the PR panel. If the value is TRUE, the device names are shown in a shortened format. Otherwise, the name is shown with dots between subtypes. FALSE is the default.	UPROFLG2.UPRO2DF8
<b>Panel.PS.JESplexScope</b>	TRUE or FALSE	Controls the scope of the PS panel. If the value is TRUE, the scope of the PS panel is JESplex-wide. If the value is FALSE, the scope of the PS panel is sysplex-wide. FALSE is the default.	UPROFLG3.UPRO3JPP
<b>Panel.PUN.DevNameAlwaysShort</b>	TRUE or FALSE	Controls how device names are formatted on the PUN panel. If the value is TRUE, the device names are shown in a shortened format. Otherwise, the name is shown with dots between subtypes. FALSE is the default.	UPROFLG2.UPRO2DU8
<b>Panel.RDR.DevNameAlwaysShort</b>	TRUE or FALSE	Controls how device names are formatted on the RDR panel. If the value is TRUE, the device names are shown in a shortened format. Otherwise, the name is shown with dots between subtypes. FALSE is the default.	UPROFLG2.UPRO2DR8
<b>Panel.Settings. DisablePointAndShoot</b>	TRUE or FALSE	Controls the use of point-and-shoot fields on the SDSF primary option menu and the column titles of tabular panels. If the value is TRUE, the fields are not conditioned for point-and-shoot. FALSE is the default.	UPROFLG2.UPRO2PNS

Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Panel.Settings.DisableFieldLevelHighLight</b>	TRUE or FALSE	Controls use of field level highlighting for column values. If the value is FALSE, numeric columns with a value of zero will be lowlighted even if the row is highlighted. Some zero values considered significant will not be lowlighted. FALSE is the default.	UPROFLG6.UPRO6NFH
<b>Panel.Settings.DisableRightAlignNumericCols</b>	TRUE or FALSE	Controls right alignment of values in numeric columns. If the value is FALSE, numeric values will be right aligned in the column. It is no longer necessary to define column titles with leading blanks to force alignment of the value. FALSE is the default.	UPROFLG6.UPRO6NRA
<b>Panel.SMSG.JESPLexScope</b>	TRUE or FALSE	Controls the scope of the SMSG panel. If the value is TRUE, the scope of the SMSG panel is JESPLex-wide. If the value is FALSE, the scope of the SMSG panel is sysplex-wide. FALSE is the default.	UPROFLG5.UPRO5JSG
<b>Panel.SMSV.JESPLexScope</b>	TRUE or FALSE	Controls the scope of the SMSV panel. If the value is TRUE, the scope of the SMSV panel is JESPLex-wide. If the value is FALSE, the scope of the SMSV panel is sysplex-wide. FALSE is the default.	UPROFLG5.UPRO5JSV
<b>Panel.SR.EnableRSYSFilter</b>	TRUE or FALSE	Controls the scope of the SR display. If the value is TRUE, and the user is authorized to the RSYS command, the SR display filters by the current RSYS (reply system) value. If the value is FALSE, the SR display ignores RSYS filtering. FALSE is the default.	UPROFLG6.UPRO6ERF
<b>Panel.SSI.JESPLexScope</b>	TRUE or FALSE	Controls the scope of the SSI panel. If the value is TRUE, the scope of the SSI panel is JESPLex-wide. If the value is FALSE, the scope of the SSI panel is sysplex-wide. FALSE is the default.	UPROFLG5.UPRO5JSS

Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Panel.SVC.JESplexScope</b>	TRUE or FALSE	Controls scope of the SVC panel. If the value is TRUE, the scope of the SVC panel is JESplex-wide. If the value is FALSE, the scope of the SVC panel is sysplex-wide. FALSE is the default.	UPROFLG8.UPRO8JSV
<b>Panel.SYM.JESplexScope</b>	TRUE or FALSE	Controls scope of the SYM panel. If the value is TRUE, the scope of the SYM panel is JESplex-wide. If the value is FALSE, the scope of the SYM panel is sysplex-wide. FALSE is the default.	UPROFLG4.UPRO4JSM
<b>Panel.SYS.JESplexScope</b>	TRUE or FALSE	Controls scope of the SYS panel. If the value is TRUE, the scope of the SYS panel is JESplex-wide. If the value is FALSE, the scope of the SYS panel is sysplex-wide. FALSE is the default.	UPROFLG4.UPRO4JSY
<b>Panel.SYSP.JESplexScope</b>	TRUE or FALSE	Controls scope of the SYSP panel. If the value is TRUE, the scope of the SYSP panel is JESplex-wide. If the value is FALSE, the scope of the SYSP panel is sysplex-wide. FALSE is the default.	UPROFLG8.UPRO8JSP
<b>Panel.VMAP.JESplexScope</b>	TRUE or FALSE	Controls the scope of the VMAP panel. If the value is TRUE, the scope of the VMAP panel is JESplex-wide. If the value is FALSE, the scope of the VMAP panel is sysplex-wide. FALSE is the default.	UPROFLG5.UPRO5JVM



Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Print.CCTL.AlwaysUseASA</b>	TRUE or FALSE	<p>Specifies how SDSF's print function handles carriage control. A value of TRUE causes SDSF to always use ASA carriage control when printing, regardless of the record format of the output data set. A value of FALSE causes SDSF to handle carriage control based on the record format of the output, as follows:</p> <ul style="list-style-type: none"> <li>• If the record format includes A, then the print function uses ASA (ANSI) carriage control.</li> <li>• If the record format includes M, then the print function uses machine carriage control.</li> <li>• Otherwise, SDSF removes carriage control characters if they are present in the source.</li> </ul> <p>TRUE is the default.</p>	
<b>Security.Browse.LogNOFAIL</b>	TRUE or FALSE	<p>Specifies the SAF logging option to use when a job's data sets are browsed from an SDSF panel, with the exceptions of the JDS panel. If the value is TRUE, the SAF logging setting is LOG=NOFAIL (rather than the default, LOG=ASIS). FALSE is the default.</p>	UPROFLG1.UPRO1LNF
<b>Security.Enable.Msg015</b>	TRUE or FALSE	<p>Controls whether message ISF015I is issued. ISF015I is used to report authorization decisions. However, since security for SDSF 2.5 must be implemented via SAF, the message is redundant because the security product also issues messages based on the authorization decision. By default, message ISF015I is longer issued. For compatibility, this custom property can be enabled to cause the message to be issued. TRUE indicates message ISF015I is to be issued. FALSE is the default.</p>	UPROFLG3.UPRO3M15

Table 14. Properties to Specify with the PROPERTY Statement (continued)

Name	Values	Description	Corresponding Field for User Exit
<b>Security.SAFNoDec.WarnMsg</b>	TRUE or FALSE	Specifies the SAF no-decision option in a JES3 environment. If the value is TRUE, an SDSF message is issued whenever a SAF no-decision result (return code 04) is converted to a failure. The message includes the class name, resource name and access level being checked. This setting can be helpful during a conversion period; once you have defined the SAF profiles, set the value to FALSE. FALSE is the default.	UPROFLG1.UPRO1SFW
<b>Security.Syslog.UseSAFRecvr</b>	TRUE or FALSE	Controls the use of RECVR when processing the logical SYSLOG. A value of TRUE indicates that a RECVR equal to the current user ID will be used when the logical SYSLOG is opened. This causes the authorization check to the logical SYSLOG to always succeed (see note). FALSE is the default.	UPROFLG1.UPRO1RCV

**Note:** The resource is *nodeid*.+MASTER+.SYSLOG.SYSTEM.*sysname*.

## Code page (TRTAB/TRDEF or ISFTR)

A TRTAB statement or ISFTR macro specifies the code page that SDSF uses for a group of users. SDSF uses the code page to ensure that it displays valid characters on the terminal and to convert lowercase characters to uppercase.

A code page consists of two translation tables. One table contains the character set that is valid for a group of users and the other contains the uppercase characters for that character set. SDSF folds all input data, such as action characters, to uppercase and verifies all the data it displays, such as field titles, for valid characters. If SDSF encounters a character that is not in the valid character set table, it displays that character as a blank.

The code page you specify does not apply to the pull-downs and pop-ups displayed by ISPF. For them, ISPF uses the code page defined for the terminal type currently in effect.

If none of the code pages that can be specified with the CODPAG parameter match the needs of your installation, you can code your own translation tables in ISFPARMS or in your statements. See [“Coding a translate table” on page 71](#) for more information.

The ISFTR macro in ISFPARMS must follow all ISFGRP macros.

## Examples of the TRTAB statement and ISFTR macro

TRTAB Statement	ISFTR Macro
No TRTAB coded	ISFTR

This example shows the minimum coded parameters for the ISFTR macro and the TRTAB statement. The ISFTR macro includes no parameters. THE TRTAB statement is omitted altogether. In this case, the VALTAB and UPCTAB parameters are not coded here, nor in the group definitions (ISFGRP macros or GROUP statements). All SDSF users are assigned the default code page, SDSF.

TRTAB Statement	ISFTR Macro
<pre> 1 GROUP VALTAB(VAL500) , 2   UPCTAB(UPC500) 3 GROUP CONFIRM(ON) 4 TRTAB CODPAG(CP00500) , VALTAB(VAL500) , 5   UPCTAB(UPC500) </pre>	<pre> 1 ISFGRP VALTAB=VAL500 , 2   UPCTAB=UPC500 3 ISFGRP CONFIRM=ON 4 ISFTR CODPAG=CP00500 , VALTAB=VAL500 , 5   UPCTAB=UPC500 6 ISFTR </pre>

On line **1** of the example, the VALTAB parameter specifies VAL500 as the name of the translation table that checks for valid characters.

On line **2**, the UPCTAB parameter specifies UPC500 as the name of the translation table that converts lowercase characters to uppercase.

On line **3**, the GROUP CONFIRM parameter specifies confirmation of destructive action characters (such as cancel or purge).

The translation tables are generated by an ISFTR macro or TRTAB statement that has VALTAB and UPCTAB parameters that name the same translation tables, which is found on lines **5** and **6**. The CODPAG parameter specifies the code page, CP00500, that is to be used for the group of users.

On line **6** in the assembler example is the ISFTR macro with no parameters. This assigns the default code page, SDSF, which will be used with the second group of users. Assigning the default code page in this manner is not required with statements.

## TRTAB and ISFTR syntax

### TRTAB Statement

```

TRTAB CODPAG (code-page),
      VALTAB (valid-character-translation-table-name),
      UPCTAB (uppercase-translation-table-name)

```

### ISFTR Macro

```

ISFTR CODPAG=code-page,
      VALTAB= valid-character-translation-table-name
      UPCTAB= uppercase-translation-table-name

```

### CODPAG

Specifies an alternate code page, *code-page*, that SDSF will use for a group of users. The valid character and uppercase translation tables generated by SDSF correspond to the CODPAG you specify.

If you omit this parameter, SDSF uses code page **SDSF** (or CP00037, when running SDSF in batch with program name ISFAFD).

*code-page* can be:

#### SDSF

USA WP, Original.

SDSF consists of CP00001 plus three optical character reader (OCR) characters, which results in mixed-case characters in the help panels, SDSF panels, and the SDSF Primary Option menu.

#### CASE

Same as SDSF, but characters are folded to uppercase.

**CP00037**  
USA/Canada – CECP

**CP00273**  
Germany F.R./Austria – CECP

**CP00275**  
Brazil – CECP

**CP00277**  
Denmark, Norway – CECP

**CP00278**  
Finland, Sweden – CECP

**CP00280**  
Italy – CECP

**CP00281**  
Japan (Latin) – CECP

**CP00284**  
Spain/Latin America – CECP

**CP00285**  
United Kingdom – CECP

**CP00290**  
Japanese (Katakana) Extended

**CP00297**  
France – CECP

**CP00420**  
Arabic, Bilingual

**CP00424**  
Israel (Hebrew) Extended

**CP00500**  
International #5

**CP00803**  
Hebrew Character Set A

**CP00833**  
Korean Extended

**CP00836**  
Simplified Chinese Extended

**CP00870**  
Latin 2/Multilingual/ROECE

**CP00871**  
Iceland – CECP

**CP00875**  
Greece

**CP01025**  
Cyrillic, Multilingual

**CP01026**  
Latin 5/Turkey

**CP01027**  
Japanese (Latin) Extended

**CP01047**  
Latin 1/Open systems

**CP01112**  
Baltic, Multilingual

**CP01122**

Estonia

**CP01140**

ECECP USA, Canada, Netherlands, Portugal, Brazil, Australia, New Zealand

**CP01141**

ECECP Austria, Germany

**CP01142**

ECECP Denmark, Norway

**CP01143**

ECECP Finland, Sweden

**CP01144**

ECECP Italy

**CP01145**

ECECP Spain, Latin America (Spanish)

**CP01146**

ECECP UK

**CP01147**

ECECP France

**CP01148**

ECECP Belgium, Canada, Switzerland

**CP01149**

ECECP Iceland

**CP01153**

EBCDIC Latin 2 Multilingual with Euro Extended

**CP01159**

T-Chinese EBCDIC

**VALTAB**

Specifies the name of the valid character set translation table. If omitted, SDSF uses TRTAB for the name. TRTAB cannot be used as a default name more than once.

Use the same value for *valid-character-translation-table-name* that you used in the VALTAB parameter of the ISFGRP macro or GROUP statement for the group. If you have more than one ISFTR macro in ISFPARMS, you must use a unique name for each *valid-character-translation-table-name*.

**UPCTAB**

Specifies the name of the uppercase translation table. If omitted, SDSF uses TRTAB2 for the name. TRTAB2 cannot be used as a default name more than once.

Use the same value for *uppercase-translation-table-name* that you used in the UPCTAB parameter of the ISFGRP macro or GROUP statement for the group. If you have more than one ISFTR macro in ISFPARMS, you must use a unique name for each *uppercase-translation-table-name*.

## Coding a translate table

To code your own translate table, use the VALTAB and UPCTAB parameters of an ISFGRP macro or GROUP statement to assign the translate tables to a group of users. Then, if you are using ISFPARMS assembler macros, code the translate table in the ISFPARMS module, after the ISFGRP macros. If you are using statements, define the translate table with the TRDEF statement.

The translate tables must be 256 bytes each.

## TRDEF syntax

### TRDEF Statement

TRDEF NAME(*table-name*),  
DATA(*hex-characters*)

#### NAME(*table-name*)

names the translate table being defined. The name is referenced in the UPCTAB or VALTAB parameter of a GROUP statement.

#### DATA(*hex-characters*)

specifies the translate table, which must be 256 bytes.

### Example of the TRDEF statement

```
1 GROUP VALTAB(UVALTAB),
2   UPCTAB(UUPCTAB)
3 TRDEF NAME(UVALTAB), /* Valid character table */
4   DATA(000102030405060708090A0B0C0D0E0F, /* 00-0F */
        101112131415161718191A1B1C1D1E1F, /* 10-1F */
        202122232425262728292A2B2C2D2E2F, /* 20-2F */
        303132333435363738393A3B3C3D3E3F, /* 30-3F */
        404142434445464748494A4B4C4D4E4F, /* 40-4F */
        505152535455565758595A5B5C5D5E5F, /* 50-5F */
        606162636465666768696A6B6C6D6E6F, /* 60-6F */
        707172737475767778797A7B7C7D7E7F, /* 70-7F */
        808182838485868788898A8B8C8D8E8F, /* 80-8F */
        909192939495969798999A9B9C9D9E9F, /* 90-9F */
        A0A1A2A3A4A5A6A7A8A9AAABACADAFAF, /* A0-AF */
        B0B1B2B3B4B5B6B7B8B9BABBBBCDBEBF, /* B0-BF */
        C0C1C2C3C4C5C6C7C8C9CACBCCDCECF, /* C0-CF */
        D0D1D2D3D4D5D6D7D8D9DADBDCDDDEDF, /* D0-DF */
        E0E1E2E3E4E5E6E7E8E9EAEBECEDEEEF, /* E0-EF */
        F0F1F2F3F4F5F6F7F8F9FAFBFCFDFEFF) /* F0-FF */
5 TRDEF NAME(UUPCTAB), /* Upper case table */
6   DATA(000102030405060708090A0B0C0D0E0F, /* 00-0F */
        101112131415161718191A1B1C1D1E1F, /* 10-1F */
        202122232425262728292A2B2C2D2E2F, /* 20-2F */
        303132333435363738393A3B3C3D3E3F, /* 30-3F */
        404142434445464748494A4B4C4D4E4F, /* 40-4F */
        505152535455565758595A5B5C5D5E5F, /* 50-5F */
        606162636465666768696A6B6C6D6E6F, /* 60-6F */
        707172737475767778797A7B7C7D7E7F, /* 70-7F */
        808182838485868788898A8B8C8D8E8F, /* 80-8F */
        909192939495969798999A9B9C9D9E9F, /* 90-9F */
        A0A1A2A3A4A5A6A7A8A9AAABACADAFAF, /* A0-AF */
        B0B1B2B3B4B5B6B7B8B9BABBBBCDBEBF, /* B0-BF */
        C0C1C2C3C4C5C6C7C8C9CACBCCDCECF, /* C0-CF */
        D0D1D2D3D4D5D6D7D8D9DADBDCDDDEDF, /* D0-DF */
        E0E1E2E3E4E5E6E7E8E9EAEBECEDEEEF, /* E0-EF */
        F0F1F2F3F4F5F6F7F8F9FAFBFCFDFEFF) /* F0-FF */
```

On the line marked with **1**, a GROUP statement begins the definition of a group and the VALTAB parameter gives the valid character translation table the name UVALTAB. On the line marked with **2**, the UPCTAB parameter gives the uppercase translation table the name UUPCTAB. The names UVALTAB and UUPCTAB are used to associate these parameters with TRDEF statements on lines **3** and **5**. The valid character translate table is defined beginning on line **4**. The uppercase translate table is defined beginning on line **6**.

## Chapter 3. Using the SDSF server

The SDSF server is an address space that SDSF uses to:

- Process ISFPARMS statements.
- Provide sysplex support. This consists of sysplex-wide data for JES2 devices and for system resources.
- Manage the starting and stopping of the SDSFAUX address space. SDSFAUX is used to provide data gathering support and other services for SDSF panels.

The SDSF server is required for SDSF 2.5 and later.

It is recommended that you place the SDSF and SDSFAUX address spaces in the medium priority started task WLM service class. Because SDSFAUX is responsible for data collection, it should be placed into a higher priority WLM service class. For example, SDSF could be placed into STCMD and SDSFAUX placed in STCHI.

SDSF includes a server startup option, **NOPARM**, that allows the server and SDSFAUX to be started and the panels that require SDSFAUX are available, but ISFPRMxx is not processed. When the client then accesses SDSF, a noparm condition is returned by the server and the server falls back to ISFPARMS. The user must have READ access to the **SERVER.NOPARM** resource in the SDSF class to use ISFPARMS instead of ISFPRMxx.

Only a single SDSF (and associated SDSFAUX) address space can be active at the same time. All SDSF users will connect to the one (and only) SDSF address space that is active. An attempt to start a second SDSF address space (regardless of server name) is rejected with a "server already active" message.

You control the server through the MVS operator START, STOP, and MODIFY commands. For details on the commands, see [“Server operator commands” on page 75](#).

Sample JCL for the server is in member ISFSRJCL (alias SDSF) of data set ISF.SISFJCL.

Sample JCL for SDSFAUX is in member HSFSRJCL (alias SDSFAUX) of data set ISF.SISFJCL.

**Note:** SDSF requires that ISF.SISFLOAD be in the system lnklst.

### Configuring server security

The SDSF server requires security configuration before it can be started. The server consists of two address spaces, by default named SDSF and SDSFAUX.

Configure the server as follows:

1. Ensure that the SAF SDSF class is RACLISTed. For more information on RACLIST, see [Chapter 6, “SDSF and RACF,” on page 219](#).
2. Define a user ID associated with the SDSF and SDSFAUX address spaces by adding a profile to the SAF STARTED class. The same user ID can be used for both address spaces. For example:

```
RDEFINE STARTED SDSF*. * STDATA(USER(SDSF))
```

associates user ID SDSF with both the SDSF and SDSFAUX address spaces.

3. Allow the SDSF server to access your WLM policy. For example:

```
PERMIT MVSADMIN.WLM.POLICY ACCESS(READ) CLASS(FACILITY) ID(SDSF)
```

allows user ID SDSF to gather WLM data.

4. Allow the SDSFAUX server to gather RMF information. For example:

```
PERMIT ERBSDS.MON2DATA ACCESS(READ) CLASS(FACILITY) ID(SDSF)
```

5. Ensure that the user ID associated with the SDSFAUX address space has an OMVS segment so that it can invoke USS services. UID(0) is not required.

Additional SAF resources are used to secure other functions of the SDSF server, including:

- Reverting from ISFPRMxx to the assembler style ISFPARMS when the initial ISFPRMxx fails to activate.
- Use of the server operator parms.

For more information, see [“SDSF server” on page 338](#).

## Defining the input

---

The input to the SDSF server is the ISFPARMS statements. By default, SDSF assumes the statements reside in PARMLIB, in member ISFPRM00. You can use a PARMLIB member with a different suffix by specifying that suffix on the command you use to start the server. See [“Start the SDSF server” on page 75](#). Or you can use your own partitioned data set, rather than PARMLIB, by defining it using ddname SDSFPARM in the server JCL.

For details on defining the ISFPARMS statements, see [Chapter 2, “Using ISFPARMS for customization,” on page 5](#).

## Starting the server

---

You start the server using the START command. The command takes the server name as a parameter. Optional parameters identify the suffix of PARMLIB member ISFPRMxx that contains the statements to be read, as well as other options. For details, see [“Start the SDSF server” on page 75](#).

If the SDSF server fails to start, see the information in the troubleshooting topic [“The SDSF server fails to start” on page 498](#).

## Starting the SDSFAUX server

---

The SDSFAUX address space is automatically started by the SDSF server address space when the server starts. Conversely, SDSFAUX is automatically stopped when the SDSF server is stopped.

Keep the following considerations in mind:

- By default, the SDSF server starts SDSFAUX. You can change the SDSFAUX procedure and job names using the AUXPROC and AUXNAME keywords of the CONNECT statement as described in the [“CONNECT statement” on page 16](#).
- If SDSFAUX is already active, any changes to parameters related to SDSFAUX on the CONNECT statement such as AUXPROC, AUXNAME, and AUXSAF are ignored. If you make changes to the CONNECT statement related to SDSFAUX, stop the SDSF server and wait for SDSFAUX to end. Then, restart the SDSF server for the changes to take effect.

## Processing the statements

---

When the server is started, it reads the statements from the input data set.

You can activate new parameters at any time with the MODIFY command, which you can enter from the console or from SDSF by users that are authorized to use the slash (/) command. Changes take effect the *next* time users access SDSF. A TEST parameter allows you to check the syntax of the statements without activating them. See [“Refresh ISFPARMS” on page 85](#) for more information.

## Accessing the server

---

When the user accesses SDSF, the SDSF client attempts to connect to the SDSF server. The SDSF address space must be active.

**Note:** Only a single server can be active on the system.



# Logging

The SDSF server logs all statements processed, and any associated error messages, to a log file. With the server START command, you can control the destination of the log file (SYSOUT or the hardcopy log). When the destination is SYSOUT, SDSF uses the class specified in the server JCL if one is specified there, or the class specified in the LOGCLASS option on the START command. If no SYSOUT class is specified, SDSF uses class A. When SDSF dynamically allocates the log, it is freed when it is closed. In the event of an error allocating the log, SDSF redirects any log messages to the hardcopy log. Messages issued by the server are documented in [Chapter 10, “SDSF messages and codes,”](#) on page 367.

The SDSFAUX log is written to the HSFLOG data set allocated by the SDSF server address space. It contains messages related to processing for use by IBM service personnel.

# Security

Security for the SDSF server is provided with SAF resources. You can protect these aspects of the server related to processing ISFPARMS statements:

- Reverting from ISFPARMS in statement format to ISFPARMS in assembler macro format.
- Use of the server operator commands.

For details on these aspects of server security, see [“SDSF server”](#) on page 338.

# Server operator commands


You control the server with the MVS operator commands described on the pages that follow.

## Start the SDSF server


Use the server START command to initialize the SDSF server address space, and to control server options. When the server is initialized, the server is ready to process requests from the SDSF application.

### Format


#### Server START Command



#### Address Space




#### Message Folding




### Log Class




### Log Type




### ARM




### Trace



### Trace SYSOUT Class



### Debug



### *proc-name*

is the name of the SDSF server to be started. The SDSF server name is the same as the procedure name; the server must run as a started task.

### *identifier*

is an identifier that is used as the server name, instead of the procedure name.

### **MEMBER or M=xx**

specifies the suffix of member name ISFPRMxx, which contains the statements to be read. The default for xx is 00. The data set is either PARMLIB or a data set defined in the server JCL using ddname SDSFPARM.

### *parameters*

are the following:

#### **REUSASID**

**YES** specifies that SDSF and SDSFAUX will attempt to use an ASID from the reusable address space pool. This is strongly recommended.

**NOFOLDMSG or NOFM**

specifies that server messages should not be folded to uppercase; they are in mixed case. This is the default.

**FOLDMSG or FM**

specifies that server messages should be folded to uppercase.

**LOGCLASS or LC (class)**

specifies the default SYSOUT class for the server log. If no SDSFLOG is defined in the JCL, SDSF will dynamically allocate a log to this class. The default is A.

**LOGTYPE or LT**

specifies the destination of the server log. The options are as follows:

**FILE or FI**

specifies that the report will be written to file with the ddname SDSFLOG. This is the default, unless the SDSF server is running under MSTR.

**HARDCPY or HC**

specifies that messages issued during processing of ISFPARMS will be written to the hardcopy log (syslog). This is the default if the SDSF server is running under MSTR.

**ARM**

specifies that ARM registration will be done if ARM is active in the system. The server will register using the following values:

- element name: ISFserver-name@&sysclone
- element type: SYSSDSF
- termtype: ELEMENTYPE

**NOARM**

specifies that ARM registration will not be done.

**NOPARM**

allows the server and SDSFAUX to be started, but ISFPRMxx is not processed. When the client accesses SDSF, a noparm condition is returned by the server and the server falls back to ISFPARMS.

**Note:** IBM recommends that ISFPRMxx be used in place of ISFPARMS. If you cannot use ISFPRMxx until you have converted ISFPARMS, use the NOPARM option to make all SDSF functions available to users when running in fallback mode.

When accessing SDSF, clients will fall back to ISFPARMS if they have authority to do so. The user must have READ access to the **SERVER.NOPARM** resource in the SDSF class so that ISFPARMS can be used instead of ISFPRMxx. See [“NOPARM fallback” on page 7](#) for a description of **SERVER.NOPARM**.

After the server is started in NOPARM mode, a **MODIFY REFRESH** command will ignore ISFPRMxx. You must restart the server without NOPARM for ISFPRMxx to be processed.

A generic tracker event is created for this condition to alert you that fallback is occurring. See [z/OS MVS Diagnosis: Tools and Service Aids](#) for information on generic tracker events. You can use the [“Generic Tracker panel \(GT\)” on page 115](#) to view the generic tracker event. The generic tracker event for this condition includes the following fields:

- **OWNER** is IBMSDSF.
- **EVENTDESC** is SDSF DISPLAY ACTIVE FALLBACK: ISFMIGDA ALLOCATED .
- **PROGRAM** is the SDSF module that detected the event.
- **EVENTDATA** is set to zeros.

**TRACE or TR**

specifies the trace option. Tracing should be used under the direction of IBM service personnel. The options are as follows:

**ALL**

enables all trace records.

**NONE**

disables all trace records.

**ON**

enables a subset of trace records.

**TRCLASS or TC (*sysout-class*).**

specifies the SYSOUT class to be used when dynamically allocating a trace file. If no ISFTRACE ddname is present in the server JCL, a trace will be allocated to SYSOUT using this class.

**NODEBUG or NODB**

specifies that the server should not run in diagnostic mode. This is the default.

**DEBUG or DB**

specifies that the server should run in diagnostic mode. This parameter is intended for use by IBM Service.

**Notes to users**

1. You must start the server before any users access SDSF, so that the statements can be read.
2. You can start only a single server.
3. When tracing is active, significant performance degradation may occur. A significant amount of trace output may be generated.
4. If the installation has defined an SDSFLOG DD statement in the server proc and SDSF is running under MSTR, you must specify LOGTYPE=FILE. The default value of HARDCPY will cause the server log not to be written to SDSFLOG.
5. The SDSFAUX log is written to the HSFLOG data set allocated by the SDSF server address space. It contains messages related to processing.

**Examples**

1. S SDSF

This command starts the SDSF server address space with the name SDSF.

2. S SDSF,M=01

This command starts the SDSF server address space with the name SDSF. Statements will be read from member ISFPRM01 of the data set defined in the server JCL. Member ISFPRM01 is made the default member for any subsequent MODIFY *server*, REFRESH commands.

3. S SDSF,M=01,P='FM,LC(H)'

This command starts the SDSF server address space, with the name SDSF. Statements will be read from member ISFPRM01 of the data set defined in the server JCL. Server messages will be folded to uppercase. The default SYSOUT class for the server log is H.

4. S SDSFT.SDSF

This command starts the SDSF server with procedure name SDSFT and server name SDSF.

**Start Aux**

Use the MODIFY,START command to start the SDSFAUX address space.

**Format**

The syntax is shown in [Figure 1 on page 79](#).




Figure 1. Start Aux Options – Syntax

**server-name**

is the name of the SDSF server.

**START or S**

starts the address space.

**AUX**

starts the SDSFAUX address space using the AUXNAME and AUXPROC settings from the CONNECT statement in ISFPRMxx. If the SDSFAUX address space is still active, message ISF453I is issued.

During normal SDSF server startup, SDSFAUX is automatically started if the ISFPRMxx member has been successfully parsed and processed.

**Important:** Do not start the SDSFAUX address space manually using the **S SDSFAUX** operator command.

**Example**

```
F SDSF, S AUX
```


This command starts the SDSFAUX address space.

**Change server options**


Use the MODIFY command to dynamically change server options. You can specify a test mode to cause the syntax of the statements to be checked without activating the statements.

**Format**


The syntax is shown in [Figure 2 on page 80](#).




## Message Folding




## Log Class



## Log Type



## Trace SYSOUT Class



## Debug




Figure 2. Change Server Options — Syntax

### **server-name**

is the name of the SDSF server to be modified.

### **TEST**

indicates that the syntax of the statements is to be syntax checked, but the statements are not to be activated.

### **parameter**

is one of the following:

#### **NOFOLDMSG or NOFM**

specifies that server messages should not be folded to uppercase; they are in mixed case. This is the default.

#### **FOLDMSG or FM**

specifies that server messages be folded to uppercase.

#### **LOGCLASS or LC (class)**

specifies the default SYSOUT class for the server log. If no SDSFLOG is defined in the JCL, SDSF will dynamically allocate a log to this class. The default is A.

#### **LOGTYPE or LT**

specifies the destination of the server log. The options are as follows:

**FILE or FI**

specifies that the report will be written to file with the ddname SDSFLOG.

**HARDCPY or HC**

specifies that messages issued during processing of ISFPARMS will be written to the hardcopy log (syslog)

**TRCLASS or TC (*sysout-class*)**

specifies the SYSOUT class to be used when dynamically allocating a trace file. If no ISFTRACE ddname is present in the server JCL, a trace will be allocated to SYSOUT using this class.

**NODEBUG or NODB**

specifies that the server should not run in diagnostic mode.

**DEBUG or DB**

specifies that the server should run in diagnostic mode. This parameter is intended for use by IBM Service.

**Note to users**

When tracing is active, significant performance degradation may occur. A significant amount of trace output may be generated.

**Example**

```
F SDSF,LC(H)
```


This command changes the default SYSOUT class for the server log to H.

**Display Exit**

Use the MODIFY,D command to display invocation counts for the various system exits and ENF listener routines that have been installed by the SDSF server.

**Format**

The syntax is shown in [Figure 3 on page 81](#).



*Figure 3. Display Exit Options — Syntax*

***server-name***

is the name of the SDSF server.

**DISPLAY or D**

displays information about the server.

**EXIT**

shows invocation counts for the various system exits and ENF listener routines that have been installed by the SDSF server. The output from the DISPLAY EXIT command is message ISF356I.

**Example**

```
F SDSF,D EXIT
```

This command displays invocation counts for the various system exits and ENF listener routines that have been installed by the SDSF server.

**Display Help**

Use this command to display the syntax of available SDSF modify operator commands.

## Format

The syntax is shown in [Figure 4 on page 82](#).




Figure 4. Display Help Options – Syntax

### **server-name**

is the name of the SDSF server.

### **HELP**

shows the syntax of available SDSF modify operator commands. The output from HELP is message ISF361I.

## Example

F SDSF ,HELP

This command displays the syntax of available SDSF MODIFY operator commands.

## Display JES

Use the MODIFY,D command to display known systems in the sysplex and JES subsystems in the MAS.

## Format

The syntax is shown in [Figure 5 on page 82](#).




Figure 5. Display JES Options – Syntax

### **server-name**

is the name of the SDSF server.

### **DISPLAY or D**

displays information about the server.

### **JES**

shows known systems in the sysplex and JES subsystems in the MAS. The output from the DISPLAY JES command is message ISF351I.

**Note:** It is possible to get a line for a z/OS system without any JES information as well as another line with JES information populated. This is because the source of the JES and system information comes from two sources: sysplex systems and the MAS.

## Example

F SDSF ,D JES

This command displays known systems in the sysplex and JES subsystems in the MAS.

## Display Services

Use the MODIFY,D command to display SDSF service invocation counts and date stamps.

## Format

The syntax is shown in [Figure 6 on page 83](#).






Figure 6. Display Services – Syntax

**server-name**

is the name of the SDSF server.

**DISPLAY or D**

displays information about the server.

**SERV**

shows service invocation counts and date stamps. The output from DISPLAY SERV is message ISF354I.

**Example**

F SDSF,D SERV

This command displays a list of SDSF service invocations with associated counts and date stamps.

## Display Systems

Use the MODIFY,D command to display information about the systems in the sysplex known to SDSF.

**Format**

The syntax is shown in [Figure 7 on page 83](#).



Figure 7. Display Systems Options – Syntax

**server-name**

is the name of the SDSF server.

**DISPLAY or D**

displays information about the server.

**SYS**

produces a list of systems in the sysplex, their versions, and their statuses. The output from DISPLAY SYS is message ISF349I.

**Example**

F SDSF,D SYS

This command displays a list of systems in the sysplex, their versions, and their statuses.

## Display Task

Use the MODIFY,D command to display the CPU consumption for both the SDSF and SDSFAUX address spaces by task name.

**Format**

The syntax is shown in [Figure 8 on page 84](#).




Figure 8. Display Task Options – Syntax

**server-name**

is the name of the SDSF server.

**DISPLAY or D**

displays information about the server.

**TASK**

shows the CPU consumption for both the SDSF and SDSFAUX address spaces by task name. The output from the DISPLAY TASK command is message ISF353I.

## Example

F SDSF,D TASK

This command displays the CPU consumption for both the SDSF and SDSFAUX address spaces by task name.

## Display User

Use the MODIFY,D command to display the active connected users of the SDSF server.

### Format

The syntax is shown in [Figure 9 on page 84](#).




Figure 9. Display User Options – Syntax

**server-name**

is the name of the SDSF server.

**DISPLAY or D**

displays information about the server.

**USER**

shows the active connected users of the SDSF server. The output from the DISPLAY USER command is message ISF352I.

## Example

F SDSF,D USER

This command displays the active connected users of the SDSF server.

## Display information about server communications

Use this command to display information about the servers and the communication between SDSF servers.

### Format

The syntax is shown in [Figure 10 on page 85](#).




Figure 10. Display Information About Server Communications — Syntax

**server-name**

is the name of the SDSF server.

**DISPLAY or D**

displays information about the server, including the status of the server and server communications

**COMM or C**

displays summary information about the XCF communications being used by the SDSF server. The output from the DISPLAY COMM command is message ISF315I.

**DETAIL**

displays detailed information about each XCF task. The output from the DISPLAY COMM,DETAIL command is message ISF355I.

## Refresh ISFPARMS

Use this command to refresh ISFPARMS statements. You can specify a test mode to cause the syntax of the statements to be checked without activating the statements.

### Format

The syntax is shown in [Figure 11 on page 85](#).




Figure 11. Refresh ISFPARMS — Syntax

**server-name**

is the name of the SDSF server to be modified.

**REFRESH**

indicates that a new set of statements is to be processed.

**MEMBER or M(xx)**

specifies the suffix of member name ISFPRMxx, which contains the statements to be read. The data set is either PARMLIB or a data set defined in the server JCL using ddname SDSFPARM. The default for xx is whatever was used to start the server. For example, if you start the server with S SDSF, M=01, then refresh it with F SDSF, REFRESH, the member suffix used for the refresh is 01. If no suffix was specified on the START command, the suffix default is 00.

**TEST**

indicates that the syntax of the statements is to be syntax checked, but the statements are not to be activated.

### Notes to users

1. A MODIFY REFRESH command processes only the statements defined in the current input stream. Any statements processed prior to the refresh are discarded when the new parameters are activated. If an error occurs, the current ISFPARMS remain in effect.

2. When SDSF is running on multiple systems in either a MAS or a sysplex, the SDSF server must be active on each system. Although the servers can share the same parameter data set, a MODIFY REFRESH command must be issued against each server.

## Examples

### 1. F SDSF, REFRESH

This command activates a new set of statements for server SDSF. Because no member is specified, SDSF uses the member that was used when the server was started.

### 2. F SDSFK, REFRESH, TEST

This command causes the syntax of statements to be checked for server SDSFK. The statements will not be activated.

### 3. F SDSFT, REFRESH, M=01, TEST

This command causes the syntax of statements to be checked for server SDSFT. Statements will be read from member ISFPRM01 of the data set defined in the server JCL. The statements will not be activated.

## Refresh JES

Use this command to manually refresh the SDSF server list of known JES subsystems. Although SDSF maintains a dynamic list of known JES subsystems, there can be instances where system problems prevent the expected notifications from arriving at the SDSF server. This command requests a manual update of the known JES subsystems list.

### Format

The syntax is shown in [Figure 12 on page 86](#).




Figure 12. Refresh JES — Syntax

#### **server-name**

is the name of the SDSF server to be modified.

#### **REFRESH**

requests manual update of the known JES subsystems list.

#### **JES**

specifies that the JES subsystems list is to be updated.

## Example

F SDSF, R JES

This command requests a manual update of the known JES subsystem list.

## Refresh SYS

Use this command to manually refresh the SDSF server list of known z/OS systems in the sysplex. Although SDSF maintains a dynamic list of known z/OS systems in the sysplex, there can be instances where system problems prevent the expected notifications from arriving at the SDSF server. This command requests an manual update of the known z/OS systems list.

## Format

The syntax is shown in [Figure 13 on page 87](#).




Figure 13. Refresh SYS — Syntax

### **server-name**

is the name of the SDSF server to be modified.

### **REFRESH**

requests manual update of the known z/OS systems list.

### **SYS**

specifies that the z/OS systems list is to be updated.

## Example

F SDSF,R SYS

This command requests a manual update of the known z/OS systems list.

## Set Sample

Use the MODIFY SET command to override the sampling interval for one or more data collection agents running in the SDSF server address spaces.

**Important:** Use this command only under the direction of IBM support personnel.

## Format

The syntax is shown in [Figure 14 on page 87](#).




Figure 14. Set Sample Options — Syntax

### **server-name**

is the name of the SDSF server.

### **SET**

specifies SET server information.

### **SAMPLE(n)**

specifies the number of seconds between each data gathering sample.

### **NAME(mask)**

specifies the name mask for the affected data gathering agent(s). An asterisk (\*) can be used to specify zero or more masking characters. A percent sign (%) can be used to specify a single masking character.

## Example

F SDSF,T SAMPLE(3),NAME(HSFASD\*)

**Note:** The command accepts either = or () syntax. F SDSF,T SAMPLE=3,NAME=HSFASD\* is also valid.






Figure 16. Start Communications — Syntax

**server-name**

is the name of the SDSF server.

**START or S**

indicates that the action is start.

**COMM or C**

causes communication between servers to be started.

## Stop communications

Use this command to stop communications between SDSF servers. You might use this command if a server is known to be unavailable, so that SDSF does not send requests to that server or wait for responses from it.

### Format

The syntax is shown in [Figure 17 on page 89](#).




Figure 17. Stop Communications — Syntax

**server-name**

is the name of the SDSF server.

**STOP or P**

indicates that the action is stop.

**COMM or C**

causes communication between servers to be stopped.

**TERMINATE or TERM**

ends communications. TERM can also be used to stop communications initialization.

## Stop the SDSF server

Use the STOP command to end the server.

### Format

The syntax of the STOP command is shown in [Figure 18 on page 89](#).




Figure 18. STOP the SDSF Server — Syntax

**server-name**

is the name of the SDSF server to be stopped.

## Example

P SDSF

This command stops server SDSF.

## Stop Aux

Use the MODIFY,STOP command to stop the SDSFAUX address space.

### Format

The syntax is shown in [Figure 19 on page 90](#).




Figure 19. Stop Aux Options — Syntax

#### **server-name**

is the name of the SDSF server.

#### **STOP or P**

stops the address space.

#### **AUX**

stops the SDSFAUX address space. If the address space is not active, message ISF454I is issued. Stopping the SDSFAUX address space terminates certain data collectors, and sample displays in SDSF clients will not be able to show any data. XCF data communication services run in the SDSFAUX address space and are therefore available only when SDSFAUX is active.

Stopping the main SDSF server address space automatically stops the SDSFAUX address space.

**Important:** As of z/OS 2.3, do not stop the SDSFAUX address space manually using the **P SDSFAUX** operator command.

## Example

F SDSF,P AUX

This command stops the SDSFAUX address space.

## Switch Log

Use the MODIFY,SWITCH command to close and reopen the HSFLOG DDname allocated to the SDSF server.

### Format

The syntax is shown in [Figure 20 on page 90](#).




Figure 20. Switch Log Options — Syntax

#### **server-name**

is the name of the SDSF server.

#### **SWITCH or I**

switches the log.



closes and reopens the HSFLOG DDname allocated to the SDSF server. This allows previous output queued to HSFLOG to be spun.

F SDSF, I LOG

## Switch Trace

## Format

➡ MODIFY SDSF , SWITCH TRACE ➡

└── F ─┘ └── server-name ─┘ └── I ─┘

***server-name***

**SWITCH or I**

**TRACE**

closes and reopens the HSFTRACE DDname allocated to the SDSF server. This allows previous output queued to HSFTRACE to be spun.

## F SDSF,I TRACE

Chapter 3. Using the SDSF server **91**



# Chapter 4. Columns on the SDSF panels

This topic describes the columns on SDSF panels that display data in a tabular format. Use this information when coding:

- FLD statements or ISFFLD macros, to customize which columns are included on a tabular panel, as well as their order, titles and widths.
- REXX execs or Java programs. Reference columns by their *names* rather than by their *titles*.

Users can use the **ARRANGE** command to reorder or change the widths of the columns, and to hide columns to reduce left/right scrolling. Hidden columns are an alternative to suppressing columns with multiple field lists in ISFPARMS. Hidden columns are not visible on the tabular panels but you can still sort and filter them. The Show Columns pop-up displays all column values, even if the column is hidden. **ARRANGE** is described in the online help.

When displaying numeric values that are too large for the column width, SDSF scales them using these abbreviations: T (thousands), M (millions), B (billions), KB (kilobytes), MB (megabytes), GB (gigabytes), TB (terabytes) and PB (petabytes).

The fields on the title lines of SDSF panels cannot be customized. They are described in the online help.

In the tables that follow, an X in the *Delay* column indicates that obtaining the data may require an I/O operation. These columns are typically in the alternate field list. I/O operations are performed only when the columns are visible on the screen or being sorted. SDSF performance is best when columns that require an I/O operation are at the end of the field list. If there are no columns requiring I/O, the Delay column is not included.

## Action Help panel (ACTH)

The ACTH command displays a table of the action characters that can be issued in SDSF tabular panels.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 15. Columns on the ACTH Panel

Column name	Title (Displayed)	Width	Description
<b>COMMAND</b>	COMMAND	7	Action command. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>PANEL</b>	Panel	5	Panel name
<b>DESC</b>	Description	28	Command description
<b>AUTH</b>	AuthLevel	9	Auth level required for command
<b>JES</b>	JES	4	JES type
<b>ENV</b>	Environment	54	Valid environments
<b>NEW</b>	New	3	New action
<b>CLASS</b>	Class	8	SAF class
<b>RESOURCE</b>	Resource	64	SAF resource
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Address Space Diagnostics panel (AD)

The Address Space Diagnostics (AD) panel allows you to review identification information about each address space and the memory addresses of important control blocks. You can then use the point-and-shoot action on the control blocks to invoke memory browse.

By default, address spaces considered to be initiators are excluded from the list. You can direct the AD command to include them by using the optional ALL keyword.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 16. Columns on the AD Panel

Column name	Title (Displayed)	Width	Description
<b>JNAME</b>	JOBNAME	7	Job name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>ASIDX</b>	ASIDX	5	Address space identifier in hexadecimal
<b>STEPN</b>	StepName	8	Step name
<b>PROCS</b>	ProcStep	8	Procedure step name
<b>JOBID</b>	JobID	8	JES job ID, or work ID
<b>OWNERID</b>	Owner	8	User ID of job creator
<b>ASCB</b>	ASCB	8	ASCB address
<b>ASSB</b>	ASSB	8	ASSB address
<b>ASXB</b>	ASXB	8	ASXB address
<b>TCB</b>	TCB	8	TCB address (ASCBXTCB)
<b>OUCB</b>	OUCB	8	OUCB address
<b>JSAB</b>	JSAB	8	JSAB address
<b>POS</b>	Pos	3	Address space position
<b>SWAPR</b>	SR	2	Swap out reason code
<b>JTYPE</b>	Type	4	Job type (STC, TSU, JOB)
<b>ASID</b>	ASID	5	Address space identifier
<b>SUBSYS</b>	SSName	6	Subsystem name
<b>CVT</b>	CVT	8	CVT address
<b>ECVT</b>	ECVT	8	ECVT address
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Address Space Memory panel (AS)

The Address Space Memory (AS) panel shows system storage utilization for all address spaces in the sysplex. It provides a convenient means for identifying address spaces that are consuming the most

common storage area (CSA) and system queue area (SQA). It also shows memory object usage, such as the number of memory objects owned, the current size of the memory object, and the highest size used.

Actions on the AS panel provide access to the Job Memory (JM) panel and the Job Device (JD) panel for the selected address space. JM complements AS by showing subpool usage within the address space. JD shows allocations, TCP/IP connections, and coupling facility connection (CF) usage.

You can use the fast path select (S) command to filter results, as follows. Leading zeros are not required when specifying the job number.

- **jobname** *jobid*, where *jobid* is optional and is the job type (JOB, TSU, STC, J, T, S) followed by the job number.
- **jobname** *job-number*, where *job-number* is optional
- *job-number*

In REXX execs and Java programs, reference columns by name rather than by title.

Table 17. Columns on the AS Panel

Column name	Title (Displayed)	Width	Description
<b>JNAME</b>	JOBNAME	8	Job name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>ASIDX</b>	ASIDX	5	Address space identifier in hexadecimal
<b>REAL</b>	Real	5	Current utilization of real storage in frames
<b>FIXED</b>	Fixed	5	Number of fixed real storage frames
<b>CSA</b>	CSA	8	CSA storage below the 16MB line in bytes
<b>CSAPCT</b>	CSA%	6	Percentage of CSA storage below the line being used
<b>ECSA</b>	ECSA	8	CSA storage above the 16MB line in bytes
<b>ECSAPCT</b>	ECSA%	6	Percentage of CSA above the 16MB line being used
<b>SQA</b>	SQA	8	SQA storage below the 16MB line in bytes
<b>SQAPCT</b>	SQA%	6	Percentage of SQA below the line being used
<b>ESQA</b>	ESQA	8	SQA storage above the 16MB line in bytes
<b>ESQAPCT</b>	ESQA%	6	Percentage of SQA above the line being used
<b>AUX</b>	Aux	6	Non-VIO slots being used
<b>MEMLIMIT</b>	MemLimit	8	Memory limit for 64-bit storage objects
<b>MOBJNUM</b>	MemObjNum	9	Number of memory objects for address space
<b>MOBJ</b>	MemObjUsed	10	Total allocated memory object size in MB
<b>MOBJHWM</b>	MemObjHWM	9	High-water mark allocated to memory objects in MB
<b>HVCOMNUM</b>	HVComNum	8	Number of high virtual common memory objects
<b>HVCOM</b>	HVComUsed	9	High virtual common memory size in MB
<b>HVCOMHWM</b>	HVComHWM	8	High virtual common memory high-water mark in MB
<b>SHRMONUM</b>	ShrMONum	8	Number of shared memory objects for address space
<b>SHRMO</b>	ShrMOUsed	9	Total size of shared memory objects in MB
<b>SHRMOHWM</b>	ShrMOHWM	8	Shared memory objects high-water mark in MB
<b>FIXEDB</b>	FixedB	6	Number of fixed frames below 16MB line

Table 17. Columns on the AS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>STEPN</b>	StepName	8	Step name
<b>PROCS</b>	ProcStep	8	Procedure step name
<b>JOBID</b>	JobID	8	JES job ID, or work ID
<b>OWNERID</b>	Owner	8	User ID of job creator
<b>POS</b>	Pos	3	Address space position. For example: swapped in, swapped out, non-swappable, in transition
<b>SWAPR</b>	SR	2	Swap-out reason code
<b>JTYPE</b>	Type	4	Job type (STC, TSU, JOB)
<b>ASID</b>	ASID	5	Address space identifier
<b>SUBSYS</b>	SSName	6	Subsystem name
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system
<b>SCSAPCT</b>	SCSA%	5	System CSA usage percentage
<b>SECSAPCT</b>	SECSA%	6	System ECSA usage percentage
<b>SSQAPCT</b>	SSQA%	5	System SQA usage percentage
<b>SESQAPCT</b>	SESQA%	6	System ESQA usage percentage
<b>AUXPCT</b>	Aux%	4	Auxiliary storage utilization
<b>REALAFC</b>	RealAFC	8	Current real storage available frame count
<b>PRIV</b>	Priv	4	Private storage below 16MB line (bytes)
<b>PRIVUSE</b>	PrivUsed	8	Private storage below 16MB line used (bytes)
<b>PRIVPCT</b>	Priv%	6	Percentage of private storage below 16MB line used
<b>EPRIV</b>	EPriv	5	Private storage above 16MB line (bytes)
<b>EPRIVUSE</b>	EPrivUsed	9	Private storage above 16MB line used (bytes)
<b>EPRIVPCT</b>	EPriv%	6	Percentage of private storage above 16MB line used
<b>AUXSCM</b>	AuxSCM	6	SCM block count
<b>MOBJREAL</b>	MemObjReal	10	Real frames backing memory objects
<b>MOBJAUX</b>	MemObjAux	9	Auxiliary storage slots backing memory objects
<b>STDATE</b>	StartDate	19	Start date
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Authorized Program Facility panel (APF)

The APF panel shows the data sets defined to the authorized program facility (APF) for each system in the sysplex.

In REXX execs and Java programs, reference columns by name rather than by title.

z/OS ISPF Services Guide

Table 18. Columns on the APF Panel

Column name	Title (Displayed)	Width	Description
<b>DSNAME</b>	DSNAME	13-44 (Varies based on longest name.)	Data set name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SEQ</b>	Seq	3	Sequence number
<b>VOLSER</b>	VolSer	6	Volume serial
<b>STATUS</b>	Status	8	Data set status. The possible values are as follows: <ul style="list-style-type: none"><li>• OK - The data set was found on the volume specified.</li><li>• OK WARN - The data set was found on the volume indicated by the catalog because the APF entry specified "**SMS*". However, SDSF has determined that the volume is not SMS managed.</li><li>• ERROR - Internal error locating the UCB control block for the DASD volume serial that should contain the dataset.</li><li>• MISSING - The data set was not found on the volume specified</li><li>• MIGRATED - The data set has been migrated by DFHSM or similar product.</li></ul>
<b>BLKSIZE</b>	BlkSize	7	Data set block size
<b>EXTENT</b>	Extent	6	Number of extents
<b>SMS</b>	SMS	3	SMS indicator. YES if the data set is SMS managed. Otherwise, NO
<b>LRECL</b>	LRecL	5	Logical record length
<b>DSORG</b>	DSOrg	5	Data set organization
<b>RECFM</b>	RecFm	5	Record format
<b>DEFVOL</b>	DefVol	6	Defined volume
<b>CRDATE</b>	CrDate	8	Data set creation date
<b>REFDATE</b>	RefDate	8	Data set last referenced date
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Operating system level

## CF Connections panel (CFC)

The CF Connections (CFC) panel allows authorized users to display all coupling facility connections defined to the sysplex.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 19. Columns on the CFC Panel

Column name	Title (Displayed)	Width	Description
<b>CONNNAME</b>	CONNNAME	16	Connection name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>CONSTATE</b>	ConState	18	Connection state (active, failed-persistent, disconnecting, failing)
<b>STRNAME</b>	StrName	16	Structure name
<b>STRTYPE</b>	StrType	8	Structure type
<b>STATUS</b>	Status	16	Structure status
<b>JNAME</b>	JobName	8	Job name
<b>ASID</b>	ASID	5	Address space identifier
<b>ASIDX</b>	ASIDX	5	Address space identifier (hexadecimal)
<b>CONDISP</b>	ConDisp	6	Connection disposition (keep or delete)
<b>CONID</b>	ID	2	Structure connection ID
<b>VERSION</b>	Version	8	Structure connection version
<b>CFLEVEL</b>	CFLevel	8	Coupling facility code level
<b>CONNDATA</b>	ConData	16	Connection data
<b>DISCDATA</b>	DiscData	16	Disconnect data
<b>POLICY</b>	Policy	8	Policy name
<b>CFNAME</b>	CFName	8	Coupling facility name
<b>CFNUM</b>	NumCF	5	Number of coupling facilities
<b>CTOKEN</b>	ConTokenX	32	Connection token (hexadecimal)
<b>LEVEL</b>	ConLevel	16	Connection level
<b>STOKEN</b>	SToken	16	Address space SToken for connection requestor
<b>CONFLAGS</b>	ConFlags	8	Connection flags
<b>SYSNUM</b>	SysNum	6	Connection system number
<b>SYSSEQ</b>	SysSeq	6	Connection system sequence number
<b>SYSNAME</b>	SysName	8	System name
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## CF Data Sets panel (CFD)

The CF Data Sets (CFD) panel allows authorized users to display coupling facility data sets defined to the sysplex.

In REXX execs and Java programs, reference columns by name rather than by title.



Table 20. Columns on the CFD Panel

Column name	Title (Displayed)	Width	Description
<b>DSNAME</b>	DSNAME	6	Couple data set name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>FUNCTION</b>	Function	8	Function name
<b>TYPE</b>	Type	16	Connection data set status
<b>ALLOCTIME</b>	AllocTime	19	Timestamp when data set allocated
<b>MAXSYS</b>	MaxSys	10	Maximum number of systems supported
<b>MAXGRP</b>	MaxGrp	10	Maximum number of groups supported
<b>MAXMEM</b>	MaxMem	10	Maximum members per group
<b>PEAKGRP</b>	PeakGrp	10	Maximum number of groups ever used
<b>PEAKMEM</b>	PeakMem	10	Maximum number of members ever used
<b>VOLSER</b>	VolSer	6	Volume serial
<b>DEVICENUM</b>	Unit	4	Device number
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## CF Structure panel (CFS)

The CF Structure (CFS) panel allows authorized users to display all coupling facility structures defined to the sysplex.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 21. Columns on the CFS Panel

Column name	Title (Displayed)	Width	Description
<b>STRNAME</b>	STRNAME	16	Structure name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STRTYPE</b>	Type	8	Structure type
<b>STATUS</b>	Status	16	Structure status
<b>DISP</b>	Disp	8	Structure disposition
<b>SIZE</b>	Size	8	Size
<b>SIZE%</b>	Size%	6	Size percentage
<b>USERNUM</b>	Conn	5	Number of connections for the structure
<b>LISTNUM</b>	Lists	5	List count for the structure
<b>ENTPCT</b>	Entry%	6	Entry percentage
<b>ELEMPCT</b>	Elem%	6	Element percentage
<b>ENTUSED</b>	EntryInUse	10	Number of entries in use

Table 21. Columns on the CFS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ENTTOT</b>	EntryTotal	10	Total entries
<b>ENTCHG</b>	EntryChange	11	Entries changed
<b>ENTCPCT</b>	EntryChange%	12	Entries changed percentage
<b>ELEMUSED</b>	ElemInUse	9	Elements in use
<b>ELEMENTOT</b>	ElemTotal	9	Total elements
<b>ELEMCHG</b>	ElemChange	10	Elements changed
<b>ELEMCPCT</b>	ElemChange%	11	Elements changed percentage
<b>LOCKNUM</b>	Locks	8	Number of locks
<b>VERSION</b>	Alloc-Date-Time	19	Date and time of allocation
<b>DUPLEX</b>	Duplex	16	Duplex option (allowed, disabled, or enabled)
<b>ALLOWAA</b>	AutoAlt	7	Allow auto alt (yes or no)
<b>ALLOWRA</b>	Realloc	7	Allow realloc (yes or no)
<b>FULLTHRESH</b>	Full%	8	Full threshold percentage
<b>REBLDPCT</b>	Rebuild%	8	Rebuild percentage
<b>POLSIZE</b>	PolSize	8	Policy size (kilobytes)
<b>INITSIZE</b>	InitSize	8	Initial size (kilobytes)
<b>MINSIZE</b>	MinSize	8	Minimum size (kilobytes)
<b>MAXSIZE</b>	MaxSize	8	Maximum size (kilobytes)
<b>POLNAME</b>	Policy	8	Policy name
<b>CFNAME</b>	CFName	8	Coupling facility name
<b>ENCRYPT</b>	Encrypt	7	Structure encryption (yes or no)
<b>ENCRTYPE</b>	EncrType	8	Encryption key method
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Columns Help panel (COLH)

The COLSHELP command displays a table of the columns that can be displayed on SDSF tabular panels. You can use the COLSHELP command to find column names for use in writing REXX execs and Java programs, which reference columns by name rather than by title.

Table 22. Columns on the COLH Panel

Column name	Title (Displayed)	Width	Description
<b>COLUMN</b>	COLUMN	6	Column name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>PANEL</b>	Panel	5	Panel name

Table 22. Columns on the COLH Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>TITLE</b>	Title	18	Column title
<b>DESC</b>	Description	100	Column description
<b>DELAYED</b>	Delayed	7	Delayed status
<b>OVERTYPE</b>	Overtime	8	Overtime applicability
<b>WIDTH</b>	Width	5	Width of the column
<b>PAS</b>	PAS	4	Point and shoot (yes, no, or cond)
<b>SIGZERO</b>	SigZero	8	Zero significant (yes or no)
<b>JESTYPE</b>	JES	3	Column applicable to J2, J3, or all
<b>NEW</b>	New	8	Column new in current release (yes or no)
<b>SINCE</b>	Since	8	Column available since release
<b>CLASS</b>	Class	8	SAF class
<b>RESOURCE</b>	Resource	64	SAF resource
<b>FIXEDFLD</b>	FixedField	10	Fixed field (yes or no)
<b>SUBFIELDS</b>	SubFields	10	Number of subfields

## Command Help panel (CMDH)

The Command Help panel lists all SDSF primary commands and the SAF resource profiles that are used to protect the command.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 23. Columns on the CMDH Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	4	Command name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>DESC</b>	Description	24	Command description
<b>JES</b>	JES	3	JES dependent (yes or no)
<b>RMF</b>	RMF	3	RMF dependent (yes or no)
<b>XSYSTEM</b>	Sysplex	7	Command can be issued cross-system (yes or no)
<b>JESPLEX</b>	JESplex	7	Command supports JESplex scope (yes or no)
<b>AUX</b>	Aux	3	SDSFAUX dependent (yes or no)
<b>RELEASE</b>	Release	10	Release added
<b>CLASS</b>	Class	8	SAF class
<b>RESOURCE</b>	Resource	64	SAF resource

Table 23. Columns on the CMDH Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Common Storage Subpools panel (CS)

The Common Storage Subpools (CS) panel allows authorized users to view common storage summary usage by subpool and key.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 24. Columns on the CS Panel

Column name	Title (Displayed)	Width	Description
<b>SUBPOOL</b>	SP	2	Subpool number. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>KEY</b>	Key	3	Subpool key
<b>BBLKS</b>	BelowBlks	13	Blocks below 16MB
<b>BALLOC</b>	BelowAlloc	13	Allocated bytes below 16MB
<b>BUSED</b>	BelowUsed	13	Used bytes below 16MB
<b>BFREE</b>	BelowFree	13	Free bytes below 16MB
<b>BORPHAN</b>	BelowOrphan	13	Orphaned below 16MB
<b>ABLKS</b>	AboveBlks	13	Blocks above 16MB
<b>AALLOC</b>	AboveAlloc	13	Allocated bytes above 16MB
<b>AUSED</b>	AboveUsed	13	Used bytes above 16MB
<b>AFREE</b>	AboveFree	13	Free bytes above 16MB
<b>AORPHAN</b>	AboveOrphan	13	Orphaned above 16MB
<b>TYPE</b>	Type	4	Type SQA/CSA
<b>FPROT</b>	FProt	5	Fetch protected (yes or no)
<b>FIXED</b>	Fix	4	Fixed (yes, no, or DREF)
<b>SELECTKEY</b>	SelectKey	9	Select key
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	System level
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Common Storage Subpool Details panel (CSI)

The Common Storage Subpool Details (CSI) panel allows authorized users to view common storage details for a selected subpool and key.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 25. Columns on the CSI Panel

Column name	Title (Displayed)	Width	Description
<b>ADDRESS</b>	ADDRESS	8	Storage start address. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>ADDRESSEND</b>	AddrEnd	8	Storage end address
<b>LENGTH</b>	Length	8	Storage size
<b>STATUS</b>	Status	6	Status of storage (ALLOC or FREE)
<b>SUBPOOL</b>	SP	3	Subpool of storage
<b>KEY</b>	Key	3	Storage key
<b>BLOCKADDR</b>	BlockAddr	9	Block address start
<b>BLKSIZE</b>	BlockSize	9	Block size
<b>JNAME</b>	JobName	8	Job name that obtained it
<b>GQE</b>	GQE	8	GQE address
<b>TYPE</b>	Type	4	Storage type (SQA or CSA)
<b>ORPHAN</b>	Orphan	6	Orphaned storage
<b>JOBID</b>	JobID	8	Job ID
<b>ASID</b>	ASID	5	Address space ID (decimal)
<b>ASIDX</b>	ASIDX	5	Address space ID (hexadecimal)
<b>ADATE</b>	Date	19	Storage obtain timestamp
<b>EDATE</b>	EndDate	19	Storage orphaned timestamp
<b>CAUB</b>	CAUB	8	CAUB address
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	System level
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Common Storage Remaining panel (CSR)

The Common Storage Remaining (CSR) panel allows authorized users to list all addresses with common storage that were not released at the end of a job.

When JESplex scoping is in effect, the CSR panel will return data only for those systems that are in the same JESplex as the user.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 26. Columns on the CSR Panel

Column name	Title (Displayed)	Width	Description
<b>JNAME</b>	JOBNAME	8	Job name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>JOBID</b>	JobID	8	Job identifier
<b>ASID</b>	ASID	5	Address space identifier
<b>ASIDX</b>	ASIDX	5	Address space identifier (hexadecimal)
<b>CSA</b>	CSA	5	CSA not released (bytes)
<b>CSAPCT</b>	CSA%	7	CSA percentage not released
<b>SQA</b>	SQA	5	SQA not released (bytes)
<b>SQAPCT</b>	SQA%	7	SQA percentage not released
<b>ECSA</b>	ECSA	5	ECSA not released (bytes)
<b>ECSAPCT</b>	ECSA%	7	ECSA percentage not released
<b>ESQA</b>	ESQA	5	ESQA not released (bytes)
<b>ESQAPCT</b>	ESQA%	7	ESQA percentage not released
<b>DATE</b>	Date	19	Timestamp storage not released
<b>SCSAPCT</b>	SCSA%	5	Current system CSA utilization
<b>SECSAPCT</b>	SECSA%	7	Current system ECSA utilization
<b>SSQAPCT</b>	SSQA%	5	Current system SQA utilization
<b>SESQAPCT</b>	SESQA%	6	Current system ESQA utilization
<b>AUXPCT</b>	Aux%	4	Current auxiliary storage utilization
<b>REALAFC</b>	RealAFC	8	Current real storage available frame count
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of operating system
<b>HVCOM</b>	HVComUsed	9	64-bit common not released (bytes)
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Device Activity panel (DEV)

The Device Activity (DEV) panel allows authorized users to show online DASD volume activity in the system.

When JESplex scoping is in effect, the DEV panel returns data only for those systems that are in the same JESplex as the user.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 27. Columns on the DEV Panel

Column name	Title (Displayed)	Width	Description
<b>VOLSER</b>	VOLSER	6	Volume serial. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>UNIT</b>	Unit	4	Unit address
<b>STORGRP</b>	StorGrp	8	Storage group
<b>IOINTENS</b>	IOIntens	8	I/O intensity (the higher the greater the impact)
<b>QINTENS</b>	QIntens	7	Queuing intensity (the higher the greater the impact)
<b>SSCHRATE</b>	SSCH	8	SSCH rate (SSCH per second)
<b>RESPONSE</b>	Response	8	Average response time (milliseconds)
<b>IOSQ</b>	IOSQ	8	Average IOSQ (milliseconds)
<b>CONNECT</b>	Connect	8	Average connect time (milliseconds)
<b>DISCONN</b>	Disc	8	Average disconnect time (milliseconds)
<b>PENDING</b>	Pending	8	Average pending time (milliseconds)
<b>UTILPCT</b>	Util%	6	Device utilization percentage
<b>RESVPCT</b>	Resv%	6	Device reserve percentage
<b>PAVNUM</b>	PAVNum	6	Number of parallel access volume (PAV) exposures
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of operating system
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Display Active Users panel (DA)

The DA panel shows information about MVS address spaces (jobs, started tasks, and TSO users) that are running.

As of SDSF 2.5, the DA panel uses data gatherers running in the SDSFAUX address space and caches the information centrally.

The data gatherer supports both the RMF and non-RMF case. RMF is used when RMF is installed and is not explicitly disabled by the installation. When RMF is not available, a non-RMF data gatherer is used. Note that the non-RMF data gatherer provides only a small subset of the columns available as opposed to the RMF case. Columns for which RMF is required are indicated by <sup>RMF</sup>.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 28. Columns on the DA Panel

Column Name	Title (Displayed)	Width	Description	Delay
<b>JNAME</b>	JOBNAME	8	Job name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.	

Table 28. Columns on the DA Panel (continued)

Column Name	Title (Displayed)	Width	Description	Delay
<b>STEPN</b>	StepName	8	Job step name (TSO logon procedure name for TSO users)	
<b>PROCS</b>	ProcStep	8	Procedure step name (terminal ID for TSO users)	
<b>JTYPE</b>	Type <sup>1</sup>	4	Type of address space	
<b>JNUM</b>	JNum <sup>1</sup>	6	JES job number	
<b>JOBID</b>	JobID	8	JES job ID	
<b>OWNERID</b>	Owner	8	User ID of job owner, or default values of ++ ++++++ or ????????, if user ID not defined to RACF®	
<b>JCLASS</b>	C	1 or 8	JES input class at the time the job was selected for execution. Default width expands to 8 if there are long class names in the MAS.	
<b>POS</b>	Pos	3	Address space position	
<b>DP</b>	DP	2	Address space dispatching priority in hexadecimal	
<b>REAL</b>	Real	4	Current real storage usage in frames	
<b>PAGING</b>	Paging	6	Demand paging rate for address space	
<b>EXCPRT</b>	SIO	6	EXCP rate in EXCPs per second for address space. The value is approximate and is derived from this calculation: the job delta EXCP count (from RMF or the ASCB) divided by the total time interval.	
<b>CPUPR</b>	CPU% <sup>2</sup>	6	Percent of CPU time consumed by and on behalf of the address space during the most recent interval measured	
<b>ASID</b>	ASID	4	Address space identifier	
<b>ASIDX</b>	ASIDX	5	Address space identifier in hexadecimal	
<b>EXCP</b>	EXCP-Cnt	9	Accumulated EXCP count for the current job step for the address space. Uses hexadecimal scaling.	
<b>CPU</b>	CPU-Time	10	Accumulated CPU time consumed by and on behalf of the address space, for the current job step, in seconds	
<b>SWAPR</b>	SR	2	Swap out reason code	
<b>STATUS</b>	Status	6	JES job status	
<b>SYSNAME</b> <sup>RMF</sup>	SysName	8	System name where job is executing	
<b>SPAGING</b> <sup>RMF</sup>	SPag	4	System demand paging rate for system that the job is executing on. The value is the same for all rows for a system.	



Table 28. Columns on the DA Panel (continued)

Column Name	Title (Displayed)	Width	Description	Delay
<b>SCPU</b> <sup>RMF</sup>	SCPU%	5	System CPU percentage for system that is processing the job. The value is the same for all rows for a system.	
<b>WORKLOAD</b> <sup>RMF</sup>	Workload	8	Workload name	
<b>SRVCLASS</b> <sup>RMF</sup>	SrvClass	8	Service class name	
<b>PERIOD</b> <sup>RMF</sup>	SP	2	Service class period	
<b>RESGROUP</b> <sup>RMF</sup>	ResGroup	8	Resource group name	
<b>SERVER</b> <sup>RMF</sup>	Server	8	Server indicator (resource goals are not being honored)	
<b>QUIESCE</b> <sup>RMF</sup>	Quiesce	7	Quiesce indicator (address space is quiesced)	
<b>ECPU</b> <sup>RMF</sup>	ECPU-Time	10	Total CPU time consumed by and within the address space, for the current job step, in seconds	
<b>ECPUPR</b> <sup>RMF</sup>	ECPUP%	6	CPU usage by and within the address space	
<b>CPUCRIT</b> <sup>RMF</sup>	CPUCrit	7	Current address space CPU-protection	
<b>STORCRIT</b> <sup>RMF</sup>	StorCrit	8	Current address space storage protection	
<b>RPTCLASS</b> <sup>RMF</sup>	RptClass	8	Report class	
<b>MEMLIMIT</b> <sup>RMF</sup>	MemLimit	8	Memory limit	
<b>TRANACT</b> <sup>RMF</sup>	Tran-Act	10	Elapsed time the transaction has been active	
<b>TRANRES</b> <sup>RMF</sup>	Tran-Res	10	Elapsed time the transaction was swapped in	
<b>SPIN</b> <sup>RMF</sup>	Spin	4	Indicator of whether job can be spun	
<b>SECLABEL</b>	SecLabel	8	Security label of the address space	
<b>GCPTIME</b> <sup>RMF</sup>	GCP-Time	8	Accumulated general processor service time, in seconds	
<b>ZAAPTIME</b> <sup>RMF</sup>	zAAP-Time	9	Accumulated IBM zEnterprise Application Assist Processor (zAAP) service time, in seconds	
<b>ZAAPCPTM</b> <sup>RMF</sup>	zACP-Time	9	CPU time consumed on general processors by work that was eligible for a zAAP, in seconds	
<b>GCPUSE</b> <sup>RMF</sup>	GCP-Use%	8	Percent of the total general processor time used by the address space in the most recent interval	
<b>ZAAPUSE</b> <sup>RMF</sup>	zAAP-Use%	9	Percent of the total zAAP time used by the address space in the most recent interval	
<b>SZAAP</b> <sup>RMF</sup>	SzAAP%	6	zAAP view of CPU use for the system, in the most recent interval. The value is the same for all rows for a system.	

Table 28. Columns on the DA Panel (continued)

Column Name	Title (Displayed)	Width	Description	Delay
<b>SZIIP<sup>RMF</sup></b>	SzIIP%	6	IBM z Integrated Information Processor (zIIP) utilization for the system that is processing the job. This is a system value and so is the same for all rows for a system.	
<b>PROMOTED<sup>RMF</sup></b>	Promoted	8	Indicates whether the address space is currently promoted due to a chronic resource contention	
<b>ZAAPNTIM<sup>RMF</sup></b>	zAAP-NTime	10	Normalized zAAP service time, in seconds	
<b>ZIIPTIME<sup>RMF</sup></b>	zIIP-Time	9	CPU time consumed on zIIPs, in seconds	
<b>ZIIPCPTM<sup>RMF</sup></b>	zICP-Time	9	CPU time consumed on general processors by work that was eligible for a zIIP, in seconds	
<b>ZIIPNTIM<sup>RMF</sup></b>	zIIP-NTime	10	Normalized zIIP service time, in seconds	
<b>ZIIPUSE<sup>RMF</sup></b>	zIIP-Use%	9	Percent of the total zIIP time used by the address space in the most recent interval	
<b>SLCPU<sup>RMF</sup></b>	SLCPU%	6	Percentage of time the LPAR is busy for the system, in the most recent interval. The value for SLCPU% is the same for all rows for a system.	
<b>IOPRIOGRP<sup>RMF</sup></b>	IOPrioGrp	9	WLM I/O priority group	
<b>JOB CORR</b>	JobCorrelator	32	User portion of the job correlator (JES2 only)	
<b>TRESGROUP</b>	TenantResGroup	14	Tenant resource group indicator (YES or NO, RMF)	
<b>ESRBTIME<sup>HSF</sup></b>	ESRB-Time	9	Enclave CPU time	
<b>CPULIMIT<sup>HSF</sup></b>	CPU-Limit	9	CPU time limit	
<b>REUS<sup>HSF</sup></b>	Reus	4	Reusable address space (yes or no)	
<b>SYSLEVEL<sup>HSF</sup></b>	SysLevel	25	Level of the operating system	
<b>XCFGROUP</b>	XCFGGroup	8	JES MAS XCF group name	
<b>SSNAME</b>	SSName	6	Creating subsystem name	
<b>PAG AUX<sup>RMF</sup></b>	PageAux	7	Paging rate (auxiliary storage only)	
<b>STDATE</b>	StartDate	19	Start date	
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.	

Notes on the table:

1. Not included in the default field list.
2. SDSF calculates the value for the CPU% column. It is the ratio between the CPU time used by one job and the CPU time used by all jobs, in the interval between times that the user presses Enter.

3. Columns with information for zAAPs and zIIPs are shown only if at least one of the appropriate specialized processors (zAAP or zIIP) has been configured for a system that is within the scope of the systems being shown on the panel. Note that changing the systems being shown (with the SYSNAME or FILTER commands) once the DA panel is displayed does not affect whether SDSF includes or omits the column.
4. <sup>HSF</sup> indicates the column requires the data gatherer running in SDSFAUX.

## Dynamic Exits panel (DYNX)

The Dynamic Exits (DYNX) panel shows all of the dynamic exits in the sysplex, their status, and the modules that implement the exit.

You can use the fast path select (S) command with an EXITNAME to filter results.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 29. Columns on the DYNX Panel

Column name	Title (Displayed)	Width	Description
<b>EXITNAME</b>	EXITNAME	16	Dynamic exit name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SEQ</b>	Seq	3	Sequence number for module in list
<b>MODNAME</b>	ModName	8	Module name implementing exit
<b>ACTIVE</b>	Active	6	Exit active (YES or NO)
<b>FASTPATH</b>	FastPath	8	Exit FASTPATH option (YES or NO). FASTPATH processing means that the system does not provide as much function, and therefore the overall processing time is less.
<b>MODEPA</b>	ModEPA	8	Module entry point address
<b>MODLOADPT</b>	LoadPt	8	Module load point address if available
<b>MODSIZE</b>	ModLen	8	Module length if available
<b>JNAME</b>	FiltJob	8	Jobname for which exit is to get control
<b>STOKEN</b>	FiltSTok	16	Address space token (STOKEN) for which exit is to get control
<b>ABENDNUM</b>	NumAbend	8	Number of abends before exit inactivates
<b>ABENDCON</b>	ConAbend	8	Consecutive abend option (YES – consecutive abends before inactivation, NO – cumulative abends before inactivation)
<b>SEQMAX</b>	SeqMax	6	Maximum module sequence number
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system
<b>TYPE</b>	Type	12	Exit type
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Enclaves panel (ENC)

The Enclaves panel shows enclaves.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 30. Columns on the ENC Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	16	Token that identifies the enclave. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SSTYPE</b>	SSType	6	Subsystem type (for example, DB2).
<b>STATUS</b>	Status	8	Active or inactive
<b>ESRVCLS</b>	SrvClass	8	Service class
<b>PERIOD</b>	Per	3	Period number
<b>PGN</b>	PGN	3	Performance group
<b>RPTCLS</b>	RptClass	8	Report class
<b>RESGROUP</b>	ResGroup	8	Resource group
<b>CPU</b>	CPU-Time	10	Total CPU time
<b>OWNSYS</b>	OwnerSys	8	Enclave owner system
<b>JNAME</b>	OwnerJob	8	Enclave owner jobname
<b>ASID</b>	OwnerAS	7	Enclave owner ASID (displayed only if this enclave is the original)
<b>ASIDX</b>	OwnerASX	8	Enclave owner ASID in hexadecimal (displayed only if this enclave is the original)
<b>ORIGINAL</b>	Original	8	Indicates, for an enclave that has been exported, if this is the original. Value is YES or NO.
<b>ESCOPE</b>	Scope	8	Scope of the enclave; LOCAL (single-system) or MULTISYS (multisystem capable; there is an export token for the enclave)
<b>TYPE</b>	Type	4	IND (Independent) or DEP (dependent)
<b>WORKLOAD</b>	Workload	8	Workload name
<b>QUIESCE</b>	Quiesce	12	Indicates if the enclave is in a quiesce delay, which occurs if the address space has been reset with the MVS RESET,QUIESCE command. Value is YES, YES-IMPLICIT (quiesced through enclave server quiesce) or NO.
<b>SYSNAME</b>	SysName	8	Name of the system that provided the data
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system
<b>SUBSYS</b>	Subsys	8	Subsystem name
<b>ZAAPTIME</b>	zAAP-Time	9	Cumulative zAAP time consumed by dispatchable units running in the enclave on the local system. See note below.

Table 30. Columns on the ENC Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ZAAPCTM</b>	zACP-Time	9	Cumulative zAAP on CP time consumed by dispatchable units running in the enclave on the local system. See note below.
<b>ZIIPTIME</b>	zIIP-Time	9	Cumulative zIIP time consumed by dispatchable units running in the enclave on the local system. See note below.
<b>ZIIPCPTM</b>	zICP-Time	9	Cumulative zIIP on CP time consumed by dispatchable units running in the enclave on the local system. See note below.
<b>PROMOTED</b>	Promoted	8	Indicates whether the address space is currently promoted due to a chronic resource contention
<b>ZAAPNTIM</b> <sup>RMF</sup>	zAAP-NTime	10	zAAP service time, in seconds, normalized for the slower CP
<b>ZIIPNTIM</b> <sup>RMF</sup>	zIIP-NTime	10	zIIP service time, in seconds, normalized for the slower CP
<b>ARRTIME</b>	Arrival-Time	19	Date and time the enclave was created
<b>ARRINTV</b>	Arrival-Int	11	Interval since the enclave was created ( <i>hh:mm:ss</i> )
<b>CPUCRIT</b>	CPUCrit	7	CPU protection
<b>IOPRIOGRP</b>	IOPrioGrp	9	WLM I/O priority group
<b>USERID</b>	UserID	8	User ID associated with the request
<b>TRESGROUP</b>	TenantResGroup	14	Tenant resource group indicator (YES or NO, RMF).
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

**Note:** This column shows time consumed by dispatchable units running in the enclave on the local system. For a multisystem enclave, time consumed on other systems is not included. The value may decrease between invocations if the transaction is restarted to avoid an overflow of internal accumulators.

## Enqueue panel (ENQ)

Enqueuing is the mechanism by which a program requests control of a serially reusable resource. The Enqueue (ENQ) panel allows authorized users to display active system enqueues. The panel shows the major and minor names for the enqueuer, as well as the job name waiting for or holding the enqueue. Parameters on the ENQ command control which major and system names are shown.

By default, accessing the ENQ panel shows all enqueues with major name SYSDSN for the local system. As of V2R4, the **ENQD** command shows locally-held enqueues even when the job is running on a remote system.

You can also access the ENQ panel from the DA and AS panels using the N action character. When ENQ is accessed in this way, all enqueues used by the selected address space are shown.

**Note:** Major and minor names can contain hexadecimal characters that cannot be displayed by SDSF. SDSF translates control characters (0x00 through 0x3F) to periods. Other characters are not translated

and their display varies based on factors such as the emulator. You can use the D action character to display major and minor names in hexadecimal, but the length is limited by the message text in the response.

The **ENQC** command provides a convenient means of showing all enqueues with contention. That is, **ENQC** shows currently held enqueues that are required by another job. **ENQC** does not accept any parameters.

The **ENQD** command provides a convenient means of showing all enqueues with major name SYSDSN and any minor name for all systems. You can specify an optional pattern on the **ENQD** command for the data set name (minor name for SYSDSN) to be processed. The default is **userid**, where **userid** is the user ID of the current user.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 31. Columns on the ENQ Panel

Column name	Title (Displayed)	Width	Description
<b>MINOR</b>	MINOR	52	Minor name (RNAME). This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro. Control characters are translated to periods.
<b>MAJOR</b>	Major	8	Major name (QNAME). Control characters are translated to periods.
<b>REQTYPE</b>	Req	3	Request type (SHR or EXC)
<b>JOBNAME</b>	JobName	8	Job name holding or requesting enqueue
<b>ASID</b>	ASID	4	Job name ASID (decimal)
<b>ASIDX</b>	ASIDX	6	Job name ASID (hexadecimal)
<b>LEVEL</b>	Level	10	Request level: ENQ-normal enqueue, Reserve-hardware reserve, Global enq-hardware reserve converted to global enqueue
<b>SMC</b>	SMC	3	Step must complete indicator
<b>SCOPE</b>	Scope	8	Enqueue scope (step, system, systems, global)
<b>STATUS</b>	Status	6	Resource status (own, wait)
<b>OWNERS</b>	Owners	6	Number of resource owners for enqueue
<b>WAITERS</b>	Waiters	7	Number of tasks waiting for enqueue
<b>WAITEXC</b>	WaitExc	7	Number of tasks waiting for exclusive use
<b>WAITSHR</b>	WaitShr	7	Number of tasks waiting for shared use
<b>UNIT</b>	Unit	4	Device address for reserves
<b>USERDATA</b>	UserData	32	User data passed on ISGENQ
<b>REQTIME</b>	ReqTime	19	Date and time of request
<b>ENQTOKEN</b>	EnqToken	64	Enqueue token
<b>RNAMEL</b>	RNameLong	127	Longer version of minor name, up to 127 characters. Control characters are translated to periods.
<b>SYSNAME</b>	SysName	8	System name

Table 31. Columns on the ENQ Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Extended Console panel (EMCS)

The Extended Console (EMCS) panel shows all extended consoles defined in the sysplex. Rows for consoles with a status of ACTIVE are highlighted. This panel does not use the SYSNAME value to control which systems are shown on the panel.

You can use fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the console name pattern.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 32. Columns on the EMCS Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	8	Console name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	8	Console status
<b>KEY</b>	Key	8	Console key
<b>JNAME</b>	JobName	8	Job name of address space creating console
<b>JOBID</b>	JobID	8	Job ID of address space creating console
<b>QDEPTH</b>	QDepth	6	Data space queue depth
<b>QLIMIT</b>	QLimit	6	Data space queue limit
<b>QALERTPCT</b>	QAlert%	7	Dataspace queue alert percentage
<b>DSPSIZE</b>	DSPSizeK	8	Current data space size (kilobytes)
<b>DSPMAX</b>	DSPMaxK	8	Maximum data space size (kilobytes)
<b>ASID</b>	ASID	5	Address space identifier
<b>ASIDX</b>	ASIDX	5	Address space identifier (hexadecimal)
<b>TERMID</b>	TermID	8	Terminal identifier
<b>AUTH</b>	Auth	16	Console authority
<b>LEVEL</b>	Level	12	Message levels received by console
<b>CONSID</b>	ConsID	8	Console identifier
<b>CMDSYS</b>	CmdSys	8	Command system
<b>AUTOACT</b>	AutoAct	8	AutoAct group for system console
<b>MONITOR</b>	Monitor	20	Monitor status for console
<b>DOM</b>	DOM	6	Delete operator message attribute
<b>HC</b>	HC	3	Hardcopy message set receiver (yes or no)

Table 32. Columns on the EMCS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>AUTO</b>	Auto	4	Message automation receiver (yes or no)
<b>INTIDS</b>	IntIDs	6	Console ID zero receiver (yes or no)
<b>UNKNIDS</b>	UnknIDs	7	Unknown console ID receiver (yes or no)
<b>PD</b>	PD	3	Problem determination mode (yes or no)
<b>SYSCONS</b>	SysCons	7	System console (yes or no)
<b>MSCOPE</b>	MScope	8	Systems from which unsolicited messages are being received
<b>ROUTCDE</b>	RoutCde	32	Routing codes
<b>ROUTCDEX</b>	RoutCdeX	32	Routing codes (hexadecimal)
<b>SYSNAME</b>	SysName	8	System name where console is active
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## File Systems panel (FS)

The File System (FS) panel allows authorized users to list the file systems being used by the system.

When JESplex scoping is in effect, the FS panel returns data only for those systems that are in the same JESplex as the user.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 33. Columns on the FS Panel

Column name	Title (Displayed)	Width	Description
<b>DEVICE</b>	DEVICE	6	Unique device value (character format). This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>PATH</b>	Path	36	Directory name where file system is mounted (truncated to 63 characters)
<b>TYPE</b>	Type	8	File system type
<b>MODE</b>	Mode	4	File system mode (READ or RDWR)
<b>OWNER</b>	Owner	8	System that owns this file system
<b>DSNAME</b>	Name	44	Name of file system
<b>STATUS</b>	Status	16	File system status
<b>STATUSNUM</b>	StatNum	7	Status code corresponding to status value
<b>AUTOMOVE</b>	AutoMove	8	Automove indicator
<b>CLIENT</b>	Client	6	Client indicator (yes or no)
<b>LATCHNUM</b>	Latch	5	Latch number for the file system



Table 33. Columns on the FS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>MOUNTTIME</b>	Mount-Time-Date	19	Timestamp file system was mounted
<b>MOUNTPARM</b>	MountParm	57	Parameter specified on mount truncated to 57 characters
<b>QSYSNAME</b>	QSysName	9	System that quiesced this file system
<b>QJOBNAME</b>	QJobName	9	Jobname that quiesced this file system
<b>QPID</b>	QPID	8	PID that quiesced this file system
<b>DEVICENUM</b>	DevNum	6	Unique device value (decimal)
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of operating system
<b>TSPACE</b>	Total space	10	Total space
<b>USPACE</b>	UsedSpace	9	Used space
<b>USEDPCT</b>	Used%	8	Used space percent
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Generic Tracker panel (GT)

The Generic Tracker (GT) panel allows authorized users to list all generic tracking events that have been recorded by the system.

When JESplex scoping is in effect, the GT panel returns data only for those systems that are in the same JESplex as the user.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 34. Columns on the GT Panel

Column name	Title (Displayed)	Width	Description
<b>OWNER</b>	OWNER	8	Owner of tracked instance. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SOURCE</b>	Source	8	Source of tracked instance
<b>PROGRAM</b>	Program	8	Program name
<b>PROGOFS</b>	ProgramOffset	16	Offset into program issuing track request
<b>EVENTDESC</b>	EventDesc	64	Event description
<b>EVENTDATA</b>	EventData	32	Data associated with the event
<b>EVENTJOB</b>	EJobName	9	Event job name
<b>HOMEJOB</b>	HJobName	9	Home job name
<b>EVENTASID</b>	EASIDX	6	Event address space identifier (hexadecimal)
<b>HOMEASID</b>	HASIDX	6	Home address space identifier (hexadecimal)

Table 34. Columns on the GT Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>AUTH</b>	Auth	4	Authorized indicator (yes or no)
<b>COUNT</b>	Count	5	Number of events
<b>FIRST</b>	First-Date-Time	19	Timestamp of first event
<b>SPATHLEN</b>	SPathLen	8	Actual length of source path
<b>SOURCEPATH</b>	SourcePath	127	Source path for event (may be truncated)
<b>PPATHLEN</b>	PPathLen	8	Actual length of program path
<b>PROGRAMPATH</b>	ProgramPath	127	Program path for event (may be truncated)
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of operating system
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Health Check History panel (CKH)

The CKH panel shows information about instances of a check selected from the CK panel.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 35. Columns on the CKH Panel

Column name	Title (Displayed)	Width	Description
<b>COUNT</b>	Count	17	Count of this instance of the check
<b>OWNER</b>	CheckOwner	16	Check owner
<b>STATUS</b>	Status	18	Check status
<b>RESULT</b>	Result	6	Result code from the check
<b>DIAG1</b>	Diag1	8	Diagnostic data from check, word 1
<b>DIAG2</b>	Diag2	8	Diagnostic data from check, word 2
<b>DATEE</b>	Start-Date-Time	19	Date and time the check started (YYYY.DDD HH:MM:SS)
<b>DATEN</b>	End-Date-Time	19	Date and time the check ended (YYYY.DDD HH:MM:SS)
<b>SYSPLEX</b>	Sysplex	8	Sysplex name for the sysplex on which the check ran
<b>SYSNAME</b>	SysName	8	System name for the system on which the check ran
<b>NAME</b>	Name	32	Check name

## Health Checker panel (CK)

The CK panel shows information from IBM Health Checker for z/OS about the active checks.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 36. Columns on the CK Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	32	Check name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>OWNER</b>	CheckOwner	16	Check owner
<b>STATE</b>	State	18	Check state
<b>STATUS</b>	Status	18	Check status
<b>RESULT</b>	Result	6	Result code from the last invocation of the check
<b>DIAG1</b>	Diag1	8	Diagnostic data from check, word 1
<b>DIAG2</b>	Diag2	8	Diagnostic data from check, word 2
<b>DIAGFROM</b>	DiagFrom	8	Source of the diagnostic data, words 1 and 2: ABEND, HCHECKER or CHECKRTN
<b>GLOBAL</b>	Global	6	Indicator of whether the check is global
<b>GLOBALSYS</b>	GlobalSys	9	Name of the system on which the global check is running
<b>EXCOUNT</b>	ExcCount	8	Number of exceptions detected by this check on the last iteration
<b>COUNT</b>	RunCount	8	Number of times the check has been invoked
<b>FAIL</b>	Fail	4	Number of times the check failed
<b>SEVERITY</b>	Severity	8	Severity level of the check (HIGH, MEDIUM, LOW, NONE)
<b>SEVCODE</b>	SevCode	7	Numeric severity level of the check
<b>WTOTYPE</b>	WTOType	9	WTO type issued when an exception is found (EVENTUAL, CRITICAL, INFO, HC, NONE or a descriptor code)
<b>MODIFIED</b>	ModifiedBy	26	How the check was modified
<b>POLSTAT</b>	PolicyStatus	18	Policy error status
<b>WTONUM</b>	WTONum	6	Number of WTOS issued by the check
<b>NUMCAT</b>	NumCat	6	Number of categories in which the check is defined
<b>CATEGORY</b>	Category	16	Category name. Users can view the complete set of categories by typing + alone in this column.
<b>CATEGORY2 -CATEGORY4</b>	Category2 – Category4	16	Category names 2 to 4.
<b>CATEGORY5 -CATEGORY16</b>	Category5 – Category16	16	Category names 5 to 16. By default, these appear only in the alternate field list.
<b>EXITNAME</b>	ExitName	8	Exit modname that added the check
<b>MODNAME</b>	ModName	8	Check module name
<b>MSGNAME</b>	MsgName	8	Message load module name
<b>USERDATE</b>	UserDate	8	Current date of the check
<b>DEFDATE</b>	DefDate	8	Default date of the check

Table 36. Columns on the CK Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>DEBUG</b>	Debug	5	Debug mode indicator
<b>DATEE</b>	Start-Date-Time	19	Date and time the check last started (YYYY.DDD HH:MM:SS)
<b>INTERVAL</b>	Interval	8	Time interval at which the check runs (HHH:MM)
<b>SCHDATE</b>	NextSch-Date-Time	19	Date and time the check is next scheduled to run (YYYY.DDD HH:MM:SS)
<b>SCHINT</b>	NextSch-Int	11	Time remaining to the date and time the check is next scheduled to run, in HHHHH:MM:SS
<b>LOGDATE</b>	Log-Date-Time	19	Date and time of the last successful write to System Logger
<b>DELDATE</b>	Deleted-Date-Time	19	Date and time the check was deleted
<b>PROCNAME</b>	ProcName	8	Health Checker procedure name
<b>STCID</b>	TaskID	8	Health Checker started task ID
<b>REASON</b>	Reason	126	Description of the reason for check
<b>UPDREAS</b>	UpdateReason	48	Description of updates to the check. The width can be increased to 126.
<b>PARMLEN</b>	ParmLen	7	Length of the check parameters
<b>PARM</b>	Parameters	32	Check parameters
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system
<b>SYSNAME</b>	SysName	8	System name
<b>EINTERVAL</b>	EInterval	9	Interval at which the check will run when it has raised an exception
<b>EXECNAME</b>	ExecName	8	Name of the exec to run
<b>LOCALE</b>	Locale	8	Where the check is running
<b>ORIGIN</b>	Origin	8	Origin of the check
<b>VERBOSE</b>	Verbose	7	Verbose mode for the check
<b>REXXIN</b>	RexxIn	44	REXX input data set name
<b>REXXOUT</b>	RexxOut	44	REXX output data set name
<b>LOGSTREAM</b>	LogStream	26	Name of the logstream used to record this check
<b>REXXHLQ</b>	RexxHLQ	8	High level qualifier for REXX data sets

## Held Output panel (H)

The Held Output panel shows the user information about SYSOUT data sets for jobs, started tasks, and TSO users on any *held* JES output queue.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 37. Columns on the H Panel

Column name	Title (Displayed)	Width	Description	Delay
<b>JNAME</b>	JOBNAME	8	Job name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.	
<b>JNUM</b>	JNum <sup>1</sup>	6	JES job number	
<b>JOBID</b>	JobID	8	JES job ID	
<b>OWNERID</b>	Owner	8	User ID of SYSIN/SYSOUT owner, or default values of ++++++++ or ????????, if user ID not defined to RACF	
<b>DPRIO</b>	Prty	4	JES output group priority	
<b>OCLASS</b>	C	1	JES output class	
<b>OUTDISP</b>	ODisp	5	JES output disposition	
<b>DESTN</b>	Dest	18	JES print destination name	
<b>RECCNT</b>	Tot-Rec	9	Output total record count (lines). Blank for page-mode data.	
<b>PAGECNT</b>	Tot-Page	9	Output page count (lines). Blank if not for page-mode data.	
<b>FORMS</b>	Forms	8	Output form number	
<b>FCBID</b>	FCB	4	Output FCB ID	
<b>STATUS</b>	Status	16	JES job status	
<b>UCSID</b>	UCS	4	Output UCS ID (print train required)	
<b>WTRID</b>	Wtr	8	Output external writer name	
<b>FLASHID</b>	Flash	5	Output flash ID	
<b>BURST</b>	Burst	5	3800 burst indicator	
<b>PRMODE</b>	PrMode	8	Printer process mode	
<b>DEST</b>	Rmt	5	JES print routing. Remote number if routing is not local. (JES2 only)	
<b>NODE</b>	Node	5	JES print node (JES2 only)	
<b>SECLABEL</b>	SecLabel	8	Security label of data sets	
<b>OGNAME</b>	O-Grp-N	8	Output group name (JES2 only)	
<b>OGID</b>	OGID1	5	Output group ID 1 (JES2 only)	
<b>OGID2</b>	OGID2	5	Output group ID 2 (JES2 only)	
<b>JPRIO</b>	JP	2	Job priority	
<b>DSDATE</b>	CrDate	10	Data set creation date. The installation can change the CRDATE column to 19, so that the date and time is included. (JES2 only)	
<b>OHREASON</b>	OHR	3	Output hold reason code	
<b>OHSNTXT</b>	Output-Hold-Text	37	Output hold reason text	

Table 37. Columns on the H Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>DEVID</b>	Device	18	Output device name	
<b>DSYSID</b>	SysID	5	Printing system (JES2 only)	
<b>OFFDEVS</b>	Offs	4	List of offload devices for a job or output that has been offloaded (JES2 only)	
<b>RETCODE</b>	Max-RC	10	Return code information for the job	
<b>JTYPE</b>	Type	4	Type of address space	
<b>ROOMN</b>	RNum	8	JES job room number	X
<b>PNAME</b>	Programmer-Name	20	JES programmer name	X
<b>ACCTN</b>	Acct	4 (JES2) 8 (JES3)	JES account number	X
<b>NOTIFY</b>	Notify	8	TSO user ID from NOTIFY parameter on job card	X
<b>ISYSID</b>	ISys	4 (JES2) 8 (JES3)	JES input system ID	X
<b>TIMER</b>	Rd-Time	8	Time that the job was read in. In the SDSF task of z/OSMF, this is replaced by the Rd-DateTime column.	X
<b>DATER</b>	Rd-Date	8	Date that the job was read in. In the SDSF task of z/OSMF, this is replaced by the Rd-DateTime column.	X
<b>ESYSID</b>	ESys	4 (JES2) 8 (JES3)	JES execution system ID	X
<b>TIMEE</b>	St-Time	8	Time that execution began. In the SDSF task of z/OSMF, this is replaced by the St-DateTime column.	JES3 only.
<b>DATEE</b>	St-Date	8	Date that execution began. In the SDSF task of z/OSMF, this is replaced by the St-DateTime column.	JES3 only.
<b>TIMEN</b>	End-Time	8	Time that execution ended. In the SDSF task of z/OSMF, this is replaced by the End-DateTime column.	X
<b>DATEN</b>	End-Date	8	Date that execution ended. In the SDSF task of z/OSMF, this is replaced by the End-DateTime column.	X
<b>ICARDS</b>	Cards	5	Number of cards read for job	X
<b>JCLASS</b>	JC	1 or 8	JES input job class. Default width expands to 8 if there are long class names in the MAS.	
<b>MCLASS</b>	MC	2	Message class of job	X
<b>SUBGROUP</b>	SubGroup	8	Submittor group	X

Table 37. Columns on the H Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>JOBACCT1</b>	JobAcct1 <sup>1</sup>	20	Job accounting field 1	X
<b>JOBACCT2</b>	JobAcct2 <sup>1</sup>	20	Job accounting field 2	X
<b>JOBACCT3</b>	JobAcct3 <sup>1</sup>	20	Job accounting field 3	X
<b>JOBACCT4</b>	JobAcct4 <sup>1</sup>	20	Job accounting field 4	X
<b>JOBACCT5</b>	JobAcct5 <sup>1</sup>	20	Job accounting field 5	X
<b>JOBCORR</b>	JobCorrelator	32	User portion of the job correlator (JES2 only)	
<b>DATETIMER</b>	Rd-DateTime	19	Date and time that the job was read in. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the Rd-Date and Rd-Time columns.	X
<b>DATETIMEE</b>	St-DateTime	19	Date and time that execution began. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the St-Date and St-Time columns.	X
<b>DATETIMEN</b>	End-DateTime	19	Date and time that execution ended. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the End-Date and End-Time columns.	X
<b>BERTNUM</b>	BERTNum	7	Number of BERTs used by this JOE (JES2 only)	
<b>JOBCRDATE</b>	JobCrDate	19	Job creation date (JES2 only).	
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.	

Notes on the table:

1. This column is not included in the default field list.

## Initiator panel (INIT)

The Initiator panel allows users to display information about JES initiators that are defined in the active JES on their CPUs.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 38. Columns on the INIT Panel

Column name	Title (Displayed)	Width	Description
<b>INTNAME</b>	ID	4 (JES2) 8 (JES3)	Initiator ID (JES2) or group or class name (JES3). This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	10	Initiator status

Table 38. Columns on the INIT Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ICLASS</b>	Classes	8	JES2 initiator classes (JES2 only). Multi-character classes and groups shows as periods (.).
<b>JNAME</b>	JobName	8	Job name
<b>STEPN</b>	StepName	8	Job step name
<b>PROCS</b>	ProcStep	8	Procedure step name (JES2 only)
<b>JTYPE</b>	Type	4	Type of address space
<b>JNUM</b>	JNum <sup>1</sup>	6	JES job number
<b>JOBID</b>	JobID	8	JES job ID or work ID
<b>JCLASS</b>	C	8	JES input class at time job was selected for execution
<b>ASID</b>	ASID	4	Address space identifier
<b>ASIDX</b>	ASIDX	5	Address space identifier in hexadecimal
<b>OWNERID</b>	Owner	8	User ID of the owner of the active job
<b>SYSNAME</b>	SysName	8	System name
<b>DSYSID</b>	SysID	5 (JES2) 8 (JES3)	JES member name (JES2) or the system on which the job is active under the class (JES3, resource type of INIT)
<b>JESNAME</b>	JESN	4	JES subsystem name
<b>JESLEVEL</b>	JESLevel	8	JES level
<b>SECLABEL</b>	SecLabel	8	Security label of the job
<b>SRVCLASS</b>	SrvClass	8	For JES-managed initiators, shows the service class of the active job. For WLM-managed initiators, shows the service class the initiator is running.
<b>IMODE</b>	Mode	4	Initiator mode (group rows only)
<b>BARRIER</b>	Barrier	7	Group scheduling barrier (JES3 only, group rows only)
<b>DEFAULT</b>	Default	7	Default group indicator (JES3 only)
<b>DEFCNT</b>	DefCount	8	Defined initiator count (JES3 only, group rows only)
<b>ALLOCCNT</b>	AllocCount	10	Allocated initiator count (JES3 only)
<b>USECOUNT</b>	UseCount	8	In-use initiator count (JES3 only)
<b>ALLOC</b>	Alloc	5	Allocation option (JES3 only, group rows only), which determines when the execution resources are to be allocated to the JES-managed group
<b>UNALLOC</b>	Unalloc	7	Unallocation indicator (JES3 only, group rows only)
<b>GROUP</b>	Group	8	Group name
<b>RESTYPE</b>	ResType	7	Resource type (group or class)
<b>ICLASS1-8</b>	Class1-8	8	JES2 initiator classes 1-8, including multi-character classes and groups (JES2 only)



Table 38. Columns on the INIT Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>INTNUM</b>	IntNum	6	Initiator number (JES2 only)
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

Notes on the table:

1. JNUM is not included in the default field list.

## Input Queue panel (I)

The Input Queue panel allows the user to display information about jobs, started tasks, and TSO users on the JES input queue or executing.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 39. Columns on the I Panel

Column name	Title (Displayed)	Width	Description	Delay
<b>JNAME</b>	JOBNAME	8	Job name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.	
<b>JOBID</b>	JobID	8	JES job ID	
<b>JTYPE</b>	Type	4	Type of address space	
<b>JNUM</b>	JNum <sup>1</sup>	6	JES job number	
<b>OWNERID</b>	Owner	8	User ID of job owner, or default values of ++ ++++++ or ???????, if user ID not defined to RACF 1.9 and later	
<b>JPRI0</b>	PrtY	4	JES2 input queue priority	
<b>JCLASS</b>	C	1 or 8	JES input class. Default width expands to 8 if there are long class names in the MAS.	
<b>POS</b>	Pos	5	Position within JES input queue class	
<b>PRTDEST</b>	PrtDest	18	JES print destination name	
<b>ROUTE</b>	Rmt	5	JES print routing. Remote number if routing is not local. (JES2 only)	
<b>NODE</b>	Node	5	JES print node (JES2 only)	
<b>SYSAFF</b>	SAff	5 (JES2) 8 (JES3)	JES execution system affinity (if any)	
<b>ACTSYS</b>	ASys	4 (JES2) 8 (JES3)	JES execution system ID (for logged-on users only)	
<b>STATUS</b>	Status	17	Status of job	
<b>SECLABEL</b>	SecLabel	8	Security label of job	

Table 39. Columns on the I Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>TGNUM</b>	TGNum	5	Track groups used by job	
<b>TGPCT</b>	TGPct	6	Percentage of total track group usage	
<b>ORIGNODE</b>	OrigNode	8	Origin node name	
<b>EXECNODE</b>	ExecNode	8	Execution node name	
<b>DEVID</b>	Device	18	JES device name	
<b>SRVCLS</b>	SrvClass	8	Service class	
<b>WLMPOS</b>	WPos	5	Position on the WLM queue	
<b>SCHENV</b>	Scheduling-Env	16	Scheduling environment for the job	
<b>DELAY</b>	Dly	3	Indicator that job processing is delayed	
<b>SSMODE</b>	Mode	4	Subsystem managing the job (JES or WLM)	
<b>ROOMN</b>	RNum	8	JES job room number	X
<b>PNAME</b>	Programmer-Name	20	JES programmer name field	X
<b>ACCTN</b>	Acct	4 (JES2) 8 (JES3)	JES account number field	X
<b>NOTIFY</b>	Notify	8	TSO user ID from NOTIFY parameter on job card	X
<b>ISYSID</b>	ISys	4 (JES2) 8 (JES3)	JES input system ID	X
<b>TIMER</b>	Rd-Time	8	Time that the job was read in. In the SDSF task of z/OSMF, this is replaced by the Rd-DateTime column.	X
<b>DATER</b>	Rd-Date	8	Date that the job was read in. In the SDSF task of z/OSMF, this is replaced by the Rd-DateTime column.	X
<b>ESYSID</b>	ESys	4 (JES2) 8 (JES3)	JES execution system ID	X
<b>TIMEE</b>	St-Time	8	Time that execution began. In the SDSF task of z/OSMF, this is replaced by the St-DateTime column.	JES3 only.
<b>DATEE</b>	St-Date	8	Date that execution began. In the SDSF task of z/OSMF, this is replaced by the St-DateTime column.	JES3 only.
<b>DATE</b>	St-Date	8	Date that execution began. In the SDSF task of z/OSMF, this is replaced by the St-DateTime column.	X
<b>ICARDS</b>	Cards	5	Number of cards read for job	X
<b>MCLASS</b>	MC	2	MSGCLASS of job	X
<b>TSREC</b>	Tot-Lines	10	Total number of spool records for job	X

Table 39. Columns on the I Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>SPIN</b>	Spin	4	Indicator of whether the job is eligible to be spun	
<b>SUBGROUP</b>	SubGroup	8	Submitter group	X
<b>PHASENAME</b>	PhaseName	20	Name of the phase the job is in	
<b>PHASE</b>	Phase	8	Number of the phase the job is in	
<b>JOBACCT1</b>	JobAcct1 <sup>1</sup>	20	Job accounting field 1	X
<b>JOBACCT2</b>	JobAcct2 <sup>1</sup>	20	Job accounting field 2	X
<b>JOBACCT3</b>	JobAcct3 <sup>1</sup>	20	Job accounting field 3	X
<b>JOBACCT4</b>	JobAcct4 <sup>1</sup>	20	Job accounting field 4	X
<b>JOBACCT5</b>	JobAcct5 <sup>1</sup>	20	Job accounting field 5	X
<b>SUBUSER</b>	SubUser	8	Submitting user ID	
<b>DELAYRSN</b>	DelayRsn	32	Reason for the job delay (JES2 only). The width can be expanded to 127.	
<b>JOBCORR</b>	JobCorrelator	32	User portion of the job correlator (JES2 only)	
<b>ASID</b>	ASID	5	ASID of the active job	
<b>ASIDX</b>	ASIDX	5	ASID of the active job, in hexadecimal	
<b>SYSNAME</b>	SysName	8	MVS system name where the job is executing	
<b>JOBGROUP</b>	JobGroup	8	Name of the job group associated with job (JES2 only)	
<b>JOBGRPID</b>	JobGrpId	8	JES2 job group job ID	
<b>JOBSET</b>	JobSet	8	Job set within the job group to which this job belongs (JES2 only)	
<b>JGSTATUS</b>	JGStatus	8	Status of the job within the dependency network (JES2 only)	
<b>FLUSHACT</b>	FlushAct	8	Flush action indicator (JES2 only)	
<b>HOLDUNTIL</b>	HoldUntil	19	HOLDUNTIL date and time (JES2 only)	
<b>STARTBY</b>	StartBy	19	STARTBY date and time (JES2 only)	
<b>WITH</b>	With	19	Name of the job or started task that the job must run with (on the same system) (JES2 only)	
<b>DATETIMER</b>	Rd-DateTime	19	Date and time that the job was read in. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the Rd-Date and Rd-Time columns.	X
<b>DATETIMEE</b>	St-DateTime	19	Date and time that execution began. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the St-Date and St-Time columns.	X
<b>EMAIL</b>	Email	48	Email address (JES2 only)	X

Table 39. Columns on the I Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>BEFOREJOB</b>	BeforeJob	9	Name of job that must run before this one (JES2 only)	
<b>BEFOREJID</b>	BeforeJID	4	JobID of job that must run before this one (JES2 only)	
<b>AFTERJOB</b>	AfterJob	8	Name of job that must run after this one (JES2 only)	
<b>AFTERJID</b>	AfterJID	8	JobID of job that must run after this one (JES2 only)	
<b>SCHDELAY</b>	SchDelay	8	Job delayed due to schedule hold or after (JES2 only)	
<b>BERTNUM</b>	BERTNum	7	Number of BERTs used by this job (JES2 only)	
<b>JOENUM</b>	JOENum	6	Number of JOEs used by this job (JES2 only)	
<b>JOEBERTNUM</b>	JOEBERTs	7	Number of BERTs used for this job's JOEs (JES2 only)	
<b>DUBIOUS</b>	Dubious	7	NJE job flagged as dubious (yes or no)	
<b>NETONHOLD</b>	OrigNHold	9	Original number of job completions before this job can be released (JES2 only)	
<b>NETCNHOLD</b>	CurrNHold	9	Current number of job completions before this job can be released (JES2 only)	
<b>NETNORM</b>	Normal	6	Action to be taken when any predecessor job completes normally (D, F, or R) (JES2 only)	
<b>NETABNORM</b>	Abnormal	6	Action to be taken when any predecessor job completes abnormally (D, F, or R) (JES2 only)	
<b>NETNRCMP</b>	NrCmp	5	Network job normal completion (HOLD, NOHO, or FLSH) (JES2 only)	
<b>NETABCMP</b>	AbCmp	5	Network job abnormal completion (NOKP or KEEP) (JES2 only)	
<b>NETOPHOLD</b>	OpHold	6	Operator hold (YES or NO) (JES2 only)	
<b>JOBCRDATE</b>	JobCrDate	19	Job creation date (JES2 only).	
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.	

Notes on the table:

1. This column is not included in the default field list.

## JES Checkpoint panel (CKPT)

The JES checkpoint (CKPT) panel is a secondary panel that shows all known JES checkpoints for a specific JES subsystem. You access the CKPT panel by using the JC action character from the JES panel.

Rows for checkpoints that are in use are highlighted. This panel uses the SYSNAME value to control which systems are shown.

You can use fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the checkpoint file name pattern.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 40. Columns on the CKPT Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	8	Checkpoint file name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SIZE</b>	Size	8	Checkpoint size in bytes.
<b>SIZEPCT</b>	Size%	5	Percentage size used.
<b>SIZEUSED</b>	Size%	8	Checkpoint size used in bytes.
<b>SIZETRK</b>	SizeTrk	8	Checkpoint size in tracks if CF=NO.
<b>INUSE</b>	InUse	5	Whether or not checkpoint is in use (YES/NO).
<b>CF</b>	CF	3	Whether or not checkpoint is in coupling facility.
<b>MODE</b>	Mode	6	Checkpoint mode (DUPLEX/DUAL).
<b>DUPLEX</b>	Duplex	6	Whether or not duplex is active (YES/NO).
<b>VOLATILE</b>	Volatile	8	Whether or not duplex is volatile (YES/NO).
<b>OPVERIFY</b>	OpVerify	8	Whether or not to use operators in checkpoint reconfiguration (YES/NO).
<b>CAP</b>	Capacity	8	Checkpoint capacity in bytes.
<b>CAPPCT</b>	Cap %	4	Percentage capacity used.
<b>CAPUSED</b>	CapUsed	8	Checkpoint capacity used in bytes.
<b>CAPPAGE</b>	CapPage	8	Checkpoint capacity in 4K pages.
<b>STRNAME</b>	StrName	16	Checkpoint CF structure name (if CF=YES).
<b>DSNAME</b>	DataSetName	44	Checkpoint dataset name (if CF=NO).
<b>VOLSER</b>	VolSer	6	DASD volume serial (if CF=NO).
<b>JESNAME</b>	JESName	4	JES subsystem name.
<b>SYSNAME</b>	SysName	8	System name where console is active.
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## JESInfo panel (JRI)

The JESInfo (JRI) panel shows JES2 resource usage.

Rows representing resource shortages are highlighted. You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the pattern of the resource name.

Because the panel shows MAS-wide resources, the panel does not use the SYSNAME value.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 41. Columns on the JESInfo Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	8	Resource name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>RESSHORT</b>	Shortage	8	Resource shortage (yes or no).
<b>NPRIVSHORT</b>	NPrivShortage	13	Non-privileged shortage (yes or no).
<b>NPRIVMAX</b>	NPrivMax	8	Non-privileged maximum.
<b>NPRIVUSE</b>	NPrivUse	8	Non-privileged in use.
<b>NPRIVPCT</b>	NPrivUse%	9	Non-privileged percentage used.
<b>NPRIVEXH</b>	NPrivExhaust	12	Non-privileged exhausted (yes or no).
<b>WARNPCT</b>	NPrivWarn%	10	Non-privileged warning percentage.
<b>PRIVSUP</b>	PrivSup	7	Privileged support (on or off).
<b>RPRIVSUP</b>	ResPrivSup	10	Resource privileged support (on or off).
<b>PRIVMAX</b>	PrivMax	7	Privileged maximum.
<b>PRIVUSE</b>	PrivUse	7	Privileged usage.
<b>PRIVPCT</b>	PrivUse%	8	Privileged usage percentage.
<b>EXHAUST</b>	PrivExhaustTime	19	Timestamp of predicted privilege exhaustion.
<b>SMALLENV</b>	SmallEnv	8	Small environment (yes or no).
<b>RESDISC</b>	Description	20	Resource description.
<b>SAMPTIME</b>	SampleTime	19	Timestamp when sample obtained.
<b>JESNAME</b>	JESName	7	JES subsystem name.
<b>SYSNAME</b>	SysName	8	System name.
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## JESInfo by Job panel (JRJ)

The JESInfo by Job (JRJ) panel shows JES2 resource usage and rates by job.

Rows representing resource shortages are highlighted.

You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts up to two parameters, as follows:

- Jobname [jobid]. The jobid is JOB, TSU, STC, J, T, or S followed by the job number.

- Jobname [job number].
- Job number.

Because the panel shows jobs, the panel does not use the SYSNAME value.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 42. Columns on the JESInfo by Job Panel

Column name	Title (Displayed)	Width	Description
<b>JOBNAME</b>	JOBNAME	8	Job name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>JOBID</b>	JobID	8	Job ID.
<b>NAME</b>	Resource	8	Resource name.
<b>USE</b>	Usage	5	Resource usage.
<b>USEPCT</b>	Usage%	6	Resource usage percentage.
<b>USERATE</b>	UsageRate	9	Resource usage per minute.
<b>NPRIVMAX</b>	NPrivMax	8	Non-privileged maximum.
<b>SAMPTIME</b>	SampleTime	19	Timestamp when sample obtained.
<b>MEMBER</b>	Member	8	Member name for active job.
<b>JESNAME</b>	JESName	7	JES subsystem name.
<b>SYSNAME</b>	SysName	8	System name.
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLIDENT statement or through the <b>ARRANGE</b> command.

## JES Subsystem panel (JES)

The JES subsystem (JES) panel shows all known JES subsystems in the system.

This panel uses the SYSNAME value to control which systems are shown on the panel. Rows for JES2 primary subsystems or JES3 global subsystems are highlighted.

You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the subsystem name pattern.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 43. Columns on the JES Subsystem Panel

Column name	Title (Displayed)	Width	Description
<b>JESNAME</b>	NAME	4	Subsystem name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>JESTYPE</b>	Type	4	JES subsystem type (JES2/JES3).
<b>PRIMARY</b>	Primary	7	Is JES2 Primary subsystem (YES/NO).
<b>EMERGENCY</b>	Emergency	9	Is JES2 emergency subsystem (YES/NO).

Table 43. Columns on the JES Subsystem Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>GLOBAL</b>	Global	6	Is JES3 global subsystem (YES/NO).
<b>MEMBER</b>	Member	8	JES MAS member name.
<b>NODE</b>	OwnNode	8	JES Node name.
<b>COMCAHR</b>	ComChar	8	JES command prefix.
<b>XCFGROUP</b>	XCFGroup	8	JES MAS XCF group name.
<b>STATUS</b>	Status	32	Status of JES subsystem.
<b>VERSION</b>	Version	8	Version of JES.
<b>SERVICE</b>	Service	7	Service level of JES.
<b>SSCT</b>	SSCT	8	SSCT address of the subsystem.
<b>SYSNAME</b>	SysName	8	System name where console is active.
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## JESPLEX panel (JP)

The JESPLEX (JP) panel simplifies the display and control of members in a JES3 JESPLEX. It is analogous to the JES2 MAS panel, and they share a common field list. For a description of the columns, see “Multi-Access Spool panel (MAS) and JESPLEX (JP) panel” on page 155.

## Job Class Members panel (JCM)

The Job Class Members (JCM) panel is a secondary panel that shows the members associated with a job class. You access it by using the I action character from the JC panel in the JES3 environment. (The I action is not valid in the SDSF Java or z/OSMF environments.)

Rows that represent a class with at least one job active are highlighted.

You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the member name pattern.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 44. Columns on the JCM Panel

Column name	Title (Displayed)	Width	Description
<b>MEMBER</b>	MEMBER	8	Member for controlling class. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro. Control characters are translated to periods.
<b>JOBCL</b>	CtlClass	8	Controlling class name
<b>MLIMMAX</b>	MLimMax	7	Maximum number of jobs that can run in the controlling class
<b>MLIMCUR</b>	MLimCur	7	Current number of jobs running in controlling class



Table 44. Columns on the JCM Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>SELMODE</b>	SelMode	8	Selection mode name
<b>SYSNAME</b>	SysName	8	MVS system name for member
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job Class panel (JC)

The JC panel allows the user to display information about job classes.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 45. Columns on the JC Panel

Column name	Title (Displayed)	Width	Description
<b>JOBCL</b>	CLASS	8	Job class. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>JSTATUS</b>	Status	8	Class status
<b>MEMBER</b>	Member	8	Member name (JES3 only)
<b>GROUP</b>	Group	8	Group name
<b>JMODE</b>	Mode	4	Manager of the class
<b>WAITCNT</b>	Wait-Cnt	8	Number of jobs waiting for execution (non-WLM jobs only) (JES2 only)
<b>XEQCNT</b>	Xeq-Cnt	8	Number of active jobs
<b>HOLDCNT</b>	Hold-Cnt	8	Number of held jobs (JES2 only)
<b>JCODISP</b>	ODisp	13	Output disposition for normal and abnormal end of the job (JES2 only)
<b>QHELD</b>	QHld	4	Job class hold indicator (JES2 only)
<b>JHOLD</b>	Hold	4	Job hold indicator (JES2 only)
<b>XBM</b>	XBM	8	Name of the execution batch monitor (XBM) procedure to be executed by jobs running in the class (JES2 only)
<b>JCLIM</b>	JCLim	5	Job class limit for the system (JES2 only)
<b>TDEPTH</b>	TDepth	6	Maximum job count for the class (JES3 only). This is analogous to the JCLim column for JES2.
<b>JPGN</b>	PGN	3	Default performance-group number (JES2 only)
<b>JAUTH</b>	Auth	4	MVS operator command groups that are to be executed (JES2 only)
<b>BLP</b>	BLP	3	Perform bypass label processing (JES2 only)
<b>COMMAND</b>	Command	7	Disposition of commands read from the input stream (JES2 only)

Table 45. Columns on the JC Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>JLOG</b>	Log	3	Job log indicator
<b>MSGLEVEL</b>	MsgLV	5	Message level value (JES2 only)
<b>OUTPUT</b>	Out	3	SYSOUT write indicator (JES2 only)
<b>PROCLIB</b>	PL	2	Default procedure library number (JES2 only)
<b>PROMORT</b>	PromoRt	7	STARTBY promotion rate (JES2 only)
<b>REGION</b>	Region	6	Default region size assigned to each job step (JES2 only)
<b>SWA</b>	SWA	5	Placement of SWA control blocks created for jobs, in relation to 16 megabytes in virtual storage (JES2 only)
<b>TIME</b>	Max-Time	11	Default for the maximum time that each job step may run (JES2 only)
<b>ACCT</b>	Acct	4	Requirement for the account number on a JCL JOB statement (JES2 only)
<b>COPY</b>	Cpy	3	Queue jobs for output processing as though TYPRUN=COPY were specified on the JOB statement (JES2 only)
<b>JOURNAL</b>	Jrnl	4	Save job-related information in a job journal
<b>PGMRNAME</b>	PgNm	4	Programmer name required on a JCL JOB statement (JES2 only)
<b>RESTART</b>	Rst	3	Requeue for execution jobs that had been executing before the IPL of the system was repeated and a JES2 warm start was performed
<b>SCAN</b>	Scn	3	Queue jobs for output processing immediately after JCL conversion (JES2 only)
<b>IEFUJP</b>	UJP	3	Take the IEFUJP exit when a job is purged (JES2 only)
<b>IEFUSO</b>	USO	3	Take the IEFUSO installation exit when the SYSOUT limit is reached for a job (JES2 only)
<b>TYPE6</b>	Tp6	3	Produce type 6 SMF records (JES2 only)
<b>TYPE26</b>	Tp26	4	Produce type 26 SMF records (JES2 only)
<b>CONDPURG</b>	CPr	3	Conditionally purge system data sets in this time-sharing user class (JES2 only)
<b>JMCLASS</b>	MC	2	Message class for all time-sharing sessions (default logon message class for all TSO/E logons) (JES2 only)
<b>SCHENJC</b>	Scheduling-Env	16	Scheduling environment for the job (JES2 only)
<b>JESLOG</b>	JESLog	13	Spin options for the jobs' JES2 job log and message log
<b>XBMPROC</b>	XBMProc	8	Procedure name for XBM/2 job (JES2 only)

Table 45. Columns on the JC Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>DUPJOB</b>	DupJob	6	Duplicate job names acceptable for this class (JES2 only)
<b>SDEPTH</b>	SDepth	6	Setup depth (JES3 only)
<b>PARTNAM</b>	PartName	8	Spool partition name (JES3 only)
<b>PRITRK</b>	PriTrk	6	Primary track group allocation (JES3 only)
<b>SECTRK</b>	SecTrk	6	Secondary track group allocation (JES3 only)
<b>PRIO</b>	Prio	4	Priority (JES3 only)
<b>JOBRC</b>	JobRC	6	Indicates whether the last (LASTRC) or max (MAXRC) step completion code is reported as the job completion code (JES2 only)
<b>CLACTIVE</b>	Active	6	Indicates if the class is currently active (JES2 only)
<b>DSENQSHR</b>	DSEnqShr	8	Indicates if JES should change data set enqueues to shared access when exclusive access is not required (JES2 only)
<b>SYSSYM</b>	SysSym	8	Indicates if system symbols are allowed in batch jobs
<b>GDGBIAS</b>	GDGBias	7	GDG bias default (STEP or JOB)
<b>SYSNAME</b>	SysName	8	System name for member (JES3 only)
<b>SELMODE</b>	SelMode	8	Selection mode name (JES3 only)
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job Common Storage panel (JCS)

The Job Common Storage panel allows authorized users to view information about all allocated blocks of common storage.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 46. Columns on the JCS Panel

Column name	Title (Displayed)	Width	Description
<b>ADDRESS</b>	ADDRESS	7	Storage area address. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SIZE</b>	Size	10	Block size
<b>SP</b>	SP	3	Subpool of storage
<b>KEY</b>	Key	3	Storage key
<b>TYPE</b>	Type	4	Storage type SQA/CSA
<b>ORPHAN</b>	Orphan	6	Orphaned storage (Yes/No)
<b>JNAME</b>	JobName	8	Requestor job

Table 46. Columns on the JCS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>JOBID</b>	JobID	8	Job ID
<b>ASID</b>	ASID	5	Address space ID
<b>ASIDX</b>	ASIDX	5	Address space ID in hexadecimal
<b>GQE</b>	GQE	8	Block address
<b>CAUB</b>	CAUB	8	CAUB address
<b>ADATE</b>	AllocDate	19	Storage allocation timestamp
<b>ODATE</b>	OrphanDate	19	Storage orphaned timestamp
<b>RETURN</b>	ReturnAddr	10	Return address
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	System level
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job Data Set panel (JDS)

The Job Data Set panel allows the user to display information about SYSOUT data sets for a selected job, started task, and TSO user.

When the JDS panel is accessed from the DA, I, or ST panel, the values for all the columns are obtained from the spool data set. When the JDS panel is accessed from the H or O panel, the values for some columns are obtained from in-storage control blocks.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 47. Columns on the JDS Panel

Column name	Title (Displayed)	Width	Description	Delay
<b>DDNAME</b>	DDNAME	8	DD name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.	
<b>STEPN</b>	StepName	8	Job step name	
<b>PROCS</b>	ProcStep	8	Procedure step name	
<b>DSID</b>	DSID	4	Data set ID number	
<b>OWNERID</b>	Owner	8	User ID of SYSIN/SYSOUT owner, or default values of ++++++++ or ????????, if user ID not defined to RACF 1.9 and later	
<b>OCLASS</b>	C	1	JES output class	
<b>DESTN</b>	Dest	18	JES print destination name	
<b>RECCNT</b>	Rec-Cnt	7	Data set record count	
<b>PAGECNT</b>	Page-Cnt	8	Data set page count. Blanks if not page-mode data.	

Table 47. Columns on the JDS Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>BYTECNT</b>	Byte-Cnt	8	Data set byte count	
<b>COPYCNT</b>	CC	2	Data set copy count	
<b>DEST</b>	Rmt	5	JES2 print routing. Remote number if routing is not local (JES2 only).	
<b>NODE</b>	Node	5	JES2 print node (JES2 only)	
<b>OGNAME</b>	O-Grp-N	8	Output group name (JES2 only)	
<b>SECLABEL</b>	SecLabel	8	Security label of data sets	
<b>PRMODE</b>	PrMode	8	Data set process mode	
<b>BURST</b>	Burst	5	Data set burst indicator	
<b>DSDATE</b>	CrDate-CrTime	19	Data set creation date and time, or, if ***** N/A ***** , the creation date and time were not available.	
<b>FORMS</b>	Forms	8	Output form number	
<b>FCBID</b>	FCB	4	Output FCB ID	
<b>UCSID</b>	UCS	4	Output UCS ID	
<b>WTRID</b>	Wtr	8	Output special writer ID or data set ID	
<b>FLASHID</b>	Flash	5	Output flash ID	
<b>FLASHC</b>	FlashC	6	Flash count	
<b>SEGID</b>	SegID	5	Data set segment number	
<b>DSNAME</b>	DSName	44	Output data set name	
<b>CHARS</b>	Chars	20	Character arrangement table names	
<b>CPYMOD</b>	CpyMod	6 (JES2) 8 (JES3)	Copy modification module name	
<b>CPYMODFT</b>	CpyModFT	8	Copy modification table reference character (JES2 only)	
<b>PAGEDEF</b>	PageDef	7	Library member used by PSF to specify print characteristics such as page width	X
<b>FORMDEF</b>	FormDef	7	Library member used by PSF to specify print characteristics such as overlays	X
<b>ODTITLE</b>	Title	20	Report title to be printed on separator pages . This column can be expanded to 60.	X
<b>ODNAME</b>	Name	20	Name to be printed on separator pages . This column can be expanded to 60.	X
<b>ODBLDG</b>	Building	10	Building identification to be printed on separator pages . This column can be expanded to 60.	X

Table 47. Columns on the JDS Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>ODDEPT</b>	Department	10	Department identification to be printed on separator pages . This column can be expanded to 60.	X
<b>ODROOM</b>	Room	10	Room identification to be printed on separator pages. This column can be expanded to 60.	X
<b>ODADDR</b>	Address-Line1	20	Address to be printed on separator pages . This column can be expanded to 60	X
<b>ODADDR2</b>	Address-Line2	20	Output address line 2. This column can be expanded to 60.	X
<b>ODADDR3</b>	Address-Line3	20	Output address line 3. This column can be expanded to 60.	X
<b>ODADDR4</b>	Address-Line4	20	Output address line 4. This column can be expanded to 60.	X
<b>OUTBIN</b>	OutBn	5	Output bin	X
<b>COMSETUP</b>	ComSetup	8	Setup options for microfiche printers	X
<b>FORMLEN</b>	FormLen	10	Form length	X
<b>COLORMAP</b>	ColorMap	8	AFP resource for the data set containing color translation information	X
<b>INTRAY</b>	ITy	3	Paper source	X
<b>OVERLAYB</b>	OverlayB	8	Overlay for the back of each sheet	X
<b>OVERLAYF</b>	OverlayF	8	Overlay for the front of each sheet	X
<b>OFFSETXB</b>	OffsetXB	13	Offset in the x direction from the page origin for the back of each page	X
<b>OFFSETXF</b>	OffsetXF	13	Offset in the x direction from the page origin for the front of each page	X
<b>OFFSETYB</b>	OffsetYB	13	Offset in the y direction from the page origin for the back of each page	X
<b>OFFSETYF</b>	OffsetYF	13	Offset in the y direction from the page origin for the front of each page	X
<b>PORTNO</b>	Port	5	Number of the TCP/IP port where the FSS connects to the printer	X
<b>ODNOTIFY</b>	Notify	17	Print complete notification message	X
<b>ODUSRLIB</b>	UserLib	44	Libraries containing Advanced Function Printing (AFP) resources to be used by Print Services (PSF) when processing SYSOUT data sets.	X
<b>USERDATA</b>	UserData1	60	User data. Access values 2-16 by typing + alone in the column.	X
<b>AFPPARMS</b>	AFPParms	54	Names a data set that contains the parameters to be used by the AFPPrint Distributor	X

Table 47. Columns on the JDS Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>QUEUE</b>	Queue	5	Names the JES3 queue the data set is on (TCP, BDT, HOLD, WTR) (JES3 only)	
<b>SPIN</b>	Spin	4	Indicates whether this is a spin data set	
<b>SELECT</b>	Sel	3	Indicates whether the data set is selectable	
<b>TP</b>	TP	3	Indicates whether SYSOUT was created by a transaction program.	
<b>TPJNAME</b>	TPJName	8	Job name of the transaction program that created the data set	
<b>TPJOBID</b>	TPJobID	8	Job ID of the transaction program that created the data set	
<b>TPACCT</b>	TPAcct	8	Account number of the transaction program	
<b>TPTIMER</b>	TRd-Time	8	Start time for entry of the transaction program. In the SDSF task of z/OSMF, this is replaced by the TRd-DateTime column.	
<b>TPDATER</b>	TRd-Date	8	Start date for entry of the transaction program. In the SDSF task of z/OSMF, this is replaced by the TRd-DateTime column.	
<b>TPTIMEE</b>	TSt-Time	8	Start time for execution of the transaction program. In the SDSF task of z/OSMF, this is replaced by the TSt-DateTime column.	
<b>TPDATEE</b>	TSt-Date	8	Start date for execution of the transaction program. In the SDSF task of z/OSMF, this is replaced by the TSt-DateTime column.	
<b>RECFM</b>	RecFm	5	Record format	
<b>SPINNABLE</b>	W	3	Indicates if the data set is open and spinnable (JES2 only)	
<b>OCOPYCNT</b>	OCopyCnt	8	Copy count specified with COPYCNT. Used by InfoPrint printers.	X
<b>LRECL</b>	LRecl	5	Logical record length	
<b>TPDATETIMER</b>	TRd-DateTime	19	Start date and time for entry of the transaction program. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the TRd-Date and TRd-Time columns.	
<b>TPDATETIMEE</b>	TSt-DateTime	19	Start date and time for execution of the transaction program. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the TSt-Date and TSt-Time columns.	
<b>STEPNUM</b>	StepNum	5	Step number (JES2 only)	
<b>OUTDISP</b>	ODisp	5	JES output disposition (JES3 only)	
<b>COPYGRP</b>	CopyGroups	32	Number of copies of each page to be printed	

Table 47. Columns on the JDS Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>COMPRESS</b>	Compressed	10	Compression status (yes or no, JES2 only)	
<b>ENCRYPT</b>	Encrypted	9	Encryption status (yes or no, JES2 only)	
<b>KEYLABEL</b>	KeyLabel	64	Key-label for encryption (JES2 only)	
<b>NCOMPSize</b>	NCompByteSize	13	Data set byte size before compression (JES2 only)	
<b>COMPSize</b>	CompByteSize	12	Data set byte size after compression (JES2 only)	
<b>COMPPCT</b>	Comp%	6	Data set compression percentage (JES2 only)	
<b>AFPSTATS</b>	AFPStats	8	AFP statistics report option	X
<b>RETAINS</b>	RetainS	10	Retain time for successful transmissions	X
<b>RETAINF</b>	RetainF	10	Retain time for unsuccessful transmissions	X
<b>RETRYL</b>	RetryL	5	Maximum number of retries	X
<b>RETRYT</b>	RetryT	10	Time between retries	X
<b>PRINTO</b>	Print-Options	16	Entry in PrintWay options data set	X
<b>PRINTQ</b>	Print-Queue	60	Print queue name	X
<b>IPDEST</b>	IP-Destination	60	IP address or TCP/IP name	X
<b>MAILCC</b>	EMailCC	60	Email copy list	X
<b>MAILBCC</b>	EMailBCC	60	Email blind copy list	X
<b>MAILFROM</b>	EMailFrom	60	Email sender	X
<b>MAILTO</b>	EMailTo	60	Email recipient list	X
<b>MAILFILE</b>	EMailFileName	60	Email attachment file name	X
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.	

## Job Delay panel (JY)

The Job Delay panel allows the user to view reasons why the job might be delayed.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 48. Columns on the JY Panel

Column name	Title (Displayed)	Width	Description
<b>DESC</b>	TYPE	32	Delay description. It is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SOURCE</b>	Src	3	Source of this sample information (WLM or RMF)
<b>SAMP</b>	Samples	7	Number of samples in the interval that correspond to this delay



Table 48. Columns on the JY Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>PERCENT</b>	Percent	7	Percent of samples in the interval that correspond to this delay
<b>INTERVAL</b>	Interval	8	Sampling interval for WLM delays (milliseconds)
<b>MINTIME</b>	MinTime	8	Length of RMF sampling interval in seconds
<b>FIRSTSMP</b>	First-Sample	19	Time stamp of the first sample in the interval
<b>LASTSAMP</b>	Last-Sample	19	Time stamp of the last sample in the interval
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job Dependency panel (JP)

The Job Dependency panel allows authorized users to view, for a selected job, the jobs that it is dependent on and the jobs that have dependencies on it, or, for a selected job group, all of the dependencies in the job group. The panel shows the conditions for each dependency.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 49. Columns on the Job Dependency Panel

Column name	Title (Displayed)	Width	Description
<b>JOBNAME</b>	JOBNAME	8	Job name. It is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>JOBID</b>	JobID	8	Job ID
<b>DEPEND</b>	Dependency	10	Type of dependency the job has with the job or jobset
<b>DJOBNAME</b>	DJobName	8	Name of the job on which this job is dependent
<b>DJOBID</b>	DJobID	8	ID of the job on which this job is dependent
<b>TIME</b>	Time	19	Date and time associated with a HOLDUNTIL or STARTBY dependency
<b>WHEN</b>	When	64	Condition tested for the dependency
<b>ACTION</b>	Action	7	Action taken when the condition is met
<b>OTHERWISE</b>	Otherwise	9	Action taken when the condition is not met
<b>STATUS</b>	Status	8	Status of the dependency

Table 49. Columns on the Job Dependency Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job Device panel (JD)

The Job Device panel allows the user to display information about devices that a job is using.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 50. Columns on the JD Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	16	DDNAME, CF connection name, or TCP/IP server name. It is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SEQUENCE</b>	Seq	3	DD allocation sequence (DDs only)
<b>TYPE</b>	Type	4	Type of row item (DD, IP or CF)
<b>STATUS</b>	Status	8	Current status
<b>DSNAME</b>	DataSetName	54	Data set name (or path name) (DDs only)
<b>STRNAME</b>	StrName	8	CF structure name (CFs only)
<b>VOLSER</b>	VolSer	6	Volume serial or CF name (CFs and DDs only)
<b>UNIT</b>	Unit	4	Unit address. Only the first one is displayed. For subsystem data sets, displays the subsystem name. 'DMY', 'HFS' or 'SMS' may be displayed for applicable data sets as well.
<b>UNITCT</b>	UnitCt	6	Unit count
<b>IPADDR</b>	IPAddr	24	IP address. IP address and Port are the local address for connections with a status of 'Listen' and the remote address for other status values. (TCP/IP connections only)
<b>PORT</b>	Port	5	Port. IP address and Port are the local address for connections with a status of 'Listen' and the remote address for other status values. (TCP/IP connections only)
<b>RECFM</b>	RecFM	5	Record format
<b>LRECL</b>	LReCL	5	Logical record length
<b>BLKSIZE</b>	BlkSize	5	Block size
<b>INBUFSZ</b>	InBufSz	5	Receive buffer size (TCP/IP connections only)

Table 50. Columns on the JD Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>OUTBUFSZ</b>	OutBufSz	8	Send buffer size (TCP/IP connections only)
<b>DISP1</b>	Disp1	5	Disposition status (OLD, NEW, SHR, MOD) (DDs only)
<b>DISP2</b>	Disp2	5	Normal termination disposition (KEEP, DELETE, PASS, CATLG, UNCATLG) (DDs only)
<b>DISP3</b>	Disp3	5	Abnormal termination disposition (KEEP, DELETE, PASS, CATLG, UNCATLG) (DDs only)
<b>EXCPCT</b>	EXCP-Cnt	5	Number of requests (e.g. EXCPs or bytes, for TCP/IP connections) (DDs only and TCP/IP connections only)
<b>BYTESIN</b>	BytesIn	8	Number of bytes received on connection (TCP/IP connections only)
<b>BYTESOUT</b>	BytesOut	8	Number of bytes sent on connection (TCP/IP connections only)
<b>OPEN</b>	Open	5	Open count (DDs only)
<b>POLICY</b>	Policy	8	CF policy name (CFs only)
<b>STIME</b>	Start-Time	19	Connection start time (TCP/IP connections only)
<b>LASTIME</b>	Last-Time	19	Connection last activity time (TCP/IP connections only)
<b>RESID</b>	ResourceId	19	Resource ID (TCP/IP connections only)
<b>STACK</b>	Stack	8	Stack name (TCP/IP connections only)
<b>APPL</b>	Appl	8	TELNET target application name (TCP/IP connections only)
<b>LUNAME</b>	LUName	8	TELNET client LU name (TCP/IP connections only)
<b>CLIENT</b>	Client	8	TELNET client user ID (TCP/IP connections only)
<b>APPLDATA</b>	ApplData	40	Application data associated with the request (TCP/IP connections only)
<b>DSORG</b>	DSOrg	5	Data set organization (requires SDSFAUX)
<b>SMS</b>	SMS	3	SMS indicator: YES if data set is SMS managed (requires SDSFAUX)
<b>CONNECT</b>	ConnectTime	11	Device connect time in milliseconds (requires SDSFAUX)
<b>AVGCONN</b>	AvgConnTime	11	Average device connect time in milliseconds (requires SDSFAUX)
<b>CONDISP</b>	ConDisp	6	Connection disposition (keep or delete)
<b>CONSTATE</b>	ConState	18	Connection state (active, failed-persistent, disconnecting, failing)
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job DDName panel (JDDN)

The Job DDName (JDDN) panel is a secondary panel that shows the data set allocations associated with a job. It is similar to the Job Device (JDD) panel, except that only allocations are shown. That is, there are no rows for TCP/IP connections or coupling facility structures. You access the JDDN panel using the JDD action character from the DA, AS, I, ST, INIT, or NS panels.

You can use the **SRCH** command to locate a member within the allocations. You can ISPF browse, edit, and view MVS data sets. (Browse is not supported for JES, subsystem, or file system data sets.)

You can use the fast path select (S) and filter commands to customize the rows being shown.. The command accepts two parameters. The first parameter is a DDNAME pattern and the second parameter is the data set name pattern.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 51. Columns on the JDDN Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	8	DDNAME. It is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SEQUENCE</b>	Seq	3	DD allocation sequence.
<b>STATUS</b>	Status	8	Status.
<b>DSNAME</b>	DataSetName	54	Data set name or path name.
<b>VOLSER</b>	VolSer	6	Volume serial.
<b>UNIT</b>	Unit	4	Unit address. Only the first one is displayed. For subsystem data sets, displays the subsystem name. 'HFS' or 'SMS' may be displayed for applicable data sets as well.
<b>UNITCT</b>	UnitCt	6	Unit count.
<b>RECFM</b>	RecFM	5	Record format.
<b>LRECL</b>	LRecL	5	Logical record length.
<b>BLKSIZE</b>	BlkSize	7	Block size.
<b>DISP1</b>	Disp1	5	Disposition status (OLD, NEW, SHR, MOD).
<b>DISP2</b>	Disp2	7	Normal termination disposition (KEEP, DELETE, PASS, CATLG, UNCATLG).
<b>DISP3</b>	Disp3	7	Abnormal termination disposition (KEEP, DELETE, PASS, CATLG, UNCATLG).
<b>EXCPCT</b>	EXCP-Cnt	8	Number of requests.
<b>OPEN</b>	Open	5	Open count.
<b>DSORG</b>	DSOrg	5	Data set organization.
<b>SMS</b>	SMS	3	SMS indicator: YES if data set is SMS managed.
<b>CONNECT</b>	ConnectTime	11	Device connect time in milliseconds.
<b>AVGCONN</b>	AvgConnTime	11	Average device connect time in milliseconds.
<b>APF</b>	APF	3	APF indicator (yes, no, or blank if not a loadlib data set).
<b>SYSNAME</b>	SysName	8	MVS system name.

Table 51. Columns on the JDDN Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job Group panel (JG)

The Job Group panel allows the user to view JES2 job groups, or execution zones. Execution zones are created when JCL is submitted that describes a relationship between a set of jobs.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 52. Columns on the JG Panel

Column name	Title (Displayed)	Width	Description
<b>JOBGROUP</b>	JOBGROUP	8	Job group name. It is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>JOBGRPID</b>	JobGrpID	8	Group ID – JobId(job number) of associated logging job for the group
<b>OWNER</b>	Owner	8	User ID of the owner of the job group
<b>STATUS</b>	Status	10	Status of the job group
<b>CRETCODE</b>	Current-CC	10	Completion code of the job group.
<b>SYSAFF</b>	SAff	5	List of JES members (affinity mask) where jobs in the zone (group) can run
<b>SCHENV</b>	Scheduling-Env	16	Scheduling environment where jobs in the group can run
<b>ONERR</b>	OnError	7	Action to take when a job group is determined to be in error.
<b>ERRSTAT</b>	ErrStat	7	Current error status
<b>ERRCOND</b>	ErrorCond	18	Error condition
<b>SECLABEL</b>	SecLabel	8	Security label associated with the job group
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job Memory panel (JM)

The Job Memory panel allows the user to view the system memory being used by a job.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 53. Columns on the JM Panel

Column name	Title (Displayed)	Width	Description
<b>TYPE</b>	TYPE	8	Type of storage (for example, Private or LSQA). This is a fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SUBPOOL</b>	SP	3	Subpool number
<b>KEY</b>	Key	3	Storage key
<b>FIXED</b>	Fix	4	The default page-fix status of the subpool (YES, NO, or DREF)
<b>FPROT</b>	FP	4	The default fetch-protect status of the subpool (YES or NO)
<b>TOTAL</b>	Total	8	Total amount of allocated storage with the specified characteristics (Type/SP/Key)
<b>TOTAL24</b>	Total-24	8	Total 24-bit storage
<b>TOTAL31</b>	Total-31	8	Total 31-bit storage
<b>TOTAL64</b>	Total-64	8	Total 64-bit storage
<b>COUNT</b>	Count	8	Total number of allocated storage segments with the specified characteristics
<b>LARGEST</b>	LargestA	8	Size of the largest segment of allocated storage with the specified storage characteristics
<b>LARGESTF</b>	LargestF	8	Size of the largest segment of free storage with the specified storage characteristics
<b>FRAG</b>	Frag	8	Total number of allocated and free storage segments
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job Memory Objects panel (JMO)

The Job Memory Objects (JMO) panel is a secondary panel that shows all memory objects allocated for an address space. You access it by using the JMO action character from the DA or AS panels. Rows that represent fetch-protected objects are highlighted.

You can use the fast path select (S) and filter commands to customize the rows being shown.. The command accepts a single parameter for the type of memory object.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 54. Columns on the JMO Panel

Column name	Title (Displayed)	Width	Description
<b>TYPE</b>	TYPE	7	Memory object type (private or common). This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro. Control characters are translated to periods.
<b>START</b>	Start-Address	17	Starting address of object.

Table 54. Columns on the JMO Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>END</b>	End-Address	17	Ending address of object.
<b>SIZE</b>	Size	6	Object size (bytes).
<b>KEY</b>	Key	3	Storage key.
<b>GUARD</b>	Guard	10	Guard area definition (none, default, or nondefault).
<b>FPROT</b>	FProt	5	Fetch protected (yes or no).
<b>SHARED</b>	Shared	6	Shared (yes or no).
<b>LARGE</b>	Large	5	Object backed by large pages (yes or no).
<b>CRDATE</b>	CrDate	19	Object creation timestamp.
<b>CRRETADR</b>	PgmRetAddr	17	Return address of program creating object.
<b>JNAME</b>	JobName	8	Job name.
<b>JOBID</b>	JobID	8	Job ID.
<b>ASID</b>	ASID	5	Address space ID.
<b>ASIDX</b>	ASIDX	5	Address space ID (hexadecimal).
<b>SYSNAME</b>	SysName	8	System name.
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job Module panel (JC)

The Job Module panel allows authorized users to list the loaded modules for an address space.

You access the Job Module panel using the JC action character from the DA or AS panel.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 55. Columns on the Job Module Panel

Column name	Title (Displayed)	Width	Description
<b>MODNAME</b>	MODULE	8	Module name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>MAJOR</b>	Major	8	Major name if module is an alias
<b>MODEPA</b>	EPA	8	Module entry point address
<b>MODLEN</b>	ModLen	8	Module length (if known)
<b>SUBPOOL</b>	SP	3	Storage subpool for module
<b>TCB</b>	TCB	8	TCB address of the module
<b>PROGRAM</b>	Program	8	TCB program associated with the module
<b>JPAQ</b>	JPAQ	4	Indicates whether module is in the job pack area

Table 55. Columns on the Job Module Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>LPDE</b>	LPDE	4	Indicates whether module is in the link pack directory entry
<b>USECOUNT</b>	Use	3	Current use count for module
<b>SYSUSE</b>	SysUse	6	System use count for module
<b>AUTHCOD</b>	AC	2	Authorization code for module
<b>AMODE</b>	AM	2	Addressing mode (AMODE)
<b>RMODE</b>	RM	2	Residency mode (RMODE)
<b>APF</b>	APF	3	APF indicator (yes or no)
<b>RENT</b>	Rent	4	Reenterable indicator (yes or no)
<b>REUS</b>	Reus	4	Reusable indicator (yes or no)
<b>CDATTR</b>	Attr	5	CSVINFO attribute byte 1 in hexadecimal.
<b>CDATTR2</b>	Attr2	5	CSVINFO attribute byte 2 in hexadecimal.
<b>CDATTR3</b>	Attr3	5	CSVINFO attribute byte 3 in hexadecimal.
<b>CDATTR4</b>	Attr4	5	CSVINFO attribute byte 4 in hexadecimal.
<b>JNAME</b>	JobName	8	Job name
<b>ASID</b>	ASID	5	Address space identifier
<b>ASIDX</b>	ASIDX	5	Address space identifier in hexadecimal
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of operating system
<b>CDATTR3</b>	Attr3	5	CSVINFO attribute byte 3 in hexadecimal.
<b>CDATTR4</b>	Attr4	5	CSVINFO attribute byte 4 in hexadecimal.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job Step panel (JS)

The Job Step panel allows the user to view information about the steps for a job.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 56. Columns on the JS Panel

Column name	Title (Displayed)	Width	Description
<b>STEPNAME</b>	STEPNAME	8	Step name (fixed field)
<b>PROCS</b>	ProcStep	8	Procedure step name
<b>PGMNAME</b>	Pgm-Name	8	Program name
<b>RETCODE</b>	Step-CC	10	Step completion code



Table 56. Columns on the JS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>STEPNUM</b>	StepNum	5	Step number
<b>ABENDRSN</b>	AbendRsn	8	Abend reason
<b>ELAPSED</b>	Elapsed	11	Elapsed time for the step (SMF)
<b>CPUTIME</b>	CPU-Time	11	Total CPU time used by this step (SMF)
<b>SRBTIME</b>	SRB-Time	11	Total SRB time used by this step (SMF)
<b>EXCP</b>	EXCP-Cnt	10	Total EXCP count (SMF)
<b>CONN</b>	Conn	11	Total device connect time (SMF)
<b>SERV</b>	Serv	10	Total service units (SMF)
<b>WORKLOAD</b>	Workload	8	Workload name (SMF)
<b>PAGE</b>	Page	10	Number of pages paged in/out from auxiliary storage (SMF)
<b>SWAP</b>	Swap	10	Pages swapped in from auxiliary storage to central (SMF)
<b>VIO</b>	VIO	10	Number of VIO page-ins and page-outs for this step (SMF)
<b>SWAPS</b>	Swaps	10	Number of address space swap sequences (SMF)
<b>REGION</b>	Region	8	REGION for this step (SMF)
<b>REGIONU</b>	Rgn-Used	8	Amount of private storage used (high-water mark) (SMF)
<b>MEMLIMIT</b>	MemLimit	8	MEMLIMIT for this step (SMF)
<b>MEMLIMU</b>	MLim-Used	9	Amount of 64-bit private storage used (high-water mark) (SMF)
<b>SYSNAME</b>	SysName	8	The system name of the system on which the step ran
<b>BEGINIME</b>	Step-Begin	22	Step Begin Time
<b>ENDTIME</b>	Step-End	22	Step End time
<b>ZIIPTIME</b>	zIIP-Time	9	Total time spent on zIIP (SMF)
<b>ZIIPCPTM</b>	zICP-Time	9	Eligible zIIP time spent on CP (SMF)
<b>ZIIPNTIM</b>	zIIP-NTime	10	Normalized zIIP time (SMF)
<b>HICPUPCT</b>	HiCPU%	6	Largest percentage of CPU time used by any task in this address space, rounded to the nearest integer, as reported by interval records associated with this step
<b>HICPUPGM</b>	HiCPUPgm	8	Program name associated with the HiCPU% value
<b>TIOTHWM</b>	TIOTHWM	7	High water mark for TIOT entries used (bytes, SMF).
<b>TIOTUSED</b>	TIOTUsed	8	Current TIOT space used for entries (bytes). Applies only to interval records (SMF).
<b>TIOTAVAIL</b>	TIOTAvail	9	Size of TIOT available for entries (bytes, SMF).

Table 56. Columns on the JS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job Tasks panel (JT)

The Job Tasks panel shows the TCBs and RBs for an address space.

You access the Job Tasks panel using the JT action character from the DA or AS panel.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 57. Columns on the JT Panel

Column name	Title (Displayed)	Width	Description
<b>TCBADDR</b>	TCB	24	TCB address formatted based on task level for as many levels that fit. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>RB</b>	RB	8	RB address
<b>TYPE</b>	Type	8	RB type
<b>PROGRAM</b>	Program	8	Module associated with TCB
<b>STORAGE</b>	Storage	7	TCB storage in bytes
<b>FREESTOR</b>	FreeStor	8	TCB free storage in bytes
<b>CPUTIME</b>	CPU-Time	10	CPU time (seconds)
<b>TCBCMP</b>	TCBCMP	8	TCB completion code
<b>TCBFLAGS</b>	TCBFlags	8	TCB flags (TCBFLGS1 through TCBFLGS8)
<b>INTCOD</b>	IntC	4	Interrupt code from RBINTCOD
<b>STCB</b>	STCB	8	Secondary TCB address
<b>XSB</b>	XSB	8	XSB address
<b>OPSW</b>	OPSW	17	Old PSW from RB
<b>ASID</b>	ASID	5	Address space identifier
<b>ASIDX</b>	ASIDX	5	Address space identifier in hexadecimal
<b>TCB</b>	TCBPtr	8	TCB address (hexadecimal)
<b>LEVEL</b>	Level	5	TCB or RB level
<b>JNAME</b>	JobName	8	Job name
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of operating system

Table 57. Columns on the JT Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Job 0 (J0)

The Job 0 panel allows the user to display information about SYSOUT data sets for a JES3 job 0.

The values for all the columns are obtained from the spool data set.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 58. Columns on the J0 Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	DSPNAME	8	DSP that created the data. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>DSID</b>	DSID	4	Data set ID number
<b>OWNERID</b>	Owner	8	User ID of SYSIN/SYSOUT owner, or default values of ++++++++ or ????????, if user ID not defined to RACF 1.9 and later
<b>OCLASS</b>	C	1	JES3 output class
<b>COPYCNT</b>	CC	2	Data set copy count
<b>PRMODE</b>	PrMode	8	Data set process mode
<b>BURST</b>	Burst	5	Data set burst indicator
<b>FORMS</b>	Forms	8	Output form number
<b>FCBID</b>	FCB	4	Output FCB ID
<b>UCSID</b>	UCS	4	Output UCS ID
<b>WTRID</b>	Wtr	8	External writer name
<b>FLASHID</b>	Flash	5	Output flash ID
<b>FLASHC</b>	FlashC	6	Flash copies
<b>SEGID</b>	SegID	5	Data set segment number
<b>CHARS</b>	Chars	21	Character arrangement table names
<b>CPYMOD</b>	CpyMod	8	Copy modification module name
<b>QUEUE</b>	Queue	5	Queue the data set is on (TCP, BDT, HOLD, WTR)
<b>DESTN</b>	Dest	18	SYSOUT destination
<b>SECLABEL</b>	SecLabel	8	Security label
<b>DSDATE</b>	CrDate-CrTime	19	Data set creation date and time, or, if ***** N/A *****, the creation date and time were not available.
<b>SPIN</b>	Spin	4	Indicates whether this is a spin data set

Table 58. Columns on the JO Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>SELECT</b>	Sel	3	Indicates whether the data set is selectable
<b>RECCNT</b>	Rec-Cnt	7	Data set record count
<b>PAGECNT</b>	Page-Cnt	8	Data set page count. Blank if not page-mode data.
<b>BYTECNT</b>	Byte-Cnt	8	Data set byte count
<b>RECFM</b>	RecFm	5	Record format
<b>DDNAME</b>	DDName	8	DD name
<b>DSNAME</b>	DSName	44	Data set name
<b>STEPN</b>	StepName	8	Job step that created the SYSOUT
<b>PROCS</b>	ProcStep	8	Procedure step that created the SYSOUT
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Lines panel (LI)

The Lines panel allows the user to display information about JES lines and their associated transmitters and receivers.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 59. Columns on the LI Panel

Column name	Title (Displayed)	Width	Description
<b>DEVNAME</b>	DEVICE	12	Device name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	8	Line status
<b>UNIT</b>	Unit	5	Line address or type
<b>NNODE</b>	Node	8	Node that the line is connected to
<b>JNAME</b>	JobName	8	Job name
<b>JOBID</b>	JobID	8	JES job ID
<b>JTYPE</b>	JType	5	Type of address space
<b>JNUM</b>	JNum	6	JES job number
<b>OWNERID</b>	Owner	8	User ID of owner
<b>RECPRT</b>	Proc-Lines	10	Number of lines processed for the job.
<b>RECCNT</b>	Tot-Lines	10	Number of lines in the job.
<b>TYPE</b>	Type	4	Type of line
<b>LINELIM</b>	Line-Limit	13	Line limit for the line (JES2 only)
<b>PAGELIM</b>	Page-Limit	13	Page limit for the line (JES2 only)

Table 59. Columns on the LI Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>PRTWS</b>	Work-Selection	14	Line work selection criteria (JES2 only)
<b>SESSION</b>	Session	8	Session name (JES2 only)
<b>TOTERRS</b>	Tot-Errs	8	Error count (JES2 only)
<b>AUTODISC</b>	ADisc	5	Line disconnect option
<b>CODE</b>	Code	4	BSC adaptor code
<b>COMPRESS</b>	Comp	4	BSC data compression option
<b>APPLID</b>	ApplID	8	Application name for NJE line (JES2 only)
<b>DUPLEX</b>	Duplex	6	BSC line mode
<b>INTERFAC</b>	Intf	4	BSC adapter interface
<b>LINECCHR</b>	LineCChr	8	BSC line control characters configuration (JES2 only)
<b>LOG</b>	Log	3	Message logging option (JES2 only)
<b>REST</b>	Rest	4	Resistance rating of line (JES2 only)
<b>SPEED</b>	Speed	5	Speed of the line
<b>PTRACE</b>	Tr	3	Trace I/O option
<b>TRANSPAR</b>	Transp	6	BSC transparency feature
<b>PSWD</b>	Password	8	Password
<b>DISC</b>	Discon	9	Disconnect status: NO, INTERRUPT, or QUIESCE (only for active lines).
<b>RMTSHR</b>	RmtShr	6	Indicates whether the line is allowed to be dedicated (JES2 only)
<b>JRNUM</b>	JRNum	7	Job receivers associated with the line, either a count or D, for default (JES2 only)
<b>JTNUM</b>	JTNum	7	Job transmitters associated with the line, either a count or D, for default (JES2 only)
<b>SRNUM</b>	SRNum	7	SYSOUT receivers associated with the line, either a count or D, for default (JES2 only)
<b>STNUM</b>	STNum	7	SYSOUT transmitters associated with the line, either a count or D, for default (JES2 only)
<b>SYSNAME</b>	SysName	8	System Name
<b>DSYSID</b>	SysID	5	JES2 member name (JES2 only)
<b>JESNAME</b>	JESN	4	JES subsystem name
<b>JESLEVEL</b>	JESLevel	8	z/OS JES2 level
<b>DEVSECLB</b>	DSecLabel	9	Security label of the device (JES2 only)
<b>SOCKETN</b>	SocketN	8	Socket name (JES2 only)
<b>IPADDR</b>	IPAddr	24	IP address (JES2 only)
<b>IPNAME</b>	IPName	32	IP name (JES2 only)

Table 59. Columns on the LI Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>PORT</b>	Port	5	TCP/IP port number (JES2 only)
<b>PORTNAME</b>	PortName	8	TCP/IP port name. Blank if a port number has been set explicitly. (JES2 only)
<b>SECURE</b>	Secure	6	Secure socket (JES2 only)
<b>NSNAME</b>	NSName	8	Network server name (JES2 only)
<b>ANODE</b>	ANode	8	Adjacent node (JES2 only)
<b>LINELIML</b>	Line-Lim-Lo	11	Line limit, minimum (JES2 only)
<b>LINELIMH</b>	Line-Lim-Hi	11	Line limit, maximum (JES2 only)
<b>PAGELIML</b>	Page-Lim-Lo	11	Page limit, minimum (JES2 only)
<b>PAGELIMH</b>	Page-Lim-Hi	11	Page limit, maximum (JES2 only)
<b>CTRACE</b>	CTr	3	Common tracing (JES2 only)
<b>VTRACE</b>	VTr	3	Verbose tracing (JES2 only)
<b>JTRACE</b>	JTr	3	JES tracing (JES2 only)
<b>CONNECT</b>	Connect	7	Connect line automatically (JES2 only)
<b>CTIME</b>	Conn-Int	10	Connection interval in minutes (JES2 only)
<b>RESTART</b>	Restart	8	Restart line automatically (JES2 only)
<b>RTIME</b>	Rest-Int	10	Restart interval, in minutes (JES2 only)
<b>SODISP</b>	SODsp	5	Selection output disposition 1 (JES2 only)
<b>SODISP2</b>	SODsp2	5	Selection output disposition 2 (JES2 only)
<b>SODISP3</b>	SODsp3	5	Selection output disposition 3 (JES2 only)
<b>SODISP4</b>	SODsp4	5	Selection output disposition 4 (JES2 only)
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

Notes on the table:

1. JNUM is not included in the default field list.

## Link List sets panel (LLS)

The LLS panel displays link list sets that are defined in the sysplex. Only data sets in the current link list set are shown.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 60. Columns on the LLS Panel

Column name	Title (Displayed)	Width	Description
<b>SETNAME</b>	NAME	4	Link list set name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.

Table 60. Columns on the LLS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>STATUS</b>	Status	16	Link list status
<b>NUMASID</b>	NumASID	7	Number of address spaces using link list set
<b>NUMDATASETS</b>	NumDataSets	11	Number of data sets in the link list set
<b>LLA</b>	LLA	3	Link list lookaside managed link list set (YES or NO)
<b>SEQ</b>	Seq	3	Sequence number
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	System level
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Link List panel (LNK)

The LNK panel displays the data sets in the link list (lnklst) for each system in the sysplex. Only data sets in the current lnklst set are shown.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 61. Columns on the LNK Panel

Column name	Title (Displayed)	Width	Description
<b>DSNAME</b>	DSNAME	13-44 (Varies based on longest name.)	Data set name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SEQ</b>	Seq	3	Sequence number
<b>VOLSER</b>	VolSer	6	Volume serial
<b>BLKSIZE</b>	BlkSize	7	Data set block size
<b>EXTENT</b>	Extent	6	Number of extents
<b>SMS</b>	SMS	3	SMS indicator. YES if the data set is SMS managed. Otherwise, NO.
<b>APF</b>	APF	3	APF indicator. YES if the data set is APF authorized. Otherwise, NO.
<b>LRECL</b>	LRecl	5	Logical record length
<b>DSORG</b>	DSOrg	5	Data set organization
<b>RECFM</b>	RecFm	5	Record format
<b>CRDATE</b>	CrDate	8	Data set creation date
<b>REFDATE</b>	RefDate	8	Data set last referenced date
<b>SETNAME</b>	SetName	16	Link list set name

Table 61. Columns on the LNK Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Operating system level
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Link Pack Area panel (LPA)

The LPA panel shows the data sets in the link pack area (LPA) for each system in the sysplex.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 62. Columns on the LPA Panel

Column name	Title (Displayed)	Width	Description
<b>DSNAME</b>	DSNAME	13-44 (Varies based on longest name.)	Data set name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SEQ</b>	Seq	3	Sequence number
<b>VOLSER</b>	VolSer	6	Volume serial
<b>BLKSIZE</b>	BlkSize	7	Data set block size
<b>EXTENT</b>	Extent	6	Number of extents
<b>SMS</b>	SMS	3	SMS indicator. YES if the data set is SMS managed. Otherwise, NO.
<b>APF</b>	APF	3	APF indicator: YES if the data set is APF authorized. Otherwise, NO.
<b>LRECL</b>	LRecL	5	Logical record length
<b>DSORG</b>	DSOrg	5	Data set organization
<b>RECFM</b>	RecFm	5	Record format
<b>CRDATE</b>	CrDate	8	Data set creation date
<b>REFDATE</b>	RefDate	8	Data set last referenced date
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Operating system level

## Link Pack Directory panel (LPD)

The Link Pack Directory (LPD) panel shows details of the modules in the link pack area.



Rows representing major names (that is, non-alias names) are highlighted. You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the pattern of the module name.

This panel uses the SYSNAME value to control which systems are shown on the panel.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 63. Columns on the Link Pack Directory Panel

Column name	Title (Displayed)	Width	Description
<b>MODNAME</b>	MODNAME	8	Module name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>MAJOR</b>	Major	8	Major name when name is an alias.
<b>MODEPA</b>	EPA	17	Entry point address.
<b>MODLOADPT</b>	LoadPt	17	Load point address.
<b>LOCATION</b>	Location	16	Module location.
<b>MODSIZE</b>	ModLen	8	Module length if available.
<b>TYPE</b>	Type	7	Link pack directory type.
<b>AUTHCOD</b>	AC	2	Authorization code.
<b>AMODE</b>	AM	2	Address mode (amode).
<b>APF</b>	APF	3	APF authorization (yes or no).
<b>SEQ</b>	Seq	5	Search sequence number.
<b>SYSNAME</b>	SysName	8	System name.
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Multi-Access Spool panel (MAS) and JESPLEX (JP) panel

The Multi-Access Spool (MAS) panel simplifies the display and control of members in a JES2 MAS. The analogous JES3 JESPLEX panel simplifies the display and control of members in a JES3 JESPLEX. They share a single field list.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 64. Columns on the MAS and JP Panel

Column name	Title (Displayed)	Width	Panel	Description
<b>NAME</b>	NAME	4 (JES2) 8 (JES3)	MAS, JP	Member name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	12	MAS, JP	Member status
<b>SYSID</b>	SID	3	MAS	The system ID number

Table 64. Columns on the MAS and JP Panel (continued)

Column name	Title (Displayed)	Width	Panel	Description
<b>PREVCKPT</b>	PrevCkpt	8	MAS	Number of seconds elapsed since the previous checkpoint (ss.hh format)
<b>CKPTHOLD</b>	Hold	8	MAS	Checkpoint hold in hundredths of seconds
<b>ACTHOLD</b>	ActHold	8	MAS	Actual checkpoint hold in hundredths of seconds
<b>DORMANCY</b>	Dormancy	11	MAS	Checkpoint dormancy (minimum,maximum). Format in hundredths of seconds.
<b>ACTDORM</b>	ActDorm	7	MAS	Actual checkpoint dormancy in hundredths of seconds
<b>SYNCTOL</b>	SyncTol	7	MAS	Checkpoint synchronization tolerance in seconds
<b>SYSMODE</b>	Ind	3	MAS	Independent mode
<b>RSYSID</b>	RSID	4	MAS	Name of member performing a \$ESYS
<b>SYSNAME</b>	SysName	8	MAS, JP	System name of the MVS image on which this JES system is active
<b>VERSION</b>	Version	8	MAS, JP	JES version the system is running
<b>LASTCKPT</b>	Last-Checkpoint	22	MAS	Last date and time checkpoint was taken
<b>COMCHAR</b>	C	1 (JES2) 8 (JES3)	MAS, JP	Command character
<b>JESNAME</b>	JESN	4	MAS, JP	JES subsystem name
<b>SLEVEL</b>	SLevel	6	MAS, JP	JES service level
<b>BOSS</b>	Boss	4	MAS	Indicates if this member is a manager or "boss" of WLM service class queues
<b>GLOBAL</b>	Global	6	JP	JES3 Global member indicator
<b>COMMAND</b>	Command	8	MAS	Command in progress
<b>TYPE</b>	Start-Type	18	MAS, JP	Last start type for the member
<b>DATEE</b>	Start-Date-Time	19	MAS, JP	Date and time the member was started
<b>LASTGCON</b>	LastGCon-Date-Time	18	JP	Last time the global was contacted
<b>PTRACK</b>	PrimTG	6	JP	Primary track group allocation
<b>STRACK</b>	SecTG	6	JP	Secondary track group allocation
<b>WTOLIM</b>	WTOLim	6	JP	WTO message limit
<b>WTOINT</b>	WTOInt	6	JP	WTO message interval
<b>PCSALIM</b>	PBufCSA	7	JP	Protected buffer CSA limit

Table 64. Columns on the MAS and JP Panel (continued)

Column name	Title (Displayed)	Width	Panel	Description
<b>PAUXLIM</b>	PBufAux	7	JP	Protected buffer JES3 auxiliary limit
<b>PFIXED</b>	PBufFixed	9	JP	Fixed protected buffers
<b>USRPAGE</b>	UserPages	9	JP	User pages per open SYSOUT dataset
<b>SELMNAME</b>	SelectModeName	14	JP	Selection mode name
<b>SPARTN</b>	PartName	8	JP	Spool partition name
<b>MSGPRF</b>	MsgPrefix	11	JP	Message prefix
<b>MSGDEST</b>	MsgDest	7	JP	Message destination
<b>CONSTAT</b>	ConnStat	13	JP	Connect status
<b>ATTSTAT</b>	AttStat	11	JP	Attach status
<b>CKPTLEV</b>	CkptLevel	9	MAS, JP	JES2 checkpoint level (\$ACTIVATE level).
<b>ISFEND</b>	.END	4	MAS, JP	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Memory contents panel (MEM)

The Memory contents (MEM) panel allows authorized users to browse the memory contents for any address space within the sysplex, including common storage and 64-bit memory objects.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 65. Columns on the MEM Panel

Column name	Title (Displayed)	Width	Description
<b>ADDRESS</b>	ADDRESS	7	The memory address. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>OFFSET</b>	Off	4	Offset from the starting address in hexadecimal
<b>CONTENTS</b>	Contents	35	Memory contents in hexadecimal
<b>EBCDIC</b>	EBCDIC	16	The EBCDIC character translation of storage for the row
<b>KEY</b>	Key	3	The storage protection key
<b>FPROT</b>	FProt	5	Whether the storage is fetch protected
<b>ASCII</b>	ASCII	16	The ASCII character translation of storage for the row
<b>JNAME</b>	JobName	8	The job name of the current ASID whose memory is shown
<b>ASID</b>	ASID	5	Address space identifier in decimal
<b>ASIDX</b>	ASIDX	5	Address space identifier in hexadecimal

Table 65. Columns on the MEM Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>SYSNAME</b>	SysName	8	The system name where the memory contents were gathered
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Network Activity panel (NA)

The Network Activity (NA) panel allows authorized users to show all TCP/IP activity for all stacks in the system.

When JESplex scoping is in effect, the NA panel returns data only for those systems that are in the same JESplex as the user.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 66. Columns on the NA Panel

Column name	Title (Displayed)	Width	Description
<b>JNAME</b>	JOBNAME	8	Job name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	8	Status
<b>IPADDR</b>	IPAddr	24	IP address
<b>PORT</b>	Port	5	Port number
<b>INBUFSZ</b>	InBufSz	7	Receive buffer size
<b>OUTBUFSZ</b>	OutBufSz	8	Send buffer size
<b>EXCPCT</b>	EXCP-Cnt	8	Number of requests
<b>BYTESIN</b>	BytesIn	8	Number of bytes received
<b>BYTESOUT</b>	BytesOut	8	Number of bytes sent
<b>APPL</b>	Appl	8	Application name
<b>LUNAME</b>	LUName	8	Logical unit name
<b>CLIENT</b>	Client	8	Client user ID
<b>APPLDATA</b>	ApplData	40	Application data
<b>STACK</b>	Stack	8	Stack name
<b>ASID</b>	ASID	5	Address space identifier
<b>ASIDX</b>	ASIDX	5	Address space identifier (hexadecimal)
<b>RESID</b>	ResourceID	10	Resource ID
<b>STIME</b>	Start-Time	19	Connection start time
<b>LASTTIME</b>	Last-Time	19	Connection last activity time

Table 66. Columns on the NA Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of operating system
<b>IPADDRLOCAL</b>	IPAddrLocal	24	Local IP address
<b>PORTLOCAL</b>	PortLocal	9	Local port number
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Network Connections (NC)

The Network Connections panel allows the user to display information about JES networking connections to an adjacent node.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 67. Columns on the NC Panel

Column name	Title (Displayed)	Width	Description
<b>DEVNAME</b>	DEVICE	10	Name of the connection, transmitter or receiver. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	8	Device status
<b>TYPE</b>	Type	4	Connection type (SNA, BSC, TCP)
<b>ANODE</b>	ANode	8	Adjacent node
<b>JNAME</b>	Jobname	8	Job name of job being processed
<b>JOBID</b>	JobID	8	JES job ID of job being processed
<b>JTYPE</b>	JType	8	Type of address space being processed
<b>OWNERID</b>	Owner	8	User ID of job creator
<b>RECPRT</b>	Proc-Lines	10	Number of lines processed for the job
<b>RECCNT</b>	Tot-Lines	10	Number of lines in the job
<b>LINE</b>	Line	5	Number of line to use (JES2 only)
<b>UNIT</b>	Unit	5	Unit associated with line
<b>JRNUM</b>	JRNum	5	Job receiver count
<b>JTNUM</b>	JTNum	5	Job transmitter count
<b>SRNUM</b>	SRNum	5	SYSOUT receiver count
<b>STNUM</b>	STNum	5	SYSOUT transmitter count
<b>CONNECT</b>	Connect	7	Connect automatically (JES2 only)
<b>CTIME</b>	Conn-Int	8	Connection interval (JES2 only)
<b>PTRACE</b>	Tr	3	Tracing (JES2 only)

Table 67. Columns on the NC Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>CTRACE</b>	CTr	3	Common tracing
<b>JTRACE</b>	JTr	3	JES tracing
<b>VTRACE</b>	VTr	3	Verbose tracing
<b>LOGMODE</b>	LogMode	8	Logon mode table entry (JES2 only)
<b>REST</b>	Rest	5	Resistance of the connection (JES2 only)
<b>COMPACT</b>	Compact	8	Compaction table name (JES2 only)
<b>IPADDR</b>	IPAddr	24	IP address (JES2 only)
<b>IPNAME</b>	IPName	32	IP host name
<b>PORT</b>	Port	5	TCP/IP port number
<b>PORTNAME</b>	PortName	16	TCP/IP port name (JES2 only)
<b>SECURE</b>	Secure	6	Secure (TLS) connection
<b>LOGON</b>	Logon	5	Number of the associated LOGON device (JES2 only)
<b>NETSRV</b>	Netsrv	5	Number of the associated NETSRV device (JES2 only)
<b>RELCONN</b>	RelConn	8	Related connection name
<b>SRVNAME</b>	SrvName	10	Name of the associated server device
<b>DSECLABEL</b>	DSecLabel	9	Security label of the adjacent node (JES2 only)
<b>SYSNAME</b>	SysName	8	System name
<b>DSYSID</b>	SysID	5	JES2 member name (JES2 only)
<b>JESNAME</b>	JESN	4	JES subsystem name
<b>JESLEVEL</b>	JESLevel	8	z/OS JES version and release
<b>PRTWS</b>	Work-Selection	14	Work selection criteria (JES2, transmitters and receivers)
<b>LINELIM</b>	Line-Limit	13	Line limit for selection (JES2, transmitters and receivers)
<b>PAGELIM</b>	Page-Limit	13	Page limit for selection (JES2, transmitters and receivers)
<b>LINELIML</b>	Line-Lim-Lo	11	Line limit, minimum (JES2 only)
<b>LINELIMH</b>	Line-Lim-Hi	11	Line limit, maximum (JES2 only)
<b>PAGELIML</b>	Page-Lim-Lo	11	Page limit, minimum (JES2 only)
<b>PAGELIMH</b>	Page-Lim-Hi	11	Page limit, maximum (JES2 only)
<b>SODISP</b>	SODsp	5	Selection output disposition (JES2 only)
<b>SODISP2-4</b>	SODsp2-4	6	Selection output disposition 2-4 (JES2 only)
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Network Servers (NS)

The Network Servers panel allows the user to display information about JES server-type networking devices on the node.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 68. Columns on the NS Panel

Column name	Title (Displayed)	Width	Description
<b>DEVNAME</b>	DEVICE	10	Name of the network server. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	8	Device status
<b>DSPNAME</b>	DSPName	8	Dynamic support program name (JES3 only)
<b>APPL</b>	Appl	8	Application name (JES2 only)
<b>SOCKET</b>	Socket	8	Socket name (JES2 only)
<b>STACK</b>	Stack	8	Name of the TCP/IP stack
<b>RESTART</b>	Restart	8	Restart the device automatically (JES2 only)
<b>RTIME</b>	Rest-Int	10	Restart interval (minutes) (JES2 only)
<b>PTRACE</b>	Tr	3	Tracing (JES2 only)
<b>CTRACE</b>	CTr	3	Common tracing
<b>VTRACE</b>	VTr	3	Verbose tracing
<b>JTRACE</b>	JTr	3	JES tracing
<b>LOG</b>	Log	3	Log activity (JES2 only)
<b>ASID</b>	ASID	5	ASID of the network server
<b>SRVJOBNM</b>	SrvJobNm	8	Job name of the network server address space
<b>PASSWORD</b>	Password	8	Password (SET or NOTSET) (JES2 only)
<b>IPNAME</b>	IPName	32	Local TCP/IP host name
<b>PORT</b>	Port	5	Local TCP/IP port number
<b>PORTNAME</b>	PortName	16	Local TCP/IP port name (JES2 only)
<b>SECURE</b>	Secure	6	Secure (TLS) socket
<b>SYSNAME</b>	SysName	8	System name
<b>DSYSID</b>	SysID	5	JES2 member name (JES2 only)
<b>JESNAME</b>	JESN	4	JES subsystem name
<b>JESLEVEL</b>	JESLevel	8	z/OS JES level
<b>DEVSECLB</b>	DSecLabel	9	Security label of the device (JES2 only)
<b>NSECURE</b>	NSecure	10	Netserv secure option (required, optional, use_socket)

Table 68. Columns on the NS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Nodes panel (NO)

The Nodes panel allows the user to display information about JES nodes.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 69. Columns on the NO Panel

Column name	Title (Displayed)	Width	Description
<b>NUMBER</b>	NUMBER	5	Node number (JES2 only). For JES2, this is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>NODENAME</b>	NodeName	8	Node name. For JES3, this is the fixed field, and is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	21	Node status. By default, this shows status for the first path. Increase the width (up to 43) to show the status for the second path.
<b>AUTH</b>	Authority	17	Authority of the node (JES2 only)
<b>TRANS</b>	Trans	6	What the local node transmits to the specified node (JES2 only)
<b>RECV</b>	Recv	6	What the local node receives from the specified node (JES2 only)
<b>HOLD</b>	Hold	4	Job hold indicator for the local node
<b>NETHOLD</b>	NHold	5	Process inbound SYSOUT in NETDATA format (JES3 only)
<b>PENCRYPT</b>	PEn	3	Password encryption indicator (JES2 only)
<b>ENDNODE</b>	End	3	Eligibility for store-and-forward operations (JES2 only)
<b>RESIST</b>	Rest	4	Resistance rating of the connection (JES2 only)
<b>SENTREST</b>	SentRs	6	Whether the resistance from an adjacent node is used in calculating the resistance of an adjacent connection (JES2 only)
<b>COMPACT</b>	Cp	2	Compaction table number for outbound compaction when communicating with this node (JES2 only)
<b>LINE</b>	Line	4	Line dedicated to the NJE session for with this application (JES2 only)
<b>LNAME</b>	LineName	8	Line dedicated to NJE for this node (JES3 only)



Table 69. Columns on the NO Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>LOGMODE</b>	LogMode	8	Logon mode table entry for this application (JES2 only)
<b>PATHMGR</b>	PMg	3	Indicator of whether NCC records relevant to the path manager should be sent to this node (JES2 only)
<b>PRIVATE</b>	Prv	3	Private indicator for the connection between this node and an adjacent node (JES2 only)
<b>SUBNET</b>	Subnet	8	Name of the subnet that should include this node (JES2 only)
<b>NTRACE</b>	Tr	3	Trace option (JES2 only)
<b>VERIFYP</b>	VerifyP	8	Password received from the node
<b>SENDP</b>	SendP	8	Password sent to the node
<b>LOGON</b>	Logon	5	Number of the local logon DCT (1-999) which should be use when specifying connections to the application. The default value of 0 indicates that the logon DCT defined with the lowest number is to be. (JES2 only)
<b>SYSNAME</b>	SysName	8	System name
<b>DSYSID</b>	SysID	5	JES2 member name (JES2 only)
<b>JESNAME</b>	JESN	4	JES subsystem name
<b>JESLEVEL</b>	JESLevel	8	JES version and release
<b>NETSRV</b>	NetSrv	6	Network server number (JES2 only)
<b>DEVSECLB</b>	DSecLabel	9	Security label of the device (JES2 only)
<b>MAXRETR</b>	MaxRetries	6	Number of retries to attempt before ending the BSC NJE line (JES3 only)
<b>PATH</b>	Path	8	Name of the adjacent node in the path (JES3 only)
<b>PTYPE</b>	PType	5	Protocol type (JES3 only)
<b>BDTNAME</b>	BDTName	8	Bulk Data Transfer (BDT) ID (JES3 only)
<b>PARTNAM</b>	PartName	8	Name of the spool partition to which JES3 writes spool data for all jobs from that node (JES3 Only)
<b>MAXLINES</b>	MaxLines	3	Maximum number of lines for the node. (JES3 Only)
<b>DIRECT</b>	Direct	6	Specifies whether the node can be directly attached only
<b>SSIGNON</b>	SSignon	7	Specifies whether secure signon protocol is to be used
<b>JTNUM</b>	JTNum	5	Number of job transmitters associated with the TCP/IP node (JES3 only)
<b>JRNUM</b>	JRNum	5	Number of job receivers associated with the TCP/IP node (JES3 only)
<b>STNUM</b>	STNum	5	Number of SYSOUT transmitters associated with the TCP/IP node (JES3 only)

Table 69. Columns on the NO Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>SRNUM</b>	SRNum	5	Number of SYSOUT receivers associated with the TCP/IP node (JES3 only)
<b>SECURE</b>	Secure	6	Use secure (TLS) socket (JES3 only)
<b>PWCNTL</b>	PwCntl	8	Password encryption control (JES3 only)
<b>XNAMEREQ</b>	XNameReq	8	Specifies whether inbound SYSOUT can be held for processing by an external writer if no external writer name was supplied (JES3 only)
<b>CONNECT</b>	Connect	7	Automatically connect (JES2) or reconnect (JES3)
<b>CTIME</b>	Conn-int	8	Connection interval (minutes)
<b>BUFSIZE</b>	BufSz	5	Buffer size (JES3 only)
<b>STREAM</b>	Strm	4	Number of concurrent streams (JES3 only)
<b>PRTDEF</b>	PrtDef	8	Print class default for networking output received at the home node (JES3 only)
<b>PRTTSO</b>	PrtTSO	8	TSO data set default class for networking output received at the home node (JES3 only)
<b>PRTXWTR</b>	PrtXwtr	8	External writer data set default class for networking output received at the home node (JES3 only)
<b>PUNDEF</b>	PunDef	8	Punch class default for networking output received at the home node (JES3 only)
<b>NETPR</b>	NetPr	5	Number of logical network printers on the home node (JES3 only)
<b>NETPU</b>	NetPu	5	Number of logical network punches on the home node (JES3 only)
<b>CTCNODE</b>	CTC	5	Channel to channel node (JES3 only)
<b>VFYPATH</b>	VfyPath	7	Verify path (JES2 only)
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## OMVS options panel (BPXO)

The OMVS options (BPXO) panel shows the Unix system services (USS) options that are in effect.

**Note:** You access the panel with the **BPXO** command because SDSF interprets the OMVS command as the output panel (O) with classes M, V, and S.

You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the pattern of the USS option.

This panel uses the SYSNAME value to control which systems are shown on the panel.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 70. Columns on the OMVS Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	16	USS option name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>NUMVALUE</b>	NumericValue	12	Option value when format is numeric
<b>VALUE</b>	Value	32	Option value when format is character (up to a maximum of 127 characters). For the MAXFILESIZE option, any value greater than 522248 indicates there is NOLIMIT.
<b>STATUS</b>	Status	8	Additional status related to option
<b>SYSNAME</b>	SysName	8	System name where console is active
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command

## Output Queue panel (O)

The Output Queue panel allows the user to display information about SYSOUT data sets for jobs, started tasks, and TSO users on any *nonheld* JES output queue.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 71. Columns on the O Panel

Column name	Title (Displayed)	Width	Description	Delay
<b>JNAME</b>	JOBNAME	8	Job name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.	
<b>JNUM</b>	JNum <sup>1</sup>	6	JES job number	
<b>JOBID</b>	JobID	8	JES job ID or work ID	
<b>OWNERID</b>	Owner	8	User ID of SYSIN/SYSOUT owner, or default values of ++++++++ or ????????, if user ID not defined to RACF	
<b>DPRIO</b>	PrtY	4	JES output group priority	
<b>OCLASS</b>	C	1	JES output class	
<b>FORMS</b>	Forms	8	Output form number	
<b>DESTN</b>	Dest	18	JES print destination name	
<b>RECCNT</b>	Tot-Rec	9	Output total record count (lines). Blank for page-mode data.	
<b>RECPRT</b>	Prt-Rec	9	The number of lines printed. Blank for page-mode data. (JES2 only)	
<b>PAGECNT</b>	Tot-Page	9	Output page count. Blank if not for page-mode data.	

Table 71. Columns on the O Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>PAGEPRT</b>	Prt-Page	9	Output pages printed. Blank if not for page-mode data. (JES2 only)	
<b>DEVID</b>	Device	18	Output device name (only if it is printing)	
<b>STATUS</b>	Status	11	JES job status	
<b>SECLABEL</b>	SecLabel	8	Security label of output group	
<b>DSYSID</b>	SysID	5	System on which the output is printing (only if it is printing) (JES2 only)	
<b>DEST</b>	Rmt	5	JES2 print routing. Remote number if routing is not local. (JES2 only)	
<b>NODE</b>	Node	5	JES2 print node (JES2 only)	
<b>OGNAME</b>	O-Grp-N	8	Output group name (JES2 only)	
<b>OGID</b>	OGID1	5	Output group ID 1 (JES2 only)	
<b>OGID2</b>	OGID2	5	Output group ID 2 (JES2 only)	
<b>JPRIO</b>	JP	2	JES job priority	
<b>FCBID</b>	FCB	4	Output FCB ID	
<b>UCSID</b>	UCS	4	Output UCS ID (print train required)	
<b>WTRID</b>	Wtr	8	Output external writer name	
<b>FLASHID</b>	Flash	5	Output flash ID	
<b>BURST</b>	Burst	5	3800 burst indicator	
<b>PRMODE</b>	PrMode	8	Printer process mode	
<b>OUTDISP</b>	ODisp	5	JES2 output disposition	
<b>DSDATE</b>	CrDate	10	Output creation date. Length can be changed to 19 to produce the date and time. (JES2 only)	
<b>OHREASON</b>	OHR	3	Output hold reason code	
<b>OHRSTXT</b>	Output-Hold-Text	37	Output hold reason text	
<b>OFFDEVS</b>	Offs	4	List of offload devices for a job or output that has been offloaded (JES2 only)	
<b>RETCODE</b>	Max-RC	10	Return code information for the job	
<b>JTYPE</b>	Type	4	Type of address space	
<b>ROOMN</b>	RNum	8	JES2 job room number	X
<b>PNAME</b>	Programmer-Name	20	JES programmer name field	X
<b>ACCTN</b>	Acct	4 (JES2) 8 (JES3)	JES account number	X
<b>NOTIFY</b>	Notify	8	TSO user ID from NOTIFY parameter on job card	X

Table 71. Columns on the O Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>ISYSID</b>	ISys	4 (JES2) 8 (JES3)	JES input system ID	X
<b>TIMER</b>	Rd-Time	8	Time that the job was read in. In the SDSF task of z/OSMF, this is replaced by the Rd-DateTime column.	X
<b>DATER</b>	Rd-Date	8	Date that the job was read in. In the SDSF task of z/OSMF, this is replaced by the Rd-DateTime column.	X
<b>ESYSID</b>	ESys	4 (JES2) 8 (JES3)	JES execution system ID	X
<b>TIMEE</b>	St-Time	8	Time that execution began. In the SDSF task of z/OSMF, this is replaced by the St-DateTime column.	JES3 only.
<b>DATEE</b>	St-Date	8	Date that execution began. In the SDSF task of z/OSMF, this is replaced by the St-DateTime column.	JES3 only.
<b>TIMEN</b>	End-Time	8	Time that execution ended. In the SDSF task of z/OSMF, this is replaced by the End-DateTime column.	X
<b>DATEN</b>	End-Date	8	Date that execution ended. In the SDSF task of z/OSMF, this is replaced by the End-DateTime column.	X
<b>ICARDS</b>	Cards	5	Number of cards read for job	X
<b>JCLASS</b>	JC	1 or 8	JES input job class. Default width expands to 8 if there are long class names in the MAS.	
<b>MCLASS</b>	MC	2	Message class of job	X
<b>SUBGROUP</b>	SubGroup	8	Submitter group	X
<b>JOBACCT1</b>	JobAcct1 <sup>1</sup>	20	Job accounting field 1	X
<b>JOBACCT2</b>	JobAcct2 <sup>1</sup>	20	Job accounting field 2	X
<b>JOBACCT3</b>	JobAcct3 <sup>1</sup>	20	Job accounting field 3	X
<b>JOBACCT4</b>	JobAcct4 <sup>1</sup>	20	Job accounting field 4	X
<b>JOBACCT5</b>	JobAcct5 <sup>1</sup>	20	Job accounting field 5	X
<b>JOBCORR</b>	JobCorrelator	32	User portion of the job correlator (JES2 only)	
<b>DATETIMER</b>	Rd-DateTime	19	Date and time that the job was read in. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the Rd-Date and Rd-Time columns.	X
<b>DATETIMEE</b>	St-DateTime	19	Date and time that execution began. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the St-Date and St-Time columns.	X

Table 71. Columns on the O Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>DATETIMEN</b>	End-DateTime	19	Date and time that execution ended. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the End-Date and End-Time columns.	X
<b>BERTNUM</b>	BERTNum	7	Number of BERTs used by this JOE (JES2 only)	
<b>JOBCRDATE</b>	JobCrDate	19	Job creation date (JES2 only).	
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.	

Notes on the table:

1. This column is not included in the default field list.

## Page panel (PAG)

The PAG panel shows the paging data sets in use for each system in the sysplex.

**Note:** RMF and the RMF Monitor 1 tasks must be active in order to see rows on the SDSF PAG display. When this requirement is not met, messages HSF0030E and HSF0028E are seen during SDSFAUX initialization.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 72. Columns on the PAG Panel

Column name	Title (Displayed)	Width	Description
<b>DSNAME</b>	DSNAME	13-44 (Varies based on longest name.)	Data set name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>TYPE</b>	Type	6	Type of data set
<b>SLOTS</b>	Slots	8	Number of slots defined
<b>USENUM</b>	Used	8	Number of slots used
<b>USEPCT</b>	Use%	4	Percentage of total slots in use
<b>VOLSER</b>	VolSer	6	Volume serial
<b>STATUS</b>	Status	8	Data set status
<b>VIO</b>	VIO	3	VIO indicator. YES if data set eligible for VIO.
<b>TOTERRS</b>	IOError	7	Number of I/O errors
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Operating system level

Table 72. Columns on the PAG Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>UNIT</b>	Unit	4	Data set unit address
<b>DEVNAME</b>	DevName	8	Data set device name
<b>CUNAME</b>	CUName	8	Data set control unit name
<b>SUBCHAN</b>	SubChanSet	10	Data set subchannel set
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## PARMLIB panel (PARM)

The PARM panel shows the data sets in the PARMLIB concatenation for each system in the sysplex.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 73. Columns on the PARM Panel

Column name	Title (Displayed)	Width	Description
<b>DSNAME</b>	DSNAME	13-44 (Varies based on longest name.)	Data set name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SEQ</b>	Seq	3	Sequence number
<b>VOLSER</b>	VolSer	6	Volume serial
<b>BLKSIZE</b>	BlkSize	7	Data set block size
<b>EXTENT</b>	Extent	6	Number of extents
<b>SMS</b>	SMS	3	SMS indicator. YES if the data set is SMS managed. Otherwise, NO.
<b>LRECL</b>	LRecL	5	Logical record length
<b>DSORG</b>	DSOrg	5	Data set organization
<b>RECFM</b>	RecFm	5	Record format
<b>CRDATE</b>	CrDate	8	Data set creation date
<b>REFDATE</b>	RefDate	8	Data set last referenced date
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Operating system level
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## PC Routines panel (PC)

The PC Routines (PC) panel displays the currently defined system linkage indexes (LX) PC routines.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 74. Columns on the PC Panel

Column name	Title (Displayed)	Width	Description
<b>PCNUM</b>	PCNUM	5	PC number. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>MODULE</b>	Module	8	Module name
<b>EPA</b>	EPA	17	Entry point address
<b>DESC</b>	Description	30	Description
<b>EXECKEY</b>	Key	6	Execution key
<b>SSWITCH</b>	SSwitch	7	Address space switch
<b>AMODE</b>	AMode	5	Addressing mode
<b>ASC</b>	ASC	5	ASC mode
<b>TYPE</b>	Type	8	PC type
<b>MODE</b>	Mode	4	Execution mode
<b>SEQNUM</b>	SeqNumX	8	PC sequence number
<b>LATENTPARM</b>	LatentParm	17	Latent parameter address
<b>AKM</b>	AKM	8	Access key mask
<b>EKM</b>	EKM	8	Execution key mask
<b>PKM</b>	PKM	7	PSW key mask method
<b>EAX</b>	EAX	4	Extended authorization index
<b>SASN</b>	SASN	4	Secondary ASID setting
<b>JNAME</b>	JobName	8	Target job name for PC-ss
<b>ASID</b>	ASIDX	5	Target ASID for PC-ss
<b>LOCATION</b>	Location	16	Module location
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	System level
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Printer panel (PR)

The Printer panel allows the user to display information about JES printers printing job, started task, and TSO user output.

In REXX execs and Java programs, reference columns by name rather than by title.



Table 75. Columns on the PR Panel

Column name	Title (Displayed)	Width	Description	Delay
<b>DEVNAME</b>	PRINTER	10 <sup>1</sup>	Printer name. This is the fixed field. It is ignored in an FLD statement or ISFFLD macro.	
<b>STATUS</b>	Status	8	Printer status	
<b>GROUP</b>	Group	9	Device group (JES3 only)	
<b>SFORMS</b>	SForms	8	Printer selection form number	
<b>SFORM2-8</b>	SForm2-8	8	Printer selection form names (JES2 only)	
<b>SCLASS</b>	SClass	15	Printer output selection classes	
<b>JNAME</b>	JobName	8	Job name	X
<b>JNUM</b>	JNum <sup>2</sup>	6	JES job number	
<b>JOBID</b>	JobID	8	JES job ID or work ID	X
<b>OWNERID</b>	Owner	8	User ID of job owner, or default values of ++ ++++++ or ????????, if user ID not defined to RACF	
<b>RECCNT</b>	Rec-Cnt	7	Number of line-mode records	
<b>RECPRT</b>	Rec-Prt	7	Number of line-mode records printed	
<b>PAGECNT</b>	Page-Cnt	8	Number of output pages	
<b>PAGEPRT</b>	Page-Prt	8	Number of output pages printed	
<b>JPRIO</b>	JP	2	JES job priority	
<b>DPRIO</b>	DP	3	Output data set priority	
<b>OCLASS</b>	C	1	JES output class	
<b>SECLABEL</b>	SecLabel	8	Security label of the output group	
<b>FORMS</b>	Forms	8	Output form number	
<b>FCBID</b>	FCB	4	Output FCB ID	
<b>UCSID</b>	UCS	4	Output UCS ID (print train required)	
<b>WTRID</b>	Writer	8	Output special writer ID or data set ID (JES2 only)	
<b>FLASHID</b>	Flash	5	Output flash ID	
<b>DESTN</b>	Dest	8	JES print destination name (JES2 only)	
<b>BURST</b>	Burst	5	3800 burst indicator	
<b>SEP</b>	Sep	3	Separator page between output groups (JES2 only)	
<b>SEPDS</b>	SepDS	5	Separator page between data sets	
<b>PRMODE</b>	PrMode	8	Printer process mode	
<b>SFCBID</b>	SFCB	5	Printer selection FCB ID	
<b>SUCSID</b>	SUCS	4	Printer selection UCS ID	
<b>SWTRID</b>	SWriter	8	Printer selection writer ID (JES2 only)	

Table 75. Columns on the PR Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>SFLASHID</b>	SFlh	5	3800 Printer selection flash ID	
<b>PRTWS</b>	Work-Selection	40	Printer work selection criteria	
<b>SBURST</b>	SBurst	6	3800 output selection burst mode	
<b>SPRMODE1</b>	SPrMode1	8	Output selection process mode 1	
<b>SPRMODE2</b>	SPrMode2	8	Output selection process mode 2	
<b>SPRMODE3</b>	SPrMode3	8	Output selection process mode 3	
<b>SPRMODE4</b>	SPrMode4	8	Output selection process mode 4	
<b>SDESTN1</b>	SDest1	8	Printer selection destination name 1 (JES2 only)	
<b>SDESTN2</b>	SDest2	8	Printer selection destination name 2 (JES2 only)	
<b>SDESTN3</b>	SDest3	8	Printer selection destination name 3 (JES2 only)	
<b>SDESTN4</b>	SDest4	8	Printer selection destination name 4 (JES2 only)	
<b>SJOBNAME</b>	SJobName	8	Printer selection job name (JES2 only)	
<b>SOWNER</b>	SOwner	8	Printer selection creator ID. Use with the CREATOR work selection criteria. (JES2 only)	
<b>SRANGE</b>	SRange	22	Printer selection job number range (JES2 only)	
<b>SEPMK</b>	M	3	3800 mark forms control	
<b>NPRO</b>	NPro	4	Nonprocess run-out time in seconds (FSS only). This column is not overtypable when the printer is active.	
<b>MODE</b>	Mode	4	Control mode of printer (FSS only)	
<b>CKPTLINE</b>	CkptLine	8	Number of lines per logical page (JES2 only)	
<b>CKPTREC</b>	CkptRec	7	Number of logical records per checkpoint (JES3 only)	
<b>CKPTPAGE</b>	CkptPage	8	Number of logical pages per checkpoint	
<b>CKPTSEC</b>	CkptSec	7	Default checkpoint interval (3800-FSS) in seconds	
<b>CKPTMODE</b>	CkptMode	8	Checkpoint mode indicator (take checkpoints based on pages or seconds)	
<b>CPYMOD</b>	CpyMod	7	Copy modification module ID for the 3800 printer	
<b>UNIT</b>	Unit	5	Printer unit name	
<b>PSEL</b>	PSel	4	Preselection option (JES2 only)	
<b>OGNAME</b>	O-Grp-N	8	Output group name for the active job on the printer (JES2 only)	

Table 75. Columns on the PR Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>LINELIM</b>	Line-Limit	21	Printer line limit, <i>m-n</i> . An * indicates maximum value. (JES2 only)	
<b>PAGELIM</b>	Page-Limit	21	Printer page limit, <i>m-n</i> . Not shown for remote printers. (JES2 only)	
<b>DEVFCB</b>	DFCB	5	Device default FCB name or RESET	
<b>PSETUP</b>	Setup	6	Printer setup mode	
<b>COPYMARK</b>	CopyMark	8	Copypmark indicator. Shown only for non-impact or FSS controlled printers.	
<b>PAUSE</b>	Pau	3	Pause mode. Not shown for remote printers.	
<b>PSPACE</b>	K	1	Printer spacing. Not shown for remote printers. (JES2 only)	
<b>PTRACE</b>	Tr	3	Printer tracing	
<b>SEPCHARS</b>	SepChar	7	Separator character value. Not shown for remote printers. (JES2 only)	
<b>UCSVERIFY</b>	UCSV	4	UCS verification option. Not shown for remote printers. (JES2 only)	
<b>DEST</b>	Rmt <sup>2</sup>	5	JES print routing (JES2 only)	
<b>NODE</b>	Node <sup>2</sup>	4	JES print node (JES2 only)	
<b>FSSNAME</b>	FSSName	8	FSS defined for the printer	
<b>FSSPROC</b>	FSSProc	8	Name of the proc used to start the FSS	
<b>FSATRACE</b>	FSATrace	8	Internal rolling trace for an FSS printer (JES2 only)	
<b>SYSNAME</b>	SysName	8	System name	
<b>DSYSID</b>	SysID	5	JES member name (JES2 only)	
<b>JESNAME</b>	JESN	4	JES subsystem name	
<b>JESLEVEL</b>	JESLevel	8	JES level	
<b>DEVSECLB</b>	DSecLabel	9	Security label of the device (JES2 only)	
<b>JTYPE</b>	Type	4	Type of address space	
<b>OGID1</b>	OGID1	5	Output group ID1 for job on printer (JES2 only)	
<b>OGID2</b>	OGID2	5	Output group ID2 for job on printer (JES2 only)	
<b>PTRANS</b>	Trans	8	Data translation	
<b>TRKCELL</b>	TrkCell	7	De-spool the entire track cell (JES2 only)	
<b>NEWPAGE</b>	NewPage	7	Controls how a "skip to channel" is counted (JES2 only)	
<b>HONORTRC</b>	HonorTRC	8	Honor TRC (table reference character) keyword in JCL (JES2 only)	

Table 75. Columns on the PR Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>SVOL</b>	SVol1	6	Spool volumes for work selection (JES2 only)	
<b>SVOL2</b>	SVol2	6	Spool volume 2 for work selection (JES2 only)	
<b>SVOL3</b>	SVol3	6	Spool volume 3 for work selection (JES2 only)	
<b>SVOL4</b>	SVol4	6	Spool volume 4 for work selection (JES2 only)	
<b>CHAR1</b>	Char1	5	Character arrangement table 1	
<b>CHAR2</b>	Char2	5	Character arrangement table 2	
<b>CHAR3</b>	Char3	5	Character arrangement table 3	
<b>CHAR4</b>	Char4	5	Character arrangement table 4	
<b>FSASYSNM</b>	FSASysNm	8	MVS system where FSA is active	
<b>DSPNAME</b>	DSPName	7	Dynamic support program name (JES3 only)	
<b>DEVTYPE</b>	DevType	8	Device type name (JES3 only)	
<b>SDEST1</b>	SRout1 <sup>2</sup>	6	Selection destination 1 (JES2 only)	
<b>SDEST2</b>	SRout2 <sup>2</sup>	6	Selection destination 2 (JES2 only)	
<b>SDEST3</b>	SRout3 <sup>2</sup>	6	Selection destination 3 (JES2 only)	
<b>SDEST4</b>	SRout4 <sup>2</sup>	6	Selection destination 4 (JES2 only)	
<b>SNODE1</b>	SNode1 <sup>2</sup>	6	Selection node (JES2 only)	
<b>SNODE2</b>	SNode2 <sup>2</sup>	6	Selection node 2 (JES2 only)	
<b>SNODE3</b>	SNode3 <sup>2</sup>	6	Selection node 3 (JES2 only)	
<b>SNODE4</b>	SNode4 <sup>2</sup>	6	Selection node 4 (JES2 only)	
<b>LINELIML</b>	Line-Lim-Lo	12	Printer line limit, minimum	
<b>LINELIMH</b>	Line-Lim-Hi	12	Printer line limit, maximum	
<b>PAGELIML</b>	Page-Lim-Lo	12	Printer page limit, minimum	
<b>PAGELIMH</b>	Page-Lim-Hi	12	Printer page limit, maximum	
<b>DGRPY</b>	DGrpY	5	Device cannot process data sets that are destined for any local device (JES3 only)	
<b>DYNAMIC</b>	Dyn	3	Device can be started dynamically (JES3 only)	
<b>OPACTLOG</b>	OpLog	5	Operator command actions will be logged in the output of the modified device using message IAT7066 or IAT7067 (FSS devices, JES3 only)	
<b>CGS</b>	CGS	3	Character generation storage (JES3 only)	
<b>BURSTPAGE</b>	B	1	Burst (JES3 only)	
<b>PDEFAULT</b>	PDefault	8	Defaults that should be applied, if not defined in the job's JCL (JES3 only)	
<b>COPIES</b>	Copies	6	Copy count (JES3 only)	
<b>CLEAR</b>	CB	2	Clear printer processing indicator (JES3 only)	

Table 75. Columns on the PR Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>TRC</b>	TRC	3	Table reference character (JES3 only)	
<b>HFCB</b>	HFCB	4	Use designated FCB until status is changed (JES3 only)	
<b>HCHARS</b>	HChars	6	Use designated CHARS until status is changed (JES3 only)	
<b>HUCS</b>	HUCS	4	Use designated UCS until status is changed (JES3 only)	
<b>HCPYMOD</b>	HCpyMod	7	Use designated Copy Mod until status is changed (JES3 only)	
<b>HFLASH</b>	HFlash	6	Use designated Flash until status is changed (JES3 only)	
<b>HBURST</b>	HBurst	6	Use designated Burst until status is changed (JES3 only)	
<b>HFORMS</b>	HForms	6	Use designated Forms until status is changed (JES3 only)	
<b>ASIS</b>	AsIs	4	Send print data as is (JES2 only)	
<b>CCTL</b>	CCtl	4	Data carriage control stream	
<b>CMPCT</b>	Cmpct	4	Compaction for SNA remote punches	
<b>COMP</b>	Comp	4	Compression	
<b>COMPAC</b>	Compact	8	Compaction table name for SNA remote punches	
<b>FCBLOAD</b>	FCBl	4	JES will load FCB	
<b>LRECL</b>	LRecl	5	Logical record length	
<b>SUSPEND</b>	Sus	3	Suspend/interrupt capability (JES2 only)	
<b>SELECT</b>	Select	8	Send output to device type and subaddress	
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.	

Notes on the table follow.

<sup>1</sup> The width of the PRINTER column is 7 if the shortened format of device names has been specified.

<sup>2</sup> This column is not included in the default field list.

## Private Storage Subpool panel (USI)

The Private Storage Subpool (USI) panel allows authorized users to view private storage details for a selected subpool and key.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 76. Columns on the USI Panel

Column name	Title (Displayed)	Width	Description
<b>ADDRESS</b>	ADDRESS	8	Storage start address. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>ADDRESSEND</b>	AddrEnd	8	Storage end address
<b>LENGTH</b>	Length	8	Storage size
<b>STATUS</b>	Status	6	Status of storage (ALLOC or FREE)
<b>SUBPOOL</b>	SP	3	Subpool of storage
<b>KEY</b>	Key	3	Storage key
<b>BLOCKADDR</b>	BlockAddr	9	Block address start
<b>BLKSIZE</b>	BlockSize	9	Block size
<b>PROGRAM</b>	Program	8	Module name that obtained it
<b>TYPE</b>	Type	4	Storage type (PVT or LSQA)
<b>SHARED</b>	Shared	6	Shared storage (yes or no)
<b>TCB</b>	TCB	8	TCB address
<b>JNAME</b>	JobName	8	Job name that obtained it
<b>ASID</b>	ASID	5	Address space ID (decimal)
<b>ASIDX</b>	ASIDX	5	Address space ID (hexadecimal)
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	System level
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Proclib panel (PROC)

The Proclib (PROC) panel shows the procedure libraries being used by JES. The PROC panel shows the procedure libraries for the local member only. This panel is available only in SDSF V2R2 and only when running JES2.

You can use the fast path select (S) command with a DDNAME to filter results.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 77. Columns on the PROC Panel

Column name	Title (Displayed)	Width	Description
<b>DDNAME</b>	DDNAME	8	DDName of the data set. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SEQ</b>	Seq	3	Sequence number for data set in list
<b>DSNAME</b>	DSName	44	Data set name

Table 77. Columns on the PROC Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>VOLSER</b>	VolSer	6	Volume serial
<b>DEFVOL</b>	DefVol	6	Defined volume serial
<b>STATUS</b>	Status	8	Data set status
<b>TSO</b>	TSO	3	Proclib used for TSO (YES or NO)
<b>STC</b>	STC	3	Proclib used for started tasks (YES or NO)
<b>STATIC</b>	Static	6	Static allocation (YES or NO)
<b>BLKSIZE</b>	BlkSize	7	Block size
<b>EXTENT</b>	Extent	6	Number of data set extents
<b>SMS</b>	SMS	3	SMS indicator (YES or NO). YES if SMS managed.
<b>LRECL</b>	LRecL	5	Logical record length for data set
<b>DSORG</b>	DSOrg	5	Data set organization
<b>RECFM</b>	RecFm	5	Record format
<b>CRDATE</b>	CrDate	8	Data set creation date
<b>REFDATE</b>	RefDate	8	Data set last reference date
<b>SEQMAX</b>	SeqMax	6	Maximum sequence number for data set in list
<b>USECOUNT</b>	UseCount	8	Concatenation use count
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Processes panel (PS)

The PS panel displays information about z/OS UNIX System Services processes.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 78. Columns on the PS Panel

Column name	Title (Displayed)	Width	Description
<b>JOBNAME</b>	DSNAME	8	Job name. This is the fixed field. It is ignored on an FLD statement or ISFFLD macro.
<b>JOBID</b>	JobID	8	Job ID of the process
<b>STATUS</b>	Status	32	Status of the process
<b>OWNERID</b>	Owner	8	User ID of owner
<b>STATE</b>	State	5	State of the process or of most recently created thread (corresponds to d omvs display)
<b>CPU</b>	CPU-Time	8	Compute time in hundredths of seconds
<b>PID</b>	PID	10	Process ID

Table 78. Columns on the PS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>PPID</b>	PPID	10	Parent process ID
<b>ASID</b>	ASID	5	Address space id
<b>ASIDX</b>	ASIDX	5	Address space id in hexadecimal
<b>LATCHPID</b>	LatchWaitPID	12	PID on which this process is waiting
<b>COMMAND</b>	Command	40	Command that created process
<b>SERVER</b>	ServerName	32	Server name
<b>TYPE</b>	Type	4	Server type (only when the process is a server)
<b>ACTFILES</b>	ActFiles	8	Number of active files (only when the process is a server)
<b>MAXFILES</b>	MaxFiles	8	Maximum number of files (only when the process is a server)
<b>TIMEE</b>	St-Time	8	Time process was started. In the SDSF task of z/OSMF, this is replaced by the St-DateTime column.
<b>DATEE</b>	St-Date	8	Date process was started. In the SDSF task of z/OSMF, this is replaced by the St-DateTime column.
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system
<b>SYSNAME</b>	SysName	8	System name where process is executing
<b>SECLABEL</b>	SecLabel	8	Security label of the process
<b>DATETIMEE</b>	St-DateTime	19	Date and time that execution began. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the St-Date and St-Time columns.
<b>ZIIPTIME</b>	zIIP-Time	9	System and user compute time on zIIP.
<b>RUID</b>	RUID	8	Process real user ID.
<b>EUID</b>	EUID	8	Process effective user ID.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Punch panel (PUN)

The PUN panel allows the user to display information about punches.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 79. Columns on the PUN Panel

Column name	Title (Displayed)	Width	Description
<b>DEVNAME</b>	PUNCH	10	Device name. This is the fixed field. It is ignored on an FLD statement or ISFFLD macro.



Table 79. Columns on the PUN Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>STATUS</b>	Status	8	Punch status
<b>GROUP</b>	Group	8	Device group name (JES3 only)
<b>SFORMS</b>	SForms	8	Selection form number
<b>SFORM2</b>	SForm2	8	Selection form number 2 (JES2 only)
<b>SFORM3</b>	SForm3	8	Selection form number 3 (JES2 only)
<b>SFORM4</b>	SForm4	8	Selection form number 4 (JES2 only)
<b>SFORM5</b>	SForm5	8	Selection form number 5 (JES2 only)
<b>SFORM6</b>	SForm6	8	Selection form number 6 (JES2 only)
<b>SFORM7</b>	SForm7	8	Selection form number 7 (JES2 only)
<b>SFORM8</b>	SForm8	8	Selection form number 8 (JES2 only)
<b>JNAME</b>	JobName	8	Active job name
<b>JOBID</b>	JobID	8	Active job ID
<b>JTYPE</b>	Type	5	Type of active address space
<b>JNUM</b>	JNum <sup>1</sup>	6	Active job number
<b>OWNERID</b>	Owner	8	User ID of owner
<b>SCLASS</b>	SClass	15	Output selection classes
<b>RECCNT</b>	Rec-Cnt	7	Number of line-mode records in the job
<b>RECPRT</b>	Rec-Prt	7	Number of line-mode records printed
<b>PAGECNT</b>	Page-Cnt	8	Output page count
<b>PAGEPRT</b>	Page-Prt	8	Output pages printed
<b>SEP</b>	Sep	3	Separator page between output groups (JES2 only)
<b>SEPDS</b>	SepDS	5	Separator page between data sets
<b>CCTL</b>	CCtl	4	Data carriage control stream
<b>CMPCT</b>	Cmpct	4	Compaction for SNA remote punches
<b>COMP</b>	Comp	4	Compression
<b>COMPAC</b>	Compact	8	Compaction table name for SNA remote punches
<b>FLUSH</b>	Fls	3	Blank card after each data set
<b>SWTRID</b>	SWriter	8	Punch selection writer ID (JES2 only)
<b>PRTWS</b>	Work-Selection	40	Punch work selection criteria
<b>SPRMODE1</b>	SPrMode1	8	Output selection process mode 1
<b>SPRMODE2-4</b>	SPrMode2-4	8	Output selection process modes 2-4
<b>SDESTN1</b>	SDest1	8	Punch selection destination name 1 (JES2 only)
<b>SDESTN2-4</b>	SDest2-4	8	Punch selection destination names 2-4 (JES2 only)
<b>SJOBNAME</b>	SJobName	8	Selection job name (JES2 only)

Table 79. Columns on the PUN Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>SOWNER</b>	SOwner	8	Selection creator ID (JES2 only)
<b>SVOL</b>	SVol	6	Selection volume (JES2 only)
<b>SELECT</b>	Select	7	Send Output To (remote punches only)
<b>CKPTLINE</b>	CkptLine	8	Number of lines per logical page (JES2 only)
<b>CKPTPAGE</b>	CkptPage	8	Number of logical pages per checkpoint (JES2 only)
<b>CKPTREC</b>	CkptRec	3	Number of records per checkpoint (JES3 only)
<b>UNIT</b>	Unit	5	Punch unit name
<b>LINELIM</b>	Line-Limit	21	Punch line limit (JES2 only)
<b>SRANGE</b>	SRange	22	Selection job number range (JES2 only)
<b>LRECL</b>	LRecL	5	Logical record length of transmitted data (SNA only)
<b>PSETUP</b>	Setup	6	Setup option (JES2 only)
<b>PAUSE</b>	Pau	3	Pause mode
<b>SUSPEND</b>	Sus	3	Punch-interrupt feature option (BSC connection only, JES2 only)
<b>PTRACE</b>	Tr	3	Punch tracing
<b>SYSNAME</b>	SysName	8	System name
<b>DSYSID</b>	SysID	5	JES2 member name (JES2 only)
<b>JESNAME</b>	JESN	4	JES subsystem name
<b>JESLEVEL</b>	JESLevel	8	z/OS JES level
<b>SECLABEL</b>	Seclabel	8	Security label of the job on the device
<b>DEVSECLB</b>	DSecLabel	9	Security label of the device (JES2 only)
<b>LINELIML</b>	Line-Lim-Lo	11	Punch line limit, minimum
<b>LINELIMH</b>	Line-Lim-Hi	11	Punch line limit, maximum
<b>SVOL2-4</b>	Svol2-4	6	Selection volumes 2-4 (JES2 only)
<b>OGNAME</b>	O-Grp-N	8	Output group name (JES2 only)
<b>OGID1</b>	OGid1	5	Output group ID 1 (JES2 only)
<b>OGID2</b>	OGid2	5	Output group ID 2 (JES2 only)
<b>FORMS</b>	Forms	8	Output forms
<b>PRMODE</b>	Prmode	8	Output process mode
<b>WTRID</b>	Writer	8	Output writer name (JES2 only)
<b>DESTN</b>	Dest	8/18	Output destination (JES2 only)
<b>DPRIO</b>	DP	2	Output priority
<b>JPRIOR</b>	JP	2	Job priority
<b>OCLASS</b>	C	1	Output class
<b>DEVTYPE</b>	DevType	8	Device type (JES3 only)

Table 79. Columns on the PUN Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>DSPNAME</b>	DSPName	8	Dynamic support program name (JES3 only)
<b>HFORMS</b>	HForms	6	Use designated forms until status is changed (JES3 only)
<b>COPIES</b>	Copies	6	Copy count (JES3 only)
<b>DYNAMIC</b>	Dyn	3	Start device dynamically (JES3 only)
<b>DGRPY</b>	DGrpY	3	Device cannot process data sets that are destined for any local device (JES3 only)
<b>BURSTPAGE</b>	B	3	Punch burst page at end of job (JES3 only)
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

Notes on the table:

1. This column is not included in the default field list.

## Reader panel (RDR)

The RDR panel allows the user to display information about readers.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 80. Columns on the RDR Panel

Column name	Title (Displayed)	Width	Description
<b>DEVNAME</b>	READER	10	Device name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	8	Reader status
<b>GROUP</b>	Group	8	Device group name (JES3 only)
<b>JNAME</b>	JobName	8	Job name
<b>JOBID</b>	JobID	8	Active job ID (JES2 only)
<b>JTYPE</b>	Type <sup>1</sup>	5	Type of active address space
<b>JNUM</b>	JNum <sup>1</sup>	6	Active job number (JES2 only)
<b>OWNERID</b>	Owner	8	User ID of owner
<b>RECCNT</b>	Rec-Cnt	10	Number of records in the job (JES2 only)
<b>RECPRT</b>	Rec-Proc	10	Number of records processed
<b>RCLASS</b>	C	1 or 8	Default execution class. Default width expands to 8 if there are long class names in the MAS.
<b>RHOLD</b>	Hold	4	Job held after JCL conversion (JES2 only)
<b>RMCLASS</b>	MC	2	Message class (JES2 only)

Table 80. Columns on the RDR Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>RPRTDST</b>	PrtDest	18	Default destination for print output (JES2 only)
<b>RPUNDST</b>	PunDest	18	Default destination for punch output (JES2 only)
<b>RSYSAFF</b>	SAff	5	System affinity (JES2 only)
<b>RAUTH</b>	Authority	13	Authority of the reader (JES2 only)
<b>PRIOINC</b>	PI	2	Increment to selection priority (JES2 only)
<b>PRIOLIM</b>	PL	2	Maximum priority level that can be assigned to jobs. Any job's priority that exceeds this level is reduced to it. (JES2 only)
<b>RUNIT</b>	Unit	5	Reader unit name
<b>XEQDEST</b>	XeqDest	18	Default execution node (JES2 only)
<b>RTRACE</b>	Tr	3	Reader tracing (JES2 only)
<b>SYSNAME</b>	SysName	8	System name
<b>DSYSID</b>	SysID	5	JES2 member name (JES2 only)
<b>JESNAME</b>	JESN	4	JES subsystem name
<b>JESLEVEL</b>	JESLevel	8	z/OS JES level
<b>SECLABEL</b>	SecLabel	8	Security label of the job on the reader (JES2 only)
<b>DEVSECLB</b>	DSecLabel	9	Security label of the device (JES2 only)
<b>DEVTYPE</b>	DevType	8	Device type name (JES3 only)
<b>DSPNAME</b>	DSPName	8	Dynamic support program name (JES3 only)
<b>ACCTREQ</b>	AReq	3	Account number required on job card (JES3 only)
<b>PNAMEREQ</b>	PReq	3	Programmer name required on job card (JES3 only)
<b>SWA</b>	SWA	5	SWA ABOVE or BELOW (JES3 only)
<b>BLP</b>	BLP	3	Bypass label processing label setting is respected (JES3 only)
<b>RPRIO</b>	DP	2	Default job priority (JES3 only)
<b>RMLEVEL</b>	ML	2	Default job message level (JES3 only)
<b>RALEVEL</b>	AL	2	Default allocation message level (JES3 only)
<b>RTIME</b>	Time	10	Default time limit (JES3 only)
<b>RREGION</b>	Region	10	Default region size (JES3 only)
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

Notes on the table:

1. This column is not included in the default field list.

## Resource panel (RES)

The RES panel allows users to display information about WLM resources in a scheduling environment, or in the sysplex.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 81. Columns on the RES Panel

Column name	Title (Displayed)	Width	Description
<b>RESOURCE</b>	RESOURCE	16	Resource name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>REQSTATE</b>	ReqState	8	Required state of the resource for the scheduling environment. Displayed only if the panel is accessed with the R action character.
<b>SYS1 to SYS32</b>	Resolved from the actual names of the systems	8	Status of the resource on the system.
<b>SCHENV</b>	SchedEnv	16	Scheduling environment
<b>DESCRIPT</b>	Description	32	Resource description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

**Note:** Omit the column title when coding a field list for the RES panel. For example, you would code SYS1, , 8 for the first system column. Using statements, you would omit the TITLE keyword, for example:

```
FLDENT COLUMN(SYS1),WIDTH(*)
```

When there are more columns in the field list than are required for the panel, either because of the number of systems that are active or because the scope of the panel has been limited to systems in the MAS, SDSF displays only as many columns as are required.

## Resource Monitor panel (RM)

The Resource Monitor panel shows information about JES2 resources. (JES2 only)

In REXX execs and Java programs, reference columns by name rather than by title.

Table 82. Columns on the RM Panel

Column name	Title (Displayed)	Width	Description	Delay
<b>RESNAME</b>	RESOURCE	8	JES2 resource name	
<b>DSYSID</b>	SysID	5	JES2 member name	
<b>STATUS</b>	Status	10	Resource status	X
<b>LIMIT</b>	Limit	6	Limit for the resource	X
<b>USENUM</b>	InUse	6	Number in use	X
<b>USEPCT</b>	InUse%	6	Percentage in use	X
<b>WARNPCT</b>	Warn%	5	Warning threshold (percentage)	X

Table 82. Columns on the RM Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>INTAVG</b>	IntAvg	6	Average amount in use for the interval	X
<b>INTHIGH</b>	IntHigh	7	Highest amount in use for the interval	X
<b>INTLOW</b>	IntLow	6	Lowest amount in use for the interval	X
<b>OVERWARN</b>	OverWarn%	9	Amount in use above the warning threshold (percentage)	X
<b>TIMEE</b>	Time	8	Time that the interval began	X
<b>DATEE</b>	Date	8	Date that the interval began	X
<b>SYSNAME</b>	SysName	8	System name	
<b>JESNAME</b>	JESN	4	JES2 subsystem name	
<b>JESLEVEL</b>	JESLevel	8	z/OS JES2 level	
<b>DESCRIPT</b>	Description	20	Descriptive resource name	
<b>STMT</b>	Statement	16	Resource limit statement	
<b>KEYWORD</b>	Keyword	20	Resource limit keyword	
<b>SCOPE</b>	Scope	7	Resource scope (local or JESPLEX).	
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.	

## Resource Monitor Alerts panel (RMA)

The Job Resource Monitor Alerts (RMA) panel shows resource alert, notice, and track messages. These messages are issued when JES2 detects problems related to resources. (JES2 only)

The RMA panel requires use of the SDSFAUX address space for data gathering and is available only when running JES2.

You can use the fast path select (S) and filter commands to customize the rows being shown.. The command accepts a single parameter for the message-type pattern.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 83. Columns on the RMA Panel

Column name	Title (Displayed)	Width	Description
<b>TYPE</b>	TYPE	7	Message type (alert, notice, or track). This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>MEMBER</b>	Member	8	JES2 member name.
<b>MSGLINE1</b>	MessageLine1	71	Message line 1.
<b>MSGLINE1</b>	MessageLine2	71	Message line 2.
<b>MSGLINE3</b>	MessageLine3	71	Message line 3.

Table 83. Columns on the RMA Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>MSGLINE4</b>	MessageLine4	71	Message line 4.
<b>MSGTIME</b>	MessageTime	19	Timestamp when alert recognized.
<b>CRITICAL</b>	Critical	8	Notice is critical (yes, no, or blank).
<b>JESNAME</b>	JESN	4	JES subsystem name.
<b>SYSNAME</b>	SysName	8	MVS system name
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Scheduling Environment panel (SE)

The SE panel allows the user to display information about scheduling environments.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 84. Columns on the SE Panel

Column Name	Title (Displayed)	Width	Description
<b>SCHENV</b>	SCHEDULING-ENV	16	Scheduling environment name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>DESCRIPT</b>	Description	32	Description of scheduling environment
<b>SYSTEMS</b>	Systems	60	Systems with the scheduling environment available
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Spool Offload panel (SO)

The Spool Offload panel allows the user to display information about JES2 spool offloaders (JES2 only).

In REXX execs and Java programs, reference columns by name rather than by title.

Table 85. Columns on the SO Panel

Column name	Title (Displayed)	Width	Description
<b>DEVNAME</b>	DEVICE	8	Device name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	9	Device status
<b>TYPE</b>	Type	8	Device type

Table 85. Columns on the SO Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>JNAME</b>	Jobname	8	Active jobname
<b>JOBID</b>	JobID	8	Active JES2 job ID
<b>JTYPE</b>	JType <sup>1</sup>	5	Type of active address space
<b>JNUM</b>	JNum <sup>2</sup>	6	Active JES2 job number
<b>OWNERID</b>	Owner	8	User ID of owner
<b>LINELIM</b>	Line-Limit	21	Selection line limit
<b>PAGELIM</b>	Page-Limit	21	Selection page limit
<b>RECPRT</b>	Proc-Lines	10	Number of lines processed for the job.
<b>RECCNT</b>	Tot-Lines	10	Number of lines in the job.
<b>SCLASS</b>	SClass	15	Selection classes. Multi-character classes and groups shows as periods (.).
<b>SOWNER</b>	SOwner	8	Selection owner
<b>SHOLD</b>	SHold	5	Selection hold value
<b>SJOBNAME</b>	SJobName	8	Selection jobname
<b>SRANGE</b>	SRange	22	Selection job number range
<b>SDESTN1</b>	SDest1	18	Selection destination name
<b>SSAFF</b>	SSAff	5	Selection system affinity
<b>SDISP</b>	SDisp	6	Selection disposition
<b>SVOL</b>	SVol	6	Selection volume
<b>SBURST</b>	SBurst	6	Selection burst value
<b>SFCBID</b>	SFCB	4	Selection FCB
<b>SFLASHID</b>	SFlh	4	Selection flash
<b>SFORMS</b>	SForms	8	Selection forms name
<b>SFORM2</b>	SForm2	8	Selection forms name 2
<b>SFORM3</b>	SForm3	8	Selection forms name 3
<b>SFORM4</b>	SForm4	8	Selection forms name 4
<b>SFORM5</b>	SForm5	8	Selection forms name 5
<b>SFORM6</b>	SForm6	8	Selection forms name 6
<b>SFORM7</b>	SForm7	8	Selection forms name 7
<b>SFORM8</b>	SForm8	8	Selection forms name 8
<b>SPRMODE1</b>	SPrMode	8	Selection process mode
<b>SODISP</b>	SODsp	5	Selection output disposition
<b>SODISP2</b>	SODsp2	5	Selection output disposition 2
<b>SODISP3</b>	SODsp3	5	Selection output disposition 3
<b>SODISP4</b>	SODsp4	5	Selection output disposition 4



Table 85. Columns on the SO Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>SWTRID</b>	SWriter	8	Selection writer name
<b>SUCSID</b>	SUCS	4	Selection UCS
<b>PRTWS</b>	Work-Selection	40	Work selection criteria
<b>NOTIFY</b>	Notify	6	Notification option
<b>ODSNAME</b>	DSName	44	Data set name
<b>SSRVCLS</b>	SSrvClass	9	Selection service class value for the job receiver or job transmitter
<b>SSCHENV</b>	SScheduling-Env	16	Selection scheduling environment value for the job receiver or job transmitter
<b>MBURST</b>	MBurst	6	Modification of the burst value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.
<b>MDEST</b>	MDest	18	Modification of the destination value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.
<b>MFCB</b>	MFCB	4	Modification of the FCB value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.
<b>MFLASH</b>	MFlh	4	Modification of the flash value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.
<b>MFORMS</b>	MForms	8	Modification of the forms value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.
<b>MHOLD</b>	MHold	5	Modification of the hold value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.
<b>MSCLASS</b>	MClass	8	Modification of the class value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.
<b>MODISP</b>	MODsp	5	Modification of the output disposition value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.
<b>MPRMODE</b>	MPrMode	8	Modification of the process mode value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.
<b>MSAFF</b>	MSAff	5	Modification of the system affinity value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.
<b>MUCS</b>	MUCS	4	Modification of the universal character set (UCS) name value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.

Table 85. Columns on the SO Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>MWRITER</b>	MWriter	8	Modification of the writer name value, for post-execution jobs and output data sets that are selected for reloading, assigned during the reload process.
<b>LABEL</b>	Label	5	Label
<b>PROTECT</b>	Prot	4	Protect option
<b>RETENT</b>	RtPd	4	Retention
<b>ARCHIVE</b>	Archive	7	Archive option
<b>VALIDAT</b>	Validate	8	Validation option
<b>UNIT</b>	Unit	14	Unit
<b>VOLS</b>	Vols	4	Volume count (1-255) to be used for the offload data set
<b>SYSNAME</b>	SysName	8	System name
<b>DSYSID</b>	SysID	5	JES2 member name
<b>JESNAME</b>	JESN	4	JES2 subsystem name
<b>JESLEVEL</b>	JESLevel	8	JES2 level
<b>DEVSECLB</b>	DSecLabel	9	Security label of the device
<b>CRTIME</b>	CRTIME	7	Indicates whether to restore or reset the original creation time of the output.
<b>LINELIML</b>	Line-Lim-Lo	11	Line limit, minimum
<b>LINELIMH</b>	Line-Lim-Hi	11	Line limit, maximum
<b>PAGELIML</b>	Page-Lim-Lo	11	Page limit, minimum
<b>PAGELIMH</b>	Page-Lim-Hi	11	Page limit, maximum
<b>SCLASS1-8</b>	SClass1-8	8	Selection classes 1-8, including multi-character classes and groups (job transmitters and receivers)
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

Notes on the table:

1. JType is not included in the default field list.
2. JNum is not included in the default field list.

## Spool Volumes panel (SP)

The Spool Volumes panel lets you display and control JES2 spool volumes.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 86. Columns on the SP Panel

Column name	Title (Displayed)	Width	Description
<b>DEVNAME</b>	DSNAME	6 (JES2) 8 (JES3)	Spool volume name (JES2) or DDNAME (JES3). This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	8 (JES2) 12 (JES3)	Spool status (active, starting, halting, draining, inactive) or partition status
<b>TGPCT</b>	TGPct	5	Spool utilization
<b>TGNUM</b>	TGNum	5	Total track groups
<b>TGUSE</b>	TGUse	5	Track groups in use
<b>COMMAND</b>	Command	8	Command being processed (start, format, drain, halt) (JES2 only)
<b>SPSYSAF</b>	SAff	5	System affinity (JES2 only)
<b>EXTENT</b>	Ext	3	Extent number, in hexadecimal
<b>CYLLO</b>	LoCyl	8	Low cylinder
<b>TRKLO</b>	LoTrk	16	Absolute low track number, in hexadecimal
<b>HEADLO</b>	LoHead	8	Low head
<b>CYLHI</b>	HiCyl	8	High cylinder
<b>TRKHI</b>	HiTrk	16	Absolute high track number, in hexadecimal
<b>HEADHI</b>	HiHead	8	High head
<b>TCYL</b>	TrkPerCyl	9	Tracks per cylinder
<b>TREC</b>	RecPerTrk	9	Records per track
<b>TGTRK</b>	TrkPerTG	8	Tracks per track group
<b>TYPE</b>	Type	9	Spool type (PARTITION or EXTENT)
<b>PARTNAME</b>	PartName	8	Partition name (JES3 only)
<b>OVFNAME</b>	OverFNam	8	Overflow partition name (JES3 only)
<b>OVALLOW</b>	OverAllow	9	Indicates if overflow from this partition to another partition is allowed (JES3 only)
<b>OVOCCUR</b>	OverOccur	9	Indicates if overflow from this partition to another partition occurred (JES3 only)
<b>OVINTO</b>	OverInto	3	Indicates if overflow into this partition from another partition is allowed (JES3 only)
<b>PTRACKS</b>	PTracks	8	Total tracks in the partition
<b>PTRACKU</b>	PTrackU	8	Tracks in use in the partition
<b>DTRACKS</b>	DTracks	8	Total tracks in the data set
<b>DTRACKU</b>	DTrackU	8	Tracks in use in the data set

Table 86. Columns on the SP Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>DEFAULT</b>	Default	7	Default partition indicator (JES3 only)
<b>STUNTED</b>	Stunted	7	Extent is stunted (JES2 only)
<b>STT</b>	STT	3	Single track table indicator (JES3 only)
<b>MARGPCT</b>	MargPct	7	Marginal SLIM threshold percentage – shown only on the row for the partition (JES3 only)
<b>MARGEXC</b>	MargExc	7	Marginal threshold exceeded (JES3 only)
<b>MINPCT</b>	MinPct	6	Minimal SLIM threshold percentage (JES3 only)
<b>MINEXC</b>	MinExc	3	Marginal threshold exceeded (JES3 only)
<b>DATASET</b>	DataSetName	44	Data set name
<b>VOLSER</b>	VolSer	6	Actual volume serial upon which this spool extent resides (JES2 only)
<b>SELECT</b>	Sel	3	Indicates if work is selectable on this volume (JES2 only)
<b>RESERVED</b>	Res	3	Indicates whether this volume is reserved (active but not allocatable) (JES2 only)
<b>LGFREE</b>	LgFree	6	Largest number of contiguous free tracks (JES2 only)
<b>HIGHTRK</b>	HiUsed	6	Highest used track on the volume (JES2 only)
<b>COMPPCT</b>	Comp%	5	Percentage complete of the current action against the volume (JES2 only)
<b>PHASE</b>	Phase	12	Migration phase (JES2 only)
<b>MIGSYS</b>	MigSys	6	JES2 member performing the spool migration (JES2 only)
<b>TARGET</b>	Target	8	Volume name in JES2 where this extent is migrating to or has migrated to (JES2 only)
<b>MIGVOL</b>	MigVol	6	
<b>MIGDSN</b>	MigDSName	44	Data set name to which this extent is migrating (JES2 only)

## Search panel (SRCH)

The SRCH panel shows all data sets containing the specified member pattern. The resulting table shows all data sets containing that member pattern. You can use the SRCH command from the APF, LNK, LPA, PARM, and PROC panels.

**Note:** SRCH provides a different capability from the SEARCH command. SRCH implements a member search using a data set list, whereas SEARCH searches the SDSF help.

The SRCH panel is not available through REXX or implemented in Java. You can use the SYSDSN function in REXX to implement this function, or implement it directly in Java.

Table 87. Columns on the SRCH Panel

Column name	Title (Displayed)	Width	Description
<b>DSNAME</b>	DSNAME	13-44 (Varies based on longest name.)	Data set name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SEQ</b>	Seq	3	Sequence number
<b>VOLSER</b>	VolSer	6	Volume serial
<b>STATUS</b>	Status	16	Data set or member status
<b>DSORG</b>	DSOrg	5	Data set organization
<b>BLKSIZE</b>	BlkSize	7	Data set block size
<b>EXTENT</b>	Extent	6	Number of extents
<b>SMS</b>	SMS	3	SMS indicator: YES if data set is SMS managed. Otherwise, NO.
<b>LRECL</b>	LRecL	5	Logical record length
<b>RECFM</b>	RecFm	5	Record format
<b>CRDATE</b>	CrDate	8	Data set creation date
<b>REFDATE</b>	RefDate	8	Data set last referenced date
<b>SYSNAME</b>	Sysname	8	System name
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Search Help panel (SEARCH)

The Search Help panel shows the results of a **SEARCH** command that was entered on the command line when running SDSF under ISPF. The **SEARCH** command searches the contents of the SDSF help panels.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 88. Columns on the SEARCH Panel

Column name	Title (Displayed)	Width	Description
<b>TITLE</b>	TITLE	5	Section title in HELP. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>LINENUM</b>	Line	4	Line number in help text section
<b>DESC</b>	Help-Text	127	Help text

Table 88. Columns on the SEARCH Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## SMS Groups panel (MSG)

The SMS Groups (MSG) panel allows authorized users to display all storage groups in the system.

Use the SYSNAME command to limit the systems being shown. Remote systems must be running SDSF V2R3 and the SDSF address space must be active on the target system.

When JESplex scoping is in effect, the MSG panel returns data only for those systems that are in the same JESplex as the user.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 89. Columns on the MSG Panel

Column name	Title (Displayed)	Width	Description
<b>STORGRP</b>	NAME	8	Storage group name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>TYPE</b>	Type	16	Storage group type
<b>STATUS</b>	Status	16	SMS status
<b>TOTAL</b>	TotalMB	7	Total space in megabytes (MB)
<b>USEDPCT</b>	Used%	5	Space used percentage
<b>FREE</b>	FreeMB	6	Free space in megabytes (MB)
<b>LFREE</b>	LargestFreeMB	13	Largest free extent in megabytes (MB)
<b>NUMVOL</b>	Volume	6	Number of volumes in storage group
<b>NUMONLINE</b>	Online	6	Number of volumes online
<b>NUMOFFLINE</b>	Offline	7	Number of volumes offline
<b>NUMENABLE</b>	Enabled	7	Number of volumes enabled
<b>NUMDISABLE</b>	Disabled	8	Number of volumes disabled
<b>NUMQUIESCE</b>	Quiesced	8	Number of volumes quiesced
<b>USERID</b>	LastUser	8	Last user to modify storage group definition
<b>CHGDATE</b>	Change-Date-Time	19	Timestamp of last change to definition
<b>DESC</b>	Description	120	Description
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of operating system
<b>USED</b>	UsedMB	7	Used space in megabytes

Table 89. Columns on the SMSG Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## SMS Volumes panel (SMSV)

The SMS Volumes (SMSV) panel allows authorized users to display all SMS volumes in the system.

Use the SYSNAME command to limit the systems being shown. Remote systems must be running SDSF V2R3 and the SDSF address space must be active on the target system.

When JES Plex scoping is in effect, the SMSV panel returns data only for those systems that are in the same JES Plex as the user.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 90. Columns on the SMSV Panel

Column name	Title (Displayed)	Width	Description
<b>VOLSER</b>	VOLSER	6	Volume serial. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>STATUS</b>	Status	16	Volume status
<b>TOTAL</b>	TotalMB	7	Total space in megabytes (MB)
<b>USEDPCT</b>	Used%	5	Space used percentage
<b>FREE</b>	FreeMB	6	Free space in megabytes (MB)
<b>LFREE</b>	LargestFreeMB	13	Largest free extent in megabytes (MB)
<b>DEVSTAT</b>	Device-Status	16	MVS status
<b>UNIT</b>	Unit	4	Unit address if known
<b>STORGRP</b>	StorGrp	8	Storage group
<b>USERID</b>	LastUser	8	Last user to update storage group definition
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of operating system
<b>USED</b>	UsedMB	7	Used space in megabytes
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Status panel (ST)

The Status panel allows the user to display information about jobs, started tasks, and TSO users on the JES queues.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 91. Columns on the ST Panel

Column name	Title (Displayed)	Width	Description	Delay
<b>JNAME</b>	JOBNAME	8	Job name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.	
<b>JNUM</b>	JNum <sup>1</sup>	6	JES job number	
<b>JOBID</b>	JobID	8	JES job ID	
<b>OWNERID</b>	Owner	8	User ID of job owner, or default values of ++ ++++++ or ???????, if user ID not defined to RACF	
<b>JPRIO</b>	Prty	4	JES job queue priority	
<b>QUEUE</b>	Queue	10	JES queue name for job	
<b>JCLASS</b>	C	8	JES input class	
<b>POS</b>	Pos	5	Position in JES queue. The value in the POS column includes jobs that are held or duplicate. SDSF does not show a value for active jobs.	
<b>SYSAFF</b>	SAff	5 (JES2) 8 (JES3)	JES execution system affinity (if any)	
<b>ACTSYS</b>	ASys	4 (JES2) 8 (JES3)	JES active system ID (if job active)	
<b>STATUS</b>	Status	17	Status of job	
<b>PRTDEST</b>	PrtDest	18	JES print destination name	
<b>SECLABEL</b>	SecLabel	8	Security label of job	
<b>TGNUM</b>	TGNum	5	Track groups used by a job	
<b>TGPCT</b>	TGPct	6	Percentage of total track group usage	
<b>ORIGNODE</b>	OrigNode	8	Origin node name	
<b>EXECNODE</b>	ExecNode	8	Execution node name	
<b>DEVID</b>	Device	18	JES device name	
<b>RETCODE</b>	Max-RC	10	Return code information for the job. <ul style="list-style-type: none"> <li>• blank - No completion information</li> <li>• ABENDUxxxx - Job abended or ABEND Sxxx</li> <li>• CANCELED - Job canceled</li> <li>• CC xxxx - Job ended normally</li> <li>• CC xxxx - Job ended by CC</li> <li>• CONV ABEND - Converter abended</li> <li>• JCL ERROR - JCL error</li> <li>• SEC ERROR - Security error</li> <li>• SYS FAIL - System failure</li> </ul>	
<b>SRVCLS</b>	SrvClass	8	Service class	



Table 91. Columns on the ST Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>WLMPOS</b>	WPos	5	Position on the WLM queue	
<b>SCHENV</b>	Scheduling-Env	16	Scheduling environment for the job	
<b>DELAY</b>	Dly	3	Indicator that job processing is delayed <sup>2</sup>	
<b>SSMODE</b>	Mode	4	Subsystem managing the job (JES or WLM)	
<b>ROOMN</b>	RNum	8	JES job room number	X
<b>PNAME</b>	Programmer-Name	20	JES programmer name	X
<b>ACCTN</b>	Acct	4 (JES2) 8 (JES3)	JES account number	X
<b>NOTIFY</b>	Notify	8	TSO user ID from NOTIFY parameter on job card	X
<b>ISYSID</b>	ISys	4 (JES2) 8 (JES3)	JES input system ID	X
<b>TIMER</b>	Rd-Time	8	Time that the job was read in. In the SDSF task of z/OSMF, this is replaced by the Rd-DateTime column.	X
<b>DATER</b>	Rd-Date	8	Date that the job was read in. In the SDSF task of z/OSMF, this is replaced by the Rd-DateTime column.	X
<b>ESYSID</b>	ESys	4 (JES2) 8 (JES3)	JES execution system ID	X
<b>TIMEE</b>	St-Time	8	Time that execution began. In the SDSF task of z/OSMF, this is replaced by the St-DateTime column.	JES3 only.
<b>DATEE</b>	St-Date	8	Date that execution began. In the SDSF task of z/OSMF, this is replaced by the St-DateTime column.	JES3 only.
<b>TIMEN</b>	End-Time	8	Time that execution ended. In the SDSF task of z/OSMF, this is replaced by the End-DateTime column.	X
<b>DATEN</b>	End-Date	8	Date that execution ended. In the SDSF task of z/OSMF, this is replaced by the End-DateTime column.	X
<b>ICARDS</b>	Cards	5	Number of cards read for job	X
<b>MCLASS</b>	MC	2	MSGCLASS of job	X
<b>TSREC</b>	Tot-Lines	10	Total number of spool records for job	X
<b>OFFDEVS</b>	Offs	4	List of offload devices for a job or output that has been offloaded (JES2 only)	
<b>SPIN</b>	Spin	4	Indicator of whether the job is eligible to be spun	

Table 91. Columns on the ST Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>SUBGROUP</b>	SubGroup	8	Submitter group	X
<b>PHASENAME</b>	PhaseName	20	Name of the phase the job is in	
<b>PHASE</b>	Phase	8	Number of the phase the job is in	
<b>JTYPE</b>	Type	4	Type of address space	
<b>JOBACCT1</b>	JobAcct1 <sup>1</sup>	20	Job accounting field 1	X
<b>JOBACCT2</b>	JobAcct2 <sup>1</sup>	20	Job accounting field 2	X
<b>JOBACCT3</b>	JobAcct3 <sup>1</sup>	20	Job accounting field 3	X
<b>JOBACCT4</b>	JobAcct4 <sup>1</sup>	20	Job accounting field 4	X
<b>JOBACCT5</b>	JobAcct5 <sup>1</sup>	20	Job accounting field 5	X
<b>SUBUSER</b>	SubUser	8	Submitting user ID	X
<b>DELAYRSN</b>	DelayRsn	32	Reason for the job delay (JES2 only) <sup>3</sup> . The width can be expanded to 127.	
<b>JOBCORR</b>	JobCorrelator	32	User portion of the job correlator (JES2 only)	
<b>ASID</b>	ASID	5	ASID of the active job	
<b>ASIDX</b>	ASIDX	5	ASID of the active job, in hexadecimal	
<b>SYSNAME</b>	SysName	8	MVS system name where the job is executing	
<b>DATETIMER</b>	Rd-DateTime	19	Date and time that the job was read in. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the Rd-Date and Rd-Time columns.	X
<b>DATETIMEE</b>	St-DateTime	19	Date and time that execution began. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the St-Date and St-Time columns.	X
<b>DATETIMEN</b>	End-DateTime	19	Date and time that execution ended. This column is displayed only with the SDSF task of z/OSMF. It combines the information in the End-Date and End-Time columns.	X
<b>JOBGROUP</b>	JobGroup	8	Name of the job group associated with job (JES2 only)	
<b>JOBGRPID</b>	JobGrpID	8	JES2 job group job ID (JES2 only)	
<b>JOBSET</b>	JobSet	8	Job set within the job group to which this job belongs (JES2 only)	
<b>JGSTATUS</b>	JGStatus	8	Status of the job within the dependency network (JES2 only)	
<b>FLUSHACT</b>	FlushAct	8	Flush action indicator (JES2 only)	
<b>HOLDUNTIL</b>	HoldUntil	19	HOLDUNTIL date and time (JES2 only)	
<b>STARTBY</b>	StartBy	19	STARTBY date and time (JES2 only)	

Table 91. Columns on the ST Panel (continued)

Column name	Title (Displayed)	Width	Description	Delay
<b>WITH</b>	With	19	Name of the job or started task that the job must run with (on the same system) (JES2 only)	
<b>EMAIL</b>	EMail	48	Email address (JES2 only)	X
<b>BEFOREJOB</b>	BeforeJob	9	Name of job that must run before this one (JES2 only)	
<b>BEFOREJID</b>	BeforeJID	4	JobID of job that must run before this one (JES2 only)	
<b>AFTERJOB</b>	AfterJob	8	Name of job that must run after this one (JES2 only)	
<b>AFTERJID</b>	AfterJID	8	JobID of job that must run after this one (JES2 only)	
<b>SCHDELAY</b>	SchDelay	8	Job delayed due to schedule hold or after (JES2 only)	
<b>BERTNUM</b>	BERTNum	7	Number of BERTs used by this job (JES2 only)	
<b>JOENUM</b>	JOENum	6	Number of JOEs used by this job (JES2 only)	
<b>JOEBERTNUM</b>	JOEBERTs	7	Number of BERTs used for this job's JOEs (JES2 only)	
<b>DUBIOUS</b>	Dubious	7	NJE job flagged as dubious (yes or no)	
<b>NETONHOLD</b>	OrigNHold	9	Original number of job completions before this job can be released (JES2 only)	
<b>NETCNHOLD</b>	CurrNHold	9	Current number of job completions before this job can be released (JES2 only)	
<b>NETNORM</b>	Normal	6	Action to be taken when any predecessor job completes normally (D, F, or R) (JES2 only)	
<b>NETABNORM</b>	Abnormal	6	Action to be taken when any predecessor job completes abnormally (D, F, or R) (JES2 only)	
<b>NETNRCMP</b>	NrCmp	5	Network job normal completion (HOLD, NOHO, or FLSH) (JES2 only)	
<b>NETABCMP</b>	AbCmp	5	Network job abnormal completion (NOKP or KEEP) (JES2 only)	
<b>NETOPHOLD</b>	OpHold	6	Operator hold (YES or NO) (JES2 only)	
<b>JOBCRDATE</b>	JobCrDate	19	Job creation date (JES2 only).	
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.	

Notes on the table:

1. This column is not included in the default field list.

2. See the description of the \$D J command in JES2 Commands at [z/OS JES2 Commands](#) .
3. The DelayRsn values are provided by the MVS Subsystem Interface. See [z/OS MVS Using the Subsystem Interface](#) .

## Subsystem panel (SSI)

The Subsystem (SSI) panel allows authorized users to display the subsystems defined to the system. Both dynamic and non-dynamic subsystems are shown.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 92. Columns on the SSI Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	4	Subsystem name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>NAMEX</b>	NameX	8	Subsystem name in hexadecimal
<b>TYPE</b>	Type	8	Subsystem type (JES2 or JES3)
<b>STATUS</b>	Status	8	Subsystem status (active or inactive)
<b>PRIMARY</b>	Primary	7	Primary subsystem (yes or no)
<b>DYNAMIC</b>	Dynamic	7	Dynamic subsystem (yes or no)
<b>SETSSI</b>	SetSSI	6	Subsystem responds to SETSSI (yes or no)
<b>EVENTRTN</b>	EventRtn	8	Event routine indicator (yes or no)
<b>SSCT</b>	SSCT	8	Address of subsystem control table (SSCT)
<b>SSCTSUSE</b>	SSCTSUSE	8	Contents of SSCTSUSE field
<b>SSCTSUS2</b>	SSCTSUS2	8	Contents of SSCTSUS2 field
<b>SSVT</b>	SSVT	8	Address of subsystem vector table (SSVT)
<b>FC04</b>	FC04	4	Function code 04 active (yes or no)
<b>FC08</b>	FC08	4	Function code 08 active (yes or no)
<b>FC09</b>	FC09	4	Function code 09 active (yes or no)
<b>FC10</b>	FC10	4	Function code 10 active (yes or no)
<b>FC14</b>	FC14	4	Function code 14 active (yes or no)
<b>FC50</b>	FC50	4	Function code 50 active (yes or no)
<b>FC54</b>	FC54	4	Function code 54 active (yes or no)
<b>FC58</b>	FC58	8	Function code 58 active (yes or no)
<b>FC78</b>	FC78	8	Function code 78 active (yes or no)
<b>SEQ</b>	Seq	3	Sequence number
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system

Table 92. Columns on the SSI Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## SVC routines and ESR panel (SVC)

The SVC panel allows you to view the SVC (supervisor call instructions) as well as the ESR (extended service routines) table entries.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 93. Columns on the SVC Panel

Column name	Title (Displayed)	Width	Description
<b>NUM</b>	SVC	3	SVC number. This is a fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>NUMX</b>	SVCX	4	SVC number in hexadecimal
<b>ESRCODE</b>	ESRCode	7	ESR code in hexadecimal
<b>MODULE</b>	Module	8	Module name
<b>MACRO</b>	Macro	16	Associated macro
<b>EPA</b>	EPA	8	Entry point address
<b>LOCATION</b>	Location	16	Storage location
<b>AMODE</b>	AMode	5	Addressing mode
<b>TYPE</b>	Type	4	SVC type
<b>SYSNAME</b>	SysName	8	System name
<b>APF</b>	APF	3	APF authorized
<b>ESR</b>	ESR	3	Extended SVC route
<b>MAXESR</b>	MaxESR	6	Maximum number of ESRs
<b>ASF</b>	ASF	3	SVC assist
<b>AR</b>	AR	3	AR mode
<b>UP</b>	Upd	3	SVC updated
<b>NP</b>	NonP	4	Non-preemptive
<b>LOCKS</b>	Locks	10	Locks required
<b>UPDCNT</b>	UpdCnt	6	Update count
<b>UPDMETH</b>	UpdMeth	8	Update method
<b>UPDDATE</b>	UpdDate	10	Date SVC was updated
<b>OLDMOD</b>	OldMod	8	Old module name
<b>OLDEPA</b>	OldEPA	8	Old module EPA

Table 93. Columns on the SVC Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>OLDTYPE</b>	OldType	7	Old SVC type
<b>OLDAPF</b>	OldAPF	6	Old APF setting
<b>OLDASF</b>	OldASF	6	Old ASF setting
<b>OLDAR</b>	OldAR	5	Old AR setting
<b>OLDNP</b>	OldNP	5	Old NP setting
<b>OLDLOCKS</b>	OldLocks	10	Old locks
<b>RETADDR</b>	RetAddr	8	SVCUPDATE return address
<b>SYSLEVEL</b>	SysLevel	25	System level
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## System Symbols panel (SYM)

The System Symbols panel (SYM) allows authorized users to display the system dynamic and static symbols defined for each system in the sysplex. System symbols are elements that allow systems to share parmlib definitions while retaining unique values in those definitions. System symbols act like variables in a program; they can take on different values, based on the input to the program.

By default, the SYM panel is sorted by the system and symbol names. You can change the sort order with the **SORT** command.

The value of a static symbol is typically assigned through parmlib. In contrast, the value of a dynamic symbol is assigned by the system at the time the symbol is evaluated. For example, time and date symbols evaluate to the current time and date. The SYM panel shows the values of dynamic symbols at the time the panel is generated as an example of the value format. Jobs that reference a dynamic symbol may contain a different value when the symbol is evaluated.

**Note:** Action characters on the SYM panel generate commands to display the symbols in the syslog. Because dynamic symbols are not supported by operator commands, issuing an action against a dynamic symbol results in the message NOT VALID FOR TYPE.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 94. Columns on the System Symbols Panel

Column name	Title (Displayed)	Width	Description
<b>SYMBOL</b>	SYMBOL	16	Symbol name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>VALUE</b>	Value	44	Symbol value. For dynamic symbols, it is the current value.
<b>TYPE</b>	Type	8	Symbol type (static or dynamic)
<b>SYSLEVEL</b>	SysLevel	25	Operating system level
<b>SYSNAME</b>	SysName	8	System name
<b>IEASYM</b>	IEASYM	32	IEASYMxx value

Table 94. Columns on the System Symbols Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## System panel (SYS)

The SYS panel shows information about systems in the sysplex.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 95. Columns on the SYS Panel

Column name	Title (Displayed)	Width	Description
<b>SYSNAME</b>	SYSNAME	8	System name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SYSLEVEL</b>	SysLevel	3	Operating system level
<b>CPUPR</b>	CPU%	4	CPU percent busy for the system
<b>SIO</b>	SIO	8	Start I/O rate EXCPs per second
<b>AUXPCT</b>	Aux%	4	Auxiliary storage percentage used
<b>CSAPCT</b>	CSA%	4	Common storage area percentage used
<b>SQAPCT</b>	SQA%	4	System queue area percentage used
<b>ECSAPCT</b>	ECSA%	5	Extended common area percentage used
<b>ESQAPCT</b>	ESQA%	5	Extended system queue area percentage used
<b>UIC</b>	UIC	5	High unreferenced interval count
<b>SPOOLPCT</b>	Spool%	6	Spool utilization for primary JES
<b>CADSPCT</b>	CADS%	5	Common Access Dataspace percentage used of maximum defined
<b>PAGERATE</b>	PageRate	8	Paging rate
<b>REAL</b>	Real	8	Number of real storage frames online
<b>REALAFC</b>	RealAFC	8	Real storage available frame count
<b>REALAFCB</b>	RealAFCB	8	Real storage available frame count below 16MB line
<b>FIXPCT</b>	Fix%	4	Percentage of real storage frames that are fixed
<b>FIXBPCT</b>	FixB%	5	Percentage of real storage frames that are fixed below the 16MB line
<b>MAXASID</b>	MaxASID	7	Maximum number of address spaces
<b>FREEASID</b>	FreeASID	8	Number of free address spaces
<b>BADASID</b>	BadASID	7	Number of non-reusable address spaces
<b>STCNUM</b>	STC	6	Number of active started tasks
<b>TSUNUM</b>	TSU	6	Number of active TSO users

Table 95. Columns on the SYS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>JOBNUM</b>	Job	6	Number of active batch jobs
<b>WTORNUM</b>	WTOR	4	Number of outstanding WTORs
<b>SYSPLEX</b>	Sysplex	8	Sysplex name
<b>LPAR</b>	LPAR	8	LPAR name
<b>VMUSER</b>	VMUser	8	VM user ID
<b>JESNAME</b>	JES	4	Job entry subsystem name
<b>JESNODE</b>	JESNode	8	JES node name
<b>SMF</b>	SMF	4	SMF system ID
<b>IPLVOL</b>	IPLVol	6	IPL volume serial
<b>IPLUNIT</b>	IPLUnit	7	IPL unit address
<b>IPLDATE</b>	IPLDate	19	IPL date
<b>IPLTYPE</b>	IPLType	7	IPL type
<b>IPLDAYS</b>	IPLDays	7	Number of days since last IPL
<b>LOADPARM</b>	LoadParm	8	Load parameter
<b>CVTVERID</b>	CVTVERID	16	CVT version ID associated with system
<b>LOADDSN</b>	LoadDSName	44	LOADxx data set name
<b>LOADUNIT</b>	LoadUnit	8	LOADxx unit address
<b>IEASYS</b>	IEASYS	16	IEASYSxx parameters for the system
<b>IEASYM</b>	IEASYM	16	IEASYMxx parameters for the system
<b>GRS</b>	GRS	4	GRS mode
<b>HWNAME</b>	HWName	8	Hardware name
<b>CPC</b>	CPC	30	Central Processor Complex node descriptor
<b>MSU</b>	MSU	8	MSU rating for processor
<b>SYSMSU</b>	SysMSU	8	MSU rating for image
<b>AVGMSU</b>	AvgMSU	8	Four hour rolling MSU for system
<b>CPUNUM</b>	#CPU	4	Number of online CPUs
<b>ZAAPNUM</b>	#ZAAP	5	Number of online zAAP processors
<b>ZIIPNUM</b>	#ZIIP	5	Number of online zIIP processors
<b>OSCONFIG</b>	OSConfig	8	Operating system configuration
<b>EDT</b>	EDT	3	Eligible device table ID
<b>NUCLST</b>	NUCLST	6	NUCLSTxx member
<b>IEANUC</b>	IEANUC	6	IEANUCxx member
<b>IODFDSN</b>	IODFDSName	44	IODF data set name
<b>IODFDATE</b>	IODFDate	19	Date and time IODF last changed



Table 95. Columns on the SYS Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>CATDSN</b>	CatDSName	44	Master catalog data set name
<b>CATVOL</b>	CatVol	6	Master catalog volume serial
<b>MLA</b>	MLA	3	Multi-level alias setting for system
<b>CATTYPE</b>	CatType	7	Master catalog type
<b>NETID</b>	NetID	8	VTAM network ID
<b>SSCP</b>	SSCP	17	VTAM SSCP name
<b>STATDATE</b>	StatDate	19	Date and time statistics collected
<b>IPLCUNIT</b>	IPLCurr	7	IPL unit address (current)
<b>IODFUNIT</b>	IODFUnit	8	IODF unit address (original)
<b>IODFCUNIT</b>	IODFCurr	8	IODF unit address (current)
<b>JESTYPE</b>	JESType	7	JES type for primary JES (JES2 or JES3)
<b>TZOFFSET</b>	TimeZoneOfs	11	Timezone offset from UTC
<b>HCSUCCESS</b>	HCSuccess	9	Health Check success count
<b>HCSEVLOW</b>	HCSevLow	8	Health Check severity LOW
<b>HCSEVMEDIUM</b>	HCSevMed	8	Health Check severity MEDIUM
<b>HCSEVHIGH</b>	HCSevHigh	9	Health Check severity HIGH
<b>BOOST</b>	Boost	8	System Recovery Boost status
<b>BOOSTTYPE</b>	BoostType	10	System Recovery Boost type
<b>BOOSTCLASS</b>	BoostClass	10	System Recovery Boost class
<b>BOOSTREQ</b>	BoostReq	9	System Recovery Boost requestor
<b>BOOSTDATE</b>	BoostEndDate-Time	19	System Recovery Boost expected end date-time
<b>BOOSTINT</b>	BoostInt	8	System Recovery Boost interval until end
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## System Parameters panel (SYSP)

The SYSP panel shows the parameters that are used when the system is IPLed, including IEASYSxx PARMLIB statements and their sources.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 96. Columns on the SYSP Panel

Column name	Title (Displayed)	Width	Description
<b>PARM</b>	PARM	4	Parameter name. This is a fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.

Table 96. Columns on the SYSP Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>VALUE</b>	Value	36	Parameter value
<b>MEMBER</b>	Member	8	Parameter member
<b>REFNAME</b>	RefName	8	Parameter reference name
<b>SYSNAME</b>	SysName	8	System name
<b>DESCRIPT</b>	Description	127	Parameter description
<b>SYSLEVEL</b>	SysLevel	25	System level
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## System Requests panel (SR)

The SR panel allows the user to display outstanding system requests.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 97. Columns on the SR Panel

Column name	Title (Displayed)	Width	Description
<b>REPLYID</b>	REPLYID	7	Reply ID. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>SYSNAME</b>	SysName	8	Originating system name
<b>JNAME</b>	JobName	8	Name of the issuing job
<b>MSGTEXT</b>	Message-Text	127	Message text
<b>JOBID</b>	JobID	8	ID of the issuing job
<b>DATEE</b>	Date	10	Date the message was issued
<b>TIMEE</b>	Time	8	Time the message was issued
<b>CONSOLE</b>	Console	8	Target console
<b>ROUTECD</b>	RouteCd	7	First 28 routing codes
<b>DESC</b>	Desc	4	Descriptor codes
<b>MSGTYPE</b>	Type	6	Message type
<b>QUEUE</b>	Queue	5	Queue the message is on
<b>AUTOREPLY</b>	AutoReply	9	Automatic reply indicator
<b>AUTODELAY</b>	AutoRDelay	10	Message delay time until the automatic reply is done, in seconds
<b>AUTOTIME</b>	AutoReplyTime	19	Date and time when auto reply will be done
<b>AUTOTEXT</b>	AutoReplyText	16	Automatic reply text

Table 97. Columns on the SR Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## Virtual Storage Map panel (VMAP)

The Virtual Storage Map (VMAP) panel allows authorized users to display the virtual storage map for the system. The map shows the starting and ending virtual addresses of each storage area in the system.

When JESplex scoping is in effect, the VMAP panel returns data only for those systems that are in the same JESplex as the user.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 98. Columns on the VMAP Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	16	Storage area name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>START</b>	Start-Address	17	Starting address of area
<b>END</b>	End-Address	17	Ending address of area
<b>SIZE</b>	Size	6	Size of area (bytes)
<b>ALLOC</b>	Alloc	5	Size of allocated area (bytes)
<b>ALLOCPCT</b>	Alloc%	6	Percentage of area that is allocated
<b>ALLOCHWM</b>	HWM	6	Allocated storage high water mark
<b>ALLOCHWMPC</b>	HWM%	4	High water mark percentage
<b>SEQ</b>	Seq	3	Sequence number of area
<b>SYSNAME</b>	SysName	8	System name
<b>SYSLEVEL</b>	SysLevel	25	Level of operating system
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## WLM Policy panel (WLM)

The WLM policy (WLM) panel shows details about the current WLM policy.

No rows on this panel are highlighted. You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the pattern of the WLM attribute name.

Because the data for this panel comes from the current WLM policy, the panel does not use the SYSNAME value.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 99. Columns on the WLM Policy Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	32	WLM policy attribute name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>VALUE</b>	Value	32	Policy attribute value.
<b>DATEVALUE</b>	DateValue	19	Policy attribute date value.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## WLM Report Class panel (REPC)

The WLM report class (REPC) panel shows details about all report classes defined in the current WLM policy.

All rows on this panel are highlighted. You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the pattern of the report class name.

Because the data for this panel comes from the current WLM policy, the panel does not use the SYSNAME value.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 100. Columns on the WLM Report Class Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	8	Report class name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>DESC</b>	Description	32	Report class description.
<b>POLNAME</b>	Policy	8	Policy name in effect.
<b>POLDESC</b>	PolicyDescription	32	Policy description.
<b>POLACTDATE</b>	PolicyActDate	19	Policy activation timestamp
<b>CRUSER</b>	CrUser	8	Userid creating policydefinition.
<b>CRDATE</b>	CrDate	19	Timestamp when policy definition created.
<b>UPDUSER</b>	UpdUser	8	Userid last updating policy definition.
<b>UPDDATE</b>	UpdDate	19	Timestamp when policy definition was last updated.
<b>SYSNAME</b>	SysName	8	.System name.
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

Table 100. Columns on the WLM Report Class Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>TENANT</b>	Tenant	6	Tenant report class (yes or no).
<b>TENANTNAME</b>	TenantName	10	Associated tenant resource group.

## WLM Resource Group panel (RGRP)

The WLM resource group (RGRP) panel shows details about all resource groups defined in the current WLM policy.

All rows on this panel are highlighted. You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the pattern of the resource group name.

Because the data for this panel comes from the current WLM policy, the panel does not use the SYSNAME value.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 101. Columns on the WLM Resource Group Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	8	Resource group name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>DESC</b>	Description	32	Resource group description.
<b>POLNAME</b>	Policy	8	Policy name in effect.
<b>MINSU</b>	MinSU	8	Minimum unweighted CPU service units per second.
<b>MAXSU</b>	MaxSU	8	Maximum unweighted CPU service units per second.
<b>MINLPARPCT</b>	MinLPAR%	8	Minimum percentage of LPAR share.
<b>MAXLPARPCT</b>	MaxLPAR%	8	Maximum percentage of LPAR share.
<b>MINCPUPCT</b>	MinCPU%	7	Minimum percentage of single CPU capacity.
<b>MAXCPUPCT</b>	MaxCPU%	7	Maximum percentage of single CPU capacity.
<b>MEMLIMIT</b>	MemLimit	8	Maximum memory limit (bytes).
<b>POLDESC</b>	PolicyDescription	32	Policy description.
<b>POLACTDATE</b>	PolicyActDate	19	Policy activation timestamp
<b>CRUSER</b>	CrUser	8	Userid creating policy definition.
<b>CRDATE</b>	CrDate	19	Timestamp when policy definition created.
<b>UPDUSER</b>	UpdUser	8	Userid last updating policy definition.
<b>UPDDATE</b>	UpdDate	19	Timestamp when policy definition was last updated.
<b>SYSNAME</b>	SysName	8	.System name.
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system.

Table 101. Columns on the WLM Resource Group Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.
<b>TENANT</b>	Tenant	6	Tenant resource group (yes or no).
<b>INCLSPEC</b>	InclSpec	8	Include specialty processor (yes or no).
<b>TENANTID</b>	TenantID	8	Tenant ID.
<b>TENANTNAME</b>	TenantName	32	Tenant name.
<b>SOLUTIONID</b>	SolutionID	60	Solution ID.

## WLM Service Classes panel (SRVC)

The WLM service classes (SRVC) panel shows details about all service classes defined in the current WLM policy.

Rows for service classes with an importance level greater than zero are highlighted.

You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the pattern of the service class name.

Because the data for this panel comes from the current WLM policy, the panel does not use the SYSNAME value.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 102. Columns on the WLM Service Classes Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	8	Service class name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>RESGROUP</b>	ResGroup	8	Resource group.
<b>PERIOD</b>	Per	3	Period number.
<b>DESC</b>	Description	32	Service class description.
<b>DURATION</b>	Duration	8	Period duration in service units or zero for last period.
<b>IMPORTANCE</b>	Imp	3	Importance level in range 1 (most important) to 5.
<b>CPUCRIT</b>	CPUCrit	7	CPU critical indicator (yes or no).
<b>STORPROT</b>	StorProt	8	Storage protection indicator (yes or no).
<b>IOPRIO</b>	IOPrio	7	I/O priority group (normal or high).
<b>HONORPRIO</b>	HonorPrio	9	Honor priority (default or no).
<b>MAXPERIOD</b>	MaxPer	6	Maximum number of periods.
<b>WORKLOAD</b>	WorkLoad	8	Workload name.
<b>GOAL</b>	Goal	40	Service class goal.

Table 102. Columns on the WLM Service Classes Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>TRANSS</b>	TranSSUse	9	Used by any transaction subsystem type (yes or no).
<b>ASIDSS</b>	AddrSpcSSUse	12	Used by any address space subsystem type (yes or no).
<b>ENCSS</b>	EncSSUse	8	Used by any enclave subsystem type (yes or no).
<b>SYSH</b>	SysHUse	7	Used in non-MVS logical partitions (yes or no).
<b>CRUSER</b>	CrUser	8	Userid creating service class definition.
<b>CRDATE</b>	CrDate	19	Timestamp when service class definition created.
<b>UPDUSER</b>	UpdUser	8	Userid last updating service class definition.
<b>UPDDATE</b>	UpdDate	19	Timestamp when service class definition last updated.
<b>POLNAME</b>	Policy	8	Policy name in effect.
<b>POLDESC</b>	PolicyDescription	32	Policy description.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## WLM Workload panel (WKLD)

The WLM workload (WKLD) panel shows details about all workloads defined in the current WLM policy.

All rows on this panel are highlighted. You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts a single parameter for the pattern of the workload name.

Because the data for this panel comes from the current WLM policy, the panel does not use the SYSNAME value.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 103. Columns on the WLM Workload Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	8	Workload name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>DESC</b>	Description	32	Workload description.
<b>POLNAME</b>	Policy	8	Policy name in effect.
<b>POLDESC</b>	PolicyDescription	32	Policy description.
<b>POLACTDATE</b>	PolicyActDate	19	Policy activation timestamp
<b>CRUSER</b>	CrUser	8	Userid creating policy definition.
<b>CRDATE</b>	CrDate	19	Timestamp when policy definition created.
<b>UPDUSER</b>	UpdUser	8	Userid last updating policy definition.
<b>UPDDATE</b>	UpdDate	19	Timestamp when policy definition was last updated.

Table 103. Columns on the WLM Workload Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>SYSNAME</b>	SysName	8	.System name.
<b>SYSLEVEL</b>	SysLevel	25	Level of the operating system.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.

## XCF Members and Groups panel (XCFM)

The XCF members and groups (XCFM) panel lists the XCF groups and members defined in the sysplex.

Rows representing active members are highlighted.

You can use the fast path select (S) and filter commands to customize the rows being shown. The command accepts two parameters: the first is a group name pattern, and the second is a member name pattern.

This panel does not use the SYSNAME value to control which systems are shown on the panel.

In REXX execs and Java programs, reference columns by name rather than by title.

Table 104. Columns on the XCF Members and Groups Panel

Column name	Title (Displayed)	Width	Description
<b>NAME</b>	NAME	8	XCF group name. This is the fixed field. It is ignored if coded on an FLD statement or ISFFLD macro.
<b>MEMBER</b>	Member	16	XCF member name.
<b>JNAME</b>	JobName	8	Owning job name.
<b>SYSNAME</b>	SysName	8	System name.
<b>STALLED</b>	Stalled	7	Member stalled (yes or no).
<b>SENDCNT</b>	Sends	8	Send count.
<b>RECVCNT</b>	Receives	8	Receive count.
<b>FUNCTION</b>	Function	24	Member function.
<b>CANRECV</b>	CanRecv	7	IXCJOIN can receive setting (yes or no).
<b>CANREPLY</b>	CanReply	8	IXCJOIN can reply setting (yes or no).
<b>GT61KMSG</b>	GT61KMsg	8	IXCJOIN GT61KMSG settings (yes or no).
<b>CRITICAL</b>	Critical	8	Member critical designation (yes or no).
<b>MEMASSOC</b>	MemAssoc	9	Member association (task, jobstep, or addrspace).
<b>TERMLEVEL</b>	TermLevel	9	Termination level (memassoc, addrspace, or system).
<b>INTERVAL</b>	Interval	8	IXCJOIN interval (0.01 seconds).
<b>STATDATE</b>	StatusDate	19	Last change to status timestamp.
<b>DEFDATE</b>	JoinedDate	19	Member joined timestamp.



Table 104. Columns on the XCF Members and Groups Panel (continued)

Column name	Title (Displayed)	Width	Description
<b>DEACTDATE</b>	DeactDate	19	Timestamp when member became failed or quiesced.
<b>USERDATA</b>	UserData	8	User data.
<b>USERSTATE</b>	UserState	64	User state.
<b>ISFEND</b>	.END	4	End of list marker. All columns that appear after this column will be hidden. Ignored if specified on the ISFFLD macro in ISFPARMS. The title and width cannot be changed using the FLDENT statement or through the <b>ARRANGE</b> command.



---

## Chapter 5. Using SAF for security

Security for SDSF must be implemented via the Security Authorization Facility (SAF) interface, with an external security manager such as RACF, to provide security for SDSF. SAF is part of the z/OS environment and is always present. SDSF uses the SAF interface to route authorization requests to the external security manager.

**Important:** SDSF does not support security via the ISFPARMS mechanism. All users of SDSF 2.5 must use the Security Authorization Facility (SAF) with an External Security Manager (ESM) such as RACF, ACF2, or TSS. For information about migrating from using SDSF security with ISFPARMS (ISFPRMxx or ISFPARMS with assembler macros) to RACF security, refer to [z/OS SDSF Security Migration Guide](#).

The benefits of using SAF for SDSF security are:

- Dynamic change of security profiles
- Single image of security information
- Simple introduction of security philosophy
- Auditability
- Granular protection

---

### Relationship of SAF and ISFPARMS

Although you must use SAF for all SDSF security, you need ISFPARMS to control:

- Global values (ISFPMAC macro or OPTIONS statement)
- Any values for groups that are not related to security (ISFGRP macro or GROUP statement). .
- Code page (ISFTR macro or TRTAB statement)

If you want to customize the columns on SDSF panels, you also need ISFFLD macros or FLD statements.

---

### Changing authorization dynamically

SAF security provides a dynamic means of authorizing SDSF users to issue commands and process job output. Once a user starts an SDSF session, SDSF checks user authorization for every interaction with SDSF resources. If permissions change while a user is in SDSF, it may be necessary for the user to re-access SDSF or to log on again to pick up the permissions change.

---

### Auditing access attempts

If you are using RACF as a security product, RACF logs access attempts to protected SDSF resources according to the audit setting in the RACF profile for the resource. Logging is performed for all access attempts except for the following resource names in the SDSF class:

- ISFOPER.DEST.jesx
- ISFAUTH.DEST.destname
- ISFAUTH.DEST.destname.DATASET.dsname
- ISFOPER.ANYDEST.jesx
- All resource names beginning with ISFATTR.

Logging is not performed for these access attempts because the user is not specifically trying to gain access to those resources.

For RACF auditing information, refer to [z/OS Security Server RACF Auditor's Guide](#).

## Diagnosing security

---

SDSF's security trace function helps you understand and diagnose SDSF security using SAF. In response to the actions that you take, such as issuing commands or overtyping columns, it issues messages that describe the associated SAF resources. You control security trace with commands, REXX variable or Java methods.

- With the **SET SECTRACE** command, you turn security tracing on and specify how the associated messages are handled.
  - **SET SECTRACE ON** causes the trace messages to be sent to the ULOG.
  - **SET SECTRACE WTP** causes the messages to be issued as write-to-programmer messages. Use this if security prevents you from accessing SDSF or the user log.
- With the **SECTRACE** option on the **SDSF** command, you can turn security tracing on as soon as you access SDSF.
- When SDSF SECTRACE is active, SDSFAUX SECTRACE is also activated. SDSFAUX uses SECTRACE to record the results of security calls for diagnosis.
- With the ISFSECTRACE REXX special variable, you can control security tracing from a REXX exec.
- With ISFRequestSettings methods addISFSecTrace and removeISFSecTrace, you can control security tracing from a Java program.

For more information about the commands, refer to the online help. You could use the SEARCH command, for example, SEARCH SET SECTRACE. For more information about the REXX special variable and Java, refer to *z/OS SDSF User's Guide*.

## SAF concepts for SDSF resources

---

SDSF interacts with SAF to control access to the following resources:

- Membership in SDSF groups
- SDSF panels
- SDSF authorized commands
- Use of the / command to issue MVS and JES commands and receive responses
- Overtypable fields
- Destination names
- Operator authority by destination
- Devices and system resources, such as initiators, printers, lines, nodes and scheduling environments
- Jobs affected by action characters and overtypeable fields
- Output groups affected by action characters and overtypeable fields
- SYSIN/SYSOUT data sets for browsing and viewing
- MVS and JES commands that are generated by action characters and overtypeable fields
- Reverting to ISFPARMS in assembler macro format when the initial ISFPRMxx fails to activate or the server is started in NOPARM mode
- Use of the server MODIFY command
- Access to the log stream and the JES logical log

The SDSF resources are grouped into classes, with each resource having a resource name. SDSF translates an asterisk (\*) in resource names to a plus (+).

To accomplish security through SAF, you permit or deny users access to the SDSF resources by use of their classes and resource names.

# Protecting SDSF function

An SDSF function often requires access authority to more than one class and resource. In order to use the function, a user must have proper authority to all of the required resources.

For example, to overtype a field, a user must have access to the panel, to the overtypeable field, to the MVS or JES command that will be generated, and to the object (for example, the job, output group, initiator, or printer) being acted upon.

SDSF users must have authority to the resources at the correct access level (READ, CONTROL, UPDATE, or ALTER).

The classes used by SDSF must be defined to your security product. If you are using RACF you do not need to define the classes because they are already included in the IBM-supplied class descriptor table, ICHRRCDX.

The relationship of SDSF functions, classes and resources is shown in [“SAF classes and resources for SDSF function” on page 215](#). For some resources, only the highest level qualifier is shown. Refer to [Appendix B, “SDSF resource names for SAF security,” on page 503](#) for a table of complete SDSF resource names.

You can use the CONSOLE class to restrict the use of resources in the OPERCMDS and WRITER classes to SDSF users only. The restriction is in effect for the duration of the SDSF session. Use of the CONSOLE class is described in [“Using conditional access” on page 222](#).

## Protecting SDSF function in a sysplex environment

Several of SDSF's panels can show data from all members in the MAS in a JES2 environment. In that environment, security is as follows:

- Access to the display is controlled by the profiles on the local system, that is, the system the user is logged on to.
- Access to the objects displayed on the panel (for example, printers on the PR panel) is controlled by SAF resources that include the name of the JES subsystem for the system the object is on. In this topic, the resources show a variable *jesx* which you replace with the subsystem name.
- Which systems are included on the panel is controlled by the SYSNAME command.

## SAF classes and resources for SDSF function

This topic summarizes the SAF resources required to protect SDSF function.

Table 105. SDSF Classes and Resources

Class	SDSF Resource	Resource Name
JESSPOOL	Jobs, output groups, and SYSIN/ SYROUT data sets	<i>nodeid.userid.jobname.jobid</i> <i>nodeid.userid.jobname.jobid.</i> <i>GROUP.ogroupid</i> <i>nodeid.userid.jobname.jobid.</i> <i>Ddsid.dsname</i>
JESSPOOL	Job step information	<i>nodeid.userid.jobname.jobid.EVENTLOG.SMFSTEP</i> <i>nodeid.userid.jobname.jobid.EVENTLOG.STEPDATA</i>
JESSPOOL	Access to the JES logical log, to display the SYSLOG	<i>nodeid.+MASTER+.SYSLOG.SYSTEM.</i> <i>sysname</i>

Table 105. SDSF Classes and Resources (continued)

<b>Class</b>	<b>SDSF Resource</b>	<b>Resource Name</b>
<b>LOGSTRM</b>	Access to the log stream, to display the OPERLOG	SYSPLEX.OPERLOG
	Access to the log stream, to display check history	<i>log-stream-name</i>
<b>OPERCMDS</b>	Generated MVS and JES commands	Resource name is dependent on command generated
	Server MODIFY command	Resource name is dependent on command parameters
<b>SDSF</b>	Membership in groups	GROUP. <i>groupname</i> . <i>servername</i>
	Connection to SDSFAUX	ISF.CONNECT. <i>sysname</i>
	APF data sets	ISFAPF. <i>datasetname</i>
	CF connections	ISFCFC. <i>connectionname</i>
	CF data sets	ISFCFD. <i>function</i>
	CF structures	ISFCFS. <i>structurename</i>
	Device activity	ISFDEV. <i>volser</i>
	DYNX data sets	ISFDYNX. <i>exitname</i>
	Enqueues	ISFENQ. <i>majorname.sysname</i>
	File systems	ISFFS. <i>filesystemname</i>
	Generic tracker events	ISFGT. <i>eventowner</i>
	JES job resources	ISFJRJ. <i>name.jobid</i>
	JES resource alerts	ISFRMA. <i>type.jesx</i>
	JES resource information	ISFJRI. <i>name.jesx</i>
	JES resources	ISFRM. <i>resname.jesx</i>
	Job classes	ISFJOBCL. <i>classname.jesx</i>
	Job DDnames	ISFJOB.DDNAME. <i>owner.jobname.sysname</i>
	Job modules	ISFJOB.MODULE. <i>owner.jobname.sysname</i>
	Job tasks	ISFJOB.TASK. <i>owner.jobname.sysname</i>
	Link list data sets	ISFLNK. <i>datasetname</i>
	Link list sets	ISFLLS. <i>name.setsysname</i>
	MAS members	ISFMEMB. <i>name.jesx</i>
	Memory	ISFJOB.STORAGE. <i>owner.jobname.sysname</i>
	Network activity	ISFNETACT. <i>jobname</i>
	NJE connection objects (appl)	ISFAPPL. <i>devname.jesx</i>

Table 105. SDSF Classes and Resources (continued)

Class	SDSF Resource	Resource Name
<b>SDSF (continued)</b>	NJE connection objects (sockets)	ISFSOCK.devname.jesx
	NJE lines	ISFLINE.name.jesx
	Parmlib data sets	ISFPARM.datasetname
	Page data sets	ISFPAG.datasetname
	Proclib data sets	ISFPLIB.proclib-name
	SMS storage groups	ISFSTORGRP.storagegroupname
	SMS volumes	ISFSMSVOL.volume
	Spool offloaders	ISFSO.name.jesx
	Spool volumes	ISFSP.name.jesx
	Subsystems	ISFSUBSYS.subsysname
	System parameters	ISFSYSP.parmname
	System requests	ISFSR.type.sysname.jobname
	System symbols	ISFSYM.symbolname.sysname
	Systems	ISFSYS.sysplexname.systemname
	SDSF panels and authorized commands	ISFCMD (High-level qualifier)
	MVS/JES command line commands (/)	ISFOPER.SYSTEM
	Overtypable fields	ISFATTR (High-level qualifier)
	Destination names	ISFOPER.ANYDEST.jesx (all destinations) ISFAUTH.DEST.destname
	Operator authority by destination	ISFOPER.DEST ISFAUTH.DEST (High-level qualifiers)
	Enclaves	ISFENC.subsys-type.subsys-name
	Initiators	ISFINIT.I(xx).jesx
	Job classes	ISFJOBCL.class.jesx
	Job devices	ISFJDD.type.sysname
	JC action character (display job module)	ISFCMD.ODSP.CDE.system ISFJOB.MODULE.owner.jobname.system
	JD action character (display job devices)	ISFCMD.ODSP.DEVICE.system ISFJOB.DDNAME.owner.jobname.system
	JM action character (display job memory)	ISFCMD.ODSP.STORAGE.system ISFJOB.STORAGE.owner.jobname.system

Table 105. SDSF Classes and Resources (continued)

<b>Class</b>	<b>SDSF Resource</b>	<b>Resource Name</b>
<b>SDSF (continued)</b>	JY action character (display job delays)	ISFDISP.DELAY.owner.jobname
	JT action character (display job task)	ISFCMD.ODSP.TCB.system ISFJOB.TASK.owner.jobname.system
	MAS or JESPLEX members	ISFMEMB.membername.jesx
	Lines	ISFLINE.devicename.jesx
	Network connections	ISFAPPL.devicename.jesx ISFLINE.devicename.jesx ISFSOCK.devicename.jesx
	Network servers	ISFNS.devicename.jesx
	Nodes	ISFNODE.nodename.jesx
	Spool offloaders (JES2 only)	ISFSO.devicename.jesx
	Readers	ISFRDR.devicename.jesx
	JES resources (JES2 only)	ISFRM.resource.jesx
	Spool volumes	ISFSP.volser.jesx
	Spool partitions	ISFSP.partname.jesx
	WLM resources	ISFRES.resource.system
	Scheduling environments	ISFSE.scheduling-env.system
	z/OS UNIX processes	ISFPROC.owner.jobname
	System requests	ISFSR.type.system.jobname
	Reverting to ISFPARMS in assembler macro format	SERVER.NOPARM
	EMCS consoles	ISFEMCS.consolename
	JES subsystems	ISFJES.subsysname
	Job class members	ISFJOBCL.class.jesx
	OMVS options	ISFOMVS.optionname
	Resource monitor alerts	ISFRMS.type.jesx
	XCF groups and members	ISFXCFM.membername
	JESInfo resources	ISFJRI.resourcename.jesx
	JESInfo by job resources	ISFJRJ.jobname.jobid
<b>WRITER</b>	Printers and punches	jesx.LOCAL.devicename
		jesx.RJE.devicename
<b>XFACILIT</b>	Checks from IBM Health Checker for z/OS	HZS.sysname.checkowner.checkname.action



---

## Chapter 6. SDSF and RACF

This topic provides general information about RACF security. It also demonstrates how to establish SAF security for SDSF tasks and resources using classes, resource names, and access levels.

For specific information about how to protect SDSF tasks and resources, see [Chapter 7, “Protecting SDSF functions,”](#) on page 225.

---

### Security administration

A key feature of RACF is its hierarchical management structure. The RACF security administrator is defined at the top of the hierarchy, with authority to control security for the whole system. The RACF security administrator has the authority to work with RACF profiles and system-wide settings. The RACF auditor produces reports of security-relevant activity based on auditing records generated by RACF.

RACF security administrators generally have system-SPECIAL authority. This allows them to issue any RACF command and change any RACF profile (except for some auditing specific operands).

For complete information about the authorities required to issue RACF commands, and for information on delegating authority and the scope of a RACF group, refer to [z/OS Security Server RACF Security Administrator's Guide](#).

For information on the RACF requirements for issuing RACF commands, see the description of the specific command in [z/OS Security Server RACF Command Language Reference](#).

---

### Brief summary of RACF commands

Much of the RACF activity dealing with protected SDSF resources involves creating, changing, and deleting *general resource profiles*.

- To create a resource profile, use the RDEFINE command. Generally, once you have created a profile, you then create an access list for the profile using the PERMIT command. For example:

```
RDEFINE class_name profile_name UACC(NONE)
PERMIT profile_name CLASS(class_name) ID(user or group)
ACCESS(access_authority)
```

This document provides examples of how to do this for SDSF-related classes.

- To remove the entry for a user or group from an access list, issue the PERMIT command with the DELETE operand instead of the ACCESS operand.

```
PERMIT profile_name CLASS(class_name) ID(user or group) DELETE
```

- If you want to change a profile, for example, changing UACC from NONE to READ, use the RALTER command:

```
RALTER class_name profile_name UACC(READ)
```

- To delete a resource profile, use the RDELETE command. For example:

```
RDELETE class_name profile_name
```

- You can copy an access list from one profile to another. To do so, specify the FROM operand on the PERMIT command:

```
PERMIT profile_name CLASS(class_name)
FROM(existing-profile_name) FCLASS(class_name)
```

- You can copy information from one profile to another. To do so, specify the FROM operand on the RDEFINE or RALTER command:

```
RDEFINE class_name profile__name
FROM(existing-profile_name) FCLASS(class_name)
```

**Note:** Do not plan to do this if you are using resource group names.

- To list the names of profiles in a particular class, use the SEARCH command. The following command lists the profiles in the SDSF class:

```
SEARCH CLASS(SDSF)
```

The SDSF class must be RACLISTed. Whenever you add or change a profile in the SDSF class, you must refresh the class to pick up the change. The following command shows how to refresh the class:

```
SETR RACLIST(SDSF) REFRESH
```

## Delegation of RACF administrative authority

Your installation's security plan should indicate who is responsible for providing security for SDSF.

If you do not have the system-SPECIAL attribute, you need to be given the authority to do the following RACF-related tasks:

- Define and maintain profiles in SDSF-related general resource classes. In general, this authority is granted by assigning a user the CLAUTH (class authority) attribute in the specified classes. For example, the security administrator could issue the following command:

```
ALTUSER your_userid CLAUTH(SDSF)
```

Some of the general resource classes mentioned in this document (such as OPERCMDS and JESSPOOL) affect the operation of products other than SDSF. If you are not the RACF security administrator, you may need to ask that person to define profiles at your request.

- Add RACF user profiles to the system. In general, this authority is granted by assigning an administrator the CLAUTH (class authority) attribute in the user's profile. For example, the security administrator could issue the following command:

```
ALTUSER your_userid CLAUTH(USER)
```

Whenever you add a user to the system, you must assign that user a default connect group. Assigning that user a default connect group changes the membership of the group (by adding the user as a member of the group).

For more information about RACF general resource profiles, see [z/OS Security Server RACF Security Administrator's Guide](#). For information about the resource names used by JES2, see [z/OS JES2 Initialization and Tuning Guide](#). For information about the resource names used by JES3, see [z/OS JES3 Initialization and Tuning Guide](#).

## SDSF resource group class

The IBM-supplied class descriptor table provides a resource *group* class (GSDSF) and a resource *member* class (SDSF). For a resource group class, each user or group of users permitted access to that resource group is permitted access to all members of the resource group. For each GSDSF class created, a second class representing the members must also be created.

### Creating a resource group profile

Resource group profiles enable you to protect multiple resources with one profile. However, the resources do not have to have similar names.

A resource group profile is a general resource profile with the following special characteristics:

- Its name does not match the resource it protects.

- The ADDMEM operand of the RDEFINE command specifies the resources it protects (not the profile name itself).
- The related member class (not the resource class itself) must be RACLISTed. For example, the SDSF class must be RACLISTed, not the GSDSF class. Use the SETROPTS command with the RACLIST operand for this task.

For more information on RACF group profiles, see [z/OS Security Server RACF Security Administrator's Guide](#).

## Establishing SAF security with RACF

---

To accomplish security through SAF with RACF, you:

1. Activate generic processing before defining profiles, using the SETROPTS command.
2. Define profiles to protect the resources in the appropriate classes, using the RDEFINE command. (Classes are already defined for RACF. You must define them for other security products.)

Begin with generic profiles for broad access to resources and then define generic or discrete profiles that are more restrictive.

3. Permit users to access appropriate profiles in each class with the necessary access levels, using the PERMIT command.
4. Activate the classes, using the SETROPTS command.

You should also review installation exit routines for SAF control points. Refer to [Chapter 8, “Using installation exit routines,”](#) on page 349 for more information.

### RACF authorization checking

When the class a resource is in is inactive, or the profile to protect the resource is not defined, the result varies with the default return code for the class:

- The SDSF and OPERCMDS classes, as defined by RACF, have a default return of 04, and return an indeterminate result. Authorization is determined by the CONNECT AUXSAF(FAILRC4|NOFAILRC4) option.
- The JESSPOOL and WRITER classes, as defined by RACF, have a default return code of 08. The request fails.

### Considerations for broad access

The examples in this information typically show generic profiles that allow the user broad access to resources. The universal access authority (UACC) function of NONE is used to protect resources for all users on the system. Users of the system who are not SDSF users may be affected when trying to access those resources. The examples of WRITER class profiles have UACC(READ) so that printers can select work for all users.

If you begin by defining broad generic profiles, you can then define more restrictive generic or discrete profiles. Users permitted to access the broad profiles must also be permitted to access the more restrictive profiles if they are to retain access to all the resources.

## Using RACLIST and REFRESH

---

The SETROPTS RACLIST command copies the base segments of generic and discrete profiles into virtual storage. The profile copies are put in their own data space. RACF uses these profile copies to check the authorization of any user who wants to access a resource protected by them. Using RACLIST for the security classes improves performance.

Once a class is RACLISTed, any changes to the profiles in the class require that the class be RACLIST REFRESHed.

See the discussions of generic profiles and the RACLIST option in [z/OS Security Server RACF Command Language Reference](#).

## Using RACLIST and REFRESH with the SDSF class

When running RACF, the SDSF class must be RACLISTed.

By default, SDSF and SDSFAUX fail all authorization requests that result in return code 04 (indeterminate) from SAF. You can change this by specifying AUXSAF(NOFAILRC4) on the CONNECT statement of ISFPRMxx.

If you have not already done so, you must use the SETROPTS RACLIST command for the SDSF class.

For example, assume that you issue the following command to RACLIST the SDSF class:

```
SETROPTS RACLIST(SDSF)
```

If you then change profiles in the SDSF class, you must issue a RACLIST REFRESH command for those changes to take effect:

```
SETROPTS RACLIST(SDSF) REFRESH
```

See the discussions of generic profiles and the RACLIST option in [z/OS Security Server RACF Command Language Reference](#).

## Using RACLIST and REFRESH with the OPERCMDS class

When using RACF, you must use the SETROPTS RACLIST command for the OPERCMDS class. If you then make changes to these OPERCMDS profiles, you must issue a SETROPTS RACLIST REFRESH command for those changes to take effect.

For example, if you issue the following command to permit GROUP1 to resources in the OPERCMDS class:

```
PERMIT jess.** CLASS(OPERCMDS) ID(GROUP1) ACCESS(CONTROL)
```

you must then use the REFRESH operand for the change to be effective:

```
SETROPTS RACLIST(OPERCMDS) REFRESH
```

See the discussions of generic profiles and the RACLIST option in [z/OS Security Server RACF Command Language Reference](#).

## Using conditional access

If you use generic profiles (as in the preceding examples) to give the user access to all JES and MVS commands, the profiles not only include protection for generated MVS and JES commands within SDSF, but also for those commands used outside of SDSF.

Because of this, you may want to make the user's access conditional, only in effect when he or she is using SDSF. You can provide this conditional access for the WRITER and OPERCMDS classes. With RACF, this is done with the clause WHEN(CONSOLE(SDSF)).

To use this conditional access checking, you must have the CONSOLE class active and the SDSF console defined in the CONSOLE class.

For example, you would issue the following RACF commands:

```
SETROPTS CLASSACT(CONSOLE  
RDEFINE CONSOLE SDSF UACC(NONE)
```

Then, to give conditional access (to permit users to issue JES2 commands only while running SDSF):

```
RDEFINE OPERCMDS JES2.** UACC NONE
PERMIT JES2.** CLASS(OPERCMDS)ID(userid or groupid) ACCESS(CONTROL)
WHEN(CONSOLE(SDSF))
```

To permit users unconditionally to issue all JES2 commands:

```
PERMIT JES2.** CLASS(OPERCMDS)ID(userid or groupid) ACCESS(CONTROL)
```

See also the discussions of [“Action characters”](#) on page 225, [“Overtimeable fields”](#) on page 290, [“Printers”](#) on page 333, and [“Punches”](#) on page 335.

## Sample RACF commands

---

SDSF provides sample RACF commands for SDSF security in member ISFRAC of ISF.SISFEXEC.

## Multilevel Security

---

SDSF supports the multilevel security in z/OS V1R5. For information on implementing multilevel security, including the resources used with SDSF, see [z/OS Introduction and Release Guide](#).



---

## Chapter 7. Protecting SDSF functions

This topic describes how to protect each of the SDSF functions, which are presented in alphabetical order. It includes discussions and RACF examples.

---

### Access requirements for SDSF users

As of SDSF 2.5, access to SDSF requires the following:

- The SDSF server must be active.
- The user must have READ access to the ISF.CONNECT.*sysname* resource in the SDSF class. This allows the connection to the SDSF server.
- The user must map to an SDSF group. For information about group membership, see [“Using SAF to control group membership”](#) on page 17.

---

### Action characters

Most action characters cause an interaction with two resources:

- The object of the action character, such as an initiator, printer, MAS member, job, or data set
- The MVS command that is generated by the action

When these resources are protected, a user must have authority to both resources to use the action characters. For ISPF-only actions such as browse and edit, the user must be permitted to open the data set.

A few action characters that do not cause an interaction with a resource for an object or a system command are protected as separate resources.

Protecting action characters is the same whether they are typed in the NP column or issued from the command line.

### Protecting the objects of action characters

The objects of action characters are such things as initiators in the SDSF class, printers and punches in the WRITER class, and jobs, output groups, and SYSIN/SYSOUT data sets in the JESSPOOL class.

The resource name that protects the object and the access level required varies from panel to panel. For information about protecting the objects of action characters, see

- [“Authorized program facility data sets”](#) on page 260
- [“Checks on the CK and CKH panels”](#) on page 267
- [“Destination operator authority”](#) on page 269
- [“Device activity information”](#) on page 270
- [“Dynamic exit information”](#) on page 271
- [“EMCS consoles information”](#) on page 271
- [“Enclaves”](#) on page 272
- [“Enqueue information”](#) on page 272
- [“File system information”](#) on page 273
- [“Generic tracker events”](#) on page 273
- [“Initiators”](#) on page 274
- [“JES2 resources on the RM panel”](#) on page 274
- [“JESInfo resources”](#) on page 281

- [“JESInfo by job resources” on page 281](#)
- [“JES subsystems” on page 276](#)
- [“Job classes” on page 276](#)
- [“Job class members” on page 277](#)
- [“Job devices” on page 277](#)
- [“Jobs, job groups, output groups, and SYSIN/SYSOUT data sets” on page 278](#)
- [“Lines” on page 282](#)
- [“Link list data sets” on page 283](#)
- [“Link list sets” on page 283](#)
- [“MAS and JESPLEX members” on page 283](#)
- [“Memory contents” on page 285](#)
- [“Network activity” on page 286](#)
- [“Network connections” on page 287](#)
- [“Network servers” on page 287](#)
- [“Nodes” on page 288](#)
- [“OMVS options” on page 289](#)
- [“Page data sets” on page 332](#)
- [“PARMLIB data sets” on page 332](#)
- [“Printers” on page 333](#)
- [“Processes \(z/OS UNIX System Services\)” on page 334](#)
- [“Proclibs” on page 335](#)
- [“Punches” on page 335](#)
- [“Readers” on page 336](#)
- [“Resource monitor alerts” on page 337](#)
- [“Resources defined to WLM” on page 337](#)
- [“Scheduling environments” on page 338](#)
- [“SMS storage groups” on page 339](#)
- [“SMS volumes” on page 340](#)
- [“Spool offloaders” on page 340](#)
- [“Spool volumes” on page 341](#)
- [“Subsystems” on page 342](#)
- [“System information” on page 343](#)
- [“System Symbol information” on page 343](#)
- [“System requests” on page 345](#)
- [“Coupling facility \(CF\) connections” on page 265](#)
- [“Coupling facility \(CF\) structures” on page 266](#)
- [“Coupling facility \(CF\) data sets” on page 266](#)
- [“XCF groups and members” on page 346](#)

## Protecting the generated MVS and JES commands

Most action characters generate MVS or JES commands. The resource names that protect these commands are in the OPERCMDS class. [“Tables of action characters” on page 229](#) shows all the action characters and their resource names.



## Controlling access authority

Access to the OPERCMDS resources can be controlled by which resources a user is authorized to access and also by which access level is given to the user. For example, an installation may create just one profile to protect all commands in the OPERCMDS class, but control a user's ability to issue commands by granting the user READ, UPDATE, CONTROL, or ALTER authority. Each authority level gives the user access to a different set of commands. Other installations may choose to define several OPERCMDS resources, and authorize users to access individual resources with the appropriate levels of access.

## Permitting access only while using SDSF

Users can be conditionally permitted to access OPERCMDS resources so they are authorized to use MVS and JES commands only while they are using SDSF. See [“Using conditional access” on page 222](#) for more information.

## Protecting action characters as separate resources

Action characters that do not cause an interaction with a resource for an object or a system command are protected as separate resources. The tables that follow show the resources for specific action characters.

Table 106. SDSF Resources That Protect Action Characters.

Replace **sysname** with the name of the system that the user is logged on to.

Replace **system** with the name of the system that the resource is using.

Action Character	Panel	SDSF Resource	Required Access
JC	AD, AS, and DA	ISFCMD.ODSP.CDE.sysname	READ
		ISFJOB.MODULE.owner.jobname.system	READ
JCS	AD	ISFCMD.ODSP.GQE.sysname	READ
JD	AS, DA, I, INIT, NS and ST	ISFCMD.ODSP.DEVICE.sysname	READ
		ISFJOB.DDNAME.owner.jobname.system	READ
JDCC	AD	ISFCMD.ODSP.COUPLE.sysname	READ
JDD	AD, AS, DA, I, INIT, NS, and ST	ISFCMD.ODSP.DEVICE.sysname	READ
		ISFJOB.DDNAME.owner.jobname.system	READ
JDNA	AD	ISFCMD.ODSP.NETACT.sysname	READ
JM	AD, AS, DA, I, INIT, NS and ST	ISFCMD.ODSP.STORAGE.sysname	READ
		ISFJOB.STORAGE.owner.jobname.system	READ
JMO	AD, AS, and DA	ISFCMD.ODSP.STORAGE.sysname	READ
		ISFJOB.STORAGE.owner.jobname.system	READ
JT	AD, AS, and DA	ISFCMD.ODSP.TCB.sysname	READ
		ISFJOB.TASK.owner.jobname.system	READ
L	CS	ISFCMD.ODSP.CSI.sysname	READ
		ISFCMD.ODSP.USI.sysname	READ
		ISFJOB.STORAGE.owner.jobname.system	CONTROL (to force storage to be paged in)

Table 106. SDSF Resources That Protect Action Characters.

Replace **sysname** with the name of the system that the user is logged on to.

Replace **system** with the name of the system that the resource is using.

(continued)

Action Character	Panel	SDSF Resource	Required Access
M and S	MEM	ISFJOB.STORAGE.owner.jobname.system	CONTROL (to force storage to be paged in)
		ISFJOB.STORAGE.owner.jobname.system	READ
N	AD	ISFCMD.ODSP.ENQUEUE.sysname	READ

## Setting up generic profiles

You can set up two generic profiles to allow use of all action characters, as shown in [Table 107 on page 228](#).

Table 107. Generic Profiles for Commands Generated by Actions Characters

Generated Commands	Resource Name	Class	Access
JES Commands	jesx.**	OPERCMDS	CONTROL
MVS Commands	MVS.**	OPERCMDS	CONTROL

To protect resources individually in the OPERCMDS class with more restrictive profiles, you would use the specific resource name for the command generated by the action character. See [“Tables of action characters” on page 229](#).

**Note:** In cases where JES issues an MVS command for processing, the user ID running JES must be authorized to access the OPERCMDS profiles protecting MVS commands, or the JES task must be running in a “trusted” state.

## Examples of protecting action characters

1. To allow use of all action characters on all panels, define the following profiles:

```
RDEFINE OPERCMDS jesx.** UACC(NONE)
RDEFINE OPERCMDS MVS.** UACC(NONE)
```

Give users CONTROL access with these commands:

```
PERMIT jesx.** CLASS(OPERCMDS) ID(userid or groupid) ACCESS(CONTROL)
PERMIT MVS.** CLASS(OPERCMDS) ID(userid or groupid) ACCESS(CONTROL)
```

2. To restrict the use of the C, CD, P, and PP action characters on the Display Active Users panel, define the restrictive profiles:

```
RDEFINE OPERCMDS jesx.CANCEL.** UACC(NONE)
RDEFINE OPERCMDS MVS.CANCEL.TSU.** UACC(NONE)
```

To restrict the canceling of active APPC transaction programs define the profile:

```
RDEFINE OPERCMDS MVS.CANCEL.ATX.** UACC(NONE)
```

Giving UPDATE authority to only these three profiles will limit action character use to C, CD, P and PP on the Display Active Users panel.

## Tables of action characters

SDSF action characters, the MVS and JES commands that they generate, the necessary access authorities, and the OPERCMDS class resource names are shown in [Table 108 on page 229](#). The table shows the command that is issued, and the associated OPERCMDS resource, for the JES2 environment for each action character; if the action is available in the JES3 environment, the JES3 command and associated OPERCMDS resource are shown beneath the JES2 values.

This information is shown sorted by OPERCMDS resource names in [Table 109 on page 250](#).

Table 108. Action Characters.				
Replace <b>jesx</b> with the name of the targeted JES subsystem, for example, JES2.				
Replace <b>type</b> with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace <b>type</b> with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.				
Replace <b>hcproc</b> and <b>hcstcid</b> with the IBM Health Checker for z/OS procedure name and started task ID.				
When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).				
Action Character	SDSF Panel	Command, JES2	OPERCMDs Resource, JES2	OPERCMDs Required Access
		Command, JES3	OPERCMDs Resource, JES3	
<b>A</b>	H O	\$TO	<i>jesx.MODIFY.typeOUT</i>	UPDATE
		-	-	-
<b>A</b>	DA I ST	\$A	<i>jesx.MODIFYRELEASE.type</i>	UPDATE
		*F	<i>jesx.MODIFY.JOB</i>	
<b>A</b>	CK	F <i>hcstcid</i> ,ACTIVATE	MVS.MODIFY.STC. <i>hcproc.hcstcid</i>	UPDATE
<b>A</b>	DYNX	SETPROG EXIT, MODIFY,EXITNAME=, MODNAME=, STATE=ACTIVE	MVS.MODIFY.PROG	UPDATE
<b>A</b>	JG	\$A	<i>jesx.MODIFYRELEASE.GROUP</i>	UPDATE
<b>A</b>	SSI	SETSSI ACT,S=	MVS.SETSSI.ACTIVATE. <i>ssname</i>	CONTROL
<b>A</b>	NO	-	-	-
		*F	<i>jesx.MODIFY.NJE</i>	UPDATE
<b>A</b>	SP	-	-	-
		*F Q	<i>jesx.MODIFY.Q</i>	UPDATE
<b>AI</b>	SR	SETAUTOR	MVS.SETAUTOR.AUTOR	READ
		SETAUTOR	MVS.SETAUTOR.AUTOR	READ
<b>B</b>	PR PUN	\$B	<i>jesx.BACKSP.DEV</i>	UPDATE
		-	-	-
<b>Bnumber</b>	PR PUN	\$B	<i>jesx.BACKSP.DEV</i>	UPDATE
		-	-	-
<b>BC</b>	PR PUN	\$B	<i>jesx.BACKSP.DEV</i>	UPDATE
		*R, <i>device</i> ,C	<i>jesx.RESTART.DEV.device</i>	
<b>BCnumber</b>	PR PUN	\$B	<i>jesx.BACKSP.DEV</i>	UPDATE
		*R, <i>device</i> ,C	<i>jesx.RESTART.DEV.device</i>	UPDATE
<b>BCnumberP</b>	PR PUN	-	-	-
		*R, <i>device</i> ,C	<i>jesx.RESTART.DEV.device</i>	UPDATE
<b>BD</b>	PR PUN	\$B	<i>jesx.BACKSP.DEV</i>	UPDATE
		*R, <i>device</i> ,G	<i>jesx.RESTART.DEV.device</i>	

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>BN</b>	PR PUN	-	-	-
		*R,device,N	jesx.RESTART.DEV.device	UPDATE
<b>BNnumber</b>	PR PUN	-	-	-
		*R,device,N	jesx.RESTART.DEV.device	UPDATE
<b>BNnumberP</b>	PR PUN	-	-	-
		*R,device,N	jesx.RESTART.DEV.device	UPDATE
<b>C (TSU jobs)</b>	DA I ST	C U=	MVS.CANCEL.type.jobname	UPDATE
		*F J=,C	jesx.MODIFY.JOB	
<b>C (APPC transactions)</b>	DA	C jobname,A=	MVS.CANCEL.type.jobname	UPDATE
<b>C</b>	DA I ST	\$C	jesx.CANCEL.type	UPDATE
		*F J=,C	jesx.MODIFY.JOB	
<b>C</b>	H O	\$C	jesx.CANCEL.type	UPDATE
		\$CO	jesx.CANCEL.typeOUT	
		-	-	-
<b>C</b>	PR PUN RDR	\$C	jesx.CANCEL.DEV	UPDATE
		*CANCEL	jesx.CANCEL.DEV.device	
<b>C</b>	H (secondary JES2)	\$O,CANCEL	jesx.RELEASE.typeOUT	UPDATE
		-	-	-
<b>C (held data set)</b>	JDS	SSI <sup>1</sup>		
		*F U	jesx.MODIFY.U	UPDATE
<b>C</b>	JG	\$C	jesx.CANCEL.GROUP	UPDATE
<b>C</b>	JP	*S	jesx.START.DEV.main	UPDATE
<b>C</b>	JO	-	-	-
		*F U	jesx.MODIFY.U	UPDATE
<b>C (transmitters, receivers)</b>	LI	\$C	jesx.CANCEL.DEV	UPDATE
		-	-	-
<b>C (lines)</b>	LI	-	-	-
		*C	jesx.CANCEL.name jesx.CANCEL.DEV.name	UPDATE
<b>C</b>	NC	-	-	-
		*C	jesx.CANCEL.TCP jesx.CANCEL.devname	UPDATE

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>C</b>	NS	-	-	-
		*C	jesx.CANCEL.devname	UPDATE
<b>C (transmitters, receivers)</b>	SO	\$C	jesx.CANCEL.DEV	UPDATE
<b>C (processes)</b>	PS	C jobname,A= C U=	MVS.CANCEL.type.jobname	UPDATE
<b>C</b>	SR	K C	MVS.CONTROL.C	READ
<b>CA</b>	DA I ST	\$C,ARMRESTART	jesx.CANCEL.type	UPDATE
		*F J=,C,ARMR	jesx.MODIFY.JOB	
<b>CD (TSU jobs)</b>	DA	\$C,DUMP	MVS.CANCEL.type.jobname	UPDATE
		*F J=,C,D	jesx.MODIFY.JOB	
<b>CD (APPC transactions)</b>	DA	C jobname, DUMP,A=	MVS.CANCEL.type.jobname	UPDATE
<b>CD</b>	DA I ST	\$C,D	jesx.CANCEL.type	UPDATE
		*F J=,C,D	jesx.MODIFY.JOB	
<b>CDA</b>	DA I ST	\$C,D,ARMRESTART	jesx.CANCEL.type	UPDATE
		*F J=,C,D,ARMR	jesx.MODIFY.JOB	
<b>CDP</b>	DA I ST	-	-	-
		*F J=,CO,D	jesx.MODIFY.JOB	UPDATE
<b>CG</b>	PR PUN	-	-	-
		*C,device,G	jesx.CANCEL.DEV.device	UPDATE
<b>CJ</b>	PR PUN	-	-	-
		*C,device,J	jesx.CANCEL.DEV.device	UPDATE
<b>CP</b>	PR PUN	-	-	-
		*C,device,P	jesx.CANCEL.DEV.device	UPDATE
<b>CP</b>	JG	\$C	jesx.CANCEL.GROUP	UPDATE
<b>CP</b>	DA, I, ST	-	-	-
		*f j=,cp	jesx.MODIFY.JOB	UPDATE
<b>CT</b>	PR PUN	-	-	-
		*C,device,T	jesx.CANCEL.DEV.device	UPDATE
<b>Coptions</b>	RDR	-	-	-
		*C,device,options	jesx.CANCEL.DEV.device	UPDATE
<b>D</b>	DA I ST	\$D	jesx.DISPLAY.type	READ
		*I J=	jesx.MODIFY.JOB	

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>D</b>	APF	D PROG,APF, DSNAME=	MVS.DISPLAY.PROG.	READ
<b>D</b>	CK	F <i>hcstcid</i> ,DISPLAY	MVS.MODIFY.STC. <i>hcproc.hcstcid</i>	UPDATE
<b>D</b>	CFC	D XCF,STR,STRNM=,CONNM=	MVS.DISPLAY.XCF	READ
<b>D</b>	CFD	D XCF,COUPLE,TYPE=	MVS.DISPLAY.XCF	READ
<b>D</b>	CFS	D XCF,STR,STRNM=	MVS.DISPLAY.XCF	READ
<b>D</b>	DEV	D U,VOL=	MVS.DISPLAY.U	READ
<b>D</b>	DYNX	D PROG,EXIT,EX=	MVS.DISPLAY.PROG	READ
<b>D</b>	EMCS	D EMCS,I,CN=	MVS.DISPLAY.EMCS	READ
<b>D</b>	ENQ	D GRS,HEX,RES=	MVS.DISPLAY.GRS	READ
<b>D</b>	FS	D OMVS,F,N=	MVS.DISPLAY.OMVS	READ
<b>D</b>	GT	D GTZ, TRACKDATA=(OWNER=)	MVS.DISPLAY.GTZ	READ
<b>D</b>	JC	\$D	<i>jesx</i> .DISPLAY.JOBCLASS	READ
		*I C=	<i>jesx</i> .DISPLAY.CLASS	READ
<b>D</b>	JES	D SSI,SUB=	MVS.DISPLAY.SSI	READ
<b>D</b>	JRI	\$DLIMITS	<i>jesx</i> .DISPLAY.LIMITS	READ
<b>Doption</b>	JG	\$D	<i>jesx</i> .DISPLAY.GROUP	READ
<b>D</b>	JP	*I	<i>jesx</i> .DISPLAY.MAIN	READ
<b>D</b>	JO	*I	<i>jesx</i> .DISPLAY.U	READ
<b>D</b>	INIT	\$D	<i>jesx</i> .DISPLAY.INITIATOR	READ
		*I	<i>jesx</i> .DISPLAY.G	
<b>D</b>	LI	\$D	<i>jesx</i> .DISPLAY.L <i>jesx</i> .DISPLAY.LINE	READ
		*I	<i>jesx</i> .DISPLAY.D	
<b>D</b>	LLS	D PROG,LNKLST,NAME=	MVS.DISPLAY.PROG	READ
<b>D</b>	LNK	D PROG,LNKLST, NAME=	MVS.DISPLAY.PROG.	READ
<b>D</b>	MAS SO	\$D	<i>jesx</i> .DISPLAY.MEMBER <i>jesx</i> .DISPLAY.DEV	READ
<b>D</b>	NC	\$D	<i>jesx</i> .DISPLAY.APPL <i>jesx</i> .DISPLAY.L <i>jesx</i> .DISPLAY.LINE <i>jesx</i> .DISPLAY.SOCKET	READ
		*I	<i>jesx</i> .DISPLAY.SOCKET	
<b>D</b>	NO	\$D	<i>jesx</i> .DISPLAY.NODE	READ
		*I	<i>jesx</i> .DISPLAY.NJE	

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
D	NS	\$D	jesx.DISPLAY.NETSRV jesx.DISPLAY.LOGON	READ
		*I	jesx.DISPLAY.NETSRV	
D	PAG	D ASM,PAGE=	MVS.DISPLAY.ASM	READ
D	PAG	D ASM,SCM	MVS.DISPLAY.ASM	READ
D	PROC	\$DPROCLIB	jesx.DISPLAY.PROCLIB	READ
D	PR PUN	\$D	jesx.DISPLAY.DEV	READ
		*I	jesx.DISPLAY.D	
D	PS	D OMVS,PID=	MVS.DISPLAY.OMVS	READ
D	RDR	\$D	jesx.DISPLAY.DEV	READ
		*I		
D	RES	D	MVS.DISPLAY.WLM	READ
D	RM	\$D	jesx.DISPLAY.resource <sup>3</sup>	READ
D	SE	D	MVS.DISPLAY.WLM	READ
D	SMSG	D SMS,SG	MVS.DISPLAY.SMS	READ
D	SMSV	D SMS,VOL	MVS.DISPLAY.SMS	READ
D	SP	\$DSPL	jesx.DISPLAY.SPOOL	READ
		*I Q	jesx.DISPLAY.Q	
D	SR	D	MVS.DISPLAY.R	READ
D	SSI	D SSI,SUB=	MVS.DISPLAY.SSI	READ
D	SYM	D SYMBOLS,S=	MVS.DISPLAY.SYMBOLS	READ
D	SYS	D IPLINFO	MVS.DISPLAY.IPLINFO	READ

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>D</b>	SYSP	D AUTOR,P D C D CEE,ALL D D,E D DEVSUP D DIAG D GRS,SYSTEM D GTZ,TRACKDATA=(ALL) D IKJTSO D IPLINFO,BOOST,STATE D IPLINFO,OSPROTECT D IPLINFO,ZAAPZIIP,STATE D IQP D IZU D LOGREC D OMVS,O D PPT,ALL D PROD,REG D PROG,APF,ALL D PROG,LNKLST D PROG,LPA,CSAMIN D SMF,O D SMS D SSI,ALL D VIRTSTOR,HVCOMMON D VIRTSTOR,HVSHARE D VIRTSTOR,LFAREA D XCF D XCF,COUPLE	MVS.DISPLAY.ALLOC MVS.DISPLAY.AUTOR MVS.DISPLAY.CEE MVS.DISPLAY.CONSOLES MVS.DISPLAY.DEVSUP MVS.DISPLAY.DIAG MVS.DISPLAY.DUMP MVS.DISPLAY.FXE MVS.DISPLAY.GRS MVS.DISPLAY.GTZ MVS.DISPLAY.ICSF MVS.DISPLAY.IEFOPZ MVS.DISPLAY.IKJTSO MVS.DISPLAY.IOS MVS.DISPLAY.IPLINFO MVS.DISPLAY.IQP MVS.DISPLAY.IZU MVS.DISPLAY.JOB MVS.DISPLAY.LOGGER MVS.DISPLAY.LOGREC MVS.DISPLAY.OMVS MVS.DISPLAY.PPT MVS.DISPLAY.PROD MVS.DISPLAY.PROG MVS.DISPLAY.SMF MVS.DISPLAY.SMFLIM MVS.DISPLAY.SMS MVS.DISPLAY.SSI MVS.DISPLAY.UNI MVS.DISPLAY.VIRTSTOR MVS.DISPLAY.XCF	READ
<b>D</b>	XCFM	D XCF,GROUP, <i>groupname,membername</i>	MVS.DISPLAY.XCF	READ
<b>DA</b>	APF	D PROG,APF,ALL	MVS.DISPLAY.PROG	READ
<b>DA</b>	CFC	D XCF,STR,STRNM=ALL	MVS.DISPLAY.XCF	READ
<b>DA</b>	CFD	D XCF,COUPLE	MVS.DISPLAY.XCF	READ
<b>DA</b>	CFS	D XCF,STR,STRNM=ALL	MVS.DISPLAY.XCF	READ
<b>DA</b>	DEV	D U,ALLOC	MVS.DISPLAY.U	READ
<b>DA</b>	DYNX	D PROG,EXIT,ALL	MVS.DISPLAY.PROG	READ
<b>DA</b>	FS	D OMVS,F	MVS.DISPLAY.OMVS	READ
<b>DA</b>	GT	D GTZ,TRACKDATA=(ALL)	MVS.DISPLAY.GTZ	READ
<b>DA</b>	JD	D TCPIP, <i>procname</i> , N,ALL,IPP=	MVS.DISPLAY.TCPIP	READ
<b>DA</b>	NA	D TCPIP, <i>stack</i> ,N,ALL,IPP=	MVS.DISPLAY.TCPIP	READ
<b>DA</b>	NS	\$D	<i>jesx</i> .DISPLAY.APPL	READ
		-	-	-
<b>DA</b>	SSI	D SSI,ALL	MVS.DISPLAY.SSI	READ



Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDs Resource, JES2	OPERCMDs Required Access
		Command, JES3	OPERCMDs Resource, JES3	
<b>DA</b>	XCFM	D XCF, GROUP, <i>groupname</i> , ALL	MVS.DISPLAY.XCF	READ
<b>DAA</b>	SYS	D A, ALL	MVS.DISPLAY.JOB	READ
<b>DAI</b>	DYNX	D PROG, EXIT, ALL, IMPLICIT	MVS.DISPLAY.PROG	READ
<b>DAL</b>	JD	D TCPIP, <i>procname</i> , N, ALL, IPP=, FORMAT=LONG	MVS.DISPLAY.TCPIP	READ
<b>DAL</b>	NA	D TCPIP, <i>stack</i> , N, ALL, IPP=, FORMAT=LONG	MVS.DISPLAY.TCPIP	READ
<b>DAL</b>	SYS	D A, L	MVS.DISPLAY.JOB	READ
<b>DALO</b>	SYS	D ALLOC, OPTIONS	MVS.DISPLAY.ALLOC	READ
<b>DB</b>	JD	D TCPIP, <i>procname</i> , N, BYTE, IDLETIME, IPA=	MVS.DISPLAY.TCPIP	READ
<b>DB</b>	NA	D TCPIP, <i>stack</i> , N, BYTE, IDLETIME, IPA=	MVS.DISPLAY.TCPIP	READ
<b>DB</b>	SYS	D IPLINFO, BOOST, STATE	MVS.DISPLAY.IPLINFO	READ
<b>DBL</b>	JD	D TCPIP, <i>procname</i> , N, BYTE, IDLETIME, IPA=, FORMAT=LONG	MVS.DISPLAY.TCPIP	READ
<b>DBL</b>	NA	D TCPIP, <i>stack</i> , N, BYTE, IDLETIME, IPA=, FORMAT=LONG	MVS.DISPLAY.TCPIP	READ
<b>DC</b>	JD	D XCF, CF, CFNM=	MVS.DISPLAY.XCF	READ
<b>DC</b>	NO	\$D	<i>jesx</i> .DISPLAY.NODE	READ
		-	-	-
<b>DC</b>	PAG	D ASM, COMMON	MVS.DISPLAY.ASM	READ
<b>DC</b>	JC	-	-	-
		*I G, <i>main</i> , C, <i>class</i>	<i>jesx</i> .DISPLAY.G	READ
<b>DC</b>	SMSV	D SMS, CFVOL	MVS.DISPLAY.SMS	READ
<b>DC</b>	SYS	D C	MVS.DISPLAY.CONSOLES	READ
<b>DCEE</b>	SYS	D CEE, ALL	MVS.DISPLAY.CEE	READ
<b>DD</b>	CK	F HZSPROC, DISPLAY, CHECKS, DETAIL, DIAG, CHECK=	MVS.MODIFY.STC. <i>hcproc</i> . <i>hcstcid</i>	UPDATE
<b>DD</b>	DYNX	D PROG, EXIT, EX=, DIAG	MVS.DISPLAY.PROG	READ
<b>DD</b>	GT	D GTZ, DEBUG	MVS.DISPLAY.GTZ	READ
<b>DD</b>	PAG	D ASM, PAGEDEL	MVS.DISPLAY.ASM	READ
<b>DD</b>	PROC	\$DPROCLIB, DEBUG	<i>jesx</i> .DISPLAY.PROCLIB	READ
<b>DD</b>	SYS	D D, E	MVS.DISPLAY.DUMP	READ

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
DE	DA I ST	-	-	-
		*I J=,E	jesx.DISPLAY.JOBE	READ
DE	FS	D OMVS,F,E	MVS.DISPLAY.OMVS	READ
DE	GT	D GTZ,EXCLUDE	MVS.DISPLAY.GTZ	READ
DE	LI	-	-	-
		*I	jesx.DISPLAY.T	READ
DE	PARM	D PARMLIB,ERRORS	MVS.DISPLAY.PARMLIB	READ
DEM	SYS	D EMCS	MVS.DISPLAY.EMCS	READ
DG	JC	-	-	-
		*I G,main,G,group	jesx.DISPLAY.G	READ
DG	SYS	D GRS,SYSTEM	MVS.DISPLAY.GRS	READ
DG	XCFM	D XCF, GROUP,groupname	MVS.DISPLAY.XCF	READ
DH	GT	D GTZ,TRACKDATA=(HOMEJOB=)	MVS.DISPLAY.GTZ	READ
DI	DEV	D U,IPLVOL	MVS.DISPLAY.U	READ
DI	DYNX	D PROG,EXIT,INSTALLATION	MVS.DISPLAY.PROG	READ
DI	SYS	D IOS,CONFIG	MVS.DISPLAY.IOS	READ
DIQP	SYS	D IQP	MVS.DISPLAY.IQP	READ
DL	CK	F hcstcid,DISPLAY	MVS.MODIFY.STC.hcproc.hcstcid	UPDATE
DL	DA	\$D	jesx.DISPLAY.type	READ
		*I A,J=	jesx.DISPLAY.A	
DL	I ST	\$D	jesx.DISPLAY.type	READ
		*X DISPLAY,J=	jesx.CALL.DISPLAY.type	UPDATE
DL	EMCS	D EMCS,F,CN=	MVS.DISPLAY.EMCS	READ
DL	JRI	\$DLIMITS	jesx.DISPLAY.LIMITS	READ
DL	INIT	\$D	jesx.DISPLAY.INITIATOR	READ
		*I	jesx.DISPLAY.G	
DL	JC	\$DJOBCLASS,L	jesx.DISPLAY.JOBCLASS	READ
DL	JP	*I	jesx.DISPLAY.MAINX	READ
DL	LI	\$D	jesx.DISPLAY.L jesx.DISPLAY.LINE	READ
		*I	jesx.DISPLAY.D	
DL	MAS SO	\$D	jesx.DISPLAY.MEMBER jesx.DISPLAY.DEV	READ

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
DL	NC	\$D	jesx.DISPLAY.LINE	READ
		-	-	-
DL	NS	\$D	jesx.DISPLAY.NETSRV jesx.DISPLAY.LOGON	READ
		*I	jesx.DISPLAY.NETSRV	
DL	NO	\$D	jesx.DISPLAY.NODE	READ
		*I	jesx.DISPLAY.NJE	READ
DL	PAG	D ASM,LOCAL	MVS.DISPLAY.ASM	READ
DL	PR PUN	\$D	jesx.DISPLAY.DEV	READ
		*I	jesx.DISPLAY.D	
DL	RDR	\$D	jesx.DISPLAY.DEV	READ
DL	SMSG	D SMS,SG,LISTVOL	MVS.DISPLAY.SMS	READ
DL	SP	\$DSPL,L	jesx.DISPLAY.SPOOL	READ
		*I Q	jesx.DISPLAY.Q	
DL	SYM	D SYMBOLS	MVS.DISPLAY.SYMBOLS	READ
DL	SYS	D LLA	MVS.DISPLAY.LLA	READ
DLI	JRJ	\$DLIMITS	jesx.DISPLAY.LIMITS	READ
DLL	SYS	D LLA	MVS.DISPLAY.LLA	READ
DLO	SYS	D LOGGER	MVS.DISPLAY.LOGGER	READ
DLR	SYS	D LOGREC	MVS.DISPLAY.LOGREC	READ
DM	JP	*START	jesx.START.MONITOR	UPDATE
DM	SYS	D M	MVS.DISPLAY.M	READ
DMA	I ST	-	-	-
		*I S,A,J=	jesx.DISPLAY.S	READ
DMC	SYS	D M=CPU	MVS.DISPLAY.M	READ
DMP	SYS	D MPF	MVS.DISPLAY.MPF	READ
DMR	I ST	-	-	-
		*I S,R,J=	jesx.DISPLAY.S	READ
DMSS	I ST	-	-	-
		*I S,SS,J=	jesx.DISPLAY.S	READ
DMSV	I ST	-	-	-
		*I S,SV,J=	jesx.DISPLAY.S	READ

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
DMU	I ST	-	-	-
		*I S,U,J=	jesx.DISPLAY.S	READ
DN	JD	D TCPIP,procname, N,CO,APPLDATA,IPP=	MVS.DISPLAY.TCPIP	READ
DN	LNK	D PROG,LNKST, NAMES	MVS.DISPLAY.PROG	READ
DN	NA	D TCPIP,stack, N,CO,APPLDATA,IPP=	MVS.DISPLAY.TCPIP	READ
DNL	JD	D TCPIP,procname, N,CO,APPLDATA, IPP=,FORMAT=LONG	MVS.DISPLAY.TCPIP	READ
DNL	NA	D TCPIP,stack, N,CO,APPLDATA,IPP=, FORMAT=LONG	MVS.DISPLAY.TCPIP	READ
DNP	DYNX	D PROG,EXIT,NOTPROGRAM	MVS.DISPLAY.PROG	READ
DO	OMVS	D OMVS,O	MVS.DISPLAY.OMVS	READ
DO	SSI	D OPDATA	MVS.DISPLAY.OPDATA	READ
DO	SYS	D OMVS,O	MVS.DISPLAY.OMVS	READ
DP	DYNX	D PROG,EXIT,PROGRAM	MVS.DISPLAY.PROG	READ
DP	JD	D XCF,POL,TYPE=CFRM	MVS.DISPLAY.XCF	READ
DP	CK	F hcstcid,DISPLAY	MVS.MODIFY.STC.hcproc.hcstcid	UPDATE
DP	NO	\$D,PATH	jesx.DISPLAY.NODE	READ
		-	-	-
DP	PAG	D ASM,PLPA	MVS.DISPLAY.ASM	READ
DP	SYS	D PROD,REG	MVS.DISPLAY.PROD	READ
DP	I ST	\$Dtype	jesx.DISPLAY.type	UPDATE
DPCD	SYS	D PCIE,DD	MVS.DISPLAY.PCIE	READ
DPCI	SYS	D PCIE	MVS.DISPLAY.PCIE	READ
DPO	CK	F hcstcid,DISPLAY	MVS.MODIFY.STC.hcproc.hcstcid	UPDATE
DR	JD	D TCPIP,procname, N,ROUTE,IPA=	MVS.DISPLAY.TCPIP	READ
DR	NA	D TCPIP,stack,N,ROUTE,IPA=	MVS.DISPLAY.TCPIP	READ
DRD	JD	D TCPIP,procname,N,ROUTE, DETAIL,IPA=	MVS.DISPLAY.TCPIP	READ
DRD	NA	D TCPIP,stack ,N,ROUTE,DETAIL, IPA=	MVS.DISPLAY.TCPIP	READ

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDs Resource, JES2	OPERCMDs Required Access
		Command, JES3	OPERCMDs Resource, JES3	
<b>DRDL</b>	JD	D TCPIP, <i>procname</i> , N,ROUTE,DETAIL, IPA=,FORMAT=LONG	MVS.DISPLAY.TCPIP	READ
<b>DRDL</b>	NA	D TCPIP, <i>stack</i> ,N,ROUTE, DETAIL,IPA=, FORMAT=LONG	MVS.DISPLAY.TCPIP	READ
<b>DRL</b>	JD	D TCPIP, <i>procname</i> , N,ROUTE,IPA=, FORMAT=LONG	MVS.DISPLAY.TCPIP	READ
<b>DRL</b>	NA	D TCPIP, <i>stack</i> ,N,ALL,IPA=	MVS.DISPLAY.TCPIP	READ
<b>DS</b>	CK	F <i>hcstcid</i> ,DISPLAY	MVS.MODIFY.STC. <i>hcproc.hcstcid</i>	UPDATE
<b>DS</b>	GT	D GTZ,STATUS	MVS.DISPLAY.GTZ	READ
<b>DS</b>	JD	D XCF,STR,STRNM=	MVS.DISPLAY.XCF	READ
<b>DS</b>	NS	\$D	<i>jesx</i> .DISPLAY.SOCKET	READ
		-	-	-
<b>DS</b>	PAG	D ASM,SCM	MVS.DISPLAY.ASM	READ
<b>DS</b>	SMSV	D SMS,SG	MVS.DISPLAY.SMS	READ
<b>DS</b>	CFC	D XCF,STR,STRNM=	MVS.DISPLAY.XCF	READ
<b>DSF</b>	SYS	D SMF,O	MVS.DISPLAY.SMF	READ
<b>DSL</b>	SMSV	D SMS,SG,LISTVOL	MVS.DISPLAY.SMS	READ
<b>DSL</b>	SYS	D SLIP	MVS.DISPLAY.SLIP	READ
<b>DSM</b>	SYS	D SMS	MVS.DISPLAY.SMS	READ
<b>DSP</b>	DEV	DS P	MVS.DEVSERV	READ
<b>DSQD</b>	DEV	DS QD	MVS.DEVSERV	READ
<b>DSQP</b>	DEV	DS QP	MVS.DEVSERV	READ
<b>DSS</b>	DEV	DS S	MVS.DEVSERV	READ
<b>DSY</b>	SYS	D SYMBOLS	MVS.DISPLAY.SYMBOLS	READ
<b>DT</b>	SYS	D T	MVS.DISPLAY.TIMEDATE	READ
<b>DTO</b>	SYS	D IKJTSO	MVS.DISPLAY.IKJTSO	READ
<b>DTR</b>	SYS	D TRACE	MVS.DISPLAY.TRACE	READ
<b>DTS</b>	SYS	D TS,L	MVS.DISPLAY.JOB	READ
<b>DU</b>	LLS	D PROG,LNKLST,USERS,NAME=	MVS.DISPLAY.PROG	READ
<b>DW</b>	SYS	D WLM	MVS.DISPLAY.WLM	READ
<b>DX</b>	SYS	D XCF	MVS.DISPLAY.XCF	READ
<b>E</b>	CK	F <i>hcstcid</i> ,REFRESH	MVS.MODIFY.STC. <i>hcproc.hcstcid</i>	UPDATE

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>E</b>	DA I ST	\$E	<i>jesx.RESTART.BAT</i>	CONTROL
		*R MAIN,J=	<i>jesx.RESTART.DEV.main</i>	
<b>E (lines)</b>	LI	\$E	<i>jesx.RESTART.LINE</i>	CONTROL
		*R	<i>jesx.RESTART.RJP</i>	UPDATE
<b>E (transmitters, receivers)</b>	LI	\$E	<i>jesx.RESTART.DEV</i>	UPDATE
		-	-	-
<b>E</b>	EMCS	RESET CN()	MVS.RESET.CN	CONTROL
<b>E</b>	NC	\$E	<i>jesx.RESTART.DEV</i>	UPDATE
		-	-	-
<b>E (subdevice)</b>	NC	\$E	<i>jesx.RESTART.LINE</i>	CONTROL
		-	-	-
<b>E (connection)</b>	NS	\$E	<i>jesx.RESTART.DEV</i>	UPDATE
		*R	<i>jesx.RESTART.DEV.devname</i>	
<b>E (transmitters)</b>	SO	\$E	<i>jesx.RESTART.DEV</i>	UPDATE
<b>E</b>	MAS	\$E	<i>jesx.RESTART.SYS</i>	CONTROL
<b>E</b>	PR PUN	\$E	<i>jesx.RESTART.DEV</i>	UPDATE CONTROL
		*R	<i>jesx.RESTART.DEV.device</i>	UPDATE
<b>Eoptions</b>	PR PUN	-	-	-
		*R,device,options	<i>jesx.RESTART.DEV.device</i>	UPDATE
<b>EC</b>	DA I ST	\$E,C	<i>jesx.RESTART.BAT</i>	CONTROL
<b>EL</b>	NO	-	-	-
		*F	<i>jesx.MODIFY.NJE</i>	UPDATE
<b>ES</b>	DA I ST	\$E	<i>jesx.RESTART.BAT</i>	CONTROL
		-	-	-
<b>ESH</b>	DA I ST	\$E	<i>jesx.RESTART.BAT</i>	CONTROL
		-	-	-
<b>F</b>	JP	*S	<i>jesx.START.DEV.main</i>	UPDATE
<b>F</b>	PR PUN	\$F	<i>jesx.FORWARD.DEV</i>	UPDATE
		-	-	-
<b>Fnumber</b>	PR PUN	\$F	<i>jesx.FORWARD.DEV</i>	UPDATE
		*R,device,R	<i>jesx.RESTART.DEV.device</i>	

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>FC</b>	PR PUN	\$F	<i>jesx.FORWARD.DEV</i>	UPDATE
		*R, <i>device</i> ,R,C	<i>jesx.RESTART.DEV.device</i>	
<b>FCnumber</b>	PR PUN	\$F	<i>jesx.FORWARD.DEV</i>	UPDATE
		*R, <i>device</i> ,R,C	<i>jesx.RESTART.DEV.device</i>	
<b>FCnumberP</b>	PR PUN	-	-	-
		*R, <i>device</i> ,R,C	<i>jesx.RESTART.DEV.device</i>	UPDATE
<b>FD</b>	PR	\$F	<i>jesx.FORWARD.DEV</i>	UPDATE
		-	-	-
<b>FN</b>	PR PUN	-	-	-
		*R, <i>device</i> ,R,N	<i>jesx.RESTART.DEV.device</i>	UPDATE
<b>FNnumber</b>	PR PUN	-	-	-
		*R, <i>device</i> ,R,N	<i>jesx.RESTART.DEV.device</i>	UPDATE
<b>FNnumberP</b>	PR PUN	-	-	-
		*R, <i>device</i> ,R,N	<i>jesx.RESTART.DEV.device</i>	UPDATE
<b>H</b>	CK	F <i>hcstcid</i> , DEACTIVATE	MVS.MODIFY.STC. <i>hcproc.hcstcid</i>	UPDATE
<b>H</b>	DYNX	SETPROG EXIT, MODIFY,EXITNAME=, MODNAME=, STATE=INACTIVE	MVS.SET.PROG	UPDATE
<b>H</b>	DA I ST	\$H	<i>jesx.MODIFYHOLD.type</i>	UPDATE
		*F J=,H	<i>jesx.MODIFY.JOB</i>	
<b>H</b>	O	\$TO	<i>jesx.MODIFY.typeOUT</i>	UPDATE
		-	-	-
<b>H</b>	JDS	SSI <sup>1</sup>	None	
		*F U,J=	<i>jesx.MODIFY.U</i>	UPDATE
<b>H</b>	JG	\$H	<i>jesx.MODIFYHOLD.GROUP</i>	UPDATE
<b>H</b>	JO	-	-	-
		*F U,J	<i>jesx.MODIFY.U</i>	UPDATE
<b>H</b>	NO	-	-	-
		*F	<i>jesx.MODIFY.NJE</i>	UPDATE
<b>H</b>	SP	-	-	-
		*F Q	<i>jesx.MODIFY.Q</i>	UPDATE
<b>H</b>	SSI	SETSSI DEACT,S=	MVS.SETSSI.DEACTIVATE. <i>ssname</i>	CONTROL

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>HC</b>	SP	-	-	-
		*F Q	jesx.MODIFY.Q	UPDATE
<b>HP</b>	SP	-	-	-
		*F Q	jesx.MODIFY.Q	UPDATE
<b>I</b>	LI	\$TLINE,D=	jesx.MODIFY.LINE	CONTROL
		*C	jesx.CANCEL.device	UPDATE
<b>I</b>	PR PUN	\$I	jesx.INTERRUPT.DEV	UPDATE
		-	-	-
<b>I</b>	ENC I ST			
<b>J</b>	I ST	\$SJ	jesx.START.BAT	UPDATE
		*F J=,RUN	jesx.MODIFY.JOB	
<b>J</b>	SP	\$DJOBQ,SPL=	jesx.DISPLAY.JST	READ
		*I Q	jesx.DISPLAY.Q	
<b>J (members)</b>	MAS	\$J	jesxMON.DISPLAY.MONITOR	READ
<b>J</b>	RMA	\$JDMONITOR	JES2MON.DISPLAY.MONITOR	READ
<b>JCS<sup>4</sup></b>	AD	None	None	None
<b>JD</b>	RMA	\$JDDetails	JES2MON.DISPLAY.DETAIL	READ
<b>JD (members)</b>	MAS	\$J	jesxMON.DISPLAY.DETAIL	READ
<b>JD<sup>4</sup></b>	AS, DA, I, INIT, NS and ST	None	None	None
<b>JDD<sup>4</sup></b>	AD	None	None	None
<b>JDCC<sup>4</sup></b>	AD	None	None	None
<b>JDNA<sup>4</sup></b>	AD	None	None	None
<b>JH (members)</b>	MAS	\$J	jesxMON.DISPLAY.HISTORY	READ
<b>JH</b>	RMA	\$JDHISTORY	JES2MON.DISPLAY.HISTORY	READ
<b>JJ (members)</b>	MAS	\$J	jesxMON.DISPLAY.JES	READ
<b>JJ</b>	RMA	\$JDJES	JES2MON.DISPLAY.JES	READ
<b>JM<sup>4</sup></b>	AD, AS, DA, I, INIT, NS and ST	None	None	None
<b>JP</b>	I JG ST	None	None	None
<b>JS</b>	DA H I O ST	None	None	None
<b>JS (members)</b>	MAS	\$J	jesxMON.DISPLAY.STATUS	READ
<b>JS</b>	RMA	\$JDSTATUS	JES2MON.DISPLAY.STATUS	READ
<b>JY<sup>4</sup></b>	DA	None	None	None



Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>K</b>	DA	C jobname,A=	MVS.CANCEL.type.jobname	UPDATE
		C jobname,A=	MVS.CANCEL.type.jobname	
<b>K</b>	NS	C	MVS.CANCEL.STC.servername	CONTROL
<b>K</b>	PR	F	MVS.MODIFY.STC.fssproc.fssname	UPDATE
			MVS.MODIFY.STC.fssproc.fssname	
<b>K</b>	PS	F	MVS.MODIFY.STC.BPXOINIT.BPXOINIT	UPDATE
<b>KD</b>	DA	C jobname,A=	MVS.CANCEL.type.jobname	UPDATE
		C jobname,A=	MVS.CANCEL.type.jobname	
<b>KD</b>	NS	C	MVS.CANCEL.STC.servername	CONTROL
<b>L</b>	DA I ST	\$L	jesx.DISPLAY.typeOUT	READ
		*I J=	jesx.DISPLAY.JOB	
<b>LB, LH, LT</b>	DA I ST	-	-	-
		*I J=	jesx.DISPLAY.JOB	READ
<b>L</b>	H O	\$DO	jesx.DISPLAY.typeOUT	READ
		-	-	-
<b>L</b>	LI	-	-	-
		*FAIL	jesx.FAIL.device	CONTROL
<b>L</b>	NS	-	-	-
		*FAIL	jesx.FAIL.DEVdevname	CONTROL
<b>L</b>	PR RDR	-	-	-
		*FAIL	jesx.FAIL.DEV.device	CONTROL
<b>L</b>	PUN	-	-	-
		*FAIL	jesx.FAIL.dspname	CONTROL
<b>LD</b>	LI	-	-	-
		*FAIL	jesx.FAIL.device	CONTROL
<b>LD</b>	PR RDR	-	-	-
		*FAIL	jesx.FAIL.DEV.device	CONTROL
<b>LD</b>	PUN	-	-	-
		*FAIL	jesx.FAIL.dspname	CONTROL
<b>LL</b>	DA	\$L	jesx.DISPLAY.typeOUT	READ
<b>LL</b>	H O ST	\$DO	jesx.DISPLAY.typeOUT	READ
		-	-	-
<b>M</b>	ENC	None	None	None

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>N</b> <sup>4</sup>	AD	None	None	None
<b>N</b>	DA PR PUN	\$N	jesx.REPEAT.DEV	UPDATE
		-	-	-
<b>O</b>	ST H	\$O \$TO	jesx.RELEASE.typeOUT jesx.MODIFY.typeOUT	UPDATE
		-	-	-
<b>N</b>	OMVS	SETOMVS option=NOLIMIT	MVS.SETOMVS.OMVS	UPDATE
<b>O (Held data set)</b>	JDS	SSI <sup>1</sup>		
		*F U,J=	jesx.MODIFY.U	UPDATE
<b>O</b>	JO	-	-	-
		*F U,J	jesx.MODIFY.U	UPDATE
<b>OK</b>	H	\$TO	jesx.MODIFY.typeout	UPDATE
		-	-	-
<b>P</b>	CK	F hcstcid,DELETE	MVS.MODIFY.STC.hcproc.hcstcid	UPDATE
<b>P</b>	EMCS	SETCON DELETE,CN=	MVS.SETCON.DELETE	UPDATE
<b>P (TSU jobs)</b>	DA I ST	C U= \$CT	MVS.CANCEL.type.jobname jesx.CANCEL.type	UPDATE
		F J=,C	jesx.MODIFY.JOB	
<b>P (APPC transactions)</b>	DA	C jobname,A=	MVS.CANCEL.type.jobname	UPDATE
		C jobname,A=	MVS.CANCEL.type.jobname	
<b>P</b>	DA I ST	\$C	jesx.CANCEL.type	UPDATE
		*F J=,CO	jesx.MODIFY.JOB	
<b>P</b>	DYNX	SETPROG EXIT, DELETE,EXITNAME=, MODNAME=	MVS.SET.PROG	UPDATE
<b>P</b>	H O H O	\$C \$CO	jesx.CANCEL.type jesx.CANCEL.typeOUT	UPDATE
		-	-	-
<b>P (Held data set)</b>	JDS	SSI <sup>1</sup>		
		*F U,J=	jesx.MODIFY.U	UPDATE
<b>P</b>	JG	\$P	jesx.CANCEL.GROUP	UPDATE
<b>P</b>	JP	-	-	-
		*RETURN	jesx.STOP.RETURN	CONTROL

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>P</b>	JO	-	-	-
		*F U,J=	jesx.MODIFY.U	UPDATE
<b>P</b>	SO MAS	\$P	jesx.STOP.DEV jesx.STOP.SYS	UPDATE CONTROL
<b>P</b>	INIT	\$P	jesx.STOP.INITIATOR	CONTROL
		*F	jesx.MODIFY.G	UPDATE
<b>P (lines)</b>	LI	\$P	jesx.STOP.LINE	CONTROL
		-	-	-
<b>P (transmitters, receivers)</b>	LI	\$P	jesx.STOP.DEV	UPDATE
		-	-	-
<b>P</b>	NC	\$P	jesx.STOP.DEV	UPDATE
		-	-	-
<b>P</b>	NS	\$P	jesx.STOP.DEV	UPDATE
		-	-	-
<b>P</b>	PR PUN RDR	\$P	jesx.STOP.DEV	UPDATE
		-	-	-
<b>P (spool volumes)</b>	SP	\$PSPL	jesx.STOP.SPOOL	CONTROL
		*F Q	jesx.MODIFY.Q	UPDATE
<b>PC (spool volumes)</b>	SP	\$PSPL	jesx.STOP.SPOOL	CONTROL
		-	-	-
<b>PC</b>	MAS	\$PCNVT	jesx.STOP.SYS	CONTROL
		-	-	-
<b>PF</b>	SSI	SETSSI DELETE,S=,FORCE	MVS.SETSSI.DEACTIVATE.ssname	CONTROL
<b>PP (TSU jobs)</b>	DA I ST	C U= \$C	MVS.CANCEL.type.jobname jesx.CANCEL.type	UPDATE
<b>PF</b>	CK	F hcstcid,DELETE	MVS.MODIFY.STC.hcproc.hcstcid	UPDATE
<b>PF</b>	DYNX	SETPROG EXIT, DELETE,EXITNAME=, MODNAME=, FORCE=YES	MVS.SET.PROG	UPDATE
<b>PP (APPC transactions)</b>	DA	C jobname,A=	MVS.CANCEL.type.jobname	UPDATE
<b>PP</b>	DA I ST	\$C	jesx.CANCEL.type	UPDATE
<b>PX</b>	MAS	\$P	jesx.STOP.SYS	CONTROL
	JP	*F	jesx.MODIFY.V	UPDATE

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>Q</b>	LI	\$TLINE,D=	<i>jesx</i> .MODIFY.LINE	CONTROL
		-	-	-
<b>R</b>	CK	F <i>hcstcid</i> ,RUN	MVS.MODIFY.STC. <i>hcproc.hcstcid</i>	UPDATE
<b>R<sup>RMF</sup></b>	DA	RESET	MVS.RESET	UPDATE
		RESET	MVS.RESET	
<b>R</b>	ENC	None	None	None
<b>R</b>	SR	R	MVS.REPLY	READ
<b>R</b>	SE	None	None	None
<b>RQ<sup>RMF</sup></b>	DA	RESET	MVS.RESET	UPDATE
		RESET	MVS.RESET	
<b>RQ</b>	ENC	None	None	None
<b>S</b>	INIT	\$S	<i>jesx</i> .START.INITIATOR	CONTROL
		*F	<i>jesx</i> .MODIFY.G	UPDATE
<b>S</b>	SO INIT MAS	\$S	<i>jesx</i> .START.DEV <i>jesx</i> .START.SYS	UPDATE CONTROL
<b>S (members)</b>	JP	*S	<i>jesx</i> .START.JSS	UPDATE
<b>S (lines)</b>	LI	\$S	<i>jesx</i> .START.LINE	CONTROL
		*S	<i>jesx</i> .START.DEV. <i>device</i>	
<b>S (transmitters, receivers)</b>	LI	\$S	<i>jesx</i> .START.DEV	UPDATE
		-	-	-
<b>S</b>	NC	\$S	<i>jesx</i> .START.DEV	UPDATE
		-	-	-
<b>S</b>	NS	\$S	<i>jesx</i> .START.DEV	UPDATE
		-	-	-
<b>S</b>	PR PUN RDR	\$S	<i>jesx</i> .START.DEV	UPDATE
		*S <i>device</i>	<i>jesx</i> .START.DEV. <i>device</i>	
<b>S (spool volumes)</b>	SP	\$SSPL	<i>jesx</i> .START.SPOOL	CONTROL
<b>Soptions</b>	PR PUN RDR	-	-	-
		*S, <i>device</i>	<i>jesx</i> .START.DEV. <i>device</i>	UPDATE
<b>S, SB, SE</b>	CK CKH DA H I JDS JG JS JO O ST	None	None	None
<b>SBI, SBO, SEI, SEO</b>	CK	None	None	None

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>SC</b>	MAS	\$SCNVT	jesx.START.SYS	CONTROL
		-	-	-
<b>SJ</b>	DA H I JDS JG JS O ST	None	None	None
<b>SL</b>	LI	-	-	-
		*S	jesx.START.DEV.device	CONTROL
<b>SM</b>	JP	*CALL	jesx.CALL.MONITOR	UPDATE
<b>SN</b>	LI	\$SN	jesx.START.NET	CONTROL
		-	-	-
<b>SN</b>	NO	\$SN	jesx.START.NET	CONTROL
		*S	jesx.START.TCP	UPDATE
		*X	jesx.CALL.NJE	
<b>SN</b>	NC	\$SN	jesx.START.NET	CONTROL
		*S	jesx.START.TCP	UPDATE
		*X	jesx.CALL.NJE	
<b>SNL, SNR</b>	LI	-	-	-
		*S	jesx.START.DEV.device	CONTROL
<b>SR</b>	LI	-	-	-
		*S	jesx.START.DEV.device	CONTROL
<b>SR</b>	SO	\$S	jesx.START.DEV	UPDATE
<b>SRJP</b>	LI	-	-	-
		*S	jesx.START.RJP	UPDATE
<b>ST</b>	SO	\$S	jesx.START.DEV	UPDATE
<b>ST</b>	JC JG SE	None	None	None
<b>SX</b>	MAS	\$S	jesx.START.SYS	CONTROL
<b>T</b>	PS	F	MVS.MODIFY.STC.BPXOINIT.BPXOINIT	UPDATE
<b>U</b>	CK	Fhcstcid,UPDATE	MVS.MODIFY.STC.hcproc.hcstcid	UPDATE
<b>U</b>	DYNX	SETPROG EXIT, UNDEFINE, EXITNAME=	MVS.SET.PROG	UPDATE
<b>U</b>	SP	-	-	-
		*F Q	jesx.MODIFY.Q	UPDATE
<b>V</b>	DEV	V ONLINE	MVS.VARY.DEV	UPDATE
<b>V</b>	EMCS	V CN(), AUTH=	MVS.VARYAUTH.CN	CONTROL
<b>V</b>	JDS			

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>V</b>	JP LI PR PUN RDR	-	-	-
		*F VARY	jesx.MODIFY.V	UPDATE
<b>VD</b>	SMSG	V SMS,SG,DISABLE	MVS.VARY.SMS	UPDATE
<b>VD</b>	SMSV	V SMS,VOL,DISABLE	MVS.VARY.SMS	UPDATE
<b>VDN</b>	SMSG	V SMS,SG,DISABLE,NEW	MVS.VARY.SMS	UPDATE
<b>VDN</b>	SMSV	V SMS,VOL,DISABLE,NEW	MVS.VARY.SMS	UPDATE
<b>VE</b>	SMSG	V SMS,SG,ENABLE	MVS.VARY.SMS	UPDATE
<b>VE</b>	SMSV	V SMS,VOL,ENABLE	MVS.VARY.SMS	UPDATE
<b>VF</b>	DEV	V OFFLINE	MVS.VARY.DEV	UPDATE
<b>VF</b>	JP LI PR PUN RDR	-	-	-
		*F VARY	jesx.MODIFY.V	UPDATE
<b>VQ</b>	SMSG	V SMS,SG,QUIESCE	MVS.VARY.SMS	UPDATE
<b>VQ</b>	SMSV	V SMS,VOL,QUIESCE	MVS.VARY.SMS	UPDATE
<b>VQN</b>	SMSG	V SMS,SG,QUIESCE,NEW	MVS.VARY.SMS	UPDATE
<b>VQN</b>	SMSV	V SMS,VOL,QUIESCE,NEW	MVS.VARY.SMS	UPDATE
<b>VS</b>	SMSG	V SMS,SG,SPACE	MVS.VARY.SMS	UPDATE
<b>VS</b>	SMSV	V SMS,VOL,SPACE	MVS.VARY.SMS	UPDATE
<b>WRMF</b>	DA I ST	\$T	jesx.MODIFY.BAT jesx.MODIFY.TSU jesx.MODIFY.STC	UPDATE
		*F J=,SPIN	jesx.MODIFY.JOB	
<b>W</b>	JDS	\$T	jesx.MODIFY.BAT jesx.MODIFY.TSU jesx.MODIFY.STC	UPDATE
		-	-	
<b>X</b>	CK CKH DA H I JDS JG JS JO O ST			
<b>X</b>	NS	-	-	-
		*C	jesx.CALL.TCP	UPDATE
<b>X</b>	PR PUN	-	-	-
		*X,WTR,OUT=	jesx.CALL.dspname	UPDATE
<b>Xoptions</b>	PR PUN	-	-	-
		*X,WTR,OUT=	jesx.CALL.dspname	UPDATE

Table 108. Action Characters.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an action character does not apply in a particular environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Action Character	SDSF Panel	Command, JES2	OPERCMDS Resource, JES2	OPERCMDS Required Access
		Command, JES3	OPERCMDS Resource, JES3	
<b>X</b>	RDR	-	-	-
		*X CR,IN=device	jesx.CALL.CR	UPDATE
<b>Xoptions</b>	RDR	-	-	-
		*X CR,IN=device	jesx.CALL.CR	UPDATE
<b>yRMF</b>	DA	STOP	MVS.STOP.type.jobname MVS.STOP.type.jobname.id	UPDATE
		STOP	MVS.STOP.type.jobname MVS.STOP.type.jobname.id	
<b>Z</b>	DA	FORCE	MVS.FORCE.type.jobname MVS.FORCE.type.jobname.id	CONTROL
		FORCE	MVS.FORCE.type.jobname MVS.FORCE.type.jobname.id	
<b>Z</b>	INIT	\$Z	jesx.HALT.INITIATOR	CONTROL
<b>Z</b>	NS	FORCE	MVS.FORCE.STC.servername	CONTROL
<b>Z</b>	PR PUN RDR	\$Z	jesx.HALT.DEV	UPDATE
		-	-	
<b>Z</b>	SP	\$ZSPL	jesx.HALT.SPOOL	CONTROL
<b>ZM</b>	MAS	\$J	jesxMON.STOP.MONITOR	CONTROL
	JP	*CANCEL	jesx.CANCEL.MONITOR	UPDATE
<b>?</b>	DA H I JG JO O ST			
<b>//</b>	all tabular panels			
<b>=</b>	all tabular panels			
<b>+</b>	all tabular panels			
<b>%</b>	all tabular panels	None	None	None
<b>Any</b>	Sysplex-wide panels <sup>2</sup>	ROUTE	MVS.ROUTE	READ

Notes for Table 108 on page 229:

<sup>1</sup> SDSF uses the subsystem interface (SSI) when you enter a C, H, O, or P action character on the JDS panel. When all data sets are deleted by use of the C and P action characters on the H panel, SDSF issues \$O.

<sup>2</sup> SDSF uses the MVS ROUTE command to route commands to a system in a sysplex other than the one the user is logged on to.

<sup>3</sup> The SAF resource varies with the JES2 resource. See “JES2 resources” on page 259.

<sup>4</sup> Refer to “Protecting action characters as separate resources ” on page 227.

**RMF** The DA panel must be using RMF as the source of its data.

In Table 109 on page 250, many action characters have more than one OPERCMDS resource name associated with them. The names vary according to the panel. Choose the OPERCMDS resource name that is related to the panel for which action character access is being given.

<p><i>Table 109. Action Characters by OPERCMDS Resource Name.</i></p> <p>Replace <b>jesx</b> with the name of the targeted JES subsystem, for example, JES2.</p> <p>Replace <b>type</b> with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace <b>type</b> with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.</p> <p>Replace <b>hcproc</b> and <b>hcstcid</b> with the IBM Health Checker for z/OS procedure name and started task ID.</p> <p>Resources apply to the JES indicated by the command in the JES/MVS Command column: the \$ command character indicates a JES2 command and the * command character indicates a JES3 command.</p>				
OPERCMDs Resource Name	Required Access	Action Character	JES/MVS Command	SDSF Panel
JES2MON.DISPLAY.DETAIL	READ	JD	\$JDDetails	RMA
JES2MON.DISPLAY.HISTORY	READ	JH	\$JDHistory	RMA
JES2MON.DISPLAY.JES	READ	JJ	\$JDJES	RMA
JES2MON.DISPLAY.MONITOR	READ	J	\$JDMonitor	RMA
JES2MON.DISPLAY.STATUS	READ	JS	\$JDStatus	RMA
jesx.BACKSP.DEV	UPDATE	Bnumber	\$B	PR PUN
jesx.CALL.CR	UPDATE	X	*X CR	RDR
jesx.CALL.dspname	UPDATE	X	*X	PR PUN
jesx.CALL.MONITOR	UPDATE	SM	*X	JP
jesx.CALL.NJE	UPDATE	SN	*X	NC NO
jesx.CANCEL.DEV	UPDATE	C	\$C	PR PUN LI SO RDR
jesx.CANCEL.DEV.device	UPDATE	C	*CANCEL	LI NC NS PR PUN RDR
jesx.CANCEL.device	UPDATE	C, I	*CANCEL	LI
jesx.CANCEL.type	UPDATE	C C CA CD CDA P P PP	\$C \$CO \$C,ARMRESTART \$C,D \$C,D,ARMRESTART \$C \$CO \$C	DA I O ST H H O DA I ST <sup>1</sup> DA I ST DA I ST DA I H O ST H O DA I ST
jesx.CANCEL.type	UPDATE	P	SSI	H
jesx.CANCEL.type	UPDATE	PP (TSU jobs)	\$C	DA
jesx.CANCEL.GROUP	UPDATE	C CP P	\$C	JG
jesx.CANCEL.MONITOR	UPDATE	ZM	*CANCEL	JP
jesx.CANCEL.TCP	UPDATE	C	*CANCEL	NC
jesx.DISPLAY.resource <sup>4</sup>	READ	D	\$T	RM
jesx.DISPLAY.typeOUT	READ	L, LL	\$DO \$L	H O ST DA I
jesx.DISPLAY.type	READ	D, DL, DP	\$D	ST I DA
jesx.DISPLAY.A	READ	DL	*I	DA



Table 109. Action Characters by OPERCMDS Resource Name.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the JES/MVS Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	Action Character	JES/MVS Command	SDSF Panel
<b>jesx.DISPLAY.APPL</b>	READ	DA	\$D	NC NS
<b>jesx.DISPLAY.CLASS</b>	READ	D	*I	JC
<b>jesx.DISPLAY.D</b>	READ	D, DL	*I	LI
<b>jesx.DISPLAY.D</b>	READ	D, DL	*I	PR PUN
<b>jesx.DISPLAY.DEV</b>	READ	D, DL	\$D	PR PUN SO RDR
<b>jesx.DISPLAY.G</b>	READ	D, DL	*I	INIT
<b>jesx.DISPLAY.G</b>	READ	DC, DG	*I	JC
<b>jesx.DISPLAY.GROUP</b>	READ	D	\$D	JG
<b>jesx.DISPLAY.INITIATOR</b>	READ	D, DL	\$D	INIT
<b>jesx.DISPLAY.JOB</b>	READ	D, DL	\$D	JC
<b>jesx.DISPLAY.JOB</b>	READ	D, L, LB, LH, LT	*I	DA I ST
<b>jesx.DISPLAY.JOBE</b>	READ	DE	*I	DA I ST
<b>jesx.DISPLAY.JST</b>	READ	J	\$D	SP
<b>jesx.DISPLAY.L</b>	READ	D	\$D	LI NC
<b>jesx.DISPLAY.LINE</b>	READ	D	\$D	LI NC
<b>jesx.DISPLAY.LINE</b>	READ	DL	\$D	NC
<b>jesx.DISPLAY.LIMITS</b>	READ	D	\$DLIMITS	JRI
<b>jesx.DISPLAY.LIMITS</b>	READ	DL	\$DLIMITS	JRI
<b>jesx.DISPLAY.LIMITS</b>	READ	DLI	\$DLIMITS	JRJ
<b>jesx.DISPLAY.LOGON</b>	READ	D	\$D	NS
<b>jesx.DISPLAY.MAIN</b>	READ	D	*I	JP
<b>jesx.DISPLAY.MAINX</b>	READ	DL	*I	JP
<b>jesx.DISPLAY.MEMBER</b>	READ	D	\$D	MAS
<b>jesx.DISPLAY.NETSRV</b>	READ	D, DL	\$D *I	NS
<b>jesx.DISPLAY.NJE</b>	READ	D, DL	*I	NO
<b>jesx.DISPLAY.NODE</b>	READ	D, DC, DL, DP	\$D	NO
<b>jesx.DISPLAY.PROCLIB</b>	READ	D	\$DPROCLIB	PROC
<b>jesx.DISPLAY.PROCLIB</b>	READ	DD	\$DPROCLIB,DEBUG	PROC
<b>jesx.DISPLAY.Q</b>	READ	D, DL, J	*I Q	SP
<b>jesx.DISPLAY.S</b>	READ	DMA, DME, DMR, DMSS, DMSV, DMU	*I	I ST

Table 109. Action Characters by OPERCMDS Resource Name.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the JES/MVS Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDS Resource Name	Required Access	Action Character	JES/MVS Command	SDSF Panel
<b>jesx.DISPLAY.SOCKET</b>	READ	D	\$D *I	NC
<b>jesx.DISPLAY.SOCKET</b>	READ	DS	\$D	NS
<b>jesx.DISPLAY.SPOOL</b>	READ	D, DL	\$D	SP
<b>jesx.DISPLAY.T</b>	READ	DE	*I	LI
<b>jesx.DISPLAY.U</b>	READ	D	*I U J	J0
<b>jesx.FAIL.DEV.device</b>	CONTROL	L	*FAIL	NS
<b>jesx.FAIL.DEV.device</b>	CONTROL	L, LD	*FAIL	PR RDR
<b>jesx.FAIL.device</b>	CONTROL	L, LD	*FAIL	LI
<b>jesx.FAIL.dspname</b>	CONTROL	L, LD	*FAIL	PUN
<b>jesx.FORWARD.DEV</b>	UPDATE	Fnumber	\$F	PR PUN
<b>jesx.HALT.DEV</b> <b>jesx.HALT.INITIATOR</b> <b>jesx.HALT.SPOOL</b>	UPDATE CONTROL CONTORL	Z	\$Z	PR PUN RDR INIT SP
<b>jesx.INTERRUPT.DEV</b>	UPDATE	I	\$I	PR PUN
<b>jesx.MODIFY.G</b>	UPDATE	P, S	*F	INIT
<b>jesx.MODIFY.JOB</b>	UPDATE	A, C, CA, CD, CDA, CDP, H, P, W	*F	DA I ST
<b>jesx.MODIFY.JOB</b>	UPDATE	J	*F	I ST
<b>jesx.MODIFY.type</b>	UPDATE	W	\$T	DA I JDS ST
<b>jesx.MODIFY.typeOUT</b>	UPDATE	A H OK	\$TO	O H O H H
<b>jesx.MODIFY.LINE</b>	CONTROL	I Q	\$TLINE \$TLINE	LI
<b>jesx.MODIFY.NJE</b>	UPDATE	A, EL, H	*F	NO
<b>jesx.MODIFY.Q</b>	UPDATE	A, H, HC, HP, P, U	*F Q	SP
<b>jesx.MODIFY.U</b>	UPDATE	C, H, O, P	*F	JDS J0
<b>jesx.MODIFY.V</b>	UPDATE	PX, V, VF V, VF	*F	JP LI PR PUN RDR
<b>jesx.MODIFYHOLD.type</b>	UPDATE	H	\$H	DA I ST
<b>jesx.MODIFYHOLD.GROUP</b>	UPDATE	H	\$H	JG
<b>jesx.MODIFYRELEASE.type</b>	UPDATE	A	\$A	DA I ST
<b>jesx.MODIFYRELEASE.GROUP</b>	UPDATE	A	\$A	JG

Table 109. Action Characters by OPERCMDS Resource Name.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the JES/MVS Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDS Resource Name	Required Access	Action Character	JES/MVS Command	SDSF Panel
<b>jesxMON.DISPLAY.DETAIL</b>	READ	JD	\$J	MAS
<b>jesxMON.DISPLAY.HISTORY</b>	READ	JH	\$J	MAS
<b>jesxMON.DISPLAY.JES</b>	READ	JJ	\$J	MAS
<b>jesxMON.DISPLAY.MONITOR</b>	READ	J	\$J	MAS
<b>jesxMON.DISPLAY.STATUS</b>	READ	JS	\$J	MAS
<b>jesxMON.STOP.MONITOR</b>	CONTROL	ZM	\$J	MAS
<b>jesx.MSEND.CMD</b>	READ	Any	\$M	I ST
<b>jesx.RELEASE.typeOUT</b>	UPDATE	C O P	\$O \$O \$O	H <sup>1</sup> ST H <sup>1</sup>
<b>jesx.REPEAT.DEV</b>	UPDATE	N	\$N	PR PUN
<b>jesx.RESTART.BAT</b>	CONTROL	E (all forms)	\$E	DA I ST
<b>jesx.RESTART.DEV</b> <b>jesx.RESTART.LINE</b> <b>jesx.RESTART.SYS</b>	UPDATE CONTROL CONTROL	E, EC E	\$E	PR PUN LI SO LI MAS
<b>jesx.RESTART.DEV</b>	UPDATE	E	\$E	NC NS
<b>jesx.RESTART.DEV.device</b>	UPDATE	E	*R	NS
<b>jesx.RESTART.DEV.device</b>	UPDATE	B, E, F	*R	PR PUN
<b>jesx.RESTART.DEV.main</b>	CONTROL	E	*R	DA I ST
<b>jesx.RESTART.LINE</b>	CONTROL	E	\$E	NC
<b>jesx.RESTART.RJP</b>	UPDATE	E	*R	LI
<b>jesx.START.BAT</b>	UPDATE	J	\$SJ	I ST
<b>jesx.START.DEV</b>	UPDATE	S	\$S	NC NS PR PUN LI SO RDR
<b>jesx.START.DEV</b>	UPDATE	SR, ST	\$S	SO
<b>jesx.START.DEV.device</b>	CONTROL	S	*START	LI
<b>jesx.START.DEV.device</b>	UPDATE	S	*START	PR PUN RDR
<b>jesx.START.DEV.main</b>	UPDATE	C, F	*S	JP
<b>jesx.START.INITIATOR</b>	CONTROL	S	\$S	INIT
<b>jesx.START.JSS</b>	UPDATE	S	*S	JP
<b>jesx.START.LINE</b>	CONTROL	S	\$S	LI
<b>jesx.START.MONITOR</b>	UPDATE	DM	*S	JP
<b>jesx.START.NET</b>	CONTROL	SN	\$S	LI NC NO
<b>jesx.START.SPOOL</b>	CONTROL	SP	\$S	SP

Table 109. Action Characters by OPERCMDS Resource Name.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the JES/MVS Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	Action Character	JES/MVS Command	SDSF Panel
<b>jesx.START.SYS</b>	CONTROL	S	\$S	MAS
<b>jesx.START.TCP</b>	UPDATE	SN	*S	NC
<b>jesx.START.TCP</b>	UPDATE	SN	*S	NO
<b>jesx.STOP.DEV</b>	UPDATE	P	\$P	NC NS PR PUN LI SO RDR
<b>jesx.STOP.INITIATOR</b>	CONTROL	P	\$P	INIT
<b>jesx.STOP.LINE</b>	CONTROL	P	\$P	LI
<b>jesx.STOP.SPOOL</b>	CONTROL	P, PC	\$P	SP
<b>jesx.STOP.SYS</b>	CONTROL	P	\$P	MAS
<b>jesx.STOP.RETURN</b>	CONTROL	P	*RETURN	JP
<b>MVS.CANCEL.type.jobname</b>	UPDATE	C CD K, KD P PP	C U=userid C U=, DUMP C jobname,A=asid C U=userid C U=userid C jobname,A=asid <sup>2</sup>	DA
<b>MVS.CANCEL.type.jobname</b>	UPDATE	C	C U=userid C jobname,A=asid	PS
<b>MVS.CANCEL.STC.servername</b>	CONTROL	K, KD	C	NS
<b>MVS.CONTROL.C</b>	READ	C	K C	SR
<b>MVS.DISPLAY.ALLOC</b>	READ	DALO	D ALLOC,OPTIONS	SYS
<b>MVS.DISPLAY.AUTOR</b>	READ	D	D AUTOR,P	SYSP
<b>MVS.DEVSERV</b>	READ	DSP	DS P	DEV
	READ	DSQD	DS QD	DEV
	READ	DSQP	DS QP	DEV
	READ	DSS	DS S	DEV
<b>MVS.DISPLAY.ASM</b>	READ	D	D ASM,PAGE=	PAG
	READ	D	D ASM,SCM	PAG
	READ	DC	D ASM,COMMON	PAG
	READ	DD	D ASM,PAGEDEL	PAG
	READ	DL	D ASM,LOCAL	PAG
	READ	DP	D ASM,PLPA	PAG
	READ	DS	D ASM,SCM	PAG
<b>MVS.DISPLAY.CEE</b>	READ	DCEE	D CEE,ALL	SYS
	READ	D	D CEE,ALL	SYSP

Table 109. Action Characters by OPERCMDS Resource Name.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the JES/MVS Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDS Resource Name	Required Access	Action Character	JES/MVS Command	SDSF Panel
<b>MVS.DISPLAY.CONSOLES</b>	READ	DC	D C	SYS
	READ	D	D C	SYSP
<b>MVS.DISPLAY.DEVSUP</b>	READ	D	D DEVSUP	SYSP
<b>MVS.DISPLAY.DIAG</b>	READ	D	D DIAG	SYSP
<b>MVS.DISPLAY.DUMP</b>	READ	DD	D D,E	SYS
	READ	D	D D,E	SYSP
<b>MVS.DISPLAY.EMCS</b>	READ	DEM	D EMCS	SYS
	READ	DL	D EMCS,F,CN=	EMCS
<b>MVS.DISPLAY.GRS</b>	READ	D	D GRS,HEX,RES=	ENQ
	READ	DG	D GRS,SYSTEM	SYS
	READ	D	D GRS,SYSTEM	SYSP
<b>MVS.DISPLAY.GTZ</b>	READ	D	D GTZ,TRACKDATA=(OWNER=)	GT
	READ	D	D GTZ,TRACKDATA=(ALL)	SYSP
	READ	DA	D GTZ,TRACKDATA=(ALL)	GT
	READ	DD	D GTZ,DEBUG	GT
	READ	DE	D GTZ,EXCLUDE	GT
	READ	DH	D GTZ,TRACKDATA=(HOMEJOB=)	GT
<b>MVS.DISPLAY.IKJTSO</b>	READ	DS	D GTZ,STATUS	GT
	READ	DS	D GTZ,STATUS	GT
<b>MVS.DISPLAY.IKJTSO</b>	READ	DTO	D IKJTSO	SYS
	READ	DTO	D IKJTSO	SYSP
<b>MVS.DISPLAY.IOS</b>	READ	DI	D IOS,CONFIG	SYS
<b>MVS.DISPLAY.IPLINFO</b>	READ	D	D IPLINFO,BOOST,STATE-SYS	SYSP
	READ	D	D IPLINFO,OSPROTECT	SYSP
	READ	D	D IPLINFO,ZAAPZIIP,STATE	SYSP
<b>MVS.DISPLAY.IQP</b>	READ	DIQP	D IQP	SYS
	READ	D	D IQP	SYSP
<b>MVS.DISPLAY.IZU</b>	READ	D	D IZU	SYSP
<b>MVS.DISPLAY.JOB</b>	READ	DTS	D TS,L	SYS
	READ	DTS	D TS,L	SYSP
	READ	DAA	D A,ALL	SYS
	READ	DAL	D A,L	SYS
<b>MVS.DISPLAY.LLA</b>	READ	DLL	D LLA	SYS

Table 109. Action Characters by OPERCMDS Resource Name.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the JES/MVS Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDS Resource Name	Required Access	Action Character	JES/MVS Command	SDSF Panel
<b>MVS.DISPLAY.LOGGER</b>	READ	DLO	D LOGGER	SYS
<b>MVS.DISPLAY.LOGREC</b>	READ	DLR	D LOGREC	SYS
	READ	DLR	D LOGREC	SYSP
<b>MVS.DISPLAY.M</b>	READ	DM	D M	SYS
<b>MVS.DISPLAY.MPF</b>	READ	DMP	D MPF	SYS
<b>MVS.DISPLAY.OMVS</b>	READ	DO	D OMVS,O	SYS
	READ	DO	D OMVS,O	SYSP
	READ	D	D OMVS,F,N=	FS
	READ	DA	D OMVS,F	FS
	READ	DE	D OMVS,F,E	FS
	READ	DO	D OMVS,O	OMVS
<b>MVS.DISPLAY.OPDATA</b>	READ	DO	D OPDATA	SSI
<b>MVS.DISPLAY.PARMLIB</b>	READ	DE	D PARMLIB,ERRORS	PARM
	READ	D	D PARMLIB	PARM
<b>MVS.DISPLAY.PCIE</b>	READ	DPCD	D PCIE,DD	SYS
	READ	DPCI	D PCIE	SYS
<b>MVS.DISPLAY.PPT</b>	READ	D	D PPT,ALL	SYSP
<b>MVS.DISPLAY.PROD</b>	READ	DP	D PROD,REG	SYS
	READ	D	D PROD,REG	SYSP
<b>MVS.DISPLAY.PROG</b>	READ	D	D PROG,APF, DSNAME=	APF
	READ	D	D PROG,EXIT,EX=	DYNX
	READ	D	D PROG,LNKLST, NAME=	LNK
	READ	D	D PROG,APF,ALL	SYSP
	READ	D	D PROG,LNKLST	SYSP
	READ	D	D PROG,LPA,CSAMIN	SYSP
	READ	DA	D PROG,APF,ALL	APF
	READ	DA	D PROG,EXIT,ALL	DYNX
	READ	DAI	D PROG,EXIT,ALL,IMPLICIT	DYNX
	READ	DD	D PROG,EXIT,EX=,DIAG	DYNX
	READ	DI	D PROG,EXIT,INSTALLATION	DYNX
	READ	DN	D PROG,LNKLST, NAMES	LNK
	READ	DNP	D PROG,EXIT,NOTPROGRAM	DYNX
	READ	DP	D PROG,EXIT,PROGRAM	DYNX

Table 109. Action Characters by OPERCMDS Resource Name.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the JES/MVS Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	Action Character	JES/MVS Command	SDSF Panel
<b>MVS.DISPLAY.R</b>	READ	D	D	SR
<b>MVS.DISPLAY.SLIP</b>	READ	DSL	D SLIP	SYS
<b>MVS.DISPLAY.SMF</b>	READ	DSF	D SMF,O	SYS
	READ	D	D SMF,O	SYSP
<b>MVS.DISPLAY.SMS</b>	READ	D	D SMS	SYSP
	READ	DSM	D SMS	SYS
	READ	D	D SMS,SG	SMSG
	READ	D	D SMS,VOL	SMSV
	READ	DC	D SMS,CFVOL	SMSV
	READ	DL	D SMS,SG,LISTVOL	SMSG
	READ	DS	D SMS,SG	SMSV
	READ	DSL	D SMS,SG,LISTVOL	SMSV
<b>MVS.DISPLAY.SSI</b>	READ	D	D SSI,ALL	SYSP
<b>MVS.DISPLAY.SYMBOLS</b>	READ	DSY	D SYMBOLS	SYS
	READ	DL	D SYMBOLS	SYM
<b>MVS.DISPLAY.TCPIP</b>	READ	D	D	JD
	READ	DA	D TCPIP,stack, N,ALL,IPP=	NA
	READ	DAL	D TCPIP,stack, N,ALL,IPP=, FORMAT=LONG	NA
	READ	DB	D TCPIP,stack, N,BYTE,IDLETIME, IPA=	NA
	READ	DBL	D TCPIP,stack, N,BYTE,IDLETIME, IPA=,FORMAT=LONG=	NA
	READ	DN	D TCPIP,stack, N,CO,APPLDATA, IPP=	NA
	READ	DNL	D TCPIP,stack, N,CO,APPLDATA, IPP=,FORMAT=LONG	NA
	READ	DR	D TCPIP,stack, N,ROUTE,IPP=	NA
	READ	DRD	D TCPIP,stack, N,ROUTE,DETAIL, IPP=	NA
	READ	DRDL	D TCPIP,stack, N,ROUTE,DETAIL, IPP=,FORMAT=LONG	NA
	READ	DRL	D TCPIP,stack, N,ALL,IPP=	NA
<b>MVS.DISPLAY.TIMEDATE</b>	READ	DT	D T	SYS
<b>MVS.DISPLAY.TRACE</b>	READ	DTR	D TRACE	SYS

Table 109. Action Characters by OPERCMDS Resource Name.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the JES/MVS Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDS Resource Name	Required Access	Action Character	JES/MVS Command	SDSF Panel
<b>MVS.DISPLAY.VIRTSTOR</b>	READ	D	D VIRTSTOR,HVCOMMON D VIRTSTOR,HVSHARE	SYSP
<b>MVS.DISPLAY.XCF</b>	READ	D	D	JD
	READ	D	D XCF,COUPLE	SYSP
	READ	D	D XCF,GROUP, <i>groupname</i> , <i>membername</i>	XCFM
	READ	DA	D XCF,GROUP, <i>groupname</i> ,ALL	XCFM
	READ	DG	D XCF, GROUP, <i>groupname</i>	XCFM
	READ	DX	D XCF	SYM
	READ	D	D XCF,COUPLE,TYPE= <i>type</i>	CFD
	READ	DA	D XCF,COUPLE	CFD
<b>MVS.DISPLAY.U</b>	READ	D	D U,VOL=	DEV
	READ	DA	D U,ALLOC	DEV
<b>MVS.FORCE.type.jobname</b> <b>MVS.FORCE.type.jobname.id</b>	CONTROL	Z	FORCE	DA
<b>MVS.FORCE.STC.servername</b>	CONTROL	Z	FORCE	NS
<b>MVS.MODIFY.STC.fssproc.fssname</b>	UPDATE	K	F	PR
<b>MVS.MODIFY.STC.hcproc.hcstcid</b>	UPDATE	A, D, DL, DP, DPO, DS, E, H, P, PF, R, U	F	CK
<b>MVS.MODIFY.STC.BPXOINIT.BPXOINIT</b>	UPDATE	K, T	F	PS
<b>MVS.DISPLAY.WLM</b>	READ	D	D	SE RES
	READ	DW	D WLM	SYS
<b>MVS.SETCON.DELETE</b>	UPDATE	P	SETCON DELETE,CN=	EMCS
<b>MVS.SETOMVS.OMVS</b>	UPDATE	N	SETOMVS <i>optionname</i> =NOLIMIT	OMVS
<b>MVS.RESET</b>	UPDATE	R	RESET	DA <sup>RMF</sup>
<b>MVS.RESET</b>	UPDATE	RQ	RESET	DA <sup>RMF</sup>
<b>MVS.RESET.CN</b>	CONTROL	E	RESET CN()	EMCS
<b>MVS.REPLY</b>	READ	R	R	SR
<b>MVS.ROUTE</b>	READ	Any	ROUTE	DA ENC INIT LI NO MAS PR PS PUN RDR SO <sup>3</sup>
<b>MVS.SETAUTOR.AUTOR</b>	READ	AI	SETAUTOR	SR
<b>MVS.SETSSI.ACTIVATE.ssname</b>	CONTROL	A	SETSSI ACT,S=	SSI



Table 109. Action Characters by OPERCMDS Resource Name.

Replace **jesx** with the name of the targeted JES subsystem, for example, JES2.

Replace **type** with BAT (batch jobs), STC (started tasks), or TSU (TSO users). For APPC transactions, replace **type** with STC for transaction SYSOUT on the H and O panels, or ATX for transactions on the DA, I, and ST panels.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the JES/MVS Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	Action Character	JES/MVS Command	SDSF Panel
<b>MVS.SETSSI.DEACTIVATE.ssname</b>	CONTROL	H	SETSSI DEACT,S=	SSI
	CONTROL	PF	SETSSI DELETE, S=,FORCE	SSI
<b>MVS.STOP.type.jobname</b> <b>MVS.STOP.type.jobname.id</b>	UPDATE	Y	STOP	DA <sup>RMF</sup>
<b>MVS.VARYAUTH.CN</b>	CONTROL	V	V CN(), AUTH=	EMCS
<b>MVS.VARY.DEV</b>	UPDATE	V	V ONLINE	DEV
	UPDATE	VF	V OFFLINE	DEV
<b>MVS.VARYAUTH.CN</b>	CONTROL	V	V CN(), AUTH=	EMCS
<b>MVS.VARY.SMS</b>	UPDATE	VD	V SMS,SG, DISABLE	SMSG
	UPDATE	VD	V SMS,VOL, DISABLE	SMSV
	UPDATE	VDN	V SMS,SG, DISABLE,NEW	SMSG
	UPDATE	VDN	V SMS,VOL, DISABLE,NEW	SMSV
	UPDATE	VE	V SMS,SG,ENABLE	SMSG
	UPDATE	VE	V SMS,VOL,ENABLE	SMSV
	UPDATE	VQ	V SMS,SG, QUIESCE	SMSG
	UPDATE	VQ	V SMS,VOL, QUIESCE	SMSV
	UPDATE	VQN	V SMS,SG, QUIESCE,NEW	SMSG
	UPDATE	VQN	V SMS,VOL, QUIESCE,NEW	SMSV
	UPDATE	VS	V SMS,SG,SPACE	SMSG
	UPDATE	VS	V SMS,VOL, SPACE	SMSV

Notes for Table 109 on page 250:

<sup>1</sup> This occurs only on a secondary JES system.

<sup>2</sup> This form of the CANCEL command is issued against APPC transaction programs.

<sup>3</sup> SDSF uses the MVS ROUTE command to route commands to a system in a sysplex other than the one the user is logged on to, for these panels, when they are showing sysplex-wide data: CK, ENC, INIT, LI, NO, PR, PS, PUN, RDR, RM and SO.

<sup>4</sup> The SAF resource varies with the JES2 resource. See “JES2 resources” on page 259.

**RMF** The DA panel must be using RMF as the source of its data.

## JES2 resources

The following table shows the SAF resources in the OPERCMDS class for the JES2 resources displayed on the RM panel.

Table 110. OPERCMDS Resources That Protect Issuing Action Characters for JES2 Resources

JES2 Resource	OPERCMDS Resource	Required Access
BERT	jesx.DISPLAY.CKPTSPACE	READ
BSCB	jesx.DISPLAY.TPDEF	READ
BUFX	jesx.DISPLAY.BUFDEF	READ
CKVR	jesx.DISPLAY.CKPTDEF	READ
CMBS	jesx.DISPLAY.CONDEF	READ
CMDS	jesx.DISPLAY.CONDEF	READ
ICES	jesx.DISPLAY.TPDEF	READ
JNUM	jesx.DISPLAY.JOBDEF	READ
JOES	jesx.DISPLAY.OUTDEF	READ
JQES	jesx.DISPLAY.JOBDEF	READ
LBUF	jesx.DISPLAY.BUFDEF	READ
NHBS	jesx.DISPLAY.NJEDEF	READ
SMFB	jesx.DISPLAY.SMFDEF	READ
TBUF	Not applicable	
TGS	jesx.DISPLAY.SPOOLDEF	READ
TTAB	jesx.DISPLAY.TRACEDEF	READ
VTMB	jesx.DISPLAY.TPDEF	READ
ZJC	jesx.DISPLAY.GRPDEF	READ

## Authorized program facility data sets

### Protecting authorized program facility data sets

Protect authorized program facility data sets by defining resource names in the SDSF class. The resources are shown in [Table 111 on page 260](#).

Table 111. SAF Resources for Authorized Program Facility Data Sets

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFAPF.datasetname	SDSF	READ
DA	ISFAPF.datasetname	SDSF	READ

To control access to the APF panel, protect the APF command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting authorized program facility data sets

To protect all authorized program facility data sets and permit a user to control them, define a generic profile as follows:

```
REDEFINE SDSF ISFAPF.** UACC(NONE)
PERMIT ISFAPF.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Authorized SDSF commands

The authorized SDSF commands are the SDSF commands that can be on the AUTH parameter in ISFPARMS, with the addition of OWNER, which can only be protected through SAF. If no SAF protection exists for the OWNER command, then all users can issue the OWNER command.

Only those SDSF panel commands (such as DA, I, and O) for which the user is authorized are displayed on the SDSF Primary Option Menu.

## Protecting SDSF commands

Protect authorized SDSF commands by defining resource names in the SDSF class.

SDSF authorized commands and their resource names are listed in [Table 112 on page 261](#).

*Table 112. SDSF Class Resource Names and SDSF Commands.*

Replace **sysname** with the name of the system that the user is logged on to.

Command	SDSF Class Resource Name	Class	Required Access
<b>ACTION</b>	ISFCMD.FILTER.ACTION	SDSF	READ
<b>AD</b>	ISFCMD.ODSP.AD.sysname	SDSF	READ
<b>APF</b>	ISFCMD.ODSP.APF.sysname	SDSF	READ
<b>AS</b>	ISFCMD.ODSP.AS.sysname	SDSF	READ
<b>BPXO</b>	ISFCMD.ODSP.OMVS.sysname	SDSF	READ
<b>CFC</b>	ISFCMD.ODSP.COUPLE.sysname	SDSF	READ
<b>CFD</b>	ISFCMD.ODSP.COUPLED.S.sysname	SDSF	READ
<b>CFS</b>	ISFCMD.ODSP.CFSTRUCT.sysname	SDSF	READ
<b>CK</b>	ISFCMD.ODSP.HCHECKER.sysname	SDSF	READ
<b>CKPT</b>	ISFCMD.ODSP.JESCKPT.jesx	SDSF	READ
<b>CS</b>	ISFCMD.ODSP.CS.sysname	SDSF	READ
<b>CSR</b>	ISFCMD.ODSP.CSR.sysname	SDSF	READ
<b>DA</b>	ISFCMD.DSP.ACTIVE.jesx	SDSF	READ
<b>DEST</b>	ISFCMD.FILTER.DEST	SDSF	READ
<b>DEV</b>	ISFCMD.ODSP.DEVACT.sysname	SDSF	READ
<b>DYNX</b>	ISFCMD.ODSP.DYNX.sysname	SDSF	READ
<b>EMCS</b>	ISFCMD.ODSP.EMCS.sysname	SDSF	READ
<b>ENC</b>	ISFCMD.ODSP.ENCLAVE.sysname	SDSF	READ
<b>ENQ</b>	ISFCMD.ODSP.ENQUEUE.sysname	SDSF	READ
<b>FINDLIM</b>	ISFCMD.FILTER.FINDLIM	SDSF	READ
<b>FS</b>	ISFCMD.ODSP.FILESYS.sysname	SDSF	READ
<b>GT</b>	ISFCMD.ODSP.TRACKER.sysname	SDSF	READ
<b>H</b>	ISFCMD.DSP.HELD.jesx	SDSF	READ
<b>I</b>	ISFCMD.DSP.INPUT.jesx	SDSF	READ

Table 112. SDSF Class Resource Names and SDSF Commands.

Replace **sysname** with the name of the system that the user is logged on to.

(continued)

Command	SDSF Class Resource Name	Class	Required Access
<b>INIT</b>	ISFCMD.ODSP.INITIATOR.jesx	SDSF	READ
<b>INPUT</b>	ISFCMD.FILTER.INPUT	SDSF	READ
<b>JO (JES3 only)</b>	ISFCMD.ODSP.JOB0.jesx	SDSF	READ
<b>JC</b>	ISFCMD.ODSP.JOBCLASS.jesx	SDSF	READ
<b>JES</b>	ISFCMD.ODSP.JES.sysname	SDSF	READ
<b>JESNAME</b> parameter on <b>SDSF</b> command	ISFCMD.OPT.JESNAME	SDSF	READ
<b>JES3NAME</b> parameter on <b>SDSF</b> command	ISFCMD.OPT.JES3NAME	SDSF	READ
<b>JG (JES2 only)</b>	ISFCMD.DSP.JGROUP.jesx	SDSF	READ
<b>JP and MAS</b>	ISFCMD.ODSP.MAS.jesx	SDSF	READ
<b>JRI</b>	ISFCMD.ODSP.JESINFO.jesx	SDSF	READ
<b>JRJ</b>	ISFCMD.ODSP.JESINFO.jesx	SDSF	READ
<b>LI</b>	ISFCMD.ODSP.LINE.jesx	SDSF	READ
<b>LLS</b>	ISFCMD.ODSP.LLS.sysname	SDSF	READ
<b>LNK</b>	ISFCMD.ODSP.LNK.sysname	SDSF	READ
<b>LOG</b>	ISFCMD.ODSP.SYSLOG.jesx	SDSF	READ
<b>LPA</b>	ISFCMD.ODSP.LPA.sysname	SDSF	READ
<b>LPD</b>	ISFCMD.ODSP.LPD.sysname	SDSF	READ
<b>MAS and JP</b>	ISFCMD.ODSP.MAS.jesx	SDSF	READ
<b>MEM</b>	ISFJOB.STORAGE.owner.jobname.sysname	SDSF	CONTROL (displays pages not currently paged in)
	ISFCMD.ODSP.MEM.sysname	SDSF	READ (displays pages already paged in)
<b>NA</b>	ISFCMD.ODSP.NETACT.sysname	SDSF	READ
<b>NC</b>	ISFCMD.ODSP.NC.jesx	SDSF	READ
<b>NO</b>	ISFCMD.ODSP.NODE.jesx	SDSF	READ
<b>NS</b>	ISFCMD.ODSP.NS.jesx	SDSF	READ
<b>O</b>	ISFCMD.DSP.OUTPUT.jesx	SDSF	READ
<b>OWNER</b>	ISFCMD.FILTER.OWNER	SDSF	READ
<b>PAG</b>	ISFCMD.ODSP.PAGE.sysname	SDSF	READ
<b>PARM</b>	ISFCMD.ODSP.PARMLIB.sysname	SDSF	READ

Table 112. SDSF Class Resource Names and SDSF Commands.

Replace **sysname** with the name of the system that the user is logged on to.

(continued)

Command	SDSF Class Resource Name	Class	Required Access
<b>PC</b>	ISFCMD.ODSP.PC. <i>sysname</i>	SDSF	READ
<b>PR</b>	ISFCMD.ODSP.PRINTER. <i>jesx</i>	SDSF	READ
<b>PREFIX</b>	ISFCMD.FILTER.PREFIX	SDSF	READ
<b>PROC (JES2 only)</b>	ISFCMD.ODSP.PROCLIB. <i>jesx</i>	SDSF	READ
<b>PS</b>	ISFCMD.ODSP.PROCESS. <i>sysname</i>	SDSF	READ
<b>PUN</b>	ISFCMD.ODSP.PUNCH. <i>jesx</i>	SDSF	READ
<b>RDR</b>	ISFCMD.ODSP.READER. <i>jesx</i>	SDSF	READ
<b>REPC</b>	ISFCMD.ODSP.REPC. <i>sysname</i>	SDSF	READ
<b>RES</b>	ISFCMD.ODSP.RESOURCE. <i>sysname</i>	SDSF	READ
<b>RGRP</b>	ISFCMD.ODSP.RGRP. <i>sysname</i>	SDSF	READ
<b>RM (JES2 only)</b>	ISFCMD.ODSP.RESMON. <i>jesx</i>	SDSF	READ
<b>RMA</b>	ISFCMD.ODSP.RESMON. <i>jesx</i>	SDSF	READ
<b>RSYS</b>	ISFCMD.FILTER.RSYS	SDSF	READ
<b>SE</b>	ISFCMD.DSP.SCHENV. <i>sysname</i>	SDSF	READ
<b>SMSG</b>	ISFCMD.ODSP.STORGRP. <i>sysname</i>	SDSF	READ
<b>SMSV</b>	ISFCMD.ODSP.SMSVOL. <i>sysname</i>	SDSF	READ
<b>SO (JES2 only)</b>	ISFCMD.ODSP.SO. <i>jesx</i>	SDSF	READ
<b>SP</b>	ISFCMD.ODSP.SPOOL. <i>jesx</i>	SDSF	READ
<b>SR</b>	ISFCMD.ODSP.SR. <i>sysname</i>	SDSF	READ
<b>SRVC</b>	ISFCMD.ODSP.SRVC. <i>sysname</i>	SDSF	READ
<b>SSI</b>	ISFCMD.ODSP.SUBSYS. <i>sysname</i>	SDSF	READ
<b>ST</b>	ISFCMD.DSP.STATUS. <i>jesx</i>	SDSF	READ
<b>SVC</b>	ISFCMD.ODSP.SVC. <i>sysname</i>	SDSF	READ
<b>SYM</b>	ISFCMD.DSP.SYMBOL. <i>sysname</i>	SDSF	READ
<b>SYS</b>	ISFCMD.ODSP.SYSTEM. <i>sysname</i>	SDSF	READ
<b>SYSP</b>	ISFCMD.ODSP.PARMLIB. <i>sysname</i>	SDSF	READ
<b>SYSID</b>	ISFCMD.FILTER.SYSID	SDSF	READ
<b>SYSNAME</b>	ISFCMD.FILTER.SYSNAME	SDSF	READ
<b>TRACE</b>	ISFCMD.MAINT.TRACE	SDSF	READ access required for all traces
<b>ULOG</b>	ISFCMD.ODSP.ULOG. <i>jesx</i>	SDSF	READ access is required only when the custom property Console.EMCS.UlogAuthReq is set to TRUE

Table 112. SDSF Class Resource Names and SDSF Commands.

Replace **sysname** with the name of the system that the user is logged on to.

(continued)

Command	SDSF Class Resource Name	Class	Required Access
<b>VMAP</b>	ISFCMD.ODSP.VIRTSTOR. <i>sysname</i>	SDSF	READ
<b>WKLD</b>	ISFCMD.ODSP.WKLD. <i>sysname</i>	SDSF	READ
<b>WLM</b>	ISFCMD.ODSP.WLM. <i>sysname</i>	SDSF	READ
<b>XCFM</b>	ISFCMD.ODSP.CFMEMBER. <i>sysname</i>	SDSF	READ

The DEST command is protected like any other SDSF authorized command, but you can also protect the destination names used with the DEST command. What is actually shown on the tabular SDSF panels can be affected by your destination authority, as explained in [“Destination names” on page 268](#).

## Setting up generic profiles

You can set up different levels of generic profiles to allow use of different kinds of SDSF commands:

Generic Profile	Type of Command	Protects
<b>ISFCMD.**</b>	All	All SDSF authorized commands
<b>ISFCMD.MAINT.*</b>	Maintenance commands	TRACE
<b>ISFCMD.DSP.*</b>	End user displays	DA, H, I, JG, O, ST, SE, SYM
<b>ISFCMD.ODSP.*</b>	Operator displays	AD, APF, AS, BPXO, CFC, CFD, CFS, CK, CKPT, CS, CSR, DEV, DYNX, EMCS, ENC, ENQ, FS, GT, INIT, JES, JC, JP, JO, JRI, JRJ, LI, LLS, LNK, LOG, LPA, LPD, MAS, NA, NC, NO, NS, PAG, PARM, PC, PR, PROC, PS, PUN, RDR, REPC, RES, RGRP, RM, RMA, SMSG, SMSV, SO, SP, SR, SRVC, SSI, SVC, SYS, SYSP, ULOG, VMAP, WKLD, WLM, XCFM
<b>ISFCMD.FILTER.*</b>	Filtering commands	ACTION, DEST, FINDLIM, INPUT, OWNER, PREFIX, RSYS, SYSID, SYSNAME
<b>ISFCMD.OPT.**</b>	Parameters on the SDSF command	JESNAME, JES3NAME

## Examples of protecting commands

1. To protect all commands and grant access to user SHERRYF, issue the following:

```
RDEFINE SDSF ISFCMD.** UACC(NONE)
PERMIT ISFCMD.** CLASS(SDSF) ID(SHERRYF) ACCESS(READ)
```

2. To allow access only to the DA, H, I, JG, O, SE, ST and SYM panels, issue the following:

```
RDEFINE SDSF ISFCMD.DSP.** UACC(NONE)
PERMIT ISFCMD.DSP.** CLASS(SDSF) ID(SHERRYF) ACCESS(READ)
```

3. To protect the DA command, issue the following:

```
RDEFINE SDSF ISFCMD.DSP.ACTIVE.jessx UACC(NONE)
PERMIT ISFCMD.DSP.ACTIVE.jessx CLASS(SDSF) ID(SHERRYF) ACCESS(READ)
```

## Address spaces

### Protecting address spaces

Protect address spaces by defining resource names in the SDSF class. The resources are shown in [Table 113 on page 265](#).

Table 113. SAF Resources for Address Spaces

Action Characters and Overtypes	Resource Name	Class	Access Required
JC	ISFCMD.ODSP.CDE.sysname ISFJOB.MODULE.owner.jobname.system	SDSF	READ
JCS	ISFCMD.ODSP.GQE.system	SDSF	READ
JDCC	ISFCMD.ODSP.COUPLE.system	SDSF	READ
JDD	ISFCMD.ODSP.DEVICE.system ISFJOB.DDNAME.owner.jobname.system	SDSF	READ
JDNA	ISFCMD.ODSP.NETACT.system	SDSF	READ
JM	ISFCMD.ODSP.STORAGE.system ISFJOB.STORAGE.owner.jobname.system	SDSF	READ
JMO	ISFCMD.ODSP.STORAGE.system ISFJOB.STORAGE.owner.jobname.system	SDSF	READ
JT	ISFCMD.ODSP.TCB.system ISFJOB.TASK.owner.jobname.system	SDSF	READ
N	ISFCMD.ODSP.ENQUEUE.system	SDSF	READ

To control access to the AD panel, protect the AD command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of address spaces

To protect an address space and permit a user to control it, define a generic profile as follows:

```
RDEFINE SDSF ISFCMD.ODSP.AD.sysname UACC(NONE)
PERMIT ISFCMD.ODSP.AD.sysname CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Coupling facility (CF) connections

### Protecting CF connections

Protect CF connections by defining resource names in the SDSF class. The resources are shown in [Table 114 on page 265](#).

Table 114. SAF Resources for CF Connections

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFCFC.connectionname	SDSF	READ
DL	ISFCFC.connectionname	SDSF	READ
DS	ISFCFC.connectionname	SDSF	READ

To control access to the CFC panel, protect the CFC command. This is described in [“Authorized SDSF commands”](#) on page 261.

## Example of CF connections

To protect a CF connection and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFCFC.** UACC(NONE)
PERMIT ISFCFC.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Coupling facility (CF) data sets

### Protecting CF data sets

Protect CF data sets by defining resource names in the SDSF class. The resources are shown in [Table 115](#) on page 266.

Table 115. SAF Resources for CF Data Sets

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFCFD.function	SDSF	READ
DA	ISFCFD.function	SDSF	READ

To control access to the CFD panel, protect the CFD command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of CF data sets

To protect a CF data set and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFCFD.** UACC(NONE)
PERMIT ISFCFD.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Coupling facility (CF) structures

### Protecting CF structures

Protect CF structures by defining resource names in the SDSF class. The resources are shown in [Table 116](#) on page 266.

Table 116. SAF Resources for CF Structures

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFCFS.structurename	SDSF	READ
DL	ISFCFS.structurename	SDSF	READ

To control access to the CFS panel, protect the CFS command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of CF structures

To protect an CF structure and permit a user to control it, define a generic profile as follows:



```

REDEFINE SDSF ISFCFS.** UACC(NONE)
PERMIT ISFCFS.** CLASS(SDSF) ID(userid) ACCESS(READ)

```

## Checks on the CK and CKH panels

You can protect the checks from IBM Health Checker for z/OS that are displayed on the CK and CKH panels.

### Protecting checks

Protect checks by defining resource names in the XFACILIT class. The resources are shown in [Table 117](#) on page 267.

Table 117. Authority Required to Checks for Actions and Overtypes

Action Character or Overtypable Field	Panel	Resource Name	Class	Access
<b>A action character</b>	CK	HZS.sysname.checkowner.checkname.ACTIVATE	XFACILIT	UPDATE
<b>D action character</b>	CK	HZS.sysname.checkowner.checkname.QUERY	XFACILIT	READ
<b>E action character</b>	CK	HZS.sysname.checkowner.checkname.REFRESH	XFACILIT	CONTROL
<b>H action character</b>	CK	HZS.sysname.checkowner.checkname.DEACTIVATE	XFACILIT	UPDATE
<b>P action character</b>	CK	HZS.sysname.checkowner.checkname.DELETE	XFACILIT	CONTROL
<b>R action character</b>	CK	HZS.sysname.checkowner.checkname.RUN	XFACILIT	UPDATE
<b>S and X action characters</b>	CK, CKH	HZS.sysname.checkowner.checkname.MESSAGES	XFACILIT	READ
<b>U action character and all overtypeable fields</b>	CK	HZS.sysname.checkowner.checkname.UPDATE	XFACILIT	UPDATE

Protect access to the log stream that is used to record check history by defining a resource in the LOGSTRM class.

Table 118. Authority Required to the Log Stream Used for Check History

Action Character or Overtypable Field	Resource Name	Class	Access
<b>L action character on the CK panel</b>	<i>log-stream-name</i>	LOGSTRM	READ

To protect the MVS commands generated by action characters and overtypeable fields on the CK panel, see [“Tables of action characters”](#) on page 229 and [“Tables of overtypeable fields”](#) on page 293.

To control access to the CK and CKH panels, protect the CK command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of protecting checks

To protect all checks and permit a user to control the checks, you can define generic profiles as follows:

```

RDEFINE XFACILIT HZS.** UACC(NONE)
PERMIT HZS.** CLASS(XFACILIT) ID(userid or groupid) ACCESS(CONTROL)

```

# Destination names

You can protect destination names that are used on the DEST command and the IDEST parameter of ISFPARMS.

You can also give users operator authority by destination to jobs, output groups, and SYSIN/SYSOUT data sets without explicitly authorizing the users to the JESSPOOL resources. For more information see [“Destination operator authority” on page 269](#).

The DEST command is protected like any other SDSF authorized command; see [“Authorized SDSF commands” on page 261](#).

## Protecting destination names

You use two resources:

- ISFOPER.ANYDEST.*jesx*
- ISFAUTH.DEST.*destname*

You must define the ISFOPER.ANYDEST.*jesx* resource before defining any ISFAUTH.DEST.*destname* resources. Otherwise, unexpected authorization results may occur.

The resources are described in [Table 119 on page 268](#).

Table 119. Authority Required for Destination Names

Object	Resource Names	Class	Access
<b>Any destination name on the DEST command or IDEST list</b>	ISFOPER.ANYDEST. <i>jesx</i>	SDSF	READ
<b>Specific destination names on the DEST command or IDEST list</b>	ISFAUTH.DEST. <i>destname</i>	SDSF	READ

In the table,

*jesx*

is the name of the JES subsystem. For example, it might be JES2, JESA, or, to protect all JES2 subsystems, JES%.

*destname*

is a destination name in the standard form: ISFAUTH.DEST.Nx.Rx

## Initializing destinations

Each SDSF user should have a set of default destinations. SDSF uses these default destinations to:

- Initialize the SDSF panels
- Respond to a DEST command that is entered with no parameters

When no default destinations are defined, the user's destination filter is set to blanks or the character string ????????, and no jobs appear on the tabular SDSF panels. To establish the default destinations you can:

- Use the IDEST parameter in ISFPARMS. Refer to [“Group function parameters reference” on page 18](#) for more information.
- Give the user access to all destinations with the ISFOPER.ANYDEST.*jesx* resource.
- Give the user access to specific destinations with the ISFAUTH.DEST.*destname* resource.

If you don't define default destinations with the IDEST parameter, give the user authority to issue the DEST command. DEST allows the user to define a default set of destinations. The command only has to be entered once, as SDSF saves the values across sessions.

## Example of protecting destination names

To allow USER1 unlimited use of all destination names, define the following profile and give the user READ authority:

```
RDEFINE SDSF ISFOPER.ANYDEST.jesx UACC(NONE)
PERMIT ISFOPER.ANYDEST.jesx CLASS(SDSF) ID(USER1) ACCESS(READ)
```

Then, to restrict the use of the destination names for USER2, define profiles for a specific destination name and give that user READ authority to only that resource:

```
RDEFINE SDSF ISFAUTH.DEST.RMT1 UACC(NONE)
PERMIT ISFAUTH.DEST.RMT1 CLASS(SDSF) ID(USER2) ACCESS(READ)
```

## Destination operator authority

You can give operators access to jobs, output groups, or SYSIN/SYSOUT data sets for a particular destination, without authorizing the operators to those jobs, output groups, or SYSIN/SYSOUT data sets through the JESSPOOL class.

To provide destination operator authority you:

1. Give the user READ authority to the ISFOPER.DEST.jesx profile in the SDSF class. This identifies a user as a destination operator for the SDSF session.
2. Give the user authorization for the profiles that protect destinations for jobs, output groups, and data sets.

The ability to modify output descriptors (Address, Building and so on) on the JDS panel in a JES3 environment cannot be granted using destination operator authority. You must use the resources in the JESSPOOL class, as described in [“Jobs, job groups, output groups, and SYSIN/SYSOUT data sets”](#) on page 278.

## Protecting operator authority by destination

The resources are shown in [Table 120 on page 269](#).

Table 120. Authority Required for Destination Operator Authority

Action Characters and Overtypable Fields	Resource Name	Class	Access
//, =, +, ? or Q action characters on the DA, H, I, JDS, JO, O, and ST panels	No security checking is done.	N/A	N/A
S, X, or V action characters on the H, I, JDS, JO, O, and ST panels	ISFOPER.DEST.jesx ISFAUTH.DEST.destname.DATASET.dsname	SDSF	READ READ
S, X, or V action characters on the DA panel	ISFOPER.DEST.jesx ISFAUTH.DEST..DATASET.dsname	SDSF	READ READ
D or L action characters on the H, I, O, and ST panels	ISFOPER.DEST.jesx ISFAUTH.DEST.destname	SDSF	READ READ
D or L action characters on the DA panel	ISFOPER.DEST.jesx ISFAUTH.DEST.	SDSF	READ READ

Table 120. Authority Required for Destination Operator Authority (continued)

Action Characters and Overtypable Fields	Resource Name	Class	Access
All others on the H, I, JDS, JO, O, and ST panels	ISFOPER.DEST.jesx ISFAUTH.DEST.destname	SDSF	READ ALTER
All others on the DA panel	ISFOPER.DEST.jesx ISFAUTH.DEST.	SDSF	READ ALTER

If the user does not have authority to both of the required resources, then the user must have access to the individual job or data set defined in the JESSPOOL class.

If your installation is performing SECLABEL checking, a user must be logged on with the appropriate SECLABEL in order to access the JESSPOOL resources even if the user has operator authorization. For more information about SECLABEL checking, see *z/OS Security Server RACF Security Administrator's Guide*.

The authority level (READ or ALTER) must be the same as the authority for the JESSPOOL resources, as described in “Jobs, job groups, output groups, and SYSIN/SYSOUT data sets” on page 278.

## Device activity information

### Protecting device activity

Protect device activity by defining resource names in the SDSF class. The resources are shown in [Table 121 on page 270](#).

Table 121. SAF Resources for Device Activity

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFDEV.volser	SDSF	READ
DA	ISFDEV.volser	SDSF	READ
DI	ISFDEV.volser	SDSF	READ
DSP	ISFDEV.volser	SDSF	READ
DSQD	ISFDEV.volser	SDSF	READ
DSQP	ISFDEV.volser	SDSF	READ
DSS	ISFDEV.volser	SDSF	READ
V	ISFDEV.volser	SDSF	CONTROL
VF	ISFDEV.volser	SDSF	CONTROL

To control access to the DEV panel, protect the DEV command. This is described in “Authorized SDSF commands” on page 261.

### Example of protecting device information

To protect device information and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFDEV.** UACC(NONE)
PERMIT ISFDEV.** CLASS(SDSF) ID(userid) ACCESS(CONTROL)
```

## Dynamic exit information

### Protecting dynamic exits

Protect dynamic exits by defining resource names in the SDSF class. The resources are shown in [Table 122 on page 271](#).

Table 122. SAF Resources for Dynamic Exits

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>A</b>	ISFDYNX. <i>exitname</i>	SDSF	UPDATE
<b>D</b>	ISFDYNX. <i>exitname</i>	SDSF	READ
<b>DA</b>	ISFDYNX. <i>exitname</i>	SDSF	READ
<b>DAI</b>	ISFDYNX. <i>exitname</i>	SDSF	READ
<b>DD</b>	ISFDYNX. <i>exitname</i>	SDSF	READ
<b>DI</b>	ISFDYNX. <i>exitname</i>	SDSF	READ
<b>DNP</b>	ISFDYNX. <i>exitname</i>	SDSF	READ
<b>DP</b>	ISFDYNX. <i>exitname</i>	SDSF	READ
<b>H</b>	ISFDYNX. <i>exitname</i>	SDSF	UPDATE
<b>P</b>	ISFDYNX. <i>exitname</i>	SDSF	ALTER
<b>PF</b>	ISFDYNX. <i>exitname</i>	SDSF	ALTER
<b>U</b>	ISFDYNX. <i>exitname</i>	SDSF	ALTER

To control access to the DYNX panel, protect the DYNX command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting dynamic exits

To protect dynamic exits and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFDYNX.** UACC(NONE)
PERMIT ISFDYNX.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## EMCS consoles information

### Protecting EMCS consoles

Protect EMCS consoles by defining resource names in the SDSF class. The resources are shown in [Table 123 on page 271](#).

Table 123. SAF Resources for EMCS Consoles

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>D</b>	ISFEMCS. <i>consolename</i>	SDSF	READ
<b>DL</b>	ISFEMCS. <i>consolename</i>	SDSF	READ
<b>E</b>	ISFEMCS. <i>consolename</i>	SDSF	CONTROL

Table 123. SAF Resources for EMCS Consoles (continued)

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>P</b>	ISFEMCS.consolename	SDSF	UPDATE
<b>All others</b>	ISFEMCS.consolename	SDSF	UPDATE

To control access to the EMCS panel, protect the EMCS command. This is described in [“Authorized SDSF commands”](#) on page 261.

## Example of protecting EMCS consoles

To protect EMCS consoles and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFEMCS.** UACC(NONE)
PERMIT ISFEMCS.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Enclaves

### Protecting enclaves

Protect enclaves by defining resource names in the SDSF class. The resources are shown in [Table 124](#) on page 272.

Table 124. SAF Resources for Enclaves

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>R and RQ action characters and SrvClass overtype</b>	ISFENC.subsystem-type.subsystem-name	SDSF	ALTER

To control access to the ENC panel, protect the ENC command. This is described in [“Authorized SDSF commands”](#) on page 261.

## Example of protecting enclaves

To protect all enclaves and permit a user to control them, define a generic profile as follows:

```
RDEFINE SDSF ISFENC.** UACC(NONE)
PERMIT ISFENC.** CLASS(SDSF) ID(userid) ACCESS(ALTER)
```

## Enqueue information

### Protecting Enqueue Information

Protect enqueue information by defining resource names in the SDSF class. The resources are shown in [Table 125](#) on page 272.

Table 125. SAF Resources for Enqueue Information

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>D</b>	ISFENQ.majorname.sysname	SDSF	READ

To control access to the ENQ panel, protect the ENQ command. This is described in [“Authorized SDSF commands”](#) on page 261.

To protect the N action character to display enqueues from the DA panel, protect the ENQ command. This is described in [“Authorized SDSF commands”](#) on page 261. The N action is valid only in the interactive environment. It is not supported in REXX, Java, or the z/OSMF. You can obtain this information by invoking the ENQ panel directly and implementing logic to filter by ASID.

## Example of protecting enqueue information

To protect enqueue information and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFENQ.** UACC(NONE)
PERMIT ISFENQ.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## File system information

### Protecting file systems

Protect file systems by defining resource names in the SDSF class. The resources are shown in [Table 126 on page 273](#).

Table 126. SAF Resources for File Systems

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFFS.filesystemname	SDSF	READ
DA	ISFFS.filesystemname	SDSF	READ
DE	ISFFS.filesystemname	SDSF	READ

To control access to the FS panel, protect the FS command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of protecting file systems

To protect file systems and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFFS.** UACC(NONE)
PERMIT ISFFS.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Generic tracker events

### Protecting generic tracker events

Protect generic tracker events by defining resource names in the SDSF class. The resources are shown in [Table 127 on page 273](#).

Table 127. SAF Resources for Generic Tracker Events

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFGT.eventowner	SDSF	READ
DA	ISFGT.eventowner	SDSF	READ
DD	ISFGT.eventowner	SDSF	READ

Table 127. SAF Resources for Generic Tracker Events (continued)

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>DE</b>	ISFGT.eventowner	SDSF	READ
<b>DH</b>	ISFGT.eventowner	SDSF	READ
<b>DS</b>	ISFGT.eventowner	SDSF	READ

To control access to the GT panel, protect the GT command. This is described in [“Authorized SDSF commands”](#) on page 261.

## Example of protecting generic tracker events

To protect a generic tracker event and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFGT.** UACC(NONE)
PERMIT ISFGT.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Initiators

You can protect the initiators that are displayed on the INIT panel.

## Protecting initiators

Protect initiators by defining resource names in the SDSF class. The resources are shown in [Table 128](#) on page 274.

Table 128. Authority Required to Initiator Resource for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
<b>D action character</b>	ISFINIT.I(xx).jesx	SDSF	READ
<b>All others except the JD and JM action characters</b>	ISFINIT.I(xx).jesx	SDSF	CONTROL

In the table, *jesx* is the name of the JES subsystem the initiator is on.

To protect the MVS or JES commands generated by action characters or overtypable fields, see [“Tables of action characters”](#) on page 229 and [“Tables of overtypable fields”](#) on page 293.

No SDSF resource protects the initiator for the JD and JM action characters. Refer to [“Protecting action characters as separate resources”](#) on page 227

To control access to the INIT panel, protect the INIT command. This is described in [“Authorized SDSF commands”](#) on page 261.

## Example of protecting initiators

To protect all initiators and permit a user to control the initiators, define a generic profile as follows:

```
RDEFINE SDSF ISFINIT.** UACC(NONE)
PERMIT ISFINIT.** CLASS(SDSF) ID(userid) ACCESS(CONTROL)
```

## JES2 resources on the RM panel

You can protect the JES2 resources that are displayed on the RM panel (JES2 only).



## Protecting JES2 resources

Protect the JES2 resources by defining resource names in the SDSF class. The resources are shown in [Table 129 on page 275](#).

Table 129. Authority Required to JES2 Resources for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
D action characters	ISFRM.resource.jesx	SDSF	READ
All others	ISFRM.resource.jesx	SDSF	CONTROL

The values for *resource* are:

### BERT

block extension reuse table

### BSCB

bisynchronous buffers

### BUFX

extended logical buffers

### CKVR

checkpoint versions

### CMBS

console message buffers

### CMDS

console message buffers for command processing

### ICES

SNA interface control elements

### LBUF

logical buffers

### JNUM

job numbers

### JQES

job queue elements

### JOES

job output elements

### NHBS

NJE header/trailer buffers

### SMFB

system management facilities buffers

### TGS

spool space/track groups

### TTAB

trace tables

### VTMB

VTAM® buffers

### ZJC

JOBGROUP info CBs

To protect the MVS commands generated, see [“Tables of action characters” on page 229](#) and [“Tables of overtypable fields” on page 293](#).

To control access to the RM panel, protect the RM command. This is described in [“Authorized SDSF commands”](#) on page 261.

## Example of protecting JES2 resources

To protect all JES2 resources and permit a user to control them, you can define generic profiles as follows:

```
RDEFINE SDSF ISFRM.** UACC(NONE)
PERMIT ISFRM.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
```

## JES subsystems

You can protect the JES subsystems that are displayed on the JES panel.

### Protecting JES subsystems

Protect the JES subsystems by defining resource names in the SDSF class. The resources are shown in [Table 130 on page 276](#).

Table 130. SAF Resources for JES subsystems

Action Character or Overtypable Field	Resource Name	Class	Access
D	ISFJES.subsysname	SDSF	READ
All others	ISFJES.subsysname	SDSF	UPDATE

To control access to the JES panel, protect the JES command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of protecting JES subsystems

To protect all JES subsystems and permit a user to control them, you can define generic profiles as follows:

```
REDEFINE SDSF ISFJES.** UACC(NONE)
PERMIT ISFJES.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Job classes

You can protect the job classes that are displayed on the JC panel.

### Protecting job classes

Protect job classes by defining resource names in the SDSF class. The resources are shown in [Table 131 on page 276](#).

Table 131. Authority Required to Job Class Resource for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
D, DL, and ST action characters	ISFJOBCL.class.jesx	SDSF	READ
Overtypes	ISFJOBCL.class.jesx	SDSF	CONTROL

To protect the MVS or JES commands generated by action characters or overtypeable fields, see [“Tables of action characters”](#) on page 229 and [“Tables of overtypeable fields”](#) on page 293.

To protect the ST action character, protect the ST command. To control access to the JC panel, protect the JC command. This is described in [“Authorized SDSF commands”](#) on page 261.

## Example of protecting job classes

To protect all job classes and permit a user to control them, define a generic profile as follows:

```
RDEFINE SDSF ISFJOBCL.** UACC(NONE)
PERMIT ISFJOBCL.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
```

## Job class members

### Protecting job class members

Protect job class members by defining resource names in the SDSF class. The resources are shown in [Table 132 on page 277](#).

Table 132. SAF Resources for Job Class Members

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFJOBCL.class.jesx	SDSF	READ

To control access to the JCM panel, protect the JCM command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of protecting job class members

To protect a job class member and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFJOBCL.** UACC(NONE)
PERMIT ISFJOBCL.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Job devices

You can protect the job devices that are displayed on the Job Device panel.

### Protecting job devices

Protect devices being used by a job by defining resource names in the SDSF class. The resources are shown in [Table 133 on page 277](#).

Table 133. SAF Resources for Job Devices

Action Characters	Resource Name	Class	Access Required
D (all forms)	ISFJDD.type.sysname	SDSF	READ

In the table, *type* is the type of device: DD (DD allocation), IP (TCP/IP connection), or CF (coupling facility connection).

### Example of protecting job devices

To protect all job devices and permit a user to display them, define a generic profile as follows:

```
RDEFINE SDSF ISFJDD.** UACC(NONE)
PERMIT ISFJDD.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Jobs, job groups, output groups, and SYSIN/SYSOUT data sets

JES uses the JESSPOOL class to protect SYSIN/SYSOUT data sets and the EVENTLOG, which SDSF uses to display job step information. SDSF extends the use of the JESSPOOL class to protect SDSF job and output group resources as well.

SDSF checks a user's SAF authorization to:

- Job resources on the Display Active Users, Input Queue, and Status panels
- Job groups on the Job Group panel
- Output groups on the Held Output Queue, Job Data Set, Output Queue, and Output Descriptors panels
- SYSIN/SYSOUT data sets on the Job Data Set panel, Job 0 panel, and any other panel used for browsing with the S or V action characters and printing with the X action character
- The JES EVENTLOG data set, used for job step information on the Job Step panel.

Controlling access to the commands that display jobs, job groups and output is described in [“Authorized SDSF commands”](#) on page 261.

Protection for each type of resource can be defined separately, so that, for example, a user may be authorized to issue action characters for a job, but not be authorized to browse that job's data sets. Users can always access the JESSPOOL resources they own; they do not need additional authority to work with their own jobs and output.

### Protecting jobs, job groups, output groups, and SYSIN/SYSOUT data sets

If you don't want to make a distinction between types of resources, you can allow users access to everything with the following profile for USER1 on node N1:

```
RDEFINE JESSPOOL N1.USER1.** UACC(NONE)
```

You may also want to allow users to access all JESSPOOL resources by giving them operator authority, as described in [“Destination operator authority”](#) on page 269. Operators do not need explicit authorization to access JESSPOOL resources if they are given operator authority.

In addition, you can use the JESSPOOL class to permit users to select other user's jobs, output, and SYSIN/SYSOUT data sets for browsing, viewing and printing, as described in [“Permitting other users to view your data”](#) on page 279. Also, the JESSPOOL class can be used to provide function comparable to the notify authority provided by ISFPARMS (by specifying NOTIFY for CMDAUTH and DSPAUTH) as described in [“Providing function comparable to NOTIFY authority”](#) on page 279.

Typically, when you define SAF authority for JESSPOOL resources, you will also need to define other authority for action characters and overttypeable fields. See [Table 108 on page 229](#) and [Table 150 on page 293](#) for the resources to define them. For most action characters, a user must be authorized for jobs or output groups. However, the S, V, and X action characters require authorization only for SYSIN/SYSOUT data sets. No security checking is made for the object when the ?, JD, JM, JP, JS, JY or Q action character is used.

### Job step data

If SMF data exists for the job, SDSF attempts to use SMF records from the JES EVENTLOG data set that are protected by the *nodeid.userid.jobname.jobid.EVENTLOG.SMFSTEP* resource. If access to that resource is denied, or if no SMF data exists for the job, SDSF attempts to use records that are protected by the *nodeid.userid.jobname.jobid.EVENTLOG.STEPDATA* resource. If access to that resource is also denied, access to the JS panel is denied.

Be aware that JES only checks the resource *node.userid.jobname.jobid.EVENTLOG* (without the last qualifier). As a result, to create profiles that work for both cases, you should do one of the following:

- Create two profiles, defined as:

- `node.user.jobname.jobid.EVENTLOG`
- `node.user.jobname.jobid.EVENTLOG.*`
- Create a single profile defined as `node.user.jobname.jobid.EVENTLOG*`.

## Security label (SECLABEL) checking

If your installation is performing security label (SECLABEL) checking, a user must be logged on with the appropriate SECLABEL to access JESSPOOL resources. For more information about SECLABEL checking, see [z/OS Security Server RACF Security Administrator's Guide](#).

## Permitting other users to view your data

Users can permit others to select their jobs, output groups, and SYSIN/SYSOUT data sets using the S (browse), V (view page mode), and X (print) action characters.

When using the S, V, and X action characters, the user is not automatically authorized to access all SYSIN/SYSOUT data sets within a job or output group when the user is authorized to access the job or output group itself. Security checks are made for each data set within the job or output group to verify the user's authority to access each data set, and only those SYSIN/SYSOUT data sets to which the user has at least READ authority are displayed.

To protect all of the user's jobs, output groups, and SYSIN/SYSOUT data in the same way, use the following profile to protect resources for USER1 on node N1:

```
RDEFINE JESSPOOL N1.USER1.** UACC(NONE)
```

To just permit USER2 to browse USER1's output:

1. Define the profile:

```
RDEFINE JESSPOOL N1.USER1.*.*.D*. * UACC(NONE)
```

2. Permit USER2 to read USER1's output:

```
PERMIT N1.USER1.*.*.D*. * CLASS(JESSPOOL) ID(USER2) ACCESS(READ)
```

To provide short-term authorization, a user can overtype the DEST field with another user's user ID. This can be done on either the O or H panels.

## Providing function comparable to NOTIFY authority

**Note:** As of SDSF 2.5, the NOTIFY value of DSPAUTH and CMDAUTH is no longer used. The following discussion describes how to use RACF to implement a similar capability.

By specifying a value of NOTIFY for the DSPAUTH and CMDAUTH parameters in the ISFGRP macros or GROUP statements, you can allow a group member to display output and issue commands, respectively, for any job that has the NOTIFY parameter on its job card set to the member's user or group ID. There is no one-to-one SAF equivalent for this authorization.

However, when using RACF, the security administrator and job owner can give a user comparable authority, under the scope of the GENERICOWNER option of the SETROPTS command, through profiles that use the JESSPOOL class, and for CMDAUTH, the OPERCMDS class.

With RACF, when GENERICOWNER processing is in effect, a security administrator can assign ownership to profiles in a general resource class, so that end users can create and/or manipulate those general resource class profiles they own, while ensuring that the end users cannot interfere with profiles created by another user. (For the impact of GENERICOWNER on the CLAUTH user attribute and on the system as a whole, see [z/OS Security Server RACF Security Administrator's Guide](#)).

For an example of providing NOTIFY authority, see [“Examples of protecting jobs and output groups” on page 280](#).

## Examples of protecting jobs and output groups

1. To protect all jobs for user ID USER1 on node N1, issue the following command:

```
RDEFINE JESSPOOL N1.USER1.*.* UACC(NONE)
```

To permit USER2 to access the resource, issue the following command:

```
PERMIT N1.USER1.*.* CLASS(JESSPOOL) ID(USER2) ACCESS(ALTER)
```

2. To protect all output groups for user ID USER1 on node N1, issue the following command:

```
RDEFINE JESSPOOL N1.USER1.*.*.GROUP.* UACC(NONE)
```

Then, to permit USER2 to access this resource, issue the following command:

```
PERMIT N1.USER1.*.*.GROUP.* CLASS(JESSPOOL) ID(USER2) ACCESS(ALTER)
```

The use of the GROUP character string in the fifth qualifier of the profile name distinguishes the output group's profile from other JESSPOOL profiles.

3. To protect all SYSIN/SYSOUT data sets for jobs beginning with DPT on node N1, use the following:

```
RDEFINE JESSPOOL N1.*.DPT*.*.D*.* UACC(NONE)
PERMIT N1.*.DPT*.*.D*.* CLASS(JESSPOOL) ID(USER2) ACCESS(READ)
```

The use of the D character string in the fifth qualifier of the profile name distinguishes the data set's profile from other JESSPOOL profiles.

4. The following example shows how a security administrator can give USER1 at node N1 authority to control access to his own output via the JESSPOOL class. USER1 can then give authority to USER2 to some or all of that output. A generic refresh for USER2 on the JESSPOOL class generic profiles is required for this support to take effect.

The security administrator does the following:

- Activates the GENERICOWNER option:

```
SETROPTS GENERICOWNER
```

- Owns the least specific JESSPOOL profile:

```
RDEFINE JESSPOOL N1.** UACC(NONE) OWNER(SECADM)
RDEFINE JESSPOOL ** UACC(NONE) OWNER(SECADM)
```

- Gives USER1 the ability to create JESSPOOL profiles more specific than N1.USER1.\*\* and to control access to the jobs, output groups, and SYSIN/SYSOUT data sets governed by those profiles:

```
RDEFINE JESSPOOL N1.USER1.** UACC(NONE) OWNER(USER1)
```

The above profile, along with a generic refresh, restricts a user with JESSPOOL class authorization to create and manipulate only a small subset of profiles within the JESSPOOL class (such as N1.USER1.\*\* and any that are more specific).

The security administrator should caution the user not to delete the *nodeid.userid.\*\** profile. If deleted, the user may lose control over any more specific profiles created and the access to them.

- Gives USER1 class authorization to the JESSPOOL class:

```
ALTUSER USER1 CLAUTH(JESSPOOL)
```

- Effects a generic refresh so this support will take effect for newly created profiles, by either:

Creating an STC (started task) that will automatically refresh a specific general resource class at specified intervals of time, or

Instructing USER2, after being permitted by USER1, to log off and logon to effect the refresh. (This method will not work when the JESSPOOL class has SETROPTS RACLIST or GENLIST processing activated.)

With GENERICOWNER support in effect, USER1 can create and manipulate JESSPOOL profiles to control another user's access to his output. USER1 does this as follows:

- The profile N1.USER1.\*\* is defined by the security administrator and USER1 has the following output groups on the Held Output Queue panel:

JOBNAME	JOBID	OWNER
JOBA	JOB123	USER1
JOBB	JOB345	USER1
JOBC	JOB678	USER1

- To permit USER2 to browse only JOB123, USER1 issues the following commands:

```
RDEFINE JESSPOOL N1.USER1.JOBA.JOB123.**  
PERMIT N1.USER1.JOBA.JOB123.** CLASS(JESSPOOL) ID(USER2) ACCESS(READ)
```

- To permit USER2 to issue action characters and overtypes against JOB123, USER1 gives USER2 access of ALTER. Also, USER2 must have authority to the OPERCMDS resources for the MVS and JES commands generated, as described in [“Action characters”](#) on page 225 and [“Overtypable fields”](#) on page 290.
- For USER2's authorization to take effect, a generic refresh is required. This will be automatic if there is an STC in effect, or USER2 can log off and logon when RACLIST or GENLIST processing for the JESSPOOL class is not in effect.

## JESInfo resources

You can protect JESInfo resources that are displayed on the JRI panel.

### Protecting JESInfo resources

Protect the JESInfo resources by defining resource names in the SDSF class. The resources are shown in [Table 134 on page 281](#).

*Table 134. SAF Resources for JESInfo Resources*

Action Character or Overtypable Field	Resource Name	Class	Access
D	ISFJRI.resourcename.jesx	SDSF	READ
DL	ISFJRI.resourcename.jesx	SDSF	UPDATE

To control access to the JRI panel, protect the JRI command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of protecting JESInfo resources

To protect all JESInfo resources and permit a user to control them, you can define generic profiles as follows:

```
REDEFINE SDSF ISFJRI.** UACC(NONE)  
PERMIT ISFJRI.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## JESInfo by job resources

You can protect JESInfo by job resources that are displayed on the JRJ panel.

## Protecting JESInfo by job resources

Protect the JESInfo by job resources by defining resource names in the SDSF class. The resources are shown in [Table 135 on page 282](#).

Table 135. SAF Resources for JESInfo by Job Resources

Action Character or Overtypable Field	Resource Name	Class	Access
<b>D</b>	ISFJRJ.jobname.jobid	SDSF	READ
<b>DLI</b>	ISFJRJ.jobname.jobid	SDSF	UPDATE

To control access to the JRI panel, protect the JRI command. This is described in [“Authorized SDSF commands” on page 261](#).

## Example of protecting JESInfo by job resources

To protect all JESInfo by job resources and permit a user to control them, you can define generic profiles as follows:

```
REDEFINE SDSF ISFJRJ.** UACC(NONE)
PERMIT ISFJRJ.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Lines

You can protect the lines displayed on the LI panel.

## Protecting lines

Protect lines by defining resource names in the SDSF class. The resources are shown in [Table 136 on page 282](#).

Table 136. Authority Required to Lines Resources for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
<b>D action character</b>	ISFLINE.device-name.jesx	SDSF	READ
<b>C action character</b>	ISFLINE.device-name.jesx	SDSF	ALTER
<b>All others</b>	ISFLINE.device-name.jesx	SDSF	CONTROL

In the table,

**device-name**

is the name of the line, transmitter, or receiver.

**jesx**

is the name of the JES subsystem.

To protect the MVS and JES commands generated, see [“Tables of action characters” on page 229](#) and [“Tables of overtypeable fields” on page 293](#).

To control access to the LI panel, protect the LI command. This is described in [“Authorized SDSF commands” on page 261](#).

## Example of protecting lines

To protect all lines, issue the following commands:

```
RDEFINE SDSF ISFLINE.** UACC(NONE)
```



```
PERMIT ISFLINE.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
```

## Link list sets

### Protecting link list sets

Protect link list sets by defining resource names in the SDSF class. The resources are shown in [Table 137 on page 283](#).

Table 137. SAF Resources for Link List Sets

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFLLS.name.target-sysname	SDSF	READ
DU	ISFLLS.name.target-sysname	SDSF	READ

To control access to the LNK panel, protect the LNK command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting link list sets

To protect all link list sets and permit a user to control them, define a generic profile as follows:

```
REDEFINE SDSF ISFLLS.** UACC(NONE)
PERMIT ISFLNK.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Link list data sets

### Protecting link list data sets

Protect link list data sets by defining resource names in the SDSF class. The resources are shown in [Table 138 on page 283](#).

Table 138. SAF Resources for Link List Data Sets

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFLNK.datasetname	SDSF	READ
DN	ISFLNK.datasetname	SDSF	READ

To control access to the LLS panel, protect the LLS command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting link list data sets

To protect all link list data sets and permit a user to control them, define a generic profile as follows:

```
REDEFINE SDSF ISFLNK.** UACC(NONE)
PERMIT ISFLNK.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## MAS and JESPLEX members

You can protect the members of a JES2 MAS, displayed on the MAS panel, and the members of a JES3 JESPLEX, displayed on the JP panel.

## Protecting MAS and JESPLEX members

Protect members of a MAS or JESPLEX by defining resource names in the SDSF class. The resources are shown in [Table 139 on page 284](#).

Table 139. Authority Required to MAS or JESPLEX Members for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
<b>D, DL (JP only) and J action characters</b>	ISFMEMB. <i>member-name.jesx</i>	SDSF	READ
<b>E action character (MAS only)</b>	ISFMEMB. <i>member-name.jesx</i>	SDSF	ALTER
<b>P action character (MAS only)</b>	ISFMEMB. <i>member-name.jesx</i>	SDSF	ALTER
<b>All others</b>	ISFMEMB. <i>member-name.jesx</i>	SDSF	CONTROL

where *member-name* is a member name in a JES2 environment and main name in a JES3 environment.

Commands sent to target systems are routed using the MVS ROUTE command. This occurs when the generated command is for a system other than the one to which the user is logged on to.

To protect the MVS or JES commands generated, see [“Tables of action characters” on page 229](#) and [“Tables of overtypeable fields” on page 293](#).

To control access to the MAS and JP panels, protect the MAS and JP commands. This is described in [“Authorized SDSF commands” on page 261](#).

## Example of protecting MAS members

To protect all MAS members and permit a user to control the members, you can define generic profiles as follows:

```
RDEFINE SDSF ISFMEMB.** UACC(NONE)
PERMIT ISFMEMB.** CLASS(SDSF) ID(userid or groupid) ACCESS(ALTER)
```

## Membership in groups

You can control membership in groups defined by ISFPARMS using SAF. This is an alternative to using ISFPARMS to control membership in the groups.

## Controlling membership in groups

Define a resource in the SDSF class. The resource is shown in [Table 140 on page 284](#).

Table 140. Authority Required for membership in an ISFPARMS group

Function	Resource Name	Class	Access
<b>Membership in group</b>	GROUP. <i>group-name.server-name</i>	SDSF	READ

For more information, see [“Using SAF to control group membership” on page 17](#).

## Example of protecting membership in a group in ISFPARMS

To authorize membership in a group in ISFPARMS, issue the following commands:

```
RDEFINE SDSF GROUP.group-name.server-name UACC(NONE)
PERMIT GROUP.group-name.server-name CLASS(SDSF) ID(userid or groupid)
ACCESS(READ)
```

## Memory contents

You can protect the memory contents for address spaces within the sysplex, including common storage and 64-bit memory objects, that are displayed on the MEM panel.

### Protecting memory contents

Protect the memory contents for address spaces by defining resource names in the SDSF class. The resources are shown in [Table 141 on page 285](#).

*Table 141. Authority Required to MEM for Actions and Overtypes*

Action Character or Overtypable Field	Resource Name	Class	Access
<b>M</b>	ISFJOB.STORAGE.owner.jobname.tsy stem	SDSF	READ
<b>S</b>	ISFJOB.STORAGE.owner.jobname.tsy stem	SDSF	ALTER

To control access to the MEM panel, protect the MEM command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting memory contents

To protect all memory contents and permit a user to control the members, you can define generic profiles as follows:

```
REDEFINE SDSF .** UACC(NONE)
PERMIT ISFJOB.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## MVS and JES commands on the command line

You can control a user's authority to use the SDSF slash (/) command to issue MVS or JES commands from SDSF. SAF checks the user's authority to use the slash command, but does not check the MVS or JES command or the object of the command. MVS and JES command authorization to the OPERCMDS class is done by MVS and JES only after SDSF authorizes use of the slash command.

You should control use of the slash command as you would a console with master authority.

The character for the slash command can be changed from the default, /, to some other character with a custom property in ISFPARMS. For more information, refer to [“Customized properties \(PROPLIST\)” on page 54](#).

For more information on the console used by SDSF to issue the command, see [“Issuing MVS and JES commands” on page 356](#). For more information on protecting the console, see [z/OS MVS Planning: Operations](#).

### Protecting the slash command

Protect the slash command by defining a resource name in the SDSF class. The resource is shown in [Table 142 on page 285](#).

*Table 142. Authority Required for the Slash Command*

Command	Resource Name	Class	Access
<b>Slash (/)</b>	ISFOPER.SYSTEM	SDSF	READ

**Note:** The WHEN (CONSOLE (SDSF) ) clause for conditional access checking does not apply to commands issued from the command line.

The character for the slash command can be changed from the default, /, to some other character with a custom property in ISFPARMS. For more information, refer to [“Customized properties \(PROPLIST\)”](#) on page 54.

For more information on the console used by SDSF to issue the command, see [“Issuing MVS and JES commands”](#) on page 356. For more information on protecting the console, see [z/OS MVS Planning: Operations](#).

## Slash command and User Log

The slash command can return a response to the user terminal and write a response to the User Log (ULOG). To have the response sent back to the user's terminal, the user needs authorization to the ULOG command and to the extended console. See [“User log \(ULOG\)”](#) on page 345 for information.

## Example of protecting the slash command

To authorize use of the slash command, issue the following commands:

```
RDEFINE SDSF ISFOPER.SYSTEM UACC(NONE)
PERMIT ISFOPER.SYSTEM CLASS(SDSF) ID(userid or groupid) ACCESS(READ)
```

## Network activity

### Protecting network activity

Protect network activity by defining resource names in the SDSF class. The resources are shown in [Table 143 on page 286](#).

Table 143. SAF Resources for Network Activity

Action Characters and Overtypes	Resource Name	Class	Access Required
DA	ISFNETACT.jobname	SDSF	READ
DAL	ISFNETACT.jobname	SDSF	READ
DB	ISFNETACT.jobname	SDSF	READ
DBL	ISFNETACT.jobname	SDSF	READ
DN	ISFNETACT.jobname	SDSF	READ
DNL	ISFNETACT.jobname	SDSF	READ
DR	ISFNETACT.jobname	SDSF	READ
DRD	ISFNETACT.jobname	SDSF	READ
DRDL	ISFNETACT.jobname	SDSF	READ
DRL	ISFNETACT.jobname	SDSF	READ

To control access to the NA panel, protect the NA command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of protecting network activity

To protect a network activity and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFNETACT.** UACC(NONE)
PERMIT ISFNETACT.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Network connections

You can protect the network connections displayed on the NC panel.

### Protecting network connections

Protect network connections by defining resource names in the SDSF class. The resources are shown in [Table 144 on page 287](#).

Table 144. Authority Required to Network Connection Resources for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
<b>D action character</b>	ISFAPPL. <i>device-name.jesx</i> (APPLs)	SDSF	READ
	ISFSOCK. <i>device-name.jesx</i> (sockets)		
	ISFLINE. <i>device-name.jesx</i> (lines, transmitters or receivers)		
<b>All others</b>	ISFAPPL. <i>device-name.jesx</i>	SDSF	CONTROL
	ISFSOCK. <i>device-name.jesx</i>		
	ISFLINE. <i>device-name.jesx</i>		

In the table,

***device-name***

is the name of the device.

***jesx***

is the name of the JES subsystem.

To protect the JES commands generated, see [“Tables of action characters” on page 229](#) and [“Tables of overtypable fields” on page 293](#).

To control access to the NC panel, protect the NC command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting network connections

To protect all network connections, issue the following commands:

```
RDEFINE SDSF ISFNC.** UACC(NONE)
PERMIT ISFAPPL.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
PERMIT ISFSOCK.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
PERMIT ISFLINE.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
```

## Network servers

You can protect the network servers displayed on the NS panel.

### Protecting network servers

Protect network servers by defining resource names in the SDSF class. The resources are shown in [Table 145 on page 288](#).

Table 145. Authority Required to Network Servers Resources for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
<b>D action character</b>	ISFNS. <i>device-name.jesx</i>	SDSF	READ
<b>All others except the JD and JM action characters</b>	ISFNS. <i>device-name.jesx</i>	SDSF	CONTROL

In the table,

***device-name***

is the name of the device.

***jesx***

is the name of the JES subsystem.

To protect the MVS and JES commands generated, see [“Tables of action characters” on page 229](#) and [“Tables of overtypeable fields” on page 293](#).

No SDSF resource protects the network server for the JD and JM action characters. Refer to [“Protecting action characters as separate resources” on page 227](#)

To control access to the NS panel, protect the NS command. This is described in [“Authorized SDSF commands” on page 261](#).

## Example of protecting network servers

To protect all network servers, issue the following commands:

```
RDEFINE SDSF ISFNS.** UACC(NONE)
PERMIT ISFNS.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
```

## Nodes

You can protect the nodes displayed on the NO panel.

## Protecting nodes

Protect nodes by defining resource names in the SDSF class. The resources are shown in [Table 146 on page 288](#).

Table 146. Authority Required to Nodes Resources for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
<b>D action character</b>	ISFNODE. <i>node-name.jesx</i>	SDSF	READ
<b>All others</b>	ISFNODE. <i>node-name.jesx</i>	SDSF	CONTROL

In the table,

***node-name***

is the name of the node.

***jesx***

is the name of the JES subsystem.

To protect the MVS and JES commands generated, see [“Tables of action characters” on page 229](#) and [“Tables of overtypeable fields” on page 293](#).

To control access to the NO panel, protect the NO command. This is described in [“Authorized SDSF commands” on page 261](#).

## Example of protecting nodes

To protect all nodes, issue the following commands:

```
RDEFINE SDSF ISFNODE.** UACC(NONE)
PERMIT ISFNODE.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
```

## OMVS options

### Protecting OMVS options

Protect OMVS options by defining resource names in the SDSF class. The resources are shown in [Table 147 on page 289](#).

Table 147. SAF Resources for OMVS Options

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFOMVS.option-name	SDSF	READ

To control access to the OMVS panel, protect the OMVS command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting OMVS options

To protect OMVS options and permit a user to control them, define a generic profile as follows:

```
REDEFINE SDSF ISFOMVS.** UACC(NONE)
PERMIT ISFOMVS.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## OPERLOG

The OPERLOG is a merged, sysplex-wide system message log. It is provided by a log stream, which is a collection of log data used by the MVS System Logger.

You protect the OPERLOG panel by controlling:

- Access to the LOG command, which displays the log panel. This is explained in [“Authorized SDSF commands” on page 261](#).
- Authorization to the log stream used for OPERLOG. The system logger, rather than SDSF, issues a SAF call to ensure the authorization.

Parameters of the LOG command allow users to choose the SYSLOG rather than the OPERLOG. For information on protecting the SYSLOG, see [“SYSLOG” on page 342](#).

### Protecting the log stream

Protect the log stream user for OPERLOG by defining a resource name in the LOGSTRM class. The resource is shown in [Table 148 on page 289](#).

Table 148. Authority Required for Accessing the Log Stream

Function	Resource Name	Class	Access
Access to the log stream	SYSPLEX.OPERLOG	LOGSTRM	READ

## Overtimeable fields

---

Use of an overtimeable field causes an interaction with three resources, all of which must be protected:

- The overtimeable field
- The object of the overtimeable field, such as an initiator, printer, MAS member, or job
- The MVS or JES command generated by overtyping the field

Protecting overtimeable fields is the same whether they are overtyped in the table or from the command line.

### Protecting the overtimeable field

The resource names for the overtimeable fields are in the SDSF class or GSDSF class and have a high level qualifier of ISFATTR. A user must have UPDATE authority to the ISFATTR resource to overtype a field. The fields and their resource names are shown in [“Tables of overtimeable fields” on page 293](#).

If the user is not authorized to overtype the field, the field is displayed on the panel but is not overtimeable. (The ISFFLD macros or the FLD statements of ISFPARMS can be used to control whether a field is displayed.)

### Protecting the objects of overtimeable fields

The objects of the overtimeable fields are such things as jobs, output groups, initiators, MAS members, nodes, printers, and so on. For information about protecting the objects see:

- [“Checks on the CK and CKH panels” on page 267](#)
- [“Destination operator authority” on page 269](#)
- [“Enclaves” on page 272](#)
- [“Initiators” on page 274](#)
- [“JES2 resources on the RM panel” on page 274](#)
- [“Job classes” on page 276](#)
- [“Jobs, job groups, output groups, and SYSIN/SYSOUT data sets” on page 278](#)
- [“Lines” on page 282](#)
- [“MAS and JESPLEX members” on page 283](#)
- [“Network connections” on page 287](#)
- [“Network servers” on page 287](#)
- [“Nodes” on page 288](#)
- [“Printers” on page 333](#)
- [“Processes \(z/OS UNIX System Services\)” on page 334](#)
- [“Proclibs” on page 335](#)
- [“Punches” on page 335](#)
- [“Readers” on page 336](#)
- [“Resources defined to WLM” on page 337](#)
- [“Scheduling environments” on page 338](#)
- [“Spool offloaders” on page 340](#)
- [“Spool volumes” on page 341](#)
- [“System requests” on page 345](#)



## Protecting the generated MVS and JES commands

Overtyping fields generates MVS and JES commands. The resource names that protect these commands are in the OPERCMDS class and are shown in [“Tables of overtypeable fields” on page 293](#). The tables also contain the access levels required.

### Permitting access only while using SDSF

Users can be conditionally permitted to access OPERCMDS resources so they are authorized to use MVS and JES commands only while they are using SDSF. See [“Using conditional access” on page 222](#) for more information.

## Generic profiles

You can set up a generic profile in the SDSF class to allow access to all overtypeable fields. To protect resources individually in the SDSF class with more restrictive profiles, use the specific resource name associated with the overtypeable field. [Table 150 on page 293](#) contains these resource names.

Generic profiles in the SDSF class that protect different types of overtypeable fields are shown in [Table 149 on page 291](#). For the generic profiles in the OPERCMDS class, use [Table 152 on page 316](#).

*Table 149. Generic Profiles for Overtypeable Fields*

Generic Profile	Protects
ISFATTR.**	All
ISFATTR.INIT.**	JES3 initiators
ISFATTR.JOB.**	DA, I, ST (jobs)
ISFATTR.JOBGROUPS.**	JG
ISFATTR.OUTPUT.**	JDS (job data sets), J0 (JES3 job 0), H and O (output groups)
ISFATTR.OUTDESC.**	JDS (job data sets), J0 (JES3 job 0)
ISFATTR.CHECK.**	CK (checks)
ISFATTR.CKPT.**	CKPT
ISFATTR.EMCS.**	EMCS
ISFATTR.ENCLAVE.**	ENC (enclaves)
ISFATTR.JOBCL.**	JC (job classes)
ISFATTR.LINE.**	LI (lines), NC (network connections)
ISFATTR.LOGON.**	NS (network servers)
ISFATTR.MEMBER.**	MAS (members of the MAS), JP (members of the JESPLEX)
ISFATTR.MODIFY.**	SO (spool offloaders)
ISFATTR.NETOPTS.**	NC, NS
ISFATTR.NODE.**	NO (nodes), NC
ISFATTR.OFFLOAD.**	SO (spool offloaders)
ISFATTR.OMVS.**	OMVS
ISFATTR.PROPTS.**	LI, NC, NS, PR (printers), PUN (punches)
ISFATTR.RDR.**	RDR (readers)
ISFATTR.RESMON.**	RM (JES2 resources)

Table 149. Generic Profiles for Overtypable Fields (continued)

Generic Profile	Protects
<b>ISFATTR.RESOURCE.**</b>	RES (WLM resources)
<b>ISFATTR.SELECT.**</b>	INIT, LI, NC, NS, PR, PUN, SO (selection criteria for devices)
<b>ISFATTR.SPOOL.**</b>	SP (spool volumes)

## Examples of protecting overtypable fields

In the following examples, *jesx* is the name of the JES2 or JES3 subsystem. For example, it might be *JES2*, *JESA*, or to protect all JES2 subsystems, *JES%*.

1. To protect all overtypable fields, the objects of the overtypable fields, and the commands they generate, define the following profiles:

```
RDEFINE SDSF ISFAPPL.** UACC(NONE)
RDEFINE SDSF ISFATTR.** UACC(NONE)
RDEFINE SDSF ISFDISP.** UACC(NONE)
RDEFINE SDSF ISFINIT.** UACC(NONE)
RDEFINE SDSF ISFENC.** UACC(NONE)
RDEFINE SDSF ISFJDD.** UACC(NONE)
RDEFINE SDSF ISFJOBCL.** UACC(NONE)
RDEFINE SDSF ISFLINE.** UACC(NONE)
RDEFINE SDSF ISFNS.** UACC(NONE)
RDEFINE SDSF ISFNODE.** UACC(NONE)
RDEFINE SDSF ISFMEMB.** UACC(NONE)
RDEFINE SDSF ISFRDR.** UACC(NONE)
RDEFINE SDSF ISFRM.** UACC(NONE)
RDEFINE SDSF ISFRES.** UACC(NONE)
RDEFINE SDSF ISFSO.** UACC(NONE)
RDEFINE SDSF ISFSOCK.** UACC(NONE)
RDEFINE SDSF ISFSP.** UACC(NONE)
RDEFINE WRITER jesx.** UACC(NONE)
RDEFINE JESSPOOL ** UACC(NONE)
RDEFINE OPERCMDS jesx.CALL.** UACC(NONE)
RDEFINE OPERCMDS jesx.MODIFY.** UACC(NONE)
RDEFINE OPERCMDS jesx.RESTART.** UACC(NONE)
RDEFINE OPERCMDS jesx.ROUTE.** UACC(NONE)
RDEFINE OPERCMDS jesx.START.** UACC(NONE)
RDEFINE OPERCMDS MVS.DISPLAY.** UACC(NONE)
RDEFINE OPERCMDS MVS.MODIFY.** UACC(NONE)
RDEFINE OPERCMDS MVS.RESET UACC(NONE)
RDEFINE XFACILIT HZS.** UACC(NONE)
```

2. To restrict the use of the overtypable fields for all output groups on the Held Output Queue and Output Queue panels, define the more restrictive profiles:

```
RDEFINE SDSF ISFATTR.OUTPUT.** UACC(NONE)
RDEFINE JESSPOOL *.*.*.GROUP.* UACC(NONE)
RDEFINE OPERCMDS jesx.MODIFY.BATOUT UACC(NONE)
RDEFINE OPERCMDS jesx.MODIFY.STCOUT UACC(NONE)
RDEFINE OPERCMDS jesx.MODIFY.TSUOUT UACC(NONE)
```

3. To further restrict the use to only the DEST field on the Held Output Queue and Output Queue panels, define the more restrictive profiles:

```

RDEFINE SDSF ISFATTR.OUTPUT.DEST UACC(NONE)
RDEFINE JESSPOOL *.*.*.*.GROUP.* UACC(NONE)
RDEFINE OPERCMDS jesx.MODIFY.BATOUT UACC(NONE)
RDEFINE OPERCMDS jesx.MODIFY.STCOUT UACC(NONE)
RDEFINE OPERCMDS jesx.MODIFY.TSUOUT UACC(NONE)

```

## Tables of overtypeable fields

The following tables describe the SDSF classes and resource names for each overtypeable field and the panels on which they are valid. The table shows the command that is issued, and the associated OPERCMDS resource, for the JES2 environment for each overtypeable field; if the field is overtypeable in the JES3 environment, the JES3 command and associated OPERCMDS resource are shown beneath the JES2 values.

For an alphabetical list by field name, see [Table 150 on page 293](#).

For an alphabetical list by OPERCMDS resource name, see [Table 152 on page 316](#).

Appendix B, “SDSF resource names for SAF security,” on page 503 contains a table of all overtypeable fields.

<p><i>Table 150. Overtypeable Fields.</i></p> <p>The variable <i>jesx</i> should be replaced by the name of the targeted JES subsystem.</p> <p>When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.</p> <p>Replace <i>hcproc</i> and <i>hcstcid</i> with the IBM Health Checker for z/OS procedure name and started task ID.</p> <p>When an overtypable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).</p>					
Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>System</b>	RES	ISFATTR.RESOURCE.system	F	MVS.MODIFY.WLM	UPDATE
<b>ACCT</b>	JC	ISFATTR.JOBCL.ACCT	\$T	<i>jesx</i> .MODIFY.JOBCLASS	CONTROL
<b>ACTIVE</b>	JC	ISFATTR.JOBCL.ACTIVE	\$T	<i>jesx</i> .MODIFY.JOBCLASS	CONTROL
<b>ADDRESS</b>	JDS	ISFATTR.OUTDESC.ADDRESS	SSI		
			SSI		
<b>ADISC</b>	LI	ISFATTR.LINE.AUTODISC	\$T	<i>jesx</i> .MODIFY.LINE	CONTROL
			-	-	-
<b>AFPPARMS</b>	JDS	ISFATTR.OUTDESC.AFPPARMS	SSI		
			SSI		
<b>ALLOC</b>	INIT	ISFATTR.INIT.ALLOC	-	-	-
			*F	<i>jesx</i> .MODIFY.G	UPDATE
<b>ANODE</b>	NC	ISFATTR.NETOPTS.NODE	\$T	<i>jesx</i> .MODIFY.APPL <i>jesx</i> .MODIFY.SOCKET <i>jesx</i> .MODIFY.LINE	CONTROL
			-	-	-
<b>AFPSTATS</b>	JDS	ISFATTR.OUTDESC.AFPSTATS	SSI		
			SSI		
<b>APPL</b>	NS	ISFATTR.NETOPTS.APPL	\$T	<i>jesx</i> .MODIFY.LOGON	CONTROL
			-	-	-

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>APPLID</b>	LI	ISFATTR.LINE.APPLID	\$S	jesx.START.NET	CONTROL
			-	-	-
<b>ARCHIVE</b>	SO	ISFATTR.OFFLOAD.ARCHIVE	\$T	jesx.MODIFY.OFFLOAD	CONTROL
<b>ASIS</b>	PR	ISFATTR.PROPTS.ASIS	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>AUTH</b>	JC	ISFATTR.JOBCL.AUTH	\$T	jesx.MODIFY.JOBCLASS	CONTROL
<b>AUTH</b>	EMCS	ISFATTR.EMCS.AUTH	V CN(), AUTH=	MVS.VARY.CN	UPDATE
<b>AUTHORITY</b>	RDR	ISFATTR.RDR.AUTHORITY	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>AUTHORITY</b>	NO	ISFATTR.NODE.AUTHORITY	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>B</b>	PR PUN	ISFATTR.PROPTS.BPAGE	-	-	-
			See note 3.		
<b>BARRIER</b>	INIT	ISFATTR.INIT.BARRIER	-	-	-
			*F	jesx.MODIFY.G	UPDATE
<b>BLP</b>	JC	ISFATTR.JOBCL.BLP	\$T	jesx.MODIFY.JOBCLASS	CONTROL
<b>BUILDING</b>	JDS	ISFATTR.OUTDESC.BLDG	SSI		
			SSI		
<b>BURST</b>	H O	ISFATTR.OUTPUT.BURST	\$TO	jesx.MODIFY.BATOUT jesx.MODIFY.STCOUT jesx.MODIFY.TSUOUT	UPDATE
<b>BURST</b>	JDS J0	ISFATTR.OUTPUT.BURST	-	-	-
			*F	jesx.MODIFY.U	UPDATE
<b>C</b>	H O	ISFATTR.OUTPUT.CLASS	\$TO <sup>1</sup>	jesx.MODIFY.BATOUT jesx.MODIFY.STCOUT jesx.MODIFY.TSUOUT	UPDATE
<b>C</b>	JDS J0	ISFATTR.OUTPUT.CLASS	SSI <sup>1</sup>		
			*F	jesx.MODIFY.U	UPDATE
<b>C</b>	I ST	ISFATTR.JOB.CLASS	\$T	jesx.MODIFY.BAT jesx.MODIFY.STC jesx.MODIFY.TSU	UPDATE
			*F J	jesx.MODIFY.JOB	UPDATE
<b>C</b>	RDR	ISFATTR.RDR.CLASS	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>CC</b>	JDS J0	ISFATTR.OUTPUT.COPYCNT	SSI		
			*F	jesx.MODIFY.U	UPDATE
<b>CATEGORY</b>	CK	ISFATTR.CHECK.CATEGORY	F	MVS.MODIFY.STC. hcproc.hcstcid	UPDATE
<b>CB</b>	PR	ISFATTR.PROPTS.CB	-	-	-
			*S, *X	See note 3.	
<b>CCTL</b>	PR PUN	ISFATTR.PROPTS.CCTL	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>CHARS</b>	JDS J0	ISFATTR.OUTPUT.CHARS	-	-	-
			*F	jesx.MODIFY.U	UPDATE
<b>CHAR1-4</b>	PR	ISFATTR.PROPTS.CHAR	\$T	jesx.MODIFY.DEV	UPDATE
<b>CHAR1</b>			See note 3.		
<b>CKPTHOLD</b>	MAS	ISFATTR.MEMBER.CKPTHOLD	\$T	jesx.MODIFY.MASDEF	CONTROL
<b>CKPTLINE</b>	PR	ISFATTR.PROPTS.CKPTLINE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>CKPTLINE</b>	PUN	ISFATTR.PROPTS.CKPTLINE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>CKPTMODE</b>	PR	ISFATTR.PROPTS.CKPTMODE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>CKPTPAGE</b>	PR	ISFATTR.PROPTS.CKPTPAGE	\$T	jesx.MODIFY.DEV	UPDATE
			See note 3.		
<b>CKPTPAGE</b>	PUN	ISFATTR.PROPTS.CKPTPAGE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>CKPTSEC</b>	PR	ISFATTR.PROPTS.CKPTSEC	\$T	jesx.MODIFY.DEV	UPDATE
			See note 3.		
<b>CLASSES</b>	INIT	ISFATTR.SELECT.JOBCLASS	\$T	jesx.MODIFY.INITIATOR	CONTROL
			-	-	-
<b>CLASS1-8</b>	INIT	ISFATTR.SELECT.JOBCLASS	\$T	jesx.MODIFY.INITIATOR	CONTROL
			-	-	-
<b>CMPCT</b>	PR PUN	ISFATTR.PROPTS.CMPCT	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>CODE</b>	LI	ISFATTR.LINE.CODE	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>COLORMAP</b>	JDS	ISFATTR.OUTDESC.COLORMAP	SSI		
			SSI		
<b>COMMAND</b>	JC	ISFATTR.JOBCL.COMMAND	\$T	jesx.MODIFY.JOBCLASS	CONTROL
<b>COMP</b>	LI	ISFATTR.LINE.COMPRESS	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>COMP</b>	PR PUN	ISFATTR.PROPTS.COMPRESS	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>COMPACT</b>	NC	ISFATTR.NODE.COMPACT	\$T	jesx.MODIFY.APPL	CONTROL
			-	-	-
<b>COMPACT</b>	PR PUN	ISFATTR.PROPTS.COMPACT	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>COMSETUP</b>	JDS	ISFATTR.OUTDESC.COMSETUP	SSI		
			SSI		
<b>CONNECT</b>	LI	ISFATTR.NETOPTS.CONNECT	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>CONNECT</b>	NC	ISFATTR.NETOPTS.CONNECT	\$T	jesx.MODIFY.APPL jesx.MODIFY.SOCKET jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>CONNECT</b>	NO	ISFATTR.NETOPTS.CONNECT	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>CONN-INT</b>	LI	ISFATTR.NETOPTS.CTIME	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>CONN-INT</b>	NC	ISFATTR.NETOPTS.CTIME	\$T	jesx.MODIFY.APPL jesx.MODIFY.SOCKET jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>CONN-INT</b>	NO	ISFATTR.NETOPTS.CTIME	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>COPIES</b>	PR PUN	ISFATTR.PROPTS.COPIES	-	-	-
			See note 3.		

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDs Resource, JES2	Required Access
			Command, JES3	OPERCMDs Resource, JES3	
COPYMARK	PR	ISFATTR.PROPTS.COPYMARK	\$T	jesx.MODIFY.DEV	UPDATE
			See note 3.		
CP	NO	ISFATTR.NODE.COMPACT	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
CPR	JC	ISFATTR.JOBCL.CONDPURG	\$T	jesx.MODIFY.JOBCLASS	CONTROL
CPY	JC	ISFATTR.JOBCL.COPY	\$T	jesx.MODIFY.JOBCLASS	CONTROL
CPYMOD	JDS	ISFATTR.OUTPUT.COPYMOD	-	-	-
			*F	jesx.MODIFY.U	UPDATE
CPYMOD	JO PR	ISFATTR.PROPTS.COPYMOD	\$T	jesx.MODIFY.DEV	UPDATE
			*S	jesx.START.DEV.device	
CRTIME	SO	ISFATTR.OFFLOAD.CRTIME	\$T	jesx.MODIFY.OFFLOAD	CONTROL
CTR	LI	ISFATTR.PROPTS.CTRACE	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
CTR	NC	ISFATTR.PROPTS.CTRACE	\$T	jesx.MODIFY.LINE	CONTROL
			*F	jesx.MODIFY.SOCKET	UPDATE
CTR	NS	ISFATTR.PROPTS.CTRACE	\$T	jesx.MODIFY.NETSRV	CONTROL
			*F	jesx.MODIFY.NETSERV	
DEBUG	CK	ISFATTR.CHECK.DEBUG	F	MVS.MODIFY.STC. hcproc.hcstcid	UPDATE
DEFPCOUNT	INIT	ISFATTR.INIT.DEFCNT	-	-	-
			*F	jesx.MODIFY.G	UPDATE
DEPARTMENT	JDS	ISFATTR.OUTDESC.DEPT	SSI		
			SSI		
DEST	H O	ISFATTR.OUTPUT.DEST	\$TOF <sup>1</sup>	jesx.MODIFY.BATOUT jesx.MODIFY.STCOUT jesx.MODIFY.TSUOUT	UPDATE
			-	-	-
DEST	JDS JO	ISFATTR.OUTPUT.DEST	SSI <sup>1</sup>		
			*F	jesx.MODIFY.U	UPDATE
DEST (secondary JES2)	H	ISFATTR.OUTPUT.DEST	\$O	jesx.RELEASE.BATOUT jesx.RELEASE.STCOUT jesx.RELEASE.TSUOUT	UPDATE
			-	-	-

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>DFCB</b>	PR	ISFATTR.PROPTS.DEVFCB	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>DGRPY</b>	PR PUN	ISFATTR.PROPTS.DGRPY	-	-	-
			*F	jesx.MODIFY.W	UPDATE
<b>DIRECT</b>	NO	SFATTR.NODE.DIRECT	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>DORMANCY</b>	MAS	ISFATTR.MEMBER.DORMANCY	\$T	jesx.MODIFY.MASDEF	CONTROL
<b>DSENQSHR</b>	JC	ISFATTR.JOBCL.DSENQSHR	\$T	jesx.MODIFY.JOBCLASS	CONTROL
			-	-	-
<b>DSNAME</b>	SO	ISFATTR.OFFLOAD.DATASET	\$T	jesx.MODIFY.OFFLOAD	CONTROL
<b>DUPLEX</b>	LI	ISFATTR.LINE.DUPLEX	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>DYN</b>	PR PUN	ISFATTR.PROPTS.DYN	-	-	-
			*F	jesx.MODIFY.W	UPDATE
<b>EINTERVAL</b>	CK	ISFATTR.CHECK.EINTERVAL	F	MVS.MODIFY.STC. hcproc.hcstcid	UPDATE
<b>END</b>	NO	ISFATTR.NODE.ENDNODE	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>EXECNODE</b>	I ST	ISFATTR.JOB.EXECNODE	\$R	jesx.ROUTE.JOBOUT	UPDATE
			-	-	-
<b>FCB</b>	H O	ISFATTR.OUTPUT.FCB	\$TO	jesx.MODIFY.BATOUT jesx.MODIFY.STCOUT jesx.MODIFY.TSUOUT	UPDATE
			-	-	-
<b>FCB</b>	JDS JO	ISFATTR.OUTPUT.FCB	-	-	-
			*F U	jesx.MODIFY.U	UPDATE
<b>FCBL</b>	PR	ISFATTR.PROPTS.FCBL	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>FLASH</b>	H O	ISFATTR.OUTPUT.FLASH	\$TO	jesx.MODIFY.BATOUT jesx.MODIFY.STCOUT jesx.MODIFY.TSUOUT	UPDATE
			-	-	-



Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
FLASH	JDS J0	ISFATTR.OUTPUT.FLASH	-	-	-
			*F	jesx.MODIFY.U	UPDATE
FLS	PUN	ISFATTR.PROPTS.FLUSH	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
FORMDEF	JDS	ISFATTR.OUTDESC.FORMDEF	SSI		
			SSI		
FORMLEN	JDS	ISFATTR.OUTDESC.FORMLEN	SSI		
			SSI		
FORMS	H O	ISFATTR.OUTPUT.FORMS	\$TO	jesx.MODIFY.BATOUT jesx.MODIFY.STCOUT jesx.MODIFY.TSUOUT	UPDATE
			-	-	-
FORMS	JDS J0	ISFATTR.OUTPUT.FORMS	SSI		
			*F U	jesx.MODIFY.U	UPDATE
FSATRACE	PR	ISFATTR.PROPTS.FSATRACE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
FSSNAME	PR	ISFATTR.PROPTS.FSSNAME	F	jesx.MODIFY.DEV	UPDATE
			-	-	-
GDGBIAS	JC	ISFATTR.JOBCL.GDGBIAS	\$TJOBCLASS, GDGBIAS=	jesx.MODIFY.JOBCLASS	CONTROL
GROUP	INIT	ISFATTR.INIT.GROUP	-	-	-
			*F	jesx.MODIFY.C	UPDATE
GROUP	JC	ISFATTR.JOBCL.GROUP	\$T	jesx.MODIFY.JOBCLASS	CONTROL
HOLD	JC	ISFATTR.JOBCL.HOLD	\$T	jesx.MODIFY.JOBCLASS	CONTROL
HOLD	RDR	ISFATTR.RDR.HOLD	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
HONORTRC	PR	ISFATTR.PROPTS.HONORTRC	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
INTERVAL	CK	ISFATTR.CHECK.INTERVAL	F	MVS.MODIFY.STC. hcproc.hcstcid	UPDATE
INTF	LI	ISFATTR.LINE.INTERFACE	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
INTIDS	EMCS	ISFATTR.EMCS.INTIDS	V CN(), INTIDS=	MVS.VARY.CN	UPDATE

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
IPDEST	JDS	ISFATTR.OUTDESC.IPDEST	SSI		
			SSI		
IPNAME	NC	ISFATTR.NETOPTS.IPNAME	\$T	jesx.MODIFY.SOCKET	CONTROL
			*F	jesx.MODIFY.SOCKET	UPDATE
IPNAME	NS	ISFATTR.NETOPTS.IPNAME	\$T	jesx.MODIFY.SOCKET	CONTROL
			*F	jesx.MODIFY.NETSERV	UPDATE
ITY	JDS	ISFATTR.OUTDESC.INTRAY	SSI		
			SSI		
JCLIM	JC	ISFATTR.JOBCL.JCLIM	\$T	jesx.MODIFY.JOBCLASS	CONTROL
JESLOG	JC	ISFATTR.JOBCL.JESLOG	\$T	jesx.MODIFY.JOBCLASS	CONTROL
			*F	jesx.MODIFY.C	UPDATE
JOBRC	JC	ISFATTR.JOBCL.JOBRC	\$T	jesx.MODIFY.JOBCLASS	CONTROL
			-	-	-
JRNL	JC	ISFATTR.JOBCL.JOURNAL	\$T	jesx.MODIFY.JOBCLASS	CONTROL
JRNUM	LI	ISFATTR.LINE.JRNUM	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
JRNUM	NO	ISFATTR.NODE.JRNUM	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
JTNUM	LI	ISFATTR.LINE.JTNUM	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
JTNUM	NO	ISFATTR.NODE.JTNUM	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
JTR	LI	ISFATTR.PROPTS.JTRACE	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
JTR	NC	ISFATTR.PROPTS.JTRACE	\$T	jesx.MODIFY.LINE	CONTROL
			*F	jesx.MODIFY.SOCKET	UPDATE
JTR	NS	ISFATTR.PROPTS.JTRACE	\$T	jesx.MODIFY.NETSRV	CONTROL
			*F	jesx.MODIFY.NETSERV	UPDATE
K	PR	ISFATTR.PROPTS.SPACE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
LABEL	SO	ISFATTR.OFFLOAD.LABEL	\$T	jesx.MODIFY.OFFLOAD	CONTROL
LIMIT	RM	ISFATTR.RESMON.LIMIT	\$T	jesx.MODIFY.resource <sup>2</sup>	CONTROL

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
LINE	NC	ISFATTR.NODE.LINE	\$T	jesx.MODIFY.APPL jesx.MODIFY.SOCKET	CONTROL
			-	-	-
LINE	NO	ISFATTR.NODE.LINE	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
LINECCHR	LI	ISFATTR.LINE.LINECCHR	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
LINE-LIMIT	LI NC	ISFATTR.SELECT.LIM	\$T	jesx.MODIFY.L	CONTROL
			-	-	-
LINE-LIMIT	PR	ISFATTR.SELECT.LIM	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
LINE-LIMIT	PUN	ISFATTR.SELECT.LIM	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
LINE-LIMIT	SO	ISFATTR.SELECT.LIM	\$T	jesx.MODIFY.OFF	CONTROL
			-	-	-
LINE-LIM-HI	PR PUN	ISFATTR.SELECT.LIM	-	-	-
			See note 3.		
LINE-LIM-LOW	PR PUN	ISFATTR.SELECT.LIM	-	-	-
			See note 3.		
LOG	LI	ISFATTR.LINE.LOG	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
LOG	JC	ISFATTR.JOBCL.JLOG	\$T	jesx.MODIFY.JOBCLASS	CONTROL
			*F	jesx.MODIFY.C	UPDATE
LOG	NS	ISFATTR.NETOPTS.LOG	\$T	jesx.MODIFY.LOGON	CONTROL
			-	-	-
LOGMODE	NC	ISFATTR.NODE.LOGMODE	\$T	jesx.MODIFY.APPL	CONTROL
			-	-	-
LOGMODE	NO	ISFATTR.NODE.LOGMODE	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
LOGON	NC	ISFATTR.NETOPTS.LOGON	\$T	jesx.MODIFY.APPL	CONTROL
			-	-	-
LOGON	NO	ISFATTR.NODE.LOGON	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>LRECL</b>	PUN	ISFATTR.PROPTS.LRECL	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>M</b>	PR	ISFATTR.PROPTS.MARK	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>MAILBCC</b>	JDS	ISFATTR.OUTDESC.MAILBCC	SSI		
			SSI		
<b>MAILCC</b>	JDS	ISFATTR.OUTDESC.MAILCC	SSI		
			SSI		
<b>MAILFILE</b>	JDS	ISFATTR.OUTDESC.MAILFILE	SSI		
			SSI		
<b>MAILFROM</b>	JDS	ISFATTR.OUTDESC.MAILFROM	SSI		
			SSI		
<b>MAILTO</b>	JDS	ISFATTR.OUTDESC.MAILTO	SSI		
			SSI		
<b>MAX-TIME</b>	JC	ISFATTR.JOBCL.TIME	\$T	jesx.MODIFY.JOBCLASS	CONTROL
<b>MAXRETRIES</b>	NO	ISFATTR.NODE.MAXRETR	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
<b>MBURST</b>	SO	ISFATTR.MODIFY.BURST	\$T	jesx.MODIFY.OFF	CONTROL
<b>MC</b>	RDR	ISFATTR.RDR.MCLASS	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>MC</b>	JC	ISFATTR.JOBCL.MSGCLASS	\$T	jesx.MODIFY.JOBCLASS	CONTROL
<b>MCLASS</b>	SO	ISFATTR.MODIFY.CLASS	\$T	jesx.MODIFY.OFF	CONTROL
<b>MDEST</b>	SO	ISFATTR.MODIFY.DEST	\$T	jesx.MODIFY.OFF	CONTROL
<b>MFCB</b>	SO	ISFATTR.MODIFY.FCB	\$T	jesx.MODIFY.OFF	CONTROL
<b>MFLH</b>	SO	ISFATTR.MODIFY.FLASH	\$T	jesx.MODIFY.OFF	CONTROL
<b>MFORMS</b>	SO	ISFATTR.MODIFY.FORMS	\$T	jesx.MODIFY.OFF	CONTROL
<b>MHOLD</b>	SO	ISFATTR.MODIFY.HOLD	\$T	jesx.MODIFY.OFF	CONTROL
<b>MINPCT</b>	SP	ISFATTR.SPOOL.MINPCT	-	-	-
			*F Q	jesx,MODIFY.Q	UPDATE
<b>MODE</b>	INIT	ISFATTR.INIT.MODE	-	-	-
			*F	jesx,MODIFY.G	UPDATE
<b>MODE</b>	JC	ISFATTR.JOBCL.MODE	\$T	jesx.MODIFY.JOBCLASS	CONTROL

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>MODE</b>	PR	ISFATTR.PRPOPTS.MODE	\$T	jesx.MODIFY.DEV	UPDATE
			*F	jesx.MODIFY.F	
<b>MODSP</b>	SO	ISFATTR.MODIFY.ODISP	\$T	jesx.MODIFY.OFF	CONTROL
<b>MPRMODE</b>	SO	ISFATTR.MODIFY.PRMODE	\$T	jesx.MODIFY.OFF	CONTROL
<b>MSAFF</b>	SO	ISFATTR.MODIFY.SYSAFF	\$T	jesx.MODIFY.OFF	CONTROL
<b>MSCOPE</b>	EMCS	ISFATTR.EMCS.MSCOPE	V CN(), MSCOPE=	MVS.VARY.CN	UPDATE
<b>MSGLV</b>	JC	ISFATTR.JOBCL.MSGLEVEL	\$T	jesx.MODIFY.JOBCLASS	CONTROL
<b>MUCS</b>	SO	ISFATTR.MODIFY.UCS	\$T	jesx.MODIFY.OFF	CONTROL
<b>MWRITER</b>	SO	ISFATTR.MODIFY.WRITER	\$T	jesx.MODIFY.OFF	CONTROL
<b>NAME</b>	JDS	ISFATTR.OUTDESC.NAME	SSI		
			SSI		
<b>NSECURE</b>	NS	ISFATTR.NETOPTS.NSECURE	\$TNETSRV, SECURE=	jesx.MODIFY.NETSRV	CONTROL
<b>NETSRV</b>	NC	ISFATTR.NETOPTS.NETSRV	\$T	jesx.MODIFY.SOCKET	CONTROL
			-	-	-
<b>NETSRV</b>	NO	ISFATTR.NODE.NETSRV	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>NEWPAGE</b>	PR	ISFATTR.PROPTS.NEWPAGE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>NHOLD</b>	NO	ISFATTR.NODE.ETHOLD	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
<b>NODE</b>	LI	ISFATTR.LINE.NODE	\$SN	jesx.START.NET	CONTROL
			*X	jesx.CALL.NJE	UPDATE
<b>NODENAME</b>	NO	ISFATTR.NODE.NODENAME	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>NOTIFY</b>	JDS	ISFATTR.OUTDESC.NOTIFY	SSI		
			SSI		
<b>NOTIFY</b>	SO	ISFATTR.OFFLOAD.NOTIFY	\$T	jesx.MODIFY.OFF	CONTROL
<b>NPRO</b>	PR	ISFATTR.PROPTS.NPRO	\$T	jesx.MODIFY.DEV	UPDATE
			See note 3.		
<b>NUMVALUE</b>	OMVS	ISFATTR.OMVS.VALUE	SETOMVS optionname=	MVS.SETOMVS.OMVS	UPDATE

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
OCOPYCNT	JDS	SFATTR.OUTDESC.OCOPYCNT	SSI		
			SSI		
ODISP	JC	ISFATTR.JOBCL.ODISP	\$T	jesx.MODIFY.JOBCLASS	CONTROL
ODISP	H JDS O	ISFATTR.OUTPUT.ODISP	\$TO	jesx.MODIFY.BATOUT jesx.MODIFY.STCOUT jesx.MODIFY.TSUOUT	UPDATE
			-	-	-
OFFSETXB	JDS	ISFATTR.OUTDESC.OFFSETXB	SSI		
			SSI		
OFFSETXF	JDS	ISFATTR.OUTDESC.OFFSETXF	SSI		
			SSI		
OFFSEYB	JDS	ISFATTR.OUTDESC.OFFSEYB	SSI		
			SSI		
OFFSEYF	JDS	ISFATTR.OUTDESC.OFFSEYF	SSI		
			SSI		
OPLOG	PR	ISFATTR.PROPTS.OPACTLOG	-	-	-
			*F	jesx.MODIFY.W	UPDATE
OUT	JC	ISFATTR.JOBCL.OUTPUT	\$T	jesx.MODIFY.JOBCLASS	CONTROL
OUTBN	JDS	ISFATTR.OUTDESC.OUTBIN	SSI		
			SSI		
OVERFNAM	SP	ISFATTR.SPOOL.OVFNAME	-	-	-
			*F Q	jesx.MODIFY.Q	UPDATE
OVERLAYB	JDS	ISFATTR.OUTDESC.OVERLAYB	SSI		
			SSI		
OVERLAYF	JDS	ISFATTR.OUTDESC.OVERLAYF	SSI		
			SSI		
PAGEDEF	JDS	ISFATTR.OUTDESC.PAGEDEF	SSI		
			SSI		
PAGE-LIMIT	LI NC	ISFATTR.SELECT.PLIM	\$T	jesx.MODIFY.L	CONTROL
			-	-	-
PAGE-LIMIT	PR	ISFATTR.SELECT.PLIM	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
PAGE-LIMIT	SO	ISFATTR.SELECT.PLIM	\$T	jesx.MODIFY.OFF	CONTROL

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
PAGE-LIM-HI	PR	ISFATTR.SELECT.PLIM	-	-	-
			See note 3.		
PAGE-LIM-LOW	PR	ISFATTR.SELECT.PLIM	-	-	-
			See note 3.		
PARAMETERS	CK	ISFATTR.CHECK.PARM	F	MVS.MODIFY.STC. <i>hcproc.hcstcid</i>	UPDATE
PARTNAME	JC	ISFATTR.JOBCL.PARTNAME	-	-	-
			*F	jesx.MODIFY.C	UPDATE
PARTNAME	JP	ISFATTR.SPOOL.SPARN	-	-	-
			*F	jesx.MODIFY.G	UPDATE
PARTNAME	NO	ISFATTR.NODE.PARTNAM	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
PARTNAME	SP	ISFATTR.SPOOL.PARTNAME	-	-	-
			*F Q	jesx.MODIFY.Q	UPDATE
PASSWORD	LI	ISFATTR.LINE.PASSWORD	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
PASSWORD	NS	ISFATTR.LOGON.PASSWORD	\$T	jesx.MODIFY.LOGON	CONTROL
			-	-	-
PATH	NO	ISFATTR.NODE.PATH	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
PAU	PR PUN	ISFATTR.PROPTS.PAUSE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
PDEFAULT	PR	ISFATTR.PROPTS.PDEFAULT	-	-	-
			*F	jesx.MODIFY.F	CONTROL
PEN	NO	ISFATTR.NODE.PENCRYPT	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
PGN	DA	ISFATTR.JOB.PGN	RESET	MVS.RESET	UPDATE
PGN	JC	ISFATTR.JOBCL.PGN	\$T	jesx.MODIFY.JOBCLASS	CONTROL
PGNM	JC	ISFATTR.JOBCL.PGMRNAME	\$T	jesx.MODIFY.JOBCLASS	CONTROL
PI	RDR	ISFATTR.RDR.PRIOINC	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDs Resource, JES2	Required Access
			Command, JES3	OPERCMDs Resource, JES3	
<b>PL</b>	RDR	ISFATTR.RDR.PRIOLIM	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>PL</b>	JC	ISFATTR.JOBCL.PROCLIB	\$T	jesx.MODIFY.JOBCLASS	CONTROL
<b>PMG</b>	NO	ISFATTR.NODE.PATHMGR	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>PORT</b>	JDS	ISFATTR.OUTDESC.PORTNO	SSI		
			SSI		
<b>PORT</b>	NC	ISFATTR.NETOPTS.PORT	\$T	jesx.MODIFY.SOCKET	CONTROL
			*F	jesx.MODIFY.SOCKET	UPDATE
<b>PORT</b>	NS	ISFATTR.NETOPTS.PORT	\$T	jesx.MODIFY.SOCKET	CONTROL
			*F	jesx.MODIFY.NETSERV	UPDATE
<b>PRINTO</b>	JDS	ISFATTR.OUTDESC.PRINTO	SSI		
			SSI		
<b>PRINTQ</b>	JDS	ISFATTR.OUTDESC.PRINTQ	SSI		
			SSI		
<b>PRMODE</b>	JDS JO	ISFATTR.OUTPUT.PRMODE	-	-	-
			*F U	jesx.MODIFY.U	UPDATE
<b>PRMODE</b>	H O	ISFATTR.OUTPUT.PRMODE	\$TO	jesx.MODIFY.BATOUT jesx.MODIFY.STCOUT jesx.MODIFY.TSUOUT	UPDATE
			-	-	-
<b>PRMODE</b>	JDS	ISFATTR.OUTPUT.PRMODE	-	-	-
			*F	jesx.MODIFY.U	UPDATE
<b>PROMORT</b>	JC	ISFATTR.JOBCL.PROMORATE	\$TJOBCLASS, PROMO=	jesx.MODIFY.JOBCLASS	CONTROL
<b>PROT</b>	SO	ISFATTR.OFFLOAD.PROTECT	\$T	jesx.MODIFY.OFFLOAD	CONTROL
<b>PRTDEF</b>	NO	ISFATTR.NODE.PRTDEF	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
<b>PRTDEST</b>	I ST	ISFATTR.JOB.PRTDEST	\$R	jesx.ROUTE.JOBOUT	UPDATE
<b>PRTDEST</b>	RDR	ISFATTR.RDR.PRTDEST	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>PRTTSO</b>	NO	ISFATTR.NODE.PRTTSO	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE



Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
PRTXWTR	NO	ISFATTR.NODE.PRTXWTR	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
PRTY	I ST	ISFATTR.JOB.PRTY	\$T	jesx.MODIFY.BAT jesx.MODIFY.STC jesx.MODIFY.TSU	UPDATE
			*F J,P	jesx.MODIFY.JOBP	UPDATE
PRTY	H O	ISFATTR.OUTPUT.PRTY	\$TO	jesx.MODIFY.BATOUT jesx.MODIFY.STCOUT jesx.MODIFY.TSUOUT	UPDATE
			-	-	-
PRV	NO	ISFATTR.NODE.PRIVATE	\$T	jesx.MODIFY.NODE	CONTROL
PSEL	PR	ISFATTR.PROPTS.PRESELECT	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
PTYPE	NO	ISFATTR.NODE.PTYPE	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
PUNDEF	NO	ISFATTR.NODE.PUNDEF	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
PUNDEST	RDR	ISFATTR.RDR.PUNDEST	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
PWCNTL	NO	SFATTR.NODE.PWCNTL	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
QHLD	JC	ISFATTR.JOBCL.QHLD	\$T	jesx.MODIFY.JOBCLASS	CONTROL
QUIESCE	DA	ISFATTR.JOB.QUIESCE	RESET	MVS.RESET	UPDATE
RECV	NO	ISFATTR.NODE.RECEIVE	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
REGION	JC	ISFATTR.JOBCL.REGION	\$T	jesx.MODIFY.JOBCLASS	CONTROL
RES	SP	ISFATTR.SPOOL.RESERVED	\$T	jesx.MODIFY.SPOOL	CONTROL
			-	-	-
REST	LI	ISFATTR.LINE.REST	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
REST	NC	ISFATTR.LINE.REST	\$T	jesx.MODIFY.APPL jesx.MODIFY.SOCKET	CONTROL
			-	-	-

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>REST</b>	NO	ISFATTR.NODE.REST	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>RESTART</b>	LI	ISFATTR.PROPTS.RESTART	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>RESTART</b>	NS	ISFATTR.PROPTS.RESTART	\$T	jesx.MODIFY.LOGON jesx.MODIFY.NETSRV	CONTROL
			-	-	-
<b>REST-INT</b>	LI	ISFATTR.PROPTS.RTIME	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>REST-INT</b>	NS	ISFATTR.PROPTS.RTIME	\$T	jesx.MODIFY.LOGON jesx.MODIFY.NETSRV	CONTROL
			-	-	-
<b>RETAINF</b>	JDS	ISFATTR.OUTDESC.RETAINF	SSI		
			SSI		
<b>RETAINS</b>	JDS	ISFATTR.OUTDESC.RETAINS	SSI		
			SSI		
<b>RETRYL</b>	JDS	ISFATTR.OUTDESC.RETRYL	SSI		
			SSI		
<b>RETRYT</b>	JDS	ISFATTR.OUTDESC.RETRYT	SSI		
			SSI		
<b>REXXHLQ</b>	CK	ISFATTR.CHECK.REXXHLQ	MODIFY	MVS.MODIFY.STC.hcproc. hcstcid	UPDATE
			MODIFY	MVS.MODIFY.STC.hcproc. hcstcid	UPDATE
<b>ROUTCDE</b>	EMCS	ISFATTR.EMCS.ROUTCDE	V CN(),ROUT	MVS.VARY.CN	UPDATE
<b>RST</b>	JC	ISFATTR.JOBCL.RESTART	\$T	jesx.MODIFY.JOBCLASS	CONTROL
<b>RTPD</b>	SO	ISFATTR.OFFLOAD.RETENT	\$T	jesx.MODIFY.OFFLOAD	CONTROL
<b>ROOM</b>	JDS	ISFATTR.OUTDESC.ROOM	SSI		
			SSI		
<b>SAFF</b>	I ST	ISFATTR.JOB.SYSAFF	\$T	jesx.MODIFY.BAT jesx.MODIFY.STC jesx.MODIFY.TSU	UPDATE
<b>SAFF</b>	JG	ISFATTR.JOBGROUP.SYSAFF	\$T	jesx.MODIFY.GROUP	UPDATE

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>SAFF</b>	SP	ISFATTR.SPOOL.SYSAFF	\$T	jesx.MODIFY.SPOOL	CONTROL
<b>SAFF1</b>	RDR	ISFATTR.RDR.SYSAFF	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SBURST</b>	PR	ISFATTR.SELECT.BURST	\$T	jesx.MODIFY.DEV	UPDATE
			*S, *X	See note 3.	
<b>SBURST</b>	SO	ISFATTR.SELECT.BURST	\$T	jesx.MODIFY.OFF	CONTROL
<b>SCHEDULING -ENV</b>	JC	ISFATTR.JOBCL.SCHENV	\$T	jesx.MODIFY.JOBCLASS	CONTROL
<b>SCHEDULING -ENV</b>	I ST	ISFATTR.JOB.SCHENV	\$T	jesx.MODIFY.BAT	UPDATE
<b>SCHEDULING -ENV</b>	JG	ISFATTR.JOBGROUP.SCHENV	\$T	jesx.MODIFY.GROUP	UPDATE
<b>SCLASS</b>	PR PUN	ISFATTR.SELECT.CLASS	\$T	jesx.MODIFY.DEV	UPDATE
			See note 3.		
<b>SCLASS</b>	SO	ISFATTR.SELECT.CLASS	\$T	jesx.MODIFY.OFF	CONTROL
<b>SCLASS1-8</b>	SO	ISFATTR.SELECT.CLASS	\$T	jesx.MODIFY.OFF	CONTROL
<b>SCN</b>	JC	ISFATTR.JOBCL.SCAN	\$T	jesx.MODIFY.JOBCLASS	CONTROL
<b>SDEPTH</b>	JC	ISFATTR.JOBCL.SDEPTH	-	-	-
			*F	jesx.MODIFY.C	UPDATE
<b>SDEST1</b>	PR	ISFATTR.SELECT.DEST	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SDEST1</b>	PUN	ISFATTR.SELECT.DEST	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SDEST1</b>	SO	ISFATTR.SELECT.DEST	\$T	jesx.MODIFY.OFF	CONTROL
<b>SDISP</b>	SO	ISFATTR.SELECT.DISP	\$T	jesx.MODIFY.OFF	CONTROL
<b>SECURE</b>	NO	ISFATTR.NETOPTS.SECURE	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
<b>SECURE</b>	NS	ISFATTR.NETOPTS.SECURE	\$T	jesx.MODIFY.SOCKET	CONTROL
			-	-	-
<b>SECURE</b>	NC	ISFATTR.NETOPTS.SECURE	\$T	jesx.MODIFY.SOCKET	CONTROL
			-	-	-
<b>SELECT</b>	PR PUN	ISFATTR.PROPTS.SELECT	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>SELECTMODE NAME</b>	JP	ISFATTR.MEMBER.SELMNAME	-	-	-
			*F	jesx.MODIFY.G	UPDATE
<b>SENDP</b>	NO	ISFATTR.NODE.SENDP	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>SENTRS</b>	NO	ISFATTR.NODE.SENTREST	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>SEP</b>	PR	ISFATTR.PROPTS.SEP	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SEP</b>	PUN	ISFATTR.PROPTS.SEP	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SEPCHAR</b>	PR	ISFATTR.PROPTS.SEPCHARS	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SEPDS</b>	PR PUN RDR	ISFATTR.PROPTS.SEPDS	\$T	jesx.MODIFY.DEV	UPDATE
			See note 3.		
<b>SETUP</b>	PR PUN	ISFATTR.PROPTS.SETUP	\$T	jesx.MODIFY.DEV	UPDATE
			*F	jesx.MODIFY.W	
<b>SETUP</b>	PUN	ISFATTR.PROPTS.SETUP	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SEVERITY</b>	CK	ISFATTR.CHECK.SEVERITY	F	MVS.MODIFY.STC. hcproc.hcstcid	UPDATE
<b>SFCB</b>	PR	ISFATTR.SELECT.FCB	\$T	jesx.MODIFY.DEV	UPDATE
			See note 3.		
<b>SFCB</b>	SO	ISFATTR.SELECT.FCB	\$T	jesx.MODIFY.OFF	CONTROL
<b>SFLH</b>	SO	ISFATTR.SELECT.FLASH	\$T	jesx.MODIFY.OFF	CONTROL
<b>SFLH</b>	PR	ISFATTR.SELECT.FLASH	\$T	jesx.MODIFY.DEV	UPDATE
			*R, *S	See note 3.	
<b>SFORMS</b>	PR PUN	ISFATTR.SELECT.FORMS	\$T	jesx.MODIFY.DEV	UPDATE
			See note 3.		
<b>SFORMS</b>	SO	ISFATTR.SELECT.FORMS	\$T	jesx.MODIFY.OFF	CONTROL
<b>SHOLD</b>	SO	ISFATTR.SELECT.HOLD	\$T	jesx.MODIFY.OFF	CONTROL
<b>SJOBNAME</b>	PR PUN	ISFATTR.SELECT.JOBNAME	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>SJOBNAME</b>	SO	ISFATTR.SELECT.JOBNAME	\$T	jesx.MODIFY.OFF	CONTROL
<b>SOCKET</b>	NS	ISFATTR.NETOPTS.SOCKET	\$T	jesx.MODIFY.NETSRV	CONTROL
			*F	jesx.MODIFY.NETSERV	UPDATE
<b>SODSP</b>	LI	ISFATTR.SELECT.OUTDISP	\$T	jesx.MODIFY.L	CONTROL
			-	-	-
<b>SODSP</b>	NC	ISFATTR.SELECT.ODISP	\$T	jesx.MODIFY.L	CONTROL
			-	-	-
<b>SODSP</b>	SO	ISFATTR.SELECT.ODISP	\$T	jesx.MODIFY.OFF	CONTROL
<b>SOWNER</b>	PR	ISFATTR.SELECT.OWNER	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SOWNER</b>	PUN	ISFATTR.SELECT.OWNER	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SOWNER</b>	SO	ISFATTR.SELECT.OWNER	\$T	jesx.MODIFY.OFF	CONTROL
<b>SPEED</b>	LI	ISFATTR.LINE.SPEED	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>SPRMODE1</b>	SO	ISFATTR.SELECT.PRMODE	\$T	jesx.MODIFY.OFF	CONTROL
<b>SPRMODE1</b>	PR PUN RDR	ISFATTR.SELECT.PRMODE	\$T	jesx.MODIFY.DEV	UPDATE
			See note 3.		
<b>SRANGE</b>	PR	ISFATTR.SELECT.RANGE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SRANGE</b>	PUN	ISFATTR.SELECT.RANGE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SRANGE</b>	SO	ISFATTR.SELECT.RANGE	\$T	jesx.MODIFY.OFF	CONTROL
<b>SRNUM</b>	LI	ISFATTR.LINE.SRNUM	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>SRNUM</b>	NO	ISFATTR.NODE.SRNUM	-	-	-
			*F	jesx.MODIFY.NJE	UPDATE
<b>SRVCLASS</b>	DA	ISFATTR.JOB.SRVCLASS	RESET	MVS.RESET	UPDATE
<b>SRVCLASS</b>	I ST	ISFATTR.JOB.SRVCLS	\$T	jesx.MODIFY.BAT jesx.MODIFY.STC jesx.MODIFY.TSU	CONTROL
			*F J	jesx.MODIFY.JOB	UPDATE

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
<b>SRVCLASS</b>	ENC	ISFATTR.ENCLAVE.SRVCLASS			
<b>SRVNAME</b>	NC	ISFATTR.NETOPTS.NETSRV	-	-	-
			*F	jesx.MODIFY.SOCKET	UPDATE
<b>SSAFF</b>	SO	ISFATTR.SELECT.SYSAFF	\$T	jesx.MODIFY.OFF	CONTROL
<b>SSCHEDULING -ENV</b>	SO	ISFATTR.SELECT.SCHENV	\$T	jesx.MODIFY.OFF	CONTROL
<b>SSRVCLASS</b>	SO	ISFATTR.SELECT.SRVCLS	\$T	jesx.MODIFY.OFF	CONTROL
<b>SSIGNON</b>	NO	ISFATTR.NODE.SSIGNON	\$T	jesx.MODIFY.NODE	CONTROL
			*F	jesx.MODIFY.NJE	UPDATE
<b>STACK</b>	NS	ISFATTR.NETOPTS.STACK	\$T	jesx.MODIFY.NETSRV	CONTROL
			*F	jesx.MODIFY.NETSERV	
<b>STNUM</b>	LI	ISFATTR.LINE.STNUM	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
<b>SUBNET</b>	NO	ISFATTR.NODE.SUBNET	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
<b>SUCS</b>	PR	ISFATTR.SELECT.UCS	\$T	jesx.MODIFY.DEV	UPDATE
			See note 3.		
<b>SUCS</b>	SO	ISFATTR.SELECT.UCS	\$T	jesx.MODIFY.OFF	CONTROL
<b>SUS</b>	PUN	ISFATTR.PROPTS.SUSPEND	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SVOL</b>	SO	ISFATTR.SELECT.VOL	\$T	jesx.MODIFY.OFF	CONTROL
<b>SVOL</b>	PR PUN	ISFATTR.SELECT.VOL	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SWA</b>	JC	ISFATTR.JOBCL.SWA	\$T	jesx.MODIFY.JOBCLASS	CONTROL
<b>SWRITER</b>	PR PUN	ISFATTR.SELECT.WRITER	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
<b>SWRITER</b>	SO	ISFATTR.SELECT.WRITER	\$T	jesx.MODIFY.OFF	CONTROL
<b>SYNCTOL</b>	MAS	ISFATTR.MEMBER.SYNCTOL	\$T	jesx.MODIFY.MASDEF	CONTROL
<b>SYSSYM</b>	JC	ISFATTR.JOBCL.SYSSYM	\$T	jesx.MODIFY.JOBCLASS	CONTROL
			*F	jesx.MODIFY.C	UPDATE
<b>TDEPTH</b>	JC	ISFATTR.JOBCL.TDEPTH	-	-	-
			*F	jesx.MODIFY.C	UPDATE

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
TITLE	JDS	ISFATTR.OUTDESC.TITLE	SSI		
			SSI		
TP6	JC	ISFATTR.JOBCL.TYPE6	\$T	jesx.MODIFY.JOBCLASS	CONTROL
TP26	JC	ISFATTR.JOBCL.TYPE26	\$T	jesx.MODIFY.JOBCLASS	CONTROL
TR	LI NC	ISFATTR.PROPTS.TRACE	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
TR	NO	ISFATTR.NODE.TRACE	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
TR	NS	ISFATTR.PROPTS.TRACE	\$T	jesx.MODIFY.LOGON jesx.MODIFY.NETSRV	CONTROL
			-	-	-
TR	PR PUN	ISFATTR.PROPTS.TRACE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
TR	RDR	ISFATTR.RDR.TRACE	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
TRANS	PR	ISFATTR.PROPTS.TRANS	\$T	jesx.MODIFY.DEV	UPDATE
			*F	jesx.MODIFY.F	
TRANS	NO	ISFATTR.NODE.TRANSMIT	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
TRANSP	LI	ISFATTR.LINE. TRANSPARENCY	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
TRKCELL	PR	ISFATTR.PROPTS.TRKCELL	PR	jesx.MODIFY.DEV	UPDATE
			-	-	-
UCS	H O	ISFATTR.OUTPUT.UCS	\$TO	jesx.MODIFY.BATOUT jesx.MODIFY.STCOUT jesx.MODIFY.TSUOUT	UPDATE
			-	-	-
UCS	JDS J0	ISFATTR.OUTPUT.UCS	-	-	-
			*F	jesx.MODIFY.U	UPDATE
UCSV	PR	ISFATTR.PROPTS.UCSVERIFY	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
UJP	JC	ISFATTR.JOBCL.IEFUJP	\$T	jesx.MODIFY.JOBCLASS	CONTROL

Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
UNALLOC	INIT	ISFATTR.INIT.UNALLOC	-	-	-
			*F	jesx.MODIFY.G	UPDATE
UNIT	LI	ISFATTR.PROPTS.UNIT	\$T	jesx.MODIFY.LINE	UPDATE
			-	-	-
UNIT	PR PUN	ISFATTR.PROPTS.UNIT	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
UNIT	SO	ISFATTR.PROPTS.UNIT	\$T	jesx.MODIFY.OFFLOAD	CONTROL
UNIT	RDR	ISFATTR.RDR.UNIT	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-
UNKNIDS	EMCS	ISFATTR.EMCS.UNKNIDS	V CN(), UNKNIDS=	MVS.VARY.CN	UPDATE
USERDATA1	JDS	ISFATTR.OUTDESC.USERDATA	SSI		
			SSI		
USERDATE	CK	ISFATTR.CHECK.USERDATE	F	MVS.MODIFY.STC. hcproc.hcstcid	UPDATE
USERLIB	JDS	ISFATTR.OUTDESC.USERLIB	SSI		
			SSI		
USO	JC	ISFATTR.JOBCL.IEFUSO	\$T	jesx.MODIFY.JOBCLASS	CONTROL
VALIDATE	SO	ISFATTR.OFFLOAD.VALIDATE	\$T	jesx.MODIFY.OFFLOAD	CONTROL
VERBOSE	CK	ISFATTR.CHECK.VERBOSE	F	MVS.MODIFY.STC. hcproc.hcstcid	UPDATE
VERIFYP	NO	ISFATTR.NODE.VERIFYP	\$T	jesx.MODIFY.NODE	CONTROL
			-	-	-
VFYPATH	NO	ISFATTR.NODE.VFYPATH	\$TNODE, VFYPATH=	jesx.MODIFY.NODE	CONTROL
VOLS	SO	ISFATTR.OFFLOAD.VOLS	\$T	jesx.MODIFY.OFFLOAD	CONTROL
VTR	LI	ISFATTR.PROPTS.VTRACE	\$T	jesx.MODIFY.LINE	CONTROL
			-	-	-
VTR	NC	ISFATTR.PROPTS.VTRACE	\$T	jesx.MODIFY.LINE	CONTROL
			*F	jesx.MODIFY.SOCKET	UPDATE
VTR	NS	ISFATTR.PROPTS.VTRACE	\$T	jesx.MODIFY.NETSRV	CONTROL
			*F	jesx.MODIFY.NETSERV	UPDATE
WARN%	RM	ISFATTR.RESMON.WARNPCT	\$T	jesx.MODIFY.resource <sup>2</sup>	CONTROL



Table 150. Overtypable Fields.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

When a set of related fields can be overtyped with the Overtyping Extension pop-up, all of the fields in the set are protected by the same resource.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

When an overtypeable field does not apply in a particular JES environment, the command and OPERCMDS resource are shown as a hyphen (-).

(continued)

Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)	Command, JES2	OPERCMDS Resource, JES2	Required Access
			Command, JES3	OPERCMDS Resource, JES3	
WORK-SELECTION	LI NC	ISFATTR.PROPTS.WS	\$T	jesx.MODIFY.L	CONTROL
			-	-	-
WORK-SELECTION	PR	ISFATTR.PROPTS.WS	\$T	jesx.MODIFY.DEV	UPDATE
			*R	jesx.RESTART.DEV.device	
WORK-SELECTION	PUN	ISFATTR.PROPTS.WS	\$T	jesx.MODIFY.DEV	UPDATE
			See note 3.		
WORK-SELECTION	SO	ISFATTR.PROPTS.WS	\$T	jesx.MODIFY.OFF	CONTROL
WTOTYPE	CK	ISFATTR.CHECK.WTOTYPE	F	MVS.MODIFY.STC. hcproc.hcstcid	UPDATE
WTR	H O	ISFATTR.OUTPUT.WRITER	\$TO	jesx.MODIFY.BATOUT jesx.MODIFY.STCOUT jesx.MODIFY.TSUOUT	UPDATE
			-	-	-
WTR	JDS JO	ISFATTR.OUTPUT.WRITER	SSI		
			SSI		
XBM	JC	ISFATTR.JOBCL.XBM	\$T	jesx.MODIFY.JOBCLASS	CONTROL
XEQDEST	RDR	ISFATTR.RDR.XEQDEST	\$T	jesx.MODIFY.DEV	UPDATE
			-	-	-

Notes for Table 150 on page 293:

<sup>1</sup> SDSF uses the subsystem interface (SSI) when you overtype the C (JES output class) or DEST (JES print destination name) on the JDS panel. You can change the class or destination without releasing the output. In order to release output when the JESSPOOL class is enabled, the user must have ALTER authority to the JESSPOOL resource. This authority is implied for the JESSPOOL resources created by the user.

<sup>2</sup> The SAF resource varies with the JES2 resource. Refer to “JES2 resources” on page 331.

<sup>3</sup> In a JES3 environment, you must also type an action character when overtyping the field. The command issued and OPERCMDS resource depend on the action character that is used with the overtype. Refer to Table 151 on page 315.

Table 151. Actions with Overtypes on the PR and PUN Panels in a JES3 Environment

Action Character	Command	OPERCMDS Resource	Required Access
<b>B, E, F</b>	*RESTART	jesx.RESTART.DEV.device	UPDATE
<b>S</b>	*START	jesx.START.DEV.device	UPDATE
<b>X</b>	*CALL	jesx.CALL.dsppname	UPDATE

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
		SSI	ADDRESS	JDS	ISFATTR.OUTDESC.ADDRESS
		SSI	AFPPARMS	JDS	ISFATTR.OUTDESC.AFPPARMS
		SSI	AFPSTATS	JDS	ISFATTR.OUTDESC.AFPSTATS
		SSI	BUILDING	JDS	ISFATTR.OUTDESC.BLDG
		SSI <sup>1</sup>	C	JDS J0	ISFATTR.OUTPUT.CLASS
		SSI	CC	JDS J0	ISFATTR.OUTPUT.COPYCNT
		SSI	COLORMAP	JDS	ISFATTR.OUTDESC. COLORMAP
		SSI	COMSETUP	JDS	ISFATTR.OUTDESC. COMSETUP
		SSI	DEPARTMENT	JDS	ISFATTR.OUTDESC.DEPT
		SSI <sup>1</sup>	DEST	JDS J0	ISFATTR.OUTPUT.DEST
		SSI	FORMDEF	JDS	ISFATTR.OUTDESC.FORMDEF
		SSI	FORMLEN	JDS	ISFATTR.OUTDESC.FORMLEN
		SSI	FORMS	JDS J0	ISFATTR.OUTPUT.FORMS
		SSI	INTRAY	JDS	ISFATTR.OUTDESC.INTRAY
		SSI	IPDEST	JDS	ISFATTR.OUTDESC.IPDEST
		SSI	MAILBCC	JDS	ISFATTR.OUTDESC.MAILBCC
		SSI	MAILCC	JDS	ISFATTR.OUTDESC.MAILCC
		SSI	MAILFILE	JDS	ISFATTR.OUTDESC.MAILFILE
		SSI	MAILFROM	JDS	ISFATTR.OUTDESC.MAILFROM
		SSI	MAILTO	JDS	ISFATTR.OUTDESC.MAILTO
		SSI	NAME	JDS	ISFATTR.OUTDESC.NAME
		SSI	OCOPYCNT	JDS	ISFATTR.OUTDESC.OCOPYCNT
		SSI	OFFSETXB	JDS	ISFATTR.OUTDESC. OFFSETXB
		SSI	OFFSETXF	JDS	ISFATTR.OUTDESC. OFFSETXF
		SSI	OFFSETYB	JDS	ISFATTR.OUTDESC. OFFSETYB
		SSI	OFFSETYF	JDS	ISFATTR.OUTDESC. OFFSETYF
		SSI	NOTIFY	JDS	ISFATTR.OUTDESC.NOTIFY
		SSI	OUTBN	JDS	ISFATTR.OUTDESC.OUTBIN
		SSI	OVERLAYB	JDS	ISFATTR.OUTDESC. OVERLAYB

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
		SSI	OVERLAYF	JDS	ISFATTR.OUTDESC.OVERLAYF
		SSI	PAGEDEF	JDS	ISFATTR.OUTDESC.PAGEDEF
		SSI	PORT	JDS	ISFATTR.OUTDESC.PORTNO
		SSI	PRINTO	JDS	ISFATTR.OUTDESC.PRINTO
		SSI	PRINTQ	JDS	ISFATTR.OUTDESC.PRINTQ
		SSI	PRMODE	JDS J0	ISFATTR.OUTPUT.PRMODE
		SSI	RETAINF	JDS	ISFATTR.OUTDESC.RETAINF
		SSI	RETAINS	JDS	ISFATTR.OUTDESC.RETAINS
		SSI	RETRYL	JDS	ISFATTR.OUTDESC.RETRYL
		SSI	RETRYT	JDS	ISFATTR.OUTDESC.RETRYT
		SSI	ROOM	JDS	ISFATTR.OUTDESC.ROOM
		SSI	TITLE	JDS	ISFATTR.OUTDESC.TITLE
		SSI	UCS	JDS J0	ISFATTR.OUTPUT.UCS
		SSI	USERDATA1	JDS	ISFATTR.OUTDESC.USERDATA
		SSI	USERLIB	JDS	ISFATTR.OUTDESC.USERLIB
			SRVCLASS	ENC	ISFATTR.ENCLAVE.SRVCLASS
		SSI	WTR	JDS J0	ISFATTR.OUTPUT.WRITER
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	B	PUN	ISFATTR.PROPTS.BPAGE
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	CB	PR	ISFATTR.PROPTS.CB
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	CHAR1	PR	ISFATTR.PROPTS.CHAR
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	CKPTPAGE	PR	ISFATTR.PROPTS.CKPTPAGE
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	CKPTSEC	PR	ISFATTR.PROPTS.CKPTSEC
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	COPIES	PR	ISFATTR.PROPTS.COPIES
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	COPYMARK	PR	ISFATTR.PROPTS.COPYMARK
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	LINE-LIM-HI	PR PUN	ISFATTR.SELECT.LIM
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	LINE-LIM-LO	PR PUN	ISFATTR.SELECT.LIM
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	NPRO	PR	ISFATTR.PROPTS.NPRO

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	PAGE-LIM-HI	PR	ISFATTR.SELECT.PLIM
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	PAGE-LIM-LO	PR	ISFATTR.SELECT.PLIM
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	SBURST	PR	ISFATTR.SELECT.BURST
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	SCLASS	PR PUN	ISFATTR.SELECT.CLASS
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	SEPDS	PUN	ISFATTR.PROPTS.SEPDS
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	SFCB	PR	ISFATTR.SELECT.FCB
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	SFORMS	PR PUN	ISFATTR.SELECT.FORMS
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	SPRMODE1	PR PUN	ISFATTR.SELECT.PRMODE
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	SUCS	PR	ISFATTR.SELECT.UCS
<b>jesx.CALL.dspname</b>	UPDATE	*X. See note 3.	WORK-SELECTION	PUN	ISFATTR.PROPTS.WS
<b>jesx.CALL.NJE</b>	UPDATE	*X	NODE	LI NO	ISFATTR.LINE.NODE
<b>jesx.MODIFY.resource<sup>2</sup></b>	CONTROL	\$T	LIMIT	RM	ISFATTR.RESMON.LIMIT
<b>jesx.MODIFY.resource<sup>2</sup></b>	CONTROL	\$T	WARN%	RM	ISFATTR.RESMON.WARNPCT
<b>jesx.MODIFY.APPL</b>	CONTROL	\$T	ANODE	NC	ISFATTR.NETOPTS.NODE
<b>jesx.MODIFY.APPL</b>	CONTROL	\$T	COMPACT	NC	ISFATTR.NODE.COMPACT
<b>jesx.MODIFY.APPL</b>	CONTROL	\$T	CONNECT	NC	ISFATTR.NETOPTS.CONNECT
<b>jesx.MODIFY.APPL</b>	CONTROL	\$T	CONN-INT	NC	ISFATTR.NETOPTS.CTIME
<b>jesx.MODIFY.APPL</b>	CONTROL	\$T	LINE	NC	ISFATTR.NODE.LINE
<b>jesx.MODIFY.APPL</b>	CONTROL	\$T	LOGMODE	NC	ISFATTR.NODE.LOGMODE
<b>jesx.MODIFY.APPL</b>	CONTROL	\$T	LOGON	NC	ISFATTR.NETOPTS.LOGON
<b>jesx.MODIFY.APPL</b>	CONTROL	\$T	REST	NC	ISFATTR.LINE.REST
<b>jesx.MODIFY.BAT</b>	UPDATE	\$T	SCHEDULING-ENV	I ST	ISFATTR.JOB.SCHENV
<b>jesx.MODIFY.BAT</b> <b>jesx.MODIFY.STC</b> <b>jesx.MODIFY.TSU</b>	UPDATE	\$T	SAFF	I ST	ISFATTR.JOB.SYSAFF
<b>jesx.MODIFY.BAT</b> <b>jesx.MODIFY.STC</b> <b>jesx.MODIFY.TSU</b>	UPDATE	\$T	C	I ST	ISFATTR.JOB.CLASS
<b>jesx.MODIFY.BAT</b> <b>jesx.MODIFY.STC</b> <b>jesx.MODIFY.TSU</b>	UPDATE	\$T	PRTY	I ST	ISFATTR.JOB.PRTY

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.MODIFY.BAT</b> <b>jesx.MODIFY.STC</b> <b>jesx.MODIFY.TSU</b>	CONTROL	\$T	SRVCLASS	I ST	ISFATTR.JOB.SRVCLS
<b>jesx.MODIFY.BATOUT</b> <b>jesx.MODIFY.STCOUT</b> <b>jesx.MODIFY.TSUOUT</b>	UPDATE	\$TO	BURST	H O	ISFATTR.OUTPUT.BURST
<b>jesx.MODIFY.BATOUT</b> <b>jesx.MODIFY.STCOUT</b> <b>jesx.MODIFY.TSUOUT</b>	UPDATE	\$TO SSI <sup>1</sup>	C	H O	ISFATTR.OUTPUT.CLASS
<b>jesx.MODIFY.BATOUT</b> <b>jesx.MODIFY.STCOUT</b> <b>jesx.MODIFY.TSUOUT</b>	UPDATE	\$TO SSI <sup>1</sup>	DEST	H O	ISFATTR.OUTPUT.DEST
<b>jesx.MODIFY.BATOUT</b> <b>jesx.MODIFY.STCOUT</b> <b>jesx.MODIFY.TSUOUT</b>	UPDATE	\$TO	FCB	H O	ISFATTR.OUTPUT.FCB
<b>jesx.MODIFY.BATOUT</b> <b>jesx.MODIFY.STCOUT</b> <b>jesx.MODIFY.TSUOUT</b>	UPDATE	\$TO	FLASH	H O	ISFATTR.OUTPUT.FLASH
<b>jesx.MODIFY.BATOUT</b> <b>jesx.MODIFY.STCOUT</b> <b>jesx.MODIFY.TSUOUT</b>	UPDATE	\$TO	FORMS	H O	ISFATTR.OUTPUT.FORMS
<b>jesx.MODIFY.BATOUT</b> <b>jesx.MODIFY.STCOUT</b> <b>jesx.MODIFY.TSUOUT</b>	UPDATE	\$TO	ODISP	H O	ISFATTR.OUTPUT.ODISP
<b>jesx.MODIFY.BATOUT</b> <b>jesx.MODIFY.STCOUT</b> <b>jesx.MODIFY.TSUOUT</b>	UPDATE	\$TO	PRMODE	H O	ISFATTR.OUTPUT.PRMODE
<b>jesx.MODIFY.BATOUT</b> <b>jesx.MODIFY.STCOUT</b> <b>jesx.MODIFY.TSUOUT</b>	UPDATE	\$TO	PRTY	H O	ISFATTR.OUTPUT.PRTY
<b>jesx.MODIFY.BATOUT</b> <b>jesx.MODIFY.STCOUT</b> <b>jesx.MODIFY.TSUOUT</b>	UPDATE	\$TO	UCS	H O	ISFATTR.OUTPUT.UCS
<b>jesx.MODIFY.BATOUT</b> <b>jesx.MODIFY.STCOUT</b> <b>jesx.MODIFY.TSUOUT</b>	UPDATE	\$TO	WTR	H O	ISFATTR.OUTPUT.WRITER
<b>jesx.MODIFY.C</b>	UPDATE	*F	JESLOG	JC	ISFATTR.JOBCL.JESLOG
<b>jesx.MODIFY.C</b>	UPDATE	*F	LOG	JC	ISFATTR.JOBCL.JLOG
<b>jesx.MODIFY.C</b>	UPDATE	*F	PARTNAME	JC	ISFATTR.JOBCL.PARTNAME
<b>jesx.MODIFY.C</b>	UPDATE	*F	SDEPTH	JC	ISFATTR.JOBCL.SDEPTH
<b>jesx.MODIFY.C</b>	UPDATE	*F	SYSSYM	JC	ISFATTR.JOBCL.SYSSYM
<b>jesx.MODIFY.C</b>	UPDATE	*F	TDEPTH	JC	ISFATTR.JOBCL.TDEPTH
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	ASIS	PR	ISFATTR.PROPTS.ASIS
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	CCTL	PR PUN	ISFATTR.PROPTS.CCTL
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	CHAR1–4	PR	ISFATTR.PROPTS.CHAR

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	CMPCT	PR PUN	ISFATTR.PROPTS.CMPCT
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	COMP	PR PUN	ISFATTR.PROPTS.COMPRESS
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	COMPACT	PR PUN	ISFATTR.PROPTS.COMPACT
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	CKPTLINE	PR PUN	ISFATTR.PROPTS.CKPTLINE
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	CKPTMODE	PR	ISFATTR.PROPTS.CKPTMODE
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	CKPTPAGE	PR PUN	ISFATTR.PROPTS.CKPTPAGE
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	CKPTSEC	PR	ISFATTR.PROPTS.CKPTSEC
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	COPYMARK	PR	ISFATTR.PROPTS.COPYMARK
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	CPYMOD	PR	ISFATTR.PROPTS.COPYMOD
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	DFCB	PR	ISFATTR.PROPTS.DEVFCB
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	FCBL	PR	ISFATTR.PROPTS.FCBLOAD
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	FSSNAME	PR	ISFATTR.PROPTS.FSSNAME
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	HONORTRC	PR	ISFATTR.PROPTS.HONORTRC
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	K	PR	ISFATTR.PROPTS.SPACE
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	LINE-LIMIT	PR PUN	ISFATTR.SELECT.LIM
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	LRECL	PR PUN	ISFATTR.PROPTS.LRECL
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	M	PR	ISFATTR.PROPTS.MARK
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	MODE	PR	ISFATTR.PROPTS.MODE
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	NEWPAGE	PR	ISFATTR.PROPTS.NEWPAGE
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	NPRO	PR	ISFATTR.PROPTS.NPRO
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	PAGE-LIMIT	PR	ISFATTR.SELECT.PLM
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	PAU	PR PUN	ISFATTR.PROPTS.PAUSE
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	PSEL	PR	ISFATTR.PROPTS.PRESELCT
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SBURST	PR SO	ISFATTR.SELECT.BURST
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SCLASS	PR PUN	ISFATTR.SELECT.CLASS
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SDEST1	PR PUN	ISFATTR.SELECT.DEST
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SELECT	PR PUN	ISFATTR.PROPTS.SELECT
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SEP	PR PUN	ISFATTR.PROPTS.SEP
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SEPCHAR	PR	ISFATTR.PROPTS.SEPCHARS
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SEPDS	PR PUN	ISFATTR.PROPTS.SEPDS
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SETUP	PR PUN	ISFATTR.PROPTS.SETUP
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SFCB	PR	ISFATTR.SELECT.FCB
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SFLH	PR	ISFATTR.SELECT.FLASH
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SFORMS	PR PUN	ISFATTR.SELECT.FORMS
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SJOBNAME	PR PUN	ISFATTR.SELECT.JOBNAME

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SOWNER	PR PUN	ISFATTR.SELECT.OWNER
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SPRMODE1	PR PUN	ISFATTR.SELECT.PRMODE
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SRANGE	PR PUN	ISFATTR.SELECT.RANGE
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SUCS	PR	ISFATTR.SELECT.UCS
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SUS	PR PUN	ISFATTR.SELECT.SUSPEND
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SVOL1	PR	ISFATTR.SELECT.VOL
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SWRITER	PR PUN	ISFATTR.SELECT.WRITER
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	TR	PR PUN	ISFATTR.PROPTS.TRACE
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	TRANS	PR	ISFATTR.PROPTS.TRANS
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	TRKCELL	PR	ISFATTR.PROPTS.TRKCELL
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	UCSV	PR	ISFATTR.PROPTS.UCSVERIFY
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	UNIT	PR PUN	ISFATTR.PROPTS.UNIT
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	WORK- SELECTION	PR PUN	ISFATTR.PROPTS.WS
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	FLS	PUN	ISFATTR.PROPTS.FLUSH
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	LINE-LIMIT	PUN	ISFATTR.SELECT.LIM
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SVOL	PUN	ISFATTR.SELECT.VOL
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	AUTHORITY	RDR	ISFATTR.RDR.AUTHORITY
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	C	RDR	ISFATTR.RDR.CLASS
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	HOLD	RDR	ISFATTR.RDR.HOLD
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	MC	RDR	ISFATTR.RDR.RMCLASS
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	PI	RDR	ISFATTR.RDR.PRIOINC
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	PL	RDR	ISFATTR.RDR.PRIOLIM
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	PRTDEST	RDR	ISFATTR.RDR.PRTDEST
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	PUNDEST	RDR	ISFATTR.RDR.PUNDEST
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	SAFF	RDR	ISFATTR.RDR.SYSAFF
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	TR	RDR	ISFATTR.RDR.TRACE
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	UNIT	RDR	ISFATTR.RDR.UNIT
<b>jesx.MODIFY.DEV</b>	UPDATE	\$T	XEQDEST	RDR	ISFATTR.RDR.XEQDEST
<b>jesx.MODIFY.F</b>	UPDATE	*F	MODE	PR	ISFATTR.PROPTS.MODE
<b>jesx.MODIFY.F</b>	CONTROL	*F	PDEFAULT	PR	ISFATTR.PROPTS.PDEFAULT
<b>jesx.MODIFY.F</b>	UPDATE	*F	SETUP	PR	ISFATTR.PROPTS.SETUP
<b>jesx.MODIFY.F</b>	UPDATE	*F	TRANS	PR	ISFATTR.PROPTS.TRANS
<b>jesx.MODIFY.G</b>	UPDATE	*F	ALLOC	INIT	ISFATTR.INIT.ALLOC
<b>jesx.MODIFY.G</b>	UPDATE	*F	BARRIER	INIT	ISFATTR.INIT.BARRIER

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.MODIFY.G</b>	UPDATE	*F	DEFCOUNT	INIT	ISFATTR.INIT.DEFCOUNT
<b>jesx.MODIFY.C</b>	UPDATE	*F	GROUP	INIT	ISFATTR.INIT.GROUP
<b>jesx.MODIFY.G</b>	UPDATE	*F	MODE	INIT	ISFATTR.INIT.MODE
<b>jesx.MODIFY.G</b>	UPDATE	*F	UNALLOC	INIT	ISFATTR.INIT.UNALLOC
<b>jesx.MODIFY.G</b>	UPDATE	*F	SELECTMODE NAME	JP	ISFATTR.MEMBER.SELMNAME
<b>jesx.MODIFY.G</b>	UPDATE	*F	PARTNAME	JP	ISFATTR.MEMBER.SPARTN
<b>jesx.MODIFY.GROUP</b>	UPDATE	\$T	SAFF	JG	ISFATTR.JOBGROUP.SYSAFF
<b>jesx.MODIFY.GROUP</b>	UPDATE	\$T	SCHEDULING-ENV	JG	ISFATTR.JOBGROUP.SCHENV
<b>jesx.MODIFY.INITIATOR</b>	CONTROL	\$T	CLASSES	INIT	ISFATTR.SELECT.JOBCLASS
<b>jesx.MODIFY.INITIATOR</b>	CONTROL	\$T	CLASS1-8	INIT	ISFATTR.SELECT.JOBCLASS
<b>jesx.MODIFY.JOB</b>	UPDATE	*F	C	I ST	ISFATTR.JOB.CLASS
<b>jesx.MODIFY.JOB</b>	UPDATE	*F	SRVLCASS	I ST	ISFATTR.JOB.SRVCLS
<b>jesx.MODIFY.JOB</b>	UPDATE	*F	C	I ST	ISFATTR.JOB.CLASS
<b>jesx.MODIFY.JOBP</b>	UPDATE	*F	PRTY	I ST	ISFATTR.JOB.PRTY
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	ACCT	JC	ISFATTR.JOBCL.ACCT
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	ACTIVE	JC	ISFATTR.JOBCL.ACTIVE
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	AUTH	JC	ISFATTR.JOBCL.AUTH
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	BLP	JC	ISFATTR.JOBCL.BLP
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	COMMAND	JC	ISFATTR.JOBCL.COMMAND
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	CPR	JC	ISFATTR.JOBCL.CONDPURG
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	CPY	JC	ISFATTR.JOBCL.COPY
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	DSENQSHR	JC	ISFATTR.JOBCL.DSENQSHR
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	GDGBIAS	JC	ISFATTR.JOBCL.GDGBIAS
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	GROUP	JC	ISFATTR.JOBCL.GROUP
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	HOLD	JC	ISFATTR.JOBCL.HOLD
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	JCLIM	JC	ISFATTR.JOBCL.JCLIM
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	JESLOG	JC	ISFATTR.JOBCL.JESLOG
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	JOBRC	JC	ISFATTR.JOBCL.JOBRC
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	JRNL	JC	ISFATTR.JOBCL.JOURNAL
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	LOG	JC	ISFATTR.JOBCL.LOG
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	MAX-TIME	JC	ISFATTR.JOBCL.TIME
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	MC	JC	ISFATTR.JOBCL.MSGCLASS
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	MODE	JC	ISFATTR.JOBCL.MODE
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	MSGLV	JC	ISFATTR.JOBCL.MSGLEVEL



Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDS Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	ODISP	JC	ISFATTR.JOBCL.ODISP
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	OUT	JC	ISFATTR.JOBCL.OUTPUT
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	PGN	JC	ISFATTR.JOBCL.PGN
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	PGNM	JC	ISFATTR.JOBCL.PGMRNAME
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	PROMORT	JC	ISFATTR.JOBCL.PROMORATE
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	QHLD	JC	ISFATTR.JOBCL.QHELD
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	REGION	JC	ISFATTR.JOBCL.REGION
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	RST	JC	ISFATTR.JOBCL.RESTART
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	SCHEDULING-ENV	JC	ISFATTR.JOBCL.SCHENV
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	SCN	JC	ISFATTR.JOBCL.SCAN
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	SWA	JC	ISFATTR.JOBCL.SWA
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	SYSSYM	JC	ISFATTR.JOBCL.SYSSYM
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	TP6	JC	ISFATTR.JOBCL.TYPE6
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	TP26	JC	ISFATTR.JOBCL.TYPE26
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	UJP	JC	ISFATTR.JOBCL.IEFUJP
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	USO	JC	ISFATTR.JOBCL.IEFUSO
<b>jesx.MODIFY.JOBCLASS</b>	CONTROL	\$T	XBM	JC	ISFATTR.JOBCL.XBM
<b>jesx.MODIFY.L</b>	CONTROL	\$T	LINE-LIMIT	LI NC	ISFATTR.SELECT.LIM
<b>jesx.MODIFY.L</b>	CONTROL	\$T	PAGE-LIMIT	LI NC	ISFATTR.SELECT.PLM
<b>jesx.MODIFY.L</b>	CONTROL	\$T	SODSP	LI NC	ISFATTR.SELECT.OUTDISP
<b>jesx.MODIFY.L</b>	CONTROL	\$T	WORK-SELECTION	LI NC	ISFATTR.PROPTS.WS
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	ADISC	LI	ISFATTR.LINE.AUTODISC
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	ANODE	NC	ISFATTR.NETOPTS.NODE
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	CONNECT	NC	ISFATTR.NETOPTS.CONNECT
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	CONN-INT	NC	ISFATTR.NETOPTS.CTIME
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	CODE	LI	ISFATTR.LINE.CODE
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	COMP	LI	ISFATTR.LINE.COMPRESS
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	CONNECT	LI	ISFATTR.NETOPTS.CONNECT
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	CONN-INT	LI	ISFATTR.NETOPTS.CTIME
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	CTR	LI NC	ISFATTR.PROPTS.CTRACE
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	DUPLEX	LI	ISFATTR.LINE.DUPLEX
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	INTF	LI	ISFATTR.LINE.INTERFACE
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	JRNUM	LI	ISFATTR.LINE.JRNUM
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	JTNUM	LI	ISFATTR.LINE.JTNUM

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	JTR	LI NC	ISFATTR.PROPTS.JTRACE
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	LINECCHR	LI	ISFATTR.LINE.LINECCHR
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	LOG	LI	ISFATTR.LINE.LOG
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	REST	LI	ISFATTR.LINE.REST
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	RESTART	LI	ISFATTR.PROPTS.RESTART
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	REST-INT	LI	ISFATTR.PROPTS.RTIME
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	SPEED	LI	ISFATTR.LINE.SPEED
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	SRNUM	LI	ISFATTR.LINE.SRNUM
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	STNUM	LI	ISFATTR.LINE.STNUM
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	TR	LI NC	ISFATTR.PROPTS.TRACE
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	TRANSP	LI	ISFATTR.LINE. TRANSPARENCY
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	UNIT	LI	ISFATTR.PROPTS.UNIT
<b>jesx.MODIFY.LINE</b>	CONTROL	\$T	VTR	LI NC	ISFATTR.PROPTS.VTRACE
<b>jesx.MODIFY.LOGON</b>	CONTROL	\$T	APPL	NS	ISFATTR.NETOPTS.APPL
<b>jesx.MODIFY.LOGON</b>	CONTROL	\$T	LOG	NS	ISFATTR.NETOPTS.LOG
<b>jesx.MODIFY.LOGON</b>	CONTROL	\$T	PASSWORD	NS	ISFATTR.LOGON.PASSWORD
<b>jesx.MODIFY.LOGON</b>	CONTROL	\$T	RESTART	NS	ISFATTR.PROPTS.RESTART
<b>jesx.MODIFY.LOGON</b>	CONTROL	\$T	RESTART-INT	NS	ISFATTR.PROPTS.RTIME
<b>jesx.MODIFY.LOGON</b>	CONTROL	\$T	TR	NS	ISFATTR.PROPTS.TRACE
<b>jesx.MODIFY.MASDEF</b>	CONTROL	\$T	CKPTHOLD	MAS	ISFATTR.MEMBER.CKPTHOLD
<b>jesx.MODIFY.MASDEF</b>	CONTROL	\$T	DORMANCY	MAS	ISFATTR.MEMBER.DORMANCY
<b>jesx.MODIFY.MASDEF</b>	CONTROL	\$T	SYNCTOL	MAS	ISFATTR.MEMBER.SYNCTOL
<b>jesx.MODIFY.NETSRV</b>	CONTROL	\$T	CTR	NS	ISFATTR.PROPTS.CTRACE
<b>jesx.MODIFY.NETSRV</b>	CONTROL	\$T	JTR	NS	ISFATTR.PROPTS.JTRACE
<b>jesx.MODIFY.NETSRV</b>	CONTROL	\$T	NSECURE	NS	ISFATTR.NETOPTS.NSECURE
<b>jesx.MODIFY.NETSRV</b>	CONTROL	\$T	RESTART	NS	ISFATTR.PROPTS.RESTART
<b>jesx.MODIFY.NETSRV</b>	CONTROL	\$T	RESTART-INT	NS	ISFATTR.PROPTS.RTIME
<b>jesx.MODIFY.NETSRV</b>	CONTROL	\$T	SOCKET	NS	ISFATTR.NETOPTS.SOCKET
<b>jesx.MODIFY.NETSRV</b>	CONTROL	\$T	STACK	NS	ISFATTR.NETOPTS.STACK
<b>jesx.MODIFY.NETSRV</b>	CONTROL	\$T	TR	NS	ISFATTR.PROPTS.TRACE
<b>jesx.MODIFY.NETSRV</b>	CONTROL	\$T	VTR	NS	ISFATTR.PROPTS.VTRACE
<b>jesx.MODIFY.NETSERV</b>	CONTROL	*F	CTR	NS	ISFATTR.PROPTS.CTRACE
<b>jesx.MODIFY.NETSERV</b>	UPDATE	*F	IPNAME	NS	ISFATTR.NETOPTS.HOSTNAME

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDS Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.MODIFY.NETSERV</b>	UPDATE	*F	JTR	NS	ISFATTR.PROPTS.JTRACE
<b>jesx.MODIFY.NETSERV</b>	UPDATE	*F	PORT	NS	ISFATTR.NETOPTS.PORT
<b>jesx.MODIFY.NETSERV</b>	UPDATE	*F	SOCKET	NS	ISFATTR.NETOPTS.SOCKET
<b>jesx.MODIFY.NETSERV</b>	UPDATE	*F	STACK	NS	ISFATTR.NETOPTS.STACK
<b>jesx.MODIFY.NETSERV</b>	UPDATE	*F	TR	NS	ISFATTR.PROPTS.VTRACE
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	HOLD	NO	ISFATTR.NODE.HOLD
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	JRNUM	NO	ISFATTR.NODE.JRNUM
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	JTNUM	NO	ISFATTR.NODE.JTNUM
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	NHOLD	NO	ISFATTR.NODE.NETHOLD
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	MAXRETRIES	NO	ISFATTR.NODE.MAXRETR
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	PARTNAME	NO	ISFATTR.NODE.PARTNAM
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	PATH	NO	ISFATTR.NODE.PATH
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	PRTDEF	NO	ISFATTR.NODE.PRTDEF
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	PRTTSO	NO	ISFATTR.NODE.PRTTSO
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	PRTXWTR	NO	ISFATTR.NODE.PRTXWTR
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	PTYPE	NO	ISFATTR.NODE.PTYPE
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	PUNDEF	NO	ISFATTR.NODE.PUNDEF
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	PWCNTL	NO	ISFATTR.NODE.PWCNTL
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	SECURE	NO	ISFATTR.NODE.SECURE
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	SRNUM	NO	ISFATTR.NODE.SRNUM
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	SSIGNON	NO	ISFATTR.NODE.SSIGNON
<b>jesx.MODIFY.NJE</b>	UPDATE	*F	STNUM	NO	ISFATTR.NODE.STNUM
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	AUTHORITY	NO	ISFATTR.NODE.AUTHORITY
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	CONNECT	NO	ISFATTR.NETOPTS.CONNECT
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	CONN-INT	NO	ISFATTR.NETOPTS.CTIME
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	CP	NO	ISFATTR.NODE.COMPACT
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	DIRECT	NO	ISFATTR.NODE.DIRECT
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	END	NO	ISFATTR.NODE.ENDNODE
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	HOLD	NO	ISFATTR.NODE.HOLD
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	LINE	NO	ISFATTR.NODE.LINE
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	LOGMODE	NO	ISFATTR.NODE.LOGMODE
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	NODENAME	NO	ISFATTR.NODE.LOGON
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	NETSRV	NO	ISFATTR.NODE.NETSRV
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	PEN	NO	ISFATTR.NODE.PENCRYPT
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	PMG	NO	ISFATTR.NODE.PATHMGR

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	PRV	NO	ISFATTR.NODE.PRIVATE
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	RECV	NO	ISFATTR.NODE.RECEIVE
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	REST	NO	ISFATTR.NODE.REST
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	SENDP	NO	ISFATTR.NODE.SENDP
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	SENTRS	NO	ISFATTR.NODE.SENTREST
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	SSIGNON	NO	ISFATTR.NODE.SSIGNON
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	SUBNET	NO	ISFATTR.NODE.SUBNET
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	TR	NO	ISFATTR.NODE.TRACE
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	TRANS	NO	ISFATTR.NODE.TRANSMIT
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	VERIFYFP	NO	ISFATTR.NODE.VERIFYFP
<b>jesx.MODIFY.NODE</b>	CONTROL	\$T	VFYPATH	NO	ISFATTR.NODE.VFYPATH
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	LINE-LIMIT	SO	ISFATTR.SELECT.LIM
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MBURST	SO	ISFATTR.MODIFY.BURST
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MCLASS	SO	ISFATTR.MODIFY.CLASS
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MDEST	SO	ISFATTR.MODIFY.DEST
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MFCB	SO	ISFATTR.MODIFY.FCB
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MFLH	SO	ISFATTR.MODIFY.FLASH
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MFORMS	SO	ISFATTR.MODIFY.FORMS
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MHOLD	SO	ISFATTR.MODIFY.HOLD
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MODSP	SO	ISFATTR.MODIFY.ODISP
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MPRMODE	SO	ISFATTR.MODIFY.PRMODE
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MSAFF	SO	ISFATTR.MODIFY.SYSAFF
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MUCS	SO	ISFATTR.MODIFY.UCS
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	MWRITER	SO	ISFATTR.MODIFY.WRITER
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	NOTIFY	SO	ISFATTR.OFFLOAD.NOTIFY
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	PAGE-LIMIT	SO	ISFATTR.SELECT.PLIM
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SBURST	SO	ISFATTR.SELECT.BURST
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SCLASS	SO	ISFATTR.SELECT.CLASS
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SCLASS1-8	SO	ISFATTR.SELECT.CLASS
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SDEST1	SO	ISFATTR.SELECT.DEST
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SDISP	SO	ISFATTR.SELECT.DISP
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SRANGE	SO	ISFATTR.SELECT.RANGE
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SFCB	SO	ISFATTR.SELECT.FCB
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SFLH	SO	ISFATTR.SELECT.FLASH
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SFORMS	SO	ISFATTR.SELECT.FORMS

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SHOLD	SO	ISFATTR.SELECT.HOLD
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SJOBNAME	SO	ISFATTR.SELECT.JOBNAME
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SODSP	SO	ISFATTR.SELECT.ODISP
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SOWNER	SO	ISFATTR.SELECT.OWNER
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SPRMODE1	SO	ISFATTR.SELECT.PRMODE
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SSAFF	SO	ISFATTR.SELECT.SYSAFF
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SSCHEDULING-ENV	SO	ISFATTR.SELECT.SCHENV
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SSRVCLASS	SO	ISFATTR.SELECT.SRVCLS
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SUCS	SO	ISFATTR.SELECT.UCS
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SVOL	SO	ISFATTR.SELECT.VOL
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	SWRITER	SO	ISFATTR.SELECT.WRITER
<b>jesx.MODIFY.OFF</b>	CONTROL	\$T	WORK-SELECTION	SO	ISFATTR.PROPTS.WS
<b>jesx.MODIFY.OFFLOAD</b>	CONTROL	\$T	ARCHIVE	SO	ISFATTR.OFFLOAD.ARCHIVE
<b>jesx.MODIFY.OFFLOAD</b>	CONTROL	\$T	CRTIME	SO	ISFATTR.OFFLOAD.CRTIME
<b>jesx.MODIFY.OFFLOAD</b>	CONTROL	\$T	DSNAME	SO	ISFATTR.OFFLOAD.DATASET
<b>jesx.MODIFY.OFFLOAD</b>	CONTROL	\$T	LABEL	SO	ISFATTR.OFFLOAD.LABEL
<b>jesx.MODIFY.OFFLOAD</b>	CONTROL	\$T	PROT	SO	ISFATTR.OFFLOAD.PROTECT
<b>jesx.MODIFY.OFFLOAD</b>	CONTROL	\$T	RTPD	SO	ISFATTR.OFFLOAD.RETENT
<b>jesx.MODIFY.OFFLOAD</b>	CONTROL	\$T	UNIT	SO	ISFATTR.PROPTS.UNIT
<b>jesx.MODIFY.OFFLOAD</b>	CONTROL	\$T	VALIDATE	SO	ISFATTR.OFFLOAD.VALIDATE
<b>jesx.MODIFY.Q</b>	UPDATE	*F	MINPCT	SP	ISFATTR.SPOOL.MINPCT
<b>jesx.MODIFY.Q</b>	UPDATE	*F	OVERFNAM	SP	ISFATTR.SPOOL.OVFNAME
<b>jesx.MODIFY.Q</b>	UPDATE	*F	PARTNAME	SP	ISFATTR.SPOOL.PARTNAME
<b>jesx.MODIFY.SOCKET</b>	CONTROL	\$T	ANODE	NC	ISFATTR.NETOPTS.NODE
<b>jesx.MODIFY.SOCKET</b>	CONTROL	\$T	CONNECT	NC	ISFATTR.NETOPTS.CONNECT
<b>jesx.MODIFY.SOCKET</b>	CONTROL	\$T	CONN-INT	NC	ISFATTR.NETOPTS.CTIME
<b>jesx.MODIFY.SOCKET</b>	UPDATE	*F	CTR	NC	ISFATTR.PROPTS.CTRACE
<b>jesx.MODIFY.SOCKET</b>	CONTROL	\$T	IPNAME	NS	ISFATTR.NETOPTS.IPNAME
<b>jesx.MODIFY.SOCKET</b>	CONTROL	\$T	IPNAME	NC	ISFATTR.NETOPTS.IPNAME
<b>jesx.MODIFY.SOCKET</b>	UPDATE	*F	IPNAME	NC	ISFATTR.NETOPTS.IPNAME
<b>jesx.MODIFY.SOCKET</b>	UPDATE	*F	JTR	NC	ISFATTR.PROPTS.JTRACE
<b>jesx.MODIFY.SOCKET</b>	CONTROL	\$T	LINE	NC	ISFATTR.NODE.LINE
<b>jesx.MODIFY.SOCKET</b>	CONTROL	\$T	NETSRV	NC	ISFATTR.NETOPTS.NETSRV
<b>jesx.MODIFY.SOCKET</b>	CONTROL	\$T	PORT	NC NS	ISFATTR.NETOPTS.PORT

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.MODIFY.SOCKET</b>	UPDATE	*F	PORT	NC	ISFATTR.NETOPTS.PORT
<b>jesx.MODIFY.SOCKET</b>	CONTROL	\$T	REST	NC	ISFATTR.LINE.REST
<b>jesx.MODIFY.SOCKET</b>	CONTROL	*F	SRVNAME	NC	ISFATTR.NETOPTS.NETSRV
<b>jesx.MODIFY.SOCKET</b>	UPDATE	*F	VTR	NC	ISFATTR.PROPTS.VTRACE
<b>jesx.MODIFY.SPOOL</b>	CONTROL	\$T	RES	SP	ISFATTR.SPOOL.SYSAFF
<b>jesx.MODIFY.SPOOL</b>	CONTROL	\$T	SAFF	SP	ISFATTR.SPOOL.RESERVED
<b>jesx.MODIFY.U</b>	UPDATE	*F	BURST	JDS	ISFATTR.OUTPUT.BURST
<b>jesx.MODIFY.U</b>	UPDATE	*F	C	JDS	ISFATTR.OUTPUT.CLASS
<b>jesx.MODIFY.U</b>	UPDATE	*F	CC	JDS	ISFATTR.OUTPUT.COPYCNT
<b>jesx.MODIFY.U</b>	UPDATE	*F	CHARS	JDS	ISFATTR.OUTPUT.CHARS
<b>jesx.MODIFY.U</b>	UPDATE	*F	CPYMOD	JDS	ISFATTR.OUTPUT.COPYMOD
<b>jesx.MODIFY.U</b>	UPDATE	*F	CPYMOD	JO	ISFATTR.PRTOPTS.COPYMOD
<b>jesx.MODIFY.U</b>	UPDATE	*F	DEST	JDS	ISFATTR.OUTPUT.DEST
<b>jesx.MODIFY.U</b>	UPDATE	*F	FCB	JDS	ISFATTR.OUTPUT.FCB
<b>jesx.MODIFY.U</b>	UPDATE	*F	FLASH	JDS	ISFATTR.OUTPUT.FLASH
<b>jesx.MODIFY.U</b>	UPDATE	*F	FORMS	JDS	ISFATTR.OUTPUT.FORMS
<b>jesx.MODIFY.U</b>	UPDATE	*F	PRMODE	JDS	ISFATTR.OUTPUT.PRMODE
<b>jesx.MODIFY.U</b>	UPDATE	*F	UCS	JDS	ISFATTR.OUTPUT.UCS
<b>jesx.MODIFY.W</b>	UPDATE	*F	DGRPY	PR PUN	ISFATTR.PROPTS.DGRPY
<b>jesx.MODIFY.W</b>	UPDATE	*F	DYN	PR PUN	ISFATTR.PROPTS.DYN
<b>jesx.MODIFY.W</b>	UPDATE	*F	OPLOG	PR	ISFATTR.PROPTS.OPACTLOG
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	B	PUN	ISFATTR.PROPTS.BPAGE
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	CHAR1	PR	ISFATTR.PROPTS.CHAR
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	CKPTPAGE	PR	ISFATTR.PROPTS.CKPTPAGE
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	CKPTSEC	PR	ISFATTR.PROPTS.CKPTSEC
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	COPIES	PR PUN	ISFATTR.PROPTS.COPIES
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	COPYMARK	PR	ISFATTR.PROPTS.COPYMARK
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	LINE-LIM-HI	PR PUN	ISFATTR.SELECT.LIM
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	LINE-LIM-LO	PR PUN	ISFATTR.SELECT.LIM
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	NPRO	PR	ISFATTR.PROPTS.NPRO

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	PAGE-LIM-HI	PR	ISFATTR.SELECT.PLIM
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	PAGE-LIM-LO	PR	ISFATTR.SELECT.PLIM
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	SCLASS	PR PUN	ISFATTR.SELECT.CLASS
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	SEPDS	PR PUN	ISFATTR.PROPTS.SEPDS
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	SFCB	PR	ISFATTR.SELECT.FCB
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	SFLH	PR	ISFATTR.SELECT.FLASH
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	SFORMS	PR PUN	ISFATTR.SELECT.FORMS
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	SPRMODE1	PR	ISFATTR.SELECT.PRMODE
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R. See note 3.	SUCS	PR	ISFATTR.SELECT.UCS
<b>jesx.RESTART.DEV.device</b>	UPDATE	*R	WORK-SELECTION	PR PUN	ISFATTR.PROPTS.WS
<b>jesx.ROUTE.JOBOUT</b>	UPDATE	\$R	EXECNODE	I ST	ISFATTR.JOB.EXECNODE
<b>jesx.ROUTE.JOBOUT</b>	UPDATE	\$R	PRTDEST	I ST	ISFATTR.JOB.PRTDEST
<b>jesx.START.DEV.device</b>	UPDATE	*S	B	PR PUN	ISFATTR.PROPTS.BPAGE
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	CHAR1	PR	ISFATTR.PROPTS.CHAR
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	CB	PR	ISFATTR.PROPTS.CB
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	CKPTPAGE	PR	ISFATTR.PROPTS.CKPTPAGE
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	CKPTSEC	PR	ISFATTR.PROPTS.CKPTSEC
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	COPIES	PR PUN	ISFATTR.PROPTS.COPIES
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	COPYMARK	PR	ISFATTR.PROPTS.COPYMARK
<b>jesx.START.DEV.device</b>	UPDATE	*S	CPYMOD	PR	ISFATTR.PROPTS.COPYMOD
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	LINE-LIM-HI	PR PUN	ISFATTR.SELECT.LIM
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	LINE-LIM-LO	PR PUN	ISFATTR.SELECT.LIM
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	NPRO	PR	ISFATTR.PROPTS.NPRO
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	PAGE-LIM-HI	PR PUN	ISFATTR.SELECT.PLIM

Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDS Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	PAGE-LIM-LO	PR PUN	ISFATTR.SELECT.PLIM
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	SBURST	PR	ISFATTR.SELECT.BURST
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	SCLASS	PR PUN	ISFATTR.SELECT.CLASS
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	SEPDS	PUN	ISFATTR.PROPTS.SEPDS
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	SFCB	PR	ISFATTR.SELECT.FCB
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	SFLH	PR	ISFATTR.SELECT.FLASH
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	SFORMS	PR PUN	ISFATTR.SELECT.FORMS
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	SPRMODE1	PR PUN	ISFATTR.SELECT.PRMODE
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	SUCS	PR	ISFATTR.SELECT.UCS
<b>jesx.START.DEV.device</b>	UPDATE	*S. See note 3.	WORK-SELECTION	PUN	ISFATTR.PROPTS.WS
<b>jesx.START.NET</b>	CONTROL	\$S	APPLID	LI	ISFATTR.LINE.APPLID
<b>MVS.MODIFY.STC. hcproc.hcstcid</b>	UPDATE	MODIFY	CATEGORY	CK	ISFATTR.CHECK.CATEGORY
<b>MVS.MODIFY.STC. hcproc.hcstcid</b>	UPDATE	MODIFY	DEBUG	CK	ISFATTR.CHECK.DEBUG
<b>MVS.MODIFY.STC. hcproc.hcstcid</b>	UPDATE	MODIFY	EINTERVAL	CK	ISFATTR.CHECK.EINTERVAL
<b>MVS.MODIFY.STC. hcproc.hcstcid</b>	UPDATE	MODIFY	INTERVAL	CK	ISFATTR.CHECK.INTERVAL
<b>MVS.MODIFY.STC. hcproc.hcstcid</b>	UPDATE	MODIFY	REXXHLQ	CK	ISFATTR.CHECK.REXXHLQ
<b>MVS.MODIFY.STC. hcproc.hcstcid</b>	UPDATE	MODIFY	PARAMETERS	CK	ISFATTR.CHECK.PARM
<b>MVS.MODIFY.STC. hcproc.hcstcid</b>	UPDATE	MODIFY	SEVERITY	CK	ISFATTR.CHECK.SEVERITY
<b>MVS.MODIFY.STC. hcproc.hcstcid</b>	UPDATE	MODIFY	USERDATE	CK	ISFATTR.CHECK.USERDATE
<b>MVS.MODIFY.STC. hcproc.hcstcid</b>	UPDATE	MODIFY	VERBOSE	CK	ISFATTR.CHECK.VERBOSE
<b>MVS.MODIFY.STC. hcproc.hcstcid</b>	UPDATE	MODIFY	WTOTYPE	CK	ISFATTR.CHECK.WTOTYPE
<b>MVS.MODIFY.WLM</b>	UPDATE	MODIFY	System	RES	ISFATTR.RESOURCE.system
<b>MVS.RESET</b>	UPDATE	RESET	PGN	DA	ISFATTR.JOB.PGN



Table 152. Overtypable Fields Sorted by OPERCMDS Resource Name.

The variable **jesx** should be replaced by the name of the targeted JES subsystem.

Replace **hcproc** and **hcstcid** with the IBM Health Checker for z/OS procedure name and started task ID.

Resources apply to the JES indicated by the command in the MVS/JES Command column: the \$ command character indicates a JES2 command and the \* command character indicates a JES3 command.

(continued)

OPERCMDs Resource Name	Required Access	MVS/JES Command	Overtypable Field	SDSF Panel	SDSF Resource Name (UPDATE Authority Required)
<b>MVS.RESET</b>	UPDATE	RESET	QUIESCE	DA	ISFATTR.JOB.QUIESCE
<b>MVS.RESET</b>	UPDATE	RESET	SRVCLASS	DA	ISFATTR.JOB.SRVCLASS
<b>MVS.ROUTE</b>	READ	RO	Any, when the system is other than the one the user is logged on to	DA INIT MAS PR	

Notes on Table 152 on page 316:

1. SDSF uses the subsystem interface (SSI) when you overtype the C (JES output class) or DEST (JES print destination name) on the JDS panel. You can change the class or destination without releasing the output. In order to release output when the JESSPOOL class is enabled, the user must have ALTER authority to the JESSPOOL resource. This authority is implied for the JESSPOOL resources created by the user.
2. The SAF resource varies with the JES2 resource. See “JES2 resources” on page 331.
3. In a JES3 environment, the command issued and OPERCMDS resource depend on the action character that is used with the overtype. See Table 151 on page 315.

## Access authority

Multiple OPERCMDS class resources are often provided for the same overtypeable field, but they are for different panels. You choose the OPERCMDS resource that you need according to the panels you are protecting. In the table, *jesx* should be replaced by the name of the targeted JES subsystem.

## JES2 resources

The following table shows the SAF resources in the OPERCMDS class for the JES2 resources displayed on the RM panel.

Table 153. OPERCMDS Resources That Protect Overtyping JES2 Resources

JES2 Resource	OPERCMDs Resource	Required Access
<b>BERT</b>	<i>jesx</i> .MODIFY.CKPTSPACE	CONTROL
<b>BSCB</b>	<i>jesx</i> .MODIFY.TPDEF	CONTROL
<b>BUFX</b>	<i>jesx</i> .MODIFY.BUFDEF	CONTROL
<b>CKVR</b>	<i>jesx</i> .MODIFY.CKPTDEF	CONTROL
<b>CMBS</b>	<i>jesx</i> .MODIFY.CONDEF	CONTROL
<b>CMDS</b>	<i>jesx</i> .MODIFY.CONDEF	CONTROL
<b>ICES</b>	<i>jesx</i> .MODIFY.TPDEF	CONTROL
<b>JNUM</b>	<i>jesx</i> .MODIFY.JOBDEF	CONTROL
<b>JOES</b>	<i>jesx</i> .MODIFY.OUTDEF	CONTROL

Table 153. OPERCMDS Resources That Protect Overtyping JES2 Resources (continued)

JES2 Resource	OPERCMDS Resource	Required Access
JQES	jesx.MODIFY.JOBDEF	CONTROL
LBUF	jesx.MODIFY.BUFDEF	CONTROL
NHBS	jesx.MODIFY.NJEDEF	CONTROL
SMFB	jesx.MODIFY.SMFDEF	CONTROL
TBUF	Not applicable	
TGS	jesx.MODIFY.SPOOLDEF	CONTROL
TTAB	jesx.MODIFY.TRACEDEF	CONTROL
VTMB	jesx.MODIFY.TPDEF	CONTROL
ZJC	jesx.MODIFY.GRPDEF	CONTROL

## Page data sets

### Protecting page data sets

Protect page data sets by defining resource names in the SDSF class. The resources are shown in [Table 154 on page 332](#).

Table 154. SAF Resources for Page Data Sets

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFPAG.datasetname	SDSF	READ
DC	ISFPAG.datasetname	SDSF	READ
DD	ISFPAG.datasetname	SDSF	READ
DL	ISFPAG.datasetname	SDSF	READ
DP	ISFPAG.datasetname	SDSF	READ
DS	ISFPAG.datasetname	SDSF	READ

To control access to the PAG panel, protect the PAG command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting page data sets

To protect all page data sets and permit a user to control them, define a generic profile as follows:

```
REDEFINE SDSF ISFPAG.** UACC(NONE)
PERMIT ISFPAG.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## PARMLIB data sets

### Protecting PARM data sets

Protect PARM data sets by defining resource names in the SDSF class. The resources are shown in [Table 155 on page 333](#).

Table 155. SAF Resources for PARM Data Sets

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>D</b>	ISFPARM. <i>datasetname</i>	SDSF	READ
<b>DE</b>	ISFPARM. <i>datasetname</i>	SDSF	READ

To control access to the PARM panel, protect the PARM command. This is described in [“Authorized SDSF commands”](#) on page 261.

## Example of protecting PARM data sets

To protect all PARM data sets and permit a user to control them, define a generic profile as follows:

```
REDEFINE SDSF ISFPARM.** UACC(NONE)
PERMIT ISFPARM.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Printers

You can protect the printers displayed on the PR panel.

Authority to access the job on the printer is not checked.

## Protecting printers

Protect printers by defining resource names in the WRITER class. The resources are shown in [Table 156](#) on page 333.

Table 156. Authority Required to Printer Resources for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
<b>D action character</b>	<i>jesx.LOCAL.device-name</i> for local printers <i>jesx.RJE.device-name</i> for remote printers	WRITER	READ
<b>C action character</b>	<i>jesx.LOCAL.device-name</i> for local printers <i>jesx.RJE.device-name</i> for remote printers	WRITER	ALTER
<b>K action character, FSSName overtype</b>	<i>jesx.LOCAL.device-name</i> <i>jesx.RJE.device-name</i>	WRITER	CONTROL
<b>All others</b>	<i>jesx.LOCAL.device-name</i> for local printers <i>jesx.RJE.device-name</i> for remote printers	WRITER	CONTROL

In the table,

***jesx***

is the name of the JES subsystem the printer is on.

***device-name***

is the name of the printer.

To protect the MVS and JES commands generated by action characters or overtypes, see [“Tables of action characters”](#) on page 229 and [“Tables of overtypeable fields”](#) on page 293.

To control access to the PR panel, protect the PR command. This is described in [“Authorized SDSF commands”](#) on page 261.

# Permitting access only while using SDSF

Users can be conditionally permitted to access the WRITER class resources so that they only can access printers through SDSF. See [“Using conditional access” on page 222](#) for more information.

## Examples of protecting printers

In the following examples, *jesx* is the name of the JES subsystem. For example, it might be *JES2*, *JESA*, or to protect all JES subsystems, *JES%*.

1. To protect all printers and punches, issue the following commands:

```
RDEFINE WRITER jesx.* UACC(READ)
PERMIT jesx.* CLASS(WRITER) ID(userid or groupid) ACCESS(ALTER)
```

2. To restrict printers to only be used through SDSF, issue the following command:

```
PERMIT jesx.* CLASS(WRITER) ID(userid or groupid) ACCESS(ALTER)
WHEN(CONSOLE(SDSF))
```

You must have the CONSOLE class active, the SDSF console defined in the console class, and the user authorized to use the SDSF console through the CONSOLE class, as follows:

```
SETROPTS CLASSACT(CONSOLE)
RDEFINE CONSOLE SDSF UACC(NONE)
PERMIT SDSF CLASS(CONSOLE) ID(userid or groupid) ACCESS(READ)
```

## Processes (z/OS UNIX System Services)

You can protect the z/OS UNIX System Services (z/OS UNIX) processes displayed on the PS panel.

### Protecting processes

Protect processes by defining resource names in the SDSF class. The resources are shown in [Table 167 on page 340](#).

Table 157. Authority Required to z/OS UNIX Processes for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
D action character	ISFPROC. <i>owner.jobname</i>	SDSF	READ
All others	ISFPROC. <i>owner.jobname</i>	SDSF	ALTER

In the table,

***owner***

is the owner of the z/OS UNIX process.

***jobname***

is the jobname of the z/OS UNIX process.

To protect the MVS and JES commands generated, see [“Tables of action characters” on page 229](#).

To control access to the PS panel, protect the PS command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting processes

To protect all processes issue the following commands:

```
RDEFINE SDSF ISFPROC.** UACC(NONE)
PERMIT ISFPROC.** CLASS(SDSF) ID(userid or groupid)
ACCESS(ALTER)
```

## Proclibs

### Protecting proclibs

Protect Proclibs by defining resource names in the SDSF class. The resources are shown in [Table 158 on page 335](#).

Table 158. SAF Resources for Proclibs

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>D</b>	ISFPLIB. <i>proclib-name</i>	SDSF	READ
<b>DD</b>	ISFPLIB. <i>proclib-name</i>	SDSF	READ

To control access to the PROC panel, protect the PROC command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting proclibs

To protect Proclibs and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFPLIB.** UACC(NONE)
PERMIT ISFPLIB.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Punches

You can protect the punches displayed on the PUN panel.

### Protecting punches

Protect punches by defining resource names in the WRITER class. The resources are shown in [Table 159 on page 335](#).

Table 159. Authority Required to Punch Resources for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
<b>D action character</b>	<i>jesx.LOCAL.device-name</i> for local punches <i>jesx.RJE.device-name</i> for remote punches	WRITER	READ
<b>C action character</b>	<i>jesx.LOCAL.device-name</i> for local punches <i>jesx.RJE.device-name</i> for remote punches	WRITER	ALTER
<b>All others</b>	<i>jesx.LOCAL.device-name</i> for local punches <i>jesx.RJE.device-name</i> for remote punches	WRITER	CONTROL

In the table,

***jesx***

is the name of the JES subsystem.

**device-name**

is the name of the punch.

To protect the MVS and JES commands generated, see [“Tables of action characters” on page 229](#) and [“Tables of overtypeable fields” on page 293](#).

To control access to the PUN panel, protect the PUN command. This is described in [“Authorized SDSF commands” on page 261](#).

## Permitting access only while using SDSF

Users can be conditionally permitted to access the WRITER class resources so that they only can access punches through SDSF. With RACF, the user can be permitted to access the WRITER profiles using the clause `WHEN(CONSOLE(SDSF))` with the PERMIT command. See [“Using conditional access” on page 222](#) for more information.

## Example of protecting punches

To protect all punches and printers issue the following commands:

```
RDEFINE WRITER jesx.** UACC(READ)
PERMIT jesx.** CLASS(WRITER) ID(userid or groupid) ACCESS(ALTER)
```

## Readers

You can protect the readers displayed on the RDR panel.

## Protecting readers

Protect readers by defining resource names in the SDSF class. The resources are shown in [Table 160 on page 336](#).

Table 160. Authority Required to Reader Resources for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
<b>D action character</b>	ISFRDR. <i>device-name.jesx</i>	SDSF	READ
<b>C action character</b>	ISFRDR. <i>device-name.jesx</i>	SDSF	ALTER
<b>All others</b>	ISFRDR. <i>device-name.jesx</i>	SDSF	CONTROL

In the table,

**jesx**

is the name of the JES subsystem.

**device-name**

is the name of the reader.

To protect the MVS and JES commands generated, see [“Tables of action characters” on page 229](#) and [“Tables of overtypeable fields” on page 293](#).

To control access to the RDR panel, protect the RDR command. This is described in [“Authorized SDSF commands” on page 261](#).

## Example of protecting readers

To protect all readers issue the following commands:

```
RDEFINE SDSF ISFRDR.** UACC(NONE)
PERMIT ISFRDR.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
```

## Resource monitor alerts

### Protecting resource monitor alerts

Protect resource monitor alerts by defining resource names in the SDSF class. The resources are shown in Table 161 on page 337.

Table 161. SAF Resources for Resource Monitor Alerts

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>J</b>	ISFRMA.type.jesx	SDSF	READ
<b>JD</b>	ISFRMA.type.jesx	SDSF	READ
<b>JH</b>	ISFRMA.type.jesx	SDSF	READ
<b>JJ</b>	ISFRMA.type.jesx	SDSF	READ
<b>JS</b>	ISFRMA.type.jesx	SDSF	READ

To control access to the RMA panel, protect the RMA command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of protecting resource monitor alerts

To protect resource monitor alerts and permit a user to control them, define a generic profile as follows:

```
REDEFINE SDSF ISFRMA.** UACC(NONE)
PERMIT ISFRMA.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## Resources defined to WLM

You can protect the WLM resources that are displayed on the RES panel.

### Protecting WLM resources

Protect WLM resources by defining SAF resource names in the SDSF class. The SAF resources are shown in Table 162 on page 337.

Table 162. Authority Required to SAF Resources for WLM Resources

Action Character or Overtypable Field	Resource Name	Class	Access
<b>D action character</b>	ISFRES.resource.system	SDSF	READ
<b>Overtypable system</b>	ISFRES.resource.system	SDSF	ALTER

To protect the MVS commands generated by action characters or overtypable fields, see [“Tables of action characters”](#) on page 229 and [“Tables of overtypable fields”](#) on page 293.

To control access to the RES panel, protect the RES command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of protecting resources

To protect all resources and permit a user to control them, define a generic profile as follows:

```
RDEFINE SDSF ISFRES.** UACC(NONE)
PERMIT ISFRES.** CLASS(SDSF) ID(userid or groupid) ACCESS(ALTER)
```

## Scheduling environments

You can protect the WLM scheduling environments that are displayed on the SE panel.

### Protecting scheduling environments

Protect scheduling environments by defining resource names in the SDSF class. The resources are shown in [Table 163 on page 338](#).

Table 163. Authority Required to Scheduling Environment Resource for Actions

Action Character or Overtypable Field	Resource Name	Class	Access
D, R and ST action characters	ISFSE.sched-env.system	SDSF	READ

To protect the MVS command generated by the D action character, see [“Tables of action characters” on page 229](#).

To protect the R and ST action characters, protect the RES and ST commands. To control access to the SE panel, protect the SE command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting scheduling environments

To protect all scheduling environments and permit a user to control them, define a generic profile as follows:

```
RDEFINE SDSF ISFSE.** UACC(NONE)
PERMIT ISFSE.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
```

## SDSF server

The SDSF server is used to process ISFPARMS statements and to provide sysplex data on the sysplex-wide device panels (PR, INIT, PUN, RDR and so on). For more information, refer to [Chapter 3, “Using the SDSF server,” on page 73](#).

You can protect these aspects of the SDSF server:

- Reverting from ISFPARMS in statement format to ISFPARMS in assembler macro format, when the server is not available or no ISFPARMS statements are defined.
- Use of the server operator commands.

### Protecting the SDSF server

The resources related to server processing of ISFPARMS are shown in [Table 164 on page 338](#).

Table 164. Authority Required to Server Functions

Function	Resource Name	Class	Access
Reverting to ISFPARMS in assembler macro format	SERVER.NOPARM	SDSF	READ
MODIFY server,DISPLAY server command	server-name.MODIFY.DISPLAY	OPERCMDS	READ
All other server MODIFY commands	server-name.MODIFY.modify-parm	OPERCMDS	CONTROL

In the table,



**server-name**

is the name of the SDSF server specified either by the ISFPMAC macro or SDSF command.

**modify-parm**

is one of these parameters of the MODIFY command: DEBUG, DISPLAY, FOLDMSG, LOGCLASS, LOGTYPE, REFRESH, START, STOP, TRACE, TRCLASS. The MODIFY command is described in [Chapter 3, “Using the SDSF server,”](#) on page 73.

The server START and STOP commands are protected by MVS. The resources are MVS.START.STC.*server-name* and MVS.STOP.STC.*server-name*, respectively. Both are in the OPERCMDS class and require UPDATE authority.

## Examples of protecting the SDSF server

1. To allow SDSF to revert from the ISFPARMS defined with statements to the ISFPARMS defined with assembler macros, issue the following commands:

```
RDEFINE SDSF SERVER.NOPARM UACC(NONE)
PERMIT SERVER.NOPARM CLASS(SDSF) ID(userid or groupid) ACCESS(READ)
```

2. To protect use of all MODIFY command parameters for server SDSF, issue the following commands:

```
RDEFINE OPERCMDS SDSF.MODIFY.** UACC(NONE)
PERMIT SDSF.MODIFY.** CLASS(OPERCMDS) ID(userid) ACCESS(CONTROL)
```

## SMS storage groups

### Protecting SMS storage groups

Protect SMS storage groups by defining resource names in the SDSF class. The resources are shown in [Table 165 on page 339](#).

Table 165. SAF Resources for SMS Storage Groups

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>D</b>	ISFSTORGRP. <i>storagegroupname</i>	SDSF	READ
<b>DL</b>	ISFSTORGRP. <i>storagegroupname</i>	SDSF	READ
<b>VD</b>	ISFSTORGRP. <i>storagegroupname</i>	SDSF	UPDATE
<b>VDN</b>	ISFSTORGRP. <i>storagegroupname</i>	SDSF	UPDATE
<b>VE</b>	ISFSTORGRP. <i>storagegroupname</i>	SDSF	UPDATE
<b>VQ</b>	ISFSTORGRP. <i>storagegroupname</i>	SDSF	UPDATE
<b>VQN</b>	ISFSTORGRP. <i>storagegroupname</i>	SDSF	UPDATE
<b>VS</b>	ISFSTORGRP. <i>storagegroupname</i>	SDSF	UPDATE

To control access to the SMSG panel, protect the SMSG command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of protecting SMS storage groups

To protect an SMS storage group and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFSTORGRP.** UACC(NONE)
PERMIT ISFSTORGRP.** CLASS(SDSF) ID(userid) ACCESS(UPDATE)
```

## SMS volumes

### Protecting SMS volumes

Protect SMS volumes by defining resource names in the SDSF class. The resources are shown in [Table 166 on page 340](#).

Table 166. SAF Resources for SMS Volumes

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFSMSVOL.volume	SDSF	READ
DC	ISFSMSVOL.volume	SDSF	READ
DS	ISFSMSVOL.volume	SDSF	READ
DSL	ISFSMSVOL.volume	SDSF	READ
VD	ISFSMSVOL.volume	SDSF	UPDATE
VDN	ISFSMSVOL.volume	SDSF	UPDATE
VE	ISFSMSVOL.volume	SDSF	UPDATE
VQ	ISFSMSVOL.volume	SDSF	UPDATE
VQN	ISFSMSVOL.volume	SDSF	UPDATE
VS	ISFSMSVOL.volume	SDSF	UPDATE

To control access to the SMSV panel, protect the SMSV command. This is described in [“Authorized SDSF commands” on page 261](#).

### Example of protecting SMS volumes

To protect an SMS volume and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFSMSVOL.** UACC(NONE)
PERMIT ISFSMSVOL.** CLASS(SDSF) ID(userid) ACCESS(UPDATE)
```

## Spool offloaders

You can protect the offloaders displayed on the SO panel (JES2 only).

### Protecting spool offloaders

Protect spool offloaders by defining resource names in the SDSF class. The resources are shown in [Table 167 on page 340](#).

Table 167. Authority Required to Offloader Resources for Actions and Overtypes

Action Character or Overtypable Field	Resource Name	Class	Access
D action character	ISFSO.device-name.jesx	SDSF	READ
C action character	ISFSO.device-name.jesx	SDSF	ALTER
All others	ISFSO.device-name.jesx	SDSF	CONTROL

In the table,

**device-name**

is the name of the offloader, transmitter, or receiver.

**jesx**

is the name of the JES2 subsystem.

To protect the MVS and JES2 commands generated, see [“Tables of action characters” on page 229](#) and [“Tables of overtypable fields” on page 293](#).

To control access to the SO panel, protect the SO command. This is described in [“Authorized SDSF commands” on page 261](#).

## Example of protecting spool offloaders

To protect all offloaders issue the following commands:

```
RDEFINE SDSF ISFSO.** UACC(NONE)
PERMIT ISFSO.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
```

## Spool volumes

You can protect the spool volumes displayed on the SP panel.

### Protecting spool volumes

Protect spool volumes by defining resource names in the SDSF class. The resources are shown in [Table 167 on page 340](#).

Table 168. Authority Required to Spool Volume Resources for Actions and Overtypes

Action Character or Overtypable Field	Resource Name (JES2)	Class	Access
	Resource Name (JES3)		
D, DL and J action character	ISFSP.volser.jesx	SDSF	READ
	ISFSP.ddname.jesx		
	ISFSP.partitionname.jesx		
All others	ISFSP.volser.jesx	SDSF	CONTROL
	ISFSP.ddname.jesx		
	ISFSP.partitionname.jesx		

In the table,

**volser**

is the volume serial of the spool volume.

**ddname**

is the ddname.

**partitionname**

is the name of the partition.

**jesx**

is the name of the JES subsystem.

To protect the MVS and JES commands generated, see [“Tables of action characters” on page 229](#) and [“Tables of overtypable fields” on page 293](#).

To control access to the SP panel, protect the SP command. This is described in [“Authorized SDSF commands” on page 261](#).

# Example of protecting spool volumes

To protect all spool volumes issue the following commands:

```
RDEFINE SDSF ISFSP.** UACC(NONE)
PERMIT ISFSP.** CLASS(SDSF) ID(userid or groupid) ACCESS(CONTROL)
```

# Subsystems

## Protecting subsystems

Protect subsystems by defining resource names in the SDSF class. The resources are shown in [Table 169 on page 342](#).

Table 169. SAF Resources for Subsystems

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFSUBSYS.subsysname	SDSF	READ

To control access to the SSI panel, protect the SSI command. This is described in [“Authorized SDSF commands” on page 261](#).

## Example of protecting subsystems

To protect a subsystem and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFSUBSYS.** UACC(NONE)
PERMIT ISFSUBSYS.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

# System parameters

## Protecting subsystem parameters

Protect subsystem parameters by defining resource names in the SDSF class. The resources are shown in [Table 170 on page 342](#).

Table 170. SAF Resources for Subsystem Parameters

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFSYSP.name	SDSF	READ

To control access to the SYSP panel, protect the SYSP command. This is described in [“Authorized SDSF commands” on page 261](#).

## Example of protecting subsystem parameters

To protect subsystem parameters and permit a user to control them, define a generic profile as follows:

```
REDEFINE SDSF ISFSYSP.** UACC(NONE)
PERMIT ISFSYSP.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

# SYSLOG

You can control access to the SYSLOG that is displayed on the LOG panel by controlling:

- Access to the LOG command, which displays the LOG panel. This is explained in [“Authorized SDSF commands”](#) on page 261.
- Access to the JES logical log. JES, rather than SDSF, issues the SAF call to check user authorization.

Parameters of the LOG command allow users to choose the sysplex-wide OPERLOG rather than the single-system SYSLOG. For information on protecting the OPERLOG, see [“OPERLOG”](#) on page 289.

## Protecting the logical log

Protect the logical log by defining a resource name in the JESSPOOL class. The resource is shown in [Table 171 on page 343](#).

*Table 171. Authority Required for Accessing the Logical Log*

Function	Resource Name	Class	Access
<b>Access to the JES logical log</b>	<i>nodeid.+MASTER+.SYSLOG.SYSTEM.sysname</i>	JESSPOOL	READ

As an alternative to defining the JESSPOOL profiles, you can define the custom property `Security.Syslog.UseSAFRecvr` in `ISFPARMS` to force the SAF call to always succeed even when the profile is not defined. This may be useful as you migrate to using the new logical log. For more information, see [“Customized properties \(PROPLIST\)”](#) on page 54.

## System Symbol information

### Protecting system symbol information

Protect system symbol information by defining resource names in the SDSF class. The resources are shown in [Table 172 on page 343](#).

*Table 172. SAF Resources for System Symbol Information*

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>D</b>	<i>ISFSYM.symbolname.sysname</i>	SDSF	READ

To control access to the SYM panel, protect the SYM command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of protecting system symbol information

To protect all system symbol information and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFSYM.** UACC(NONE)
PERMIT ISFSYM.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## System information

### Protecting system information

Protect system information by defining resource names in the SDSF class. The resources are shown in [Table 173 on page 344](#).

Table 173. SAF Resources for System Information

Action Characters and Overtypes	Resource Name	Class	Access Required
<b>D</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DAA</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DAL</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DALO</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DB</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DC</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DCEE</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DD</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DEM</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DG</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DI</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DIQP</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DLL</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DLO</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DLR</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DM</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DMC</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DMP</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DO</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DP</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DPCD</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DPCI</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DSF</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DSL</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DSM</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DSY</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DT</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DTO</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DTR</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DTS</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DW</b>	ISFSYS.sysplexname.systemname	SDSF	READ
<b>DX</b>	ISFSYS.sysplexname.systemname	SDSF	READ

To control access to the SYS panel, protect the SYS command. This is described in [“Authorized SDSF commands” on page 261](#).

## Example of protecting system information

To protect system information and permit a user to control it, define a generic profile as follows:

```
REDEFINE SDSF ISFSYS.** UACC(NONE)
PERMIT ISFSYS.** CLASS(SDSF) ID(userid) ACCESS(READ)
```

## System requests

You can protect the system requests displayed on the SR panel.

### Protecting system requests

Protect system requests by defining resource names in the SDSF class. The resources are shown in [Table 164 on page 338](#).

Table 174. Authority Required to System Request Resource for Action Characters

Action Character	Resource Name	Class	Access
D	ISFSR.type.system.jobname	SDSF	READ
C	ISFSR.ACTION.system.jobname	SDSF	READ
AI, R	ISFSR.REPLY.system.jobname	SDSF	READ

In the table,

**type**

is the message type, either ACTION or REPLY.

**system**

is the name of the originating system.

**jobname**

is the name of the issuing job.

To protect the MVS commands generated, see “[Tables of action characters](#)” on page 229.

To control access to the SR panel, protect the SR command. This is described in “[Authorized SDSF commands](#)” on page 261.

### Example of protecting system requests

To protect all system requests issue the following commands:

```
RDEFINE SDSF ISFSR.** UACC(NONE)
PERMIT ISFSR.** CLASS(SDSF) ID(userid or groupid) ACCESS(READ)
```

## User log (ULOG)

Users can browse the ULOG to see all system commands and responses issued during their user session, including commands generated by SDSF. If the installation activates message suppression attributes, all command responses may not be returned.

SDSF uses MVS console services to acquire an extended console for the user; all commands issued use that console identifier.

### Protecting the ULOG

You protect the ULOG by:

- Controlling access to the ULOG command when the custom property Console.EMCS.UlogAuthReq is set to TRUE. This is described in [“PROPLIST syntax”](#) on page 55 and [“Authorized SDSF commands”](#) on page 261.
- Controlling access to the extended console that SDSF acquires. The extended console is protected by a resource in the OPERCMDS class, shown in [Table 175](#) on page 346.

Table 175. Resource that Protects the Extended Console

Function	Resource Name	Class
Extended console	MVS.MCSOPER.console-name	OPERCMDS

The console name used by SDSF defaults to the user ID. When SDSF needs to activate a console and the default console name is already in use, SDSF attempts to use a modified console name, which consists of the default name plus a single-character suffix. Users can change the console name with the SET CONSOLE command.

SDSF supplies an OPERPARM with master level authority when activating the console. Since SDSF supplies the OPERPARM, the user's OPERPARM segment (defined through RACF) is ignored.

When SDSF is using an extended console and commands are issued through the / (slash) command, some subsystems (such as NetView\* and CICS\*) require the console name to be defined to the subsystem.

For more information on the console used by SDSF, see [“Issuing MVS and JES commands”](#) on page 356. For more information on protecting the extended console, see [z/OS MVS Planning: Operations](#).

## Examples of protecting ULOG

1. To activate the OPERCMDS class and define a resource for the extended console, use the following RACF commands:

```
RDEFINE OPERCMDS MVS.MCSOPER.console-name
PERMIT MVS.MCSOPER.console-name ID(userid) ACCESS(READ)
```

2. To refresh the OPERCMDS class, issue the following:

```
SETROPTS RACLIST(OPERCMDS) REFRESH
```

## XCF groups and members

### Protecting XCF groups and members

Protect XCF groups and members by defining resource names in the SDSF class. The resources are shown in [Table 176](#) on page 346.

Table 176. SAF Resources for XCF Groups and Members

Action Characters and Overtypes	Resource Name	Class	Access Required
D	ISFXCFM.membername	SDSF	READ
DA	ISFXCFM.membername	SDSF	READ
DG	ISFXCFM.membername	SDSF	READ

To control access to the XCF panel, protect the XCF command. This is described in [“Authorized SDSF commands”](#) on page 261.

### Example of protecting XCF groups and members

To protect resource monitor alerts and permit a user to control them, define a generic profile as follows:



```
REDEFINE SDSF ISFXCFM.** UACC(NONE)  
PERMIT ISFXCFM.** CLASS(SDSF) ID(userid) ACCESS(READ)
```



---

## Chapter 8. Using installation exit routines

This topic describes how to use an installation exit routine to customize your security authorization strategy.

**Note:** SDSF's support for installation exits can change. With each new release of SDSF, you should review your exit routines to ensure that they still function correctly, and make changes as necessary. For the most common uses, SDSF's installation exits have been superseded by custom properties in ISFPARMS, which are significantly easier to define and maintain. For more information, see [“Customized properties \(PROPLIST\)”](#) on page 54.

As of SDSF 2.5, only the ISFUSER initialization, termination, and pre-SAF exits are called. In addition, the exits receive control in key 4, rather than key 1 as in prior releases. If you have existing ISFUSER exit routines, these environmental changes might affect their functionality and resource use (such as the storage subpool and key for any GETMAIN or FREEMAIN operations).

**Important:** The pre-SAF exit is driven *before* the initialization exit due to the security processing logic that is used to build the user's environment prior to SDSF initialization.

---

### Installation exit routines

You can write installation exit routines for the set of installation exit points provided by SDSF. These routines can supplement the authorization you established with ISFPARMS and the SAF security interface. Your installation exit routines supply customized authorization processing for your installation and return to SDSF their authorization decisions.

The PROPLIST and PROPERTY statements provide an alternative to some of the customization available through the exit routines. For more information, see [“Customized properties \(PROPLIST\)”](#) on page 54.

### Using the ISFUSER module

You add your installation exit routines to the ISFUSER module supplied by SDSF in member ISFUSER of the ISF.SISFSRC data set. As supplied, module ISFUSER performs no authorization functions and is always present, whether you add installation exit routines or not.

Instructions for the use of module ISFUSER are contained in the module, which indicates where you should add the code to be used for each exit point. The module also has information about the function codes and registers used in the exit point interface. Note that the pre-SAF exit will be the first exit point.

ISFUSER is called and must return in 31-bit mode, key 4, and supervisor state. To install the ISFUSER module after adding installation exit routines, perform SMP/E RECEIVE and APPLY.

You cannot share the ISFUSER module across SDSF releases. Although your implementation may be the same, you must re-install your modifications on each release running SDSF.

### ISFUPRM macro

The installation exit routine can use parameters supplied in the ISFUPRM macro, which maps the user parameter area. A pointer to the user parameter area is passed to ISFUSER upon entry. The user parameter area contains such information as:

- User ID, logon procedure name, and terminal name
- User authority based on ISFGRP macro or GROUP specifications
- Prefix and group prefix information defined in ISFGRP macros or GROUP statements
- Pointers to include and exclude lists defined in ISFGRP macros or GROUP statements
- Pointers to the primary and alternate field lists defined in ISFFLD macros or FLD statements

- Pointers to destination name tables and user selected node/remote names defined in ISFNTBL macros or NTBL statements
- Trace table information
- Job information

To communicate between exits, you can establish a user data area and anchor it in field UPRUWORD. This field is passed unmodified to all exits. If you obtain storage and anchor it in UPRUWORD, you must release the storage in the termination exit.

## Installation exit points

The installation exit points within SDSF link to the ISFUSER module at entry point ISFUSER. SDSF provides the following exit points for installation routines to customize authorization:

Exit Point	Use to Control
<b>Initialization</b>	Who can use SDSF
<b>SDSF termination</b>	Termination processing
<b>Pre-SAF</b>	How the SAF authorization decision is to be made

These exit points are described in detail in the remainder of this topic. The descriptions include input, output (if any), and return codes.

Note that the following exit points are obsolete in SDSF 2.5:

Exit Point	Previously Used to Control
<b>Command Authority</b>	Which commands users can issue
<b>SYSOUT Display Authority</b>	For which jobs users can display output
<b>Post-SAF</b>	Accept or ignore result of SAF authorization
<b>SAF indeterminate</b>	Action for SAF indeterminate responses
<b>Table build</b>	What is displayed on tabular panels

## SAF considerations for exit points

For information about the SAF resources used for SDSF security, see [Chapter 7, “Protecting SDSF functions,”](#) on page 225.

As of SDSF 2.5, the Command Authority and SYSOUT Display Authority exits are no longer taken.

Use the SDSF exits for SAF calls made by SDSF. SAF calls may be made by other components; for example, JES2 makes a SAF call for a resource in the JESSPOOL class when you browse a data set. You cannot affect SAF calls made by other components with the SDSF exits.

## Initialization exit point

This exit is taken during SDSF initialization after all of the authorization parameters from ISFPARMS and the ISPF profile have been moved into the user parameter area. The initialization exit routine can control authorization to use SDSF.

The initialization exit routine also controls the source of information for the Display Active Users panel.

The initialization exit point may not be the first exit called by SDSF. In particular, security related exits such as the pre-SAF exit are called prior to the initialization exit point.

In addition, your initialization exit can set the following to B'1' to perform other functions.

**Note:** Many of these settings are also controlled through custom properties defined in ISFPRMxx. Using ISFPRMxx is the preferred method of enabling an option, rather than implementing the initialization exit.

Field	Description
<b>UPRSFLAG.UPRNORMF</b>	Derive information for the DA panel directly from MVS control blocks rather than from RMF
<b>UPRSFLAG.UPRNORMS</b>	Disable use of sysplex DA
<b>UPRCKLIM</b>	Sets the default maximum number of instances for each health check that will be read from the logstream for the CKH panel. Users can override this with the SET CKLIM command.
<b>UPRCMDLM</b>	Sets the number of system commands entered with the / command that SDSF stores. When the number is exceeded, the oldest command is removed from the list. The default is 1,000. System commands are stored only when using SDSF under ISPF.
<b>UPROFLG1.UPRO1GHO</b>	Append a generic pattern-matching character to the job specified with the H command, unless the prefix already ends with a generic character or is already the maximum length (8 characters). For example, if the user enters H GREER, this setting would result in a prefix of H GREER*.
<b>UPROFLG1.UPRO1GPF</b>	Append a generic pattern-matching character to the prefix specified with the PREFIX command, unless the prefix already ends with a generic character or is already the maximum length (8 characters). For example, if the user enters PREFIX JONES, this would result in a prefix of JONES*.
<b>UPROFLG1.UPRO1GST</b>	Append a generic pattern-matching character to the job specified with the ST command, unless the prefix already ends with a generic character or is already the maximum length (8 characters). For example, if the user enters ST GREER, this setting would result in a prefix of ST GREER*.
<b>UPROFLG1.UPRO1LNF</b>	Specifies the SAF logging option to use when a job's data sets are browsed from an SDSF panel, with the exception of the JDS panel. If the value is TRUE, the SAF logging setting is LOG=NOFAIL (rather than the default, LOG=ASIS).
<b>UPROFLG1.UPRO1SFW</b>	Controls issuing a warning message when a SAF no-decision is converted to a failure
<b>UPROFLG2.UPRO2DNL</b>	Affects normalization of the CPU% column on the DA panel. If the value is TRUE, the CPU% column is normalized using the LPAR value for CPU busy for the system. If the value is FALSE, the CPU% column is normalized with the MVS value for CPU busy for the system. The LPAR value takes into account several states related to PR/SM. The LPAR value requires RMF. If the LPAR value is not available, SDSF uses the MVS value to normalize the CPU% column. FALSE is the default.
<b>UPROFLG2.UPRO2DU8</b>	Controls how device names are formatted on the PUN panel. If the value is TRUE, the device names are shown in a shortened format. Otherwise, the name is shown with dots between subtypes.

Field	Description
<b>UPROFLG2.UPRO2DR8</b>	Controls how device names are formatted on the RDR panel. If the value is TRUE, the device names are shown in a shortened format. Otherwise, the name is shown with dots between subtypes.
<b>UPROFLG2.UPRO2NMD</b>	Disables modification of the console name when console activation fails due to the console being in use. A value of TRUE disables the function and a value of FALSE enables it. FALSE is the default.
<b>UPROFLG2.UPRO2NPS</b>	Disables point-and-shoot fields such as column titles.
<b>UPROFLG3.UPRO3NOD</b>	Controls whether duplicate SYSOUT data sets are included when you browse or print a job.
<b>UPRSFLG3.UPRS3MEM</b>	Restricts user access to jobs that have run or will run on another member in a MAS configuration
<b>UPRSFLG3.UPRS3NOF</b>	Bypasses all filtering for DA, H, I, O and ST, including include and exclude lists set in ISFPARMS
<b>UPRSFLG3.UPRS3SWP</b>	Specifies that, when browsing job data sets, SDSF should not gather data from in-core buffers if the job is swapped out. This is ignored for systems other than the one you are logged onto.
<b>UPROFLG4.UPRO4CDP</b>	Controls whether the size of the System Command Extension pop-up varies with the screen size of the emulator session.
<b>UPROFLG4.UPRO4JSM</b>	Controls scope of the SYM panel.
<b>UPRSFLG4.UPRS4NCM</b>	Disables use of communications between servers in a server group
<b>UPRSFLG5.UPRS5CSX</b>	Allows sharing of an EMCS console if it is in use but was activated in a different address space than the user. Console sharing means that commands will be issued using that console, and any responses will be directed to the ULOG for the task that has activated the console. The option to allowing sharing is effective only when console sharing is permitted. See UPRSFLAG.UPRSNOCS.
<b>UPRSFLG5.UPRS5DSI</b>	Specifies that the system SIO rate is included on the title line of the DA panel, but the system zAAP use is not.
<b>UPROFLG6.UPRO6NJM</b>	Disables use of SDSFAUX for Job Memory (JM) panel. Ignored, SDSFAUX is always used.
<b>UPROFLG6.UPRO6NJD</b>	Disables use of SDSFAUX for Job Device (JD) panel. Ignored, SDSFAUX is always used.
<b>UPROFLG6.UPRO6NMT</b>	Controls format of main menu.
<b>UPROFLG6.UPRO6INN</b>	Controls command generation on the initiator panel.
<b>UPROFLG6.UPRO6NRA</b>	Controls right alignment of values in numeric columns.
<b>UPROFLG6.UPRO6NDA</b>	Controls use of the SDSFAUX data gatherer for the DA panel.
<b>UPRSFLG6.UPRS6JS3</b>	ON if SDSF is running under JES3. <sup>1</sup>
<b>UPRS6FSY</b>	Controls the use of system symbols with filtering.
<b>UPRSSNME</b>	Contains the JES subsystem name for the JES that SDSF is running under. <sup>1</sup>

Field	Description
<b>UPXCONSF</b>	Names the list of suffixes to use when modifying the console name when the console activation fails due to the console being in use. The default is \$#@12345.

**Note:**

1. SDSF invokes other exit points prior to the initialization exit point (such as the pre-SAF call). Fields listed for the initialization exit point are not available for exit points that are invoked earlier.

## Input

- Function code (X'00') in register 0
- Address of user parameters (ISFUPRM) in register 1

## Return codes

### 00

Allows the user to use SDSF.

### Nonzero

The user is not authorized to use SDSF. Message ISF024I is issued.

## SDSF termination exit point

This exit is taken during SDSF termination prior to any data sets being closed or storage being freed.

## Input

- Function code (X'0C') in register 0
- Address of user parameters (ISFUPRM) in register 1

## Return codes

No return codes are expected from this exit.

## Pre-SAF exit point

This exit is taken prior to the call to SAF and prior to the initialization exit. It allows the installation to control how the authorization decision is to be made. It is taken only for SAF calls done by SDSF. In addition to the SAF calls done by SDSF, SAF calls may be made by other components.

## Input

- Function code (X'10') in register 0
- Address of user parameters (ISFUPRM) in register 1
- SAF class name being checked is in field UPRCLASS
- Resource name area is pointed to by UPRRSCN. The first halfword is the length of the resource name which is followed by the resource name.
- Authorization required for the resource is in field UPRATTR. The values are:
  - X'02'— READ
  - X'04'— UPDATE
  - X'08'— CONTROL
  - X'80'— ALTER

## **Return codes**

### **00**

Perform SDSF SAF call.

### **04**

Skip SDSF SAF call and allow access.

### **08**

Skip SDSF SAF call and deny access.

### **Other**

Same as return code 08, but IBM recommends that the return code be explicitly set to 08 to indicate that access is to be denied.



# Chapter 9. Installation and configuration considerations

This topic discusses special considerations for JES.

## JES3 considerations

SDSF may be invoked on either a local or global processor.

SDSF retrieves information about the JES being processed, including the JES3 global system name, during initialization. As a result, if a JES3 DSI is done to move the global system, SDSF users must re-access SDSF so that initialization can take place.

ISFPARMS must be in the statement format (parmlib member ISFPRMxx) rather than the assembler macro format. ISFPRMxx is processed by the SDSF server, which must be started. If the initial ISFPRMxx fails to activate and the server falls back to ISFPARMS, SDSF will use the default ISFPARMS regardless of any modifications you have made to ISFPARMS.

SDSF security must be provided by SAF rather than ISFPARMS.

For new SDSF function to be available, both the processor from which SDSF is invoked and the JES3 global processor must have SDSF at the level that provides the new function.

## Getting started running SDSF in the JES3 environment

The following tasks are associated with running SDSF in a JES3 environment.

Task	Reference Information
<b>Prepare ISFPRMxx. If you are beginning with an ISFPARMS in assembler macro format, convert it to statement format.</b>	<a href="#">“ISFPARMS in the JES3 environment” on page 355</a> <a href="#">“Converting ISFPARMS assembler macros to statements” on page 6</a>
<b>Start the SDSF server.</b>	<a href="#">Chapter 3, “Using the SDSF server,” on page 73</a>
<b>Implement SAF security.</b>	<a href="#">Chapter 5, “Using SAF for security,” on page 213</a>

## ISFPARMS in the JES3 environment

The statements in parmlib member ISFPRMxx are largely the same for JES2 and JES3 environments. If you have a mixed JES2 and JES3 environment, you can use a single ISFPRMxx parmlib member. When processing ISFPRMxx, SDSF ignores statements and keywords that do not apply to the current JES type, such as statements and keywords that define field lists for panels that are not supported in the JES3 environment.

A JES3NAME parameter of the OPTIONS statement allows you to specify the JES3 that is to be processed. The syntax is as follows:

JES3NAME (\*) | (JES-name)

Indicates the name of the JES3 subsystem. The name can be 1 to 4 characters. The default is \*, which requests the JES system the user is currently running under.

The details of the differences for the JES3 environment are included in the descriptions of the ISFPARMS statements in [Chapter 2, “Using ISFPARMS for customization,” on page 5](#).

You can use the SET SECTTRACE command, or the SECTTRACE parameter on the SDSF command, to view the results of all SAF calls in the ULOG.

## JES2 considerations

---

### DESTDEF considerations

The JES2 DESTDEF initialization statement controls how destination names are displayed and controlled. The values of DESTDEF control how SDSF processes destinations.

If DESTDEF SHOWUSER=WITHLOCAL is coded, then destinations of the form *local-node.userid*, which are otherwise displayed as *userid*, are displayed as *LOCAL.userid*.

If you changed the field list definitions for the PR display and you coded a default width for the destination column in the ISFFLD macro or FLD statement (that is a width of 'D'), then the length of the column will be 18 rather than 8 to accommodate the longer destination name that will be displayed.

### SDSF with a secondary JES2 subsystem

SDSF can process data from a secondary JES2 subsystem. This allows you to use SDSF for JES subsystems that you may be testing.

All SDSF functions are available when processing a secondary JES, with the following restrictions:

- The LOG command displays all SYSLOG data sets on spool. Since MVS allocates the SYSLOG data sets using the primary JES, there may be no SYSLOG data sets on the secondary spool. This may lead to no data being shown when the LOG display is accessed. However, if OPERLOG is active, the LOG command will display the log data from the OPERLOG regardless of the JES being processed.
- The C, O, and P action characters, and the C and DEST overtypes will not be available on the Job Data Set (JDS) display.

## SDSF considerations

---

SDSF does not support more than a single instance of SDSF executing under the same task control block (TCB).

SDSF makes use of 64-bit memory wherever possible. If you use the z/OS default of 2GB for all address spaces, then no action is required. If you have set a MEMLIMIT default for TSO users and batch jobs that is below 512MB, consider increasing the value to avoid any problems relating to SDSF use of 64-bit memory.

## Issuing MVS and JES commands

---

SDSF uses a console when issuing MVS or JES commands that were entered with a / command. The console used varies.

System commands are stored in the ISPF profile for use the next time that you access SDSF. To increase the number of commands that are stored, you can allocate an ISPF table data set.

### Console for issuing MVS and JES commands

SDSF uses a console when issuing MVS or JES commands that were entered with a / command. The console used varies. SDSF attempts to activate an extended console so that command responses can be returned to the user. If console activation fails, SDSF uses console ID 0 (the internal console) when issuing commands. Any command responses will appear in the SYSLOG, but will not be returned to the user.

As of SDSF 2.5, ULOG authority is no longer required to activate an extended console. The console will be activated as long as the user has READ access to the MVS.MCSOPER.consname resource in the OPERCMDS class.

Users can request that SDSF use a console ID of 0 with the *i* parameter on the / command (*i/command*). For this to be accepted, a console ID of 0 must be allowed by the setting for EMCSREQ in ISFPARMS.

Installations should control use of the / command as they would a console with master authority. For more information, see “Group function parameters reference” on page 18. For information on protecting consoles, see *z/OS MVS Planning: Operations*.

## Extended console name

The name of the extended console used by SDSF defaults to the user ID. Users can change it with the SET CONSOLE command.

When SDSF needs to activate an extended console and the default console name is in use (for example, when you invoke SDSF from a REXX exec while also using SDSF interactively) SDSF attempts to activate a new console with a different name, which is derived by modifying the default console name. To modify the name, SDSF appends a single-character suffix. SDSF can try up to 32 different characters until a unique console name is obtained. The original console name must be fewer than 8 characters for the modification to occur.

You can control console name modification with:

- The SET CONMOD (ON|OFF) command, which turns console name modification on and off.
- In ISFPARMS, the custom property Console.EMCS.ConModChars, which specifies the characters to be used as the suffix. By default, the characters are \$#@12345.
- In ISFPARMS, the custom property Console.EMCS.NoConMod, which turns console name modification off.
- In a REXX exec, with the ISFCONMOD special variable.
- In a Java program, with ISFRequestSettings.

## Storing MVS and JES commands

System commands that are entered with the slash (/) command, along with any comments and groups, are stored on exiting SDSF, so that they can be displayed and reissued in the next SDSF session. By default, they are stored in the ISPF profile. Up to 50 commands can be stored this way.

When an ISPF table data set is allocated for that purpose, SDSF can store up to 2,000 commands, depending on an option for your installation. The default is 1,000.

The 20 most recent commands are displayed in the list on the System Command Extension pop-up. The complete list is displayed with the Details function key (PF6).

The ISPF table data set must exist before using SDSF, and have these properties:

### Type

PDS or PDSE

### RECFM

FB

### LRECL

80

### Size

A good starting point is 100 blocks using a block size of 29720. The size that is required depends on the length of the commands, comments and group names, as well as the block size of the data set. The maximum size of each command entry is approximately 500 bytes. SDSF also adds header information.

If the data set runs out of space, a system abend occurs, and commands created during that session are lost. To avoid the abend, allocate the space generously and use secondary extents.

**Note:** The maximum size of a command entry may change in the future.

Once the table data set is created, it must be allocated to DDNAME ISFTABL prior to accessing SDSF. For example, if the data set is `ibmuser.sdsf.tabl`, you could use this command:

```
alloc fi(isftabl) da('ibmuser.sdsf.tabl') shr reus
```

Like the ISPF profile, the ISFTABL data set should be unique for each user. IBM does not recommend sharing the ISFTABL data set across users.

For more information about the option to control the number of commands that are stored, refer to the description of the `Command.SLASH.CommandLimit` custom property in [“Customized properties \(PROPLIST\)”](#) on page 54.

## Recovering from the system abend

### About this task

If the table data set runs out of space, a system abend occurs, and commands entered during that session are lost.

You then need to perform the following.

### Procedure

1. Exit SDSF
2. Free the table data set
3. Re-access ISPF
4. Allocate a data set with a larger size
5. Copy the contents of the original data set to the new data set, so that you don't lose any previously stored commands
6. Allocate the new data set to DDNAME ISFTABL.

## RMF considerations

The following require that RMF Monitor I be started:

- The DA panel for all columns
- LPAR, zIIP, and zAAP statistics on the DA panel
- The PAG panel
- The DEV panel

By default, Monitor I is started when you start RMF.

**Note:** When RMF Monitor I is not active or RMF is not installed, the DA panel will show a small subset of all panels.

RMF Monitor I is also needed to obtain the LPAR and zAAP views of CPU utilization displayed on the title line of the DA panel, and the values for the SzAAP% and SzIIP% columns on the DA panel.

The following requires that RMF Monitor III be started:

- The Job Delay panel (accessed with the JY action character).

RMF Monitor III can be started with an operator command similar to the following, once the RMF control session has been started:

```
F RMF,S III
```

For more information, refer to [z/OS Resource Measurement Facility User's Guide](#).

SDSF uses RMF to gather data for the DA, PAG, DEV, and job delay panels. Use of RMF is protected using resources in the FACILITY class. The following resources are required to allow SDSF to use RMF for data gathering:

Table 177. Required Resource Access for RMF-based Panels		
User	FACILITY class resource name	Required access
SDSF server (typically userid SDSF)	ERBSDS.MON2DATA	READ
SDSF users	ERBSDS.MON3DATA ERBSDS.MON3EXIT.ISFRMFXY	READ

Access to these resources is optional. However, when the server or the user does not have the required access, the RMF-based panels are not available.

## ISPF considerations

z/OS provides sample ISPF primary option menus with SDSF and other elements and features already added under option 13.14, as described in the program directory. If you want to add SDSF to your own customized ISPF menu, you should add text to the body for the SDSF menu option, for example:

```
S  SDSF          System Display and Search Facility
```

and update the ZSEL statement in the PROC section to invoke SDSF with the ISFISP entry point, as shown in the following except. The lines added for SDSF are shown in **bold**.

```
.
.
.
7,'PGM(ISPYXDR) PARM(&ZTAPPLID) SCRNAME(DTEST) NOCHECK'
8,'PANEL(ISRLPRIM) SCRNAME(LMF)'
9,'PANEL(ISRDIIS) ADDPOP'
10,'PGM(ISRSCLM) SCRNAME(SCLM) NOCHECK'
11,'PGM(ISRUDA) PARM(ISRWORK) SCRNAME(WORK)'
  S,'PANEL(ISFSDOP2) NEWAPPL(ISF) SCRNAME(SDSF)'
X,EXIT
SP,'PGM(ISPSAM) PARM(PNS)'
.
.
*, '?' )
IF (&ZCMD = 'S')
  &ZSEL = 'PGM(ISFISP) NOCHECK NEWAPPL(ISF) SCRNAME(SDSF)'
IF (&ZCMD = 'S.')
  &ZSEL = 'PGM(ISFISP) NOCHECK NEWAPPL(ISF) SCRNAME(SDSF)'
```

**Note:** The IF statements are required. Failure to include this logic may result in an incorrect number of rows being displayed on split screens, a failure to process additional options specified on the S command, or message ISF922E. The IF statements must be added after the ZSEL statement.

If you want to be able to invoke SDSF as a command from within ISPF, you can add SDSF to the ISPF command table. This can be done using the ISPF Command Table Utility accessed with ISPF option 3.9. You can define the entry to start SDSF with an initial panel, or can specify whether ISPF is to start a new session or a new instance of SDSF running in the same session.

The following examples show different types of invocations.

Example 1: SDSF is invoked as a separate session using option S. It is assumed option S has been added to the main ISPF panel.

```
Verb T Action
SDSF 0 SELECT PGM(ISPSTRT) PARM(S)
```

Example 2: SDSF is invoked as a new instance. If an SDSF environment does not exist, one is created. If an environment already exists, the current instance is suspended and a new instance is created.

Verb	T	Action
SDSF	0	SELECT PGM(ISFISP) NEWAPPL(ISF) SCRNAME(SDSF)

Example 3: SDSF is invoked as in example 2, but an optional initial command can be provided when issuing the command.

Verb	T	Action
SDSF	0	SELECT PGM(ISFISP) NEWAPPL(ISF) PARM(&ZPARM)

In this example, if the command SDSF DA is issued, SDSF is invoked and accesses the DA panel.

Example 4: SDSF is invoked as in example 2, but the H panel is accessed directly.

Verb	T	Action
SDHQ	0	SELECT PGM(ISFISP) NEWAPPL(ISF) PARM(H)

In this example, the command SDHQ invokes SDSF and accesses the H panel.

## Scrollable main menu and fallback

SDSF features a scrollable main menu with the ability to sort, filter, and hide unavailable options. You can revert to the old-style non-scrollable menu if you choose.

The old-style non-scrollable main menu is provided for compatibility with prior releases. You might require this menu if you have scripts or other automation that relies on the format. You can use the generic tracker event described below (and displayed with the SDSF GT command) to discover if the old-style menu is being used at your installation. However, you should take steps to remove dependencies on the old-style format.

### Using the MENU command

Use the **MENU** command to display the main panel. The command can be issued from an SDSF panel and will immediately redisplay the main panel.

### Forcing the use of the non-scrollable menu

You can force the use of the old style non-scrollable main panel in two ways:

- Define the **Panel.Main.DisableTable** custom property in ISFPRMxx to control use of the main panel table. The custom property is set at the group level. When set to TRUE, the old style non-scrollable panel is shown. When the old panel is used, not all options may be visible. Only those options that fit within the current screen depth are shown.
- Allocate the special ddname **ISFMIGMN**. This allows individual users to control whether the old style panel is shown. You can allocate **ISFMIGMN** at the user level.

To use the special ddname from TSO, use a command similar to the following:

```
alloc fi(isfmigmn) dummy reus
```

Batch jobs that depend on the old-style format can include the special ddname in the JCL using a statement similar to the following:

```
//ISFMIGMN DD DUMMY
```

### Generic tracker non-scrollable menu event

A non-scrollable main menu fallback generic tracker event occurs when the old style non-scrollable main menu is used. This occurs when the **ISFMIGMN** ddname is allocated to the session.



### ***action-character***

Is an action character to be applied to the tabular panel. If building the panel or applying the filters results in more than one row, or if the panel is not a tabular panel, the action character is ignored. This is valid only when ISPF is invoked from a web client.

## **Specifying that SDSF should process JES2**

By default, SDSF determines whether to process JES2 or JES3. You can specify that SDSF should not do that determination and process JES2 by invoking it with an alternate command: use ISFISP2 rather than ISFISP in the PROC section of an ISPF panel, and SDSF2 rather than SDSF in an ISPF command table.

## **z/OSMF considerations**

---

IBM® z/OS Management Facility (z/OSMF) provides a framework for managing various aspects of a z/OS system through a web browser interface. By streamlining some traditional tasks and automating others, z/OSMF can help to simplify some areas of z/OS system management.

The SDSF task of z/OSMF lets you see key summary information about your sysplex in graphical form, work with jobs and checks for IBM z/OS Health Checker, and issue system commands. It includes function that is analogous to these functions of z/OS SDSF:

- AS, DA, H, I, O, ST, Job Data Set and Output Data Set (browse) panels, for jobs and job output
- CK and Health Check History panels, for health checks
- APF, DEV, FS, LLS, LNK, LPA, SMSG, SP, NA, OMVS options (BPXO), PAG, PARM, SMSG, SMSV, SYS, CFS panels
- ULOG panel, for command and message responses issued during the current session
- Editing JCL
- Action characters for controlling jobs, devices, and checks
- Overtypable fields, for modifying the attributes of jobs and checks
- Slash (/) command, for issuing system commands
- PREFIX, DEST, OWNER, SYSNAME, FILTER and SORT commands, for filtering and sorting tabular data
- ARRANGE command, for customizing the order and widths of columns

To select the SDSF task, double-click the SDSF icon on the z/OSMF desktop.

### **Requirements**

The SDSF task requires a TSO logon proc and related settings, which you specify using the **Settings** option within the SDSF task. When you first access the SDSF task, you will be presented with the **Settings** dialog to provide those settings.

**Note:** The SDSF Settings icon on the z/OSMF desktop is no longer used.

The TSO logon proc is used to launch a TSO address space that is created on behalf of the user. For details on the settings, refer to [“Defining required settings for the SDSF task” on page 363](#).

### **Adding the SDSF task to z/OSMF**

To add the SDSF task to z/OSMF, you import a properties file through the Import Manager task of z/OSMF, which is in the z/OSMF Administration category. This process is described in the z/OSMF online help.

By default, the properties file for SDSF is `/usr/lpp/sdsf/zosmf/sdsf.properties`. Specify this file name in the Import dialog.

The import is generally a one-time process. The SDSF plug-in only needs to be imported the first time you are installing SDSF or after you have deleted the plug-in and want to restore it.



## Defining required settings for the SDSF task

When the user launches SDSF the first time (by double-clicking the SDSF icon on the z/OSMF desktop), the **Settings** dialog is shown. The following information is required to complete the settings:

For TSO logon proc, you can specify any logon proc for which the user is authorized that is suitable for SDSF, as long as it contains either a //SYSEXEC or //SYSPROC that references data set ISF.SISFEXEC.

You do not need to create a new logon procedure for exclusive use of the z/OSMF SDSF task.

**Example:** The following is a sample logon proc that can be used by the SDSF task, with the minimum allocations. You may need to adjust the data set name for your installation.

```
//SDSF EXEC PGM=IKJEFT01,DYNAMNBR=500  
//SYSEXEC DD DISP=SHR,DSN=ISF.SISFEXEC
```

The SDSF task does not use ISPF, so ISPF allocations are not required. If you use a logon proc that includes ISPF allocations, ensure that the allocations can be shared between the launched TSO address space and a standard TSO login. In particular, ensure that any ISPF profile allocation will allow both the launched TSO address space and the standard login to proceed.

If your logon proc invokes an initial command (using the PARM= keyword on the EXEC statement), the command must return to the TSO READY prompt. When the logon completes, SDSF waits for the TSO READY prompt before proceeding.

If the logon fails when launching the SDSF task, click the TSO Messages link to view TSO messages that were issued during logon. Common errors preventing a successful launch include a JCL error in the logon proc, an invalid account number, and a missing ISF.SISFEXEC data set in the //SYSEXEC concatenation.

## Reviewing z/OS Unix System Services settings

SDSF uses the z/OS Unix System Services interprocess communications (IPC) message queue for communications between SDSF and z/OSMF. The maximum message size is controlled by the size of the queue defined by the IPCMSGQBYTES option of PARMLIB member BPXPRMxx.

Message sizes used by SDSF vary based on the request type and amount of data returned in the response. You should review the setting of IPCMSGQBYTES on your system (using the BPXO panel or the D OMVS,O operator command) to ensure it is large enough for the messages sent by SDSF.

For details, refer to the topic about BPXPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

## Protecting SDSF function in z/OSMF

The function provided by the SDSF task in z/OSMF is protected just as z/OS SDSF is protected, with the same SAF resources.

To determine group membership, SDSF checks the SAF resource GROUP.group-name.server-name in the SDSF class. This is explained in detail in [“Using SAF to control group membership” on page 17](#).

To hide SDSF functions that you are not authorized to, open the **Settings** dialog, open the User Preferences tab, and select the Hide functions option.

To use the SDSF task in z/OSMF:

- You must have access to resources in the ZMFAPLA class.

Table 178. Resources in the ZMFAPLA Class

z/OSMF Task	Resource	Access Required	Class
SDSF	saf-prefix.ZOSMF.IBMDSF.SDSF.JOBS	READ	ZMFAPLA

You configure *saf-prefix* in z/OSMF. The default is IZUDFLT.

- Your user ID must be connected to the IZUUSER group.

Access to views in z/OSMF is protected in the same way as the corresponding panel command in z/OS SDSF. For a description of protecting SDSF commands with SAF, refer to [“Authorized SDSF commands”](#) on page 261. For a description of protecting SDSF commands with the AUTH parameter of ISFPARMS, refer to [“Group function parameters reference”](#) on page 18.

*Table 179. z/OSMF Views and Corresponding z/OS SDSF Commands*

<b>View</b>	<b>SDSF Command</b>
Active jobs	DA
All jobs	ST
Input queue	I
Output queue	O
Held output queue	H
Address space memory	AS
Unix processes	PS
Job groups	JG
Spool data sets	SP
CF structures	CFS
APF data sets	APF
Page data sets	PG
Link list data sets	LNK
Link pack data sets	LPA
Parmlib data sets	PARM
OMVS options	BPXO
System parameters	SYSP
Link list sets	LLS
z/OS health checks	CK
Systems information	SYS
Network activity	NA
Devices activity	DEV
SMS storage groups	SMSG
SMS volumes	SMSV
File systems	FS

The Home view requires access to these SDSF functions:

- The DA and SP panels for the system activity graph
- The CK panel for the active health check graph
- The slash (/) command, for the system command line

Modifying values in tables or on property sheets in z/OSMF is protected in the same way as overtyping fields in z/OS SDSF. The columns have the same titles in z/OSMF as in z/OS SDSF. For more information about protecting overtyping fields with SAF, refer to [“Overtypable fields”](#) on page 290.

Actions on tables in z/OSMF are protected in the same way as the corresponding action characters in z/OS SDSF. When using the zosmf UI, the dialog that displays actions for a selected item(s) internally generates the same SDSF action characters that are used interactively. The same SAF profiles that are already defined for SDSF are used for the zosmf UI. You can use the SECTRACE facility to determine the resources that are checked. For a complete discussion of protecting action characters with SAF, refer to [“Action characters”](#) on page 225.

## Managing security for SDSF with the Security Configuration Assistant task

The z/OSMF Security Configuration Assistant is a component of z/OSMF that provides the ability to check SAF definitions. The Security Configuration Assistant task can be used to verify that security is properly configured for SAF resources that are used by SDSF.

**Note:** To use this functionality, SDSF APAR PH53477 must be applied.

You must first import the SDSF security descriptor file into the Security Configuration Assistant task as follows:

1. Log in to z/OSMF.
2. Launch the Security Configuration Assistant from your z/OSMF desktop, or if not present, find the tool in the App Center.
3. Once the task has been launched, click **Import**.
4. Import all files contained in the `/usr/lpp/sdsf/sca` directory.

Once the security descriptor file has been imported, you can review and validate the SAF resources that are required for SDSF.

For additional information related to using the Security Configuration Assistant task, click the question mark (help) icon on the Security Configuration Assistant task main panel. This will open the help topics that describe the Security Configuration Assistant task and its capabilities.

## Diagnosing problems in z/OSMF

**TSO messages:** In addition to z/OSMF messages that are displayed in a message window, TSO messages may be issued in response to starting a session or other interactions. To display these messages, click **TSO Messages**.

**Log files in z/OSMF:** The directory of the z/OSMF log file is configurable, as described in [IBM z/OS Management Facility Configuration Guide](#).

**Determining the level of the SDSF plug-in:** From the z/OSMF Welcome panel, click the About link. Find the IBM SDSF plug-in in the list. The associated information contains the SDSF FMID and the service level of the plug-in.

## Removing the SDSF task from z/OSMF

To remove the SDSF and SDSF Settings tasks from z/OSMF, use the Import Manager task to import properties file `/usr/lpp/sdsf/zosmf/sdsfDelete.properties`.

## Using the SDSF classic interface

SDSF function is available through the z/OSMF ISPF task. To use the ISPF task, select ISPF in the z/OS Classic Interfaces category.

You can link to SDSF function that is available through the z/OSMF ISPF task from other function in z/OSMF. To do that, register the SDSF function as an event handler for z/OSMF events. For more information, refer to [Linking z/OSMF tasks and external applications in z/OSMF Configuration](#).



---

## Chapter 10. SDSF messages and codes

This topic explains the messages and abend codes that SDSF issues to the terminal or console.

### Displaying message help

---

There is a help panel for each SDSF message. To display the help for a message, in ISPF you can:

- Use the **SEARCH** command, for example **SEARCH ISF024I**.
- **CSRSEARCH** enables cursor-sensitive search on SDSF panels when SDSF is running under ISPF. To use **CSRSEARCH**, assign the **CSRSEARCH** command to a PF key, place the cursor under the word to be searched, and press the PF key. It is recommended that you redefine key PF6 for this purpose. Key PF6, previously used for the **BOOK** command, by default now invokes the **LOOKAT** command. You can change the default to **CSRSEARCH** using the ISFPRMxx **OPTIONS CSRSEARCH** parameter.

### User authorization

---

You might see a message that you are not authorized to perform a certain task. If you should be authorized, do the following:

1. Issue the **WHO** command. This displays your user ID, TSO logon procedure name, terminal ID, group index, and group name of the authorization group you have been assigned to based on ISFGRP macros or **GROUP** statements in ISFPARMS. (The index indicates the group by a count of groups. For example, an index of 3 indicates the group defined by the third **GROUP** statement in ISFPARMS.)
2. Check or ask the system programmer to check your authorization group against the ISFGRP, ISFNTBL, and ISFFLD macros in ISFPARMS. The macros are described in [Chapter 2, “Using ISFPARMS for customization,” on page 5](#).
3. If SAF rejects the security check, do the following:
  - a. Issue the TSO command **PROFILE WTPMSG**.
  - b. Try the SDSF request that failed.
  - c. Note the text of the ICH408I message that appears. This message identifies the profile (by name and class) that caused the authorization failure. Report the complete text of this message when asking for authorization.
4. Turn on security trace (**SET SECTRACE ON**) and retry the request. Review the security messages that are written to ULOG to determine the resource that has failed.

### SDSF messages

---

This section explains the SDSF messages. The messages are in alphabetic order.

Write-to-operator messages appear at the bottom of the log panels. For information on those messages, see [“Messages with ISF message numbers” on page 420](#).

Messages issued in response to SDSF's checks for IBM Health Checker for z/OS are described in [“Messages for IBM Health Checker for z/OS” on page 483](#).

The entry for each message includes a brief description of the meaning of the message and a suggested response.

#### Routing and descriptor codes

Writer-to-operator messages use the following default routing and/or descriptor codes:

- Routing codes 2 and 10

- Descriptor code 4

When a message issues a different routing or descriptor code, the codes that are issued are provided in the message.

---

**ACTIVE**  
**MODIFY**  
**INVALID**

### Explanation

An attempt to issue an action character or to modify a field for an active job, user, started task, printer or node was made. However, the action character or field modification is invalid for the active job, user, started task, or printer or node.

### User response

Remove the action character or modification from the panel by restoring or blanking the field, or enter the RESET command.

---

**AFD CURSOR**  
*row,column*

### Explanation

A job that invokes SDSF with program name ISFAFD has encountered an error in working with an SDSF panel. The cursor is positioned at *row,column*, where *row* is the number of rows from the top of the display, and *column* is the number of characters from the left of the panel. The possible values for *row* and *column* are 1-9999.

#### User response:

Use the cursor location to determine the row and column in error and retry the request.

---

**AFD ERROR**  
*error-number*

### Explanation

An error has been encountered in a job that invokes SDSF with program name ISFAFD.

### User response

Use the error number to resolve the error. The error numbers are:

#### 001

A comment has not been closed. Comments should be enclosed in /\* \*/ , for example: /\* This is a comment \*/

#### 002

An action character or overwrite has been entered on a non-tabular panel, such as a print panel.

Action characters and overtypes are valid only on tabular panels.

#### 003

A record has exceeded the maximum length of 9999 bytes. Trailing commas are treated as a continuation character.

#### 004

There is an error in the input syntax. Correct the syntax.

#### 005

Input could not be processed because there are no rows on the panel. This may be because all rows have been blanked out by filters such as FILTER, PREFIX, DEST, and OWNER.

#### 006

An attempt was made to enter an action character, but the NP column is not conditioned for input. The NP column is not conditioned for input on the OD panel. On other tabular panels, the problem may be that there are no rows because all rows have been filtered out by filters such as FILTER, PREFIX, DEST, and OWNER.

#### 007

The specified column could not be found. Either it is not a valid column for the panel, or the column name is an abbreviation that does not uniquely identify a column on the panel. If the column name is an abbreviation, specify the full column name.

#### 008

An attempt has been made to overwrite a column that is not overwriteable. If the column is a valid overwriteable column for the panel, it may be that the user is not authorized for that column either through ISFPARMS or SAF.

#### 009

Brackets with no column or value, that is <>, were entered on a tabular panel. This syntax is valid only on non-tabular panels such as the print panels.

#### 010

An overwrite with no column name, that is <=value> was entered on a tabular panel. This syntax is valid only on non-tabular panels such as the print panels.

#### 011

An attempt has been made to overwrite the fixed field. The fixed field is not overwriteable.

#### 012

The input could not be processed because there were no rows on the screen. This may be because

all rows have been filtered out by filters such as FILTER, PREFIX, DEST, and OWNER.

**013**

There is an error in the input syntax. Correct the syntax..

---

**ALLOC ERROR**

*return-code*

*error-code*

*information-  
code*

**Explanation**

Dynamic allocation of the print file failed. SDSF was unable to allocate or create a print file in response to a PRINT command, to a print action character (X), or to the processing of an open print data set panel.

An accompanying message that describes the error can also appear.

For information on dynamic allocation error codes, see the appropriate manual concerning system macros and facilities, or job management.

**User response**

Use the codes in the message text to determine the source of the error.

---

**ALLOCATION**

**ERROR - error-  
code**

**Explanation**

An error has occurred during the dynamic allocation of a SYSOUT data set.

**User response**

For information on dynamic allocation error codes, see the appropriate manual concerning system macros and facilities, or job management.

---

**APPL NOT  
AVAILABLE****Explanation**

An action or overtype requires a SNA application to be associated with the object. However, no SNA application is associated with the object

**User response**

Remove the action character or modification from the panel by restoring or blanking the field, or type the RESET command.

---

**ARR CRITERIA  
DISCARDED****Explanation**

SDSF detected that the arrange criteria that had been saved from a previous session is invalid. The arrange criteria were deleted from your ISPF profile.

**User response**

Use the Arrange pop-up or the ARRANGE command to rearrange columns.

---

**ARRANGE  
CRITERIA  
OBSOLETE****Explanation**

One or more of the columns saved from a previous arrange command has been removed from the ISFPARMS definition for this panel. A column might have been removed because of security changes, release migration, or customization of the field lists.

**User response**

Look at the INVALID COLUMN message displayed in the message line to see the number of obsolete columns.

---

**ARRANGE  
PENDING****Explanation**

You selected a column or block of columns but did not enter the destination for it.

**User response**

Scroll the list to the desired column and mark the destination by typing a or b next to it.

---

**AUTHORIZED  
DEST  
REQUIRED****Explanation**

During SDSF initialization or DEST command processing, SDSF did not find any authorized destination names. You are not authorized to access all destinations, therefore, a valid destination list, specified by IDEST in ISFPARMS, is required. This message also appears in response to a destination query command (DEST ?) if no destination names are authorized.

### User response

Enter the DEST command specifying one or more authorized destinations. Notify the SDSF or security administrator regarding the ISF005I messages issued during session initialization.

---

**AUTHORIZED  
DESTINATION  
REQUIRED.  
PRESS THE  
HELP KEY FOR  
MORE  
INFORMATION**

### Explanation

This message corresponds to the current AUTHORIZED DEST REQUIRED message, and is issued when you display the Destination pop-up.

### User response

Press PF1 for complete information, and contact the system programmer.

---

**\*\*\*\* AUTO  
UPDATE -  
*number*  
SECONDS \*\*\*\***

### Explanation

SDSF is running in automatic update mode. The interval between updates is given in seconds. (See the online help for more information on automatic update mode.)

### User response

None.

---

**BLOCK  
COMMAND  
INCOMPLETE**

### Explanation

You entered a block command but did not close it (the beginning of a block has been marked with //, but the end has not been marked with //). SDSF does not process pending actions until you close the block.

### User response

Close the open block, or use the RESET command to cancel all pending actions.

---

**BLOCK  
COMMAND  
INVALID**

### Explanation

You entered data both on the first and last rows of the block you want to repeat. Only the first or last row of the block can contain data.

### User response

Blank out the changes on either the first or last row of the block, or use the RESET command to cancel all pending actions.

---

**BLOCK INPUT  
REQUIRED**

### Explanation

You entered a block command but did not specify the action character or overtype. The first row of the block is made current to allow you to enter the action character or overtype to be repeated throughout the block.

### User response

Specify the action character or overtype on either on the first or last row of the block or use the RESET command to cancel all pending actions.

---

**BLOCK IS  
INCOMPLETE**

### Explanation

You marked the beginning of a block with //, but the end has not been marked with //.

### User response

Mark the end of the block with //.

---

**BOOKMANAGE  
R IS REQUIRED**

### Explanation

The command or pull-down choice requires BookManager READ/MVS.

### User response

Blank out the command or pull-down choice.



**BOOKMGR**  
**SELECT**  
**RC=return-code**

**Explanation**

The BOOK command has been issued but SDSF was unable to invoke BookManager. The message text contains the decimal return code from the ISPF select service used to invoke the BOOKMGR command.

**User response**

Ensure that BookManager is installed and available to your SDSF session, and then retry the BOOK command.

**\*BOTTOM OF  
DATA  
REACHED\***

**Explanation**

A FIND command reached the bottom of the data without finding the requested character string.

**User response**

Use the Repeat-Find PF key, or enter an F on the command line, to resume the search at the top of the data.

**BRIF ERROR**  
**RC=return-code**

**Explanation**

An unexpected error occurred during invocation of the ISPF browse service. The message contains the decimal *return-code* from ISPF. SDSF terminates the browse request.

**User response**

Refer to [z/OS ISPF Services Guide](#).

**BROWSE NOT  
AVAILABLE**

**Explanation**

The SB action character was entered to browse a data set using ISPF, but either SDSF is not running under ISPF or the ISPF level is insufficient. Instead, SDSF does the browse.

**User response**

Reenter the SB action character when running under the required level of ISPF.

**CANNOT MOVE  
FIXED FIELD**

**Explanation**

You have attempted to move the fixed field with the ARRANGE command. ARRANGE can be used to move columns after the fixed field, but the fixed field itself cannot be moved.

**User response**

None

*number* CHARS  
'string'

**Explanation**

In response to a FIND ALL command on the ODS panel or the logs, a number of occurrences of a character string have been found. If SDSF finds more than 999,999 occurrences, *number* is displayed as 999999+. The cursor is positioned on the character string.

**User response**

None.

CHARS 'string'  
FOUND

**Explanation**

In response to a FIND command, a character string has been found. The cursor is positioned on the character string.

**User response**

None.

*number* CHARS  
'string' FOUND

**Explanation**

In response to a FIND ALL command a number of occurrences of a character string has been found. If SDSF finds more than 9,999 occurrences, *number* is displayed as 9999+. The cursor is positioned on the character string.

## User response

None.

---

### CHECK NO LONGER VALID

## Explanation

An attempt was made to browse a check. However, the instance of the check has changed since the CK panel was displayed, probably because the check has run.

## User response

Press Enter to refresh the CK panel, then browse the check again.

---

### CHECKPOINT OUT OF DATE

## Explanation

A checkpoint version has been obtained, but the data might not be current. This can indicate that JES2 is down or not responding. The panel is built using the old data.

## User response

Retry the request. If the problem persists, contact your system programmer to determine the cause of the out-of-date data.

---

### CHECKPOINT READ ERROR

## Explanation

An error occurred when SDSF attempted to read from the checkpoint data set in order to determine a user's authority to issue a command.

## User response

Retry the command. If the problem persists, contact the system programmer.

---

### CHOICE NOT AVAILABLE ON THIS PANEL

## Explanation

The pull-down choice is not available on the current SDSF panel.

## User response

Use the HELP PF key for information on the pull-down choice.

---

### CKPT OBT ERR *return-code-* *reason-code*

## Explanation

An error has occurred obtaining a checkpoint version. In the message text, *return-code* is the hexadecimal SSI return code from SSOBRETN and *reason-code* is the hexadecimal reason code from field SSJIRETN. The version is not obtained.

## User response

Contact your system programmer to determine the reason for the failure. The return and reason codes are documented in macro IAZSSJI.

---

### CKPT REL ERR *return-code-* *reason-code*

## Explanation

An error has occurred releasing a checkpoint version. In the message text, *return-code* is the hexadecimal SSI return code from SSOBRETN and *reason-code* is the hexadecimal reason code from file SSJIRETN. The version is not released.

## User response

Contact your system programmer to determine the reason for the failure. The return and reason codes are documented in macro IAZSSJI.

---

### CLEAR COMPLETE

## Explanation

A request to clear commands from the list of saved system commands has been completed. The commands have been removed from the list.

## User response

None required.

---

### CMD NOT ISSUED – NO CONS

### Explanation

The function that was attempted requires an EMCS console to issue a system command, and an EMCS console was not available. The command was not issued.

### User response

None required.

---

**count CMDS  
NOT ISSUED**

### Explanation

A block of action characters was discarded at the request of the user. *count* is the number of action characters that were discarded. No commands were issued.

### User response

None.

---

**COLUMN NOT  
ALLOWED**

### Explanation

A command has referenced a column that is not allowed. Some columns are defined by SDSF as special. Special columns have restrictions on the commands that can reference them.

For **SORT** and **FILTER**, the .END column cannot be sorted or filtered.

### User response

Remove the column from the command and retry the request.

---

**COLUMN NOT  
FOUND**

### Explanation

You specified a column that does not exist for the panel. The cursor is positioned under the column name.

### User response

Correct the column name and reenter the command.

---

**COLUMN NOT  
UNIQUE**

### Explanation

The column name matches more than one column on the current panel. The cursor is positioned under the column name.

### User response

Reenter the column name.

---

**COLUMN  
TRUNCATED**

### Explanation

The column width specified with the Arrange function for one or more columns is shorter than the title for the column. The column will be truncated to the specified width.

### User response

None required.

---

**COMM NO  
LONGER AVAIL**

### Explanation

The user is no longer communicating with the local SDSF server. SDSF will show only data for the system the user is logged on to.

### User response

The system may have issued a previous message describing the error. To restore communications, correct any errors and re-access SDSF.

---

**COMMAND  
ISSUED**

### Explanation

SDSF has issued the requested MVS or JES system command.

### User response

None.

---

**COMMAND NOT  
APPLICABLE**

### Explanation

The command does not apply to the current panel and so is not allowed. It may be valid only on tabular panels.

## User response

Access a panel to which the command applies and try the command again. For more information, see "Where used" in the online help for the command.

---

### COMMAND NOT AUTHORIZED

## Explanation

You entered an SDSF command that you are not authorized to issue. Refer to ["User authorization"](#) on page 367 for more information.

## User response

Delete the command.

---

### COMMAND NOT ISSUED

## Explanation

An action character was discarded at the request of the user. No command was issued.

## User response

None.

---

### COMMAND NOT VALID

## Explanation

The command is not valid on the command line of the pop-up.

## User response

Correct or erase the command.

---

### COMMAND OBSOLETE

## Explanation

The command is obsolete and is no longer used. The command is accepted but has no effect. Operands are not syntax checked.

## User response

Discontinue use of the command.

---

### COMMAND SAVED

## Explanation

The list of commands was updated with the command. The command was not issued. If there is already an entry in the list with the same command text and group, only the comment is updated. If there is not already an entry in the list with the same command text and group, a new entry is added to the list.

## User response

None required.

---

### COMMAND TRUNCATED

## Explanation

You have overtyped more fields than can be processed in a single JES request. All fields up to the JES limit are processed.

## User response

Refresh the SDSF displays and overwrite the fields that were not updated.

---

### *command-count* COMMANDS ISSUED

## Explanation

A block command has successfully executed and *command-count* commands have been issued.

## User response

None.

---

### CONS ACT ERR *returncode-reasoncode*

## Explanation

An attempt to activate an extended console has failed. The message text contains the hexadecimal return code and reason code from the MCSOPER macro. Message ISF032I is also written to the ULOG display.

## User response

Use the return code and reason code to determine the cause of the error. Issue the ULOG command to activate the console.

---

### CONS ACT ERR – IN USE

### Explanation

An attempt to activate an extended console has failed because the console name is in use. The MCSOPER macro return code is 4 and reason code is 0.

### User response

None required. Use the SET CONSOLE command to specify a different console.

---

**CONS DEACT  
ERR**  
*returncode-  
reasoncode*

### Explanation

An attempt to deactivate an extended console has failed. The message text contains the hexadecimal return code and reason code from the MCSOPER macro.

### User response

Use the return and reason codes to determine the cause of the error. For the MCSOPER return and reason codes, see [z/OS MVS Programming: Authorized Assembler Services Reference LLA-SDU](#).

---

**CONSOLE**  
*console-name*  
**SHARED**

### Explanation

An attempt has been made to activate an extended console but the console is in use. SDSF shares the console by issuing commands using its console ID. However, responses are not returned to the SDSF session issuing the commands.

If the console is in use by another SDSF session (such as through split screen), any command responses caused by the shared session is returned to that session.

Message ISF031I is written to the ULOG display.

### User response

None

---

**CONVERSION  
COMPLETE**

### Explanation

SDSF parameters in ISFPARMS have been assembled through the conversion utility and converted to ISFPARMS in statement format.

### User response

You can edit the statements from the pop-up. To activate the ISFPARMS, or check their syntax, use the MODIFY command.

---

**DATA ACCESS  
ERROR**

### Explanation

An error has occurred retrieving data to build an SDSF panel. Communications with the server may have been lost, or an error may have occurred accessing a job. Additional messages may have been issued to describe the error.

### User response

See accompanying messages, if any, for more information about the problem. Retry the request.

---

**DATA NOT  
AVAIL** *system-  
name*

### Explanation

A sysplex request for data has been processed, but the data from *system-name* cannot be gathered. The plus (+) character is shown if more than one system is not responding, if there is available space. The data could not be gathered because the system is not at the required level, the SDSF server is not active, XCF is not configured, or a data gatherer is not active.

An asterisk is shown after the *system-name* if the data is out of date because it could not be collected during the last data-gathering interval.

### User response

None if the system is not at the required level. Otherwise, ensure that the SDSF server is started and configured to process XCF and data-gathering requests.

---

**DATA NOT  
SAVED**

### Explanation

A user entered the SE action character to edit a data set using ISPF, and either entered the SAVE

command or made changes to the data during the ISPF session. The changes were not saved upon exit since permanent changes cannot be made.

### User response

None.

---

#### DATA SET ALLOCATED

### Explanation

In response to a browse action, a data set has been allocated.

### User response

None.

---

#### DATA SET DISPLAYED

### Explanation

SDSF is displaying the requested SYSOUT data set on the Output Data Set panel.

### User response

None.

---

#### \*\*\*\* DATA SET NOT CATALOGED DSNAME= *data-set-name*

### Explanation

The required data set is not cataloged. This message accompanies the message `ALLOC ERRORreturn-code error-code information-code`, or `LOCATE ERRORreturn-code`, and explains why allocation of the print file failed.

### User response

None.

---

#### DATA SET NOT ELIGIBLE

### Explanation

The data set is not eligible for the operation. The data set is not changed. This condition can occur if the output group is in operator or system hold or is currently being processed by the SSI.

### User response

Ensure that the output group is not in operator or system hold.

---

#### DATA SET NOT FOUND

### Explanation

A data set entered on an SDSF panel could not be located.

### User response

Either allocate the data set or change the name of the data set on the SDSF panel.

---

#### \*\*\*\*\* DATA SET NOT ON VOLUME DSNAME= *data-set-name*

### Explanation

The required data set is not on the specified volume. This message accompanies the message `ALLOC ERRORreturn-code error-code information-code`, or `OBTAIN ERRORreturn-code`, and explains why allocation of the print file failed.

### User response

None.

---

#### \*\*\*\* DATA SET OPEN DSNAME = *data-set-* *name*

### Explanation

The data set *data-set-name* is open. This message accompanies the message `ALLOC ERRORreturn-code error-code information-code`, and explains why dynamic allocation of the print file failed.

### User response

None.

---

#### \*\*\*\* DATA SET UNAVAILABLE DSNAME= *data-set-name*

## Explanation

The required data set is unavailable. This message accompanies the message `ALLOC ERROR`*return-code error-code information-code*, and explains why dynamic allocation of the print file failed.

## User response

None.

---

**DATA  
TRUNCATED  
FOR EDIT**

## Explanation

A request has been made to edit a data set using the SE action character, but the job contains a data set that exceeds the maximum record length supported by edit. The edit request is processed, but the data is truncated to the 255 character maximum.

## User response

Use the S or SB action characters to display the entire record.

---

**DEALLOCATION  
ERROR -  
error-code**

## Explanation

An error has occurred during the dynamic deallocation of a SYSOUT data set.

## User response

For information on dynamic allocation error codes, see the appropriate manual concerning system macros and utilities or job management.

---

**DEST ALREADY  
EXISTS**

## Explanation

The DEST command was issued to add a destination that already exists in the current destination list.

## User response

Use DEST ? or SET DISPLAY to display the current destinations and correct the command.

---

**DEST NOT  
FOUND**

## Explanation

The DEST command was issued to delete a destination that is not in the current destination list. The destination not in the list has the cursor positioned under it.

## User response

Use DEST ? or SET DISPLAY to display the current destinations and correct the command.

---

**DETAIL NOT  
AVAIL**

## Explanation

A request to retrieve the enclave detail information has failed because the information is not available. The enclave may no longer be valid.

## User response

None required.

---

**DISPLAY  
RESET**

## Explanation

The logical screen size changed, causing SDSF to rebuild the display. SDSF ignored and cleared any action characters or commands you had entered but had not yet executed.

## User response

None.

---

**DSORG NOT PS  
OR PO**

## Explanation

In a PRINT ODSN command, the specified data set was not sequential, (DSORG=PS) or partitioned (DSORG=PO).

## User response

Reissue the PRINT ODSN command specifying an acceptable data set name. When the data set is allocated, a data set organization of sequential or partitioned must be specified.

---

**EDIF ERROR  
RC=return-code**

### Explanation

An unexpected error occurred during invocation of the ISPF edit service. The message contains the decimal *return-code* from ISPF. SDSF terminates the edit request.

### User response

Refer to [z/OS ISPF Services Guide](#).

---

### EDIT NOT AVAILABLE

### Explanation

The SE action character was entered to edit a data set using ISPF, but SDSF is not running under ISPF. Instead, SDSF does a browse.

### User response

Reenter the SE action character when SDSF is running under the required level of ISPF.

---

### ENC IMPLICITLY QUIESCED

### Explanation

An attempt was made to quiesce an enclave that is already implicitly quiesced because one or more address spaces associated with it is quiesced.

### User response

None required.

---

### END OF DATA ON MENU

### Explanation

SDSF could not read a requested help panel from the SDSF help panel data set.

### User response

The system programmer should check any changes that have been made to the SDSF help panel data set. If the problem cannot be found, the system programmer might want to replace the installed SDSF help panel data set with the original help panel data set on the SDSF distribution tape.

---

### %exec-name ENDED

### Explanation

A REXX exec invoked with the % action character ended without returning a return code.

### User response

None required.

---

### ENGLISH HELP NOT AVAILABLE

### Explanation

You selected the English language but the English help panels are not available.

### User response

Erase the selection or see your system programmer about the installation.

---

### ENTER REQUIRED FIELD

### Explanation

Data is missing for a required field. The cursor is positioned at the field in error.

### User response

Enter the requested data.

---

### ERROR IN ASSEMBLING PARAMETERS. RETURN CODE *return-code*

### Explanation

SDSF parameters being assembled through the conversion utility caused assembly errors.

### User response

Use the return code from the assembler to help identify the problem. The conversion utility pop-up lets you edit the ISFPARMS source data set (PF4) or browse the assembler listing (PF5).

---

### ERROR PROCESSING DATA



### Explanation

SDSF could not successfully process the spool control blocks of one of the jobs on the panel.

### User response

The user or system programmer could use one of the filter commands to identify which job is causing the problem.

For example, the user's panel shows these jobs:  
ABLEJOB ABLEBJOB ANDJOB BJOB BBBJOB CJOB

The user issues PREFIX A\*, and the panel shows these jobs: ABLEJOB ABLEBJOB ANDJOB

The error message still appears on the panel, so the problem is with one of the three jobs shown. The user then issues a second PREFIX command, PREFIX ABLE\*. The panel then shows: ABLEJOB ABLEBJOB

The error message no longer appears on the panel. The user knows that the problem is not with ABLEJOB or ABLEBJOB; the problem must be with ANDJOB.

---

**ERROR  
PROCESSING  
LINE** *line-  
number: text-  
of-line*

### Explanation

The conversion exec has encountered an error in the indicated line.

### User response

Follow your local procedure for reporting a problem to IBM

---

**EXEC NAME  
REQUIRED**

### Explanation

The % action character was issued without an exec name and SDSF is not running under ISPF.

### User response

Supply the name of the REXX exec and any arguments after the % action character, for example, %abc arg1 arg2

Alternatively, access SDSF from ISPF. Then, you can type the % action character by itself to display a pop-up on which you can supply the exec name and any arguments.

---

**service FAILED  
WITH  
RC=return-code  
REASON=ispf-  
message-text**

### Explanation

An ISPF or TSO service, *service*, failed with the indicated return code, and text of an ISPF message if it is available.

### User response

Use the return code and the message text, if any, to understand and resolve the problem. If the problem persists, follow your local procedure for reporting a problem to IBM

---

**FIELD INVALID**

### Explanation

Invalid information was typed in a field.

### User response

Correct what was typed in the field or type RESET on the command line.

---

**FIELD NOT  
NUMERIC**

### Explanation

A numeric field was overtyped with non-numeric data, or there are blanks in the numeric field. The cursor is positioned at the field in error.

### User response

Enter the field using numeric data. Within a tabular panel, use the RESET command to clear any overtyped data.

---

**FILE SIZE NOT  
AVAILABLE**

### Explanation

A request has been made to view a data set, but the file size (in bytes) is not available from JES. The file size is required by SDSF to allocate the temporary file used by GDDM

---

**FILTER CRIT  
DISCARDED**

## Explanation

SDSF detected that the filter criteria that had been saved from a previous session are invalid. The filter criteria were deleted from your ISPF profile.

## User response

Use the Filter pop-up or FILTER command to define filters.

---

### **FILTER CRITERIA OBSOLETE**

## Explanation

One or more of the columns saved from a previous session has been removed from the ISFPARMS definition for this panel. A column might have been removed because of security changes, release migration, customization of the field lists in ISFPARMS, or other customization of function such as symbol support. The obsolete filter criteria are deleted.

SDSF filtered the columns using the remaining columns. Look at the INVALID COLUMN message displayed in the message line to see the number of obsolete columns.

## User response

No action is required.

---

### **FILTER NOT FOUND**

## Explanation

An attempt was made to delete a filter that does not exist.

## User response

No action is required. If the command to delete the filter was entered incorrectly, correct the command.

---

### **FILTER VALUE TRUNCATED**

## Explanation

A filter value entered with a previous command exceeds the 25-character length of the value field on the Filter pop-up. The value is truncated to fit the field.

## User response

None required. To change the value, type the changes on the pop-up.

---

### **FILTERING IS ON|OFF**

## Explanation

In response to a query of the filters, the current state of filtering is displayed.

## User response

If a filter is displayed on the command line, pressing Enter issues the command and makes the filter active.

---

### **GDDM ERROR severity- msgnumber**

## Explanation

An error occurred during execution of a GDDM service. *severity* is the severity code, in decimal, of the message; *msgnumber* is the GDDM message number in decimal.

The request to view a data set is ended. Other explanatory messages might have been issued by GDDM.

## User response

Correct the error described by the GDDM message text and retry the view request.

---

### **GDDM LEVEL ERR *gddm-level***

### **Explanation:**

The view function was requested, but the installed level of GDDM cannot be used by SDSF. *gddm-level* is the level of GDDM currently being accessed by SDSF. SDSF requires GDDM Version 2 Release 2 or a later release.

### **User response:**

The system programmer should ensure that the correct level of GDDM is available to the SDSF session either through a STEPLIB or the system LINKLST.

---

### **GDDM NOT AVAILABLE**

### **Explanation:**

SDSF was unable to load the GDDM interface module, ADMASPT, in response to a view request to compose a page-mode data set. The view function is not available because GDDM services cannot be used.

### **User response:**

The system programmer should ensure the GDDM load modules are available to the SDSF session either through a STEPLIB or the system LINKLST.

---

**GET ERROR**  
**RC=return-code**

### Explanation

The GET request for the spool data for a job failed. The job's SYSOUT is not displayed. This may occur if the job was purged or if the SYSOUT data was selected from the Display Active Users (DA) panel and the job was swapped out.

### User response

Try displaying the SYSOUT later. If the job was active and swapped out, the SYSOUT will be accessible. If the job was purged, the SYSOUT will not be found. For a description of the return codes, refer to [\*z/OS DFSMS Macro Instructions for Data Sets\*](#).

---

**GROUP NAME**  
**NOT VALID**

### Explanation

The name provided for a command group is not valid. A group name must consist of alphanumeric characters or these special characters: @ # \$ . : - It must begin with an alphabetic character and cannot begin with isf or ibm. Those names are reserved for use by IBM. It cannot contain embedded blanks.

### User response

Type a valid name. For a list of groups, press the Prompt key (PF4) with the cursor in the field.

---

**GROUP OLD-  
NAME  
RENAMED TO  
NEW-NAME:  
COUNT  
COMMANDS,  
SKIP-COUNT  
SKIPPED**

### Explanation

Command group *old-name* has been renamed to group *new-name* and *count* commands have been changed.

The skip-count is the number of commands that were not changed because they already exist in the new group. The skipped commands remain in the old group.

### User response

No response is required. If commands were skipped, review them and delete them if necessary.

---

**HC NOT  
ACTIVE  
sysname |  
count SYSTEMS**

### Explanation

Checks could not be displayed because z/OS is not running. If a single system reports that z/OS is not running, the system name, *sysname*, is displayed. If more than one system reports that z/OS is not running, the number of systems, *count*, is shown.

### User response

For information on starting z/OS, the system programmer should refer to [\*IBM Health Checker for z/OS User's Guide\*](#).

---

**HELP MENU  
ERROR=  
member-name**

### Explanation

SDSF could not find the requested help panel.

### User response

The system programmer should check any changes that have been made to the SDSF help panel data set. If the problem cannot be found, the system programmer might want to replace the installed SDSF help panel data set with the original help panel data set supplied by IBM

---

**HEX STRING  
INVALID**

### Explanation

The FIND command with a hexadecimal string has been issued on a panel other than the logs or ODS panels.

### User response

Correct the command and reissue it.

---

**INACTIVE  
MODIFY  
INVALID**

### Explanation

An attempt to issue an action character or to modify a field for an inactive job, user, started task, printer or node was made. However, the action character or field

modification is invalid for the inactive job, user, started task, or printer or node.

### User response

Remove the action character or modification from the panel by restoring or blanking the field, or enter the RESET command.

---

#### **INCONSISTENT PARAMETERS**

### Explanation

The FIND command has been issued with parameters that conflict.

### User response

Correct the command and reissue it.

---

\*\*\*\*

#### **INCORRECT UNIT NAME SUPPLIED**

### Explanation

The dynamic allocation of a tape drive failed with a X'021C' return code. This return code specifies that an incorrect unit name has been supplied. The valid units that are supported are: 3480, 3400-3, 3400-5, 3400-6, and 3400-9.

### User response

Specify a cataloged data set name that is on a supported tape unit.

---

#### **INPUT FILE ALLOC FAILED**

### Explanation

An error occurred trying to allocate the input file to be composed. Additional messages describing the reason for the allocation failure is issued by the system. The file cannot be viewed using GDDM.

#### **User response:**

Contact your system programmer to determine the cause of the error.

---

#### **INPUT INVALID WITH BLOCK**

### Explanation

An action character or overtype was entered within an open block. Data to be repeated can only be entered on the first or last row of the block. The display is positioned to the row containing the data within the block.

### User response

Blank out the data on the row or enter the RESET command to cancel all pending actions.

---

#### **INPUT INVALID WITHIN BLOCK**

### Explanation

You entered one or more characters within a block on the pop-up.

### User response

Erase the character.

---

#### **INT CONSOLE NOT ALLOWED**

### Explanation

An attempt was made to issue a system command using console ID 0 (INTERNAL), but an EMCS console is required by values specified in ISFPARMS.

### User response

Reissue the command using an EMCS console. If you are issuing a command using i/, remove the i.

---

#### **INVALID CALL TYPE**

### Explanation

During initialization, SDSF found an error processing ISFPARMS. The error is in the ISFNTBL macro or NTBL statement named in the IDEST parameter of the ISFGRP macro or GROUP statement for the user.

### User response

The system programmer should check the ISFNTBL macro or NTBL statement named in the IDEST parameter of the ISFGRP macro or GROUP statement that was used to place the user in a user group.

The system programmer might also want to put the installation-defined names last in the ISFNTBL macro

or NTBL statement, as the installation-defined names can be the most likely to cause an error. When SDSF encounters an error in the destination names during initialization, it continues initialization with the destination names that were successfully processed before the error.

---

**INVALID  
CLASS class  
ENTERED**

**Explanation**

An invalid class was entered with the ST, I, or O command. The class is ignored. Valid class names are:

- ST command:**  
A-Z, 0-9, +, !, \$, \*, ), -, ?, #, @. = and /
- I command:**  
A-Z, 0-9, !, \$, \*, #, and @
- JC command:**  
A-Z, 0-9, \$ and #
- O command:**  
A-Z, 0-9, and @

**User response**

Retry the command with a valid class.

---

**INVALID  
CLASS NAME**

**Explanation**

This field was updated with an invalid class name. Valid class names consist of the characters A-Z and 0-9.

**User response**

Type either a valid class name or a blank in the field, or type RESET in the command line.

---

**INVALID  
COLUMN:  
column-info**

**Explanation**

Column criteria for this panel were saved from a previous SDSF session, but one or more of the columns have been removed from this panel. SDSF ignores the criteria and deletes it from your SDSF profile. *column-info* is either a number of columns, or, for SORT, a list of columns. This message is issued as explanatory information with the ARRANGE, FILTER, or SORT CRITERIA OBSOLETE message.

**User response**

No action is required. You can establish new arrange, filter, or sort criteria.

---

**INVALID  
COMMAND**

**Explanation**

A command or action character was entered that is not recognized by SDSF, was entered in an unsupported environment, or was entered on a panel or row for which it is invalid. The command or action character might have been entered with an invalid parameter.

**User response**

Correct the command or action character and retry the request. See the SDSF publications or online help for a list of valid SDSF commands and action characters. For system commands, see the appropriate MVS and JES manuals. For the AFD command, see [z/OS SDSF User's Guide](#).

---

**INVALID  
DESTINATION  
NAME**

**Explanation**

The specified destination name is invalid for this system. If the destination name is an installation-defined destination name, this message might be issued because JES is not active. When JES is not active, the installation-defined destination names are not available to SDSF.

**User response**

Enter a valid destination name.

---

**INVALID DSN -  
LENGTH**

**Explanation**

A data set name has been entered that is longer than 44 characters.

**User response**

Correct the data set name being entered.

---

**INVALID DSN -  
QUOTES**

## Explanation

A data set name has been entered with unmatched quotes.

## User response

Correct the data set name being entered.

---

**INVALID HEX  
STRING**

## Explanation

Invalid hexadecimal data has been entered either by overtyping a field or with a FIND command. The invalid data contains non-hexadecimal characters or has an uneven number of digits.

## User response

Correct the hexadecimal string.

---

**INVALID LEFT  
BOUNDARY**

## Explanation

The value entered for the starting column with a FIND command is greater than the logical record size or is greater than the length of the field.

## User response

Correct the FIND command and reissue it.

---

**INVALID  
RETURN CODE**

## Explanation

An invalid return code has been received after a call to an internal SDSF subroutine. The table being displayed might be incomplete.

## User response

Retry the command, and if the problem persists, contact IBM

---

**INVALID  
SAVED DEST**

## Explanation

A saved destination name from a previous SDSF session is no longer valid. This could occur if an enhanced destination name was retrieved from an SDSF session that was running on a system prior to

MVS/ESA SP-JES2 4.2.0. Use DEST ? or SET DISPLAY ON to view the current destination list.

## User response

None. SDSF is initialized using any remaining saved values.

---

**INVALID  
SCROLL  
AMOUNT**

## Explanation

The amount specified in the SCROLL field of the panel, or in a scroll command, is invalid.

## User response

Enter one of the following valid scroll amounts:

### Page

to scroll one panel.

### Half

to scroll half of one panel.

### *number*

to scroll a specific number of lines or columns.  
*number* can be up to four digits.

### Max

to scroll to the end of the data.

### Csr

to scroll to the position of the cursor.

### Data

to scroll one line or column less than one page.  
This is valid only under ISPF.

If the message is accompanied by an audible alarm, it was issued by ISPF. Pressing the PF key assigned to HELP signals ISPF to display the valid scroll entries on line 3 of the display.

---

**INVALID  
SELECTION**

## Explanation

The input is not valid for this panel.

## User response

Enter a valid command or menu option.

---

**INVALID  
SYNTAX**

## Explanation

The command entered on the command line has too many parameters, has unmatched quotes, or is an invalid range.

## User response

Use the appropriate manual or online help to find the syntax of the command.

---

### INVALID UNIT

## Explanation

Either an invalid device number was entered on the PR, PUN, RDR or LI panel, or both a volume serial and a generic unit have been specified on the open print data set panel.

For the PR or PUN panel, the unit device number must consist of all hexadecimal digits. Leading zeros are required.

For the LI panel, the unit device number must be either all hexadecimal digits or SNA. Leading zeros are required.

The device number can be preceded with a slash (/).

For the open print data set panel, only one of the fields (volume serial or unit) can be specified.

## User response

Enter a valid device number or specify only one of the print panel fields.

---

### INVALID UPDATE VALUE

## Explanation

The user has entered an invalid update value for an overtypeable field. Invalid values include: a semicolon, a comma when not enclosed in parentheses, or a left parenthesis if it is the first update character in a field that does not allow multiple values to be entered.

## User response

Enter a valid name.

---

### INVALID VALUE

## Explanation

A value has been entered that is unrecognized or not allowed on the current panel.

## User response

Change the input to an allowable value.

---

### IRXEXEC RC=return-code

## Explanation

An error occurred after invocation of the IRXEXEC interface in response to a % action character. The message contains the return code from IRXEXEC.

## User response

Examine the return code and associated system messages, if any. For more information on the return codes from IRXEXEC, refer to [z/OS TSO/E REXX Reference](#).

---

### ISFTRACE DD MISSING

## Explanation

A TRACE command has been entered, but the ISFTRACE file is not allocated. The TRACE command is not processed.

## User response

Allocate the ISFTRACE file and reissue the TRACE command.

---

### ISPF REQUIRED

## Explanation

The command was issued when SDSF was not operating under ISPF. Some commands are valid only when SDSF was accessed through ISPF.

## User response

Access SDSF through ISPF and reissue the command.

---

### JAPANESE HELP NOT AVAILABLE

## Explanation

The Japanese Help/Tutorial feature is not installed.

**Note:** As of z/OS V2R3 the help and tutorial panels are no longer translated into Japanese.

## User response

See your system programmer.

---

### JCT NOT AVAILABLE

## Explanation

Either the object has no job control table (JCT) or an error occurred trying to process the JCT for the object.

## User response

Delete the command or type RESET on the command line.

---

### *jesx* NOT ACTIVE

## Explanation

The JES subsystem *jesx* is not active and one of the following has happened:

- You attempted to enter a command, select a pull-down choice, or process a pop-up that requires JES.
- SDSF attempted to obtain a checkpoint version. The checkpoint is not obtained.

## User response

Exit SDSF and retry the request when *jesx* is active.

---

### JES REQUIRED

## Explanation

You issued a command, selected a pull-down choice or attempted to process a pop-up that requires JES. JES is not currently active.

## User response

Contact the system programmer. When JES is active again, exit SDSF and re-access it to make all SDSF functions available.

---

### JES REQUIRED FOR MAS

## Explanation

The RES panel was accessed with the default parameter of MAS, either with the command or pull-down choice, but SDSF cannot determine which members are in the MAS. SDSF requires JES2 to determine the members in the MAS, and JES2 is unavailable. As a result, the panel shows all systems in the sysplex.

## User response

None required.

---

### JES 1.7 REQUIRED

## Explanation

The function that was attempted requires z/OS V1R7 JES2. For action characters and overtypable columns, both the user's system and the object's system must be at z/OS V1R7 JES2.

## User response

Delete the action character or overtype.

---

### JES2 ENVIRONMENT ONLY

## Explanation

A command or option was entered that requires SDSF to be processing a JES2 subsystem, but SDSF is processing a JES3 subsystem. The command is rejected.

## User response

None required.

---

### JES3 ENVIRONMENT ONLY

## Explanation

A command or option was entered that requires SDSF to be processing a JES3 subsystem, but SDSF is processing a JES2 subsystem. The command is rejected.

## User response

None required.

---

### JES2 REQUIRED FOR MAS

## Explanation

A command included the MAS option when SDSF was processing a JES3 subsystem. The MAS option requires the JES2 environment. The option is internally converted to ALL.



### User response

None required.

---

#### **JOB IS PROTECTED**

### Explanation

The P action character has been used against a protected job. The job has not been canceled.

### User response

Use the PP action character to cancel a protected job.

---

#### **JOB NO LONGER VALID**

### Explanation

A command that was issued for a job failed, which may be because:

- The job has been purged
- The output group is no longer available. This could be because the characteristics have changed.
- The job is no longer active in the address space.

### User response

If the output group is no longer available but the data sets still exist, re-access the panel again and try again.

---

#### **JPN HELP NOT AVAILABLE**

### Explanation

The Japanese Help/Tutorial feature is not installed.

**Note:** As of z/OS V2R3 the help and tutorial panels are no longer translated into Japanese.

### User response

See your system programmer.

---

#### **number LINES PRINTED**

### Explanation

In response to a PRINT command or print action character (X), *number* lines have been printed. When you enter multiple X action characters, *number* is the lines in the last printed data set.

### User response

None.

---

#### **LINE NOT AVAILABLE**

### Explanation

An action or overwrite requires a line device to be associated with the object. However, no line device is associated with the object

### User response

Remove the action character or modification from the panel by restoring or blanking the field, or type the RESET command.

---

#### **LOCATE ERROR *return-code***

### Explanation

An attempt was made to open a print data set. A LOCATE request for the specified data set failed with return code *return-code*. The system can also issue an explanatory message.

### User response

Ensure that the data set being processed is an existing data set.

---

#### **LOG BROWSE ERR *returncode- reasoncode***

### Explanation

An error occurred in trying to browse the log stream displayed on the OPERLOG panel. The message text contains the hexadecimal return and reason codes from the IXGBRWSE macro.

### User response

Try issuing the LOG command again or scrolling up or down with a scroll amount of MAX. If the problem persists, use the return and reason codes to determine the cause of the error.

---

#### **LOG CONN ERR *returncode- reasoncode***

## Explanation

An error occurred in trying to connect to the log stream when displaying the OPERLOG panel. The message text contains the hexadecimal return and reason codes from the IXGCONN macro.

## User response

Use the return and reason codes to determine the cause of the error.

---

### LOG DISC ERR

*returncode-  
reasoncode*

## Explanation

An error occurred in trying disconnect from the log stream displayed on the OPERLOG panel. The message text contains the hexadecimal return and reason codes from the IXGCONN macro.

## User response

Use the return and reason codes to determine the cause of the error.

---

### LOG FUNCTION INOPERATIVE

## Explanation

The SDSF SYSLOG panel is not available due to an SDSF initialization error.

## User response

The system programmer should check the accompanying write-to-operator message for more information.

---

### LOGIC ERROR

**1**

## Explanation

SDSF could not process the command as it was entered.

## User response

Delete the command or enter the correct command.

---

### LOGIC ERROR

**2**

## Explanation

SDSF could not process the command as it was entered.

## User response

Delete the command or enter the correct command.

---

### LOGIC ERROR

**3**

## Explanation

An internal error has occurred processing action characters or overtypes. Some actions since the last enter might have been lost.

## User response

Press Enter to refresh the display and retry the actions or overtypes. If the problem persists, contact IBM for assistance.

---

### LOGLIM

*yyyy.ddd  
hh:mm:ss*

## Explanation

The OPERLOG is being filtered and the limit for the number of hours to search has been reached. *yyyy.ddd hh:mm:ss* is the date and time of the record being processed when the limit was reached. Processing is ended for the current request.

SDSF might have been reading forward or backward in the OPERLOG. If SDSF detected more than one limit in processing a single request, the message is issued for the last record that was processed.

## User response

Enter the LOGLIM command to change the limit for the operlog display. You can also enter the LOCATE command (by date and time) the NEXT and PREV commands, or SCROLL UP or DOWN MAX commands to scroll to a new position in the OPERLOG.

---

### LRECL TOO LARGE FOR GDDM

## Explanation

An attempt was made to view a file using the V action character. However, GDDM could not be invoked because the input record length of the file exceeded the maximum that can be processed by GDDM. See the

GDDM documentation for the maximum record lengths acceptable to GDDM.

### User response

The view request is terminated. The file can be browsed using SDSF, but not viewed using GDDM.

---

### MEMBER NAME MISSING

### Explanation

A member name was not specified on an SDSF panel, but the data set being used is partitioned.

### User response

Specify a member name for the data set, or use a different data set name.

---

### MEMBER NAME NOT ALLOWED

### Explanation

A member name was specified on a command or panel, but the data set being used is sequential.

### User response

Delete the member name for the data set, or use a different data set name.

---

### MEMBER NOT FOUND

### Explanation

A member of a PDS was specified on an SDSF panel, but the PDS does not contain a member with that name.

### User response

Correct the member name.

---

### MENU READ LOOP

### Explanation

A loop has occurred processing the SDSF help panels under TSO.

### User response

Contact IBM for assistance.

---

### MERGE ERROR *returncode-* *reasoncode*

### Explanation

An error occurred issuing an SJF merge request. In the message text, *returncode* is the decimal return code from the SJF merge service and *reasoncode* is the decimal reason code.

### User response

Attempt to reissue the modify request. If the error persists, contact your system programmer for assistance.

---

### MIGRAT ALLOC FAILURE

### Explanation

In response to a PRINT ODSN command, the required print data set was migrated and could not be allocated.

### User response

Recall the print data set and reissue the PRINT ODSN command.

---

### MOD NOT ALLOWED FOR PDS

### Explanation

An attempt has been made to allocate a print data set with MOD, but the data set is partitioned. SDSF does not support MOD for this case.

### User response

Change the disposition to OLD or NEW or specify a sequential data set.

---

### MODULE NOT FOUND

### Explanation

A QUERY MODULE command was issued for a module but the module could not be located.

### User response

The module named on the QUERY MODULE command must be an SDSF module that is accessible or currently loaded by SDSF.

---

**MODIFY  
ISSUED-  
number DS****Explanation**

A request to modify the output descriptors has been scheduled. *number* is a count of the number of data sets in the output group at the time the request was issued (leading zeros suppressed). A SWB modify request applies to all the data sets in the group.

**User response**

None.

---

**MUTUALLY  
EXCLUSIVE  
UPD****Explanation**

The use of an action character or overtype was incompatible with the concurrent use of another overtype. For example, you cannot use the P action character on the H display while simultaneously overtyping the class field. Purge and the class change are mutually exclusive.

**User response**

Either restore or delete the field, or type RESET on the command line.

---

**NO *sysid*  
SYSLOG FOUND****Explanation**

SDSF is unable to locate any SYSLOG data sets for the SYSID being processed.

**User response**

Use the SYSID command to change the SYSID, for example SYSID IP01.

---

**NO CHARS  
'string' FOUND****Explanation**

The FIND command could not find the character string *string*.

**User response**

None.

---

**NO  
COMMANDS  
FOUND IN  
GROUP  
GROUP-NAME****Explanation:**

No commands were found in group *group-name* to process. The commands have been left unchanged.

**User response:**

No response is required.

---

**NO COMMAND  
PROVIDED****Explanation**

No command text was entered with the command on the System Command Extension pop-up or the / command, or no action character or overtype was entered with row numbers on the command line.

**User response**

None required. If you are attempting to save a command on the System Command Extension pop-up, type a command on the command line and then press the Save PF key (PF10).

To issue an action character from the command line, use this syntax:

*rows action-character*

To overtype a field from the command line, use this syntax:

*rows column-title=value*

*rows* can be one or more row numbers or ranges of row numbers.

---

**NO DATA IN  
DATA SETS****Explanation**

The data sets for the job that has been selected are all empty data sets. There is no data to browse.

**User response**

None.

---

**NO DATA SETS  
ALLOCATED****Explanation**

An allocation failure has occurred for each data set in the job to be displayed. Since no data sets were allocated, they cannot be browsed.

Additional messages describing the specific allocation failures might have been issued by the system.

### User response

Use the system messages to determine the reason for the allocation failure and retry the request.

---

#### **NO DATA SETS AUTHORIZED**

### Explanation

An attempt was made to display a job but there is no data set the user is authorized to view.

### User response

If you have been denied access in error, see [“User authorization” on page 367](#) for more information.

---

#### **NO DATA SETS OPENED**

### Explanation

An open failure occurred for each data set in the job to be displayed. Since no data sets were opened, they cannot be browsed.

Additional messages can be issued by the system describing the error.

### User response

Determine the reason for the open failure using the error codes in the message.

---

#### **NO DATA TO DISPLAY**

### Explanation

There is no data to display for the request. If you are requesting slash command details or groups, there may not be data because there are no commands in the list. The value for Show may be excluding commands from the list. If you are accessing an SDSF panel, data may not yet be available.

### User response

To see command or group details, try changing the value for Show to include commands in the list. For example, a value of \* includes all commands for all groups, including commands that are not assigned to a group. To see panel data, try accessing the panel again. For the main panel, use the **SET MENU ALL** command to display hidden entries.

---

#### **NO DISPLAYABLE DATA**

### Explanation

A user has attempted to display a job's SYSOUT data, but the job has no data that can be displayed by that user.

### User response

Delete the command or type RESET on the command line.

---

#### **NO FILTERS AVAILABLE**

### Explanation

An attempt was made to turn filtering on when there are no available filters.

### User response

None required. To filter the panel, type a filter command or type FILTER ? to enter a filter on the Filter pop-up.

---

#### **NO HELP AVAILABLE**

### Explanation

SDSF could not show a help panel under TSO because it was unable to allocate or open the SDSF help panel data set.

### User response

Check that the SDSFMENU data set is allocated to the SDSF help panel library. Check the MENUS and MENUVOL parameters in ISFPARMS to see that they are coded correctly.

---

#### **NO OPERLOG FOUND**

### Explanation

You entered a LOG command to display the OPERLOG panel, but no log stream is available to display.

### User response

To display the SYSLOG panel, which contains messages for a single system, type LOG S.

---

**NO PREFIX  
'string' FOUND****Explanation**

The character string *string* was not found in response to a FIND command.

**User response**

None.

---

**NO PREVIOUS  
INPUT****Explanation**

You entered a repeat command, but no modification has yet been done to repeat.

**User response**

Enter an action character or overwrite a field prior to using the repeat command.

---

**NO PROMPT  
AVAILABLE****Explanation**

The Prompt function is not available for the selected field.

**User response**

None required.

---

**NO RESPONSE  
FROM RMF****Explanation**

SDSF has passed the timeout limit awaiting a response from RMF to display the DA panel.

**User response**

Retry the request. To bypass the error, use the SYSNAME command or pull-down choice to limit the number of systems being processed.

---

**NO RESPONSE  
RECEIVED****Explanation**

The delay interval for a command response or sysplex data had been reached. The command response or data on the SDSF panel is not shown. Sysplex data not shown may include WTORs on the Log panel, when you

have used the SYSID command to request the log for a system other than the one you are logged on to.

**User response**

To see the command response, issue the ULOG command to view the user log. To increase the delay interval, use the SET DELAY command.

To increase the delay interval for sysplex data, use the SET TIMEOUT command.

You might also try limiting the amount of sysplex data being returned, with one or more of the following:

- Parameters on the panel command, for example, PR 1 to see only printer 1.
- The SYSNAME command or pull-down choice, to restrict the systems to be included.
- The DEST command or pull-down choice, to restrict the destinations to be included.
- The SELECT command, to temporarily restrict the panel based on the fixed field, for example, SELECT PRT33 to see only printer PRT33.

Note that the Filter function does not have the effect of limiting the data returned

If the problem cannot be corrected with these methods, the operator or system programmer should ensure that one or more SDSF servers has not been stopped by issuing the F *server*,D,C command.

---

**NO STEP DATA  
FOUND****Explanation**

No job step data was found in response to a JS action character.

**User response:**

No response is required.

---

**NO SUFFIX  
'string' FOUND****Explanation**

The character string *string* was not found in response to a FIND command.

**User response**

None.

---

**NO WORD  
'string' FOUND**

### Explanation

The character string *string* was not found in response to a FIND command.

### User response

None.

---

**NOT ALL  
SYMBOLS  
SHOWN**

### Explanation

The number of symbols exceeds the number of symbols that can be shown by the pop-up.

### User response

Follow your local procedure for reporting a problem to IBM.

---

**NOT ALLOWED  
- PRIOR OD**

### Explanation

The % action character was used to invoke a REXX exec, but REXX execs are not allowed because the current panel was accessed from the OD (Output Descriptor) panel.

### User response

Delete the action character. If possible, access the panel without first accessing OD, then try the action character again.

---

**NOT ALLOWED  
WITH  
OUTDESC**

### Explanation

A value for forms, process mode, PAGEDEF, or FORMDEF has been entered along with an Output Descriptor Name. Those fields cannot be specified when Output Descriptor Name is used.

### User response

Delete the value for forms, process mode, PAGEDEF, or FORMDEF if an Output Descriptor Name is to be used. Alternatively, delete the Output Descriptor Name.

---

**NOT AUTH TO  
LOGSTREAM**

### Explanation

You are not authorized to the log stream. Access to the log stream is required for this function.

### User response

Contact your security administrator for authorization to the log stream.

---

**NOT AUTH TO  
OPERLOG**

### Explanation

You entered a LOG command to display the OPERLOG panel, but are not authorized to the log stream that is displayed on the OPERLOG panel.

### User response

To display the SYSLOG panel, which contains messages for a single system, type LOG S.

---

**NOT  
AUTHORIZED  
BY EXIT**

### Explanation

You attempted to issue a command that you are not authorized by the SDSF user exit to issue.

### User response

Delete the command.

If you have been denied authorization in error, the system programmer should check the SDSF user exit module, ISFUSER.

---

**NOT  
AUTHORIZED  
FOR CHECK**

### Explanation

You are not authorized to issue the command for the check.

### User response

Delete the command.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR CHOICE**

## Explanation

You are not authorized for the pull-down choice.

## User response

Select another choice or press PF3 to close the pull-down. If your authorization has changed during the current SDSF session and the change is not yet reflected in the pull-down, either type the SDSF command associated with the choice or exit and reenter SDSF.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR CLASS**

## Explanation

The user is not authorized to issue commands against the class.

## User response

Delete the command.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR CMD**

## Explanation

You attempted to issue an action character, overwrite a field, or issue an MVS or JES command that you are not authorized to issue.

## User response

Delete the action character, overtyped information, or MVS or JES command.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR CONS**

## Explanation

You attempted to activate an extended console but are not authorized to the console. The console is not

activated, and the message responses is not available to the ULOG panel or with the slash command.

## User response

Contact your security administrator to grant you access to the extended console.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR DEV**

## Explanation

The user is not authorized to issue commands against the device.

## User response

Delete the command.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR DEST**

## Explanation

You are not authorized for a requested destination name.

## User response

Delete the destination name.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR ENC**

## Explanation

The user is not authorized to issue commands for the enclave.

## User response

Delete the command.



---

**NOT  
AUTHORIZED  
FOR FUNCTION**

**Explanation**

You are not authorized for the function provided by a pop-up.

**User response**

Cancel the pop-up.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR INIT**

**Explanation**

You are not authorized to issue commands to the initiator.

**User response**

Delete the command.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR JOB**

**Explanation**

You are not authorized to issue commands against the job.

**User response**

Delete the command.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR NODE**

**Explanation**

The user is not authorized to issue commands against the node.

**User response**

Delete the command.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR PROC**

**Explanation**

You are not authorized to issue commands to the z/OS UNIX process.

**User response**

Delete the command.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR PRT**

**Explanation**

You are not authorized to issue commands to the printer.

**User response**

Delete the command.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR RES**

**Explanation**

You are not authorized to issue commands to the system resource.

**User response**

Delete the command.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR SE**

## Explanation

You are not authorized to issue commands to the WLM scheduling environment.

## User response

Delete the command.

If you have been denied authorization in error, see “User authorization” on [page 367](#) for more information.

---

**NOT  
AUTHORIZED  
FOR SYS**

## Explanation

You are not authorized to issue commands for the member of the MAS.

## User response

Delete the command.

If you have been denied authorization in error, see “User authorization” on [page 367](#) for more information.

---

**NOT  
AUTHORIZED  
TO DATA**

## Explanation

The server has rejected a request for sysplex data due to an authorization failure. The data is not displayed.

## User response

Exit SDSF and then re-access it.

---

**NOT PAGE  
MODE DATA**

## Explanation

A view request was entered for a data set that is not page mode. SDSF considers a data set to be page mode only if it is identified as being page mode by JES. SDSF converts the view request to browse. The data set is not be composed by the view utility, but is displayed on the ODS panel.

## User response

None.

---

**NOT VALID FOR  
TYPE**

## Explanation

The action character is not a valid action against that object type.

## User response

Enter the correct action character.

---

**NOT VALID  
WHEN REXX**

## Explanation

An SDSF command was issued or a command operand was used that is not valid in the REXX environment.

## User response

Delete the command or operand.

Refer to [z/OS SDSF User's Guide](#) for more information.

---

**"O" ACTION  
REQUIRED**

## Explanation

The field modification the user has attempted requires the O action character.

## User response

Issue the O action character.

---

**OBTAIN ERROR  
return-code**

## Explanation

An attempt was made to open a print data set. An OBTAIN request failed with return code *return-code*.

The system can also issue an explanatory message.

## User response

Ensure that the data set being processed exists either on the volume pointed to by the catalog or specified on the request.

For a description of the return code, refer to [z/OS DFSMSdfp Advanced Services](#).

---

**OFFSET NOT  
ZERO**

## Explanation

The number specified after the destination name in an ISFNTBL macro is not 1. The number must be

1 in ISFNTBL macros that are named in the IDEST parameter.

**User response**

The system programmer should check the ISFNTBL macros named in the IDEST parameter of the ISFGRP macro.

---

**OLD AND NEW  
NAMES MUST  
BE DIFFERENT**

**Explanation**

A command group is being renamed but the new name is the same as the old name.

**User response**

Ensure that the new name is different from the old name.

---

**OPERLOG NOT  
ACTIVE**

**Explanation**

You entered the LOG O command but OPERLOG is not active on the system to which you are logged on. The OPERLOG panel is displayed, but may not contain messages from the system to which you are logged on.

**User response**

To see messages from the system to which you are logged on, type LOG or LOG S.

---

**OPTION  
LOCALLY  
DISABLED**

**Explanation**

The command or option has been disabled by the installation.

**User response**

If the command or option should be allowed, contact your system programmer to review the SDSF configuration options.

---

**OPTS=*mask*  
REC-  
CNT=*record-  
count*  
DSNAME=*data-  
set-name***

**Explanation**

This message is issued to the message line in response to a TRACE command. *mask* is the event mask used for tracing; *record-count* indicates the number of records written to the trace data set; *data-set-name* is the name of the trace data set.

**User response**

None.

---

**\*\*\*\* OS CVOL  
ERROR**

**Explanation**

This message accompanies the ALLOC ERROR*return-code error-code information code* message.

**User response**

None.

---

**OUTADD  
ERROR *return-  
code-reason-  
code***

**Explanation**

An error occurred creating an output descriptor for the PRINT command. *return-code* is the decimal return code from the OUTADD macro, and *reason-code* is the hexadecimal reason code. The PRINT request is not executed.

**User response**

Use the return and reason codes to diagnose the error.

---

**OUTPUT DESC  
NOT AVAIL  
*return-code***

**Explanation**

An error occurred trying to obtain the output descriptors for at least one data set being displayed on the JDS panel. The output descriptor fields begin with the PageDef column in the default field list (PageDef, FormDef, Title, Name, and so on) in the default field list. See [“Job Data Set panel \(JDS\)” on page 134](#).

In the message text, *return-code* is a reason code describing the source of the error, as follows:

- 01**  
SJF service error

**02**

SWBIT block validation error

**03**

SWBIT job or data set key validation error

**04**

SWBIT read I/O error.

The output descriptors for the data set are not shown. If the reason code is 01, message ISF027I is also issued to further identify the data set and error that occurred.

### User response

Contact your system programmer to determine the cause of the error.

---

**OVERTYPE  
VALUE TOO  
LONG**

### Explanation

The value typed on an overtime extension pop-up is longer than the maximum width for the field.

### User response

Correct the value.

---

**number PAGES  
PRINTED**

### Explanation

In response to a PRINT command, *number* pages were printed.

### User response

None.

---

**PARM INVALID**

### Explanation

You entered a command with an invalid parameter, invalid printer name, invalid row number or row number range, invalid action character, or the parameter is not allowed in the current environment. The cursor is positioned under the parameter in error.

### User response

Correct the invalid parameter.

---

**PARM NOT  
ACCEPTABLE**

### Explanation

The command that was entered is not valid in the current environment. It may have been rejected because of a setting in the SDSF configuration parameters, ISFPARMS.

### User response

Correct the invalid parameter.

---

**PARTIAL DATA  
SHOWN**

### Explanation

While generating the PR panel, SDSF detected that printers were being added dynamically. SDSF was unable to build a complete printer list because the list exceeded a table retry limit. The printer list is incomplete.

### User response

Refresh the PR panel after dynamic addition of printers is complete.

---

**POINT ERROR  
RC=return-code**

### Explanation

The POINT request for the spool data for a job failed. The job's SYSOUT is not displayed. This may occur if the job was purged or if the SYSOUT data was selected from the Display Active Users (DA) panel and the job was swapped out.

### User response

Try displaying the SYSOUT later. If the job was active and swapped out, the SYSOUT will be accessible. If the job was purged, the SYSOUT will not be found. For a description of the return codes, refer to [z/OS DFSMS Macro Instructions for Data Sets](#).

---

**number  
PREFIX string**

### Explanation

In response to a FIND command, a number of occurrences of a character string have been found. If SDSF finds more than 999999 occurrences, *number* is 999999+. The cursor is positioned on the character string.

## User response

None.

---

### **PREFIX INVALID**

## Explanation

The PREFIX parameter was used with the FIND command on a panel other than the SYSLOG or ODS panel. The cursor is positioned on the character string.

## User response

None.

---

### **PRINT ABEND *abend-code***

## Explanation

An abend occurred during an SDSF print request. *abend-code* is the abend completion code in hexadecimal. The print operation is terminated and the print file is closed.

## User response

Use the abend code to determine the reason for the abend. Additional explanatory messages might have been issued by the system to further describe the abend.

---

### **PRINT ALREADY OPEN**

## Explanation

An attempt has been made to open a previously opened print file.

## User response

If a different print file is to be used, issue a PRINT CLOSE command to close the current file.

If the current print file is to be used, use the PRINT command or print action character (X) to print to the file.

---

### **PRINT CLOSED *number* LINE**

## Explanation

In response to a PRINT CLOSE command or a print action character, *number* lines were printed before the print file was closed.

## User response

None.

---

### **PRINT ENDED — LOOP COND**

## Explanation

An attempt was made to print an open print data set. The data set was not printed. This error occurs if you are trying to print an active print file or trying to print the active SDSF trace data set.

## User response

Data sets other than the open print data set belonging to the user's TSO session can be printed individually from the JDS panel. Issue a PRINT CLOSE or TRACE OFF command before printing.

---

### **PRINT FILE ERROR**

## Explanation

The *ddname* you specified for printing cannot be found.

## User response

Allocate a *ddname* and retry the request.

---

### **PRINT NOT OPENED**

## Explanation

A command requiring an open print data set was issued, but the print data set has not been opened.

## User response

Issue either the PRINT OPEN or PRINT ODSN command to retry the request. For information on printing, see the online help.

---

### **PRINT OPEN ERROR**

## Explanation

The PRINT OPEN command or print action character failed.

## User response

See the online help to diagnose the cause of error.

---

### **PRINT OPENED**

## Explanation

The print file has been successfully opened.

## User response

None.

---

**PRINT SCREEN  
UNAVAILABLE**

## Explanation

Another print job was in progress when you requested the print screen panel.

## User response

Retry the command.

---

**\*\*\*\* PRIVATE  
CATALOG  
ERROR**

## Explanation

This message accompanies the `ALLOC ERRORreturn-code error-code information-code` or `LOCATE ERRORreturn-code` message, and explains why the allocation of the print file failed.

## User response

Ensure that the data set used in the `PRINT ODSN` command is an existing data set.

---

**PROFILE  
DESCRIPTION  
S CREATED.**

## Explanation

The first step of the ISFPARMS-to-RACF conversion is complete. Profile descriptions have been created for the ISFPARMS.

## User response

Review the profile descriptions for completeness and appropriateness. In particular, look for lines marked `CHANGE`. These lines need to be edited.

---

**PROFILE  
DESCRIPTION  
S DATA SET  
MUST BE  
ALLOCATED.**

## Explanation

The menu option that has been selected requires the profile description data set, but the data set has not been allocated. The data set is named on the conversion utility profile pop-up, which you display with option 1 of the conversion utility menu.

## User response

Choose another menu option, or allocate the profile description data set. It must be a sequential file with record length of at least 80.

---

**PROMPT NOT  
AVAILABLE**

## Explanation

The Prompt function is not available. It may have been disabled by the installation.

## User response

None required. You can type the desired value in the field.

---

**RACF  
COMMANDS  
CREATED.**

## Explanation

Creation of the RACF commands from profile descriptions is complete.

## User response

Review the RACF commands for completeness and appropriateness. In particular, look for lines marked `CHANGE`. These lines need to be edited.

---

**RACF  
COMMANDS  
DATA SET  
MUST BE  
ALLOCATED.**

## Explanation

The menu option that has been selected requires the RACF commands data set, but the data set has not been allocated. The data set is specified in the SDSF Security Assist profile.

## User response

Choose another menu option, or allocate the RACF commands data set. It must be a sequential file with record length of at least 133.

---

**%exec-name**

**RC=return-code**

## Explanation

A REXX exec invoked with the % action character ended and returned the string *return-code*.

## User response

Examine the return code and respond as appropriate.

---

**number**

**RECORDS**

**SEARCHED**

## Explanation

A FIND command searched *number* SYSLOG or output data set records without finding the requested character string. The FIND ended before FINDLIM was reached.

## User response

Use the Repeat-Find PF key or enter an F in the command input area to resume the search, or reset FINDLIM if authorized.

---

**RESPONSE**

**NOT RECEIVED**

## Explanation

The timeout interval has been reached before one or more SDSF servers responded with data. The data on the SDSF panel is incomplete.

## User response

To increase the timeout interval, use the SET TIMEOUT command or pull-down choice.

You might also try limiting the amount of sysplex data being returned, with one or more of the following:

- Parameters on the panel command, for example, PR 1 to see only printer 1.
- The SYSNAME command or pull-down choice, to restrict the systems to be included.
- The DEST command or pull-down choice, to restrict the destinations to be included.

- The SELECT command, to temporarily restrict the panel based on the fixed field, for example, SELECT PRT33 to see only printer PRT33.

Note that the Filter function does not have the effect of limiting the data returned

If the problem cannot be corrected with these methods, the operator or system programmer should ensure that one or more SDSF servers has not been stopped by issuing the F *server*,D,C command. WebSphere® MQ support is obsolete as of z/OS V2R3.

---

**number**

**RESPONSES**

**NOT SHOWN**

## Explanation

An action character or slash command has been entered that results in messages being displayed on the screen, and the number of message responses received exceeds the screen depth. *number* message responses could not be shown.

## User response

Enter the ULOG or LOG commands to view all of the message responses.

---

**RMF EXIT NOT  
INSTALLED**

## Explanation

The SDSF-supplied RMF data reduction exit is not installed on all systems in the sysplex. RMF is installed and active, but the SDSF exit is not in the RMF steplib or accessible to it.

## User response

Ensure that the exit is installed. Refer to “[RMF considerations](#)” on page 358 for information.

---

**RMF III NOT  
AVAILABLE**

## Explanation

An attempt was made to access a panel that requires RMF Monitor III, and RMF Monitor III is not started. SDSF uses RMF Monitor III to obtain data for the panel.

## User response

Ensure that RMF Monitor III is started. For more information, refer to “[RMF considerations](#)” on page 358.

---

**RMF LOCAL  
ERR**  
*returncode-  
reasoncode***Explanation**

An error occurred during invocation of the RMF ERBSMFI Application Interface. *returncode-reasoncode* is the decimal return and reason code from the interface.

**User response**

Use the return code and reason code, along with the appropriate RMF documentation, to determine the cause of the error.

---

**RMF NOT  
ENABLED****Explanation**

An attempt was made to access the DA panel with RMF as the source of the data. RMF is not enabled on your system.

**User response**

None required. The DA panel is displayed with information derived from MVS control blocks rather than RMF. To request that DA use the MVS control blocks rather than RMF, and prevent display of this message, the installation can use the installation exit point of ISFUSER. For more information on the installation exit routines, refer to [Chapter 8, “Using installation exit routines,”](#) on page 349.

---

**RMF PLEX ERR**  
*returncode-  
reasoncode***Explanation**

An error occurred during invocation of the RMF ERB2XDGS Application Interface. *returncode-reasoncode* is the decimal return and reason code from the interface.

**User response**

Use the return code and reason code, along with the appropriate RMF documentation, to determine the cause of the error.

You can bypass the problem by typing SYSNAME with no operands to see data for the local system.

---

**RMF  
REQUIRED****Explanation**

An attempt was made to access the DA panel when SDSF is processing JES3, and either RMF is not installed or is disabled. The command is rejected.

**User response**

None required.

---

**RMF SYSPLEX  
NOT ACTIVE****Explanation**

The RMF server is not active. Sysplex data cannot be obtained for the DA display.

**User response**

You can bypass the problem by typing SYSNAME with no operands to see data for the local system.

For information about the RMF server, see your system programmer.

---

**SAPI ERROR**  
*returncode -  
reasoncode***Explanation**

A problem was encountered related to the SYSOUT application programming interface (SAPI). The return code *returncode* is from the SSOBRETN field and the reason code *reasoncode* is from the SSS2REAS field.

**User response**

For a description of the return code and reason code, see [z/OS MVS Using the Subsystem Interface](#).

---

**SCREEN  
DEFINITION  
ERROR****Explanation**

Incorrect or invalid screen dimensions have been specified for SDSF running in batch. The dimensions are ignored.

Possible causes of this error are:

- Dimensions out of bounds
- Non-numeric dimensions
- Syntax error specifying parameter.



### User response

Correct the screen dimensions and resubmit the SDSF job.

---

### SCREEN IMAGE PRINTED

### Explanation

The contents of the screen have been printed in response to an SDSF PRINT SCREEN command.

### User response

None.

---

### SDSF ABEND *abend-code*

### Explanation

A recoverable abend occurred. *abend-code* is the abend completion code in hexadecimal. SDSF continues; some functions may not be available.

### User response

Use the abend code and the dump to diagnose the problem.

---

### SERVER NAME *server-name* TOO LONG

### Explanation

The server name *server-name* specified on the SERVER parameter is longer than 8 characters.

### User response

Correct *server-name*.

---

### SERVER NOT COMPATIBLE

### Explanation

The SDSF client attempted to connect to an SDSF server, but the level of the server is not compatible with the level of the client.

### User response

Ensure the client is connecting to the correct server. To see the name of the server, issue the WHO command.

Refer to “Accessing the server” on page 74 for details on how SDSF selects a server for connection.

---

### SERVER *server-* *name* NOTAVAIL

### Explanation

SDSF was invoked using the SERVER keyword, but the named server is not available. SDSF continues execution using the parameters from the ISFPARMS in assembler macro format.

### User response

Ensure that the named server is running and that the ISFPARMS statements have been activated.

---

### SET COMMAND COMPLETE

### Explanation

The user issued the SET command and it has been completed successfully.

### User response

None.

---

### SET SCREEN FAILED *function code*

### Explanation

SDSF has received an error from the ISPF dialog manager. *function* is a number indicating the ISPF dialog function that failed. The numbers and the functions they represent are:

- 01** VDEFINE
- 02** VGET
- 03** DISPLAY
- 04** VPUT
- 05** VCOPY
- 06** ADDPOP
- 07** VREPLACE

*code* is the return code from the failing function. Refer to [z/OS ISPF Dialog Developer's Guide and Reference](#) or [z/OS ISPF Services Guide](#) for the meaning of the return code.

## User response

The system programmer should correct the error with the ISPF function.

---

### SHOW VALUE NOT VALID

## Explanation

The value provided for Show is not valid. It must be a valid group name, or a group name with the pattern matching characters (\* and % by default). A group name must consist of alphanumeric characters or these special characters: @ # \$ . : - It must begin with an alphabetic character and cannot begin with isf or ibm. Those names are reserved for use by IBM. It cannot contain embedded blanks.

## User response

Type a valid name. For a list of groups, press the Prompt key (PF4) with the cursor in the field.

---

### SOCKET NOT AVAILABLE

## Explanation

An action or overtime requires a socket to be associated with the object. However, no socket is associated with the object

## User response

Remove the action character or modification from the panel by restoring or blanking the field, or type the RESET command.

---

### SORT COLUMN NOT FOUND

## Explanation

A SORT command was entered specifying a column name that does not exist for this panel. The cursor is positioned under the column name that was not recognized.

## User response

Correct the column name and reenter the command.

---

### SORT COLUMN NOT UNIQUE

## Explanation

A SORT command was entered using an abbreviated column name that does not uniquely identify one

column in the panel. The cursor is positioned under the column name in error.

## User response

Reenter the command specifying a unique abbreviation or a full column name.

---

### SORT COLUMN REPEATED

## Explanation

In a sort request, a column was specified more than once.

## User response

Correct the sort request so that no column is specified more than once.

---

### SORT CRITERIA OBSOLETE

## Explanation

During the current SDSF session, this is the first display of this panel. This first display uses sort criteria saved from a previous session. One or more of the saved criteria specify a column name that has been removed from the ISFPARMS definition of this panel. A column might have been removed because of security changes, release migration, or customization of the installation supplied field lists.

The obsolete criteria are deleted. If there are any valid sort criteria, the panel is sorted using only the valid criteria.

An additional message, INVALID COLUMN, is displayed in the message line and indicates the column name that no longer exists.

## User response

No action is required. A new SORT command can be issued to establish new sort criteria. See the additional message in the message line for more information.

---

### SORT ORDER NOT A OR D

## Explanation

A SORT command was entered, but the sort order specified is not A (for ascending sort) or D (for descending sort). The cursor is positioned under the operand in error.

### User response

Correct the command and reenter it.

---

### SPOOL DATA ERROR

### Explanation

The spool data for a job became invalid while the job's SYSOUT data was being displayed. This might occur if the job was purged or if the SYSOUT data was selected from the DA panel and the job was swapped out.

### User response

Try displaying the SYSOUT later. If the job was active and swapped out, the SYSOUT is accessible. If the job was purged, the SYSOUT will not be found.

---

### SRVCLASS NAME INVALID

### Explanation

The value entered for a service class was rejected by the WLM programmable service IWMERES.

### User response

Refer to *z/OS MVS Programming: Workload Management Services* for more information about service classes.

---

### SSI 82 ERR *returncode - reasoncode*

### Explanation

A problem was encountered retrieving data from SSI 82. The return code is from the SSOBRETN field and the reason code is from the SSJPRETN field.

### User response

For a description of the return and reason code, see *z/OS MVS Using the Subsystem Interface*.

---

### SSI RETURN CODE *return- code*

### Explanation

A subsystem interface (SSI) return code of *return-code* was issued when a user tried to requeue an output group from the H panel or the JDS panel or tried to overwrite a field on the OD panel.

### User response

The system programmer should see one of the following return codes:

- 4** Subsystem does not support this function
- 8** Subsystem exists but is not up
- 12** Subsystem does not exist
- 16** Function not completed
- 20** Logical error.

---

### SSOB RETURN CODE *return- code*

### Explanation

An SSOB return code of *return-code* was issued when a user tried to requeue an output group from the H panel or the JDS panel.

### User response

The system programmer should see one of the following return codes:

- 4** No more data sets to select
- 8** Job not found
- 12** Invalid search arguments
- 16** Unable to process now
- 20** Duplicate job names
- 24** Invalid combination of job name and job ID
- 28** Invalid destination specified.

---

### STEP NAME NOT AVAILABLE

### Explanation

The user is trying to reset the performance group number for a started task and the step name is unavailable.

## User response

None.

---

### STORAGE NOT AVAILABLE

## Explanation

A request to obtain storage failed because the storage was not available.

## User response

The request is not processed. If possible, increase the region size used to invoke SDSF.

In the REXX environment, use special variables or other filter options to limit the number of REXX variables needed to satisfy a request. For more information, type REXXHELP (ISPF only).

---

### SUBS RETURN CODE *return-code*

## Explanation

SDSF has issued a return code of *return-code*.

## User response

The system programmer should refer to the return code for a description of the error. The return codes are:

- 4** Bad option passed
- 8** Not in an authorized state
- 12** Different JES system
- 16** Requested address space identifier not valid
- 20** Requested address space identifier not a TSO user
- 24** JES not active
- 28** Bad job key
- 32** SRB abend
- 36** Parameter invalid
- 40** User swapped out

**48**

Abend processing parameter

**52**

Bad data set key

**56**

Bad member-track-track-record (MTTR).

If SUBS RETURN CODE 56 appears randomly on the log, and disappears when the user presses Enter, and if the system has a high paging rate, the message might indicate a timing exposure. Press Enter when the message appears.

**60**

Buffer full

**64**

GETMAIN failed

**68**

User canceled

**72**

Attention key pressed

**76**

Cross-memory not active

**80**

Bad application copy error

**84**

Application copy level error

**88**

Application copy update error

**92**

Application copy no longer available

**96**

ECSA application copy no longer available

**100**

Invalid spool data set name call

**104**

Buffer size invalid

**108**

Dynamic printer addition overflow

**112**

JQE no longer valid

**116**

SJB/SDB invalid.

**120**

Checkpoint version error

**124**

Subsystem not defined

**128**

Invalid buffer header

**132**

Unable to obtain printer data

---

***number* SUFFIX  
'string'**

### Explanation

In response to a FIND ALL command, *number* occurrences of a character string have been found. If SDSF finds more than 999,999 occurrences, *number* is 999999+. The cursor is positioned on the character string.

### User response

None.

---

**SUFFIX  
INVALID**

### Explanation

The SUFFIX parameter was used with the FIND command on a panel other than the logs or ODS panels.

### User response

Correct the command and reissue it.

---

**SWB ERROR  
*nnnn-rea1-rea2***

### Explanation

An error occurred issuing a SWB modify request. In the message text, *nnnn* is the decimal return code from the SWB modify request. *rea1* and *rea2* are the decimal reason codes.

### User response

Attempt to reissue the modify request. If the error persists, contact your system programmer for assistance.

---

***field-name*  
SYNTAX  
ERROR**

### Explanation

An output descriptor has been overtyped, but SJF has detected a syntax error in the input for the *field-name* keyword. The variable *field-name* is the name of the output descriptor and might not necessarily be the same as the field title shown on the display.

### User response

Correct the overtype.

---

**SYSOUT NOT  
FOUND**

### Explanation

An attempt to work with SYSOUT was rejected by the subsystem interface (SSI).

### User response

Try the request again.

---

**SYSOUT  
REQUEUED**

### Explanation

In response to your request, SYSOUT has been requested or purged.

### User response

None.

---

***number*  
SYSOUT  
REQUEUED |  
PURGED**

### Explanation

In response to your request, *number* SYSOUT data sets have been requested or purged.

### User response

None.

---

**SYSPLEX DA  
NOT AVAIL**

### Explanation

You requested a sysplex-wide DA display, but either the RMF ERB2XDGS interface could not be loaded, or the installation has disabled the use of RMF for the DA display.

### User response

No action is required. For information about the RMF server, see your system programmer.

---

**SYSTEM BUSY,  
RETRY**

### Explanation

SDSF was unable to gather the data for a panel because a required system was busy.

## User response

Refresh the panel by pressing Enter. If the problem persists, follow your local procedure for contacting IBM for service.

---

### SYSTEM MESSAGES NOTAVAIL

## Explanation

An error occurred initializing the Consoles query environment. WTORs and AMRF queue entries will not be displayed on the SR panel or the LOG panel.

## User response

See your system programmer. SDSF may have previously issued a message describing the error.

---

### SYSTEM NOT CONNECTED

## Explanation

A command has been issued for a member of the MAS, but the command must be routed to the system and the system is not accessible.

## User response

Retry the command when the system is connected.

---

### TEMP FILE ALLOC FAILED

## Explanation

An error occurred attempting to allocate the temporary file required by the GDDM view utility. The request to view a data set is ended.

## User response

See the accompanying explanatory system message describing the error.

---

### TEMP FILE OPEN FAILED *reason-code*

## Explanation

An error occurred in the attempt to open the temporary file required by the GDDM view utility. The request to view a data set is ended. *reason-code* is one of the following:

### 01 –

SDSF was unable to open the temporary file DCB. Accompanying messages can further describe the error.

### 02 –

The block size of the temporary file exceeded the capacity of the DASD device on which it is allocated.

## User response

Determine the reason for the failure and retry the view request. If *reason-code* is 02, the system programmer should change the unit name for the temporary file (defined by the VIO keyword in the ISFGRP macro of ISFPARMS) to a device capable of holding a copy of the page-mode data to be composed.

---

### TOO FEW PARMS

## Explanation

There were not enough parameters specified on the command. SDSF does not process the command.

## User response

Correct the command and retry the request.

---

### TOO MANY COLUMNS SELECTED

## Explanation

You have selected too many columns or blocks on the pop-up.

## User response

Correct the selection. For ARRANGE, you can select one column.

---

### TOO MANY DEST NAMES

## Explanation

More than four destination names were specified in an ISFNTBL macro or NTBL statement that is named in the IDEST parameter of the user's ISFGRP macro or GROUP statement.

No more than four destination names can be specified in an ISFNTBL macro or NTBL statement that is named in the IDEST parameter of the ISFGRP macro or GROUP statement.

**User response**

The system programmer should correct ISFPARMS. The user should correct or delete the DEST command so the maximum number is not exceeded.

---

**TOO MANY  
FILTERS**

**Explanation**

An attempt was made to enter more filters than are allowed. The maximum number of filters is 25.

**User response**

Delete the command. You can remove a filter with `FILTER -column`. Under ISPF, you can use `FILTER ?` to display the pop-up, which allows you to modify filters, or delete them by blanking them out.

---

**TOO MANY  
PARAMETERS**

**Explanation**

Too many parameters were specified with a command.

**User response**

Correct or delete the command.

---

**TOO MANY  
PARMS**

**Explanation**

Too many parameters were specified with a command.

**User response**

Correct or delete the command.

---

**TOO MANY  
COLUMNS  
SELECTED**

**Explanation**

You have selected too many columns or blocks on the pop-up.

**User response**

Correct the selection. For `ARRANGE`, you can select one column.

---

**\* TOP OF DATA  
REACHED \***

**Explanation**

A `FIND PREV` or `FIND FIRST` command reached the top of the data without finding the requested character string.

**User response**

Use the Repeat-Find PF key or enter an F in the command input area to resume the search at the bottom of the data.

---

**TRACE DCB  
ALREADY  
CLOSED**

**Explanation**

A `TRACE OFF` command was entered, but the ISFTRACE file has already been closed. The `TRACE OFF` command is ignored.

**User response**

None.

---

**TRACE DCB  
ALREADY  
OPENED**

**Explanation**

A `TRACE ON` command was entered, but the ISFTRACE file has already been opened. The `TRACE ON` command is ignored.

**User response**

None.

---

**TRACE DCB  
CLOSED**

**Explanation**

In response to a `TRACE OFF` command, the ISFTRACE file has been closed.

**User response**

None.

---

**TRACE DCB  
OPENED**

**Explanation**

In response to a `TRACE ON` command, the ISFTRACE file has been opened.

## User response

None.

---

### TRACE NOT AVAILABLE

## Explanation

SDSF is operating in split-screen mode, and the trace facility is not available in the session in which the message was issued. The trace facility is available in the other session.

## User response

To use the trace facility, swap sessions.

---

### TRACE OFF - ABEND *abend-code*

## Explanation

An I/O error has caused SDSF to turn tracing off. A system abend with an abend code of *abend-code* has occurred but has been handled by SDSF.

## User response

To continue tracing, allocate a new trace data set. For more information on the abend, see the appropriate system codes manual.

---

### TRACE OFF - PERM I/O ERR

## Explanation

An I/O error has caused SDSF to turn tracing off.

## User response

To continue tracing, allocate a new trace data set.

---

### TRACING IS ON|OFF

## Explanation

In response to a TRACE command, the status of tracing is shown to be on or off.

## User response

None.

---

### TYPE A COLUMN NAME

## Explanation

You left a field requiring a column name blank.

## User response

Type a valid column name in the field.

---

### TYPE A NUMBER IN THIS FIELD

## Explanation

You typed data that was not numeric in a numeric field, or there are blanks in the numeric field. The cursor is positioned on the field in error.

## User response

Enter numeric data in the field.

---

### TYPE A OR D FOR SORT ORDER

## Explanation

You typed something other than an A, D, or a blank on the Sort pop-up. The valid values are A (for ascending) or D (for descending). If the character is blank, the order is ascending.

## User response

Type an A or D or blank out the character.

---

### TYPE LINES OR TIMES AND DATES

## Explanation

You pressed Enter on a Print pop-up but didn't specify either lines or times and dates to print.

## User response

Type values for either lines or times and dates.

---

### ULOG CLOSED

## Explanation

A ULOG CLOSE command was issued and the user log has been successfully closed. All message responses have been deleted from the user log and the extended console has been deactivated.



### User response

None.

---

#### UNABLE TO FIND ORIGINAL

### Explanation

The user attempted an action on a foreign, independent enclave, but the corresponding original enclave could not be found. The original enclave may have terminated before the action was attempted.

### User response

None.

---

#### UNABLE TO FIND OWNER

### Explanation

The user attempted an action on a dependent enclave, but the owning address space could not be found. The owning address space may have ended before the action was attempted, or may be running on a system that does not support the Enclave Reset function.

### User response

None.

---

#### UNABLE TO MAP

### Explanation

A user has attempted to map a block of memory that is not contiguous. Possible reasons for this error are that the entire block was not available or that the storage key changed at some point between the start and end of the memory. The formatting of the map is terminated.

### User response

Validate that the entire block is available in contiguous memory and that the storage key is consistent throughout.

---

#### UNBALANCED PARENTHESIS

### Explanation

In attempting to overwrite a field, the user has omitted a required parenthesis.

### User response

Enter the required parenthesis.

---

#### UNBALANCED QUOTES

### Explanation

An ending quotation mark is either missing or you have an extra quote at the end.

### User response

Correct the quote marks or enter a new string.

---

#### UPDATE LENGTH TOO LONG

### Explanation

The update interval entered with the & command is longer than three digits.

### User response

Retry the & command with an interval of 999 or less.

---

#### UPDATE NOT AUTHORIZED

### Explanation

You have attempted to issue the & command to enter automatic update mode, but are not authorized to do so.

### User response

Delete the & command.

If you have been denied authorization in error, see [“User authorization” on page 367](#) for more information.

---

#### UPDATE TIME TOO SMALL

### Explanation

The user has issued the & command to enter automatic update mode, but the update interval specified was less than the installation-defined minimum.

### User response

Retry the & command with a larger interval.

---

**USE EQ,NE  
WITH  
PATTERNS****Explanation**

You specified an operator with less than or greater than and the value contained pattern matching.

**User response**

Change the operator to EQ or NE, or remove the pattern matching.

---

**USE EQ OR NE  
WHEN THE  
FILTER VALUE  
INCLUDES  
PATTERN  
MATCHING****Explanation**

You specified an operator with less than or greater than and the value contained pattern matching.

**User response**

Change the operator to EQ or NE, or remove the pattern matching.

---

**VALUE NOT  
AUTHORIZED****Explanation**

The value that was specified in an overtypable field was rejected by SAF security. The value is ignored.

**User response**

None required. You can overwrite the field with a different value. If the value should be allowed, contact your security administrator.

---

**VALUE TOO  
LONG****Explanation**

An attempt was made to add a value that was selected from a list to existing text. The resulting combination was too long for the field. As a result, the existing text was not changed.

**User response**

None required. You might change or delete the existing text and then try selecting a value from the list again.

---

**VIIF ERROR  
RC=return-code****Explanation**

An unexpected error occurred during invocation of the ISPF/PDF View service. The message contains the decimal return code from ISPF/PDF. SDSF ends the View request.

**User response**

See *z/OS ISPF Messages and Codes* for a description of the error codes for ISPF/PDF.

---

**\*\*\*\* VOLUME  
NOT MOUNTED****Explanation**

This message accompanies message ALLOC ERROR *return-code error-code information-code* or OBTAIN ERROR *return-code* and explains why allocation of the print file failed.

**User response**

Ensure that the PRINT ODSN command is issued using a valid existing data set.

---

**WIDTH  
CANNOT  
EXCEED  
maximum****Explanation**

The column width specified with the Arrange function is longer than the maximum allowed, which is *maximum*.

**User response**

Change the width to a number that is valid.

---

**WIDTH  
CHANGE NOT  
ALLOWED****Explanation**

An **ARRANGE** command was used to change the width of a special column. The column width for a special column such as **.END** cannot be changed.

**User response**

Do not use the **ARRANGE** command to change column width of a special column.

***number* WORD**  
**'string'**

**Explanation**

In response to a FIND ALL command, *number* occurrences of a character string have been found. If SDSF finds more than 999,999 occurrences, *number* is 999999+. The cursor is positioned on the character string.

**User response**

None.

**WORD INVALID**

**Explanation**

The WORD parameter was used with the FIND command on a panel other than the logs or ODS panels.

**User response**

None.

**Messages with HSF message numbers**

This section describes messages issued with HSF message numbers.

A letter following the message number indicates the severity of the message:

- I**  
Information.
- W**  
Warning.
- E**  
Error.

**HSF0001I      Server initializing**

**Explanation**

The SDSFAUX server is initializing. This message is issued when the SDSFAUX server starts the SDSFAUX address space.

The SDSFAUX address space provides data collection services used by various SDSF commands and displays.

**User response**

No response is required.

**User response**

No response is required.

**HSF0003E      Connect failed. RC=return-code  
RSN=reason**

**Explanation**

The connection request to the SDSFAUX server has failed for the indicated return and reason codes.

The SDSFAUX services are unavailable to the caller.

**User response**

Verify that the SDSFAUX server is active and that the caller has the required security access.

**HSF0002I      Server initialization complete.**

**Explanation**

SDSFAUX server initialization is complete. This message indicates that the SDSFAUX server has finished initializing and is ready to accept requests from SDSF users.

The SDSFAUX address space provides data collection services used by various SDSF commands and displays.

**HSF0004E      Cross-system resource group  
version mismatch with member**

**Explanation**

The SDSFAUX server has detected an unsupported version of SDSF on the specified member and has stopped its XCF data collection agent.

SDSFAUX cannot share XCF resources with an unsupported release of SDSF.

### User response

Update to a supported release of SDSF on the member listed.

---

<b>HSF0005E</b>	<b>SDSFAUX server is already active on this system.</b>
-----------------	---

---

### Explanation

An attempt has been made to start the SDSFAUX server, which was already active on the system.

The SDSFAUX server attempting to start will stop.

There must only be one SDSFAUX server active at any one time.

### User response

Before you restart the SDSFAUX or SDSF server, stop the current instance and ensure SDSFAUX is inactive.

---

<b>HSF0006E</b>	<b>Operating system level not supported.</b>
-----------------	--

---

### Explanation

An attempt has been made to start the SDSFAUX server on a system that is running an unsupported version of the operating system.

The SDSFAUX server will stop.

### User response

Upgrade to a supported release of the operating system.

---

<b>HSF0007I</b>	<b>Joined data-sharing group <i>name</i> as <i>member</i>.</b>
-----------------	--

---

### Explanation

The SDSFAUX server has successfully joined the indicated XCF group. The server will use this XCF group to perform cross-system data gathering requests.

### User response

No response is required.

---

<b>HSF0009E</b>	<b>Incorrect execution key.</b>
-----------------	---------------------------------

---

### Explanation

The SDSFAUX server cannot start because the execution key of the HSFSRV00 program did not match the IBM value of 4.

The SDSFAUX server will not start.

### User response

Verify that all required maintenance has been applied for SDSF and confirm that there are no modifications to the SCHEDxx PARMLIB members that override the IBM PPT entry for HSFSRV00.

---

<b>HSF0010I</b>	<b>Module <i>name</i> loaded successfully at address <i>hex</i>.</b>
-----------------	--

---

### Explanation

The SDSFAUX server successfully loaded the indicated module at the specified address.

This message appears only in the HSFLOG output.

### User response

No response is required.

---

<b>HSF0011I</b>	<b>Queue recovery for <i>jobname</i> ASCB( <i>ascb</i> ) TCB( <i>tcb</i> ) RB( <i>rb</i> )</b>
-----------------	--

---

### Explanation

The SDSFAUX server has attempted to recover a pending request for the indicated unit of work. The requestor's ASCB, TCB and RB addresses are listed.

This message is issued when there are problems with the task that owns the request queue in the SDSFAUX server. Typically there was an abend or server error when there were active requests.

This message appears only in the HSFLOG output.

### User response

The requesting unit of work will be resumed with an appropriate return and reason code.

---

<b>HSF0020I</b>	<b>Command entered: <i>command</i></b>
-----------------	--

---

### Explanation

The SDSFAUX server has received the specified operator command.

### User response

No response is required.

---

<b>HSF0025E</b>	<b>Unknown operation</b>
-----------------	--------------------------

---

### Explanation

The SDSFAUX server has received an unknown operator command. Only DISPLAY and MODIFY operations are supported.

## User response

Issue a supported operator command.

---

**HSF0026I**      **Command accepted: *text***

## Explanation

The SDSFAUX server has accepted the specified operator command.

## User response

No response is required.

---

**HSF0027E**      **Invalid command : *text***

## Explanation

The SDSFAUX server has rejected the specified operator command because it is unrecognized or contains invalid syntax.

## User response

Examine related messages and correct the operator command.

---

**HSF0028W**      **RMF data collection failed  
ERBSMFI RC=*rc* RSN=*rsn***

## Explanation

The SDSF data collection task received a non-zero return code and reason code from the RMF interface program ERBSMFI. Any SDSF commands that depend on the data collected by this RMF interface program will not be able to show any results.

## User response

Ensure that RMF Monitor I has been started and that the ERBSMFI program is available to SDSFAUX.

---

**HSF0030W**      **Critical error in data collection for  
*name***

## Explanation

The named task has encountered a non-recoverable error during data collection. Any SDSF commands that depend on the data collected by this task will not be able to show any results.

## User response

Look for any other earlier error messages issued by this task to determine the root cause of the problem.

---

**HSF0031I**      **Keyword *keyword* updated with  
new value *value***

## Explanation

The SDSFAUX server has refreshed the specified keyword with the new value.

## User response

No response is required.

---

**HSF0032W**      **Internal resource shortage *type* :  
*percent***

## Explanation

The SDSFAUX server has detected an internal resource shortage of the specified type. The percentage of the maximum limit for the resource type is listed.

Known types:

- PRV-STOR : Private storage below 16Mb
- EPRV-STOR : Private storage above 16Mb

## User response

Examine the resource type to see if there is an underlying issue that is causing the shortage.

---

**HSF0033I**      **Internal resource shortage  
relieved for *type***

## Explanation

The SDSFAUX server internal resource shortage of the indicated type has been relieved.

Known types:

- PRV-STOR : Private storage below 16Mb
- EPRV-STOR : Private storage above 16Mb

## User response

No response is required.

---

**HSF0034I**      **Task *name* terminated RC= *rc***

## Explanation

The SDSFAUX server task has terminated with the specified return code.

This message is written to the HSFLOG output.

## User response

No response is required.

**HSF0035W**      **SAF Class SDSF not active RC= rc  
RSN= rsn**

### Explanation

The SDSF SAF class is required for the SDSFAUX server to protect its services. A RACROUTE REQUEST=STAT service for the class has responded with the specified return and reason code.

All protected services will return a SAF "No Decision" return code.

### User response

Activate the SDSF SAF class and define the required profiles to protect the SDSFAUX services.

For more information see [Chapter 5, "Using SAF for security,"](#) on page 213.

**HSF0036I**      **Task name initialization complete**

### Explanation

The SDSFAUX server task successfully initialized.

This message is written to the HSFLOG output.

### User response

No response is required.

**HSF0037W**      **SAF Class SDSF not RACLISTed**

### Explanation

The SDSF SAF class is not RACLISTed. The SDSFAUX server uses RACROUTE REQUEST=FASTAUTH to verify access to its services, and therefore, must have the SDSF class RACLISTed.

All protected services will return a SAF "No Decision" return code.

### User response

RACLIST the SDSF class so that the SDSFAUX server can use the RACROUTE REQUEST=FASTAUTH service.

For more information see [Chapter 6, "SDSF and RACF,"](#) on page 219.

**HSF0038W**      **SAF Class class not enabled for  
GENERIC profiles**

### Explanation

The SDSF SAF class is not enable for generic profiles.

### User response

If applicable for your security product, enable the GENERIC attribute for the SDSF SAF class so that profiles with generic masking characters can be defined.

**HSF0040I**      **ENF listener name installed for  
event code**

### Explanation

The SDSFAUX server has successfully installed the specified module as an ENF listener for the event code.

This message appears only in the HSFLOG output.

### User response

No response is required.

**HSF0041I**      **ENF listener name delete for event  
code RC= rc**

### Explanation

The SDSFAUX server has attempted to delete the specified module from the ENF listeners for the event code.

This message appears only in the HSFLOG output.

### User response

If the return code is non-zero, contact IBM Software Support.

**HSF0042E**      **ENF listener install for name event  
code num failed RC= rc**

### Explanation

The SDSFAUX server has attempted to install the specified module as an ENF listener for the event code, and the operation has failed with the indicated return code.

### User response

Contact IBM Software Support.

**HSF0044E**      **Command name install failed RC=  
RC RSN= rsn**

### Explanation

The SDSFAUX server has attempted to install the specified command and the operation has failed with the indicated return and reason code.

The command and its associated data gathering service will be unavailable.

**User response**

Contact IBM Software Support.

---

<b>HSF0045I</b>	<b>Command <i>name</i> installed successfully</b>
-----------------	---

---

**Explanation**

The SDSFAUX server has successfully installed the specified command.

This command and its associated data gathering service will be available.

This message appears only in the HSFLOG output.

**User response**

No response is required.

---

<b>HSF0047I</b>	<b>Left data-sharing group <i>name</i></b>
-----------------	--

---

**Explanation**

The SDSFAUX server has left its data-sharing group.

All cross-system services for this SDSFAUX server are now marked unavailable.

This message appears only in the HSFLOG output.

**User response**

No response is required.

---

<b>HSF0048I</b>	<b>No active users</b>
-----------------	------------------------

---

**Explanation**

During shutdown, the SDSFAUX server determined that there are no connected users. Shutdown will proceed without delay.

**User response**

No response is required.

---

<b>HSF0049E</b>	<b>Required SDSF server not active</b>
-----------------	--

---

**Explanation**

During startup the SDSFAUX server has determined that the SDSF server is not active.

The SDSFAUX server will stop.

**User response**

The SDSFAUX server is typically started automatically by the SDSF server. Restart the SDSF server.

---

<b>HSF0050I</b>	<b>Sectoken \ <i>userid</i> <i>lvl</i> access to <i>name</i> class profile <i>res</i></b>
-----------------	---

---

**Explanation**

This message appears in the HSFTRACE output when the SDSFAUX security trace is active.

The userid has requested the indicated level of access to the SAF class profile.

The result of this access request will be described by a subsequent HSF0061I message that uses the same sectoken value.

**User response**

No response is required.

---

<b>HSF0051I</b>	<b>SDSFAUX RESPONSE IN PROGRESS / RESPONSE COMPLETE <i>Sysname</i> <i>JES</i> Version <i>Status</i></b>
-----------------	---

---

**Explanation**

This message is produced in response to the SDSFAUX DISPLAY JES operator command.

The "RESPONSE IN PROGRESS" message will be followed by a list of the systems, JES subsystems and versions that are known by the SDSFAUX server.

After all responses are sent, the "RESPONSE COMPLETE" message is issued.

**User response**

No response is required.

---

<b>HSF0052I</b>	<b>SDSFAUX RESPONSE IN PROGRESS / RESPONSE COMPLETE <i>Jobname</i> <i>ASID</i> <i>TCB</i> Connect <i>UCON</i></b>
-----------------	---

---

**Explanation**

This message is produced in response to the SDSFAUX DISPLAY USER operator command.

A "RESPONSE IN PROGRESS" message will be followed by a list of the active SDSFAUX users and their connect date stamps.

After all responses are sent, the "RESPONSE COMPLETE" message is issued.

## User response

No response is required.

---

<b>HSF0053I</b>	<b>SDSFAUX RESPONSE IN PROGRESS / RESPONSE COMPLETE</b> <i>TaskTCB RXTA Flag Samples CPU</i>
-----------------	--

---

## Explanation

This message is produced in response to the SDSFAUX DISPLAY TASK operator command.

A "RESPONSE IN PROGRESS" message will be followed by a list of the active SDSFAUX tasks and their resource consumption.

After all responses are sent, the "RESPONSE COMPLETE" message is issued..

## User response

No response is required.

---

<b>HSF0054I</b>	<b>SDSFAUX RESPONSE IN PROGRESS / RESPONSE COMPLETE</b> <i>Name Active Get Free Lost RXBP</i>
-----------------	---

---

## Explanation

This message is produced in response to the SDSFAUX DISPLAY BPOOL operator command.

A "RESPONSE IN PROGRESS" message will be followed by a list of the SDSFAUX buffer pools.

After all responses are sent, the "RESPONSE COMPLETE" message is issued.

## User response

No response is required.

---

<b>HSF0056I</b>	<b>SDSFAUX RESPONSE IN PROGRESS / RESPONSE COMPLETE</b> <i>Name EPA Invoke Normal Return Abend</i>
-----------------	--

---

## Explanation

This message is produced in response to the SDSFAUX DISPLAY EXIT operator command.

A "RESPONSE IN PROGRESS" message will be followed by a list of the system exits installed by SDSFAUX.

After all responses are sent, the "RESPONSE COMPLETE" message is issued.

## User response

No response is required.

---

<b>HSF0057I</b>	<b>SDSFAUX RESPONSE IN PROGRESS / RESPONSE COMPLETE</b> <i>Name Jobname TCB CPU-SRB CPU-TCB</i>
-----------------	---

---

## Explanation

This message is produced in response to the SDSFAUX DISPLAY ZIIP operator command.

A "RESPONSE IN PROGRESS" message will be followed by a list of the zIIP offload environments managed by SDSFAUX.

After all responses are sent, the "RESPONSE COMPLETE" message is issued.

## User response

No response is required.

---

<b>HSF0060E</b>	<b>SDSFAUX must be started under SDSF server control</b>
-----------------	--

---

## Explanation

The SDSFAUX server address space has been started with a native z/OS **START** operator command (for example, **S SDSFAUX**). The SDSFAUX server address space must be started under the control of the main SDSF server address space using the **F SDSF,S AUX** operator command.

## User response

Use the **F SDSF,S AUX** operator command to start the SDSFAUX server address space.

---

<b>HSF0061I</b>	<b>Sectoken token SAF RC= <i>safrc</i> RACF RC= <i>rc</i> RACF RSN= <i>rsn</i></b>
-----------------	--

---

## Explanation

This message appears in the HSFTRACE output when the SDSFAUX security trace is active.

This trace message qualifies an earlier HSF0050I message with the same internal sectoken value. The HSF0050I message will describe the access request details.

The message specifies the SAF return code and the RACF return and reason codes from the RACROUTE REQUEST=FASTAUTH service.



## User response

No response is required.

---

**HSF0062I**      **Server shutdown waiting for users to disconnect**

---

## Explanation

During shutdown, the SDSFAUX server will wait for connected users to gracefully disconnect before shutdown proceeds.

The SDSFAUX server lists any connected users in a ISF352I message.

The SDSFAUX waits for a short period of time for users to disconnect and then shuts down.

## User response

No response is required.

## Descriptor code:

7,11

---

**HSF0063E**      **level access to name class profile resource failed**

---

## Explanation

The SDSF server does not have sufficient access to the specified resource in the named class and cannot gather the associated data. This error can cause data to be missing from SDSF command displays that reply on the SDSF server successfully extracting data protected by the indicated security resource.

## User response

Permit the user ID associated with the SDSF server to access the indicated resource.

---

**HSF0064E**      **Service name failed RC= rc RSN= rsn**

---

## Explanation

The named service failed with the specified return and reason code.

This is a generic message that is used to present non-zero return codes from both internal SDSF services and other external programs and interfaces.

## User response

When the service name is clear, refer to the return and reason codes in the appropriate manual for the owning software product.

If the cause is unclear, contact IBM Software Support.

---

**HSF0065E**      **Data not available for name task**

---

## Explanation

The SDSF server task cannot gather some or all of the expected data. Missing data in the SDSF server can cause SDSF command displays to have empty values in certain columns.

## User response

Examine previous error messages to discover the cause of the failure to collect the data. If the cause is unclear, contact IBM support.

---

**HSF0067E**      **CSVDYLPA add for module name failed RC= rc RSN= rsn DIAG= code**

---

## Explanation

The SDSFAUX server failed to dynamically add the specified module into LPA.

After this error, the SDSFAUX server issues a user abend and stops.

## User response

Refer to the return and reason codes for the CSVDYLPA service in *z/OS MVS Programming: Authorized Assembler Services Reference LLA-SDU*.

If the cause is unclear, contact IBM Software Support.

---

**HSF0072I**      **Server shutdown proceeding**

---

## Explanation

During shutdown processing, SDSF has determined that no users are connected or that the time allowed for users to disconnect has been exceeded.

Shutdown processing continues and any user who is still connected will receive an error response when they resume processing.

## User response

No response is required.

---

**HSF00741I**      **CSVDYLPA delete for type module name RC= rc RSN= rsn**

---

## Explanation

The SDSFAUX server attempted to delete the specified module from LPA and it completed with the indicated return and reason code.

## User response

If the return code is non-zero, refer to the return and reason code descriptions for the CSVDYLP service in [z/OS MVS Programming: Authorized Assembler Services Reference LLA-SDU](#).

If the cause is unclear, contact IBM Software Support.

---

**HSF0078I RMF Monitor I not active – some data may not be available**

---

## Explanation

The SDSF server has detected that RMF Monitor I is not active. Any SDSF commands that depend on the data collected by RMF will not be able to show any results.

## User response

Ensure that RMF Monitor I has been started and that the ERBSMFI program is available to SDSFAUX.

---

**HSF0079I RMF Monitor I data now available**

---

## Explanation

After previously being unavailable, RMF Monitor I data that is required for various SDSF displays is now available.

## User response

None.

---

**HSF0080I Event : text**

---

## Explanation

The SDSFAUX server is logging the occurrence of a specific event in the HSFLOG output for diagnostic purposes.

## User response

No response is required.

# Messages with ISF message numbers

---

This section describes messages issued by SDSF with message numbers.

A letter following the message number indicates the severity of the message:

**I**

Information.

**W**

Warning. The command will be processed, or the ISFPARMS will be activated. For ISFPARMS, SDSF has found an inconsistency and may have changed a value for a parameter.

**E**

Error. A command will not be processed, or the ISFPARMS will not be activated.

---

**ISF005I INVALID IDEST FOR userid entry reason**

---

## Explanation

During initialization for *userid*, SDSF found an error processing *entry* in the ISFNTBL macro named in the IDEST parameter of the ISFGRP macro. The ISFGRP macro is in the ISFPARMS module.

The values for *reason* are:

### INVALID CALL

means that a logic error exists in SDSF. Follow your local procedure for calling IBM. Have the following documentation of the problem ready:

- A description of the panel being used and the operation being performed when the message was received
- A record of the message

- The name of the module that issues the message

### INVALID DEST

means that the destination name is invalid for this system. If the name is an installation-defined name, the error could be caused by the JES system not being active during the installation of SDSF.

### NAME NOT AUTH

At SDSF initialization, SDSF found the user was not authorized to access one or more destination names specified in the ISFNTBL macro for the IDEST parameter in the user's ISFGRP macro. If both the IDEST and DEST parameters are coded, the destination names in the IDEST ISFNTBL macro must also be in the DEST ISFNTBL macro in order for the user to be authorized.

If this is not the problem, a logic error might exist in SDSF. Follow your local procedure for calling IBM and have the following documentation of the problem ready:

- A description of the panel being used and the operation being performed when the message was received
- A record of the message
- The name of the module that issues the message

#### **nnnn NOT SPECIFIED**

During SDSF initialization or DEST command processing, SDSF did not find any authorized destination names. The user is not authorized to access all destinations, therefore, a valid authorized destination list is required. *nnnn* is the number of destinations.

This message also appears in response to a destination query command (DEST ?) if no destination names are authorized.

The system programmer or security administrator should either add an IDEST parameter to the user's ISFGRP macro, or authorize the user to access the ISFOPER.ANYDEST.jesx resource. If these conditions are not met, the user's destination filter is set to blanks or the character string QQQQ, and no jobs appear on the panels.

#### **OFFSET NOT ZERO**

means that the number specified after the destination name in the ISFNTBL macro is not 1. This number must be 1 in ISFNTBL macros that are named in the IDEST parameter.

#### **TOO MANY DESTS**

means that more than four destination names were specified. No more than four destination names can be specified in ISFNTBL macros that are named in the IDEST parameter.

### **User response**

The system programmer should check the ISFNTBL macros named in the IDEST parameter of the user's ISFGRP macro. The ISFGRP macro is described in [“Group authorization parameters \(GROUP or ISFGRP\)”](#) on page 17.

The system programmer might also want to put the installation-defined names last in the ISFNTBL macros, as the installation-defined names can be the most likely to cause an error. When SDSF encounters an error in the destination names during initialization, it continues initialization with the destination names that were successfully processed before the error.

---

**ISF006I**      **ERROR PROCESSING INITIAL  
CHECKPOINT REQUEST  
FOR SUBSYSTEM *subsystem-  
name*, CODE=*error-code*,  
REASON=*reason-code***

### **Explanation**

An error occurred during SDSF initialization attempting to obtain checkpoint data from *subsystem-name*. The *error-code* contains the reason for the failure and is listed below. If the error occurred processing a checkpoint version, *reason-code* indicates the return code (SSJIRETN) from the checkpoint version obtain request.

### **User response**

Use the return and reason codes to diagnose the error.

- 4**            Bad option passed
- 8**            Not in an authorized state
- 12**          Different JES system
- 16**          Requested address space identifier not valid
- 20**          Requested address space identifier not a TSO user
- 24**          JES not active
- 28**          Bad job key
- 32**          SRB abend
- 36**          Parameter invalid
- 40**          User swapped out
- 48**          Abend processing parameter
- 52**          Bad data set key
- 56**          Bad member-track-track-record (MTTR)
- 60**          Buffer full
- 64**          GETMAIN failed
- 68**          User canceled
- 72**          Attention key pressed
- 76**          Cross-memory not active
- 80**          Bad application copy error

- 84** Application copy level error
- 88** Application copy update error
- 92** Application copy no longer available
- 96** ECSA application copy no longer available
- 100** Invalid spool data set name call
- 104** Buffer size invalid
- 108** Dynamic printer definition overflow
- 112** JQE no longer valid
- 116** SJB/SDB invalid.
- 120** Checkpoint version error
- 124** Subsystem not defined

---

**ISF008I**      **DYNAMIC ALLOCATION ERROR**  
**RC=return-code EC=error-code**  
**IC=information-code DDN=ddname**  
**VOL=volume-serial DSN=data-set-**  
**name \*\*\*\*\***

### Explanation

An error has occurred during the dynamic allocation of a data set.

### User response

For information on dynamic allocation return, error, and information codes, see the appropriate manual concerning system macros and facilities, or job management.

---

**ISF009I**      **SDSF TRACE I/O ERROR**

### Explanation

An error occurred while writing a record to the trace output data set. Trace is no longer available for this SDSF session.

### User response

Allocate a new trace output data set.

---

**ISF011I**      **OPEN ERROR ddname**

### Explanation

An error occurred trying to open the indicated *ddname*, which is SDSFMENU, the SDSF help panel data set.

### User response

Verify the *ddname* is allocated to the proper data set.

---

**ISF012I**      **SDSF ABEND USER|SYSTEM**  
**abend-code AT address IN**  
**MODULE module-name OFFSET**  
**offset**

### Explanation

SDSF has abended with the user or system abend code *abend-code*. User abend codes are in decimal; system abend codes are in hexadecimal.

If the abend address is not in module *module-name*, UNKNOWN is displayed for *address*.

### User response

The system programmer should see “SDSF user abend codes” on page 493 for information on the user abend codes, or the appropriate system codes manual for information on the system abend codes.

---

**ISF013I**      **Rx-Ryrega\_rega regb\_regb**  
**regc\_regc regd\_regd**

### Explanation

The registers listed here are displayed in conjunction with ISF012I. Rx-Ry indicates the range of registers and *rega\_rega regb\_regb regc\_regc regd\_regd* is the contents of those registers.

### User response

None.

---

**ISF014I**      **TEA=tea BEA=bea IN MODULE**  
**module-name OFFSET offset**

### Explanation

This message is displayed in conjunction with ISF012I. TEA is the translation exception address and BEA is the breaking event address. If they cannot be displayed, the message shows N/A.

### User response

None.

---

<b>ISF015I</b>	<b>ISF015I SDSF COMMAND ATTEMPTED EXECUTED <i>command</i> <i>userid logon-proc terminal-name</i></b>
----------------	--

---

## Explanation

For COMMAND EXECUTED, a user issued an MVS or JES system command. For COMMAND ATTEMPTED, a user attempted to issue an MVS or JES system command that the user is not authorized to issue. *command* is the first 42 characters of the command text. If the text exceeds 42 characters, the text ends with a plus sign (+).

## User response

For COMMAND ATTEMPTED, the operator should take whatever action is appropriate according to the installation's procedures.

**Note:** If the command attempted or executed is the REPLY command, the command field of this message contains "REPLY *nn* TEXT of REPLY IS SUPPRESSED". The text of the REPLY command is suppressed to prevent confidential data from being logged.

---

<b>ISF019I</b>	<b>OUTPUT REQUEUE RELEASE  PURGE ATTEMPTED SUCCESSFUL JOBNAME=<i>jobname</i> JOBID=<i>jobid</i> CLASS=<i>class</i> DEST=<i>dest</i> <i>userid</i> <i>logon-proc terminal-name</i></b>
----------------	---

---

## Explanation

A user *userid* running with logon procedure *logon-proc* on terminal *terminal-name* has requested that the indicated job (*jobname* and *jobid*) be requeued to the class *class* and destination *dest*, or released to the output queue to the class *class* and destination *dest*, or purged. If the message indicates the requeue was attempted rather than successful, the user was not authorized to make the request.

## User response

None.

### Routing code:

9

### Descriptor code:

7

---

<b>ISF020E</b>	<b>SDSF LEVEL ERROR FOR MODULE <i>module</i>, SDSF ASSEMBLED FOR <i>module_level</i> BUT <i>name</i> IS AT <i>name_level</i></b>
----------------	--

---

## Explanation

SDSF has determined that the assembly level *module\_level* of the indicated module *module* does not match the named execution level *name\_level*. SDSF initialization continues and the message is written to ULOG.

## User response

The system programmer should verify that SDSF has been installed correctly and that the current runtime data sets are not from other releases of SDSF or local copies of SDSF members from other releases.

### Routing code:

11

### Descriptor code:

7

---

<b>ISF023I</b>	<b>I/O ERROR <i>text</i></b>
----------------	------------------------------

---

## Explanation

An I/O error occurred while SDSF was creating the temporary file used as input for the GDDM view utility. In the message, *text* describes the type of error.

All records up to the record causing the error are passed to the view utility. Other records are ignored. Because only partial data is passed to the view utility, formatting errors can occur.

## User response

Ensure that the data set being viewed contains the correct data streams for the view utility.

---

<b>ISF024I</b>	<b>USER <i>user-id</i> NOT AUTHORIZED TO SDSF, <i>reason</i></b>
----------------	--

---

## Explanation

An unauthorized user, *user-id*, has attempted to use SDSF.

## User response

Contact the system programmer or the Help Desk to find out if the user should be authorized to use SDSF.

A user is not authorized to use SDSF for one of these reasons:

- COMMAND OPTION ERROR. A failure occurred in parsing the parameters passed to SDSF. Initialization failed. If this problem persists, contact IBM support.
- CONNECT FAILED. SDSF was unable to connect to the SDSF server, possibly because the task is

already connected. Additional messages may have been issued by the server.

- **CONNECT NOT AUTHORIZED.** SDSF was unable to connect to the server because the user is not authorized. Additional messages may have been issued by the server
- **DENIED BY EXIT.** An initialization exit routine has denied authority.
- **INVALID BCP LEVEL.** SDSF was invoked under an unsupported level of the BCP. Initialization failed. Be sure the appropriate level of SDSF is being used with the level of operating system that you are running.
- **NO GROUP ASSIGNMENT.** The user does not fall into any group of users defined by ISFPARMS. For more information, see [“Group authorization parameters \(GROUP or ISFGRP\)”](#) on page 17.
- **PRODUCT NOT ENABLED.** SDSF has attempted to register its invocation on a z/OS system, and the registration has failed. If SDSF should be enabled for execution, check the IFAPRDxx member of your parmlib concatenation for an entry for SDSF.
- **REXX INIT FAILED.** Initialization of the REXX environment failed.
- **SERVER NOT AVAILABLE.** The SDSF server is required for ISFPARMS but is not active. The server is required for ISFPARMS when the user is not authorized to revert to an ISFPARMS defined with assembler macros. For more information, see [Chapter 3, “Using the SDSF server,”](#) on page 73.
- **STORAGE NOT AVAIL.** The amount of storage available was insufficient to complete the request.
- **UNEXPECTED INIT FAIL.** SDSF has encountered an unrecoverable error during execution. Follow your local procedure for reporting a problem to IBM.
- **NOPARM DENIED.** The SDSF server is running in NOPARM mode, but the user does not have access to the SERVER.NOPARM resource in the SDSF class. The SDSF server runs in NOPARM mode when either the initial ISFPRMxx encounters a syntax error or the server is started in NOPARM mode. When the server is in NOPARM mode, the user must be authorized to the SERVER.NOPARM resource in the SDSF class. Either grant the user access to the resource or correct the syntax error in ISFPRMxx.

**ISF025E SDSF TERMINATING DUE TO ISFPARMS VERIFICATION FAILURE, REASON=reason-code**

## Explanation

SDSF failed to initialize because SDSF detected that ISFPARMS is invalid. The reason code describes the verification failure, as follows:

Reason code (hexadecimal)	Description
00000004	ISFPMAC is not at current release level
00000008	ISFPMAC is not at current feature level
0000000C	ISFGRP length incorrect
00000010	ISFGRP version incorrect
00000014	ISFPMAC version incorrect

This problem is generally caused by using a copy of ISFPARMS from a different SDSF release or failing to reassemble ISFPARMS using the current SDSF macros.

SDSF terminates with a U0083 abend.

## User response

Ensure that the correct level of ISFPARMS is being used and reassemble using the current SDSF macros if necessary. Consider migrating to ISFPRMxx rather than using ISFPARMS.

## Routing code:

11

**ISF027I ERROR OCCURRED PROCESSING OUTPUT DESCRIPTORS FOR jobname, procstep, stepname, ddname, RC=return-code reason-code**

## Explanation

An error occurred retrieving the output descriptors for job *jobname*, procedure step *procstep*, step *stepname*, and ddname *ddname*. The scheduler JCL facility (SJF) SWBTUREQ service failed with return-code *return-code* and reason-code *reason-code*.

The output descriptors for the indicated data set are not shown on the JDS panel. The message OUTPUT DESC NOT AVAIL is issued in the SDSF message area.

## User response

The meanings of the return and reason codes are documented in the SJF macro IEF SJTRC. Use the SDSF TRACE command to trace the SJF service calls to obtain additional information about the problem.

**ISF028E ISFGRP INDEX return-code HAS AN INVALID ISFNTBL SPECIFICATION for listname.**

## Explanation

During SDSF initialization, an include or exclude list was being processed for a non-destination list. However, an ISFNTBL TYPE=DEST macro was used to specify the list. In the message text, *return-code* is the index number of the ISFGRP macro being processed, and *listname* is the name of the ISFGRP list that was being processed. (The index indicates the group by a count of groups. For example, an index of 3 indicates the group defined by the third GROUP statement in ISFPARMS.)

Initialization is terminated with a U0016 abend after the remaining include and exclude lists are processed.

## User response

Correct the ISFNTBL macro pointed to by the indicated ISFGRP statement.

---

<b>ISF029I</b>	<b>SWB MODIFY ATTEMPTED  EXECUTED <i>data-set-name</i> <i>userid</i> <i>logon-proc terminal-name</i></b>
----------------	--

---

## Explanation

A user *userid* running with logon procedure *logon-proc* on terminal *terminal-name* has requested that output descriptors for data set *data-set-name* be modified.

If the message indicates ATTEMPTED, the user was not authorized to make the request. If the message indicates EXECUTED, the request has been scheduled for execution.

## User response

None.

---

<b>ISF031I</b>	<b>CONSOLE <i>console-name</i> (<i>migration-id</i>) ACTIVATED (<i>share-status</i>)</b>
----------------	--

---

## Explanation

A user log has been started using console *console-name*. If a migration identifier has been assigned, *migration-id* contains the ID being used. If the console is being shared, the *share-status* is (SHARED).

## User response

None.

---

<b>ISF032I</b>	<b>CONSOLE <i>console-name</i> ACTIVATE FAILED, RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i></b>
----------------	--

---

## Explanation

An attempt to activate an extended console has failed. The message text contains the hexadecimal *return-code* and *reason-code* from the MCSOPER macro.

## User response

Use the return and reason codes to determine the cause of the error. For the MCSOPER return and reason codes, see [z/OS MVS Programming: Authorized Assembler Services Reference LLA-SDU](#).

---

<b>ISF033I</b>	<b><i>console-name</i> MESSAGE RETRIEVAL FAILED, MCSOPMSG RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i></b>
----------------	--

---

## Explanation

An attempt to retrieve a message from the extended console *console-name* failed. The message text contains the hexadecimal *return-code* and *reason-code* from the MCSOPMSG macro. Some messages might have been discarded by consoles.

## User response

Use the return and reason codes to determine the cause of the error. You can reset the console by issuing a ULOG CLOSE command, followed by a ULOG command.

---

<b>ISF034I</b>	<b>ULOG IS EMPTY</b>
----------------	----------------------

---

## Explanation

An attempt has been made to access the user log, but it contains no records.

## User response

If the ULOG is inactive, issue the ULOG command to activate it.

---

<b>ISF035I</b>	<b>SDSF TDUMP FAILED, RETURN CODE=<i>return-code</i> REASON=<i>reason-code</i></b>
----------------	--

---

## Explanation

SDSF failed to take a transaction dump (TDUMP). The IEATDUMP return and reason codes are shown in the message.

## User response

Use the return and reason codes to determine the cause of the error. For more information, refer to



---

**ISF036I NO RECORDS TO DISPLAY**

---

**Explanation**

A LOG command has been entered to display the OPERLOG panel, but there are no log records to display.

**User response**

To display the SYSLOG panel, which contains messages for a single system, type LOG S.

---

**ISF037I dump-type NOT TAKEN, SUPPRESSED BY DAE**

---

**Explanation**

SDSF attempted to take a *dump-type*, but it has been suppressed by the Dump Analysis and Elimination (DAE) component.

**User response**

None.

---

**ISF039I ERROR PROCESSING ISPF service RC=return-code: message-text**

---

**Explanation**

An error has been encountered in using the ISPF service *service*. The return code from the service and the text of the ISPF short and long message is displayed.

**User response**

Use the return code and message text to understand and resolve the problem. If the problem persists, follow your local procedure for reporting a problem to IBM.

If the error is a system abend due to an out-of-space condition (such as SB37, SD37, or SE37) for table ISFACMTB, the table data set allocated to DDNAME ISFTABL is too small to store all of the commands. Reallocate the data set to a larger size. After the abend, the data set may still be in use by ISPF; exit ISPF to free it. When allocating the new data set, copy the existing ISFACMTB table to the new table to preserve your stored commands. Due to the abend, commands added during the current session are not preserved. For more information, refer to [“Issuing MVS and JES commands”](#) on page 356.

---

**ISF040I****INVALID MDB DISCARDED FOR BLOCKID *blockid***

---

**Explanation**

SDSF encountered an invalid message data block (MDB) in the log stream when displaying the OPERLOG panel. The MDB is discarded. The ID of the block in which the MDB was found is *blockid*.

**User response**

None.

**Routing code**

ERLOG

---

**ISF041I****CONSOLE *console-name* IS IN USE**

---

**Explanation**

SDSF needed to activate an extended console and the default console name was already in use. As a result, SDSF activated a console with a unique name generated by modifying the default name.

**User response**

None.

---

**ISF042I****CONSOLE *console-name* IS IN USE**

---

**Explanation**

SDSF attempted to activate an extended console but the console name was in use. The console was not activated. The console will be shared by SDSF if sharing has not been disabled.

**User response**

Use the SET CONMOD ON command to allow SDSF to retry the activation using a modified console name, or change the console name with the SET CONSOLE command.

For more information, refer to [“Issuing MVS and JES commands”](#) on page 356.

---

**ISF045W****UNABLE TO OPEN TABLE LIBRARY ISFTABL, NUMBER OF SAVED COMMANDS MAY BE LIMITED.**

---

**Explanation**

SDSF could not open the table library that uses DDNAME ISFTABL, which is used to store system commands. The number of stored commands is limited to those saved in the ISPF profile. This



message appears in the user log only when the STORELIMIT warning option is in effect. STORELIMIT is displayed below the command line on the System Command Extension pop-up.

User response

None required. To allow more commands to be stored, allocate the table library ISFTABL. To suppress the message, use the Options pull-down to turn the store limit warning off.

For more information, refer to “Issuing MVS and JES commands” on page 356.

ISF050I	USER=user GROUP=group PROC=proc TERMINAL=terminal
---------	--

Explanation

Tracing of messages related to security has been requested, or the user has been assigned to a group in ISFPARMS. The message identifies the user by user ID, group in ISFPARMS, logon procedure and terminal.

User response

None required.

ISF051I	SAF authorization SAFRC=saf-rc ACCESS=access CLASS=class RESOURCE=resource RECVR=userid
---------	---

Explanation

A SAF check has been performed.

**authorization**  
describes the decision by SAF.

**saf-rc**  
is a return code from SAF, or N/A, when the pre-SAF exit is being used.

**access**  
is the access mode that was requested.

**class**  
is the SAF class.

**resource**  
is the SAF resource.

**userid**  
is the user's ID. RECVR= is included only if it is specified by this SAF check.

User response

None required. For more information on SAF resources used by SDSF, refer to Chapter 7, “Protecting SDSF functions,” on page 225.

Routing code:

11

Descriptor code:

7

ISF052I	ISFUSER exit-type authorization EXITRC=exit-rc SAFRC=saf-rc ACCESS=access CLASS=classRESOURCE=resource RECVR=userid
---------	---

Explanation

A SAF check has been performed.

**exit-type**  
is the type of exit.

**authorization**  
describes the security decision.

**exit-rc**  
is a return code from the exit.

**saf-rc**  
is a return code from SAF, or N/A, when the pre-SAF exit is being used.

**access**  
is the access mode that was requested.

**class**  
is the SAF class.

**resource**  
is the SAF resource.

**userid**  
is the user's ID. RECVR= is included only if it is specified by this SAF check.

User response

None required. For more information on SAF resources used by SDSF, refer to Chapter 7, “Protecting SDSF functions,” on page 225. For more information on user exit routines, refer to Chapter 8, “Using installation exit routines,” on page 349.

ISF053I	COMMAND=command authorization
---------	----------------------------------

Explanation

A check of ISFPARMS security for an SDSF command has been performed.

**command**  
is the command.

**authorization**  
describes the security decision.

## User response

None required. For more information, refer to the AUTH parameter in [“Group function parameters reference”](#) on page 18.

---

**ISF054I**                    **DEST= destination authorization**

---

## Explanation

A check of ISFPARMS security for a destination has been performed.

**destination**  
is the destination.

**authorization**  
describes the security decision.

## User response

None required. For more information, refer to the DEST parameter in [“Group function parameters reference”](#) on page 18.

---

**ISF055I**                    **ACTION=action-character  
authorization USERLEVEL=user-  
level REQLEVEL=required-level  
jobname jobid RSN=reason**

---

## Explanation

A check of ISFPARMS security for an action character has been performed.

**action-character**  
is the action character.

**authorization**  
describes the security decision.

**user-level**  
is the user's command level.

**required-level**  
is the required command level.

**jobname**  
is the job name, if applicable.

**jobid**  
is the job ID, if applicable.

**reason**  
is the reason that authorization was denied. It is included only if authorization is denied. The reasons are:

**RSN=01 Job no longer valid**  
Either the job has been purged or the output group is no longer available.

**RSN=02 CMDAUTH ALL was not specified**  
The action requires a value of ALL for CMDAUTH in ISFPARMS.

## RSN=03 Not authorized for INIT command

The user is not authorized to the INIT command.

## RSN=04 Destination not specified

A destination that is required was not specified.

## RSN=05 Not a JES command

The command that was issued must be a JES command but was not.

## RSN=06 Not authorized for command

The user is not authorized for the command.

## RSN=07 Job name not in include list

An include list is defined with Ixxx parameters in ISFPARMS.

## RSN=08 Job name in exclude list

An exclude list is defined with Xxxx parameters in ISFPARMS.

## RSN=09 Command authority insufficient

The user does not have the required command authority.

## User response

None required. For more information, refer to the CMDLEV parameter in [“Group function parameters reference”](#) on page 18.

---

**ISF056I**                    **ISFUSER=exit-type authorization  
ACTION=action-character  
EXITRC=exit-rc jobname jobid**

---

## Explanation

An exit has made a security check for an action character.

**exit-type**  
is the type of exit.

**authorization**  
describes the security decision.

**action-character**  
is the action character.

**exit-rc**  
is the return code from the exit.

**jobname**  
is the job name, if applicable.

**jobid**  
is the job ID, if applicable.

## User response

None required. For more information, refer to Chapter 8, [“Using installation exit routines,”](#) on page 349.

---

ISF057I	<b>GROUP=group authorization</b> <b>USERAUTH=user-authorization</b> <b>REQAUTH=req-authorization</b> <b>RSN=reason</b>
---------	---

---

## Explanation

A security check has been made for a group in ISFPARMS.

### **group**

is the name of the group.

### **authorization**

describes the security decision.

### **user-authorization**

is the list of user authority (OPER, ACCT, JCL, MOUNT).

### **req-authorization**

is the authority that is required by the group.

### **reason**

is the reason authorization was denied. It is included only if authorization was denied. The reasons are:

#### **RSN=01 User has insufficient authority**

The user does not have the required authority.

#### **RSN=02 User ID is not in include list (IUID)**

The include list is defined with the IUID parameter in ISFPARMS.

#### **RSN=03 user ID is in exclude list (XUID)**

The exclude list is defined with the XUID parameter in ISFPARMS.

#### **RSN=04 logon proc is not in include list (ILPROC)**

The include list is defined with the ILPROC parameter in ISFPARMS.

#### **RSN=05 logon proc is in exclude list (XLPROC)**

The exclude list is defined with the XLPROC parameter in ISFPARMS.

#### **RSN=06 terminal is not in include list (ITNAME)**

The include list is defined with the ITNAME parameter in ISFPARMS.

#### **RSN=07 terminal is in exclude list (XTNAME)**

The exclude list is defined with the XTNAME parameter in ISFPARMS.

## User response

None required. For more information, refer to [“Group function parameters reference”](#) on page 18.

---

ISF058I	<b>COLUMN column</b> <b>authorization USERLEVEL=user-level</b> <b>REQLEVEL=required-level</b>
---------	---

---

## Explanation

A security check has been made for an overtypeable column.

### **column**

is the column title, or, for REXX, the column name.

### **authorization**

describes the security decision.

### **user-level**

is the user's authority, specified by the CMDLEV parameter in ISFPARMS.

### **required-level**

is the required authority.

## User response

None required. For more information, refer to the CMDLEV parameter in [“Group function parameters reference”](#) on page 18.

---

ISF059I	<b>SAF ACCESS auth SAFRC=(rc, rrc, rrs) ACCESS=access</b> <b>CLASS=class RESOURCE=resource,</b> <b>REQSTOR=requestor</b>
---------	--

---

## Explanation

A security check was performed by the SDSFAUX address space on behalf of the user.

### **auth**

describes the security decision.

### **rc,rrc,rrs**

is the SAF return code, RACF return code, and RACF reason code.

### **access**

is the access level requested.

### **resource**

is the resource name being checked.

**Note:** This message may be truncated if the resource name or requestor are lengthy.

## User response

No response is required.

### **Routing code:**

11

### **Descriptor code:**

7

---

ISF060I	<b>Access access-result</b> <b>for CLASS=class-name</b> <b>RESOURCE=resource-name due to</b> <b>fail-rc option.</b>
---------	--

---

## Explanation

This message is issued when security tracing is active to describe the action taken when SAF returns an indeterminate (no decision) result. In the message text, *access-result* is allowed or denied, *class-name* and *resource-name* are the SAF resources being checked, and *fail-rc* is the AUXSAF FAILRC4 or NOFAILRC4 server option in effect.

## User response

No response is required.

---

**ISF099I SDSF copyright statement**

## Explanation

The current SDSF copyright statement is shown.

## User response

No response is required.

---

**ISF101E SDSF INTERNAL ERROR  
OCCURRED IN MODULE *module*,  
REASON CODE *reason-code*.  
ADDITIONAL INFORMATION:  
*additional-information***

## Explanation

An error occurred in SDSF or in a system service required by SDSF.

## User response

Use the reason code and additional information (if any) to determine the cause of the error.

The reason codes are:

- 101** The execution environment was not recognized.
- 104** The SVT for the server failed a validity check.
- 105** A call to the IFAEDREG service failed.
- 106** A call to the IFAEDDRG service failed.
- 110** The system symbol service ASASYMBM failed.
- 111** The output area provided for the system symbol service ASASYMBM is too small.
- 120** A ENFREQ listen request has failed.

- 121** A ENFREQ delete listen request has failed.
- 124** The console query service CNZQUERY has failed.
- 130** The level was invalid for the name/token service.
- 131** The persist indicator was invalid for the name/token service.
- 132** A name/token service call has terminated with an error.
- 142** The IXCARM register service has failed.
- 143** The IXCARM ready service has failed.
- 144** The IXCARM deregister service has failed.
- 160** The SAF encryption service has failed.
- 161** The encryption key is invalid.
- 176** An error occurred during the AXSET service.
- 178** An error occurred establishing an ESTAE.
- 179** An error occurred deleting an ESTAE.
- 180** An error occurred during the ATTACH service.
- 182** An error occurred attempting to ENQ a resource.
- 184** An error occurred attempting to DEQ a resource.
- 185** The CIB contained an unexpected command verb.
- 186** An error occurred during execution the QEDIT service.
- 187** An error occurred creating a resource termination manager.
- 188** An error occurred deleting a resource termination manager.
- 189** An error occurred obtaining the current task token.
- 190** An error occurred obtaining the job step task token.

<b>192</b>	An error occurred attempting to issue an ETDES service.	<b>555</b>	An error occurred in setting the CIB count using QEDIT.
<b>197</b>	An error occurred invoking the DEVTYPE service.	<b>557</b>	The LX system token contains an invalid LX value.
<b>211</b>	TCB address not found in task management table.	<b>558</b>	Unable to reserve a system LX.
<b>301</b>	A required REQ address was not provided.	<b>559</b>	Unable to create an entry table.
<b>302</b>	An unexpected request was sent to a routine.	<b>560</b>	Unable to connect an entry table.
<b>303</b>	A request level is not supported by the current version.	<b>561</b>	The ALESERV extract service has failed.
<b>511</b>	An invalid parameter value was detected by a routine.	<b>562</b>	The ALESERV add service has failed.
<b>512</b>	An invalid function code was detected by a routine.	<b>563</b>	The ALESERV delete service has failed.
<b>513</b>	A service was invoked in an invalid environment, such as a client request in the server environment.	<b>564</b>	The ALESERV search service has failed.
<b>514</b>	A required storage area does not exist.	<b>576</b>	Unable to insert a node in a linked list.
<b>515</b>	A storage area is not accessible or is in the wrong key.	<b>577</b>	An error occurred during processing of a DETACH macro.
<b>516</b>	An unexpected condition was detected which indicates a logic error.	<b>578</b>	Unable to delete a node from a linked list.
<b>517</b>	A mutually exclusive value was detected which indicates a logic error.	<b>583</b>	Unexpected token passed to a parse action routine.
<b>519</b>	An invalid sub-type code was detected by a routine.	<b>584</b>	Unrecognized parse token.
<b>520</b>	A required module was not loaded or available.	<b>585</b>	Invalid display type key.
<b>530</b>	An error occurred during execution of the STIMER service.	<b>586</b>	A buffer is too small.
<b>531</b>	An error occurred during execution of the STIMER service.	<b>587</b>	A required buffer is not provided or the buffer length is zero.
<b>532</b>	An error occurred during execution of the TTIMER service.	<b>601</b>	A default CSCA was not found on the CSCA chain.
<b>533</b>	A failure occurred during termination of a server subtask.	<b>602</b>	A local server was not found in the server group.
		<b>603</b>	No servers were found in the server group.
		<b>604</b>	A communications protocol was not specified for a server in a server group.
		<b>605</b>	A communications protocol type was invalid.

- 606**  
The request queue name was not provided.
- 607**  
An index into the server status table was invalid.
- 608**  
A request requires the server status table but it is not defined.
- 609**  
The server status table is not marked active.
- 610**  
Unable to build the server status table.
- 611**  
An error occurred receiving a message.
- 612**  
The associated data retrieval routine for a request was not assigned.
- 613**  
Field offsets within the request were not assigned.
- 614**  
The transmission length for a request is zero.
- 615**  
The transmission length for a request is greater than the total length of the request.
- 616**  
The request origin is invalid in the current context. The request may have been forwarded but is not trusted.
- 617**  
The request is rejected because the request has already been marked as failed.
- 618**  
The request queue name is invalid, possibly because it is too long.
- 619**  
A server status value is incorrect.
- 620**  
A server status value is not expected in the current state.
- 621**  
A server request is not expected with the current server status.
- 622**  
The platform code for a queue manager is unacceptable.
- 623**  
The req fixed length is zero or greater than the total req length.
- 624**  
An invalid action character was detected.
- 625**  
An unsupported field was overtyped.

- 626**  
A base64 encoding has failed.
- 627**  
A data compression request has failed.
- 628**  
A data masking request has failed.
- 650**  
A JSON parse has failed.

---

**ISF102E**      **I/O ERROR DETECTED BY module ON I/O request FOR DDNAME *ddname*, RETURN CODE *return-code*, REASON CODE *reason-code*, additional-information.**

---

### Explanation

An error occurred in an input or output function requested by SDSF.

### User response

The additional information (if any) may include system messages for the requested I/O function. See the appropriate system messages manual for more information.

---

**ISF103E**      **MEMBER *member-name* NOT FOUND, DDNAME *ddname*.**

---

### Explanation

A member name specified as input to the server could not be found.

### User response

Correct the member name and retry the request.

---

**ISF104E**      **ALLOCATION OF LOGICAL PARMLIB FAILED, RETURN CODE *return-code*, REASON *reason-code***

---

### Explanation

An error occurred attempting to allocate the logical parmlib using the IEFPRMLB service.

### User response

Use the return and reason codes from the service to determine the cause of the error.

---

**ISF105E**      **DEALLOCATION OF LOGICAL PARMLIB FAILED, RETURN CODE *return-code*, REASON *reason-code***

---

## Explanation

An error occurred attempting to deallocate the logical parmlib using the IEFPRMLB service.

## User response

Use the return and reason codes from the service to determine the cause of the error.

---

<b>ISF106W</b>	<b>SDUMP ERROR OCCURRED IN MODULE <i>module</i>, RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	--

---

## Explanation

An error in taking an SDUMP occurred in module *module* with the indicated return and reason codes.

## User response

Use the return and reason codes to determine the cause of the error.

---

<b>ISF108E</b>	<b>DCB SYNAD INFORMATION <i>synad-text</i>.</b>
----------------	---

---

## Explanation

An I/O error has occurred on an input or output function requested by SDSF. The DCB SYNAD information returned as a result of the error is listed in *synad-text*.

## User response

Use the text to determine the cause of the error.

---

<b>ISF109E</b>	<b>DYNAMIC ALLOCATION OF DDNAME <i>ddname</i> FAILED, RETURN CODE <i>return-code</i>, REASON <i>reason-code</i>, INFO CODE <i>information-code</i>.</b>
----------------	---

---

## Explanation

SDSF attempted to allocate ddname *ddname*, but the allocation failed.

## User response

For information on dynamic allocation error codes, see the appropriate manual concerning system macros and facilities, or job management.

---

<b>ISF110I</b>	<b>LOGGING TO DDNAME <i>ddname</i> SUSPENDED, MESSAGES WILL BE DIRECTED TO THE HARDCOPY LOG.</b>
----------------	--

---

## Explanation

SDSF encountered an error using *ddname* as the server log. All server messages that are written to the log will be directed to the hardcopy log.

## User response

None required. If you want server messages to be written to the server log, stop and start the server, being sure you have a server log allocated. If you do not want logging, allocate the server log to a dummy data set.

---

<b>ISF111E</b>	<b>DYNAMIC ALLOCATION OF <i>dataset-name</i> FAILED, RETURN CODE <i>return-code</i>, REASON <i>reason-code</i>, INFO CODE <i>information-code</i></b>
----------------	---

---

## Explanation

SDSF attempted to allocate data set *dataset-name*, but the allocation failed.

## User response

For information on dynamic allocation error codes, see the appropriate manual concerning system macros and facilities, or job management.

---

<b>ISF112I</b>	<b>SDSF ABEND <i>ab-code</i> REASON <i>code</i> SERVER <i>server-name</i> MODULE <i>x</i> OFFSET <i>y</i> LEVEL <i>z</i> PSW <i>psw</i> CAB <i>cab</i> TEA <i>tea</i> BEA <i>bea</i> MODULE <i>x</i> OFFSET <i>y</i> <i>contents-of-registers</i></b>
----------------	---

---

## Explanation

SDSF has abended with the user or system abend code *ab-code*. User abend codes are in decimal; system abend codes are in hexadecimal. Variable *tea* is the translation exception address; *bea* is the breaking event address. The contents of registers, *contents-of-registers*, are displayed two registers per line, in the format *access-register/ general-purpose-register*.

## User response

The system programmer should refer to “SDSF user abend codes” on page 493 for information on the user abend codes, or the appropriate system codes manual for information on the system abend codes.

---

<b>ISF115E</b>	<b>SECURITY ERROR DETECTED BY <i>module-name</i> ON OPEN FOR DDNAME <i>ddname</i> resource-name</b>
----------------	---

---

### Explanation

An error occurred in an OPEN operation. In response to a SAF check from JES, SAF denied access to a SYSOUT data set.

### User response

See your security administrator.

---

<b>ISF116E</b>	<b>UNABLE TO LOCATE REQUESTED <i>jes-type</i> SUBSYSTEM NAMED <i>subsystem-name</i>.</b>
----------------	--

---

### Explanation

SDSF is attempting to process the JES2 or JES3 subsystem *subsystem-name* but it is not defined to the system. SDSF initialization is terminated with a U0080 abend.

### User response

Ensure that the subsystem has been specified correctly on the OPTIONS statement in ISFPRMxx, the JESNAME or JES3NAME command invocation options, or the isfjesname and isfjes3name REXX special variables.

---

<b>ISF120E</b>	<b>REQUEST FAILED, MODULE <i>module-name</i> WAS UNABLE TO OBTAIN <i>number</i> BYTES OF STORAGE FOR <i>area-name</i>.</b>
----------------	--

---

### Explanation

A request to obtain storage by SDSF *module-name* for *area-name* failed because the indicated bytes of storage were not available.

### User response

The request is not processed. If possible, increase the region size used to invoke SDSF.

In the REXX environment, use special variables or other filter options to limit the number of REXX variables needed to satisfy a request. For more information, type REXXHELP (ISPF only).

---

<b>ISF121I</b>	<b>MODULE ISFSM64 WAS UNABLE TO OBTAIN <i>number</i> BYTES OF STORAGE ( <i>nnn</i> SEGMENTS). CHECK MEMLIMIT VALUE.</b>
----------------	---

---

### Explanation

SDSF attempted to obtain storage that is above the bar (above the 2-gigabyte line) but the amount of storage was not available. The value for MEMLIMIT for the user ID may be too low. This message is issued only once per session.

### System action

SDSF attempts to obtain storage below the bar.

### User response

Contact your system programmer. If SDSF could not obtain the required storage below the bar, the request is not processed and an additional message is issued.

---

<b>ISF130E</b>	<b>UNABLE TO ADD <i>check-name</i> HEALTH CHECK, HZSADDCK RETURN CODE <i>return-code</i> REASON CODE <i>reason-code</i>.</b>
----------------	--

---

### Explanation

SDSF is attempting to add the check *check-name* to IBM Health Checker for z/OS. The HZSADDCK service has failed with the indicated return and reason codes. The check is not added. .

### User response

Use the return and reason codes to diagnose the error. They are described in [\*IBM Health Checker for z/OS User's Guide\*](#).

---

<b>ISF137I</b>	<b>SDSF SDUMP NOT TAKEN, SUPPRESSED BY DAE.</b>
----------------	---

---

### Explanation

SDSF attempted to take an SDUMP, but it has been suppressed by the Dump Analysis and Elimination (DAE) component.

### User response

None.

---

<b>ISF138E</b>	<b>POINT FAILED READING <i>dataset-</i> <i>name</i>, RETURN CODE <i>return-</i> <i>code</i>, RPLFDBK <i>feedback-code</i>, RPLRBAR <i>rba</i>.</b>
----------------	--

---

### Explanation

A POINT request failed in an attempt to read *dataset-name* with the indicated return code, RPL feedback



and relative block address. SDSF is unable to read the file.

When SYSLOG is being processed, *dataset-name* may be a logical data set name of the form *sysname*.SYSLOG.SYSTEM, where *sysname* is the MVS system name for the SYSLOG being processed. SDSF uses the current value of the SYSID command to derive the system name.

In a JES3 environment, a value of FF04FFFFFFFFFFFFFF for *rba* might indicate the SYSLOG data set is empty. This is to be expected if the SYSLOG is on a JES3 local system and no records have been written to it. In that case, you can issue the command SYSID \* to specify the global system. The global SYSLOG is processed regardless of which system you are logged on to.

### User response

Use the return code and feedback to diagnose the error. If the SYSLOG was being processed, verify that the value of SYSID is correct for the SYSLOG you want to process.

---

<b>ISF139E</b>	<b>GET FAILED READING <i>dataset-name</i>, RETURN CODE <i>return-code</i>, RPLFDBK <i>feedback-code</i>.</b>
----------------	--

---

### Explanation

A GET request failed in an attempt to read *dataset-name* with the indicated return code and RPL feedback. SDSF is unable to read the file.

### User response

Use the return code and feedback to diagnose the error.

---

<b>ISF142E</b>	<b>DEVICE NAME CONVERSION ERROR OCCURRED FOR DEVICE ID <i>device-id</i>, RETURN CODE <i>return-code</i>, REASON <i>reason-code</i>, INFO CODE <i>info-code</i>.</b>
----------------	---

---

### Explanation

An error occurred during the invocation of the JES device name conversion SSI. In the message text, the device id is the JES internal device being converted, the return code is from IEFSSREQ, the reason code is from SSOBRETN, and the info code is from SSJIRETN.

### User response

Use the return and reason codes to diagnose the error, and then follow your local procedures for contacting IBM for support.

---

<b>ISF144E</b>	<b>UNABLE TO OBTAIN HEALTH CHECKER CHECK INFORMATION ON SYSTEM <i>system</i>, HZSQQUERY CHECKINFO RETURN CODE <i>return-code</i>, REASON <i>reason-code</i>.</b>
----------------	--

---

### Explanation

An attempt to gather IBM Health Checker for z/OS data was unsuccessful because the HZSQQUERY CHECKINFO service failed.

### User response

See *IBM Health Checker for z/OS User's Guide* and use the return and reason codes from the HZSQQUERY CHECKINFO service to diagnose the error. If the error persists, follow your local procedures for calling IBM for service.

---

<b>ISF145E</b>	<b>REXX REQUEST SERVICE <i>service-name</i> FAILED, RETURN CODE <i>return-code</i>, REASON <i>reason-code</i>.</b>
----------------	--

---

### Explanation

An invocation of the REXX service *service-name* failed with the indicated return and reason code.

### User response

The request is not processed. Use the return and reason codes from the service to diagnose the error.

---

<b>ISF146I</b>	<b>REXX VARIABLE <i>variable-name</i> SET, RETURN CODE <i>return-code</i>, VALUE IS '<i>value</i>'.</b>
----------------	---

---

### Explanation

The indicated REXX variable has been assigned the indicated value. The return code corresponds to the SHVRET field returned by the IRXEXCOM service. This message is issued only in verbose mode.

### User response

None.

---

<b>ISF147I</b>	<b>REXX VARIABLE <i>variable-name</i> FETCHED, RETURN CODE <i>return-code</i>, VALUE IS '<i>value</i>'.</b>
----------------	---

---

### Explanation

The indicated REXX variable has been obtained and contains the indicated value. The return code corresponds to the SHVRET field returned by the

IRXEXCOM service. This message is issued only in verbose mode.

## User response

None.

---

<b>ISF148E</b>	<b>UNABLE TO OBTAIN SUBSYSTEM INFORMATION FOR SUBSYSTEM <i>subsystem-name</i>, RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	--

---

## Explanation

SDSF has attempted to obtain information about *subsystem-name* using the subsystem version information (SSVI) subsystem interface call but the SSI has failed. In the message text, *return-code* is the return code from IEFSSREQ and *reason-code* is the reason code in SSOBRETN.

## User response

Use the return and reason codes to diagnose the error or follow your local procedures to contact IBM for support.

---

<b>ISF149E</b>	<b>UNABLE TO OBTAIN <i>ssi-request</i> DATA FOR SUBSYSTEM <i>subsystem-name</i>, RETURN CODE <i>return-code</i>, SSOBRETN <i>ssob-return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	--

---

## Explanation

A subsystem request directed to *subsystem-name* failed for *ssi-request* data with the referenced SSI return code and SSOB return code. The reason code is for the specific SSI function being performed. The SDSF function that required the SSI data cannot be performed.

## User response

Use the request type and return codes to diagnose the error.

---

<b>ISF150E</b>	<b>COMMUNICATIONS ERROR OCCURRED PROCESSING <i>service-name</i>, RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>. ADDITIONAL INFORMATION: <i>additional information</i></b>
----------------	--

---

## Explanation

A error occurred while processing the indicated communications service. The required communication is not completed.

## User response

If the service name begins with MQ, a WebSphere MQ service has failed. Use the WebSphere MQ service return and reason codes, and the additional information to determine the cause of the error.

---

<b>ISF151E</b>	<b>MESSAGE REJECTED FROM UNSUPPORTED PLATFORM, PLATFORM CODE <i>code</i>, PLATFORM NAME <i>name</i></b>
----------------	---

---

## Explanation

An error occurred in communications between SDSF servers. A message was received from a platform that is not supported. The message is ignored.

## User response

If the message has been received in error, follow your local procedures for contacting IBM support.

---

<b>ISF152E</b>	<b>MESSAGE REJECTED FROM USER <i>user-identity</i> DUE TO UNEXPECTED FORMAT NAME <i>format-name</i>.</b>
----------------	--

---

## Explanation

A server request has been rejected due to an incorrect format name. The format is not recognized. The server does not process the request.

## User response

None required. If the message has been received in error, follow your local procedures for contacting IBM support.

---

<b>ISF153E</b>	<b>MESSAGE REJECTED FROM USER <i>user-identity</i> DUE TO INCORRECT APPLICATION IDENTITY.</b>
----------------	---

---

## Explanation

A server request has been rejected due to invalid data in the application identity data section of the message context. The request is not processed

## User response

If the message is issued in error, follow your local procedures for contacting IBM for support.

---

<b>ISF154E</b>	<b>REQUEST REJECTED, TARGET JES UNACCEPTABLE FOR REQUESTOR.</b>
----------------	---

---

### Explanation

A request for data has been processed by the server, but the target JES is not in the same MAS as the requestor. The request is rejected.

### User response

Ensure that the server group definition references only those JES subsystems in the same MAS as the client. If the problem persists, follow your local procedures for contacting IBM support.

---

<b>ISF155E</b>	<b>REQUEST REJECTED, TARGET SYSPLEX UNACCEPTABLE FOR REQUESTOR.</b>
----------------	---

---

### Explanation

A request for data has been processed by the server, but the target sysplex is not in the same sysplex as the requestor. The request is rejected.

### User response

Ensure that the server group definition references only those systems in the same sysplex as the client. If the problem persists, follow your local procedures for contacting IBM support.

---

<b>ISF156I</b>	<b>UNABLE TO OBTAIN SYSPLEX INFORMATION, IXCQUERY <i>function-name</i> FAILED, RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	--

---

### Explanation

An error occurred using the IXCQUERY service to gather sysplex information. The sysplex information is not shown.

### User response

Use the return and reason codes to diagnose the error.

---

<b>ISF160E</b>	<b>IXCSEND TO SERVER <i>server-name</i> FAILED, RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	---

---

### Explanation

The IXCSEND service has failed sending a message to *server-name* with the indicated return and reason code. The request is not processed.

### User response

Use the return and reason codes to diagnose the problem. Refer to [z/OS MVS Programming: Sysplex Services Reference](#). If the error persists, follow your local procedures for contacting IBM support.

---

<b>ISF161E</b>	<b>IXCSEND FROM SERVER <i>server-name</i> FAILED, RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	---

---

### Explanation

The IXCSEND service has failed receiving a message to *server-name* with the indicated return and reason code. The request is not processed.

### User response

Use the return and reason codes to diagnose the problem. Refer to [z/OS MVS Programming: Sysplex Services Reference](#). If the error persists, follow your local procedures for contacting IBM support.

---

<b>ISF162E</b>	<b>START SERVER <i>server-name</i> FAILED, IXCSRVR RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	--

---

### Explanation

The IXCSRVR start service has failed processing *server-name* with the indicated return and reason code. The request is not processed.

### User response

Use the return and reason codes to diagnose the problem. Refer to [z/OS MVS Programming: Sysplex Services Reference](#). If the error persists, follow your local procedures for contacting IBM support.

---

<b>ISF163E</b>	<b>STOP SERVER <i>server-name</i> FAILED, IXCSRVR RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	---

---

### Explanation

The IXCSRVR stop service has failed processing *server-name* with the indicated return and reason code. The request is not processed.

### User response

Use the return and reason codes to diagnose the problem. Refer to [z/OS MVS Programming: Sysplex](#)

*Services Reference*. If the error persists, follow your local procedures for contacting IBM support.

---

<b>ISF166E</b>	<b>SEND FAILED, BPX4QSN RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>, msgtype <i>message-type</i>, length <i>length</i>.</b>
----------------	--

---

### Explanation

An error occurred in sending a message using the BPX4QSN service with the indicated return and reason codes. The message type used when sending the message was *message-type*. The size of the message being sent is indicated by *length*. The message is not sent.

### User response

Use the return and reason codes to diagnose the error.

For return code 121 reason code xxxx030B, the size of the USS interprocess communication (IPC) message queue may be too small for SDSF to put a message on the queue. The message size needed by SDSF varies based on the type of request and the size of the response. Determine the maximum size of the queue by issuing the D OMVS,O operator command and inspecting the value of the IPCMSGQBYTES option. Use the length of the message being sent from the message text to increase the size of the queue as necessary.

Refer to [z/OS UNIX System Services Messages and Codes](#).

---

<b>ISF167E</b>	<b>RECEIVE FAILED, BPX4QRC RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>, msgtype <i>message-type</i>.</b>
----------------	---

---

### Explanation

An error occurred in receiving a message using the BPX4QRC service with the indicated return and reason codes. The message type used when sending the message was *message-type*. The message is not sent.

### User response

Use the return and reason codes to diagnose the error. Refer to [z/OS UNIX System Services Messages and Codes](#).

---

<b>ISF170I</b>	<b>SERVER <i>server-name</i> ARM REGISTRATION COMPLETE FOR ELEMENT TYPE <i>element-type</i>, ELEMENT NAME <i>element-name</i>.</b>
----------------	--

---

### Explanation

The server has successfully registered with ARM with the indicated element type and name.

### User response

None required.

---

<b>ISF171E</b>	<b>SERVER <i>server-name</i> ARM REGISTRATION FAILED FOR ELEMENT TYPE <i>element-type</i>, ELEMENT NAME <i>element-name</i>, RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	--

---

### Explanation

The server has attempted to register with ARM with the indicated element name and type. However, the registration has failed with the listed return and reason codes from the IXCARM macro.

### User response

Use the return and reason codes to understand the problem. Refer to [z/OS Security Server RACF Security Administrator's Guide](#).

---

<b>ISF172E</b>	<b>SERVER <i>server-name</i> ARM DEREGISTRATION FAILED, RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	---

---

### Explanation

The server has attempted to deregister from ARM, but the IXCARM service has failed with the indicated return and reason codes.

### User response

Use the return and reason codes to understand the problem. See [z/OS Security Server RACF Security Administrator's Guide](#).

---

<b>ISF174E</b>	<b>xxxx UNABLE TO LOAD MODULE <i>module</i>, RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	--

---

### Explanation

SDSF was unable to load the indicated module.

### User response

See the return and reason codes for information about the problem. If the codes indicate that the load module was not found, the libraries containing

the SDSF load modules may not have been correctly installed.

---

<b>ISF175W</b>	<b>xxxx UNABLE TO DELETE MODULE <i>module</i>, RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	--

---

### Explanation

SDSF was unable to delete the indicated module.

### User response

See the return and reason codes for information about the problem.

---

<b>ISF176E</b>	<b>UNABLE TO GATHER DATA FOR <i>jobname</i>, MODULE <i>module-name</i> LEVEL ERROR.</b>
----------------	---

---

### Explanation

A request to gather data for *jobname* failed because the level of *module-name* is incompatible with the SDSF requester. The SISFLPA and SISFLOAD data sets are not at the same level.

### User response

Ensure that the SISFLPA data set is at the same level as the SISFLOAD data set.

---

<b>ISF177E</b>	<b>UNABLE TO GATHER DATA FOR <i>jobname</i>, MODULE <i>module-name</i> NOT FOUND.</b>
----------------	---

---

### Explanation

A request to gather data for *jobname* failed because module *module-name* was not found. This may be because the SISFLPA and SISFLOAD data sets are not at the same level.

### User response

Ensure that the SISFLPA data set is at the same level as the SISFLOAD data set.

---

<b>ISF180I</b>	<b>TASK <i>task-id</i> IS BEING RESTARTED DUE TO ABEND.</b>
----------------	---

---

### Explanation

In response to an abend, the task indicated by *task-id* is being restarted.

### User response

None required.

---

<b>ISF181I</b>	<b>TASK (<i>task-name</i>, <i>taskid</i>) CANNOT BE RESTARTED DUE TO ABEND.</b>
----------------	---

---

### Explanation

The indicated task has abended and cannot be restarted. If the task is required for SDSF server execution, the server will be terminated.

### User response

Correct the problems indicated by the abend, or follow your local procedures for contacting IBM support

---

<b>ISF182I</b>	<b>TASK (<i>task-name</i>, <i>taskid</i>) HAS BEEN RESTARTED.</b>
----------------	---

---

### Explanation

The indicated task has been successfully restarted.

### User response

None required.

---

<b>ISF185E</b>	<b>ISF185E Internal SDSF parse error RC=<i>return-code</i> RSN=<i>reason-code</i></b>
----------------	---

---

### Explanation

During ISFPRMxx statement parsing an expected error was encountered. The parsing operation is abandoned and the SDSF parameters are left unchanged.

### User response

Follow your local procedures for reporting a problem to IBM.

---

<b>ISF190E</b>	<b>UNABLE TO CREATE DATASPACE <i>dataspace-name</i>, DSPSERV RETURN CODE <i>return-code</i>, REASON CODE <i>reason-code</i>.</b>
----------------	--

---

### Explanation

A failure has occurred trying to create the named data space. WTORs will not be displayed on the SR panel or on the Log panel.

### User response

Follow your local procedures for reporting a problem to IBM.

---

<b>ISF191E</b>	<b>UNABLE TO DELETE DATASPACE <i>dataspace-name</i> (<i>dataspace-generated-name</i>),</b>
----------------	--

---

**DSPSERV RETURN CODE** *return-code*, **REASON CODE** *reason-code*.

## Explanation

A failure has occurred trying to delete the named data space.

## User response

Follow your local procedures for reporting a problem to IBM.

---

**ISF192E**      **DATA NOT AVAILABLE, module RETURN CODE** *return-code*, **REASON CODE** *reason-code*, *additional-information*

## Explanation

A request for data could not be satisfied. The request failed with the indicated return and reason codes from the indicated module. If appropriate, additional information, *additional-information*, is added.

## User response

Use the return and reason code for the indicated module, and *additional-information* if it is included, to diagnose the error.

If *additional-information* refers to the SRB, retry the request.

For information about RMF return and reason codes, refer to [z/OS Resource Measurement Facility Messages and Codes](#).

---

**ISF193E**      **DATA NOT AVAILABLE, module SECURITY ERROR, RETURN CODE** *return-code*, **REASON CODE** *reason-code*.

## Explanation

A request for data could not be satisfied because of SAF security. The request failed with the indicated return and reason codes from the module *module*.

## User response

If you have been denied access in error, contact your security administrator.

Use the return and reason code for the indicated module to diagnose the error.

For information about RMF return and reason codes, refer to [z/OS Resource Measurement Facility Messages and Codes](#).

---

**ISF194E**

**INVOCATION OF IRXEXEC FAILED PROCESSING EXEC** *exec-name*, **RETURN CODE** *return-code*.

## Explanation

An unexpected error occurred after invocation of the IRXEXEC interface in response to a % action character. The message contains the return code from IRXEXEC.

## User response

Examine the return code and associated system messages, if any. For more information on the return codes from IRXEXEC, refer to [z/OS TSO/E REXX Reference](#).

---

**ISF195I**      **REXX EXEC** *exec-name*.

## Explanation

The REXX exec *exec-name* ended without returning a return code.

## User response

None required.

---

**ISF196I**      **REXX EXEC** *exec-name* **ENDED, RETURN CODE** *return-code*.

## Explanation

The REXX exec *exec-name* ended with the indicated return code.

## User response

Respond as appropriate, based on the return code.

---

**ISF197E**      **UNABLE TO INVOKE EXEC** *exec-name*, **NEITHER SYSPROC NOR SYSEXEC ALLOCATED.**

## Explanation

A % action character was issued to invoke a REXX exec against a row in a table, but neither the SYSEXC nor SYSPROC DD was allocated. The data set containing the exec must be allocated to either SYSEXEC or SYSPROC.

## User response

Allocate the data set containing the exec to either SYSEXEC or SYSPROC.

---

**ISF198E**      **UNABLE TO INVOKE EXEC** *exec-name*, **EXEC NOT FOUND.**

## Explanation

A % action character was issued to invoke a REXX exec, *exec-name*, against a row in a table. No data sets allocated to SYSEXC or SYSPROC contain a member with that name.

## User response

If the exec name was entered incorrectly, try the % action character again with the correct name. If the exec name is correct, ensure that the data set containing the exec is allocated to SYSEXEC or SYSPROC.

---

<b>ISF199E</b>	<b>ABEND <i>abend-code</i> REASON CODE <i>reason-code</i> OCCURRED PROCESSING REXX EXEC <i>exec-name</i>, EXEC STOPPED.</b>
----------------	---

---

## Explanation

An abend occurred in processing a REXX exec, *exec-name*. Process of the exec stopped.

## User response

Use the abend code and reason code to diagnose the problem.

---

<b>ISF300E</b>	<b>MODIFY COMMAND IGNORED DUE TO ERRORS.</b>
----------------	--

---

## Explanation

The text of an operator MODIFY command *command* was not recognized.

## User response

Correct the command and retry the request.

**Descriptor code:**  
5

---

<b>ISF301E</b>	<b><i>value</i> WAS EXPECTED IN COMMAND POSITION <i>position</i> BEFORE <i>keyword</i>.</b>
----------------	---

---

## Explanation

A value, *value*, was missing in the indicated position in the command.

## User response

Correct the command and retry the request.

**Descriptor code:**  
5

---

<b>ISF302E</b>	<b><i>value</i> WAS SEEN IN COMMAND POSITION <i>position</i> WHERE ONE OF THE FOLLOWING WAS EXPECTED: <i>valid-values</i>.</b>
----------------	--

---

## Explanation

An invalid value, *value*, was found at the indicated position in the command.

## User response

Correct the command using one of the listed valid values.

**Descriptor code:**  
5

---

<b>ISF303E</b>	<b>MODIFY COMMAND TEXT MISSING, COMMAND IGNORED.</b>
----------------	--

---

## Explanation

The MODIFY command was entered without required command text. The command is ignored.

## User response

Correct the command and retry the request.

**Descriptor code:**  
5

---

<b>ISF304I</b>	<b>MODIFY <i>parameter</i> COMMAND ACCEPTED.</b>
----------------	--

---

## Explanation

The indicated parameter of the MODIFY command was accepted for processing.

## User response

None required.

**Descriptor code:**  
5

---

<b>ISF305E</b>	<b>ABEND <i>abend-code</i> OCCURRED PROCESSING MODIFY COMMAND.</b>
----------------	--

---

## Explanation

An abend occurred in processing the MODIFY command. The command is not executed.

## User response

Use the abend code to diagnose the problem.

**Descriptor code:**

**ISF306E**      **MODIFY** *command* **COMMAND**  
**IGNORED DUE TO**  
**AUTHORIZATION FAILURE.**

### Explanation

A MODIFY command could not be processed because SAF checking has determined that the user is not authorized to issue the command.

### User response

If you have been denied access in error, refer to “[User authorization](#)” on page 367 for more information.

### Routing code:

2, 9

### Descriptor code:

5

**ISF307E**      **MODULE** *module* **NOT FOUND.**

### Explanation

A MODIFY D,MODULE command was issued for a module, but the module could not be located.

### User response

Verify that the module name was entered correctly. The module must be accessible or currently loaded by SDSF.

### Descriptor code:

5

**ISF308E**      **"value"** **WAS SEEN IN COMMAND**  
**POSITION** *position* **BUT NOT**  
**EXPECTED.**

### Explanation

An invalid value, *value*, was found at the indicated position in the command. The command is not processed.

### User response

Correct the command.

**ISF309E**      **Operator command rejected, not**  
**issued to main SDSF server.**

### Explanation

An operator command was issued to the SDSFAUX address space. This is not supported. All SDSF

operator commands must be issued to the main SDSF server address space.

### User response

Re-issue the command to the main SDSF server address space. If you are trying to stop the SDSFAUX address space, you must use the **F SDSF ,P AUX** command instead of **P SDSFAUX**.

### Descriptor code:

5

**ISF310I**      *server-name* **COMMUNICATIONS**  
**ID SERVER STATUS**  
**SYSTEM JESN MEMREQSPROC**  
*requests-processed***BER**  
*id server status*  
*system jesn member*  
**QMGR:** *qmgr* **REQUESTQ:** *server-q*  
**QMGR:** *qmgr* **CLIENTQ:** *client-q*  
**CLUSTER/CLUSTERNL:** *cluster-*  
*name*

### Explanation

Information about communication between SDSF servers is displayed in response to an operator command:

#### id

an identifier associated with the server

#### server

name of the server

#### status

status of the server

#### system

system on that the server is processing

#### jesn

JES2 subsystem for which the server gathers data

#### member

member of the MAS for the JES2 subsystem

#### requests-processed

number of requests processed

#### qmgr

name of the WebSphere MQ queue manager

#### server-q

name of the server request queue (shown only for the local server). The server request queue is used by the local server to get requests from the remote servers.

#### client-q

name of the client request queue. The client request queue is used by the client to send messages to the local server, and by the local server to send messages to the remote servers.



**cluster-name**  
name of the WebSphere MQ cluster or cluster  
name-list

**User response**

None required.

**ISF311I**                    **SERVER COMMUNICATIONS NOT  
ACTIVE.**

**Explanation**

A command to display information about server communication was issued, but communication between SDSF servers is not active.

**User response**

None required.

**Descriptor code:**

5

**ISF312I**                    *server-name* **DISPLAY**  
**SERVER STATUS: status** **DEFAULT:**  
*status*  
**COMMUNICATIONS: status**  
**PARMS: member/dataset-name**  
**XCF COMMUNICATIONS: xcf-**  
*status*

**Explanation**

In response to an operator command, information about the status of server communications is displayed. The server status codes are:

- CloseQ**  
request queue being closed
- Connected**  
connect to queue manager complete
- Connecting**  
connect to queue manager in progress
- CreateModelQ**  
create of model queue in progress
- CreatedModelQ**  
model queue create complete
- DeleteClientQ**  
delete of client queue in progress
- DeletedClientQ**  
delete of client queue complete
- DeleteModelQ**  
delete of model queue in progress
- DisableClientQ**  
client queue being disabled

- Disconnecting**  
disconnect from queue manager in progress
  - EnableClientQ**  
client queue being enabled
  - EnabledClientQ**  
client queue enable complete
  - Failed**  
prior initialization failed
  - Inactive**  
communications not active
  - OpenReqQ**  
request queue open in progress
  - OpenedReqQ**  
request queue open complete
  - OpenClientQ**  
client queue open in progress
  - OpenedClientQ**  
client queue open complete
  - SetSignal**  
event signal being set
  - Signalled**  
event signal complete
  - Starting**  
communications being started
  - Stopping**  
communications being stopped
  - TaskInit**  
task initialization in progress
  - TaskTerm**  
task termination in progress
  - TestComm**  
test communication in progress
- The **PARMS** keyword displays \*NONE\* rather than the ISFPRMxx member name when the server is started in NOPARM mode.
- Values for XCF application server status, *xcf-status*, are:
- Configured**  
SDSF can exploit XCF for sysplex requests
  - Not Configured**  
the server is not configured to use XCF for sysplex requests
- User response**
- None required.
- Descriptor code:**
- 4, 5
- ISF313I**                    *server-name* **MODULE DISPLAY**

**NAME:** *name* **EPADDR:** *entry-address*  
**FMID:** *module-fmid* **LEVEL:** *apar-level*  
**COMPDATE:** *date* **COMPTIME:** *time*

## Explanation

The service-level information for module *name*, including its compile date and time is displayed in response to a MODIFY D,MODULE command.

## User response

None.

**Descriptor code:**  
4, 5

**ISF314I** **ACCESS DENIED TO *class-name/***  
***resource-name* LEVEL *access-level***  
**DUE TO SAF NO DECISION.**

## Explanation

An attempt to access the resource *resource-name* protected by SAF class *class-name* with a requested access level of *access-level* has been denied. The SAF authorization check has resulted in a no-decision (indeterminate) result and SDSF has consequently failed the request.

## User response

In the JES3 environment, all resources must be protected through SAF. It may be necessary to define profiles so that the named resources can be accessed.

**ISF315I** ***server-name* XCF**  
**COMMUNICATIONS**  
**APPLICATION SERVER NAME:**  
***name***  
**TASKS ACTIVE: *nnn* IDLE: *nnn***  
**SENDS: *count* RECEIVES: *count***

## Explanation

In response to a display communications command, XCF communications data is displayed. *name* is the application server name being used by SDSF for XCF communications. A task is active if it is actively processing a request. An idle task is waiting for work. The send and receive counts indicate the number of messages sent or received by the server. The count is scaled using the K, M, G, T, and P characters or all asterisks if the count exceeds the space available.

## User response

None.

**Descriptor code:**  
4, 5

**ISF349I** **SDSF Sysplex Systems *sysname***  
***version status***

## Explanation

This message is issued in response to the **F SDSF,D SYS** operator command and shows the list of known systems in the sysplex. The z/OS operating system level is displayed (if known) in addition to the sysplex status of the system. Note that if the z/OS operating system level is not displayed, then the CFRM couple data sets will require reformatting to enable the required enhanced record format.

## User response

None.

**ISF351I** **SDSF JES Subsystems *Sysname***  
***JES Version Status***

## Explanation

In response to a **F SDSF,D JES** operator command, SDSF displays information about each JES subsystem in the MAS. The fields in the response are as follows:

- *Sysname* - System name for JES subsystem.
- *JES* - JES subsystem name.
- *Version* - JES level.
- *Status* - Status of the subsystem.

This command and response are intended for use by IBM service personnel.

## User response

None.

**ISF352I** **SDSF Connected Users *jobname***  
***ASID TCB connect group sessionID***

## Explanation

In response to a **F SDSF,D USER** operator command, SDSF displays information about each connected user. The fields in the response are as follows:

- *jobname* - Job name for the user.
- *ASID* - Hexadecimal address space ID.
- *TCB* - TCB address of the task that performed the connect.

- *connect* - Date stamp of the connect (yyyy/mm/dd-hh:mm:ss).
- *group* - SDSF group name assigned to the user.
- *sessionID* - The internal session ID.

## User response

None.

---

**ISF353I**      **SDSF Tasks** *Task TCB Jobname*  
*Samples CPU*

## Explanation

In response to a **F SDSF,D TASK** operator command, SDSF displays information about the CPU consumption of each server task. The fields in the response are as follows:

- *Task* - The server task name.
- *TCB* - The task TCB address.
- *Jobname* - Jobname of the SDSF server where the task is running.
- *Samples* - The number of performance samples.
- *CPU* - The amount of CPU consumed by the task (seconds).

## User response

None.

---

**ISF354I**      **SDSF Services** *name total first last*  
*diag*

## Explanation

This message is issued in response to an **F SDSF,D SERV** command. SDSF displays information about each data collection service that has been requested.

### *name*

The name of the SDSF command/service requested.

### *total*

The total number of requests issued since SDSF server start.

### *first*

The date and time of the first request (yyyy/mm/dd-hh:mm:ss).

### *last*

The date and time of the most recent request (yyyy/mm/dd-hh:mm:ss).

### *diag*

Internal diagnostic field for IBM.

## User response

None.

---

**ISF355I**      **SDSF XCF Communications**  
**Application server name:**  
*servername Name TCB RecvReq*  
*RecvData SendReq SendData*

## Explanation

In response to a **F SDSF,D COMM,DETAIL** command, SDSF displays information about each XCF communications task. The fields in the response are as follows:

- *Name* - Task name.
- *TCB* - TCB address of the task.
- *RecvReq* - Total number of IXCRECV requests.
- *RecvData* - Total bytes received.
- *SendReq* - Total number of IXCSEND requests.
- *SendData* - Total bytes sent.

## User response

None.

---

**ISF356I**      **SDSF Exits** *Name EPA Invoke*  
*Normal Return Abend*

## Explanation

In response to an **F SDSF,D EXIT** operator command, SDSF displays information about its exits and ENF routines. The fields in the response are as follows:

- *Name* - Exit routine name.
- *EPA* - Entry point address.
- *Invoke* - Number of times the exit has been driven.
- *Normal* - Number of normal execution responses.
- *Return* - Number of times the exit returned normally.
- *Abend* - Number of times the exit abended and recovered.

## User response

None.

---

**ISF361I**      **SDSF Command Help** *text*

## Explanation

This message is issued in response to the **F SDSF,HELP** operator command to list the syntax of all SDSF operator commands.

## User response

None.

---

<b>ISF401I</b>	<b>SERVER <i>server-name</i></b> <b>COMMUNICATIONS</b> <b>INITIALIZATION IN PROGRESS.</b>
----------------	---

---

## Explanation

The communications between SDSF servers is being initialized.

## User response

None required.

## Descriptor code:

3

---

<b>ISF402I</b>	<b>SERVER <i>server-name</i></b> <b>COMMUNICATIONS READY.</b>
----------------	--

---

## Explanation

Initialization of communications for the indicated SDSF server has completed successfully. The server is ready to begin communications with other SDSF servers.

## User response

None required.

---

<b>ISF403E</b>	<b>SERVER <i>server-name</i></b> <b>COMMUNICATIONS</b> <b>INITIALIZATION FAILED,</b> <b>COMMUNICATIONS NOT</b> <b>AVAILABLE.</b>
----------------	--

---

## Explanation

Communications for the indicated SDSF server did not initialize successfully. The server is not ready to begin communications with other SDSF servers.

## User response

See associated messages for an explanation of the error.

## Descriptor code:

7, 11

---

<b>ISF404I</b>	<b>SERVER <i>server-name</i></b> <b>COMMUNICATIONS STOPPED.</b>
----------------	--

---

## Explanation

Communications for the indicated server was stopped. Communications is no longer available.

## User response

Correct your server group definition in ISFPARMS and refresh them.

---

<b>ISF405I</b>	<b>SERVER <i>server-name</i></b> <b>COMMUNICATIONS IN USE,</b> <b>SERVERGROUP DEFINITION</b> <b>UNCHANGED.</b>
----------------	---

---

## Explanation

An attempt was made to modify the server group in ISFPARMS after the ISFPARMS were already being processed by the SDSF server. The request is ignored.

## User response

None required. You cannot change the properties of a server group defined in ISFPARMS after the server has begun processing the ISFPARMS. To change the properties of the server group, first stop the server with the STOP command.

---

<b>ISF406I</b>	<b>SERVER <i>server-name</i></b> <b>COMMUNICATIONS WAITING FOR</b> <b>CONNECTION.</b>
----------------	---

---

## Explanation

Communications for the indicated server are waiting for a connection. The server cannot communicate with other servers in the group, and data from that server will not be included on the SDSF panels. It may be that WebSphere MQ is not active.

## User response

See accompanying messages for more information. If WebSphere MQ is not active, start it.

## Descriptor code:

7, 11

---

<b>ISF407I</b>	<b>SERVER <i>server-name</i></b> <b>COMMUNICATIONS WAITING FOR</b> <b>ACCESS TO REQUEST QUEUE.</b>
----------------	--

---

## Explanation

During communications initialization, the server detected that the request queue name was in use. The server requires exclusive control of the request queue. Initialization will wait until the queue name is available. If the server has been recycled, there might be a delay until the queue manager marks the queue as being available.

The server will periodically try the failing request until the queue name is accessed.

## User response

See accompanying messages for more information. Verify that the queue name is not in use by any other application.

### Descriptor code:

7, 11

<b>ISF408I</b>	<b>SERVER <i>server-name</i> DEFINING OBJECT <i>object-name</i> ON QUEUE MANAGER <i>queue-manager-name</i>.</b>
----------------	---

## Explanation

SDSF is attempting to define an object using the named queue manager.

## User response

None required.

<b>ISF409E</b>	<b>SERVER <i>server-name</i> UNABLE TO DEFINE OBJECT <i>object-name</i> ON QUEUE MANAGER <i>queue-manager-name</i>.</b>
----------------	---

## Explanation

SDSF was unable to define the indicated object on the named WebSphere MQ queue manager.

## User response

See additional messages for more information.

<b>ISF410I</b>	<b>SERVER <i>server-name</i> HAS DEFINED OBJECT <i>object-name</i> ON QUEUE MANAGER <i>queue-manager-name</i>.</b>
----------------	--

## Explanation

SDSF defined the indicated object on the named WebSphere MQ queue manager.

## User response

None required.

<b>ISF411I</b>	<b>RESPONSE FROM <i>queue-manager</i>: <i>response-text</i>.</b>
----------------	--

## Explanation

The SDSF server has invoked the WebSphere MQ system command interface to perform an administrative request, such as creating a queue. The queue manager has responded with the indicated text.

## User response

None required.

<b>ISF412I</b>	<b>COMMUNICATIONS WITH SERVER <i>server-name</i> SYSTEM <i>system-name</i> STOPPED.</b>
----------------	---

## Explanation

Communications has been stopped with the indicated server in the server group. Requests will no longer be forwarded to the server for processing.

## User response

Use the start communications command to resume processing for the server.

### Descriptor code:

7, 11

<b>ISF413E</b>	<b>SERVER ID <i>server-id</i> NOT PROCESSED, SERVER NOT FOUND IN SERVERGROUP.</b>
----------------	---

## Explanation

A command was entered to modify a server in the server group, but the server ID was not recognized. The command is not processed.

## User response

Retry the command with the correct server ID. To display the server ID, use the server operator command `F server-name, DISPLAY,C`.

### Descriptor code:

5

<b>ISF414I</b>	<b>SERVER <i>server-name</i> SYSTEM <i>system-name</i> NOT PROCESSED, SERVER NOT FOUND IN SERVERGROUP.</b>
----------------	--

## Explanation

A command was entered to modify a server in the server group, but the server and system name patterns did not match any server. The command is not processed.

## User response

Retry the command with the correct server ID. To display the server and system names, use the server operator command:

```
F server-name, DISPLAY,C.
```

**Descriptor code:**

5

---

**ISF415I**      **SERVER *server-name* SYSTEM *system-name* STARTED, CURRENT STATUS IS *status-text*.**

---

**Explanation**

A server with the indicated name has been started.  
The status of the server is *status-text*.

**User response**

None required.

**Descriptor code:**

5

---

**ISF416I**      **SERVER *server-name* COMMUNICATIONS WILL BE RESTARTED.**

---

**Explanation**

Communications with *server-name* is being restarted.  
A restart may have been necessary because the connection was broken or was quiescing. Additional messages will be issued indicating when the restart is complete.

**User response**

None required.

---

**ISF417I**      **SERVER *server-name* COMMUNICATIONS STOPPING.**

---

**Explanation**

Communications is ending for *server-name*. No additional sysplex requests will be processed.

**User response**

None required.

---

**ISF418I**      **COMMAND TO *queue-manager-name*: *command-text***

---

**Explanation**

The indicated queue manager administrative command is being sent to the queue manager for processing.

**User response**

None required.

**ISF420I**


---

**SERVER *server-name* DELETING OBJECT *object-name* ON QUEUE MANAGER *queue-manager-name*.**

---

**Explanation**

The SDSF server is deleting the indicated WebSphere MQ object on queue manager *queue-manager-name*, because QDELETE(YES) was specified on the COMM statement in ISFPARMS for the server. The object was originally created by the SDSF server.

**User response**

None required.

**ISF421I**


---

**SERVER *server-name* HAS DELETED OBJECT *object-name* ON QUEUE MANAGER *queue-manager-name*.**

---

**Explanation**

The SDSF server has deleted the indicated WebSphere MQ object on queue manager *queue-manager-name*. The object was originally created by the SDSF server.

**User response**

None required.

**ISF422E**


---

**SERVER *server-name* UNABLE TO DELETE OBJECT *object-name* ON QUEUE MANAGER *queue-manager-name*.**

---

**Explanation**

The indicated WebSphere MQ object was not deleted by the SDSF server because the object was in use by WebSphere MQ. The server attempted to delete the object because QDELETE(YES) was specified on the COMM statement of ISFPARMS.

**User response**

See additional messages in the server joblog for more information.

**ISF423I**


---

**SERVER *server-name* COMMUNICATIONS WAITING FOR ACCESS TO CLIENT REQUEST QUEUE.**

---

**Explanation**

During communications initialization, the SDSF server detected that the client request queue was in use. The server requires exclusive control of the client request

queue. Initialization will wait until the queue name is available. If the server has been recycled, there might be a delay until the queue manager marks the queue as being available.

The server will periodically try the failing request until the queue name is accessed.

### User response

None required.

### Descriptor code:

7, 11

---

**ISF424E**      **SERVER *server-name* UNABLE TO DEFINE OBJECT *object-name* ON QUEUE MANAGER *queue-manager-name*, OBJECT ALREADY EXISTS.**

---

### Explanation

The SDSF server was unable to create the indicated WebSphere for MQ object on the named queue manager because the object already exists.

### User response

To have the object redefined by the server, specify QREPLACE(YES) on the COMM statement for the server in ISFPARMS.

---

**ISF425I**      **SERVER *server-name* CLIENT QUEUE *queue-name* HAS A TARGET OF *target-queue-name* THAT DIFFERS FROM THE REQUEST QUEUE NAME OF *request-queue-name*.**

---

### Explanation

During communications initialization, the SDSF server has detected that the client request queue has been defined with a target queue that differs from the expected name. The client request queue should be a queue alias for the server request queue. Processing continues. However, the server may not receive messages sent to the client queue because the target does not match.

### User response

To have the server redefine the client request queue, specify QREPLACE(YES) on the COMM statement of ISFPARMS for the server.

---

**ISF426E**      **SERVER *server-name* CLIENT QUEUE *queue-name* CONFIGURED FOR CLUSTER *cluster-name* BUT**

---

### **QUEUE DEFINED FOR CLUSTER *cluster-name-two*.**

### Explanation

The SDSF server has detected an inconsistency in the definition of WebSphere MQ queue *queue-name*. The cluster name specified on the COMM statement of ISFPARMS does not match the cluster attribute for the queue. The cluster name specified for the SDSF server in ISFPARMS must match the name associated with the queue. Communications initialization failed.

### User response

Check that the cluster name on the COMM statement is correct. To have the server redefine the queue, use the QREPLACE(YES) option of the COMM statement.

---

**ISF427E**      **SERVER *server-name* CLIENT QUEUE *queue-name* CONFIGURED FOR CLUSTER NAMELIST *comm-namelist-name* BUT QUEUE DEFINED FOR CLUSTER NAMELIST *queue-namelist-name*.**

---

### Explanation

The SDSF server has detected an inconsistency in the definition of WebSphere MQ queue *queue-name*. The cluster namelist specified on the COMM statement of ISFPARMS does not match the cluster attribute for the queue. The cluster namelist specified for the SDSF server in ISFPARMS must match the namelist associated with the queue. Communications initialization failed.

### User response

Check that the cluster namelist on the COMM statement is correct. To have the server redefine the queue, specify QREPLACE(YES) on the COMM statement in ISFPARMS.

---

**ISF428I**      **SERVER *server-name* UNABLE TO DISABLE OBJECT *object-name*.**

---

### Explanation

During server termination, a communications error prevented the server from disabling *object-name*. An object is disabled to prevent subsequent requests from being directed to it. Server communications continues.

Other servers in the server group may continue to send requests to this server. This may result in delays because the requests will timeout rather than being rejected immediately.

## User response

Use any additional error messages issued by the server to determine the cause of the problem.

---

<b>ISF429I</b>	<b>SERVER <i>server-name</i> NOT DEFINING OBJECT <i>object-name</i>, QUEUE DEFINITION PROHIBITED.</b>
----------------	---

---

## Explanation

The server is not defining *object-name* because the QDEFINE initialization option has been specified as NO. Initialization continues. However, if *object-name* is required by the server but has not already been defined, initialization may fail.

## User response

You can change the QDEFINE initialization option on the COMM statement of ISFPARMS.

**Note:** The COMM statement is obsolete as of z/OS V2R3 because WebSphere MQ support is removed. The statement is accepted but not syntax checked. A diagnostic message is issued to the log.

---

<b>ISF432E</b>	<b>SETTINGS DESCRIPTOR COLUMNS LENGTH <i>length</i> EXCEEDS MAXIMUM LENGTH OF <i>maximum-length</i>.</b>
----------------	--

---

## Explanation

The columns list provided in the settings descriptor is too long and exceeds the maximum length. The columns list is ignored. An external call environment is used by the SDSF CIM provider.

## User response

Follow your local procedures for contacting IBM for service.

---

<b>ISF433I</b>	<b>SERVER <i>server-name</i> XCF CONNECTION ESTABLISHED AS SERVER <i>xcf-application-server-name</i>.</b>
----------------	---

---

## Explanation

The SDSF server *server-name* has identified itself as *xcf-application-server-name* and is ready to process requests using XCF.

## User response

None.

---

<b>ISF434I</b>	<b>SERVER <i>server-name</i> CONNECTION WITH XCF STOPPING.</b>
----------------	--

---

## Explanation

The SDSF server *server-name* is stopping communication with XCF.

## User response

None.

---

<b>ISF435I</b>	<b>SERVER <i>server-name</i> CONNECTION WITH XCF STOPPED.</b>
----------------	---

---

## Explanation

The SDSF server *server-name* has stopped communication with XCF.

## User response

None.

---

<b>ISF436E</b>	<b>NO SYSTEMS SATISFY SYSTEM NAME FILTER. USE THE SYSNAME COMMAND TO CHANGE THE VALUE.</b>
----------------	--

---

## Explanation

A request for sysplex data has been processed but the current SYSNAME value does not match any system in the sysplex. The request is not processed.

## User response

Use the SYSNAME command to change the system names that will be processed.

---

<b>ISF437I</b>	<b>DATA NOT AVAILABLE FROM SYSTEMS: <i>system-name-list</i>.</b>
----------------	--

---

## Explanation

A sysplex request has been sent but was not completed because one or more systems could not process it. Results will be shown for the systems that were able to respond.

This condition can occur when the target system level is not at the level required by the requestor, the data returned by the system is out of date, or the timeout interval has been exceeded.

Data for a system may be out of date if SDSFAUX is not active or the required data gatherer is stopped. When the system is out of date, data from the last data



gathering interval will be shown. An asterisk will be appended to the system name in the *system-name-list* to identify the system.

### User response

If the systems are not at the required level, no action is necessary. However, the request cannot be completed until all systems are at the required level.

If the system is out of date, ensure SDSFAUX is active and that all required data gatherer tasks are running. An SDSFAUX restart may be required.

If the timeout interval has been exceeded, issue the **SET TIMEOUT** command to change the interval and retry the request.

---

<b>ISF438I</b>	<b>XCF SERVER NAME <i>server-name</i> NOT PROCESSED SINCE SERVER <i>xcf-application-name</i> ALREADY ACTIVE.</b>
----------------	--

---

### Explanation

A request to start XCF communications using *server-name* has not been processed because SDSF is already connected to the XCF application server *xcf-application-name*. *server-name* cannot be changed while the application server is active.

### User response

Stop SDSF XCF communications and then retry the request.

---

<b>ISF439I</b>	<b>SERVER <i>server-name</i> XCF CONNECTION ALREADY ESTABLISHED AS SERVER <i>xcf-application-name</i>.</b>
----------------	--

---

### Explanation

SDSF server *server-name* has processed a request to start XCF communications, but the application server is already active as *xcf-application-name*.

### User response

None.

---

<b>ISF440I</b>	<b>XCF SERVER <i>xcf-application-name</i> CANNOT BE UNDEFINED SINCE IT IS ALREADY ACTIVE.</b>
----------------	---

---

### Explanation

While processing a command to refresh ISFPRMxx, SDSF encountered a CONNECT statement that defines XCFSRVNM(NONE) to disable the use of XCF. However,

the XCF application server is already active. The refresh is processed but there is no change to the XCF status.

### User response

To undefine XCF, stop communications prior to the refresh or restart the server.

---

<b>ISF441E</b>	<b>DATA NOT AVAILABLE FROM ANY SYSTEM.</b>
----------------	--

---

### Explanation

A request for sysplex data has been made, but no systems have responded within the timeout interval. The systems may be busy or unable to process the request.

### User response

Review the timeout interval specified with the SET TIMEOUT command and retry the request.

---

<b>ISF442I</b>	<b>SERVER <i>server-name</i> XCF COMMUNICATIONS READY.</b>
----------------	--

---

### Explanation

SDSF is ready to accept sysplex requests using XCF. *server-name* is the name of the SDSF server.

### User response

None.

---

<b>ISF443I</b>	<b>DATA NOT AVAILABLE FROM SYSTEM <i>system-name</i>, system level too low.</b>
----------------	---

---

### Explanation

A sysplex request has been sent but could not be completed because the target system level is too low. The level of the target system is not at the level required by the requestor, so no data is returned.

### User response

None required. However, the request cannot be completed until the system is at the required level.

---

<b>ISF450I</b>	<b>SERVER <i>server-name</i> starting <i>sdsfaux-name</i></b>
----------------	---

---

### Explanation

SDSF server *server-name* has determined that the SDSFAUX address space is not active and is starting *sdsfaux-name*.

## User response

No response is required.

**ISF451I**      **SERVER** *server-name* stopping  
*sdsfaux-name*

## Explanation

During the shutdown of SDSF server *server-name*, SDSF has determined that SDSFAUX address space is active and is stopping *sdsfaux-name*.

## User response

No response is required.

**ISF452E**      **SDSFAUX COMMUNICATIONS  
FAILED, RETURN CODE** *0xreturn-  
code*, **REASON CODE** *0xreason-  
code*, **function** *function-name*,  
**additional information**

## Explanation

An internal SDSF request (*function-name*) has been sent to the SDSFAUX address space but has failed with the indicated return and reason code in hexadecimal. If available, additional information may be provided that describes the error.

The return code is as follows:

Return code (hexadecimal)	Description
00	Success
04	Warning
08	Error
0C	Environment error
10	Severe error
14	Fatal error

The *reason-code* is of the form *xxxxrrrr* where *xxxx* is an internal identifier for the module that has detected the error and *rrrr* is the reason code. The *reason-code* is as follows:

Reason code (hexadecimal)	Description	Response
xxxx0406	Not ready	A request could not be processed because the SDSF server is initializing or

Reason code (hexadecimal)	Description	Response
		ISFPRMxx has not yet been activated. Reaccess SDSF and try the request later.
xxxx040A	Results truncated	SDSF was unable to complete all data gathering requests because too much data was returned. Refine your request if possible and retry.
xxxx040C	Not started	SDSF was unable to complete all data gathering requests because a required MVS service or component was not started.  For the CSR panel, ensure that VSM CSA and SQA storage tracking are active.  For the GT panel, ensure that the generic tracker is tracking events.
xxxx0410	Partial results	SDSF was unable to complete all data gathering requests because too much data was returned. Refine your request if possible and retry.

Reason code (hexadecimal)	Description	Response
xxxx0411	Partial results	SDSF was unable to complete all data gathering requests because too much data was returned. Refine your request if possible and retry.
xxxx0412	RMF required	SDSF was unable to complete a data gathering request because RMF is required. Verify that RMF Monitor I is active.
xxxx0413	RMF not installed	SDSF was unable to complete a data gathering request because RMF is not installed. Verify that module ERBSMFI can be loaded.
xxxx0415	Out of date	A data gatherer task was stopped or unavailable. The results being shown may be out of date.
xxxx0801	Not found	Ensure that the SDSFAUX address space has been started.
xxxx0804	System level too low	A request has been directed to a target system that does not support it. The system level is too low for the request.

Reason code (hexadecimal)	Description	Response
xxxx0805	Not active	A request could not be completed because a required component is not active. Verify that SDSFAUX is started and active.
xxxx0806	Access denied	For function connect, verify user is authorized to the ISF.CONNECT. <i>system</i> resource in the SDSF class.  For other functions, enable security tracing using the SET SECTRACE command to determine the resource for which access is needed.
xxxx080F	Timeout	A request did not complete with the timeout interval.  Some requests may be delayed if they require I/O to complete or if the system is busy. You can increase the timeout interval with the SET TIMEOUT command.

Reason code (hexadecimal)	Description	Response
xxxx0813	SDSFAUX unavailable	A request could not be processed because SDSFAUX is not started. Ensure the SDSF server is active and refresh ISFPRMxx to restart SDSFAUX.
xxxx081B	User ID no longer valid	SDSF was unable to complete all data gathering requests. This might happen if a valid user ID does not exist or if the user ID has been revoked in the remote system.
xxxx081E	Connect failed	SDSF was unable to connect to the SDSF server. This may be due to the task already being connected.
xxxx082F	Send to SDSFAUX failed	SDSF was unable to gather remote data because the send using XCF failed. Verify that all target systems are available.
xxxx0830	Receive by SDSFAUX failed	SDSF was unable to receive results from XCF possibly because too much data was returned or a timeout occurred. Refine your request

Reason code (hexadecimal)	Description	Response
		and use the SET TIMEOUT command to increase the timeout.
xxxx0832	SDSFAUX server down	The SDSFAUX server is down. Re-access SDSF after the server restarts and retry your request.
xxxx0840	Bad ASID	The address space ID is invalid or the target job is no longer valid, possibly because the job has ended.
xxxx0852	ASID not found	ASID not found in server for client, possibly because the client is no longer connected.
xxxx0858	SDSFAUX shutdown in progress	SDSFAUX is shutting down. Retry your request after SDSFAUX restarts.
xxxx0880	Connect failed, no group assignment	Server connect failed because the user could not be mapped to an SDSF group.
xxxx0896	Connect failed	Server connect failed due to failure to establish SDSF environment.
xxxx089C	HZSQUERY failed	The z/OS Health Checker service HZSQUERY has failed.

Reason code (hexadecimal)	Description	Response
xxxx089D	Request failed	Client request failed because server not able to process request.
xxxx089E	Request failed	Client request failed because server not able to processed authorized service or user not authorized.
xxxx08A6	Not authorized to JES name	Server connect failed because client not authorized to requested JES name.
xxxx08A7	JES not available	A request was not completed because the JES subsystem is not available.
xxxx08A8	JES SSI failed	A data gathering request failed because an error was returned by the subsystem interface.
Other	Internal error	An internal error has occurred. Follow your local procedures for contacting IBM for support.

### User response

Use the additional information to diagnose the error. If no information is provided or the error cannot be resolved, contact IBM Software Support.

---

**ISF453I**      *sdsfaux-name is already active*

### Explanation

During initialization of the SDSF server or a refresh of ISFPRMxx, SDSF has determined that SDSFAUX is already active and does not need to be started.

Parameters related to SDSFAUX on the CONNECT statement such as AUXPROC, AUXNAME, and AUXSAF are ignored.

### User response

If changes have been made to the CONNECT statement related to SDSFAUX, stop and start the SDSF server for the changes to take effect.

---

**ISF454I**      **jobname not active, STOP command ignored**

### Explanation

An attempt was made to stop the SDSFAUX address space using the **F SDSF, STOP AUX** operator command. The SDSF server has determined that the SDSFAUX address space is not active and has ignored the STOP command.

### User response

None.

---

**ISF455I**      **Command entered: opercmd**

### Explanation

The *opercmd* has been entered as a modify command to the SDSF server. This message logs the command text in the HSFLOG DDname.

### User response

None.

---

**ISF456I**      **Jobname *jobname* stopped, processing complete**

### Explanation

During SDSF and/or SDSFAUX termination, this message is issued when main processing has stopped and just prior to the address space termination.

### User response

None.

---

**ISF458E**      **NOT AUTHORIZED TO CONNECT TO SDSF SERVER. VERIFY READ ACCESS TO THE ISF.CONNECT.system RESOURCE IN THE SDSF CLASS**

### Explanation

An attempt to connect to the SDSF server has been denied. The probable cause is the user does not

have read access to the resource ISF.CONNECT.system in the SDSF SAF class. Connection to the server is required for access to SDSF functionality.

### User response

Ensure the user has access to the SAF resource that controls connection to the SDSF server. Additional messages may have been issued by your external security manager (such as RACF) that further describe the error.

---

<b>ISF488E</b>	<b>SDSF NOT STARTED DUE TO ERRORS IN START PARAMETERS.</b>
----------------	--

---

### Explanation

One or more parameters on the EXEC statement for the SDSF server was not recognized.

### User response

Correct the parameters and retry the request.

---

<b>ISF491E</b>	<b>value WAS EXPECTED IN START PARAMETER POSITION <i>position</i> BEFORE <i>string</i>.</b>
----------------	---

---

### Explanation

SDSF encountered an error in a parameter on the START command.

### User response

Use the position and string values to identify the parameter in error. Retry the START command with a corrected parameter.

---

<b>ISF492E</b>	<b>value WAS SEEN IN START PARAMETER POSITION <i>position</i> WHERE ONE OF THE FOLLOWING WAS EXPECTED: <i>list-of-values</i>.</b>
----------------	---

---

### Explanation

SDSF encountered an error in a parameter on the START command. The position of the error in the command string is indicated by *position*.

### User response

Retry the START command using one of the valid values.

---

<b>ISF493I</b>	<b>ABEND <i>abend-code</i> OCCURRED PROCESSING START PARAMETERS.</b>
----------------	--

---

### Explanation

An abend occurred in processing the START command. The command is executed with any parameters that were processed prior to the abend.

### User response

Use the abend code to diagnose the problem. You may want to use the MODIFY command to reset server options.

---

<b>ISF515E</b>	<b>SDSF INITIALIZATION FAILED FOR SERVER <i>server</i>.</b>
----------------	---

---

### Explanation

Initialization of server *server* failed to complete. Messages describing the reason for the failure will have been issued prior to this one.

### User response

Use the error messages issued by SDSF to determine the cause of the initialization failure.

---

<b>ISF517E</b>	<b>SDSF SERVER WAS NOT STARTED DUE TO INVALID EXECUTION ENVIRONMENT, POSSIBLE MISSING PPT ENTRY.</b>
----------------	--

---

### Explanation

The SDSF server could not start due to an incorrect execution environment. The server is not running in the correct protect key.

### User response

Verify that a PPT entry has been defined in your SCHEDxx member of the parmlib concatenation for program ISFHCTL.

---

<b>ISF518E</b>	<b>SDSF SERVER <i>server</i> NOT STARTED, NOT ENABLED FOR EXECUTION</b>
----------------	---

---

### Explanation

The SDSF server has attempted to register its invocation on a z/OS system, but the registration has failed. The server is not initialized.

### User response

If SDSF should be enabled for execution, check the IFAPRDxx member of your parmlib concatenation for an entry for SDSF.

---

<b>ISF527E</b>	<b>SDSF SERVER <i>server</i> NOT STARTED, START COMMAND MUST BE USED.</b>
----------------	---

---

### Explanation

An attempt was made to start the SDSF server *server* through a batch job. The server must be started with the MVS START command.

### User response

Issue the MVS START command to start the SDSF server.

---

<b>ISF528E</b>	<b>SDSF SERVER <i>server</i> NOT STARTED, INVALID OPERATING SYSTEM LEVEL.</b>
----------------	---

---

### Explanation

The SDSF server requires a higher level of the operating system than was found. The server was not started.

### User response

None.

---

<b>ISF538E</b>	<b>SDSF SERVER <i>server</i> ALREADY ACTIVE.</b>
----------------	--

---

### Explanation

The START command was entered for an SDSF server that is already active. The command was ignored.

### User response

None.

---

<b>ISF540I</b>	<b>SERVER <i>server-name</i> ASSIGNED AS DEFAULT SERVER.</b>
----------------	--

---

### Explanation

The indicated SDSF server has been made the default server. If no server is specified in the assembler ISFPARMS, users who do not explicitly state the server name on the SDSF command will connect to this server when accessing SDSF. Any server specified in ISFPARMS will be ignored.

### User response

None required.

---

<b>ISF541I</b>	<b>SERVER <i>server-name</i> UNASSIGNED AS DEFAULT SERVER.</b>
----------------	--

---

### Explanation

The indicated SDSF server had been the default server but is no longer the default server. Either another server has been made the default server, or the server is terminating, or ISFPARMS has been refreshed with a different option on the CONNECT statement.

### User response

None required.

---

<b>ISF542I</b>	<b>SERVER <i>server-name</i> NOT ASSIGNED AS DEFAULT SERVER, SERVER <i>server-default-name</i> ALREADY ASSIGNED.</b>
----------------	--

---

### Explanation

The indicated SDSF server, *server-name*, was not made the default server because a default server, *server-default-name*, already has been assigned.

### User response

None required. To make the server the default, regardless of whether a default has already been assigned, change the DEFAULT option on the CONNECT statement in ISFPARMS to DEFAULT(YES).

---

<b>ISF543I</b>	<b>SERVER <i>server-name</i> ALREADY ASSIGNED AS DEFAULT SERVER, ASSIGNMENT UNCHANGED.</b>
----------------	--

---

### Explanation

Processing ISFPARMS has resulted in no change to the default SDSF server. The indicated server, *server-name*, is the default server.

### User response

None required.

---

<b>ISF544E</b>	<b><i>option</i> REJECTED, NOT AUTHORIZED FOR USE.</b>
----------------	--

---

### Explanation

The named REXX option was rejected because the user is not authorized to use it.

### User response

None required.

---

**ISF546I**                    **OPTIONS NOT APPLICABLE TO THE INITIAL COMMAND IGNORED.**

---

**Explanation**

SDSF was invoked with initial command options, but the options are not applicable to the initial panel being invoked. The initial options are ignored.

**User response**

None required.

---

**ISF595I**                    **Task *taskname* property *propname* set to *value***

---

**Explanation**

During SDSFAUX task initialization, the *taskname* has set the *propname* to the indicated *value*. These properties control the performance policy for data collection task. This message appears only in the HSFLOG output.

**User response**

None.

---

**ISF701I**                    **SDSF TRACE STARTED USING TRACE MASK *trace-mask*.**

---

**Explanation**

In response to an operator command, the current trace mask is displayed.

**User response**

None required.

---

**ISF702I**                    **SERVER *server-name* DEBUG MODE IS ENABLED.**

---

**Explanation**

In response to an operator command, the current status for diagnostic mode is displayed.

**User response**

None required.

---

**ISF703I**                    **SERVER *server-name* DEBUG MODE IS DISABLED.**

---

**Explanation**

In response to an operator command, the current status for diagnostic mode is displayed.

**User response**

None required.

---

**ISF709I**                    **SDSF TRACE IS INACTIVE, TRACE MASK IS "*trace-mask*".**

---

**Explanation**

In response to an operator command, the current status for SDSF server trace is displayed.

**User response**

None required.

---

**ISF710I**                    **SDSF TRACE IS ACTIVE USING TRACE MASK "*trace-mask*".**

---

**Explanation**

In response to an operator command, the current status for SDSF server trace is displayed.

**User response**

None required.

---

**ISF711I**                    **SDSF TRACE STARTED USING TRACE MASK *trace-mask*.**

---

**Explanation**

In response to the TRACE command, tracing has been started with the indicated trace mask.

**User response**

None required.

---

**ISF713E**                    **SDSF TRACE INITIALIZATION FAILED, RETURN CODE *return-code*, REASON CODE *reason-code*.**

---

**Explanation**

In response to the TRACE command, initialization of SDSF trace has failed with the indicated return and reason codes.

**User response**

Use the indicated return and reason codes to diagnose the problem.

**Descriptor code:**

7, 11

---

**ISF714I**                    **SDSF TRACE IS NOW INACTIVE.**

---



## Explanation

In response to a TRACE OFF command, SDSF trace has become inactive.

## User response

None required.

---

<b>ISF715I</b>	<b>SDSF TRACE IS ALREADY ACTIVE USING TRACE MASK <i>trace-mask</i></b>
----------------	--

---

## Explanation

A TRACE ON command was entered, but SDSF trace is already active, with the indicated trace mask.

## User response

None required.

---

<b>ISF716E</b>	<b>SDSF TRACE DATA SET IS NOT ALLOCATED.</b>
----------------	--

---

## Explanation

A TRACE ON command was entered, but the SDSF trace data set could not be dynamically allocated. SDSF trace is not started.

## User response

Additional system messages may have been issued to the console. See them for additional information.

---

<b>ISF717I</b>	<b>SDSF TRACE IS ALREADY INACTIVE.</b>
----------------	--

---

## Explanation

A TRACE OFF command was entered, but SDSF trace is already inactive. The command is ignored.

## User response

None required.

---

<b>ISF718E</b>	<b>SDSF TRACE FAILED TO INACTIVATE.</b>
----------------	---

---

## Explanation

A TRACE OFF command was entered, but SDSF trace was not turned off. Tracing continues.

## User response

Retry the request.

---

<b>ISF724I</b>	<b>SDSF LEVEL <i>fmid</i> INITIALIZATION COMPLETE FOR SERVER <i>server</i>.</b>
----------------	---

---

## Explanation

The SDSF server was successfully initialized.

## User response

None.

---

<b>ISF725I</b>	<b>SDSF SHUTDOWN IN PROGRESS FOR SERVER <i>server</i>.</b>
----------------	--

---

## Explanation

The SDSF server is being shut down.

## User response

None.

---

<b>ISF726I</b>	<b>SDSF PARAMETER PROCESSING STARTED.</b>
----------------	---

---

## Explanation

The processing of the SDSF parameters has started.

## User response

None.

---

<b>ISF727I</b>	<b>SDSF PARAMETER PROCESSING STARTED IN TEST MODE.</b>
----------------	--

---

## Explanation

The processing of the SDSF parameters has started in test mode. The syntax of the parameters will be checked, but the parameters will not be activated.

## User response

None.

---

<b>ISF728I</b>	<b>SDSF PARAMETERS HAVE BEEN ACTIVATED.</b>
----------------	---

---

## Explanation

The processing of the SDSF parameters was successful and the parameters are now active.

## User response

None.

---

<b>ISF729I</b>	<b>NO ERRORS DETECTED IN SDSF PARAMETERS.</b>
----------------	---

---

## Explanation

The processing of the SDSF parameters completed with no errors.

## User response

None.

---

<b>ISF730I</b>	<b>SDSF PARAMETERS NOT READ FROM ISFPRMxx DUE TO NOPARM INITIALIZATION OPTION.</b>
----------------	--

---

## Explanation

SDSF was started with the NOPARM initialization option, which bypasses processing of any ISFPRMxx PARMLIB member. SDSF will continue to initialization with a base set of default values. The SDSFAUX server will be started and data collection will be activated.

## User response

No response is required.

---

<b>ISF731E</b>	<b>SDSF PARAMETERS NOT ACTIVATED DUE TO ERRORS.</b>
----------------	---

---

## Explanation

Errors were found in the SDSF parameters. The parameters are not activated.

## User response

Use the log file to review the parameters. Correct the errors and process the parameters again.

### Descriptor code:

7, 11

---

<b>ISF732I</b>	<b>ERRORS DETECTED IN SDSF PARAMETERS.</b>
----------------	--

---

## Explanation

Errors were found in the SDSF parameters.

## User response

Use the log file to review the parameters. Correct the errors and process the parameters again.

---

<b>ISF733E</b>	<b>UNABLE TO READ SDSF PARAMETERS DUE TO I/O ERROR.</b>
----------------	---

---

## Explanation

An I/O error prevented SDSF from reading the SDSF parameters.

## User response

See accompanying system messages for more information about the I/O error.

---

<b>ISF734I</b>	<b>SDSF PARAMETERS HAVE BEEN ACTIVATED, WARNINGS WERE ISSUED.</b>
----------------	---

---

## Explanation

SDSF ISFPARMS have been activated; however, during syntax checking of the ISFPARMS, SDSF issued warning messages.

## User response

Check the server log for the warning messages. If you change the ISFPARMS, activate the changes with the MODIFY command.

---

<b>ISF735E</b>	<b>SDSF PARAMETERS ARE NOT ACTIVE.</b>
----------------	--

---

## Explanation

An error was detected in the SDSF parameters when the SDSF server was started. SDSF parameters are not activated.

## User response

Use the log file to review the parameters. Correct the errors and activate the parameters with the MODIFY command.

### Descriptor code:

7, 11

---

<b>ISF736I</b>	<b>SDSF SHUTDOWN PROCEEDING FOR SERVER <i>server-name</i>.</b>
----------------	--

---

## Explanation

A STOP command has been issued to shut down an SDSF server. The server is waiting for completion of outstanding work.

## User response

None required.

---

<b>ISF737E</b>	<b>SDSF PARAMETERS NOT ACTIVATED DUE TO ABEND.</b>
----------------	--

---

## Explanation

Due to an abend, SDSF parameters were not activated.

## User response

Use the MODIFY command to active the parameters. The MODIFY command is described in [“Server operator commands”](#) on page 75.

### Descriptor code:

7, 11

---

<b>ISF738I</b>	<b>ABEND <i>abend-code</i> DETECTED PROCESSING SDSF PARAMETERS.</b>
----------------	---

---

## Explanation

While SDSF parameters were being processed in test mode, an abend was detected.

## User response

Use the abend code to diagnose the problem.

---

<b>ISF739I</b>	<b>SDSF PARAMETERS BEING READ FROM MEMBER <i>member-name</i> OF DATA SET <i>dataset-name</i>.</b>
----------------	---

---

## Explanation

The SDSF server is reading SDSF parameters from the indicated data set and member. A data set-name of SYS1.PARMLIB+ indicates that the logical parmlib concatenation is being used.

## User response

None required.

---

<b>ISF740E</b>	<b>VARIABLE <i>variable-name</i> DATA VALUE '<i>value</i>' IS TOO LONG.</b>
----------------	---

---

## Explanation

The value for the named special variable exceeds the valid length.

## User response

Special variables that are associated with SDSF commands cannot exceed the SDSF command length. Adjust the value of the special variable to the valid length.

---

<b>ISF741E</b>	<b>ERROR PROCESSING COMMAND '<i>command</i>' ASSOCIATED WITH VARIABLE <i>variable-name</i>, REASON: <i>reason-text</i>.</b>
----------------	---

---

## Explanation

The value of the special variable *variable-name* was rejected with the indicated reason text. The command is not processed.

## User response

Ensure that the syntax of the special variable *variable-name* conforms to the syntax required by the SDSF command *command-name*. The syntax of the commands is described in the online help.

---

<b>ISF742E</b>	<b>COLUMN <i>column-name</i> NAMED IN <i>variable-name</i> VARIABLE IGNORED, NOT FOUND IN CURRENT FIELD LIST.</b>
----------------	---

---

## Explanation

The named column was not found in the current field list. A REXX variable will not be created with its value.

## User response

Ensure the column name specified in *variable-name* are valid for the current field list. If the column is valid for the panel, but is found only on the alternate field list, use the ALTERNATE option on the SDSF host command used to invoke the panel. Refer to "Issuing commands with ISFEXEC" in [z/OS SDSF User's Guide](#) for more information.

---

<b>ISF743E</b>	<b>VARIABLE <i>variable-name</i> HAS A DATA VALUE EXCEEDING <i>number</i> BYTES AND IS TOO LONG.</b>
----------------	--

---

## Explanation

The value of the special variable *variable-name* was rejected because the data value is too long. The associated command is not processed.

## User response

Ensure that the syntax of the special variable *variable-name* conforms to the syntax required by the associated SDSF command. For the syntax of an SDSF command, see the online help.

---

<b>ISF744E</b>	<b>UNABLE TO FETCH REXX VARIABLE <i>variable-name</i>, IRXEXCOM SHVRET RETURN CODE <i>return-code</i>.</b>
----------------	--

---

## Explanation

SDSF was unable to read the value of *variable-name*. The IRXEXCOM service failed to fetch the variable

with return code *return-code* for field SHVRET. The associated command will not be processed.

## User response

Use the return code from the IRXEXCOM service as described in *z/OS TSO/E REXX Reference* to diagnose the error.

---

<b>ISF745E</b>	<b>ERROR PROCESSING '<i>command</i>', REASON: <i>reason-code</i>.</b>
----------------	---

---

## Explanation

SDSF was unable to run command. The error is described by *reason-code*.

## User response

Use the reason code to diagnose the error. For syntax errors, correct the command format or the operands specified on a special variable. For authorization errors, ensure the user has the appropriate authority to the command.

---

<b>ISF746E</b>	<b>ACTION REQUEST REJECTED, ROW TOKEN INVALID.</b>
----------------	--

---

## Explanation

A row token referenced on an ISFACT command has failed a validity check. The action is not performed.

## User response

The row token is created by the ISFEXEC command and must be passed unmodified to SDSF on the ISFACT command. Some of the conditions causing the token to become invalid are:

- The token has been modified or contains an invalid character
- The token does not correspond to the display being modified. For example, the token was generated for a row on the H panel but is being used on the O panel.
- The token was generated on a different level of SDSF than the one currently being run.
- The token was generated for a different use ID than the one performing the action.

---

<b>ISF747E</b>	<b>ACTION REQUEST REJECTED, ROW NOT FOUND.</b>
----------------	--

---

## Explanation

A row token referencing a row that no longer exists was encountered during processing of an ISFACT command. The requested action is not performed.

## User response

None.

---

<b>ISF748E</b>	<b>ACTION REQUEST REJECTED, ROW NOT UNIQUE.</b>
----------------	---

---

## Explanation

A row token that references a row that is not unique was encountered during processing of an ISFACT command. The requested action is not performed.

## User response

Obtain a new row token by running the ISFEXEC command again and retrying the ISFACT request.

---

<b>ISF749E</b>	<b>ACTION REQUEST REJECTED, <i>column-name</i> IS NOT MODIFIABLE.</b>
----------------	---

---

## Explanation

An attempt to modify a column that could not be modified was encountered during processing of an ISFACT command. The requested modification was not performed.

## User response

Verify that the named column can be modified. You must be authorized to modify the column. For a list of columns, issue the COLSHELP command from any SDSF command line under ISPF.

---

<b>ISF750E</b>	<b>ACTION REQUEST REJECTED, <i>column-name</i> NOT FOUND IN CURRENT FIELD LIST.</b>
----------------	---

---

## Explanation

A column that is not in the current field list was encountered during processing of an ISFACT command. The request was not performed.

## User response

Ensure that you have included the necessary option on the ISFACT command:

- If the column is in the alternate field list, use ALTERNATE or ALTERNATE2 (when the panel is accessed from another panel with an action character)
- If the column is a delayed-access column, use DELAYED or DELAYED2.

To find which columns are available in your REXX exec, access the panel and display the contents of the ISFCOLS or ISFCOLS2 special variable.

To display a list of columns that identifies which are delayed access, type COLSHelp in SDSF's help (ISPF only).

The system programmer can specify the columns that are included in the primary and alternate field lists using ISFPARMS. Refer to “Variable field lists (FLD or ISFFLD)” on page 47 for more information.

---

**ISF751E**      **COLUMN *column-name* ACTION IGNORED, NO DATA PROVIDED.**

---

### Explanation

Data to modify a column was null or all blanks when processing an ISFACT command. The request is ignored.

### User response

Ensure that the data to be used to modify a column is non-blank.

---

**ISF752E**      **COLUMN *column-name* ACTION REJECTED, DATA LENGTH *data-length* EXCEEDS THE MAXIMUM OF *maximum-length*.**

---

### Explanation

On an ISFACT command, the data to modify column *column-name* is too long. The request is rejected.

### User response

Ensure that the length of the data to be modified does not exceed the maximum width for the field.

---

**ISF753E**      **ACTION REQUEST REJECTED, COMMAND *command* NOT ACCEPTABLE.**

---

### Explanation

A command, *command*, that is not acceptable to ISFACT was encountered while processing the ISFACT command.

### User response

Ensure that the command used on ISFACT is a command to access a tabular panel.

---

**ISF754I**      **COMMAND '*command*' GENERATED FROM ASSOCIATED VARIABLE *variable-name*.**

---

### Explanation

The SDSF command *command* was run based on the data contained in the REXX special variable *variable-name*.

### User response

None.

---

**ISF755E**      **HOST COMMAND NOT PROVIDED.**

---

### Explanation

The REXX SDSF host command environment was invoked but no command was provided.

### User response

Ensure that a command is passed to the SDSF host command environment.

---

**ISF756I**      **NO ACTIONS PERFORMED, ROW NOT MODIFIED.**

---

### Explanation

No actions were provided or accepted for the row. The row has not been modified.

### User response

None.

---

**ISF757I**      **VARIABLE *variable-name* BEING PROCESSED WITH VALUE '*value*'.**

---

### Explanation

The indicated special variable has been retrieved and contains the indicated value.

### User response

None.

---

**ISF758E**      **ERROR PROCESSING DATA ASSOCIATED WITH VARIABLE *variable-name*, REASON: *reason-text*.**

---

### Explanation

An error occurred processing the data associated with the indicated variable. The reason is given by *reason-text*.

### User response

The function is not performed.

---

<b>ISF759E</b>	<b>PRINT ERROR OCCURRED: <i>error-text</i>.</b>
----------------	---

---

### Explanation

In the processing of a print request, an error occurred. The error is described by *error-text*.

### User response

None.

---

<b>ISF760I</b>	<b>HOST COMMAND BEING PROCESSED: <i>command</i>.</b>
----------------	--

---

### Explanation

SDSF has been invoked to process the REXX host command *command*.

### User response

None.

---

<b>ISF761E</b>	<b>COLUMN <i>column-name</i> ACTION REJECTED, DATA VALUE '<i>value</i>' UNACCEPTABLE.</b>
----------------	---

---

### Explanation

An action for a row was rejected because the modified data was unacceptable for the column. For example, the overtime extension character (+) was specified, and that is not valid in the REXX environment.

### User response

Correct the data to be used to modify the column.

---

<b>ISF762I</b>	<b>COLUMN <i>column-name</i> ACTION REJECTED, VALUE '<i>value</i>' EXCEEDS THE MAXIMUM NUMBER OF VALUES OF <i>max-values</i>.</b>
----------------	---

---

### Explanation

The number of values being used to modify the indicated column exceeds the maximum number of related values allowed for that column. The request is rejected.

### User response

Correct the data so that the number of related values does not exceed the maximum number of values for the column. For more information, see the online help for overtyping columns on that panel.

---

<b>ISF763E</b>	<b>COLUMN <i>column-name</i> ACTION REJECTED, DATA VALUE '<i>value</i>' INVALID, REASON: <i>reason text</i>.</b>
----------------	--

---

### Explanation

An action taken against a row was rejected because the modified data failed a syntax check for the column. The reason is indicated by *reason-text*. For example, a syntax error can occur if the column is defined for numeric data but an attempt was made to modify it with non-numeric data.

### User response

Correct the data to be used to modify the column.

---

<b>ISF764I</b>	<b>COMMAND '<i>command</i>' GENERATED FROM ASSOCIATED VARIABLE <i>variable-name</i>, STATUS: <i>status</i>.</b>
----------------	---

---

### Explanation

The SDSF command *command* was run based on the data contained in the REXX special variable *variable-name* with any completion status indicated in the status text.

### User response

None.

---

<b>ISF765I</b>	<b>VARIABLE <i>variable-name</i> NOT DEFINED, DEFAULT VALUE '<i>value</i>' BEING USED.</b>
----------------	--

---

### Explanation

The named REXX variable was not found so the indicated value was applied as a default.

### User response

None.

---

<b>ISF766I</b>	<b>REQUEST COMPLETED, STATUS: <i>completion-status</i>.</b>
----------------	---

---

### Explanation

An SDSF request has completed with the indicated status. The completion status is the text from the SDSF message area and also corresponds to the REXX special variable ISFMSG.

### User response

None.

---

<b>ISF767I</b>	<b>REQUEST COMPLETED, STATUS: <i>completion-status</i>.</b>
----------------	---

---

### Explanation

An SDSF request has completed with no additional status. The REXX special variable ISFMSG contains no data.

### User response

None.

---

<b>ISF768I</b>	<b>COLUMN <i>column-name</i> NAMED IN <i>variable-name</i> VARIABLE IGNORED, NOT APPLICABLE IN THIS ENVIRONMENT.</b>
----------------	--

---

### Explanation

The named column found in the current field list but is not valid in the current environment. The column is ignored. For example, the ISFEND column has no effect in the SDSF/REXX environment and is ignored.

### User response

No response is required.

---

<b>ISF769I</b>	<b>SYSTEM COMMAND ISSUED, COMMAND TEXT: <i>command-text</i>.</b>
----------------	--

---

### Explanation

A system command was issued with the ISFEXEC command *command* or the ISFSLASH command. The text of the command is shown in *command-text*.

### User response

None.

---

<b>ISF770W</b>	<b>REQUEST LIMIT <i>limit</i> FROM VARIABLE <i>variable-name</i> REACHED.</b>
----------------	---

---

### Explanation

The limit for the number of requests, *limit*, set by special variable *variable-name*, has been reached.

### User response

If necessary, change the limit.

---

<b>ISF771E</b>	<b>VARIABLE <i>variable-name</i> NOT ACCESSIBLE, PROCESSING TERMINATED.</b>
----------------	---

---

### Explanation

Variable *variable-name* does not exist or could not be fetched. Processing is stopped.

### User response

Verify that the variable name is correct and exists.

---

<b>ISF772I</b>	<b>VARIABLE <i>variable-name</i> IGNORED, DOES NOT CONTAIN DATA.</b>
----------------	--

---

### Explanation

Variable *variable-name* does not contain any data and is skipped.

### User response

Verify that the variable name is correct.

---

<b>ISF775E</b>	<b>VARIABLE <i>variable-name</i> NOT ACCEPTABLE, DOES NOT CONTAIN DATA.</b>
----------------	---

---

### Explanation

Variable *variable-name* has been fetched, but does not contain data. A value for this variable is required.

### User response

Verify that the value for the variable is present.

---

<b>ISF776I</b>	<b>PROCESSING STARTED FOR ACTION <i>action-count</i> OF <i>total-count</i>.</b>
----------------	---

---

### Explanation

When processing actions or commands, SDSF started processing the action that is number *action-count* out of the total number, *total-count*.

### User response

None required.

---

<b>ISF777E</b>	<b>STOP TIME AND DATE INCONSISTENT WITH START TIME AND DATE.</b>
----------------	--

---

### Explanation

A date range is not acceptable because the ending time and date is prior to the starting time and date.

## User response

Correct the time and date range.

---

<b>ISF778I</b>	<b>STOP REQUEST BEING PROCESSED.</b>
----------------	--------------------------------------

---

## Explanation

SDSF is processing a stop request and will end.

## User response

None required.

---

<b>ISF779E</b>	<b>PARSING ERROR OCCURRED WHILE PROCESSING JSON REQUEST, RETURN CODE=<i>return-code</i>, REASON=<i>reason</i>.</b>
----------------	--

---

## Explanation

A parsing error occurred while parsing a JSON document as described by *return-code* and *reason*. The document may not be well formed or may contain a syntax error. The document is not processed. The return-code is an internal code that can be used by IBM to diagnose the error.

## User response

Correct the document and retry the request.

---

<b>ISF780E</b>	<b>JSON PROPERTY <i>property-name</i> NOT RECOGNIZED OR NOT IN CORRECT CONTEXT.</b>
----------------	---

---

## Explanation

A JSON document was being processed, and *property-name* was not recognized as a valid property, or the property is not a valid subproperty of an object. The document is not processed.

## User response

Correct the document and retry the request.

---

<b>ISF781E</b>	<b>JSON OBJECT NESTING LEVEL EXCEEDED.</b>
----------------	--

---

## Explanation

A JSON document was being processed and too many levels of subproperties were found. The document was not processed.

## User response

Correct the document and retry the request.

---

<b>ISF782W</b>	<b>NO ROWS SATISFY REQUEST.</b>
----------------	---------------------------------

---

## Explanation

A request was received but constraints resulted in no rows being generated for the response.

## User response

None.

---

<b>ISF783E</b>	<b>ERROR OCCURRED GENERATING JSON DOCUMENT FOR REQUEST.</b>
----------------	---

---

## Explanation

An unrecoverable error occurred in generating a document for a JSON response.

## User response

Refer to additional messages that further describe the error.

---

<b>ISF784E</b>	<b>VARIABLE <i>variable</i> REQUIRES SPECIFICATION OF VARIABLE <i>variable</i>.</b>
----------------	---

---

## Explanation

A variable was specified that requires another variable that is missing. The request may fail or be processed as if neither variable were specified.

## User response

Correct the error and retry the request.

---

<b>ISF785E</b>	<b>VARIABLE <i>variable1</i> VALUE '<i>value</i>' MUST NOT BE LESS THAN VARIABLE <i>variable12</i> VALUE '<i>value</i>'.</b>
----------------	--

---

## Explanation

The value in *variable1* is less than the value in *variable12*. This is not allowed.

## User response

Correct the error and retry the request.

---

<b>ISF786E</b>	<b>VARIABLE ISFFIND VALUE '<i>string</i>' WITH LENGTH <i>length</i> IS TOO LONG FOR SPECIFIED COLUMN RANGE <i>start-column</i> TO <i>end-column</i>.</b>
----------------	--

---



## Explanation

The string specified in the ISFFIND variable is too long to fit within the specified column range.

## User response

Correct the error and retry the request.

---

<b>ISF787E</b>	<b>VARIABLE <i>variable</i> VALUE '<i>value</i>' EXCEEDS THE RECORD LENGTH OF THE DATA.</b>
----------------	---

---

## Explanation

The value of *variable* is greater than the record length of the data that is being browsed. The request cannot be processed.

## User response

Correct the error and retry the request.

---

<b>ISF788E</b>	<b>VARIABLE <i>variable</i> IS IGNORED, IT CONTAINS A TOKEN THAT IS NOT VALID.</b>
----------------	--

---

## Explanation

The value of variable *variable* is a token that is not valid. The request is processed as if the variable were not specified.

## User response

Ensure that the token was not modified before you attempted to use it.

---

<b>ISF789E</b>	<b>VARIABLE <i>variable</i> IS IGNORED, IT CONTAINS A TOKEN THAT IS NOT VALID IN THIS CONTEXT.</b>
----------------	--

---

## Explanation

The value of variable *variable* is a token that is not valid for this request. The request is processed as if the variable were not specified.

## User response

Ensure that the token was not modified before you attempted to use it. The variable that contains the token may not have been cleared before it was set. To clear variables, use the ISFRESET function.

---

<b>ISF790E</b>	<b>THE VALUE SPECIFIED FOR VARIABLE <i>variable</i> IS NOT VALID ON THE <i>panel</i> PANEL.</b>
----------------	---

---

## Explanation

The value of variable *variable* is a token that is not valid for the current panel. The request cannot be processed.

## User response

Correct the value that is in error. For the value that is in error, see the previous ISF757I message. For information about the valid values, use the SEARCH command or the REXXH command.

---

<b>ISF791E</b>	<b>VARIABLE <i>variable</i> IS IGNORED, THE TOKEN REPRESENTS A RECORD THAT NO LONGER EXISTS.</b>
----------------	--

---

## Explanation

The record represented by the token in variable *variable* does not exist. The request is specified as if the variable were not specified.

## User response

None required.

---

<b>ISF792E</b>	<b>DATA NOT AVAILABLE, NOT AUTHORIZED TO COMMAND <i>command</i>.</b>
----------------	--

---

## Explanation

A request for data could not be satisfied. The request requires a command that you are not authorized to use.

## User response

For authorization to the command, contact your security administrator.

---

<b>ISF793E</b>	<b>DATA NOT AVAILABLE, HEALTH CHECKER NOT ACTIVE ON SYSTEM <i>system-name</i>.</b>
----------------	--

---

## Explanation

A request for data could not be satisfied because IBM Health Checker for z/OS is not active on the indicated system.

## User response

Contact your system programmer to activate IBM Health Checker for z/OS.

**ISF794W**      **MAXIMUM RESPONSE SIZE REACHED, ROWS *row-1* THROUGH *row-2* NOT PROCESSED.**

### Explanation

The size of the response exceeds the maximum allowed. Rows *row-1* through *row-2* are skipped. They are not included in the response.

### User response

Use filters to limit the number of rows being selected, then try the request again.

**ISF795I**      **Variable *variable-name* is obsolete and will be ignored**

### Explanation

Variable *variable* has been assigned a value but the variable is obsolete. No syntax checking is done and the value is ignored.

### User response

No action is necessary but it is recommended you remove references to the obsolete variable.

**ISF796I**      **Server task name *taskname* trace level set to *value***

### Explanation

In response to a **F SDSF,SET TRACE(n) NAME(taskname)** operator command, the trace level for *taskname* has been changed to level *value*.

### User response

None.

**ISF797I**      **SPECIAL DDNAME *ddname* PROCESSED**

### Explanation

The special ddname *ddname* was allocated and recognized by SDSF. The options associated with the ddname are processed.

### User response

No response is required.

### Descriptor code:

7, 11

**ISF799I**      **SDSF falling back to the ISFPARMS load module.**

### Explanation

### User response

No response is required.

### Descriptor code:

7, 11

**ISF800E**      **UNEXPECTED END OF FILE ENCOUNTERED PROCESSING STATEMENT NUMBER *number*.**

### Explanation

While processing a continuation statement, the end of file was reached.

### User response

Use the log file to review the parameters. Correct the errors and process the parameters again.

**ISF801E**      **STATEMENT NUMBER *number* IS TOO LONG.**

### Explanation

SDSF parameter statement number *number* is longer than the maximum allowed length of 32756 characters.

### User response

Use the log file to review the parameters. Ensure that a statement is not continued incorrectly. Correct the statement in error and process the parameters again.

**ISF802E**      **INPUT FILE IS EMPTY.**

### Explanation

The input file for processing SDSF parameters contained no parameters.

### User response

Correct the input file and retry the request.

**ISF803E**      **COMMENT NOT CLOSED ON LINE NUMBER *number*.**

### Explanation

A comment opened on line number *number* was not closed. Comments must be complete on a single line.

## User response

Use the log file to locate the line and close the comment.

---

<b>ISF804E</b>	<b>PROCESSING ENDED DUE TO I/O ERROR.</b>
----------------	---

---

## Explanation

Processing of SDSF parameters ended due to an input or output error. Either SDSF or the system may have issued additional messages describing the error.

## User response

Use the messages to determine the cause of the I/O error.

---

<b>ISF805I</b>	<b>PREVIOUSLY PROCESSED statement-type AT STATEMENT statement-number BEING REPLACED.</b>
----------------	--

---

## Explanation

A statement of the same type has already been processed and will be replaced by the later statement. The statement being replaced is *statement-number*.

## User response

None required. However, you should check your ISFPARMS to remove duplicate statements.

---

<b>ISF806E</b>	<b>parameter VALUE value IS IN ERROR, INVALID SYNTAX SPECIFIED.</b>
----------------	---

---

## Explanation

The value indicated by *value* in the parameter indicated by *parameter* contains invalid syntax.

## User response

Correct the syntax.

---

<b>ISF807E</b>	<b>parameter VALUE value IS TOO LONG, MAXIMUM LENGTH ALLOWED IS maximum.</b>
----------------	--

---

## Explanation

The value indicated by *value* in the parameter indicated by *parameter* is longer than the maximum allowed length, indicated by *maximum*.

## User response

Correct the length of the value.

---

<b>ISF808E</b>	<b>parameter VALUE value IS NOT NUMERIC.</b>
----------------	--

---

## Explanation

The value indicated by *value* in the parameter indicated by *parameter* is not numeric. It must be numeric.

## User response

Correct the value.

---

<b>ISF809E</b>	<b>parameter VALUE value IS TOO SMALL, MINIMUM VALUE ALLOWED IS minimum.</b>
----------------	--

---

## Explanation

The value indicated by *value* in the parameter indicated by *parameter* is smaller than the minimum allowed value, indicated by *minimum*.

## User response

Correct the value.

---

<b>ISF810E</b>	<b>parameter VALUE value IS TOO LARGE, MAXIMUM VALUE ALLOWED IS maximum.</b>
----------------	--

---

## Explanation

The value indicated by *value* in the parameter indicated by *parameter* is larger than the maximum allowed value, indicated by *maximum*.

## User response

Correct the value.

---

<b>ISF811E</b>	<b>parameter VALUE value IS INVALID.</b>
----------------	--

---

## Explanation

The value indicated by *value* in the parameter indicated by *parameter* is invalid.

## User response

Correct the value.

---

<b>ISF812E</b>	<b>parameter VALUE value IS AN INVALID SYSOUT CLASS.</b>
----------------	--

---

### Explanation

The value indicated by *value* in the parameter indicated by *parameter* is not a valid SYSOUT class. Valid classes are A-Z and 0-9.

### User response

Correct the value.

---

**ISF813E**      *parameter* VALUE *value* CONTAINS INVALID HEXADECIMAL DIGITS.

### Explanation

The value indicated by *value* in the parameter indicated by *parameter* contains characters that are not valid hexadecimal digits. Valid hexadecimal digits are 0-9 and A-F.

### User response

Correct the value.

---

**ISF814E**      *parameter* VALUE *value* IS TOO SHORT, MINIMUM LENGTH ALLOWED IS *minimum*.

### Explanation

The value indicated by *value* in the parameter indicated by *parameter* is shorter than the minimum allowed length, indicated by *minimum*.

### User response

Correct the value.

---

**ISF815E**      *parameter* VALUE *values* MUST HAVE DIFFERENT CHARACTERS FOR EACH VALUE.

### Explanation

The values indicated by *values* are not unique. Each value specified on this parameter must be unique.

### User response

Correct the values so that each is unique.

---

**ISF816E**      *first-parameter* IS MUTUALLY EXCLUSIVE WITH *second-parameter*.

### Explanation

The parameters indicated by *first-parameter* and *second-parameter* cannot be used together.

### User response

Delete one of the parameters.

---

**ISF817I**      GROUP INDEX *group-index-number* ASSIGNED TO GROUP *group-name*.

### Explanation

The index number indicated by *group-index-number* is assigned to the group indicated by *group-name*. The name, *group-name*, is a name assigned by you with the NAME parameter, or, if NAME is omitted, it is a name assigned by SDSF.

### User response

None required.

---

**ISF818I**      GROUP *group-name* REPLACES STATEMENT *statement-type*, GROUP INDEX IS *index-number* .

### Explanation

A group named *group-name* has been encountered more than once; the latest occurrence replaces the previous occurrence. The index number assigned to the group is indicated by *index-number*. (The index indicates the group by a count of groups. For example, an index of 3 indicates the group defined by the third GROUP statement in ISFPARMS.)

### User response

None required. You should check your parameters to remove duplicate group statements.

---

**ISF819I**      *statement-type* NAMED *name* REPLACES STATEMENT *number*.

### Explanation

The statement named *name* has been encountered more than once. The latest occurrence replaces the previous occurrence.

### User response

None required. You should check your parameters to remove duplicate statements.

---

**ISF820I**      *statement* NAMED *name* FOR *display1* DISPLAY CONFLICTS WITH PRIOR DEFINITION FOR *display2*.

## Explanation

An FLD statement with the name *name*, for the indicated SDSF display, conflicts with an FLD statement for another display that has already been encountered.

## User response

None required. You should check your parameters to remove duplicate statements.

---

<b>ISF821E</b>	<b><i>string</i> WAS EXPECTED BEFORE <i>string</i> ON LINE <i>line-number</i> COLUMN <i>column-number</i>.</b>
----------------	--

---

## Explanation

A syntax error has been encountered at the indicated line and column.

## User response

Correct the statement.

---

<b>ISF822E</b>	<b><i>value</i> WAS SEEN ON LINE <i>line-number</i> COLUMN <i>column-number</i> WHERE ONE OF THE FOLLOWING WAS EXPECTED: <i>valid-values</i>.</b>
----------------	---

---

## Explanation

An invalid value, *value*, was found at the indicated line and column. The valid values are shown in *valid-values*.

## User response

Correct the statement using one of the listed values.

---

<b>ISF823I</b>	<b>INPUT SKIPPED UP TO THE NEXT <i>value</i>.</b>
----------------	---

---

## Explanation

A syntax error has occurred on a previously identified statement. SDSF is skipping to the indicated *value* to continue processing.

## User response

Correct the statement in error.

---

<b>ISF824E</b>	<b><i>error-string</i> ON LINE <i>line-number</i> COLUMN <i>column-number</i> SHOULD BE DELETED.</b>
----------------	--

---

## Explanation

The character string *error-string* located on the indicated line and column is in error and should be deleted.

## User response

Delete or correct the string in error.

---

<b>ISF825I</b>	<b><i>string</i> IS INSERTED BEFORE THE ERROR POINT.</b>
----------------	--

---

## Explanation

In response to previous syntax errors, SDSF has inserted a character string, *string* before the error in order to continue processing.

## User response

Correct the error.

---

<b>ISF826E</b>	<b><i>statement</i> OFFSET OF <i>offset</i> IS TOO LONG FOR USE WITH STRING <i>string</i>, MAXIMUM COMBINED OFFSET AND STRING LENGTH IS <i>maximum</i>.</b>
----------------	---

---

## Explanation

In the indicated statement, the offset *offset*, when used with the string *string*, results in an invalid value for that statement. The maximum for the combination of the offset and string length is *maximum*.

## User response

Correct the string or offset.

---

<b>ISF828E</b>	<b><i>first-statement</i> STATEMENT REQUIRED PRIOR TO THIS <i>second-statement</i>.</b>
----------------	---

---

## Explanation

You must include a statement of the type indicated by *first-statement* before the statement indicated by *second-statement*.

## User response

Reorder or add statements to achieve the required order.

---

<b>ISF829E</b>	<b><i>first-value</i> AND <i>second-value</i> MUST HAVE DIFFERENT VALUES.</b>
----------------	---

---

## Explanation

The values indicated by *first-value* and *second-value* are the same. They must be different.

## User response

Change one or both of the values so that they are different.

---

<b>ISF830E</b>	<b><i>parameter</i> VALUE IS TOO SHORT, VALUE MUST BE <i>required-length</i> BYTES BUT IS ONLY <i>actual-length</i>.</b>
----------------	--

---

## Explanation

The value specified for the indicated parameter is too short. The message indicates the required length of the value (*required-length*) and the length of the value that was actually specified (*actual-length*).

## User response

Correct the value to be the required number of bytes.

---

<b>ISF831E</b>	<b><i>parameter</i> VALUE IS TOO LONG, VALUE MUST BE <i>required-length</i> BYTES BUT IS <i>actual-length</i>.</b>
----------------	--

---

## Explanation

The value specified for the indicated parameter is too long. The message indicates the required length of the value (*required-length*) and the length of the value that was actually specified (*actual-length*).

## User response

Correct the value to be the required number of bytes.

---

<b>ISF832I</b>	<b><i>statement</i> NAMED <i>name</i> CONFLICTS WITH PREVIOUS DEFINITION FOR <i>statement</i>.</b>
----------------	--

---

## Explanation

The statement with the name *name* conflicts with another statement of a different type that has already been encountered.

## User response

None required. You should review your statements to remove the conflict.

---

<b>ISF833E</b>	<b>COLUMN <i>column</i> IS NOT VALID FOR THE <i>display</i> DISPLAY.</b>
----------------	--

---

## Explanation

The indicated column has been specified with an FLDENT statement for a display on which it is not valid.

## User response

Remove the FLDENT statement for that display, or change the display with which the FLDENT statement is associated.

---

<b>ISF834E</b>	<b><i>string</i> WAS EXPECTED BEFORE <i>string</i> IN STATEMENT <i>statement-number</i>.</b>
----------------	--

---

## Explanation

A syntax error has been encountered at the indicated statement.

## User response

Correct the statement.

---

<b>ISF835E</b>	<b><i>value</i> WAS SEEN IN STATEMENT <i>statement</i> WHERE ONE OF THE FOLLOWING WAS EXPECTED: <i>valid-values</i>.</b>
----------------	--

---

## Explanation

An invalid value, *value*, was found at the indicated statement. The valid values are shown in *valid-values*.

## User response

Correct the statement using one of the listed values.

---

<b>ISF836E</b>	<b><i>parameter</i> VALUE <i>string</i> IS IN ERROR, INVALID DATA SET NAME SYNTAX.</b>
----------------	--

---

## Explanation

The indicated parameter specifies a data set name containing invalid syntax.

## User response

Correct the data set name and retry the request.

---

<b>ISF837E</b>	<b><i>parameter</i> VALUE CONTAINS <i>number</i> CHARACTERS, BUT IT MUST BE EVEN.</b>
----------------	---

---

## Explanation

The value specified on the indicated parameter is an odd number of characters; the value must be an even number of characters.

## User response

Correct the value to contain an even number of characters.

---

<b>ISF838E</b>	<b><i>secondary-statement-type</i> NAMED <i>secondary-statement-name</i> REFERENCED BY <i>primary-statement-type primary-statement-name</i> NOT FOUND.</b>
----------------	--

---

## Explanation

A statement indicated by *primary-statement-type primary-statement-name* references a statement, *secondary-statement-type secondary-statement-name* that could not be found.

## User response

Correct the parameters so that the group definition and the name of the referenced statement agree.

---

<b>ISF839I</b>	<b><i>statement-type</i> NAMED <i>name</i> IS NOT REFERENCED BY ANY OTHER STATEMENT.</b>
----------------	--

---

## Explanation

The indicated statement is valid only when referred to by another statement. It was encountered, but no other statement referred to it.

## User response

None required. However, if the statement is to be used, you must correct the parameters so that the statement name is referred to in a parameter in a group definition.

---

<b>ISF840I</b>	<b><i>statement</i> NAMED <i>name</i> CONTAINS NO ENTRIES.</b>
----------------	--

---

## Explanation

The indicated statement contains no column or list entries. It is ignored.

## User response

Delete or complete the statement.

---

<b>ISF841E</b>	<b>GROUP <i>group-name</i> REFERENCES <i>statementname</i> WHICH IS AN INVALID TYPE FOR <i>group-keyword</i>.</b>
----------------	---

---

## Explanation

The indicated group statement references a statement that is the wrong type.

## User response

Correct one or both statements.

---

<b>ISF842E</b>	<b><i>group-statement</i> IN GROUP <i>group-name</i> IS FOR DISPLAY TYPE <i>type</i> BUT REFERENCES <i>statement</i> NAMED <i>name</i> FOR DISPLAY TYPE <i>type</i>.</b>
----------------	--

---

## Explanation

The indicated group statement references a statement that is for the wrong SDSF display.

## User response

Correct one or both statements.

---

<b>ISF843E</b>	<b><i>value</i> VALUE REQUIRED FOR THIS <i>statement</i> STATEMENT.</b>
----------------	---

---

## Explanation

The indicated statement is missing a required value.

## User response

Complete the statement by adding the missing value.

---

<b>ISF844W</b>	<b><i>statement</i> VALUE <i>value</i> EXCEEDS THE MAXIMUM ALLOWED, CHANGED TO <i>new-value</i>.</b>
----------------	--

---

## Explanation

The indicated value in the indicated statement was greater than the maximum allowed; SDSF has changed the value to *new-value*.

## User response

Correct the value to be less than or equal to the maximum allowed.

---

<b>ISF845W</b>	<b><i>statement</i> VALUE <i>value</i> TOO LONG FOR COLUMN WIDTH, TRUNCATED TO <i>number</i> CHARACTERS.</b>
----------------	--

---

## Explanation

The indicated value in the statement type indicated by *statement* is too long for the width of the column. It is truncated to fit the column.

## User response

None required. To avoid truncation of the value, correct it to fit the column width, or lengthen the column.

---

**ISF846W**      **NO GROUPS HAVE BEEN DEFINED.**

## Explanation

The ISFPARMS contained no GROUP statements. At least one GROUP statement is required.

## User response

Add at least one GROUP statement to the ISFPARMS.

---

**ISF847I**      **WHEN STATEMENT SELECTED FOR THIS SYSTEM.**

## Explanation

The WHEN statement has been selected for this system. All statements that follow the WHEN statement will be processed for this system, until another WHEN statement is encountered.

## User response

None required.

---

**ISF848I**      **WHEN STATEMENT DOES NOT MATCH THIS SYSTEM, FOLLOWING STATEMENTS SKIPPED UNTIL NEXT WHEN.**

## Explanation

The WHEN statement specified conditions that do not match the current system. Subsequent statements will be checked for syntax but not processed, until the next WHEN statement is found.

## User response

None required.

---

**ISF849I**      ***statement-name* STATEMENT NOT SELECTED DUE TO PREVIOUS WHEN STATEMENT.**

## Explanation

Because it follows a WHEN statement that contained conditions that were not met, the statement is checked for syntax but not otherwise processed.

## User response

None required.

---

**ISF850E**

***primary-statement* CONTAINS NO *secondary-statement* ENTRIES.**

## Explanation

A statement, *primary-statement*, was encountered that requires other statements, *secondary-statement*, but no such statements followed it. The statement *primary-statement* is ignored.

## User response

Either delete the statement *primary-statement*, or add the required statements indicated by *secondary-statement*.

---

**ISF851E**      **LOCAL SERVER NOT DEFINED IN SERVER GROUP (SERVER NAME *server-name*, SYSTEM NAME *system-name*).**

## Explanation

A server group was defined for the indicated server on the indicated system, but the server group did not include the local server. A server group must include the local server. The local server is the currently executing server that is running on this system.

## User response

Add a SERVER statement for the local server to the server group definition.

---

**ISF852I**      ***statement-type* STATEMENT IGNORED, *statement-type* IN USE.**

## Explanation

An attempt was made to modify an initialization statement after the SDSF server was already active. The statement is ignored.

## User response

To change a server group after the server group is in use, you can:

1. Make the change to ISFPARMS.
2. End server communications with the MODIFY *server-name*, STOP,C, TERM command.
3. Use the MODIFY *server-name*, REFRESH command to cause the new ISFPARMS to be processed.

---

**ISF853E**      **INSUFFICIENT SERVERS DEFINED IN SERVER GROUP.**



### Explanation

A SERVERGROUP statement was encountered, but there are not at least two SERVER statements following it. A server group must consist of at least two servers, including the local server. The server group is not defined.

### User response

Correct the server group definition so that it includes at least two servers.

---

<b>ISF854E</b>	<b>NUMBER OF SERVERS IN SERVER GROUP <i>number</i> EXCEEDS THE MAXIMUM OF <i>maximum</i>.</b>
----------------	---

---

### Explanation

A SERVERGROUP statement was encountered with more than the maximum number of allowed SERVER statements following it.

### User response

Correct the server group definition so that it includes a valid number of servers.

---

<b>ISF855E</b>	<b>SERVER <i>server-name</i> DUPLICATES DEFINITION OF SERVER <i>server-name</i> ON STATEMENT <i>statement-number</i> FOR SYSTEM <i>system-name</i>, JESNAME <i>jes-name</i>, MEMBER <i>member-name</i>.</b>
----------------	---

---

### Explanation

A duplicate definition has been detected in the server group for the indicated system, JES, and member. More than one server in the server group is defined as processing a system, JES and member. This is not allowed.

### User response

Correct the server group definition in ISFPARMS.

---

<b>ISF856I</b>	<b>PARAMETER <i>parameter</i> IS OBSOLETE AND IS IGNORED.</b>
----------------	---

---

### Explanation

An obsolete parameter has been encountered. It will be ignored.

### User response

None required. To avoid seeing this message in the future, delete the parameter from ISFPARMS.

---

<b>ISF857E</b>	<b>COMMAND IS TOO LONG, MAXIMUM LENGTH ALLOWED IS <i>maximum-length</i>.</b>
----------------	--

---

### Explanation

The command or parameter being processed causes the resulting command to exceed the valid maximum length.

### User response

Ensure that the total length of the command conforms to the valid length.

---

<b>ISF858E</b>	<b>VALUE '<i>value</i>' IS NOT VALID, BEGINS WITH THE RESTRICTED CHARACTERS <i>characters</i>.</b>
----------------	--

---

### Explanation

The value of an option is not valid because it has a prefix that consists of the restricted characters, *characters*. The option is not processed.

### User response

Ensure that the value does not start with restricted characters. For example, the value of the REXX prefix option cannot start with ISF.

---

<b>ISF859E</b>	<b>COMMAND IS TOO SHORT, MINIMUM LENGTH ALLOWED IS <i>minimum-length</i>.</b>
----------------	---

---

### Explanation

The command being processed is too short.

### User response

Ensure that the command conforms to the valid length.

---

<b>ISF860I</b>	<b><i>statement</i> STATEMENT IGNORED, NOT SUPPORTED IN THIS RELEASE.</b>
----------------	---

---

### Explanation

The indicated statement in ISFPARMS has been ignored during ISFPARMS processing because it is not supported in this release of SDSF.

### User response

None required, though you may want to remove the statement from ISFPARMS or use the WHEN statement to provide conditional processing of the statement.

---

<b>ISF861I</b>	<b>STATEMENT <i>statement</i> KEYWORD <i>keyword</i> IGNORED, NOT SUPPORTED IN THIS RELEASE.</b>
----------------	--

---

### Explanation

The indicated keyword in ISFPARMS has been ignored during ISFPARMS processing because it is not supported in this release of SDSF.

### User response

None required, though you may want to remove the keyword from ISFPARMS or use the WHEN statement to provide conditional processing of the statement that contains it.

---

<b>ISF862I</b>	<b>KEYWORD <i>keyword</i> VALUE <i>value</i> IGNORED, NOT SUPPORTED IN THIS RELEASE.</b>
----------------	--

---

### Explanation

The indicated value in ISFPARMS has been ignored during ISFPARMS processing because it is not supported in this release of SDSF.

### User response

None required, though you may want to change the value in ISFPARMS or use the WHEN statement to provide conditional processing of the statement that contains it.

---

<b>ISF863E</b>	<b><i>option</i> IS REQUIRED WHEN <i>keyword</i> IS SPECIFIED.</b>
----------------	--

---

### Explanation

The command keyword *keyword* requires that option *option* also be specified, but it was omitted. The command or statement is not processed.

### User response

Correct the command.

---

<b>ISF864E</b>	<b>PROPERTY <i>property</i> VALUE CANNOT BE AN ARRAY.</b>
----------------	---

---

### Explanation

A JSON document was being processed and *property* was recognized but its value was an array. The property cannot define array values. The document was not processed.

### User response

Correct the document and retry the request.

---

<b>ISF865E</b>	<b>PROPERTY <i>property</i> VALUE CANNOT BE NUMERIC.</b>
----------------	--

---

### Explanation

A JSON document was being processed and *property* was recognized but its value was numeric. The property cannot define numeric values. The document was not processed.

### User response

Correct the document and retry the request.

---

<b>ISF866E</b>	<b>PROPERTY <i>property</i> VALUE CANNOT BE BOOLEAN.</b>
----------------	--

---

### Explanation

A JSON document was being processed and *property* was recognized but its value was Boolean. The property cannot define Boolean values. The document was not processed.

### User response

Correct the document and retry the request.

---

<b>ISF867E</b>	<b><i>value-name1</i> VALUE <i>value1</i> IS INCONSISTENT WITH <i>value-name2</i> VALUE <i>value2</i>.</b>
----------------	--

---

### Explanation

The named values have dependencies that are inconsistent. For example, a starting value is greater than an ending value. The document is not processed.

### User response

Correct the document and retry the request.

---

<b>ISF868E</b>	<b>PROPERTY <i>property-name</i> VALUE CANNOT BE A STRING.</b>
----------------	--

---

### Explanation

In a JSON document, *property-name* was recognized. Its value was a string, but the property cannot define string values.

### User response

Correct the document and retry the request.

---

**ISF869W**      **statement STATEMENT IGNORED  
DUE TO SDSF INTERNAL ERROR.**

---

### Explanation

An earlier SDSF internal error prevents the indicated statement from being processed correctly. SDSF parameter processing continues with the next statement. However, activation will be prevented.

### User response

Contact IBM support.

---

**ISF870W**      **keyword KEYWORD IGNORED, IT  
CANNOT BE SPECIFIED FOR THE  
column-name COLUMN**

---

### Explanation

The named *keyword* has been found when processing an FLDENT statement for *column-name* in ISFPARMS. However, is it not supported and is ignored

### User response

Remove the unsupported keyword.

---

**ISF880I**      **Line: *line-number* : *text***

---

### Explanation

Line *line-number* has been read from ISFPRMxx with the *text* shown. The message is written to the SDSFLOG as the lines are read.

### User response

None.

---

**ISF881E**      **Duplicate keyword *keyword*  
specified in the statement  
statement**

---

### Explanation

The *keyword* has been specified more than once on the same *statement*.

### User response

Remove the duplicate keyword specification.

---

**ISF882E**      **Unknown keyword *keyword* in the  
statement *statement***

---

### Explanation

The *keyword* has not been recognized as valid syntax for the *statement*.

### User response

Correct or remove the unknown keyword.

---

**ISF883E**      **Open parenthesis on line number  
*line-number1* conflicts with line  
*line-number2***

---

### Explanation

The open parenthesis on line number *line-number2* does not have a matching close parenthesis before line *line-number1*.

### User response

Ensure that open and close parenthesis characters are matched.

---

**ISF884E**      **Close parenthesis on line number  
*line-number* without matching  
previous open parenthesis**

---

### Explanation

The close parenthesis on line number *line-number* does not have a matching open parenthesis earlier in the current statement.

### User response

Ensure that open and close parenthesis characters are matched.

---

**ISF886E**      **A valid statement cannot be found**

---

### Explanation

During ISFPRMxx member processing, a valid statement has not been found.

### User response

Ensure that there are valid statements in the ISFPRMxx member and that comments are correctly specified.

---

**ISF889E**      **Keyword *keyword* value *value*  
contains unsupported logical  
operators**

---

### Explanation

The keyword value contains > or < symbols in the first character without being enclosed in quotes. Because these symbols are not enclosed in quotes, they are interpreted as logical operators. However, the syntax rule for the keyword does not support logical operators.

## User response

Respecify the *value* for the *keyword*.

---

<b>ISF892I</b>	<b>Statement <i>statement</i> keyword keyword set to value <i>value</i></b>
----------------	---

---

## Explanation

The named *statement keyword* has been set to the indicated value, including keywords that have been set to their default value.

## User response

None.

---

<b>ISF893E</b>	<b>Keyword <i>keyword</i> value <i>value</i> contains invalid characters for its data type</b>
----------------	--

---

## Explanation

The characters in *value* are invalid for the syntax rules for the *keyword* keyword.

## User response

Refer to the allowable character values for the **statement** keyword.

---

<b>ISF894I</b>	<b>Statement <i>statement</i> keyword keyword accepted as valid</b>
----------------	---

---

## Explanation

The value for the named *statement keyword* is valid and has been accepted. This message is issued instead of ISF892I when the length of the keyword data would make the message too long.

## User response

No response is required.

---

<b>ISF896E</b>	<b>Quotes used outside of parentheses on line number <i>line- number</i></b>
----------------	--

---

## Explanation

The quote character is not supported outside of values enclosed by parenthesis.

## User response

Remove the quote character.

---

<b>ISF898E</b>	<b>Unbalanced parentheses on line number <i>line-number</i></b>
----------------	---

---

## Explanation

The statement on line *line-number* does not have the same number of open and close parentheses.

## User response

Verify that a trailing close parenthesis is not missing and correct the statement with unbalanced parentheses.

---

<b>ISF901E</b>	<b>BINARY CONVERSION ERROR OCCURRED IN ISSUING AN SDSF MESSAGE.</b>
----------------	---

---

## Explanation

In issuing an SDSF message, SDSF encountered a binary conversion error.

## User response

Follow your local procedure to call IBM for service.

---

<b>ISF902E</b>	<b>INSERT OF AN INVALID TYPE WAS ENCOUNTERED IN AN SDSF MESSAGE.</b>
----------------	--

---

## Explanation

In issuing an SDSF message, SDSF encountered a problem in inserting a value into a message.

## User response

Follow your local procedure to call IBM for service.

---

<b>ISF903E</b>	<b>INVALID INSERT NUMBER WAS ENCOUNTERED IN AN SDSF MESSAGE.</b>
----------------	--

---

## Explanation

In issuing an SDSF message, SDSF encountered a problem in inserting a value into a message.

## User response

Follow your local procedure to call IBM for service.

---

<b>ISF904E</b>	<b>SDSF MESSAGE TOO LONG.</b>
----------------	-------------------------------

---

## Explanation

In issuing an SDSF message, SDSF encountered a message that exceeded the maximum allowed length.

## User response

Follow your local procedure to call IBM for service.

---

<b>ISF905E</b>	<b>INCORRECT NUMBER OF INSERTS PASSED FOR AN SDSF MESSAGE.</b>
----------------	--

---

### Explanation

In issuing an SDSF message, SDSF encountered a problem with inserting values into the message.

### User response

Follow your local procedure to call IBM for service.

---

<b>ISF906E</b>	<b>SDSF MESSAGE NOT ISSUED, SDSF MESSAGE TABLE NOT LOADED.</b>
----------------	--

---

### Explanation

SDSF could not issue a message because the message table containing the messages was not loaded.

### User response

Follow your local procedure to call IBM for service.

---

<b>ISF908E</b>	<b>MESSAGE <i>message-number</i> LINE <i>line-number</i> NOT FOUND IN MESSAGE TABLE.</b>
----------------	--

---

### Explanation

SDSF could not issue a message because the message or a line in the multi-line message was not found in the message table.

### User response

Follow your local procedure to call IBM for service.

---

<b>ISF912E</b>	<b>MESSAGE <i>message-number</i> REMOVED IN <i>release</i>: <i>message-</i> <i>inserts</i>.</b>
----------------	---

---

### Explanation

Message *message-number* was removed in a previous release of SDSF, but SDSF attempted to issue it with the indicated inserts. *release* shows the version, release and FMID.

### User response

Message *message-number* is not issued. Follow your local procedures for contacting IBM for service.

---

<b>ISF922E</b>	<b>SDSF CONFIGURATION ERROR.</b>
----------------	----------------------------------

---

### Explanation

SDSF has been invoked incorrectly when running as an ISPF dialog.

### User response

The system programmer should correct the invocation of SDSF. For an example of the statements needed to invoke SDSF from the ISPF main menu, refer to member ISF@PRI4 in data set ISF.SISFPLIB and “ISPF considerations” on page 359.

---

<b>ISF999I</b>	<b>DIAG: <i>diagnostic-data</i>.</b>
----------------	--------------------------------------

---

### Explanation

SDSF has encountered an internal condition in which diagnostic data has been collected.

### User response

Follow your local procedure for reporting a problem to IBM.

---

<b>ISF2001E</b>	<b>SDSF INVOCATION FAILED, RETURN CODE <i>return-code</i>.</b>
-----------------	--

---

### Explanation

The SDSF Java API attempted to perform an SDSF request, but the invocation failed with the indicated return code. The return codes are the standard SDSF return codes documented in the class description for ISFBase.

### User response

To determine the source of the error, list the SDSF messages contained in the ISFRequestResults object used for the request.

---

<b>ISF2002E</b>	<b>COMMAND NOT PROVIDED.</b>
-----------------	------------------------------

---

### Explanation

A method was invoked that requires a command to be provided but the command was missing.

### User response

Supply a command as required by the method parameters.

---

<b>ISF2003E</b>	<b>PROPERTY NAME ARRAY DIMENSION DIFFERENT THAN VALUE ARRAY DIMENSION.</b>
-----------------	--

---

## Explanation

The requestPropertyChange method was invoked to change the property of an object. However, the number of property names does not match the number of supplied property values.

## User response

The property name array must correspond one-to-one with the values supplied in the property value array. Correct the arrays that are passed in to the method.

---

<b>ISF2004E</b>	<b>PROPERTY NAME MISSING IN ARRAY ELEMENT <i>element-number</i>.</b>
-----------------	--

---

## Explanation

The requestPropertyChange method was invoked to change the property of an object. However, the number of property names does not match the number of supplied property values.

## User response

Correct the property name array.

---

<b>ISF2005E</b>	<b>RESULTS OBJECT NOT PROVIDED.</b>
-----------------	-------------------------------------

---

## Explanation

SDSF was invoked to perform a function but the results object was not provided.

## User response

Follow your local procedures for contacting IBM for support.

---

<b>ISF2006E</b>	<b>ROW TOKEN WAS NOT PROVIDED FOR OBJECT <i>object-name</i>.</b>
-----------------	--

---

## Explanation

An action was attempted against a row object, but the object does not contain a row token. The object name is the fixed field for the object. The action cannot be performed.

## User response

Verify that the object was not modified in any way such that the action cannot be performed. Check that the nomodify request setting was not used when the object was originally retrieved.

---

<b>ISF2007E</b>	<b>ROW TOKEN WAS NOT PROVIDED FOR OBJECT <i>object-name</i> IN REPEAT LIST ENTRY <i>entry- number</i>.</b>
-----------------	--

---

## Explanation

An action was attempted against a row object using a repeat list, but the object does not contain a row token. The object name is the fixed field and the entry number is the position of the object in the repeat list.

## User response

Verify that the object was not modified in any way such that the action cannot be performed. Check that the nomodify request setting was not used when the object was originally retrieved.

---

<b>ISF2008E</b>	<b>PROPERTY NAME ARRAY NOT PROVIDED.</b>
-----------------	--

---

## Explanation

The requestPropertyChange method was invoked to change the property of an object. However, the property name array was not provided.

## User response

Supply the property name array.

---

<b>ISF2009E</b>	<b>PROPERTY VALUE ARRAY NOT PROVIDED.</b>
-----------------	---

---

## Explanation

The requestPropertyChange method was invoked to change the property of an object. However, the property value array was not provided.

## User response

Supply the property value array.

---

<b>ISF2010E</b>	<b>PARAMETER <i>parameter-name</i> MUST HAVE THE VALUE <i>parameter-value</i>.</b>
-----------------	--

---

## Explanation

A method was invoked using *parameter-name*, but the required value was not provided.

## User response

Verify the parameter values for the method are correct.

---

<b>ISF2011E</b>	<b>INCONSISTENT INDEXES IN SETTINGS, <i>fromIndex</i>, <i>from-index</i>, IS EQUAL TO <i>toIndex</i>, <i>to-index</i>.</b>
-----------------	--

---

## Explanation

The request settings have been used to specify a range of rows to return. However, the range indexes are not consistent because the from-index is equal to the to-index.

## User response

Correct the request settings and retry the request.

---

<b>ISF2012E</b>	<b>INCONSISTENT INDEXES IN SETTINGS, fromIndex, from-index, IS GREATER THAN toIndex, to-index.</b>
-----------------	--

---

## Explanation

The request settings have been used to specify a range of rows to return. However, the range indexes are not consistent because the from-index is greater than the to-index.

## User response

Correct the request settings and retry the request.

---

<b>ISF2101E</b>	<b>SDSF INTERNAL ERROR OCCURRED IN <i>class-name#method-name</i>, REASON=<i>reason-code</i>.</b>
-----------------	--

---

## Explanation

An internal error occurred in the indicated class and method.

## User response

Follow your local procedures to contact IBM for support.

---

<b>ISF2102E</b>	<b>TRACE TABLE ENTRY TOO LARGE.</b>
-----------------	-------------------------------------

---

## Explanation

An error occurred processing an internal trace entry.

## User response

Follow your local procedures to contact IBM for support.

---

<b>ISF2103E</b>	<b>TRACE TABLE TOO LARGE.</b>
-----------------	-------------------------------

---

## Explanation

An error occurred processing the internal trace table.

## User response

Follow your local procedures to contact IBM for support.

---

<b>ISF2104E</b>	<b>TRACE TABLE ENTRY TOO SMALL.</b>
-----------------	-------------------------------------

---

## Explanation

An error occurred processing an internal trace entry.

## User response

Follow your local procedures to contact IBM for support.

---

<b>ISF2105E</b>	<b>TRACE TABLE TOO SMALL.</b>
-----------------	-------------------------------

---

## Explanation

An error occurred processing the internal trace table.

## User response

Follow your local procedures to contact IBM for support.

---

<b>ISF2106E</b>	<b>CANNOT CONVERT VALUE <i>value</i> WITH RESULT <i>result</i>.</b>
-----------------	---

---

## Explanation

An error occurred processing an internal trace entry.

## User response

Follow your local procedures to contact IBM for support.

---

<b>ISF2201W</b>	<b>RESPONSE LIMIT IN EFFECT, <i>number</i> OF <i>total</i> OBJECTS RETURNED.</b>
-----------------	--

---

## Explanation

A request limit was set for the current request. The number of objects returned is limited by the request limit in ISFRequestSettings.

## User response

None.

---

<b>ISF2202I</b>	<b>PROCESSING STARTED...</b>
-----------------	------------------------------

---

## Explanation

SDSF has started processing a request.

### User response

None.

---

**ISF2203I            PROCESSING COMPLETED.**

### Explanation

SDSF has finished processing a request.

### User response

None.

---

**ISF2204E            VALUE NOT ALLOWED FOR  
                      OPTION "option".**

### Explanation

A value was specified for option *option*, but the option does not accept values.

### User response

Remove the value from the option and retry the request.

---

**ISF2205E            VALUE REQUIRED FOR OPTION  
                      "option".**

### Explanation

An option was specified without a value, but the option requires that a value be used.

### User response

Add a value to the option and retry the request.

---

**ISF2206I            REPORT BEING WRITTEN TO  
                      pathname.**

### Explanation

A report has been requested and is being written to the named path.

### User response

None.

---

**ISF2207E            UNABLE TO OPEN REPORT FILE  
                      pathname, REASON=reason-text.**

### Explanation

An error occurred attempting to open the report file using the named path. The report will be written to stdout.

### User response

Ensure the path names a valid path for the report.

---

**ISF2208E            UNRECOGNIZED OPTION "option".**

### Explanation

An unknown option was specified.

### User response

Correct the option and try the request again.

---

**ISF2209I            PARAMETERS IGNORED.**

### Explanation

A request was processed that does not accept parameters, but parameters were specified. The parameters are ignored and processing continues.

### User response

Remove the unsupported parameters.

---

**ISF2210W            RESPONSE LIMIT IN EFFECT,  
                      number OBJECTS RETURNED.**

### Explanation

A response limit was set for the current request. The number of objects returned is limited by the response limit in ISFRequestSettings.

### User response

None required.

---

**ISF2211I            OPTION *option* IS OBSOLETE AND  
                      IGNORED**

### Explanation

The named invocation *option* is obsolete and ignored. Note that the option must be syntactically correct.

### User response

None required. It is recommended that you remove the option because it is not supported.



## Messages for IBM Health Checker for z/OS

---

This section describes messages that are issued as output of SDSF's checks for IBM Health Checker for z/OS.

---

**ISFH1001I**      **SDSF server *server-name* is using statements from member *member-name* of data set *dataset-name*.**

### Explanation

The SDSF server is active and using the indicated parmlib member from the named data set.

### System action

None.

### Operator response

None.

### System programmer response

None.

### Problem determination

None.

### Source

z/OS SDSF Operation and Customization

### Module

ISFHCPRM

### Automation

None.

### Reference documentation

z/OS SDSF Operation and Customization

---

**ISFH1002I**      **SDSF server *server-name* is not active, parmlib statements are not being used.**

### Explanation

The SDSF server is not active. The use of the SDSF parmlib member ISFPRMxx requires that the SDSF server be active.

IBM recommends that you use parmlib member ISFPRMxx rather than assembler macro ISFPARMS

to configure SDSF. The statements in ISFPRMxx are easier to define and more dynamic than assembler macros. Some functions, such as sysplex support, are not available using the assembler macros.

### System action

In a JES2 environment, SDSF uses the assembler macro ISFPARMS for configuration parameters. In a JES3 environment, SDSF assigns default values.

### Operator response

None.

### System programmer response

Consider migrating from the assembler macro ISFPARMS to parmlib member ISFPRMxx if you plan on changing any SDSF configuration values from their default settings.

### Problem determination

None.

### Source

z/OS SDSF Operation and Customization

### Module

ISFHCPRM

### Automation

None.

### Reference documentation

z/OS SDSF Operation and Customization

---

**ISFH1003I**      **SDSF server *server-name* is active but parmlib statements are not being used. A possible syntax error in the statements may exist.**

### Explanation

The SDSF server is active but parmlib member ISFPRMxx is not being used to configure SDSF. This may be because the SDSF server detected a syntax error in the configuration statements.

**System action**

In a JES2 environment, SDSF uses the assembler macro ISFPARMS for configuration parameters. In a JES3 environment, SDSF assigns default values.

**Operator response**

None.

**System programmer response**

Examine the server initialization log for errors in ISFPRMxx statements. Correct any errors that prevent the statements from being activated and then use the SDSF server refresh command to reprocess the statements.

**Problem determination**

None.

**Source**

z/OS SDSF Operation and Customization

**Module**

ISFHCPRM

**Automation**

None.

**Reference documentation**

z/OS SDSF Operation and Customization

<b>ISFH1004I</b>	<b>SDSF is not using parmlib statements for its configuration parameters. However, no values have been customized.</b>
------------------	--

**Explanation**

SDSF is not using parmlib member ISFPRMxx for its configuration parameters, and SDSF-supplied defaults are being used for all values.

**System action**

If this is a JES2 environment, SDSF is using the assembler macro based ISFPARMS. No values have been changed in ISFPARMS. If this is a JES3 environment, SDSF is using default values and is not using the assembler macro based ISFPARMS.

**Operator response**

None.

**System programmer response**

If you plan on changing any SDSF configuration values from their default settings, use parmlib member ISFPRMxx for your configuration changes.

You can use the sample members ISFPRM00 and ISFPRM01 in ISF.SISFJCL to assist you in defining your configuration.

**Source**

z/OS SDSF Operation and Customization

**Module**

ISFHCPRM

**Automation**

None.

**Reference documentation**

z/OS SDSF Operation and Customization

<b>ISFH1005E</b>	<b>SDSF is using assembler macro ISFPARMS for its configuration parameters.</b>
------------------	---

**Explanation**

SDSF is using the assembler macro based ISFPARMS for its configuration parameters rather than parmlib member ISFPRMxx. ISFPARMS has been customized by the installation.

**System action**

None.

**Operator response**

None.

**System programmer response**

IBM recommends that you use parmlib member ISFPRMxx rather than assembler macro ISFPARMS to configure SDSF. The statements in ISFPRMxx are easier to define and more dynamic than assembler macros. Some functions, such as sysplex support, are not available using the assembler macros.

Consider migrating from the assembler macro ISFPARMS to parmlib member ISFPRMxx.

You can use the migration tool ISFACP, supplied with SDSF, to convert your existing ISFPARMS to the statement format required by parmlib member ISFPRMxx. You can also use the sample members ISFPRM00 and ISFPRM01 in ISF.SISFJCL to define your configuration.

After defining the configuration statements, refer to Chapter 3, “Using the SDSF server,” on page 73 for the steps necessary to start the SDSF server and activate the configuration.

**Source**

z/OS SDSF Operation and Customization

**Module**

ISFHCPRM

**Automation**

None.

**Reference documentation**

z/OS SDSF Operation and Customization

<b>ISFH1006I</b>	<b>ISFPARMS module being analyzed has a service level of <i>service-level</i>, and a compile date and time of <i>compile-date compile-time</i>.</b>
------------------	---

**Explanation**

ISFPARMS will be analyzed for installation customization changes. The service level, compile date, and compile time of the ISFPARMS module that has been found are listed.

This message is only issued when the check is running in verbose mode.

**System action**

Processing continues.

**Operator response**

None.

**System programmer response**

Use the details from the message to determine that the intended level of ISFPARMS has been found on your system.

**Source**

z/OS SDSF Operation and Customization

**Module**

ISFHCPRM

**Automation**

None.

**Reference documentation**

z/OS SDSF Operation and Customization

<b>ISFH1007I</b>	<b>ISFPARMS group structure has been customized. No further analysis of ISFPARMS will be performed.</b>
------------------	---

**Explanation**

The groups in ISFPARMS have been customized. Either the number of groups has been changed, or the group names have been changed from the defaults supplied by SDSF.

No further analysis of ISFPARMS will be performed to determine if other customizations are present.

**System action**

No further checking is done to determine which group keywords vary from the SDSF defaults.

**Operator response**

None.

**System programmer response**

Assess whether the customization is still required. Consider migrating from the assembler macro ISFPARMS to parmlib member ISFPRMxx if the configuration parameter is required.

You can use the migration tool ISFACP, supplied with SDSF, to convert your existing ISFPARMS to the statement format required by parmlib member ISFPRMxx. You can also use the sample members

ISFPRM00 and ISFPRM01 in ISF.SISFJCL to define your configuration.

**Source**

z/OS SDSF Operation and Customization

**Module**

ISFHCPRM

**Automation**

None.

**Reference documentation**

z/OS SDSF Operation and Customization

<b>ISFH1008I</b>	<b>This check is not applicable since SDSF is not enabled for execution on this system.</b>
------------------	---

**Explanation**

The IFAEDSTA service has indicated that SDSF is not enabled for execution on this system.

**System action**

The check is disabled and no further checking will be done.

**Operator response**

None.

**System programmer response**

If SDSF should be enabled, verify that the statements in the IFAPRDxx member of parmlib are correct.

**Problem determination**

None.

**Source**

z/OS SDSF Operation and Customization

**Module**

ISFHCPRM

**Automation**

None.

**Reference documentation**

z/OS SDSF Operation and Customization

<b>ISFH1009I</b>	<b>Load of ISFPARMS failed with abend code <i>abend-code</i> reason code <i>reason-code</i>. Analysis of ISFPARMS will not be performed.</b>
------------------	--

**Explanation**

The load of the ISFPARMS module failed with the indicated abend and reason codes. In a JES3 environment in which the SDSF JES2 feature is not installed, ISFPARMS will not be present and this error can be ignored.

**System action**

No analysis of ISFPARMS can be done to determine if it has been customized.

**Operator response**

None.

**System programmer response**

Use the abend return and reason codes to determine why ISFPARMS cannot be loaded.

**Problem determination**

None.

**Source**

z/OS MVS System Codes

**Module**

ISFHCPRM

**Automation**

None.

**Reference documentation**

z/OS SDSF Operation and Customization

<b>ISFH1010R</b>	<b>ISFPARMS Customization Report</b>
------------------	--------------------------------------

**Explanation**

Header line for SDSF\_ISFPARMS\_IN\_USE check.

**System action**

Processing continues.

**Operator response**

None.

**System programmer response**

None.

**Problem determination**

None.

**Source**

None.

**Module**

ISFHCPRM

**Automation**

None.

**Reference documentation**

None.

<b>ISFH1011R</b>	<b>S Macro Name Parameter Changed Comments</b>
------------------	--

**Explanation**

Header line for SDSF\_ISFPARMS\_IN\_USE check.

**System action**

Processing continues.

**Operator response**

None.

**System programmer response**

None.

**Problem determination**

None.

**Source**

None.

**Module**

ISFHCPRM

**Automation**

None.

**Reference documentation**

None.

<b>ISFH1012R</b>	<b>----- -----</b>
------------------	------------------------

**Explanation**

Header line for SDSF\_ISFPARMS\_IN\_USE check.

**System action**

Processing continues.

**Operator response**

None.

**System programmer response**

None.

**Problem determination**

None.

**Source**

None.

**Module**

ISFHCPRM

**Automation**

None.

**Reference documentation**

None.

<b>ISFH1013R</b>	<b><i>status macro name parameter changed comments</i></b>
------------------	--

**Explanation**

Detail line for SDSF\_ISFPARMS\_IN\_USE check.

### System action

Processing continues.

### Operator response

None.

### System programmer response

None.

### Problem determination

None.

### Source

None.

### Module

ISFHCPRM

### Automation

None.

### Reference documentation

None.

---

<b>ISFH1014R</b>	<b>Total changes found: <i>change-count</i>.</b>
------------------	--

### Explanation

Total line for SDSF\_ISFPARMS\_IN\_USE check.

### System action

Processing continues.

### Operator response

None.

### System programmer response

None.

### Problem determination

None.

### Source

None.

### Module

ISFHCPRM

### Automation

None.

### Reference documentation

None.

---

<b>ISFH1015I</b>	<b>The class <i>class-name</i> is active.</b>
------------------	---

### Explanation

The indicated SAF class is active, as recommended.

### System action

None.

### Operator response

None.

### System programmer response

None.

### Problem determination

None.

### Source

None.

### Module

ISFHCPRM

### Automation

None.

### Reference documentation

None.

---

<b>ISFH1016E</b>	<b>The class <i>class-name</i> is not active.</b>
------------------	---

### Explanation

The indicated SAF class is not active.

**System action**

If this is a JES2 environment, SDSF will use ISFPARMS to make authorization decisions related to the class. If this is a JES3 environment, requests for authorization that are related to the class will be denied.

**Operator response**

None.

**System programmer response**

IBM recommends that the security administrator activate this class and define profiles in it to protect use of SDSF function. In the JES3 environment, use of SAF security is required. The class should be activated and defined with the appropriate profiles so SDSF can be used with JES3.

**Problem determination**

None.

**Source**

None.

**Module**

ISFHCSAF

**Automation**

None.

**Reference documentation**

None.

<b>ISFH1017I</b>	<b>RACROUTE request-type completed. SAF return code <i>saf-return-code</i>, return code <i>return-code</i>, reason code <i>reason-code</i>.</b>
------------------	---

**Explanation**

The named RACROUTE request issued by the check has completed with the indicated return and reason codes. This message is only issued in debug mode.

**System action**

None.

**Operator response**

None.

**System programmer response**

None.

**Problem determination**

None.

**Source**

None.

**Module**

ISFHCSAF

**Automation**

None.

**Reference documentation**

None.

<b>ISFH1018R</b>	<b>SDSF Class Resource Report</b>
------------------	-----------------------------------

**Explanation**

Header line for SDSF\_CLASS\_SDSF\_ACTIVE check.

**System action**

Processing continues.

**Operator response**

None.

**System programmer response**

None.

**Problem determination**

None.

**Source**

None.

**Module**

ISFHCSAF

**Automation**

None.

## Reference documentation

None.

---

### ISFH1019R      S Decision Access Resource

#### Explanation

Header line for SDSF\_CLASS\_SDSF\_ACTIVE check.

#### System action

Processing continues.

#### Operator response

None.

#### System programmer response

None.

#### Problem determination

None.

#### Source

None.

#### Module

ISFHCSAF

#### Automation

None.

#### Reference documentation

None.

---

### ISFH1020R      -----

-----  
-----

#### Explanation

Header line for SDSF\_CLASS\_SDSF\_ACTIVE check.

#### System action

Processing continues.

#### Operator response

None.

## System programmer response

None.

#### Problem determination

None.

#### Source

None.

#### Module

ISFHCSAF

#### Automation

None.

#### Reference documentation

None.

---

### ISFH1021R      *status decision access resource*

#### Explanation

Detail line for SDSF\_CLASS\_SDSF\_ACTIVE check, where the values for *status*, *decision*, *access*, and *resource* are described in message ISFH1026R.

#### System action

Processing continues.

#### Operator response

None.

#### System programmer response

None.

#### Problem determination

None.

#### Source

None.

#### Module

ISFHCSAF

#### Automation

None.



## Reference documentation

None.

---

### ISFH1022E      Unable to locate resource.

#### Explanation

ISFZVTBL could not be located to perform a resource level health check. This message is only issued in debug mode.

#### System action

Processing continues.

#### Operator response

None.

#### System programmer response

Ensure that ISF.SISFLPA is in the LPA library.

#### Problem determination

None.

#### Source

None.

#### Module

ISFHCSAF

#### Automation

None.

#### Reference documentation

None.

---

### ISFH1023E      Unable to obtain resource to build profile table.

#### Explanation

Storage could not be obtained to build the resource profile table. This message is only issued in debug mode.

#### System action

Processing continues.

## Operator response

None.

## System programmer response

None.

## Problem determination

None.

## Source

None.

## Module

ISFHCSAF

## Automation

None.

## Reference documentation

None.

---

### ISFH1024E      Unable to obtain resource data.

#### Explanation

No resource was defined or the resource vector could not be obtained. This message is only issued in debug mode.

#### System action

Processing continues.

#### Operator response

None.

#### System programmer response

None.

#### Problem determination

None.

#### Source

None.

#### Module

ISFHCSAF

## Automation

None.

## Reference documentation

None.

**ISFH1025I**      The class SDSF is not RACLISTed.

## Explanation

The SDSF class is not RACLISTed.

## System action

Processing continues.

## Operator response

None.

## System programmer response

None.

## Problem determination

None.

## Source

z/OS SDSF Operation and Customization

## Module

ISFHCSAF

## Automation

None.

## Reference documentation

z/OS SDSF Operation and Customization

**ISFH1026R**      - S (Status) of \*\* indicates the resource is not defined to SAF.  
- Decision indicates how SDSF will determine access to the resource:  
- SAFRC indicates SDSF will use the result from SAF.  
- FAILRC4 indicates access will be denied due to SAF no decision result and FAILRC4 specified in ISFPRMxx.  
- NOFAILRC4 indicates access will be allowed due to SAF no decision

result and NOFAILRC4 specified in ISFPRMxx.

- Access indicates the required access level for the resource.
- Resource is the resource name being processed.

## Explanation

Header line for SDSF\_CLASS\_SDSF\_ACTIVE check.

## System action

None.

## Operator response

None.

## System programmer response

None.

## Problem determination

None.

## Source

z/OS SDSF Operation and Customization

## Module

ISFHCSAF

## Automation

None.

## Reference documentation

z/OS SDSF Operation and Customization

**ISFH1027E**      At least one SDSF resource resulted in a SAF no decision.

## Explanation

SAF could not make a decision for one or more entries in a table. Access to the resource will be either allowed or denied based on the FAILRC4 or NOFAILRC4 specification in ISFPRMxx.

## System action

None.

## Operator response

None.

## System programmer response

IBM recommends that all resources have corresponding profiles so that a SAF indeterminate result does not occur.

## Problem determination

None.

## Source

z/OS SDSF Operation and Customization

## Module

ISFHCSAF

## Automation

None.

## Reference documentation

z/OS SDSF Operation and Customization

## SDSF user abend codes

This section explains the codes that SDSF issues in the case of an abend. The entry for each abend code includes a brief description of the meaning of the code and a suggested response for the system programmer.

The SDSF abend codes are issued in the SDSF ABEND USER message described in [Chapter 10, “SDSF messages and codes,”](#) on page 367 (ISF012I). System abend codes are in the SDSF ABEND SYSTEM message (also ISF012I). See the appropriate system codes manual for information on system abend codes.

Table 180. SDSF Abend Codes

Abend Code	Explanation
<b>0010</b>	SDSF was invoked in an inconsistent manner. <i>System Programmer Response:</i> Check that SDSF was not invoked using an incorrect entry point, such as a line mode invocation using an interactive entry point.
<b>0011</b>	The logical screen size was changed to less than the minimum width of 80 characters. <i>User Response:</i> Change the logical screen size to have a width of at least 80 characters.
<b>0012</b>	SDSF detected a non-supported terminal. The terminal has a line length of less than 80 characters. <i>User Response:</i> Use a terminal with a line length of at least 80 characters.
<b>0013</b>	An error has occurred opening a file. A read to the job file control block (JFCB) may have failed. <i>System Programmer Response:</i> Check for a JCL or hardware error. If you are running SDSF in batch, be sure you have allocated both ISFIN and ISFOUT.
<b>0015</b>	A system initialization error has occurred. <i>System Programmer Response:</i> See an accompanying write-to-operator message for more information.

Table 180. SDSF Abend Codes (continued)

Abend Code	Explanation
<b>0016</b>	<p>During SDSF initialization, an include or exclude list was being processed that specified an ISFNTBL TYPE=DEST macro. However, the list being processed is not for destinations. SDSF initialization is terminated after all include and exclude lists are processed. Message ISF028E is issued to further describe the error.</p> <p><i>System Programmer Response:</i> Ensure that the ISFNTBL macro is coded correctly for the include or exclude list being processed.</p>
<b>0019</b>	<p>During SDSF initialization, module ISFZVTBL was not located in LPA or the version of the module was incorrect. SDSF initialization is terminated. The reason code indicates the error found:</p> <ul style="list-style-type: none"> <li>• xxxx0001 - CSVQUERY failed to locate module in LPA</li> <li>• xxxx0002 - Entry address not found</li> <li>• xxxx0003 - Version level mismatch with client</li> <li>• xxxx0004 - Feature level mismatch with client</li> </ul> <p><i>System Programmer Response:</i> Ensure the correct level of ISFZVTBL is installed in LPA.</p>
<b>0028</b>	<p>An error was encountered while attempting to locate, retrieve, or process a SYSOUT data set record.</p> <p><i>System Programmer Response:</i> Follow your local procedure to call IBM for service.</p>
<b>0031</b>	<p>An invalid function code was passed to the SDSF I/O interface routine.</p> <p><i>System Programmer Response:</i> Follow your local procedure to call IBM for service.</p>
<b>0032</b>	<p>An unrecoverable error has occurred in an SDSF storage management routine. A storage request could not be satisfied.</p> <p><i>System Programmer Response:</i> Follow your local procedure for reporting a problem to IBM.</p>
<b>0041</b>	<p>There is a logic error in the SDSF DA panel routine.</p> <p><i>System Programmer Response:</i> Follow your local procedure to call IBM for service.</p>
<b>0053</b>	<p>A dynamic allocation error has occurred.</p> <p><i>System Programmer Response:</i> See the associated write-to-operator message for more information.</p>
<b>0061</b>	<p>The initialization of SDSF under ISPF was unsuccessful. The support for ISPF might have been installed incorrectly, or SDSF might have been put into the TSO authorized command tables. SDSF cannot run from the TSO authorized command tables.</p> <p><i>System Programmer Response:</i> Check the support for ISPF, and be sure that SDSF is not in the TSO authorized command tables.</p>
<b>0071</b>	<p>The terminal has become disconnected, or there is a logic error in the terminal or display routine.</p> <p><i>System Programmer Response:</i> None, if terminal has been disconnected. Otherwise, follow your local procedure to call IBM for service.</p>
<b>0072</b>	<p>SDSF has abended because the Attention key was pressed.</p> <p><i>User Response:</i> Reaccess SDSF.</p>
<b>0073</b>	<p>The menu data set is defective.</p> <p><i>System Programmer Response:</i> If you have made changes to the menu data set, check the changes. If the problem cannot be found, you can replace the installed SDSF panel data set with the original panel data set on the SDSF distribution tape.</p>

Table 180. SDSF Abend Codes (continued)

Abend Code	Explanation
<b>0080</b>	<p>A SDSF initialization failure has occurred processing the JES2 checkpoint. Message ISF006I contains the explanatory information.</p> <p><i>System Programmer Response:</i> See the accompanying write-to-operator message for information.</p>
<b>0081</b>	<p>The level of JES2 that SDSF was assembled for does not match the level of JES2 that is being executed.</p> <p><i>System Programmer Response:</i> Ensure that SDSF has been assembled for the proper set of JES2 macro libraries for the execution system. If the JES2 macro libraries were not correct, reassemble SDSF for the correct JES2 macro libraries. See the accompanying ISF020E message for more information on JES2 levels. Also, check the SDSF library concatenations and the library authorizations to be sure the correct level of SDSF is being used.</p>
<b>0082</b>	<p>The level of the SDSF JES2 feature is not compatible with the level of the SDSF base code. This error may occur if maintenance is required by both the SDSF base and feature FMIDs but has been applied to only one of the FMIDs.</p> <p><i>System Programmer Response:</i> Ensure that a consistent level of the SDSF load modules is being used. Check the lnkfst data sets for compatible versions of the SISFLOAD and SISFMOD1 data sets. If maintenance has been applied to either SISFLOAD or SISFMOD1, ensure that any co-requisite relationships have been preserved when applying PTFs.</p>
<b>0083</b>	<p>ISFPARMS was found to not be generated at the current level.</p> <p><i>System Programmer Response:</i> ISFPARMS was assembled using an incorrect macro level or with macros that do not correspond to this release. Reassemble ISFPARMS using the correct macro level. The abend reason codes (hexadecimal) are as follows:</p> <ul style="list-style-type: none"> <li>• 04 - Incorrect ISFPMAC release level</li> <li>• 08 - Incorrect ISFPMAC feature level</li> <li>• 0C - Incorrect ISFGRP entry length</li> <li>• 10 - Incorrect ISFGRP version</li> <li>• 14 - Incorrect ISFPMAC version</li> </ul>
<b>0091</b>	<p>SDSF has detected an error return code during the execution of an ISPF service. SDSF execution has terminated.</p> <p><i>System Programmer Response:</i> See the accompanying ISF039I message for more information.</p>
<b>0092</b>	<p>A failure occurred when SDSF invoked an ISPF dialog service.</p> <p><i>System Programmer Response:</i> See the accompanying ISF039I message for more information.</p>
<b>0093</b>	<p>SDSF has detected an error return code during the execution of an ISPF service. SDSF execution has terminated.</p> <p><i>System Programmer Response:</i> See the accompanying ISF039I message for more information.</p>
<b>0105</b>	<p>A logic error has been encountered during SAF processing. Expected parameters were not available; SAF processing is unable to continue.</p> <p><i>System Programmer Response:</i> Follow your local procedure to call IBM for service.</p>
<b>0113</b>	<p>An unexpected error has occurred.</p> <p><i>System Programmer Response:</i> Follow your local procedure to call IBM for service.</p>

Table 180. SDSF Abend Codes (continued)

Abend Code	Explanation
<b>0201</b>	An unrecoverable error has occurred which causes the server to abend. The reason code indicates the cause for the error:
<b>0001</b>	Unable to obtain storage for the CAB.
<b>0002</b>	Unable to obtain storage for the SAB.
<b>0003</b>	Incorrect execution environment. The server is not running in the correct protect key. Verify that a PPT entry has been defined in the SCHEDxx member of the parmlib concatenation for program ISFHCTL.
<b>0405</b>	Task already active.
<b>040C</b>	Not started correctly.
<b>0804</b>	Incorrect operating system level.
<b>0819</b>	Incorrect execution/key storage.
<b>082C</b>	Invalid environment detected.
<b>0868</b>	Module LOAD failed.
<b>0874</b>	- LPA module version mismatch.
<b>0C04</b>	SDSF server unexpectedly unavailable.
<b>0222</b>	SDSF abended in response to the ABEND command.
	<i>System Programmer Response:</i> The person who issued the ABEND command can print or display the dump that was requested.

---

## Appendix A. SDSF problem management

This topic is a guide to resolving problems with SDSF. It includes hints for observing and identifying a problem and a reference for managing problems.

### Observing and identifying a problem

---

The following are some questions you might ask yourself when you experience a problem with SDSF. They may help you to identify and resolve the problem, or to give needed information to IBM personnel at the IBM Support Center.

- Are you using new levels of JES, ISPF, or TSO? The problem may be in the relationship between SDSF and JES, ISPF, or TSO.
- Was any maintenance applied, or hardware change made, at the time the problem first appeared? The problem may be in the maintenance or hardware change.
- If maintenance has been applied recently, does SDSF run properly when it is removed? Again, the maintenance may have been improperly applied, or may itself have a problem.
- Are all users of SDSF affected by the problem, or just a few users?
- If it is a recurring problem, does it always show the same symptoms?

### Gathering information about a problem

---

Use this section when you need to gather information about a problem with SDSF, either to analyze the problem yourself, or to describe the problem to the IBM Support Center.

#### Dumps

SDSF requests an SDUMP whenever an abend occurs. This dump will be written to the SYS1.DUMPxx data sets. If the Dump Analysis and Elimination (DAE) component is active, duplicate dumps will be suppressed

When sending module listings to IBM along with a dump, be sure that the module listings have the same date as the date of the modules in the dump.

#### Trace

The trace facility is used to create trace records containing key environmental data useful for servicing SDSF. Trace records can be written to either a SYSOUT file or a wraparound DASD data set from strategic points throughout the SDSF code.

The trace facility is intended to be used under the direction of IBM Service.

#### Module information

Use the commands under the direction of IBM Service to gather module level and compile information.

##### SDSF client

To gather information on the SDSF client, use the QUERY MODULE command. The syntax is as follows:

```
➡ QUERY _____ MODULE _____ module-name ➡  
   |         |         |  
   Q         MOD
```


### **module-name**

is the name of the SDSF module. The module must be in ISFVTBL or currently be loaded.

## **SDSF server**

To gather information on the SDSF server, use the MODIFY command. The syntax is as follows:

### **Display Server Options**



### **csect-pattern**

is a pattern naming a csect within the module.

### **module-name**

is the name of the load module.

## **SDSF problem index**

### **The SDSF server fails to start**

The SDSF server is mandatory for using SDSF. If the server fails to start or encounters severe errors during ISFPRMxx processing, remedial actions must be taken to restore functionality. There are two server start failure scenarios to consider:

- Failure of the server operator START command
- Failure to activate the initial ISFPRMxx parameters

#### **Server operator START command failure**

The SDSF server might fail to start when there is a JCL error or when a fatal environmental error is encountered.

In the event of a JCL error, SDSF cannot be used on the local system to browse the server output. However, the following alternate methods can be used:

- Access the SDSF started task output from another member system in the same MAS.
- Use ISPF option 3.8 (OUTLIST) to browse the output. This option requires TSO customization (via exit IKJEFF53) to allow you to see output for jobs that are not prefixed with your user ID. Refer to the topic *Writing an exit for the OUTPUT, STATUS, and CANCEL commands* in the [z/OS TSO/E Customization](#) documentation.

If a fatal environmental error occurs, the SDSF server issues a WTO message and then issues a U0201 abend. The root causes for this situation might be one or more of the following:

- Invalid entry in the program properties table (PPT)
- Invalid operating system release
- SDSF server not started as a started task
- Severe system storage shortage

If a U0201 abend occurs, refer to the message issued by the SDSF server and take corrective actions. If the appropriate corrective action is unclear, follow local procedures to contact IBM Software Support.



## Initial ISFPRXxx parameter failure

When the SDSF server address space starts, but fails to activate the initial ISFPRMxx member, message ISF731E is issued, and SDSF attempts to fall back to the ISFPARMS load module for skeleton definitions.

In this state, most SDSF users cannot access SDSF. However, users with READ access to the SERVER.NOPARM resource in the SDSF SAF class can connect to the SDSF server and access the product in a limited capacity to resolve the issues. Any command that requires SDSFAUX (such as DA) is not available, but a user with SERVER.NOPARM access can use JES-related commands such as ST, H, and O to examine the SDSF output and determine the cause of the parameter activation failure.

**Note:** SERVER.NOPARM access to SDSF is intended for emergency maintenance mode only and should not be considered for normal SDSF operations.

If SDSF cannot be used interactively to browse JES output, and no access to the output is possible from other members of the MAS, the SDSF server can be stopped and then restarted with the runtime parameter **LOGTYPE=HC** to send the ISFPRMxx failure messages via WTO to the console and to hardcopy SYSLOG. Note that doing so might generate a large number of messages to the console.

An alternative to restarting the server with **LOGTYPE=HC** is to add an SDSFLOG DD statement to the SDSF started task JCL that points to a data set with DSORG=PS, RECFM=VB, LRECL=256, and BLKSIZE=32760, and then use ISPF to browse the data set.

Once errors in ISFPRMxx have been corrected, the operator command `F SDSF , REF M=xxx` can be issued to refresh the parameters from ISFPRMxx. SDSF is supplied with a minimal ISFPRM00 PARMLIB member in SISFJCL that in most cases should activate when you issue `F SDSF , REF M=00`.

## Problems with the Repeat-Find PF keys (PF5 and PF17)

If you use the Repeat-Find PF keys under ISPF and they don't invoke the Repeat Find function, the problem may be that the SDSF table library was not concatenated correctly with the ISPF table libraries. You may also see the ISPF message RFIND NOT ACTIVE to indicate this. The SDSF Repeat-Find key should be defined as IFIND.

## Problems with the LOG and RETRIEVE commands

If you issue a LOG or RETRIEVE command from ISPF and it does not invoke the SDSF LOG or RETRIEVE function, the problem may be that the SDSF table library was not concatenated correctly with the ISPF table libraries.

## Users are experiencing authorization problems

If users are incorrectly being denied authorization to issue commands or access data sets, there are several possible explanations:

- The users are being placed in the wrong authorization group. Have the users issue the WHO command to display their authorization group index, and check the ISFGRP, ISFNTBL, and ISFFLD macros in ISFPARMS or the GROUP, NTBL, and FLD initialization statements to see that they are coded correctly. In ISFPARMS, be sure that you have used commas and continuation characters correctly with macros that occupy more than one line. (The index indicates the group by a count of groups. For example, an index of 3 indicates the group defined by the third GROUP statement in ISFPARMS.)

Also, if the problem is with issuing MVS or JES2 commands from the command line, check the CMDAUTH parameter for that group. For users to issue MVS or JES2 commands from the command line, ALL must have been specified for CMDAUTH for their group. See the description of the CMDAUTH parameter in [“Group authorization parameters \(GROUP or ISFGRP\)”](#) on page 17.

- For SAF users, SAF resources were not authorized properly. See [Chapter 7, “Protecting SDSF functions,”](#) on page 225 for more information on authorizing users to use commands, action characters, overtypeable fields, and jobs using the SAF interface.

- The user exit module, ISFUSER, contains errors. Check any authorization code you have added to the user exit. For more information see Chapter 8, “Using installation exit routines,” on page 349.

If the authorization macros and the user exit appear to be coded correctly, follow your local procedures for calling the IBM Support Center. Have the following documentation ready:

- A description of the panel being used and the action being performed when the problem occurred
- A listing of the authorization parameters, and a listing of the user exit routine, if you have written one
- Output from SDSF trace with mask X'C000'.

## **SDSF has abended**

If the abend message and code, along with the explanations in the documentation, don't provide you with enough information to resolve the problem, follow your local procedure for calling IBM. Use the ABEND keyword to describe the problem and have the following documentation ready:

- A description of the panel being used and the operation being performed when the abend occurred.
- A record of any messages and abend codes issued. An error message at the system console includes such information as the name of the failing module and the contents of the registers.
- A dump. SDSF should have requested a dump be sent to a SYS1.DUMP data set.
- If the problem is related to the SYSLOG panel, a dump of the SDSF SYSLOG index and a listing of the SYSLOG messages.
- Output from SDSF trace with mask X'C000'.

## **Documentation is incorrect**

Determine whether the problem directly affects your ability to use SDSF. If the problem does directly affect your ability to use SDSF, follow your local procedures for reporting a problem to IBM. Use the DOC keyword when calling IBM.

If the problem does not directly affect your ability to use SDSF, fill out and mail the Readers' Comment Form that is at the back of this manual, or write to the address shown in the edition notice at the front of this manual.

## **An SDSF message is incorrect**

Follow your local procedure for calling IBM. Have the following documentation ready, using the MSG keyword to describe the problem:

- A description of the panel being used and the operation being performed when the message was received
- A record of the incorrect message

## **Data on an SDSF panel is garbled or incorrect**

Verify your ISFPARMS assembly condition code. Also, ensure that the SDSF panel library is concatenated correctly.

If the panel library is concatenated correctly, follow your local procedure for calling IBM. Have the following documentation of the problem ready:

- A printout of the screen. To print the screen, use the PRINT SCREEN command if you entered SDSF through TSO, or the ISPF PRINT-HI command if you entered SDSF through ISPF.

## **RMF exit is not installed**

If you are trying to use the sysplex DA support and receive the message RMF Exit Is Not Installed, SDSF has not been properly defined to RMF.

SDSF supplies an exit module that must be accessible to the RMF started task. The exit module may reside in the linklist, lpa, or in a steplib defined to the RMF started task. The error message is issued when RMF attempts to load the exit routine but it is not found.

If you are running RMF and want to use the sysplex DA function in SDSF, modules in the SISFLOAD data set must be made accessible to the RMF started task on each system in the sysplex.

If you installed ISF.SISFLOAD in the link list or link pack area, no action is necessary. RMF will be able to load the SDSF modules it needs from the LNKLIST or LPA.

If you are running SDSF in a TSO STEPLIB, you will need to add a steplib to the RMF started task procedure. Add the following statement to your RMF procedure JCL for each system in the sysplex:

```
//STEPLIB DD DSN=ISF.SISFLOAD,DISP=SHR
```



## Appendix B. SDSF resource names for SAF security

The following tables contain a list of all the resource names you need to use SAF security. See [Chapter 5, “Using SAF for security,”](#) on page 213 for more information about using the SAF Security Interface.

Table 181. Security Classes, Resource Names, and What They Protect

Class	Resource Name	Protects
<b>JESSPOOL</b>	<i>nodeid.userid.jobname.jobid</i>	Jobs
<b>JESSPOOL</b>	<i>nodeid.userid.jobname.jobid. GROUP.ogroupid</i>	Output groups
<b>JESSPOOL</b>	<i>nodeid.userid.jobname.jobid. Ddsid.dsname</i>	SYSIN/SYSOUT data sets
<b>JESSPOOL</b>	<i>nodeid.+MASTER+.SYSLOG.SYSTEM. sysname</i>	Access to the JES logical log, for displaying the SYSLOG
<b>JESSPOOL</b>	<i>nodeid.userid.jobname.jobid.EVENTLOG.SMFSTEP nodeid.userid.jobname.jobid.EVENTLOG.STEPDATA</i>	JES data sets used for job steps
<b>JESSPOOL</b>	<i>nodeid.userid.groupname.groupid</i>	Job groups
<b>LOGSTRM</b>	See <a href="#">“OPERLOG”</a> on page 289.	Log stream used for OPERLOG
<b>LOGSTRM</b>	See <a href="#">“Checks on the CK and CKH panels”</a> on page 267.	Log stream for check history (CKH panel)
<b>OPERCMDs</b>	See <a href="#">Chapter 7, “Protecting SDSF functions,”</a> on page 225.	MVS and JES generated commands
<b>OPERCMDs</b>	<i>server-name.MODIFY.DEBUG</i>	DEBUG parameter of MODIFY
<b>OPERCMDs</b>	<i>server-name.MODIFY.DISPLAY</i>	DISPLAY parameter of MODIFY
<b>OPERCMDs</b>	<i>server-name.MODIFY.FOLDMSG</i>	FOLDMSG parameter of MODIFY
<b>OPERCMDs</b>	<i>server-name.MODIFY.LOGCLASS</i>	LOGCLASS parameter of MODIFY
<b>OPERCMDs</b>	<i>server-name.MODIFY.REFRESH</i>	REFRESH parameter of MODIFY
<b>OPERCMDs</b>	<i>server-name.MODIFY.START</i>	START parameter of MODIFY
<b>OPERCMDs</b>	<i>server-name.MODIFY.STOP</i>	STOP parameter of MODIFY
<b>OPERCMDs</b>	<i>server-name.MODIFY.TRACE</i>	TRACE parameter of MODIFY
<b>OPERCMDs</b>	<i>server-name.MODIFY.TRCLASS</i>	TRCLASS parameter of MODIFY

Table 181. Security Classes, Resource Names, and What They Protect (continued)

<b>Class</b>	<b>Resource Name</b>	<b>Protects</b>
<b>SDSF</b>	GROUP.group-name.server-name	Membership in groups defined in ISFPARMS
<b>SDSF</b>	ISF.CONNECTsystem	To connect to the SDSF server, the user must have READ access
<b>SDSF</b>	ISFCMD.DSP.ACTIVE.jesx	DA panel command
<b>SDSF</b>	ISFCMD.DSP.HELD.jesx	H panel command
<b>SDSF</b>	ISFCMD.DSP.JGROUP.jesx	JG panel command
<b>SDSF</b>	ISFCMD.DSP.INPUT.jesx	I panel command
<b>SDSF</b>	ISFCMD.DSP.OUTPUT.jesx	O panel command
<b>SDSF</b>	ISFCMD.DSP.SCHENV.system	SE panel command
<b>SDSF</b>	ISFCMD.DSP.STATUS.jesx	ST panel command
<b>SDSF</b>	ISFCMD.ODSP.APF.system	APF panel command
<b>SDSF</b>	ISFCMD.ODSP.AS.system	AS panel command
<b>SDSF</b>	ISFCMD.ODSP.CDE.system	JC action character
<b>SDSF</b>	ISFCMD.ODSP.CSR.system	CSR panel command
<b>SDSF</b>	ISFCMD.ODSP.DEVACT.system	DEV panel command
<b>SDSF</b>	ISFCMD.ODSP.DYNX.system	DYNX panel command
<b>SDSF</b>	ISFCMD.ODSP.EMCS.system	EMCS panel command
<b>SDSF</b>	ISFCMD.ODSP.ENCLAVE.system	ENC panel command
<b>SDSF</b>	ISFCMD.ODSP.ENQUEUE.system	ENQ panel command
<b>SDSF</b>	ISFCMD.ODSP.HCHECKER.system	CK panel command
<b>SDSF</b>	ISFCMD.ODSP.FILESYS.system	FS panel command
<b>SDSF</b>	ISFCMD.ODSP.TCB.system	JT action character
<b>SDSF</b>	ISFCMD.ODSP.TRACKER.system	GT panel command
<b>SDSF</b>	ISFCMD.ODSP.INITIATOR.jesx	INIT panel command
<b>SDSF</b>	ISFCMD.ODSP.JOBCLASS.jesx	JC panel command
<b>SDSF</b>	ISFCMD.ODSP.DEVICE.system	JD action character
<b>SDSF</b>	ISFCMD.ODSP.DEVICE.system	JDD action character on DA, AS, I, ST, INIT, and NS panels
<b>SDSF</b>	ISFCMD.ODSP.JESCKPT.jesname	JC action character (CKPT panel)
<b>SDSF</b>	ISFCMD.ODSP.JES.system	JES panel command
<b>SDSF</b>	ISFCMD.ODSP.STORAGE.system	JM action character
<b>SDSF</b>	ISFCMD.ODSP.STORAGE.system	JMO action character

Table 181. Security Classes, Resource Names, and What They Protect (continued)

<b>Class</b>	<b>Resource Name</b>	<b>Protects</b>
<b>SDSF</b>	ISFCMD.ODSP.JOB0.jesx	J0 panel command
<b>SDSF</b>	ISFCMD.ODSP.LINE.jesx	LI panel command
<b>SDSF</b>	ISFCMD.ODSP.LNK.system	LNK panel command
<b>SDSF</b>	ISFCMD.ODSP.LPA.system	LPA panel command
<b>SDSF</b>	ISFCMD.ODSP.LPD.system	LPD panel command
<b>SDSF</b>	ISFCMD.ODSP.MAS.jesx	MAS panel command
<b>SDSF</b>	ISFCMD.ODSP.NETACT.system	NA panel command
<b>SDSF</b>	ISFCMD.ODSP.NC.jesx	NC panel command
<b>SDSF</b>	ISFCMD.ODSP.NODE.jesx	NO panel command
<b>SDSF</b>	ISFCMD.ODSP.NS.jesx	NS panel command
<b>SDSF</b>	ISFCMD.ODSP.OMVS.system	OMVS panel command
<b>SDSF</b>	ISFCMD.ODSP.PAGE.system	PAGE panel command
<b>SDSF</b>	ISFCMD.ODSP.PARMLIB.system	PARM panel command
<b>SDSF</b>	ISFCMD.ODSP.PRINTER.jesx	PR panel command
<b>SDSF</b>	ISFCMD.ODSP.PROCESS.system	PS panel command
<b>SDSF</b>	ISFCMD.ODSP.PROCLIB.jesx	PROC panel command
<b>SDSF</b>	ISFCMD.ODSP.PUNCH.jesx	PUN panel command
<b>SDSF</b>	ISFCMD.ODSP.READER.jesx	RDR panel command
<b>SDSF</b>	ISFCMD.ODSP.RESMON.jesx	RM panel command
<b>SDSF</b>	ISFCMD.ODSP.REPC.system	REPC panel command
<b>SDSF</b>	ISFCMD.ODSP.RESOURCE.system	RES panel command
<b>SDSF</b>	ISFCMD.ODSP.RGRP.system	RGRP panel command
<b>SDSF</b>	ISFCMD.ODSP.RESMON.jesx	RMA panel command
<b>SDSF</b>	ISFCMD.ODSP.SO.jesx	SO panel command
<b>SDSF</b>	ISFCMD.ODSP.SPOOL.jesx	SP panel command
<b>SDSF</b>	ISFCMD.ODSP.SR.system	SR panel command
<b>SDSF</b>	ISFCMD.ODSP.SRVC.system	SRVC panel command
<b>SDSF</b>	ISFCMD.ODSP.STORGRP.system	SMSG panel command
<b>SDSF</b>	ISFCMD.ODSP.SMSVOL.system	SMSV panel command
<b>SDSF</b>	ISFCMD.OPT.JESNAME	JESNAME parameter on SDSF command
<b>SDSF</b>	ISFCMD.DSP.SYMBOL.system	SYM panel command
<b>SDSF</b>	ISFCMD.ODSP.SYSTEM.system	SYS panel command
<b>SDSF</b>	ISFCMD.ODSP.VIRTSTOR.system	VMAP panel command
<b>SDSF</b>	ISFCMD.ODSP.COUPLE.system	CFC panel command

Table 181. Security Classes, Resource Names, and What They Protect (continued)

<b>Class</b>	<b>Resource Name</b>	<b>Protects</b>
<b>SDSF</b>	ISFCMD.ODSP.COUPLED.SYSNAME	CFD panel
<b>SDSF</b>	ISFCMD.ODSP.CFSTRUCT.SYSTEM	CFS panel command
<b>SDSF</b>	ISFCMD.ODSP.SYSLOG.JESX	LOG panel command
<b>SDSF</b>	ISFCMD.ODSP.ULOG.JESX	ULOG panel command
<b>SDSF</b>	ISFCMD.ODSP.WKLD.SYSTEM	WKLD panel command
<b>SDSF</b>	ISFCMD.ODSP.WLM.SYSTEM	WLM panel command
<b>SDSF</b>	ISFCMD.ODSP.CFMEMBER.SYSTEM	XCFM panel command
<b>SDSF</b>	ISFCMD.FILTER.ACTION	ACTION command
<b>SDSF</b>	ISFCMD.FILTER.DEST	DEST command
<b>SDSF</b>	ISFCMD.FILTER.FINDLIM	FINDLIM command
<b>SDSF</b>	ISFCMD.FILTER.INPUT	INPUT command
<b>SDSF</b>	ISFCMD.FILTER.OWNER	OWNER command
<b>SDSF</b>	ISFCMD.FILTER.PREFIX	PREFIX command
<b>SDSF</b>	ISFCMD.FILTER.RSYS	RSYS command
<b>SDSF</b>	ISFCMD.FILTER.SYSID	SYSID command
<b>SDSF</b>	ISFCMD.FILTER.SYSNAME	SYSNAME command
<b>SDSF</b>	ISFCMD.MAINT.TRACE	TRACE command
<b>SDSF</b>	ISFDISP.DELAY.OWNER.JOBNAME	JY action character on the DA panel
<b>SDSF</b>	ISFJOB.DDNAME.OWNER.JOBNAME.SYSTEM	JD action character on the AS, DA, I, INIT, NS and ST panels
<b>SDSF</b>	ISFJOB.DDNAME.OWNER.JOBNAME.SYSTEM	JDD action character on the DA, AS, I, ST, INIT, and NS panels
<b>SDSF</b>	ISFJOB.STORAGE.OWNER.JOBNAME.SYSTEM	JM action character on the AD, AS, DA, I, INIT, NS and ST panels
<b>SDSF</b>	ISFJOB.STORAGE.OWNER.JOBNAME.SYSTEM	JMO action character on the DA and AS panels
<b>SDSF</b>	ISFJOB.TASK.OWNER.JOBNAME.SYSTEM	JT action character
<b>SDSF</b>	ISFOPER.SYSTEM	Command line commands
<b>SDSF</b>	ISFOPER.DEST.JESX	Operator authority
<b>SDSF</b>	ISFAPF.DATASETNAME	APF data sets
<b>SDSF</b>	ISFDEV.VOLSER	DEV device activity
<b>SDSF</b>	ISFDYNX.EXITNAME	DYNX data sets
<b>SDSF</b>	ISFENQ.MAJORNAME.SYSNAME	Enqueues



Table 181. Security Classes, Resource Names, and What They Protect (continued)

<b>Class</b>	<b>Resource Name</b>	<b>Protects</b>
<b>SDSF</b>	ISFEMCS.consolename	Extended console
<b>SDSF</b>	ISFJOBCL.class.jesx	Job class members
<b>SDSF</b>	ISFOMVS.optionname	OMVS options
<b>SDSF</b>	ISFRMA.type.jesx	RMA monitor alerts
<b>SDSF</b>	ISFXCFM.membername	XCF Groups and Members
<b>SDSF</b>	ISFJES.subsysname	JES subsystems
<b>SDSF</b>	ISFJRI.resourcenamajesx	JES subsystems
<b>SDSF</b>	ISFJRJ.jobnamejobid	JES subsystems
<b>SDSF</b>	ISFFS.filesystemname	FS file systems
<b>SDSF</b>	ISFGT.eventowner	GT generic tracking events
<b>SDSF</b>	ISFLNK.datasetname	LnkLst data sets
<b>SDSF</b>	ISFNETACT.jobname	NA network activity
<b>SDSF</b>	ISFPARM.datasetname	Parmlib data sets
<b>SDSF</b>	ISFPAG.datasetname	Page data sets
<b>SDSF</b>	ISFPLIB.proc-name	PROC data sets
<b>SDSF</b>	ISFSTORGRP.storagegroupname	SMSG storage groups
<b>SDSF</b>	ISFSMSVOL.filesystemname	SMS storage volumes
<b>SDSF</b>	ISFSUBSYS.subsysname	SSI subsystems
<b>SDSF</b>	ISFSYM.symbolname.sysname	System symbols
<b>SDSF</b>	ISFSYS.sysplexname.systemname	Systems
<b>SDSF</b>	ISFCFC.connectionname	CFC connections
<b>SDSF</b>	ISFCFS.structurename	CFS structures
<b>SDSF</b>	ISFAUTH.DEST.destname	Operator destinations for command objects and destination names for the DEST command
<b>SDSF</b>	ISFAUTH.DEST.destname.DATASET.dsname ISFAUTH.DEST.DATASET.dsname	Operator destination to browse objects
<b>SDSF</b>	ISFOPER.ANYDEST.jesx	All destinations for the DEST command
<b>SDSF</b>	ISFENC.subsys-type.subsys-name	Enclaves
<b>SDSF</b>	ISFINIT.I(xx).jesx	Initiators
<b>SDSF</b>	ISFJDD.CF.sysname	Coupling facility on the JD panel
<b>SDSF</b>	ISFJDD.IP.sysname	TCP/IP server on the JD panel

Table 181. Security Classes, Resource Names, and What They Protect (continued)

Class	Resource Name	Protects
<b>SDSF</b>	ISFJOBCL.class.jesx	Job classes
<b>SDSF</b>	ISFLINE.device-name.jesx	Lines
<b>SDSF</b>	ISFAPPL.device-name.jesx ISFSOCK.device-name.jesx ISFLINEdevice-name.jesx	Network connections
<b>SDSF</b>	ISFNODE.node-name.jesx	Nodes
<b>SDSF</b>	ISFNS.device-name.jesx	Network servers
<b>SDSF</b>	ISFPROC.owner.jobname	z/OS UNIX processes
<b>SDSF</b>	ISFSO.device-name.jesx	Offloaders
<b>SDSF</b>	ISFRDR.device-name.jesx	Readers
<b>SDSF</b>	ISFRES.resource.system	WLM resources
<b>SDSF</b>	ISFRM.resource.jesx	JES resources
<b>SDSF</b>	ISFSE.sched-env.system	Scheduling environments
<b>SDSF</b>	ISFSP.volser.jesx	Spool volumes
<b>SDSF</b>	ISFSR.ACTION.system.jobname	C action character
<b>SDSF</b>	ISFSR.msg-type.system.jobname	System requests, where <i>message-type</i> is ACTION or REPLY
<b>SDSF</b>	ISFSR.REPLY.system.jobname	AI, R action characters
<b>SDSF</b>	SERVER.NOPARM	Fall-back to ISFPARMS in assembler format
<b>WRITER</b>	jesx.LOCAL.devicename	Local printers and punches, including those on other systems
<b>WRITER</b>	jesx.RJE.devicename	RJE devices
<b>XFACILIT</b>	HZS.sysname.checkowner.checkname. action  where <i>action</i> is ACTIVATE, DEACTIVATE, DELETE, QUERY, REFRESH, RUN, UPDATE or MESSAGES	IBM Health Checker for z/OS

Table 182. SDSF Class Resource Names and Overtypable Fields

SDSF Resource Name (UPDATE Authority Required)	Overtypable Field	Panel
<b>ISFATTR.CHECK.CATEGORY</b>	CATEGORY	CK
<b>ISFATTR.CHECK.DEBUG</b>	DEBUG	CK
<b>ISFATTR.CHECK.EINTERVAL</b>	EINTERVAL	CK
<b>ISFATTR.CHECK.INTERVAL</b>	INTERVAL	CK

Table 182. SDSF Class Resource Names and Overtypable Fields (continued)

<b>SDSF Resource Name (UPDATE Authority Required)</b>	<b>Overtypable Field</b>	<b>Panel</b>
<b>ISFATTR.CHECK.PARM</b>	PARAMETERS	CK
<b>ISFATTR.CHECK.REXXHLQ</b>	REXXHLQ	CK
<b>ISFATTR.CHECK.SEVERITY</b>	SEVERITY	CK
<b>ISFATTR.CHECK.USERDATE</b>	USERDATE	CK
<b>ISFATTR.CHECK.VERBOSE</b>	VERBOSE	CK
<b>ISFATTR.CHECK.WTOTYPE</b>	WTOTYPE	CK
<b>ISFATTR.CKPT.OPVERIFY</b> (requires CONTROL access)	OPVERIFY	CKPT
<b>ISFATTR.ENCLAVE.SRVCLASS</b>	SRVCLASS	ENC
<b>ISFATTR.EMCS.AUTH</b>	AUTH	EMCS
<b>ISFATTR.EMCS.INTIDS</b>	INTIDS	EMCS
<b>ISFATTR.EMCS.ROUTCDE</b>	ROUTCDE	EMCS
<b>ISFATTR.EMCS.MSCOPE</b>	MSCOPE	EMCS
<b>ISFATTR.EMCS.UNKNIDS</b>	UNKNIDS	EMCS
<b>ISFATTR.INIT.ALLOC</b>	ALLOC	INIT
<b>ISFATTR.INIT.BARRIER</b>	BARRIER	INIT
<b>ISFATTR.INIT.DEFCNT</b>	DEFCOUNT	INIT
<b>ISFATTR.INIT.GROUP</b>	GROUP	INIT
<b>ISFATTR.INIT.MODE</b>	MODE	INIT
<b>ISFATTR.INIT.UNALLOC</b>	UNALLOC	INIT
<b>ISFATTR.JOB.CLASS</b>	C	I ST
<b>ISFATTR.JOB.EXECNODE</b>	EXECNODE	I ST
<b>ISFATTR.JOB.PGN</b>	PGN	DA
<b>ISFATTR.JOB.PRTDEST</b>	PRTDEST	I ST
<b>ISFATTR.JOB.PRTY</b>	PRTY	I ST
<b>ISFATTR.JOB.QUIESCE</b>	QUIESCE	DA
<b>ISFATTR.JOB.SCHENV</b>	SCHEDULING-ENV	I ST
<b>ISFATTR.JOB.SRVCLASS</b>	SRVCLASS	DA
<b>ISFATTR.JOB.SRVCLS</b>	SRVCLASS	I ST
<b>ISFATTR.JOB.SYSAFF</b>	SAFF	I ST
<b>ISFATTR.JOBCL.ACCT</b>	ACCT	JC
<b>ISFATTR.JOBCL.ACTIVE</b>	ACTIVE	JC
<b>ISFATTR.JOBCL.AUTH</b>	AUTH	JC
<b>ISFATTR.JOBCL.BLP</b>	BLP	JC

Table 182. SDSF Class Resource Names and Overtypable Fields (continued)

<b>SDSF Resource Name (UPDATE Authority Required)</b>	<b>Overtypable Field</b>	<b>Panel</b>
<b>ISFATTR.JOBCL.COMMAND</b>	COMMAND	JC
<b>ISFATTR.JOBCL.CONDPURG</b>	CPR	JC
<b>ISFATTR.JOBCL.COPY</b>	CPY	JC
<b>ISFATTR.JOBCL.GDGBIAS</b>	GDGBIAS	JC
<b>ISFATTR.JOBCL.GROUP</b>	GROUP	JC
<b>ISFATTR.JOBCL.HOLD</b>	HOLD	JC
<b>ISFATTR.JOBCL.IEFUJP</b>	UJP	JC
<b>ISFATTR.JOBCL.IEFUSO</b>	USO	JC
<b>ISFATTR.JOBCL.JCLIM</b>	JCLIM	JC
<b>ISFATTR.JOBCL.JESLOG</b>	JESLOG	JC
<b>ISFATTR.JOBCL.JLOG</b>	LOG	JC
<b>ISFATTR.JOBCL.JOBRC</b>	JOBRC	JC
<b>ISFATTR.JOBCL.JOURNAL</b>	JRNL	JC
<b>ISFATTR.JOBCL.MODE</b>	MODE	JC
<b>ISFATTR.JOBCL.MSGCLASS</b>	MC	JC
<b>ISFATTR.JOBCL.MSGLEVEL</b>	MSGLV	JC
<b>ISFATTR.JOBCL.ODISP</b>	ODISP	JC
<b>ISFATTR.JOBCL.OUTPUT</b>	OUT	JC
<b>ISFATTR.JOBCL.PARTNAME</b>	PARTNAME	JC
<b>ISFATTR.JOBCL.PGMRNAME</b>	PGNM	JC
<b>ISFATTR.JOBCL.PGN</b>	PGN	JC
<b>ISFATTR.JOBCL.PROCLIB</b>	PL	JC
<b>ISFATTR.JOBCL.PROMORATE</b>	PROMORT	JC
<b>ISFATTR.JOBCL.QHLD</b>	QHLD	JC
<b>ISFATTR.JOBCL.REGION</b>	REGION	JC
<b>ISFATTR.JOBCL.RESTART</b>	RST	JC
<b>ISFATTR.JOBCL.SCAN</b>	SCN	JC
<b>ISFATTR.JOBCL.SCHENV</b>	SCHEDULING-ENV	JC
<b>ISFATTR.JOBCL.SDEPTH</b>	SDEPTH	JC
<b>ISFATTR.JOBCL.SWA</b>	SWA	JC
<b>ISFATTR.JOBCL.SYSSYM</b>	SYSSYM	JC
<b>ISFATTR.JOBCL.TDEPTH</b>	TDEPTH	JC
<b>ISFATTR.JOBCL.TIME</b>	MAX-TIME	JC
<b>ISFATTR.JOBCL.TYPE26</b>	TP26	JC

Table 182. SDSF Class Resource Names and Overtypable Fields (continued)

<b>SDSF Resource Name (UPDATE Authority Required)</b>	<b>Overtypable Field</b>	<b>Panel</b>
<b>ISFATTR.JOBCL.TYPE6</b>	TP6	JC
<b>ISFATTR.JOBCL.XBM</b>	XBM	JC
<b>ISFATTR.JOBGROUP.SCHENV</b>	SCHEDULING-ENV	JG
<b>ISFATTR.JOBGROUP.SYSAFF</b>	SAFF	JG
<b>ISFATTR.LINE.TRANSPARENCY</b>	TRANSP	LI
<b>ISFATTR.LINE.APPLID</b>	APPLID	LI
<b>ISFATTR.LINE.AUTODISC</b>	ADISC	LI
<b>ISFATTR.LINE.CODE</b>	CODE	LI
<b>ISFATTR.LINE.COMPRESS</b>	COMP	LI
<b>ISFATTR.LINE.DUPLEX</b>	DUPLEX	LI
<b>ISFATTR.LINE.INTERFACE</b>	INTF	LI
<b>ISFATTR.LINE.JRNUM</b>	JRNUM	LI
<b>ISFATTR.LINE.JTNUM</b>	JTNUM	LI
<b>ISFATTR.LINE.LINECCHR</b>	LINECCHR	LI
<b>ISFATTR.LINE.LOG</b>	LOG	LI
<b>ISFATTR.LINE.NODE</b>	NODE	LI
<b>ISFATTR.LINE.PASSWORD</b>	PASSWORD	LI
<b>ISFATTR.LINE.REST</b>	REST	LI NC
<b>ISFATTR.LINE.SPEED</b>	SPEED	LI
<b>ISFATTR.LINE.SRNUM</b>	SRNUM	LI
<b>ISFATTR.LINE.STNUM</b>	STNUM	LI
<b>ISFATTR.LOGON.PASSWORD</b>	PASSWORD	NS
<b>ISFATTR.MEMBER.CKPTHOLD</b>	CKPTHOLD	MAS
<b>ISFATTR.MEMBER.DORMANCY</b>	DORMANCY	MAS
<b>ISFATTR.MEMBER.SELMNAME</b>	SELECTMODENAME	JP
<b>ISFATTR.MEMBER.SPARTN</b>	PARTNAME	JP
<b>ISFATTR.MEMBER.SYNCTOL</b>	SYNCTOL	MAS
<b>ISFATTR.MODIFY.BURST</b>	MBURST	SO
<b>ISFATTR.MODIFY.CLASS</b>	MCLASS	SO
<b>ISFATTR.MODIFY.DEST</b>	MDEST	SO
<b>ISFATTR.MODIFY.FCB</b>	MFCB	SO
<b>ISFATTR.MODIFY.FLASH</b>	MFLH	SO
<b>ISFATTR.MODIFY.FORMS</b>	MFORMS	SO
<b>ISFATTR.MODIFY.HOLD</b>	MHOLD	SO

Table 182. SDSF Class Resource Names and Overtypable Fields (continued)

<b>SDSF Resource Name (UPDATE Authority Required)</b>	<b>Overtypable Field</b>	<b>Panel</b>
<b>ISFATTR.MODIFY.ODISP</b>	MODSP	SO
<b>ISFATTR.MODIFY.PRMODE</b>	MPRMODE	SO
<b>ISFATTR.MODIFY.SYSAFF</b>	MSAFF	SO
<b>ISFATTR.MODIFY.UCS</b>	MUCS	SO
<b>ISFATTR.MODIFY.WRITER</b>	MWRITER	SO
<b>ISFATTR.NETOPTS.APPL</b>	APPL	NS
<b>ISFATTR.NETOPTS.CONNECT</b>	CONNECT	LI NC NO
<b>ISFATTR.NETOPTS.CTIME</b>	CONN-INT	LI NC NO
<b>ISFATTR.NETOPTS.IPNAME</b>	IPNAME	NC NS
<b>ISFATTR.NETOPTS.LINE</b>	LINE	NC
<b>ISFATTR.NETOPTS.LOG</b>	LOG	NS
<b>ISFATTR.NETOPTS.LOGON</b>	LOGON	NC
<b>ISFATTR.NETOPTS.NETSRV</b>	NETSRV	NC
<b>ISFATTR.NETOPTS.NETSRV</b>	SRVNAME	NC
<b>ISFATTR.NETOPTS.NSECURE</b>	NSECURE	NS
<b>ISFATTR.NETOPTS.NODE</b>	ANODE	NC
<b>ISFATTR.NETOPTS.PORT</b>	PORT	NC NS
<b>ISFATTR.NETOPTS.SECURE</b>	SECURE	NC NO NS
<b>ISFATTR.NETOPTS.SOCKET</b>	SOCKET	NS
<b>ISFATTR.NETOPTS.STACK</b>	STACK	NS
<b>ISFATTR.NODE.AUTHORITY</b>	AUTHORITY	NO
<b>ISFATTR.NODE.COMPACT</b>	COMPACT	NC
<b>ISFATTR.NODE.COMPACT</b>	CP	NO
<b>ISFATTR.NODE.DIRECT</b>	DIRECT	NO
<b>ISFATTR.NODE.ENDNODE</b>	END	NO
<b>ISFATTR.NODE.HOLD</b>	HOLD	NO
<b>ISFATTR.NODE.JRNUM</b>	JRNUM	NO
<b>ISFATTR.NODE.JTNUM</b>	JTNUM	NO
<b>ISFATTR.NODE.LINE</b>	LINE	NC NO
<b>ISFATTR.NODE.LOGMODE</b>	LOGMODE	NC NO
<b>ISFATTR.NODE.LOGON</b>	LOGON	NO
<b>ISFATTR.NODE.MAXRETR</b>	MAXRETRIES	NO
<b>ISFATTR.NODE.NETHOLD</b>	NHOLD	NO
<b>ISFATTR.NODE.NETSRV</b>	NETSRV	NO

Table 182. SDSF Class Resource Names and Overtypable Fields (continued)

<b>SDSF Resource Name (UPDATE Authority Required)</b>	<b>Overtypable Field</b>	<b>Panel</b>
<b>ISFATTR.NODE.NODENAME</b>	NODENAME	NO
<b>ISFATTR.NODE.PARTNAM</b>	PARTNAME	NO
<b>ISFATTR.NODE.PATH</b>	PATH	NO
<b>ISFATTR.NODE.PATHMGR</b>	PMG	NO
<b>ISFATTR.NODE.PENCRYPT</b>	PEN	NO
<b>ISFATTR.NODE.PRIVATE</b>	PRV	NO
<b>ISFATTR.NODE.PRTDEF</b>	PRTDEF	NO
<b>ISFATTR.NODE.PRTTSO</b>	PRTTSO	NO
<b>ISFATTR.NODE.PRTXWTR</b>	PRTXWTR	NO
<b>ISFATTR.NODE.PTYPE</b>	PTYPE	NO
<b>ISFATTR.NODE.PUNDEF</b>	PUNDEF	NO
<b>ISFATTR.NODE.PWCNTL</b>	PWCNTL	NO
<b>ISFATTR.NODE.RECEIVE</b>	RECV	NO
<b>ISFATTR.NODE.REST</b>	REST	NO
<b>ISFATTR.NODE.SENDP</b>	SENDP	NO
<b>ISFATTR.NODE.SENTREST</b>	SENTRS	NO
<b>ISFATTR.NODE.SRNUM</b>	SRNUM	NO
<b>ISFATTR.NODE.SSIGNON</b>	SSIGNON	NO
<b>ISFATTR.NODE.STNUM</b>	STNUM	NO
<b>ISFATTR.NODE.SUBNET</b>	SUBNET	NO
<b>ISFATTR.NODE.TRACE</b>	TR	NO
<b>ISFATTR.NODE.TRANSMIT</b>	TRANS	NO
<b>ISFATTR.NODE.VERIFYP</b>	VERIFYP	NO
<b>ISFATTR.NODE.VFYPATH</b>	VFYPATH	NO
<b>ISFATTR.OFFLOAD.ARCHIVE</b>	ARCHIVE	SO
<b>ISFATTR.OFFLOAD.CRTIME</b>	CRTIME	SO
<b>ISFATTR.OFFLOAD.DATASET</b>	DSNAME	SO
<b>ISFATTR.OFFLOAD.LABEL</b>	LABEL	SO
<b>ISFATTR.OFFLOAD.NOTIFY</b>	NOTIFY	SO
<b>ISFATTR.OFFLOAD.PROTECT</b>	PROT	SO
<b>ISFATTR.OFFLOAD.RETENT</b>	RTPD	SO
<b>ISFATTR.OFFLOAD.VALIDATE</b>	VALIDATE	SO
<b>ISFATTR.OFFLOAD.VOLS</b>	VOLS	SO
<b>ISFATTR.OMVS.VALUE</b>	NUMVALUE	OMVS

Table 182. SDSF Class Resource Names and Overtypable Fields (continued)

<b>SDSF Resource Name (UPDATE Authority Required)</b>	<b>Overtypable Field</b>	<b>Panel</b>
<b>ISFATTR.OUTDESC.ADDRESS</b>	ADDRESS	JDS
<b>ISFATTR.OUTDESC.AFPPARMS</b>	AFPPARMS	JDS
<b>ISFATTR.OUTDESC.AFPSTATS</b>	AFPSTATS	JDS
<b>ISFATTR.OUTDESC.BLDG</b>	BUILDING	JDS
<b>ISFATTR.OUTDESC.COLORMAP</b>	COLORMAP	JDS
<b>ISFATTR.OUTDESC.COMSETUP</b>	COMSETUP	JDS
<b>ISFATTR.OUTDESC.DEPT</b>	DEPARTMENT	JDS
<b>ISFATTR.OUTDESC.FORMDEF</b>	FORMDEF	JDS
<b>ISFATTR.OUTDESC.FORMLEN</b>	FORMLEN	JDS
<b>ISFATTR.OUTDESC.IPDEST</b>	IPDEST	JDS
<b>ISFATTR.OUTDESC.MAILBCC</b>	MAILBCC	JDS
<b>ISFATTR.OUTDESC.MAILCC</b>	MAILCC	JDS
<b>ISFATTR.OUTDESC.MAILFILE</b>	MAILFILE	JDS
<b>ISFATTR.OUTDESC.MAILFROM</b>	MAILFROM	JDS
<b>ISFATTR.OUTDESC.MAILTO</b>	MAILTO	JDS
<b>ISFATTR.OUTDESC.NOTIFY</b>	NOTIFY	JDS
<b>ISFATTR.OUTDESC.OCOPYCNT</b>	OCOPYCNT	JDS
<b>ISFATTR.OUTDESC.OFFSETXB</b>	OFFSETXB	JDS
<b>ISFATTR.OUTDESC.OFFSETXF</b>	OFFSETXF	JDS
<b>ISFATTR.OUTDESC.OFFSETYB</b>	OFFSETYB	JDS
<b>ISFATTR.OUTDESC.OFFSETYF</b>	OFFSETYF	JDS
<b>ISFATTR.OUTDESC.OUTBIN</b>	OUTBN	JDS
<b>ISFATTR.OUTDESC.OVERLAYB</b>	OVERLAYB	JDS
<b>ISFATTR.OUTDESC.OVERLAYF</b>	OVERLAYF	JDS
<b>ISFATTR.OUTDESC.PAGEDEF</b>	PAGEDEF	JDS
<b>ISFATTR.OUTDESC.PORTNO</b>	PORT	JDS
<b>ISFATTR.OUTDESC.PRINTO</b>	PRTOPTNS	JDS
<b>ISFATTR.OUTDESC.PRINTQ</b>	PRTQUEUE	JDS
<b>ISFATTR.OUTDESC.RETAINF</b>	RETAINF	JDS
<b>ISFATTR.OUTDESC.RETAINS</b>	RETAINS	JDS
<b>ISFATTR.OUTDESC.RETRYL</b>	RETRYL	JDS
<b>ISFATTR.OUTDESC.RETRYT</b>	RETRYT	JDS
<b>ISFATTR.OUTDESC.ROOM</b>	ODROOM	JDS
<b>ISFATTR.OUTDESC.TITLE</b>	ODTITLE	JDS



Table 182. SDSF Class Resource Names and Overtypable Fields (continued)

<b>SDSF Resource Name (UPDATE Authority Required)</b>	<b>Overtypable Field</b>	<b>Panel</b>
<b>ISFATTR.OUTDESC.USERDATA</b>	USERDATA1	JDS
<b>ISFATTR.OUTDESC.USERLIB</b>	USERLIB	JDS
<b>ISFATTR.OUTPUT.BURST</b>	BURST	JDS J0
<b>ISFATTR.OUTPUT.BURST</b>	BURST	H O
<b>ISFATTR.OUTPUT.CHARS</b>	CHARS	JDS J0
<b>ISFATTR.OUTPUT.CLASS</b>	C	H O JDS J0
<b>ISFATTR.OUTPUT.COPYCNT</b>	CC	JDS J0
<b>ISFATTR.OUTPUT.COPYMOD</b>	CPYMOD	JDS
<b>ISFATTR.OUTPUT.DEST</b>	DEST (secondary JES2)	H
<b>ISFATTR.OUTPUT.DEST</b>	DEST	H O JDS J0
<b>ISFATTR.OUTPUT.FCB</b>	FCB	JDS J0
<b>ISFATTR.OUTPUT.FCB</b>	FCB	H O
<b>ISFATTR.OUTPUT.FLASH</b>	FLASH	JDS J0
<b>ISFATTR.OUTPUT.FLASH</b>	FLASH	H O
<b>ISFATTR.OUTPUT.FORMS</b>	FORMS	H O JDS J0
<b>ISFATTR.OUTPUT.ODISP</b>	ODISP	H JDS O
<b>ISFATTR.OUTPUT.PRMODE</b>	PRMODE	H O JDS J0
<b>ISFATTR.OUTPUT.PRTY</b>	PRTY	H O
<b>ISFATTR.OUTPUT.UCS</b>	UCS	H O JDS J0
<b>ISFATTR.OUTPUT.WRITER</b>	WTR	H O JDS J0
<b>ISFATTR.PROPTS.ASIS</b>	ASIS	PR
<b>ISFATTR.PROPTS.BPAGE</b>	B	PR PUN
<b>ISFATTR.PROPTS.CB</b>	CB	PR
<b>ISFATTR.PROPTS.CCTL</b>	CCTL	PR PUN
<b>ISFATTR.PROPTS.CHAR</b>	CHAR1-4	PR
<b>ISFATTR.PROPTS.CKPTLINE</b>	CKPTLINE	PR PUN
<b>ISFATTR.PROPTS.CKPTMODE</b>	CKPTMODE	PR
<b>ISFATTR.PROPTS.CKPTPAGE</b>	CKPTPAGE	PR PUN
<b>ISFATTR.PROPTS.CKPTSEC</b>	CKPTSEC	PR
<b>ISFATTR.PROPTS.CMPCT</b>	CMPCT	PR PUN
<b>ISFATTR.PROPTS.COMPACT</b>	COMPACT	PR PUN
<b>ISFATTR.PROPTS.COMPRESS</b>	COMP	PR PUN
<b>ISFATTR.PROPTS.COPIES</b>	COPIES	PR PUN
<b>ISFATTR.PROPTS.COPYMARK</b>	COPYMARK	PR

Table 182. SDSF Class Resource Names and Overtypable Fields (continued)

<b>SDSF Resource Name (UPDATE Authority Required)</b>	<b>Overtypable Field</b>	<b>Panel</b>
<b>ISFATTR.PROPTS.COPYMOD</b>	CPYMOD	JO PR
<b>ISFATTR.PROPTS.CTRACE</b>	CTR	LI NC NS
<b>ISFATTR.PROPTS.DEVFCB</b>	DFCB	PR
<b>ISFATTR.PROPTS.DGRPY</b>	DGRPY	PR PUN
<b>ISFATTR.PROPTS.DYN</b>	DYN	PR PUN
<b>ISFATTR.PROPTS.FLUSH</b>	FLS	PUN
<b>ISFATTR.PROPTS.FSATRACE</b>	FSATRACE	PR
<b>ISFATTR.PROPTS.FSSNAME</b>	FSSNAME	PR
<b>ISFATTR.PROPTS.HONORTRC</b>	HONORTRC	PR
<b>ISFATTR.PROPTS.JTRACE</b>	JTR	LI NC NS
<b>ISFATTR.PROPTS.LRECL</b>	LRECL	PUN
<b>ISFATTR.PROPTS.MARK</b>	M	PR
<b>ISFATTR.PROPTS.NEWPAGE</b>	NEWPAGE	PR
<b>ISFATTR.PROPTS.NPRO</b>	NPRO	PR
<b>ISFATTR.PROPTS.OPACTLOG</b>	OPLOG	PR PUN
<b>ISFATTR.PROPTS.PAUSE</b>	PAU	PR PUN
<b>ISFATTR.PROPTS.PDEFAULT</b>	PDEFAULT	PR
<b>ISFATTR.PROPTS.PRESELCT</b>	PSEL	PR
<b>ISFATTR.PROPTS.RESTART</b>	RESTART	LI
<b>ISFATTR.PROPTS.RTIME</b>	REST-INT	LI NS
<b>ISFATTR.PROPTS.SELECT</b>	SELECT	PR PUN
<b>ISFATTR.PROPTS.SEP</b>	SEP	PR PUN
<b>ISFATTR.PROPTS.SEPCHARS</b>	SEPCHAR	PR
<b>ISFATTR.PROPTS.SEPDS</b>	SEPDS	PR PUN RDR
<b>ISFATTR.PROPTS.SETUP</b>	SETUP	PR PUN
<b>ISFATTR.PROPTS.SPACE</b>	K	PR
<b>ISFATTR.PROPTS.SUSPEND</b>	SUS	PUN
<b>ISFATTR.PROPTS.TRACE</b>	TR	LI NC NS PR PUN
<b>ISFATTR.PROPTS.TRANS</b>	TRANS	PR
<b>ISFATTR.PROPTS.TRKCELL</b>	TRKCELL	PR
<b>ISFATTR.PROPTS.UCSVERIFY</b>	UCSV	PR
<b>ISFATTR.PROPTS.UNIT</b>	UNIT	LI PR PUN SO
<b>ISFATTR.PROPTS.VTRACE</b>	VTR	LI NC NS
<b>ISFATTR.PROPTS.WS</b>	WORK- SELECTION	LI PR PUN SO

Table 182. SDSF Class Resource Names and Overtypable Fields (continued)

<b>SDSF Resource Name (UPDATE Authority Required)</b>	<b>Overtypable Field</b>	<b>Panel</b>
<b>ISFATTR.PROPTS.MODE</b>	MODE	PR
<b>ISFATTR.RDR.AUTHORITY</b>	AUTHORITY	RDR
<b>ISFATTR.RDR.CLASS</b>	C	RDR
<b>ISFATTR.RDR.HOLD</b>	HOLD	RDR
<b>ISFATTR.RDR.MCLASS</b>	MC	RDR
<b>ISFATTR.RDR.PRIOINC</b>	PI	RDR
<b>ISFATTR.RDR.PRIOLIM</b>	PL	RDR
<b>ISFATTR.RDR.PRTDEST</b>	PRTDEST	RDR
<b>ISFATTR.RDR.PUNDEST</b>	PUNDEST	RDR
<b>ISFATTR.RDR.SYSAFF</b>	SAFF1	RDR
<b>ISFATTR.RDR.TRACE</b>	TR	RDR
<b>ISFATTR.RDR.UNIT</b>	UNIT	RDR
<b>ISFATTR.RDR.XEQDEST</b>	XEQDEST	RDR
<b>ISFATTR.RESMON.LIMIT</b>	LIMIT	RM
<b>ISFATTR.RESMON.WARNPCT</b>	WARN%	RM
<b>ISFATTR.RESOURCE.system</b>	System	RES
<b>ISFATTR.SELECT.BURST</b>	SBURST	PR SO
<b>ISFATTR.SELECT.CLASS</b>	SCLASS	PR PUN
<b>ISFATTR.SELECT.CLASS</b>	SCLASS, SCLASS1-8	SO
<b>ISFATTR.SELECT.DEST</b>	SDEST1	PR PUN SO
<b>ISFATTR.SELECT.DISP</b>	SDISP	SO
<b>ISFATTR.SELECT.FCB</b>	SFCB	PR SO
<b>ISFATTR.SELECT.FLASH</b>	SFLH	PR SO
<b>ISFATTR.SELECT.FORMS</b>	SFORMS	PR PUN SO
<b>ISFATTR.SELECT.HOLD</b>	SHOLD	SO
<b>ISFATTR.SELECT.JOBCLASS</b>	CLASSES, CLASS1-8	INIT
<b>ISFATTR.SELECT.JOBNAME</b>	SJOBNAME	PR PUN SO
<b>ISFATTR.SELECT.LIM</b>	LINE-LIM-LO	PR PUN
<b>ISFATTR.SELECT.LIM</b>	LINE-LIM-HI	PR PUN
<b>ISFATTR.SELECT.LIM</b>	LINE-LIMIT	LI NC PR PUN SO
<b>ISFATTR.SELECT.ODISP</b>	SODSP	NC SO
<b>ISFATTR.SELECT.OUTDISP</b>	SODSP	LI
<b>ISFATTR.SELECT.OWNER</b>	SOWNER	PR PUN SO
<b>ISFATTR.SELECT.PLIM</b>	PAGE-LIM-LOW	PR

Table 182. SDSF Class Resource Names and Overtypable Fields (continued)

<b>SDSF Resource Name (UPDATE Authority Required)</b>	<b>Overtypable Field</b>	<b>Panel</b>
<b>ISFATTR.SELECT.PLIM</b>	PAGE-LIM-HI	PR
<b>ISFATTR.SELECT.PLIM</b>	PAGE-LIMIT	LI NC PR SO
<b>ISFATTR.SELECT.PRMODE</b>	SPRMODE1	PR PUN RDR
<b>ISFATTR.SELECT.PRMODE</b>	SPRMODE1	SO
<b>ISFATTR.SELECT.RANGE</b>	SRANGE	PUN SO
<b>ISFATTR.SELECT.RANGE</b>	SRANGE	PR
<b>ISFATTR.SELECT.SCHENV</b>	SSCHEDULING-ENV	SO
<b>ISFATTR.SELECT.SRVCLS</b>	SSRVCLASS	SO
<b>ISFATTR.SELECT.SYSAFF</b>	SSAFF	SO
<b>ISFATTR.SELECT.UCS</b>	SUCS	PR SO
<b>ISFATTR.SELECT.VOL</b>	SVOL1	PR
<b>ISFATTR.SELECT.VOL</b>	SVOL	PUN SO
<b>ISFATTR.SELECT.WRITER</b>	SWRITER	PR PUN SO
<b>ISFATTR.SPOOL.MINPCT</b>	MINPCT	SP
<b>ISFATTR.SPOOL.OVFNAME</b>	OVERFNAM	SP
<b>ISFATTR.SPOOL.PARTNAME</b>	PARTNAME	SP
<b>ISFATTR.SPOOL.RESERVED</b>	RES	SP
<b>ISFATTR.SPOOL.SYSAFF</b>	SAFF	SP

---

## Appendix C. Accessibility

Accessible publications for this product are offered through [IBM Documentation \(www.ibm.com/docs/en/zos\)](http://www.ibm.com/docs/en/zos).

If you experience difficulty with the accessibility of any z/OS information, send a detailed message to the [Contact the z/OS team web page \(www.ibm.com/systems/campaignmail/z/zos/contact\\_z\)](http://www.ibm.com/systems/campaignmail/z/zos/contact_z) or use the following mailing address.

IBM Corporation  
Attention: MHVRCFS Reader Comments  
Department H6MA, Building 707  
2455 South Road  
Poughkeepsie, NY 12601-5400  
United States



## Notices

---

This information was developed for products and services that are offered in the USA or elsewhere.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing  
IBM Corporation  
North Castle Drive, MD-NC119  
Armonk, NY 10504-1785  
United States of America*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing  
Legal and Intellectual Property Law  
IBM Japan Ltd.  
19-21, Nihonbashi-Hakozakicho, Chuo-ku  
Tokyo 103-8510, Japan*

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:** INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

This information could include missing, incorrect, or broken hyperlinks. Hyperlinks are maintained in only the HTML plug-in output for IBM Documentation. Use of hyperlinks in other output formats of this information is at your own risk.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Corporation  
Site Counsel  
2455 South Road*

Poughkeepsie, NY 12601-5400  
USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

## Terms and conditions for product documentation

---

Permissions for the use of these publications are granted subject to the following terms and conditions.

### **Applicability**

These terms and conditions are in addition to any terms of use for the IBM website.

### **Personal use**

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

### **Commercial use**

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or



reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

## Rights

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

## IBM Online Privacy Statement

---

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies that collect each user's name, email address, phone number, or other personally identifiable information for purposes of enhanced user usability and single sign-on configuration. These cookies can be disabled, but disabling them will also eliminate the functionality they enable.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at [ibm.com/privacy](http://ibm.com/privacy) and IBM's Online Privacy Statement at [ibm.com/privacy/details](http://ibm.com/privacy/details) in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at [ibm.com/software/info/product-privacy](http://ibm.com/software/info/product-privacy).

## Policy for unsupported hardware

---

Various z/OS elements, such as DFSMSdfp, JES2, JES3, and MVS™, contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

## Minimum supported hardware

---

The minimum supported hardware for z/OS releases identified in z/OS announcements can subsequently change when service for particular servers or devices is withdrawn. Likewise, the levels of other software products supported on a particular release of z/OS are subject to the service support lifecycle of those

products. Therefore, z/OS and its product publications (for example, panels, samples, messages, and product documentation) can include references to hardware and software that is no longer supported.

- For information about software support lifecycle, see: [IBM Lifecycle Support for z/OS \(www.ibm.com/software/support/systemsz/lifecycle\)](http://www.ibm.com/software/support/systemsz/lifecycle)
- For information about currently-supported IBM hardware, contact your IBM representative.

## Programming interface information

---

This book is intended to help the customer customize SDSF and set up SDSF security.

This publication primarily documents information that is NOT intended to be used as Programming Interfaces of SDSF.

This publication also documents intended Programming Interfaces that allow the customer to write programs to obtain the services of SDSF. This information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

Programming Interface Information
End Programming Interface Information

---

# Index

## Special Characters

- ? query character
  - defining with DCHAR parameter [14](#)
- \* character, with SCHARS parameter [15](#)
- / command
  - authority to enter MVS and JES commands [285](#)
- &; (automatic reissue of commands)
  - interval, specifying minimum [25](#)
  - restricting use of [18](#)
- % character, with SCHARS parameter [15](#)

## A

- AALLOC default field title
  - CS panel [102](#)
- abbreviations in column data [49](#)
- abend
  - codes [493](#)
  - managing [500](#)
- ABENDCON default field title
  - Dynamic Exits panel [109](#)
- ABENDNUM default field title
  - Dynamic Exits panel [109](#)
- ABENDRSN default field title
  - Job Step panel [147](#)
- ABLKs default field title
  - CS panel [102](#)
- access authority, SAF [215](#)
- access requirements, users [225](#)
- accessibility
  - contact IBM [519](#)
- ACCT default field title
  - Held Output Queue panel [120](#)
  - Input Queue panel [124](#)
  - JC panel [132](#)
  - Output Queue panel [166](#)
  - Status panel [195](#)
- ACTDORM default field title
  - Multi-Access Spool panel [156](#)
- ACTFILES default field title
  - Process panel [178](#)
- ACTHOLD default field title
  - Multi-Access Spool panel [156](#)
- action characters
  - confirmation of [27](#)
  - specifying authorization to use [27](#), [225](#)
- ACTION command
  - authorization to issue [261](#)
- ACTION default field title
  - Job Dependencies panel [139](#)
- Action Help panel [93](#)
- action messages
  - protecting with SAF [345](#)
- ACTION parameter [18](#)
- ACTIONBAR parameter in ISFPARMS [24](#)
- ACTIVE default field title
  - Dynamic Exits panel [109](#)
- ACTIVE, default field title
  - Job Class panel [133](#)
- ADATE default field title
  - CSI panel [103](#)
  - JCS panel [134](#)
- ADDRESS default field title
  - CSI panel [103](#)
  - JCS panel [133](#)
  - MEM panel [157](#)
  - USI panel [176](#)
- Address Space Diagnostic panel
  - ADFLDS parameter [24](#)
  - variable field list of
    - primary, defining [24](#)
- Address Space Diagnostics panel [94](#)
- Address Space Memory panel
  - ASFLD2 parameter [25](#)
  - ASFLDS parameter [25](#)
  - variable field list of
    - alternate, defining [25](#)
    - primary, defining [25](#)
- ADDRESS-LINE1 default field title
  - Job Data Set panel [136](#)
- ADDRESS-LINE2 default field title
  - Job Data Set panel [136](#)
- ADDRESS-LINE3 default field title
  - Job Data Set panel [136](#)
- ADDRESS-LINE4 default field title
  - Job Data Set panel [136](#)
- ADDRESSEND default field title
  - CSI panel [103](#)
  - USI panel [176](#)
- ADFLDS parameter in ISFPARMS [24](#)
- ADISC default field title
  - Lines panel [151](#)
- ADMSYMBL [13](#)
- AFPPARMS Default field title
  - Job Data Set panel [136](#)
- AFPSTATS default field title
  - Job Data Set panel [138](#)
- AFREE default field title
  - CS panel [102](#)
- AFTERJID default field title
  - Input Queue panel [126](#)
  - Status panel [197](#)
- AFTERJOB default field title
  - Input Queue panel [126](#)
  - Status panel [197](#)
- AKM default field title
  - PC panel [170](#)
- ALL value
  - for ACTION parameter [24](#)
  - for CMDAUTH parameter [27](#)
- Alloc default field title

Alloc default field title (*continued*)  
 Initiator panel [122](#)  
 ALLOC default field title  
 VMAP panel [205](#)  
 allocating  
 SDSF data sets [14](#)  
 AllocCount default field title  
 Initiator panel [122](#)  
 ALLOCHWM default field title  
 VMAP panel [205](#)  
 ALLOCHWMPC default field title  
 VMAP panel [205](#)  
 ALLOCPCT default field title  
 VMAP panel [205](#)  
 ALLOCTIME default field title  
 CFD panel [99](#)  
 ALLOWAA default field title  
 CFS panel [100](#)  
 ALLOWRA default field title  
 CFS panel [100](#)  
 alternate field list for SDSF panels  
 defining [47](#)  
 AMODE default field title  
 Job Module panel [146](#)  
 Link Pack Directory panel [155](#)  
 PC panel [170](#)  
 SVC panel [199](#)  
 ANode default field title  
 NC panel [159](#)  
 ANODE default field title  
 LI panel [152](#)  
 AORPHAN default field title  
 CS panel [102](#)  
 APF default field title  
 Job DDName panel [142](#)  
 Job Module panel [146](#)  
 Link Pack Area panel [154](#)  
 Link Pack Directory panel [155](#)  
 SVC panel [199](#)  
 APF indicator default field title  
 Link List panel [153](#)  
 APPC parameter in ISFPARMS [25](#)  
 Appl default field title  
 NS panel [161](#)  
 APPL default field title  
 Job Device panel [141](#)  
 NA panel [158](#)  
 APPLDATA default field title  
 Job Device panel [141](#)  
 NA panel [158](#)  
 APPLID default field title  
 Lines panel [151](#)  
 AR default field title  
 SVC panel [199](#)  
 ARCHIVE default field title  
 Spool Offload panel [188](#)  
 AReq default field title  
 Reader panel [182](#)  
 ARM registration of server [75](#)  
 ARRINTV default field title  
 Enclaves panel [111](#)  
 ARRTIME default field title  
 Enclaves panel [111](#)  
 ASC default field title

ASC default field title (*continued*)  
 PC panel [170](#)  
 ASCB default field title  
 AD panel [94](#)  
 ASCII default field title  
 MEM panel [157](#)  
 ASF default field title  
 SVC panel [199](#)  
 ASID default field title  
 AD panel [94](#)  
 Address Space Memory panel [96](#)  
 CFC panel [98](#)  
 CSI panel [103](#)  
 CSR panel [104](#)  
 Display Active Users Panel [106](#)  
 Enqueue panel [112](#)  
 Extended Console panel [113](#)  
 Initiator panel [122](#)  
 Input Queue panel [125](#)  
 JCS panel [134](#)  
 Job Memory Objects panel [145](#)  
 Job Module panel [146](#)  
 JT panel [148](#)  
 MEM panel [157](#)  
 NA panel [158](#)  
 NS panel [161](#)  
 PC panel [170](#)  
 Process panel [178](#)  
 Status panel [196](#)  
 USI panel [176](#)  
 ASIDSS default field title  
 WLM service classes panel [209](#)  
 ASIDX default field title  
 AD panel [94](#)  
 Address Space Memory panel [95](#)  
 CFC panel [98](#)  
 CSI panel [103](#)  
 CSR panel [104](#)  
 Display Active Users Panel [106](#)  
 Enqueue panel [112](#)  
 Extended Console panel [113](#)  
 Initiator panel [122](#)  
 Input Queue panel [125](#)  
 JCS panel [134](#)  
 Job Memory Objects panel [145](#)  
 Job Module panel [146](#)  
 JT panel [148](#)  
 MEM panel [157](#)  
 NA panel [158](#)  
 Process panel [178](#)  
 Status panel [196](#)  
 USI panel [176](#)  
 ASIS default field title  
 Printer panel [175](#)  
 ASSB default field title  
 AD panel [94](#)  
 assistive technologies [519](#)  
 ASXB default field title  
 AD panel [94](#)  
 ASYS default field title  
 Input Queue panel [123](#)  
 Status panel [194](#)  
 AttStat default field title  
 MAS and JESPLEX panels [157](#)

- auditing
  - commands with MSG [27](#)
  - SAF requests [213](#)
- AUPDT parameter [18](#)
- AUSED default field title
  - CS panel [102](#)
- AUTH default field title
  - ACTH panel [93](#)
  - Extended Console panel [113](#)
  - GT panel [116](#)
  - JC panel [131](#)
- AUTHCOD default field title
  - Job Module panel [146](#)
  - Link Pack Directory panel [155](#)
- AUTHORITY default field title
  - NODE panel [162](#)
  - Reader panel [182](#)
- authorization
  - using SAF to change [213](#)
- authorization group
  - users placed in wrong [499](#)
  - with error messages [367](#)
- authorization parameters
  - quick reference to [18](#)
  - using to define
    - automatic update interval [18](#)
    - default address space types and positions
    - displayed on Display Active Users panel [29](#)
    - destination names used with DEST command [33](#)
    - groups of users [17](#)
    - jobs displayed on SDSF panels [33](#), [39](#), [40](#)
    - jobs for which commands can be issued [27](#)
    - SYSLOG displayed in multi-access spool environment [45](#)
    - WTOR messages displayed on SYSLOG [24](#)
- Authorized Program Facility panel
  - APFFLD2 parameter [25](#)
  - APFFLDS parameter [24](#)
  - variable field list of
    - alternate, defining [25](#)
    - primary, defining [24](#)
- authorizing users
  - problems with [499](#)
  - with an installation exit routine [349](#)
- AUTOACT default field title
  - Extended Console panel [113](#), [114](#)
- AUTODELAY default field title
  - SR panel [204](#)
- Automatic Restart Manager (ARM) registration of server [75](#)
- automatic update
  - interval, specifying minimum [18](#)
  - restricting use of [18](#)
- AUTOMOVE default field title
  - FS panel [114](#)
- AUTOREPLY default field title
  - SR panel [204](#)
- AUTOTEXT default field title
  - SR panel [204](#)
- AUTOTIME default field title
  - SR panel [204](#)
- Aux
  - starting [78](#)
  - stopping [90](#)
- Aux default field title

- Aux default field title (*continued*)
  - Address Space Memory panel [95](#)
- AUX default field title
  - CMDH panel [101](#)
- AUXPCT default field title
  - Address Space Memory panel [96](#)
  - CSR panel [104](#)
  - SYS panel [201](#)
- AUXSCM default field title
  - Address Space Memory panel [96](#)
- AVGCONN default field title
  - Job DDName panel [142](#)
  - Job Device panel [141](#)
- AVGMSU default field title
  - SYS panel [202](#)

## B

- B abbreviation in column data [49](#)
- B default field title
  - Printer panel [174](#)
- BADASID default field title
  - SYS panel [201](#)
- BALLOC default field title
  - CS panel [102](#)
- Barrier default field title
  - Initiator panel [122](#)
- batch job
  - displaying on Display Active Users panel [29](#)
- BBLKS default field title
  - CS panel [102](#)
- BDTNAME default field title
  - NODE panel [163](#)
- BEFOREJID default field title
  - Input Queue panel [126](#)
  - Status panel [197](#)
- BEFOREJOB default field title
  - Input Queue panel [126](#)
  - Status panel [197](#)
- BEGINTME default field title
  - Job Step panel [147](#)
- BERTNUM default field title
  - Held Output Queue panel [121](#)
  - Input Queue panel [126](#)
  - Output Queue panel [168](#)
  - Status panel [197](#)
- BFREE default field title
  - CS panel [102](#)
- BLKSIZE default field title
  - Authorized Program Facility panel [97](#)
  - CSI panel [103](#)
  - Job DDName panel [142](#)
  - Job Device panel [140](#)
  - Link List panel [153](#)
  - Link Pack Area panel [154](#)
  - PARMLIB panel [169](#)
  - PROC panel [177](#)
  - SRCH panel [191](#)
  - USI panel [176](#)
- BLOCKADDR default field title
  - CSI panel [103](#)
  - USI panel [176](#)
- BLP default field title
  - JC panel [131](#)

- BLP default field title (*continued*)
  - Reader panel [182](#)
- BOOST default field title
  - SYS panel [203](#)
- BOOSTCLASS default field title
  - SYS panel [203](#)
- BOOSTDATE default field title
  - SYS panel [203](#)
- BOOSTINT default field title
  - SYS panel [203](#)
- BOOSTREQ default field title
  - SYS panel [203](#)
- BOOSTTYPE default field title
  - SYS panel [203](#)
- BORPHAN default field title
  - CS panel [102](#)
- BOSS default field title
  - MAS and JESPLEX panels [156](#)
- browsing output
  - custom property [55](#)
  - SAF authority [225](#), [278](#)
- BUFSIZE default field title
  - NODE panel [164](#)
- BUILDING default field title
  - Job Data Set panel [135](#)
- BURST default field title
  - Held Output Queue panel [119](#)
  - Job 0 panel [149](#)
  - Job Data Set panel [135](#)
  - Output Queue panel [166](#)
  - Printer panel [171](#)
- BURSTPAGE default field title
  - Punch panel [181](#)
- BUSED default field title
  - CS panel [102](#)
- BYTE-CNT default field title
  - Job 0 panel [150](#)
  - Job Data Set panel [135](#)
- BYTESIN default field title
  - Job Device panel [141](#)
  - NA panel [158](#)
- BYTESOUT default field title
  - Job Device panel [141](#)
  - NA panel [158](#)

## C

- C default field title
  - Display Active Users panel [106](#)
  - Held Output Queue panel [119](#)
  - Initiator panel [122](#)
  - Input Queue panel [123](#)
  - Job 0 panel [149](#)
  - Job Data Set panel [134](#)
  - Output Queue panel [165](#)
  - Printer panel [171](#)
  - Reader panel [181](#)
  - Status panel [194](#)
- CADSPCT default field title
  - SYS panel [201](#)
- CANCEL (\$C) command
  - authorization with SAF [215](#)
- canceling jobs
  - authorization with SAF [215](#)

- CANRECV default field title
  - XCF Members and Groups panel [210](#)
- CANREPLY default field title
  - XCF Members and Groups panel [210](#)
- CAP default field title
  - CKPT panel [127](#)
- CAPPAGE default field title
  - CKPT panel [127](#)
- CAPPCT default field title
  - CKPT panel [127](#)
- CAPUSED default field title
  - CKPT panel [127](#)
- CARDS default field title
  - Held Output Queue panel [120](#)
  - Input Queue panel [124](#)
  - Output Queue panel [167](#)
  - Status panel [195](#)
- carriage control
  - custom property [67](#)
- case of panels, specifying [68](#)
- CATDSN default field title
  - SYS panel [203](#)
- CATEGORY default field title
  - CK panel [117](#)
- CATTYPE default field title
  - SYS panel [203](#)
- CATVOL default field title
  - SYS panel [203](#)
- CAUB default field title
  - CSI panel [103](#)
  - JCS panel [134](#)
- CC default field title
  - Job 0 panel [149](#)
  - Job Data Set panel [135](#)
  - Job Step panel [146](#)
- CCTL default field title
  - Printer panel [175](#)
  - Punch panel [179](#)
- CDATTR default field title
  - Job Module panel [146](#)
- CDATTR2 default field title
  - Job Module panel [146](#)
- CDATTR3 default field title
  - Job Module panel [146](#)
- CDATTR4 default field title
  - Job Module panel [146](#)
- CF Connections panel [97](#)
- CF Data Sets panel [98](#)
- CF default field title
  - CKPT panel [127](#)
- CF Structure panel [99](#)
- CFC panel
  - CFCFLDS parameter [26](#)
  - variable field list of
    - primary, defining [26](#)
- CFD panel
  - CFDFLDS parameter [26](#)
  - variable field list of
    - primary, defining [26](#)
- CFLEVEL default field title
  - CFC panel [98](#)
- CFNAME default field title
  - CFC panel [98](#)
  - CFS panel [100](#)

CFNUM default field title  
     CFC panel [98](#)  
 CFS panel  
     CFSFLDS parameter [26](#)  
     variable field list of  
         primary, defining [26](#)  
 CGS default field title  
     Printer panel [174](#)  
 changing  
     class of output of jobs  
         authorization with SAF [215](#)  
 CHAR1 default field title  
     Printer panel [174](#)  
 CHAR2 default field title  
     Printer panel [174](#)  
 CHAR3 default field title  
     Printer panel [174](#)  
 CHAR4 default field title  
     Printer panel [174](#)  
 CHARS default field title  
     Job 0 panel [149](#)  
     Job Data Set panel [135](#)  
 CHGDATE default field title  
     MSG panel [192](#)  
 CK command  
     authorization to issue [261](#)  
 CK panel [116](#)  
 CK panel scope  
     controlling [60](#)  
 CKH panel  
     CKHFLDS parameter [26](#)  
     limiting [60](#), [351](#)  
     variable field list of  
         alternate, defining [26](#)  
         primary, defining [26](#)  
 CKPTLEV default field title  
     MAS and JESPLEX panels [157](#)  
 CKPTLINE default field title  
     Printer panel [172](#)  
 CKPTMODE default field title  
     Printer panel [172](#)  
 CKPTPAGE default field title  
     Printer panel [172](#)  
     Punch panel [180](#)  
 CKPTREC default field title  
     Printer panel [172](#)  
     Punch panel [180](#)  
 CKPTSEC default field title  
     Printer panel [172](#)  
 CKTPLINE default field title  
     Punch panel [180](#)  
 CL default field title  
     Punch panel [179](#)  
 CLASS default field title  
     ACTH panel [93](#)  
     CMDH panel [101](#)  
     COLH panel [101](#)  
 Class1-8 default field titles  
     Initiator panel [122](#)  
 CLASSES default field title  
     Initiator panel [122](#)  
 CLEAR default field title  
     Printer panel [174](#)  
 CLIENT default field title  
     CLIENT default field title (*continued*)  
         FS panel [114](#)  
         Job Device panel [141](#)  
         NA panel [158](#)  
 CMDAUTH parameter [27](#)  
 CMDSYS default field title  
     Extended Console panel [113](#)  
 CMPCT default field title  
     Printer panel [175](#)  
 CODE default field title  
     Lines panel [151](#)  
 code pages [68](#)  
 CODPAG parameter [69](#)  
 COLORMAP default field title  
     Job Data Set panel [136](#)  
 COLUMN default field title  
     COLH panel [100](#)  
 column headings [47](#)  
 Columns Help panel [100](#)  
 COMCAHR default field title  
     JES Subsystem [130](#)  
 COMCHAR default field title  
     MAS and JESPLEX panels [156](#)  
 command authority exit point [353](#)  
 COMMAND default field title  
     ACTH panel [93](#)  
     JC panel [131](#)  
     MAS and JESPLEX panels [156](#)  
     Process panel [178](#)  
     Spool Volumes panel [189](#)  
 Command Help panel [101](#), [191](#)  
 commands  
     and EMCS [31](#)  
     authorization to issue  
         problems with [499](#)  
         with installation exit routines [349](#)  
         with SAF security scheme [226](#), [261](#), [285](#), [291](#)  
     authorized SDSF commands [261](#)  
     generated MVS/JES commands [215](#), [216](#)  
     ISFACP [6](#)  
     logging of [27](#)  
     MVS and JES, issuing [27](#), [285](#)  
     unauthorized use of, tracking [27](#)  
 Common Storage Remaining panel [103](#)  
 Common Storage Subpool Details panel [103](#)  
 Common Storage Subpools panel [102](#)  
 communications  
     starting between servers [88](#)  
     stopping [89](#)  
 COMP default field title  
     Lines panel [151](#)  
     Printer panel [175](#)  
     Punch panel [179](#)  
 Comp% default field title  
     Spool Volumes panel [190](#)  
 COMPAC default field title  
     Printer panel [175](#)  
 Compact default field title [160](#)  
 COMPACT default field title  
     NODE panel [162](#)  
     Punch panel [179](#)  
 COMPPCT default field title  
     Job Data Set panel [138](#)  
 COMPRESS default field title



COMPRESS default field title (*continued*)

Job Data Set panel [138](#)

COMPSIZE default field title

Job Data Set panel [138](#)

COMSETUP default field title

Job Data Set panel [136](#)

CONDISP default field title

CFC panel [98](#)

Job Device panel [141](#)

conditional access with RACF [222](#)

conditional processing of ISFPARMS

WHEN statement [10](#), [12](#)

CONFIRM parameter [27](#)

confirmation of action characters, controlling [27](#)

CONFLAGS default field title

CFC panel [98](#)

CONID default field title

CFC panel [98](#)

CONN default field title

Job Step panel [147](#)

Conn-Int default field title

LI panel [152](#)

NC panel [159](#)

CONNDATA default field title

CFC panel [98](#)

Connect default field title [159](#)

CONNECT default field title

DEV panel [105](#)

Job DDName panel [142](#)

Job Device panel [141](#)

LI panel [152](#)

NODE panel [164](#)

CONNECT statement [16](#)

ConnStat default field title

MAS and JESPLEX panels [157](#)

CONSID default field title

Extended Console panel [113](#)

console

name [357](#)

CONSOLE class [215](#), [222](#)

CONSOLE default field title

SR panel [204](#)

CONSTATE default field title

CFC panel [98](#)

Job Device panel [141](#)

contact

z/OS [519](#)

CONTENTS default field title

MEM panel [157](#)

converting assembler macros to statements [6](#)

COPIES default field title

Printer panel [174](#)

Punch panel [181](#)

COPYGRP default field title

Job Data Set panel [137](#)

COPYMARK default field title

Printer panel [173](#)

COUNT default field title

CK panel [117](#)

GT panel [116](#)

Job Memory panel [144](#)

CPC default field title

SYS panel [202](#)

CPR default field title

CPR default field title (*continued*)

JC panel [132](#)

CPU default field title

Process panel [177](#)

CPU use

custom property [60](#)

CPU-TIME default field title

Display Active Users Panel [106](#)

Enclave panel [110](#)

CPU% default field title

Display Active Users Panel [106](#)

CPUCRIT default field title

Display Active Users panel [107](#)

Enclaves panel [111](#)

WLM service classes panel [208](#)

CPUFMT parameter [27](#)

CPULIMIT default field title

Display Active Users panel [108](#)

CPUNUM default field title

SYS panel [202](#)

CPUPR default field title

SYS panel [201](#)

CPUTIME default field title

Job Step panel [147](#)

JT panel [148](#)

CPY default field title

JC panel [132](#)

CPYMOD default field title

Job 0 panel [149](#)

Job Data Set panel [135](#)

Printer panel [172](#)

CPYMODFT default field title

Job Data Set panel [135](#)

CRDATE default field title

Authorized Program Facility panel [97](#)

Held Output Queue panel [119](#)

Job Memory Objects panel [145](#)

Link List panel [153](#)

Link Pack Area panel [154](#)

Output Queue panel [166](#)

PARMLIB panel [169](#)

PROC panel [177](#)

SRCH panel [191](#)

WLM report class panel [206](#)

WLM resource group panel [207](#)

WLM service classes panel [209](#)

WLM Workload panel [209](#)

CRDATE-CRTIME default field title

Job Data Set panel [135](#), [149](#)

CRETCODE default field title

Job Group panel [143](#)

CRITICAL default field title

RMA panel [185](#)

XCF Members and Groups panel [210](#)

CRRETADR default field title

Job Memory Objects panel [145](#)

CRTIME default field title

Spool Offload panel [188](#)

CRUSER default field title

WLM report class panel [206](#)

WLM resource group panel [207](#)

WLM service classes panel [209](#)

WLM Workload panel [209](#)

CSA default field title



- CSA default field title (*continued*)
  - Address Space Memory panel [95](#)
  - CSR panel [104](#)
- CSAPCT default field title
  - Address Space Memory panel [95](#)
  - CSR panel [104](#)
  - SYS panel [201](#)
- CSR panel
  - CSRFLDS parameter [28](#)
  - variable field list of
    - primary, defining [28](#)
- CSR panel scope
  - controlling [60](#)
- CSRSEARCH [14](#)
- CTCNODE default field title
  - NODE panel [164](#)
- CTIME default field title
  - NODE panel [164](#)
- CTITLE parameter [28](#)
- CTOKEN default field title
  - CFC panel [98](#)
- CTr default field title
  - NC panel [160](#)
  - NS panel [161](#)
- CTR default field title
  - LI panel [152](#)
- CUNAME default field title
  - PAG panel [169](#)
- CURSOR parameter [28](#)
- cursor placement, controlling [28](#)
- CUSTOM parameter [29](#)
- customizing parameters [29](#)
- customizing properties [54](#)
- customizing SDSF
  - writing an installation exit routine [349](#)
- CVT default field title
  - AD panel [94](#)
- CVTVERID default field title
  - SYS panel [202](#)

## D

- d [118](#)
- DA command
  - authorization to issue [261](#)
- DA panel scope
  - controlling [61](#)
- DADFLT parameter [29](#)
- data sets
  - allocating SDSF [14](#)
  - freeing dynamically allocated [16](#)
- DataSetName default field title
  - Spool Volumes panel [190](#)
- DATE default field title
  - CSR panel [104](#)
  - SR panel [204](#)
- date format, controlling [29](#)
- DATE parameter [29](#)
- date separator, controlling [29](#)
- DATEE default field title
  - CK panel [118](#)
  - CKH panel [116](#)
  - Process panel [178](#)
  - RM panel [184](#)

- DATEN default field title
  - CKH panel [116](#)
- DATESEP parameter [29](#)
- DATETIMEE default field title
  - Held Output Queue panel [121](#)
  - Input Queue panel [125](#)
  - Output Queue panel [167](#)
  - Process panel [178](#)
  - Status panel [196](#)
- DATETIMEN default field title
  - Held Output Queue panel [121](#)
  - Output Queue panel [168](#)
  - Status panel [196](#)
- DATETIMER default field title
  - Held Output Queue panel [121](#)
  - Input Queue panel [125](#)
  - Output Queue panel [167](#)
  - Status panel [196](#)
- DATEVALUE default field title
  - WLM Policy panel [206](#)
- DCHAR parameter [14](#)
- DDNAME default field title
  - Job 0 panel [150](#)
  - Job Data Set panel [134](#)
- DEACTDATE default field title
  - XCF Members and Groups panel [211](#)
- DEBUG default field title
  - CK panel [118](#)
- Default default field title
  - Initiator panel [122](#)
  - Spool Volumes panel [190](#)
- default field title
  - JC panel [131](#)
- DefCount default field title
  - Initiator panel [122](#)
- DEFDATE default field title
  - CK panel [117](#)
  - XCF Members and Groups panel [210](#)
- DEFVOL default field title
  - Authorized Program Facility panel [97](#)
  - PROC panel [177](#)
- DELAYED default field title
  - COLH panel [101](#)
- DELAYRSN default field title
  - Input Queue panel [125](#)
  - Status panel [196](#)
- DELDATE default field title
  - CK panel [118](#)
- DEPARTMENT default field title
  - Job Data Set panel [136](#)
- DEPEND default field title
  - Job Dependencies panel [139](#)
- DESC default field title
  - ACTH panel [93](#)
  - CMDH panel [101](#)
  - COLH panel [101](#)
  - Job Delay panel [138](#)
  - PC panel [170](#)
  - SEARCH panel [191](#)
  - SMSG panel [192](#)
  - SR panel [204](#)
  - WLM report class panel [206](#)
  - WLM resource group panel [207](#)
  - WLM service classes panel [208](#)

DESC default field title (*continued*)  
WLM Workload panel [209](#)

DESCRIPT  
RES panel [183](#)

DESCRIPT default field title  
RM panel [184](#)  
SE panel [185](#)  
SYSP panel [204](#)

DEST command  
destination names used on [33](#)  
how to protect with SAF [268](#)

DEST default field title  
Held Output Queue panel [119](#)  
Job 0 panel [149](#)  
Job Data Set panel [134](#)  
Output Queue panel [165](#)  
Printer panel [171](#)

DESTDEF  
coding [356](#)

destination names of jobs  
SAF authorization [268](#)  
used to control  
authorization to issue commands [27](#)  
jobs displayed on SDSF panels [33](#), [34](#), [47](#)

destination operator authority [215](#), [217](#), [269](#)

DESTN default field title  
Punch panel [180](#)

DEV panel  
DEVFLDS parameter [30](#)  
variable field list of  
primary, defining [30](#)

DEV panel scope  
controlling [61](#)

Device Activity panel [104](#)

DEVICE default field title  
FS panel [114](#)  
Held Output Queue panel [120](#)  
Input Queue panel [124](#)  
Output Queue panel [166](#)  
Status panel [194](#)

DEVICENUM default field title  
CFD panel [99](#)  
FS panel [115](#)

DEVNAME default field title  
PAG panel [169](#)

DEVSTAT default field title  
SMSV panel [193](#)

DevType default field title  
Reader panel [182](#)

DEVTYPE default field title  
Printer panel [174](#)  
Punch panel [180](#)

DFCB default field title  
Printer panel [173](#)

DFIELD2 parameter [30](#)

DFIELDS parameter [30](#)

DGRPY default field title  
Printer panel [174](#)  
Punch panel [181](#)

DIAG1 default field title  
CK panel [117](#)  
CKH panel [116](#)

DIAG2 default field title  
CK panel [117](#)

DIAG2 default field title (*continued*)  
CKH panel [116](#)

DIAGFROM default field title  
CK panel [117](#)

diagnostic information, modules [497](#)

DIRECT default field title  
NODE panel [163](#)

DISCDATA default field title  
CFC panel [98](#)

DISCON default field title  
LI panel [151](#)

DISCONN default field title  
DEV panel [105](#)

DISP default field title  
CFS panel [99](#)

DISP1 default field title  
Job DDName panel [142](#)  
Job Device panel [141](#)

DISP2 default field title  
Job DDName panel [142](#)  
Job Device panel [141](#)

DISP3 default field title  
Job DDName panel [142](#)  
Job Device panel [141](#)

Display Active Users panel  
address space types and positions on, specifying  
in ISFPARMS [29](#)  
and RMF [358](#)  
authorization to display [261](#)  
jobs displayed on  
by owner [39](#)  
variable field list of  
alternate, defining [47](#)  
primary, defining [47](#)

DISPLAY parameter in ISFPARMS [30](#)

displaying  
message help [367](#)

DJOBID default field title  
Job Dependencies panel [139](#)

DJOBNAME default field title  
Job Dependencies panel [139](#)

DLY default field title  
Input Queue panel [124](#)  
Status panel [195](#)

DOM default field title  
Extended Console panel [113](#)

DORMANCY default field title  
Multi-Access Spool panel  
[156](#)

DP default field title  
Display Active Users panel [106](#)  
Printer panel [171](#)

DPRIO default field title  
Punch panel [180](#)

DSecLabel default field title [160](#)

DSECLABEL default field title  
LI panel [151](#)  
NODE panel [163](#)  
NS panel [161](#)  
Printer panel [173](#)  
Punch panel [180](#)  
Reader panel [182](#)  
Spool Offload panel [188](#)

DSENQSHR, default field title

DSENGSHR, default field title (*continued*)

Job Class panel [133](#)

DSI parameter [14](#)

DSID default field title

Job 0 panel [149](#)

Job Data Set panel [134](#)

DSNAME default field title

CFD panel [99](#)

CKPT panel [127](#)

FS panel [114](#)

Job 0 panel [150](#)

Job Data Set panel [135](#)

Job DDName panel [142](#)

Job Device panel [140](#)

PROC panel [176](#)

Spool Offload panel [187](#)

DSORG default field title

Authorized Program Facility panel [97](#)

Job DDName panel [142](#)

Job Device panel [141](#)

Link List panel [153](#)

Link Pack Area panel [154](#)

PARMLIB panel [169](#)

PROC panel [177](#)

SRCH panel [191](#)

DSPMAX default field title

Extended Console panel [113](#)

DSPName default field title

NS panel [161](#)

DSPNAME default field title

Printer panel [174](#)

Punch panel [181](#)

Reader panel [182](#)

DSPSIZE default field title

Extended Console panel [113](#)

DSYSID default field title

RM panel [183](#)

DTracks default field title

Spool Volumes panel [189](#)

DTrackU default field title

Spool Volumes panel [189](#)

DUBIOUS default field title

Input Queue panel [126](#)

Status panel [197](#)

dump

of SDSF, taking [497](#)

with abends [493](#)

DUMPHLQ parameter [14](#)

DUPJOB, default field title

Job Class panel [133](#)

DUPLEX default field title

CFS panel [100](#)

CKPT panel [127](#)

Lines panel [151](#)

DURATION default field title

WLM service classes panel [208](#)

DYNAMIC default field title

Printer panel [174](#)

Punch panel [181](#)

SSI panel [198](#)

Dynamic Exits panel

ASFLD2 parameter [30](#)

DYNXFLDS parameter [30](#)

variable field list of

Dynamic Exits panel (*continued*)

variable field list of (*continued*)

alternate, defining [30](#)

primary, defining [30](#)

dynamically allocated data sets

enqueueing on [14](#)

freeing [16](#)

## E

EAX default field title

PC panel [170](#)

EBCDIC default field title

MEM panel [157](#)

ECPU—Time default field title

Display Active Users panel [107](#)

ECPU% default field title

Display Active Users panel [107](#)

ECSA default field title

Address Space Memory panel [95](#)

CSR panel [104](#)

ECSAPCT default field title

Address Space Memory panel [95](#)

CSR panel [104](#)

SYS panel [201](#)

ECVT default field title

AD panel [94](#)

EDATE default field title

CSI panel [103](#)

EDT default field title

SYS panel [202](#)

EINTERVAL default field title

CK panel [118](#)

EKM default field title

PC panel [170](#)

ELAPSED default field title

Job Step panel [147](#)

ELEMCHG default field title

CFS panel [100](#)

ELEMCPCT default field title

CFS panel [100](#)

ELEMPCT default field title

CFS panel [99](#)

ELEMTOT default field title

CFS panel [100](#)

ELEMUSED default field title

CFS panel [100](#)

EMAIL default field title

Input Queue panel [125](#)

Status panel [197](#)

EMCS authority [31](#)

EMCS console

name modification [58](#)

sharing [58](#), [352](#)

ULOG authorization [58](#)

EMCS panel

EMCSFLDS parameter [31](#)

variable field list of

primary, defining [31](#)

EMCS required for system commands [31](#)

EMCSAUTH parameter [31](#)

EMCSREQ parameter [31](#)

EMERGENCY default field title

JES Subsystem [129](#)

- ENC command
  - authorization to issue [261](#)
- ENC panel scope
  - controlling [61, 63](#)
- ENCFLD2 parameter [31](#)
- ENCFLDS parameter [31](#)
- Enclaves panel
  - authorization to display [261](#)
  - variable field list [110](#)
  - variable field list of
    - alternate, defining [31](#)
    - primary, defining [31](#)
- ENCRTYPE default field title
  - CFS panel [100](#)
- ENCRYPT default field title
  - CFS panel [100](#)
  - Job Data Set panel [138](#)
- ENCSS default field title
  - WLM service classes panel [209](#)
- END default field title
  - Job Memory Objects panel [145](#)
  - NODE panel [162](#)
  - VMAP panel [205](#)
- END-DATE default field title
  - Held Output Queue panel [120](#)
  - Output Queue panel [167](#)
  - Status panel [195](#)
- END-TIME default field title
  - Held Output Queue panel [120](#)
  - Output Queue panel [167](#)
  - Status panel [195](#)
- ENDTIME default field title
  - Job Step panel [147](#)
- ENQTOKEN default field title
  - Enqueue panel [112](#)
- Enqueue panel
  - ENQFLDS parameter [31](#)
  - variable field list of
    - primary, defining [31](#)
- enqueueing on dynamically allocated data sets [14](#)
- ENTCHG default field title
  - CFS panel [100](#)
- ENTCPCT default field title
  - CFS panel [100](#)
- ENTPCT default field title
  - CFS panel [99](#)
- ENTTOT default field title
  - CFS panel [100](#)
- ENTUSED default field title
  - CFS panel [99](#)
- ENV default field title
  - ACTH panel [93](#)
- EPA default field title
  - PC panel [170](#)
  - SVC panel [199](#)
- EPRIV default field title
  - Address Space Memory panel [96](#)
- EPRIVPCT default field title
  - Address Space Memory panel [96](#)
- EPRIVUSE default field title
  - Address Space Memory panel [96](#)
- ERRCOND default field title
  - Job Group panel [143](#)
- ERRSTAT default field title
  - Job Group panel [143](#)
- ERRSTAT default field title (*continued*)
  - Job Group panel [143](#)
- ESQA default field title
  - Address Space Memory panel [95](#)
  - CSR panel [104](#)
- ESQAPCT default field title
  - Address Space Memory panel [95](#)
  - CSR panel [104](#)
  - SYS panel [201](#)
- ESR default field title
  - SVC panel [199](#)
- ESRBTIME default field title
  - Display Active Users panel [108](#)
- ESRCODE default field title
  - SVC panel [199](#)
- ESYS default field title
  - Held Output Queue panel [120](#)
  - Input Queue panel [124](#)
  - Output Queue panel [167](#)
  - Status panel [195](#)
- EUID default field title
  - Process panel [178](#)
- EVENTASID default field title
  - GT panel [115](#)
- EVENTDATA default field title
  - GT panel [115](#)
- EVENTDESC default field title
  - GT panel [115](#)
- EVENTJOB default field title
  - GT panel [115](#)
- EVENTRTN default field title
  - SSI panel [198](#)
- EXCOUNT default field title
  - CK panel [117](#)
- EXCP default field title
  - Job Step panel [147](#)
- EXCP-Cnt default field title
  - Display Active Users Panel [106](#)
- EXCPCT default field title
  - Job DDName panel [142](#)
  - Job Device panel [141](#)
  - NA panel [158](#)
- EXECKEY default field title
  - PC panel [170](#)
- EXECNAME default field title
  - CK panel [118](#)
- EXECNODE default field title
  - Input Queue panel [124](#)
  - Status panel [194](#)
- EXHAUST default field title
  - JESInfo panel [128](#)
- exit point
  - command authority [353](#)
  - initialization [350](#)
  - installation of [350](#)
  - pre-SAF [353](#)
- EXITNAME default field title
  - CK panel [117](#)
- exits
  - displaying information about [81, 82](#)
- EXT default field title
  - Spool Volumes panel [189](#)
- extended console
  - name [357](#)

extended console (*continued*)

OPERPARM [346](#)

EXTENT default field title

Authorized Program Facility panel [97](#)

Link List panel [153](#)

Link Pack Area panel [154](#)

PARMLIB panel [169](#)

PROC panel [177](#)

SRCH panel [191](#)

## F

FAIL default field title

CK panel [117](#)

FASTPATH default field title

Dynamic Exits panel [109](#)

FC04 default field title

SSI panel [198](#)

FC08 default field title

SSI panel [198](#)

FC09 default field title

SSI panel [198](#)

FC10 default field title

SSI panel [198](#)

FC14 default field title

SSI panel [198](#)

FC50 default field title

SSI panel [198](#)

FC54 default field title

SSI panel [198](#)

FC58 default field title

SSI panel [198](#)

FC78 default field title

SSI panel [198](#)

FCB default field title

Held Output Queue panel [119](#)

Job 0 panel [149](#)

Job Data Set panel [135](#)

Output Queue panel [166](#)

Printer panel [171](#)

FCBLOAD default field title

Printer panel [175](#)

feedback [xxvii](#)

field title

Reader panel [182](#)

fields on SDSF panels

defining in ISFPARMS [47](#)

defining with statements [47](#)

overtyping

authorization with SAF [290](#)

File Systems panel [114](#)

FILTER command

limit of lines searched on OPERLOG [15](#)

filtering

bypassing [352](#)

FIND command

limit of lines searched for, specifying  
in ISFPARMS [14](#)

FINDLIM command

authorization to issue [261](#)

FINDLIM parameter [14](#)

FIRST default field title

GT panel [116](#)

FIRSTSMP default field title

FIRSTSMP default field title (*continued*)

Job Delay panel [139](#)

FIXBPCT default field title

SYS panel [201](#)

FIXED default field title

Address Space Memory panel [95](#)

CS panel [102](#)

Job Memory panel [144](#)

FIXEDB default field title

Address Space Memory panel [95](#)

FIXEDFLD default field title

COLH panel [101](#)

FIXPCT default field title

SYS panel [201](#)

FLASH default field title

Held Output Queue panel [119](#)

Job 0 panel [149](#)

Job Data Set panel [135](#)

Output Queue panel [166](#)

Printer panel [171](#)

FLASHC default field title

Job 0 panel [149](#)

Job Data Set panel [135](#)

FLD statement

parameters [48](#)

FLDENT statement

parameters [48](#)

FLS default field title

Punch panel [179](#)

FLUSHACT default field title

Input Queue panel [125](#)

Status panel [196](#)

format of CPU busy, controlling [27](#)

FORMDEF default field title

Job Data Set panel [135](#)

FORMLEN default field title

Job Data Set panel [136](#)

FORMS default field title

Held Output Queue panel [119](#)

Job 0 panel [149](#)

Job Data Set panel [135](#)

Output Queue panel [165](#)

Printer panel [171](#)

Punch panel [180](#)

FPROT default field title

CS panel [102](#)

Job Memory Objects [145](#)

Job Memory panel [144](#)

MEM panel [157](#)

FRAG default field title

Job Memory panel [144](#)

FREE default field title

SMSG panel [192](#)

SMSV panel [193](#)

FREEASID default field title

SYS panel [201](#)

freeing dynamically allocated data sets [16](#)

FREESTOR default field title

JT panel [148](#)

FS panel scope

controlling [62](#)

FSASYSNM default field title

Printer panel [174](#)

FSATTRACE default field title

- FSATTRACE default field title (*continued*)
  - Printer panel [173](#)
- FSSNAME default field title
  - Printer panel [173](#)
- FSSPROC default field title
  - Printer panel [173](#)
- FULLTHRESH default field title
  - CFS panel [100](#)
- FUNCTION default field title
  - CFD panel [99](#)
  - XCF Members and Groups panel [210](#)

## G

- G abbreviation in column data [49](#)
- GB abbreviation in column data [49](#)
- GCP-Use% default field title
  - Display Active Users panel [107](#)
- GCP—Time default field title
  - Display Active Users panel [107](#)
- GDDM (Graphical Data Display Manager)
  - invoking with V action character [13](#)
  - viewing page-mode output [279](#)
- GDGBIAS, default field title
  - Job Class panel [133](#)
- generated MVS/JES commands [215](#), [216](#)
- Generic Tracker panel [115](#)
- GLOBAL default field title
  - CK panel [117](#)
  - JES Subsystem [130](#)
  - MAS and JESPLEX panels [156](#)
- global search characters, specifying [15](#)
- GOAL default field title
  - WLM service classes panel [208](#)
- GPLEN parameter [32](#)
- GPREF parameter [32](#)
- GQE default field title
  - CSI panel [103](#)
  - JCS panel [134](#)
- Group default field title
  - Initiator panel [122](#)
- GROUP default field title
  - Printer panel [171](#)
  - PUN panel [179](#)
  - RDR panel [181](#)
- Group field
  - JC panel [131](#)
- group membership
  - defining with SAF [17](#)
- group prefix
  - defining [32](#)
  - using to control
    - jobs users can display [40](#)
    - jobs users can issue commands for [27](#)
- GROUP statement
  - examples of [17](#)
  - parameters [17](#), [18](#)
  - purpose of [17](#)
- GROUP value
  - for PREFIX parameter [40](#)
- groups of users, defining [17](#)
- GRS default field title
  - SYS panel [202](#)
- GSDSF class [220](#)

- GT panel
  - GTFLDS parameter [32](#)
  - variable field list of
    - primary, defining [32](#)
- GT panel scope
  - controlling [62](#)
- GT61KMSG default field title
  - XCF Members and Groups panel [210](#)
- GUARD default field title
  - Job Memory Objects panel [145](#)

## H

- H command
  - adding generic character [56](#), [351](#)
  - authorization to issue [261](#)
- HBURST default field title
  - Printer panel [175](#)
- HC default field title
  - Extended Console panel [113](#)
- HCHARS default field title
  - Printer panel [175](#)
- HCPYMOD default field title
  - Printer panel [175](#)
- HCSEVHIGH default field title
  - SYS panel [203](#)
- HCSEVLOW default field title
  - SYS panel [203](#)
- HCSEVMEDIUM default field title
  - SYS panel [203](#)
- HCSUCCESS default field title
  - SYS panel [203](#)
- headings on SDSF panels, defining [47](#)
- Health Check history panel
  - variable field list of
    - alternate, defining [47](#)
    - primary, defining [47](#)
- Health Check History panel [116](#)
- Health Checker panel
  - authorization to display [261](#)
  - CKFLD2 parameter [26](#)
  - CKFLDS parameter [26](#)
  - variable field list of
    - alternate, defining [26](#)
    - primary, defining [26](#)
- Held Output Queue panel
  - authority to display [261](#)
  - jobs displayed on, controlling
    - by destination name [33](#)
    - by job name [34](#)
    - by job name prefix [40](#)
    - by owner [39](#)
  - variable field list of
    - alternate, defining [47](#)
    - primary, defining [47](#)
- help
  - for messages [367](#)
  - search [367](#)
- Help
  - displaying [81](#), [83](#)
- HFCB default field title
  - Printer panel [175](#)
- HFIELD2 parameter [32](#)
- HFLASH default field title

- HFLASH default field title (*continued*)
  - Printer panel [175](#)
- HFORMS default field title
  - Printer panel [175](#)
  - Punch panel [181](#)
- HICPUPCT default field title
  - Job Step panel [147](#)
- HICPUPGM default field title
  - Job Step panel [147](#)
- HiCyl default field title
  - Spool Volumes panel [189](#)
- highlighting
  - controlling [65](#)
- HiHead default field title
  - Spool Volumes panel [189](#)
- HITRK default field title
  - Spool Volumes panel [189](#)
- HiUsed default field title
  - Spool Volumes panel [190](#)
- HOLD (\$H) command
  - authorization to issue [27](#)
- HOLD default field title
  - Multi-Access Spool panel [156](#)
  - NODE panel [162](#)
  - Reader panel [181](#)
- HOLD-CNT default field title
  - JC panel [131](#)
- HOLDUNTIL default field title
  - Input Queue panel [125](#)
  - Status panel [196](#)
- HOMEASID default field title
  - GT panel [115](#)
- HOMEJOB default field title
  - GT panel [115](#)
- HONORPRIO default field title
  - WLM service classes panel [208](#)
- HONORTRC default field title
  - Printer panel [173](#)
- HUCS default field title
  - Printer panel [175](#)
- HVCOM default field title
  - Address Space Memory panel [95](#)
  - CSR panel [104](#)
- HVCOMHWM default field title
  - Address Space Memory panel [95](#)
- HVCOMNUM default field title
  - Address Space Memory panel [95](#)
- HWNAME default field title
  - SYS panel [202](#)

## I

- I command
  - authorization to issue [261](#)
- IBM Health Checker for
  - z/OS
    - CK panel [116](#)
    - CKH panel [116](#)
- ICMD parameter [32](#)
- IDEST parameter
  - Specifying with SAF [33](#)
- IEANUC default field title
  - SYS panel [202](#)

- IEASYM default field title
  - SYS panel [202](#)
  - System Symbol panel [200](#)
- IEASYS default field title
  - SYS panel [202](#)
- IFIELD2 parameter [33](#)
- IFIELDS parameter [33](#)
- ILOGCOL parameter
  - SYSLOG position, specifying [33](#)
- IMPORTANCE default field title
  - WLM service classes panel [208](#)
- IN value [29](#)
- INBUFSZ default field title
  - Job Device panel [140](#)
  - NA panel [158](#)
- INCLSPEC default field title
  - WLM resource group panel [208](#)
- IND default field title
  - Multi-Access Spool panel [156](#)
- index, to help [367](#)
- INIT command
  - authorization to issue [261](#)
- INIT panel
  - default initiators [56](#)
- INIT value [29](#)
- initialization exit point [350](#)
- initialization parameters
  - sample of [7](#)
- initiator panel [121](#)
- Initiator panel
  - authority to display, specifying [27](#)
  - variable field list of
    - alternate, defining [47](#)
    - primary, defining [47](#)
- initiators
  - authority to control from Initiator panel, specifying [27](#)
  - displaying
    - on Display Active Users panel [29](#)
  - SAF authorization [215](#)
- INITSIZE default field title
  - CFS panel [100](#)
- INPUT command
  - authorization to issue [261](#)
- INPUT parameter [33](#)
- Input Queue panel
  - authority to display [261](#)
  - jobs displayed on, controlling
    - by destination name [33](#)
    - by job name [34](#)
    - by job name prefix [40](#)
    - by owner [39](#)
  - variable field list [123](#)
  - variable field list of
    - alternate, defining [47](#)
    - primary, defining [47](#)
- installation exit points [350](#)
- installation exit routines [349](#)
- installing SDSF
  - with JES2 secondary subsystem [356](#)
- INTAVG default field title
  - RM panel [184](#)
- INTCOD default field title
  - JT panel [148](#)



- INTERRUPT (\$I) command
  - authorization to issue [215](#)
- INTERVAL default field title
  - CK panel [118](#)
  - Job Delay panel [139](#)
  - XCF Members and Groups panel [210](#)
- INTF default field title
  - Lines panel [151](#)
- INTFLD2 parameter [34](#)
- INTFLDS parameter [34](#)
- INTHIGH default field title
  - RM panel [184](#)
- INTIDS default field title
  - Extended Console panel [114](#)
- INTLOW default field title
  - RM panel [184](#)
- INTNUM default field titles
  - Initiator panel [123](#)
- INUSE default field title
  - CKPT panel [127](#)
- IODFCUNIT default field title
  - SYS panel [203](#)
- IODFDATE default field title
  - SYS panel [202](#)
- IODFDSN default field title
  - SYS panel [202](#)
- IODFUNIT default field title
  - SYS panel [203](#)
- IOINTENS default field title
  - DEV panel [105](#)
- IOPRIO default field title
  - WLM service classes panel [208](#)
- IOPRIOGRP default field title
  - Display Active Users panel [108](#)
  - Enclaves panel [111](#)
- IOSQ default field title
  - DEV panel [105](#)
- IPAddr default field title
  - NC panel [160](#)
- IPADDR default field title
  - Job Device panel [140](#)
  - LI panel [151](#)
  - NA panel [158](#)
- IPADDRLOCAL default field title
  - NA panel [159](#)
- IPDEST default field title
  - Job Data Set panel [138](#)
- IPLCUNIT default field title
  - SYS panel [203](#)
- IPLDATE default field title
  - SYS panel [202](#)
- IPLDAYS default field title
  - SYS panel [202](#)
- IPLTYPE default field title
  - SYS panel [202](#)
- IPLUNIT default field title
  - SYS panel [202](#)
- IPLVOL default field title
  - SYS panel [202](#)
- IPName default field title
  - NC panel [160](#)
  - NS panel [161](#)
- IPNAME default field title
  - LI panel [151](#)

- ISFACP command [6](#)
- ISFEND default field title
  - AD panel [93](#), [94](#), [102](#), [192](#)
  - Address Space Memory panel [96](#)
  - CFC panel [98](#)
  - CFD panel [99](#)
  - CFS panel [100](#), [127](#)
  - CS panel [102](#)
  - CSI panel [103](#)
  - CSR panel [104](#)
  - DEV panel [105](#)
  - Display Active Users panel [108](#)
  - Dynamic Exits panel [109](#)
  - Enclaves panel [111](#)
  - Enqueue panel [113](#)
  - Extended Console panel [114](#), [143](#), [185](#)
  - FS panel [115](#)
  - GT panel [116](#)
  - Held Output Queue panel [121](#)
  - Initiator panel [123](#)
  - Input Queue panel [126](#)
  - JCS panel [134](#)
  - Job Class Memory panel [131](#)
  - Job Class panel [133](#)
  - Job Data Set panel [130](#), [138](#)
  - Job Delay panel [139](#)
  - Job Dependencies panel [140](#)
  - Job Device panel [141](#)
  - Job Group panel [143](#)
  - Job Memory Objects panel [145](#)
  - Job Memory panel [144](#)
  - Job Module panel [146](#)
  - Job O panel [150](#)
  - Job Step panel [148](#)
  - Job Tasks panel [149](#)
  - JRI panel [128](#)
  - JRJ panel [129](#)
  - LI panel [152](#)
  - Link List panel [154](#)
  - Link List sets panel [153](#)
  - Link Pack Directory panel [155](#)
  - MAS and JESPLEX panels [157](#)
  - MEM panel [158](#)
  - NA panel [159](#)
  - NC panel [160](#)
  - NODE panel [164](#)
  - NS panel [162](#)
  - OMVS options panel [165](#)
  - Output Queue panel [168](#)
  - PAG panel [169](#)
  - PARMLIB panel [169](#)
  - PC panel [170](#)
  - Printer panel [175](#)
  - PROC panel [177](#)
  - Process panel [178](#)
  - Punch panel [181](#)
  - Reader panel [182](#)
  - RES panel [183](#)
  - RM panel [184](#)
  - SE panel [185](#)
  - SMSG panel [193](#)
  - SMSV panel [193](#)
  - Spool Offload panel [188](#)
  - SR panel [205](#)



## ISFEND default field title (*continued*)

- SRCH panel [191](#)
- SSI panel [199](#)
- ST panel [197](#)
- SVC panel [200](#)
- SYS panel [203](#)
- SYSP panel [204](#)
- System Symbol panel [201](#)
- USI panel [176](#)
- VMAP panel [205](#)
- WLM Policy panel [206](#)
- WLM report class panel [206](#)
- WLM resource group panel [208](#)
- WLM service classes panel [209](#)
- WLM workload panel [210](#)
- XCF Members and Groups panel [211](#)

ISFFLD macro

- parameters [48](#)

ISFGRP macro

- parameters [17](#), [18](#)

ISFGRP macros

- checking authorization [367](#)

ISFISP [362](#)

ISFISP2 [362](#)

ISFNTBL macro

- examples of [54](#)
- format of [54](#)
- parameters [54](#)
- purpose of [53](#)

ISFPARMS

- refreshing [85](#)

ISFPARMS module

- conditional processing in [10](#), [12](#)
- converting to statements [6](#)
- NTBL statements in [5](#)
- sample [7](#)
- symbols in [12](#)
- WHEN statement [10](#)

ISFPMAC macro [12](#), [13](#)

ISFTR macro

- syntax [69](#)
- using for defining code pages [68](#)
- using UPCTAB parameter with [68](#)
- using VALTAB parameter with [68](#)

ISFUSER module, using to customize SDSF [349](#)

ISPF (Interactive System Productivity Facility)

- adding SDSF to menu [359](#)
- main menu [359](#)
- main menu fallback [360](#)

ISR@PRIM [359](#)

ISTATUS parameter [34](#)

ISYS default field title

- Held Output Queue panel [120](#)
- Input Queue panel [124](#)
- Output Queue panel [167](#)
- Status panel [195](#)

ISYS parameter [34](#)

ITY default field title

- Job Data Set panel [136](#)

## J

J0 command

- authorization to issue [261](#)

J0FLD2 parameter [37](#)

J0FLDS parameter [37](#)

JC default field title

- Held Output Queue panel [120](#)
- Output Queue panel [167](#)

JCFLD2 parameter [35](#)

JCFLDS parameter [34](#)

JCLIM default field title

- JC panel [131](#)

JDDFLD2 parameter [35](#)

JDDFLDS parameter [35](#)

JDDNFLDS parameter [35](#)

JDMFLD2 parameter [35](#)

JDMFLDS parameter [35](#)

JDPFLD2 parameter [35](#)

JDPFLDS parameter [35](#)

JDSFLD2 parameter [36](#)

JDSFLDS parameter [35](#)

JDYFLD2 parameter [36](#)

JDYFLDS parameter [36](#)

JES

- displaying information about [82](#)
- refreshing list of subsystems [86](#)

JES checkpoint panel

- CKPTFLDS parameter [26](#)
- variable field list of
  - primary, defining [26](#)

JES Checkpoint panel [126](#)

JES commands, issuing

- authorization for, specifying
  - problems with [499](#)
  - with a user exit routine [349](#)
  - with SAF security [215](#)
  - with statements [27](#)

JES default field title

- ACTH panel [93](#)
- CMDH panel [101](#)

JES panel

- JESFLDS parameter [36](#)
- variable field list of
  - primary, defining [36](#)

JES panel scope

- controlling [62](#)

JES subsystem panel

- variable field list for [129](#)

JES Subsystem panel [129](#)

JES2

- DESTDEF considerations [356](#)
- secondary subsystems, installing SDSF with [356](#)
- subsystem name, specifying [14](#)

JES2 resources [183](#), [184](#)

JES2, processed by SDSF [362](#)

JES3

- considerations [355](#)
- global [355](#)
- subsystem name, specifying [14](#), [355](#)

JES3, processed by SDSF [362](#)

JES3NAME parameter [14](#), [355](#)

JESInfo by job panel [128](#)

JESInfo panel [127](#)

JESLevel default field title [160](#)

JESLEVEL default field title

- Initiator panel [122](#)
- LI panel [151](#)

JESLEVEL default field title (*continued*)

- NODE panel [163](#)
- NS panel [161](#)
- Printer panel [173](#)
- Punch panel [180](#)
- Reader panel [182](#)
- RM panel [184](#)
- Spool Offload panel [188](#)

JESLOG, default field title

- Job Class panel [132](#)

JESN default field title

- LI panel [151](#)
- NODE panel [163](#)
- NS panel [161](#)
- Punch panel [180](#)
- Reader panel [182](#)

JESNAME default field title

- CKPT panel [127](#)
- Initiator panel [122](#)
- JESInfo by job panel [129](#)
- JESInfo panel [128](#)
- MAS and JESPLEX panels [156](#)
- Printer panel [173](#)
- RM panel [184](#)
- RMA panel [185](#)
- Spool Offload panel [188](#)
- SYS panel [202](#)

JESNAME parameter [14](#)

JESNODE default field title

- SYS panel [202](#)

JESPLEX (JP) panel [155](#)

JESPLEX default field title

- CMDH panel [101](#)

JESPLEX panel

- authorization to display [261](#)

JESSPOOL class [269](#), [278](#)

JESTYPE default field title

- COLH panel [101](#)
- JES Subsystem panel [129](#)
- SYS panel [203](#)

JG command

- authorization to issue [261](#)

JGFLD2 parameter [36](#)

JGFLDS parameter [36](#)

JGSTATUS default field title

- Input Queue panel [125](#)
- Status panel [196](#)

JMO panel

- JMOFLDS parameter [36](#)
- variable field list of  
primary, defining [36](#)

JNAME default field title

- AD panel [94](#)
- CFC panel [98](#)
- CSI panel [103](#)
- CSR panel [104](#)
- Dynamic Exits panel [109](#)
- Extended Console panel [113](#)
- JCS panel [133](#)
- Job Memory Objects panel [145](#)
- Job Module panel [146](#)
- JT panel [148](#)
- MEM panel [157](#)
- NA panel [158](#)

JNAME default field title (*continued*)

- Output Queue panel [165](#)
- PC panel [170](#)
- USI panel [176](#)
- XCF Members and Groups panel [210](#)

JNUM default field title

- Display Active Users panel [106](#)
- Held Output Queue panel [119](#)
- Initiator panel [122](#)
- Input Queue panel [123](#)
- LI panel [150](#)
- Printer panel [171](#)
- Punch panel [179](#)
- Reader panel [181](#)
- Status panel [194](#)

job 0 panel [149](#)

Job 0 panel

- variable field list for [149](#)

Job Class Members panel [130](#)

Job Class panel

- fields [131](#)
- variable field list of  
primary, defining [47](#)
- Job Common Storage panel [133](#)
- Job Data Set panel
- variable field list for [134](#)
- variable field list of  
alternate, defining [47](#)
- primary, defining [47](#)

Job DDName panel [142](#)

Job Delay panel

- variable field list of  
primary, defining [47](#)

Job Dependency panel [139](#)

Job Device panel

- variable field list of  
primary, defining [47](#)

job devices

- protecting [277](#)

Job Group panel [143](#)

Job Memory Objects panel [144](#)

Job Memory panel

- variable field list of  
primary, defining [47](#)

Job Module panel [145](#)

Job Module panel

- CDEFLDS parameter [26](#)

- variable field list of  
primary, defining [26](#)

Job Status panel [193](#)

Job Step panel [146](#)

job steps

- SAF authority to [278](#)

Job Tasks panel

- TCBFLDS parameter [46](#)
- variable field list of  
primary, defining [46](#)

JOB value [29](#)

JOBACCT1 default field title

- Held Output Queue panel [121](#)
- Input Queue panel [125](#)
- Output Queue panel [167](#)
- Status panel [196](#)

JOBACCT2 default field title

JOBACCT2 default field title (*continued*)

Held Output Queue panel [121](#)  
Input Queue panel [125](#)  
Output Queue panel [167](#)  
Status panel [196](#)

JOBACCT3 default field title

Held Output Queue panel [121](#)  
Input Queue panel [125](#)  
Output Queue panel [167](#)  
Status panel [196](#)

JOBACCT4 default field title

Held Output Queue panel [121](#)  
Input Queue panel [125](#)  
Output Queue panel [167](#)  
Status panel [196](#)

JOBACCT5 default field title

Held Output Queue panel [121](#)  
Input Queue panel [125](#)  
Output Queue panel [167](#)  
Status panel [196](#)

JOBCL default field title

Job Class Members panel [130](#)

JOB CORR default field title

Display Active Users panel [108](#)  
Held Output Queue panel [121](#)  
Input Queue panel [125](#)  
Output Queue panel [167](#)  
Status panel [196](#)

JOB CRDATE default field title

Held Output Queue panel [121](#)  
Input Queue panel [126](#)  
Output Queue panel [168](#)  
ST panel [197](#)

JOB GROUP default field title

Input Queue panel [125](#)  
Job Group panel [143](#)  
Status panel [196](#)

JOB GRPID default field title

Input Queue panel [125](#)  
Job Group panel [143](#)  
Status panel [196](#)

JobID default field title

NC panel [159](#)

JOBID default field title

AD panel [94](#)  
Address Space Memory panel [96](#)  
CSI panel [103](#)  
CSR panel [104](#)  
Display Active Users panel [106](#)  
Extended Console panel [113](#)  
Held Output Queue panel [119](#)  
Initiator panel [122](#)  
Input Queue panel [123](#)  
JCS panel [134](#)  
JESInfo by Job panel [129](#)  
Job Dependencies panel [139](#)  
Job Memory Objects panel [145](#)  
LI panel [150](#)  
Output Queue panel [165](#)  
Printer panel [171](#)  
Process panel [177](#)  
Punch panel [179](#)  
Reader panel [181](#)  
Spool Offload panel [186](#)

JOBID default field title (*continued*)

SR panel [204](#)  
Status panel [194](#)

Jobname default field title

NC panel [159](#)

JOBNAME default field title

Enqueue panel [112](#)  
Initiator panel [122](#)  
Job Dependencies panel [139](#)  
LI panel [150](#)  
Printer panel [171](#)  
Punch panel [179](#)  
Reader panel [181](#)  
Spool Offload panel [186](#)  
SR panel [204](#)

JOBNUM default field title

SYS panel [202](#)

JOBRC, default field title

Job Class panel [133](#)

jobs

controlling  
by issuing MVS/JES command for [27](#)  
displayed on SDSF panels, controlling  
by destination name [33](#)  
by job name [34](#), [47](#)  
SAF authorization [215](#), [278](#)  
steps

SAF authority to [215](#)

JOBSET default field title

Input Queue panel [125](#)  
Status panel [196](#)

JOEBERTNUM default field title

Input Queue panel [126](#)  
Status panel [197](#)

JOENUM default field title

Input Queue panel [126](#)  
Status panel [197](#)

JP (JESPLEX) panel [155](#)

JP command

authorization to issue [261](#)

JP default field title

Held Output Queue panel [119](#)  
Output Queue panel [166](#)  
Printer panel [171](#)

JPAQ default field title

Job Module panel [145](#)

JPRIO default field title

Punch panel [180](#)

JR default field title

LI panel [151](#)

JRI panel

JRIFLDS parameter [36](#)  
variable field list of  
primary, defining [36](#)

JRJ panel

JRJFLDS parameter [36](#)  
variable field list of  
primary, defining [36](#)

JRNL default field title

JC panel [132](#)

JRNum default field title

NC panel [159](#)

JRNUM default field title

NODE panel [163](#)

- JSAB default field title
  - AD panel [94](#)
- JSFLD2 parameter [37](#)
- JSFLDS parameter [37](#)
- JT default field title
  - LI panel [151](#)
- JTNum default field title
  - NC panel [159](#)
- JTNUM default field title
  - NODE panel [163](#)
- JTr default field title
  - NC panel [160](#)
  - NS panel [161](#)
- JTR default field title
  - LI panel [152](#)
- JType default field title
  - NC panel [159](#)
- JTYPE default field title
  - AD panel [94](#)
  - Address Space Memory panel [96](#)
  - LI panel [150](#)

## K

- K default field title
  - Printer panel [173](#)
- KEY default field title
  - CS panel [102](#)
  - CSI panel [103](#)
  - Extended Console panel [113](#)
  - JCS panel [133](#)
  - Job Memory Objects panel [145](#)
  - Job Memory panel [144](#)
  - MEM panel [157](#)
  - USI panel [176](#)
- keyboard
  - navigation [519](#)
  - PF keys [519](#)
  - shortcut keys [519](#)
- KEYLABEL default field title
  - Job Data Set panel [138](#)
- KEYWORD default field title
  - RM panel [184](#)

## L

- LABEL default field title
  - Spool Offload panel [188](#)
- LARGE default field title
  - Job Memory Objects panel [145](#)
- LARGEST default field title
  - Job Memory panel [144](#)
- LARGESTF default field title
  - Job Memory panel [144](#)
- LAST-CHECKPOINT default field title
  - Multi-Access Spool panel [156](#)
- Last-GCon-Date-Tim default field title
  - MAS and JESPLEX panels [156](#)
- LASTIME default field title
  - Job Device panel [141](#)
- LASTSAMP default field title
  - Job Delay panel [139](#)

- LASTTIME default field title
  - NA panel [158](#)
- LATCHNUM default field title
  - FS panel [114](#)
- LATCHWAITPID default field title
  - Process panel [178](#)
- LATENTPARM default field title
  - PC panel [170](#)
- LENGTH default field title
  - CSI panel [103](#)
  - USI panel [176](#)
- length of fields, specifying [47](#)
- LEVEL default field title
  - CFC panel [98](#)
  - Enqueue panel [112](#)
  - Extended Console panel [113](#)
  - JT panel [148](#)
- LFREE default field title
  - SMSG panel [192](#)
  - SMSV panel [193](#)
- LgFree default field title
  - Spool Volumes panel [190](#)
- LI command
  - authorization to issue [261](#)
- LIMIT default field title
  - RM panel [183](#)
- limit of lines searched on OPERLOG [15](#)
- limit of lines searched with FIND command [14](#)
- Line default field title
  - NC panel [159](#)
- LINE default field title
  - NODE panel [162](#)
- Line-Lim-Hi default field title
  - LI panel [152](#)
- Line-Lim-Lo default field title
  - LI panel [152](#)
- Line-Limit default field title [160](#)
- LINE-LIMIT default field title
  - LI panel [150](#)
  - Printer panel [173](#)
  - Punch panel [180](#)
  - Spool Offload panel [186](#)
- Line-Limit-Hi default field title [160](#)
- Line-Limit-Lo default field title [160](#)
- LINECCHR default field title
  - Lines panel [151](#)
- LINECNT parameter [15](#)
- LINEFLD2 parameter [37](#)
- LINEFLDS parameter [37](#)
- LINELIMH default field title
  - Printer panel [174](#)
  - Punch panel [180](#)
  - Spool Offload panel [188](#)
- LINELIML default field title
  - Printer panel [174](#)
  - Punch panel [180](#)
  - Spool Offload panel [188](#)
- LINENUM default field title
  - SEARCH panel [191](#)
- lines
  - protecting with SAF [282](#)
- Lines panel
  - authorization to display [261](#)
  - variable field list [150](#)

- Lines panel (*continued*)
  - variable field list of
    - alternate, defining [47](#)
    - primary, defining [47](#)
- lines per page of printed output, specifying [15](#)
- Link List panel
  - LNKFLD2 parameter [37](#)
  - LNKFLDS parameter [37](#)
  - variable field list of
    - alternate, defining [37](#)
    - primary, defining [37](#)
- Link List sets panel [152](#)
- Link Pack Area panel
  - LPAFLD2 parameter [38](#)
  - LPAFLDS parameter [38](#)
  - variable field list of
    - alternate, defining [38](#)
    - primary, defining [38](#)
- Link Pack Directory panel [154](#)
- LIST (\$L) command
  - authorization to issue, specifying [215](#)
- LISTNUM default field title
  - CFS panel [99](#)
- LLA default field title
  - Link List sets panel [153](#)
- LLS panel scope
  - controlling [62](#)
- LNAME default field title
  - NODE panel [162](#)
- LNK panel scope
  - controlling [62](#)
- LOADDSN default field title
  - SYS panel [202](#)
- LOADPARM default field title
  - SYS panel [202](#)
- LOADUNIT default field title
  - SYS panel [202](#)
- LOCAL value [34](#)
- LOCALE default field title
  - CK panel [118](#)
- LOCATION default field title
  - Link Pack Directory panel [155](#)
  - PC panel [170](#)
  - SVC panel [199](#)
- LOCKNUM default field title
  - CFS panel [100](#)
- LOCKS default field title
  - SVC panel [199](#)
- LoCyl default field title
  - Spool Volumes panel [189](#)
- Log
  - displaying information about [90](#)
- LOG command
  - authorization to issue [261](#)
- Log default field title
  - NS panel [161](#)
- LOG default field title
  - JC panel [132](#)
  - Lines panel [151](#)
- LOGDATE default field title
  - CK panel [118](#)
- logical log [342](#)
- logical SYSLOG [342](#)
- LOGLIM parameter [15](#)

- LogMode default field title [160](#)
- LOGMODE default field title
  - NODE panel [163](#)
- Logon default field title
  - NC panel [160](#)
  - NODE panel [163](#)
- logon procedure
  - using to define a group of users [17](#)
- LOGSTREAM default field title
  - CK panel [118](#)
- LOGSTRM class [289](#)
- LoHead default field title
  - Spool Volumes panel [189](#)
- LOTRK default field title
  - Spool Volumes panel [189](#)
- LPA panel scope
  - controlling [62](#)
- LPAR default field title
  - SYS panel [202](#)
- LPD panel
  - LPDFLDS parameter [38](#)
  - variable field list of
    - primary, defining [38](#)
- LPD panel scope
  - controlling [63](#)
- LPDE default field title
  - Job Module panel [146](#)
- LRECL default field title
  - Authorized Program Facility panel [97](#)
  - Job Data Set panel [137](#)
  - Job DDName panel [142](#)
  - Job Device panel [140](#)
  - Link List panel [153](#)
  - Link Pack Area panel [154](#)
  - PARMLIB panel [169](#)
  - Printer panel [175](#)
  - PROC panel [177](#)
  - Punch panel [180](#)
  - SRCH panel [191](#)
- LUNAME default field title
  - Job Device panel [141](#)
  - NA panel [158](#)

## M

- M abbreviation in column data [49](#)
- M default field title
  - Printer panel [172](#)
- MACRO default field title
  - SVC panel [199](#)
- MAILBCC default field title
  - Job Data Set panel [138](#)
- MAILCC default field title
  - Job Data Set panel [138](#)
- MAILFILE default field title
  - Job Data Set panel [138](#)
- MAILFROM default field title
  - Job Data Set panel [138](#)
- MAILTO default field title
  - Job Data Set panel [138](#)
- Main panel scope
  - controlling [63](#)
- MAJOR default field title
  - Enqueue panel [112](#)

MAJOR default field title (*continued*)  
 Job Module panel [145](#)  
 Link Pack Directory panel [155](#)  
 MargExc default field title  
 Spool Volumes panel [190](#)  
 MargPct default field title  
 Spool Volumes panel [190](#)  
 MAS (Multi-access spool) panel [155](#)  
 MAS command  
 authorization to issue [261](#)  
 MAS panel  
 authorization to display [261](#)  
 MAX-RC default field title  
 Held Output Queue panel [120](#)  
 Output Queue panel [166](#)  
 Status panel [194](#)  
 MAX-TIME default field  
 title  
 JC panel [132](#)  
 MAXASID default field title  
 SYS panel [201](#)  
 MAXCPUPCT default field title  
 WLM resource group panel [207](#)  
 MAXESR default field title  
 SVC panel [199](#)  
 MAXFILES default field title  
 Process panel [178](#)  
 MAXGRP default field title  
 CFD panel [99](#)  
 MAXLINES default field title  
 NODE panel [163](#)  
 MAXLPARPCT default field title  
 WLM resource group panel [207](#)  
 MAXMEM default field title  
 CFD panel [99](#)  
 MAXPERIOD default field title  
 WLM service classes panel [208](#)  
 MAXRETR default field title  
 NODE panel [163](#)  
 MAXSIZE default field title  
 CFS panel [100](#)  
 MAXSU default field title  
 WLM resource group panel [207](#)  
 MAXSYS default field title  
 CFD panel [99](#)  
 MB abbreviation in column data [49](#)  
 MBURST default field title  
 Spool Offload panel [187](#)  
 MC default field title  
 Held Output Queue panel [120](#)  
 Input Queue panel [124](#)  
 JC panel [132](#)  
 Output Queue panel [167](#)  
 Reader panel [181](#)  
 Status panel [195](#)  
 MCLASS default field title  
 Spool Offload panel [187](#)  
 MDEST default field title  
 Spool Offload panel [187](#)  
 MEM panel  
 MEMFLDS parameter [38](#)  
 variable field list of  
 primary, defining [38](#)  
 MEM panel scope

MEM panel scope (*continued*)  
 controlling [63](#)  
 MEMASSOC default field title  
 XCF Members and Groups panel [210](#)  
 MEMBER default field title  
 JES Subsystem [130](#)  
 JESInfo by Job panel [129](#)  
 RMA panel [184](#)  
 SYSP panel [204](#)  
 XCF Members and Groups panel [210](#)  
 MEMBER field  
 JC panel [131](#)  
 membership in groups, SAF control of [284](#)  
 MEMLIMIT default field title  
 Address Space Memory panel [95](#)  
 Display Active Users panel [107](#)  
 Job Step panel [147](#)  
 WLM resource group panel [207](#)  
 MEMLIMU default field title  
 Job Step panel [147](#)  
 Memory contents panel [157](#)  
 messages  
 help panels [367](#)  
 problem with [500](#)  
 MESSATE-TEXT default field  
 title  
 SR panel [204](#)  
 MFCB default field title  
 Spool Offload panel [187](#)  
 MFLH default field title  
 Spool Offload panel [187](#)  
 MFORMS default field title  
 Spool Offload panel [187](#)  
 MHOLD default field title  
 Spool Offload panel [187](#)  
 MigDSName default field title  
 Spool Volumes panel [190](#)  
 MigPhase default field title  
 Spool Volumes panel [190](#)  
 migrating  
 to statements for ISFPARMS [6](#)  
 MigSys default field title  
 Spool Volumes panel [190](#)  
 MigVol default field title  
 Spool Volumes panel [190](#)  
 MINCPUPCT default field title  
 WLM resource group panel [207](#)  
 MinExc default field title  
 Spool Volumes panel [190](#)  
 MINLPARPCT default field title  
 WLM resource group panel [207](#)  
 MinPct default field title  
 Spool Volumes panel [190](#)  
 MINSIZE default field title  
 CFS panel [100](#)  
 MINSU default field title  
 WLM resource group panel [207](#)  
 MINTIME default field title  
 Job Delay panel [139](#)  
 mixed case, specifying [68](#)  
 MLA default field title  
 SYS panel [203](#)  
 MLIMCUR default field title  
 Job Class Members panel [130](#)

- MLIMMAX default field title
  - Job Class Members panel [130](#)
- MOBJ default field title
  - Address Space Memory panel [95](#)
- MOBJAUX default field title
  - Address Space Memory panel [96](#)
- MOBJHWM default field title
  - Address Space Memory panel [95](#)
- MOBJNUM default field title
  - Address Space Memory panel [95](#)
- MOBJREAL default field title
  - Address Space Memory panel [96](#)
- Mode default field title
  - Initiator panel [122](#)
- MODE default field title
  - CKPT panel [127](#)
  - FS panel [114](#)
  - JC panel [131](#)
  - PC panel [170](#)
  - Printer panel [172](#)
- MODEPA default field title
  - Dynamic Exits panel [109](#)
  - Job Module panel [145](#)
  - Link Pack Directory panel [155](#)
- MODIFIED default field title
  - CK panel [117](#)
- MODLEN default field title
  - Job Module panel [145](#)
- MODLOADPT default field title
  - Dynamic Exits panel [109](#)
  - Link Pack Directory panel [155](#)
- MODNAME default field title
  - CK panel [117](#)
  - Dynamic Exits panel [109](#)
  - Job Module panel [145](#)
- MODSIZE default field title
  - Dynamic Exits panel [109](#)
  - Link Pack Directory panel [155](#)
- MODSP default field title
  - Spool Offload panel [187](#)
- MODULE default field title
  - PC panel [170](#)
  - SVC panel [199](#)
- module information, displaying [497](#)
- modules, SDSF
  - ISFPARMS [7](#)
  - ISFUSER [349](#)
- MONITOR default field title
  - Extended Console panel [113](#)
- mount messages
  - protecting with SAF [345](#)
- MOUNTPARM default field title
  - FS panel [115](#)
- MOUNTTIME default field title
  - FS panel [115](#)
- MPRMODE default field title
  - Spool Offload panel [187](#)
- MSAFF default field title
  - Spool Offload panel [187](#)
- MSCOPE default field title
  - Extended Console panel [114](#)
- MSG value [27](#)
- MsgDest default field title
  - MAS and JESPLEX panels [157](#)

- MSGLINE1 default field title
  - RMA panel [184](#)
- MSGLINE3 default field title
  - RMA panel [184](#)
- MSGLINE4 default field title
  - RMA panel [185](#)
- MSGLV default field title
  - JC panel [132](#)
- MsgPrefix default field title
  - MAS and JESPLEX panels [157](#)
- MSGTIME default field title
  - RMA panel [185](#)
- MSGTYPE default field title
  - SR panel [204](#)
- MSU default field title
  - SYS panel [202](#)
- MUCS default field title
  - Spool Offload panel [187](#)
- multi-access spool [155](#)
- multi-access spool (MAS) panel [155](#)
- Multi-Access Spool environment
  - specifying JES2 system ID in [45](#)
- MVS/JES commands
  - authorization for, specifying
    - problems with [499](#)
    - with a user exit routine [349](#)
    - with SAF [217](#), [285](#)
- MVS/JES commands, console used to issue [356](#)
- MVS/JES commands, storing [357](#)
- MWRITER default field title
  - Spool Offload panel [188](#)

## N

- NA panel
  - NAFLDS parameter [38](#)
  - variable field list of
    - primary, defining [38](#)
- NA panel scope
  - controlling [63](#)
- NAME default field title
  - CKH panel [116](#)
  - CKPT panel [127](#)
  - CMDH panel [101](#)
  - JESInfo by Job panel [129](#)
  - Job Data Set panel [135](#)
  - Job DDName panel [142](#)
  - Job Device panel [140](#)
  - VMAP panel [205](#)
- NAMEX default field title
  - SSI panel [198](#)
- navigation
  - keyboard [519](#)
- NC command
  - authorization to issue [261](#)
- NC panel
  - variable field list [159](#)
- NCFLD2 parameter [38](#)
- NCFLDS parameter [38](#)
- NCOMPSIZE default field title
  - Job Data Set panel [138](#)
- NETABCMP default field title
  - Input Queue panel [126](#)
  - ST panel [197](#)



- NETABNORM default field title
  - Input Queue panel [126](#)
  - ST panel [197](#)
- NETCNHOLD default field title
  - Input Queue panel [126](#)
  - ST panel [197](#)
- NETHOLD default field title
  - NODE panel [162](#)
- NETID default field title
  - SYS panel [203](#)
- netmail [41](#)
- NETNORM default field title
  - Input Queue panel [126](#)
  - ST panel [197](#)
- NETNRCMP default field title
  - Input Queue panel [126](#)
  - ST panel [197](#)
- NETONHOLD default field title
  - Input Queue panel [126](#)
  - ST panel [197](#)
- NETOPHOLD default field title
  - Input Queue panel [126](#)
  - ST panel [197](#)
- NETPR default field title
  - NODE panel [164](#)
- NETPU default field title
  - NODE panel [164](#)
- Netsrv default field title
  - NC panel [160](#)
- NETSRV default field title
  - NODE panel [163](#)
- Network Activity panel [158](#)
- Network Connection panel
  - variable field list of
    - primary, defining [47](#)
- network connections
  - protecting with SAF [287](#)
- Network Server panel
  - variable field list of
    - primary, defining [47](#)
- network servers
  - protecting with SAF [287](#)
- NEW default field title
  - ACTH panel [93](#)
  - COLH panel [101](#)
- NEWPAGE default field title
  - Printer panel [173](#)
- NO command
  - authorization to issue [261](#)
- NO panel
  - variable field list [162](#)
- NODE default field title
  - Held Output Queue panel [119](#)
  - Input Queue panel [123](#)
  - JES Subsystem [130](#)
  - Job Data Set panel [135](#)
  - LI panel [150](#)
  - Output Queue panel [166](#)
  - Printer panel [173](#)
- NODEFLD2 parameter [39](#)
- NODEFLDS parameter [39](#)
- NODENAME default field title
  - NODE panel [162](#)
- nodes
  - nodes (continued)*
    - protecting with SAF [288](#)
  - Nodes panel
    - authorization to display [261](#)
    - variable field list of
      - alternate, defining [47](#)
      - primary, defining [47](#)
  - NONE value [39](#), [40](#)
  - NOPARM fallback [7](#)
  - NOTIFY default field title
    - Held Output Queue panel [120](#)
    - Input Queue panel [124](#)
    - Job Data Set panel [136](#)
    - Output Queue panel [166](#)
    - Spool Offload panel [187](#)
    - Status panel [195](#)
  - NOTIFY parameter of job card, using to control authorization [27](#)
  - NP default field title
    - SVC panel [199](#)
  - NPRIVEXH default field title
    - JESInfo panel [128](#)
  - NPRIVMAX default field title
    - JESInfo panel [128](#), [129](#)
  - NPRIVPCT default field title
    - JESInfo panel [128](#)
  - NPRIVSHORT default field title
    - JESInfo panel [128](#)
  - NPRIVUSE default field title
    - JESInfo panel [128](#)
  - NPRO default field title
    - Printer panel [172](#)
  - NS command
    - authorization to issue [261](#)
  - NS panel
    - variable field list [161](#)
  - NSECURE default field title
    - NS panel [161](#)
  - NSFLD2 parameter [39](#)
  - NSFLDS parameter [39](#)
  - NSNAME default field title
    - LI panel [152](#)
  - NTBL statement
    - examples of [54](#)
    - format of [54](#)
    - parameters [54](#)
    - purpose of [53](#)
  - NTBLENT statement
    - examples of [54](#)
    - purpose of [53](#)
  - NUCLST default field title
    - SYS panel [202](#)
  - NUM default field title
    - SVC panel [199](#)
  - NUMASID default field title
    - Link List sets panel [153](#)
  - NUMCAT default field title
    - CK panel [117](#)
  - NUMDATASETS default field title
    - Link List sets panel [153](#)
  - NUMDISABLE default field title
    - SMSG panel [192](#)
  - NUMENABLE default field title
    - SMSG panel [192](#)



- numeric values, scaling [49](#)
- NUMOFFLINE default field title
  - SMSG panel [192](#)
- NUMONLINE default field title
  - SMSG panel [192](#)
- NUMQUIESCE default field title
  - SMSG panel [192](#)
- NUMVALUE default field title
  - OMVS Options panel [165](#)
- NUMVOL default field title
  - SMSG panel [192](#)
- NUMX default field title
  - SVC panel [199](#)

## O

- O command
  - authorization to issue [261](#)
- O-GRP-N default field title
  - Held Output Queue panel [119](#)
  - Job Data Set panel [135](#)
  - Output Queue panel [166](#)
  - Printer panel [172](#)
- OCLASS default field title
  - Punch panel [180](#)
- OCOPYCNT default field title
  - Job Data Set panel [137](#)
- ODATE default field title
  - JCS panel [134](#)
- ODISP default field title
  - Held Output Queue panel [119](#)
  - JC panel [131](#)
  - Output Queue panel [166](#)
- offloaders
  - protecting with SAF [334](#), [340](#), [341](#)
- Offs default field title
  - Status panel [195](#)
- Offs default field title
  - Held Output Queue panel [120](#)
  - Output Queue panel [166](#)
- OFFSET default field title
  - MEM panel [157](#)
- OFFSETXB default field title
  - Job Data Set panel [136](#)
- OFFSETXF default field title
  - Job Data Set panel [136](#)
- OFFSETYB default field title
  - Job Data Set panel [136](#)
- OFFSETYF default field title
  - Job Data Set panel [136](#)
- OFIELD2 parameter [39](#)
- OFIELDS parameter [39](#)
- OGID default field title
  - Held Output Queue panel [119](#)
- OGID1 default field title
  - Output Queue panel [166](#)
  - Printer panel [173](#)
  - Punch panel [180](#)
- OGID2 default field title
  - Held Output Queue panel [119](#)
  - Output Queue panel [166](#)
  - Printer panel [173](#)
  - Punch panel [180](#)
- OGNAME default field title

- OGNAME default field title (*continued*)
  - Punch panel [180](#)
- OHR default field title
  - Held Output Queue panel [119](#)
  - Output Queue panel [166](#)
- OLDAPF default field title
  - SVC panel [200](#)
- OLDAR default field title
  - SVC panel [200](#)
- OLDASF default field title
  - SVC panel [200](#)
- OLDEPA default field title
  - SVC panel [199](#)
- OLDLOCKS default field title
  - SVC panel [200](#)
- OLDMOD default field title
  - SVC panel [199](#)
- OLDNP default field title
  - SVC panel [200](#)
- OLDTYPE default field title
  - SVC panel [200](#)
- OMVS panel
  - OMVSFLDS parameter [39](#)
  - variable field list of
    - primary, defining [39](#)
- OMVS panel scope
  - controlling [63](#)
- ONERR default field title
  - Job Group panel [143](#)
- OPACTLOG default field title
  - Printer panel [174](#)
- OPEN default field title
  - Job DDName panel [142](#)
  - Job Device panel [141](#)
- OPERCMD class [227](#)
- OPERLOG panel
  - including inactive log stream data [59](#)
  - limiting amount searched [15](#)
- OPSW default field title
  - JT panel [148](#)
- OPTIONS statement
  - parameters [13](#)
- OPVERIFY default field title
  - CKPT panel [127](#)
- ORIGIN default field title
  - CK panel [118](#)
- ORIGINAL default field title
  - Enclave panel [110](#)
- ORIGNODE default field title
  - Input Queue panel [124](#)
  - Status panel [194](#)
- ORPHAN default field title
  - CSI panel [103](#)
  - JCS panel [133](#)
- OSCONFIG default field title
  - SYS panel [202](#)
- OTHERWISE default field title
  - Job Dependencies panel [139](#)
- OUCB default field title
  - AD panel [94](#)
- OUT default field title
  - JC panel [132](#)
- OUT value [29](#)
- OUTBIN default field title

OUTBIN default field title (*continued*)

Job Data Set panel [136](#)

OUTBUFSZ default field title

Job Device panel [141](#)

NA panel [158](#)

OUTDISP default field title

Job Data Set panel [137](#)

Output Data Set panel

authorization to use, specifying [349](#)

output groups

SAF authority to [215](#), [278](#)

output of jobs

controlling

by issuing MVS/JES commands for [27](#)

displaying

specifying authorization for [349](#)

Output Queue panel

authorization to display [261](#)

authorization to display, specifying [261](#)

jobs displayed on, controlling

by destination name [33](#)

by job name [34](#)

by job name prefix [40](#)

by owner [39](#)

variable field list of

alternate, defining [47](#)

primary, defining [47](#)

OUTPUT-HOLD-TEXT default field title

Held Output Queue panel [119](#)

Output Queue panel [166](#)

OVA default field title

Spool Volumes panel [189](#)

OverFNam default field title

Spool Volumes panel [189](#)

OverInto default field title

Spool Volumes panel [189](#)

OVERLAYB default field title

Job Data Set panel [136](#)

OVERLAYF default field title

Job Data Set panel [136](#)

OverOccur default field title

Spool Volumes panel [189](#)

OVERTYPE default field title

COLH panel [101](#)

overtimeable fields

setting up generic and discrete profiles [291](#)

tables [293](#)

overtyping fields

authorization for [27](#)

authorization for, SAF [215](#), [217](#), [290](#)

OVERWARN default field title

RM panel [184](#)

OWNER command

authorization [506](#)

Owner default field title

NC panel [159](#)

OWNER default field title

CKH panel [116](#)

Display Active Users panel [106](#)

FS panel [114](#)

GT panel [115](#)

Held Output Queue panel [119](#)

Initiator panel [122](#)

OWNER default field title (*continued*)

Input Queue panel [123](#)

Job 0 panel [149](#)

Job Data Set panel [134](#)

Job Group panel [143](#)

LI panel [150](#)

Output Queue panel [165](#)

Printer panel [171](#)

Process panel [177](#)

Punch panel [179](#)

Reader panel [181](#)

Spool Offload panel [186](#)

Status panel [194](#)

OWNERAS default field title

Enclave panel [110](#)

OWNERASX default field title

Enclave panel [110](#)

OWNERID default field title

AD panel [94](#)

Address Space Memory panel [96](#)

OWNERJOB default field title

Enclave panel [110](#)

OWNERS default field title

Enqueue panel [112](#)

OWNERSYS default field title

Enclave panel [110](#)

## P

P abbreviation in column data [49](#)

PAG AUX default field title

Display Active Users panel [108](#)

PAGE default field title

Job Step panel [147](#)

Page panel

PAG parameter [40](#)

variable field list of

alternate, defining [40](#)

primary, defining [40](#)

PAGE-CNT default field title

Job 0 panel [150](#)

Job Data Set panel [134](#)

Printer panel [171](#)

Punch panel [179](#)

Page-Lim-Hi default field title

LI panel [152](#)

Page-Lim-Lo default field title

LI panel [152](#)

Page-Limit default field title [160](#)

PAGE-LIMIT default field title

LI panel [150](#)

Printer panel [173](#)

Spool Offload panel [186](#)

Page-Limit-Hi default field title [160](#)

Page-Limit-Lo default field title [160](#)

PAGE-PRT default field title

Printer panel [171](#)

Punch panel [179](#)

PAGEDEF default field title

Job Data Set panel [135](#)

PAGELIMH default field title

Printer panel [174](#)

Spool Offload panel [188](#)

PAGELIML default field title

PAGELIML default field title (*continued*)

Printer panel [174](#)

Spool Offload panel [188](#)

PAGERATE default field title

SYS panel [201](#)

PAGING default field title

Display Active Users Panel [106](#)

PANEL default field title

ACTH panel [93](#)

COLH panel [100](#)

Panel scope

controlling [59–61](#)

panels

description of

ACTH [93](#)

AD [94](#)

Address Space Memory [94](#)

Authorized Program Facility [96](#)

CFC [97](#)

CFD [98](#)

CFS [99](#)

CK [116](#)

CKH [116](#)

CKPT [126](#)

CMDH [101](#)

COLH [100](#)

CS [102](#)

CSI [103](#)

CSR [103](#)

DEV [104](#)

Display Active Users [105](#)

Dynamic Exits [109](#)

Enclaves panel [110](#)

Enqueue [111](#), [113](#)

FS [114](#)

GT [115](#)

Held Output panel [118](#)

Initiator panel [121](#)

Input Queue panel [123](#)

JC [145](#)

JCS [133](#)

JESInfo [127](#)

JESInfo by job [128](#)

Job Class Members [130](#)

Job Memory Objects [144](#)

JT [148](#)

LI panel [150](#)

Link List [153](#)

Link List sets [152](#)

Link Pack Area [154](#)

Link Pack Directory [154](#)

MEM [157](#)

multi-access spool (MAS) panel [155](#)

NA [158](#)

NC panel [159](#)

NO panel [162](#)

NS panel [161](#)

OMVS [164](#)

Output Queue panel [165](#)

PAG [168](#)

PARM [169](#)

PC [170](#)

Printer panel [170](#)

PROC [176](#)

panels (*continued*)

description of (*continued*)

Process panel [177](#)

PUN panel [178](#)

RDR panel [181](#)

SEAR [191](#)

SMSG [192](#)

SMSV [193](#)

Spool Offload panel [185](#)

Spool Volumes panel [188](#)

SRCH [190](#)

SSI [198](#)

Status panel [193](#)

SVC [199](#)

SYS [201](#)

SYSP [203](#)

System Symbols [200](#)

USI [175](#)

VMAP [205](#)

WLM report class [206](#)

WLM resource group [207](#)

WLM service classes [208](#)

WLM workload [205](#), [209](#)

XCF members and groups [210](#)

Panels

AD panel [94](#)

Address Space Memory panel [95](#)

Authorized Program Facility panel [96](#)

CF panel [97](#)

CFD panel [98](#)

CFS panel [99](#)

CKPT panel [126](#)

CS panel [102](#)

CSI panel [103](#)

CSR panel [103](#)

DEV panel [104](#)

Dynamic Exits panel [109](#)

Enqueue panel [111](#)

FS panel [114](#)

GT panel [115](#)

JCS panel [133](#)

Job Module panel [145](#)

Job Tasks panel [148](#)

Link List panel [153](#)

Link List sets panel [152](#)

Link Pack Area panel [154](#)

MEM panel [157](#)

NA panel [158](#)

PAG panel [168](#)

PARMLIB panel [169](#)

PC panel [170](#)

PROC panel [176](#)

SMSG panel [192](#), [193](#)

SRCH panel [190](#)

SSI panel [198](#)

SVC panel [199](#)

SYS panel [201](#)

SYSP panel [203](#)

System Symbols panel [200](#)

USI panel [175](#)

VMAP panel [205](#)

PARM default field title

CK panel [118](#)

SYSP panel [203](#)

- PARM panel scope
  - controlling [63](#)
- PARMLen default field title
  - CK panel [118](#)
- PARMLIB panel
  - PARMFLD2 parameter [40](#)
  - PARMFLDS parameter [40](#)
  - variable field list of
    - alternate, defining [40](#)
    - primary, defining [40](#)
- PARTNAM default field title
  - NODE panel [163](#)
- PARTNAM, default field title
  - Job Class panel [133](#)
- PartName default field title
  - MAS and JESPLEX panels [157](#)
  - Spool Volumes panel [189](#)
- PAS default field title
  - COLH panel [101](#)
- Password default field title
  - NS panel [161](#)
- PASSWORD default field title
  - Lines panel [151](#)
- password protection
  - bypassing [12](#)
- PATH default field title
  - FS panel [114](#)
  - NODE panel [163](#)
- pattern matching characters, for PREFIX [15](#)
- PAU default field title
  - Printer panel [173](#)
  - Punch panel [180](#)
- PAVNUM default field title
  - DEV panel [105](#)
- PB abbreviation in column data [49](#)
- PBufAux default field title
  - MAS and JESPLEX panels [157](#)
- PBufCSA default field title
  - MAS and JESPLEX panels [156](#)
- PBufFixed default field title
  - MAS and JESPLEX panels [157](#)
- PC panel
  - PCFLDS parameter [40](#)
  - variable field list of
    - primary, defining [40](#)
- PC panel scope
  - controlling [64](#)
- PC Routines panel [170](#)
- PCNUM default field title
  - PC panel [170](#)
- PD default field title
  - Extended Console panel [114](#)
- PDefault default field title
  - Printer panel [174](#)
- PEAKGRP default field title
  - CFD panel [99](#)
- PEAKMEM default field title
  - CFD panel [99](#)
- PEN default field title
  - NODE panel [162](#)
- PENDING default field title
  - DEV panel [105](#)
- PER default field title
  - Enclave panel [110](#)

- PERCENT default field title
  - Job Delay panel [139](#)
- PERIOD default field title
  - WLM service classes panel [208](#)
- permitting other users to view your jobs [279](#)
- PGMNAME default field title
  - Job Step panel [146](#)
- PGN default field title
  - Enclave panel [110](#)
  - JC panel [131](#)
- PGNM default field title
  - JC panel [132](#)
- PHASE default field title
  - Input Queue panel [125](#)
  - Status panel [196](#)
- PHASENAME default field title
  - Input Queue panel [125](#)
  - Status panel [196](#)
- PI default field title
  - Reader panel [182](#)
- PID default field title
  - Process panel [177](#)
- PKM default field title
  - PC panel [170](#)
- PL default field title
  - JC panel [132](#)
- PLult field title
  - Reader panel [182](#)
- PMGR default field title
  - NODE panel [163](#)
- point-and-shoot
  - custom property [64](#)
- POLACTDATE default field title
  - WLM report class panel [206](#)
  - WLM resource group panel [207](#)
  - WLM Workload panel [209](#)
- POLDESC default field title
  - WLM report class panel [206](#)
  - WLM resource group panel [207](#)
  - WLM service classes panel [209](#)
  - WLM Workload panel [209](#)
- POLICY default field title
  - CFC panel [98](#)
  - Job Device panel [141](#)
- POLNAME default field title
  - CFS panel [100](#)
  - WLM report class panel [206](#)
  - WLM resource group panel [207](#)
  - WLM service classes panel [209](#)
  - WLM Workload panel [209](#)
- POLSIZE default field title
  - CFS panel [100](#)
- POLSTAT default field title
  - CK panel [117](#)
- Port default field title
  - NC panel [160](#)
  - NS panel [161](#)
- PORT default field title
  - Job Data Set panel [136](#)
  - Job Device panel [140](#)
  - LI panel [152](#)
  - NA panel [158](#)
- PORTLOCAL default field title
  - NA panel [159](#)

- PortName default field title [160](#)
- PORTNAME default field title
  - LI panel [152](#)
  - NS panel [161](#)
- POS default field title
  - AD panel [94](#)
  - Address Space Memory panel [96](#)
  - Display Active Users panel [106](#)
  - Input Queue panel [123](#)
  - Status panel [194](#)
- PPATHLEN default field title
  - GT panel [116](#)
- PPID default field title
  - Process panel [178](#)
- PR command
  - authorization to issue [261](#)
- PR panel
  - device name format [64](#)
- pre-SAF exit point [353](#)
- prefix
  - of job names, using to control jobs
    - with ISFPARMS [40](#)
    - with SDSF's internal parameters [32](#)
- PREFIX command
  - adding generic character [57](#), [351](#)
  - authorization to issue [261](#)
- PREFIX parameter [40](#)
- PREq default field title
  - Reader panel [182](#)
- PREVCKPT default field title
  - Multi-Access Spool panel [156](#)
- PRIMARY default field title
  - JES Subsystem [129](#)
  - SSI panel [198](#)
- primary field lists for SDSF panels [47](#), [49](#)
- primary option menu
  - case of [68](#)
- PrimTG default field title
  - MAS and JESPLEX panels [156](#)
- PRINT command
  - default SYSOUT class for [15](#)
  - lines per page [15](#)
- Printer panel
  - authorization to display [261](#)
  - controlling, using job destination name [33](#)
  - variable field list of
    - alternate, defining [47](#)
    - primary, defining [47](#)
- printers
  - authorization to control [215](#), [334](#)
  - controlling
    - by issuing MVS/JES commands [27](#)
- printing
  - controlling lines per page [15](#)
  - custom property [67](#)
- PRINTO default field title
  - Job Data Set panel [138](#)
- PRINTQ default field title
  - Job Data Set panel [138](#)
- PRIO, default field title
  - Job Class panel [133](#)
- PRITRK, default field title
  - Job Class panel [133](#)

- PRIV default field title
  - Address Space Memory panel [96](#)
- Private Storage Subpool panel [175](#)
- PRIVMAX default field title
  - JESInfo panel [128](#)
- PRIVPCT default field title
  - Address Space Memory panel [96](#)
  - JESInfo panel [128](#)
- PRIVSUP default field title
  - JESInfo panel [128](#)
- PRIVUSE default field title
  - Address Space Memory panel [96](#)
  - JESInfo panel [128](#)
- PRMODE default field title
  - Held Output Queue panel [119](#)
  - Job 0 panel [149](#)
  - Job Data Set panel [135](#)
  - Output Queue panel [166](#)
  - Printer panel [171](#)
  - Punch panel [180](#)
- problems
  - management of [497](#)
- PROC default field title
  - Job Step panel [146](#)
- PROC panel [176](#)
- Proc-Lines default field title
  - NC panel [159](#)
- PROC-LINES default field title
  - LI panel [150](#)
  - SO panel [186](#)
- Process panel
  - authorization to display [261](#)
  - variable field list of
    - alternate, defining [41](#)
    - primary, defining [41](#)
- Proclib panel
  - PROCFLD2 parameter [41](#)
  - PROCFLDS parameter [41](#)
  - variable field list of
    - alternate, defining [41](#)
    - primary, defining [41](#)
- PROCNAME default field title
  - CK panel [118](#)
- PROCS default field title
  - AD panel [94](#)
  - Address Space Memory panel [96](#)
- PROCSTEP default field title
  - Display Active Users pane [106](#)
  - Initiator panel [122](#)
  - Job 0 panel [150](#)
  - Job Data Set panel [134](#)
- PROGOFs default field title
  - GT panel [115](#)
- PROGRAM default field title
  - GT panel [115](#)
  - Job Module panel [145](#)
  - JT panel [148](#)
  - USI panel [176](#)
- PROGRAMMER-NAME default field title
  - Held Output Queue panel [120](#)
  - Input Queue panel [124](#)
  - Output Queue panel [166](#)
  - Status panel [195](#)
- PROGRAMPATH default field title

PROGRAMPATH default field title (*continued*)  
     GT panel [116](#)  
 PROMORT default field title  
     JC panel [132](#)  
 PROMOTED default field title  
     Display Active Users panel [108](#)  
     Enclaves panel [111](#)  
 properties for use with the PROPERTY statement [55](#)  
 PROPERTY statement  
     parameters [55](#)  
 PROPLIST statement  
     parameters [55](#)  
 PROT default field title  
     Spool Offload panel [188](#)  
 PRT-PAGE default field title  
     Output Queue panel [166](#)  
 PRT-REC default field title  
     Output Queue panel [165](#)  
 PRTDEF default field title  
     NODE panel [164](#)  
 PRTDEST default field title  
     Input Queue panel [123](#)  
     Reader panel [182](#)  
     Status panel [194](#)  
 PRTFLD2 parameter [41](#)  
 PRTFLDS parameter [41](#)  
 PRTTSO default field title  
     NODE panel [164](#)  
 PRTXWTR default field title  
     NODE panel [164](#)  
 PRTY default field title  
     Held Output Queue panel [119](#)  
     Input Queue panel [123](#)  
     Output Queue panel [165](#)  
     Status panel [194](#)  
 PRVT default field title  
     NODE panel [163](#)  
 PS command  
     authorization to issue [261](#)  
 PS panel scope  
     controlling [64](#)  
 PSEL default field title  
     Printer panel [172](#)  
 PSFLD2 parameter [41](#)  
 PSFLDS parameter [41](#)  
 PTracks default field title  
     Spool Volumes panel [189](#)  
 PTrackU default field title  
     Spool Volumes panel [189](#)  
 PTYPE default field title  
     NODE panel [163](#)  
 PUN command  
     authorization to issue [261](#)  
 PUN panel  
     device name format [64](#)  
     variable field list [178](#)  
     variable field list of [179](#)  
 Punch panel  
     authorization to display [261](#)  
 punches  
     authorization to control [336](#)  
     protecting with SAF [335](#)  
 PUNDEF default field title  
     NODE panel [164](#)

PUNDEST default field title  
     Reader panel [182](#)  
 PUNFLD parameter [41](#)  
 PUNFLD2 parameter [41](#)  
 PURGE (\$C) command  
     authorization with SAF [215](#)  
 PWCNTL default field title  
     NODE panel [164](#)

## Q

QALERTPCT default field title  
     Extended Console panel [113](#)  
 QDEPTH default field title  
     Extended Console panel [113](#)  
 QHLD default field title  
     JC panel [131](#)  
 QINTENS default field title  
     DEV panel [105](#)  
 QJOBNAME default field title  
     FS panel [115](#)  
 QLIMIT default field title  
     Extended Console panel [113](#)  
 QPID default field title  
     FS panel [115](#)  
 QSYSNAME default field title  
     FS panel [115](#)  
 query character, specifying [14](#)  
 QUERY MODULE command [497](#)  
 QUEUE default field title  
     SR panel [204](#)  
     Status panel [194](#)  
 QUEUE Default field title  
     Job 0 panel [149](#)  
     Job Data Set panel [137](#)  
 QUIESCE default field title  
     Display Active Users panel [107](#)  
     Enclave panel [110](#)

## R

RACF  
     brief summary of commands [219](#)  
     conditional access [222](#)  
     creating a resource group profile [220](#)  
     delegation of authority [220](#)  
     establishing security [221](#)  
     security administration [219](#)  
     using RACLIST [221](#), [222](#)  
     using RACLIST REFRESH [221](#), [222](#)  
 RACLIST [221](#), [222](#), [280](#), [281](#)  
 RALEVEL default field title  
     Reader panel [182](#)  
 RB default field title  
     JT panel [148](#)  
 RD-DATE default field title  
     Held Output Queue panel [120](#)  
     Input Queue panel [124](#)  
     Output Queue panel [167](#)  
     Status panel [195](#)  
 RD-TIME default field title  
     Held Output Queue panel [120](#)  
     Input Queue panel [124](#)

RD-TIME default field title *(continued)*  
 Output Queue panel [167](#)  
 Status panel [195](#)  
 RDR panel  
 device name format [64](#)  
 variable field list [181](#)  
 variable field list of [181](#)  
 Reader panel  
 authorization to display [261](#)  
 readers  
 protecting with SAF [336](#)  
 READY value [29](#)  
 REAL default field title  
 Address Space Memory panel [95](#)  
 Display Active Users Panel [106](#)  
 REALAFC default field title  
 Address Space Memory panel [96](#)  
 CSR panel [104](#)  
 SYS panel [201](#)  
 REALAFCB default field title  
 SYS panel [201](#)  
 REASON default field title  
 CK panel [118](#)  
 REBLDPCT default field title  
 CFS panel [100](#)  
 REC-CNT default field title  
 Job 0 panel [150](#)  
 Job Data Set panel [134](#)  
 Printer panel [171](#)  
 Punch panel [179](#)  
 Reader panel [181](#)  
 REC-PROC default field title  
 Reader panel [181](#)  
 REC-PRT default field title  
 Printer panel [171](#)  
 Punch panel [179](#)  
 RECEIVE default field title  
 NODE panel [162](#)  
 RECFM default field title  
 Authorized Program Facility panel [97](#)  
 Job 0 panel [150](#)  
 Job Data Set panel [137](#)  
 Job DDName panel [142](#)  
 Job Device panel [140](#)  
 Link List panel [153](#)  
 Link Pack Area panel [154](#)  
 PARMLIB panel [169](#)  
 PROC panel [177](#)  
 SRCH panel [191](#)  
 RECPERTRK default field title  
 Spool Volumes panel [189](#)  
 RECVCNT default field title  
 XCF Members and Groups panel [210](#)  
 REFDATE default field title  
 Authorized Program Facility panel [97](#)  
 Link List panel [153](#)  
 Link Pack Area panel [154](#)  
 PARMLIB panel [169](#)  
 PROC panel [177](#)  
 SRCH panel [191](#)  
 REFNAME default field title  
 SYSP panel [204](#)  
 REFRESH [221](#), [222](#)  
 Region default field title

Region default field title *(continued)*  
 Reader panel [182](#)  
 REGION default field title  
 JC panel [132](#)  
 Job Step panel [147](#)  
 REGIONU default field title  
 Job Step panel [147](#)  
 RelConn default field title  
 NC panel [160](#)  
 RELEASE (\$A) command  
 authorization to issue [215](#)  
 RELEASE (\$O) command  
 authorization to issue [215](#)  
 RELEASE default field title  
 CMDH panel [101](#)  
 RENT default field title  
 Job Module panel [146](#)  
 REPC panel  
 REPCFLDS parameter [42](#)  
 variable field list of  
 primary, defining [42](#)  
 REPEAT (\$N) command  
 authorization to issue [215](#)  
 Repeat-Find PF key  
 problems with [499](#)  
 reply messages  
 protecting with SAF [345](#)  
 REQSTATE default field title  
 RES panel [183](#)  
 REQTIME default field title  
 Enqueue panel [112](#)  
 REQTYPE default field title  
 Enqueue panel [112](#)  
 requests  
 protecting with SAF [345](#)  
 RESDESC default field title  
 JESInfo panel [128](#)  
 Reserved default field title  
 Spool Volumes panel [190](#)  
 RESET (E) command  
 authorization to issue, specifying [215](#)  
 RESFLD2 parameter [42](#)  
 RESFLDS parameter [42](#)  
 RESGROUP default field title  
 Display Active Users panel [107](#)  
 Enclave panel [110](#)  
 WLM service classes panel [208](#)  
 RESID default field title  
 Job Device panel [141](#)  
 NA panel [158](#)  
 RESOURCE default field title  
 ACTH panel [93](#)  
 CMDH panel [101](#)  
 COLH panel [101](#)  
 resource group class  
 GSDSF [220](#)  
 RACLIST [220](#)  
 Resource Monitor Alerts panel  
 variable field list [184](#)  
 Resource Monitor panel  
 authorization to display [261](#)  
 RMFLD2 parameter [42](#)  
 RMFLDS parameter [42](#)  
 variable field list [183](#)



- Resource Monitor panel (*continued*)
  - variable field list of
    - primary, defining [42](#)
- Resource panel
  - variable field list [183](#)
  - variable field list of
    - alternate, defining [47](#)
    - primary, defining [47](#)
- resources [183](#), [184](#)
- RESPONSE default field title
  - DEV panel [105](#)
- RESSHORT default field title
  - JESInfo panel [128](#)
- Rest default field title
  - NC panel [160](#)
- REST default field title
  - Lines panel [151](#)
  - NODE panel [162](#)
- Rest-Int default field title
  - LI panel [152](#)
  - NS panel [161](#)
- RESTART (\$E) command
  - authorization to issue, specifying [215](#)
- Restart default field title
  - NS panel [161](#)
- RESTART default field title
  - LI panel [152](#)
- ResType default field title
  - Initiator panel [122](#)
- RESULT default field title
  - CK panel [117](#)
  - CKH panel [116](#)
- RESVPCT default field title
  - DEV panel [105](#)
- RETADDR default field title
  - SVC panel [200](#)
- RETAINF default field title
  - Job Data Set panel [138](#)
- RETAINS default field title
  - Job Data Set panel [138](#)
- RETRYL default field title
  - Job Data Set panel [138](#)
- RETRYT default field title
  - Job Data Set panel [138](#)
- RETURN default field title
  - JCS panel [134](#)
- REUS default field title
  - Display Active Users panel [108](#)
  - Job Module panel [146](#)
- REXXHLQ default field title
  - CK panel [118](#)
- REXXIN default field title
  - CK panel [118](#)
- REXXOUT default field title
  - CK panel [118](#)
- RFIND NOT ACTIVE message, ISPF [499](#)
- RGRP panel
  - RGRPFLDS parameter [42](#)
  - variable field list of
    - primary, defining [42](#)
- RM command
  - authorization to issue [261](#)
- RMA panel
  - RMAFLDS parameter [42](#)

- RMA panel (*continued*)
  - variable field list of
    - primary, defining [42](#)
- RMF (Resource Measurement Facility)
  - bypassing [351](#)
  - Display Active Users panel [105](#)
  - exit not installed [500](#)
  - migration considerations [358](#)
  - services, protecting [358](#)
- RMF default field title
  - CMDH panel [101](#)
- RMLEVEL default field title
  - Reader panel [182](#)
- RMODE default field title
  - Job Module panel [146](#)
- RMT default field title
  - Held Output Queue panel [119](#)
  - Input Queue panel [123](#)
  - Job Data Set panel [135](#)
  - Output Queue panel [166](#)
  - Printer panel [173](#)
- RMTSHR default field title
  - LI panel [151](#)
- RNAMEL default field title
  - Enqueue panel [112](#)
- RNUM default field title
  - Held Output Queue panel [120](#)
  - Input Queue panel [124](#)
  - Output Queue panel [166](#)
  - Status panel [195](#)
- ROOM default field title
  - Job Data Set panel [136](#)
- ROUTCDE default field title
  - Extended Console panel [114](#)
- ROUTCDEX default field title
  - Extended Console panel [114](#)
- ROUTE (\$R) command
  - authorization to issue, specifying [215](#)
- ROUTECD default field title
  - SR panel [204](#)
- routing codes
  - and WTOR messages displayed on the SYSLOG [24](#)
- RPRIO default field title
  - Reader panel [182](#)
- RPRIVSUP default field title
  - JESInfo panel [128](#)
- RPTCLASS default field title
  - Display Active Users panel [107](#)
  - Enclave panel [110](#)
- RSID default field title
  - Multi-Access Spool panel [156](#)
- RST default field title
  - JC panel [132](#)
- RSYS command
  - authorization to issue [261](#)
- RTPD default field title
  - Spool Offload panel [188](#)
- RUID default field title
  - Process panel [178](#)

## S

SAF



- SAF (*continued*)
  - grouping class [220](#)
  - using to define group membership [17](#)
- SAF logging
  - custom property [67](#)
- SAF security
  - access authority [215](#)
  - action characters [225](#), [250–259](#)
  - address space diagnostics [265](#)
  - APF [260](#)
  - auditing requests [213](#)
  - Authorized program facility data sets [260](#)
  - CF structures [266](#)
  - checks on the CK and CKH panels [267](#)
  - classes [215](#)
  - coupling facility (CF) connections [265](#)
  - coupling facility (CF) data sets [266](#)
  - DEST command [268](#)
  - destination names [268](#)
  - destination operator authority [269](#)
  - DEV [265](#), [266](#), [270](#), [273](#), [286](#), [339](#), [340](#), [342](#)
  - Device activity information [270](#)
  - devices used by a job [277](#)
  - Dynamic exit information [271](#)
  - DYNX [271](#)
  - EMCS [271](#), [277](#)
  - EMCS consoles information [271](#)
  - enclaves [272](#)
  - ENQ [272](#)
  - Enqueue information [272](#)
  - establishing
    - broad access considerations [221](#)
    - conditional access [222](#)
    - RACLIST command [221](#), [222](#)
    - REFRESH command [221](#), [222](#)
  - File system information [273](#)
  - generated MVS and JES commands [226](#), [229](#), [291](#)
  - Generic tracker events [273](#)
  - initiators [274](#)
  - JES subsystems on the JES panel [276](#)
  - JES2 resources on the RM panel [274](#)
  - JESInfo on the JRI panel [281](#)
  - JESInfo subsystems on the JRI panel [281](#)
  - JESPLEX members [283](#)
  - JESSPOOL class [269](#), [278](#)
  - Job class members [277](#)
  - job classes [276](#)
  - job groups [278](#)
  - job steps [278](#)
  - jobs [278](#)
  - jobs, devices used by [277](#)
  - lines [282](#)
  - Link list data sets [283](#)
  - Link list sets [283](#)
  - LLS [283](#)
  - LNK [283](#)
  - MAS members [283](#)
  - memory contents [285](#)
  - MVS and JES commands on command line [285](#)
  - Network activity [286](#)
  - network connections [287](#)
  - network servers [287](#)
  - nodes [288](#)
  - offloaders [334](#), [340](#), [341](#)

- SAF security (*continued*)
  - OMVS [289](#)
  - OMVS options [289](#)
  - output groups [278](#)
  - overtimeable fields [290](#), [331](#)
  - PAG [332](#)
  - Page data sets [332](#)
  - PARM [332](#)
  - PARM data sets [332](#)
  - permitting other users to view your data [279](#)
  - printers [333](#)
  - PROC [335](#)
  - Proclibs [335](#)
  - protecting SDSF tasks [215](#)
  - punches [335](#)
  - readers [336](#)
  - Resource monitor alerts [337](#)
  - resource names [215](#), [503](#)
  - RMA [337](#)
  - scheduling environments [338](#)
  - SDSF commands [261](#)
  - SDSF resources [214](#), [225](#)
  - server [338](#)
  - SMS storage groups [339](#)
  - SMS volumes [340](#)
  - Subsystems [342](#)
  - supplementing [349](#)
  - SYM [343](#)
  - SYS [343](#)
  - SYSIN/SYSOUT data sets [278](#)
  - SYSLOG [342](#)
  - System information [343](#)
  - system parameters [342](#)
  - system requests [345](#)
  - System Symbol information [343](#)
  - Table of SDSF Resource Names [503](#)
  - WLM enclaves [272](#)
  - WLM resources [337](#)
  - XCF [346](#)
  - XCF groups and members [346](#)
- SAFF default field title
  - Input Queue panel [123](#)
  - Reader panel [182](#)
  - Spool Volumes panel [189](#)
  - Status panel [194](#)
- SAMP default field title
  - Job Delay panel [138](#)
- sample
  - ISFPARMS module [7](#)
- Sampling interval
  - setting [87](#)
- SAMPTIME default field title
  - JESInfo by Job panel [129](#)
  - JESInfo panel [128](#)
- SASN default field title
  - PC panel [170](#)
- SBURST default field title
  - Printer panel [172](#)
  - Spool Offload panel [186](#)
- scaling, numeric values [49](#)
- SCHARS parameter [15](#)
- SCHDATE default field title
  - CK panel [118](#)
- SCHDELAY default field title

SCHDELAY default field title (*continued*)

Input Queue panel [126](#)

Status panel [197](#)

Scheduling Environment panel

variable field list of

alternate, defining [47](#)

primary, defining [47](#)

scheduling environments [185](#)

Scheduling-Env default field title

JC panel [132](#)

SCHENV

RES panel [183](#)

SCHENV default field title

Input Queue panel [124](#)

Job Group panel [143](#)

Status panel [195](#)

SCHINT default field title

CK panel [118](#)

SCLASS default field title

Printer panel [171](#)

Punch panel [179](#)

Spool Offload panel [186](#)

SCLASS1-8 default field title

Spool Offload panel [188](#)

SCN default field title

JC panel [132](#)

SCOPE default field title

Enclave panel [110](#)

Enqueue panel [112](#)

RM panel [184](#)

SCPU default field title

Display Active Users panel [107](#)

screen size

specifying maximum supported [15](#)

SCRSIZE parameter [15](#)

SCSAPCT default field title

Address Space Memory panel [96](#)

CSR panel [104](#)

SDEPTH, default field title

Job Class panel [133](#)

SDEST1 default field title

Printer panel [172](#)

Punch panel [179](#)

Spool Offload panel [186](#)

SDEST2 default field title

Printer panel [172](#)

SDEST2-4 default field titles

Punch panel [179](#)

SDEST3 default field title

Printer panel [172](#)

SDEST4 default field title

Printer panel [172](#)

SDISP default field title

Spool Offload panel [186](#)

SDSF, multiple instances of [356](#)

SE panel [185](#)

search characters [15](#)

Search panel [190](#)

SecLabel default field title

Display Active Users panel [107](#)

Initiator panel [122](#)

Process panel [178](#)

Reader panel [182](#)

SECLABEL default field title

SECLABEL default field title (*continued*)

Held Output Queue panel [119](#)

Input Queue panel [123](#)

Job 0 panel [149](#)

Job Data Set panel [135](#)

Job Group panel [143](#)

Output Queue panel [166](#)

Printer panel [171](#)

Punch panel [180](#)

Status panel [194](#)

secondary JES2 subsystems [356](#)

SECSAPCT default field title

Address Space Memory panel [96](#)

CSR panel [104](#)

SecTG default field title

MAS and JESPLEX panels [156](#)

SECTRK, default field title

Job Class panel [133](#)

Secure default field title

NC panel [160](#)

NS panel [161](#)

SECURE default field title

LI panel [152](#)

NODE panel [164](#)

SEFLD2 parameter [43](#)

SEFLDS parameter [43](#)

SEGID default field title

Job 0 panel [149](#)

Job Data Set panel [135](#)

Sel default field title

Spool Volumes panel [190](#)

SELECT default field title

Printer panel [175](#)

Punch panel [180](#)

SELECT Default field title

Job 0 panel [150](#)

Job Data Set panel [137](#)

SELECT-RANGE default field title

Spool Offload panel [186](#)

SELECTKEY default field title

CS panel [102](#)

SelectModeName default field title

MAS and JESPLEX panels [157](#)

SELMODE default field title

Job Class Members panel [131](#)

SELMODE, default field title

Job Class panel [133](#)

SENDCNT default field title

XCF Members and Groups panel [210](#)

sending to IBM

reader comments [xxvii](#)

SENDP default field title

NODE panel [163](#)

SENTRS default field title

NODE panel [162](#)

SEP default field title

Printer panel [171](#)

Punch panel [179](#)

SEPCHAR default field title

Printer panel [173](#)

SEPDS default field title

Printer panel [171](#)

Punch panel [179](#)

SEQ default field title

SEQ default field title (*continued*)  
 Authorized Program Facility panel [97](#)  
 Dynamic Exits panel [109](#)  
 Link List panel [153](#)  
 Link List sets panel [153](#)  
 Link Pack Area panel [154](#)  
 Link Pack Directory panel [155](#)  
 PARMLIB panel [169](#)  
 PROC panel [176](#)  
 SRCH panel [191](#)  
 SSI panel [198](#)  
 VMAP panel [205](#)  
 SEQMAX default field title  
 Dynamic Exits panel [109](#)  
 PROC panel [177](#)  
 SEQNUM default field title  
 PC panel [170](#)  
 SEQUENCE default field title  
 Job DDName panel [142](#)  
 Job Device panel [140](#)  
 SERV default field title  
 Job Step panel [147](#)  
 server  
 accessing [74](#)  
 changing options [79](#)  
 DISPLAY command [84](#), [497](#)  
 group  
 displaying information about [84](#)  
 starting communications [88](#)  
 input to [74](#)  
 introduction [73](#)  
 logging [75](#)  
 multiple servers on a system [73](#)  
 operator commands [75](#)  
 options [75](#)  
 processing statements [74](#)  
 protecting with SAF [338](#)  
 REFRESH command [85](#)  
 REFRESH JES command [86](#)  
 REFRESH SYS command [86](#)  
 refreshing ISFPARMS [85](#)  
 refreshing list of JES subsystems [86](#)  
 refreshing list of z/OS systems [86](#)  
 registering with ARM [75](#)  
 security [75](#)  
 START,COMM command [88](#)  
 starting [75](#)  
 STOP,COMM command [89](#)  
 stopping [89](#)  
 stopping communications [89](#)  
 XCF [16](#)  
 SERVER default field title  
 Display Active Users panel [107](#)  
 Process panel [178](#)  
 SERVER parameter  
 SAF authorization for [261](#)  
 SERVICE default field title  
 JES Subsystem [130](#)  
 SESQAPCT default field title  
 Address Space Memory panel [96](#)  
 CSR panel [104](#)  
 SESSION default field title  
 LI panel [151](#)  
 SETNAME default field title

SETNAME default field title (*continued*)  
 Link List sets panel [152](#)  
 Link Listpanel [153](#)  
 SETSSI default field title  
 SSI panel [198](#)  
 SETUP default field title  
 Printer panel [173](#)  
 Punch panel [180](#)  
 SEVCODE default field title  
 CK panel [117](#)  
 SEVERITY default field title  
 CK panel [117](#)  
 SFCB default field title  
 Printer panel [171](#)  
 Spool Offload panel [186](#)  
 SFLH default field title  
 Printer panel [172](#)  
 Spool Offload panel [186](#)  
 SFORM2 default field title  
 Punch panel [179](#)  
 Spool Offload panel [186](#)  
 SFORM2-8 default field title  
 Printer panel [171](#)  
 SFORM3 default field title  
 Punch panel [179](#)  
 Spool Offload panel [186](#)  
 SFORM4 default field title  
 Punch panel [179](#)  
 Spool Offload panel [186](#)  
 SFORM5 default field title  
 Punch panel [179](#)  
 Spool Offload panel [186](#)  
 SFORM6 default field title  
 Punch panel [179](#)  
 Spool Offload panel [186](#)  
 SFORM7 default field title  
 Punch panel [179](#)  
 Spool Offload panel [186](#)  
 SFORM8 default field title  
 Punch panel [179](#)  
 Spool Offload panel [186](#)  
 SFORMS default field title  
 Printer panel [171](#)  
 Punch panel [179](#)  
 Spool Offload panel [186](#)  
 SHARED default field title  
 Job Memory Objects panel [145](#)  
 USI panel [176](#)  
 shared spool [155](#)  
 SHOLD default field title  
 Spool Offload panel [186](#)  
 shortcut keys [519](#)  
 SHRMO default field title  
 Address Space Memory panel [95](#)  
 SHRMOHWM default field title  
 Address Space Memory panel [95](#)  
 SHRMONUM default field title  
 Address Space Memory panel [95](#)  
 SID default field title  
 MAS panel [155](#)  
 Multi-Access Spool panel [155](#)  
 SIGZERO default field title  
 COLH panel [101](#)

SINCE default field title  
     COLH panel [101](#)  
 SIO default field title  
     Display Active Users Panel [106](#)  
     SYS panel [201](#)  
 SIZE default field title  
     CFS panel [99](#)  
     CKPT panel [127](#)  
     Job Memory Objects panel [145](#)  
     VMAP panel [205](#)  
 SIZE% default field title  
     CFS panel [99](#)  
 SIZEPCT default field title  
     CKPT panel [127](#)  
 SIZETRK default field title  
     CKPT panel [127](#)  
 SIZEUSED default field title  
     CKPT panel [127](#)  
 SJOBNAME default field title  
     Printer panel [172](#)  
     Punch panel [179](#)  
     Spool Offload panel [186](#)  
 Slash command  
     modifying the character used [57](#)  
     modifying the number of stored commands [57](#)  
 SLCPU default field title  
     Display Active Users panel [108](#)  
 SLEVEL default field title  
     MAS and JESPLEX panels [156](#)  
 SLOTS default field title  
     PAG panel [168](#)  
 SMALLENV default field title  
     JESInfo panel [128](#)  
 SMC default field title  
     Enqueue panel [112](#)  
 SMF default field title  
     SYS panel [202](#)  
 SMS default field title  
     Authorized Program Facility panel [97](#)  
     Job DDName panel [142](#)  
     Job Device panel [141](#)  
     Link List panel [153](#)  
     Link Pack Area panel [154](#)  
     PARMLIB panel [169](#)  
     PROC panel [177](#)  
     SRCH panel [191](#)  
 SMS Groups panel [192](#)  
 SMS Volumes panel [193](#)  
 SMSG panel  
     MSGFLDS parameter [43](#)  
     variable field list of  
         primary, defining [43](#)  
 SMSG panel scope  
     controlling [65](#)  
 SMSV panel  
     MSVFLDS parameter [43](#)  
     variable field list of  
         primary, defining [43](#)  
 SMSV panel scope  
     controlling [65](#)  
 SNODE1 default field title  
     Printer panel [174](#)  
 SNODE2 default field title  
     Printer panel [174](#)  
 SNODE3 default field title  
     Printer panel [174](#)  
 SNODE4 default field title  
     Printer panel [174](#)  
 SO command  
     authorization to issue [261](#)  
 Socket default field title  
     NS panel [161](#)  
 SOCKETN default field title  
     LI panel [151](#)  
 SODISP default field title  
     LI panel [152](#)  
     Spool Offload panel [186](#)  
 SODISP2 default field title  
     LI panel [152](#)  
     Spool Offload panel [186](#)  
 SODISP3 default field title  
     LI panel [152](#)  
     Spool Offload panel [186](#)  
 SODISP4 default field title  
     LI panel [152](#)  
     Spool Offload panel [186](#)  
 SODsp default field title  
     NC panel [160](#)  
 SOFLD2 parameter [43](#)  
 SOFLDS parameter [43](#)  
 SOLUTIONID default field title  
     WLM resource group panel [208](#)  
 SOURCE default field title  
     GT panel [115](#)  
     Job Delay panel [138](#)  
 SOURCEPATH default field title  
     GT panel [116](#)  
 SOWNER default field title  
     Printer panel [172](#)  
     Punch panel [180](#)  
     Spool Offload panel [186](#)  
 SP command  
     authorization to issue [261](#)  
 SP default field title  
     Display Active Users panel [107](#)  
     JCS panel [133](#)  
 SPAGING default field title  
     Display Active Users panel [106](#)  
 SPATHLEN default field title  
     GT panel [116](#)  
 SPEED default field title  
     Lines panel [151](#)  
 SPIN default field title  
     Display Active Users panel [107](#)  
     Input Queue panel [125](#)  
 SPIN Default field title  
     Job 0 panel [149](#)  
     Job Data Set panel [137](#)  
 SPINNABLE default field title  
     Job Data Set panel [137](#)  
 spool data set  
     data sets, number of supported by SDSF [14](#)  
     password protecting [12](#)  
     RACF protecting [12](#)  
     specifying prefix for [14](#)  
 Spool Offload panel  
     authorization to display [261](#)  
     variable field list [185](#)

- Spool Offload panel (*continued*)
  - variable field list of
    - alternate, defining [47](#)
    - primary, defining [47](#)
- spool offloaders
  - protecting with SAF [334](#), [340](#), [341](#)
  - SAF authorization [218](#)
- Spool Volumes panel
  - authorization to display [261](#)
  - SPFLD2 parameter [44](#)
  - SPFLDS parameter [43](#)
  - variable field list [188](#)
  - variable field list of
    - alternate, defining [44](#)
    - primary, defining [43](#)
- SPOOLPCT default field title
  - SYS panel [201](#)
- SPRMODE1 default field title
  - Printer panel [172](#)
  - Punch panel [179](#)
  - Spool Offload panel [186](#)
- SPRMODE2 default field title
  - Printer panel [172](#)
- SPRMODE2-4 default field titles
  - Punch panel [179](#)
- SPRMODE3 default field title
  - Printer panel [172](#)
- SPRMODE4 default field title
  - Printer panel [172](#)
- SQA default field title
  - Address Space Memory panel [95](#)
  - CSR panel [104](#)
- SQAPCT default field title
  - Address Space Memory panel [95](#)
  - CSR panel [104](#)
  - SYS panel [201](#)
- SR command
  - authorization to issue [261](#)
- SR default field title
  - LI panel [151](#)
- SR panel scope
  - controlling [65](#)
- SRANGE default field title
  - Printer panel [172](#)
  - Punch panel [180](#)
- SRBTIME default field title
  - Job Step panel [147](#)
- SRCH panel
  - SRCH parameter [44](#)
  - variable field list of
    - alternate, defining [44](#)
    - primary, defining [44](#)
- SRFLD2 parameter [44](#)
- SRFLDS parameter [44](#)
- SNum default field title
  - NC panel [159](#)
- SRNUM default field title
  - NODE panel [164](#)
- SRout1 default field title
  - Printer panel [174](#)
- SRout2 default field title
  - Printer panel [174](#)
- SRout3 default field title
  - Printer panel [174](#)
- SRout4 default field title
  - Printer panel [174](#)
- SRVC panel
  - SRVCLDS parameter [44](#)
  - variable field list of
    - primary, defining [44](#)
- SrvClass default field title
  - Initiator panel [122](#)
- SRVCLASS default field title
  - Enclave panel [110](#)
  - Input Queue panel [124](#)
  - Status panel [194](#)
- SrvJobNm default field title
  - NS panel [161](#)
- SrvName default field title [160](#)
- SSAFF default field title
  - Spool Offload panel [186](#)
- SSCHEDULING—ENV default field title
  - Spool Offload panel [187](#)
- SSCHRATE default field title
  - DEV panel [105](#)
- SSCP default field title
  - SYS panel [203](#)
- SSCT default field title
  - JES Subsystem [130](#)
  - SSI panel [198](#)
- SSCTSUS2 default field title
  - SSI panel [198](#)
- SSCTSUSE default field title
  - SSI panel [198](#)
- SSI panel
  - SSIFLDS parameter [44](#)
  - variable field list of
    - primary, defining [44](#)
- SSI panel scope
  - controlling [65](#)
- SSIGNON default field title
  - NODE panel [163](#)
- SSMODE default field title
  - Input Queue panel [124](#)
- SSNAME default field title
  - Display Active Users panel [108](#)
- SSQAPCT default field title
  - Address Space Memory panel [96](#)
  - CSR panel [104](#)
- SSRVCLASS default field title
  - Spool Offload panel [187](#)
- SSTYPE default field title
  - Enclave panel [110](#)
- SSVT default field title
  - SSI panel [198](#)
- SSWITCH default field title
  - PC panel [170](#)
- ST command
  - adding generic character [58](#), [351](#)
  - authorization to issue [261](#)
- ST default field title
  - LI panel [151](#)
- ST-DATE default field title
  - Held Output Queue panel [120](#), [124](#)
  - Input Queue panel [124](#)
  - Output Queue panel [167](#)
  - Status panel [195](#)
- ST-TIME default field title

ST-TIME default field title (*continued*)  
 Held Output Queue panel [120](#)  
 Input Queue panel [124](#)  
 Output Queue panel [167](#)  
 Status panel [195](#)  
 Stack default field title  
 NS panel [161](#)  
 STACK default field title  
 Job Device panel [141](#)  
 NA panel [158](#)  
 STALLED default field title  
 XCF Members and Groups panel [210](#)  
 START (\$S) command  
 authorization to issue [215](#)  
 START default field title  
 Job Memory Objects panel [144](#)  
 VMAP panel [205](#)  
 Start-Date-Time default field  
 title  
 MAS and JESPLEX panels [156](#)  
 Start-Type default field title  
 MAS and JESPLEX panels [156](#)  
 STARTBY default field title  
 Input Queue panel [125](#)  
 Status panel [196](#)  
 STATDATE default field title  
 SYS panel [203](#)  
 XCF Members and Groups panel [210](#)  
 STATE default field title  
 CK panel [117](#)  
 Process panel [177](#)  
 STATIC default field title  
 PROC panel [177](#)  
 Status default field title  
 NC panel [159](#)  
 STATUS default field title  
 Authorized Program Facility panel [97](#)  
 CFC panel [98](#)  
 CFS panel [99](#)  
 CK panel [117](#)  
 CKH panel [116](#)  
 CSI panel [103](#)  
 Display Active Users panel [106](#)  
 Enclave panel [110](#)  
 Enqueue panel [112](#)  
 Extended Console panel [113](#)  
 FS panel [114](#)  
 Held Output Queue panel [119](#)  
 Initiator panel [121](#)  
 Input Queue panel [123](#)  
 JES Subsystem [130](#)  
 JESPLEX panel [155](#)  
 Job Dependencies panel [139](#)  
 Job Group panel [143](#)  
 LI panel [150](#)  
 Link List sets panel [153](#)  
 NA panel [158](#)  
 NODE panel [162](#)  
 NS panel [161](#)  
 OMVS options panel [165](#)  
 Output Queue panel [166](#)  
 PAG panel [168](#)  
 Printer panel [171](#)  
 PROC panel [177](#)

STATUS default field title (*continued*)  
 Process panel [177](#)  
 PUN panel [179](#)  
 RDR panel [181](#)  
 RM panel [183](#)  
 SMSG panel [192](#)  
 SMSV panel [193](#)  
 Spool Offload panel [185](#)  
 Spool Volumes panel [189](#)  
 SRCH panel [191](#)  
 SSI panel [198](#)  
 Status panel [194](#)  
 USI panel [176](#)  
 STATUS field  
 JC panel [131](#)  
 Status panel  
 authority to display [261](#)  
 jobs displayed on, controlling  
 by destination name [33](#)  
 by job name [34](#), [47](#)  
 by job name prefix [40](#)  
 by owner [39](#)  
 variable field list of  
 alternate, defining [47](#)  
 primary, defining [47](#)  
 STATUSNUM default field title  
 FS panel [114](#)  
 STC default field title  
 PROC panel [177](#)  
 STC value [29](#)  
 STCB default field title  
 JT panel [148](#)  
 STCID default field title  
 CK panel [118](#)  
 STCNUM default field title  
 SYS panel [201](#)  
 STDATE default field title  
 Address Space Memory panel [96](#)  
 Display Active Users panel [108](#)  
 STEPN default field title  
 AD panel [94](#)  
 Address Space Memory panel [96](#)  
 STEPNAME default field title  
 Display Active Users panel [106](#)  
 Initiator panel [122](#)  
 Job 0 panel [150](#)  
 Job Data Set panel [134](#)  
 Job Step panel [146](#)  
 STEPNUM default field title  
 Job Data Set panel [137](#)  
 Job Step panel [147](#)  
 STFLD2 parameter [44](#)  
 STFLDS parameter [44](#)  
 STIME default field title  
 Job Device panel [141](#)  
 NA panel [158](#)  
 STMT default field title  
 RM panel [184](#)  
 STNum default field title  
 NC panel [159](#)  
 STNUM default field title  
 NODE panel [163](#)  
 STOKEN default field title  
 CFC panel [98](#)

STOKEN default field title (*continued*)  
     Dynamic Exits panel [109](#)  
 STOP (\$P) command  
     authorization to issue [215](#)  
 STOP command [89](#)  
 stopping the server [89](#)  
 STORAGE default field title  
     JT panel [148](#)  
 STORCRIT default field title  
     Display Active Users panel [107](#)  
 STORGRP default field title  
     DEV panel [105](#)  
     MSG panel [192](#)  
     MSV panel [193](#)  
 STORPROT default field title  
     WLM service classes panel [208](#)  
 STREAM default field title  
     NODE panel [164](#)  
 STRNAME default field title  
     CFC panel [98](#)  
     CFS panel [99](#)  
     CKPT panel [127](#)  
     Job Device panel [140](#)  
 STRTYPE default field title  
     CFC panel [98](#)  
     CFS panel [99](#)  
     JCS panel [133](#)  
 STT default field title  
     Spool Volumes panel [190](#)  
 Stunted default field title  
     Spool Volumes panel [190](#)  
 SUBCHAN default field title  
     PAG panel [169](#)  
 SUBFIELDS default field title  
     COLH panel [101](#)  
 SubGroup default field title  
     Held Output Queue panel [120](#)  
     Input Queue panel [125](#)  
     Output Queue panel [167](#)  
     Status panel [196](#)  
 SUBNET default field title  
     NODE panel [163](#)  
 SUBPOOL default field title  
     CS panel [102](#)  
     CSI panel [103](#)  
     Job Memory panel [144](#)  
     Job Module panel [145](#)  
     USI panel [176](#)  
 SUBSYS default field title  
     AD panel [94](#)  
     Address Space Memory panel [96](#)  
     Enclave panel [110](#)  
 subsystem name, JES2, specifying [14](#)  
 subsystem name, JES3, specifying [14](#), [355](#)  
 Subsystem panel [198](#)  
 SUBUSER default field title  
     Input Queue panel [125](#)  
     Status panel [196](#)  
 SUCS default field title  
     Printer panel [171](#)  
     Spool Offload panel [187](#)  
 summary of changes [xxix](#)  
 SUS default field title  
     Punch panel [180](#)  
 SUSPEND default field title  
     Printer panel [175](#)  
 SVC panel  
     SVCFLDS parameter [45](#)  
     variable field list of  
         primary, defining [45](#)  
 SVC panel scope  
     controlling [66](#)  
 SVC routines panel [199](#)  
 SVOL default field title  
     Printer panel [174](#)  
     Punch panel [180](#)  
     Spool Offload panel [186](#)  
 SVOL2 default field title  
     Printer panel [174](#)  
 SVOL2-4 default field title  
     Punch panel [180](#)  
 SVOL3 default field title  
     Printer panel [174](#)  
 SVOL4 default field title  
     Printer panel [174](#)  
 SWA default field title  
     JC panel [132](#)  
     Reader panel [182](#)  
 SWAP default field title  
     Job Step panel [147](#)  
 SWAPR default field title  
     AD panel [94](#)  
     Address Space Memory panel [96](#)  
     Display Active Users panel [106](#)  
 SWAPS default field title  
     Job Step panel [147](#)  
 SWRITER default field title  
     Printer panel [171](#)  
     Punch panel [179](#)  
 SWRITER. default field title  
     Spool Offload panel [187](#)  
 SYM panel scope  
     controlling [66](#)  
 symbols, using in ISFPARMS [12](#)  
 SYNCTOL default field title  
     Multi-Access Spool panel  
         [156](#)  
 SYS panel scope  
     custom property [66](#)  
 SYSAFF default field title  
     Job Group panel [143](#)  
 SYSCONS default field title  
     Extended Console panel [114](#)  
 SYSH default field title  
     WLM service classes panel [209](#)  
 SYSID (system ID)  
     parameter in ISFPARMS [45](#)  
     specifying in Multi-Access Spool environment  
         [45](#)  
     system ID of, specifying [45](#)  
 SYSID command  
     authorization to issue [261](#)  
 SysID default field title  
     NC panel [160](#)  
     NODE panel [163](#)  
 SYSID default field title  
     Held Output Queue panel [120](#)  
     Initiator panel [122](#)



SYSID default field title (*continued*)

- LI panel [151](#)
- NS panel [161](#)
- Output Queue panel [166](#)
- Printer panel [173](#)
- Punch panel [180](#)
- Reader panel [182](#)
- Spool Offload panel [188](#)

SYSID3 (system ID)

- parameter in ISFPARMS [45](#)
- specifying in JES3 environment [45](#)

SYSIN/SYSOUT

- SAF authorization [215](#), [278](#)

SYSLEV default field title

- CK panel [118](#)

SYSLEVEL default field title

- AD panel [94](#)
- Address Space Memory panel [96](#)
- Authorized Program Facility panel [97](#)
- CKPT panel [127](#)
- CS panel [102](#)
- CSI panel [103](#)
- CSR panel [104](#)
- DEV panel [105](#)
- Display Active Users panel [108](#)
- Dynamic Exits panel [109](#)
- Enclave panel [110](#)
- Extended Console panel [114](#)
- FS panel [115](#)
- GT panel [116](#)
- JCS panel [134](#)
- JES Subsystem [130](#)
- JESInfo by job panel [129](#)
- JESInfo panel [128](#)
- Job DDName panel [143](#)
- Job Memory Objects panel [145](#)
- Job Module panel [146](#)
- JT panel [148](#)
- Link List panel [154](#)
- Link List sets panel [153](#)
- Link Pack Area panel [154](#)
- Link Pack Directory panel [155](#)
- MEM panel [158](#)
- NA panel [159](#)
- OMVS options panel [165](#)
- PAG panel [168](#)
- PARMLIB panel [169](#)
- PC panel [170](#)
- Process panel [178](#)
- RMA panel [185](#)
- SMSG panel [192](#)
- SMSV panel [193](#)
- SSI panel [198](#)
- SVC panel [200](#)
- SYS panel [201](#)
- SYSP panel [204](#)
- System Symbol panel [200](#)
- USI panel [176](#)
- VMAP panel [205](#)
- WLM report class panel [206](#)
- WLM resource group panel [207](#)
- WLM Workload panel [210](#)

SYSLOG

- protecting with SAF [342](#)

SYSLOG index

- name of [14](#)

SYSLOG panel

- system ID of SYSLOG displayed on [45](#)

SYSMSU default field title

- SYS panel [202](#)

SYSNAME

- command [34](#)

SYSNAME command

- authorization to issue [261](#)

SysName default field title

- NODE panel [163](#)

SYSNAME default field title

- AD panel [94](#)
- Address Space Memory panel [96](#)
- Authorized Program Facility panel [97](#)
- CFC panel [98](#)
- CK panel [118](#)
- CKH panel [116](#)
- CKPT panel [127](#)
- CS panel [102](#)
- CSI panel [103](#)
- CSR panel [104](#)
- DEV panel [105](#)
- Dynamic Exits panel [109](#)
- Enclave panel [110](#)
- Enqueue panel [112](#)
- Extended Console panel [114](#)
- FS panel [115](#)
- GT panel [116](#)
- Initiator panel [122](#)
- Input Queue panel [125](#)
- JCS panel [134](#)
- JES Subsystem [130](#)
- JESInfo by job panel [129](#)
- JESInfo panel [128](#)
- JESplex panel [156](#)
- Job Class Memory panel [131](#)
- Job DDName panel [142](#)
- Job Memory Objects panel [145](#)
- Job Module panel [146](#)
- Job Step panel [147](#)
- JT panel [148](#)
- LI panel [151](#)
- Link List panel [154](#)
- Link Pack Area panel [154](#)
- Link Pack Directory panel [155](#)
- MEM panel [158](#)
- Multi-Access Spool panel [156](#)
- NA panel [159](#)
- NS panel [161](#)
- OMVS options panel [165](#)
- PAG panel [168](#)
- PARMLIB panel [169](#)
- PC panel [170](#)
- Printer panel [173](#)
- Process panel [178](#)
- Punch panel [180](#)
- Reader panel [182](#)
- RM panel [184](#)
- RMA panel [185](#)
- SMSG panel [192](#)
- SMSV panel [193](#)
- Spool Offload panel [188](#)



- SYSNAME default field title *(continued)*
  - SR panel [204](#)
  - SSI panel [198](#)
  - Status panel [196](#)
  - SVC panel [199](#)
  - SYSP panel [204](#)
  - System Symbol panel [200](#)
  - USI panel [176](#)
  - VMAP panel [205](#)
  - WLM report class panel [206](#)
  - WLM resource group panel [207](#)
  - WLM Workload panel [210](#)
  - XCF Members and Groups panel [210](#)
- SYSNAME indicator default field title
  - Link List sets panel [153](#)
- SYSNAME, default field title
  - Job Class panel [133](#)
- SYSNUM default field title
  - CFC panel [98](#)
- SYSOUT (system output)
  - class, specifying default for [16](#)
  - displaying for jobs
    - specifying authorization for [349](#)
- SYSOUT parameter [15](#)
- SYSP panel
  - SYSPFLDS parameter [46](#)
  - variable field list of
    - primary, defining [46](#)
- SYSP panel scope
  - custom property [66](#)
- sysplex
  - ISFPARMS in [10](#)
- sysplex DA
  - disabling [351](#)
  - migration considerations [358](#)
- SYSPLEX default field title
  - CKH panel [116](#)
  - SYS panel [202](#)
- SYSSEQ default field title
  - CFC panel [98](#)
- SYSSYM, default field title
  - Job Class panel [133](#)
- system commands, console used to issue [356](#)
- system commands, storing [357](#)
- SYSTEM default field title
  - Display Active Users panel [106](#)
- system field
  - RES panel [183](#)
- system ID, specifying [45](#)
- system log
  - protecting with SAF [342](#)
- system output (SYSOUT)
  - class, specifying default for [16](#)
  - displaying for jobs
    - specifying authorization for [349](#)
- System panel
  - SYS parameter [45](#)
  - variable field list of
    - alternate, defining [45](#)
    - primary, defining [45](#)
- System Parameters panel [203](#)
- system requests
  - protecting with SAF [345](#)
- system symbols

- system symbols *(continued)*
  - disabling [56](#)
- System symbols panel
  - SYMFLDS parameter [45](#)
  - variable field list of
    - primary, defining [45](#)
- System Symbols panel [200](#)
- system symbols, using in ISFPARMS [12](#)
- SYSTEMS default field title
  - SE panel [185](#)
- SYSUSE default field title
  - Job Module panel [146](#)
- SzAAP% default field title
  - Display Active Users panel [107](#)
- SzIIP% default field title
  - Display Active Users panel [108](#)

## T

- T abbreviation in column data [49](#)
- Target default field title
  - Spool Volumes panel [190](#)
- TASK
  - displaying information about [83](#)
- TB abbreviation in column data [49](#)
- TCB default field title
  - AD panel [94](#)
  - Job Module panel [145](#)
  - JT panel [148](#)
  - USI panel [176](#)
- TCBADDR default field title
  - JT panel [148](#)
- TCBCMP default field title
  - JT panel [148](#)
- TCBFLAGS default field title
  - JT panel [148](#)
- TDEPTH default field title
  - JC panel [131](#)
- TENANT default field title
  - WLM report class panel [207](#)
  - WLM resource group panel [208](#)
- TENANTID default field title
  - WLM resource group panel [208](#)
- TENANTNAME default field title
  - WLM report class panel [207](#)
  - WLM resource group panel [208](#)
- TERMID default field title
  - Extended Console panel [113](#)
- terminal names
  - using to define a group of users [17](#)
- terminal screen, largest supported [15](#)
- TERMLEVEL default field title
  - XCF Members and Groups panel [210](#)
- TGNUM default field title
  - Input Queue panel [124](#)
  - Spool Volumes panel [189](#)
  - Status panel [194](#)
- TGPCT default field title
  - Input Queue panel [124](#)
  - Spool Volumes panel [189](#)
  - Status panel [194](#)
- TGUE default field title
  - Spool Volumes panel [189](#)
- Time default field title

- Time default field title (*continued*)
  - Reader panel [182](#)
- TIME default field title
  - Job Dependencies panel [139](#)
  - SR panel [204](#)
- TIMEE default field title
  - Process panel [178](#)
  - RM panel [184](#)
- TIMEOUT interval, default [15](#)
- TIMEOUT parameter [15](#)
- TIOTAVAIL default field title
  - Job Step panel [147](#)
- TIOTHWM default field title
  - Job Step panel [147](#)
- TIOTUSED default field title
  - Job Step panel [147](#)
- title [48](#)
- TITLE default field title
  - COLH panel [101](#)
  - Job Data Set panel [135](#)
  - SEARCH panel [191](#)
- TOT-ERRS default field title
  - LI panel [151](#)
- Tot-Lines default field title
  - NC panel [159](#)
- TOT-LINES default field title
  - Input Queue panel [124](#)
  - LI panel [150](#)
  - SO panel [186](#)
  - Status panel [195](#)
- TOT-PAGE default field title
  - Held Output Queue panel [119](#)
  - Output Queue panel [165](#)
- TOT-REC default field title
  - Held Output Queue panel [119](#)
  - Output Queue panel [165](#)
- TOTAL default field title
  - Job Memory panel [144](#)
  - SMSG panel [192](#)
  - SMSV panel [193](#)
- TOTAL24 default field title
  - Job Memory panel [144](#)
- TOTAL31 default field title
  - Job Memory panel [144](#)
- TOTAL64 default field title
  - Job Memory panel [144](#)
- TOTERRS default field title
  - PAG panel [168](#)
- TP Default field title
  - Job Data Set panel [137](#)
- TP26 default field title
  - JC panel [132](#)
- TP6 default field title
  - JC panel [132](#)
- TPACCT default field title
  - Job Data Set panel [137](#)
- TPDATEE default field title
  - Job Data Set panel [137](#)
- TPDATER default field title
  - Job Data Set panel [137](#)
- TPDATETIMEE default field title
  - Job Data Set panel [137](#)
- TPDATETIMER default field title
  - Job Data Set panel [137](#)

- TPJNAME default field title
  - Job Data Set panel [137](#)
- TPJOBID default field title
  - Job Data Set panel [137](#)
- TPTIMEE default field title
  - Job Data Set panel [137](#)
- TPTIMER default field title
  - Job Data Set panel [137](#)
- Tr default field title
  - NC panel [159](#)
  - NS panel [161](#)
- TR default field title
  - Lines panel [151](#)
  - NODE panel [163](#)
  - Printer panel [173](#)
  - Punch panel [180](#)
- Trace
  - displaying information about [91](#)
  - setting [88](#)
- TRAN-ACT default field title
  - Display Active Users panel [107](#)
- TRAN-RES default field title
  - Display Active Users panel [107](#)
- TRANS default field title
  - Printer panel [173](#)
- TRANS value [29](#)
- translation tables [68](#)
- TRANSMIT default field title
  - NODE panel [162](#)
- TRANSP default field title
  - Lines panel [151](#)
- TRANSS default field title
  - WLM service classes panel [209](#)
- TRC default field title
  - Printer panel [175](#)
- TRCLASS parameter [16](#)
- TRDEF statement
  - syntax [71](#)
- TRESGROUP default field title
  - Display Active Users panel [108](#)
  - Enclaves panel [111](#)
- TRKCELL default field title
  - Printer panel [173](#)
- TRKPERCYL default field title
  - Spool Volumes panel [189](#)
- TRKPERTG default field title
  - Spool Volumes panel [189](#)
- TRTAB statement
  - syntax [69](#)
  - using for defining code pages [68](#)
  - using UPCTAB parameter with [68](#)
  - using VALTAB parameter with [68](#)
- TSO default field title
  - PROC panel [177](#)
- TSPACE default field title
  - FS panel [115](#)
- TSU value [29](#)
- TSUNUM default field title
  - SYS panel [201](#)
- Type default field title
  - NC panel [159](#)
  - Spool Volumes panel [189](#)
- TYPE default field title
  - CFD panel [99](#)

## TYPE default field title *(continued)*

- CS panel [102](#)
- CSI panel [103](#)
- Display Active Users panel [106](#)
- Dynamic Exits panel [109](#)
- Enclave panel [110](#)
- FS panel [114](#)
- Held Output Queue panel [120](#)
- Initiator panel [122](#)
- Input Queue panel [123](#)
- JCS panel [133](#)
- Job DDName panel [142](#)
- Job Device panel [140](#)
- Job Memory panel [144](#)
- JT panel [148](#)
- LI panel [150](#)
- Link Pack Directory panel [155](#)
- Output Queue panel [166](#)
- PAG panel [168](#)
- Printer panel [173](#)
- Process panel [178](#)
- Punch panel [179](#)
- Reader panel [181](#)
- RMA panel [184](#)
- SMSG panel [192](#)
- Spool Offload panel [185](#)
- SSI panel [198](#)
- Status panel [196](#)
- SVC panel [199](#)
- System Symbol panel [200](#)
- USI panel [176](#)

TYPE parameter [49](#)

TYPE=DEST parameter [54](#)

TZOFFSET default field title

- SYS panel [203](#)

## U

UCS default field title

- Held Output Queue panel [119](#)

- Job 0 panel [149](#)

- Job Data Set panel [135](#)

- Output Queue panel [166](#)

- Printer panel [171](#)

UCSV default field title

- Printer panel [173](#)

UIC default field title

- SYS panel [201](#)

UJP default field title

- JC panel [132](#)

ULOG panel

- authority to display, specifying [345](#)

- authorization to display [261](#)

- extended console

- CICS [346](#)

- NetView [346](#)

UnAlloc default field title

- Initiator panel [122](#)

UNALLOC parameter [16](#)

deallocating dynamically allocated data sets [16](#)

Unit default field title

- NC panel [159](#)

UNIT default field title

- DEV panel [105](#)

## UNIT default field title *(continued)*

- Enqueue panel [112](#)

- Job DDName panel [142](#)

- Job Device panel [140](#)

- LI panel [150](#)

- PAG panel [169](#)

- Printer panel [172](#)

- Punch panel [180](#)

- Reader panel [182](#)

- SMSV panel [193](#)

- Spool Offload panel [188](#)

UNITCT default field title

- Job DDName panel [142](#)

- Job Device panel [140](#)

UNKNIDS default field title

- Extended Console panel [114](#)

UP default field title

- SVC panel [199](#)

UPCTAB parameter

- lowercase to uppercase, converting from [46](#)

- requesting a code page, using for [46](#)

- translate tables, defining [46](#)

UPDCNT default field title

- SVC panel [199](#)

UPDDATE default field title

- SVC panel [199](#)

- WLM report class panel [206](#)

- WLM resource group panel [207](#)

- WLM service classes panel [209](#)

- WLM Workload panel [209](#)

UPDMETH default field title

- SVC panel [199](#)

UPDREASON default field title

- CK panel [118](#)

UPDUSER default field title

- WLM report class panel [206](#)

- WLM resource group panel [207](#)

- WLM service classes panel [209](#)

- WLM Workload panel [209](#)

uppercase, specifying [68](#)

USE default field title

- JESInfo by Job panel [129](#)

UseCount default field title

- Initiator panel [122](#)

USECOUNT default field title

- Job Module panel [146](#)

- PROC panel [177](#)

USED default field title

- SMSG panel [192](#), [193](#)

USEDPCT default field title

- FS panel [115](#)

- SMSG panel [192](#)

- SMSV panel [193](#)

USENUM default field title

- PAG panel [168](#)

- RM panel [183](#)

USEPCT default field title

- JESInfo by Job panel [129](#)

- PAG panel [168](#)

- RM panel [183](#)

User

- displaying information about [84](#)

user authorization [367](#)

user exit routine, SDSF [349](#)

- user groups, defining [17](#)
- user ID
  - using to restrict
    - authority to issue commands for jobs [27](#)
    - jobs displayed on SDSF panels [39](#), [40](#)
- user interface
  - ISPF [519](#)
  - TSO/E [519](#)
- USERATE default field title
  - JESInfo by Job panel [129](#)
- USERDATA default field title
  - Enqueue panel [112](#)
  - XCF Members and Groups panel [211](#)
- USERDATA Default field title
  - Job Data Set panel [136](#)
- USERDATE default field title
  - CK panel [117](#)
- USERID default field title
  - Enclaves panel [111](#)
  - SMSG panel [192](#)
  - SMSV panel [193](#)
- USERID value [39](#), [40](#)
- USERLIB default field title
  - Job Data Set panel [136](#)
- USERNUM default field title
  - CFS panel [99](#)
- UserPages default field title
  - MAS and JESPLEX panels [157](#)
- USERSTATE default field title
  - XCF Members and Groups panel [211](#)
- USO default field title
  - JC panel [132](#)
- USPACE default field title
  - FS panel [115](#)
- UTILPCT default field title
  - DEV panel [105](#)

## V

- VALIDATE default field title
  - Spool Offload panel [188](#)
- VALTAB parameter
  - checking for valid characters, using for [46](#)
  - requesting a code page, using for [46](#)
- VALUE default field title
  - OMVS options panel [165](#)
  - SYSP panel [204](#)
  - System Symbol panel [200](#)
  - WLM Policy panel [206](#)
- variable field list
  - for SDSF panels, defining [47](#)
- VERBOSE default field title
  - CK panel [118](#)
- VERIFYP default field title
  - NODE panel [163](#)
- VERSION default field title
  - CFC panel [98](#)
  - CFS panel [100](#)
  - JES Subsystem [130](#)
  - Multi-Access Spool panel [156](#)
- VFYPATH default field title
  - NODE panel [164](#)
- viewing page-mode output

- viewing page-mode output (*continued*)
  - authorization
    - ISFPARMS [30](#), [46](#)
    - SAF [278](#), [279](#)
    - specifying unit name of temporary file [46](#)
- VIO default field title
  - Job Step panel [147](#)
  - PAG panel [168](#)
- VIO parameter [46](#)
- Virtual Storage Map panel [205](#)
- VMAP panel
  - variable field list of
    - primary, defining [46](#)
    - VMAPFLDS parameter [46](#)
- VMAP panel scope
  - controlling [66](#)
- VMUSER default field title
  - SYS panel [202](#)
- VOLATILE default field title
  - CKPT panel [127](#)
- VOLS default field title
  - Spool Offload panel [188](#)
- VolSer default field title
  - Spool Volumes panel [190](#)
- VOLSER default field title
  - Authorized Program Facility panel [97](#)
  - CFD panel [99](#)
  - CKPT panel [127](#)
  - DEV panel [105](#)
  - Job DDName panel [142](#)
  - Job Device panel [140](#)
  - Link List panel [153](#)
  - Link Pack Area panel [154](#)
  - PAG panel [168](#)
  - PARMLIB panel [169](#)
  - PROC panel [177](#)
  - SMSV panel [193](#)
  - SRCH panel [191](#)
- VS/JES commands
  - authorization for, specifying
    - with statements parameters [27](#)
- VTr default field title
  - NC panel [160](#)
  - NS panel [161](#)
- VTR default field title
  - LI panel [152](#)

## W

- WAIT-CNT default field title
  - JC panel [131](#)
- WAITERS default field title
  - Enqueue panel [112](#)
- WAITEXC default field title
  - Enqueue panel [112](#)
- WAITSHR default field title
  - Enqueue panel [112](#)
- WARNPCT default field title
  - JESInfo panel [128](#)
  - RM panel [183](#)
- WHEN default field title
  - Job Dependencies panel [139](#)
- WHEN statement [10](#)
- who can use SDSF, specifying [350](#)

- WIDTH default field title
  - COLH panel [101](#)
- WITH default field title
  - Input Queue panel [125](#)
  - Status panel [197](#)
- WKLD panel
  - variable field list of
    - primary, defining [47](#)
  - WKLDFLDS parameter [47](#)
- WLM panel
  - variable field list of
    - primary, defining [47](#)
  - WLMFLDS parameter [47](#)
- WLM report class panel [206](#)
- WLM resource group panel [207](#)
- WLM resources [183](#)
- WLM scheduling environments [185](#)
- WLM service classes panel [208](#)
- WLM workload panel [205](#), [209](#)
- Work-Selection default field title
  - NC panel [160](#)
- WORK-SELECTION default field title
  - LI panel [151](#)
  - Printer panel [172](#)
  - Punch panel [179](#)
  - Spool Offload panel [187](#)
- WORKLOAD default field title
  - Display Active Users panel [107](#)
  - Enclave panel [110](#)
  - Job Step panel [147](#)
  - WLM service classes panel [208](#)
- WPOS default field title
  - Input Queue panel [124](#)
  - Status panel [195](#)
- write-to-operator (WTO) messages, issuing for commands [27](#)
- write-to-operator-with-reply (WTOR) messages
  - displayed on SYSLOG panel
  - specifying in ISFPARMS [24](#)
- WRITER default field title
  - Printer panel [171](#)
- WTOINT default field title
  - MAS and JESPLEX panels [156](#)
- WTOLIM default field title
  - MAS and JESPLEX panels [156](#)
- WTONUM default field title
  - CK panel [117](#)
- WTORNUM default field title
  - SYS panel [202](#)
- WTOTYPE default field title
  - CK panel [117](#)
- WTR default field title
  - Held Output Queue panel [119](#)
  - Job 0 panel [149](#)
  - Job Data Set panel [135](#)
  - Output Queue panel [39](#), [166](#)
- WTRID default field title
  - Punch panel [180](#)

## X

- XBM default field title

- XBM default field title (*continued*)
  - JC panel [131](#)
- XBMPROC, default field title
  - Job Class panel [132](#)
- XCF application server
  - specifying [16](#)
- XCF members and groups panel [210](#)
- XCFGROUP default field title
  - Display Active Users panel [108](#)
  - JES Subsystem [130](#)
- XEQ-CNT default field title
  - JC panel [131](#)
- XEQDEST default field title
  - Reader panel [182](#)
- XNAMEREQ default field title
  - NODE panel [164](#)
- XSB default field title
  - JT panel [148](#)
- XSTATUS parameter [47](#)
- XSYSTEM default field title
  - CMDH panel [101](#)

## Z

- z/OS systems
  - refreshing list of [86](#)
- z/OSMF
  - adding the SDSF task [362](#)
  - properties file [362](#)
  - settings [363](#)
  - TSO logon proc [363](#)
- zAAP use
  - custom property [61](#)
- zAAP-Time default field title
  - Display Active Users panel [107](#)
  - ENC panel [110](#)
- zAAP-Use% default field title
  - Display Active Users panel [107](#)
- ZAAPNTIM default field title
  - Display Active Users panel [108](#)
  - Enclaves panel [111](#)
- ZAAPNUM default field title
  - SYS panel [202](#)
- zACP-Time default field title
  - Display Active Users panel [107](#)
  - ENC panel [111](#)
- zICP-Time default field title
  - ENC panel [111](#)
- zIIP-Time default field title
  - ENC panel [111](#)
- ZIIPCPTM default field title
  - Display Active Users panel [108](#)
  - Job Step panel [147](#)
- ZIIPNTIM default field title
  - Display Active Users panel [108](#)
  - Enclaves panel [111](#)
  - Job Step panel [147](#)
- ZIIPNUM default field title
  - SYS panel [202](#)
- ZIIPTIME default field title
  - Display Active Users panel [108](#)
  - Job Step panel [147](#)

ZIIPTIME default field title (*continued*)

Process panel [178](#)

ZIIPUSE default field title

Display Active Users panel [108](#)





Product Number: 5650-ZOS

SA23-2274-50

