

```

    "description": "AUS/NRD",
    "parentId": undefined,
    "properties": {
      "0BC_REG.MIDDLE_TEXT": "AUS/NRD",
      "0BC_REG.DISPLAY_KEY_NC": "NRD"
    }
  },
  ...,
  {
    "@MeasureDimension": {
      "id": "0002TLJDAAI840CJLDKA0280K",
      "description": "0BC_AMT",
      "parentId": undefined,
      "rawValue": "3649995.68"
      "formattedValue": "DM3,649,995.68"
    },
    "0BC_REG": { // no properties are returned here as the
                  // total value doesn't have properties
      "id": "SUMME",
      "description": "Totals",
      "parentId": undefined
    }
  }
}]

```

KIT_0BOC_TEST_DATATYPES_1

				Measures	0BC_AMT	0BC_MAX
0BC_REG	0BC_REG (MIDDLE...	0BC_REG (DISPLAY_KEY_NC)	Description	ID		
AUS/NRD	AUS/NRD	NRD	AUS/NRD	AUS/NRD	DM49,996....	—
DE/BAW	DE/BAW	BAW	DE/BAW	DE/BAW	DM1,102,7...	1,134.620 KG
DE/BAY	DE/BAY	BAY	DE/BAY	DE/BAY	DM1,068,7...	1,183.430 KG
DE/SAC	DE/SAC	SAC	DE/SAC	DE/SAC	DM1,428,5...	1,169.430 KG
Totals					DM3,649,9...	1,183.430 KG

Figure 43 Get Dimension Attributes

5.8.1.5 Retrieving Visible Dimension Properties

You can retrieve additional dimension properties, the visible dimension properties, that were configured in the *Builder* panel at design time using the Data Source script API.

Note: Currently, this is supported only by data sources of Table widgets.