



PALO ALTO NETWORKS EDU-210

Lab 13: Active/Passive High Availability

Document Version: 2017-09-29

Copyright © 2017 Network Development Group, Inc.
www.netdevgroup.com

NETLAB Academy Edition, NETLAB Professional Edition, and NETLAB+ are registered trademarks of Network Development Group, Inc.

VMware is a registered trademark of VMware, Inc. Cisco, IOS, Cisco IOS, Networking Academy, CCNA, and CCNP are registered trademarks of Cisco Systems, Inc. EMC² is a registered trademark of EMC Corporation.

Contents

Introduction	3
Objectives.....	3
Lab Topology	4
Lab Settings	5
13 Lab: Active/Passive High Availability	6
13.1 Load Lab Configuration.....	6
13.2 Display the HA Widget.....	7
13.3 Configure the HA Interface.....	7
13.4 Configure Active/Passive HA	8
13.5 Configure HA Monitoring	12
13.6 Observe the HA Widget	15


Introduction

The board and the executives have become worried that we could experience downtime with the current configuration. They have therefore approved the purchase of a second Palo Alto Networks firewall like the first one and to implement Active/Passive High Availability to prevent possible downtime. We are going to test the process of configuring the feature before the second device arrives. We will then be able to duplicate the process when the second device arrives and turn it on.

Objectives

- Display the Dashboard HA widget.
- Configure a dedicated HA interface.
- Configure active/passive HA.
- Configure HA monitoring.
- Observe the HA widget.

Lab Topology



Lab Settings


The information in the table below will be needed in order to complete the lab. The task sections below provide details on the use of this information.

Virtual Machine	IP Address	Account (if needed)	Password (if needed)
Client – Windows 2012 R2	192.168.1.20	lab-user	Pal0Alt0
Firewall – PA-VM	192.168.1.254	admin	admin


13 Lab: Active/Passive High Availability

13.0 Load Lab Configuration

1. In the WebUI select **Device > Setup > Operations**.
2. Click **Load named configuration snapshot**:



3. Select **edu-210-lab-13** and click **OK**.



4. Click **Close**.
5. **Commit** all changes.


13.1 Display the HA Widget

If high availability (HA) is enabled, the High Availability widget on the Dashboard indicates the HA status.

1. In the WebUI click the **Dashboard** tab to display current firewall information.



2. If the High Availability panel is not displayed, select **Widgets > System > High Availability** to enable the display:




The High Availability Widget now displays on the Dashboard:



13.2 Configure the HA Interface

Each HA interface has a specific function: One interface is for configuration synchronization and heartbeats, and the other interface is for state synchronization (not configured in this lab).


1. In the WebUI select **Network > Interfaces > Ethernet**.



2. Click **ethernet1/6** to open the configuration window for that interface.

ethernet1/5	Virtual Wire		none	none	Untagged
ethernet1/6			none	none	Untagged
ethernet1/7			none	none	Untagged


3. Select **HA** on the Interface Type drop-down list and click **OK**:




13.3 Configure Active/Passive HA

In this deployment, the active firewall continuously synchronizes its configuration and session information with the passive firewall over two dedicated interfaces. In the event of a hardware or software disruption on the active firewall, the passive firewall becomes active automatically without loss of service. Active/passive HA deployments are supported by the interface modes Virtual Wire, Layer 2, and Layer 3.

1. In the WebUI select **Device > High Availability > General**.




- Click the **Edit** icon of the *Setup* panel to open the Setup configuration window.



- Configure the following:

Parameter	Value
Enable HA	<input checked="" type="checkbox"/> Enable HA
Group ID	60 (This field is required, and must be unique, if multiple HA pairs reside on the same broadcast domain.)
Mode	Active Passive
Enable Config Sync	<input checked="" type="checkbox"/> Enable Config Sync (Select this option to enable synchronization of configuration settings between the peers.)
Peer HA1 IP Address	172.16.3.11




- Click **OK** to close the *Setup* configuration window.

- Click the **Edit** icon of the *Active/Passive Settings* panel:




- Select the **Auto** radio button. When Auto is selected, the links that have physical connectivity remain physically up but in a disabled state. They do not participate in ARP or packet forwarding. This configuration helps reduce convergence times during failover because no time is required to activate the links. To avoid network loops, do not select this option if the firewall has any Layer 2 interfaces configured.



- Click **OK** to close the *Active/Passive Settings* configuration window.
- Click the **Edit** icon of the Election Settings panel to configure failover behavior:

Parameter	Value
Device Priority	80 Enter a priority value (range is 0–255) to identify the active firewall. The firewall with the lower value (higher priority) becomes the active firewall when the preemptive capability is enabled on both firewalls in the pair.)
Preemptive	<input checked="" type="checkbox"/> Preemptive Enables the higher priority firewall to resume active operation after recovering from a failure. This parameter must be enabled on both firewalls but is not always a recommended practice.
Heartbeat Backup	<input type="checkbox"/> Heartbeat Backup Uses the management ports on the HA firewalls to provide a backup path for heartbeat and hello messages






The **Election Settings** window shows the following configuration:

- Device Priority: 80
- ☒ Preemptive
- ☐ Heartbeat Backup
- HA Timer Settings: Recommended

The **OK** button is highlighted with a red box and a mouse cursor.

9. Click **OK** to close the *Election Settings* configuration window.
10. Click the **Edit** icon of the *Control Link (HA1)* panel to configure the HA1 link. The firewalls in an HA pair use HA links to synchronize data and maintain state information:

Parameter	Value
Port	ethernet1/6
IP address	172.16.3.10
Netmask	255.255.255.0

The **Control Link (HA1)** window shows the following configuration:


- Port: ethernet1/6
- IPv4/IPv6 Address: 172.16.3.10
- Netmask: 255.255.255.0
- Gateway: (empty)
- ☐ Encryption Enabled
- Monitor Hold Time (ms): 3000

The **OK** button is highlighted with a red box and a mouse cursor.

11. Click **OK** to close the *Control Link (HA1)* configuration window.
12. Click the **Edit** icon of the *Data Link (HA2)* configuration window.




13. Deselect the **Enable Session Synchronization** check box:



14. Click **OK** to close the *Data Link (HA2)* configuration window.


13.4 Configure HA Monitoring

1. In the WebUI select **Device > High Availability > Link and Path Monitoring**.



2. Click the **Edit** icon of the *Link Monitoring* panel to configure link failure detection. Link monitoring enables failover to be triggered when a physical link or group of physical links fails.



Parameter	Value
Enabled	<input checked="" type="checkbox"/> Enabled
Failure Condition	Any



3. Click **OK** to close the *Link Monitoring* configuration window.

4. Click **Add** in the Link Group panel to configure the traffic links to monitor:


Parameter	Value
Name	traffic-links
Enabled	<input checked="" type="checkbox"/> Enabled
Failure Condition	Any
Interface	ethernet1/1 ethernet1/2



5. Click **OK** to close the *Link Group* configuration window.
6. Click the **Edit** icon of the *Path Monitoring* panel to configure the Path Failure detection. Path monitoring enables the firewall to monitor specified destination IP addresses by sending ICMP ping messages to ensure that they are responsive.

Parameter	Value
Enabled	<input checked="" type="checkbox"/> Enabled
Failure Condition	Any



Path Monitoring 


Enabled ☒


Failure Condition **any**

7. Click **OK** to close the *Path Monitoring* configuration window.
8. Find the Path Group panel and click **Add Virtual Router Path** to configure the path failure condition:

Parameter	Value
Name	lab-vr
Enabled	<input checked="" type="checkbox"/> Enabled
Failure Condition	Any
Destination IP	8.8.8.8

Path Group

	Name	Type	Enabled	Failure Condition	Source IP
<div> Add Virtual Wire Path  Add VLAN Path  Add Virtual Router Path  Delete</div>					



The image shows the 'HA Path Group Virtual Router' configuration window. The 'Name' field is set to 'lab-vr'. The 'Enabled' checkbox is checked. The 'Failure Condition' is set to 'Any'. A table with one item is shown, with the 'Destination IP' set to '8.8.8.8'. The 'Add' button is highlighted. The 'Ping Interval' is set to 200 and the 'Ping Count' is set to 10. The 'OK' button is highlighted.


9. Click **OK** to close the HA Path Group Virtual Router configuration window.

10. **Commit** all changes.




13.5 Observe the HA Widget

1. In the WebUI click the **Dashboard tab** and view the High Availability status widget for the firewall. Active-passive mode should be enabled and the local firewall should be active (green). However, because there is no peer firewall, the status of most monitored items is unknown (yellow). Because HA1 has no peer, its state is down (red):



2. If a peer was configured and was operating in passive mode, the High Availability widget on the Dashboard would appear as follows. In order to avoid overwriting the wrong firewall configuration, the firewalls are not automatically synchronized. You must manually synchronize a firewall to the firewall with the "valid" configuration by clicking Sync to peer.



Stop. This is the end of the Active/Passive High Availability lab.

