
MON+ *Symbolic Debugger*

for the ProDOS 8 version of ORCA/M

By Dave Winzler of Microseeds, Inc.

Copyright 1987



Limited Warranty - Subject to the below stated limitations, Byte Works Inc. hereby warrants that the programs contained in this unit will load and run on the standard manufacturer's configuration for the computer listed for a period of ninety (90) days from date of purchase. Except for such warranty, this product is supplied on an "as is" basis without warranty as to merchantability or its fitness for any particular purpose. The limits of warranty extend only to the original purchaser.

Neither Byte Works Inc. nor the authors of this program are liable or responsible to the purchaser and/or user for loss or damage caused, or alleged to be caused, directly or indirectly by this software and its attendant documentation, including (but not limited to) interruption of service, loss of business, or anticipatory profits.

To obtain the warranty offered, the enclosed purchaser registration card must be completed and returned to the Byte Works Inc. within ten (10) days of purchase.

Important Notice - This is a fully copyrighted work and as such is protected under copyright laws of the United States of America. According to these laws, consumers of copywritten material may make copies for their personal use only. Duplication for any purpose whatsoever would constitute infringement of copyright laws and the offender would be liable to civil damages of up to \$50,000 in addition to actual damages, plus criminal penalties of up to one year imprisonment and/or a \$10,000 fine.

This product is sold for use on a *single computer* at a single location. Contact the publisher for information regarding licensing for use at multiple-workstation or multiple computer installations.

ORCA/M is a trademark of the Byte Works, Inc.

Apple Computer, Inc. MAKES NO WARRANTIES, EITHER EXPRESSED OR IMPLIED, REGARDING THE ENCLOSED COMPUTER SOFTWARE PACKAGE, ITS MERCHANTABILITY OR ITS FITNESS FOR ANY PARTICULAR PURPOSE. THE EXCLUSION OF IMPLIED WARRANTIES IS NOT PERMITTED BY SOME STATES. THE ABOVE EXCLUSION MAY NOT APPLY TO YOU. THIS WARRANTY PROVIDES YOU WITH SPECIFIC LEGAL RIGHTS. THERE MAY BE OTHER RIGHTS THAT YOU MAY HAVE WHICH VARY FROM STATE TO STATE.

ProDOS is a copyrighted program of Apple Computer, Inc. licensed to Byte Works, Inc. to distribute for use only in combination with ORCA/Pascal. Apple software shall not be copied onto another diskette (except for archive purpose) or into memory unless as part of the execution of ORCA/Pascal. When ORCA/Pascal has completed execution Apple Software shall not be used by any other program.

Apple is a registered trademark of Apple Computer, Inc.

Program, Documentation and Design
Copyright 1984, 1985, 1986
The Byte Works, Inc.

MON+ ***6502/65C02 Symbolic Debugger***

MON+ is a powerful debugging tool for the ORCA environment. It provides a complete set of memory examination and manipulation commands, arithmetic and logical functions, a disassembler, a mini-assembler and, as its most powerful feature, a step and trace facility that includes the ability to set and clear break points as well as have free-running subroutines. The disassembler, the mini-assembler, and the tracer all support a symbol table. Entries can be either manually-defined, or included as data tables in the object code of the program being debugged, and copied automatically into the symbol table. Likewise, the standard 65C02 instruction set is supported by these three functions, although the tracer will only work properly if there is a 65C02 processor installed in the machine.

Each of the MON+ commands is explained in detail below. In the description that follows, the meta-symbol *adr* (address) stands for any hexadecimal number in the range \$0000..\$FFFF. A user-defined symbol (see SYMBOL below) may be used anywhere *adr* may be used, provided the symbol is preceded by a @ sign. The meta-symbol *byte* stands for any hexadecimal number in the range \$00.41717. Square brackets around command parameters indicate that the bracketed parameter is optional.

The meta-symbol *filename* can be replaced by any valid ProDOS file name or full or partial path name.

Using MON+

Before using MON+, it must be installed in the utility subdirectory. This is the same directory that contains all of the ORCA utilities, such as PEEK. If, for example, you are using the default configuration, you would copy MON+ to the Utilities disk using the command

```
COPY /MONPLUS/DEBUG /UTILITY
```

MON+ Symbolic Debugger

The next step is to enable the `DEBUG` command using the `ORCA COMMANDS` utility. The reference manual for ORCA explains how to do this. Add `DEBUG` as a utility command. After installing `MON+`, you can execute it from any directory by typing `DEBUG`.

The program's version number and copyright notice will be displayed, and the cursor will appear next to the prompt (which is the `+` symbol). Any of the `MON+` commands may then be entered; for example, to display memory in the range `$2000` through `$201F`, enter the command:

```
LIST 2000.201F
```

Most commands may be shortened to one or two characters; the above example could have been shortened to:

```
L 2000.201F
```

The commands are checked in the order in which the `HELP` command lists them, and the first one which matches the entered command is used. Extra letters are ignored. The above example could be lengthened to:

```
LISTLESSLY 2000.201F
```

and it would still have done the same thing.

Using Break Points

When the `SETB` command is used to set a break point, `MON+` stores the break point address away in its break point table, along with the operation code at that address, and replaces the operation code with a `BRK` instruction. When control passes to that address, the `BRK` instruction is treated like an interrupt; a routine in the Apple F8 Monitor ROM saves the contents of tile 6502 registers, and passes control to `MON+`'s break point handler (via the hook at `$3FO`). `MON+` fixes the stack pointer, tells the user where the break occurred, and checks to see if that address is in its break point table. If it is, `MON+` replaces the original operation code, executes the instruction, replaces the `BRK` instruction, and enters the trace mode. If the `BRK` instruction isn't in the break point table, `MON+` will simply wait for the next command.

To use a break point, it's necessary to have both the program being debugged and `MON+` in memory at the same time.

MON+ Symbolic Debugger

While debugging a program using break points, it's most convenient to have both an assembly listing of the program, as well as a link editor listing, which shows where each subroutine starts. It is then a simple matter to add the relative address within each routine to the absolute address of the start of the machine (using MON+'s ADD instruction) to get the absolute address of an instruction within a routine. Here's a quick and easy method for getting MON+ and a program into memory at the same time, with MON+ in control:

- 1) Type DEBUG.
- 2) Use MON+'s BLOAD command to load in the program.
- 3) At this point the program can be listed, break points set, symbols entered, and the program traced. All of MON+'s other features may be used to debug the program as well.
- 4) When a session is done, use the QUIT command to return to the ORCA monitor.

If it's more convenient, it isn't always necessary to have the most recent listing, although obviously the more recent the listing, the better. Use the FIND command to search for a series of bytes in the vicinity of a target area, and then use LIST to pinpoint the actual addresses or code in question.

Note that when a break point is encountered, the break point handler will execute the instruction and stop *after* the break point, not before. For example, suppose that in the following piece of code:

```
3A06: LDA #6
3A08: STA $3A74
3A0B: JMP $3A05
```

a break point is placed at the STA instruction at \$3A08. When that break point is encountered, the STA instruction is executed, MON+ displays the instruction and the registers, enters the TRACE mode automatically, and then waits for a key press. At this point, since the STA instruction has been executed, location \$3A74 contains a 6.

A more sophisticated way of dealing with break points - and one which can all but eliminate the need for a current program listing for reference - is to

MON+ Symbolic Debugger

use symbols to refer to addresses; for an explanation of symbols, see the SYMBOL and GETSYM commands described below.

Memory Usage

MON+ loads into memory at \$9000. Except for the bottom thirty-two bytes of the stack, (\$100 - \$11F), MON+ does not directly use any memory below \$9000. It "borrows" page zero memory by swapping a copy of user page zero and MON+'s page zero.

Input and Output

Like most debuggers, MON+ uses the input and output routines provided by the operating system. This makes it difficult to trace screen output of keyboard input operations. As a result, you should always execute subroutines that will do screen output or keyboard input at full speed, using the GO or JUMP commands.

Disk input and output presents another problem. Disk routines are very time critical, and cannot be traced using a debugger. It is best to always execute calls to ProDOS at full speed, again using the GO command. Unless you over ride MON+ it will automatically execute any JSR to either ProDOS or the ORCA/HOST shell at full speed.

MON+ Commands

ADD [adr1[adr2[adr3 ...]]]

Displays the sum of the operands (adr1 + adr2) in hex and, in parentheses, decimal. Zero or more operands may be specified.

AND [adr1[adr2[adr3 ... 13]]

Displays the logical (bitwise) AND of the operands. Zero or more operands may be specified.

MON+ Symbolic Debugger

ASM *adr*

Enters the mini-assembler. The current address (set if *adr* is specified) is displayed, followed by a colon. The miniassembler is ready for input. A RETURN exits the mini-assembler.

If you enter something on the command line other than a valid 65C02 instruction mnemonic, MON+ will try to use it as a command. For example, you can still list memory while assembling a program.

The mini-assembler's syntax is slightly different from the standard 6502 syntax in that no operands are specified for the accumulator addressing mode. ROR means rotate right accumulator, but ROR A means rotate right memory address \$0A. All numbers in the mini-assembler are interpreted as hexadecimal, so the leading dollar sign (\$) is optional. Symbols may be used wherever an address is expected, provided they have been previously defined and are preceded with the @ sign. All 65C02 mnemonics and addressing modes are supported.

An example of the use of the ASM command, with symbols, is shown below. The symbol ABC must have been defined previously.

```
+ASM 2000
2000: LDA 5000
2003: STA @ABC
2006:
+
```

The mini-assembler was exited by typing RETURN in response to the 2006: prompt, causing the MON+ prompt to re-appear.

There are two important predefined symbols, @PRODOS and @ORCAHOST. These are the locations of the ProDOS entry vector (\$BFOO) and the ORCA/HOST entry vector (\$OOFD). MON+ handles these symbols in a special way. Whenever a JSR to one of the symbols is assembled, MON+ automatically leaves three bytes after the JSR to give you room to add the ProDOS or ORCA operation code and a pointer to the parameter table.

BLOAD *filename*

Loads the binary file specified by *filename*. The file is loaded at its default address. An error message is generated if *filename* isn't found, or if it's not a

MON+ Symbolic Debugger

binary file. Needless to say, if a file is loaded on top of either MON+ (\$9000 - \$BFOO) the operating system (\$D000 - \$FFFF), or ORCA (\$800 - \$IFFF) the system will crash.

BRUN filename

BLOADs *filename*, then does a JSR to the file's load address.

CONTINU

CONTINU is a special form of the JUMP command that continues execution from the last executed location. For example, after tracing the program with the TRACE command, you might CONTINU program execution at full speed.

CAT [filename]

Displays a disk catalog. *Filename* is optional. If specified, it must be the name of a directory file; that directory will be cataloged.

CLRB adr

Clears the break point specified at *adr* and displays a list of the remaining break points. Beeps if there is no break point at *adr*. If *adr* is not specified, the routine displays the current break points. If *adr* is specified, and there is a break point at *adr*, the routine removes the break point and restores the original operation code at *adr*.

CLRSYM

This command clears the symbol table, setting it back to its original state. It does not remove the two special symbols, @PRODOS and @ORCAHOST. Since the command is potentially dangerous, you will be asked if you are sure about the choice before the table is cleared.

COMPARE adr1.adr2 adr3

Compare the contents of the memory range *adr1* through *adr2* with a range of the same length, starting at *adr3*. If any byte does not match, the address within the first range is displayed, along with the differing bytes. If any of the operands are missing, an error message is displayed.

MON+ Symbolic Debugger

CONFIG

CONFIG allows the selection of two operational "preferences." In response to the CONFIG command, two prompts are displayed:

Display stack? **N**

Pause on JSR? **Y**

The default responses are indicated in boldface; to accept them, simply press RETURN. The Display Stack option enables or disables the printing of the values of the top eight stack entries during tracing, causing the trace for each instruction to span two lines; by disabling this feature, only a single-line instruction disassembly and register dump is listed. The Pause on JSR? option enables or disables a trace. With pause enabled, rather than continuing directly to the next instruction, a key press must be made. At this point, the subroutine may be executed as "free-running" -- that is, not traced, by pressing the R key. See the description of the TRACE command for details.

EOR [adr1[adr2[adr3 ...]]]

Displays the logical (bitwise) exclusive OR of the operands. Zero or more operands may be specified.

FIND adr1.adr2 list

Find and display all occurrences of list in the memory range *adr1* through *adr2*. List may be composed of hex bytes or ASCII strings within quotes; use double quotes for high order bit on, single quotes for high order bit off.

FILL adr1.adr2 byte

Fills the memory range *adr1* through *adr2* with the value *byte*. An error message is generated if any operand is missing. Because it is a potentially dangerous command, it responds with an 'Are you Sure' prompt. Enter Y to execute, N to cancel.

GO [adr]

Calls *adr* as a subroutine (performs a JSR to *adr*). If *adr* is not specified, GO uses the current value of the program counter, stored at \$3A and \$3B.

MON+ Symbolic Debugger

When an RTS is encountered, GO returns control to the MON+ command handler.

GETSYM *adr*

Copies symbol table entries from memory (presumably, from a loaded code file containing them), starting at *adr*. The format of the symbol table entries is:

bytes 1..10	Label name, with high bit of each character set
bytes 11..12	Address, in low-high order

A list of entries may be placed in memory; the end of the list is indicated by a zero. The GETSYM command is intended to provide a simple yet effective mechanism for transferring symbolic values from a program into the MON+ symbol table. There is no direct mechanism for transferring all global labels from an object module into the MON+ symbol table; instead, labels whose value is desired for debugging a given subroutine or series of routines are manually entered into the program source code in the following way:

```
ABC    START
XYZ    GEQU    $1234
        LDA    #5
        STA    XYZ
        RTS
        END

SYMBOLS DATA
        DC     C'ABC'  ',A'ABC'
        DC     C'XYZ'  ',A'XYZ'
        DC     H'00'   INDICATES END OF TABLE
        END
```

If the address of SYMBOLS is known (from the global symbol table listing of the link editor - in this example, suppose the value is \$2006), and the code file has been previously loaded into memory from MON+, a GETSYM command of the form

```
GET 2006
```

will copy the label names and their values into the MON+ symbol table.

MON+ Symbolic Debugger

Now if a TRACE command, for example, is used on the short program listed above, symbols will appear in disassembled trace:

```
2000: A905   ABC      LDA   #$05   A=05 X=00 Y=D8 P=30 S=83
2002: BD3412 STA      XYZ      A=05 X=00 Y~D8 P=30 S=83
2005: 60      RTS      A=05 X=00 Y=D8 P=30 S=83
```

Symbols may also be entered manually after a GET, and multiple GETs may be used, with the same or different address; if a label with the same address as an existing label is entered, a Duplicate Symbol error message is displayed, and the new entry is skipped. For manual symbol entry, see SYMBOL.

There is a macro file on the MON+ disk called M6502.MONPLUS. It contains a macro called SYM, which simplifies the inclusion of symbol tables in a source program. Its usage is:

```
SYM      ABC
SYM      XYZ
DC       H'00'
```

This will create a symbol table identical to the one indicated above; note that a zero must still be placed at the end of the table.

MON+ starts out with two symbols already defined. ProDOS is defined as \$BFOO, and ORCAHOST is defined as \$OOFD. These special symbols cannot be deleted. They are marked in the symbol table with a special P flag.

HELP

Displays a listing of all of the available MON+ commands.

JUMP (adr]

Transfers control to *adr*; essentially, does a JMP to *adr*. If *adr* is not specified, it uses the current value of the program counter, stored at \$3A and \$313. JUMP is useful for continuing a program in real time after a break point.

MON+ Symbolic Debugger

`LIST adr | LIST adr1.adr2 | LIST | LIST adr ln`

Disassembles a machine language program. If a range is specified, the entire memory range is disassembled. If *adr*, *adr1.adr2* or *ln* are not specified, the next twenty instructions are disassembled. If *ln* is specified, the next *ln* instructions are disassembled. 65C02 operation codes will be disassembled when encountered. Disassembly of JSR instructions to either of the special labels (@PRODOS or @ORCAHOST) will display the operation code and parameter table address in a special format in the operand field.

`LABEL [adr label]`

LABEL is another name for the SYMBOL command. See the SYMBOL command for a description of its use.

`MEM adr | MEM adr1.adr2`

Displays contents of memory in both hexadecimal and ASCII. If only one address is specified, the contents of the address are displayed. If a range is specified, the contents of that memory range are displayed. It is an error if *adr* is missing. (Note the description of the shorthand notation described immediately below.)

`MEM adr [list]`

Store *[list]* into memory starting at *adr*. *[list]* can be composed of hexadecimal bytes or ASCII strings within quotes (double quotes for high order bit on, single quotes for high order bit off).

For example:

```
MEM 2000 A9 'Z' 20 ED FD 'A long string'
```

There is a shorthand notation for either version of the MEM command: the arguments of the MEM command, such as a number range

```
2000.20FF
```

may be entered without being preceded by an explicit MEM command; MON+ defaults to interpreting commands as MEM only if numeric arguments are provided.

MON+ Symbolic Debugger

MOVE *adr1.adr2 adr3*

Copy the memory range *adr1* through *adr2* to memory starting at *adr3*. The routine can move a block of memory up or down, with or without overlaps, with no side effects. An error message is displayed if any of the operands are missing. Because it is a potentially dangerous command, it responds with an 'Are you sure?' prompt. Enter Y to execute, N to cancel.

NEGATE *adr*

Displays the two's complement (negative) of *adr*. Extra operands are ignored.

NOT *adr*

The one's complement of the operand is displayed. Additional parameters are ignored.

OR [*adr[adr2[adr3 ...]]*]

Displays the logical OR of the operands. Zero or more operands may be specified.

PAGE [*adr*]

Displays the contents of an entire memory page, starting at *adr*. If *adr* is missing, the routine continues displaying the next page.

PREFIX *filename*

Set the default prefix to *filename*.

PROFF

Turns off the printer. Subsequent output is sent to the screen.

PRON

Turns on the printer. Subsequent output is sent to the printer.

MON+ Symbolic Debugger

QUIT

Returns to the ORCA monitor via an RTS. It also restores tile BRK vector (if it was changed by SETB).

READ *block1* [*.block2*] *adr* [,SSlot,Ddrive]

Reads 512 byte disk blocks starting with *block1* and continuing to *block2* into memory starting at *adr*. Because the command is potentially dangerous, it responds with the 'Are you sure?' prompt.

REG

Displays the current 6502 register values (A, X, Y, Status and Stack Pointer). Their values may be changed as each register is displayed in turn. Press RETURN to leave the contents alone, or enter a new hex value to change the contents of the register being displayed.

SETB [*adr*] [*label*]

Sets a break point at *adr* and displays a list of all break points. If *adr* is missing, the routine simply displays the break points. If *adr* is specified, it is added to the list of active break points. The operation code that was at *adr* is replaced with a BRK instruction; it then modifies the BRK vector to point to the MON+ break point handler, after first saving the original value.

The optional label parameter allows a symbolic name to be assigned to the break point as it is defined.

SUB [*adr1*][*adr2*][*adr3*

... *I*]

Displays the difference of the operands (*adr1* - *adr2* ...). Zero or more operands are allowed. If more than two operands are supplied, tile second through tile last are all subtracted from the first.

SYMBOL [*adr* *label*]

Associates *adr* with the symbol *label*. If *adr* is already in the symbol table replaces that entry with *label*, but leaves the break flag intact. If *label* is already assigned to another address, an error message is displayed and the

MON+ Symbolic Debugger

command is ignored. If no operands are specified, the entire symbol table is displayed.

Once a symbol has been defined, it may be used anywhere an *adr* may be used, including within the mini-assembler. For example, if MYLAB is associated the address \$2000 (SYM 2000 MYLAB), these two statements produce identical results:

```
LIST 2000
LIST @MYLAB
```

Or from the mini-assembler:

```
3000: LDA @MYLAB
```

or like so:

```
ADD 10 @MYLAB
```

The result is \$2010.

TRACE [*adr*]

Executes (and traces) code starting at *adr*. If the operand is missing, it executes the instruction at the location of the current program counter stored at \$3A and \$313. When this command is invoked, the instruction a *adr* is executed, and the instruction mnemonic and the contents of the register are displayed. The following single-key commands are active during a trace:

SPACE	single steps one instruction, then pauses.
RETURN	traces quickly until a key is pressed.
F	causes a fast trace (turns off display) until and RTS is encountered.
R	executes a subroutine in real time (only available after a JSR is displayed; causes a fast-trace if another instruction is displayed.
C	continues the program in real time (no trace).

MON+ Symbolic Debugger

ESC returns to the MON+ command handler.

VECTOR

Displays the current RESET, BRK and IRQ vectors. Their values may be changed as each vector is displayed in turn. Press RETURN to leave the contents alone, or enter a new hex value to change the contents of the register being displayed. (Use with caution!)

WRITE *block1*[.*block2*] *adr*[,*Sslot*,*Ddrive*]

Writes the disk blocks starting with *block1* and continuing to *block2* from memory starting at *adr*. Optional slot and drive parameters may be specified. Because the command is potentially dangerous, it responds with the 'Are you sure?' prompt.

MON+ COMMAND SUMMARY

ADD	[adr1[adr2[adr3 ...]]]	addition: <i>adr1</i> + <i>adr2</i>
AND	[adr1[adr2[adr3 ...]]]	logical and: <i>adr1</i> AND <i>adr2</i>
ASM	adr	enters mini-assembler
BLOAD	filename	load binary file into memory
BRUN	filename	loads and runs binary file
CONTINU		continue program execution
CAT	filename	displays catalog
CLRB	adr	clear break point
CLRSYM		clear symbol table
COMPARE	adr1.adr2 adr3	compare memory
CONFIG		configure debugger
EOR	[adr1[adr2[adr3...]]]	exclusive or: <i>adr1</i> EOR <i>adr2</i>
FIND	adr1.adr2 list	find <i>list</i> in memory range <i>adr1</i> - <i>adr2</i>
FILL	adr1.adr2 byte	fill memory range <i>adr1</i> - <i>adr2</i> with <i>byte</i>
GO	[adr]	execute code at <i>adr</i> (via JSR)
GETSYM	adr	gets symbol table entries from memory
HELP		list commands
JUMP	[adr]	execute code at <i>adr</i> (via JMP)
LIST	adr1 [.adr2] [ln]	disassemble code
LABEL	[adr label]	define label; same as SYMBOL
MEM	adr1 [.adr2]	display or change memory byte (or range)
MOVE	adr1.adr2 adr3	copy memory range <i>adr1</i> - <i>adr2</i> to <i>adr3</i>
NEGATE	adr	two's complement: 0 MINUS <i>adr</i>
NOT	adr	one's complement: <i>adr</i> EOR #\$FF
OR	[adr1[adr2[adr3...]]]	logical or: <i>adr1</i> OR <i>adr2</i>
PAGE	[adr]	display memory page
PREFIX	filename	set prefix
PROFF		turns off output to the printer
PRON		turns on output to the printer
QUIT		re-enters ORCA monitor
READ	block1 [.block2] adr[,S,D]	read disk blocks
REG		display/change 6502 registers
SETB	[adr] [label]	set break point
SUB	[adr1[adr2[adr3...]]]	subtraction: <i>adr1</i> - <i>adr2</i>
SYMBOL	[adr label]	associates <i>label</i> with <i>adr</i> in symbol table
TRACE	[adr]	trace program
VECTOR		display/change RESET, BREAK and IRQ vectors
WRITE	block1.block2] adr[,S,D]	write disk blocks