


# Booting Procedure and kernel Parameters

## Diagram Booting process:-



**BIOS:** - Perform POST → Loads MBR

**MBR:** - Loads GRUB2Boot Loader

**GRUB2:** - Loads the vmlinuzkernel image → Extracts the contents of initramfsimage

**KERNEL:** - Loads necessary driver modules from initrd image → Starts systems 1st process -systemd

**SYSTEMD:** - Reads configuration files from the /etc/systemd directory →

- Reads file linked by /etc/systemd/system/default.target →
- Brings the system to the state defined by the system target

## GRUB 2 menu-configuration

```
[root@vivek ~]# cat /etc/default/grub
GRUB_TIMEOUT=5
GRUB_DISTRIBUTOR="$(sed 's, release .*$,,g' /etc/system-release)"
GRUB_DEFAULT=saved
GRUB_DISABLE_SUBMENU=true
GRUB_TERMINAL_OUTPUT="console"
GRUB_CMDLINE_LINUX="crashkernel=auto resume=/dev/mapper/rhel-swap rd.lvm.lv=rhel/root rd.lvm.lv=rhel/swap rhgb quiet"
GRUB_DISABLE_RECOVERY="true"
GRUB_ENABLE_BLSCFG=true
```

## list of default helper scripts located

```
[root@vivek grub2]# ll /etc/grub.d
total 84
-rwxr-xr-x. 1 root root 8958 Dec 5 2019 00_header
-rwxr-xr-x. 1 root root 1043 Dec 11 2019 00_tuned
-rwxr-xr-x. 1 root root 1240 Dec 5 2019 01_menu_auto_hide
-rwxr-xr-x. 1 root root 232 Dec 5 2019 01_users
-rwxr-xr-x. 1 root root 13434 Dec 5 2019 10_linux
-rwxr-xr-x. 1 root root 11696 Dec 5 2019 20_linux_xen
-rwxr-xr-x. 1 root root 2559 Dec 5 2019 20_ppc_terminfo
-rwxr-xr-x. 1 root root 10670 Dec 5 2019 30_os-prober
-rwxr-xr-x. 1 root root 1412 Dec 5 2019 30_uefi-firmware
-rwxr-xr-x. 1 root root 214 Dec 5 2019 40_custom
-rwxr-xr-x. 1 root root 216 Dec 5 2019 41_custom
-rw-r--r--. 1 root root 483 Dec 5 2019 README
```

## Booting Procedure and kernel Parameters

### To view all available targets

```
[root@vivek grub2]# systemctl list-units --type=target --all
```

UNIT	LOAD	ACTIVE	SUB	DESCRIPTION
basic.target	loaded	active	active	Basic System
cryptsetup.target	loaded	active	active	Local Encrypted Volumes
emergency.target	loaded	inactive	dead	Emergency Mode
getty-pre.target	loaded	inactive	dead	Login Prompts (Pre)
getty.target	loaded	active	active	Login Prompts
graphical.target	loaded	active	active	Graphical Interface
initrd-fs.target	loaded	inactive	dead	Initrd File Systems

### To view all targets installed on disk

```
[root@vivek grub2]# systemctl list-unit-files --type=target --all
```

UNIT	FILE	STATE
anaconda.target		static
basic.target		static
bluetooth.target		static
cryptsetup-pre.target		static
cryptsetup.target		static
ctrl-alt-del.target		disabled
default.target		indirect

### To view current default target, run

```
[root@vivek grub2]# systemctl get-default
```

graphical.target

### switch to a different target

```
[root@vivek grub2]# systemctl isolate multi-user.target
```

### To set a default target, run

```
[root@vivek ~]# systemctl set-default multi-user.target
Removed /etc/systemd/system/default.target.
Created symlink /etc/systemd/system/default.target → /usr/lib/systemd/system/multi-user.target.
[root@vivek ~]# systemctl get-default
multi-user.target
```

### Output

```
Red Hat Enterprise Linux 8.2 (Ootpa)
Kernel 4.18.0-193.el8.x86_64 on an x86_64

Activate the web console with: systemctl enable --now cockpit.socket

vivek login: _
```