

# Configuring the self-hosted runner application as a service

## In this article

- Installing the service
- Installing the service
- Starting the service
- Checking the status of the service
- Stopping the service
- Uninstalling the service
- Customizing the self-hosted runner service
- Customizing the self-hosted runner service

You can configure the self-hosted runner application as a service to automatically start the runner application when the machine starts.

Mac Windows Linux

**Note:** GitHub-hosted runners are not currently supported on GitHub Enterprise Server. You can see more information about planned future support on the [GitHub public roadmap](#).

**Note:** You must add a runner to GitHub Enterprise Server before you can configure the self-hosted runner application as a service. For more information, see "[Adding self-hosted runners](#)."

For Linux systems that use `systemd`, you can use the `svc.sh` script that is created after successfully adding the runner to install and manage using the application as a service.

On the runner machine, open a shell in the directory where you installed the self-hosted runner application. Use the commands below to install and manage the self-hosted runner service.

**Note:** Configuring the self-hosted runner application as a service on Windows is part of the application configuration process. If you have already configured the self-hosted runner application but did not choose to configure it as a service, you must remove the runner from GitHub and re-configure the application. When you re-configure the application, choose the option to configure the application as a service.

For more information, see "[Removing self-hosted runners](#)" and "[Adding self-hosted runners](#)."

You can manage the runner service in the Windows **Services** application, or you can use PowerShell to run the commands below.

**Note:** You must add a runner to GitHub Enterprise Server before you can configure the self-hosted runner application as a service. For more information, see "[Adding self-hosted runners](#)."

On the runner machine, open a shell in the directory where you installed the self-hosted runner application. Use the commands below to install and manage the self-hosted runner service.

## Installing the service [↗](#)

---

❶ Stop the self-hosted runner application if it is currently running.

❷ Install the service with the following command:

```
sudo ./svc.sh install
```

❸ Alternatively, the command takes an optional `user` argument to install the service as a different user.

```
./svc.sh install USERNAME
```

## Installing the service [↗](#)

---

❶ Stop the self-hosted runner application if it is currently running.

❷ Install the service with the following command:

```
./svc.sh install
```

## Starting the service [↗](#)

---

Start the service with the following command:

```
sudo ./svc.sh start
```

```
Start-Service "actions.runner.*"
```

```
./svc.sh start
```

## Checking the status of the service [↗](#)

---

Check the status of the service with the following command:

```
sudo ./svc.sh status
```

```
Get-Service "actions.runner.*"
```

```
./svc.sh status
```

For more information on viewing the status of your self-hosted runner, see "[Monitoring and troubleshooting self-hosted runners](#)."

## Stopping the service [↗](#)

---

Stop the service with the following command:

```
sudo ./svc.sh stop
```

```
Stop-Service "actions.runner.*"
```

```
./svc.sh stop
```

## Uninstalling the service [↗](#)

---

- 1 Stop the service if it is currently running.
- 2 Uninstall the service with the following command:

```
sudo ./svc.sh uninstall
```

```
Remove-Service "actions.runner.*"
```

```
./svc.sh uninstall
```

## Customizing the self-hosted runner service [↗](#)

---

If you don't want to use the above default `systemd` service configuration, you can create a customized service or use whichever service mechanism you prefer. Consider using the `serviced` template at `actions-runner/bin/actions.runner.service.template` as a reference. If you use a customized service, the self-hosted runner service must always be invoked using the `runsvc.sh` entry point.

## Customizing the self-hosted runner service [↗](#)

---

If you don't want to use the above default `launchd` service configuration, you can create a customized service or use whichever service mechanism you prefer. Consider using the `plist` template at `actions-runner/bin/actions.runner.plist.template` as a reference. If you use a customized service, the self-hosted runner service must always be invoked using the `runsvc.sh` entry point.

### Legal