

## BGP Step 2 - Add the announcement network

Announcement network

Pre-configuration

BGP neighbor configurations.(Refer the [Enterprise SONiC] BGP Step 1 - Establish BGP Session)

Enter VTYSH mode

Procedure

Step 1. Announced 192.168.1.0/24 routing.

Switch#1

```
sonic# configure terminal
sonic(config)# router-id 3.3.3.3
sonic(config)# router bgp 65101
sonic(config-router)# neighbor 10.3.0.2 remote-as 65102
sonic(config-router)# address-family ipv4
sonic(config-router-af)# network 192.168.1.0/24
sonic(config-router)# end
```

Switch#2

```
sonic# configure terminal
sonic(config)# router-id 4.4.4.4
sonic(config)# router bgp 65102
sonic(config-router)# neighbor 10.3.0.3 remote-as 65101
sonic(config-router)# end
```

Note:

This configuration example says that network 192.168.1.0/24 will be announced to all neighbors.

(Optional)Redistribute routing entires such as local network, static route (refer to this article)

Step 2. Check network result

Switch#1

```
sonic# show ip bgp ipv4
BGP table version is 1, local router ID is 3.3.3.3, vrf id 0
Default local pref 100, local AS 65101
Status codes:  s suppressed, d damped, h history, * valid, > best, = multipath,
                i internal, r RIB-failure, S Stale, R Removed
Nexthop codes: @NNN nexthop's vrf id, < announce-nh-self
Origin codes:  i - IGP, e - EGP, ? - incomplete
```

Network	Next Hop	Metric	LocPrf	Weight	Path
*> 192.168.1.0/24	0.0.0.0	0		32768	i

Displayed 1 routes and 1 total paths

Switch#2

```
sonic# show ip bgp neighbors 10.3.0.3 routes
BGP table version is 1, local router ID is 4.4.4.4, vrf id 0
Default local pref 100, local AS 65102
Status codes:  s suppressed, d damped, h history, * valid, > best, = multipath,
                i internal, r RIB-failure, S Stale, R Removed
Nexthop codes: @NNN nexthop's vrf id, < announce-nh-self
Origin codes:  i - IGP, e - EGP, ? - incomplete
```

Network	Next Hop	Metric	LocPrf	Weight	Path
*> 192.168.1.0/24	10.3.0.3	0		0	65101 i

Displayed 1 routes and 1 total paths

Step 3. Save the setting.

```
sonic# write
```

Note: this version of vtysh never writes vtysh.conf  
Building Configuration...  
Integrated configuration saved to /etc/frr/frr.conf  
[OK]