

Create users in SONiC

Create a user with the Home Directory.

Step 1: Create a user.

```
admin@sonic:~$ sudo useradd -m newuser
```

Note:

-m: this option is to create the user home directory as /home/"username".

Step 2: Setting the password for "newuser".

```
admin@sonic:~$ sudo passwd newuser
```

New password:

Retype new password:

passwd: password updated successfully

Result:

```
admin@sonic:/home$ ls -al
total 20
drwxr-xr-x 1 root  root  4096 Oct 14 08:04 .
drwxr-xr-x 1 root  root  4096 Oct 12 08:33 ..
drwxr-xr-x 1 admin admin 4096 Oct 13 02:06 admin
drwxr-xr-x 2 newuser newuser 4096 Oct 14 08:04 newuser
```

Login to the SONiC with "newuser".

sonic login: **newuser**

Password:

Linux sonic 5.10.0-8-2-amd64 #1 SMP Debian 5.10.46-4 (2021-08-03) x86_64

You are on

```

_ _ _ _ _
/_|/_\|\|(_)/_|
\_ \| \| \| \| \|
_ ) \| \| \| \| _
|_|/_\|/_\|/_\|_|
```

-- Software for Open Networking in the Cloud --

Unauthorized access and/or use are prohibited.
All access and/or use are subject to monitoring.

Help: <http://azure.github.io/SONiC/>

Last login: Fri Oct 14 08:22:08 UTC 2022 from 188.188.36.10 on pts/1

\$

\$ id

uid=1001(newuser) gid=1002(newuser) groups=1002(newuser)

\$

\$ groups

newuser

Allow the existing users to do the configuration.

Step 1: add the group of the "sudo" and "docker" to the user.

admin@sonic:~\$ `sudo usermod -G sudo,docker newuser`

Note:

-G: this option is for adding the secondary groups and allows add multiple groups.

The group of the "sudo" allows users could do the command with sudo.

The group of the "docker" allows users could login to the FRR to set the routing setting.

Result:

sonic login: newuser

Password:

Linux sonic 5.10.0-8-2-amd64 #1 SMP Debian 5.10.46-4 (2021-08-03) x86_64

You are on

```

_ _ _ _ _
/ _ | / _ \ \ | ( ) / _ |
\_ \ \ \ \ \ \ \ \ \
_ ) | | | | \ | | | _
| _ / \ _ / | | \ | | \ _ |
```

-- Software for Open Networking in the Cloud --

Unauthorized access and/or use are prohibited.
All access and/or use are subject to monitoring.

Help: <http://azure.github.io/SONiC/>

Last login: Tue Oct 25 03:13:23 UTC 2022 from 188.188.36.10 on pts/1

\$

\$ groups

newuser **sudo docker**

\$

\$ sudo config interface ip add Ethernet0 192.168.1.1/24

\$ show ip int

Interface	Master	IPv4 address/mask	Admin/Oper	BGP Neighbor	Neighbor IP
Ethernet0		192.168.1.1/24	up/down	N/A	N/A
docker0		240.127.1.1/24	up/down	N/A	N/A
eth0		188.188.36.204/16	up/up	N/A	N/A
lo		127.0.0.1/16	up/up	N/A	N/A

\$

\$ vtysh

Hello, this is FRRouting (version 8.1).

Copyright 1996-2005 Kunihiro Ishiguro, et al.

sonic#

Change the Login Shell for the existing user.

Step 1: Specify the shell for the existing user.

admin@sonic:~\$ **sudo usermod -s /bin/bash newuser**

Note:

- When create a user without specify the shell, it will use /bin/sh.
 - The default "admin" use the /bin/bash.
1. "/bin/sh" cannot press tab to check what command can use.

2. "bin/sh" cannot see the path from the command line.

/bin/sh

\$

\$ sudo config interface ip -----> press the tab

\$

\$

\$ cd /etc/sonic

\$ pwd

/etc/sonic

/bin/bash

newuser@sonic:~\$

newuser@sonic:~\$ sudo config interface ip -----> press the tab

ip ipv6

newuser@sonic:~\$

newuser@sonic:~\$

newuser@sonic:~\$ cd /etc/sonic/

newuser@sonic:/etc/sonic\$