

Article Number: 000220585

 [Print](#)


## NetWorker: How to configure a Smart Scale device on an NVE Server or Storage Node

Summary: Unable to label to Smart Scale device in NetWorker Virtual Edition Server (NVE) and Storage Node. This is due to the entfirewall no permitting outbound connections to port 2053.

### Article Content

#### Instructions

Create a custom outbound firewall to port 2053 of the Smart Scale server on the NetWorker Virtual Edition (NVE) Server and Storage node:

 **NOTE:** The below steps are intended for NetWorker Virtual Edition servers and storage nodes. If the NetWorker server and storage node are from another operating system vendor, see operating system-specific documentation for creating and modifying firewall settings.

1. Log in to the NVE as admin, then switch to root user:

```
sudo su -
```

2. As a root user run, run the following script to modify the `entfirewall` rules:

```
/usr/local/avamar/lib/admin/security/ent-edit-firewall-rules.sh
```

3. Enter 1 to use the Add a custom rule option:

```
Choose an Action
-----
1) Add a custom rule
2) Remove a custom rule
3) List Current Custom Rules
4) Exit
5) Save Changes
Enter desired action: 1
```

4. Select 1IPv4 rule:

```
Firewall Rule Types
-----
1) IPv4 Rule
2) IPv6 Rule
Enter Firewall Rule Type: 1
```

5. Select 1 OUTPUT rule:

```
Firewall Chains
-----
1) OUTPUT
2) INPUT
3) LOGDROP
4) FORWARD
Select Chain: 1
```

6. Select 1 TCP rule:

```
Protocol
-----
1) TCP
2) UDP
3) ICMP
Enter Protocol: 1
```

7. Leave the source IP field blank and press Enter:

```
Enter source IP (leave blank for none):
```

8. Leave the source port field blank and press Enter:

```
Enter source port (leave blank for none):
```

9. Leave the Destination IP Address blank and press Enter:

```
Enter Destination IP Address (leave blank for none):
```

10. Enter port 2053 for Destination Port:

```
Enter Destination Port (Use comma for multiple ports. Leave blank for none): 2053
```

11. Enter 1 for ACCEPT:

```
Targets
-----
1) ACCEPT
2) REJECT
3) DROP
4) LOGDROP
Select Target: 1
```

12. Enter A to append:

```
Run Order
-----
I) Insert (Inserts rule before default AV Firewall rules are applied)
A) Append (Standard behavior. Rule is appended, with default AV Firewall rules taking precedent)

Select run order for this rule [A]:A
```

13. Confirm adding a custom rule:

```
Add rule |||2053|tcp||ACCEPT|OUTPUT|A to custom rules file? (Y/N): Y
```

14. Answer No to adding another rule:

```
Add another firewall rule? (Y/N): N
```

15. Answer Yes to return to the main menu:

```
Return to main menu? (Y/N): Y
```

16. Save changes, option 5, answer No to return to the main menu:

```
Choose an Action
-----
1) Add a custom rule
2) Remove a custom rule
3) List Current Custom Rules
4) Exit
5) Save Changes
Enter desired action: 5
```

17. Confirm the changes.

```
Save and execute rules now? (Y/N): Y

Rules have been saved to /usr/local/avamar/lib/admin/security/entfwb_custom_config.txt
[DONE]
```

18. Restart entfirewall services:

```
systemctl restart entfirewall
```

After this point, you can label the Smart Scale device.

Article Properties

---

Product

PowerProtect Data Domain Management Center

Last Published Date

21 Feb 2024

Version

2

Article Type

How To