

The decNumber C library

Mike Cowlshaw

IBM Fellow
IBM UK Laboratories

mfc@uk.ibm.com

Table of Contents

	5
	9
Example 1 – simple addition	11
Example 2 – compound interest	12
Example 3 – passive error handling	13
Example 4 – active error handling	14
Example 5 – compressed formats	16
Example 6 – Packed Decimal numbers	18
Example 7 – Using the decQuad module	19
Example 8 – Using decQuad with decNumber	20
	21
decContext module	22
Definitions	24
Functions	25
decNumber module	30
Definitions	32
Functions	32
Conversion functions	33
Arithmetic and logical functions	34
Utility functions	41
decimal32, decimal64, and decimal128 modules	48
Definitions	48
Functions	49
decFloats modules	52
Definitions	53
Functions	53
decPacked module	67
Definitions	67
Functions	67
	69
Customization parameters	70
Tuning parameters	71
Print and testing parameters	72
	73
Description of the tables	73

decDouble performance tables 74
decQuad performance tables 76
Notes 77

79

87

Overview

The `decNumber` library implements the ¹in ANSI C. This specification defines a decimal arithmetic which meets the requirements of commercial, financial, and human-oriented applications. It also matches the decimal arithmetic in the IEEE 754 Standard for Floating Point Arithmetic.²

The library fully implements the specification, and hence supports integer, fixed-point, and floating-point decimal numbers directly, including infinite, NaN (Not a Number), and subnormal values. Both arbitrary-precision and fixed-size representations are supported.

The arbitrary-precision code is optimized and tunable for common values (tens of digits) but can be used without alteration for up to a billion digits of precision and 9-digit exponents. It also provides functions for conversions between concrete representations of decimal numbers, including Packed BCD (4-bit Binary Coded Decimal) and the three primary IEEE 754 fixed-size formats of decimal floating-point (`decimal32`, `decimal64`, and `decimal128`).

The three fixed-size formats are also supported by three modules called *decFloats* (see page 52), which have an extensive set of functions that work directly from the formats and provide arithmetical, logical, and shifting operations, together with conversions to binary integers, Packed BCD, and 8-bit BCD. Most of the functions defined in IEEE 754 are included, together with other functions outside the scope of that standard but essential for a decimal-only language implementation.

Library structure

The library comprises several modules (corresponding to classes in an object-oriented implementation). Each module has a *header* file (for example, `decNumber.h`) which defines its data structure, and a *source* file of the same name (, `decNumber.c`) which implements the operations on that data structure. These correspond to the instance variables and methods of an object-oriented design.

The core of the library is the *decNumber* module. This uses an arbitrary-precision decimal number representation designed for efficient computation in software and implements the arithmetic and logical operations, together with a number of conversions and utilities. Once a number is held as a `decNumber`, no further conversions are necessary to carry out arithmetic.

Most functions in the `decNumber` module take as an argument a *decContext* structure, which provides the context for operations (precision, rounding mode,) and also controls the handling of exceptional conditions (corresponding to the flags and trap enablers in a hardware floating-point implementation).

¹ See <http://speleotrove.com/decimal/> for details.

² Approved June 2008, expected to be published later in the year.

The decNumber representation is variable-length and machine-dependent (for example, it contains integers which may be big-endian or little-endian).

In addition to the arbitrary-precision decNumber format, three fixed-size compact formats are provided for conversions and interchange.³ These formats are endian-dependent but otherwise are machine-independent:

- decimal32* a 32-bit decimal floating-point representation which provides 7 decimal digits of precision in a compressed format
- decimal64* a 64-bit decimal floating-point representation which provides 16 decimal digits of precision in a compressed format
- decimal128* a 128-bit decimal floating-point representation which provides 34 decimal digits of precision in a compressed format.

A fourth, machine-independent, Binary Coded Decimal (BCD) format is also provided:

- decPacked* The decPacked format is the classic packed decimal format implemented by IBM S/360 and later machines, where each digit is encoded as a 4-bit binary sequence (BCD) and a number is ended by a 4-bit sign indicator. The decPacked module accepts variable lengths, allowing for very large numbers (up to a billion digits), and also allows the specification of a *scale*.

The module for each format provides conversions to and from the core decNumber format. The decimal32, decimal64, and decimal128 modules also provide conversions to and from character string format.

The decimal32, decimal64, and decimal128 formats are also supported directly by three modules which can be used stand-alone (that is, they have no dependency on the decNumber module). These are:

- decSingle* a module that provides the functions for the decimal32 format; this format is intended for storage and interchange only and so the module provides utilities and conversions but no arithmetic functions
- decDouble* a module that provides the functions for the decimal64 format; this format is an IEEE 754 *basic format* and so a full set of arithmetic and other functions is included
- decQuad* a module that provides the functions for the decimal128 format; this format is an IEEE 754 *basic format*; it contains the same set of functions as decDouble.⁴

These modules use the same context mechanism (decContext) as decNumber and so can be used together with the decNumber module when required in order to use the mathematical functions in that module or to use its arbitrary-precision capability. Examples are included in the User's Guide (see page 9).

Relevant standards

It is intended that, where applicable, functions provided in the decNumber package follow the requirements of:

- the decimal arithmetic requirements of IEEE 754 except that:

³ See <http://speleotrove.com/decimal/decbits.html> for details of the formats.

⁴ Except for two which convert to or from a wider format.

1. the IEEE remainder operator (`decNumberRemainderNear`) is restricted to those values where the intermediate integer can be represented in the current precision, because the conventional implementation of this operator would be very long-running for the range of numbers supported (up to $\pm 10^{1,000,000,000}$).
 2. the mathematical functions in the `decNumber` module do not, in general, correspond to the recommended functions in IEEE 754 with the same or similar names; in particular, the *power* function has some different special cases, and most of the functions may be up to one unit wrong in the last place (note, however, that the *squareroot* function is correctly rounded)
- the floating-point decimal arithmetic defined in ANSI X3.274-1996⁵ (including errata through 2001); note that this applies to functions in the `decNumber` module only, with appropriate context.

Please advise the author of any discrepancies with these standards.

5

National Standards Institute, New York, 1996.

, American

User's Guide

To use the decNumber library efficiently it is best to first convert the numbers you are working with from strings or another coded representation into decNumber format, then carry out calculations on them, and finally convert them back into the desired string or coded format.

Conversions to and from the decNumber format are fast; they are usually faster than all but the simplest calculations (= +1, for example). Therefore, in general, the cost of conversions is small compared to that of calculation.

The coded formats currently provided for in the library are

- strings (ASCII bytes, terminated by ' \0 ', as usual for C)
- three formats of compressed floating-point decimals
- Packed Decimal numbers with optional scale.

However, when arbitrary-precision calculation is not required (that is, up to 34 digits of precision is all that is required) it is even more efficient to use one of the *decFloats* modules (see page 52) for arithmetic and other operations. The decFloats modules work directly from the decimal-encoded compressed formats and avoid the need for conversions to and from the decNumber format. Tables comparing the performance of the decFloats modules with decNumber can be found in Appendix A (see page 73).

The remainder of this section illustrates the performance of the decFloat modules.

ANSI C99 standard (ISO/IEC 9899:1999). If your C compiler does not supply `stdint.h`, the following will suffice:

```
/* stdint.h -- some standard integer types from C99 */
typedef unsigned char  uint8_t;
typedef          char   int8_t;
typedef unsigned short uint16_t;
typedef          short  int16_t;
typedef unsigned int   uint32_t;
typedef          int    int32_t;
typedef unsigned long long uint64_t;
typedef          long long int64_t;
```

You may need to change these if (for example) the `int` type in your compiler does not describe a 32-bit integer. If there are no 64-bit integers available with your compiler, set the `DECUSE64` tuning parameter (see page [70](#)) to 0; the last two typedefs above are then not needed.

4. One aspect of the examples is implementation-defined. It is assumed that the default handling of the SIGFPE signal is to end the program. If your implementation ignores this signal, the lines with `set.traps=0;` would not be needed in the simpler examples.

Example 1 – simple addition

This example is a simple test program which can easily be extended to demonstrate more complicated operations or to experiment with the functions available.

```
1. // example1.c -- convert the first two argument words to decNumber,
2. // add them together, and display the result
3.
4. #define DECNUMDIGITS 34           // work with up to 34 digits
5. #include "decNumber.h"           // base number library
6. #include <stdio.h>                // for printf
7.
8. int main(int argc, char *argv[]) {
9.     decNumber a, b;               // working numbers
10.    decContext set;                // working context
11.    char string[DECNUMDIGITS+14];  // conversion buffer
12.
13.    if (argc<3) {                  // not enough words
14.        printf("Please supply two numbers to add.\n");
15.        return 1;
16.    }
17.    decContextDefault(&set, DEC_INIT_BASE); // initialize
18.    set.traps=0;                    // no traps, thank you
19.    set.digits=DECNUMDIGITS;        // set precision
20.
21.    decNumberFromString(&a, argv[1], &set);
22.    decNumberFromString(&b, argv[2], &set);
23.    decNumberAdd(&a, &a, &b, &set);      // a=a+b
24.    decNumberToString(&a, string);
25.    printf("%s + %s => %s\n", argv[1], argv[2], string);
26.    return 0;
27. } // main
```

This example is a complete, runnable program. In later examples we'll leave out some of the “boilerplate”, checking, , but this one should compile and be usable as it stands.

Lines 1 and 2 document the purpose of the program.

Line 4 sets the maximum precision of decNumbers to be used by the program, which is used by the embedded header file in line 5 (and also elsewhere in this program).

Line 6 includes the C library for input and output, so we can use the `printf` function. Lines 8 through 11 start the `main` function, and declare the variables we will use. Lines 13 through 16 check that enough argument words have been given to the program.

Lines 17–19 initialize the `decContext` structure, turn off error signals, and set the working precision to the maximum possible for the size of decNumbers we have declared.

Lines 21 and 22 convert the first two argument words into numbers; these are then added together in line 23, converted back to a string in line 24, and displayed in line 25.

Note that there is no error checking of the arguments in this example, so the result will be NaN (Not a Number) if one or both words is not a number. Error checking is introduced in Example 3 (see page [13](#)).

Example 2 – compound interest

This example takes three parameters (initial amount, interest rate, and number of years) and calculates the final accumulated investment. For example:

100000 at 6.5% for 20 years => 352364.51

The heart of the program is:

```
1. decNumber one, mtwo, hundred;           // constants
2. decNumber start, rate, years;           // parameters
3. decNumber total;                        // result
4. decContext set;                         // working context
5. char string[DECNUMDIGITS+14];           // conversion buffer
6.
7. decContextDefault(&set, DEC_INIT_BASE);  // initialize
8. set.traps=0;                             // no traps
9. set.digits=25;                           // precision 25
10. decNumberFromString(&one, "1", &set);    // set constants
11. decNumberFromString(&mtwo, "-2", &set);
12. decNumberFromString(&hundred, "100", &set);
13.
14. decNumberFromString(&start, argv[1], &set); // parameter words
15. decNumberFromString(&rate, argv[2], &set);
16. decNumberFromString(&years, argv[3], &set);
17.
18. decNumberDivide(&rate, &rate, &hundred, &set); // rate=rate/100
19. decNumberAdd(&rate, &rate, &one, &set);    // rate=rate+1
20. decNumberPower(&rate, &rate, &years, &set); // rate=rate**years
21. decNumberMultiply(&total, &rate, &start, &set); // total=rate*start
22. decNumberRescale(&total, &total, &mtwo, &set); // two digits please
23.
24. decNumberToString(&total, string);
25. printf("%s at %s%% for %s years => %s\n",
26.        argv[1], argv[2], argv[3], string);
27. return 0;
```

These lines would replace the content of the main function in Example 1 (adding the check for the number of parameters would be advisable).

As in Example 1, the variables to be used are first declared and initialized (lines 1 through 12), with the working precision being set to 25 in this case. The parameter words are converted into decNumbers in lines 14–16.

The next four function calls calculate the result; first the rate is changed from a percentage (, 6.5) to a per annum rate (1.065). This is then raised to the power of the number of years (which must be a whole number), giving the rate over the total period. This rate is then multiplied by the initial investment to give the result.

Next (line 22) the result is rescaled so it will have only two digits after the decimal point (an exponent of -2), and finally (lines 24–26) it is converted to a string and displayed.

Example 3 – passive error handling

Neither of the previous examples provides any protection against invalid numbers being passed to the programs, or against calculation errors such as overflow. If errors occur, therefore, the final result will probably be NaN or infinite (decNumber result structures are always valid after an operation, but their value may not be useful).

One way to check for errors would be to check the *status* field of the decContext structure after every decNumber function call. However, as that field accumulates errors until cleared deliberately it is often more convenient and more efficient to delay the check until after a sequence is complete.

This passive checking is easily added to Example 2. Replace lines 14 through 22 in that example with (the original lines repeated here are unchanged):

```
1. decNumberFromString(&start, argv[1], &set);      // parameter words
2. decNumberFromString(&rate, argv[2], &set);
3. decNumberFromString(&years, argv[3], &set);
4. if (set.status) {
5.     printf("An input argument word was invalid [%s]\n",
6.           decContextStatusToString(&set));
7.     return 1;
8. }
9. decNumberDivide(&rate, &rate, &hundred, &set); // rate=rate/100
10. decNumberAdd(&rate, &rate, &one, &set);        // rate=rate+1
11. decNumberPower(&rate, &rate, &years, &set);     // rate=rate**years
12. decNumberMultiply(&total, &rate, &start, &set); // total=rate*start
13. decNumberRescale(&total, &total, &mtwo, &set); // two digits please
14. if (set.status & DEC_Errors) {
15.     set.status &= DEC_Errors;                  // keep only errors
16.     printf("Result could not be calculated [%s]\n",
17.           decContextStatusToString(&set));
18.     return 1;
19. }
```

Here, in the if statement starting on line 4, the error message is displayed if the *status* field of the *set* structure is non-zero. The call to `decContextStatusToString` in line 6 returns a string which describes a set status bit (probably “Conversion syntax”).

In line 14, the test is augmented by anding the *set.status* value with `DEC_Errors`. This ensures that only serious conditions trigger the message. In this case, it is possible that the `DEC_Inexact` and `DEC_Rounded` conditions will be set (if an overflow occurred) so these are cleared in line 15.

With these changes, messages are displayed and the main function ended if either a bad input parameter word was found (for example, try passing a non-numeric word) or if the calculation could not be completed (, try a value for the third argument which is not an integer).⁶

⁶ Of course, in a user-friendly application, more detailed and specific error messages are appropriate. But here we are demonstrating error handling, not user interfaces.

Example 4 – active error handling

The last example handled errors passively, by testing the context *status* field directly. In this example,

Here, a work variable is declared in line 1 and the signal handler function is registered (identified to the C run time) in line 3. The call to the `signal` function identifies the signal to be handled (`SIGFPE`) and the function (`signalHandler`) that will be called when the signal is raised, and enables the handler.

Next, in line 4, the `setjmp` function is called. On its first call, this saves the current point of execution into the `preserve` variable and then returns 0. The following lines (5–8) are then not executed and execution of the `main` function continues as before.

If a trap later occurs (for example, if one of the arguments is not a number) then the following takes place:

1. the `SIGFPE` signal is raised by the `decNumber` library
2. the `signalHandler` function is called by the C run time with argument `SIGFPE`
3. the function re-enables the signal, and then calls `longjmp`
4. this in turn causes the execution stack to be “unwound” to the point which was preserved in the initial call to `setjmp`
5. the `setjmp` function then returns, with the (non-0) value passed to it in the call to `longjmp`
6. the test in line 5 then succeeds, so line 6 clears any informational status bits in the `status` field in the context structure which was given to the `decNumber` routines and line 7 displays a message, using the same structure
7. finally, in line 8, the `main` function is ended by the `return` statement.

Of course, different behaviors are possible both in the signal handler, as already noted, and after the jump; the main program could prompt for new values for the input parameters and then continue as before, for example.

Example 5 – compressed formats

The previous examples all used `decNumber` structures directly, but that format is not necessarily compact and is machine-dependent. These attributes are generally good for performance, but are less suitable for the storage and exchange of numbers.

The `decimal32`, `decimal64`, and `decimal128` forms are provided as efficient, formats used for storing numbers of up to 7, 16 or 34 decimal digits respectively, in 4, 8, or 16 bytes. These formats are similar to, and are used in the same manner as, the C `float` and `double` data types.

Here's an example program. Like Example 1, this is runnable as it stands, although it's recommended that at least the argument count check be added.

```
1. // example5.c -- decimal64 conversions
2. #include "decimal64.h"           // decimal64 and decNumber library
3. #include <stdio.h>               // for (s)printf
4.
5. int main(int argc, char *argv[]) {
6.     decimal64 a;                 // working decimal64 number
7.     decNumber d;                 // working number
8.     decContext set;              // working context
9.     char string[DECIMAL64_String]; // number->string buffer
10.    char hexes[25];               // decimal64->hex buffer
11.    int i;                        // counter
12.
13.    decContextDefault(&set, DEC_INIT_DECIMAL64); // initialize
14.
15.    decimal64FromString(&a, argv[1], &set);
16.    // lay out the decimal64 as eight hexadecimal pairs
17.    for (i=0; i<8; i++) {
18.        sprintf(&hexes[i*3], "%02x ", a.bytes[i]);
19.    }
20.    decimal64ToNumber(&a, &d);
21.    decNumberToString(&d, string);
22.    printf("%s => %s=> %s\n", argv[1], hexes, string);
23.    return 0;
24. } // main
```

Here, the `#include` on line 2 not only defines the `decimal64` type, but also includes the `decNumber` and `decContext` header files. Also, if `DECNUMDIGITS` (see page 30) has not already been defined, the `decimal64.h` file sets it to 16 so that any `decNumbers` declared will be exactly the right size to take any `decimal64` without rounding.

The declarations in lines 6–11 create three working structures and other work variables; the `decContext` structure is initialized in line 13 (here, `set.traps` is 0).

Line 15 converts the input argument word to a `decimal64` (with a function call very similar to `decNumberFromString`). Note that the value would be rounded if the number needed more than 16 digits of precision.

Lines 16–19 lay out the `decimal64` as eight hexadecimal pairs in a string, so that its encoding can be displayed.

Lines 20–22 show how `decimal64` numbers are used. First the `decimal64` is converted to a `decNumber`, then arithmetic could be carried out, and finally the `decNumber` is converted back to some standard form (in this case a string, so it can be displayed in line 22). For example, if the input argument were “79”, the following would be displayed on a big-endian machine:

79 => 22 38 00 00 00 00 00 79 => 79

(On a little-endian machine the byte order would be reversed.)

The decimal32 and decimal128 forms are used in exactly the same way, for working with up to 7 or up to 34 digits of precision respectively. These forms have the same constants and functions as decimal64 (with the obvious name changes).

Like `decimal64.h`, the decimal32 and decimal128 header files define the `DECNUMDIGITS` constant (see page 30) to either 7 or 34 if it has not already been defined.

It is also possible to work with the decimal128 () formats directly, without converting to and from the `decNumber` format; this is much faster when only the fixed-size formats are needed. Example 7 (see page 19) shows how to use the `decQuad` module for calculations in the 128-bit format.

Example 6 – Packed Decimal numbers

This example reworks Example 2, starting and ending with Packed Decimal numbers. First, lines 4 and 5 of Example 1 (which Example 2 modifies) are replaced by the line:

```
1. #include "decPacked.h"
```

Then the following declarations are added to the main function:

```
1. uint8_t startpack[]={0x01, 0x00, 0x00, 0x0C}; // investment=100000
2. int32_t startscale=0;
3. uint8_t ratepack[]={0x06, 0x5C}; // rate=6.5%
4. int32_t ratescale=1;
5. uint8_t yearspack[]={0x02, 0x0C}; // years=20
6. int32_t yearsscale=0;
7. uint8_t respack[16]; // result, packed
8. int32_t resscale; // ..
9. char hexes[49]; // for packed->hex
10. int i; // counter
```

The first three pairs declare and initialize the three parameters, with a Packed Decimal byte array and associated scale for each. In practice these might be read from a file or database. The fourth pair is used to receive the result. The last two declarations (lines 9 and 10) are work variables used for displaying the result.

Next, in Example 2, line 5 is removed, and lines 14 through 26 are replaced by:

```
1. decPackedToNumber(startpack, sizeof(startpack), &startscale, &start);
2. decPackedToNumber(ratepack, sizeof(ratepack), &ratescale, &rate);
3. decPackedToNumber(yearspack, sizeof(yearspack), &yearsscale, &years);
4.
5. decNumberDivide(&rate, &rate, &hundred, &set); // rate=rate/100
6. decNumberAdd(&rate, &rate, &one, &set); // rate=rate+1
7. decNumberPower(&rate, &rate, &years, &set); // rate=rate**years
8. decNumberMultiply(&total, &rate, &start, &set); // total=rate*start
9. decNumberRescale(&total, &total, &mtwo, &set); // two digits please
10.
11. decPackedFromNumber(respack, sizeof(respack), &resscale, &total);
12.
13. // lay out the total as sixteen hexadecimal pairs
14. for (i=0; i<16; i++) {
15.     sprintf(&hexes[i*3], "%02x ", respack[i]);
16. }
17. printf("Result: %s (scale=%ld)\n", hexes, (long int)resscale);
```

Here, lines 1 through 3 convert the Packed Decimal parameters into decNumber structures. Lines 5-9 calculate and rescale the total, as before, and line 11 converts the final decNumber into Packed Decimal and scale. Finally, lines 13-17 lay out and display the result, which should be:

```
Result: 00 00 00 00 00 00 00 00 00 00 00 00 03 52 36 45 1c (scale=2)
```

Note that the number is right-aligned, with a sign nibble.

Example 7 – Using the decQuad module

This example reworks Example 1, but using the decQuad module for all conversions and the arithmetic.

```
1. // example7.c -- using decQuad to add two numbers together
2.
3. #include "decQuad.h"           // decQuad library
4. #include <stdio.h>             // for printf
5.
6. int main(int argc, char *argv[]) {
7.     decQuad a, b;              // working decQuads
8.     decContext set;            // working context
9.     char string[DECQUAD String]; // number->string buffer
10.
11.     if (argc<3) {              // not enough words
12.         printf("Please supply two numbers to add.\n");
13.         return 1;
14.     }
15.     decContextDefault(&set, DEC_INIT DECQUAD); // initialize
16.
17.     decQuadFromString(&a, argv[1], &set);
18.     decQuadFromString(&b, argv[2], &set);
19.     decQuadAdd(&a, &a, &b, &set); // a=a+b
20.     decQuadToString(&a, string);
21.
22.     printf("%s + %s => %s\n", argv[1], argv[2], string);
23.     return 0;
24. } // main
```

This example is a complete, runnable program. Like Example 1, it takes two argument words, converts them to a decimal format (in this case decQuad, the 34-digit format), adds them, and converts the result back to a string for display.

Line 3 includes the decQuad header file. This in turn includes the other necessary header, decContext. The context variable `set` is used to set the rounding mode for the conversions from string and for the add, and its status field is used to report any errors (not checked in this example). No other field in the context is used.

To compile and run this, only the files `example7.c`, `decContext.c`, and `decQuad.c` are needed.

To use the 16-digit format instead of the 34-digit format, change `decQuad` to `decDouble` and `QUAD` to `DOUBLE` in the example. Note that in this case the file `decQuad.c` is still needed (must be compiled), because `decDouble` requires `decQuad`.

Example 8 – Using decQuad with decNumber

This example shows how the decNumber and decQuad modules can be mixed, in this case to raise one number to the power of another. (In this case, the use of the decQuad module could be avoided – this is just to demonstrate how to use the two modules together.)

```
1. // example8.c -- using decQuad with the decNumber module
2.
3. #include "decQuad.h"           // decQuad library
4. #include "decimall28.h"       // interface to decNumber
5. #include <stdio.h>            // for printf
6.
7. int main(int argc, char *argv[]) {
8.     decQuad a;                 // working decQuad
9.     decNumber numa, numb;      // working decNumbers
10.    decContext set;             // working context
11.    char string[DECQUAD String]; // number->string buffer
12.
13.    if (argc<3) {               // not enough words
14.        printf("Please supply two numbers for power(2*a, b).\n");
15.        return 1;
16.    }
17.    decContextDefault(&set, DEC_INIT DECQUAD); // initialize
18.
19.    decQuadFromString(&a, argv[1], &set);      // get a
20.
```

□□□

)xample8.c.

Module descriptions

The section contains a detailed description of each of the modules in the library. Each description is in three parts:

1. An overview of the module and a description of its primary data structure.
2. A description of other definitions in the header (**.h**) file. This summarizes the content of the header file rather than detailing every constant as it is assumed that users will have a copy of the header file available.
3. A description of the functions in the source (**.c**) file. This is a detailed description of each function and how to use it, the intent being that it should not be necessary to have the source file available in order to use the functions.

The modules all conform to some general rules:

- They are reentrant (they have no static variables and may safely be used in multi-threaded applications), and use only aligned integers and strict aliasing.
- All data structures are passed by reference, for best performance. Data structures whose references are passed as inputs are never altered unless they are also used as a result. Where appropriate, functions return a reference to a result argument.
- Only arbitrary-precision calculations might allocate memory. Up to some maximum precision (chosen by a tuning parameter in the `decNumberLocal.h` file), even these calculations do not require allocated memory, except for rounded input arguments and some mathematical functions. Whenever memory is allocated, it is always released before the function returns or raises any traps. The latter constraint implies that long jumps may safely be made from a signal handler handling any traps, for example.
- The names of all modules start with the string “dec”, and the names of all public constants start with the string “DEC”.
- Public functions (and macros used as functions) in a module have names which start with the name of the module (for example, `decNumberAdd`). This naming scheme corresponds to the common naming scheme in object-oriented languages, where that function (method) might be called `decNumber.add`.
- The types `int` and `long` are not used; instead types defined in the C99 `stdint.h` header file are used to ensure integers are of the correct length.
- Strings always follow C conventions. That is, they are always terminated by a null character (`'\0'`).

decContext module

The decContext module defines the data structure used for providing the context for operations and for managing exceptional conditions. The decNumber module uses all of these fields for full control of arbitrary-precision arithmetic; the decFloats modules (decQuad,) are fixed-size and fixed-format and use only the *round* and *status* fields.

The decContext structure comprises the following fields:

<i>digits</i>	<p>The <i>digits</i> field is used to set the precision to be used for an operation. The result of an operation will be rounded to this length if necessary, and hence the space needed for the result decNumber structure is limited by this field.</p> <p><i>digits</i> is of type <code>int32_t</code>, and must have a value in the range 1 through 999,999,999.</p>																
<i>emax</i>	<p>The <i>emax</i> field is used to set the magnitude of the largest <i>adjusted exponent</i> that is permitted. The adjusted exponent is calculated as though the number were expressed in scientific notation (that is, except for 0, expressed with one non-zero digit before the decimal point).</p> <p>If the adjusted exponent for a result or conversion would be larger than <i>emax</i> then an overflow results.</p> <p><i>emax</i> is of type <code>int32_t</code>, and must have a value in the range 0 through 999,999,999.</p>																
<i>emin</i>	<p>The <i>emin</i> field is used to set the smallest <i>adjusted exponent</i> that is permitted for normal numbers. The adjusted exponent is calculated as though the number were expressed in scientific notation (that is, except for 0, expressed with one non-zero digit before the decimal point).</p> <p>If the adjusted exponent for a result or conversion would be smaller than <i>emin</i> then the result is subnormal. If the result is also inexact, an underflow results. The exponent of the smallest possible number (closest to zero) will be <i>emin-digits</i>+1.⁷ <i>emin</i> is usually set to <i>-emax</i> or to <i>-(emax-1)</i>.</p> <p><i>emin</i> is of type <code>int32_t</code>, and must have a value in the range -999,999,999 through 0.</p>																
<i>round</i>	<p>The <i>round</i> field is used to select the rounding algorithm to be used if rounding is necessary during an operation. It must be one of the values in the <code>rounding</code> enumeration:</p> <table><tr><td><code>DEC_ROUND_CEILING</code></td><td>Round towards +Infinity.</td></tr><tr><td><code>DEC_ROUND_DOWN</code></td><td>Round towards 0 (truncation).</td></tr><tr><td><code>DEC_ROUND_FLOOR</code></td><td>Round towards -Infinity.</td></tr><tr><td><code>DEC_ROUND_HALF_DOWN</code></td><td>Round to nearest; if equidistant, round down.</td></tr><tr><td><code>DEC_ROUND_HALF_EVEN</code></td><td>Round to nearest; if equidistant, round so that the final digit is even.</td></tr><tr><td><code>DEC_ROUND_HALF_UP</code></td><td>Round to nearest; if equidistant, round up.</td></tr><tr><td><code>DEC_ROUND_UP</code></td><td>Round away from 0.</td></tr><tr><td><code>DEC_ROUND_05UP</code></td><td>The same as <code>DEC_ROUND_UP</code>, except that rounding up only</td></tr></table>	<code>DEC_ROUND_CEILING</code>	Round towards +Infinity.	<code>DEC_ROUND_DOWN</code>	Round towards 0 (truncation).	<code>DEC_ROUND_FLOOR</code>	Round towards -Infinity.	<code>DEC_ROUND_HALF_DOWN</code>	Round to nearest; if equidistant, round down.	<code>DEC_ROUND_HALF_EVEN</code>	Round to nearest; if equidistant, round so that the final digit is even.	<code>DEC_ROUND_HALF_UP</code>	Round to nearest; if equidistant, round up.	<code>DEC_ROUND_UP</code>	Round away from 0.	<code>DEC_ROUND_05UP</code>	The same as <code>DEC_ROUND_UP</code> , except that rounding up only
<code>DEC_ROUND_CEILING</code>	Round towards +Infinity.																
<code>DEC_ROUND_DOWN</code>	Round towards 0 (truncation).																
<code>DEC_ROUND_FLOOR</code>	Round towards -Infinity.																
<code>DEC_ROUND_HALF_DOWN</code>	Round to nearest; if equidistant, round down.																
<code>DEC_ROUND_HALF_EVEN</code>	Round to nearest; if equidistant, round so that the final digit is even.																
<code>DEC_ROUND_HALF_UP</code>	Round to nearest; if equidistant, round up.																
<code>DEC_ROUND_UP</code>	Round away from 0.																
<code>DEC_ROUND_05UP</code>	The same as <code>DEC_ROUND_UP</code> , except that rounding up only																

⁷ See <http://speleotrove.com/decimal/decarith.html> for details.

	occurs if the digit to be rounded up is 0 or 5 and after Overflow the result is the same as for <code>DEC_ROUND_DOWN</code> .
	<code>DEC_ROUND_DEFAULT</code> The same as <code>DEC_ROUND_HALF_EVEN</code> .
<i>status</i>	<p>The <i>status</i> field comprises one bit for each of the exceptional conditions described in the specifications (for example, Division by zero is indicated by the bit defined as <code>DEC_Division_by_zero</code>). Once set, a bit remains set until cleared by the user, so more than one condition can be recorded.</p> <p><i>status</i> is of type <code>uint32_t</code> (unsigned integer). Bits in the field must only be set if they are defined in the <code>decContext</code> header file. In use, bits are set by the <code>decNumber</code> library modules when exceptional conditions occur, but are never reset. The library user should clear the bits when appropriate (for example, after handling the exceptional condition), but should never set them.</p>
<i>traps</i>	<p>The <i>traps</i> field is used to indicate which of the exceptional conditions should cause a <i>trap</i>. That is, if an exceptional condition bit is set in the <i>traps</i> field, then a trap event occurs when the corresponding bit in the <i>status</i> field is set and <code>decContextSetStatus</code> is called (which happens automatically at the end of any operation which sets a status bit).</p> <p>In this implementation, a trap is indicated by raising the signal <code>SIGFPE</code> (defined in <code>signal.h</code>), the Floating-Point Exception signal.</p> <p>Applications may ignore traps, or may use them to recover from failed operations. Alternatively, applications can prevent all traps by clearing the <i>traps</i> field, and inspect the <i>status</i> field directly to determine if errors have occurred.</p> <p><i>traps</i> is of type <code>uint32_t</code>. Bits in the field must only be set if they are defined in the <code>decContext</code> header file.</p> <p>Note that the result of an operation is always a valid number, but after an exceptional condition has been detected its value may be one of the <i>special values</i> (NaN or infinite). These values can then propagate through other operations without further conditions being raised.</p>
<i>clamp</i>	<p>The <i>clamp</i> field controls explicit exponent clamping, as is applied when a result is encoded in one of the compressed formats. When 0, a result exponent is limited to a maximum of <i>emax</i> and a minimum of <i>emin</i> (for example, the exponent of a zero result will be clamped to be in this range). When 1, a result exponent has the same minimum but is limited to a maximum of <i>emax</i>-(<i>digits</i>-1). As well as clamping zeros, this may cause the coefficient of a result to be padded with zeros on the right in order to bring the exponent within range.</p> <p>For example, if <i>emax</i> is +96 and <i>digits</i> is 7, the result 1.23E+96 would have a [<i>sign</i>, <i>coefficient</i>, <i>exponent</i>] of [0, 123, 94] if <i>clamp</i> were 0, but would give [0, 1230000, 90] if <i>clamp</i> were 1.</p> <p>Also when 1, <i>clamp</i> limits the length of NaN payloads to <i>digits</i>-1 (rather than <i>digits</i>) when constructing a NaN by conversion from a string.</p> <p><i>clamp</i> is of type <code>uint8_t</code> (an unsigned byte).</p>
<i>extended</i>	<p>The <i>extended</i> field controls the level of arithmetic supported. When 1, special values are possible, some extra checking required for IEEE 754 conformance is enabled, and subnormal numbers can result from operations (that is, results whose adjusted exponent</p>

is as low as $emin-(digits-1)$ are possible). When 0, the X3.274 subset is supported; in particular, -0 is not possible, operands are rounded, and the exponent range is balanced.

If *extended* will always be 1, then the DECSUBSET tuning parameter (see page 70) may be set to 0 in `decContext.h`. This will remove the *extended* field from the structure, and also remove all code that refers to it. This gives a 10%–20% speed improvement for many operations.

extended is of type `uint8_t` (an unsigned byte).

Please see the arithmetic specification for further details on the meaning of specific settings (for example, the rounding mode).

Definitions

The `decContext.h` header file defines the context used by most functions in the `decNumber` module; it is therefore automatically included by `decNumber.h`. In addition to defining the `decContext` data structure described above, it also includes:

- The enumeration of the rounding modes supported by this implementation (for the *round* field of the `decContext`).
- The `decClass` enumeration (and corresponding strings) which is used to classify numbers with the `decNumberClass` function (see page 41) or the equivalent functions in `decQuad`,
- The exceptional condition flags, used in the *status* and *traps* fields. The flags used can be modified by the `DECEXTFLAG` tuning parameter (see page 70).
- Constants describing the range of precision and adjusted exponent supported by the `decNumber` package.
- Groupings for the exceptional conditions flags indicating how they correspond to the named conditions defined in `Ibs fdingMeed` are pseadl oiger d e res `□X6ENU±_qqf`

Unlike the other status flags, which indicate error conditions, execution continues normally when these events occur and the result is a number (unless an error condition also occurs). As usual, any or all of the conditions can be enabled for traps and in this case the operation is completed before the trap takes place.

Note that of the above only the `DEC_Inexact` flag is set by the `decFloats` modules. The other informational flags are only set by the `decNumber` module.

Functions

The `decContext.c` source file contains the public functions defined in the header file, as follows. In all these functions, only status bits () that are defined in the `decContext.h` header file should be used.⁸

decContextClearStatus(context, status)

This function is used to clear (set to zero) one or more status bits in the *status* field of a `decContext`.

The arguments are:

context (decContext *) Pointer to the structure whose status is to be updated.
status (uint32_t) Any 1 (set) bit in this argument will cause the corresponding bit to be cleared in the context status field.

Returns *context*.

decContextDefault(context, kind)

This function is used to initialize a `decContext` structure to default values. It is strongly recommended that this function always be used to initialize a `decContext` structure, even if most or all of the fields are to be set explicitly (in case new fields are added to a later version of the structure).

The arguments are:

context (decContext *) Pointer to the structure to be initialized.
kind (int32_t) The kind of initialization to be performed. Only the values defined in the `decContext` header file are permitted (any other value will initialize the structure to a valid condition, but with the `DEC_Invalid_operation` status bit set).

When *kind* is `DEC_INIT_BASE`, the defaults for the ANSI X3.274 arithmetic subset are set. That is, the *digits* field is set to 9, the *emax* field is set to 999999999, the *round* field is set to `ROUND_HALF_UP`, the *status* field is cleared (all bits zero), the *traps* field has all the `DEC_Errors` bits set (`DEC_Rounded`, `DEC_Inexact`, `DEC_Lost_digits`, and `DEC_Subnormal` are 0), *clamp* is set to 0, and *extended* (if present) is set to 0.

When *kind* is `DEC_INIT_DECIMAL32` or `DEC_INIT_DECSINGLE`, defaults for a *decimal32* number using IEEE 754 rules are set. That is, the *digits* field is set to 7, the *emax* field is set to 96, the *emin* field is set to -95, the *round* field is set to `DEC_ROUND_HALF_EVEN`, the *status* field is cleared (all bits zero), the *traps* field is cleared (no traps are enabled), *clamp* is set to 1, and *extended* (if present) is set to 1.

When *kind* is `DEC_INIT_DECIMAL64` or `DEC_INIT_DECDOUBLE`, defaults for a

⁸ If “private” bits were allowed, future extension of the library with other conditions would be impossible.

decimal64 number using IEEE 754 rules are set. That is, the *digits* field is set to 16, the *emax* field is set to 384, the *emin* field is set to -383, and the other fields are set as for DEC_INIT_DECIMAL32.

When *kind* is DEC_INIT_DECIMAL128 or DEC_INIT_DECQUAD, defaults for a *decimal128* number using IEEE 754 rules are set. That is, the *digits* field is set to 34, the *emax* field is set to 6144, the *emin* field is set to -6143, and the other fields are set as for DEC_INIT_DECIMAL32.

Returns *context*.

decContextGetRounding(context)

This function is used to return the *round* (rounding mode) field of a decContext.

The argument is:

context (decContext *) Pointer to the structure whose rounding mode is to be returned.

Returns the enum `rounding` rounding mode.

decContextGetStatus(context)

This function is used to return the *status* field of a decContext.

The argument is:

context (decContext *) Pointer to the structure whose status is to be returned.

Returns the `uint32_t` status field.

decContextRestoreStatus(context, status, mask)

This function is used to restore one or more status bits in the *status* field of a decContext from a saved status field.

The arguments are:

context (decContext *) Pointer to the structure whose status is to be updated.

status (uint32_t) A saved status field (as saved by `decContextSaveStatus` or retrieved by `decContextGetStatus`).

mask (uint32_t) Any 1 (set) bit in this argument will cause the corresponding bit to be restored (set to 0 or 1, taken from the corresponding bit in *status*) in the context status field.

Returns *context*.

Note that setting a bit using this function does not cause a trap (use the `decContextSetStatus` function can be used to raise a trap, if desired).

decContextSaveStatus(context, mask)

This function is used to save one or more status bits from the *status* field of a decContext.

The arguments are:

context (decContext *) Pointer to the structure whose status is to be saved.
mask (uint32_t) Any 1 (set) bit in this argument will cause the corresponding bit to be saved from the context status field.

Returns the `uint32_t` which is the logical And of the context status field and the *mask*.

decContextSetRounding(context, rounding)

This function is used to set the rounding mode in the *round* field of a decContext.

The arguments are:

context (decContext *) Pointer to the structure whose rounding mode is to be set.
rounding (enum rounding) The rounding mode to be copied to the context *round* field.

Returns *context*.

decContextSetStatus(context, status)

This function is used to set one or more status bits in the *status* field of a decContext. If any of the bits being set have the corresponding bit set in the *traps* field, a trap is raised (regardless of whether the bit is already set in the *status* field). Only one trap is raised even if more than one bit is being set.

The arguments are:

context (decContext *) Pointer to the structure whose status is to be set.
status (uint32_t) Any 1 (set) bit in this argument will cause the corresponding bit to be set in the context status field.

Returns *context*.

Normally, only library modules use this function. Applications may clear status bits but should not set them (except, perhaps, for testing).

Note that a signal handler which handles a trap raised by this function may execute a C long jump, and hence control may not return from the function. It should therefore only be invoked when any state and resources used (such as allocated memory) are clean.

decContextSetStatusFromString(context, string)

This function is used to set a status bit in the *status* field of a decContext, using the name of the bit as returned by the `decContextStatusToString` function. If the bit being set has the corresponding bit set in the *traps* field, a trap is raised (regardless of whether the bit is already set in the *status* field).

The arguments are:

context (decContext *) Pointer to the structure whose status is to be set.
string (char *) A string which must be exactly equal to one that might be returned by `decContextStatusToString`. If the string is “No status”, the status is not changed and no trap is raised. If the string is “Multiple status”, or is not recognized, then the call is in error.

Returns *context* unless the *string* is in error, in which case `NULL` is returned.

Normally, only library and test modules use this function. Applications may clear status bits but should not set them (except, perhaps, for testing).

Note that a signal handler which handles a trap raised by this function may execute a C long jump, and hence control may not return from the function. It should therefore only be invoked when any state and resources used (such as allocated memory) are clean.

decContextSetStatusFromStringQuiet(context, string)

This function is identical to `decContextSetStatusFromString` except that the context *traps* field is ignored (, no trap is raised).

decContextSetStatusQuiet(context, status)

This function is identical to `decContextSetStatus` except that the context *traps* field is ignored (, no trap is raised).

decContextStatusToString(context)

This function returns a pointer (`char *`) to a human-readable description of a status bit. The string pointed to will be a constant.

The argument is:

context (decContext *) Pointer to the structure whose status is to be returned as a string. The bits set in the *status* field must comprise only bits defined in the header file.

If no bits are set in the *status* field, a pointer to the string “No status” is returned. If more than one bit is set, a pointer to the string “Multiple status” is returned.

Note that the content of the string pointed to is a programming interface (it is understood by the `decContextSetStatusFromString` function) and is therefore not language- or locale-dependent.

decContextTestEndian(quiet)

This function checks that the `DECLITEND` tuning parameter (see page 70) is set correctly.

The argument is:

quiet (uint8_t) If 0, a warning message is displayed (using *printf*) if `DECLITEND` is set incorrectly. If 1, no message is displayed.

Returns 0 if the `DECLITEND` parameter is correct, 1 if it is incorrect and should be set to 1, and -1 if it is incorrect and should be set to 0.

decContextTestSavedStatus(status, mask)

This function is used to test one or more status bits in a saved status field.

The arguments are:

status (uint32_t) A saved status field (as saved by `decContextSaveStatus` or retrieved by `decContextGetStatus`).

mask (uint32_t) Any 1 (set) bit in this argument will cause the corresponding bit in *status* to be included in the test.

Returns the uint32_t which is the logical And of *status* and *mask*.

decContextTestStatus(context, mask)

This function is used to test one or more status bits in a context.

The arguments are:

context (decContext *) Pointer to the structure whose status is to be tested.

mask (uint32_t) Any 1 (set) bit in this argument will cause the corresponding bit in context *status* field to be included in the test.

Returns the uint32_t which is the logical And of the context *status* field and *mask*.

decContextZeroStatus(context)

This function is used to clear (set to zero) all the status bits in the *status* field of a decContext.

The argument is:

context (decContext *) Pointer to the structure whose status is to be zeroed.

Returns *context*.

decNumber module

The decNumber module defines the data structure used for representing numbers in a form suitable for computation, and provides the functions for operating on those values.

The decNumber structure is optimized for efficient processing of relatively short numbers (tens or hundreds of digits); in particular it allows the use of fixed sized structures and minimizes copy and move operations. The functions in the module, however, support arbitrary precision arithmetic (up to 999,999,999 decimal digits, with exponents up to 9 digits).

The essential parts of a decNumber are the *coefficient*, which is the significand of the number, the *exponent* (which indicates the power of ten by which the *coefficient* should be multiplied), and the *sign*, which is 1 if the number is negative, or 0 otherwise. The numerical *value* of the number is then given by: $(-1)^{\text{sign}} \times \text{coefficient} \times 10^{\text{exponent}}$.

Numbers may also be a *special value*. The special values are *NaN* (Not a Number), which may be *quiet* (propagates quietly through operations) or *signaling* (raises the Invalid operation condition when encountered), and $\pm\text{infinity}$.

These parts are encoded in the four fields of the decNumber structure:

- digits* The *digits* field contains the length of the *coefficient*, in decimal digits.
digits is of type `int32_t`, and must have a value in the range 1 through 999,999,999.
- exponent* The *exponent* field holds the exponent of the number. Its range is limited by the requirement that the range of the *adjusted exponent* of the number be balanced and fit within a whole number of decimal digits (in this implementation, be -999,999,999 through +999,999,999). The adjusted exponent is the exponent that would result if the number were expressed with a single digit before the decimal point, and is therefore given by $\text{exponent} + \text{digits} - 1$.

When the *extended* flag in the context is 1, gradual underflow (using *subnormal* values) is enabled. In this case, the lower limit for the adjusted exponent becomes -999,999,999 - (*precision* - 1), where *precision* is the digits setting from the context; the adjusted exponent may then have 10 digits.
exponent is of type `int32_t`.
- bits* The *bits* field comprises one bit which indicates the *sign* of the number (1 for negative, 0 otherwise), 3 bits which indicate the special values, and 4 further bits which are unused and reserved. These reserved bits must be zero.

If the number has a special value, just one of the indicator bits (DECINF, DECNAN, or DECSNAN) will be set (along with DECNEG iff the sign is 1). If DECINF is set *digits* must be 1 and the other fields must be 0. If the number is a NaN, the *exponent* must be zero and the coefficient holds any diagnostic information (with *digits* indicating its length, as for finite numbers). A zero coefficient indicates no diagnostic information.
bits is of type `uint8_t` (an unsigned byte). Masks for the named bits, and some useful macros, are defined in the header file.
- lsu* The *lsu* field is one or more *units* in length (of type `decNumberUnit`, an unsigned integer), and contains the digits of the *coefficient*. Each unit represents one or more of the digits in the *coefficient* and has a binary value in the range 0 through $10^n - 1$, where *n* is the number of digits in a unit, set by the compile-time definition `DECDFUN` (see page 71).

The size of a unit is the smallest of 1, 2, or 4 bytes which will contain the maximum value held in the unit.

The units comprising the *coefficient* start with the least significant unit (lsu). Each unit except the most significant unit (msu) contains DECDPUN digits. The msu contains from 1 through DECDPUN digits, and must not be 0 unless *digits* is 1 (for the value zero). Leading zeros in the msu are never included in the *digits* count, except for the value zero.

The number of units predefined for the *lsu* field is determined by DECNUMDIGITS, which defaults to 1 (the number of units will be DECNUMDIGITS divided by DECDPUN, rounded up to a whole unit).

For many applications, there will be a known maximum length for numbers and DECNUMDIGITS can be set to that length, as in Example 1 (see page 11). In others, the length may vary over a wide range and it then becomes the programmer's responsibility to ensure that there are sufficient units available immediately following the decNumber *lsu* field. This can be achieved by enclosing the decNumber in other structures which append various lengths of unit arrays, or in the more general case by allocating storage with sufficient space for the other decNumber fields and the units of the number.

lsu is an array of type decNumberUnit (an unsigned integer whose length depends on the value of DECDPUN), with at least one element. If *digits* needs fewer units than the size of the array, remaining units are not used (they will neither be changed nor referenced). For special values, only the first unit need be 0.

It is expected that decNumbers will usually be constructed by conversions from other formats, such as strings or decimal64 structures, so the decNumber structure is in some sense an "internal" representation; in particular, it is machine-dependent.⁹

If DECDPUN were 4, the value -1234.50 would be encoded with:

```
digits = 6  
exponent = -2  
bits = 0x80  
lsu = { 3450 , 12 }
```

the value 0 would be:

```
digits = 1  
exponent = 0  
bits = 0x00  
lsu = { 0 }
```

and $-\infty$ (minus infinity) would be:

```
digits = 1  
exponent = 0  
bits = 0xC0  
lsu = { 0 }
```

⁹ The layout of an integer might be big-endian or little-endian, for example.

Definitions

The `decNumber.h` header file defines the `decNumber` data structure described above. It also includes:

- The tuning parameter `DECDPUN`.
This sets the number of digits held in one *unit* (see page 30), which in turn alters the performance and other characteristics of the library. Further details are given in the tuning section (see page 71).
If this parameter is changed, the `decNumber.c` source file must be recompiled for the change to have effect.
- The `decClass` enumeration (and corresponding strings) which is used to classify `decNumbers` with the `decNumberClass` function (see page 41).
- Constants naming the bits in the *bits* field, such as `DECNEG`, the sign bit.
- Definitions of the public functions and macros in the `decNumber` module.

Functions

The `decNumber.c` source file contains the public functions defined in the header file. These comprise conversions to and from strings, the arithmetic and logical operations, and some utility functions.

The functions all follow some general rules:

- Operands to the functions which are `decNumber` structures (referenced by an argument) are never modified unless they are also specified to be the result structure (which is always permitted).
Often, operations which do specify an operand and result as the same structure can be carried out in place, giving improved performance. For example, `x = +1`, using the `decNumberAdd` function, can be several times faster than `x = +1`.
- Each function forms its primary result by setting the content of one of the structures referenced by the arguments; a pointer to this structure is returned by the function.
- Exceptional conditions and errors are reported by setting a bit in the *status* field of a referenced `decContext` structure (see page 22). The corresponding bit in the *traps* field of the `decContext` structure determines whether a trap is then raised, as also described earlier.
- If an argument to a function is *corrupt* (it is a `NULL` reference, or it is an input argument and the content of the structure it references is inconsistent), the function is unprotected (may “crash”) unless `DECHECK` is enabled (see the next rule). However, in normal operation (that is, no argument is corrupt), the result will always be a valid `decNumber` structure. The value of the `decNumber` result may be infinite or a quiet NaN if an error was detected (, if one of the `DEC_Errors` bits (see page 24) is set in the `decContext status` field).
- For best performance, input operands are assumed to be valid (not corrupt) and are not checked unless `DECHECK` (see page 72) is 1, which enables full operand checking. Whether `DECHECK` is 0 or 1, the value of a result is undefined if an argument is corrupt. `DECHECK` checking is a diagnostic tool only; it will report the error and prevent code failure by ensuring that results are

valid numbers (unless the result reference is NULL), but it does not attempt to correct arguments.

Conversion functions

The conversion functions build a `decNumber` from a string, or lay out a `decNumber` as a character string. Additional Utility functions (see page 41) are included in the package for conversions to and from BCD strings and binary integers.

decNumberFromString(number, string, context)

This function is used to convert a character string to `decNumber` format. It implements the **to-number** conversion from the arithmetic specification.

The conversion is exact provided that the numeric string has no more significant digits than are specified in `context.digits` and the adjusted exponent is in the range specified by `context.emin` and `context.emax`. If there are more than `context.digits` digits in the string, or the exponent is out of range, the value will be rounded as necessary using the `context.round` rounding mode. The `context.digits` field therefore both determines the maximum precision for unrounded numbers and defines the minimum size of the `decNumber` structure required.

The arguments are:

<i>number</i>	(<code>decNumber *</code>) Pointer to the structure to be set from the character string.
<i>string</i>	(<code>char *</code>) Pointer to the input character string. This must be a valid numeric string, as defined in the appropriate specification. The string will not be altered.
<i>context</i>	(<code>decContext *</code>) Pointer to the context structure whose <i>digits</i> , <i>emin</i> , and <i>emax</i> fields indicate the maximum acceptable precision and exponent range, and whose <i>status</i> field is used to report any errors. If its <i>extended</i> field is 1, then special values ($\pm\text{Inf}$, $\pm\text{Infinity}$, $\pm\text{NaN}$, or $\pm\text{sNaN}$, independent of case) are accepted, and the sign and exponent of zeros are preserved. NaNs may also specify diagnostic information as a string of digits following the name.

Returns *number*.

Possible errors are `DEC_Conversion_syntax` (the string does not have the syntax of a number, which depends on the setting of *extended* in the context), `DEC_Overflow` (the adjusted exponent of the number is larger than `context.emax`), or `DEC_Underflow` (the adjusted exponent is less than `context.emin` and the conversion is not exact). If any of these conditions are set, the *number* structure will have a defined value as described in the arithmetic specification (this may be a subnormal or infinite value).

decNumberToString(number, string)

This function is used to convert a `decNumber` number to a character string, using scientific notation if an exponent is needed (that is, there will be just one digit before any decimal point). It implements the **to-scientific-string** conversion.

The arguments are:

<i>number</i>	(<code>decNumber *</code>) Pointer to the structure to be converted to a string.
<i>string</i>	(<code>char *</code>) Pointer to the character string buffer which will receive the converted number.

It must be at least 14 characters longer than the number of digits in the number
(`number->digits`).

Returns *string*.

No error is possible from this function. Note that non-numeric strings (one of `+Infinity`, `-Infinity`, `NaN`, or `sNaN`) are possible, and NaNs may have a `-` sign and/or diagnostic information.

decNumberToEngString(number, string)

This function is used to convert a `decNumber` number to a character string, using engineering notation (where the exponent will be a multiple of three, and there may be up to three digits before any decimal point) if an exponent is needed. It implements the **to-engineering-string** conversion.

The arguments and result are the same as for the `decNumberToString` function, and similarly no error is possible from this function.

Arithmetic and logical functions

The arithmetic and logical functions all follow the same syntax and rules, and are summarized below. They all take the following arguments:

- number* (`decNumber *`) Pointer to the structure where the result will be placed.
- lhs* (`decNumber *`) Pointer to the structure which is the left hand side (lhs) operand for the operation. This argument is omitted for monadic operations.
- rhs* (`decNumber *`) Pointer to the structure which is the right hand side (rhs) operand for the operation.
- context* (`decContext *`) Pointer to the context structure whose settings are used for determining the result and for reporting any exceptional conditions.

Each function returns *number*. The `decNumberFMA` function (see page 36) also takes a third numeric operand *fhs* (`decNumber *`), a pointer to the structure which is the “far hand side” operand for the operation.

Some functions, such as `decNumberExp`, are described as *mathematical functions*. These have some restrictions: `context.emax` must be $< 10^6$, `context.emin` must be $> -10^6$, and `context.digits` must be $< 10^6$. Non-zero operands to these functions must also fit within these bounds.

The precise definition of each operation can be found in the specification document.

decNumberAbs(number, rhs, context)

The *number* is set to the absolute value of the *rhs*. This has the same effect as `decNumberPlus` unless *rhs* is negative, in which case it has the same effect as `decNumberMinus`.

decNumberAdd(number, lhs, rhs, context)

The *number* is set to the result of adding the *lhs* to the *rhs*.

decNumberAnd(number, lhs, rhs, context)

The *number* is set to the result of the digit-wise logical *and* of *lhs* and *rhs*.

decNumberCompare(number, lhs, rhs, context)

This function compares two numbers numerically. If the *lhs* is less than the *rhs* then the *number* will be set to the value -1 . If they are equal (that is, when subtracted the result would be 0), then *number* is set to 0. If the *lhs* is greater than the *rhs* then the *number* will be set to the value 1. If the operands are not comparable (that is, one or both is a NaN) the result will be NaN.

decNumberCompareSignal(number, lhs, rhs, context)

This function compares two numbers numerically. It is identical to *decNumberCompare* except that all NaNs (including quiet NaNs) signal.

decNumberCompareTotal(number, lhs, rhs, context)

This function compares two numbers using the IEEE 754 total ordering. If the *lhs* is less than the *rhs* in the total order then the *number* will be set to the value -1 . If they are equal, then *number* is set to 0. If the *lhs* is greater than the *rhs* then the *number* will be set to the value 1.

The total order differs from the numerical comparison in that: $-\text{NaN} < -\text{sNaN} < -\text{Infinity} < -\text{finites} < -0 < +0 < +\text{finites} < +\text{Infinity} < +\text{sNaN} < +\text{NaN}$. Also, $1.000 < 1.0$ () and NaNs are ordered by payload.

decNumberCompareTotalMag(number, lhs, rhs, context)

This function compares the magnitude of two numbers using the IEEE 754 total ordering. It is identical to *decNumberCompareTotal* except that the signs of the operands are ignored and taken to be 0 (non-negative).

decNumberDivide(number, lhs, rhs, context)

The *number* is set to the result of dividing the *lhs* by the *rhs*.

decNumberDivideInteger(number, lhs, rhs, context)

The *number* is set to the integer part of the result of dividing the *lhs* by the *rhs*.

Note that it must be possible to express the result as an integer. That is, it must have no more digits than *context.digits*. If it does then *DEC_Division_impossible* is raised.

decNumberExp(number, rhs, context)

The *number* is set to *1* raised to the power of *rhs*, rounded if necessary using the digits setting in the *context* and using the *round-half-even* rounding algorithm.

Finite results will always be full precision and inexact, except when *rhs* is a zero or $-\text{Infinity}$ (giving 1 or 0 respectively). Inexact results will almost always be correctly rounded, but may be up to 1 (unit in last place) in error in rare cases.

This is a mathematical function; the 10^6 restrictions on precision and range apply as described above.

decNumberFMA(number, lhs, rhs, fhs, context)

The *number* is set to the result of multiplying the *lhs* by the *rhs* and then adding *fhs* to that intermediate result. It is equivalent to a multiplication followed by an addition except that the intermediate result is not rounded and will not cause overflow or underflow. That is, only the final result is rounded and checked.

This is a mathematical function; the 10^6 restrictions on precision and range apply as described above.

decNumberInvert(number, rhs, context)

The *number* is set to the result of the digit-wise inversion of *rhs* (A 0 digit becomes 1 and vice versa.)

decNumberLn(number, rhs, context)

The *number* is set to the natural logarithm (logarithm in base e) of *rhs*, rounded if necessary using the digits setting in the *context* and using the *round-half-even* rounding algorithm. *rhs* must be positive or a zero.

Finite results will always be full precision and inexact, except when *rhs* is equal to 1, which gives an exact result of 0. Inexact results will almost always be correctly rounded, but may be up to 1 (unit in last place) in error in rare cases.

This is a mathematical function; the 10^6 restrictions on precision and range apply as described above.

decNumberLogB(number, rhs, context)

The *number* is set to the adjusted exponent of *rhs*, according to the rules for the “logB” operation of IEEE 754. This returns the exponent of *rhs* as though its decimal point had been moved to follow the first digit while keeping the same value. The result is not limited by *emin* or *emax*.

decNumberLog10(number, rhs, context)

The *number* is set to the logarithm in base ten of *rhs*, rounded if necessary using the digits setting in the *context* and using the *round-half-even* rounding algorithm. *rhs* must be positive or a zero.

Finite results will always be full precision and inexact, except when *rhs* is equal to an integral power of ten, in which case the result is the exact integer.

Inexact results will almost always be correctly rounded, but may be up to 1 (unit in last place) in error in rare cases.

This is a mathematical function; the 10^6 restrictions on precision and range apply as described above.

decNumberMax(number, lhs, rhs, context)

This function compares two numbers numerically and sets *number* to the larger. If the numbers compare equal then *number* is chosen with regard to sign and exponent. Unusually, if one operand is a quiet NaN and the other a number, then the number is returned.

decNumberMaxMag(number, lhs, rhs, context)

This function compares the magnitude of two numbers numerically and sets *number* to the larger. It is identical to `decNumberMax` except that the signs of the operands are ignored and taken to be 0 (non-negative).

decNumberMin(number, lhs, rhs, context)

This function compares two numbers numerically and sets *number* to the smaller. If the numbers compare equal then *number* is chosen with regard to sign and exponent. Unusually, if one operand is a quiet NaN and the other a number, then the number is returned.

decNumberMinMag(number, lhs, rhs, context)

This function compares the magnitude of two numbers numerically and sets *number* to the smaller. It is identical to `decNumberMin` except that the signs of the operands are ignored and taken to be 0 (non-negative).

decNumberMinus(number, rhs, context)

The *number* is set to the result of subtracting the *rhs* from 0. That is, it is negated, following the usual arithmetic rules; this may be used for implementing a prefix minus operation.

decNumberMultiply(number, lhs, rhs, context)

The *number* is set to the result of multiplying the *lhs* by the *rhs*.

decNumberNextMinus(number, rhs, context)

The *number* is set to the closest value to *rhs* in the direction of $-\text{Infinity}$. This is computed as though by subtracting an infinitesimal amount from *rhs* using `DEC_ROUND_FLOOR`, except that no flags are set unless *rhs* is an sNaN.

This function is a generalization of the IEEE 754 *nextDown* operation.

decNumberNextPlus(number, rhs, context)

The *number* is set to the closest value to *rhs* in the direction of $+\text{Infinity}$. This is computed as though by adding an infinitesimal amount to *rhs* using `DEC_ROUND_CEILING`, except that no flags are set unless *rhs* is an sNaN.

This function is a generalization of the IEEE 754 *nextUp* operation.

decNumberNextToward(number, lhs, rhs, context)

The *number* is set to the closest value to *lhs* in the direction of *rhs*. This is computed as though by adding or subtracting an infinitesimal amount to *lhs* using `DEC_ROUND_CEILING` or `DEC_ROUND_FLOOR`, depending on whether *rhs* is larger or smaller than *lhs*. If *rhs* is numerically equal to *lhs* then the result is a copy of *lhs* with the *sign* taken from *rhs*. Flags are set as usual for an addition or subtraction except that if the operands are equal or the result is normal (finite, non-zero, and not subnormal) no flags are set.

This function is a generalization of the proposed IEEE 754 *nextAfter* operation.¹⁰

decNumberOr(number, lhs, rhs, context)

The *number* is set to the result of the digit-wise logical of *lhs* and *rhs*.

decNumberPlus(number, rhs, context)

The *number* is set to the result of adding the *rhs* to 0. This takes place according to the settings given in the *context*, following the usual arithmetic rules. This may therefore be used for rounding or for implementing a prefix plus operation.

decNumberPower(number, lhs, rhs, context)

The *number* is set to the result of raising the *lhs* to the power of the *rhs*, rounded if necessary using the settings in the *context*.

Results will be exact when the *rhs* has an integral value and the result does not need to be rounded, and also will be exact in certain special cases, such as when the *lhs* is a zero (see the arithmetic specification for details).

Inexact results will always be full precision, and will almost always be correctly rounded, but may be up to 1 (unit in last place) in error in rare cases.

This is a mathematical function; the 10⁶ restrictions on precision and range apply as described above, except that the normal range of values and context is allowed if the *rhs* has an integral value in the range -1999999997 through +999999999.¹¹

decNumberQuantize(number, lhs, rhs, context)

This function is used to modify a number so that its exponent has a specific value, equal to that of the *rhs*. The *decNumberRescale* (see page 39) function may also be used for this purpose, but requires the exponent to be given as a decimal number.

When *rhs* is a finite number, its *exponent* is used as the requested exponent (it provides a “pattern” for the result). Its coefficient and sign are ignored.

The *number* is set to a value which is numerically equal (except for any rounding) to the *lhs*, modified as necessary so that it has the requested exponent. To achieve this, the *coefficient* of the *number* is adjusted (by rounding or shifting) so that its *exponent* has the requested value. For example, if the *lhs* had the value 123.4567, and the *rhs* had the value 0.12, the result would be 123.46 (that is, 12346 with an *exponent* of -2, matching the exponent of the *rhs*).

Note that the exponent of the *rhs* may be positive, which will lead to the *number* being adjusted so that it is a multiple of the specified power of ten.

If adjusting the exponent would mean that more than `context.digits` would be needed in the *coefficient*, then the `DEC_Invalid_operation` condition is raised. This guarantees that in the absence of error the exponent of *number* is always equal to that of the *rhs*.

If either operand is a *special value* then the usual rules apply, except that if either operand is infinite and

¹⁰ The *nextAfter* operation was dropped from the proposed standard during the ballot process.

¹¹ This relaxation of the restrictions provides upwards compatibility with an earlier version of the *decNumberPower* function which could only handle an *rhs* with an integral value.

the other is finite then the `DEC_Invalid_operation` condition is raised, or if both are infinite then the result is the first operand.

decNumberRemainder(number, lhs, rhs, context)

Integer-divides *lhs* by *rhs* and places the remainder from the division in *number*.

That is, if the same *lhs*, *rhs*, and *context* arguments were given to the `decNumberDivideInteger` and `decNumberRemainder` functions, resulting in *int* and *rem* respectively, then the identity

$$lhs = (int \times rhs) + rem$$

holds.

Note that, as for `decNumberDivideInteger`, it must be possible to express the integer part of the result (*i*) as an integer. That is, it must have no more digits than `context.digits`. If it does have more then `DEC_Division_impossible` is raised.

decNumberRemainderNear(number, lhs, rhs, context)

The *number* is set to the remainder when *lhs* is divided by the *rhs*, using the rules defined in IEEE 754. This follows the same definition as `decNumberRemainder`, except that the nearest integer (or the nearest even integer if the remainder is equidistant from two) is used for *int* instead of the result from `decNumberDivideInteger`.

For example, if *lhs* had the value 10 and *rhs* had the value 6 then the result would be -2 (instead of 4) because the nearest multiple of 6 is 12 (rather than 6).

decNumberRescale(number, lhs, rhs, context)

This function is used to rescale a number so that its exponent has a specific value, given by the *rhs*. The `decNumberQuantize` (see page 38) function may also be used for this purpose, and is often easier to use.

The *rhs* must be a whole number (before any rounding); that is, any digits in the fractional part of the number must be zero. It must have no more than nine digits, or `context.digits` digits, (whichever is smaller) in the integer part of the number.

The *number* is set to a value which is numerically equal (except for any rounding) to the *lhs*, rescaled so that it has the requested exponent. To achieve this, the *coefficient* of the *number* is adjusted (by rounding or shifting) so that its *exponent* has the value of the *rhs*. For example, if the *lhs* had the value 123.4567, and `decNumberRescale` was used to set its exponent to -2, the result would be 123.46 (that is, 12346 with an *exponent* of -2).

Note that the *rhs* may be positive, which will lead to the *number* being adjusted so that it is a multiple of the specified power of ten.

If adjusting the scale would mean that more than `context.digits` would be needed in the *coefficient*, then the `DEC_Invalid_operation` condition is raised. This guarantees that in the absence of error the exponent of *number* is always equal to the *rhs*.

decNumberRotate(number, lhs, rhs, context)

This function is used to rotate the digits in the coefficient of a number as though its coefficient had the

length given by `context.digits` and its most-significant digit were connected to its least-significant digit.

The *number* is set to a copy of *lhs* with the digits of its coefficient rotated to the left (if *rhs* is positive) or to the right (if *rhs* is negative) without adjusting the exponent or the sign. If *lhs* has fewer digits than `context.digits` the coefficient is padded with zeros on the left before the rotate. Any insignificant leading zeros in the result are removed, as usual.

rhs is the count of digits to rotate; it must be an integer (that is, it must have an *exponent* of 0) and must be in the range `-context.digits` through `+context.digits`.

decNumberSameQuantum(number, lhs, rhs)

This function is used to test whether the exponents of two numbers are equal. The coefficients and signs of the operands (*lhs* and *rhs*) are ignored.

If the exponents of the operands are equal, or if they are both Infinities or they are both NaNs, *number* is set to 1. In all other cases, *number* is set to 0. No error is possible.

decNumberScaleB(number, lhs, rhs, context)

This function is used to adjust (scale) the exponent of a number, using the rules of the “scaleB” operation in IEEE 754. The *number* is set to the result of multiplying *lhs* by ten raised to the power of *rhs*. *rhs* must be an integer (that is, it must have an *exponent* of 0) and it must also be in the range `-1999999997` through `+999999999`.¹²

decNumberShift(number, lhs, rhs, context)

This function is used to shift the digits in the coefficient of a number. The *number* is set to a copy of *lhs* with the digits of its coefficient shifted to the left (if *rhs* is positive) or to the right (if *rhs* is negative) without adjusting the exponent or the sign. The coefficient is padded with zeros on the left or right, as necessary. Any leading zeros in the result are ignored, as usual.

rhs is the count of digits to shift; it must be an integer (that is, it must have an *exponent* of 0) and must be in the range `-context.digits` through `+context.digits`.

decNumberSquareRoot(number, rhs, context)

The *number* is set to the square root of the *rhs*, rounded if necessary using the digits setting in the *context* and using the *round-half-even* rounding algorithm. The preferred exponent of the result is `floor(exponent / 2)`.

decNumberSubtract(number, lhs, rhs, context)

The *number* is set to the result of subtracting the *rhs* from the *lhs*.

¹² This range is an implementation restriction and is smaller than that suggested by the arithmetic specification. The restriction can be worked around by calling the function more than once.

decNumberToIntegralExact(number, rhs, context)

The *number* is set to the *rhs*, with any fractional part removed if necessary using the rounding mode in the *context*.

The `Inexact` flag is set if the result is numerically different from *rhs*. Other than that, no flags are set (unless the operand is a signaling NaN). The result may have a positive exponent.

decNumberToIntegralValue(number, rhs, context)

The *number* is set to the *rhs*, with any fractional part removed if necessary using the rounding mode in the *context*.

No flags, not even `Inexact`, are set (unless the operand is a signaling NaN). The result may have a positive exponent.

decNumberXor(number, lhs, rhs, context)

The *number* is set to the result of the digit-wise logical of *lhs* and *rhs*.

Utility functions

The utility functions include copying, trimming, test, and initializing functions, along with specialized conversions and a function for determining the version of the decNumber package.

decNumberClass(number, context)

This function is used to determine the class of a decNumber. The arguments are:

number (decNumber *) Pointer to the decNumber to be classified.

context (decContext *) Pointer to the context (the value of *emin* is used to determine if a finite number is normal or subnormal).

Returns an enum `decClass` (defined in `decNumber.h`), which can be converted to a character string using `decNumberClassToString`. No error is possible from this function.

decNumberClassToString(number, context)

This function is used to convert a `decClass` enumeration to a string. The argument is:

class (enum `decClass`) The enumeration to be converted.

Returns a string (`const char *`) which points to one of the constant strings "sNaN", "NaN", "-Infinity", "-Normal", "-Subnormal", "-Zero", "+Zero", "+Subnormal", "+Normal", "+Infinity", or "Invalid". No error is possible from this function.

decNumberCopy(number, source)

This function is used to copy the content of one decNumber structure to another. It is used when the structures may be of different sizes and hence a straightforward structure copy by C assignment is inappropriate. It also may have performance benefits when the number is short relative to the size of the structure, as only the units containing the digits in use in the source structure are copied.

The arguments are:

number (decNumber *) Pointer to the structure to receive the copy. It must have space for `source->digits` digits.

source (decNumber *) Pointer to the structure which will be copied to *number*. All fields are copied, with the units containing the `source->digits` digits being copied starting from *lsu*. The *source* structure is unchanged.

Returns *number*. No error is possible from this function.

decNumberCopyAbs(number, source)

This function is used to copy the absolute value of the content of one decNumber structure to another. It is identical to `decNumberCopy` except that the *sign* of the result is always 0. This is equivalent to the quiet *abs* function described in IEEE 754.

Returns *number*. No error is possible from this function.

decNumberCopyNegate(number, source)

This function is used to copy the value of the content of one decNumber structure to another while inverting its sign. It is identical to `decNumberCopy` except that the *sign* of the result is the inverse of that in *source*. This is equivalent to the quiet *negate* function described in IEEE 754.

Returns *number*. No error is possible from this function.

decNumberCopySign(number, source, pattern)

This function is used to copy the value of the content of one decNumber structure to another and changing its sign to that of a third. It is identical to `decNumberCopy` except that the *sign* of the result is taken from the third argument instead of from *source*. This is equivalent to the quiet *copysign* function described in IEEE 754.

The first two arguments are as for `decNumberCopy`. The third is:

pattern (decNumber *) Pointer to the structure which provides the sign.

Returns *number*. No error is possible from this function.

decNumberFromInt32(number, i)

This function is used to convert a signed (two's complement) 32-bit binary integer to a decNumber. The arguments are:

number (decNumber *) Pointer to the structure that will received the converted integer. This must have space for the digits needed to represent the value of *i*, which may need up to ten digits.

i (int32_t) The integer to be converted.

Returns *number*. No error is possible from this function.

decNumberFromUInt32(number, u)

This function is used to convert an unsigned 32-bit binary integer to a `decNumber`. The arguments are:

number (`decNumber *`) Pointer to the structure that will received the converted integer. This must have space for the digits needed to represent the value of *u*, which may need up to ten digits.

u (`uint32_t`) The integer to be converted.

Returns *number*. No error is possible from this function.

decNumberGetBCD(number, bcd)

This function is used to convert the coefficient of a `decNumber` to Binary Coded Decimal, one digit (value 0–9) per byte. The arguments are:

number (`decNumber *`) Pointer to the structure containing the coefficient to be converted.

bcd (`uint8_t *`) Pointer to the byte array which will receive the converted coefficient; the most significant digit of the coefficient will be placed in `bcd[0]`. The first `number->digits` elements of *bcd* will have their values set; no other elements are affected.

Returns *bcd*. No error is possible from this function.

decNumberIsCanonical(number)

This function is used to test whether the encoding of a `decNumber` is canonical.

The argument is:

number (`decNumber *`) Pointer to the structure whose value is to be tested.

Returns 1 (true) always, because `decNumbers` always have canonical encodings (the function is provided for compatibility with the IEEE 754 operation *isCanonical*). This function may be implemented as a macro; no error is possible.

decNumberIsFinite(number)

This function is used to test whether a number is finite.

The argument is:

number (`decNumber *`) Pointer to the structure whose value is to be tested.

Returns 1 (true) if the number is finite, or 0 (false) otherwise (that is, it is an infinity or a NaN). This function may be implemented as a macro; no error is possible.

decNumberIsInfinite(number)

This function is used to test whether a number is infinite.

The argument is:

number (`decNumber *`) Pointer to the structure whose value is to be tested.

Returns 1 (true) if the number is infinite, or 0 (false) otherwise (that is, it is a finite number or a NaN). This function may be implemented as a macro; no error is possible.

decNumberIsNaN(number)

This function is used to test whether a number is a NaN (quiet or signaling).

The argument is:

number (decNumber *) Pointer to the structure whose value is to be tested.

Returns 1 (true) if the number is a NaN, or 0 (false) otherwise. This function may be implemented as a macro; no error is possible.

decNumberIsNegative(number)

This function is used to test whether a number is negative (either minus zero, less than zero, or a NaN with a *sign* of 1). Note that in the decFloats packages, this is called (for example) *decQuadIsSigned*, and *decQuadIsNegative* does not include zeros or NaNs.

The argument is:

number (decNumber *) Pointer to the structure whose value is to be tested.

Returns 1 (true) if the number is negative, or 0 (false) otherwise. This function may be implemented as a macro; no error is possible.

decNumberIsNormal(number)

This function is used to test whether a number is normal (that is, finite, non-zero, and not subnormal).

The arguments are:

number (decNumber *) Pointer to the structure whose value is to be tested.

context (decContext *) Pointer to the context (the value of *emin* is used to determine if a finite number is normal or subnormal).

Returns 1 (true) if the number is normal, or 0 (false) otherwise. This function may be implemented as a macro; no error is possible.

decNumberIsQNaN(number)

This function is used to test whether a number is a Quiet NaN.

The argument is:

number (decNumber *) Pointer to the structure whose value is to be tested.

Returns 1 (true) if the number is a Quiet NaN, or 0 (false) otherwise. This function may be implemented as a macro; no error is possible.

decNumberIsSNaN(number)

This function is used to test whether a number is a Signaling NaN.

The argument is:

number (decNumber *) Pointer to the structure whose value is to be tested.

Returns 1 (true) if the number is a Signaling NaN, or 0 (false) otherwise. This function may be

implemented as a macro; no error is possible.

decNumberIsSpecial(number)

This function is used to test whether a number has a special value (Infinity or NaN); it is the inversion of `decNumberIsFinite` (see page 43).

The argument is:

number (decNumber *) Pointer to the structure whose value is to be tested.

Returns 1 (true) if the number is special, or 0 (false) otherwise. This function may be implemented as a macro; no error is possible.

decNumberIsSubnormal(number)

This function is used to test whether a number is subnormal (that is, finite, non-zero, and magnitude less than $10^{e_{min}}$).

The arguments are:

number (decNumber *) Pointer to the structure whose value is to be tested.

context (decContext *) Pointer to the context (the value of *e_{min}* is used to determine if a finite number is normal or subnormal).

Returns 1 (true) if the number is subnormal, or 0 (false) otherwise. This function may be implemented as a macro; no error is possible.

decNumberIsZero(number)

This function is used to test whether a number is a zero (either positive or negative).

The argument is:

number (decNumber *) Pointer to the structure whose value is to be tested.

Returns 1 (true) if the number is zero, or 0 (false) otherwise. This function may be implemented as a macro; no error is possible.

decNumberRadix()

This function returns the radix (number base) used by the `decNumber` package. This always returns 10. This function may be implemented as a macro; no error is possible.

decNumberReduce(number, rhs, context)

This function has the same effect as `decNumberPlus` except that the final result is set to its simplest (shortest) form without changing its value. That is, a non-zero number which has any trailing zeros in the coefficient has those zeros removed by dividing the coefficient by the appropriate power of ten and adjusting the exponent accordingly, and a zero has its exponent set to 0.

The `decNumberTrim` function (see page 46) can be used to remove only fractional trailing zeros.

This function was previously called `decNumberNormalize` (and is still available under that name for compatibility).

decNumberSetBCD(number, bcd, n)

This function is used to set the coefficient of a *decNumber* from a Binary Coded Decimal array which has one digit (value 0–9) per byte. The arguments are:

number (decNumber *) Pointer to the structure whose coefficient is to be set.
bcd (uint8_t *) Pointer to the byte array which provides the coefficient; the most significant digit of the coefficient is at *bcd*[0] and the least significant is at *bcd*[*n*-1].
n (uint32_t *) Count of the BCD digits to be converted.

number must have space for at least *n* digits. If *number* is a NaN, or is Infinite, or is to become a zero, *n* must be 1 and *bcd*[0] must be zero.

Returns *number*. No error is possible from this function.

decNumberToInt32(number, context)

This function is used to convert a *decNumber* to a signed (two's complement) 32-bit binary integer. The arguments are:

number (decNumber *) Pointer to the structure that will have its value converted.
context (decContext *) Pointer to the context (used only for reporting an error).

The DEC_Invalid_operation condition is raised if *number* does not have an exponent of 0, or if it is a NaN or Infinity, or if it is out-of-range (cannot be represented). In this case the result is 0. Note that a -0 is not out of range (it is numerically equal to zero and will be converted without raising the condition).

Returns the signed integer (int32_t).

decNumberToUInt32(number, context)

This function is used to convert a *decNumber* to an unsigned 32-bit binary integer. The arguments are:

number (decNumber *) Pointer to the structure that will have its value converted.
context (decContext *) Pointer to the context (used only for reporting an error).

The DEC_Invalid_operation condition is raised if *number* does not have an exponent of 0, or if it is a NaN or Infinity, or if it is out-of-range (cannot be represented). In this case the result is 0. Note that a -0 is not out of range (but all values less than zero are).

Returns the unsigned integer (uint32_t).

decNumberTrim(number)

This function is used to remove insignificant trailing zeros from a number, unconditionally. That is, if the number has any fractional trailing zeros they are removed by dividing the coefficient by the appropriate power of ten and adjusting the exponent accordingly. The *decNumberReduce* function (see page 45) can be used to remove all trailing zeros.

The argument is:

number (decNumber *) Pointer to the structure whose value is to be trimmed.

Returns *number*. No error is possible from this function.

decNumberVersion()

This function returns a pointer (`char *`) to a human-readable description of the version of the decNumber package being run. The string pointed to will have at most 16 characters and will be a constant, and will comprise two words (the name and a decimal number identifying the version) separated by a blank. For example:

```
decNumber 3.40
```

No error is possible from this function.

decNumberZero(number)

This function is used to set the value of a decNumber structure to zero.

The argument is:

number

decimal32, decimal64, and decimal128 modules

The decimal32, decimal64, and decimal128 modules define the data structures and conversion functions for the IEEE 754 decimal-encoded compressed decimal formats which are 32, 64, or 128 bits (4, 8, or 16 bytes) long, respectively. These provide up to 7, 16, or 34 digits of decimal precision in a compact and machine-independent form. Details of the formats are available at:

<http://speleotrove.com/decimal/decbits.html>

These modules provide the interface between the compressed numbers and the decNumber internal format (and also provide string conversions). The *decFloats* modules (see page 52) provide arithmetic and other functions which work on data in the same formats directly. Example 7 and Example 8 in the User's Guide (see page 19) show how to work with data in the formats with or without using the decNumber module.

Apart from the different lengths and ranges of the numbers, these three modules are identical, so this section just describes the decimal64 module. The definitions and functions for the other two formats are the same, except for the obvious name and value changes.

In this implementation each format is represented as an array of unsigned bytes. There is therefore just one field in the decimal64 structure:

bytes The *bytes* field represents the eight bytes of a decimal64 number, using Densely Packed Decimal encoding for the coefficient.¹³

The storage of a number in the bytes array is assumed to follow the byte ordering ("endianness") of the computing platform (if big-endian, then `bytes[0]` contains the sign bit of the format). The code in these modules requires that the DECLITEND tuning parameter (see page 70) be set to match the endianness of the platform.

Note that the equivalent structures in the decFloats modules are identical except for their names. It is therefore safe to cast pointers between them if they are the same size (for example between decimal64 and decDouble). This means that these modules can be used as *proxies* between the decNumber module and the decFloats modules.

The decimal64 module includes private functions for coding and decoding Densely Packed Decimal data; these functions are shared by the other compressed format modules. Hence, when using any of these three then `decimal64.c` must be compiled too.

Definitions

The `decimal64.h` header file defines the decimal64 data structure described above. It includes the `decNumber.h` header file, to simplify use, and (if not already defined) it sets the `DECNUMDIGITS` constant to 16, so that any declared decNumber will be the right size to contain any decimal64 number.

If more than one of the three decimal format header files are used in a program, they must be included in decreasing order of size so that the largest value of `DECNUMDIGITS` will be used.

The `decimal64.h` header file also contains:

- Constants defining aspects of decimal64 numbers, including the maximum precision, the minimum and maximum (adjusted) exponent supported, the bias applied to the exponent, the

¹³ See <http://speleotrove.com/decimal/DPDecimal.html> for a summary of Densely Packed Decimal encoding.

length of the number in bytes, and the maximum number of characters in the string form of the number (including terminator)

- Definitions of the public functions in the decimal64 module.

The decimal64 module also contains the shared routines for compressing and expanding Densely Packed Decimal data, and uses the `decDPD.h` header file. The latter contains look-up tables which are used for encoding and decoding Densely Packed Decimal data (only three of the tables in the header file are used). These tables are automatically generated and should not need altering.

Functions

The `decimal64.c` source file contains the public functions defined in the header file. These comprise conversions to and from strings and `decNumbers`, and some utilities.

When a `decContext` structure is used to report errors, the same rules are followed as for other modules. That is, a trap may be raised,

decimal64FromString(decimal64, string, context)

This function is used to convert a character string to decimal64 format. It implements the **to-number** conversion in the arithmetic specification (that is, it accepts subnormal numbers, NaNs, and infinities, and it preserves the sign and exponent of 0). If necessary, the value will be rounded to fit.

The arguments are:

- decimal64* (`decimal64 *`) Pointer to the structure to be set from the character string.
- string* (`char *`) Pointer to the input character string. This must be a valid numeric string, as defined in the specification. The string will not be altered.
- context* (`decContext *`) Pointer to the context structure which controls the conversion, as for the `decNumberFromString` function (see page 33) except that the precision and exponent range are fixed for each format (the values of *emax*, *emin*, and *digits* are ignored).

Returns *decimal64*.

Possible errors are `DEC_Conversion_syntax` (the string does not have the syntax of a number), `DEC_Overflow` (the adjusted exponent of the number is positive and is greater than *emax* for the format), or `DEC_Underflow` (the adjusted exponent of the number is negative and is less than *emin* for the format and the conversion is not exact). If one of these conditions is set, the *decimal64* structure will have the value `NaN`, `±Infinity` or the largest possible finite number, or a finite (possibly subnormal) number respectively, with the same sign as the converted number after overflow or underflow.

decimal64ToString(decimal64, string)

This function is used to convert a decimal64 number to a character string, using scientific notation if an exponent is needed (that is, there will be just one digit before any decimal point). It implements the **to-scientific-string** conversion in the arithmetic specification.

The arguments are:

- decimal64* (`decimal64 *`) Pointer to the structure to be converted to a string.

string (char *) Pointer to the character string buffer which will receive the converted number. It must be at least DECIMAL64_String (24) characters long.

Returns *string*; no error is possible from this function.

decimal64ToEngString(decimal64, string)

This function is used to convert a decimal64 number to a character string, using engineering notation (where the exponent will be a multiple of three, and there may be up to three digits before any decimal point) if an exponent is needed. It implements the **to-engineering-string** conversion in the arithmetic specification.

The arguments and result are the same as for the decimal64ToString function, and similarly no error is possible from this function.

decimal64FromNumber(decimal64, number, context)

This function is used to convert a decNumber to decimal64 format.

The arguments are:

decimal64 (decimal64 *) Pointer to the structure to be set from the decNumber. This may receive a numeric value (including subnormal values and -0) or a special value.

number (decNumber *) Pointer to the input structure. The decNumber structure will not be altered.

context (decContext *) Pointer to a context structure whose *status* field is used to report any error and whose other fields are used to control rounding, , as required.

Returns *decimal64*.

The possible errors are as for the decimal64FromString function (see page 49), except that DEC_Conversion_syntax is not possible.

decimal64ToNumber(decimal64, number)

This function is used to convert a decimal64 number to decNumber form in preparation for arithmetic or other operations.

The arguments are:

decimal64 (decimal64 *) Pointer to the structure to be converted to a decNumber. The decimal64 structure will not be altered.

number (decNumber *) Pointer to the result structure. It must have space for 16 digits of precision.

Returns *number*; no error is possible from this function.

decimal64Canonical(decimal64, source)

This function is used to ensure that a decimal64 number is encoded with the canonical form. That is, all declets use the preferred 1000 encodings and an infinity has a coefficient of zero.

The arguments are:

decimal64 (decimal64 *) Pointer to the structure to receive a copy of *source*, with canonical encoding.

source (decimal64 *) Pointer to the structure to be converted to a canonical encoding.

Returns *decimal64*; no error is possible from this function.

decimal64IsCanonical(decimal64)

This function is used to test whether a decimal64 number is encoded with the canonical form. That is, that all declets use the preferred 1000 encodings and an infinity has a coefficient of zero.

The argument is:

decimal64 (decimal64 *) Pointer to the structure to be tested.

Returns an unsigned integer (uint32_t *) which is 1 if *decimal64* has canonical encoding, or 0 otherwise. No error is possible from this function.

decFloats modules

The *decFloats* modules are *decSingle*, *decDouble*, and *decQuad*. These are based on the 32-bit, 64-bit, and 128-bit decimal types in the IEEE 754 Standard for Floating Point Arithmetic.

In contrast to the arbitrary-precision *decNumber* module, these modules work directly from the decimal-encoded formats designed by the IEEE 754 committee, which are also now implemented in IBM System z (z9 and z10) and IBM System p (POWER6) processors, and in SAP NetWeaver 7.1.¹⁴

Conversions to and from the *decNumber* internal format are not needed (typically the numbers are represented internally in “unpacked” BCD or in a base of some other power of ten), and no memory allocation is necessary, so these modules are much faster than using *decNumber* for implementing the types.

Like the *decNumber* module, the *decFloats* modules

- need only 32-bit integer support; 64-bit integers are not required and binary floating-point is not used
- support both big-endian and little-endian encodings and platforms
- support both ASCII/UTF8 and EBCDIC strings
- are reentrant and use only aligned integers and strict aliasing
- use only ANSI C.

The modules should therefore be usable on any platform with an ANSI C compiler that supports 32-bit integers.

The *decFloats* modules define the data structures and a large set of functions for working directly with the same compressed formats as *decimal32*, *decimal64*, and *decimal128*. The names are different to allow them to be used stand-alone or with the *decNumber* module, as illustrated in Examples 7 and 8 in the User’s Guide (see page 19).

These three modules all share many of the same functions (working on the different sizes of the formats). The *decQuad* module has all the same functions as *decDouble* except for two functions which would convert to or from a wider format. The *decSingle* module is a limited (“storage”) format which has only a few conversion and miscellaneous functions; it is intended that any computation be carried out in a wider format.

The remainder of this section therefore describes only the *decDouble* format – in the list of functions, assume that there is a corresponding *decQuad* format function unless stated and assume there is a corresponding *decSingle* format function unless stated.

In this implementation each format is represented as an array of unsigned bytes. There is therefore just one field in the *decDouble* structure:

bytes The *bytes* field represents the eight bytes of a *decDouble* number, using Densely Packed Decimal encoding for the coefficient. As of *decNumber* 3.56 the structure has been changed to a union of the *bytes* array with arrays of larger integers; see the header file for each type for details.¹⁵

¹⁴ IBM, the IBM logo, System p, System z, and POWER6 are trademarks of International Business Machines Corporation in the United States, other countries, or both. SAP and SAP NetWeaver are trademarks of SAP AG, in Germany, other countries, or both.

¹⁵ See <http://speleotrove.com/decimal/DPDecimal.html> for a summary of Densely Packed Decimal encoding.

The storage of a number in the bytes array is assumed to follow the byte ordering (“endianness”) of the computing platform (if big-endian, then `bytes[0]` contains the sign bit of the format). The code in these modules requires that the `DECLITEND` tuning parameter (see page 70) be set to match the endianness of the platform.

The `decSingle` and `decDouble` modules both require that the next wider format be included in a program compilation (so that conversion to and from that wider format can be effected), hence the `decQuad` module is always needed.¹⁶ It, therefore, contains the constant lookup tables from the `decDPD.h` header file which are shared by all three modules. These tables are automatically generated and should not need altering.

Most of the code for these modules is included from the shared source files `decCommon.c` and `decBasic.c`. The former contains the functions available in all three modules¹⁷ and the latter the functions available only in `decDouble` and `decQuad`.

Definitions

The `decDouble.h` header file defines the `decDouble` data structure described above. It includes the `decContext.h` and `decQuad.h` header files, which are both required for use.¹⁸ If more than one of the three `decFloats` formats are used in a program, it is only necessary to include the smaller or smallest.

The `decDouble.h` header file also contains:

- Constants defining aspects of `decDouble` numbers, including the maximum precision, the minimum and maximum (adjusted) exponent supported, the bias applied to the exponent, the length of the number in bytes, and the maximum number of characters in the string form of the number (including terminator)
- Definitions of the public functions in the `decDouble` module
- Macros defining conversions to and from the `decNumber` format. These are macros in order to avoid a compile-time dependency on the `decNumber` module; they use `decimal64` as a proxy, and their usage is shown in Example 8 in the User’s Guide (see page 20).

Functions

The `decDouble.c` source file contains the public functions defined in the header file. These comprise conversions to and from strings and other formats, arithmetic and logical operations, and utilities.

The functions are described briefly, below. More details of the operation of each function can be found in the description of the corresponding function in the `decNumber` module and details of the underlying model and arithmetic can be found in the¹⁹

In the descriptions below, many parameters are defined as one of the following:

`x, y, z` `(const decDouble *)` decimal input arguments to a function

¹⁶ This requirement is different from the `decimal32`, `decimal64`, and `decimal128` modules because they can convert to wider or narrower formats using the `decNumber` format as an intermediate step.

¹⁷ Except that the widening and narrowing functions are not used by `decQuad`.

¹⁸ The `decSingle.h` header file also includes `decDouble.h`, but the `decQuad.h` header file only includes `decContext.h`.

¹⁹ See <http://speleotrove.com/decimal/#arithmetic> for details.

r (decDouble *) a decimal result argument to a function (which may be the same as an input argument); unless stated otherwise this is also the return value from the function, and the result will be canonical

set (decContext *) the context for a function. Only two fields of the context structure are used: *round* (the rounding mode) and *status* (the bits in which are used to indicate any error,).

Note that the *trap* field in the context is not used; the decDouble functions do not check for traps after every operation to avoid the overhead that would incur. The decContextSetStatus function (see page 27) can be used to explicitly test status to trap.

Note also that the only informational flag set by decNumber is DEC_Inexact; the others are never set by the decFloats module in order to improve performance and also to avoid the need for passing a context to many functions.²⁰

In the following list, every function has corresponding decQuad format function (for example, decQuadAbs(*r*, *x*, *set*)) unless stated, and does have a corresponding decSingle format function unless stated.

decDoubleAbs(r, x, set)

Returns the absolute value of *x*. This has the same effect as decDoublePlus unless *x* is negative, in which case it has the same effect as decDoubleMinus. The effect is also the same as decDoubleCopyAbs except that NaNs are handled normally (the sign of a NaN is not affected, and an sNaN will set DEC_Invalid_operation) and the result will be canonical.

decDoubleAdd(r, x, y, set)

Adds *x* and *y* and places the result in *r*.

decDoubleAnd(r, x, y, set)

Carries out the digit-wise logical And of *x* and *y* and places the result in *r*.

The operands must be zero or positive (sign=0), an integer (finite with exponent=0) and comprise only zeros and/or ones; if not, DEC_Invalid_operation is set.

decDoubleCanonical(r, x)

This copies *x* to *r*, ensuring that the encoding of *r* is canonical.

decDoubleClass(x)

This returns the class (enum decClass) of the argument *x*.

decDoubleClassString(x)

This returns a description of the class of the argument *x* as a string (const char *).

²⁰ The DEC_Subnormal flag is particularly expensive to maintain.

decDoubleCompare(r, x, y, set)

Compares `x` and `y` numerically and places the result in `set`.

The result may be -1, 0, 1, or NaN (unordered); -1 indicates that `x` is less than `y`, 0 indicates that they are numerically equal, and 1 indicates that `x` is greater than `y`. NaN is returned only if `x` or `y` is a NaN.

decDoubleCompareSignal(r, x, y, set)

The same as `decDoubleCompare`, except that a quiet NaN argument is treated like a signaling NaN (causes `DEC_Invalid_operation` to be set).

decDoubleCompareTotal(r, x, y)

Compares `x` and `y` using the IEEE 754 total ordering (which takes into account the exponent) and places the result in `set`. No status is set (a signaling NaN is ordered between Infinity and NaN). The result will be -1, 0, or 1.

decDoubleCompareTotalMag(r, x, y)

The same as `decDoubleCompareTotal` except that the absolute values of the two arguments are used (as though modified by `decDoubleCopyAbs`).

decDoubleCopy(r, x)

Copies `x` to `r` quietly (no status is set). This is a bit-wise operation and so the result might not be canonical.

decDoubleCopyAbs(r, x)

Copies `x` to `r` quietly and sets the sign of `r` to 0 (no status is set). This is a bit-wise operation and so the result might not be canonical.

decDoubleCopyNegate(r, x)

Copies `x` to `r` quietly and inverts the sign of `r` (no status is set). This is a bit-wise operation and so the result might not be canonical.

decDoubleCopySign(r, x, y)

Copies `x` to `r` quietly with the sign of `r` set to the sign of `y` (no status is set). This is a bit-wise operation and so the result might not be canonical.

decDoubleDigits(x)

Returns the number of significant digits in `x` as an unsigned 32-bit integer (`uint32_t`). If `x` is a zero or is infinite, 1 is returned. If `x` is a NaN then the number of digits in the payload is returned.

decDoubleDivide(r, x, y, set)

Divides `x` by `y` and places the result in `r`.

decDoubleDivideInteger(r, x, y, set)

Divides `y` by `x` and places the integer part of the result (rounded towards zero) in `r` with exponent=0. If the result would not fit in `r` (because it would have more than `DECDOUBLE_Pmax` digits) then `DEC_Division_impossible` is set.

decDoubleFMA(r, x, y, z, set)

Calculates the fused multiply-add $x \times y + z$ and places the result in `r`. The multiply is carried out first and is exact, so this operation has only the one, final, rounding.

decDoubleFromBCD(r, exp, bcd, sign)

Sets `r` from an exponent `exp` (which may indicate a NaN or infinity), a BCD array `bcd`, and a `sign`.

`(int32_t)` is an in-range unbiased exponent or a special value in the form returned by `decDoubleGetExponent` (listed in `decQuad.h`).

`(const uint8_t *)` is an array of `DECDOUBLE_Pmax` elements, one digit in each byte (BCD8 encoding); the first (most significant) digit is ignored if the result will be a NaN; all are ignored if the result is infinite. All bytes must be in the range 0–9.

`(int32_t)` is an integer which must be `DECFLOAT_Sign` to set the sign bit of `r` to 1, or 0 to set it to 0.

For speed, the arguments are not checked; no status is set by this function. The content of `r` is undefined if the arguments are invalid or out of range (that is, could not be produced by `decDoubleToBCD`).

(This function is also available in the `decSingle` module.)

decDoubleFromInt32(r, i)

Sets `r` from the signed 32-bit integer `(int32_t)`. The result is exact; no error is possible.

decDoubleFromNumber(r, dn, set)

This function is implemented as a macro and sets `r` from a `decNumber`, `dn`, using a decimal64 as a proxy as illustrated in Example 8 in the User's Guide (see page 20).

To use this macro, the `decimal64.h` header file must be included (see the text following the example for more details about compilation).

(This function is also available in the `decSingle` module.)

decDoubleFromPacked(r, exp, pack)

Sets `r` from an exponent `exp` (which may indicate a special value) and a packed BCD array, `pack`.

`(int32_t)` is an in-range unbiased exponent or a special value in the form returned by `decDoubleGetExponent` (listed in `decQuad.h`).

`(const uint8_t *)` is an array of `DECDOUBLE_Pmax` packed decimal digits (one digit per four-bit nibble) followed by a sign nibble, and (for `decDouble` and `decQuad` only) prefixed with an extra pad nibble (which is ignored); the sign nibble must be any of the six sign codes listed in `decQuad.h`.

and described for the `decPacked` module (see page 67), and digit nibbles must be in the range 0–9.

Like the `decDoubleFromBCD` function, the first nibble of `pack` (after the pad nibble, if any) is ignored if the result will be a NaN, and all are ignored if the result is infinite.

For speed, the arguments are not checked; no status is set by this function. The content of `set` is undefined if the arguments are invalid or out of range (that is, could not be produced by `decNumberToPacked`, except that all six sign codes are permitted).

(This function is also available in the `decSingle` module.)

decDoubleFromPackedChecked(r, exp, pack)

Sets `r` from an exponent `exp` (which may indicate a special value) and a packed BCD array, `pack`, with the input values fully checked.

`(int32_t)` must be an in-range unbiased exponent or a special value in the form returned by `decDoubleGetExponent` (listed in `decQuad.h`).

`(const uint8_t *)` is an array of `DECDOUBLE_Pmax` packed decimal digits (one digit per four-bit nibble) followed by a sign nibble, and (for `decDouble` and `decQuad` only) prefixed with an extra pad nibble (which must be zero); the sign nibble must be one of the six sign codes listed in `decQuad.h` and described for the `decPacked` module (see page 67), and digit nibbles must be in the range 0–9.

The first nibble of `pack` (after the pad nibble, if any) must be zero if the result will be a NaN, and all digit nibbles must be zero if the result is infinite.

No status is set by this function. `NULL` is returned instead of `r` if an argument is invalid or out of range (that is, could not be produced by `decNumberToPacked`, except that all six sign codes are permitted).

(This function is also available in the `decSingle` module.)

decDoubleFromString(r, string, set)

Sets `r` from a character string, `string` (`const char *`).

The length of the coefficient and the size of the exponent are checked by this routine, so rounding will be applied if necessary, and this may set status flags (underflow, overflow) will be reported, or rounding applied, as necessary.

There is no limit to the coefficient length for finite inputs; NaN payloads must be integers with no more than `DECDOUBLE_Pmax-1` digits. Exponents may have up to nine significant digits. The syntax of the `string` is fully checked; if it is not valid, the result will be a quiet NaN and an error flag will be set.

(This function is also available in the `decSingle` module.)

decDoubleFromUInt32(r, u)

Sets `r` from the unsigned 32-bit integer `u` (`uint32_t`). The result is exact and no error is possible.

decDoubleFromWider(r, dq, set)

Sets `r` from an instance, `dq`, of the next-wider format (`const decQuad *`). This narrowing function

can cause rounding, overflow, , but not Invalid operation (sNaNs are copied and do not signal).
(This function is also available in the decSingle module, but is not available in the decQuad module.)

decDoubleGetCoefficient(x, bcd)

Extracts the coefficient of as a BCD integer into the array (uint8_t *) and returns the sign as a signed 32-bit integer (int32_t). The returned value will be DECFLOAT_Sign if has sign=1 or otherwise will be 0.

The digits of the coefficient are written, one digit per byte, into DECDOUBLE_Pmax elements of the array. If is a NaN the first byte will be zero (the remainder will be the payload), and if it is infinite then all of will be zero.

(This function is also available in the decSingle module.)

decDoubleGetExponent(x)

Returns the exponent of as a 32-bit integer (int32_t). If is infinite or is a NaN (a special value) the first seven bits of the decDouble are returned, padded with 25 zero bits on the right and with the most significant (sign) bit set to 0. For example, -sNaN would return 0x7e000000 (DECFLOAT_sNaN). The possible return values for infinities and NaNs are listed in decQuad.h.

(This function is also available in the decSingle module.)

decDoubleInvert(r, x, set)

Carries out the digit-wise logical inversion of and places the result in .

The operand must be zero or positive (sign=0), an integer (finite with exponent=0) and comprise only zeros and/or ones; if not, DEC_Invalid_operation is set.

decDoubleIsCanonical(x)

Returns an unsigned integer (uint32_t) which will be 1 if the encoding of is canonical, or 0 otherwise.

decDoubleIsFinite(x)

Returns an unsigned integer (uint32_t) which will be 1 if is neither infinite nor a NaN, or 0 otherwise.

decDoubleIsInfinite(x)

Returns an unsigned integer (uint32_t) which will be 1 if the encoding of is an infinity, or 0 otherwise.

decDoubleIsInteger(x)

Returns an unsigned integer (uint32_t) which will be 1 if is finite and has exponent=0, or 0 otherwise.

decDoubleIsLogical(x)

Returns an unsigned integer (`uint32_t`) which will be 1 if `x` is a valid argument for logical operations (that is, `x` is zero or positive (`sign=0`), an integer (finite with `exponent=0`) and comprises only zeros and/or ones), or 0 otherwise.

decDoubleIsNaN(x)

Returns an unsigned integer (`uint32_t`) which will be 1 if `x` is a NaN (quiet or signaling), or 0 otherwise.

decDoubleIsNegative(x)

Returns an unsigned integer (`uint32_t`) which will be 1 if `x` is less than zero and not a NaN, or 0 otherwise.

decDoubleIsNormal(x)

Returns an unsigned integer (`uint32_t`) which will be 1 if `x` is a normal number (that is, is finite, non-zero, and not subnormal), or 0 otherwise.

decDoubleIsPositive(x)

Returns an unsigned integer (`uint32_t`) which will be 1 if `x` is greater than zero and not a NaN, or 0 otherwise.

decDoubleIsSignaling(x)

Returns an unsigned integer (`uint32_t`) which will be 1 if `x` is a signaling NaN, or 0 otherwise.

decDoubleIsSignalling(x)

Returns an unsigned integer (`uint32_t`) which will be 1 if `x` is a signaling NaN, or 0 otherwise. (This is an alternative spelling of `decDoubleIsSignaling`.)

decDoubleIsSigned(x)

Returns an unsigned integer (`uint32_t`) which will be 1 if `x` has `sign=1`, or 0 otherwise. Note that zeros and NaNs may have `sign=1`.

decDoubleIsSubnormal(x)

Returns an unsigned integer (`uint32_t`) which will be 1 if `x` is subnormal (that is, finite, non-zero, and with magnitude less than 10^{emin}), or 0 otherwise.

decDoubleIsZero(x)

Returns an unsigned integer (`uint32_t`) which will be 1 if `x` is a zero, or 0 otherwise.

decDoubleLogB(r, x, set)

Returns the adjusted exponent of x , according to IEEE 754 rules. That is, the exponent returned is calculated as if the decimal point followed the first significant digit (so, for example, if x were 123 then the result would be 2).

If x is infinite, the result is +Infinity. If x is a zero, the result is -Infinity, and the `DEC_Division_by_zero` flag is set. If x is less than zero, the absolute value of x is used. If $set = 1$, the result is 0. NaNs are handled (propagated) as for arithmetic operations.

decDoubleMax(r, x, y, set)

If both arguments are numeric (not NaNs) this returns the larger of x and y (compared using `decDoubleCompareTotal`, to give a well-defined result).

If either (but not both of) x or y is a quiet NaN then the other argument is the result; otherwise NaNs are handled as for arithmetic operations.

decDoubleMaxMag(r, x, y, set)

The same as `decDoubleMax` except that the absolute values of the two arguments are used (as though modified by `decDoubleCopyAbs`).

decDoubleMin(r, x, y, set)

If both arguments are numeric (not NaNs) this returns the smaller of x and y (compared using `decDoubleCompareTotal`, to give a well-defined result).

If either (but not both of) x or y is a quiet NaN then the other argument is the result; otherwise NaNs are handled as for arithmetic operations.

decDoubleMinMag(r, x, y, set)

The same as `decDoubleMin` except that the absolute values of the two arguments are used (as though modified by `decDoubleCopyAbs`).

decDoubleMinus(r, x, set)

This has the same effect as $0 - x$ where the exponent of the zero is the same as that of x (if x is finite). The effect is also the same as `decFloatCopyNegate` except that NaNs are handled as for arithmetic operations (the sign of a NaN is not affected, and an sNaN will signal), the result is canonical, and a zero result has `sign=0`.

decDoubleMultiply(r, x, y, set)

Multiplies x by y and places the result in r .

decDoubleNextMinus(r, x, set)

Returns the “next” `decDouble` to x in the direction of -Infinity according to IEEE 754 rules for *nextDown*. The only status possible is `DEC_Invalid_operation` (from an sNaN).

decDoubleNextPlus(r, x, set)

Returns the “next” decDouble to in the direction of +Infinity according to IEEE 754 rules for *nextUp*. The only status possible is DEC_Invalid_operation (from an sNaN).

decDoubleNextToward(r, x, y, set)

Returns the “next” decDouble to in the direction of according to proposed IEEE 754 rules for *nextAfter*.²¹

If = the result is decDoubleCopySign(r, x, y). If either operand is a NaN the result is as for arithmetic operations. Otherwise (the operands are numeric and different) the result of adding (or subtracting) an infinitesimal positive amount to and rounding towards +Infinity (or -Infinity) is returned, depending on whether is larger (or smaller) than . The addition will set flags, except that if the result is normal (finite, non-zero, and not subnormal) no flags are set.

decDoubleOr(r, x, y, set)

Carries out the digit-wise logical inclusive Or of and and places the result in .

The operands must be zero or positive (sign=0), an integer (finite with exponent=0) and comprise only zeros and/or ones; if not, DEC_Invalid_operation is set.

decDoublePlus(r, x, set)

This has the same effect as 0+ where the exponent of the zero is the same as that of (if is finite). The effect is also the same as decFloatCopy except that NaNs are handled as for arithmetic operations (the sign of a NaN is not affected, and an sNaN will signal), the result is canonical, and a zero result has sign=0.

decDoubleQuantize(r, x, y, set)

Returns set to have the same quantum as , if possible (that is, numerically the same value but rounded or padded if necessary to have the same exponent as , for example to round a monetary quantity to cents). More details and an example are given with the decNumberQuantize function (see page 38).

decDoubleRadix(x)

Returns an unsigned integer (uint32_t) set to the base used for arithmetic in this module (always ten).

(This function is also available in the decSingle module.)

decDoubleReduce(r, x, set)

Returns a copy of with its coefficient reduced to its shortest possible form without changing the value of the result. This removes all possible trailing zeros from the coefficient (some may remain when the number is very close to the most positive or most negative number). Infinities and NaNs are unchanged and no status is set unless is an sNaN. If is a zero the result exponent is 0.

²¹ The nextAfter operation was dropped from the proposed standard during the ballot process.

decDoubleRemainder(r, x, y, set)

Integer-divides `y` by `x` and places the remainder from the division in `r`. That is, if the same `x` and `y` were given to the `decDoubleDivideInteger` and `decDoubleRemainder` functions, resulting in `q` and `r` respectively, then the identity $y = (q \times x) + r$ holds.

Note that, as for `decDoubleDivideInteger`, it must be possible to express the intermediate result (`q`) as an integer. That is, it must have no more than `DECDOUBLE_Pmax` digits. If it has too many then `DEC_Division_impossible` is raised.

decDoubleRemainderNear(r, x, y, set)

This is the same as `decDoubleRemainder` except that the nearest integer (or the nearest even integer if the remainder is equidistant from two) is used for `q` instead of the result from `decDoubleDivideInteger`. Again, that integer must fit.

decDoubleRotate(r, x, y, set)

The result is a copy of `y` with the digits of the coefficient rotated to the left (if `x` is positive) or to the right (if `x` is negative) without adjusting the exponent or the sign of `y`.

`x` is the count of positions to rotate and must be a finite integer (with exponent=0) in the range $-DECDOUBLE_Pmax$ through $+DECDOUBLE_Pmax$. NaNs are propagated as usual. If `x` is infinite the result is Infinity of the same sign. No status is set unless `x` is invalid or an operand is an sNaN.

decDoubleSameQuantum(x, y)

Returns an unsigned integer (`uint32_t`) which will be 1 if the operands have the same exponent or are both NaNs (quiet or signaling) or both infinite. In all other cases, 0 is returned. No error or status is possible.

decDoubleScaleB(r, x, y, set)

This calculates $y \times 10^x$ and places the result in `r`. `x` must be an integer (finite with exponent=0) in the range $\pm 2 \times (DECDOUBLE_Pmax + DECDOUBLE_Emax)$, typically resulting from `decDoubleLogB`. Underflow and overflow might occur. NaNs propagate as usual.

decDoubleSetCoefficient(r, bcd, sign)

Sets the coefficient of `r` from a BCD integer in the array `bcd` (`uint8_t *`) and the signed 32-bit integer (`int32_t`) `sign`. `bcd` must have `DECDOUBLE_Pmax` elements in the range 0–9, and `sign` must be `DECFLOAT_Sign` to set the sign bit of `r` to 1, or 0 to set it to 0.

If `r` is a NaN the first byte of `bcd` will be ignored (the remainder will be the payload), and if it is infinite then all of `bcd` will be ignored (the coefficient will become zero).

For speed, the arguments are not checked; no status is set by this function. The result is undefined if the arguments are invalid or out of range (that is, could not have been produced by `decDoubleGetCoefficient`).

(This function is also available in the `decSingle` module.)

decDoubleSetExponent(r, set, exp)

Sets the exponent of `r` from the signed 32-bit integer (`int32_t`) `exp`. `exp` is either an in-range exponent or a special code as returned by `decDoubleGetExponent`. If `r` becomes infinite then its coefficient is set to zero, if it becomes NaN then the first digit of the coefficient is lost,²² otherwise the coefficient is unchanged.

For speed, `exp` is not checked; however, underflow or overflow can result. The result is undefined if `exp` is not a value that could have been produced by `decDoubleGetExponent`.

(This function is also available in the `decSingle` module.)

decDoubleShift(r, x, y, set)

The result is a copy of `r` with the digits of the coefficient shifted to the left (if `x` is positive) or to the right (if `x` is negative) without adjusting the exponent or the sign of `r`. Any digits “shifted in” from the left or from the right will be 0.

`y` is the count of positions to shift and must be a finite integer (with exponent=0) in the range `-DECDOUBLE_Pmax` through `+DECDOUBLE_Pmax`. NaNs are propagated as usual. If `r` is infinite the result is Infinity of the same sign. No status is set unless `y` is invalid or an operand is an sNaN.

decDoubleShow(x, tag)

This function uses `printf` to display a readable rendering of `x`, showing both the encoding (in hexadecimal) and the value, and returns nothing (`void`). The string `tag` (`const char *`) is included in the display and may be used as an identifier for the displayed data.

This function is intended as a debug aid. It is not a programming interface – the format of the displayed data may change from release to release.

(This function is also available in the `decSingle` module.)

decDoubleSubtract(r, x, y, set)

Subtracts `y` from `x` and places the result in `r`.

decDoubleToBCD(x, exp, bcd)

Converts `x` into an exponent (`int32_t *`) and a BCD array (`uint8_t *`). `exp` is set to the value that would be returned by `decDoubleGetExponent(x)`, and `bcd` is set to the returned integer (`int32_t`) as from `decDoubleGetCoefficient(x, bcd)`.

(This function is also available in the `decSingle` module.)

decDoubleToEngString(x, string)

The same as `decDoubleToString(x, string)` except that if exponential notation is used the exponent will be a multiple of 3 (“engineering notation”).

(This function is also available in the `decSingle` module.)

²² A NaN payload has one fewer digit than the coefficient of a finite number.

decDoubleToInt32(x, set, round)

Returns a signed 32-bit integer (`int32_t`) which is the value of `x`, rounded to an integer if necessary using the explicit rounding mode `round` (enum `rounding`) instead of the rounding mode in `decFloatEnv`.

If `x` is infinite, is a NaN, or after rounding is outside the range of the result, then `DEC_Invalid_operation` is set. The `DEC_Inexact` flag is not set by this function, even if rounding occurred.

decDoubleToInt32Exact(x, set, round)

The same as `decDoubleToInt32` except that if rounding removes non-zero digits then the `DEC_Inexact` flag is set.

decDoubleToIntegralExact(r, x, set)

Returns the value of `x`, rounded to an integral value using the rounding mode in `decFloatEnv`.

If `x` is infinite, Infinity of the same sign is returned. If `x` is a NaN, the result is as for other arithmetic operations. If rounding removes non-zero digits then the `DEC_Inexact` flag is set.

decDoubleToIntegralValue(r, x, set, round)

Returns the value of `x`, rounded to an integral value using the explicit rounding mode `round` (enum `rounding`) instead of the rounding mode in `decFloatEnv`.

If `x` is infinite, Infinity of the same sign is returned. If `x` is a NaN, the result is as for other arithmetic operations. The `DEC_Inexact` flag is not set by this function, even if rounding occurred.

decDoubleToNumber(x, dn)

This function is implemented as a macro and sets a `decNumber`, `dn`, from `x` using a `decimal64` as a proxy as illustrated in Example 8 in the User's Guide (see page 20). The `decNumber` must have sufficient space for the digits in `x`.

To use this macro, the `decimal64.h` header file must be included (see the text following the example for more details). A pointer to `dn` is returned (`decNumber *`).

(This function is also available in the `decSingle` module.)

decDoubleToPacked(x, exp, pack)

Converts `x` into an exponent (`int32_t *`) and a Packed BCD array (`uint8_t *`). `exp` is set to the value that would be returned by `decDoubleGetExponent(x)`.

`pack` receives `DECDOUBLE_Pmax` packed decimal digits (one digit per four-bit nibble) followed by a sign nibble and prefixed (for `decDouble` and `decQuad` only) with an extra pad nibble (which is 0). The sign nibble will be `DECPMINUS` if `x` has `sign=1` or `DECPPLUS` otherwise. The digit nibbles will be in the range 0–9.

A signed 32-bit integer (`int32_t`) is returned; it will be `DECFLOAT_Sign` if `x` has `sign=1` or otherwise will be 0.

(This function is also available in the `decSingle` module.)

decDoubleToString(x, string)

Converts `x` to a zero-terminated string in the character array `string` (`char *`) and returns `string`. `string` must have at least `DECDOUBLE_String` elements (this count includes the terminator character).

Finite numbers will be converted to a string with exponential notation if the exponent is positive or if the magnitude of `x` is less than 1 and would require more than five zeros between the decimal point and the first significant digit.

Note that strings which are not simply numbers (one of `Infinity`, `-Infinity`, `NaN`, or `sNaN`) are possible. A `NaN` string may have a leading `-` sign and/or following payload digits. No digits follow the `NaN` string if the payload is 0.

(This function is also available in the `decSingle` module.)

decDoubleToUInt32(x, set, round)

Returns an unsigned 32-bit integer (`uint32_t`) which is the value of `x`, rounded to an integer if necessary using the explicit rounding mode `round` (`enum rounding`) instead of the rounding mode in `decNumberDefaultRounding`.

If `x` is infinite, is a `NaN`, or after rounding is outside the range of the result, then `DEC_Invalid_operation` is set. The `DEC_Inexact` flag is not set by this function, even if rounding occurred.

Note that `-0` converts to 0 and is valid, but all negative numbers are not valid.

decDoubleToUInt32Exact(x, set, round)

The same as `decDoubleToUInt32` except that if rounding removes non-zero digits then the `DEC_Inexact` flag is set.

decDoubleToWider(x, dq)

Converts `x` into a structure, `dq`, of the next-wider format (`decQuad *`) and returns `dq`. Widening is always exact; no status is set (`sNaNs` are copied and do not signal). The result will be canonical if `x` is canonical, but otherwise might not be.

(This function is also available in the `decSingle` module, but is not available in the `decQuad` module.)

decDoubleVersion(void)

Returns a pointer to a character string (`const char *`) which includes the name and the version of the `decNumber` package.

(This function is also available in the `decSingle` module.)

decDoubleXor(r, x, y, set)

Carries out the digit-wise logical exclusive Or of `x` and `y` and places the result in `r`.

The operands must be zero or positive (`sign=0`), an integer (finite with `exponent=0`) and comprise only zeros and/or ones; if not, `DEC_Invalid_operation` is set.

decDoubleZero(r)

Sets `r` to the unsigned integer zero (that is, with the coefficient, the exponent, and the sign all set to 0).
(This function is also available in the `decSingle` module.)

decPacked module

The `decPacked` module provides conversions to and from Packed Decimal numbers. Unlike the other modules, no specific `decPacked` data structure is defined because packed decimal numbers are usually held as simple byte arrays, with a scale either being held separately or implied.

Packed Decimal numbers are held as a sequence of Binary Coded Decimal digits, most significant first (at the lowest offset into the byte array) and one per 4 bits (that is, each digit taking a value of 0–9, and two digits per byte), with optional leading zero digits. The final sequence of 4 bits (called a “*nibble*”) will have a value greater than nine which is used to represent the sign of the number. The sign nibble may be any of the six possible values:

1010 (0x0a) plus
1011 (0x0b) minus
1100 (0x0c) plus (preferred)
1101 (0x0d) minus (preferred)
1110 (0x0e) plus
1111 (0x0f) plus²³

Packed Decimal numbers therefore represent decimal integers. They often have associated with them a second integer, called a *scale*. The scale of a number is the number of digits that follow the decimal point, and hence, for example, if a Packed Decimal number has the value `-123456` with a scale of 2, then the value of the combination is `-1234.56`.

Definitions

The `decPacked.h` header file does not define a specific data structure for Packed Decimal numbers.

It includes the `decNumber.h` header file, to simplify use, and (if not already defined) it sets the `DECNUMDIGITS` constant to 32, to allow for most common uses of Packed Decimal numbers. If you wish to work with higher (or lower) precisions, define `DECNUMDIGITS` to be the desired precision before including the `decPacked.h` header file.

The `decPacked.h` header file also contains:

- Constants describing the six possible values of sign nibble, as described above.
- Definitions of the public functions in the `decPacked` module.

Functions

The `decPacked.c` source file contains the public functions defined in the header file. These provide conversions to and from `decNumber` form.

decPackedFromNumber(bytes, length, scale, number)

This function is used to convert a `decNumber` to Packed Decimal format.

²³ Conventionally, this sign code can also be used to indicate that a number was originally unsigned.

The arguments are:

bytes (uint8_t *) Pointer to an array of unsigned bytes which will receive the number.
length (int32_t) Contains the length of the byte array, in bytes.
scale (int32_t *) Pointer to an int32_t which will receive the scale of the number.
number (decNumber *) Pointer to the input structure. The decNumber structure will not be altered.

Returns *bytes* unless the decNumber has too many digits to fit in *length* bytes (allowing for the sign) or is a special value (an infinity or NaN), in which cases NULL is returned and the *bytes* and *scale* values are unchanged.

The number is converted to bytes in Packed Decimal format, right aligned in the *bytes* array, whose length is given by the second parameter. The final 4-bit nibble in the array will be one of the preferred sign nibbles, 1100 (0x0c) for + or 1101 (0x0d) for -. The maximum number of digits that will fit in the array is therefore $length \times 2 - 1$. Unused bytes and nibbles to the left of the number are set to 0.

The *scale* is set to the scale of the number (this is the exponent, negated). To force the number to a particular scale, first use the decNumberRescale function (see page 39) on the number, negating the required scale in order to adjust its *exponent* and *coefficient* as necessary.

decPackedToNumber(*bytes*, *length*, *scale*, *number*)

This function is used to convert a Packed Decimal format number to decNumber form in preparation for arithmetic or other operations.

The arguments are:

bytes (uint8_t *) Pointer to an array of unsigned bytes which contain the number to be converted.
length (int32_t) Contains the length of the byte array, in bytes.
scale (int32_t *) Pointer to an int32_t which contains the scale of the number to be converted. This must be set; use 0 if the number has no associated scale (that is, it is an integer). The effective exponent of the resulting number (that is, the number of significant digits in the number, less the *scale*, less 1) must fit in 9 decimal digits.
number (decNumber *) Pointer to the decNumber structure which will receive the number. It must have space for $length \times 2 - 1$ digits.

Returns *number*, unless the effective exponent was out of range or the format of the *bytes* array was invalid (the final nibble was not a sign, or an earlier nibble was not in the range 0–9). In these error cases, NULL is returned and *number* will have the value 0.

Note that -0 and zeros with non-zero exponents are possible resulting numbers.

Additional options

This section describes some additional features of the decNumber package, intended to be used when customizing, tuning, or testing the package. If you are just using the package for applications, using full IEEE arithmetic, you should not need to modify the parameters controlling these features unless compiling for a big-endian target, in which case the `DECLITEND` setting will need to be altered.

If any of these parameters is changed, all the decNumber source files being used must be recompiled to ensure correct operation.

Each parameter is set to a default value in one of the header files, as noted below. The parameters are only set if undefined, so the defaults can be overridden by compiler command-line definitions (, with the option `-DDECUSE64=0`).

Customization parameters

The `decNumber` package includes four compile-time parameters for customizing its use.

The first parameter controls the layout of the compressed decimal formats (see page 48). The storage of a number in these formats must follow the byte ordering (“endianness”) of the computing platform; this parameter determines how the formats are loaded and stored. The parameter is set in the `decNumberLocal.h` file, and is:

DECLITEND This must be either 1 or 0. If 1, the target platform is assumed to be *little-endian* (for example, AMD and Intel x86 architecture machines are *little-endian*, where the byte containing the sign bit of the format is at the highest memory address). If 0, the target platform is assumed to be *big-endian* (for example, for IBM System z machines are *big-endian*, where the byte containing the sign bit of the format is at the lowest memory address).

Many compilers provide a compile-time definition for determining the endianness of the target platform, and `DECLITEND` can in that case be defined to use the provided definition.

The `decContextTestEndian` function can be called to check that the `DECLITEND` parameter is set correctly.

A second customization parameter allows the use of 64-bit integers to improve the performance of certain operations (notably multiplication and the mathematical functions), even when `DECDPUN` (see page 71) is less than 5. (64-bit integers are required for the `decNumber` module when `DECDPUN` is 5 or more.) The parameter is set in the `decNumberLocal.h` file, and is:

DECUSE64 This must be either 1 or 0. If 1, which is recommended, 64-bit integers will be used for most multiplications and mathematical functions when `DECDPUN` ≤ 4, and for most operations when `DECDPUN` > 4. If set to 0, 64-bit integer support is not used when `DECDPUN` ≤ 4, and the maximum value for `DECDPUN` is then 4. Full 64-bit support is not assumed; only 32×32 to 64 and the inverse (divide) are used; most 32-bit compilers will be able to handle these efficiently without requiring 64-bit hardware.

Another customization parameter controls whether the status flags returned by `decNumber` are restricted to the five IEEE flags or comprise an extended set which gives more detail about invalid operations along with some extra flags (this does not affect performance). The parameter is set in the `decContext.h` file, and is:

DECEXTFLAG This must be either 1 or 0. If 1, the extended set of flags is used. If 0, only 5 bits are used, corresponding to the IEEE 754 flags.

The fourth customization parameter enables the inclusion of extra code which implements and enforces the subset arithmetic defined by ANSI X3.274. This option should be disabled, for best performance, unless the subset arithmetic is required.

The parameter is set in the `decContext.h` file, and is:

DECSUBSET This must be either 1 or 0. If 1, subset arithmetic is enabled. This setting includes the *extended* flag in the `decContext` structure and all code which depends on that flag. Setting `DECSUBSET` to 0 improves the performance of many operations by 10%–20%.

Tuning parameters

The `decNumber` package incorporates two compile-time parameters for tuning the performance of the `decNumber` module. These are used to tune the trade-offs between storage use and speed. The first of these determines the granularity of calculations (the number of digits per unit of storage) and is normally set to three or to a power of two. The second is normally set so that short numbers (tens of digits) require no storage management – working buffers for operations will be stack based, not dynamically allocated. These are:

DECDPUN This parameter is set in the `decNumber.h` file, and must be an integer in the range 1 through 9. It sets the number of digits held in one *unit* (see page 30), which in turn alters the performance and other characteristics of the library. In particular:

- If **DECDPUN** is 1, conversions are fast, but arithmetic operations are at their slowest. In general, as the value of **DECDPUN** increases, arithmetic speed improves and conversion speed gets worse.
- Conversions between the `decNumber` internal format and the `decimal64` and other compressed formats are fastest – sometimes by as much as a factor of 4 or 5 – when **DECDPUN** is 3 (because `Densely Packed Decimal` encodes digits in groups of three).
- If **DECDPUN** is not 1, 3, or a power of two, calculations converting digits to units and vice versa are slow; this may slow some operations by up to 20%.
- If **DECDPUN** is greater than 4, either non-ANSI-C-89 integers or library calls have to be used for 64-bit intermediate calculations.²⁴

The suggested value for **DECDPUN** is 3, which gives good performance for working with the compressed decimal formats. If the compressed formats are not being used, or 64-bit integers are unavailable (see **DECUSE64**, below), then measuring the effect of changing **DECDPUN** to 4 is suggested. If the library is to be used for high precision calculations (many tens of digits) then it is recommended that measurements be made to evaluate whether to set **DECDPUN** to 8 (or possibly to 9, though this will often be slower).

DECBUFFER This parameter is set in the `decNumberLocal.h` file, and must be a non-negative integer. It sets the precision, in digits,²⁵ which the operator functions will handle without allocating dynamic storage.

One or more buffers of at least **DECBUFFER** bytes will be allocated on the stack, depending on the function. It is recommended that **DECBUFFER** be a multiple of **DECDPUN** and also a multiple of 4, and large enough to hold common numbers in your application.

²⁴ The `decNumber` library currently assumes that non-ANSI-C-89 64-bit integers are available if **DECDPUN** is greater than 4. See also the **DECUSE64** code parameter.

²⁵ Dynamic storage may still be allocated in certain cases, but in general this is rare.

Print and testing parameters

The `decNumber` package includes a compile-time parameter that can be used to prevent the package using the `printf` function. This parameter is set in the `decNumberLocal.h` file, and is:

DECPRINT This must be either 1 or 0. If 1, calls to `printf` are permitted; if 0, they will not. In the latter case, the `decContextTestEndian` will not display a warning message (even if its argument is 0), and also the functions `decSingleShow`, `decDoubleShow`, and `decQuadShow` will be excluded from compilation.

The `decNumber` package also incorporates three compile-time parameters which control the inclusion of extra code which provides for extra checking of input arguments, run-time internal tracing control, and storage allocation auditing. These options are usually disabled, for best performance, but are useful for testing and when introducing new conversion routines. It is recommended that **DECHECK** be set to 1 while developing an application that uses `decNumber`.

These test settings may all report errors using the `printf` function, so **DECPRINT** must be set to 1 if any of them are used. The parameters are all set in the `decNumberLocal.h` file, and are:

DECHECK This must be either 1 or 0. If 1, extra checking code, including input structure reference checks, will be included in the module. The latter checks that the structure references are not `NULL`, and that they refer to valid (internally consistent in the current context) structures. If an invalid reference is detected, the `DEC_Invalid_operation` status bit is set (which may cause a trap), a message may be displayed using `printf`, and any result will be a valid number of undefined value. This option is especially useful when testing programs that construct `decNumber` structures explicitly.

Some operations take more than twice as long with this checking enabled, so it is normally assumed that all `decNumbers` are valid and **DECHECK** is set to 0.

DECALLOC This must be either 1 or 0. If 1, all dynamic storage usage is audited and extra space is allocated to enable buffer overflow corruption checks. The cost of these checks is fairly small, but the setting should normally be left as 0 unless changes are being made to the `decNumber.c` source file.

DECTRACE This must be either 1 or 0. If 1, certain critical values are traced (using `printf`) as operations take place. This is intended for `decNumber` development use only, so again should normally be left as 0.

Appendix A – Library performance

The decNumber module implements arbitrary-precision arithmetic with fully tailorable parameters (rounding precision, exponent range, and other factors can all be changed at run time). All decNumber operations can accept arbitrary-length operands. Further, decNumber uses a general-purpose internal format (tunable at compile time) which therefore requires conversions to and from any external format (such as strings, BCD, or the IEEE 754 fixed-size decimal encodings).

As a result, the module has significant overheads compared to the dedicated decFloats modules (see page 52) which work directly on the fixed-size encodings. This appendix compares the performance of the decNumber module with the decDouble and decQuad implementations of the same operations. As the tables below show, there is a significant performance advantage in using the decFloats modules when arbitrary-precision operations are not required.

Description of the tables

In the following tables, timings for each operation are given in processor clock cycles. While generally a more useful indicator of comparative performance than “wall clock” times, cycle counts vary considerably with processor architecture. For example, the times below are cycles measured on an Intel Pentium M processor in an IBM X41T Thinkpad;²⁶ on a Pentium 4 or RISC processor most of the tests would show significantly higher cycle counts. The compiler used also makes a measurable difference. Details of the tests and compiler are given in the notes at the end of this appendix.

Throughout the tables, worst-case cycle times are shown for the main operations in the decDouble and decQuad modules, compared with the same operations using the decNumber module (which requires conversion of operands and results).

Worst-case timings are quoted because best-case timings are generally trivial special cases (such as NaN arguments) and “typical” instruction mixes are very application-dependent.

For each operation, the name of the operation is given, along with a brief description of the worst-case form of the operation. This is the worst case for the decFloats module (in some cases the worst case is different for the decNumber module).

²⁶ “Intel” and “Pentium” are trade marks of the Intel Corporation. “Thinkpad” is a trade mark of Lenovo.

decDouble performance tables

16-digit finite (with exponent)	39	481
16-digit finite (with exponent)	46	327
16-digit, with exponent	84	133
16-digit, with exponent (unrounded)	229	196
16-digit, rounded, with exponent (rounded (see page 77))	266	548
16-digit, with exponent	30	209
From most negative int	39	199
To most negative int32	32	136

(classify datum) Negative small subnormal	37	113
(Abs/Negate/Sign) CopySign, copy needed	25	338
Single digit	24	122
16-digit (digitwise)	23	510
Rotate 15 digits	154	583

(same-sign addition) 16-digit, unaligned, rounded	248	848
(different-signs addition) 16-digit, unaligned, rounded, borrow	288	
16-digit, unaligned, mismatch at end	126	442
16-digit, unaligned, mismatch at end	149	594
16- by 16-digit (rounded)	828	1576
(fused multiply-add) 16-digit, subtraction, rounded	785	1683
(returns a decDouble) Negative result	48	279
16-digit, unaligned, mismatch at end	155	656
16×16-digit, round needed	362	1305
16-digit, round all-nines	112	422
(from decDoubles) Underflow	212	513
16-digit, round all-nines	135	709

decQuad performance tables

34-digit finite (with exponent)	53	460
34-digit finite (with exponent)	74	307
34-digit, with exponent	183	239
34-digit, with exponent (unrounded)	297	597
34-digit, rounded, with exponent (rounded (see page 77))	451	956
34-digit, all nines	140	612
From most negative int	44	199
To most negative int32	32	156

(classify number) Negative small subnormal	53	133
(Abs/Negate/Sign) CopySign, copy needed	27	380
Single digit	27	138
34-digit (digitwise)	27	622
Rotate 33 digits	222	812

(same-sign addition) 34-digit, aligned	433	1180
(different-signs addition) 34-digit, unaligned, rounded, borrow	457	
34-digit, unaligned, mismatch at end	187	1125
34-digit, unaligned, mismatch at end	238	778
34- by 34-digit (rounded)	2018	3172
(fused multiply-add) 34-digit, subtraction, rounded	1622	2707
(returns a decQuad) Negative result	58	299
34-digit, unaligned, mismatch at end	241	857
34×34-digit, round needed	821	2235
34-digit, round all-nines	209	670
(from decQuads) Underflow	263	553
34-digit, round all-nines	233	886

Notes

The following notes apply to all the tables in this appendix.

1. All timings were made on an IBM X41T Tablet PC (Pentium M, 1.5GHz, 1.5GB RAM) under Windows XP Tablet Edition with SP2; the modules were compiled using GCC version 3.4.4 with optimization settings `-O3 -march=i686`.
2. The default tuning parameters were used (DECUSE64=1, DECDPUN=3, etc.); some of these only affect decNumber.
3. Timings include call/return overhead, and for the decNumber module also include the costs of converting operand(s) to decNumbers and results back to the appropriate format using the decimal64 or decimal128 module.
4. “BCD” for decNumber is Packed BCD, using the decPacked module; for decFloats it is 8-bit BCD.
5. The worst case for each operation is not always obvious from the code and is implementation-dependent (for example, in the decFloats modules, an unaligned add is sometimes faster than an aligned add). It is possible that there may be unusual cases which are slower than the decFloats

counts listed above, although a wide variety of micro-benchmarks have been tried.

6. A string-to-number conversion can theoretically have an arbitrarily large worst case as the string could contain any number of leading, trailing, or embedded zeros; the timings above measured cases where the input string's coefficient had up to eight more digits than the precision of the destination format.

Appendix B – Changes

This appendix documents changes since the first (internal) release of this document (Draft 1.50, 21 Feb 2001).

Changes in Draft 1.60 (9 July 2001)

- The significand of a number has been renamed from *integer* to *coefficient*, to remove possible ambiguities.
- The **decNumberRescale** function has been redefined to match the base specification. In particular its *rhs* now specifies the new exponent directly, rather than as a negated exponent.
- In general, all functions now return a reference to their primary result structure.
- The **decPackedToNumber** function now handles only “classic” Packed Decimal format (there must be a sign nibble, which must be the final nibble of the packed bytes). This improved conversion speed by a factor of two.
- Minor clarifications and editorial changes have been made.

Changes in Draft 1.65 (25 September 2001)

- The rounding modes `DEC_ROUND_CEILING` and `DEC_ROUND_FLOOR` have been added.
- Minor clarifications and editorial changes have been made.

Changes in Version 2.00 (4 December 2001)

This is the first public release of this document.

- The **decDoubleToSingle** function will now round the value of the `decDouble` number if it has more than 15 digits.
- The **decNumberToInteger**, **decNumberRemainderNear**, and **decNumberVersion** functions have been added.
- Relatively minor changes have been made throughout to reflect support for the extended specification.

Changes in Version 2.11 (25 March 2002)

- The header files have been reorganized in order to move private type names (such as `Int` and `Flag`) out of the external interface header files. In the external interface, integer types now use

the `stdint.h` names from C99.

- All but one of the compile-time parameters have been moved to the “internal” `decNumberLocal.h` header file, and so are described in a new section (see page 69).
- The **`decNumberAbs`**, **`decNumberMax`**, and **`decNumberMin`** functions have been added.
- Minor clarifications and editorial changes have been made.

Changes in Version 2.12 (23 April 2002)

- The **`decNumberTrim`** function has been added.
- The **`decNumberRescale`** function has been updated to match changed specifications; it now sets the exponent as requested even for zero values.
- Minor clarifications and editorial changes have been made.

Changes in Version 2.15 (5 July 2002)

The package has been updated to reflect the changes included in the combined arithmetic specification. These preserve more digits of the coefficient together with extended zero values if *extended* in the context is 1. Notably:

- The **`decNumberDivide`** and **`decNumberPower`** functions do not remove trailing zeros after the operation. (The **`decNumberTrim`** function can be used to effect this, if required.)
- A non-zero exponent on a zero value is now possible and is preserved in a manner consistent with other numbers (that is, zero is no longer a special case).
- The **`decPackedToNumber`** function has been enhanced to allow zeros with non-zero exponents to be converted without loss of information.

Changes in Version 2.17 (1 September 2002)

- The **`decNumberFromString`**, **`decSingleFromString`**, and **`decDoubleFromString`** functions will now round the coefficient of a number to fit, if necessary. They also now accept subnormal values and preserve the exponent of a 0. If an overflow or underflow occurs, the `DEC_Overflow` or `DEC_Underflow` conditions are raised, respectively.
- The package has been corrected to ensure that subnormal values are no more precise than permitted by IEEE 854.
- The underflow condition is now raised according to the IEEE 854 untrapped underflow criteria (instead of according to the IEEE 854 trapped criteria). That is, underflow is now only raised when a result is both subnormal and inexact.
- The `DEC_Subnormal` condition has been added so that subnormal results can be detected even if no Underflow condition is raised.
- Minor clarifications and editorial changes have been made.

Changes in Version 2.28 (1 November 2002)

- The **decNumberNormalize** function has been added, as an operator. This makes the coefficient of a number as short as possible while maintaining its numerical value.
- The **decNumberSquareRoot** function has been added. This returns the exact square root of a number, rounded to the specified precision and normalized.
- When the *extended* setting is 1, long operands are used without input rounding, to give a correctly rounded result (without double rounding). The DEC_Lost_digits flag can therefore only be set when *extended* is 0.
- Minor editorial changes have been made.

Changes in Version 3.04 (22 February 2003)

The major change in decNumber version 3 is the replacement of the decSingle and decDouble formats by the three new formats *decimal32*, *decimal64*, and *decimal128*. These formats are now [June 2008] included in the IEEE-SA 754 standard.

Related and other enhancements include:

- The exponent minimum field, *emin*, has been added to the decContext structure. This allows the unbalanced exponents used in the new formats.
- The exponent clamping flag, *clamp*, has been added to the decContext structure. This provides explicit exponent clamping as used in the new formats.
- A new condition flag, DEC_Clamped has been introduced. This reports any situation where the exponent of a finite result has been limited to fit in the available exponent range.
- The header file *bcd2dpd.h* has been renamed *decDPD.h* to better describe its function.
- The DECSUBSET tuning parameter has been added. This controls the inclusion of the code and flags required for subset arithmetic; when set to 0, the performance of many operations is improved by 10%–20%.
- Double rounding which was possible with certain subnormal results has been eliminated.
- Minor editorial changes have been made.

Changes in Version 3.09 (23 July 2003)

This version implements some minor changes which track changes agreed by the IEEE 754 revision committee.

- The **decNumberQuantize** function has been added. Its function is identical to **decNumberRescale** except that the second argument specifies the target exponent “by example” rather than by value.
- The **decNumberQuantize** and **decNumberRescale** functions now report DEC_Invalid_operation rather than DEC_Overflow if the result cannot fit.
- The **decNumberToInteger** function has been replaced by the **decNumberToIntegralValue** function. This implements the new rules for agreed by IEEE 754r.
Notably:

- the exponent is only set to zero if the operand had a negative exponent
- the Inexact flag is not set.
- The **decNumberSquareRoot** function no longer normalizes. Its preferred exponent is `floor(operand.exponent/2)`.

Changes in Version 3.12 (1 September 2003)

This version adds a new function and slightly reorganizes the decimalnn modules.

- The **decNumberSameQuantum** function has been added. This tests whether two numbers have the same exponents.
- The `decimal128.h`, `decimal64.h`, and `decimal32.h` header files now check that (if more than one is included) they are included in order of reducing size. This makes it harder to use a `decNumber` structure which is too small.
- . The shared DPD pack/unpack routines have been moved from `decimal32.c` to `decimal64.c`, because the latter is more likely to be used alone.

Changes in Version 3.16 (2 October 2003)

- NaN values may now use the coefficient to convey diagnostic information, and NaN sign information is propagated along with that information.
- The **decNumberQuantize** function now allows both arguments to be infinite, and treats NaNs in the same way as other functions.

Changes in Version 3.19 (21 November 2003)

- The **decNumberIsInfinite**, **decNumberIsNaN**, **decNumberIsNegative**, and **decNumberIsZero** functions have been added to simplify tests on numbers. These functions are currently implemented as macros.

Changes in Version 3.24 (25 August 2004)

- The **decNumberMax** and **decNumberMin** functions have been altered to conform to the `decNumberIsNaN` and `decNumberIsZero` functions in IEEE 754. That is, a total ordering is provided for numerical comparisons, and if one operand is a quiet NaN but the other is a number then the number is returned.
- The **decimal64FromString** function (and the same function for the other two formats) now uses the rounding mode provided in the context structure.

Changes in Version 3.25 (15 June 2005)

- Arguments to functions which are “input only” are now decorated with the `const` keyword to make the functions easier and safer to call from a C++ wrapper class.
- The performance of arithmetic when `DECDPUN<=3` has been improved substantially; `DECDPUN==3` performance is now similar to `DECDPUN==4`.

- An error in the `decNumberRescale` and `decNumberQuantize` functions has been corrected. This returned 1.000 instead of NaN for `quantize(0.9998, 0.001)` under a context with `precision=3`.

Changes in Version 3.32 (12 December 2005)

- The **`decNumberExp`** function has been added. This returns `10` raised to the power of the operand.
- The **`decNumberLn`** and **`decNumberLog10`** functions have been added. These return the natural logarithm (logarithm in base `e`) or the logarithm in the base ten of the operand, respectively.
- The **`decNumberPower`** function has been enhanced by removing restrictions; notably it now allows raising numbers to non-integer powers.
- The `DECENDIAN` tuning parameter has been added. This allows the compressed decimal formats (see page 48) to be stored using platform-dependent ordering for better performance and compatibility with binary formats. This parameter can be set to 0 to get the same (big-endian) ordering on all platforms, as in earlier versions of the `decNumber` package.
- The `DECUSE64` tuning parameter (see page 70) has been added. This allows 64-bit integers to be used to improve the performance of operations when `DECDPUN<=4`. This parameter can be set to 0 to ensure only 32-bit integers are used when `DECDPUN<=4`.
- The compressed decimal formats are widely used with the `decNumber` package, so the initial setting of `DECDPUN` has been changed to 3 (from 4), and `DECENDIAN` and `DECUSE64` are both set to 1 (to use platform ordering and 64-bit arithmetic). These settings significantly improve the speed of conversions to and from the compressed formats and the speed of multiplications and other operations.
- Minor clarifications and editorial changes have been made.

Changes in Version 3.37 (22 November 2006)

- The **`decNumberCompareTotal`** (total ordering comparison), **`decNumberIsQNaN`**, and **`decNumberIsSNaN`** functions have been added.

Changes in Version 3.40 (18 April 2007)

This is a major upgrade to `decNumber` to add logical and shifting functions together with generalizations of most of the new functions required by the IEEE 754 standard.

The changes included in this update are:

- Thirty-four new functions have been added to the `decNumber` module (all names have the prefix **`decNumber`**): **`And`**, **`CompareSignal`**, **`CompareTotalMag`**, **`CopyAbs`**, **`CopyNegate`**, **`CopySign`**, **`Class`**, **`ClassToString`**, **`FMA`**, **`FromInt`**, **`FromUInt`**, **`GetBCD`**, **`Invert`**, **`IsCanonical`**, **`IsFinite`**, **`IsNormal`**, **`IsSpecial`**, **`IsSubnormal`**, **`LogB`**, **`MaxMag`**, **`MinMag`**, **`NextMinus`**, **`NextPlus`**, **`NextToward`**, **`Or`**, **`Radix`**, **`Rotate`**, **`ScaleB`**, **`SetBCD`**, **`Shift`**, **`ToIntegralExact`**, **`ToInt32`**, **`ToUInt32`**, **`Xor`**.
- Two new functions have been added to each of the three `decimalNN` modules: **`decimalNNIsCanonical`**, **`decimalNNCanonical`**.

- The `DECENDIAN` setting (in `decNumberLocal.h`) has been removed to improve performance; instead, you must set the `DECLITEND` parameter (see page 70) to 1 if compiling for a little-endian target, or to 0 if compiling for a big-endian target. If `DECHECK` is set to 1 (highly recommended while testing), any call to `decContextDefault` will check that `DECLITEND` is set correctly.
- The `DECEXTFLAG` parameter (see page 70) has been added (in `decContext.h`). This controls whether the status flags returned by `decNumber` are restricted to the five IEEE flags or comprise an extended set which gives more detail about invalid operations along with some extra flags (this does not affect performance). The default is the extended set of flags, as in earlier versions of `decNumber`.

Changes in Version 3.41 (7 May 2007)

- Minor corrections (notably to the descriptions of the **FromString** functions) and clarifications have been made.

Changes in Version 3.50 (4 June 2007)

This is a major upgrade to `decNumber` which adds three new modules (`decSingle`, `decDouble`, and `decQuad`) with 175 new functions. These modules provide functions which work directly with the `decimal32`, `decimal64`, and `decimal128` formats, to provide high performance when arbitrary-precision calculations are not needed.

In addition to the new modules, the changes included in this update are:

- Two new examples have been added to the User's Guide, showing how to use the new modules either stand-alone or in conjunction with the `decNumber` module.
- Eleven new functions have been added to the `decContext` module to match those required by the IEEE 754 standard.
- Synonyms for `DEC_INIT_DECIMAL32`, , have been provided to match the names of the new modules, called `DEC_INIT_DECSINGLE`,
- The `decClasses` enumeration and strings have been moved from `decNumber.h` to `decContext.h` so that they can be used from all modules.
- The `DECVERSION` constant has been moved from `decNumber.h` to `decNumberLocal.h` so that it can be used from all modules.
- The `decNumberNormalize` function has been renamed `decNumberReduce` for clarity (it is still available in the code and header file under the old name, for compatibility).
- A new appendix comparing the performance of the `decNumber` module to the new `decDouble` and `decQuad` modules has been added.
- Numerous clarifications and editorial changes have been made.

Changes in Version 3.53 (7 September 2007)

This release of `decNumber` is a code maintenance release; the problems corrected are:

- `decNumberRemainder`: the sign of a zero result was occasionally different from that specified

by IEEE 854

- `decNumberSquareRoot`: several problems related to subnormal results that were not covered by Hull's algorithm and also when the input argument was wider than the requested result width
- `decNumber` and `decFloats`: under the `DEC_ROUND_05UP` rounding mode Infinity was being returned after overflow instead of the number with the greatest possible magnitude
- `decQuadDivide`: divisions where both operands had more than 27 digits and the result was extremely close to one (all but the last few digits the same) could return a value slightly larger than one instead of just less than one; this also affected the `decQuadDivideInteger` and `remainder` functions (but not `decDouble` or `decNumber` divisions or remainder)
- `decDoubleFromString` and `decQuadFromString`: the restriction that the input string should not be followed by unaddressable memory has been removed
- numerous code changes have been made to avoid new warnings in recent releases of GCC.

New testcases have been added for all the above cases.

Changes in Version 3.56 (12 October 2007)

This release of `decNumber` is a code maintenance release primarily to widen the applicability of the package. The changes are:

- The modules now conform to the C99 strict aliasing rules (that is, no longer cast `char *` pointers to `int *`, because such casts are forbidden in C99).
- As a consequence of the previous change, the `decDouble ()` structures have been changed to unions, allowing access through wider integer types as well as by bytes.
- Accesses to memory through an integer type are now always aligned. (Some RISC platforms reported alignment problems with parts of the code; thanks are due to Nelson Beebe for identifying and testing these cases.)
- The **`decContextTestEndian`** function has been added. This tests that the `DECLITEND` tuning parameter (see page 70) is set correctly, and optionally displays a message if it is not. A call to this function has been added to `example1.c`. This test is no longer automatic under `DECHECK` (it was inconvenient in some cases).
- The customization and tuning parameters are now only set to default values in the header files if not already defined. These means that they can be set from the compiler command line if desired (, with the option `-DDECUSE64=0`).
- The **`decDoubleFromPackedChecked`** function has been added (also for `decSingle` and `decQuad`); this is the same as `decDoubleFromPacked` except that all input values are checked.
- Edge-case errors in multiply, FMA, and remainder functions have been corrected.
- Minor code changes have been made to improve performance in some areas.

Changes in Version 3.61 (29 July 2008)

This release of `decNumber` is a code maintenance and performance release. The changes are:

- A fastpath has been added to `decDoubleAdd` and `decQuadAdd` for the common case of aligned

additions with exact results. This typically improves the performance in these cases by 2× or 3× respectively.

- The performance of `decNumberSquareRoot` has been improved when the result is exact or definitely inexact.
- The IEEE 854 names in `decContext.h` are now supplied with IEEE 754 names too (`DEC_IEEE_754_Inexact`).
- References to IEEE 854 and the old IEEE 754 standard have been removed and/or changed to refer to IEEE 754-2008.
- All references to the General Decimal Arithmetic website have been updated to <http://speleotrove.com/decimal> (its new location).
- A problem in `decFloatSubtract` and `decFloatQuantize` due to the `ISCOEFFZERO` macro re-using `UBTOUI` has been corrected (this only affected compilers that take advantage of C99 strict aliasing rules). This problem was previously published as an errata to 3.56.
- A buffer in `decQuadQuantize` was two bytes too short when the coefficient of the first operand had to be extended with 33 zeros; this is now corrected. This problem was previously published as an errata to 3.56.

The document is now formatted using OpenOffice (generated from GML), for improved PDF files with bookmarks, hot links, There are no technical changes.

Changes in Version 3.68 (23 January 2010)

This release of `decNumber` is primarily a code maintenance release. The changes are:

- Minor problems in the `decNumberLogB`, `decNumberScaleB`, `decDoubleIsSigned`, and `decQuadIsSigned` functions have been corrected. These problems were previously published as errata to 3.61.
- The **`decDoubleIsLogical`**, **`decDoubleIsNegative`**, and **`decDoubleIsPositive`** functions have been added (also for `decQuad`); these test whether the argument is valid for use as an operand to the logical functions, or is less than zero, or is greater than zero, respectively.
- The `DECPRINT` compile-time parameter has been added. This may be set to 0 to prevent the package using the `printf` function.

Index

6

64-bit integers 10, 70

A

abs operation 34, 54
abs operation, quiet 42, 55
addition 34, 36, 40, 54, 63
adjusted exponent 22, 30
aliasing, strict 21, 52
and, logical 35, 54
ANSI standard
 for REXX 7
 X3.274-1996 7
arbitrary precision 5
arguments
 corrupt 32
 modification of 32
 passed by reference 21
arithmetic
 decimal 5
 decNumber 34
 functions 34
 specification 5
auditing, of storage allocation 72

B

base 45
basic format 6
BCD
 see Binary Coded Decimal 5, 6
BCD8 encoding 56
big-endian 48, 53, 70
Binary Coded Decimal 5, 6, 43, 46, 67
Binary Coded Decimal
 conversion 56, 57, 63, 64
binary integer conversion 42, 43, 46, 56, 57, 64, 65
bits
 in a nibble 67
 in decNumber 30
bytes

 in decDouble 52
 in decimal128 48
 in decimal32 48
 in decimal64 48
 in decQuad 52
 in decSingle 52

C

canonical form 50, 51, 54
checking, of arguments 32, 72
clamp 81
clamp
 in decContext 23
Clamped condition 24
class of numbers 41, 54
classification of numbers 41, 54
code parameter
 DECALLOC 72
 DECCHECK 72
 DECEXTFLAG 70
 DECLITEND 70
 DECPRINT 72
 DECSUBSET 70
 DECTTRACE 72
 DECUSE64 70
coefficient
 in decNumber 30
 rotating 39
 shifting 40
comparison 35-37, 55
compile-time parameters 70-72
compound interest 12
compressed formats 5, 16
constants
 naming convention 21
conversion
 BCD to decFloat 56, 57
 binary integer to decFloat 56, 57
 binary integer to number 42, 43
 decFloat to BCD 63, 64
 decFloat to binary integer 64, 65

- decFloat to decNumber 20, 64
- decFloat to packed 64
- decimal128 to number 50
- decimal128 to string 49, 50
- decimal32 to number 50
- decimal32 to string 49, 50
- decimal64 to number 50
- decimal64 to string 49, 50
- decNumber 33
- decNumber to decFloat 20, 56
- number to binary integer 46
- number to decimal128 50
- number to decimal32 50
- number to decimal64 50
- number to packed 67
- number to string 33, 34
- packed to decFloat 56, 57
- packed to number 68
- string to decFloat 57
- string to decimal128 49
- string to decimal32 49
- string to decimal64 49
- string to number 33
- copying numbers 41, 42, 55
- corrupt arguments 32
- customization 70
- cycle times 73

D

- DEC_Clamped condition 24
- DEC_Divide_by_zero 60
- DEC_Division_impossible 35, 39, 56, 62
- DEC_Errors bits 13, 14, 24, 32
- DEC_Inexact condition 13, 24
- DEC_Invalid_operation condition 38, 39
- DEC_Lost_digits condition 24
- DEC_ROUND_05UP 22
- DEC_ROUND_CEILING 22
- DEC_ROUND_DEFAULT 23
- DEC_ROUND_DOWN 22
- DEC_ROUND_FLOOR 22
- DEC_ROUND_HALF_DOWN 22
- DEC_ROUND_HALF_EVEN 22
- DEC_ROUND_HALF_UP 22
- DEC_ROUND_UP 22
- DEC_Rounded condition 13, 24
- DEC_Subnormal condition 24
- DECALLOC code parameter 72
- DECBUFFER tuning parameter 71
- DECHECK code parameter 32, 72
- decClass enumeration 24, 32
- decContext 5, 19
 - clamp 23

- digits 22
- emax 22
- emin 22
- extended 23
- module 22
- round 22
- status 23
- traps 23
- decContext.h file 24, 70
- decContextClearStatus function 25
- decContextDefault function 25
- decContextGetRounding function 26
- decContextGetStatus function 26
- decContextRestoreStatus function 26
- decContextSaveStatus function 26
- decContextSetRounding function 27
- decContextSetStatus function 27
- decContextSetStatusFromString function 27
- decContextSetStatusFromStringQuiet function 28
- decContextSetStatusQuiet function 28
- decContextStatusToString function 28
- decContextTestEndian function 28
- decContextTestSavedStatus function 28
- decContextTestStatus function 29
- decContextZeroStatus function 29
- decDouble 6, 9
 - bytes 52
 - module 52
 - performance 74
 - using 19
- decDouble.h file 53
- decDoubleAbs function 54
- decDoubleAdd function 54
- decDoubleAnd function 54
- decDoubleCanonical function 54
- decDoubleClass function 54
- decDoubleClassString function 54
- decDoubleCompare function 55
- decDoubleCompareSignal function 55
- decDoubleCompareTotal function 55
- decDoubleCompareTotalMag function 55
- decDoubleCopy function 55
- decDoubleCopyAbs function 55
- decDoubleCopyNegate function 55
- decDoubleCopySign function 55
- decDoubleDigits function 55
- decDoubleDivide function 55
- decDoubleDivideInteger function 56
- decDoubleFMA function 56
- decDoubleFromBCD function 56
- decDoubleFromInt32 function 56
- decDoubleFromNumber function 56
- decDoubleFromPacked function 56
- decDoubleFromPackedChecked function 57

- decDoubleFromString function 57
- decDoubleFromUInt32 function 57
- decDoubleFromWider function 57
- decDoubleGetCoefficient function 58
- decDoubleGetExponent function 58
- decDoubleInvert function 58
- decDoubleIsCanonical function 58
- decDoubleIsFinite function 58
- decDoubleIsInfinite function 58
- decDoubleIsInteger function 58
- decDoubleIsLogical function 59
- decDoubleIsNaN function 59
- decDoubleIsNegative function 59
- decDoubleIsNormal function 59
- decDoubleIsPositive function 59
- decDoubleIsSignaling function 59
- decDoubleIsSignalling function 59
- decDoubleIsSigned function 59
- decDoubleIsSubnormal function 59
- decDoubleIsZero function 59
- decDoubleLogB function 60
- decDoubleMax function 60
- decDoubleMaxMag function 60
- decDoubleMin function 60
- decDoubleMinMag function 60
- decDoubleMinus function 60
- decDoubleMultiply function 60
- decDoubleNextMinus function 60
- decDoubleNextPlus function 61
- decDoubleNextToward function 61
- decDoubleOr function 61
- decDoublePlus function 61
- decDoubleQuantize function 61
- decDoubleRadix function 61
- decDoubleReduce function 61
- decDoubleRemainder function 62
- decDoubleRemainderNear function 62
- decDoubleRotate function 62
- decDoubleSameQuantum function 62
- decDoubleScaleB function 62
- decDoubleSetCoefficient function 62
- decDoubleSetExponent function 63
- decDoubleShift function 63
- decDoubleShow function 63
- decDoubleSubtract function 63
- decDoubleToBCD function 63
- decDoubleToEngString function 63
- decDoubleToInt32 function 64
- decDoubleToInt32Exact function 64
- decDoubleToIntegralExact function 64
- decDoubleToIntegralValue function 64
- decDoubleToNumber function 64
- decDoubleToPacked function 64
- decDoubleToString function 65

- decDoubleToUInt32 function 65
- decDoubleToUInt32Exact function 65
- decDoubleToWider function 65
- decDoubleVersion function 65
- decDoubleXor function 65
- decDoubleZero function 66
- decDPD.h file 49, 53
- DECDPUN tuning parameter 30, 32, 71
- DECENDIAN tuning parameter 84
- DECEXTFLAG code parameter 70
- DECEXTFLAG tuning parameter 24, 84
- decFloats 5, 6, 9
 - performance 73
 - using 19, 20
- decFloats modules 52
- decimal arithmetic 5
 - using 9
- decimal128 6
 - bytes 48
 - module 48
 - using 17
- decimal128.h file 48
- decimal128Canonical function 50
- decimal128FromNumber function 50
- decimal128FromString function 49
- decimal128IsCanonical function 51
- decimal128ToEngString function 50
- decimal128ToNumber function 50
- decimal128ToString function 49
- decimal32 6
 - bytes 48
 - module 48
 - using 17
- decimal32.h file 48
- decimal32Canonical function 50
- decimal32FromNumber function 50
- decimal32FromString function 49
- decimal32IsCanonical function 51
- decimal32ToEngString function 50
- decimal32ToNumber function 50
- decimal32ToString function 49
- decimal64 6
 - bytes 48
 - module 48
 - using 16
- decimal64 numbers 16
- decimal64.h file 48
- decimal64Canonical function 50
- decimal64FromNumber function 50
- decimal64FromString function 49
- decimal64IsCanonical function 51
- decimal64ToEngString function 50
- decimal64ToNumber function 50
- decimal64ToString function 49

DECLITEND code parameter 70
 DECLITEND tuning parameter 48, 53
 DECNEG sign bit 32
 decNumber 5, 30

- bits 30
- coefficient 30
- digits 30
- examples 31
- exponent 30
- lsu 30
- module 30
- msu 30
- performance 73
- sign 30
- significand 30
- size 30
- special values 30
- version 47, 65

decNumber.h file 11, 71
 decNumberAbs function 34
 decNumberAdd function 34
 decNumberAnd function 35
 decNumberClass function 41
 decNumberClassToString function 41
 decNumberCompare function 35
 decNumberCompareSignal function 35
 decNumberCompareTotal function 35
 decNumberCompareTotalMag function 35
 decNumberCopy function 41
 decNumberCopyAbs function 42
 decNumberCopyNegate function 42
 decNumberCopySign function 42
 decNumberDivide function 35
 decNumberDivideInteger function 35
 decNumberExp function 35
 decNumberFMA function 36
 decNumberFromInt32 function 42
 decNumberFromString function 33
 decNumberFromUInt32 function 43
 decNumberGetBCD function 43
 decNumberInvert function 36
 decNumberIsCanonical function 43
 decNumberIsFinite function 43
 decNumberIsInfinite function 43
 decNumberIsNaN function 44
 decNumberIsNegative function 44
 decNumberIsNormal function 44
 decNumberIsQNaN function 44
 decNumberIsSNaN function 44
 decNumberIsSpecial function 45
 decNumberIsSubnormal function 45
 decNumberIsZero function 45
 decNumberLn function 36
 decNumberLocal.h file 21, 70-72

decNumberLog10 function 36
 decNumberLogB function 36
 decNumberMax function 36
 decNumberMaxMag function 37
 decNumberMin function 37
 decNumberMinMag function 37
 decNumberMinus function 37
 decNumberMultiply function 37
 decNumberNextMinus function 37
 decNumberNextPlus function 37
 decNumberNextToward function 37
 decNumberNormalize
 see decNumberReduce 45
 decNumberOr function 38
 decNumberPlus function 38
 decNumberPower function 38
 decNumberQuantize function 38
 decNumberRadix function 45
 decNumberReduce function 45
 decNumberRemainder function 39
 decNumberRemainderNear function 39
 decNumberRescale function 39
 decNumberRotate function 39
 decNumberSameQuantum function 40
 decNumberScaleB function 40
 decNumberSetBCD function 46
 decNumberShift function 40
 decNumberSquareRoot function 40
 decNumberSubtract function 40
 decNumberToEngString function 34
 decNumberToInt32 function 46
 decNumberToIntegralExact function 41
 decNumberToIntegralValue 81
 decNumberToIntegralValue function 41
 decNumberToString function 33
 decNumberToUInt32 function 46
 decNumberTrim function 46
 decNumberUnit type 31, 71
 decNumberVersion function 47
 decNumberXor function 41
 decNumberZero function 47
 DECNUMDIGITS constant 16, 17, 31
 set by decimal128.h 48
 set by decimal32.h 48
 set by decimal64.h 48
 set by decPacked.h 67
 decPacked 6
 module 67
 using 18
 decPacked.h file 67
 decPackedFromNumber function 67
 decPackedToNumber function 68
 DECPRINT code parameter 72
 decQuad 6, 9

- bytes 52
- decNumber use 20
- module 52
- performance 76
- using 19, 20
- decQuad.h file 53
- decQuadAbs function 54
- decQuadAdd function 54
- decQuadAnd function 54
- decQuadCanonical function 54
- decQuadClass function 54
- decQuadClassString function 54
- decQuadCompare function 55
- decQuadCompareSignal function 55
- decQuadCompareTotal function 55
- decQuadCompareTotalMag function 55
- decQuadCopy function 55
- decQuadCopyAbs function 55
- decQuadCopyNegate function 55
- decQuadCopySign function 55
- decQuadDigits function 55
- decQuadDivide function 55
- decQuadDivideInteger function 56
- decQuadFMA function 56
- decQuadFromBCD function 56
- decQuadFromInt32 function 56
- decQuadFromNumber function 56
- decQuadFromPacked function 56
- decQuadFromPackedChecked function 57
- decQuadFromString function 57
- decQuadFromUInt32 function 57
- decQuadGetCoefficient function 58
- decQuadGetExponent function 58
- decQuadInvert function 58
- decQuadIsCanonical function 58
- decQuadIsFinite function 58
- decQuadIsInfinite function 58
- decQuadIsInteger function 58
- decQuadIsLogical function 59
- decQuadIsNaN function 59
- decQuadIsNegative function 59
- decQuadIsNormal function 59
- decQuadIsPositive function 59
- decQuadIsSignaling function 59
- decQuadIsSignalling function 59
- decQuadIsSigned function 59
- decQuadIsSubnormal function 59
- decQuadIsZero function 59
- decQuadLogB function 60
- decQuadMax function 60
- decQuadMaxMag function 60
- decQuadMin function 60
- decQuadMinMag function 60
- decQuadMinus function 60

- decQuadMultiply function 60
- decQuadNextMinus function 60
- decQuadNextPlus function 61
- decQuadNextToward function 61
- decQuadOr function 61
- decQuadPlus function 61
- decQuadQuantize function 61
- decQuadRadix function 61
- decQuadReduce function 61
- decQuadRemainder function 62
- decQuadRemainderNear function 62
- decQuadRotate function 62
- decQuadSameQuantum function 62
- decQuadScaleB function 62
- decQuadSetCoefficient function 62
- decQuadSetExponent function 63
- decQuadShift function 63
- decQuadShow function 63
- decQuadSubtract function 63
- decQuadToBCD function 63
- decQuadToEngString function 63
- decQuadToInt32 function 64
- decQuadToInt32Exact function 64
- decQuadToIntegralExact function 64
- decQuadToIntegralValue function 64
- decQuadToNumber function 64
- decQuadToPacked function 64
- decQuadToString function 65
- decQuadToUInt32 function 65
- decQuadToUInt32Exact function 65
- decQuadVersion function 65
- decQuadXor function 65
- decQuadZero function 66
- decSingle 6, 9
 - bytes 52
 - module 52
- decSingle.h file 53
- decSingleFromBCD function 56
- decSingleFromNumber function 56
- decSingleFromPacked function 56
- decSingleFromPackedChecked function 57
- decSingleFromString function 57
- decSingleFromWider function 57
- decSingleGetCoefficient function 58
- decSingleGetExponent function 58
- decSingleRadix function 61
- decSingleSetCoefficient function 62
- decSingleSetExponent function 63
- decSingleShow function 63
- decSingleToBCD function 63
- decSingleToEngString function 63
- decSingleToNumber function 64
- decSingleToPacked function 64
- decSingleToString function 65

- decSingleToWider function 65
- decSingleVersion function 65
- decSingleZero function 66
- DECSUBSET code parameter 70
- DECSUBSET tuning parameter 24
- DECTrace code parameter 72
- DECUSE64 code parameter 70
- DECUSE64 tuning parameter 10
- Densely Packed Decimal 48, 49, 52, 53, 71
- Densely Packed Decimal
 - coding and decoding 48
- development aids 72
- digits
 - in a decFloat 55
 - in decContext 22
 - in decNumber 30
- division 35, 39, 55, 56
- DPD
 - see Densely Packed Decimal 48, 52
- dynamic storage 21, 32, 71, 72
 - auditing 72

E

- e 35, 36
- emax
 - in decContext 22
- emin 81
- emin
 - in decContext 22
- endian 48, 53, 70
- engineering notation 34, 50, 63
- error handling 23
- error handling
 - active 14
 - passive 13
 - with signal 14
- example 9
 - active error handling 14
 - compound interest 12
 - compressed formats 16
 - decimal64 numbers 16
 - decNumber 31
 - decPacked module 18
 - decQuad module 19, 20
 - Example 1 11
 - Example 2 12
 - Example 3 13
 - Example 4 14
 - Example 5 16
 - Example 6 18
 - Example 7 19
 - Example 8 20
 - passive error handling 13

- simple addition 11
- special values 31
- exceptional conditions 23
- exclusive or, logical 41, 65
- exp operation 35
- exponent
 - adjusted 22, 30
 - adjusting 40
 - checking 40
 - in decNumber 30
 - maximum 22
 - minimum 22
 - scaling 40
 - setting 38, 39
- exponentiation 35, 38
- extended
 - in decContext 23

F

- features, extra 69
- file
 - header 5
 - source 5
- fixed-size representations 5
- FMA
 - see fused multiply-add 36
- functions
 - arithmetic 34
 - conversions 33
 - logical 34
 - mathematical 34
 - naming convention 21
 - utilities 41
- fused multiply-add operation 36, 56

G

- General Decimal Arithmetic 5, 53

H

- header file 5
 - decContext 24
 - decDouble 53
 - decDPD 49, 53
 - decimal128 48
 - decimal32 48
 - decimal64 48
 - decNumber 32
 - decNumberLocal 21, 71, 72
 - decPacked 67
 - decQuad 53
 - decSingle 53

I

- inclusive or, logical 38, 61
- Inexact condition 13, 24
- infinite results 32
- infinity 30
- initializing numbers 33, 47
- int data type 21
- integer rounding 41, 64
- integers
 - 64-bit 21, 52
 - unaligned 21, 52
- invert, logical 36, 58

L

- little-endian 48, 53, 70
- ln operation 36
- log10 operation 36
- logarithm
 - base 10 36
 - base e 36
 - exponent 36
 - natural 36
- logB operation 36
- LogB operation 60
- logical
 - and 35, 54
 - exclusive or 41, 65
 - functions 34
 - inclusive or 38, 61
 - invert 36
 - or 38, 61, 65
 - xor 41
- long data type 21
- longjmp function 14
- Lost digits condition 24
- lsu, in decNumber 30

M

- mathematical functions 34
- max operation 36, 60
- maximum exponent 22
- maxmag operation 37, 60
- min operation 37, 60
- minimum exponent 22
- minmag operation 37, 60
- minus operation 37, 60
- minus operation
 - quiet 42, 55
- modification of arguments 32
- module 21
 - decContext 22
 - decDouble 52
 - decimal128 48

- decimal32 48
- decimal64 48
- decNumber 30
- decPacked 67
- decQuad 52
- decSingle 52
- naming convention 21
- reentrancy 21, 52
- unaligned integers 21, 52
- monadic operators 34
- msu, in decNumber 30
- multiplication 36, 37, 60

N

- naming convention
 - constants 21
 - functions 21
 - modules 21
- NaN 30
 - diagnostic 30
 - quiet 30
 - results 32
 - signaling 30
- narrowing decFloat 57
- negation 37, 42, 55
- negative, testing for 59
- nibble 56, 57, 64, 67
- normal values 22, 44, 45
- normalizing numbers 45, 61, 81

O

- options, extra 69
- or, logical 38, 41, 61, 65

P

- packed BCD 56, 57
 - checking 57
- Packed Decimal 5, 6, 67
- parameters
 - compile-time 69
 - tuning 32, 71
- performance 73
 - cycles 73
 - decDouble 74
 - decQuad 76
 - notes 77
 - tables 73
- performance tuning 71
- plus operation 38, 61
- positive, testing for 59
- power operator 38
- prefix
 - abs 34

- minus 37
- plus 38
- printf a decFloat 63
- printf function 11, 28, 72
- proxies 48, 53

Q

- quantizing 38, 40, 61
 - to integral 41, 64
- quiet NaN 30

R

- radix 45, 61
- reduce operation 45, 61
- reentrant modules 21, 52
- references, to arguments 21
- remainder 39, 62
- rescaling 38-40
- results
 - rounding of 24
 - undefined 32
- root, square 40
- rotating 39, 62
- round
 - in decContext 22
 - see rounding 30
- round enumeration 24
- round-to-integer operation 41, 64
- Rounded condition 13, 24
- rounding
 - detection of 24
 - enumeration 22
 - to decimal places 38
 - to integer 38, 41, 64
 - using decNumberPlus 38

S

- scale 6, 67
- scale
 - by powers of ten 40, 62
 - checking 40
 - setting 38, 39
- scientific notation 33, 49
- setjmp function 14, 15
- shifting 40, 63
- showing a decFloat 63
- SIGFPE
 - implementation issues 10
- signal 14, 15, 23
- sign
 - copying 42, 55
 - DECNEG bit 32
 - in decNumber 30

- signal
 - function 14, 15
 - handler 14
- signaling NaN 30
- significand
 - in decNumber 30
 - see coefficient 30
- size, of decNumber 30
- source file 5
 - decContext 25
 - decDouble 53
 - decimal128 49
 - decimal32 49
 - decimal64 49
 - decNumber 32
 - decPacked 67
 - decQuad 53
 - decSingle 53
- special values 23, 30, 31
- special values
 - in decNumber 30
- specification
 - arithmetic 5
- speed of operations 32, 71
- square root operation 40, 81, 82
- status
 - in decContext 23
- stdint.h file 10
- stdio.h file 11
- storage allocation 72
 - auditing 72
- strict aliasing 21, 52
- Subnormal condition 24
- subnormal values 22, 30, 33, 41, 44, 45, 80
- subset arithmetic, enabling 70
- subtraction 40, 63

T

- test aids 63, 72
- testing decFloats 58, 59, 62
- testing numbers 43-45
- trailing zeros, removing 45, 46, 61
- traps 23
 - in decContext 23
- trimming numbers 46
- tuning parameter 21, 71
 - DECBUFFER 71
 - DECDPUN 32, 71
 - DECEXTFLAG 24
 - DECLITEND 48, 53
 - DECSUBSET 24

U

unaligned integers 21, 52

undefined results 32

unit

in decNumber 30

size of 30, 32, 71

User's Guide 9

utilities

decNumber 41

V

value of a number 30

version, of decNumber 47, 65

W

widening decFloats 65

X

xor, logical 41

Z

zero

decDouble 66

decNumber 31, 47

decQuad 66

setting 47, 66

testing for 45, 59

zero decNumber 31

zeros, removing trailing 45, 46, 61

.

.c (source) files 5

.h (header) files 5

/

// comments in C programs 9