


Specify the computer to be used to find classes, relationships, etc. Clicking No will assume localhost is your SCSM server.



1. Projection Name – **Required** – This will be the ‘short name’ of the projection in the Management Pack
2. Projection Display Name – Optional – This will be what is displayed anywhere you can pick the Projection. Example:

Select a Class

Select the class you want and click OK. You can use Filter by name and the View list to better define the list of displayed classes.


Filter: jkw

Combination classes

| Name               | Management Pack                | Description |
|--------------------|--------------------------------|-------------|
| JKW Printer (Full) | JKW.Projection.Printer.Full_MP |             |
| JKW Printer(Owner) | JKW.Projection.Printer.MP      |             |

Choosing to not provide a DisplayName will cause the Displayname to be the same as the Projection Name

- Management Pack Name – Optional – This will be the name of the Management Pack. Should **NOT** contain spaces or special characters. This field is not validated! Choosing to not provide a Management Pack Name will cause the Management Pack Name to become the Projection Name + “.MP”
- Management Pack Version – Optional – Should be in the format Major.Minor.Build.Revision(ie 7.5.7487.0) – This field is validated. If the version is not in the correct format the Build button will not be enabled. Choosing to not provide a version will cause the version to be “1.0.0.0”
- Save Path - **Required** – This is the path that the XML or MP file will be saved to.
- Key Path – Optional – If the MP is to be sealed, this field is required. This is the location of the .SNK file to be used for sealing the MP. Failing to provide the SNK file and checking ‘Seal’ will cause the Build button to not be enabled. Note: there is no validation that the file being picked is a valid .SNK file. Choose wisely.
- Company – Optional - If the MP is to be sealed, this field is required. This is the Company name provided to the MP sealing process. Failing to provide the Company name and checking ‘Seal’ will cause the Build button to not be enabled.
- Computer – Optional – If the MP is to be imported, this field is required. This is the computer that will be asked to import the MP. Failing to provide the Computer and checking ‘Import’ will cause the Build button to not be enabled. Note: If ‘Import’ is checked and the computer name is provided and the Build button is still not enabled, try clicking out of the Computer name field. Computer validation is done when the Computer field loses focus.
- Class – **Required** – This is the Class the Projection will be based on. The Filter field can be used to filter the class list:



10. Relationships – **Required** – These are the relationships that will act as components in the Type Projection. At least one relationship must be selected for the Build button to become enabled.
11. Selected – This displays the already selected relationships/components for the Type Projection. The Remove button can be used to remove previously selected relationship by highlighting them in the grid and clicking Remove.
12. Seal/Import – Optional – To seal the MP, check the Seal checkbox. Remember to provide a Key Path and a Company Name. To import the MP, check the Import checkbox. Remember to provide a SCSM Management server in the computer field.
13. Build – This button will use all the options provided and compile the Management Pack and save it to the specified Save Path. If Seal is checked, the output will be a .MP file.