

NCR Command Center CMC Installer Configuration



CMCInst.exe Command Line Arguments:

/InstallPath path - Specify the full path to install CMCAgent. If the path has spaces, use double-quotes around the path.

/SiteID number - Set the site's CMC ID number to a specific numeric value. This is used when you are provided a pre-generated Site ID.

/POSID entry - Set the site's POS ID, a configurable descriptor that allows letters and numbers.

/NodeID number - When installing on a node/terminal, set the node's ID to a specific (numeric > 0) value. This can only be used on node/terminal machines.

/NodeName name - Set the machine's node name to configure how it will appear in the CMC store tree.

/Industry name - Specifies the Industry name in the "Industry.config" file. Usually set to "Aloha", "Retail", or "Generic", depending on site.

/DataCenter or /DC - Configures connection to the named DataCenter.

1. **PROD** - US-Production datacenter at rdf2.alohaenterprise.com. This is the default DC.
2. **HK** - Hong Kong Production datacenter at cmc.alohaenterprise.hk.
3. **EMEA** or **EU** - European production datacenter at cmc.alohaenterprise.eu.
4. **CN** - Shanghai, China production datacenter at cmc.alohaenterprise.cn.
5. **Retail** - Retail Industry datacenter at NCRCommandCenter4Retail.com.
6. **Preprod** - Preproduction datacenter, used for testing, at cmctest.dev.alohaenterprise.com.

/ForceAlohaRestart - On Aloha POS installs, forces POS terminals to restart to immediately complete the terminal bootstrapping installation process through BIN Sync.

/OnlineOrder or **/OnlineOrderOn** - Configures and enables online ordering with the default commandcenter.config settings.

/OnlineOrderOff - Removes online ordering configuration from commandcenter.config, restarts CMCAgent service.

/CPS - Configures whether Online Ordering CPS (Consumer Profile Service) is required [On, Off]

/SiteHealth - Configures and starts the Site Health Agent service.

/SiteHealthDisable - Stops and disables the Site Health Agent service.

/Server1 ip/hostname - In a Retail, ACS Dual Server environment, specifies the IP address/hostname of one of the store servers (Industry.config must be set to "Retail").

/Server2 ip/hostname - In a Retail, ACS Dual Server environment, specifies the IP address/hostname of the other store server (Industry.config must be set to "Retail").

/PreApp service - Specifies the PVNC pre-app. This will configure CMCAgent to disable this service before starting PVNC to avoid VNC service collision.

/PostApp service - Specifies the PVNC post-app. This will configure CMCAgent to enable the service after PVNC has closed to put the machine back into its original state.



CMC Installer Configuration - Quick Reference

/ForceInstall - Installs CMCAgent and related services, ignoring prerequisite check (cmcreqcheck.exe) failures.

/InstallDisabled - Installs CMCAgent and related services with startup type "Disabled". Removes the "Proxy" startup on UAC-enabled systems.

/InstallManual - Installs CMCAgent and related services with startup type "Manual". Removes the "Proxy" startup on UAC-enabled systems.

/Pause - Before exiting, requires user input (for console inspection).

/Help or **/?** - Shows a help message in the command prompt, providing the information from this document to assist with CMCInst.exe install parameter information.

Support

Click **Contact Us** to email the Command Center support team with questions, issues, enhancement suggestions, and more.

Support@alohaenterprise.com

You can also contact support from the Command Center Login screen.