

OpenCV for Unity based on OpenCV3.0.0 beta5

iOS & Android support

WindowsStoreApps8.1 & WindowsPhone8.1 support

Win & Mac & Linux Standalone support

Support for preview in the Editor

Work with Unity Free & Pro

System Requirements

Build Win Standalone & Preview Editor : Windows7 or later

Build Mac Standalone & Preview Editor : OSX 10.8 or later

OpenCV for Unity is an Assets Plugin for using **OpenCV** from within **Unity**.

- Since this package is a **clone of OpenCV Java**, you can use as it is **all** the API Reference OpenCV Java 3.0.0.
- You can image processing in **real-time** by using the **WebCamTexture** capabilities of Unity. (**real-time face detection works smoothly in iPhone 5**)
- Provides a method to interconversion of **Unity's Texture2D** and **OpenCV's Mat**.
- Includes many classes from OpenCVForUnity, and implements **IDisposable**. You can manage the resources with the **"using"** statement.

Please download [Demo Application](#) for Android and watch Setup Tutorial Video([Unity4](#) [Unity5](#)).

[API Reference OpenCV for Unity](#)

SampleCode using OpenCV for Unity is available.

- [MarkerBased AR Sample](#)
- [FaceTracker Sample](#)
- [Vuforia with OpenCV for Unity Sample](#)
- [Kinect with OpenCV for Unity Sample](#)

Version changes

Beta5 [Linux]Add Linux Support. [WindowsStoreApp8.1]Support for methods using Low-level Native Plugin Interface. [Common]Rewrite SampleScene.


Beta4 [Common]Add Utils. getGraphicsDeviceType(). [Common]Add SampleScene Setup Tutorial Video for Unity5.

Beta3 [Common]Add CamShiftSample.(Object Tracking) [Common]Add OpenCVForUnityMenuItem.cs.(This script set plugin import settings automatically from MenuItem.)

Beta2 [iOS] Fix problem when working with Metaio(UnityAppController problem). [Common]Add [System.Serializable] to basic class. [Common] change folder name from “OpenCVForUnity/OpenCVForUnity_Editor/” to “OpenCVForUnity/Editor/”. [iOS]Move “OpenCVForUnity/OpenCVForUnity_Editor/opencv2.framework” to “OpenCVForUnity/Plugins/iOS”folder.

Quick setup procedure to run the sample scene(Setup Tutorial Video [Unity4](#) [Unity5](#))


1. Select MenuItem[Tools/OpenCV for Unity/Set Plugin Import Settings].



2. Move “OpenCVForUnity/StreamingAssets/”folder to “Assets/”folder.
3. Please set [PlayerSettings]-[Resolution and Presentation]-[Orientation]-[Default Orientation : Landscape Left] when you build the sample scene.
4. Add all of the “***.unity” in the “OpenCVForUnity” folder to [Build Settings] – [Scene In Build].


※Inspector Setting of “opencv2.framework” and “opencvforunity.bundle” might have been reset at the time of import. In that case, re-setup is required.

Screenshot after the setup




Android Setup Procedure

- “OpenCVForUnity/Plugins/Android/opencvforunity.jar” – Select platform Android in Inspector.
- “OpenCVForUnity/Plugins/libs/armeabi-v7a/*.so” - Select platform Android and CPU ARMv7 in Inspector.




- “OpenCVForUnity/Plugins/libs/x86/*.so” – Select platform Android and CPU x86 in Inspector.




- Put the file that you want to use for `Utils.getFilePath()` in the “Assets/StreamingAssets/” folder. (haarcascade_frontalface_alt.xml etc is for `OpenCVForUnitySample.scene`. Please copy only when necessary.)

iOS Setup Procedure

- “OpenCVForUnity/Plugins/iOS/libopencvforunity.a” – Select platform iOS in Inspector.




- “OpenCVForUnity/Plugins/iOS/opencv2.framework” – Set all the check box a non-choice state.




- Put the file that you want to use for `Utils.getFilePath()` in the “Assets/StreamingAssets/” folder. (haarcascade_frontalface_alt.xml etc is for OpenCVForUnitySample.scene. Please copy only when necessary.)

Win Standalone Setup Procedure

- “OpenCVForUnity/Plugins/x86/opencvforunity.dll” – Select platform Editor, Standalone and CPU x86 and OS Windows in Inspector.




- “OpenCVForUnity/Plugins/x86_64/opencvforunity.dll” – Select platform Editor, Standalone and CPU x86_64 and OS Windows in Inspector.



- Put the file that you want to use for `Utils.getFilePath()` in the "Assets/StreamingAssets/". (haarcascade_frontalface_alt.xml etc is for OpenCVForUnitySample.scene. Please copy only when necessary.)
- If you use the "VideoCapture(string filename)", require setup.
 - 1)Download "OpenCV for Windows Version 3.0.0"(<http://opencv.org/downloads.html>).
 - 2)Set Path to "opencv_ffmpeg300.dll"
 - if 32bit, "C:\opencv\build\x86\vc12\bin".
 - if 64bit, "C:\opencv\build\x64\vc12\bin".

Mac Standalone Setup Procedure


- “OpenCVForUnity/Plugins/opencvforunity.bundle” – Select platform Editor, Standalone and CPU x86_64 and OS OSX in Inspector.




- Put the file that you want to use for `Utils.getFilePath()` in the “Assets/StreamingAssets/”. (haarcascade_frontalface_alt.xml etc is for `OpenCVForUnitySample.scene`. Please copy only when necessary.)

WindowsStoreApps8.1 & WindowsPhone8.1 Setup Procedure


- “OpenCVForUnity/Plugins/WSA/SDK81/ARM/*.dll” - Select platform WSAPlayer and SDK81 and CPU ARM in Inspector. Set “x86” and “x64” in the same way as “ARM”.



- “OpenCVForUnity/Plugins/WSA/PhoneSDK81/ARM/*.dll” - Select platform WSAPlayer and PhoneSDK81 and CPU ARM in Inspector. Set “x86” in the same way as “ARM”.



- Put the file that you want to use for `Utils.getFilePath()` in the "Assets/StreamingAssets/". (haarcascade_frontalface_alt.xml etc is for `OpenCVForUnitySample.scene`. Please copy only when necessary.)
- If use `webCamTextue` class, Please choose "WebCam" in [PlayerSettings]-[PublishingSettings]-[Capabilities].




Linux Setup Procedure

- Install OpenCV3.0.0 (require opencv-contrib module)


Example of Install command

1. `sudo apt-get -y install libopencv-dev build-essential cmake git libgtk2.0-dev pkg-config python-dev python-numpy libdc1394-22 libdc1394-22-dev libjpeg-dev libpng12-dev libtiff4-dev libjasper-dev libavcodec-dev libavformat-dev libswscale-dev libxine-dev libgstreamer0.10-dev libgstreamer-plugins-base0.10-dev libv4l-dev libtbb-dev libqt4-dev libfaac-dev libmp3lame-dev libopencore-amrnb-dev libopencore-amrwb-dev libtheora-dev libvorbis-dev libxvidcore-dev x264 v4l-utils unzip`
2. `mkdir opencv`
3. `cd opencv`
4. `wget https://github.com/Itseez/opencv/archive/3.0.0.zip -O opencv-3.0.0.zip`
5. `unzip opencv-3.0.0.zip`
6. `wget https://github.com/Itseez/opencv_contrib/archive/3.0.0.zip -O opencv_contrib-3.0.0.zip`
7. `unzip opencv_contrib-3.0.0.zip`
8. `cd opencv-3.0.0`
9. `mkdir build`
10. `cd build`
11. `cmake -D CMAKE_BUILD_TYPE=RELEASE -D CMAKE_INSTALL_PREFIX=/usr/local -D WITH_TBB=ON -D BUILD_NEW_PYTHON_SUPPORT=ON -D WITH_V4L=ON -D WITH_QT=ON -D WITH_OPENGL=ON -D OPENCV_EXTRA_MODULES_PATH=../../opencv_contrib-3.0.0/modules ..`
12. `make -j $(nproc)`
13. `sudo make install`
14. `sudo /bin/bash -c 'echo "/usr/local/lib" > /etc/ld.so.conf.d/opencv.conf'`
15. `sudo ldconfig`

- “OpenCVForUnity/Plugins/x86/libopencvforunity.so” – Select platform Editor,Standalone and CPU x86 and OS Linux in Inspector.



- “OpenCVForUnity/Plugins/x86_64/libopencvforunity.so” – Select platform Editor, Standalone and CPU x86_64 and OS Linux in Inspector.



- Put the file that you want to use for `Utils.getFilePath()` in the “Aseets/StreamingAssets/”. (`haarcascade_frontalface_alt.xml` etc is for `OpenCVForUnitySample.scene`. Please copy only when necessary.)

Q & A

Q1.

“`DllNotFoundException: opencvforunity`” is displayed on the console when run the sample scene.

A1.

Plugin does not seem to be loaded correctly. Please check the setup procedure.

Q2.

“`ArgumentException: The output Mat object has to be of the same size`” is displayed on the console when run the sample scene.

A2.

After having set up Plugin, Plugin may work well when you reboot Unity.

Q3.

“`Level 'Texture2DtoMatSample' (-1) could not be loaded because it has not been added to the build settings.`” is displayed on the console when run the sample scene.

A3.

Please Add all of the “`***.unity`” in the “OpenCVForUnity” folder to [Build Settings] – [Scene In Build].

Q4.

In DetectFaceSample or WebCamTextureDetectFaceSample, red rectangle is not displayed around face.

A4.

you might have failed to read the "haarcascade_frontalface_alt.xml".Please confirm whether there is "OpenCVForUnity/StreamingAssets" folder at the right position.

Q5.

Support Web platform?

A5.

Since the Unity Web Player does not support the native plugin, "OpenCV for Unity" does not support "WebPlayer Platform".

Q6.

Support WindowsStoreApps8.1 & WindowsPhone8.1.

A6.

If you want to try the Beta Version of "OpenCV for Untiy" based on "OpenCV3.0.0"(Support WindowsStoreApps8.1 & WindowsPhone8.1)
, unzip the OpenCVForUntiy3.0.0-beta.zip, please replace the "OpenCVForUnity" folder."OpenCV for Untiy" based on "OpenCV3.0.0" support Unity5.not support Unity4.

IMPORTANT: READ BEFORE DOWNLOADING, COPYING, INSTALLING OR USING.

By downloading, copying, installing or using the software you agree to this license.
If you do not agree to this license, do not download, install,
copy or use the software.

License Agreement
For Open Source Computer Vision Library

Copyright (C) 2000-2008, Intel Corporation, all rights reserved.
Copyright (C) 2008-2011, Willow Garage Inc., all rights reserved.
Third party copyrights are property of their respective owners.

Redistribution and use in source and binary forms, with or without modification,
are permitted provided that the following conditions are met:

- * Redistributions of source code must retain the above copyright notice,
this list of conditions and the following disclaimer.
- * Redistributions in binary form must reproduce the above copyright notice,
this list of conditions and the following disclaimer in the documentation
and/or other materials provided with the distribution.
- * The name of the copyright holders may not be used to endorse or promote products
derived from this software without specific prior written permission.

This software is provided by the copyright holders and contributors "as is" and
any express or implied warranties, including, but not limited to, the implied
warranties of merchantability and fitness for a particular purpose are disclaimed.
In no event shall the Intel Corporation or contributors be liable for any direct,
indirect, incidental, special, exemplary, or consequential damages
(including, but not limited to, procurement of substitute goods or services;
loss of use, data, or profits; or business interruption) however caused
and on any theory of liability, whether in contract, strict liability,

or tort (including negligence or otherwise) arising in any way out of the use of this software, even if advised of the possibility of such damage.