

Basic Types Of Controls in Settings Bundle Root.plist

Control type	Type Key	Outputs	Associated Keys	Description
Group	PSGroupSpecifier	None	Title	Groups other specifiers together with a title.
Title	PSTitleValueSpecifier	None	Title Key(Identifier)	Read only string value in settings, Can be set in app.
Text Field	PSTextFieldSpecifier	String	Title Key(Identifier) DefaultValue IsSecure KeyboardType AutocapitalizationType AutocorrectionType	Displays a title and inputs a text field.
Toggle Switch	PSToggleSwitchSpecifier	Bool Dual Values	Title Key(Identifier) DefaultValue	Displays a title and toggle switch
Slider	PSSliderSpecifier	NSNumber (real number)	Key DefaultValue MinimumValue MaximumValue MinimumValueImage MaximumValueImage	A slider. Set a minimum, maximum and start value for a slider.
Multi-Value	PSMultiValueSpecifier	Any type	Title Key(Identifier) Values Titles	Creates a selection list of values with titles for descriptions. Value type set in values.

Keys in Root.plist

Key	Property list name	Value	Used by
Type	Type	String	All
Title	Title	Title	Toggle Switch, Multi-Value, Slider Text Field, Group, Title
Key	Identifier	String	Toggle Switch, Multi-Value, Slider, Text Field
DefaultValue	Default Value	Varies by context default String	Toggle Switch, Multi-Value, Slider, Text Field
Values	Values	Varies by context default String	Multi-Value
Titles	Titles	String	Multi-Value
MinimumValue	Minimum Value	Number	Slider
MaximumValue	Maximum Value	Number	Slider
MinimumValueImage	Maximum Value Image	String	Slider
MaximumValueImage	Minimum Value Image	String	Slider
IsSecure	Text Field is secure	Bool	Text Field
KeyboardType	Keyboard Type	String	Text Field
AutocapitalizationType	Autocapitalization Style	String	Text Field
AutocorrectionType	Autocorrection Style	String	Text Field
TrueValue	Value for ON	String default	Toggle Switch
FalseValue	Value for OFF	String default	Toggle Switch