

## NetSim - Batch Automation


**Software Recommended:** NetSim Standard v12.1 (32/64 bit)

### Introduction:

NetSim Batch Automation allows users to execute a series of simulations without manual intervention.

Consider the example, where a user wishes to create and simulate thousands of network scenarios and store and analyse the performance metrics of each simulation run. It is impossible to do this manually using the GUI. However, this can be done by using NetSim Batch Automation script which runs NetSim via CLI.


Following is a depiction of how the files related to Batch automation is organized.



### File Organization

#### Pre – Configuring Batch Automation for first run:


1. Open the folder Config\_batch\_run present in the NetSim\_Batch\_Automation directory.




2. Open Run\_Batch\_Process.bat file in a text editor and modify the value of the variable NETSIM\_PATH to the path where NetSim is installed in your system. Make sure that the path separator is modified to "\\" wherever you have "\".  
For Eg: If the path is "C:\Program Files\NetSim\Standard\_v12\_1\bin\bin\_x64", modify it to "C:\\Program Files\\NetSim\\Standard\_v12\_1\\bin\\bin\_x64". Save and close the file.

```
@echo off
SET NETSIM_PATH="C:\\Program Files\\NetSim\\Standard_v12_1\\bin\\bin_x64"
FOR /d /r %i IN (*) DO (
    pushd "%i"
    call Identify_Config.bat "%~i" %NETSIM_PATH%
    popd
)
```

3. Open the Input folder present in the Config\_batch\_run directory.



4. Open NetSim\_Params.bat in a text editor and modify the NetSim license server IP as per the IP of the system that is running licenses in your network. Save and close the file.




```
@echo off
SET DIR=\"%2\"
SET NETSIM_PATH=\"%1\"

CD %2

%1\NetSimCore.exe -apppath %1 -iopath %2 -license 5053@192.168.0.9
exit
```

5. Open Output\_Script.py in a text editor and modify the value of the variable OUTPUT\_PATH to the path of NetSim\_Batch\_Automation directory in your system. This is the directory where the Output folder is present. Also modify the value of the variable TEMP\_PATH to the path of temp available in NetSim Batch Automation directory.




```
Output_Script.py - Notepad
File Edit Format View Help
import os
import sys
import subprocess
import random
import os.path
import filecmp
import shutil


result=[]
result.append("File Location -----> File Status \n")
a=sys.argv[1]
b=sys.argv[2]
DIR=a
OUTPUT_PATH='C:\\Users\\TETCOS-PC\\Desktop\\NetSim_Batch_Automation_v12.1'
NETSIM_PATH="" + b + ""
TEMP_PATH=OUTPUT_PATH + "\\temp"
os.chdir(DIR)

def filecheck(line):
    name=line+"_Results"
    DIR_C=OUTPUT_PATH + "\\Output\\" + name
    if os.path.exists(DIR_C):
        shutil.rmtree(DIR_C)
    if not os.path.exists(DIR_C):
        os.makedirs(DIR_C)
    os.chdir(TEMP_PATH)
    files=os.listdir(TEMP_PATH)
```

6. Create a system environment variable with name **NETSIM\_AUTO** and set its value to **1**. This is required to prevent user keystroke at the end of simulation.



7. Users can place the input Configuration files inside the Input directory. The Configuration files need to be suitably renamed to avoid conflict, before placing in the input directory.



- To start the Batch script the file Run\_Batch\_Process.bat can be double clicked. This will initiate a command window as shown below:

```

C:\windows\system32\cmd.exe
@[0mConfig file reading complete
License re-validation complete
Protocol binaries loaded
Stack variables initialized
Could Not Find C:\Users\Vishal\Desktop\NetSim_Batch_Automation_v12.0-master\NetSim_Batch_Automation_v12.0\temp\Plot_*.
Metrics variables initialized
C:\Users\Vishal\Desktop\NetSim_Batch_Automation_v12.0-master\NetSim_Batch_Automation_v12.0\temp\StaticIPConfigure3.txt:
No such file or directory
@[31m@[1m
*****
In 413 line of G:\NetSimBackend\12.0\Simulation\IP\IP_Routing.c file following error occurs
Unable to open routing file C:\Users\Vishal\Desktop\NetSim_Batch_Automation_v12.0-master\NetSim_Batch_Automation_v12.0\te
mp\StaticIPConfigure3.txt
*****
@[0mProtocol variables initialized
Executing command --- DEL "C:\Users\Vishal\Desktop\NetSim_Batch_Automation_v12.0-master\NetSim_Batch_Automation_v12.0\te
mp\*.pcap"
Could Not Find C:\Users\Vishal\Desktop\NetSim_Batch_Automation_v12.0-master\NetSim_Batch_Automation_v12.0\temp\*.pcap
Emulation is disabled
Could Not Find C:\Users\Vishal\Desktop\NetSim_Batch_Automation_v12.0-master\NetSim_Batch_Automation_v12.0\temp\Animation
*
Applications created

***
Simulation in progress...
Press CTRL+C to terminate the simulation. Results will be calculated till termination time

64 % is completed... Simulation Time=126948.193 ms Event Id=3560


```

Configuration files placed in the Input Directory will be executed one after the other and the progress of each simulation can be viewed in the above window. This is like what happens when users click on the run simulation button in NetSim's GUI.

**Note:** Close all running instances of NetSim before starting Batch Automation. This will help in avoiding conflicts in accessing files in NetSim folder present in system temp directory.

- Output files (Metrics.xml, PacketTrace.csv, EventTrace.csv, Animation.txt etc) based on whichever features were enabled, will be stored in dedicated folders inside the Output directory. The folders will have the Configuration file name followed by "\_Results".

For eg: If the configuration file has the name "TEST1.netsim" then the Output directory will have the name "TEST1.netsim\_Results".



10. The Output folders can be backed up to prevent getting overwritten on subsequent runs. This may happen if a Configuration file with a similar name is simulated later. The Output folder can also be cleared as a best practice before each run after placing the input files in the Input folder.