

TEST SUMMARY REPORT STR



Test Summary Report

Purpose.....	3
Application Overview.....	3
Test Tree.....	4
Metrics.....	7
Recommendations.....	10
Conclusion.....	10
Bugs List.....	11
Bugs Report.....	14

Test Summary Report

Purpose

This document presents the results of the tests carried out on the website- **"MY JEANS"**.

which has an online store and a physical store in Israel.

The company's website was checked.

The tests were performed on the main functions of the site, which include actions such as- displaying the menu, graphic design, proper functioning of placing an order, registering on the website, reading the information, and using various features.

Application Overview

"My Jeans" is an online platform that offers a seamless shopping experience for clothing, particularly jeans. Accessible via desktops, laptops, tablets, or smartphones, the website provides convenience from anywhere and at any time.

Designed to be user-friendly, the website boasts an intuitive interface, making it easy for users to browse and find the desired products. By offering filters for categories, cuts, and other specifications, users can quickly refine their search.

Detailed information, including photos and specifications, accompanies each product, helping customers make informed decisions. To enhance the shopping experience further, the site incorporates helpful features such as a wish list for saving desired items and a size guide for ensuring the perfect fit.

Furthermore, "My Jeans" website provides a range of payment and delivery options, including home delivery and in-store pickup, allowing customers to choose what works best for them. Additionally, a dedicated customer service section is available, offering answers to common inquiries and assisting with support-related matters.

In summary, "My Jeans" offers a convenient and efficient platform for purchasing clothing and accessories, showcasing a diverse product range, user-friendly tools, and flexible payment and delivery choices.

Test Summary Report

Test Tree

1. Hamburger menu at the top left side:

- Store +
 - "קולקציית ספורט" link
 - "ג'ינסים" link
 - "SALE" link
 - "ביוסיקים"
 - "אביזרים" link
- Shop all jeans
- Shop all
- What's my size?
 - inputs
 - "הבא" and "הקודם" buttons
 - valid characters inside the inputs
- Gift Card
 - "בא לך לפנק" cube:
 - ❖ Price buttons
 - ❖ "שם" "אימייל" inputs
 - ❖ "שם", "ברכה" inputs
 - ❖ "הוספה לסל" button
 - ❖ "תיאור" button
 - ❖ "הרכב בד" button
 - ❖ "משלוחים והחזרות" button
 - "יש לך כבר גיפט קארד שלנו" cube:
 - ❖ Check link button (Failed)
- My Account
 - "התנתקות"
 - "פרטי חשבון"
 - "הגיפט קארדים שלי"
 - "רשימת המשאלות"
 - ❖ Checkbox button near the product
 - ❖ "בחר אפשרויות" button
 - ❖ "APPLY ACTIONS" button
 - ❖ Email, WhatsApp, Twitter, Copy, Pinterest links
 - "ההזמנות שלי"

- Login form
 - ❖ "כתובת מייל \ שם משתמש" input
 - ❖ "סיסמא" input
 - ❖ "זכור אותי" checkbox
 - ❖ "התחבר" button
 - ❖ "איפוס סיסמא" button
- Sign up form
 - ❖ "כתובת אימייל" input
 - ❖ "תאריך לידה" input
 - ❖ "הרשמה" button

2. Home Page:

Top Menu

- MY JEANS link
- Heart Icon
- Search icon
 - ❖ Search Input
 - ❖ Close button
- My Account icon
- Shopping cart icon
- Products link

3. Accessibility Menu

- Private Area
- Main
- Stop all movement.
- הפעל פוקוס מקלדת
- Enlarge text.
- Reset text.
- Reduce text.
- Dark colors
- Original colors
- Bright colors
- Bg colors
- Heading colors
- Text colors
- Normal cursor
- Black cursor
- Highlighting links
- Change to a font Arial.

4. Footer

- TikTok link

- Instagram link
- Facebook link
- WhatsApp link
- אודות
- צרו קשר
- תקנון
- הצהרת נגישות
- מדיניות החזרות והחלפות
- הזמנת שליח
- שאלות ותשובות
- "רוצה להישאר מעודכנת"
 - ❖ "שם מלא" input
 - ❖ "דוא"ל" input
 - ❖ "תשאירו אותי מעודכנת" button

5. Product Page:


- Heart icon
- Size checkbox
- "הוספה לסל" button
- "תיאור" button
- "הרכב בד" button
- "משלוחים והחזרות" button
- **Disable size button**
 - ❖ Email Address input

Test Summary Report

Metrics

TEST CASES - STATUS


Passed	Failed	Not Run	Total
64	28	11	103



Test Summary Report

SEVERITY BUGS - STATUS


S1- Show Stopper	S2- Critical	S3- Major	S4- Minor	S5- Low	Total
0	1	6	8	13	28



Test Summary Report

Defect Distribution- Module Wise

	Functionality	Accessibility	UI \ UX	Localization	security	Total
Show Stopper	0	0	0	0	0	0
Critical	0	0	0	0	1	1
Major	4	1	0	1	0	6
Minor	8	1	1	0	0	10
Low	6	0	5	0	0	11
Total	18	2	6	1	1	28



Test Summary Report

Recommendations

1. Uniformity language for the entire site, make Hebrew the default language.
2. Change the **"My Account"** page to a dynamic page that responds according to logged-in users and not logged-in users, dynamic buttons, forms, and a menu.
3. Improve **the accessibility menu** so that all its functions work as they should.
4. Add an option to change the language of the website, at least for English \ Arabian \ and Russian.
5. Optimize Page Load Speed: Optimize the website's code and image sizes to improve page load speed. Slow loading times can result in higher bounce rates and lower user engagement.
6. Add a **Loading Icon** to let the user know that their action has been accepted.

Conclusion

Following tests on the "MY JEANS" website, several bugs were identified with different levels of Severity, spanning from low to critical issues.

In summary, it can be concluded that the "MY JEANS" website has a strong foundation, featuring an intuitive interface and successfully executing the majority of its core functions.

Nevertheless, it is important to address the identified bugs as their resolution would enhance user satisfaction and potentially boost sales.

Despite this, my recommendation is to proceed with the website's release.

Test Summary Report

Bugs List

MJ1- On the shopping cart page in the "שם פרטי" field you can fill in characters and signs without letters.

MJ2- On the shopping cart page in the "שם משפחה" field you can fill in characters and signs without letters.

MJ3- At the search area, the user can't make a random search, the system can only get certain keyboards.

MJ4- The search input gets only words in English and not in Hebrew, even though the site is written in Hebrew.

MJ5- On the "GIFT CARD" page, the names of the fields appear on the left side of the box instead of the right side.

MJ6- On the "Wish List" page, after selecting desired products and clicking the "Apply Action" button, a message pop-up: No items or actions are selected, because we did not select the desired size.

MJ7- In "My Account" page when clicking on the logout button logo, the site leads to an error.

MJ8- When adding items to the "Wish List", the number 0 still appears at the top right side of the page.

MJ9- Pressing on "Store+" button at the hamburger menu opens a menu, but a second press doesn't close it.

MJ10- When I press on "הוספה לסל", there is no clear indication that the product has been added successfully.

MJ11- On "My Account" page the links inside the cubes only work when clicking on the icon or the text, and not on the whole cube.

MJ12- The "My Account" page is not dynamic for logged-in users and not logged-in users.

MJ13- On the "My Account" page, there are cubes with irrelevant links that when clicked, the pages load for nothing.

MJ14- On the "גיפטקארדים שלי" page, there is an "ADD NEW" button written in English, but the web is written in Hebrew.

MJ15- There is no option to scroll down when the hamburger menu is open.

MJ16- When clicking on the heart icon of any product, there is a pop-up with two options that after a few seconds leads the user to the "המשאלות שלי" page without any permission from the user.

MJ17- When the user logged out, and then presses on the back button in the browser, the page is back to the user account without any password or email validation.

MJ18- When clicking on the "WhatsApp" icon on the lower right side of the page, the application opens at the current screen instead of in a new window.

MJ19- By clicking on the "Tiktok" icon at the footer of the page the link leads to the company's "Instagram" page.

MJ20- In the accessibility menu at the left bottom side, when you enter a private area and hover over the first option, the text is cut.

MJ21- There is no logo icon on the tab browser.

MJ22- On the "Create new gift card" page, when a price is marked, it is not clear to the user whether it was marked.

MJ23- On the "Create new gift card" there is no character limit in "ברכה" input.

MJ24- On the "Create new gift card" page, there is a CSS code as a text Description. icons disappear.

MJ25- On the "ABOUT" page, the text is misaligned and looks messy.

MJ26- On the accessibility menu, when pressing on "צבע בהיר" "Bright Colors" the

MJ27- When changing the language in the accessibility menu to English and increasing the font, the lines of text in the "MAIN" area overlap one another.

MJ28- When changing the language in the accessibility menu to English, the second option "הפעל פוקוס מקלדת" remains written in Hebrew.


Bugs Report

[MJ-1] [On the shopping cart page- in the "שם פרטי" field you can fill in characters and signs without letters](#) Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Lowest
Reporter:	מיתר אוהיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:



Severity:	Low
-----------	-----

Description

Steps To Reproduce:

1. Press on the hamburger menu
2. Click on shop all jeans
3. Click on "My super dark blue" jeans
4. Choose a size- 25\0
5. Press on "הוספה לסל" bottom
6. Then will open a pop-up window at the left side of the screen and press on "מעבר לסל הקניות"
7. At the left side of the screen, there is a window, press on "התקדם לצ'ק אאוט"
8. In the "שם פרטי" field, fill in the value- "12#\$"

Actual Result:

In the "שם פרטי" field, you can fill in characters and symbols without letters

Expected Result:


Only letters can be filled in the "שם פרטי" field

[MJ-2] [On the shopping cart page- in the "שם משפחה" field you can fill in characters and signs without letters](#) Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Lowest
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		

Time Spent:	Not Specified
Original estimate:	Not Specified
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)

Attachments:	
Severity:	Low

Description

Steps To Reproduce:

1. Press on the hamburger menu
2. Click on shop all jeans
3. Click on "My super dark blue" jeans
4. Choose a size- 25\0
5. Press on "הוספה לסל" bottom
6. Then will open a pop-up window at the left side of the screen and press on "מעבר לסל הקניות"
7. At the left side of the screen, there is a window, press on "התקדם לצ'ק אאוט"
8. In the "שם משפחה" field, fill in the value- "12#\$"

Actual Result:

In the "שם משפחה" field, you can fill in characters and symbols without letters

Expected Result:


Only letters can be filled in the "שם משפחה" field

[MJ-3] [At the search area, the user can't make a random search, the system can only get certain keywords](#) Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None

Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Medium
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Major

Description

The system can only get certain keywords, which means that the user can't make a random search. The system would not get the word "T-shirt", but it would get the word "T-shirt".

Steps To Reproduce:

1. Press on the Search Engine on the right side above
2. At the search input, write- "קולקציית ספורט"
3. Click Enter

Actual Result:

A message : "מצטערים, אבל לא מצאנו את מה שחיפשת. נסה שוב עם מילות חיפוש אחרות"


Expected Result:

We expect the system to take us to the page with the "קולקציית ספורט" products

[MJ-4] [The search input get only words in English and not in Hebrew, Even though the site is written in hebrew](#) Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Medium
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Major

Description

Steps To Reproduce:

1. Press on the Search Engine on the right side above
2. Fill- ספורט
3. Click Enter
4. Fill- sport
5. Click Enter

Actual Result:

When I fill in an entry in "ספורט" at the search input, there an error message: מצטערים, אבל לא מצאנו את מה שחיפשת. נסה שוב עם מילות חיפוש אחרות.

But the system finds the products when I fill in "sport" in the search input.


Expected Result:

The system will find the products when they are written in Hebrew and also in English

[MJ-5] [On the Gift Card page, the names of the fields appear on the left side of the box instead of the right side](#) Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Lowest
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Low

Description

Steps To Reproduce:

1. Press on the hamburger menu
2. Click on "Gift Card"
3. Click on "גיפט קארד חדש"

Actual Result:

The field names will appear on the right side of the box

Expected Result:


The field names appear on the left side of the box

[MJ-6] [On the Wish List page, after selecting desired products and clicking the Apply Action button, a message pop up: No items or actions are selected, because we did not select the desired size](#) Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		

Environment:	Windows 11
	Chrome Version 114.0.5735.199 (official version) (64-bit)

Attachments:	
	Severity: Low

Description

Steps To Reproduce:

1. Press on the hamburger menu
2. Click on the heart icon at the "Shop all jeans"
3. Click on the heart icon at the "My super black" jeans
4. Click on "My super light blue" jeans
5. Then will open a pop-up window: press on "צפה ברשימת המשאלות"
6. Mark the "My Super Dark Blue" checkbox at the right side of the table.
7. Mark the "My Super Black" checkbox at the right side of the table.
8. Click on "Apply Actions"

Actual Result:

There is an alert error message: No items or actions are selected

Expected Result:

We expect that the system will tell us to choose a size, or the system will give us the option to choose a size from the table


[MJ-7] [In "My Account" Page when clicking on the Logout button logo, the site leads to an error](#)

Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
---------	-------

Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוניון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Major

Description

Steps To Reproduce:

1. Press on the hamburger menu at the top left side of the page.
2. Click on "My Account"
3. Click on the logo of the "התנתקות" cube

Actual Result:

The site goes to an error message

Expected Result:


The system will log out from the personal account

[MJ-8] [When adding items to the Wish List, the number 0 still appear at the top right side of the page](#)

Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Lowest
Reporter:	מיתר אוהיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Low

Description

Steps To Reproduce:

1. Click on the Hamburger menu
2. press on "Shop All Jeans"
3. Add the item "My Super Black" to the Wish List (Click on the heart icon at the top left side of the product cube)
4. Add the item "My Super Light Black" to the Wish List (Click on the heart icon at the top left side of the product cube)
5. Check the wish list button

Actual Result:

The number at the heart icon at the top right side of the page is 0

Expected Result:


We expect that the number of products at the heart icon will be incremented by one.

[MJ-9] [Pressing on the "Store +" button at the hamburger menu opens a menu, but a second press doesn't close it](#) Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans

Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Lowest
Reporter:	מיתר אוהיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Low

Description

Steps To Reproduce:

1. Press the Hamburger button
2. Click on "Store +"
3. After the menu opens, click again

Actual Result:

The menu remains open.


Expected Result:

We expected that after the menu was opened with the first click, it would be closed with a second click.

[MJ-10] [When I press on "הוספה לסל", there is no clearly indication that the product is added successfully](#) Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Minor

Description

Steps To Reproduce:

1. Press the Hamburger button
2. Click on "Shop All"
3. Choose "My Super Dark Blue"
4. Press on "הוספה לסל"

Actual Result:

The site is staying on the same product page, and there is a small message on top of the page that the product added to the cart

Expected Result:


The expectation is that will be a loading message, a clear message that the product added to the cart, and then the page will lead us to the home page

[MJ-11] [On "my account" page – the links inside the cubes only work when clicking on the icon or the text, and not on the whole cube](#) Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None


Type:	Bug	Priority:	Lowest
-------	-----	-----------	--------

Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Low

Description

Steps To Reproduce:

1. Click the man icon on the top right side of the page:

2. Try to click on the "ההזמנות שלי" cube, but not on the icon or the text

Actual Result:


Nothing happens by clicking on the cube

Expected Result:

We expect the whole cube to be used as a link.

[MJ-12] The "my account" page is not dynamic for logged-in users and not logged in users Created: 16/Jul/23 Updated: 16/Jul/23	
Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Low

Description

Intro:

The my account is not dynamic. There are many options that are not relevant to the situation.

Example:

1. there is a "logout" option when I'm not logged in
2. There in "account details" when I'm not logged in
3. There in "my orders" when I'm not logged in

Steps To Reproduce:

1. Do not login
2. Click on the Hamburger Menu
3. Click on "my Account"
4. Watch the options: "ההזמנות שלי", "פרטי חשבון", "התנתקות"

Actual Result:

There are 3 options that are not relevant for not logged-in users

Expected Result:

We expect a "sign in" page for not logged in users, and we expect a "user account" page for logged in users


[MJ-13] [On the "My Account" page, there are cubes with irrelevant links that when clicked, the pages load for nothing](#)

Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Medium
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		

Remaining Estimate:	Not Specified
Time Spent:	Not Specified
Original estimate:	Not Specified
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)

Attachments:	
Severity:	Major

Description

Intro:

On the "My Account" page, there are cubes with irrelevant links that when clicked, the pages load for nothing, and finally, the link leads me to the same page without any changes. This action is making more stress on the server

Steps To Reproduce:

1. Click on the hamburger menu
2. Click on "My Account"
3. Do not login
4. Click on "פרטי חשבון"
5. Click on "התנתקות"
6. Click on "ההזמנות שלי"

You can see that the links leads you to the same page but with a long loading time for nothing.

Actual Result:

By clicking on the irrelevant links, the click action leads me to the same page with a long loading time

Expected Result:


We expect that the links would not exist, or disable buttons

[MJ-14] [On the "גיפטקארדים שלי" page, there is an "ADD NEW" button written in English, but the web is written in Hebrew](#) Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
---------	-------

Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Lowest
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Low

Description

Steps To Reproduce:

1. Click on the hamburger menu

2. Click on "My Account"
3. Log in to the system
4. Press on "הגיפט קארדים שלי" cube
5. There is a 'ADD NEW' red button.

Actual Result:

The button written in English

Expected Result:

I expect that the button will be written in Hebrew as "הוסף חדש"

[MJ-15] [There is no option to scroll down when the Hamburger menu is open](#) Created:

16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Lowest
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Severity:	Low
-----------	-----

Description

Steps To Reproduce:

1. Click on the Hamburger menu at the top left side of the page
2. Try to scroll down with the mouse

Actual Result:

The user can't scroll down while the hamburger menu is open

Expected Result:

The user can scroll down while the hamburger menu is open


[MJ-16] [When clicking on the heart icon of any product, there is a pop-up with 2 options that after a few seconds leads the user to the "המשאלות שלי" page without any permission from the user](#) Created:

16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוהיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		

Original estimate:	Not Specified
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)

Attachments:	
Severity:	Minor

Description

Steps To Reproduce:

1. Press on the Hamburger menu
2. Click on "SHOP ALL JEANS"
3. Click on the Heart icon at the top left of "my Super Black" product
4. There is a pop up window with 2 options: "צפה ברשימת המשאלות" and "Close X"
5. Do not press on any of them, wait a few seconds
The page automatically leads you to the "המשאלות שלי" page

Actual Result:

The page is waiting a few seconds and then leads the user to the "המשאלות שלי" page


Expected Result:

The page will wait to the user reaction instead of leads him to other page without any request from his side

[MJ-17] [When the user logged out, and then press on back button in the browser, the page is back to the user account without any password or email validation](#) Created: 16/Jul/23 Updated: 16/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None

Fix versions:	None
---------------	------

Type:	Bug	Priority:	High
Reporter:	מיתר אוניון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		
Attachments:			
Severity:	Critical		

Description

Steps To Reproduce:

1. Click on the hamburger menu

2. Click on my account
3. Log in to the system
4. Logout from the system
5. Click on the **back** button in the browser:



Actual Result:

The user is still logged in instead of being logged out

Expected Result:

I expect the logout process to be completed end-to-end.

If the user did a logout process, it should be completely logged out

[MJ-18] [When clicking on the "WhatsApp" icon on the lower right side of the page, the application opens on the current screen instead of in a new window](#) Created: 18/Jul/23 Updated: 18/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		

Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)
---------------------	---

Severity:	Minor
------------------	-------

Description

Steps To Reproduce:

1. Click on the "Whatsapp" link at the bottom of the home page on the right side

Actual Result:

The "WhatsApp" window opens on the current window

Expected Result:


We expect "WhatsApp" to open in a new window so that the user can be on the site at the same time

[MJ-19] [By clicking on the "Tiktok" icon at the footer of the page the link leads to the company's "Instagram" page](#) Created: 18/Jul/23 Updated: 18/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		

Remaining Estimate:	Not Specified
Time Spent:	Not Specified
Original estimate:	Not Specified
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)

Attachment s:	
Severity:	Major

Description

Steps To Reproduce:

1. Click on the "Tiktok" link at the bottom of the home page on the right side

Actual Result:

The "Tiktok" link leads to the company's "Instagram" page instead of leading us to the company's "Tiktok" page


Expected Result:

The "Tiktok" icon link should lead us to the company's "Tiktok" page

[MJ-20] [In the "accessibility" menu at the left bottom side, when you enter a private area and hover over the first option, the text is cut](#) Created: 18/Jul/23 Updated: 18/Jul/23

Status:	To Do
---------	-------

Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוהיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		
Attachments:			
Severity:	Minor		

Description

Steps To Reproduce:

1. Clicking on the "accessibility" button on the bottom left
2. Clicking on "Private area"
3. Hover with the cursor over the first option

Actual Result:

The text in the first option is cut and above it appears a black background that erases the text

Expected Result:


We expect the text to be readable and accessible

[MJ-21] [There is no logo icon on the tab browser](#) Created: 19/Jul/23 Updated: 19/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		

Environment:	Windows 11
	Chrome Version 114.0.5735.199 (official version) (64-bit)


Attachments:	
Severity:	Minor

Description
<p>Steps To Reproduce:</p> <ol style="list-style-type: none"> 1. Open "MyJeans" on the browser <p>Actual Result:</p> <p>There is no logo in the browser tab</p> <p>Expected Result:</p> <p>We expect that the site's logo be present in a browser tab</p>

<p>[MJ-22] On the "Create a new gift card" page, when a price is marked, it is not clear to the user whether it was marked Created: 19/Jul/23 Updated: 19/Jul/23</p>			
Status:	To Do		
Project:	My Jeans		
Components:	None		
Affects versions:	None		
Fix versions:	None		

Type:	Bug	Priority:	Low
--------------	-----	------------------	-----

Reporter:	מיתר אוהיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments			
	Severity:	Minor	

Description

Steps To Reproduce:

1. Click on the hamburger menu
2. Click on "GIFT CARD"
3. Click on "גיפט קארד חדש" button in the right cube
4. In the price area at the right side of the screen, click on 100 ₪
5. Click on 200 ₪

Actual Result:

When I clicked on a random price, the button doesn't change or marked

Expected Result:

We expect that when clicking on some price button, it will be marked

[MJ-23] [On the "Create a new gift card" there is no character limit in "ברכה" input](#) Created:

19/Jul/23 Updated: 19/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	<div data-bbox="416 197 1348 913"> <div data-bbox="416 197 1348 230">myjeans.co.il/product/giftcard/</div> <div data-bbox="416 230 1348 913"> <div data-bbox="416 230 735 913"> <div data-bbox="416 230 735 275">Gift Card/200</div> <div data-bbox="416 275 735 320"> <div data-bbox="416 275 735 297">מאת:</div> <div data-bbox="416 297 735 320">אל: 00000000000000000000</div> </div> <div data-bbox="416 320 735 913"> <p> Lorem ipsum dolor sit amet, consectetur adipiscing elit. Nam dictum, est eu facilisis tempus, turpis odio tincidunt tortor, sit amet finibus magna sem vel ex. Integer in consectetur nisl, eu dignissim purus. Suspendisse potenti. Phasellus sagittis efficitur placerat. Sed nec velit sit amet ex maximus posuere sit amet eget ligula. Etiam dictum, eros at pulvinar elementum, neque metus ullamcorper odio, vel consectetur justo felis non leo. Duis a lacinia metus. Quisque vestibulum pharetra erat, quis feugiat turpis pharetra tincidunt. Nunc pulvinar risus vel porta pellentesque. </p> <p> Maecenas dolor purus, eleifend non aliquam eu, volutpat vitae dui. Ut sed sapien condimentum, ultrices purus vitae, varius felis. In hac habitasse platea dictumst. Vivamus sagittis malesuada nibh, a venenatis tellus ultricies elementum. Morbi non feugiat eros, id fringilla quam. Quisque scelerisque tempus quam, nec scelerisque tellus sodales eget. Pellentesque interdum dignissim arcu, finibus auctor .tortor tincidunt et. </p> <p> Nam lacinia rhoncus nibh, ut placerat dolor finibus id. </p> </div> </div> <div data-bbox="735 230 1348 913"> <div data-bbox="735 230 1348 275">שם: 00000000000000000000</div> <div data-bbox="735 275 1348 320">אוסף: יש להכניס את סמל האוסף של קובצת המזון</div> <div data-bbox="735 320 1348 365">הפרטים שלך</div> <div data-bbox="735 365 1348 409">שם: יש להכניס את שםך</div> <div data-bbox="735 409 1348 913"> <div data-bbox="735 409 1348 566"> <div data-bbox="735 409 1348 454">ברכה:</div> <div data-bbox="735 454 1348 566"> dui. Ut sed sapien condimentum, ultrices purus vitae, varius felis. In hac habitasse platea dictumst. Vivamus sagittis malesuada nibh, a venenatis tellus ultricies elementum. Morbi non feugiat eros, id fringilla quam. Quisque scelerisque tempus quam, nec scelerisque tellus sodales eget. Pellentesque interdum dignissim arcu, finibus auctor tortor tincidunt et. </div> </div> <div data-bbox="735 566 1348 723"> <div data-bbox="735 566 1348 611"></div> <div data-bbox="735 611 1348 723"> Nam lacinia rhoncus nibh, ut placerat dolor finibus id. Duis in dolor quis leo sodales interdum. Quisque tincidunt pharetra magna, eget euismod mauris porta sed. Nulla id varius tellus, in rhoncus libero. Etiam pharetra lacus sem. Vivamus elementum dui ac neque porta elementum. Quisque id vehicula massa. Aenean pellentesque velit malesuada sapien .consectetur tempor. Morbi quis ligula ut risus dictum cursus. </div> </div> <div data-bbox="735 723 1348 913"> <div data-bbox="735 723 1348 790"> <div data-bbox="735 723 1348 768"></div> <div data-bbox="735 768 1348 790"> Nam sem nunc, pellentesque at ligula vel, convallis laoreet lacus. Pellentesque efficitur sit amet nibh sed luctus. Fusce varius consectetur justo, ut feugiat urna hendrerit eu. </div> </div> <div data-bbox="735 790 1348 857"> <div data-bbox="735 790 1348 835"></div> <div data-bbox="735 835 1348 857"> Vestibulum sagittis tortor sem, tincidunt sollicitudin erat luctus et. Vestibulum commodo est vitae erat venenatis porta. Vivamus aliquet dictum vestibulum. Curabitur feugiat turpis tortor, id laculis orci posuere ac. Nam vitae massa molestie erat. </div> </div> </div> </div> </div> </div></div>
Severity:	Minor

Description

Steps To Reproduce:

1. Click on the hamburger menu
2. Click on "GIFT CARD"
3. Click on "גיפט קארד חדש" btn in the right cube
4. Add 5000 words to the "ברכה" input, the fourth from the top.

Actual Result:

There is no limit to the number of characters

The input on the left that displays the text, becomes long and infinite, without any limitation

Expected Result:

Expect the button to limit the number of characters to a reasonable amount

[MJ-24] [On the "Create new gift card" page, there is a CSS code as a text Description](#) Created:

20/Jul/23 Updated: 20/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Medium
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	 <p>The screenshot shows the 'myjeans.co.il/product/giftcard/' page. It features a form for creating a gift card. The top section, titled 'הפרטים שלך' (Your details), includes a text input for 'שם' (Name) and a larger text area for 'ברכה' (Blessing). Below this is a black button labeled 'הוספה לסל' (Add to cart). The bottom section, also titled 'הפרטים שלך', includes a 'תיאור' (Description) button highlighted with a red border. The page URL 'myjeans.co.il/product/giftcard/' is visible in the browser's address bar.</p>
Severity:	Minor

Description

Steps To Reproduce:

1. Click on the hamburger menu
2. Click on "GIFT CARD"
3. Click on "גיפט קארד חדש" button in the right cube
4. Click on "תיאור" button

Actual Result:

There is a CSS code

Expected Result:

When clicking on the "תיאור" button, it will present a description

[MJ-25] On the "About" page, the text is misaligned and looks messy Created: 20/Jul/23 Updated: 20/Jul/23	
Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Lowest
Reporter:	מיתר אוהיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachment

MY JEANS.

קצת עלינו

הרי כל אחת יודעת ש'ג'ינס' הוא פריט חובה בארון.
ליום יום, לחתנים, לציאה בערב ובכל המדנות שרק אפשר!
אז תחשבי איזה כף זה שיש לך 'ג'ינס' שיושב עליך בול - כאילו נחפר במיוחד עבורך ♥

אנחנו כאן כדי לנרם לך לראות את הגרסא הכי טובה של הגוף שלך דרך הג'ינסים שלנו, לנרם לך להסתכל במראה ולהתאהב! ♥

אז מה בעצם כל כך מיוחד בג'ינס שלנו?
ה'ג'ינסים' מיוצרים על ידנו בקפידה רבה, במפעלי בוטיק.
לאחר עבודה קשה וממושכת הצלחנו למצוא את הנוסחא המושלמת לג'ינס שינרם לך לגנוב לכולן את ההצגה.
ה'ג'ינס' בגזרה גבוהה, מבד סטרא' ומחטב שתרגישי בתוכו נינוחה ומשוחזרת.
והדודבן שבקצפת-
בנוסף למידות הרחב ישנן גם מידות ארוך!!!
לקפל את הג'ינס - NO MORE.

MYJEANS. הוא מותג צעיר, חדשני והכי חשוב במחירים אטרקטיביים ונגישים, מתחייבות לשירות אמין מקצועי

Severity:	Low
-----------	-----

Description

Steps To Reproduce:

1. Scroll down to the footer.
2. Click on "אודות"

Actual Result:

The text looks messy and misaligned

Expected Result:

Centered, aligned text that starts and ends at the same position

[MJ-26] [On the accessibility menu- when pressing on "צבע בהיר" / "Bright Colors", the icons are dissapear](#) Created: 20/Jul/23 Updated: 20/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Medium
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11		

	Chrome Version 114.0.5735.199 (official version) (64-bit)
--	---

Attachments:	
Severity:	Major

Description	
Steps To Reproduce: <ol style="list-style-type: none"> 1. Click on the accessibility menu on the left side at the bottom 2. Click on "צבע בהיר" \ Bright Colors" 	
Actual Result: The icons are disappear	
Expected Result: After changing the background color to bright, the color of the icons will be adjusted to the background color	
[MJ-27] When changing the language in the accessibility menu to English and increasing the font, the lines of text in the "MAIN" area overlap one another Created: 21/Jul/23 Updated: 21/Jul/23	
Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוזנין	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Low

Description

Steps To Reproduce:

1. Click on the accessibility button on the bottom left
2. Click on the gear icon
3. change the language to English
4. At the top right side of the accessibility menu, Click on the button that increases the accessibility menu (the button to the left of the X)

5. Click on MAIN

Actual Result:

The lines of text overlap and are not clear


Expected Result:

Have a comfortable space between the lines of text and links

[MJ-28] [When changing the language in the accessibility menu to English, the second option " הפעל " פוקוס מקלדת](#) Created: 21/Jul/23 Updated: 21/Jul/23

Status:	To Do
Project:	My Jeans
Components:	None
Affects versions:	None
Fix versions:	None

Type:	Bug	Priority:	Low
Reporter:	מיתר אוחיון	Assignee:	Unassigned
Resolution:	Unresolved	Votes:	0
Labels:	None		
Remaining Estimate:	Not Specified		
Time Spent:	Not Specified		
Original estimate:	Not Specified		
Environment:	Windows 11 Chrome Version 114.0.5735.199 (official version) (64-bit)		

Attachments:	
Severity:	Low

Description

Steps To Reproduce:

1. Click on the accessibility button on the bottom left
2. Click on the gear icon and change the language to English
3. Moving to "MAIN"

Actual Result:

A second option "הפעל פוקוס מקלדת" remains in Hebrew

Expected Result:

The entire menu will be written in English uniformly