### MPI: A Message-Passing Interface Standard Version 4.0

(Draft)

Unofficial, for comment only

Message Passing Interface Forum

November 15, 2020

#-... all changes #-nnn by issue nnn

#-PRnnn by pull request

Non problematic fomatting-changes and typo-corrections are not listed Embiggening: only new \_c versions are marked, all other is not listed

New or changed content

Problematic fomatting-changes are listed

Errors in RC 40 - also marked with #-error or #-error! B.m.n: i. - refers to Change-Log section B.m.n, Item i

Updates after the rc-40 vote

#-error #-error!


#-update1...

This document describes the 2020 Draft Specification of the Message-Passing Interface (MPI) standard, intended for comment. It is not an official version of the standard. The MPI standard includes point-to-point message-passing, collective communications, group and communicator concepts, process topologies, environmental management, process creation and management, one-sided communications, extended collective operations, external interfaces, I/O, some miscellaneous topics, and a profiling interface. Language bindings for C and Fortran are defined.

Historically, the evolution of the standards is from MPI-1.0 (May 5, 1994) to MPI-1.1 (June 12, 1995) to MPI-1.2 (July 18, 1997), with several clarifications and additions and published as part of the MPI-2 document, to MPI-2.0 (July 18, 1997), with new functionality, to MPI-1.3 (May 30, 2008), combining for historical reasons the documents 1.1 and 1.2 and some errata documents to one combined document, and to MPI-2.1 (June 23, 2008), combining the previous documents. Version MPI-2.2 (September 4, 2009) added additional clarifications and seven new routines. Version MPI-3.0 (September 21, 2012) is an extension of MPI-2.2. Version MPI-3.1 (June 4, 2015) adds clarifications and minor extensions to MPI-3.0.

Comments. Please send comments on MPI to the MPI Forum as follows:

- 1. Subscribe to https://lists.mpi-forum.org/mailman/listinfo/mpi-comments
- 2. Send your comment to: mpi-comments@lists.mpi-forum.org, together with the version of the MPI standard and the page and line numbers on which you are commenting.
  - Your comment will be forwarded to MPI Forum committee members for consideration. Messages sent from an unsubscribed e-mail address will not be considered.



2020 Draft Specification, November, 2020. This document contains a draft of the MPI specification as of the date of publication. It has not been adopted as an official MPI specification, and is provided for comment only. This document includes a number of new features that will be present in the final MPI-4.0 document. The largest changes are the addition of persistent collectives, partitioned communication, application info assertions, and improvements to the definitions of error handling. In addition, there are a number of smaller improvements and corrections.

Version 3.1: June 4, 2015. This document contains mostly corrections and clarifications to the MPI-3.0 document. The largest change is a correction to the Fortran bindings introduced in MPI-3.0. Additionally, new functions added include routines to manipulate MPI\_Aint values in a portable manner, nonblocking collective I/O routines, and routines to get the index value by name for MPI\_T performance and control variables.

Version 3.0: September 21, 2012. Coincident with the development of MPI-2.2, the MPI Forum began discussions of a major extension to MPI. This document contains the MPI-3 Standard. This draft version of the MPI-3 standard contains significant extensions to MPI functionality, including nonblocking collectives, new one-sided communication operations, and Fortran 2008 bindings. Unlike MPI-2.2, this standard is considered a major update to the MPI standard. As with previous versions, new features have been adopted only when there were compelling needs for the users. Some features, however, may have more than a minor impact on existing MPI implementations.

Version 2.2: September 4, 2009. This document contains mostly corrections and clarifications to the MPI-2.1 document. A few extensions have been added; however all correct MPI-2.1 programs are correct MPI-2.2 programs. New features were adopted only when there were compelling needs for users, open source implementations, and minor impact on existing MPI implementations.

Version 2.1: June 23, 2008. This document combines the previous documents MPI-1.3 (May 30, 2008) and MPI-2.0 (July 18, 1997). Certain parts of MPI-2.0, such as some sections of Chapter 4, Miscellany, and Chapter 7, Extended Collective Operations, have been merged into the Chapters of MPI-1.3. Additional errata and clarifications collected by the MPI Forum are also included in this document.

Version 1.3: May 30, 2008. This document combines the previous documents MPI-1.1 (June 12, 1995) and the MPI-1.2 Chapter in MPI-2 (July 18, 1997). Additional errata collected by the MPI Forum referring to MPI-1.1 and MPI-1.2 are also included in this document.

Version 2.0: July 18, 1997. Beginning after the release of MPI-1.1, the MPI Forum began meeting to consider corrections and extensions. MPI-2 has been focused on process creation and management, one-sided communications, extended collective communications, external interfaces and parallel I/O. A miscellary chapter discusses items that do not fit elsewhere, in particular language interoperability.

#-other #-done

Version 1.2: July 18, 1997. The MPI-2 Forum introduced MPI-1.2 as Chapter 3 in the standard "MPI-2: Extensions to the Message-Passing Interface", July 18, 1997. This section contains clarifications and minor corrections to Version 1.1 of the MPI Standard. The only new function in MPI-1.2 is one for identifying to which version of the MPI Standard the implementation conforms. There are small differences between MPI-1 and MPI-1.1. There are very few differences between MPI-1.1 and MPI-1.2, but large differences between MPI-1.2 and MPI-2.

Version 1.1: June, 1995. Beginning in March, 1995, the Message-Passing Interface Forum reconvened to correct errors and make clarifications in the MPI document of May 5, 1994, referred to below as Version 1.0. These discussions resulted in Version 1.1. The changes from Version 1.0 are minor. A version of this document with all changes marked is available.

Version 1.0: May, 1994. The Message-Passing Interface Forum (MPIF), with participation from over 40 organizations, has been meeting since January 1993 to discuss and define a set of library interface standards for message passing. MPIF is not sanctioned or supported by any official standards organization.

The goal of the Message-Passing Interface, simply stated, is to develop a widely used standard for writing message-passing programs. As such the interface should establish a practical, portable, efficient, and flexible standard for message-passing.

This is the final report, Version 1.0, of the Message-Passing Interface Forum. This document contains all the technical features proposed for the interface. This copy of the draft was processed by LATEX on May 5, 1994.

## Contents

т:	et of	Figures		•		xix
וענ	ist OI	Figures				XIX
Li	ist of	Tables				xxi
A	cknov	vledgments				xxiii
1	Intr	oduction to MPI				1
_	1.1	Overview and Goals				1
	1.2	Background of MPI-1.0				2
	1.3	Background of MPI-1.1, MPI-1.2, and MPI-2.0				2
	1.4	Background of MPI-1.3 and MPI-2.1				3
	1.5	Background of MPI-2.2				4
	1.6	Background of MPI-3.0				4
	1.7	Background of MPI-3.1				4
	1.8	Background of 2020 Draft Specification				5
	1.9	Who Should Use This Standard?				5
	1.10	What Platforms Are Targets for Implementation?				5
		What Is Included in the Standard?				5
	1.12	What Is Not Included in the Standard?				6
	1.13	Organization of This Document				6
2	MPI	Terms and Conventions				9
	2.1	Document Notation				9
	2.2	Naming Conventions				9
	2.3	Procedure Specification				10
	2.4	Semantic Terms				11
		2.4.1 MPI Operations				11
		2.4.2 MPI Procedures				13
		2.4.3 MPI Datatypes				15
	2.5	Data Types				16
		2.5.1 Opaque Objects				16
		2.5.2 Array Arguments				18
		2.5.3 State				18
		2.5.4 Named Constants				18
		2.5.5 Choice				19
		2.5.6  Absolute Addresses and Relative Address Displacements				20
		2.5.7 File Offsets				20
		2.5.8 Counts				20

	2.6	Language Binding
		2.6.1 Deprecated and Removed Interfaces
		2.6.2 Fortran Binding Issues
		2.6.3 C Binding Issues
		2.6.4 Functions and Macros
	2.7	Processes
	2.8	Error Handling
	2.9	Implementation Issues
		2.9.1 Independence of Basic Runtime Routines
		2.9.2 Interaction with Signals
	2.10	Examples
3	Poir	at-to-Point Communication 29
	3.1	Introduction
	3.2	Blocking Send and Receive Operations
		3.2.1 Blocking Send
		3.2.2 Message Data
		3.2.3 Message Envelope
		3.2.4 Blocking Receive
		3.2.5 Return Status
		3.2.6 Passing MPI_STATUS_IGNORE for Status
		3.2.7 Send-Receive
	3.3	Data Type Matching and Data Conversion
		3.3.1 Type Matching Rules
		Type MPI_CHARACTER
		3.3.2 Data Conversion
	3.4	Communication Modes
	3.5	Semantics of Point-to-Point Communication
	3.6	Buffer Allocation and Usage
		3.6.1 Model Implementation of Buffered Mode 5'
	3.7	Nonblocking Communication
		3.7.1 Communication Request Objects
		3.7.2 Communication Initiation
		3.7.3 Communication Completion
		3.7.4 Semantics of Nonblocking Communications
		3.7.5 Multiple Completions
		3.7.6 Non-Destructive Test of status
	3.8	Probe and Cancel
		3.8.1 Probe
		3.8.2 Matching Probe
		3.8.3 Matched Receives
		3.8.4 Cancel
	3.9	Persistent Communication Requests
	3.10	Null Processes

4	Par	titione	d Point-to-Point Communication		99
	4.1	Introdu	uction		99
	4.2	Seman	tics of Partitioned Point-to-Point Communication		100
		4.2.1	Communication Initialization and Starting with Partition	ing	102
		4.2.2	Communication Completion under Partitioning		106
		4.2.3	Semantics of Communications in Partitioned Mode		107
	4.3	Partiti	oned Communication Examples		108
		4.3.1	Partition Communication with Threads/Tasks Using O	penMP 4.0	
			and greater		108
		4.3.2	Send-only Partitioning Example with Tasks and OpenMP	version 4.0	
			and greater		109
		4.3.3	Send and Receive Partitioning Example with OpenMP	version 4.0	
			and greater		111
5		atypes			115
	5.1		d Datatypes		115
		5.1.1	Type Constructors with Explicit Addresses		117
		5.1.2	Datatype Constructors		117
		5.1.3	Subarray Datatype Constructor		129
		5.1.4	Distributed Array Datatype Constructor		131
		5.1.5	Address and Size Functions		137
		5.1.6	Lower-Bound and Upper-Bound Markers		140
		5.1.7	Extent and Bounds of Datatypes		142
		5.1.8	True Extent of Datatypes		144
		5.1.9	Commit and Free		146
			Duplicating a Datatype		148
			Use of General Datatypes in Communication		148
			Correct Use of Addresses		152
			Decoding a Datatype		153
	_ ~		Examples		162
	5.2		nd Unpack		170
	5.3	Canon	ical MPI_PACK and MPI_UNPACK		178
6	Col	lective	Communication		183
			action and Overview		183
	6.2		unicator Argument		186
	J	6.2.1	Specifics for Intra-Communicator Collective Operations		186
		6.2.2	Applying Collective Operations to Inter-Communicators		187
		6.2.3	Specifics for Inter-Communicator Collective Operations		188
	6.3		Synchronization		189
	6.4		$\operatorname{ast}$		190
		6.4.1	Example using MPI_BCAST		191
	6.5				191
	-	6.5.1	Examples using MPI_GATHER, MPI_GATHERV		196
	6.6				202
	-	6.6.1	Examples using MPI_SCATTER, MPI_SCATTERV		206
	6.7		e-to-all		209
			Example using MPI_ALLGATHER		212

6.8	All-to-	All Scatter/Gather
6.9	Global	Reduction Operations
	6.9.1	Reduce
	6.9.2	Predefined Reduction Operations
	6.9.3	Signed Characters and Reductions
	6.9.4	MINLOC and MAXLOC
	6.9.5	User-Defined Reduction Operations
		Example of User-Defined Reduce
	6.9.6	All-Reduce
	6.9.7	Process-Local Reduction
6.10	Reduc	e-Scatter
		MPI_REDUCE_SCATTER_BLOCK
		MPI_REDUCE_SCATTER
6.11		
		Inclusive Scan
		Exclusive Scan
		Example using MPI_SCAN
6.12	Nonble	ocking Collective Operations
		Nonblocking Barrier Synchronization
		Nonblocking Broadcast
		Example using MPI_IBCAST
	6.12.3	Nonblocking Gather
		Nonblocking Scatter
		Nonblocking Gather-to-all
		Nonblocking All-to-All Scatter/Gather
		Nonblocking Reduce
		Nonblocking All-Reduce
		Nonblocking Reduce-Scatter with Equal Blocks
		Nonblocking Reduce-Scatter
		Nonblocking Inclusive Scan
	6.12.12	Nonblocking Exclusive Scan
6.13		cent Collective Operations
		Persistent Barrier Synchronization
		Persistent Broadcast
	6.13.3	Persistent Gather
	6.13.4	Persistent Scatter
	6.13.5	Persistent Gather-to-all
		Persistent All-to-All Scatter/Gather
		Persistent Reduce
		Persistent All-Reduce
		Persistent Reduce-Scatter with Equal Blocks
		Persistent Reduce-Scatter
		l Persistent Inclusive Scan
		2 Persistent Exclusive Scan
6.14	Correc	

7	Gro	ups, C	Contexts, Communicators, and Caching	305
	7.1	Introd	uction	305
		7.1.1	Features Needed to Support Libraries	305
		7.1.2	MPI's Support for Libraries	306
	7.2	Basic	Concepts	308
		7.2.1	Groups	308
		7.2.2	Contexts	308
		7.2.3	Intra-Communicators	309
		7.2.4	Predefined Intra-Communicators	309
	7.3	Group	Management	310
		7.3.1	Group Accessors	310
		7.3.2	Group Constructors	312
		7.3.3	Group Destructors	318
	7.4	Comm	unicator Management	319
		7.4.1	Communicator Accessors	319
		7.4.2	Communicator Constructors	321
		7.4.3	Communicator Destructors	338
		7.4.4	Communicator Info	339
	7.5	Motiva	ating Examples	341
		7.5.1	Current Practice #1	341
		7.5.2	Current Practice #2	342
		7.5.3	(Approximate) Current Practice #3	343
		7.5.4	Example #4	344
		7.5.5	Library Example #1	345
		7.5.6	Library Example #2	346
	7.6	Inter-0	Communication	348
		7.6.1	Inter-Communicator Accessors	350
		7.6.2	Inter-Communicator Operations	352
		7.6.3	Inter-Communication Examples	356
			Example 1: Three-Group "Pipeline"	356
			Example 2: Three-Group "Ring"	357
	7.7	Cachir	ng	358
		7.7.1	Functionality	359
		7.7.2	Communicators	360
		7.7.3	Windows	366
		7.7.4	Datatypes	369
		7.7.5	Error Class for Invalid Keyval	373
		7.7.6	Attributes Example	373
	7.8	Namin	ng Objects	375
	7.9	Forma	lizing the Loosely Synchronous Model	380
		7.9.1	Basic Statements	380
		7.9.2	Models of Execution	380
			Static Communicator Allocation	380
			Dynamic Communicator Allocation	381
			The General Case	381

8	Pro	cess Topologies	383
	8.1	Introduction	383
	8.2	Virtual Topologies	384
	8.3	Embedding in MPI	384
	8.4	Overview of the Functions	385
	8.5	Topology Constructors	386
		8.5.1 Cartesian Constructor	386
		8.5.2 Cartesian Convenience Function: MPI_DIMS_CREATE	387
		8.5.3 Graph Constructor	388
		8.5.4 Distributed Graph Constructor	390
		8.5.5 Topology Inquiry Functions	397
		8.5.6 Cartesian Shift Coordinates	405
		8.5.7 Partitioning of Cartesian Structures	407
		8.5.8 Low-Level Topology Functions	408
	8.6	Neighborhood Collective Communication	410
		8.6.1 Neighborhood Gather	410
		8.6.2 Neighbor Alltoall	415
	8.7	Nonblocking Neighborhood Communication	422
		8.7.1 Nonblocking Neighborhood Gather	422
		8.7.2 Nonblocking Neighborhood Alltoall	425
	8.8	Persistent Neighborhood Communication	429
		8.8.1 Persistent Neighborhood Gather	430
		8.8.2 Persistent Neighborhood Alltoall	433
	8.9	An Application Example	437
9	MPI	Environmental Management	443
	9.1	Implementation Information	443
		9.1.1 Version Inquiries	443
		9.1.2 Environmental Inquiries	445
		Tag Values	445
		Host Rank	445
		IO Rank	446
		Clock Synchronization	446
		Inquire Processor Name	446
4	9.2	Memory Allocation	447
	9.3	Error Handling	450
		9.3.1 Error Handlers for Communicators	453
		9.3.2 Error Handlers for Windows	455
		9.3.3 Error Handlers for Files	457
		9.3.4 Error Handlers for Sessions	458
		9.3.5 Freeing Errorhandlers and Retrieving Error Strings	460
	9.4	Error Codes and Classes	461
	9.5	Error Classes, Error Codes, and Error Handlers	462
	9.6	Timers and Synchronization	469
10	The	Info Object	471

11 Process Initialization, Creation, and Management	479
11.1 Introduction	479
11.2 The World Model	480
11.2.1 Starting MPI Processes	480
11.2.2 Finalizing MPI	486
11.2.3 Determining Whether MPI Has Been Initialized When Using the Wo	
Model	
11.2.4 Allowing User Functions at MPI Finalization	
11.3 The Sessions Model	
11.3.1 Session Creation and Destruction Methods	
11.3.2 Processes Sets	
11.3.3 Runtime Query Functions	
11.3.4 Sessions Model Examples	
11.4 Common Elements of Both Process Models	504
11.4.1 MPI Functionality that is Always Available	504
11.4.2 Aborting MPI Processes	
11.5 Portable MPI Process Startup	506
11.6 MPI and Threads	508
11.6.1 General	
11.7 The Dynamic Process Model	511
11.7.1 Starting Processes	512
11.8 Process Manager Interface	513
11.8.2 Starting Processes and Establishing Communication	
11.8.3 Starting Multiple Executables and Establishing Communication	
11.8.4 Reserved Keys	
11.8.5 Spawn Example	
11.9 Establishing Communication	
11.9.1 Names, Addresses, Ports, and All That	
11.9.2 Server Routines	
11.9.3 Client Routines	
11.9.4 Name Publishing	
11.9.5 Reserved Key Values	
11.9.6 Client/Server Examples	
11.10Other Functionality	
11.10.1 Universe Size	
11.10.2 Singleton MPI Initialization	
11.10.3 MPI_APPNUM	
11.10.4 Releasing Connections	
11.10.5 Another Way to Establish MPI Communication	
	~
12 One-Sided Communications 12.1 Introduction	<b>541</b> 541
12.1 Introduction	
12.2 Initialization	
12.2.2 Window Creation	
12.2.2 WINGOW THOU WINDOWS WIGHTOLY	040

	12.2.3 Window That Allocates Shared Memory	548
	12.2.4 Window of Dynamically Attached Memory	552
		555
		556
	12.2.7 Window Info	557
12.3		559
		560
		563
		564
	_	566
		567
		569
		572
		573
		574
12.4		581
		583
		586
		588
		592
		595
		598
		599
12.6		599
		599
		600
12.7		600
		608
		608
		609
		611
12.8		612
13 Ext	ernal Interfaces	<b>321</b>
13.1	Introduction	621
13.2	Generalized Requests	621
	13.2.1 Examples	626
13.3	Associating Information with Status	628
14 I/O		331
14.1		631
		631
14.2	1	633
	1 0	633
	0	636
		636
		637
	14.2.5 Preallocating Space for a File	638

	14.2.6	Querying the Size of a File
	14.2.7	Querying File Parameters
	14.2.8	File Info
		Reserved File Hints
14.3	File V	iews
14.4	Data A	Access
	14.4.1	Data Access Routines
		Positioning
		Synchronism
		Coordination
		Data Access Conventions
	14.4.2	Data Access with Explicit Offsets
		Data Access with Individual File Pointers
		Data Access with Shared File Pointers
		Noncollective Operations
		Collective Operations
		Seek
	14.4.5	Split Collective Data Access Routines 675
14.5		teroperability
		Datatypes for File Interoperability
		External Data Representation: "external32"
		User-Defined Data Representations
		Extent Callback
		Datarep Conversion Functions
	14.5.4	Matching Data Representations
14.6		tency and Semantics
		File Consistency
		Random Access vs. Sequential Files 699
		Progress
		Collective File Operations
		Nonblocking Collective File Operations
		Type Matching
		Miscellaneous Clarifications
	14.6.8	MPI_Offset Type
		Logical vs. Physical File Layout
		File Size
		Examples
		Asynchronous I/O
14.7	I/O E	rror Handling
		rror Classes
		bles
	_	Double Buffering with Split Collective I/O
		Subarray Filetype Constructor 700

15 Too	l Supp	ort	713
15.1	Introd	$\operatorname{uction}$	713
15.2	Profili	ng Interface	713
	15.2.1	Requirements	713
	15.2.2	Discussion	714
	15.2.3	Logic of the Design	714
	15.2.4	Miscellaneous Control of Profiling	715
	15.2.5	Profiler Implementation Example	716
	15.2.6	MPI Library Implementation Example	716
		Systems with Weak Symbols	716
		Systems without Weak Symbols	717
	15.2.7	Complications	717
		Multiple Counting	717
		Linker Oddities	718
		Fortran Support Methods	718
	15.2.8	Multiple Levels of Interception	718
15.3		IPI Tool Information Interface	
	15.3.1	Verbosity Levels	720
	15.3.2	Binding MPI Tool Information Interface Variables to MPI Objects .	720
	15.3.3	Convention for Returning Strings	721
	15.3.4	Initialization and Finalization	722
	15.3.5	Datatype System	723
	15.3.6	Control Variables	726
		Control Variable Query Functions	726
		Example: Printing All Control Variables	729
		Handle Allocation and Deallocation	730
		Control Variable Access Functions	731
		Example: Reading the Value of a Control Variable	732
	15.3.7		733
		Performance Variable Classes	733
		Performance Variable Query Functions	735
		Performance Experiment Sessions	
		Handle Allocation and Deallocation	739
		Starting and Stopping of Performance Variables	740
		Performance Variable Access Functions	741
		Example: Tool to Detect Receives with Long Unexpected Message	
		Queues	743
	15.3.8	Events	745
		Event Sources	746
		Callback Safety Requirements	748
		Event Type Query Functions	750
		Handle Allocation and Deallocation	753
		Handling Dropped Events	757
		Reading Event Data	759
		Reading Event Meta Data	760
	15.3.9	Variable Categorization	761
		Category Query Functions	762
		Category Member Query Functions	764

	15.3.10 Return Codes for the MPI Tool Information Interface	766 767
16 Der	precated Interfaces	769
_		769
	Deprecated since MPI-2.2	772
	Deprecated since MPI-3.2	772
	Deprecated since MPI-4.0	772
17 Rei	moved Interfaces	775
17.1	Removed MPI-1 Bindings	775
	17.1.1 Overview	775
	17.1.2 Removed MPI-1 Functions	775
	17.1.3 Removed MPI-1 Datatypes	775
	17.1.4 Removed MPI-1 Constants	775
	17.1.5 Removed MPI-1 Callback Prototypes	776
17.2	C++ Bindings	776
18 Bac	ekward Incompatibilities	777
	Backward Incompatible since MPI-3.2	777
19 Lan	nguage Bindings	779
	Support for Fortran	779
	19.1.1 Overview	779
	19.1.2 Fortran Support Through the mpi_f08 Module	780
	19.1.3 Fortran Support Through the mpi Module	783
	19.1.4 Fortran Support Through the mpif.h Include File	785
	19.1.5 Interface Specifications, Procedure Names, and the Profiling Interface	786
	19.1.6 MPI for Different Fortran Standard Versions	791
	19.1.7 Requirements on Fortran Compilers	795
	19.1.8 Additional Support for Fortran Register-Memory-Synchronization .	796
	19.1.9 Additional Support for Fortran Numeric Intrinsic Types	797
	Parameterized Datatypes with Specified Precision and Exponent Range	798
	Support for Size-specific MPI Datatypes	802
	Communication With Size-specific Types	804
	19.1.10 Problems With Fortran Bindings for MPI	805
	19.1.11 Problems Due to Strong Typing	806
	19.1.12 Problems Due to Data Copying and Sequence Association with Sub-	
		807
	19.1.13 Problems Due to Data Copying and Sequence Association with Vector	
	Subscripts	810
	•	810
	19.1.15 Fortran Derived Types	811
	19.1.16 Optimization Problems, an Overview	812
	19.1.17 Problems with Code Movement and Register Optimization	813
	Nonblocking Operations	813
	Persistent Operations	815
	One-sided Communication	815

		MPI_BOTTOM and Combining Independent Variables in Datatypes	
		Solutions	
		The Fortran ASYNCHRONOUS Attribute	. 816
		Calling MPI_F_SYNC_REG	. 818
		A User Defined Routine Instead of MPI_F_SYNC_REG	. 819
		Module Variables and COMMON Blocks	. 819
		The (Poorly Performing) Fortran VOLATILE Attribute	
		The Fortran TARGET Attribute	
	19 1 18	8 Temporary Data Movement and Temporary Memory Modification	
		9 Permanent Data Movement	
		O Comparison with C	
10.2		ort for Large Count and Large Byte Displacement	
		age Interoperability	
19.3	Langu	age interoperability	. 828
		Introduction	
	19.3.2	Assumptions	. 828
		Initialization	
	19.3.4	Transfer of Handles	. 829
	19.3.5	Status	. 831
	19.3.6	MPI Opaque Objects	. 834
		Datatypes	. 834
		Callback Functions	. 836
		Error Handlers	
		Reduce Operations	
	19.3.7	Attributes	
	19.3.8	Extra-State	. 841
	19.3.9	Constants	. 841
	19.3.10	OInterlanguage Communication	. 842
	10.0.1	o international of the communication of the communi	. 012
A Lan	guage	Bindings Summary	845
A.1	Define	ed Values and Handles	. 845
		Defined Constants	
		Types	
		Prototype Definitions	
		C Bindings	
		Fortran 2008 Bindings with the mpi_f08 Module	
		Fortran Bindings with mpif.h or the mpi Module	
	A 1 A		
	A.1.4	T	
		Info Keys	
	A.1.6	Info Values	
A.2		ary of the Semantics of all OpRelated Routines	
A.3	C Bine		
	A.3.1	Point-to-Point Communication C Bindings	
	A.3.2	Partitioned Communication C Bindings	. 873
	A.3.3	Datatypes C Bindings	. 873
	A.3.4	Collective Communication C Bindings	. 877
	A.3.5	Groups, Contexts, Communicators, and Caching C Bindings	
	A.3.6	Process Topologies C Bindings	
	A.3.7	MPI Environmental Management C Bindings	

		A.3.8 The Info Object C Bindings	893
		A.3.9 Process Creation and Management C Bindings	894
		A.3.10 One-Sided Communications C Bindings	895
		A.3.11 External Interfaces C Bindings	898
		A.3.12 I/O C Bindings	898
		A.3.13 Language Bindings C Bindings	903
		A.3.14 Tools / Profiling Interface C Bindings	904
		A.3.15 Tools / MPI Tool Information Interface C Bindings	904
		A.3.16 Deprecated C Bindings	907
	A.4	Fortran 2008 Bindings with the mpi_f08 Module	908
		A.4.1 Point-to-Point Communication Fortran 2008 Bindings	908
		A.4.2 Partitioned Communication Fortran 2008 Bindings	917
		A.4.3 Datatypes Fortran 2008 Bindings	918
		A.4.4 Collective Communication Fortran 2008 Bindings	926
		A.4.5 Groups, Contexts, Communicators, and Caching Fortran 2008 Binding	
		A.4.6 Process Topologies Fortran 2008 Bindings	956
		A.4.7 MPI Environmental Management Fortran 2008 Bindings	965
		A.4.8 The Info Object Fortran 2008 Bindings	968
		A.4.9 Process Creation and Management Fortran 2008 Bindings	969
		A.4.10 One-Sided Communications Fortran 2008 Bindings	972
		A.4.11 External Interfaces Fortran 2008 Bindings	980
		A.4.12 I/O Fortran 2008 Bindings	980
		A.4.13 Language Bindings Fortran 2008 Bindings	993
		A.4.14 Tools / Profiling Interface Fortran 2008 Bindings	994
		A.4.15 Deprecated Fortran 2008 Bindings	994
	A.5	Fortran Bindings with mpif.h or the mpi Module	995
		A.5.1 Point-to-Point Communication Fortran Bindings	995
		A.5.2 Partitioned Communication Fortran Bindings	998
		A.5.3 Datatypes Fortran Bindings	998
		A.5.4 Collective Communication Fortran Bindings	1001
		A.5.5 Groups, Contexts, Communicators, and Caching Fortran Bindings .	1007
		A.5.6 Process Topologies Fortran Bindings	
		A.5.7 MPI Environmental Management Fortran Bindings	
	A	A.5.8 The Info Object Fortran Bindings	1017
		A.5.9 Process Creation and Management Fortran Bindings	1018
		A.5.10 One-Sided Communications Fortran Bindings	1019
		A.5.11 External Interfaces Fortran Bindings	1024
		A.5.12 I/O Fortran Bindings	1024
		A.5.13 Language Bindings Fortran Bindings	1029
		A.5.14 Tools / Profiling Interface Fortran Bindings	1029
		A.5.15 Deprecated Fortran Bindings	1029
В			1031
	B.1	0	1031
		B.1.1 Fixes to Errata in Previous Versions of MPI	1031
		B.1.2 Changes in MPI-4.0	1031
	B.2	0	1032
		B.2.1 Fixes to Errata in Previous Versions of MPI	1032

	B.2.2 Changes in MPI-3.2	
B.3	Changes from Version 3.0 to Version 3.1	
	B.3.1 Fixes to Errata in Previous Versions of MPI	
	B.3.2 Changes in MPI-3.1	
B.4	Changes from Version 2.2 to Version 3.0	
	B.4.1 Fixes to Errata in Previous Versions of MPI	
	B.4.2 Changes in MPI-3.0	
B.5	Changes from Version 2.1 to Version 2.2	
B.6	Changes from Version 2.0 to Version 2.1	. 1045
Bibliog	graphy	1051
Genera	al Index	1057
Examp	oles Index	1063
		<b>*</b>
MPI C	Constant and Predefined Handle Index	1066
MPI D	Declarations Index	1072
MPI C	Callback Function Prototype Index	1073
MPI F	unction Index	1074

# List of Figures

2.1	State Transition Diagram for Blocking Operations	12
2.2	State Transition Diagram for Nonblocking Operations	12
2.3	State Transition Diagram for Persistent Operations	13
6.1	Collective communications, an overview	185
6.2	Inter-communicator allgather	188
6.3	Inter-communicator reduce-scatter	189
6.4	Gather example	196
6.5	Gathery example with strides	197
6.6	Gatherv example, 2-dimensional	198
6.7	Gatherv example, 2-dimensional, subarrays with different sizes	199
6.8	Gatherv example, 2-dimensional, subarrays with different sizes and strides .	201
6.9	Scatter example	206
6.10	Scatter example	207
6.11	Scattery example with different strides and counts	208
6.12	Race conditions with point-to-point and collective communications	299
6.13	Overlapping Communicators Example	303
7.1	Inter-communicator creation using MPI_COMM_CREATE	327
7.2	Inter-communicator construction with MPI_COMM_SPLIT	331
7.3	Recursive communicator creation with MPI_COMM_SPLIT_TYPE	337
7.4	Three-group pipeline	356
7.5	Three-group ring	357
8.1	Neighborhood gather communication example	412
8.2	Cartesian neighborhood allgather example for 3 and 1 processes in a dimension	413
8.3	Cartesian neighborhood alltoall example for 3 and 1 processes in a dimension.	
8.4	Set-up of process structure for two-dimensional parallel Poisson solver	439
8.5	Communication routine with local data copying and sparse neighborhood	
	all-to-all.	440
8.6	Communication routine with sparse neighborhood all-to-all-w and without	
	local data copying.	441
8.7	Two-dimensional parallel Poisson solver with persistent sparse neighborhood	
	all-to-all-w and without local data copying.	442
11.1	Session handle to communicator	492
11 9	Process set examples	495

12.1	Schematic description of the public/private window operations in the	
	MPI_WIN_SEPARATE memory model for two overlapping windows	582
12.2	Active target communication	585
12.3	Active target communication, with weak synchronization	586
12.4	Passive target communication	587
12.5	Active target communication with several processes	591
12.6	Symmetric communication	610
12.7	Deadlock situation	610
12.8	No deadlock	611
14.1	Etypes and filetypes	632
14.2	Partitioning a file among parallel processes	632
	Displacements	
14.4	Example array file layout	710
14.5	Example local array filetype for process 1	710
19.1	Status conversion routines	833

# List of Tables

2.1	Deprecated and Removed constructs	23
3.1 3.2 3.3 3.4	Predefined MPI datatypes corresponding to Fortran datatypes	31 32 33 33
5.1	combiner values returned from MPI_TYPE_GET_ENVELOPE	155
7.1	MPI_COMM_* Function Behavior (in Inter-Communication Mode)	351
9.1 9.2	Error classes (Part 1)	463 464
11.1	List of MPI Functions that can be called at any time within an MPI program, including prior to MPI initialization and following MPI finalization	504
12.1	C types of attribute value argument to MPI_WIN_GET_ATTR and MPI_WIN_SET_ATTR	556
12.2	Error classes in one-sided communication routines	600
14.1	Data access routines	647
14.2	"external32" sizes of predefined datatypes	689
	"external32" sizes of optional datatypes	690
	"external32" sizes of C++ datatypes	690
14.5	I/O Error Classes	707
	MPI tool information interface verbosity levels	721
	Constants to identify associations of variables	721
	MPI datatypes that can be used by the MPI tool information interface	724
	Scopes for control variables	728
	Hierarchy of safety requirement levels for event callback routines	748
15.6	List of MPI functions that when called from within a callback function may not return MPI_T_ERR_NOT_ACCESSIBLE	749
15.7	Return codes used in functions of the MPI tool information interface	768
17.1	Removed MPI-1 functions and their replacements	775
17.2	Removed MPI-1 datatypes. The indicated routine may be used for changing the lower and upper bound respectively	776
17.3	Removed MPI-1 constants	776

1	17.4 Removed MPI-1 callback prototypes and their replacements	776
2		
3	19.1 Specific Fortran procedure names and related calling conventions	787
4	19.2 Occurrence of Fortran optimization problems	813
5		
6		
7		
8		
9		
10		
11		
12		
13		
14		
15		
16		
17		
18		
19		
20		
21		
22		
23		
24		
25		
26		
27		
28		
29		
30		
31		
32		
33		
34		
35		
36		
37		
38		
39		
40		
41		
42		
43		
44		
45		
46		

### Acknowledgments

This document is the product of a number of distinct efforts in four distinct phases: one for each of MPI-1, MPI-2, MPI-3, and MPI-4. This section describes these in historical order, starting with MPI-1. Some efforts, particularly parts of MPI-2, had distinct groups of individuals associated with them, and these efforts are detailed separately.

This document represents the work of many people who have served on the MPI Forum. The meetings have been attended by dozens of people from many parts of the world. It is the hard and dedicated work of this group that has led to the MPI standard.

The technical development was carried out by subgroups, whose work was reviewed by the full committee. During the period of development of the Message-Passing Interface (MPI), many people helped with this effort.

Those who served as primary coordinators in MPI-1.0 and MPI-1.1 are:

- Jack Dongarra, David Walker, Conveners and Meeting Chairs
- Ewing Lusk, Bob Knighten, Minutes
- Marc Snir, William Gropp, Ewing Lusk, Point-to-Point Communication
- Al Geist, Marc Snir, Steve Otto, Collective Communication
- Steve Otto, Editor
- Rolf Hempel, Process Topologies
- Ewing Lusk, Language Binding
- William Gropp, Environmental Management
- James Cownie, Profiling
- Tony Skjellum, Lyndon Clarke, Marc Snir, Richard Littlefield, Mark Sears, Groups, Contexts, and Communicators
- Steven Huss-Lederman, Initial Implementation Subset

The following list includes some of the active participants in the MPI-1.0 and MPI-1.1 process not mentioned above.

10

12

13

14

15

16

18 19

20 21

22

23 24

27

28

36 37

38

Ed Anderson	Robert Babb	Joe Baron	Eric Barszcz
Scott Berryman	Rob Bjornson	Nathan Doss	Anne Elster
Jim Feeney	Vince Fernando	Sam Fineberg	Jon Flower
Daniel Frye	Ian Glendinning	Adam Greenberg	Robert Harrison
Leslie Hart	Tom Haupt	Don Heller	Tom Henderson
Alex Ho	C.T. Howard Ho	Gary Howell	John Kapenga
James Kohl	Susan Krauss	Bob Leary	Arthur Maccabe
Peter Madams	Alan Mainwaring	Oliver McBryan	Phil McKinley
Charles Mosher	Dan Nessett	Peter Pacheco	Howard Palmer
Paul Pierce	Sanjay Ranka	Peter Rigsbee	Arch Robison
Erich Schikuta	Ambuj Singh	Alan Sussman	Robert Tomlinson
Robert G. Voigt	Dennis Weeks	Stephen Wheat	Steve Zenith

The University of Tennessee and Oak Ridge National Laboratory made the draft available by anonymous FTP mail servers and were instrumental in distributing the document.

The work on the MPI-1 standard was supported in part by ARPA and NSF under grant ASC-9310330, the National Science Foundation Science and Technology Center Cooperative Agreement No. CCR-8809615, and by the Commission of the European Community through Esprit project P6643 (PPPE).

#### MPI-1.2 and MPI-2.0:

Those who served as primary coordinators in MPI-1.2 and MPI-2.0 are:

- Ewing Lusk, Convener and Meeting Chair
- Steve Huss-Lederman, Editor
- Ewing Lusk, Miscellany
- Bill Saphir, Process Creation and Management
- Marc Snir, One-Sided Communications
- Bill Gropp and Anthony Skjellum, Extended Collective Operations
- Steve Huss-Lederman, External Interfaces
- Bill Nitzberg, I/O
- Andrew Lumsdaine, Bill Saphir, and Jeff Squyres, Language Bindings
- Anthony Skjellum and Arkady Kanevsky, Real-Time

The following list includes some of the active participants who attended MPI-2 Forum meetings and are not mentioned above.

Greg Astfalk	Robert Babb	Ed Benson	Rajesh Bordawekar
Pete Bradley	Peter Brennan	Ron Brightwell	Maciej Brodowicz
Eric Brunner	Greg Burns	Margaret Cahir	Pang Chen
Ying Chen	Albert Cheng	Yong Cho	Joel Clark
Lyndon Clarke	Laurie Costello	Dennis Cottel	Jim Cownie
Zhenqian Cui	Suresh Damodaran-Kan	nal	Raja Daoud
Judith Devaney	David DiNucci	Doug Doefler	Jack Dongarra
Terry Dontje	Nathan Doss	Anne Elster	Mark Fallon
Karl Feind	Sam Fineberg	Craig Fischberg	Stephen Fleischman
Ian Foster	Hubertus Franke	Richard Frost	Al Geist
Robert George	David Greenberg	John Hagedorn	Kei Harada
Leslie Hart	Shane Hebert	Rolf Hempel	Tom Henderson
Alex Ho	Hans-Christian Hoppe	Joefon Jann	Terry Jones
Karl Kesselman	Koichi Konishi	Susan Kraus	Steve Kubica
Steve Landherr	Mario Lauria	Mark Law	Juan Leon
Lloyd Lewins	Ziyang Lu	Bob Madahar	Peter Madams
John May	Oliver McBryan	Brian McCandless	Tyce McLarty
Thom McMahon	Harish Nag	Nick Nevin	Jarek Nieplocha
Ron Oldfield	Peter Ossadnik	Steve Otto	Peter Pacheco
Yoonho Park	Perry Partow	Pratap Pattnaik	Elsie Pierce
Paul Pierce	Heidi Poxon	Jean-Pierre Prost	Boris Protopopov
James Pruyve	Rolf Rabenseifner	Joe Rieken	Peter Rigsbee
Tom Robey	Anna Rounbehler	Nobutoshi Sagawa	Arindam Saha
Eric Salo	Darren Sanders	Eric Sharakan	Andrew Sherman
Fred Shirley	Lance Shuler	A. Gordon Smith	Ian Stockdale
David Taylor	Stephen Taylor	Greg Tensa	Rajeev Thakur
Marydell Tholburn	Dick Treumann	Simon Tsang	Manuel Ujaldon
David Walker	Jerrell Watts	Klaus Wolf	Parkson Wong
Dave Wright	\ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \		

The MPI Forum also acknowledges and appreciates the valuable input from people via e-mail and in person.

The following institutions supported the MPI-2 effort through time and travel support for the people listed above.

```
Argonne National Laboratory
                                                                                        35
Bolt, Beranek, and Newman
                                                                                        36
California Institute of Technology
                                                                                        37
Center for Computing Sciences
                                                                                        38
                                                                                        39
Convex Computer Corporation
Cray Research
                                                                                        41
Digital Equipment Corporation
                                                                                        42
Dolphin Interconnect Solutions, Inc.
                                                                                        43
Edinburgh Parallel Computing Centre
General Electric Company
                                                                                        44
German National Research Center for Information Technology
                                                                                        45
Hewlett-Packard
                                                                                        46
                                                                                        47
Hitachi
Hughes Aircraft Company
```

2 International Business Machines 3 Khoral Research Lawrence Livermore National Laboratory 5 Los Alamos National Laboratory 6 MPI Software Techology, Inc. Mississippi State University **NEC Corporation** National Aeronautics and Space Administration 10 National Energy Research Scientific Computing Center 11 National Institute of Standards and Technology 12 National Oceanic and Atmospheric Adminstration 13 Oak Ridge National Laboratory 14 The Ohio State University 15 PALLAS GmbH 16 Pacific Northwest National Laboratory 17 Pratt & Whitney 18 San Diego Supercomputer Center 19 Sanders, A Lockheed-Martin Company 20 Sandia National Laboratories 21 Schlumberger 22 Scientific Computing Associates, Inc. 23 Silicon Graphics Incorporated 24 Sky Computers 25 Sun Microsystems Computer Corporation 26 Syracuse University 27 The MITRE Corporation 28 Thinking Machines Corporation 29 United States Navy 30 University of Colorado 31 University of Denver 32 University of Houston 33 University of Illinois 34 University of Maryland 35 University of Notre Dame 36 University of San Fransisco 37 University of Stuttgart Computing Center 38 University of Wisconsin 39 MPI-2 operated on a very tight budget (in reality, it had no budget when the first

Intel Corporation

40

41

42

43

meeting was announced). Many institutions helped the MPI-2 effort by supporting the efforts and travel of the members of the MPI Forum. Direct support was given by NSF and DARPA under NSF contract CDA-9115428 for travel by U.S. academic participants and Esprit under project HPC Standards (21111) for European participants.

### MPI-1.3 and MPI-2.1:

The editors and organizers of the combined documents have been:

- Richard Graham, Convener and Meeting Chair
- Jack Dongarra, Steering Committee
- Al Geist, Steering Committee
- Bill Gropp, Steering Committee
- Rainer Keller, Merge of MPI-1.3
- Andrew Lumsdaine, Steering Committee
- Ewing Lusk, Steering Committee, MPI-1.1-Errata (Oct. 12, 1998) MPI-2.1-Errata Ballots 1, 2 (May 15, 2002)
- Rolf Rabenseifner, Steering Committee, Merge of MPI-2.1 and MPI-2.1-Errata Ballots 3, 4 (2008)

All chapters have been revisited to achieve a consistent MPI-2.1 text. Those who served as authors for the necessary modifications are:

- Bill Gropp, Front matter, Introduction, and Bibliography
- Richard Graham, Point-to-Point Communication
- Adam Moody, Collective Communication
- Richard Treumann, Groups, Contexts, and Communicators
- Jesper Larsson Träff, Process Topologies, Info-Object, and One-Sided Communications
- George Bosilca, Environmental Management
- David Solt, Process Creation and Management
- Bronis R. de Supinski, External Interfaces, and Profiling
- Rajeev Thakur, I/O
- Jeffrey M. Squyres, Language Bindings and MPI-2.1 Secretary
- Rolf Rabenseifner, Deprecated Functions and Annex Change-Log
- Alexander Supalov and Denis Nagorny, Annex Language Bindings

The following list includes some of the active participants who attended MPI-2 Forum meetings and in the e-mail discussions of the errata items and are not mentioned above.

12

13 14

15

16

17

18 19

20

21 22

23

24

26 27

28

30 31

32 33

34

35 36

37 38

41

42

43 44

1	Pavan Balaji	Purushotham V. Bangalore	Brian Barrett		
2	Richard Barrett	Christian Bell	Robert Blackmore		
3	Gil Bloch	Ron Brightwell	Jeffrey Brown		
4	Darius Buntinas	Jonathan Carter	Nathan DeBardeleben		
5	Terry Dontje	Gabor Dozsa	Edric Ellis		
6	Karl Feind	Edgar Gabriel	Patrick Geoffray		
7	David Gingold	Dave Goodell	Erez Haba		
8	Robert Harrison	Thomas Herault	Steve Hodson		
9	Torsten Hoefler	Joshua Hursey	Yann Kalemkarian		
10	Matthew Koop	Quincey Koziol	Sameer Kumar		
11	Miron Livny	Kannan Narasimhan	Mark Pagel		
12	Avneesh Pant	Steve Poole	Howard Pritchard		
13	Craig Rasmussen	Hubert Ritzdorf	Rob Ross		
14	Tony Skjellum	Brian Smith	Vinod Tipparaju		
15	Jesper Larsson Träff	Keith Underwood			
16	TI MOLE 1 1	1 1 1 1 1 1			
17	The MPI Forum also acknowledges and appreciates the valuable input from people via				
18	e-mail and in person.  The following institutions supported the MPI-2 effort through time and travel support				
19	_	s supported the MPI-2 effort t	nrough time and travel support		
20	for the people listed above.				
21	Argonne National Labora	atory			
22	Bull				
23	Cisco Systems, Inc.				
24	Cray Inc.		,		
25	The HDF Group				
26	Hewlett-Packard				
27	IBM T.J. Watson Resear	ch			
28	Indiana University				
29		nerche en Informatique et Aut	omatique (Inria)		
30	Intel Corporation				
31	Lawrence Berkeley Natio	· ·			
32	Lawrence Livermore National Laboratory				
33	Los Alamos National Laboratory				
34	Mathworks				
35	Mellanox Technologies				
36	Microsoft				
37	Myricom	NEGE			
38	NEC Laboratories Europ	· -			
39	Oak Ridge National Laboratory				
40	The Ohio State University				

Pacific Northwest National Laboratory

University of Alabama at Birmingham

QLogic Corporation

Sun Microsystems, Inc.

University of Houston

SiCortex

Sandia National Laboratories

Silicon Graphics Incorporated

41

42

43

44

45

46

University of Illinois at Urbana-Champaign University of Stuttgart, High Performance Computing Center Stuttgart (HLRS) University of Tennessee, Knoxville University of Wisconsin

Funding for the MPI Forum meetings was partially supported by award #CCF-0816909 from the National Science Foundation. In addition, the HDF Group provided travel support for one U.S. academic.

#### MPI-2.2:

All chapters have been revisited to achieve a consistent MPI-2.2 text. Those who served as authors for the necessary modifications are:

- William Gropp, Front matter, Introduction, and Bibliography; MPI-2.2 chair.
- Richard Graham, Point-to-Point Communication and Datatypes
- Adam Moody, Collective Communication
- Torsten Hoefler, Collective Communication and Process Topologies
- Richard Treumann, Groups, Contexts, and Communicators
- Jesper Larsson Träff, Process Topologies, Info-Object and One-Sided Communications
- George Bosilca, Datatypes and Environmental Management
- David Solt, Process Creation and Management
- Bronis R. de Supinski, External Interfaces, and Profiling
- Rajeev Thakur, I/O
- Jeffrey M. Squyres, Language Bindings and MPI-2.2 Secretary
- Rolf Rabenseifner, Deprecated Functions, Annex Change-Log, and Annex Language Bindings
- Alexander Supalov, Annex Language Bindings

The following list includes some of the active participants who attended MPI-2 Forum meetings and in the e-mail discussions of the errata items and are not mentioned above.

10 11

12

13 14

15

16 17

18 19

20

21 22

24

26 27

28 29

30

34 35

36

37

39

	1	Pavan Balaji	Purushotham V. Bangalore	Brian Barrett
	2	Richard Barrett	Christian Bell	Robert Blackmore
	3	Gil Bloch	Ron Brightwell	Greg Bronevetsky
	4	Jeff Brown	Darius Buntinas	Jonathan Carter
	5	Nathan DeBardeleben	Terry Dontje	Gabor Dozsa
	6	Edric Ellis	Karl Feind	Edgar Gabriel
	7	Patrick Geoffray	Johann George	David Gingold
	8	David Goodell	Erez Haba	Robert Harrison
	9	Thomas Herault	Marc-André Hermanns	Steve Hodson
	10	Joshua Hursey	Yutaka Ishikawa	Bin Jia
	11	Hideyuki Jitsumoto	Terry Jones	Yann Kalemkarian
	12	Ranier Keller	Matthew Koop	Quincey Koziol
	13	Manojkumar Krishnan	Sameer Kumar	Miron Livny
	14	Andrew Lumsdaine	Miao Luo	Ewing Lusk
	15	Timothy I. Mattox	Kannan Narasimhan	Mark Pagel
	16	Avneesh Pant	Steve Poole	Howard Pritchard
	17	Craig Rasmussen	Hubert Ritzdorf	Rob Ross
	18	Martin Schulz	Pavel Shamis	Galen Shipman
	19	Christian Siebert	Anthony Skjellum	Brian Smith
2	20	Naoki Sueyasu	Vinod Tipparaju	Keith Underwood
2	21	Rolf Vandevaart	Abhinav Vishnu	Weikuan Yu

24

25

26 27

28

29

30

31

32

33

34

35

36

37

38

39

40

41

42

43

44

The MPI Forum also acknowledges and appreciates the valuable input from people via e-mail and in person.

The following institutions supported the MPI-2.2 effort through time and travel support for the people listed above.

Argonne National Laboratory

Auburn University

Bull

Cisco Systems, Inc.

Cray Inc.

Forschungszentrum Jülich

Fujitsu

The HDF Group

Hewlett-Packard

International Business Machines

Indiana University

Institut National de Recherche en Informatique et Automatique (Inria)

Institute for Advanced Science & Engineering Corporation

Intel Corporation

Lawrence Berkeley National Laboratory

Lawrence Livermore National Laboratory

Los Alamos National Laboratory

Mathworks

45 Mellanox Technologies

46 Microsoft

47 Myricom

NEC Corporation

Oak Ridge National Laboratory	1
The Ohio State University	2
Pacific Northwest National Laboratory	3
QLogic Corporation	4
RunTime Computing Solutions, LLC	5
Sandia National Laboratories	6
SiCortex, Inc.	7
Silicon Graphics Inc.	8
Sun Microsystems, Inc.	9
Tokyo Institute of Technology	10
University of Alabama at Birmingham	11
University of Houston	12
University of Illinois at Urbana-Champaign	13
University of Stuttgart, High Performance Computing Center Stuttgart (HLRS)	14
University of Tennessee, Knoxville	15 16
University of Tokyo	17
University of Wisconsin	18
Funding for the MPI Forum meetings was partially supported by awards $\#CCF-0816909$	19
and $\#$ CCF-1144042 from the National Science Foundation. In addition, the HDF Group	20
provided travel support for one U.S. academic.	21
	22
MPI-3.0:	23
MPI-3.0 is a significant effort to extend and modernize the MPI Standard.	24
The editors and organizers of the MPI-3.0 have been:	25
The curvers und erguments of the Will David Scott.	26
• William Gropp, Steering committee, Front matter, Introduction, Groups, Contexts,	27
and Communicators, One-Sided Communications, and Bibliography	28
• Richard Graham, Steering committee, Point-to-Point Communication, Meeting Con-	29
vener, and MPI-3.0 chair	30
vener, and ivii i 3.5 chair	31
• Torsten Hoefler, Collective Communication, One-Sided Communications, and Process	32
Topologies	33
George Bosilca, Datatypes and Environmental Management	34
George Bosnica, Datatypes and Environmental Management	35
• David Solt, Process Creation and Management	36 37
- Danie D. de Carineli, Festamel Interference and Treal Comment	38
• Bronis R. de Supinski, External Interfaces and Tool Support	39
• Rajeev Thakur, I/O and One-Sided Communications	40
	41
• Darius Buntinas, Info Object	42
• Jeffrey M. Squyres, Language Bindings and MPI-3.0 Secretary	43
• Rolf Rabenseifner, Steering committee, Terms and Definitions, and Fortran Bindings,	44
Deprecated Functions, Annex Change-Log, and Annex Language Bindings	45 46
2 oprocessed a university, rannon change 206, and rannon being auge Britaings	47
• Craig Rasmussen, Fortran Bindings	40

The following list includes some of the active participants who attended MPI-3 Forum meetings or participated in the e-mail discussions and who are not mentioned above.

3			
4	Tatsuya Abe	Tomoya Adachi	Sadaf Alam
5	Reinhold Bader	Pavan Balaji	Purushotham V. Bangalore
6	Brian Barrett	Richard Barrett	Robert Blackmore
7	Aurelien Bouteiller	Ron Brightwell	Greg Bronevetsky
8	Jed Brown	Darius Buntinas	Devendar Bureddy
9	Arno Candel	George Carr	Mohamad Chaarawi
10	Raghunath Raja Chandrasekar	James Dinan	Terry Dontje
11	Edgar Gabriel	Balazs Gerofi	Brice Goglin
12	David Goodell	Manjunath Gorentla	Erez Haba
13	Jeff Hammond	Thomas Herault	Marc-André Hermanns
14	Jennifer Herrett-Skjellum	Nathan Hjelm	Atsushi Hori
15	Joshua Hursey	Marty Itzkowitz	Yutaka Ishikawa
16	Nysal Jan	Bin Jia	Hideyuki Jitsumoto
17	Yann Kalemkarian	Krishna Kandalla	Takahiro Kawashima
18	Chulho Kim	Dries Kimpe	Christof Klausecker
19	Alice Koniges	Quincey Koziol	Dieter Kranzlmueller
20	Manojkumar Krishnan	Sameer Kumar	Eric Lantz
21	Jay Lofstead	Bill Long	Andrew Lumsdaine
22	Miao Luo	Ewing Lusk	Adam Moody
23	Nick M. Maclaren	Amith Mamidala	Guillaume Mercier
24	Scott McMillan	Douglas Miller	Kathryn Mohror
25	Tim Murray	Tomotake Nakamura	Takeshi Nanri
26	Steve Oyanagi	Mark Pagel	Swann Perarnau
27	Sreeram Potluri	Howard Pritchard	Rolf Riesen
28	Hubert Ritzdorf	Kuninobu Sasaki	Timo Schneider
29	Martin Schulz	Gilad Shainer	Christian Siebert
30	Anthony Skjellum	Brian Smith	Marc Snir
31	Raffaele Giuseppe Solca	Shinji Sumimoto	Alexander Supalov
32	Sayantan Sur	Masamichi Takagi	Fabian Tillier
33	Vinod Tipparaju	Jesper Larsson Träff	Richard Treumann
34	Keith Underwood	Rolf Vandevaart	Anh Vo
35	Abhinav Vishnu	Min Xie	Enqiang Zhou
36			

The MPI Forum also acknowledges and appreciates the valuable input from people via e-mail and in person.

The MPI Forum also thanks those that provided feedback during the public comment period. In particular, the Forum would like to thank Jeremiah Wilcock for providing detailed comments on the entire draft standard.

The following institutions supported the MPI-3 effort through time and travel support for the people listed above.

Argonne National Laboratory
Bull
Cisco Systems, Inc.
Cray Inc.
CSCS

ETH Zurich
Fujitsu Ltd.
German Research School for Simulation Sciences
The HDF Group
Hewlett-Packard
International Business Machines
IBM India Private Ltd
Indiana University
Institut National de Recherche en Informatique et Automatique (Inria)
Institute for Advanced Science & Engineering Corporation
Intel Corporation
Lawrence Berkeley National Laboratory
Lawrence Livermore National Laboratory
Los Alamos National Laboratory
Mellanox Technologies, Inc.
Microsoft Corporation
NEC Corporation
National Oceanic and Atmospheric Administration, Global Systems Division
NVIDIA Corporation
Oak Ridge National Laboratory
The Ohio State University
Oracle America
Platform Computing 2
RIKEN AICS
RunTime Computing Solutions, LLC
Sandia National Laboratories
Technical University of Chemnitz
Tokyo Institute of Technology
University of Alabama at Birmingham
University of Chicago
University of Houston <sup>3</sup>
University of Illinois at Urbana-Champaign
University of Stuttgart, High Performance Computing Center Stuttgart (HLRS)
University of Tennessee, Knoxville  3
University of Tokyo
Funding for the MPI Forum meetings was partially supported by awards #CCF-0816909
and #CCF-1144042 from the National Science Foundation. In addition, the HDF Group
and Sandia National Laboratories provided travel support for one U.S. academic each
MPI-3.1:
4
MPI-3.1 is a minor update to the MPI Standard.
The editors and organizers of the MPI-3.1 have been:
• Martin Schulz, MPI-3.1 chair
• William Gropp, Steering committee, Front matter, Introduction, One-Sided Commu-
nications, and Bibliography: Overall editor

- Rolf Rabenseifner, Steering committee, Terms and Definitions, and Fortran Bindings, Deprecated Functions, Annex Change-Log, and Annex Language Bindings
- Richard L. Graham, Steering committee, Meeting Convener
- Jeffrey M. Squyres, Language Bindings and MPI-3.1 Secretary
- Daniel Holmes, Point-to-Point Communication
- George Bosilca, Datatypes and Environmental Management
- Torsten Hoefler, Collective Communication and Process Topologies
- Pavan Balaji, Groups, Contexts, and Communicators, and External Interfaces
- Jeff Hammond, The Info Object
- David Solt, Process Creation and Management
- Quincey Koziol, I/O

- Kathryn Mohror, Tool Support
- Rajeev Thakur, One-Sided Communications

The following list includes some of the active participants who attended MPI Forum meetings or participated in the e-mail discussions.

Pavan Balaji	Purushotham V. Bangalore
Wesley Bland	Michael Blocksome
Aurelien Bouteiller	Devendar Bureddy
Mohamad Chaarawi	Alexey Cheptsov
Dmitry Durnov	Thomas François
Todd Gamblin	Balazs Gerofi
David Goodell	Manjunath Gorentla Venkata
Ryan E. Grant	William Gropp
Jeff Hammond	Amin Hassani
Nathan Hjelm	Torsten Hoefler
Ātsushi Hori	Yutaka Ishikawa
Jithin Jose	Krishna Kandalla
Takahiro Kawashima	Chulho Kim
Alice Koniges	Quincey Koziol
Joshua Ladd	Ignacio Laguna
Guillaume Mercier	Kathryn Mohror
Tomotake Nakamura	Takeshi Nanri
Antonio J. Pẽna	Sreeram Potluri
Rolf Rabenseifner	Nicholas Radcliffe
Raghunath Raja	Craig Rasmussen
Kento Sato	Martin Schulz
$O1 \cdot 1 \cdot O \cdot 1 \cdot 1$	Anthony Chiellen
Christian Siebert	Anthony Skjellum
	Wesley Bland Aurelien Bouteiller Mohamad Chaarawi Dmitry Durnov Todd Gamblin David Goodell Ryan E. Grant Jeff Hammond Nathan Hjelm Atsushi Hori Jithin Jose Takahiro Kawashima Alice Koniges Joshua Ladd Guillaume Mercier Tomotake Nakamura Antonio J. Pēna Rolf Rabenseifner Raghunath Raja Kento Sato

	Hari Subramoni	Shinji Sumimoto	Alexander Supalov	1
	Bronis R. de Supinski	Sayantan Sur	Masamichi Takagi	2
	Keita Teranishi	Rajeev Thakur	Fabian Tillier	3
	Yuichi Tsujita	Geoffroy Vallée	Rolf vandeVaart	4
	Akshay Venkatesh	Jerome Vienne	Venkat Vishwanath	5
	Anh Vo	Huseyin S. Yildiz	Junchao Zhang	6
	Xin Zhao	U	G	7
				8
The MP	I Forum also acknowled	ges and appreciates	the valuable input from people via	9
e-mail and in	n person.			10
The foll	owing institutions suppo	rted the MPI-3.1 effo	ort through time and travel support	11
for the peop	le listed above.			12
Argonn	e National Laboratory			13
	University			14
	ystems, Inc.			15
Cray	ystems, mc.			16
•	The University of Edinb	umala		17
	The University of Edinb	ourgn		18
ETH Zu				19
	ngszentrum Jülich			20
Fujitsu	D 101 10 0	1 4: C:		21
	Research School for Sir	nulation Sciences		22
	F Group			23
	tional Business Machines		(7.1)	
	National de Recherche	en Informatique et <i>I</i>	Automatique (Inria)	24
	prporation	TT. 1 70 0	G (1454 HDG)	25
		e, High-Pertormance	Computing (JARA-HPC)	26
-	University			27
	ce Berkeley National Lal	-		28
	ce Livermore National L	aboratory		29
Lenovo				30
	mos National Laborator	У		31
	x Technologies, Inc.			32
	ft Corporation			33
	orporation			34
	A Corporation			35
	dge National Laboratory	•		36
	io State University			37
RIKEN				38
	National Laboratories			39
	dvanced Computing Ce	nter		40
-	nstitute of Technology			41
Univers	ity of Alabama at Birmi	ngham		42
	ity of Houston			43
Univers	ity of Illinois at Urbana-	Champaign		44
Univers	ity of Oregon			45
Univers	ity of Stuttgart, High Pe	erformance Computi	ng Center Stuttgart (HLRS)	46
Univers	ity of Tennessee, Knoxvi	ille		47
Univers	ity of Tokyo			48

MPI-4.(	):
	is a major update to the MPI Standard. tors and organizers of the MPI-4.0 have been:
• M	artin Schulz, MPI-4.0 chair, Info Object, External Interfaces
• W	esley Bland, MPI-4.0 Secretary, Backward Incompatibilities
	Filliam Gropp, MPI-4.0 Editor, Steering committee, Front matter, Introduction, One-ded Communications, and Bibliography
	olf Rabenseifner, Steering committee, Process Topologies, Deprecated Functions, emoved Interfaces, Annex Language Bindings Summary, and Annex Change-Log.
• Pı	uri Bangalore, Language Bindings
• C	laudia Blaas-Schenner, Terms and Conventions
• G	eorge Bosilca, Datatypes and Environmental Management
• R	yan Grant, Partitioned Communication
• M	arc-André Hermanns, Tool Support
• D	aniel Holmes, Point-to-Point Communication, Sessions
• G	uillaume Mercier, Groups, Contexts, Communicators, Caching
• He	oward Pritchard, Process Creation and Management
• A:	nthony Skjellum, Collective Communication, I/O
some ca	of the development of MPI-4.0, a number of working groups were established. In ses, the work for these groups overlapped with multiple chapters. The following as the major working groups and the leaders of those groups:
	cive Communication, Topology, Communicators Torsten Hoefler, Andrew amsdaine, and Anthony Skjellum
Fault T	Tolerance Wesley Bland, Aurélien Bouteiller, and Richard Graham
Hardw	are-Topologies Guillaume Mercier
Hybrid	l & Accelerator Pavan Balaji and Jim Dinan
Large	Counts Jeff Hammond
Persist	ence Anthony Skjellum
Point t	to Point Communication Richard Graham and Dan Holmes
$\mathbf{Remot}$	e Memory Access William Gropp and Rajeev Thakur
Seman	tic Terms Rolf Rabenseifner and Purushotham Bangalore
Session	as Daniel Holmes

#### Tools Kathryn Mohror and Marc-André Hermanns

The following list includes some of the active participants who attended MPI Forum meetings or participated in the e-mail discussions.

Julien Adam	Abdelhalim Amer	Charles Archer
Ammar Ahmad Awan	Pavan Balaji	Marc Gamell Balmana
Purushotham Bangalore	Mohammadreza Bayatpour	Jean-Baptiste Besnard
Claudia Blaas-Schenner	Wesley Bland	Gil Bloch
George Bosilca	Aurelien Bouteiller	Ben Bratu
Alexander Calvert	Nicholas Chaimov	Sourav Chakraborty
Steffen Christgau	Ching-Hsiang Chu	Mikhail Chuvelev
James Clark	Carsten Clauss	Giuseppe Congiu
Brandon Cook	James Custer	Anna Daly
	James Dinan	Matthew Dosanjh
Hoang-Vu Dang Murali Emani	Christian Engelmann	Noah Evans
Ana Gainaru	Esthela Gallardo	Balazs Gerofi
Salvatore Di Girolamo		Richard Graham
	Brice Goglin	
Ryan Grant	Stanley Graves	William Gropp Yanfei Guo
Siegmar Gross	Taylor Groves	
Khaled Hamidouche	Jeff Hammond	Marc-André Hermanns
Nathan Hjelm	Torsten Hoefler	Daniel Holmes
Atsushi Hori	Josh Hursey	Ilya Ivanov
Julien Jaeger	Emmanuel Jeannot	Sylvain Jeaugey
Jithin Jose	Krishna Kandalla	Takahiro Kawashima
Chulho Kim	Michael Knobloch	Alice Koniges
Sameer Kumar	Kim Kyunghun	Ignacio Laguna
Stefan Lankes	Tonglin Li	Xioyi Lu
Kavitha Madhu	Alexey Malhanov	Ryan Marshall
William Marts	Guillaume Mercier	Kathryn Mohror
Takeshi Nanri	Thomas Naughton	Takafumi Nose
Lena Oden	Steve Oyanagi	Guillaume Papauré
Ivy Peng	Ignacio Laguna Peralta	Antonio Peña
Simon Pickartz	Artem Polyakov	Sreeram Potluri
Howard Pritchard	Martina Prugger	Marc Pérache
Rolf Rabenseifner	Nicholas Radcliffe	Ken Raffenetti
Craig Rasmussen	Soren Rasmussen	Hubert Ritzdorf
Sergio Rivas-Gomez	Davide Rossetti	Martin Ruefenacht
Amit Ruhela	Joseph Schuchart	Martin Schulz
Sangmin Seo	Sameh Sharkawi	Sameer Shende
Min Si	Anthony Skjellum	Brian Smith
David Solt	Jeff Squyres	Srinivas Sridharan
Hari Subramoni	Nawrin Sultana	Shinji Sumimoto
Sayantan Sur	Hugo Taboada	Keita Teranishi
Rajeev Thakur	Keith Underwood	Isaias Alberto Compres Urena
Geoffroy Vallee	Manjunath Gorentla Venkata	Akshay Venkatesh

1 2	Jerome Vienne Anh Vo Justin Wozniak Junchao Zhang Dong Zhong Hui Zhou
3	
4	
5 6	The MPI Forum also acknowledges and appreciates the valuable input from people via e-mail and in person.
7 8	The following institutions supported the MPI-4.0 effort through time and travel support
9	for the people listed above.
10	ATOS/BULL
11	Argonne National Laboratory
12	Arm
13	Auburn University
14	Barcelona Supercomputing Center
15	CEA
16	Cisco Systems Inc.
17	Cray Inc.
18	EPCC, The University Of Edinburgh
19	ETH Zürich
20	Forschungszentrum Jülich
21	Fujitsu
22	Fulda University of Applied Sciences
23	German Research School for Simulation Sciences
24	Hewlett Packard Enterprise
25	International Business Machines
26	Institut National de Recherche en Informatique et Automatique (Inria)
27	Intel Corporation
28	Jülich Aachen Research Alliance, High-Performance Computing (JARA-HPC)
29	Jülich Supercomputing Center
30	KTH Royal Institute Of Technology
31 32	Kyushu University
33	Lawrence Berkeley National Laboratory
34	Lawrence Livermore National Laboratory
35	Lenovo Los Alamos National Laboratory
36	Mellanox Technologies, Inc.
37	Microsoft Corporation
38	NEC Corporation
39	NVIDIA Corporation
40	Oak Ridge National Laboratory
41	PAR-TEC
42	Paratools, Inc.
43	RIKEN AICS (R-CCS as of 2017)
44	RWTH Aachen University
45	Rutgers University
46	Sandia National Laboratories
47	Silicon Graphics, Inc.
48	VSC Research Center, TU Wien

Technical University Of Munich	1
The HDF Group	2
The Ohio State University	3
Texas Advanced Computing Center	4
Tokyo Institute of Technology	5
University of Alabama at Birmingham	6
University of Houston	7
University of Illinois at Urbana-Champaign and the National Center for Supercomput-	8
ing Applications	9
University of Innsbruck	10
University of Oregon	11
University of Pottsdam	12
University of Stuttgart, High Performance Computing Center Stuttgart (HLRS)	13
University of Tennessee, Chattanooga	14
University of Tennessee, Knoxville	15
University of Texas at El Paso	16
University of Tokyo	17
	18
	19
	20
	21
	22
	23
	24
	25
	26
	27
	28
	29
	30
	31
	32
	33
	34
	35
	36
	37
	38
	39
¥	40
	41
	42
	43
	44 45
	46 47
	47



# Chapter 1

# Introduction to MPI

#### 1.1 Overview and Goals

MPI (Message-Passing Interface) is a message-passing library interface specification. All parts of this definition are significant. MPI addresses primarily the message-passing parallel programming model, in which data is moved from the address space of one process to that of another process through cooperative operations on each process. Extensions to the "classical" message-passing model are provided in collective operations, remote-memory access operations, dynamic process creation, and parallel I/O. MPI is a specification, not an implementation; there are multiple implementations of MPI. This specification is for a library interface; MPI is not a language, and all MPI operations are expressed as functions, subroutines, or methods, according to the appropriate language bindings which, for C and Fortran, are part of the MPI standard. The standard has been defined through an open process by a community of parallel computing vendors, computer scientists, and application developers. The next few sections provide an overview of the history of MPI's development.

The main advantages of establishing a message-passing standard are portability and ease of use. In a distributed memory communication environment in which the higher level routines and/or abstractions are built upon lower level message-passing routines the benefits of standardization are particularly apparent. Furthermore, the definition of a message-passing standard, such as that proposed here, provides vendors with a clearly defined base set of routines that they can implement efficiently, or in some cases for which they can provide hardware support, thereby enhancing scalability.

The goal of the Message-Passing Interface simply stated is to develop a widely used standard for writing message-passing programs. As such the interface should establish a practical, portable, efficient, and flexible standard for message passing.

A complete list of goals follows.

- Design an application programming interface (not necessarily for compilers or a system implementation library).
- Allow efficient communication: Avoid memory-to-memory copying, allow overlap of computation and communication, and offload to communication co-processors, where available.
- Allow for implementations that can be used in a heterogeneous environment.
- Allow convenient C and Fortran bindings for the interface.

- Assume a reliable communication interface: the user need not cope with communication failures. Such failures are dealt with by the underlying communication subsystem.
- Define an interface that can be implemented on many vendor's platforms, with no significant changes in the underlying communication and system software.
- Semantics of the interface should be language independent.
- The interface should be designed to allow for thread safety.

### 1.2 Background of MPI-1.0

MPI sought to make use of the most attractive features of a number of existing messagepassing systems, rather than selecting one of them and adopting it as the standard. Thus, MPI was strongly influenced by work at the IBM T. J. Watson Research Center [2, 3], Intel's NX/2 [57], Express [14], nCUBE's Vertex [53], p4 [9, 10], and PARMACS [6, 11]. Other important contributions have come from Zipcode [60, 61], Chimp [20, 21], PVM [5, 18], Chameleon [31], and PICL [26].

The MPI standardization effort involved about 60 people from 40 organizations mainly from the United States and Europe. Most of the major vendors of concurrent computers were involved in MPI, along with researchers from universities, government laboratories, and industry. The standardization process began with the Workshop on Standards for Message-Passing in a Distributed Memory Environment, sponsored by the Center for Research on Parallel Computing, held April 29–30, 1992, in Williamsburg, Virginia [69]. At this workshop the basic features essential to a standard message-passing interface were discussed, and a working group established to continue the standardization process.

A preliminary draft proposal, known as MPI-1, was put forward by Dongarra, Hempel, Hey, and Walker in November 1992, and a revised version was completed in February 1993 [19]. MPI-1 embodied the main features that were identified at the Williamsburg workshop as being necessary in a message passing standard. Since MPI-1 was primarily intended to promote discussion and "get the ball rolling," it focused mainly on point-to-point communications. MPI-1 brought to the forefront a number of important standardization issues, but did not include any collective communication routines and was not thread-safe.

In November 1992, a meeting of the MPI working group was held in Minneapolis, at which it was decided to place the standardization process on a more formal footing, and to generally adopt the procedures and organization of the High Performance Fortran Forum. Subcommittees were formed for the major component areas of the standard, and an email discussion service established for each. In addition, the goal of producing a draft MPI standard by the Fall of 1993 was set. To achieve this goal the MPI working group met every 6 weeks for two days throughout the first 9 months of 1993, and presented the draft MPI standard at the Supercomputing 93 conference in November 1993. These meetings and the email discussion together constituted the MPI Forum, membership of which has been open to all members of the high performance computing community.

### 1.3 Background of MPI-1.1, MPI-1.2, and MPI-2.0

Beginning in March 1995, the MPI Forum began meeting to consider corrections and extensions to the original MPI Standard document [23]. The first product of these deliberations

was Version 1.1 of the MPI specification, released in June of 1995 [24] (see <a href="http://www.mpi-forum.org">http://www.mpi-forum.org</a> for official MPI document releases). At that time, effort focused in five areas.

- 1. Further corrections and clarifications for the MPI-1.1 document.
- 2. Additions to MPI-1.1 that do not significantly change its types of functionality (new datatype constructors, language interoperability, etc.).
- 3. Completely new types of functionality (dynamic processes, one-sided communication, parallel I/O, etc.) that are what everyone thinks of as "MPI-2 functionality."
- 4. Bindings for Fortran 90 and C++. MPI-2 specifies C++ bindings for both MPI-1 and MPI-2 functions, and extensions to the Fortran 77 binding of MPI-1 and MPI-2 to handle Fortran 90 issues.
- 5. Discussions of areas in which the MPI process and framework seem likely to be useful, but where more discussion and experience are needed before standardization (e.g., zero-copy semantics on shared-memory machines, real-time specifications).

Corrections and clarifications (items of type 1 in the above list) were collected in Chapter 3 of the MPI-2 document: "Version 1.2 of MPI." That chapter also contains the function for identifying the version number. Additions to MPI-1.1 (items of types 2, 3, and 4 in the above list) are in the remaining chapters of the MPI-2 document, and constitute the specification for MPI-2. Items of type 5 in the above list have been moved to a separate document, the "MPI Journal of Development" (JOD), and are not part of the MPI-2 Standard.

This structure makes it easy for users and implementors to understand what level of MPI compliance a given implementation has:

- MPI-1 compliance will mean compliance with MPI-1.3. This is a useful level of compliance. It means that the implementation conforms to the clarifications of MPI-1.1 function behavior given in Chapter 3 of the MPI-2 document. Some implementations may require changes to be MPI-1 compliant.
- MPI-2 compliance will mean compliance with all of MPI-2.1.
- The MPI Journal of Development is not part of the MPI Standard.

It is to be emphasized that forward compatibility is preserved. That is, a valid MPI-1.1 program is both a valid MPI-1.3 program and a valid MPI-2.1 program, and a valid MPI-1.3 program is a valid MPI-2.1 program.

### 1.4 Background of MPI-1.3 and MPI-2.1

After the release of MPI-2.0, the MPI Forum kept working on errata and clarifications for both standard documents (MPI-1.1 and MPI-2.0). The short document "Errata for MPI-1.1" was released October 12, 1998. On July 5, 2001, a first ballot of errata and clarifications for MPI-2.0 was released, and a second ballot was voted on May 22, 2002. Both votes were done electronically. Both ballots were combined into one document: "Errata for MPI-2," May 15, 2002. This errata process was then interrupted, but the Forum and its e-mail reflectors kept working on new requests for clarification.

 Restarting regular work of the MPI Forum was initiated in three meetings, at EuroPVM/MPI'06 in Bonn, at EuroPVM/MPI'07 in Paris, and at SC'07 in Reno. In December 2007, a steering committee started the organization of new MPI Forum meetings at regular 8-weeks intervals. At the January 14–16, 2008 meeting in Chicago, the MPI Forum decided to combine the existing and future MPI documents to one document for each version of the MPI standard. For technical and historical reasons, this series was started with MPI-1.3. Additional Ballots 3 and 4 solved old questions from the errata list started in 1995 up to new questions from the last years. After all documents (MPI-1.1, MPI-2, Errata for MPI-1.1 (Oct. 12, 1998), and MPI-2.1 Ballots 1–4) were combined into one draft document, for each chapter, a chapter author and review team were defined. They cleaned up the document to achieve a consistent MPI-2.1 document. The final MPI-2.1 standard document was finished in June 2008, and finally released with a second vote in September 2008 in the meeting at Dublin, just before EuroPVM/MPI'08. The major work of the current MPI Forum is the preparation of MPI-3.

### 1.5 Background of MPI-2.2

MPI-2.2 is a minor update to the MPI-2.1 standard. This version addresses additional errors and ambiguities that were not corrected in the MPI-2.1 standard as well as a small number of extensions to MPI-2.1 that met the following criteria:

- Any correct MPI-2.1 program is a correct MPI-2.2 program.
- Any extension must have significant benefit for users.
- Any extension must not require significant implementation effort. To that end, all such changes are accompanied by an open source implementation.

The discussions of MPI-2.2 proceeded concurrently with the MPI-3 discussions; in some cases, extensions were proposed for MPI-2.2 but were later moved to MPI-3.

### 1.6 Background of MPI-3.0

MPI-3.0 is a major update to the MPI standard. The updates include the extension of collective operations to include nonblocking versions, extensions to the one-sided operations, and a new Fortran 2008 binding. In addition, the deprecated C++ bindings have been removed, as well as many of the deprecated routines and MPI objects (such as the MPI\_UB datatype).

### 1.7 Background of MPI-3.1

MPI-3.1 is a minor update to the MPI standard. Most of the updates are corrections and clarifications to the standard, especially for the Fortran bindings. New functions added include routines to manipulate MPI\_Aint values in a portable manner, nonblocking collective I/O routines, and routines to get the index value by name for MPI\_T performance and control variables. A general index was also added.

### 1.8 Background of 2020 Draft Specification

The 2020 draft specification is expected to become the MPI-4.0 specification once all features have been merged. MPI-4.0 is a major update to the MPI standard. This update includes a number of new features which will be present in the final MPI-4.0 document. The largest changes are then addition of persistent collectives, partitioned communications, application info assertions, and improvements to the definitions of error handling. In addition, there are a number of smaller improvements and corrections.

#### 1.9 Who Should Use This Standard?

This standard is intended for use by all those who want to write portable message-passing programs in Fortran and C (and access the C bindings from C++). This includes individual application programmers, developers of software designed to run on parallel machines, and creators of environments and tools. In order to be attractive to this wide audience, the standard must provide a simple, easy-to-use interface for the basic user while not semantically precluding the high-performance message-passing operations available on advanced machines.

### 1.10 What Platforms Are Targets for Implementation?

The attractiveness of the message-passing paradigm at least partially stems from its wide portability. Programs expressed this way may run on distributed-memory multiprocessors, networks of workstations, and combinations of all of these. In addition, shared-memory implementations, including those for multi-core processors and hybrid architectures, are possible. The paradigm will not be made obsolete by architectures combining the shared-and distributed-memory views, or by increases in network speeds. It thus should be both possible and useful to implement this standard on a great variety of machines, including those "machines" consisting of collections of other machines, parallel or not, connected by a communication network.

The interface is suitable for use by fully general MIMD programs, as well as those written in the more restricted style of SPMD. MPI provides many features intended to improve performance on scalable parallel computers with specialized interprocessor communication hardware. Thus, we expect that native, high-performance implementations of MPI will be provided on such machines. At the same time, implementations of MPI on top of standard Unix interprocessor communication protocols will provide portability to workstation clusters and heterogenous networks of workstations.

#### 1.11 What Is Included in the Standard?

The standard includes:

- Point-to-point communication,
- Datatypes,
- Collective operations,

**Unofficial Draft for Comment Only** 

- Process groups,
- Communication contexts,
- Process topologies,
- Environmental management and inquiry,
- The Info object,
- Process creation and management,
- One-sided communication,
- External interfaces,
- Parallel file I/O,
- Language bindings for Fortran and C,
- Tool support.

### 1.12 What Is Not Included in the Standard?

The standard does not specify:

- Operations that require more operating system support than is currently standard; for example, interrupt-driven receives, remote execution, or active messages,
- Program construction tools,
- Debugging facilities.

There are many features that have been considered and not included in this standard. This happened for a number of reasons, one of which is the time constraint that was self-imposed in finishing the standard. Features that are not included can always be offered as extensions by specific implementations. Perhaps future versions of MPI will address some of these issues.

### 1.13 Organization of This Document

The following is a list of the remaining chapters in this document, along with a brief description of each.

- Chapter 2, MPI Terms and Conventions, explains notational terms and conventions used throughout the MPI document.
- Chapter 3, Point-to-Point Communication, defines the basic, pairwise communication subset of MPI. Send and receive are found here, along with many associated functions designed to make basic communication powerful and efficient.
- Chapter 5, Datatypes, defines a method to describe any data layout, e.g., an array of structures in the memory, which can be used as message send or receive buffer.

- Chapter 6, Collective Communication, defines process-group collective communication operations. Well known examples of this are barrier and broadcast over a group of processes (not necessarily all the processes). With MPI-2, the semantics of collective communication was extended to include inter-communicators. It also adds two new collective operations. MPI-3 adds nonblocking collective operations.
- Chapter 7, Groups, Contexts, Communicators, and Caching, shows how groups of processes are formed and manipulated, how unique communication contexts are obtained, and how the two are bound together into a *communicator*.
- Chapter 8, Process Topologies, explains a set of utility functions meant to assist in the mapping of process groups (a linearly ordered set) to richer topological structures such as multi-dimensional grids.
- Chapter 9, MPI Environmental Management, explains how the programmer can manage and make inquiries of the current MPI environment. These functions are needed for the writing of correct, robust programs, and are especially important for the construction of highly-portable message-passing programs.
- Chapter 10, The Info Object, defines an opaque object, that is used as input in several MPI routines.
- Chapter 11, Process Initialization, Creation, and Management, defines routines that allow for creation of processes.
- Chapter 12, One-Sided Communications, defines communication routines that can be completed by a single process. These include shared-memory operations (put/get) and remote accumulate operations.
- Chapter 13, External Interfaces, defines routines designed to allow developers to layer on top of MPI. This includes generalized requests, routines that decode MPI opaque objects, and threads.
- Chapter 14, I/O, defines MPI support for parallel I/O.
- Chapter 15, Tool Support, covers interfaces that allow debuggers, performance analyzers, and other tools to obtain data about the operation of MPI processes. This chapter includes Section 15.2 (Profiling Interface), which was a chapter in previous versions of MPI.
- Chapter 16, Deprecated Interfaces, describes routines that are kept for reference. However usage of these functions is discouraged, as they may be deleted in future versions of the standard.
- Chapter 17, Removed Interfaces, describes routines and constructs that have been removed from MPI. Some of these were deprecated in MPI-2, and the MPI Forum decided to remove these from the MPI-3 standard. Others of these were deprecated in MPI-3, and the MPI Forum decided to remove these from the MPI-4 standard.
- Chapter 18, Backward Incompatibilities, describes incompatibilities with previous versions of MPI.

1

5 6

9 10

13 14 15

16

17

18

11

12

27 28 29

30

23

24

25 26

31 32 33

34

35 36 37

38

39

41 42

43

44 45

46

47

• Chapter 19, Language Bindings, discusses Fortran issues, and describes language interoperability aspects between C and Fortran.

The Appendices are:

- Annex A, Language Bindings Summary, gives specific syntax in C and Fortran, for all MPI functions, constants, and types.
- Annex B, Change-Log, summarizes some changes since the previous version of the standard.
- Several Index pages show the locations of examples, constants and predefined handles, declarations of C and Fortran types, callback routine prototypes, and all MPI functions.

MPI provides various interfaces to facilitate interoperability of distinct MPI implementations. Among these are the canonical data representation for MPI I/O and for MPI\_PACK\_EXTERNAL and MPI\_UNPACK\_EXTERNAL. The definition of an actual binding of these interfaces that will enable interoperability is outside the scope of this document.

A separate document consists of ideas that were discussed in the MPI Forum during the MPI-2 development and deemed to have value, but are not included in the MPI Standard. They are part of the "Journal of Development" (JOD), lest good ideas be lost and in order to provide a starting point for further work. The chapters in the JOD are

- Chapter 2, Spawning Independent Processes, includes some elements of dynamic process management, in particular management of processes with which the spawning processes do not intend to communicate, that the Forum discussed at length but ultimately decided not to include in the MPI Standard.
- Chapter 3, Threads and MPI, describes some of the expected interaction between an MPI implementation and a thread library in a multithreaded environment.
- Chapter 4, Communicator ID, describes an approach to providing identifiers for communicators.
- Chapter 5, Miscellany, discusses Miscellaneous topics in the MPI JOD, in particular single-copy routines for use in shared-memory environments and new datatype constructors.
- Chapter 6, Toward a Full Fortran 90 Interface, describes an approach to providing a more elaborate Fortran 90 interface.
- Chapter 7, Split Collective Communication, describes a specification for certain nonblocking collective operations.
- Chapter 8, Real-Time MPI, discusses MPI support for real time processing.

# Chapter 2

# MPI Terms and Conventions

This chapter explains notational terms and conventions used throughout the MPI document, some of the choices that have been made, and the rationale behind those choices.

#### 2.1 Document Notation

Rationale. Throughout this document, the rationale for the design choices made in the interface specification is set off in this format. Some readers may wish to skip these sections, while readers interested in interface design may want to read them carefully. (End of rationale.)

Advice to users. Throughout this document, material aimed at users and that illustrates usage is set off in this format. Some readers may wish to skip these sections, while readers interested in programming in MPI may want to read them carefully. (End of advice to users.)

Advice to implementors. Throughout this document, material that is primarily commentary to implementors is set off in this format. Some readers may wish to skip these sections, while readers interested in MPI implementations may want to read them carefully. (End of advice to implementors.)

### 2.2 Naming Conventions

In many cases MPI names for C functions are of the form MPI\_Class\_action\_subset. This convention originated with MPI-1. Since MPI-2 an attempt has been made to standardize the names of MPI functions according to the following rules.

- In C, all routines associated with a particular type of MPI object should be of the form MPI\_Class\_action\_subset or, if no subset exists, of the form MPI\_Class\_action. In Fortran, all routines associated with a particular type of MPI object should be of the form MPI\_CLASS\_ACTION\_SUBSET or, if no subset exists, of the form MPI\_CLASS\_ACTION.
- 2. If the routine is not associated with a class, the name should be of the form MPI\_Action\_subset in C and MPI\_ACTION\_SUBSET in Fortran.

 3. The names of certain actions have been standardized. In particular, **Create** creates a new object, **Get** retrieves information about an object, **Set** sets this information, **Delete** deletes information, **Is** asks whether or not an object has a certain property.

C and Fortran names for some MPI functions (that were defined during the MPI-1 process) violate these rules in several cases. The most common exceptions are the omission of the **Class** name from the routine and the omission of the **Action** where one can be inferred.

MPI identifiers are limited to 30 characters (31 with the profiling interface). This is done to avoid exceeding the limit on some compilation systems.

MPI identifiers are limited to 32 characters (35 with the profiling and large count interfaces, and Fortran specific procedure names upto 41). This is done to avoid exceeding the limit on some compilation systems.

#### 2.3 Procedure Specification

MPI procedures are specified using a language-independent notation. The arguments of procedure calls are marked as IN, OUT, or INOUT. The meanings of these are:

- IN: the call may use the input value but does not update the argument from the perspective of the caller at any time during the call's execution,
- OUT: the call may update the argument but does not use its input value,
- INOUT: the call may both use and update the argument.

There is one special case—if an argument is a handle to an opaque object (these terms are defined in Section 2.5.1), and the object is updated by the procedure call, then the argument is marked INOUT or OUT. It is marked this way even though the handle itself is not modified—we use the INOUT or OUT attribute to denote that what the handle references is updated.

Rationale. The definition of MPI tries to avoid, to the largest possible extent, the use of INOUT arguments, because such use is error-prone, especially for scalar arguments. (End of rationale.)

MPI's use of IN, OUT, and INOUT is intended to indicate to the user how an argument is to be used, but does not provide a rigorous classification that can be translated directly into all language bindings (e.g., INTENT in Fortran 90 bindings or const in C bindings). For instance, the "constant" MPI\_BOTTOM can usually be passed to OUT buffer arguments. Similarly, MPI\_STATUS\_IGNORE can be passed as the OUT status argument.

A common occurrence for MPI functions is an argument that is used as IN by some processes and OUT by other processes. Such an argument is, syntactically, an INOUT argument and is marked as such, although, semantically, it is not used in one call both for input and for output on a single process.

Another frequent situation arises when an argument value is needed only by a subset of the processes. When an argument is not significant at a process then an arbitrary value can be passed as an argument.

Unless specified otherwise, an argument of type OUT or type INOUT cannot be aliased with any other argument passed to an MPI procedure. An example of argument aliasing in C appears below. If we define a C procedure like this,

```
void copyIntBuffer(int *pin, int *pout, int len)
{    int i;
    for (i=0; i<len; ++i) *pout++ = *pin++;
}
then a call to it in the following code fragment has aliased arguments.
int a[10];
copyIntBuffer(a, a+3, 7);</pre>
```

Although the C language allows this, such usage of MPI procedures is forbidden unless otherwise specified. Note that Fortran prohibits aliasing of arguments.

All MPI functions are first specified in the language-independent notation. Immediately below this, language dependent bindings follow:

- The ISO C version of the function.
- The Fortran version used with USE mpi\_f08.
- The Fortran version of the same function used with USE mpi or INCLUDE 'mpif.h'.

An exception is Section 15.3 "The MPI Tool Information Interface", which only provides ISO C interfaces.

"Fortran" in this document refers to Fortran 90 and higher; see Section 2.6.

The words function, routine, procedure, procedure call, and call are often used as synonyms within this standard Some MPI procedures have two interfaces for a given language support (see Sections 2.5.6 and 2.5.8).

#### 2.4 Semantic Terms

When discussing MPI procedures the following semantic terms are used. The term **message** data buffer refers to the send/receive buffer used in a communication procedure. The term file data buffer refers to the data buffers used by MPI I/O procedures. In this section we use the term data buffer and depending on the MPI procedure it will refer to message data buffer or file data buffer.

#### 2.4.1 MPI Operations

**MPI** operation An MPI operation is a sequence of steps performed by the MPI library to establish and enable data transfer and/or synchronization. It consists of four stages: initialization, starting, completion, and freeing, and it is implemented as a set of one or more MPI procedures, see Section 2.4.2.

**Initialization** hands over the argument list to the operation but not the content of the data buffers, if any. The specification of an operation may state that array arguments must not be changed until the operation is freed.

**Starting** hands over the control of the data buffers, if any, to the associated operation.

Note that **initiation** refers to the combination of the initialization and starting stages.

#-other #-error!



9 10 11

12 13 14

15 16 17

18 19

20

23 24

21 22

26 27

28

25

29 30 31

32

33

34 35 36

37

38

39 40 41

42

43

44 45

46

47 48 Completion returns control of the content of the data buffers to the application and indicates that output buffers and arguments, if any, have been updated.

Note that an MPI operation is **complete** when the MPI procedure implementing the completion stage returns.

Freeing returns control of the rest of the argument list (e.g., the data buffer address and array arguments).

MPI operations are available in one or more of these forms: blocking, nonblocking, and persistent.

Blocking operation For a blocking operation, all four stages are combined in a single procedure call (as shown in Figure 2.1 and defined in Section 2.4.2).



Figure 2.1: State Transition Diagram for Blocking Operations

Nonblocking operation For a nonblocking operation, the initialization and starting stages are combined into a single nonblocking procedure call and the completion and freeing stages are combined into a separate, single procedure call, which can be blocking or nonblocking (as shown in Figure 2.2 and defined in Section 2.4.2).



Figure 2.2: State Transition Diagram for Nonblocking Operations

Persistent operation For a persistent operation, there is a separate procedure for each of the four stages (as shown in Figure 2.3 and defined in Section 2.4.2). Each of these procedures may be blocking or nonblocking.

For a partitioned send operation, an additional call to activate each partition of the send buffer (see Section 4.2.1) is required to finish the starting stage. For a partitioned receive operation, before the operation is complete the user is allowed to access a partition of the output buffer after verifying that it has arrived (see Section 4.2.2).

Additionally, an MPI operation can be collective or noncollective.

Collective operation Collective operations are defined as operations that involve a group or groups of MPI processes. For collective operations the completion stage may or may not finish before all processes in the group have started the operation.

Collective MPI operations are also available as blocking, nonblocking, or persistent operations.

**Noncollective operation** Noncollective operations are defined as operations that are not collective.



Figure 2.3: State Transition Diagram for Persistent Operations

#### 2.4.2 MPI Procedures

All MPI procedures can either be local or non-local - defined as follows:

Non-local procedure An MPI procedure is non-local if returning may require, during its execution, some specific semantically-related MPI procedure to be called on another MPI process.

Local procedure An MPI procedure is local if it is not non-local.

An MPI operation is implemented as a set of one or more MPI procedures. An MPI operation-related procedure implements at least a part of a stage of an MPI operation as described in Section 2.4.1. An MPI operation-related procedure may also implement one or more stages of one or several MPI operations. In certain cases, more than one MPI operation-related procedure may be needed to implement a single stage.

There are also other MPI procedures that do not implement any stage of any MPI operation.

The semantics of MPI operation-related procedures are described using two orthogonal (independent) concepts: completeness (depends on which stages are included) and locality. Such procedures can be either incomplete, or completing, or freeing, or completing and freeing based on the status of the associated operation at the time the procedure returns. Also, all such procedures can be described as either blocking or nonblocking, but these latter two terms refer to combinations of the completeness and locality concepts. Additionally, all MPI operation-related procedures can be collective or noncollective.

The following are properties of MPI operation-related procedures:

Initialization procedure An MPI procedure is an initialization procedure if return from the procedure indicates that the associated operation has completed its initialization stage, which implies that the user has handed over control of the argument list (but not contents of the data buffers) to MPI. The user is still allowed to read or modify the contents of the data buffers. If an initializing procedure is not also the freeing procedure of the associated operation (see below) then the user is not permitted to deallocate the data buffers or to modify the array arguments.

Starting procedure An MPI procedure is a starting procedure if return from the procedure indicates that the associated operation has completed its starting stage, which implies that the user has handed over control of the data buffers to MPI. If a starting procedure is not also a completing procedure of the associated operation (see below) then the user is not permitted to modify input data buffers or to read output data buffers.

#-error | 36 #-update6 38

Done

in PR449 **Initiation procedure** An MPI procedure is an **initiation procedure** if return from the procedure indicates that both the initialization and the starting stage have completed, which implies control of the entire argument list is handed over to MPI.

Completing procedure An MPI procedure is called **completing** if return from the procedure indicates that at least one associated operation has finished its completion stage, which implies that the user can rely on the content of the output data buffers and modify the content of input and output data buffers of such operation(s). If a completing procedure is not also a freeing procedure (see below) then the user is not permitted to deallocate the data buffers or to modify the array arguments.

**Incomplete procedure** An MPI procedure is called **incomplete** if it is not a completing procedure.

**Freeing procedure** An MPI procedure is **freeing** if return from the procedure indicates that at least one associated operation has finished its freeing stage, which implies that the user can reuse all parameters specified when initializing such associated operation(s).

Nonblocking procedure An MPI procedure is nonblocking if it is incomplete and local.

Blocking procedure An MPI procedure is blocking if it is not nonblocking.

Advice to users. Note that for operation-related MPI procedures, in most cases incomplete procedures are local and completing procedures are non-local. Exceptions are noted where such procedures are defined. In many cases an additional prefix letter I as an abbreviation of the words **incomplete** and **immediate** marks nonblocking procedures in the procedure name.

Some categorization examples are listed below.

Nonblocking procedures:

• incomplete and local: MPI\_ISEND, MPI\_IRECV, MPI\_IBCAST, MPI\_IMPROBE, MPI\_SEND\_INIT, MPI\_RECV\_INIT, ...

Blocking procedures:

- completing and non-local: MPI\_SEND, MPI\_RECV, MPI\_BCAST, ...
- incomplete and non-local: MPI\_MPROBE, MPI\_BCAST\_INIT, ..., MPI\_FILE\_{READ|WRITE}\_{AT\_ALL|ALL|ORDERED}\_BEGIN.
- completing and local: MPI\_BSEND, MPI\_RSEND, MPI\_MRECV.

MPI procedures that are not MPI operation-related:

• MPI\_COMM\_RANK, MPI\_WTIME, MPI\_PROBE, MPI\_IPROBE, ...

(End of advice to users.)

**Collective procedure** An MPI procedure is **collective** if all processes in a group or groups of MPI processes need to invoke the procedure.

Initialization procedures of collective operations over the same process group must be executed in the same order by all members of the process group.

**Unofficial Draft for Comment Only** 

The File routines end in the Function Index with \_FN instead of \_Begin -> to be fixed

An MPI collective procedure is **synchronizing** if it will only return once all processes in the associated group or groups of MPI processes have called the appropriate matching MPI procedure.

The initiation procedures for nonblocking collective operations and the starting procedures for persistent collective operations are local and shall not be synchronizing.

All other procedures for collective operations, such as for blocking collective operations and the initialization procedures for persistent collective operations, may or may not be synchronizing.

Advice to users. Calling any synchronizing function is erroneous when there is no possibility of corresponding calls at all other processes in the associated process group.

Waiting for completion of any collective operation is erroneous when there is no possibility that all other processes in the associated group will be able to start the corresponding operation. (*End of advice to users.*)

#### 2.4.3 MPI Datatypes

For datatypes, the following terms are defined:

predefined A predefined datatype is a datatype with a predefined (constant) name (such as MPI\_INT, MPI\_FLOAT\_INT, or MPI\_PACKED) or a datatype constructed with MPI\_TYPE\_CREATE\_F90\_INTEGER, MPI\_TYPE\_CREATE\_F90\_REAL, or MPI\_TYPE\_CREATE\_F90\_COMPLEX. The former are named whereas the latter are unnamed.

**derived** A derived datatype is any datatype that is not predefined.

**portable** A datatype is portable if it is a predefined datatype, or it is derived from a portable datatype using only the type constructors MPI\_TYPE\_CONTIGUOUS, MPI\_TYPE\_VECTOR, MPI\_TYPE\_INDEXED,

MPI\_TYPE\_CREATE\_INDEXED\_BLOCK, MPI\_TYPE\_CREATE\_SUBARRAY,

MPI\_TYPE\_DUP, and MPI\_TYPE\_CREATE\_DARRAY. Such a datatype is portable because all displacements in the datatype are in terms of extents of one predefined datatype. Therefore, if such a datatype fits a data layout in one memory, it will fit the corresponding data layout in another memory, if the same declarations were used, even if the two systems have different architectures. On the other hand, if a datatype was constructed using MPI\_TYPE\_CREATE\_HINDEXED,

MPI\_TYPE\_CREATE\_HINDEXED\_BLOCK, MPI\_TYPE\_CREATE\_HVECTOR or MPI\_TYPE\_CREATE\_STRUCT, then the datatype contains explicit byte displacements (e.g., providing padding to meet alignment restrictions). These displacements are unlikely to be chosen correctly if they fit data layout on one memory, but are used for data layouts on another process, running on a processor with a different architecture.

**equivalent** Two datatypes are equivalent if they appear to have been created with the same sequence of calls (and arguments) and thus have the same typemap. Two equivalent datatypes do not necessarily have the same cached attributes or the same names.

### 2.5 Data Types

#### 2.5.1 Opaque Objects

MPI manages **system memory** that is used for buffering messages and for storing internal representations of various MPI objects such as groups, communicators, datatypes, etc. This memory is not directly accessible to the user, and objects stored there are **opaque**: their size and shape is not visible to the user. Opaque objects are accessed via **handles**, which exist in user space. MPI procedures that operate on opaque objects are passed handle arguments to access these objects. In addition to their use by MPI calls for object access, handles can participate in assignments and comparisons.

In Fortran with USE mpi or INCLUDE 'mpif.h', all handles have type INTEGER. In Fortran with USE mpi\_f08, and in C, a different handle type is defined for each category of objects. With Fortran USE mpi\_f08, the handles are defined as Fortran BIND(C) derived types that consist of only one element INTEGER: MPI\_VAL. The internal handle value is identical to the Fortran INTEGER value used in the mpi module and mpif.h. The operators .EQ., .NE., == and /= are overloaded to allow the comparison of these handles. The type names are identical to the names in C, except that they are not case sensitive. For example:

TYPE, BIND(C) :: MPI\_Comm
INTEGER :: MPI\_VAL
END TYPE MPI\_Comm

The C types must support the use of the assignment and equality operators.

Advice to implementors. In Fortran, the handle can be an index into a table of opaque objects in a system table; in C it can be such an index or a pointer to the object. (End of advice to implementors.)

Rationale. Since the Fortran integer values are equivalent, applications can easily convert MPI handles between all three supported Fortran methods. For example, an integer communicator handle COMM can be converted directly into an exactly equivalent mpi\_f08 communicator handle named comm\_f08 by comm\_f08%MPI\_VAL=COMM, and vice versa. The use of the INTEGER defined handles and the BIND(C) derived type handles is different: Fortran 2003 (and later) define that BIND(C) derived types can be used within user defined common blocks, but it is up to the rules of the companion C compiler how many numerical storage units are used for these BIND(C) derived type handles. Most compilers use one unit for both, the INTEGER handles and the handles defined as BIND(C) derived types. (End of rationale.)

Advice to users. If a user wants to substitute mpif.h or the mpi module by the mpi\_f08 module and the application program stores a handle in a Fortran common block then it is necessary to change the Fortran support method in all application routines that use this common block, because the number of numerical storage units of such a handle can be different in the two modules. (End of advice to users.)

Opaque objects are allocated and deallocated by calls that are specific to each object type. These are listed in the sections where the objects are described. The calls accept a handle argument of matching type. In an allocate call this is an OUT argument that returns

2.5. DATA TYPES 17

a valid reference to the object. In a call to deallocate this is an INOUT argument which returns with an "invalid handle" value. MPI provides an "invalid handle" constant for each object type. Comparisons to this constant are used to test for validity of the handle.

A call to a deallocate routine invalidates the handle and marks the object for deallocation. The object is not accessible to the user after the call. However, MPI need not deallocate the object immediately. Any operation pending (at the time of the deallocate) that involves this object will complete normally; the object will be deallocated afterwards. An opaque object and its handle are significant only at the process where the object was created and cannot be transferred to another process.

MPI provides certain predefined opaque objects and predefined, static handles to these objects. The user must not free such objects.

Rationale. This design hides the internal representation used for MPI data structures, thus allowing similar calls in C and Fortran. It also avoids conflicts with the typing rules in these languages, and easily allows future extensions of functionality. The mechanism for opaque objects used here loosely follows the POSIX Fortran binding standard.

The explicit separation of handles in user space and objects in system space allows space-reclaiming and deallocation calls to be made at appropriate points in the user program. If the opaque objects were in user space, one would have to be very careful not to go out of scope before any pending operation requiring that object completed. The specified design allows an object to be marked for deallocation, the user program can then go out of scope, and the object itself still persists until any pending operations are complete.

The requirement that handles support assignment/comparison is made since such operations are common. This restricts the domain of possible implementations. The alternative in C would have been to allow handles to have been an arbitrary, opaque type. This would force the introduction of routines to do assignment and comparison, adding complexity, and was therefore ruled out. In Fortran, the handles are defined such that assignment and comparison are available through the operators of the language or overloaded versions of these operators. (*End of rationale*.)

Advice to users. A user may accidentally create a dangling reference by assigning to a handle the value of another handle, and then deallocating the object associated with these handles. Conversely, if a handle variable is deallocated before the associated object is freed, then the object becomes inaccessible (this may occur, for example, if the handle is a local variable within a subroutine, and the subroutine is exited before the associated object is deallocated). It is the user's responsibility to avoid adding or deleting references to opaque objects, except as a result of MPI calls that allocate or deallocate such objects. (End of advice to users.)

Advice to implementors. The intended semantics of opaque objects is that opaque objects are separate from one another; each call to allocate such an object copies all the information required for the object. Implementations may avoid excessive copying by substituting referencing for copying. For example, a derived datatype may contain references to its components, rather than copies of its components; a call to MPI\_COMM\_GROUP may return a reference to the group associated with the communicator, rather than a copy of this group. In such cases, the implementation

must maintain reference counts, and allocate and deallocate objects in such a way that the visible effect is as if the objects were copied. (End of advice to implementors.)

#### 2.5.2 Array Arguments

An MPI call may need an argument that is an array of opaque objects, or an array of handles. The array-of-handles is a regular array with entries that are handles to objects of the same type in consecutive locations in the array. Whenever such an array is used, an additional len argument is required to indicate the number of valid entries (unless this number can be derived otherwise). The valid entries are at the beginning of the array; len indicates how many of them there are, and need not be the size of the entire array. The same approach is followed for other array arguments. In some cases NULL handles are considered valid entries. When a NULL argument is desired for an array of statuses, one uses MPI\_STATUSES\_IGNORE.

#### 2.5.3 State

MPI procedures use at various places arguments with *state* types. The values of such a data type are all identified by names, and no operation is defined on them. For example, the MPI\_TYPE\_CREATE\_SUBARRAY routine has a state argument order with values MPI\_ORDER\_C and MPI\_ORDER\_FORTRAN.

#### 2.5.4 Named Constants

MPI procedures sometimes assign a special meaning to a special value of a basic type argument; e.g., tag is an integer-valued argument of point-to-point communication operations, with a special wild-card value, MPI\_ANY\_TAG. Such arguments will have a range of regular values, which is a proper subrange of the range of values of the corresponding basic type; special values (such as MPI\_ANY\_TAG) will be outside the regular range. The range of regular values, such as tag, can be queried using environmental inquiry functions, see Chapter 9. The range of other values, such as source, depends on values given by other MPI routines (in the case of source it is the communicator size).

MPI also provides predefined named constant handles, such as MPI\_COMM\_WORLD.

All named constants, with the exceptions noted below for Fortran, can be used in initialization expressions or assignments, but not necessarily in array declarations or as labels in C switch or Fortran select/case statements. This implies named constants to be link-time but not necessarily compile-time constants. The named constants listed below are required to be compile-time constants in both C and Fortran. These constants do not change values during execution. Opaque objects accessed by constant handles are defined and do not change value between MPI initialization (MPI\_INIT) and MPI completion (MPI\_FINALIZE). The handles themselves are constants and can be also used in initialization expressions or assignments.

The constants that are required to be compile-time constants (and can thus be used for array length declarations and labels in C switch and Fortran case/select statements)

2.5. DATA TYPES 19

are: MPI\_MAX\_PROCESSOR\_NAME MPI\_MAX\_LIBRARY\_VERSION\_STRING MPI\_MAX\_ERROR\_STRING MPI\_MAX\_DATAREP\_STRING MPI\_MAX\_INFO\_KEY MPI\_MAX\_INFO\_VAL MPI\_MAX\_OBJECT\_NAME MPI\_MAX\_PORT\_NAME MPI\_VERSION MPI\_SUBVERSION MPI\_F\_STATUS\_SIZE (C only) MPI\_STATUS\_SIZE (Fortran only) MPI\_ADDRESS\_KIND (Fortran only) MPI\_COUNT\_KIND (Fortran only) MPI\_INTEGER\_KIND (Fortran only) MPI\_OFFSET\_KIND (Fortran only) MPI\_SUBARRAYS\_SUPPORTED (Fortran only) MPI\_ASYNC\_PROTECTS\_NONBLOCKING (Fortran only) The constants that cannot be used in initialization expressions or assignments in Fortran are as follows: MPI\_BOTTOM MPI\_STATUS\_IGNORE MPI\_STATUSES\_IGNORE MPI\_ERRCODES\_IGNORE MPI\_IN\_PLACE MPI\_ARGV\_NULL MPI\_ARGVS\_NULL MPI\_UNWEIGHTED MPI\_WEIGHTS\_EMPTY

11

12

13 14

15

16

17

18

19

20 21

22

23

24

26

27

28

29 30

33

34

35

36

37

39 40

41 42

43

44

45

46

47

Advice to implementors. In Fortran the implementation of these special constants may require the use of language constructs that are outside the Fortran standard. Using special values for the constants (e.g., by defining them through PARAMETER statements) is not possible because an implementation cannot distinguish these values from valid data. Typically, these constants are implemented as predefined static variables (e.g., a variable in an MPI-declared COMMON block), relying on the fact that the target compiler passes data by address. Inside the subroutine, this address can be extracted by some mechanism outside the Fortran standard (e.g., by Fortran extensions or by implementing the function in C). (End of advice to implementors.)

#### 2.5.5 Choice

MPI functions sometimes use arguments with a *choice* (or union) data type. Distinct calls to the same routine may pass by reference actual arguments of different types. The mechanism for providing such arguments will differ from language to language. For Fortran with the include file mpif.h or the mpi module, the document uses <type> to represent a choice variable; with the Fortran mpi\_f08 module, such arguments are declared with the Fortran 2008 + TS 29113 syntax TYPE(\*), DIMENSION(..); for C, we use void\*.

Advice to implementors. Implementors can freely choose how to implement choice arguments in the mpi module, e.g., with a non-standard compiler-dependent method that has the quality of the call mechanism in the implicit Fortran interfaces, or with the method defined for the mpi\_f08 module. See details in Section 19.1.1. (End of advice to implementors.)

#### 2.5.6 Absolute Addresses and Relative Address Displacements

Some MPI procedures use address arguments that represent an absolute address in the calling program, or relative displacement arguments that represent differences of two absolute addresses. The datatype of such arguments is MPI\_Aint in C and INTEGER (KIND=MPI\_ADDRESS\_KIND) in Fortran. These types must have the same width and encode address values in the same manner such that address values in one language may be passed directly to another language without conversion. There is the MPI constant MPI\_BOTTOM to indicate the start of the address range. For retrieving absolute addresses or any calculation with absolute addresses, one should use the routines and functions provided in Section 5.1.5. Section 5.1.12 provides additional rules for the correct use of absolute addresses. For expressions with relative displacements or other usage without absolute addresses, intrinsic operators (e.g., +, -, \*) can be used.

Rationale. Byte displacement values need to be large enough to encode any value used for expressing absolute or relative memory addresses. Prior to MPI-4.0, some MPI routines used int in C and INTEGER in Fortran as the type for byte displacement arguments. To avoid breaking backward compatibility, this version of the standard continues to support int in C as well as INTEGER in Fortran in such routines. In addition, this version of the standard supports using MPI\_Aint in C (via separate "\_c" suffixed procedures) as well as INTEGER (KIND=MPI\_ADDRESS\_KIND) in Fortran (via polymorphic interfaces in newer MPI Fortran bindings (USE mpi\_f08)) in such routines. See Section 19.2 for a full explanation. (End of rationale.)

#### 2.5.7 File Offsets

For I/O there is a need to give the size, displacement, and offset into a file. These quantities can easily be larger than 32 bits which can be the default size of a Fortran integer. To overcome this, these quantities are declared to be INTEGER(KIND=MPI\_OFFSET\_KIND) in Fortran. In C one uses MPI\_Offset. These types must have the same width and encode address values in the same manner such that offset values in one language may be passed directly to another language without conversion.

#### 2.5.8 Counts

As described above, MPI defines types (e.g., MPI\_Aint) to address locations within memory and other types (e.g., MPI\_Offset) to address locations within files. In addition, some MPI procedures use *count* arguments that represent a number of MPI datatypes on which to operate. Furthermore, *timestamps* in the context of the MPI Tool Information Interface are a count of clock ticks elapsed since some time in the past. At times, one needs a single type that can be used to address locations within either memory or files as well as express *count* values, and that type is MPI\_Count in C and INTEGER(KIND=MPI\_COUNT\_KIND) in Fortran. These types must have the same width and encode values in the same manner

such that count values in one language may be passed directly to another language without conversion. The size of the MPI\_Count type is determined by the MPI implementation with the restriction that it must be minimally capable of encoding any value that may be stored in a variable of type int, MPI\_Aint, or MPI\_Offset in C and of type INTEGER, INTEGER (KIND=MPI\_ADDRESS\_KIND), or INTEGER (KIND=MPI\_OFFSET\_KIND) in Fortran. Even though the MPI\_Count type is large enough to encode address locations, MPI\_Count type shall not be used to represent an absolute address.

Rationale. Count values need to be large enough to encode any value used for expressing element counts, stride, offset, index, displacement, typemaps in memory, typemaps in file views, etc. Prior to MPI-4.0, many MPI routines used int in C and INTEGER in Fortran as the type for *count* arguments. To avoid breaking backward compatibility, this version of the standard continues to support

int in C as well as INTEGER in Fortran in such routines. In addition, this version of the standard supports using MPI\_Count in C (via separate "\_c"suffixed procedures) as well as INTEGER (KIND=MPI\_COUNT\_KIND) in Fortran (via polymorphic interfaces in newer MPI Fortran bindings (USE mpi\_f08)) in such routines. See Section 19.2 for a full explanation. (End of rationale.)

The phrase large count refers to the use of MPI\_Count and INTEGER (KIND=MPI\_COUNT\_KIND) parameter types.

There are cases where MPI\_UNDEFINED can be returned in a large count OUT parameter. Per Table A.1.1 (page 847), the MPI\_UNDEFINED constant is defined to be a C int (or unnamed enum) and a Fortran INTEGER. Implementations shall therefore choose the underlying types for MPI\_Count and INTEGER(KIND=MPI\_COUNT\_KIND) such that they can be compared to MPI\_UNDEFINED.

Advice to implementors. The comparison of MPI\_UNDEFINED to an MPI\_Count or INTEGER(KIND=MPI\_COUNT\_KIND) may need to be via a casting operation. (End of advice to implementors.)

### 2.6 Language Binding

This section defines the rules for MPI language binding in general and for Fortran, and ISO C, in particular. (Note that ANSI C has been replaced by ISO C.) Defined here are various object representations, as well as the naming conventions used for expressing this standard. The actual calling sequences are defined elsewhere.

MPI bindings are for Fortran 90 or later, though they were originally designed to be usable in Fortran 77 environments. With the mpi\_f08 module, two new Fortran features, assumed type and assumed rank, are also required, see Section 2.5.5.

Since the word PARAMETER is a keyword in the Fortran language, we use the word "argument" to denote the arguments to a subroutine. These are normally referred to as parameters in C, however, we expect that C programmers will understand the word "argument" (which has no specific meaning in C), thus allowing us to avoid unnecessary confusion for Fortran programmers.

Since Fortran is case insensitive, linkers may use either lower case or upper case when resolving Fortran names. Users of case sensitive languages should avoid any prefix of the form "MPI\_" and "PMPI\_", where any of the letters are either upper or lower case.

#-other

1

#-other 12 13

#-other Done

15

16

29

30

37

38

39

40

41

42

43

44

45

46

47 48

21

22

23

\mpifunc{MPI\_ COMM\_NULL\_ COPY\_FN} #-error

#-update5

Done in PR449

#### 2.6.1 Deprecated and Removed Interfaces

A number of chapters refer to deprecated or replaced MPI constructs. These are constructs that continue to be part of the MPI standard, as documented in Chapter 16, but that users are recommended not to continue using, since better solutions were provided with newer versions of MPI. For example, the Fortran binding for MPI-1 functions that have address arguments uses INTEGER. This is not consistent with the C binding, and causes problems on machines with 32 bit INTEGERs and 64 bit addresses. In MPI-2, these functions were given new names with new bindings for the address arguments. The use of the old functions was declared as deprecated. For consistency, here and in a few other cases, new C functions are also provided, even though the new functions are equivalent to the old functions. The old names are deprecated. previously

Some of the deprecated constructs are now removed, as documented in Chapter 17. They may still be provided by an implementation for backwards compatibility, but are not required.

Table 2.1 shows a list of all of the deprecated and removed constructs. Note that some C typedefs and Fortran subroutine names are included in this list; they are the types of callback functions.

#### 2.6.2 Fortran Binding Issues

Originally, MPI-1.1 provided bindings for Fortran 77. These bindings are retained, but they are now interpreted in the context of the Fortran 90 standard. MPI can still be used with most Fortran 77 compilers, as noted below. When the term "Fortran" is used it means Fortran 90 or later; it means Fortran 2008 + TS 29113 and later if the mpi\_f08 module is used.

All MPI names have an MPI\_ prefix, and all characters are capitals. Programs must not declare names, e.g., for variables, subroutines, functions, parameters, derived types, abstract interfaces, or modules, beginning with the prefix MPI\_. To avoid conflicting with the profiling interface, programs must also avoid subroutines and functions with the prefix PMPI\_. This is mandated to avoid possible name collisions.

All MPI Fortran subroutines have a return code in the last argument. With USE mpi\_f08, this last argument is declared as OPTIONAL, except for user-defined callback functions (e.g., COMM\_COPY\_ATTR\_FUNCTION) and their predefined callbacks (e.g.,

MPI\_NULL\_COPY\_FN). A few MPI operations which are functions do not have the return code argument. The return code value for successful completion is MPI\_SUCCESS. Other error codes are implementation dependent; see the error codes in Chapter 9 and Annex A.

Constants representing the maximum length of a string are one smaller in Fortran than in C as discussed in Section 19.3.9.

Handles are represented in Fortran as INTEGERS, or as a BIND(C) derived type with the mpi\_f08 module; see Section 2.5.1. Binary-valued variables are of type LOGICAL.

Array arguments are indexed from one.

The older MPI Fortran bindings (mpif.h and use mpi) are inconsistent with the Fortran standard in several respects. These inconsistencies, such as register optimization problems, have implications for user codes that are discussed in detail in Section 19.1.16.

The support for large count and displacement in Fortran is only available when using newer MPI Fortran bindings (USE mpi\_f08).

			other mp/mpii.n caliback		#-erro	r
2.6. LANGUAGE BINDING	T J	I.	totypesFUNCTION are missing in	23	#-upd	ate3
		the	callback index			
					Done i	n
Deprecated or removed	deprecated	removed	Replacement		1 A.1.3	
construct	since	since			<sub>2</sub> and A.	1.4
MPI_ADDRESS	MPI-2.0	MPI-3.0	MPI_GET_ADDRESS		<sub>3</sub> Done	
MPI_TYPE_HINDEXED	MPI-2.0	MPI-3.0	MPI_TYPE_CREATE_HINDEXED		in all	
MPI_TYPE_HVECTOR	MPI-2.0	MPI-3.0	MPI_TYPE_CREATE_HVECTOR		4 norma	al
MPI_TYPE_STRUCT	MPI-2.0	MPI-3.0	MPI_TYPE_CREATE_STRUCT		5 chapt	ers
MPI_TYPE_EXTENT	MPI-2.0	MPI-3.0	MPI_TYPE_GET_EXTENT		6 PR44	
MPI_TYPE_UB	MPI-2.0	MPI-3.0	MPI_TYPE_GET_EXTENT		7	
MPI_TYPE_LB	MPI-2.0	MPI-3.0	MPI_TYPE_GET_EXTENT			
$MPI\_LB^1$	MPI-2.0	MPI-3.0	MPI_TYPE_CREATE_RESIZED		8	
MPI_UB <sup>1</sup>	MPI-2.0	MPI-3.0	MPI_TYPE_CREATE_RESIZED		9	
MPI_ERRHANDLER_CREATE	MPI-2.0	MPI-3.0	MPI_COMM_CREATE_ERRHANDL	ER	Done .	
MPI_ERRHANDLER_GET	MPI-2.0	MPI-3.0	MPI_COMM_GET_ERRHANDLER		in	
MPI_ERRHANDLER_SET	MPI-2.0	MPI-3.0	MPI_COMM_SET_ERRHANDLER		auuiii	
MPI_Handler_function <sup>2</sup>	MPI-2.0	MPI-3.0	MPI_Comm_errhandler_function <sup>2</sup>		12   I com	mit
MPI_KEYVAL_CREATE	MPI-2.0	0.0	MPI_COMM_CREATE_KEYVAL		13 of	
MPI_KEYVAL_FREE	MPI-2.0		MPI_COMM_FREE_KEYVAL		PR44	.9
MPI_DUP_FN <sup>3</sup>	MPI-2.0		MPI_COMM_DUP_FN <sup>3</sup>		NCTION:	
MPI_NULL_COPY_FN <sup>3</sup>	MPI-2.0		MPI_COMM_NULL_COPY_FN <sup>3</sup>	Footno	ote must be 2	<u> </u>
MPI_NULL_DELETE_FN <sup>3</sup>	MPI-2.0		MPI_COMM_NULL_DELETE_FN <sup>3</sup>		<sup>16</sup> #-error	ſ
MPI_Copy_function <sup>2</sup>	MPI-2.0		MPI_Comm_copy_attr_function <sup>2</sup>		17	
COPY_FUNCTION <sup>3</sup>	Wrong macro is use	d	COMM_COPY_ATTR_FUNCTION <sup>3</sup>		#-upda	ate/
MPI_Delete_function <sup>2</sup>	Caused Function ins		MPI_Comm_delete_attr_function <sup>2</sup>		<sub>19</sub> #-oth	er
DELETE_FUNCTION <sup>3</sup>	of Callback Index!	sieau	COMM_DELETE_ATTR_FUNCTION	VI <sup>3</sup>	19	
MPI_ATTR_DELETE	MPI-2.0		MPI_COMM_DELETE_ATTR	<u> </u>	<sub>20</sub> #-erro	_
MPI_ATTR_BELLTE MPI_ATTR_GET	MPI-2.0		MPI_COMM_GET_ATTR		21 Done	е
MPI_ATTR_GET MPI_ATTR_PUT	MPI-2.0		MPI_COMM_SET_ATTR		22	
MPI_COMBINER_HVECTOR_INTE		MPI-3.0	MPI_COMBINER_HVECTOR <sup>4</sup>		23	
		MPI-3.0	MPI_COMBINER_HVECTOR  MPI_COMBINER_HINDEXED <sup>4</sup>			
MPI_COMBINER_HINDEXED_INTE					24	
MPI_COMBINER_STRUCT_INTEGI		MPI-3.0	MPI_COMBINER_STRUCT <sup>4</sup>		25	
MPI::	MPI-2.2	MPI-3.0	C language binding		26	
MPI_CANCEL for send requests	MPI-3.2 4.0	)	no direct replacement		27	
MPI_INFO_GET	MPI-4.0		MPI_INFO_GET_STRING			
MPI_INFO_GET_VALUELEN	MPI-4.0		MPI_INFO_GET_STRING		28	
MPI_T_ERR_INVALID_ITEM	MPI-3.2 4.0		MPI_T_ERR_INVALID_INDEX		29	
MPI_SIZEOF	MPI-4.0	<b>*</b>	storage_size() $^5$ and c_sizeof()		30 #-oth	er
Predefined datatype.					31 Done	1
<sup>2</sup> Callback prototype definition.						1
<sup>3</sup> Predefined callback routine.					32	
4 Constant. storage_size()					33	
<sup>5</sup> Fortran intrinsic. It returns the		of bytes.			34	
Other entries are regular MPI ro	utines.				35	

All other mpi/mpif.h callback

#-error

Table 2.1: Deprecated and Removed constructs

#### 2.6.3 C Binding Issues

We use the ISO C declaration format. All MPI names have an MPI\_ prefix, defined constants are in all capital letters, and defined types and functions have one capital letter after the prefix. Programs must not declare names (identifiers), e.g., for variables, functions, constants, types, or macros, beginning with any prefix of the form MPI\_, where any of the letters are either upper or lower case. To support the profiling interface, programs must not declare functions with names beginning with any prefix of the form PMPI\_, where any of the letters are either upper or lower case.

The definition of named constants, function prototypes, and type definitions must be

supplied in an include file mpi.h.

Almost all C functions return an error code. The successful return code will be MPI\_SUCCESS, but failure return codes are implementation dependent.

Type declarations are provided for handles to each category of opaque objects.

Array arguments are indexed from zero.

Logical flags are integers with value 0 meaning "false" and a non-zero value meaning "true."

Choice arguments are pointers of type void\*.

#### 2.6.4 Functions and Macros

An implementation is allowed to implement MPI\_WTIME, PMPI\_WTIME, MPI\_WTICK, PMPI\_WTICK, MPI\_AINT\_ADD, PMPI\_AINT\_ADD, MPI\_AINT\_DIFF, PMPI\_AINT\_DIFF, and the handle-conversion functions (MPI\_Group\_f2c, etc.) in Section 19.3.4, and no others, as macros in C.

Advice to implementors. Implementors should document which routines are implemented as macros. (End of advice to implementors.)

Advice to users. If these routines are implemented as macros, they will not work with the MPI profiling interface. (End of advice to users.)

#### 2.7 Processes

An MPI program consists of autonomous processes, executing their own code, in an MIMD style. The codes executed by each process need not be identical. The processes communicate via calls to MPI communication primitives. Typically, each process executes in its own address space, although shared-memory implementations of MPI are possible.

This document specifies the behavior of a parallel program assuming that only MPI calls are used. The interaction of an MPI program with other possible means of communication, I/O, and process management is not specified. Unless otherwise stated in the specification of the standard, MPI places no requirements on the result of its interaction with external mechanisms that provide similar or equivalent functionality. This includes, but is not limited to, interactions with external mechanisms for process control, shared and remote memory access, file system access and control, interprocess communication, process signaling, and terminal I/O. High quality implementations should strive to make the results of such interactions intuitive to users, and attempt to document restrictions where deemed necessary.

Advice to implementors. Implementations that support such additional mechanisms for functionality supported within MPI are expected to document how these interact with MPI. (End of advice to implementors.)

The interaction of MPI and threads is defined in Section 11.6.

### 2.8 Error Handling

MPI provides the user with reliable message transmission. A message sent is always received correctly, and the user does not need to check for transmission errors, time-outs,

or other error conditions. In other words, MPI does not provide mechanisms for dealing with **transmission failures** in the communication system. If the MPI implementation is built on an unreliable underlying mechanism, then it is the job of the implementor of the MPI subsystem to insulate the user from this unreliability, and to reflect only unrecoverable transmission failures. Whenever possible, such failures will be reflected as errors in the relevant communication call.

Similarly, MPI itself provides no mechanisms for handling MPI process failures, that is, when an MPI process unexpectedly and permanently stops communicating (e.g., a software or hardware crash results in an MPI process terminating unexpectedly).

Of course, MPI programs may still be erroneous. A **program error** can occur when an MPI call is made with an incorrect argument (non-existing destination in a send operation, buffer too small in a receive operation, etc.). This type of error would occur in any implementation. In addition, a **resource error** may occur when a program exceeds the amount of available system resources (number of pending messages, system buffers, etc.). The occurrence of this type of error depends on the amount of available resources in the system and the resource allocation mechanism used; this may differ from system to system. A high-quality implementation will provide generous limits on the important resources so as to alleviate the portability problem this represents.

In C and Fortran, almost all MPI calls return a code that indicates successful completion of the operation. Whenever possible, MPI calls return an error code if an error occurred during the call. By default, an error detected during the execution of the MPI library causes the parallel computation to abort, except for file operations. However, MPI provides mechanisms for users to change this default and to handle recoverable errors. The user may specify that no error is fatal, and handle error codes returned by MPI calls by himself or herself. Also, the user may provide his or her own error-handling routines, which will be invoked whenever an MPI call returns abnormally. The MPI error handling facilities are described in Section 9.3.

Several factors limit the ability of MPI calls to return with meaningful error codes when an error occurs. MPI may not be able to detect some errors; other errors may be too expensive to detect in normal execution mode; some faults (e.g., memory faults) may corrupt the state of the MPI library and its outputs; finally some errors may be "catastrophic" and may prevent MPI from returning control to the caller. On the other hand, some errors may be detected after the associated operation has completed; some errors may not have a communicator, window, or file on which an error may be raised. In such cases, these errors will be raised on the communicator MPI\_COMM\_SELF. When MPI\_COMM\_SELF is not initialized (i.e., before MPI\_INIT\_THREAD or after MPI\_FINALIZE) the error raises the **initial error handler** (set during the launch operation, see 11.8.4).

An example of such a case arises because of the nature of asynchronous communications: MPI calls may initiate operations that continue asynchronously after the call returned. Thus, the operation may return with a code indicating successful completion, yet later cause an error to be raised. If there is a subsequent call that relates to the same operation (e.g., a call that verifies that an asynchronous operation has completed) then the error argument associated with this call will be used to indicate the nature of the error. In a few cases, the error may occur after all calls that relate to the operation have completed, so that no error value can be used to indicate the nature of the error (e.g., an error on the receiver in a send with the ready mode).

This document does not specify the state of a computation after an erroneous MPI call has occurred. The desired behavior is that a relevant error code be returned, and the effect

of the error be localized to the greatest possible extent. E.g., it is highly desirable that an erroneous receive call will not cause any part of the receiver's memory to be overwritten, beyond the area specified for receiving the message.

Implementations may go beyond this document in supporting in a meaningful manner MPI calls that are defined here to be erroneous. For example, MPI specifies strict type matching rules between matching send and receive operations: it is erroneous to send a floating point variable and receive an integer. Implementations may go beyond these type matching rules, and provide automatic type conversion in such situations. It will be helpful to generate warnings for such non-conforming behavior.

MPI defines a way for users to create new error codes as defined in Section 9.5.

### 2.9 Implementation Issues

There are a number of areas where an MPI implementation may interact with the operating environment and system. While MPI does not mandate that any services (such as signal handling) be provided, it does strongly suggest the behavior to be provided if those services are available. This is an important point in achieving portability across platforms that provide the same set of services.

#### 2.9.1 Independence of Basic Runtime Routines

MPI programs require that library routines that are part of the basic language environment (such as write in Fortran and printf and malloc in ISO C) and are executed after MPI\_INIT and before MPI\_FINALIZE operate independently and that their *completion* is independent of the action of other processes in an MPI program.

Note that this in no way prevents the creation of library routines that provide parallel services whose operation is collective. However, the following program is expected to complete in an ISO C environment regardless of the size of MPI\_COMM\_WORLD (assuming that printf is available at the executing nodes).

```
int rank;
MPI_Init((void *)0, (void *)0);
MPI_Comm_rank(MPI_COMM_WORLD, &rank);
if (rank == 0) printf("Starting program\n");
MPI_Finalize();
```

The corresponding Fortran programs are also expected to complete.

An example of what is *not* required is any particular ordering of the action of these routines when called by several tasks. For example, MPI makes neither requirements nor recommendations for the output from the following program (again assuming that I/O is available at the executing nodes).

```
MPI_Comm_rank(MPI_COMM_WORLD, &rank);
printf("Output from task rank %d\n", rank);
```

In addition, calls that fail because of resource exhaustion or other error are not considered a violation of the requirements here (however, they are required to complete, just not to complete successfully).

2.10. EXAMPLES 27


#### 2.9.2 Interaction with Signals


MPI does not specify the interaction of processes with signals and does not require that MPI be signal safe. The implementation may reserve some signals for its own use. It is required that the implementation document which signals it uses, and it is strongly recommended that it not use SIGALRM, SIGFPE, or SIGIO. Implementations may also prohibit the use of MPI calls from within signal handlers.

In multithreaded environments, users can avoid conflicts between signals and the MPI library by catching signals only on threads that do not execute MPI calls. High quality single-threaded implementations will be signal safe: an MPI call suspended by a signal will resume and complete normally after the signal is handled.

### 2.10 Examples

The examples in this document are for illustration purposes only. They are not intended to specify the standard. Furthermore, the examples have not been carefully checked or verified.





## Chapter 3

# Point-to-Point Communication

#### 3.1 Introduction

Sending and receiving of messages by processes is the basic MPI communication mechanism. The basic point-to-point communication operations are **send** and **receive**. Their use is illustrated in the example below.

```
#include "mpi.h"
int main(int argc, char *argv[])
  char message[20];
  int myrank;
 MPI_Status status;
 MPI_Init(&argc, &argv);
 MPI_Comm_rank(MPI_COMM_WORLD, &myrank);
  if (myrank == 0)
                      /* code for process zero */
      strcpy(message, "Hello, there")
      MPI_Send(message, strlen(message)+1, MPI_CHAR, 1, 99, MPI_COMM_WORLD);
  }
  else if (myrank == 1) /* code for process one */
      MPI_Recv(message, 20, MPI_CHAR, 0, 99, MPI_COMM_WORLD, &status);
      printf("received :%s:\n", message);
 MPI_Finalize()
  return 0;
}
```

In this example, process zero (myrank = 0) sends a message to process one using the send operation MPI\_SEND. The operation specifies a send buffer in the sender memory from which the message data is taken. In the example above, the send buffer consists of the storage containing the variable message in the memory of process zero. The location, size and type of the send buffer are specified by the first three parameters of the send operation. The message sent will contain the 13 characters of this variable. In addition, the send operation associates an envelope with the message. This envelope specifies the

12 13 14

15 16

18

19 20

21

22 23

26

27

28

30

33

34 35

36

37

42

43 44

> 45 46

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17 18

19 20

21

22 23 24

25 26

27

28

29

30 31

32

33

34 35

36

37

38 39

40

41

42

message destination and contains distinguishing information that can be used by the **receive** operation to select a particular message. The last three parameters of the send operation, along with the rank of the sender, specify the envelope for the message sent. Process one (myrank = 1) receives this message with the **receive** operation MPI\_RECV. The message to be received is selected according to the value of its envelope, and the message data is stored into the **receive buffer**. In the example above, the receive buffer consists of the storage containing the string message in the memory of process one. The first three parameters of the receive operation specify the location, size and type of the receive buffer. The next three parameters are used for selecting the incoming message. The last parameter is used to return information on the message just received.

The next sections describe the blocking send and receive operations. We discuss send, receive, blocking communication semantics, type matching requirements, type conversion in heterogeneous environments, and more general communication modes. Nonblocking communication is addressed next, followed by probing and canceling a message, channel-like constructs and send-receive operations, ending with a description of the "dummy" process, MPI\_PROC\_NULL.

### 3.2 Blocking Send and Receive Operations

#### 3.2.1 Blocking Send

The syntax of the blocking send operation is given below.

```
MPI_SEND(buf, count, datatype, dest, tag, comm)
```

```
IN
           buf
                                           initial address of send buffer (choice)
IN
                                           number of elements in send buffer (non-negative
           count
                                           integer)
                                           datatype of each send buffer element (handle)
IN
           datatype
IN
           dest
                                           rank of destination (integer)
                                           message tag (integer)
IN
           tag
IN
           comm
                                           communicator (handle)
```

#### C binding

#### Fortran 2008 binding

```
MPI_Send(buf, count, datatype, dest, tag, comm, ierror)
TYPE(*), DIMENSION(..), INTENT(IN) :: buf
INTEGER, INTENT(IN) :: count, dest, tag
TYPE(MPI_Datatype), INTENT(IN) :: datatype
TYPE(MPI_Comm), INTENT(IN) :: comm
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

int dest, int tag, MPI\_Comm comm)

```
MPI_Send(buf, count, datatype, dest, tag, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: dest, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI_SEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)
    <type> BUF(*)
    INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR
```

The blocking semantics of this call are described in Section 3.4.

#### 3.2.2 Message Data

The send buffer specified by the MPI\_SEND operation consists of count successive entries of the type indicated by datatype, starting with the entry at address buf. Note that we specify the message length in terms of number of *elements*, not number of *bytes*. The former is machine independent and closer to the application level.

The data part of the message consists of a sequence of count values, each of the type indicated by datatype. count may be zero, in which case the data part of the message is empty. The basic datatypes that can be specified for message data values correspond to the basic datatypes of the host language. Possible values of this argument for Fortran and the corresponding Fortran types are listed in Table 3.1.

MPI datatype	Fortran datatype
MPI_INTEGER	INTEGER
MPI_REAL	REAL
MPI_DOUBLE_PRECISION	DOUBLE PRECISION
MPI_COMPLEX	COMPLEX
MPI_LOGICAL	LOGICAL
MPI_CHARACTER	CHARACTER(1)
MPI_BYTE	
MPI_PACKED	

Table 3.1: Predefined MPI datatypes corresponding to Fortran datatypes

Possible values for this argument for C and the corresponding C types are listed in Table 3.2.

The datatypes MPI\_BYTE and MPI\_PACKED do not correspond to a Fortran or C datatype. A value of type MPI\_BYTE consists of a byte (8 binary digits). A byte is uninterpreted and is different from a character. Different machines may have different representations for characters, or may use more than one byte to represent characters. On the other hand, a byte has the same binary value on all machines. The use of the type MPI\_PACKED is explained in Section 5.2.

MPI requires support of these datatypes, which match the basic datatypes of Fortran and ISO C. Additional MPI datatypes should be provided if the host language has additional

1	MPI datatype	C datatype
2	MPI_CHAR	char
3		(treated as printable character)
4	MPI_SHORT	signed short int
5	MPI_INT	signed int
6	MPI_LONG	signed long int
7	MPI_LONG_LONG_INT	signed long long int
8	MPI_LONG_LONG (as a synonym)	signed long long int
9	MPI_SIGNED_CHAR	signed char
10		(treated as integral value)
11	MPI_UNSIGNED_CHAR	unsigned char
12		(treated as integral value)
13	MPI_UNSIGNED_SHORT	unsigned short int
14	MPI_UNSIGNED	unsigned int
15	MPI_UNSIGNED_LONG	unsigned long int
16	MPI_UNSIGNED_LONG_LONG	unsigned long long int
17	MPI_FLOAT	float
18	MPI_DOUBLE	double
19	MPI_LONG_DOUBLE	long double
20	MPI_WCHAR	wchar_t
21		(defined in <stddef.h>)</stddef.h>
22		(treated as printable character)
23	MPI_C_BOOL	_Bool
24	MPI_INT8_T	int8_t
25	MPI_INT16_T	int16_t
26	MPI_INT32_T	int32_t
27	MPI_INT64_T	int64_t
28	MPI_UINT8_T	uint8_t
29	MPI_UINT16_T	uint16_t
30	MPI_UINT32_T	uint32_t
31	MPI_UINT64_T	uint64_t
32	MPI_C_COMPLEX	float _Complex
33	MPI_C_FLOAT_COMPLEX (as a synonym)	float _Complex
34	MPI_C_DOUBLE_COMPLEX	double _Complex
35	MPI_C_LONG_DOUBLE_COMPLEX	long double _Complex
36	MPI_BYTE	
37	MPI_PACKED	

Table 3.2: Predefined MPI datatypes corresponding to C datatypes

 $^{46}$ 

data types<sup>1</sup>: MPI\_DOUBLE\_COMPLEX for double precision complex in Fortran declared to be of type DOUBLE COMPLEX; MPI\_REAL2, MPI\_REAL4, MPI\_REAL8, and MPI\_REAL16 for Fortran reals, declared to be of type REAL\*2, REAL\*4, REAL\*8, and REAL\*16, respectively; MPI\_INTEGER1, MPI\_INTEGER2, MPI\_INTEGER4, and

<sup>&</sup>lt;sup>1</sup>These types, such as DOUBLE COMPLEX and INTEGER\*4, are not specified by any Fortran standard but are extensions commonly accepted by Fortran compilers.

MPI datatype	C datatype	Fortran datatype
MPI_AINT	MPI_Aint	INTEGER (KIND=MPI_ADDRESS_KIND)
MPI_OFFSET	MPI_Offset	<pre>INTEGER (KIND=MPI_OFFSET_KIND)</pre>
MPI_COUNT	MPI_Count	INTEGER (KIND=MPI_COUNT_KIND)

Table 3.3: Predefined MPI datatypes corresponding to both C and Fortran datatypes

MPI\_INTEGER8 for Fortran integers, declared to be of type INTEGER\*1, INTEGER\*2, INTEGER\*4, and INTEGER\*8, respectively; MPI\_COMPLEX4, MPI\_COMPLEX8, MPI\_COMPLEX16, and MPI\_COMPLEX32 for complex numbers in Fortran declared to be of type COMPLEX\*4, COMPLEX\*8, COMPLEX\*16, and COMPLEX\*32, respectively; etc.

Rationale. One goal of the design is to allow for MPI to be implemented as a library, with no need for additional preprocessing or compilation. Thus, one cannot assume that a communication call has information on the datatype of variables in the communication buffer; this information must be supplied by an explicit argument. The need for such datatype information will become clear in Section 3.3.2. (End of rationale.)

The datatypes MPI\_AINT, MPI\_OFFSET, and MPI\_COUNT correspond to the MPI-defined C types MPI\_Aint, MPI\_Offset, and MPI\_Count and their Fortran equivalents INTEGER (KIND=MPI\_ADDRESS\_KIND), INTEGER (KIND=MPI\_OFFSET\_KIND), and INTEGER (KIND=MPI\_COUNT\_KIND). This is described in Table 3.3. All predefined datatype handles are available in all language bindings. See Sections 19.3.6 and 19.3.10 on page 834 and 842 for information on interlanguage communication with these types.

If there is an accompanying C++ compiler then the datatypes in Table 3.4 are also supported in C and Fortran.

	MPI datatype	C++ datatype
Ì	MPI_CXX_BOOL	bool
Ì	MPI_CXX_FLOAT_COMPLEX	std::complex <float></float>
	MPI_CXX_DOUBLE_COMPLEX	std::complex <double></double>
ĺ	MPI_CXX_LONG_DOUBLE_COMPLEX	std::complex <long double=""></long>

Table 3.4: Predefined MPI datatypes corresponding to C++ datatypes

# 3.2.3 Message Envelope

In addition to the data part, messages carry information that can be used to distinguish messages and selectively receive them. This information consists of a fixed number of fields, which we collectively call the **message envelope**. These fields are

source destination tag communicator

The message source is implicitly determined by the identity of the message sender. The other fields are specified by arguments in the send operation.

The message destination is specified by the dest argument.

The integer-valued message tag is specified by the tag argument. This integer can be used by the program to distinguish different types of messages. The range of valid tag values is  $0, \ldots, \mathsf{UB}$ , where the value of  $\mathsf{UB}$  is implementation dependent. It can be found by querying the value of the attribute  $\mathsf{MPI\_TAG\_UB}$ , as described in Chapter 9.  $\mathsf{MPI}$  requires that  $\mathsf{UB}$  be no less than 32767.

The **comm** argument specifies the **communicator** that is used for the send operation. Communicators are explained in Chapter 7; below is a brief summary of their usage.

A communicator specifies the communication context for a communication operation. Each communication context provides a separate "communication universe": messages are always received within the context they were sent, and messages sent in different contexts do not interfere.

The communicator also specifies the set of processes that share this communication context. This **process group** is ordered and processes are identified by their rank within this group. Thus, the range of valid values for **dest** is  $0, \ldots, n-1 \cup \{\text{MPI\_PROC\_NULL}\}$ , where n is the number of processes in the group. (If the communicator is an inter-communicator, then destinations are identified by their rank in the remote group. See Chapter 7.)

When using the World Model (see Section 11.1), a predefined communicator MPI\_COMM\_WORLD is provided by MPI. It allows communication with all processes that are accessible after MPI initialization and processes are identified by their rank in the group of MPI\_COMM\_WORLD.

Advice to users. Users that are comfortable with the notion of a flat name space for processes, and a single communication context, as offered by most existing communication libraries, need only use the World Model for MPI initialization, and the predefined variable MPI\_COMM\_WORLD as the comm argument. This will allow communication with all the processes available at initialization time.

Users may define new communicators, as explained in Chapter 7. Communicators provide an important encapsulation mechanism for libraries and modules. They allow modules to have their own disjoint communication universe and their own process numbering scheme. (*End of advice to users*.)

Advice to implementors. The message envelope would normally be encoded by a fixed-length message header. However, the actual encoding is implementation dependent. Some of the information (e.g., source or destination) may be implicit, and need not be explicitly carried by messages. Also, processes may be identified by relative ranks, or absolute ids, etc. (End of advice to implementors.)

# 3.2.4 Blocking Receive

The syntax of the blocking receive operation is given below.

45 46

47

```
MPI_RECV(buf, count, datatype, source, tag, comm, status)
  OUT
           buf
                                      initial address of receive buffer (choice)
  IN
                                      number of elements in receive buffer (non-negative
           count
                                      integer)
  IN
           datatype
                                      datatype of each receive buffer element (handle)
                                      rank of source or MPI_ANY_SOURCE (integer)
  IN
           source
  IN
                                      message tag or MPI_ANY_TAG (integer)
           tag
  IN
                                      communicator (handle)
           comm
                                                                                        11
  OUT
           status
                                      status object (Status)
                                                                                        12
                                                                                        13
C binding
                                                                                        14
int MPI_Recv(void *buf, int count, MPI_Datatype datatype, int source,
                                                                                        15
              int tag, MPI_Comm comm, MPI_Status *status)
                                                                                        16
int MPI_Recv_c(void *buf, MPI_Count count, MPI_Datatype datatype,
              int source, int tag, MPI_Comm comm, MPI_Status *status)
                                                                                        18
                                                                                        19
Fortran 2008 binding
                                                                                       20
MPI_Recv(buf, count, datatype, source, tag, comm, status, ierror)
                                                                                       21
    TYPE(*), DIMENSION(..) :: buf
                                                                                       22
    INTEGER, INTENT(IN) :: count, source, tag
                                                                                       23
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                        24
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Status) :: status
                                                                                        26
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       27
MPI_Recv(buf, count, datatype, source, tag, comm, status, ierror)
                                                                                       28
    TYPE(*), DIMENSION(..) :: buf
                                                                                       29
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                        30
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                        31
    INTEGER, INTENT(IN) :: source, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                        33
    TYPE(MPI_Status) :: status
                                                                                       34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       35
                                                                                       36
Fortran binding
                                                                                       37
MPI_RECV(BUF, COUNT, DATATYPE, SOURCE, TAG, COMM, STATUS, IERROR)
    <type> BUF(*)
    INTEGER COUNT, DATATYPE, SOURCE, TAG, COMM, STATUS(MPI_STATUS_SIZE),
               IERROR
                                                                                       41
                                                                                       42
    The blocking semantics of this call are described in Section 3.4.
    The receive buffer consists of the storage containing count consecutive elements of the
                                                                                       43
```

The receive buffer consists of the storage containing count consecutive elements of the type specified by datatype, starting at address buf. The length of the received message must be less than or equal to the length of the receive buffer. An overflow error occurs if all incoming data does not fit, without truncation, into the receive buffer.

If a message that is shorter than the receive buffer arrives, then only those locations corresponding to the (shorter) message are modified.

5 6

9 10

15

21

22

23

37

38

39

31

32

41 42 43

44 45

46 47

48

3.2.5

Return Status

The source or tag of a received message may not be known if wildcard values were used in the receive operation. Also, if multiple requests are completed by a single MPI function

Advice to users. The MPI\_PROBE function described in Section 3.8 can be used to receive messages of unknown length. (End of advice to users.)

Advice to implementors. Even though no specific behavior is mandated by MPI for erroneous programs, the recommended handling of overflow situations is to return in status information about the source and tag of the incoming message. The receive operation will return an error code. A quality implementation will also ensure that no memory that is outside the receive buffer will ever be overwritten.

In the case of a message shorter than the receive buffer, MPI is quite strict in that it allows no modification of the other locations. A more lenient statement would allow for some optimizations but this is not allowed. The implementation must be ready to end a copy into the receiver memory exactly at the end of the receive buffer, even if it is an odd address. (End of advice to implementors.)

The selection of a message by a receive operation is governed by the value of the message envelope. A message can be received by a receive operation if its envelope matches the source, tag and comm values specified by the receive operation. The receiver may specify a wildcard MPI\_ANY\_SOURCE value for source, and/or a wildcard MPI\_ANY\_TAG value for tag, indicating that any source and/or tag are acceptable. It cannot specify a wildcard value for comm. Thus, a message can be received by a receive operation only if it is addressed to the receiving process, has a matching communicator, has matching source unless source = MPI\_ANY\_SOURCE in the pattern, and has a matching tag unless tag = MPI\_ANY\_TAG in the pattern.

The message tag is specified by the tag argument of the receive operation. argument source, if different from MPI\_ANY\_SOURCE, is specified as a rank within the process group associated with that same communicator (remote process group, for intercommunicators). Thus, the range of valid values for the source argument is  $\{0,\ldots,n-1\}\cup$  $\{MPI\_ANY\_SOURCE\}\cup\{MPI\_PROC\_NULL\}, \text{ where } n \text{ is the number of processes in this group.}$ 

Note the asymmetry between send and receive operations: A receive operation may accept messages from an arbitrary sender, on the other hand, a send operation must specify a unique receiver. This matches a "push" communication mechanism, where data transfer is effected by the sender (rather than a "pull" mechanism, where data transfer is effected by the receiver).

Source = destination is allowed, that is, a process can send a message to itself. However, it is unsafe to do so with the blocking send and receive operations described above, since this may lead to deadlock. See Section 3.5.

Advice to implementors. Message context and other communicator information can be implemented as an additional tag field. It differs from the regular message tag in that wild card matching is not allowed on this field, and that value setting for this field is controlled by communicator manipulation functions. (End of advice to implementors.)

The use of dest = MPI\_PROC\_NULL or source = MPI\_PROC\_NULL to define a "dummy" destination or source in any send or receive call is described in Section 3.10.

(see Section 3.7.5), a distinct error code may need to be returned for each request. The information is returned by the status argument of MPI\_RECV. The type of status is MPI-defined. Status variables need to be explicitly allocated by the user, that is, they are not system objects.

In C, status is a structure that contains three fields named MPI\_SOURCE, MPI\_TAG, and MPI\_ERROR; the structure may contain additional fields. Thus, status.MPI\_SOURCE, status.MPI\_TAG and status.MPI\_ERROR contain the source, tag, and error code, respectively, of the received message.

In Fortran with USE mpi or INCLUDE 'mpif.h', status is an array of INTEGERs of size MPI\_STATUS\_SIZE. The constants MPI\_SOURCE, MPI\_TAG and MPI\_ERROR are the indices of the entries that store the source, tag and error fields. Thus, status(MPI\_SOURCE), status(MPI\_TAG) and status(MPI\_ERROR) contain, respectively, the source, tag and error code of the received message.

With Fortran USE mpi\_f08, status is defined as the Fortran BIND(C) derived type TYPE(MPI\_Status) containing three public INTEGER fields named MPI\_SOURCE, MPI\_TAG, and MPI\_ERROR. TYPE(MPI\_Status) may contain additional, implementation-specific fields. Thus, status%MPI\_SOURCE, status%MPI\_TAG and status%MPI\_ERROR contain the source, tag, and error code of a received message respectively. Additionally, within both the mpi and the mpi\_f08 modules, the constants MPI\_STATUS\_SIZE, MPI\_SOURCE, MPI\_TAG, MPI\_ERROR, and TYPE(MPI\_Status) are defined to allow conversion between both

status representations. Conversion routines are provided in Section 19.3.5.

Rationale. The Fortran TYPE(MPI\_Status) is defined as a BIND(C) derived type so that it can be used at any location where the status integer array representation can be used, e.g., in user defined common blocks. (End of rationale.)

Rationale. It is allowed to have the same name (e.g., MPI\_SOURCE) defined as a constant (e.g., Fortran parameter) and as a field of a derived type. (End of rationale.)

In general, message-passing calls do not modify the value of the error code field of status variables. This field may be updated only by the functions in Section 3.7.5 which return multiple statuses. The field is updated if and only if such function returns with an error code of MPI\_ERR\_IN\_STATUS.

Rationale. The error field in status is not needed for calls that return only one status, such as MPI\_WAIT, since that would only duplicate the information returned by the function itself. The current design avoids the additional overhead of setting it, in such cases. The field is needed for calls that return multiple statuses, since each request may have had a different failure. (End of rationale.)

The status argument also returns information on the length of the message received. However, this information is not directly available as a field of the status variable and a call to MPI\_GET\_COUNT is required to "decode" this information.

2

3

4 5

6 7

8

9

10

11

12 13

14

15

16

17

18

19

20

21

22

23

24 25

26

27

28

29

30

31

32

33 34

35

36

37

38

39

41

42

43

44

45

46

47

```
MPI_GET_COUNT(status, datatype, count)
 IN
          status
                                     return status of receive operation (Status)
 IN
          datatype
                                     datatype of each receive buffer entry (handle)
 OUT
                                     number of received entries (integer)
          count
C binding
int MPI_Get_count(const MPI_Status *status, MPI_Datatype datatype,
              int *count)
int MPI_Get_count_c(const MPI_Status *status, MPI_Datatype datatype,
              MPI_Count *count)
Fortran 2008 binding
MPI_Get_count(status, datatype, count, ierror)
    TYPE(MPI_Status), INTENT(IN) :: status
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(OUT) :: count
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Get_count(status, datatype, count, ierror)
    TYPE(MPI_Status), INTENT(IN) :: status
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: count
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_GET_COUNT(STATUS, DATATYPE, COUNT, IERROR)
```

Returns the number of entries received. (Again, we count *entries*, each of type *datatype*, not *bytes*.) The datatype argument should match the argument provided by the receive call that set the status variable. If the number of entries received exceeds the limits of the count parameter, then MPI\_GET\_COUNT sets the value of count to MPI\_UNDEFINED. There are other situations where the value of count can be set to MPI\_UNDEFINED; see Section 5.1.11.

INTEGER STATUS(MPI\_STATUS\_SIZE), DATATYPE, COUNT, IERROR

Rationale. Some message-passing libraries use INOUT count, tag and source arguments, thus using them both to specify the selection criteria for incoming messages and return the actual envelope values of the received message. The use of a separate status argument prevents errors that are often attached with INOUT argument (e.g., using the MPI\_ANY\_TAG constant as the tag in a receive). Some libraries use calls that refer implicitly to the "last message received." This is not thread safe.

The datatype argument is passed to MPI\_GET\_COUNT so as to improve performance. A message might be received without counting the number of elements it contains, and the count value is often not needed. Also, this allows the same function to be used after a call to MPI\_PROBE or MPI\_IPROBE. With a status from MPI\_PROBE or MPI\_IPROBE, the same datatypes are allowed as in a call to MPI\_RECV to receive this message. (*End of rationale*.)

The value returned as the count argument of MPI\_GET\_COUNT for a datatype of length zero where zero bytes have been transferred is zero. If the number of bytes transferred is greater than zero, MPI\_UNDEFINED is returned.

Rationale. Zero-length datatypes may be created in a number of cases. An important case is MPI\_TYPE\_CREATE\_DARRAY, where the definition of the particular darray results in an empty block on some MPI process. Programs written in an SPMD style will not check for this special case and may want to use MPI\_GET\_COUNT to check the status. (End of rationale.)

Advice to users. The buffer size required for the receive can be affected by data conversions and by the stride of the receive datatype. In most cases, the safest approach is to use the same datatype with MPI\_GET\_COUNT and the receive. (End of advice to users.)

All send and receive operations use the buf, count, datatype, source, dest, tag, comm, and status arguments in the same way as the blocking MPI\_SEND and MPI\_RECV operations described in this section.

# 3.2.6 Passing MPI\_STATUS\_IGNORE for Status

Every call to MPI\_RECV includes a status argument, wherein the system can return details about the message received. There are also a number of other MPI calls where status is returned. An object of type MPI\_Status is not an MPI opaque object; its structure is declared in mpi.h and mpif.h, and it exists in the user's program. In many cases, application programs are constructed so that it is unnecessary for them to examine the status fields. In these cases, it is a waste for the user to allocate a status object, and it is particularly wasteful for the MPI implementation to fill in fields in this object.

To cope with this problem, there are two predefined constants, MPI\_STATUS\_IGNORE and MPI\_STATUSES\_IGNORE, which when passed to a receive, probe, wait, or test function, inform the implementation that the status fields are not to be filled in. Note that MPI\_STATUS\_IGNORE is not a special type of MPI\_Status object; rather, it is a special value for the argument. In C one would expect it to be NULL, not the address of a special MPI\_Status.

MPI\_STATUS\_IGNORE, and the array version MPI\_STATUSES\_IGNORE, can be used everywhere a status argument is passed to a receive, wait, or test function. MPI\_STATUS\_IGNORE cannot be used when status is an IN argument. Note that in Fortran MPI\_STATUS\_IGNORE and MPI\_STATUSES\_IGNORE are objects like MPI\_BOTTOM (not usable for initialization or assignment). See Section 2.5.4.

In general, this optimization can apply to all functions for which status or an array of statuses is an OUT argument. Note that this converts status into an INOUT argument. The functions that can be passed MPI\_STATUS\_IGNORE are all the various forms of MPI\_RECV, MPI\_PROBE, MPI\_TEST, and MPI\_WAIT, as well as MPI\_REQUEST\_GET\_STATUS. When an array is passed, as in the MPI\_{TEST|WAIT}{ALL|SOME} functions, a separate constant, MPI\_STATUSES\_IGNORE, is passed for the array argument. It is possible for an MPI function to return MPI\_ERR\_IN\_STATUS even when MPI\_STATUS\_IGNORE or MPI\_STATUSES\_IGNORE has been passed to that function.

MPI\_STATUS\_IGNORE and MPI\_STATUSES\_IGNORE are not required to have the same values in C and Fortran.

It is not allowed to have some of the statuses in an array of statuses for  $MPI_{TEST|WAIT}_{ALL|SOME}$  functions set to  $MPI_{STATUS_{IGNORE}}$ ; one either specifies ignoring all of the statuses in such a call with  $MPI_{STATUSES_{IGNORE}}$ , or none of them by passing normal statuses in all positions in the array of statuses.

# 3.2.7 Send-Receive

The **send-receive** operations combine in one call the sending of a message to one destination and the receiving of another message, from another process. The two (source and destination) are possibly the same. A send-receive operation is very useful for executing a shift operation across a chain of processes. If blocking sends and receives are used for such a shift, then one needs to order the sends and receives correctly (for example, even processes send, then receive, odd processes receive first, then send) so as to prevent cyclic dependencies that may lead to deadlock. When a send-receive operation is used, the communication subsystem takes care of these issues. The send-receive operation can be used in conjunction with the functions described in Chapter 8 in order to perform shifts on various logical topologies. Also, a send-receive operation is useful for implementing remote procedure calls.

A message sent by a send-receive operation can be received by a regular receive operation or probed by a probe operation; a send-receive operation can receive a message sent by a regular send operation.

MPI\_SENDRECV(sendbuf, sendcount, sendtype, dest, sendtag, recvbuf, recvcount, recvtype, source, recvtag, comm, status)

IN	sendbuf	initial address of send buffer (choice)
IN	sendcount	number of elements in send buffer (non-negative integer)
IN	sendtype	type of elements in send buffer (handle)
IN	dest	rank of destination (integer)
IN	sendtag	send tag (integer)
OUT	recvbuf	initial address of receive buffer (choice)
1N	recvcount	number of elements in receive buffer (non-negative
		integer)
IN	recvtype	integer) type of elements receive buffer element (handle)
IN IN	recvtype source	,
		type of elements receive buffer element (handle)
IN	source	type of elements receive buffer element (handle) rank of source or MPI_ANY_SOURCE (integer)

#### C binding

MPI\_Datatype recvtype, int source, int recvtag, MPI\_Comm comm,
MPI\_Status \*status)

#### Fortran 2008 binding

#### Fortran binding

```
MPI_SENDRECV(SENDBUF, SENDCOUNT, SENDTYPE, DEST, SENDTAG, RECVBUF,
RECVCOUNT, RECVTYPE, SOURCE, RECVTAG, COMM, STATUS, IERROR)
<type> SENDBUF(*), RECVBUF(*)
INTEGER SENDCOUNT, SENDTYPE, DEST, SENDTAG, RECVCOUNT, RECVTYPE,
SOURCE, RECVTAG, COMM, STATUS(MPI_STATUS_SIZE), IERROR
```

Execute a blocking send and receive operation. Both send and receive use the same communicator, but possibly different tags. The send buffer and receive buffers must be disjoint, and may have different lengths and datatypes.

The semantics of a send-receive operation is what would be obtained if the caller forked two concurrent threads, one to execute the send, and one to execute the receive, followed by a join of these two threads.

# MPI\_SENDRECV\_REPLACE(buf, count, datatype, dest, sendtag, source, recvtag, comm, status)

INOUT	buf	initial address of send and receive buffer (choice)
IN	count	number of elements in send and receive buffer (non-negative integer)
IN	datatype	type of elements in send and receive buffer (handle)
IN	dest	rank of destination (integer)
IN	sendtag	send message tag (integer)
IN	source	${\rm rank\ of\ source\ or\ MPI\_ANY\_SOURCE\ (integer)}$
IN	recvtag	receive message tag or $MPI\_ANY\_TAG$ (integer)
IN	comm	communicator (handle)
OUT	status	status object (Status)

#### C binding

2

3

4

5

6

11

17

18

19

20

21 22 23

24 25

26

27 28

29 30

31

32 33

34

35

36

37

38

39

41

42

43

44

45

46

47

48

#### Fortran 2008 binding MPI\_Sendrecv\_replace(buf, count, datatype, dest, sendtag, source, recvtag, comm, status, ierror) TYPE(\*), DIMENSION(..) :: buf INTEGER, INTENT(IN) :: count, dest, sendtag, source, recvtag TYPE(MPI\_Datatype), INTENT(IN) :: datatype TYPE(MPI\_Comm), INTENT(IN) :: comm TYPE(MPI\_Status) :: status INTEGER, OPTIONAL, INTENT(OUT) :: ierror 10 Fortran binding MPI\_SENDRECV\_REPLACE(BUF, COUNT, DATATYPE, DEST, SENDTAG, SOURCE, RECVTAG, 12 COMM, STATUS, IERROR) 13 <type> BUF(\*) 14 INTEGER COUNT, DATATYPE, DEST, SENDTAG, SOURCE, RECVTAG, COMM, 15 STATUS(MPI\_STATUS\_SIZE), IERROR 16

Execute a blocking send and receive. The same buffer is used both for the send and for the receive, so that the message sent is replaced by the message received.

Advice to implementors. Additional intermediate buffering is needed for the "replace" variant. (End of advice to implementors.)

#### Data Type Matching and Data Conversion 3.3

#### Type Matching Rules 3.3.1

One can think of message transfer as consisting of the following three phases.

- 1. Data is pulled out of the send buffer and a message is assembled.
- 2. A message is transferred from sender to receiver.
- 3. Data is pulled from the incoming message and disassembled into the receive buffer.

Type matching has to be observed at each of these three phases: The type of each variable in the sender buffer has to match the type specified for that entry by the send operation; the type specified by the send operation has to match the type specified by the receive operation; and the type of each variable in the receive buffer has to match the type specified for that entry by the receive operation. A program that fails to observe these three rules is erroneous.

To define type matching more precisely, we need to deal with two issues: matching of types of the host language with types specified in communication operations; and matching of types at sender and receiver.

The types of a send and receive match (phase two) if both operations use identical names. That is, MPI\_INTEGER matches MPI\_INTEGER, MPI\_REAL matches MPI\_REAL, and so on. There is one exception to this rule, discussed in Section 5.2: the type MPI\_PACKED can match any other type.

The type of a variable in a host program matches the type specified in the communication operation if the datatype name used by that operation corresponds to the basic

type of the host program variable. For example, an entry with type name MPI\_INTEGER matches a Fortran variable of type INTEGER. A table giving this correspondence for Fortran and C appears in Section 3.2.2. There are two exceptions to this last rule: an entry with type name MPI\_BYTE or MPI\_PACKED can be used to match any byte of storage (on a byte-addressable machine), irrespective of the datatype of the variable that contains this byte. The type MPI\_PACKED is used to send data that has been explicitly packed, or receive data that will be explicitly unpacked, see Section 5.2. The type MPI\_BYTE allows one to transfer the binary value of a byte in memory unchanged.

To summarize, the type matching rules fall into the three categories below.

- Communication of typed values (e.g., with datatype different from MPI\_BYTE), where the datatypes of the corresponding entries in the sender program, in the send call, in the receive call and in the receiver program must all match.
- Communication of untyped values (e.g., of datatype MPl\_BYTE), where both sender and receiver use the datatype MPl\_BYTE. In this case, there are no requirements on the types of the corresponding entries in the sender and the receiver programs, nor is it required that they be the same.
- Communication involving packed data, where MPI\_PACKED is used.

The following examples illustrate the first two cases.

# **Example 3.1** Sender and receiver specify matching types.

```
CALL MPI_COMM_RANK(comm, rank, ierr)
IF (rank .EQ. 0) THEN
   CALL MPI_SEND(a(1), 10, MPI_REAL, 1, tag, comm, ierr)
ELSE IF (rank .EQ. 1) THEN
   CALL MPI_RECV(b(1), 15, MPI_REAL, 0, tag, comm, status, ierr)
END IF
```

This code is correct if both a and b are real arrays of size  $\geq 10$ . (In Fortran, it might be correct to use this code even if a or b have size < 10: e.g., when a(1) can be equivalenced to an array with ten reals.)

#### **Example 3.2** Sender and receiver do not specify matching types.

```
CALL MPI_COMM_RANK(comm, rank, ierr)
IF (rank .EQ. 0) THEN
   CALL MPI_SEND(a(1), 10, MPI_REAL, 1, tag, comm, ierr)
ELSE IF (rank .EQ. 1) THEN
   CALL MPI_RECV(b(1), 40, MPI_BYTE, 0, tag, comm, status, ierr)
END IF
```

This code is erroneous, since sender and receiver do not provide matching datatype arguments.

#### **Example 3.3** Sender and receiver specify communication of untyped values.

```
CALL MPI_COMM_RANK(comm, rank, ierr)

IF (rank .EQ. 0) THEN

CALL MPI_SEND(a(1), 40, MPI_BYTE, 1, tag, comm, ierr)

ELSE IF (rank .EQ. 1) THEN

CALL MPI_RECV(b(1), 60, MPI_BYTE, 0, tag, comm, status, ierr)

END IF
```

This code is correct, irrespective of the type and size of a and b (unless this results in an out of bounds memory access).

Advice to users. If a buffer of type MPI\_BYTE is passed as an argument to MPI\_SEND, then MPI will send the data stored at contiguous locations, starting from the address indicated by the buf argument. This may have unexpected results when the data layout is not as a casual user would expect it to be. For example, some Fortran compilers implement variables of type CHARACTER as a structure that contains the character length and a pointer to the actual string. In such an environment, sending and receiving a Fortran CHARACTER variable using the MPI\_BYTE type will not have the anticipated result of transferring the character string. For this reason, the user is advised to use typed communications whenever possible. (End of advice to users.)

### Type MPI\_CHARACTER

The type MPI\_CHARACTER matches one character of a Fortran variable of type CHARACTER, rather than the entire character string stored in the variable. Fortran variables of type CHARACTER or substrings are transferred as if they were arrays of characters. This is illustrated in the example below.

#### **Example 3.4** Transfer of Fortran CHARACTERs.

```
CHARACTER*10 a
29
     CHARACTER*10 b
30
31
     CALL MPI_COMM_RANK(comm, rank, ierr)
32
     IF (rank .EQ. 0) THEN
33
34
        CALL MPI_SEND(a, 5, MPI_CHARACTER, 1, tag, comm, ierr)
     ELSE IF (rank .EQ. 1) THEN
35
        CALL MPI_RECV(b(6:10), 5, MPI_CHARACTER, 0, tag, comm, status, ierr)
36
     END IF
37
```

The last five characters of string **b** at process 1 are replaced by the first five characters of string **a** at process 0.

Rationale. The alternative choice would be for MPI\_CHARACTER to match a character of arbitrary length. This runs into problems.

A Fortran character variable is a constant length string, with no special termination symbol. There is no fixed convention on how to represent characters, and how to store their length. Some compilers pass a character argument to a routine as a pair of arguments, one holding the address of the string and the other holding the length of string. Consider the case of an MPI communication call that is passed a

communication buffer with type defined by a derived datatype (Section 5.1). If this communicator buffer contains variables of type CHARACTER then the information on their length will not be passed to the MPI routine.

This problem forces us to provide explicit information on character length with the MPI call. One could add a length parameter to the type MPI\_CHARACTER, but this does not add much convenience and the same functionality can be achieved by defining a suitable derived datatype. (*End of rationale*.)

Advice to implementors. Some compilers pass Fortran CHARACTER arguments as a structure with a length and a pointer to the actual string. In such an environment, the MPI call needs to dereference the pointer in order to reach the string. (End of advice to implementors.)

#### 3.3.2 Data Conversion

One of the goals of MPI is to support parallel computations across heterogeneous environments. Communication in a heterogeneous environment may require data conversions. We use the following terminology.

type conversion changes the datatype of a value, e.g., by rounding a REAL to an INTEGER.

representation conversion changes the binary representation of a value, e.g., from Hex floating point to IEEE floating point.

The type matching rules imply that MPI communication never entails type conversion. On the other hand, MPI requires that a representation conversion be performed when a typed value is transferred across environments that use different representations for the datatype of this value. MPI does not specify rules for representation conversion. Such conversion is expected to preserve integer, logical and character values, and to convert a floating point value to the nearest value that can be represented on the target system.

Overflow and underflow exceptions may occur during floating point conversions. Conversion of integers or characters may also lead to exceptions when a value that can be represented in one system cannot be represented in the other system. An exception occurring during representation conversion results in a failure of the communication. An error occurs either in the send operation, or the receive operation, or both.

If a value sent in a message is untyped (i.e., of type MPI\_BYTE), then the binary representation of the byte stored at the receiver is identical to the binary representation of the byte loaded at the sender. This holds true, whether sender and receiver run in the same or in distinct environments. No representation conversion is required. (Note that representation conversion may occur when values of type MPI\_CHARACTER or MPI\_CHAR are transferred, for example, from an EBCDIC encoding to an ASCII encoding.)

No conversion need occur when an MPI program executes in a homogeneous system, where all processes run in the same environment.

Consider the three examples, 3.1-3.3. The first program is correct, assuming that a and b are REAL arrays of size  $\geq 10$ . If the sender and receiver execute in different environments, then the ten real values that are fetched from the send buffer will be converted to the representation for reals on the receiver site before they are stored in the receive buffer. While the number of real elements fetched from the send buffer equal the number of real elements stored in the receive buffer, the number of bytes stored need not equal the number

of bytes loaded. For example, the sender may use a four byte representation and the receiver an eight byte representation for reals.

The second program is erroneous, and its behavior is undefined.

The third program is correct. The exact same sequence of forty bytes that were loaded from the send buffer will be stored in the receive buffer, even if sender and receiver run in a different environment. The message sent has exactly the same length (in bytes) and the same binary representation as the message received. If a and b are of different types, or if they are of the same type but different data representations are used, then the bits stored in the receive buffer may encode values that are different from the values they encoded in the send buffer.

Data representation conversion also applies to the envelope of a message: source, destination and tag are all integers that may need to be converted.

Advice to implementors. The current definition does not require messages to carry data type information. Both sender and receiver provide complete data type information. In a heterogeneous environment, one can either use a machine independent encoding such as XDR, or have the receiver convert from the sender representation to its own, or even have the sender do the conversion.

Additional type information might be added to messages in order to allow the system to detect mismatches between datatype at sender and receiver. This might be particularly useful in a slower but safer debug mode. (*End of advice to implementors*.)

MPI requires support for inter-language communication, e.g., if messages are sent using an MPI procedure from the MPI C language interface and received using an MPI procedure from one of the MPI Fortran language interfaces. The behavior is defined in Section 19.3.

# 3.4 Communication Modes

The send call described in Section 3.2.1 is **blocking**: it does not return until the message data and envelope have been safely stored away so that the sender is free to modify the send buffer. The message might be copied directly into the matching receive buffer, or it might be copied into a temporary system buffer.

Message buffering decouples the send and receive operations. A blocking send can complete as soon as the message was buffered, even if no matching receive has been executed by the receiver. On the other hand, message buffering can be expensive, as it entails additional memory-to-memory copying, and it requires the allocation of memory for buffering. MPI offers the choice of several communication modes that allow one to control the choice of the communication protocol.

The send call described in Section 3.2.1 uses the **standard** communication mode. In this mode, it is up to MPI to decide whether outgoing messages will be buffered. MPI may buffer outgoing messages. In such a case, the send call may complete before a matching receive is invoked. On the other hand, buffer space may be unavailable, or MPI may choose not to buffer outgoing messages, for performance reasons. In this case, the send call will not complete until a matching receive has been posted, and the data has been moved to the receiver.

Thus, a send in standard mode can be started whether or not a matching receive has been posted. It may complete before a matching receive is posted. The standard mode send

is *non-local*: successful completion of the send operation may depend on the occurrence of a matching receive.

Rationale. The reluctance of MPI to mandate whether standard sends are buffering or not stems from the desire to achieve portable programs. Since any system will run out of buffer resources as message sizes are increased, and some implementations may want to provide little buffering, MPI takes the position that correct (and therefore, portable) programs do not rely on system buffering in standard mode. Buffering may improve the performance of a correct program, but it doesn't affect the result of the program. If the user wishes to guarantee a certain amount of buffering, the user-provided buffer system of Section 3.6 should be used, along with the buffered-mode send. (End of rationale.)

There are three additional communication modes.

A **buffered** mode send operation can be started whether or not a matching receive has been posted. It may complete before a matching receive is posted. However, unlike the standard send, this operation is *local*, and its completion does not depend on the occurrence of a matching receive. Thus, if a send is executed and no matching receive is posted, then MPI must buffer the outgoing message, so as to allow the send call to complete. An error will occur if there is insufficient buffer space. The amount of available buffer space is controlled by the user—see Section 3.6. Buffer allocation by the user may be required for the buffered mode to be effective.

According to the definitions in Section 2.4.2, MPI\_BSEND is a completing procedure and the user can re-use all resources given as arguments, including the message data buffer. It is also a local procedure because it returns immediately without depending on the execution of any MPI procedure in any other MPI process.

Advice to users. This is one of the exceptions in which a completing and therefore blocking operation-related procedure is local. (End of advice to users.)

A send that uses the **synchronous** mode can be started whether or not a matching receive was posted. However, the send will complete successfully only if a matching receive is posted, and the receive operation has started to receive the message sent by the synchronous send. Thus, the completion of a synchronous send not only indicates that the send buffer can be reused, but it also indicates that the receiver has reached a certain point in its execution, namely that it has started executing the matching receive. If both sends and receives are blocking operations then the use of the synchronous mode provides synchronous communication semantics: a communication does not complete at either end before both processes rendezvous at the communication. A send executed in this mode is *non-local*.

A send that uses the **ready** communication mode may be started *only* if the matching receive is already posted. Otherwise, the operation is erroneous and its outcome is undefined. On some systems, this allows the removal of a hand-shake operation that is otherwise required and results in improved performance. The completion of the send operation does not depend on the status of a matching receive, and merely indicates that the send buffer can be reused. A send operation that uses the ready mode has the same semantics as a standard send operation, or a synchronous send operation; it is merely that the sender provides additional information to the system (namely that a matching receive is already posted), that can save some overhead. In a correct program, therefore, a ready send could

be replaced by a standard send with no effect on the behavior of the program other than performance.

Three additional send functions are provided for the three additional communication modes. The communication mode is indicated by a one letter prefix: B for buffered, S for synchronous, and R for ready.

```
MPI_BSEND(buf, count, datatype, dest, tag, comm)
```

```
9
        IN
                    buf
                                                     initial address of send buffer (choice)
10
        IN
                                                     number of elements in send buffer (non-negative
                    count
11
                                                     integer)
12
                                                     datatype of each send buffer element (handle)
        IN
                    datatype
13
14
        IN
                    dest
                                                     rank of destination (integer)
15
        IN
                                                     message tag (integer)
                    tag
16
        IN
                    comm
                                                     communicator (handle)
17
```

#### C binding

# Fortran 2008 binding

```
MPI_Bsend(buf, count, datatype, dest, tag, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

MPI_Bsend(buf, count, datatype, dest, tag, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
```

INTEGER(KIND=MPI\_COUNT\_KIND), INTENT(IN) :: count
TYPE(MPI\_Datatype), INTENT(IN) :: datatype
INTEGER, INTENT(IN) :: dest, tag
TYPE(MPI\_Comm), INTENT(IN) :: comm
INTEGER, OPTIONAL, INTENT(OUT) :: ierror

#### Fortran binding

```
MPI_BSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)
<type> BUF(*)
INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR
Send in buffered mode.
```

```
MPI_SSEND(buf, count, datatype, dest, tag, comm)
  IN
           buf
                                      initial address of send buffer (choice)
  IN
           count
                                      number of elements in send buffer (non-negative
                                      integer)
  IN
                                      datatype of each send buffer element (handle)
           datatype
  IN
           dest
                                      rank of destination (integer)
  IN
           tag
                                      message tag (integer)
  IN
           comm
                                      communicator (handle)
                                                                                      12
C binding
                                                                                      13
int MPI_Ssend(const void *buf, int count, MPI_Datatype datatype, int dest,
                                                                                      14
              int tag, MPI_Comm comm)
                                                                                      15
int MPI_Ssend_c(const void *buf, MPI_Count count, MPI_Datatype datatype,
                                                                                      16
              int dest, int tag, MPI_Comm comm)
                                                                                      18
Fortran 2008 binding
                                                                                      19
MPI_Ssend(buf, count, datatype, dest, tag, comm, ierror)
                                                                                      20
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                      21
    INTEGER, INTENT(IN) :: count, dest, tag
                                                                                      22
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      23
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Ssend(buf, count, datatype, dest, tag, comm, ierror)
                                                                                      26
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                      27
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                      28
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      29
    INTEGER, INTENT(IN) :: dest, tag
                                                                                      30
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      33
Fortran binding
                                                                                      34
MPI_SSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)
                                                                                      35
    <type> BUF(*)
                                                                                      36
    INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR
                                                                                      37
    Send in synchronous mode.
```

40

41 42

43

44

45

46 47

```
MPI_RSEND(buf, count, datatype, dest, tag, comm)
2
       IN
                buf
                                            initial address of send buffer (choice)
3
       IN
                count
                                            number of elements in send buffer (non-negative
                                            integer)
5
6
       IN
                datatype
                                            datatype of each send buffer element (handle)
       IN
                dest
                                            rank of destination (integer)
       IN
                tag
                                            message tag (integer)
9
10
       IN
                comm
                                            communicator (handle)
11
12
     C binding
13
     int MPI_Rsend(const void *buf, int count, MPI_Datatype datatype, int dest,
14
                    int tag, MPI_Comm comm)
15
     int MPI_Rsend_c(const void *buf, MPI_Count count, MPI_Datatype datatype,
16
                    int dest, int tag, MPI_Comm comm)
17
18
     Fortran 2008 binding
19
     MPI_Rsend(buf, count, datatype, dest, tag, comm, ierror)
20
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
21
         INTEGER, INTENT(IN) :: count, dest, tag
22
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
23
         TYPE(MPI_Comm), INTENT(IN) :: comm
24
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
25
26
     MPI_Rsend(buf, count, datatype, dest, tag, comm, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
27
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
28
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
29
         INTEGER, INTENT(IN) :: dest, tag
30
         TYPE(MPI_Comm), INTENT(IN) :: comm
31
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
32
33
     Fortran binding
34
     MPI_RSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)
35
          <type> BUF(*)
36
          INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR
37
         Send in ready mode.
38
```

There is only one receive operation, but it matches any of the send modes. The receive operation described in the last section is *blocking*: it returns only after the receive buffer contains the newly received message. A receive can complete before the matching send has completed (of course, it can complete only after the matching send has started).

In a multithreaded implementation of MPI, the system may de-schedule a thread that is blocked on a send or receive operation, and schedule another thread for execution in the same address space. In such a case it is the user's responsibility not to modify a communication buffer until the communication completes. Otherwise, the outcome of the computation is undefined.

Advice to implementors. Since a synchronous send cannot complete before a matching receive is posted, one will not normally buffer messages sent by such an operation.

It is recommended to choose buffering over blocking the sender, whenever possible, for standard sends. The programmer can signal his or her preference for blocking the sender until a matching receive occurs by using the synchronous send mode.

A possible communication protocol for the various communication modes is outlined below.

ready send: The message is sent as soon as possible.

synchronous send: The sender sends a request-to-send message. The receiver stores this request. When a matching receive is posted, the receiver sends back a permission-to-send message, and the sender now sends the message.

 $standard\ send$ : First protocol may be used for short messages, and second protocol for long messages.

buffered send: The sender copies the message into a buffer and then sends it with a nonblocking send (using the same protocol as for standard send).

Additional control messages might be needed for flow control and error recovery. Of course, there are many other possible protocols.

Ready send can be implemented as a standard send. In this case there will be no performance advantage (or disadvantage) for the use of ready send.

A standard send can be implemented as a synchronous send. In such a case, no data buffering is needed. However, users may expect some buffering.

In a multithreaded environment, the execution of a blocking communication should block only the executing thread, allowing the thread scheduler to de-schedule this thread and schedule another thread for execution. (*End of advice to implementors.*)

# 3.5 Semantics of Point-to-Point Communication

A valid MPI implementation guarantees certain general properties of point-to-point communication, which are described in this section.

Order Messages are non-overtaking: If a sender sends two messages in succession to the same destination, and both match the same receive, then this operation cannot receive the second message if the first one is still pending. If a receiver posts two receives in succession, and both match the same message, then the second receive operation cannot be satisfied by this message, if the first one is still pending. This requirement facilitates matching of sends to receives. It guarantees that message-passing code is deterministic, if processes are single-threaded and the wildcard MPI\_ANY\_SOURCE is not used in receives. (Some of the calls described later, such as MPI\_CANCEL or MPI\_WAITANY, are additional sources of nondeterminism.)

If a process has a single thread of execution, then any two communications executed by this process are ordered. On the other hand, if the process is multithreaded, then the semantics of thread execution may not define a relative order between two send operations executed by two distinct threads. The operations are logically concurrent, even if one physically precedes the other. In such a case, the two messages sent can be received in any order. Similarly, if two receive operations that are logically concurrent receive two successively sent messages, then the two messages can match the two receives in either order.

**Example 3.5** An example of non-overtaking messages.

```
CALL MPI_COMM_RANK(comm, rank, ierr)

IF (rank .EQ. 0) THEN

CALL MPI_BSEND(buf1, count, MPI_REAL, 1, tag, comm, ierr)

CALL MPI_BSEND(buf2, count, MPI_REAL, 1, tag, comm, ierr)

ELSE IF (rank .EQ. 1) THEN

CALL MPI_RECV(buf1, count, MPI_REAL, 0, MPI_ANY_TAG, comm, status, ierr)

CALL MPI_RECV(buf2, count, MPI_REAL, 0, tag, comm, status, ierr)

END IF
```

The message sent by the first send must be received by the first receive, and the message sent by the second send must be received by the second receive.

Progress If a pair of matching send and receives have been initiated on two processes, then at least one of these two operations will complete, independently of other actions in the system: the send operation will complete, unless the receive is satisfied by another message, and completes; the receive operation will complete, unless the message sent is consumed by another matching receive that was posted at the same destination process.

**Example 3.6** An example of two, intertwined matching pairs.

```
CALL MPI_COMM_RANK(comm, rank, ierr)

IF (rank .EQ. 0) THEN

CALL MPI_BSEND(buf1, count, MPI_REAL, 1, tag1, comm, ierr)

CALL MPI_SSEND(buf2, count, MPI_REAL, 1, tag2, comm, ierr)

ELSE IF (rank .EQ. 1) THEN

CALL MPI_RECV(buf1, count, MPI_REAL, 0, tag2, comm, status, ierr)

CALL MPI_RECV(buf2, count, MPI_REAL, 0, tag1, comm, status, ierr)

END IF
```

Both processes invoke their first communication call. Since the first send of process zero uses the buffered mode, it must complete, irrespective of the state of process one. Since no matching receive is posted, the message will be copied into buffer space. (If insufficient buffer space is available, then the program will fail.) The second send is then invoked. At that point, a matching pair of send and receive operation is enabled, and both operations must complete. Process one next invokes its second receive call, which will be satisfied by the buffered message. Note that process one received the messages in the reverse order they were sent.

 $^{46}$ 

Fairness MPI makes no guarantee of fairness in the handling of communication. Suppose that a send is posted. Then it is possible that the destination process repeatedly posts a receive that matches this send, yet the message is never received, because it is each time overtaken by another message, sent from another source. Similarly, suppose that a receive was posted by a multithreaded process. Then it is possible that messages that match this

receive are repeatedly received, yet the receive is never satisfied, because it is overtaken by other receives posted at this node (by other executing threads). It is the programmer's responsibility to prevent starvation in such situations.

Resource limitations Any pending communication operation consumes system resources that are limited. Errors may occur when lack of resources prevent the execution of an MPI call. A quality implementation will use a (small) fixed amount of resources for each pending send in the ready or synchronous mode and for each pending receive. However, buffer space may be consumed to store messages sent in standard mode, and must be consumed to store messages sent in buffered mode, when no matching receive is available. The amount of space available for buffering will be much smaller than program data memory on many systems. Then, it will be easy to write programs that overrun available buffer space.

MPI allows the user to provide buffer memory for messages sent in the buffered mode. Furthermore, MPI specifies a detailed operational model for the use of this buffer. An MPI implementation is required to do no worse than implied by this model. This allows users to avoid buffer overflows when they use buffered sends. Buffer allocation and use is described in Section 3.6.

A buffered send operation that cannot complete because of a lack of buffer space is erroneous. When such a situation is detected, an error is signaled that may cause the program to terminate abnormally. On the other hand, a standard send operation that cannot complete because of lack of buffer space will merely block, waiting for buffer space to become available or for a matching receive to be posted. This behavior is preferable in many situations. Consider a situation where a producer repeatedly produces new values and sends them to a consumer. Assume that the producer produces new values faster than the consumer can consume them. If buffered sends are used, then a buffer overflow will result. Additional synchronization has to be added to the program so as to prevent this from occurring. If standard sends are used, then the producer will be automatically throttled, as its send operations will block when buffer space is unavailable.

In some situations, a lack of buffer space leads to deadlock situations. This is illustrated by the examples below.

# Example 3.7 An exchange of messages.

```
CALL MPI_COMM_RANK(comm, rank, ierr)

IF (rank .EQ. 0) THEN

CALL MPI_SEND(sendbuf, count, MPI_REAL, 1, tag, comm, ierr)

CALL MPI_RECV(recvbuf, count, MPI_REAL, 1, tag, comm, status, ierr)

ELSE IF (rank .EQ. 1) THEN

CALL MPI_RECV(recvbuf, count, MPI_REAL, 0, tag, comm, status, ierr)

CALL MPI_SEND(sendbuf, count, MPI_REAL, 0, tag, comm, ierr)

END IF
```

This program will succeed even if no buffer space for data is available. The standard send operation can be replaced, in this example, with a synchronous send.

**Example 3.8** An errant attempt to exchange messages.

2

3

4

5

7

8

9

10

11

12

13

14 15

16 17

18

19

20

21

22

23

24

25

26

27

28

29 30

31

32

33

34

35

36 37

38

39

41

42

43

44

45

46

47

```
CALL MPI_COMM_RANK(comm, rank, ierr)
    IF (rank .EQ. 0) THEN
       CALL MPI_RECV(recvbuf, count, MPI_REAL, 1, tag, comm, status, ierr)
       CALL MPI_SEND(sendbuf, count, MPI_REAL, 1, tag, comm, ierr)
    ELSE IF (rank .EQ. 1) THEN
6
       CALL MPI_RECV(recvbuf, count, MPI_REAL, 0, tag, comm, status, ierr)
       CALL MPI_SEND(sendbuf, count, MPI_REAL, 0, tag, comm, ierr)
    END IF
```

The receive operation of the first process must complete before its send, and can complete only if the matching send of the second processor is executed. The receive operation of the second process must complete before its send and can complete only if the matching send of the first process is executed. This program will always deadlock. The same holds for any other send mode.

**Example 3.9** An exchange that relies on buffering.

```
CALL MPI_COMM_RANK(comm, rank, ierr)
IF (rank .EQ. 0) THEN
   CALL MPI_SEND(sendbuf, count, MPI_REAL, 1, tag, comm, ierr)
   CALL MPI_RECV(recvbuf, count, MPI_REAL, 1, tag, comm, status, ierr)
ELSE IF (rank .EQ. 1) THEN
  CALL MPI_SEND(sendbuf, count, MPI_REAL, 0, tag, comm, ierr)
  CALL MPI_RECV(recvbuf, count, MPI_REAL, 0, tag, comm, status, ierr)
END IF
```

The message sent by each process has to be copied out before the send operation returns and the receive operation starts. For the program to complete, it is necessary that at least one of the two messages sent be buffered. Thus, this program can succeed only if the communication system can buffer at least count words of data.

Advice to users. When standard send operations are used, then a deadlock situation may occur where both processes are blocked because buffer space is not available. The same will certainly happen, if the synchronous mode is used. If the buffered mode is used, and not enough buffer space is available, then the program will not complete either. However, rather than a deadlock situation, we shall have a buffer overflow error.

A program is "safe" if no message buffering is required for the program to complete. One can replace all sends in such program with synchronous sends, and the program will still run correctly. This conservative programming style provides the best portability, since program completion does not depend on the amount of buffer space available or on the communication protocol used.

Many programmers prefer to have more leeway and opt to use the "unsafe" programming style shown in Example 3.9. In such cases, the use of standard sends is likely to provide the best compromise between performance and robustness: quality implementations will provide sufficient buffering so that "common practice" programs will not deadlock. The buffered send mode can be used for programs that require more buffering, or in situations where the programmer wants more control. This mode

12

13 14 15

16

18

19 20

21

22

23

26

27

28

29

30

34

35

36

37

38

41

42

might also be used for debugging purposes, as buffer overflow conditions are easier to diagnose than deadlock conditions.

Nonblocking message-passing operations, as described in Section 3.7, can be used to avoid the need for buffering outgoing messages. This prevents deadlocks due to lack of buffer space, and improves performance, by allowing overlap of computation and communication, and avoiding the overheads of allocating buffers and copying messages into buffers. (*End of advice to users*.)

# 3.6 Buffer Allocation and Usage

INTEGER SIZE, IERROR

A user may specify a buffer to be used for buffering messages sent in buffered mode. Buffering is done by the sender.

```
MPI_BUFFER_ATTACH(buffer, size)
  IN
           buffer
                                     initial buffer address (choice)
  IN
                                     buffer size, in bytes (non-negative integer)
           size
C binding
int MPI_Buffer_attach(void *buffer, int size)
int MPI_Buffer_attach_c(void *buffer, MPI_Count size)
Fortran 2008 binding
MPI_Buffer_attach(buffer, size, ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
    INTEGER, INTENT(IN) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Buffer_attach(buffer, size, ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_BUFFER_ATTACH(BUFFER, SIZE, IERROR)
    <type> BUFFER(*)
```

Provides to MPI a buffer in the user's memory to be used for buffering outgoing messages. The buffer is used only by messages sent in buffered mode. Only one buffer can be attached to a process at a time. In C, buffer is the starting address of a memory region. In Fortran, one can pass the first element of a memory region or a whole array, which must be 'simply contiguous' (for 'simply contiguous,' see also Section 19.1.12).

```
MPI_BUFFER_DETACH(buffer_addr, size)
2
       OUT
                 buffer_addr
                                            initial buffer address (choice)
3
       OUT
                size
                                            buffer size, in bytes (integer)
4
5
6
     C binding
7
     int MPI_Buffer_detach(void *buffer_addr, int *size)
     int MPI_Buffer_detach_c(void *buffer_addr, MPI_Count *size)
9
10
     Fortran 2008 binding
11
     MPI_Buffer_detach(buffer_addr, size, ierror)
12
          USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
          TYPE(C_PTR), INTENT(OUT) :: buffer_addr
13
14
          INTEGER, INTENT(OUT) :: size
15
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
16
     MPI_Buffer_detach(buffer_addr, size, ierror)
17
          USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
18
          TYPE(C_PTR), INTENT(OUT) :: buffer_addr
19
          INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: size
20
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
21
22
     Fortran binding
23
     MPI_BUFFER_DETACH(BUFFER_ADDR, SIZE, IERROR)
24
          <type> BUFFER_ADDR(*)
25
          INTEGER SIZE, IERROR
26
         Detach the buffer currently associated with MPI. The call returns the address and the
27
     size of the detached buffer. This operation will block until all messages currently in the
28
     buffer have been transmitted. Upon return of this function, the user may reuse or deallocate
29
     the space taken by the buffer.
30
         If the size of the detached buffer cannot be represented in size, it is set to
31
     MPI_UNDEFINED.
32
33
     Example 3.10 Calls to attach and detach buffers.
34
35
     #define BUFFSIZE 10000
36
     int size;
37
     char *buff;
38
     MPI_Buffer_attach(malloc(BUFFSIZE), BUFFSIZE);
39
     /* a buffer of 10000 bytes can now be used by MPI_Bsend */
40
     MPI_Buffer_detach(&buff, &size);
41
     /* Buffer size reduced to zero */
42
     MPI_Buffer_attach(buff, size);
     /* Buffer of 10000 bytes available again */
43
44
45
                             Even though the C functions MPI_Buffer_attach and
           MPI_Buffer_detach both have a first argument of type void*, these arguments are
46
47
          used differently: A pointer to the buffer is passed to MPI_Buffer_attach; the address
```

of the pointer is passed to MPI\_Buffer\_detach, so that this call can return the pointer

value. In Fortran with the mpi module or mpif.h, the type of the buffer\_addr argument is wrongly defined and the argument is therefore unused. In Fortran with the mpi\_f08 module, the address of the buffer is returned as TYPE(C\_PTR), see also Example 9.1 about the use of C\_PTR pointers. (End of advice to users.)

Rationale. Both arguments are defined to be of type void\* (rather than void\* and void\*\*, respectively), so as to avoid complex type casts. E.g., in the last example, &buff, which is of type char\*\*, can be passed as argument to MPI\_Buffer\_detach without type casting. If the formal parameter had type void\*\* then we would need a type cast before and after the call. (End of rationale.)

The statements made in this section describe the behavior of MPI for buffered-mode sends. When no buffer is currently associated, MPI behaves as if a zero-sized buffer is associated with the process.

MPI must provide as much buffering for outgoing messages as if outgoing message data were buffered by the sending process, in the specified buffer space, using a circular, contiguous-space allocation policy. We outline below a model implementation that defines this policy. MPI may provide more buffering, and may use a better buffer allocation algorithm than described below. On the other hand, MPI may signal an error whenever the simple buffering allocator described below would run out of space. In particular, if no buffer is explicitly associated with the process, then any buffered send may cause an error.

MPI does not provide mechanisms for querying or controlling buffering done by standard mode sends. It is expected that vendors will provide such information for their implementations.

Rationale. There is a wide spectrum of possible implementations of buffered communication: buffering can be done at sender, at receiver, or both; buffers can be dedicated to one sender-receiver pair, or be shared by all communications; buffering can be done in real or in virtual memory; it can use dedicated memory, or memory shared by other processes; buffer space may be allocated statically or be changed dynamically; etc. It does not seem feasible to provide a portable mechanism for querying or controlling buffering that would be compatible with all these choices, yet provide meaningful information. (End of rationale.)

#### 3.6.1 Model Implementation of Buffered Mode

The model implementation uses the packing and unpacking functions described in Section 5.2 and the nonblocking communication functions described in Section 3.7.

We assume that a circular queue of pending message entries (PME) is maintained. Each entry contains a communication request handle that identifies a pending nonblocking send, a pointer to the next entry and the packed message data. The entries are stored in successive locations in the buffer. Free space is available between the queue tail and the queue head.

A buffered send call results in the execution of the following code.

• Traverse sequentially the PME queue from head towards the tail, deleting all entries for communications that have completed, up to the first entry with an uncompleted request; update queue head to point to that entry.

• Compute the number, n, of bytes needed to store an entry for the new message. An

MPI\_PACK\_SIZE(count, datatype, comm, size), with the count, datatype and comm arguments used in the MPI\_BSEND call, returns an upper bound on the amount

of space needed to buffer the message data (see Section 5.2). The MPI constant

MPI\_BSEND\_OVERHEAD provides an upper bound on the additional space consumed

• Find the next contiguous empty space of n bytes in buffer (space following queue tail,

• Append to end of PME queue in contiguous space the new entry that contains request

handle, next pointer and packed message data; MPI\_PACK is used to pack data.

or space at start of buffer if queue tail is too close to end of buffer). If space is not

upper bound on n can be computed as follows: A call to the function

by the entry (e.g., for pointers or envelope information).

• Post nonblocking send (standard mode) for packed data.

1

- 9
- 11 12 13

10

15 16

14

17 18 • Return

19

20 21

22

23

24

25

26

27

28

29

30

31

32

33

34

35

36

37

38

39

40

41

42

43

44

45

46

47

48

3.7 Nonblocking Communication

found then raise buffer overflow error.

Nonblocking communication is important both for reasons of correctness and performance. For complex communication patterns, the use of only blocking communication (without buffering) is difficult because the programmer must ensure that each send is matched with a receive in an order that avoids deadlock. For communication patterns that are determined only at run time, this is even more difficult. Nonblocking communication can be used to avoid this problem, allowing programmers to express complex and possibly dynamic communication patterns without needing to ensure that all sends and receives are issued in an order that prevents deadlock (see Section 3.5 and the discussion of "safe" programs). Nonblocking communication also allows for the overlap of communication with different communication operations, e.g., to prevent the serialization of such operations, and for the overlap of communication with computation. Whether an implementation is able to accomplish an effective (from a performance standpoint) overlap of operations depends on the implementation itself and the system on which the implementation is running. Using nonblocking operations permits an implementation to overlap communication with computation, but does not require it to do so.

A nonblocking send start call initiates the send operation, but does not complete it. The send start call can return before the message was copied out of the send buffer. A separate send complete call is needed to complete the communication, i.e., to verify that the data has been copied out of the send buffer. With suitable hardware, the transfer of data out of the sender memory may proceed concurrently with computations done at the sender after the send was initiated and before it completed. Similarly, a nonblocking receive start call initiates the receive operation, but does not complete it. The call can return before a message is stored into the receive buffer. A separate receive complete call is needed to complete the receive operation and verify that the data has been received into the receive buffer. With suitable hardware, the transfer of data into the receiver memory may proceed concurrently with computations done after the receive was initiated and before it completed. The use of nonblocking receives may also avoid system buffering and memory-to-memory copying, as information is provided early on the location of the receive buffer.

Nonblocking send start calls can use the same four modes as blocking sends: standard, buffered, synchronous and ready. These carry the same meaning. Sends of all modes, ready excepted, can be started whether a matching receive has been posted or not; a nonblocking ready send can be started only if a matching receive is posted. In all cases, the send start call is local: it returns immediately, irrespective of the status of other processes. If the call causes some system resource to be exhausted, then it will fail and return an error code. Quality implementations of MPI should ensure that this happens only in "pathological" cases. That is, an MPI implementation should be able to support a large number of pending nonblocking operations.

The send-complete call returns when data has been copied out of the send buffer. It may carry additional meaning, depending on the send mode.

If the send mode is **synchronous**, then the send can complete only if a matching receive has started. That is, a receive has been posted, and has been matched with the send. In this case, the send-complete call is non-local. Note that a synchronous, nonblocking send may complete, if matched by a nonblocking receive, before the receive complete call occurs. (It can complete as soon as the sender "knows" the transfer will complete, but before the receiver "knows" the transfer will complete.)

If the send mode is **buffered** then the message must be buffered if there is no pending receive. In this case, the send-complete call is local, and must succeed irrespective of the status of a matching receive.

If the send mode is **standard** then the send-complete call may return before a matching receive is posted, if the message is buffered. On the other hand, the receive-complete may not complete until a matching receive is posted, and the message was copied into the receive buffer.

Nonblocking sends can be matched with blocking receives, and vice-versa.

Advice to users. The completion of a send operation may be delayed, for standard mode, and must be delayed, for synchronous mode, until a matching receive is posted. The use of nonblocking sends in these two cases allows the sender to proceed ahead of the receiver, so that the computation is more tolerant of fluctuations in the speeds of the two processes.

Nonblocking sends in the buffered and ready modes have a more limited impact, e.g., the blocking version of buffered send is capable of completing regardless of when a matching receive call is made. However, separating the start from the completion of these sends still gives some opportunity for optimization within the MPI library. For example, starting a buffered send gives an implementation more flexibility in determining if and how the message is buffered. There are also advantages for both nonblocking buffered and ready modes when data copying can be done concurrently with computation.

The message-passing model implies that communication is initiated by the sender. The communication will generally have lower overhead if a receive is already posted when the sender initiates the communication (data can be moved directly to the receive buffer, and there is no need to queue a pending send request). However, a receive operation can complete only after the matching send has occurred. The use of nonblocking receives allows one to achieve lower communication overheads without blocking the receiver while it waits for the send. (*End of advice to users*.)

3

6

9 10

11 12

13

14

15

### 3.7.1 Communication Request Objects

Nonblocking communications use opaque **request** objects to identify communication operations and match the operation that initiates the communication with the operation that terminates it. These are system objects that are accessed via a handle. A request object identifies various properties of a communication operation, such as the send mode, the communication buffer that is associated with it, its context, the tag and destination arguments to be used for a send, or the tag and source arguments to be used for a receive. In addition, this object stores information about the status of the pending communication operation.

#### 3.7.2 Communication Initiation

For the functions defined in this section, we use the same naming conventions as for blocking communication: a prefix of B, S, or R is used for **buffered**, **synchronous** or **ready** mode. In addition, for these functions a prefix of I (for **immediate** and **incomplete**) indicates that the call is nonblocking.

16 17 18

19

20

21

22

23

24

26

27

28

29 30

31

32

33 34

35 36

37

38

39

41

42

43

44 45

46

47

```
MPI_ISEND(buf, count, datatype, dest, tag, comm, request)
```

```
IN
           buf
                                           initial address of send buffer (choice)
IN
           count
                                           number of elements in send buffer (non-negative
                                           integer)
                                           datatype of each send buffer element (handle)
IN
           datatype
IN
           dest
                                           rank of destination (integer)
IN
                                           message tag (integer)
           tag
                                           communicator (handle)
IN
           comm
OUT
           request
                                           communication request (handle)
```

#### C binding

# Fortran 2008 binding

```
MPI_Isend(buf, count, datatype, dest, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

MPI_Isend(buf, count, datatype, dest, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
```

```
INTEGER, INTENT(IN) :: dest, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_ISEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
    <type> BUF(*)
    INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
    Start a standard mode, nonblocking send.
                                                                                      12
MPI_IBSEND(buf, count, datatype, dest, tag, comm, request)
                                                                                      13
                                                                                      14
 IN
           buf
                                     initial address of send buffer (choice)
                                                                                      15
 IN
                                     number of elements in send buffer (non-negative
           count
                                                                                      16
                                     integer)
 IN
           datatype
                                     datatype of each send buffer element (handle)
                                                                                      18
                                                                                      19
 IN
           dest
                                     rank of destination (integer)
                                                                                      20
 IN
                                     message tag (integer)
           tag
                                                                                     21
                                      communicator (handle)
 IN
           comm
                                                                                     22
                                                                                     23
 OUT
           request
                                      communication request (handle)
                                                                                      24
C binding
                                                                                      26
int MPI_Ibsend(const void *buf, int count, MPI_Datatype datatype, int dest,
                                                                                     27
              int tag, MPI_Comm comm, MPI_Request *request)
                                                                                     28
int MPI_Ibsend_c(const void *buf, MPI_Count count, MPI_Datatype datatype,
                                                                                     29
              int dest, int tag, MPI_Comm comm, MPI_Request *request)
                                                                                      30
Fortran 2008 binding
MPI_Ibsend(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                      33
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                     34
    INTEGER, INTENT(IN) :: count, dest, tag
                                                                                     35
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      36
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                     37
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Ibsend(buf, count, datatype, dest, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                      42
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      43
    INTEGER, INTENT(IN) :: dest, tag
                                                                                      44
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                      45
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                      46
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
1
     Fortran binding
2
     MPI_IBSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
3
         <type> BUF(*)
         INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
5
         Start a buffered mode, nonblocking send.
6
7
8
     MPI_ISSEND(buf, count, datatype, dest, tag, comm, request)
9
       IN
                buf
                                           initial address of send buffer (choice)
10
11
       IN
                count
                                           number of elements in send buffer (non-negative
                                           integer)
12
13
       IN
                datatype
                                           datatype of each send buffer element (handle)
14
                dest
                                           rank of destination (integer)
       IN
15
16
       IN
                                           message tag (integer)
                tag
17
       IN
                comm
                                           communicator (handle)
18
       OUT
                                           communication request (handle)
                request
19
20
     C binding
21
     int MPI_Issend(const void *buf, int count, MPI_Datatype datatype, int dest,
22
                    int tag, MPI_Comm comm, MPI_Request *request)
23
24
     int MPI_Issend_c(const void *buf, MPI_Count count, MPI_Datatype datatype,
25
                    int dest, int tag, MPI_Comm comm, MPI_Request *request)
26
     Fortran 2008 binding
27
     MPI_Issend(buf, count, datatype, dest, tag, comm, request, ierror)
28
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
29
         INTEGER, INTENT(IN) :: count, dest, tag
30
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
31
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
33
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
35
     MPI_Issend(buf, count, datatype, dest, tag, comm, request, ierror)
36
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
37
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, INTENT(IN) :: dest, tag
         TYPE(MPI_Comm), INTENT(IN) :: comm
41
         TYPE(MPI_Request), INTENT(OUT) :: request
42
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
43
     Fortran binding
44
     MPI_ISSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
45
         <type> BUF(*)
46
47
         INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
```

```
Start a synchronous mode, nonblocking send.
MPI_IRSEND(buf, count, datatype, dest, tag, comm, request)
  IN
           buf
                                      initial address of send buffer (choice)
  IN
                                      number of elements in send buffer (non-negative
           count
                                      integer)
  IN
           datatype
                                      datatype of each send buffer element (handle)
  IN
           dest
                                      rank of destination (integer)
                                      message tag (integer)
  IN
           tag
                                                                                       12
                                      communicator (handle)
  IN
           comm
                                                                                       13
                                                                                       14
  OUT
                                      communication request (handle)
           request
                                                                                       15
                                                                                       16
C binding
                                                                                       17
int MPI_Irsend(const void *buf, int count, MPI_Datatype datatype, int dest,
              int tag, MPI_Comm comm, MPI_Request *request)
                                                                                       19
int MPI_Irsend_c(const void *buf, MPI_Count count, MPI_Datatype datatype,
                                                                                      20
              int dest, int tag, MPI_Comm comm, MPI_Request *request)
                                                                                      21
                                                                                      22
Fortran 2008 binding
                                                                                      23
MPI_Irsend(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                       24
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
                                                                                       26
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      27
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                      28
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                      29
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      30
MPI_Irsend(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                       31
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                       33
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      34
    INTEGER, INTENT(IN) :: dest, tag
                                                                                      35
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                      36
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                      37
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_IRSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
    <type> BUF(*)
                                                                                      42
    INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
                                                                                       43
    Start a ready mode nonblocking send.
                                                                                       44
                                                                                       45
```

```
1
     MPI_IRECV(buf, count, datatype, source, tag, comm, request)
2
       OUT
                buf
                                           initial address of receive buffer (choice)
3
       IN
                count
                                           number of elements in receive buffer (non-negative
                                           integer)
5
6
       IN
                datatype
                                           datatype of each receive buffer element (handle)
                                           rank of source or MPI_ANY_SOURCE (integer)
       IN
                source
       IN
                tag
                                           message tag or MPI_ANY_TAG (integer)
9
10
       IN
                comm
                                           communicator (handle)
11
       OUT
                                           communication request (handle)
                request
12
13
     C binding
14
     int MPI_Irecv(void *buf, int count, MPI_Datatype datatype, int source,
15
                    int tag, MPI_Comm comm, MPI_Request *request)
16
17
     int MPI_Irecv_c(void *buf, MPI_Count count, MPI_Datatype datatype,
18
                    int source, int tag, MPI_Comm comm, MPI_Request *request)
19
     Fortran 2008 binding
20
     MPI_Irecv(buf, count, datatype, source, tag, comm, request, ierror)
21
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
22
         INTEGER, INTENT(IN) :: count, source, tag
23
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
24
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
26
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
27
28
     MPI_Irecv(buf, count, datatype, source, tag, comm, request, ierror)
29
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
30
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
31
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, INTENT(IN) :: source, tag
33
         TYPE(MPI_Comm), INTENT(IN) :: comm
34
         TYPE(MPI_Request), INTENT(OUT) :: request
35
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
36
     Fortran binding
37
     MPI_IRECV(BUF, COUNT, DATATYPE, SOURCE, TAG, COMM, REQUEST, IERROR)
38
         <type> BUF(*)
39
         INTEGER COUNT, DATATYPE, SOURCE, TAG, COMM, REQUEST, IERROR
41
         Start a nonblocking receive.
42
```

MPI_ISENDRECV(sendbuf, sendcount, sendtype, dest, sendtag, recvbuf, recvcount, recvtype, source, recvtag, comm, request)   1				
IN	sendbuf	initial address of send buffer (choice)	3	
IN	sendcount	number of elements in send buffer (non-negative integer)	4 5 6	
IN	sendtype	datatype of each send buffer element (handle)	7	
IN	dest	rank of destination (integer)	8	
IN	sendtag	send tag (integer)	9	
OUT	recvbuf	initial address of receive buffer (choice)	11	
IN	recvcount	number of elements in receive buffer (non-negative integer)	12 13	
IN	recvtype	datatype of each receive buffer element (handle)	14 15	
IN	source	rank of source or MPI_ANY_SOURCE (integer)	16	
IN	recvtag	receive tag or MPI_ANY_TAG (integer)	17	
IN	comm	communicator (handle)	18 19	
OUT	request	communication request (handle)	20	
001	1044000	communication request (manare)	21	
C bind	ing		22 23	
<pre>int MPI_Isendrecv(const void *sendbuf, int sendcount,</pre>				
MPI_Datatype sendtype, int dest, int sendtag, void *recvbuf, int recvcount, MPI_Datatype recvtype, int source, int recvtag,			24 25	
			26	
MPI_Comm comm, MPI_Request *request)				
	a 2008 binding		28	
MPI_Ise		ount, sendtype, dest, sendtag, recvbuf,	29	
TVE		type, source, recvtag, comm, request, ierror) ENTENT(IN), ASYNCHRONOUS :: sendbuf	30	
		endcount, dest, sendtag, recvcount, source,	31 32	
1111	recvtag	decome, desc, sendedg, recreame, searce,	33	
TYF		T(IN) :: sendtype, recvtype	34	
TYF	PE(*), DIMENSION(), A	SYNCHRONOUS :: recvbuf	35	
	PE(MPI_Comm), INTENT(IN		36	
	PE(MPI_Request), INTENT	<del>-</del>	37	
TN.I	TEGER, OPTIONAL, INTENT	((UUT) :: ierror	38	
Fortrar	n binding		39	
MPI_ISE		DUNT, SENDTYPE, DEST, SENDTAG, RECVBUF,	40 41	
RECVCOUNT, RECVTYPE, SOURCE, RECVTAG, COMM, REQUEST, IERROR)			42	
<pre><type> SENDBUF(*), RECVBUF(*) INTEGER SENDCOUNT, SENDTYPE, DEST, SENDTAG, RECVCOUNT, RECVTYPE,</type></pre>				
T 1/1 T	FE, DESI, SENDIAG, RECVOUNT, RECVITEE, G, COMM, REQUEST, IERROR	44		
<u>.</u> .			45	
Init	nate a nonblocking commu	nication request for a send and receive operation.	46	

```
1
     MPI_ISENDRECV_REPLACE(buf, count, datatype, dest, sendtag, source, recvtag, comm,
2
                     request)
3
       INOUT
                 buf
                                             initial address of send and receive buffer (choice)
       IN
                                             number of elements in send and receive buffer
                 count
5
                                             (non-negative integer)
6
7
       IN
                 datatype
                                             type of elements in send and receive buffer (handle)
       IN
                 dest
                                             rank of destination (integer)
       IN
                 sendtag
                                             send message tag (integer)
10
11
                                             rank of source or MPI_ANY_SOURCE (integer)
       IN
                 source
12
       IN
                 recvtag
                                             receive message tag or MPI_ANY_TAG (integer)
13
       IN
                 comm
                                             communicator (handle)
14
15
       OUT
                 request
                                             communication request (handle)
16
17
     C binding
18
     int MPI_Isendrecv_replace(void *buf, int count, MPI_Datatype datatype,
19
                     int dest, int sendtag, int source, int recvtag, MPI_Comm comm,
20
                    MPI_Request *request)
21
     Fortran 2008 binding
22
     MPI_Isendrecv_replace(buf, count, datatype, dest, sendtag, source, recvtag,
23
                    comm, request, ierror)
24
          TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
25
          INTEGER, INTENT(IN) :: count, dest, sendtag, source, recvtag
26
          TYPE(MPI_Datatype), INTENT(IN) :: datatype
27
          TYPE(MPI_Comm), INTENT(IN) :: comm
28
          TYPE(MPI_Request), INTENT(OUT) :: request
29
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
30
31
     Fortran binding
32
```

MPI\_ISENDRECV\_REPLACE(BUF, COUNT, DATATYPE, DEST, SENDTAG, SOURCE, RECVTAG, COMM, REQUEST, IERROR)

<type> BUF(\*)

INTEGER COUNT, DATATYPE, DEST, SENDTAG, SOURCE, RECVTAG, COMM, REQUEST, IERROR

Initiate a nonblocking communication request for a *send and receive* operation. The same buffer is used both for the send and for the receive, so that the message sent is replaced by the message received.

These calls allocate a communication request object and associate it with the request handle (the argument request). The request can be used later to query the status of the communication or wait for its completion.

A nonblocking send call indicates that the system may start copying data out of the send buffer. The sender should not modify any part of the send buffer after a nonblocking send operation is called, until the send completes.

47

33

34

35

36

37

38

39

41

42

43

44

45

A nonblocking receive call indicates that the system may start writing data into the receive buffer. The receiver should not access any part of the receive buffer after a nonblocking receive operation is called, until the receive completes.

Advice to users. To prevent problems with the argument copying and register optimization done by Fortran compilers, please note the hints in Sections 19.1.10–19.1.20. (End of advice to users.)

# 3.7.3 Communication Completion

The functions MPI\_WAIT and MPI\_TEST are used to complete a nonblocking communication. The completion of a send operation indicates that the sender is now free to update the locations in the send buffer (the send operation itself leaves the content of the send buffer unchanged). It does not indicate that the message has been received, rather, it may have been buffered by the communication subsystem. However, if a **synchronous** mode send was used, the completion of the send operation indicates that a matching receive was initiated, and that the message will eventually be received by this matching receive.

The completion of a receive operation indicates that the receive buffer contains the received message, the receiver is now free to access it, and that the status object is set. It does not indicate that the matching send operation has completed (but indicates, of course, that the send was initiated).

We shall use the following terminology: A **null handle** is a handle with value MPI\_REQUEST\_NULL. A persistent request and the handle to it are **inactive** if the request is not associated with any ongoing communication (see Section 3.9). A handle is **active** if it is neither null nor inactive. An **empty** status is a status which is set to return tag = MPI\_ANY\_TAG, source = MPI\_ANY\_SOURCE, error = MPI\_SUCCESS, and is also internally configured so that calls to MPI\_GET\_COUNT, MPI\_GET\_ELEMENTS, and MPI\_GET\_ELEMENTS\_X return count = 0 and MPI\_TEST\_CANCELLED returns false. We set a status variable to empty when the value returned by it is not significant. Status is set in this way so as to prevent errors due to accesses of stale information.

The fields in a status object returned by a call to MPI\_WAIT, MPI\_TEST, or any of the other derived functions (MPI\_{TEST|WAIT}{ALL|SOME|ANY}), where the request corresponds to a send call, are undefined, with two exceptions: The error status field will contain valid information if the wait or test call returned with MPI\_ERR\_IN\_STATUS; and the returned status can be queried by the call MPI\_TEST\_CANCELLED.

Error codes belonging to the error class MPI\_ERR\_IN\_STATUS should be returned only by the MPI completion functions that take arrays of MPI\_Status. For the functions that take a single MPI\_Status argument, the error code is returned by the function, and the value of the MPI\_ERROR field in the MPI\_Status argument is undefined (see 3.2.5).

```
MPI_WAIT(request, status)
INOUT request request (handle)
OUT status status object (Status)

C binding
int MPI_Wait(MPI_Request *request, MPI_Status *status)
```

```
Fortran 2008 binding
MPI_Wait(request, status, ierror)
        TYPE(MPI_Request), INTENT(INOUT) :: request
        TYPE(MPI_Status) :: status
        INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI_WAIT(REQUEST, STATUS, IERROR)
        INTEGER REQUEST, STATUS(MPI_STATUS_SIZE), IERROR
```

A call to MPI\_WAIT returns when the operation identified by request is complete. If the request is an active persistent request, it is marked inactive. Any other type of request is deallocated and the request handle is set to MPI\_REQUEST\_NULL. MPI\_WAIT is a non-local operation.

The call returns, in status, information on the completed operation. The content of the status object for a receive operation can be accessed as described in Section 3.2.5. The status object for a send operation may be queried by a call to MPI\_TEST\_CANCELLED (see Section 3.8).

One is allowed to call MPI\_WAIT with a null or inactive request argument. In this case the operation returns immediately with empty status.

Advice to users. Successful return of MPI\_WAIT after a MPI\_IBSEND implies that the user send buffer can be reused—i.e., data has been sent out or copied into a buffer attached with MPI\_BUFFER\_ATTACH. Note that, at this point, we can no longer cancel the send (see Section 3.8). If a matching receive is never posted, then the buffer cannot be freed. This runs somewhat counter to the stated goal of MPI\_CANCEL (always being able to free program space that was committed to the communication subsystem). (End of advice to users.)

Advice to implementors. In a multithreaded environment, a call to MPI\_WAIT should block only the calling thread, allowing the thread scheduler to schedule another thread for execution. (End of advice to implementors.)

```
34
     MPI_TEST(request, flag, status)
35
       INOUT
                 request
                                             communication request (handle)
36
37
       OUT
                 flag
                                             true if operation completed (logical)
38
       OUT
                 status
                                             status object (Status)
39
40
     C binding
41
     int MPI_Test(MPI_Request *request, int *flag, MPI_Status *status)
42
43
     Fortran 2008 binding
44
     MPI_Test(request, flag, status, ierror)
45
          TYPE(MPI_Request), INTENT(INOUT) :: request
46
          LOGICAL, INTENT(OUT) :: flag
47
          TYPE(MPI_Status) :: status
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
Fortran binding
MPI_TEST(REQUEST, FLAG, STATUS, IERROR)
INTEGER REQUEST, STATUS(MPI_STATUS_SIZE), IERROR
LOGICAL FLAG
```

A call to MPI\_TEST returns flag = true if the operation identified by request is complete. In such a case, the status object is set to contain information on the completed operation. If the request is an active persistent request, it is marked as inactive. Any other type of request is deallocated and the request handle is set to MPI\_REQUEST\_NULL. The call returns flag = false if the operation identified by request is not complete. In this case, the value of the status object is undefined. MPI\_TEST is a local operation.

The return status object for a receive operation carries information that can be accessed as described in Section 3.2.5. The status object for a send operation carries information that can be accessed by a call to MPI\_TEST\_CANCELLED (see Section 3.8).

One is allowed to call  $MPI\_TEST$  with a null or inactive request argument. In such a case the operation returns with flag = true and empty status.

The functions MPI\_WAIT and MPI\_TEST can be used to complete both sends and receives.

Advice to users. The use of the nonblocking MPI\_TEST call allows the user to schedule alternative activities within a single thread of execution. An event-driven thread scheduler can be emulated with periodic calls to MPI\_TEST. (End of advice to users.)

## Example 3.11 Simple usage of nonblocking operations and MPI\_WAIT.

```
CALL MPI_COMM_RANK(comm, rank, ierr)
IF (rank .EQ. 0) THEN
   CALL MPI_ISEND(a(1), 10, MPI_REAL, 1, tag, comm, request, ierr)
   **** do some computation to mask latency ****
   CALL MPI_WAIT(request, status, ierr)
ELSE IF (rank .EQ. 1) THEN
   CALL MPI_IRECV(a(1), 15, MPI_REAL, 0, tag, comm, request, ierr)
   **** do some computation to mask latency ****
   CALL MPI_WAIT(request, status, ierr)
END IF
```

A request object can be freed using the following MPI procedure.

MPI\_Request\_free(request, ierror)

TYPE(MPI\_Request), INTENT(INOUT) :: request

```
MPI_REQUEST_FREE(request)

INOUT request communication request (handle)

C binding
int MPI_Request_free(MPI_Request *request)

Fortran 2008 binding
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_REQUEST_FREE(REQUEST, IERROR)
    INTEGER REQUEST, IERROR
```

MPI\_REQUEST\_FREE is a local operation. Upon successful return, MPI\_REQUEST\_FREE sets request to MPI\_REQUEST\_NULL. For an inactive request representing any type of MPI operation, MPI\_REQUEST\_FREE shall do the freeing stage of the associated operation during its execution.

For a request representing a nonblocking point-to-point or a persistent point-to-point operation, it is permitted (although strongly discouraged) to call MPI\_REQUEST\_FREE when the request is active. In this special case, MPI\_REQUEST\_FREE will only mark the request for freeing and MPI will actually do the freeing stage of the associated operation later.

The use of this routine for generalized requests is described in Section 13.2.

Calling MPI\_REQUEST\_FREE with an active request representing any other type of MPI operation (e.g., any partitioned operation (see Chapter 4), any collective operation (see Chapter 6), any I/O operation (see Chapter 14), or any request-based RMA operation (see Chapter 12)) is erroneous.

Rationale. For point-to-point operations, the MPI\_REQUEST\_FREE mechanism is provided for reasons of performance and convenience on the sending side. (*End of rationale.*)

Advice to users. Once a request is freed by a call to MPI\_REQUEST\_FREE, it is not possible to check for the successful completion of the associated communication with calls to MPI\_WAIT or MPI\_TEST. Also, if an error occurs subsequently during the communication, an error code cannot be returned to the user—such an error must be treated as fatal. An active receive request should never be freed as the receiver will have no way to verify that the receive has completed and the receive buffer can be reused. (End of advice to users.)

## **Example 3.12** An example using MPI\_REQUEST\_FREE.

```
35
     CALL MPI_COMM_RANK(MPI_COMM_WORLD, rank, ierr)
36
     IF (rank .EQ. 0) THEN
37
        DO i=1,n
38
           CALL MPI_ISEND(outval, 1, MPI_REAL, 1, 0, MPI_COMM_WORLD, req, ierr)
39
           CALL MPI_REQUEST_FREE(req, ierr)
           CALL MPI_IRECV(inval, 1, MPI_REAL, 1, 0, MPI_COMM_WORLD, req, ierr)
41
           CALL MPI_WAIT(req, status, ierr)
42
        END DO
43
     ELSE IF (rank .EQ. 1) THEN
44
        CALL MPI_IRECV(inval, 1, MPI_REAL, 0, 0, MPI_COMM_WORLD, req, ierr)
45
        CALL MPI_WAIT(req, status, ierr)
46
        DO I=1, n-1
47
           CALL MPI_ISEND(outval, 1, MPI_REAL, 0, 0, MPI_COMM_WORLD, req, ierr)
           CALL MPI_REQUEST_FREE(req, ierr)
```

```
CALL MPI_IRECV(inval, 1, MPI_REAL, 0, 0, MPI_COMM_WORLD, req, ierr)
CALL MPI_WAIT(req, status, ierr)
END DO
CALL MPI_ISEND(outval, 1, MPI_REAL, 0, 0, MPI_COMM_WORLD, req, ierr)
CALL MPI_WAIT(req, status, ierr)
END IF
```

## 3.7.4 Semantics of Nonblocking Communications

The semantics of nonblocking communication is defined by suitably extending the definitions in Section 3.5.

Order Nonblocking communication operations are ordered according to the execution order of the calls that initiate the communication. The non-overtaking requirement of Section 3.5 is extended to nonblocking communication, with this definition of order being used.

**Example 3.13** Message ordering for nonblocking operations.

```
CALL MPI_COMM_RANK(comm, rank, ierr)

IF (RANK .EQ. 0) THEN

CALL MPI_ISEND(a, 1, MPI_REAL, 1, 0, comm, r1, ierr)

CALL MPI_ISEND(b, 1, MPI_REAL, 1, 0, comm, r2, ierr)

ELSE IF (rank .EQ. 1) THEN

CALL MPI_IRECV(a, 1, MPI_REAL, 0, MPI_ANY_TAG, comm, r1, ierr)

CALL MPI_IRECV(b, 1, MPI_REAL, 0, 0, comm, r2, ierr)

END IF

CALL MPI_WAIT(r1, status, ierr)

CALL MPI_WAIT(r2, status, ierr)
```

The first send of process zero will match the first receive of process one, even if both messages are sent before process one executes either receive.

Progress A call to MPI\_WAIT that completes a receive will eventually terminate and return if a matching send has been started, unless the send is satisfied by another receive. In particular, if the matching send is nonblocking, then the receive should complete even if no call is executed by the sender to complete the send. Similarly, a call to MPI\_WAIT that completes a send will eventually return if a matching receive has been started, unless the receive is satisfied by another send, and even if no call is executed to complete the receive.

## Example 3.14 An illustration of progress semantics.

```
CALL MPI_COMM_RANK(comm, rank, ierr)

IF (RANK .EQ. 0) THEN

CALL MPI_SSEND(a, 1, MPI_REAL, 1, 0, comm, ierr)

CALL MPI_SEND(b, 1, MPI_REAL, 1, 1, comm, ierr)

ELSE IF (rank .EQ. 1) THEN

CALL MPI_IRECV(a, 1, MPI_REAL, 0, 0, comm, r, ierr)

CALL MPI_RECV(b, 1, MPI_REAL, 0, 1, comm, status, ierr)

CALL MPI_WAIT(r, status, ierr)

END IF
```

This code should not deadlock in a correct MPI implementation. The first synchronous send of process zero must complete after process one posts the matching (nonblocking) receive even if process one has not yet reached the completing wait call. Thus, process zero will continue and execute the second send, allowing process one to complete execution.

If an MPI\_TEST that completes a receive is repeatedly called with the same arguments, and a matching send has been started, then the call will eventually return flag = true, unless the send is satisfied by another receive. If an MPI\_TEST that completes a send is repeatedly called with the same arguments, and a matching receive has been started, then the call will eventually return flag = true, unless the receive is satisfied by another send.

## 3.7.5 Multiple Completions

It is convenient to be able to wait for the completion of any, some, or all the operations in a list, rather than having to wait for a specific message. A call to MPI\_WAITANY or MPI\_TESTANY can be used to wait for the completion of one out of several operations. A call to MPI\_WAITALL or MPI\_TESTALL can be used to wait for all pending operations in a list. A call to MPI\_WAITSOME or MPI\_TESTSOME can be used to complete all enabled operations in a list.

#### 

```
MPI_WAITANY(count, array_of_requests, index, status)
```

```
IN count list length (non-negative integer)

INOUT array_of_requests array of requests (array of handles)

OUT index index of handle for operation that completed (integer)

OUT status status object (Status)
```

## C binding

#### Fortran 2008 binding

```
MPI_Waitany(count, array_of_requests, index, status, ierror)
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(count)
    INTEGER, INTENT(OUT) :: index
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_WAITANY(COUNT, ARRAY_OF_REQUESTS, INDEX, STATUS, IERROR)
INTEGER COUNT, ARRAY_OF_REQUESTS(*), INDEX, STATUS(MPI_STATUS_SIZE),
IERROR
```

Blocks until one of the operations associated with the active requests in the array has completed. If more than one operation is enabled and can terminate, one is arbitrarily chosen. Returns in index the index of that request in the array and returns in status the status of the completing operation. (The array is indexed from zero in C, and from one in

6

10 11

12 13

14

15

16

17

18

19

20 21

22

23

24

26

27

28

29

30

33

34

35

36

37

38

40 41

42

43 44

45

46 47

Fortran.) If the request is an active persistent request, it is marked inactive. Any other type of request is deallocated and the request handle is set to MPI\_REQUEST\_NULL.

The array\_of\_requests list may contain null or inactive handles. If the list contains no active handles (list has length zero or all entries are null or inactive), then the call returns immediately with index = MPI\_UNDEFINED, and an empty status.

The execution of MPI\_WAITANY with an array containing multiple entries has the same effect as the execution of MPI\_WAIT with the array entry indicated by the output value of index (unless the output value of index is MPI\_UNDEFINED). MPI\_WAITANY with an array containing one active entry is equivalent to MPI\_WAIT.

## MPI\_TESTANY(count, array\_of\_requests, index, flag, status)

```
IN
                                          list length (non-negative integer)
           count
INOUT
           array_of_requests
                                          array of requests (array of handles)
OUT
          index
                                          index of operation that completed or
                                          MPI_UNDEFINED if none completed (integer)
OUT
                                          true if one of the operations is complete (logical)
          flag
OUT
                                          status object (Status)
          status
```

## C binding

#### Fortran 2008 binding

```
MPI_Testany(count, array_of_requests, index, flag, status, ierror)
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(count)
    INTEGER, INTENT(OUT) :: index
    LOGICAL, INTENT(OUT) :: flag
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_TESTANY(COUNT, ARRAY_OF_REQUESTS, INDEX, FLAG, STATUS, IERROR)

INTEGER COUNT, ARRAY_OF_REQUESTS(*), INDEX, STATUS(MPI_STATUS_SIZE),

IERROR

LOGICAL FLAG
```

Tests for completion of either one or none of the operations associated with active handles. In the former case, it returns flag = true, returns in index the index of this request in the array, and returns in status the status of that operation. If the request is an active persistent request, it is marked as inactive. Any other type of request is deallocated and the handle is set to MPI\_REQUEST\_NULL. (The array is indexed from zero in C, and from one in Fortran.) In the latter case (no operation completed), it returns flag = false, returns a value of MPI\_UNDEFINED in index and status is undefined.

The array may contain null or inactive handles. If the array contains no active handles then the call returns immediately with flag = true,  $index = MPI\_UNDEFINED$ , and an empty status.

#-error #-364+405 #-update12 (#-TODO) If the array of requests contains active handles then the execution of MPI\_TESTANY has the same effect as the execution of MPI\_TEST with each of the array elements in some arbitrary order, until one call returns flag = true, or all fail. In the former case, index is set to indicate which array element returned flag = true and in the latter case, it is set to MPI\_UNDEFINED. MPI\_TESTANY with an array containing one active entry is equivalent to MPI\_TEST.

MPI\_WAITALL(count, array\_of\_requests, array\_of\_statuses)

```
IN count lists length (non-negative integer)

INOUT array_of_requests array of requests (array of handles)

OUT array_of_statuses array of status objects (array of Status)
```

## C binding

#### Fortran 2008 binding

```
MPI_Waitall(count, array_of_requests, array_of_statuses, ierror)
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(count)
    TYPE(MPI_Status) :: array_of_statuses(*)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

Blocks until all communication operations associated with active handles in the list complete, and return the status of all these operations (this includes the case where no handle in the list is active). Both arrays have the same number of valid entries. The i-th entry in array\_of\_statuses is set to the return status of the i-th operation. Active persistent requests are marked inactive. Requests of any other type are deallocated and the corresponding handles in the array are set to MPI\_REQUEST\_NULL. The list may contain null or inactive handles. The call sets to empty the status of each such entry.

The error-free execution of MPI\_WAITALL has the same effect as the execution of MPI\_WAIT for each of the array elements in some arbitrary order. MPI\_WAITALL with an array of length one is equivalent to MPI\_WAIT.

When one or more of the communications completed by a call to MPI\_WAITALL fail, it is desirable to return specific information on each communication. The function MPI\_WAITALL will return in such case the error code MPI\_ERR\_IN\_STATUS and will set the error field of each status to a specific error code. This code will be MPI\_SUCCESS, if the specific communication completed; it will be another specific error code, if it failed; or it can be MPI\_ERR\_PENDING if it has neither failed nor completed. The function MPI\_WAITALL will return MPI\_SUCCESS if no request had an error, or will return another error code if it failed for other reasons (such as invalid arguments). In such cases, it will not update the error fields of the statuses.

Rationale. This design streamlines error handling in the application. The application code need only test the (single) function result to determine if an error has occurred. It needs to check each individual status only when an error occurred. (*End of rationale*.)

## MPI\_TESTALL(count, array\_of\_requests, flag, array\_of\_statuses)

```
IN count lists length (non-negative integer)

INOUT array_of_requests array of requests (array of handles)

OUT flag (logical)

OUT array_of_statuses array of status objects (array of Status)
```

## C binding

## Fortran 2008 binding

```
MPI_Testall(count, array_of_requests, flag, array_of_statuses, ierror)
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(count)
    LOGICAL, INTENT(OUT) :: flag
    TYPE(MPI_Status) :: array_of_statuses(*)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

Returns flag = true if all communications associated with active handles in the array have completed (this includes the case where no handle in the list is active). In this case, each status entry that corresponds to an active request is set to the status of the corresponding operation. Active persistent requests are marked inactive. Requests of any other type are deallocated and the corresponding handles in the array are set to MPI\_REQUEST\_NULL. Each status entry that corresponds to a null or inactive handle is set to empty.

Otherwise, flag = false is returned, no request is modified and the values of the status entries are undefined. This is a local operation.

Errors that occurred during the execution of MPI\_TESTALL are handled in the same manner as errors in MPI\_WAITALL.

#-error #-364+405 #-update12 (#-TODO)

29 30

31

32

33

34

35

36

37

38

39

40

41

42

43

44

45

46

47

48

```
1
     MPI_WAITSOME(incount, array_of_requests, outcount, array_of_indices, array_of_statuses)
2
3
       IN
                 incount
                                             length of array_of_requests (non-negative integer)
       INOUT
                 array_of_requests
                                             array of requests (array of handles)
5
6
       OUT
                 outcount
                                             number of completed requests (integer)
       OUT
                 array_of_indices
                                             array of indices of operations that completed (array
                                             of integers)
9
       OUT
                 array_of_statuses
                                             array of status objects for operations that completed
10
                                             (array of Status)
11
12
13
     C binding
14
     int MPI_Waitsome(int incount, MPI_Request array_of_requests[],
                     int *outcount, int array_of_indices[],
15
16
                    MPI_Status array_of_statuses[])
17
     Fortran 2008 binding
18
     MPI_Waitsome(incount, array_of_requests, outcount, array_of_indices,
19
                    array_of_statuses, ierror)
20
          INTEGER, INTENT(IN) :: incount
21
          TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(incount)
22
          INTEGER, INTENT(OUT) :: outcount, array_of_indices(*)
23
          TYPE(MPI_Status) :: array_of_statuses(*)
24
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
25
26
     Fortran binding
27
```

Waits until at least one of the operations associated with active handles in the list have completed. Returns in outcount the number of requests from the list array\_of\_requests that have completed. Returns in the first outcount locations of the array array\_of\_indices the indices of these operations (index within the array array\_of\_requests; the array is indexed from zero in C and from one in Fortran). Returns in the first outcount locations of the array array\_of\_status the status for these completed operations. Completed active persistent requests are marked as inactive. Any other type or request that completed is deallocated, and the associated handle is set to MPI\_REQUEST\_NULL.

If the list contains no active handles, then the call returns immediately with outcount = MPI\_UNDEFINED.

When one or more of the communications completed by MPI\_WAITSOME fails, then it is desirable to return specific information on each communication. The arguments outcount, array\_of\_indices and array\_of\_statuses will be adjusted to indicate completion of all communications that have succeeded or failed. The call will return the error code MPI\_ERR\_IN\_STATUS and the error field of each status returned will be set to indicate success or to indicate the specific error that occurred. The call will return MPI\_SUCCESS if no request resulted in an error, and will return another error code if it failed for other

12 13

14

15 16

17

18

19

20 21

22

23

24

26

27

28

29

30

34 35

36

37

38

42

43

44

45

46 47

reasons (such as invalid arguments). In such cases, it will not update the error fields of the statuses.

MPI\_TESTSOME(incount, array\_of\_requests, outcount, array\_of\_indices, array\_of\_statuses)

```
IN
           incount
                                          length of array_of_requests (non-negative integer)
INOUT
          array_of_requests
                                          array of requests (array of handles)
OUT
          outcount
                                          number of completed requests (integer)
           array_of_indices
OUT
                                          array of indices of operations that completed (array
                                          of integers)
OUT
          array_of_statuses
                                          array of status objects for operations that completed
                                          (array of Status)
```

## C binding

#### Fortran 2008 binding

## Fortran binding

```
MPI_TESTSOME(INCOUNT, ARRAY_OF_REQUESTS, OUTCOUNT, ARRAY_OF_INDICES,

ARRAY_OF_STATUSES, IERROR)

INTEGER INCOUNT, ARRAY_OF_REQUESTS(*), OUTCOUNT, ARRAY_OF_INDICES(*),

ARRAY_OF_STATUSES(MPI_STATUS_SIZE, *), IERROR
```

Behaves like MPI\_WAITSOME, except that it returns immediately. If no operation has completed it returns outcount = 0. If there is no active handle in the list it returns outcount = MPI\_UNDEFINED.

MPI\_WAITSOME is a local operation, which returns immediately, whereas MPI\_WAITSOME will block until a communication completes, if it was passed a list that contains at least one active handle. Both calls fulfill a **fairness** requirement: If a request for a receive repeatedly appears in a list of requests passed to MPI\_WAITSOME or MPI\_TESTSOME, and a matching send has been posted, then the receive will eventually succeed, unless the send is satisfied by another receive; and similarly for send requests.

Errors that occur during the execution of  $\mathsf{MPI\_TESTSOME}$  are handled as for  $\mathsf{MPI\_WAITSOME}$ .

Advice to users. The use of MPI\_TESTSOME is likely to be more efficient than the use of MPI\_TESTANY. The former returns information on all completed communications,

```
1
          with the latter, a new call is required for each communication that completes.
2
          A server with multiple clients can use MPI_WAITSOME so as not to starve any client.
          Clients send messages to the server with service requests. The server calls
          MPI_WAITSOME with one receive request for each client, and then handles all receives
          that completed. If a call to MPI_WAITANY is used instead, then one client could starve
          while requests from another client always sneak in first. (End of advice to users.)
                                   MPI_TESTSOME should complete as many pending com-
          Advice to implementors.
9
          munications as possible. (End of advice to implementors.)
10
11
     Example 3.15 Client-server code (starvation can occur).
12
13
     CALL MPI_COMM_SIZE(comm, size, ierr)
14
     CALL MPI_COMM_RANK(comm, rank, ierr)
15
     IF (rank .GT. 0) THEN
                                      ! client code
16
        DO WHILE(.TRUE.)
17
            CALL MPI_ISEND(a, n, MPI_REAL, 0, tag,
                                                       comm, request, ierr)
            CALL MPI_WAIT(request, status, ierr)
19
        END DO
20
     ELSE
                    ! rank=0 -- server code
21
        DO i=1, size-1
22
            CALL MPI_IRECV(a(1,i), n, MPI_REAL, i, tag, &
23
                             comm, request_list(i), ierr)
24
        END DO
25
        DO WHILE(.TRUE.)
26
            CALL MPI_WAITANY(size-1, request_list, index, status, ierr)
27
            CALL DO_SERVICE(a(1,index)) ! handle one message
28
            CALL MPI_IRECV(a(1, index), n, MPI_REAL, index, tag, &
29
                             comm, request_list(index), ierr)
30
        END DO
31
     END IF
32
33
34
     Example 3.16 Same code, using MPI_WAITSOME.
35
     CALL MPI_COMM_SIZE(comm, size, ierr)
36
     CALL MPI_COMM_RANK(comm, rank, ierr)
37
     IF (rank .GT. 0) THEN
                                       ! client code
38
        DO WHILE(.TRUE.)
39
            CALL MPI_ISEND(a, n, MPI_REAL, 0, tag, comm, request, ierr)
            CALL MPI_WAIT(request, status, ierr)
41
        END DO
42
     ELSE
                    ! rank=0 -- server code
43
        DO i=1, size-1
44
            CALL MPI_IRECV(a(1,i), n, MPI_REAL, i, tag, &
45
                             comm, request_list(i), ierr)
46
        END DO
47
```

DO WHILE(.TRUE.)

```
CALL MPI_WAITSOME(size, request_list, numdone, & indices, statuses, ierr)

DO i=1,numdone

CALL DO_SERVICE(a(1, indices(i)))

CALL MPI_IRECV(a(1, indices(i)), n, MPI_REAL, 0, tag, & comm, request_list(indices(i)), ierr)

END DO

END DO

END IF
```

#### 3.7.6 Non-Destructive Test of status

This call is useful for accessing the information associated with a request, without freeing the request (in case the user is expected to access it later). It allows one to layer libraries more conveniently, since multiple layers of software may access the same completed request and extract from it the status information.

## MPI\_REQUEST\_GET\_STATUS(request, flag, status)

```
    IN request request (handle)
    OUT flag boolean flag, same as from MPI_TEST (logical)
    OUT status
    Status object if flag is true (Status)
```

#### C binding

#### Fortran 2008 binding

```
MPI_Request_get_status(request, flag, status, ierror)
    TYPE(MPI_Request), INTENT(IN) :: request
    LOGICAL, INTENT(OUT) :: flag
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_REQUEST_GET_STATUS(REQUEST, FLAG, STATUS, IERROR)
INTEGER REQUEST, STATUS(MPI_STATUS_SIZE), IERROR
LOGICAL FLAG
```

Sets flag = true if the operation is complete, and, if so, returns in status the request status. However, unlike test or wait, it does not deallocate or inactivate the request; a subsequent call to test, wait or free should be executed with that request. It sets flag = false if the operation is not complete.

One is allowed to call MPI\_REQUEST\_GET\_STATUS with a null or inactive request argument. In such a case the operation returns with flag = true and empty status.

## 3.8 Probe and Cancel

 The MPI\_PROBE, MPI\_IPROBE, MPI\_MPROBE, and MPI\_IMPROBE operations allow incoming messages to be checked for, without actually receiving them. The user can then decide how to receive them, based on the information returned by the probe (basically, the information returned by status). In particular, the user may allocate memory for the receive buffer, according to the length of the probed message.

The MPI\_CANCEL operation allows pending communications to be cancelled. This is required for cleanup. Posting a send or a receive ties up user resources (send or receive buffers), and a **cancel** may be needed to free these resources gracefully.

Cancelling a send request by calling MPI\_CANCEL is deprecated. Cancelling a sendrecv request by calling MPI\_CANCEL is not allowed.

## 3.8.1 Probe

```
MPI_IPROBE(source, tag, comm, flag, status)
```

```
IN source rank of source or MPI_ANY_SOURCE (integer)
IN tag message tag or MPI_ANY_TAG (integer)
IN comm communicator (handle)
OUT flag (logical)
OUT status status object (Status)
```

#### C binding

## Fortran 2008 binding

```
MPI_Iprobe(source, tag, comm, flag, status, ierror)
    INTEGER, INTENT(IN) :: source, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
    LOGICAL, INTENT(OUT) :: flag
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_IPROBE(SOURCE, TAG, COMM, FLAG, STATUS, IERROR)
    INTEGER SOURCE, TAG, COMM, STATUS(MPI_STATUS_SIZE), IERROR
    LOGICAL FLAG
```

MPI\_IPROBE(source, tag, comm, flag, status) returns flag = true if there is a message that can be received and that matches the pattern specified by the arguments source, tag, and comm. The call matches the same message that would have been received by a call to MPI\_RECV(..., source, tag, comm, status) executed at the same point in the program, and returns in status the same value that would have been returned by MPI\_RECV(). Otherwise, the call returns flag = false, and leaves status undefined.

If MPI\_IPROBE returns flag = true, then the content of the status object can be subsequently accessed as described in Section 3.2.5 to find the source, tag and length of the probed message.

MPI\_IPROBE is a local procedure since its return does not depend on MPI calls in other MPI processes, which is marked with the prefix I (for immediate).

A subsequent receive executed with the same communicator, and the source and tag returned in status by MPI\_IPROBE will receive the message that was matched by the probe, if no other intervening receive occurs after the probe, and the send is not successfully cancelled before the receive. If the receiving process is multithreaded, it is the user's responsibility to ensure that the last condition holds.

The source argument of MPI\_PROBE can be MPI\_ANY\_SOURCE, and the tag argument can be MPI\_ANY\_TAG, so that one can probe for messages from an arbitrary source and/or with an arbitrary tag. However, a specific communication context must be provided with the comm argument.

It is not necessary to receive a message immediately after it has been probed for, and the same message may be probed for several times before it is received.

A probe with MPI\_PROC\_NULL as source returns flag = true, and the status object returns source = MPI\_PROC\_NULL, tag = MPI\_ANY\_TAG, and count = 0; see Section 3.10.

## MPI\_PROBE(source, tag, comm, status)

```
IN source rank of source or MPI_ANY_SOURCE (integer)
IN tag message tag or MPI_ANY_TAG (integer)
IN comm communicator (handle)
OUT status status object (Status)
```

## C binding

int MPI\_Probe(int source, int tag, MPI\_Comm comm, MPI\_Status \*status)

#### Fortran 2008 binding

```
MPI_Probe(source, tag, comm, status, ierror)
    INTEGER, INTENT(IN) :: source, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_PROBE(SOURCE, TAG, COMM, STATUS, IERROR)
INTEGER SOURCE, TAG, COMM, STATUS(MPI_STATUS_SIZE), IERROR
```

MPI\_PROBE behaves like MPI\_IPROBE except that it is a non-local call that returns only after a matching message has been found.

The MPI implementation of MPI\_PROBE and MPI\_IPROBE needs to guarantee progress: if a call to MPI\_PROBE has been issued by a process, and a send that matches the probe has been initiated by some process, then the call to MPI\_PROBE will return, unless the message is received by another concurrent receive operation (that is executed by another thread at the probing process). Similarly, if a process busy waits with MPI\_IPROBE and a matching message has been issued, then the call to MPI\_IPROBE will eventually return flag

= true unless the message is received by another concurrent receive operation or matched by a concurrent matched probe.

2 3 4

22

23 24

25

44 45

46

47

48

1

```
Example 3.17 Use probe to wait for an incoming message.
```

```
5
         CALL MPI_COMM_RANK(comm, rank, ierr)
6
         IF (rank .EQ. 0) THEN
            CALL MPI_SEND(i, 1, MPI_INTEGER, 2, 0, comm, ierr)
         ELSE IF (rank .EQ. 1) THEN
9
            CALL MPI_SEND(x, 1, MPI_REAL, 2, 0, comm, ierr)
10
         ELSE IF (rank .EQ. 2) THEN
11
            D0 i=1,2
12
               CALL MPI_PROBE(MPI_ANY_SOURCE, 0, &
13
                                comm, status, ierr)
14
               IF (status(MPI_SOURCE) .EQ. 0) THEN
15
                   CALL MPI_RECV(i, 1, MPI_INTEGER, 0, 0, comm, status, ierr)
     100
16
               ELSE
17
     200
                   CALL MPI_RECV(x, 1, MPI_REAL, 1, 0, comm, status, ierr)
18
               END IF
19
            END DO
20
         END IF
21
```

Each message is received with the right type.

**Example 3.18** A similar program to the previous example, but now it has a problem.

```
26
         CALL MPI_COMM_RANK(comm, rank, ierr)
27
         IF (rank .EQ. 0) THEN
28
            CALL MPI_SEND(i, 1, MPI_INTEGER, 2, 0, comm, ierr)
29
         ELSE IF (rank .EQ. 1) THEN
30
            CALL MPI_SEND(x, 1, MPI_REAL, 2, 0, comm, ierr)
         ELSE IF (rank .EQ. 2) THEN
            D0 i=1,2
33
               CALL MPI_PROBE(MPI_ANY_SOURCE, 0, &
34
                               comm, status, ierr)
35
               IF (status(MPI_SOURCE) .EQ. 0) THEN
36
     100
                   CALL MPI_RECV(i, 1, MPI_INTEGER, MPI_ANY_SOURCE, &
37
                                  0, comm, status, ierr)
38
               ELSE
39
     200
                   CALL MPI_RECV(x, 1, MPI_REAL, MPI_ANY_SOURCE, &
40
                                  0, comm, status, ierr)
41
               END IF
42
            END DO
43
         END IF
```

In Example 3.18, the two receive calls in statements labeled 100 and 200 in Example 3.17 are slightly modified, using MPI\_ANY\_SOURCE as the source argument. The program is now incorrect: the receive operation may receive a message that is distinct from the message probed by the preceding call to MPI\_PROBE.

6

12

13

14

15

16

19

20

21 22

23 24

26

27

28

29

30

31

33

34 35

36 37

38

39

41

42

43

44 45 46

47

Advice to users. In a multithreaded MPI program, MPI\_PROBE and MPI\_IPROBE might need special care. If a thread probes for a message and then immediately posts a matching receive, the receive may match a message other than that found by the probe since another thread could concurrently receive that original message [33]. MPI\_MPROBE and MPI\_IMPROBE solve this problem by matching the incoming message so that it may only be received with MPI\_MRECV or MPI\_IMRECV on the corresponding message handle. (End of advice to users.)

Advice to implementors. A call to MPI\_PROBE(source, tag, comm, status) will match the message that would have been received by a call to MPI\_RECV(..., source, tag, comm, status) executed at the same point. Suppose that this message has source s, tag t and communicator c. If the tag argument in the probe call has value MPI\_ANY\_TAG then the message probed will be the earliest pending message from source s with communicator c and any tag; in any case, the message probed will be the earliest pending message from source s with tag t and communicator c (this is the message that would have been received, so as to preserve message order). This message continues as the earliest pending message from source s with tag t and communicator c, until it is received. A receive operation subsequent to the probe that uses the same communicator as the probe and uses the tag and source values returned by the probe, must receive this message, unless it has already been received by another receive operation. (End of advice to implementors.)

## 3.8.2 Matching Probe

The function MPI\_PROBE checks for incoming messages without receiving them. Since the list of incoming messages is global among the threads of each MPI process, it can be hard to use this functionality in threaded environments [33, 30].

Like MPI\_PROBE and MPI\_IPROBE, the MPI\_MPROBE and MPI\_IMPROBE operations allow incoming messages to be queried without actually receiving them, except that MPI\_MPROBE and MPI\_IMPROBE provide a mechanism to receive the specific message that was matched regardless of other intervening probe or receive operations. This gives the application an opportunity to decide how to receive the message, based on the information returned by the probe. In particular, the user may allocate memory for the receive buffer, according to the length of the probed message.

## MPI\_IMPROBE(source, tag, comm, flag, message, status)

```
IN
                                         rank of source or MPI_ANY_SOURCE (integer)
          source
IN
                                         message tag or MPI_ANY_TAG (integer)
          tag
IN
          comm
                                         communicator (handle)
OUT
          flag
                                         flag (logical)
OUT
                                         returned message (handle)
          message
OUT
          status
                                         status object (Status)
```

#### C binding

```
1
     Fortran 2008 binding
2
     MPI_Improbe(source, tag, comm, flag, message, status, ierror)
3
         INTEGER, INTENT(IN) :: source, tag
4
         TYPE(MPI_Comm), INTENT(IN) :: comm
5
         LOGICAL, INTENT(OUT) :: flag
6
         TYPE(MPI_Message), INTENT(OUT) :: message
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
9
     Fortran binding
10
     MPI_IMPROBE(SOURCE, TAG, COMM, FLAG, MESSAGE, STATUS, IERROR)
11
         INTEGER SOURCE, TAG, COMM, MESSAGE, STATUS(MPI_STATUS_SIZE), IERROR
12
         LOGICAL FLAG
13
```

MPI\_IMPROBE(source, tag, comm, flag, message, status) returns flag = true if there is a message that can be received and that matches the pattern specified by the arguments source, tag, and comm. The call matches the same message that would have been received by a call to MPI\_RECV(..., source, tag, comm, status) executed at the same point in the program and returns in status the same value that would have been returned by MPI\_RECV. In addition, it returns in message a handle to the matched message. Otherwise, the call returns flag = false, and leaves status and message undefined.

MPI\_IMPROBE is a local procedure. According to the definitions in Section 2.4.2 and in contrast to MPI\_IPROBE, it is a nonblocking procedure because it is the initialization of a matched receive operation.

A matched receive (MPI\_MRECV or MPI\_IMRECV) executed with the message handle will receive the message that was matched by the probe. Unlike MPI\_IPROBE, no other probe or receive operation may match the message returned by MPI\_IMPROBE. Each message returned by MPI\_IMPROBE must be received with either MPI\_MRECV or MPI\_IMRECV.

The source argument of MPI\_IMPROBE can be MPI\_ANY\_SOURCE, and the tag argument can be MPI\_ANY\_TAG, so that one can probe for messages from an arbitrary source and/or with an arbitrary tag. However, a specific communication context must be provided with the comm argument.

A synchronous send operation that is matched with MPI\_IMPROBE or MPI\_MPROBE will complete successfully only if both a matching receive is posted with MPI\_MRECV or MPI\_IMRECV, and the receive operation has started to receive the message sent by the synchronous send.

There is a special predefined message: MPI\_MESSAGE\_NO\_PROC, which is a message which has MPI\_PROC\_NULL as its source process. The predefined constant MPI\_MESSAGE\_NULL is the value used for invalid message handles.

A matching probe with source = MPI\_PROC\_NULL returns flag = true, message = MPI\_MESSAGE\_NO\_PROC, and the status object returns source = MPI\_PROC\_NULL, tag = MPI\_ANY\_TAG, and count = 0; see Section 3.10. It is not necessary to call MPI\_MRECV or MPI\_IMRECV with MPI\_MESSAGE\_NO\_PROC, but it is not erroneous to do so.

Rationale. MPI\_MESSAGE\_NO\_PROC was chosen instead of MPI\_MESSAGE\_PROC\_NULL to avoid possible confusion as another null handle constant. (End of rationale.)

MPI\_MESSAGE\_PROC\_NULL must use \constskip and not \constmain becaue it is an invalid name, i.e., not an MPI constant

#-update8 | 46 #-405 #-PR449



14

15

16

18

19

20

21

22

23 24

26

27

28

29

30 31

33 34

35

36

37 38 39

#### MPI\_MPROBE(source, tag, comm, message, status) IN rank of source or MPI\_ANY\_SOURCE (integer) source IN message tag or MPI\_ANY\_TAG (integer) tag IN comm communicator (handle) OUT returned message (handle) message OUT status status object (Status)

## C binding

```
int MPI_Mprobe(int source, int tag, MPI_Comm comm, MPI_Message *message,
             MPI_Status *status)
```

#### Fortran 2008 binding

```
MPI_Mprobe(source, tag, comm, message, status, ierror)
   INTEGER, INTENT(IN) :: source, tag
   TYPE(MPI_Comm), INTENT(IN) :: comm
   TYPE(MPI_Message), INTENT(OUT) :: message
   TYPE(MPI_Status) :: status
   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

## Fortran binding

```
MPI_MPROBE(SOURCE, TAG, COMM, MESSAGE, STATUS, IERROR)
   INTEGER SOURCE, TAG, COMM, MESSAGE, STATUS(MPI_STATUS_SIZE), IERROR
```

MPI\_MPROBE behaves like MPI\_IMPROBE except that it is a blocking call that returns only after a matching message has been found.

The implementation of MPI\_MPROBE and MPI\_IMPROBE needs to guarantee progress in the same way as in the case of MPI\_PROBE and MPI\_IPROBE.

According to the definitions in Section 2.4.2, MPI\_MPROBE is incomplete. It is also a non-local procedure.

Advice to users. This is one of the exceptions in which incomplete procedures are non-local. (End of advice to users.)

#### 3.8.3 Matched Receives

The functions MPI\_MRECV and MPI\_IMRECV receive messages that have been previously matched by a matching probe (Section 3.8.2).

44

45

46

47

48

```
MPI_MRECV(buf, count, datatype, message, status)
2
       OUT
                 buf
                                            initial address of receive buffer (choice)
3
       IN
                 count
                                            number of elements in receive buffer (non-negative
4
                                            integer)
5
6
       IN
                                            datatype of each receive buffer element (handle)
                 datatype
       INOUT
                 message
                                            message (handle)
       OUT
                 status
                                            status object (Status)
9
10
11
     C binding
     int MPI_Mrecv(void *buf, int count, MPI_Datatype datatype,
12
                    MPI_Message *message, MPI_Status *status)
13
14
     int MPI_Mrecv_c(void *buf, MPI_Count count, MPI_Datatype datatype,
15
                    MPI_Message *message, MPI_Status *status)
16
17
     Fortran 2008 binding
     MPI_Mrecv(buf, count, datatype, message, status, ierror)
18
19
          TYPE(*), DIMENSION(..) :: buf
          INTEGER, INTENT(IN) :: count
20
          TYPE(MPI_Datatype), INTENT(IN) :: datatype
21
          TYPE(MPI_Message), INTENT(INOUT) :: message
22
23
          TYPE(MPI_Status) :: status
24
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
25
     MPI_Mrecv(buf, count, datatype, message, status, ierror)
26
          TYPE(*), DIMENSION(..) :: buf
27
          INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
28
          TYPE(MPI_Datatype), INTENT(IN) :: datatype
29
          TYPE(MPI_Message), INTENT(INOUT) :: message
30
          TYPE(MPI_Status) :: status
31
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
32
33
     Fortran binding
34
     MPI_MRECV(BUF, COUNT, DATATYPE, MESSAGE, STATUS, IERROR)
35
          <type> BUF(*)
36
          INTEGER COUNT, DATATYPE, MESSAGE, STATUS (MPI_STATUS_SIZE), IERROR
37
         This call receives a message matched by a matching probe operation (Section 3.8.2).
38
         The receive buffer consists of the storage containing count consecutive elements of the
39
     type specified by datatype, starting at address buf. The length of the received message must
40
     be less than or equal to the length of the receive buffer. An overflow error occurs if all
41
     incoming data does not fit, without truncation, into the receive buffer.
42
43
```

If the message is shorter than the receive buffer, then only those locations corresponding to the (shorter) message are modified.

On return from this function, the message handle is set to MPI\_MESSAGE\_NULL. All errors that occur during the execution of this operation are handled according to the error handler set for the communicator used in the matching probe call that produced the message handle.

MPI\_MESSAGE\_NULL.

If MPI\_MRECV is called with MPI\_MESSAGE\_NO\_PROC as the message argument, the call returns immediately with the status object set to source = MPI\_PROC\_NULL, tag = 3 MPI\_ANY\_TAG, and count = 0. This is consistent with the status object produced by a call to MPI\_RECV or to MPI\_PROBE with source = MPI\_PROC\_NULL (see Section 3.10). A call to MPI\_MRECV with MPI\_MESSAGE\_NULL is erroneous. MPI\_IMRECV(buf, count, datatype, message, request) OUT initial address of receive buffer (choice) IN number of elements in receive buffer (non-negative count integer) 12 IN datatype datatype of each receive buffer element (handle) 13 14 **INOUT** message (handle) message 15 OUT communication request (handle) request 16 C binding 18 int MPI\_Imrecv(void \*buf, int count, MPI\_Datatype datatype, 19 MPI\_Message \*message, MPI\_Request \*request) 20 21 int MPI\_Imrecv\_c(void \*buf, MPI\_Count count, MPI\_Datatype datatype, 22 MPI\_Message \*message, MPI\_Request \*request) 23 Fortran 2008 binding 24 MPI\_Imrecv(buf, count, datatype, message, request, ierror) TYPE(\*), DIMENSION(..), ASYNCHRONOUS :: buf 26 INTEGER, INTENT(IN) :: count 27 TYPE(MPI\_Datatype), INTENT(IN) :: datatype 28 TYPE(MPI\_Message), INTENT(INOUT) :: message 29 TYPE(MPI\_Request), INTENT(OUT) :: request 30 INTEGER, OPTIONAL, INTENT(OUT) :: ierror MPI\_Imrecv(buf, count, datatype, message, request, ierror) 33 TYPE(\*), DIMENSION(..), ASYNCHRONOUS :: buf 34 INTEGER(KIND=MPI\_COUNT\_KIND), INTENT(IN) :: count 35 TYPE(MPI\_Datatype), INTENT(IN) :: datatype 36 TYPE(MPI\_Message), INTENT(INOUT) :: message 37 TYPE(MPI\_Request), INTENT(OUT) :: request INTEGER, OPTIONAL, INTENT(OUT) :: ierror Fortran binding MPI\_IMRECV(BUF, COUNT, DATATYPE, MESSAGE, REQUEST, IERROR) 41 <type> BUF(\*) 42 INTEGER COUNT, DATATYPE, MESSAGE, REQUEST, IERROR 43 44 MPI\_IMRECV is the nonblocking variant of MPI\_MRECV and starts a nonblocking 45 receive of a matched message. Completion semantics are similar to MPI\_IRECV as described 46 in Section 3.7.2. On return from this function, the message handle is set to

If MPI\_IMRECV is called with MPI\_MESSAGE\_NO\_PROC as the message argument, the call returns immediately with a request object which, when completed, will yield a status object set to source = MPI\_PROC\_NULL, tag = MPI\_ANY\_TAG, and count = 0, as if a receive from MPI\_PROC\_NULL was issued (see Section 3.10). A call to MPI\_IMRECV with MPI\_MESSAGE\_NULL is erroneous.

Advice to implementors. If reception of a matched message is started with MPI\_IMRECV, then it is possible to cancel the returned request with MPI\_CANCEL. If MPI\_CANCEL succeeds, the matched message must be found by a subsequent message probe (MPI\_PROBE, MPI\_IPROBE, MPI\_MPROBE, or MPI\_IMPROBE), received by a subsequent receive operation or cancelled by the sender. See Section 3.8.4 for details about MPI\_CANCEL. The cancellation of operations initiated with MPI\_IMRECV may fail. (End of advice to implementors.)

3.8.4 Cancel

```
MPI_CANCEL(request)

IN request communication request (handle)
```

C binding int MPI\_Cancel(MPI\_Request \*request)

Fortran 2008 binding

```
MPI_Cancel(request, ierror)
    TYPE(MPI_Request), INTENT(IN) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

Fortran binding

```
MPI_CANCEL(REQUEST, IERROR)
INTEGER REQUEST, IERROR
```

A call to MPI\_CANCEL marks for cancellation a pending, nonblocking communication operation (send or receive). Cancelling a send request by calling MPI\_CANCEL is deprecated. The cancel call is local. It returns immediately, possibly before the communication is actually cancelled. It is still necessary to call MPI\_REQUEST\_FREE, MPI\_WAIT or MPI\_TEST (or any of the derived operations) with the cancelled request as argument after the call to MPI\_CANCEL. If a communication is marked for cancellation, then a MPI\_WAIT call for that communication is guaranteed to return, irrespective of the activities of other processes (i.e., MPI\_WAIT behaves as a local function); similarly if MPI\_TEST is repeatedly called in a busy wait loop for a cancelled communication, then MPI\_TEST will eventually be successful.

MPI\_CANCEL can be used to cancel a communication that uses a persistent request (see Section 3.9), in the same way it is used for nonpersistent requests. Cancelling a persistent send request by calling MPI\_CANCEL is deprecated. A successful cancellation cancels the active communication, but not the request itself. After the call to MPI\_CANCEL and the subsequent call to MPI\_WAIT or MPI\_TEST, the request becomes inactive and can be activated for a new communication.

The successful cancellation of a buffered send frees the buffer space occupied by the pending message. Cancelling a buffered send request by calling MPI\_CANCEL is deprecated.

Either the cancellation succeeds, or the communication succeeds, but not both. If a send is marked for cancellation, which is deprecated, then it must be the case that either the send completes normally, in which case the message sent was received at the destination process, or that the send is successfully cancelled, in which case no part of the message was received at the destination. Then, any matching receive has to be satisfied by another send. If a receive is marked for cancellation, then it must be the case that either the receive completes normally, or that the receive is successfully cancelled, in which case no part of the receive buffer is altered. Then, any matching send has to be satisfied by another receive.

If the operation has been cancelled, then information to that effect will be returned in the status argument of the operation that completes the communication.

Rationale. Although the IN request handle parameter should not need to be passed by reference, the C binding has listed the argument type as MPI\_Request\* since MPI\_1.0. This function signature therefore cannot be changed without breaking existing MPI applications. (End of rationale.)

```
MPI_TEST_CANCELLED(status, flag)
```

```
IN status status object (Status)
OUT flag (logical)
```

## C binding

```
int MPI_Test_cancelled(const MPI_Status *status, int *flag)
```

## Fortran 2008 binding

```
MPI_Test_cancelled(status, flag, ierror)
    TYPE(MPI_Status), INTENT(IN) :: status
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_TEST_CANCELLED(STATUS, FLAG, IERROR)
INTEGER STATUS(MPI_STATUS_SIZE), IERROR
LOGICAL FLAG
```

Returns flag = true if the communication associated with the status object was cancelled successfully. In such a case, all other fields of status (such as count or tag) are undefined. Returns flag = false, otherwise. If a receive operation might be cancelled then one should call MPI\_TEST\_CANCELLED first, to check whether the operation was cancelled, before checking on the other fields of the return status.

Advice to users. Cancel can be an expensive operation that should be used only exceptionally. (End of advice to users.)

Advice to implementors. If a send operation uses an "eager" protocol (data is transferred to the receiver before a matching receive is posted), then the cancellation

6

9 10

11 12 13

14

15

16

17

18

19

20

21

22

23

24

25

26

31

32

33

34 35

36

37

38

45 46

47

CHAPTER 3. POINT-TO-POINT COMMUNICATION

of this send may require communication with the intended receiver in order to free allocated buffers. On some systems this may require an interrupt to the intended receiver. Note that, while communication may be needed to implement

MPI\_CANCEL, this is still a local operation, since its completion does not depend on the code executed by other processes. If processing is required on another process, this should be transparent to the application (hence the need for an interrupt and an interrupt handler). (End of advice to implementors.)

#### 3.9 Persistent Communication Requests

Often a communication with the same argument list (with the exception of the buffer contents) is repeatedly executed within the inner loop of a parallel computation. In such a situation, it may be possible to optimize the communication by binding the list of communication arguments to a **persistent** communication request once and, then, repeatedly using the request to initiate and complete operations. In the case of point-to-point communication, the persistent request thus created can be thought of as a communication port or a "half-channel." It does not provide the full functionality of a conventional channel, since there is no binding of the send port to the receive port. This construct allows reduction of the overhead for communication between the process and communication controller, but not of the overhead for communication between one communication controller and another. It is not necessary that messages sent with a persistent point-to-point request be received by a receive operation using a persistent point-to-point request, or vice versa.

There are also collective communication persistent operations defined in Section 6.13 and Section 8.8. The remainder of this section covers the point-to-point persistent initialization operations and the start routines, which are used for both point-to-point and collective persistent communication.

A persistent point-to-point communication request is created using one of the five following calls. These point-to-point persistent calls involve no communication.

## MPI\_SEND\_INIT(buf, count, datatype, dest, tag, comm, request)

```
buf
IN
                                           initial address of send buffer (choice)
IN
           count
                                           number of elements sent (non-negative integer)
ĪN
           datatype
                                           type of each element (handle)
IN
           dest
                                           rank of destination (integer)
IN
                                           message tag (integer)
           tag
IN
                                           communicator (handle)
           comm
OUT
                                           communication request (handle)
           request
```

## C binding

```
int MPI_Send_init(const void *buf, int count, MPI_Datatype datatype,
             int dest, int tag, MPI_Comm comm, MPI_Request *request)
int MPI_Send_init_c(const void *buf, MPI_Count count,
             MPI_Datatype datatype, int dest, int tag, MPI_Comm comm,
             MPI_Request *request)
```

```
Fortran 2008 binding
MPI_Send_init(buf, count, datatype, dest, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Send_init(buf, count, datatype, dest, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                      12
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      13
    INTEGER, INTENT(IN) :: dest, tag
                                                                                      14
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                      15
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                      16
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      18
Fortran binding
                                                                                      19
MPI_SEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
                                                                                      20
    <type> BUF(*)
                                                                                      21
    INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
                                                                                      22
    Creates a persistent communication request for a standard mode send operation, and
                                                                                     23
binds to it all the arguments of a send operation.
                                                                                      24
                                                                                      26
MPI_BSEND_INIT(buf, count, datatype, dest, tag, comm, request)
                                                                                      27
 IN
                                     initial address of send buffer (choice)
           buf
                                                                                      28
 IN
                                      number of elements sent (non-negative integer)
                                                                                      29
           count
                                                                                      30
 IN
           datatype
                                      type of each element (handle)
 IN
           dest
                                      rank of destination (integer)
                                                                                      33
 IN
           tag
                                      message tag (integer)
                                                                                      34
  IN
                                      communicator (handle)
           comm
                                                                                      35
  OUT
                                      communication request (handle)
           request
                                                                                      36
                                                                                      37
C binding
int MPI_Bsend_init(const void *buf, int count, MPI_Datatype datatype,
              int dest, int tag, MPI_Comm comm, MPI_Request *request)
int MPI_Bsend_init_c(const void *buf, MPI_Count count,
                                                                                      42
              MPI_Datatype datatype, int dest, int tag, MPI_Comm comm,
                                                                                      43
              MPI_Request *request)
                                                                                      44
Fortran 2008 binding
                                                                                      45
MPI_Bsend_init(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                      46
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
```

```
1
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
2
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
5
     MPI_Bsend_init(buf, count, datatype, dest, tag, comm, request, ierror)
6
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
9
         INTEGER, INTENT(IN) :: dest, tag
10
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
12
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
14
     Fortran binding
15
     MPI_BSEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
16
         <type> BUF(*)
17
         INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
         Creates a persistent communication request for a buffered mode send.
19
20
21
     MPI_SSEND_INIT(buf, count, datatype, dest, tag, comm, request)
22
       IN
                buf
                                           initial address of send buffer (choice)
23
^{24}
       IN
                                           number of elements sent (non-negative integer)
                count
       IN
                datatype
                                           type of each element (handle)
26
       IN
                dest
                                           rank of destination (integer)
27
       IN
28
                tag
                                           message tag (integer)
29
       IN
                                           communicator (handle)
                comm
30
       OUT
                request
                                           communication request (handle)
31
32
     C binding
33
     int MPI_Ssend_init(const void *buf, int count, MPI_Datatype datatype,
34
                    int dest, int tag, MPI_Comm comm, MPI_Request *request)
35
36
     int MPI_Ssend_init_c(const void *buf, MPI_Count count,
37
                   MPI_Datatype datatype, int dest, int tag, MPI_Comm comm,
38
                   MPI_Request *request)
39
     Fortran 2008 binding
     MPI_Ssend_init(buf, count, datatype, dest, tag, comm, request, ierror)
41
42
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
         INTEGER, INTENT(IN) :: count, dest, tag
43
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
44
         TYPE(MPI_Comm), INTENT(IN) :: comm
45
         TYPE(MPI_Request), INTENT(OUT) :: request
47
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
MPI_Ssend_init(buf, count, datatype, dest, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: dest, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_SSEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
    <type> BUF(*)
                                                                                     12
    INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
                                                                                     13
                                                                                     14
    Creates a persistent communication object for a synchronous mode send operation.
                                                                                     15
                                                                                     16
MPI_RSEND_INIT(buf, count, datatype, dest, tag, comm, request)
                                                                                     18
 IN
           buf
                                     initial address of send buffer (choice)
                                                                                     19
                                     number of elements sent (non-negative integer)
 IN
           count
                                                                                     20
 IN
           datatype
                                     type of each element (handle)
                                                                                     21
                                                                                     22
 IN
           dest
                                     rank of destination (integer)
                                                                                     23
                                     message tag (integer)
 IN
           tag
 IN
                                     communicator (handle)
           comm
                                                                                     26
                                     communication request (handle)
 OUT
           request
                                                                                     27
                                                                                     28
C binding
                                                                                     29
int MPI_Rsend_init(const void *buf, int count, MPI_Datatype datatype,
                                                                                     30
              int dest, int tag, MPI_Comm comm, MPI_Request *request)
int MPI_Rsend_init_c(const void *buf, MPI_Count count,
              MPI_Datatype datatype, int dest, int tag, MPI_Comm comm,
                                                                                     33
              MPI_Request *request)
                                                                                     34
                                                                                     35
Fortran 2008 binding
                                                                                     36
MPI_Rsend_init(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                     37
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                     42
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                     43
MPI_Rsend_init(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                     44
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                     45
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                     46
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: dest, tag
```

```
1
         TYPE(MPI_Comm), INTENT(IN) :: comm
2
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
5
     MPI_RSEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
6
         <type> BUF(*)
         INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
9
         Creates a persistent communication object for a ready mode send operation.
10
11
     MPI_RECV_INIT(buf, count, datatype, source, tag, comm, request)
12
13
                                           initial address of receive buffer (choice)
       OUT
                buf
14
       IN
                count
                                           number of elements received (non-negative integer)
15
                                           type of each element (handle)
       IN
                datatype
16
17
       IN
                source
                                           rank of source or MPI_ANY_SOURCE (integer)
                                           message tag or MPI_ANY_TAG (integer)
       IN
                tag
19
       IN
                comm
                                           communicator (handle)
20
21
       OUT
                request
                                           communication request (handle)
22
23
     C binding
24
     int MPI_Recv_init(void *buf, int count, MPI_Datatype datatype, int source,
25
                    int tag, MPI_Comm comm, MPI_Request *request)
26
     int MPI_Recv_init_c(void *buf, MPI_Count count, MPI_Datatype datatype,
27
                    int source, int tag, MPI_Comm comm, MPI_Request *request)
28
29
     Fortran 2008 binding
30
     MPI_Recv_init(buf, count, datatype, source, tag, comm, request, ierror)
31
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
32
         INTEGER, INTENT(IN) :: count, source, tag
33
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
34
         TYPE(MPI_Comm), INTENT(IN) :: comm
35
         TYPE(MPI_Request), INTENT(OUT) :: request
36
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
37
     MPI_Recv_init(buf, count, datatype, source, tag, comm, request, ierror)
38
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
39
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
41
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
42
         INTEGER, INTENT(IN) :: source, tag
         TYPE(MPI_Comm), INTENT(IN) :: comm
43
         TYPE(MPI_Request), INTENT(OUT) :: request
44
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
46
     Fortran binding
47
     MPI_RECV_INIT(BUF, COUNT, DATATYPE, SOURCE, TAG, COMM, REQUEST, IERROR)
48
```

```
<type> BUF(*)
INTEGER COUNT, DATATYPE, SOURCE, TAG, COMM, REQUEST, IERROR
```

Creates a persistent communication request for a receive operation. The argument buf is marked as OUT because the user gives permission to write on the receive buffer by passing the argument to MPI\_RECV\_INIT.

A persistent communication request is inactive after it was created—no active communication is attached to the request.

A communication that uses a persistent request is initiated by the function MPI\_START.

```
MPI_START(request)

INOUT request communication request (handle)

C binding
int MPI_Start(MPI_Request *request)

Fortran 2008 binding

MPI_Start(request, ierror)
    TYPE(MPI_Request), INTENT(INOUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding

MPI_START(REQUEST, IERROR)
    INTEGER REQUEST, IERROR
```

The argument, request, is a handle returned by one of the previous five calls. The associated request should be inactive. The request becomes active once the call is made.

If the request is for a send with ready mode, then a matching receive should be posted before the call is made. The communication buffer should not be modified after the call, and until the operation completes.

The call is local, with similar semantics to the nonblocking communication operations described in Section 3.7. That is, a call to MPI\_START with a request created by MPI\_SEND\_INIT starts a communication in the same manner as a call to MPI\_ISEND; a call to MPI\_START with a request created by MPI\_BSEND\_INIT starts a communication in the same manner as a call to MPI\_IBSEND; and so on.

```
TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(count)
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_STARTALL(COUNT, ARRAY_OF_REQUESTS, IERROR)
    INTEGER COUNT, ARRAY_OF_REQUESTS(*), IERROR
```

Start all communications associated with requests in  $array_of_requests$ . A call to MPI\_STARTALL(count,  $array_of_requests$ ) has the same effect as calls to

MPI\_START (&array\_of\_requests[i]), executed for i=0,..., count-1, in some arbitrary order. A communication started with a call to MPI\_START or MPI\_STARTALL is completed by a call to MPI\_WAIT, MPI\_TEST, or one of the derived functions described in Section 3.7.5. The request becomes inactive after successful completion of such call. The request is not deallocated and it can be activated anew by an MPI\_START or MPI\_STARTALL call.

A persistent request is deallocated by a call to MPI\_REQUEST\_FREE (Section 3.7.3).

The call to MPI\_REQUEST\_FREE can occur at any point in the program after the persistent request was created. However, the request will be deallocated only after it becomes inactive. Active receive requests should not be freed. Otherwise, it will not be possible to check that the receive has completed. Collective operation requests (defined in Section 6.12 and Section 8.7 for nonblocking collective operations, and Section 6.13 and Section 8.8 for persistent collective operations) must not be freed while active. It is preferable, in general, to free requests when they are inactive. If this rule is followed, then the functions described in this section will be invoked in a sequence of the form,

## Create (Start Complete)\* Free

where \* indicates zero or more repetitions. If the same communication object is used in several concurrent threads, it is the user's responsibility to coordinate calls so that the correct sequence is obeyed.

A send operation initiated with MPI\_START can be matched with any receive operation and, likewise, a receive operation initiated with MPI\_START can receive messages generated by any send operation.

Advice to users. To prevent problems with the argument copying and register optimization done by Fortran compilers, please note the hints in Sections 19.1.10–19.1.20. (End of advice to users.)


## 3.10 Null Processes

In many instances, it is convenient to specify a "dummy" source or destination for communication. This simplifies the code that is needed for dealing with boundaries, for example, in the case of a non-circular shift done with calls to send-receive.

The special value MPI\_PROC\_NULL can be used instead of a rank wherever a source or a destination argument is required in a call. A communication with process MPI\_PROC\_NULL has no effect. A send to MPI\_PROC\_NULL succeeds and returns as soon as possible. A receive from MPI\_PROC\_NULL succeeds and returns as soon as possible with no modifications to the receive buffer. When a receive with source = MPI\_PROC\_NULL is executed then the status object returns source = MPI\_PROC\_NULL, tag = MPI\_ANY\_TAG and count = 0. A

probe or matching probe with source = MPI\_PROC\_NULL succeeds and returns as soon as possible, and the status object returns source = MPI\_PROC\_NULL, tag = MPI\_ANY\_TAG and count = 0. A matching probe (cf. Section 3.8.2) with source = MPI\_PROC\_NULL returns flag = true, message = MPI\_MESSAGE\_NO\_PROC, and the status object returns source = MPI\_PROC\_NULL, tag = MPI\_ANY\_TAG, and count = 0.





# Chapter 4

# Partitioned Point-to-Point Communication

## 4.1 Introduction

Partitioned communication extends persistent point-to-point communication as defined in Chapter 3. Partitioned communication operations are matched based on the order in which the local initialization calls are performed. Partitioned communication is "partitioned" because it allows for multiple contributions of data to be made, potentially, from multiple actors (e.g., threads or tasks) in an MPI process to a single communication operation.

Advice to users. The techniques of partitioned communication were known as "fine-points" before their adoption into the MPI standard. We refer the interested reader to the original literature describing the design goals, functioning, initial implementation and performance improvements [28, 29]. (End of advice to users.)

Partitioned communication operations use a persistent communication style that involves a sequence of start and test or wait operations. For this sequence partitioned communications use MPI\_START or MPI\_STARTALL calls and completion mechanisms (MPI\_TEST or MPI\_WAIT). Partitioned communication is different in three fundamental ways from persistent point-to-point operations in MPI. First, partitioned communication allows additional partitioned test function calls that can expose partial completion of the operation. Second, partitioned communication may perform all of the initialization required to enable data transfer as early as its initialization phase. Third, partitioned communication allows for MPI to be independently notified of multiple contributions from the send-side to a single data buffer of a single MPI message.

Rationale. The rationale behind having different initialization behavior allowed for partitioned communication as opposed to persistent point-to-point is to enable flexibility and optimization possibilities in implementations. Buffer setup can occur in the partitioned communication initialization functions (see Section 4.2.1). However, such negotiation can be deferred until data is to be moved between two processes. This means that partitioned communication can lazily negotiate as late as testing for completion of the operation on the first iteration of a partitioned communication start and test or wait operations. Matching still occurs as if matching happened at the partitioned communication initialization functions as noted in the function descriptions. (End of rationale.)

## 4.2 Semantics of Partitioned Point-to-Point Communication

MPI guarantees certain general properties of partitioned point-to-point communication progress, which are described in this section.

Persistent communications use opaque MPI\_REQUEST objects as described in Section 3. Partitioned communication uses these same semantics for MPI\_REQUEST objects.

Partitioned communication provides fine-grained transfers on either or both sides of a send-receive operation described by requests. Persistent communication semantics are ideal for partitioned communication: they provide MPI\_PSEND\_INIT and MPI\_PRECV\_INIT functions that allow partitioned communication setup to occur prior to message transfers. Partitioned communication initialization functions are local. The partitioned communication initialization includes inputs on the number of user-visible partitions on the send-side and receive-sides, which may differ. Valid partitioned communication operations must have one or more partitions specified.

Once an MPI\_PSEND\_INIT call has been made, the user may start the operation with a call to a starting procedure and complete the operation with a number of MPI\_PREADY calls equal to the requested number of send partitions followed by a call to a completing procedure. A call to MPI\_PREADY notifies the MPI library that a specified portion of the data buffer (a specific partition) is ready to be sent. Notification of partial completion can be done via fine-grained MPI\_PARRIVED calls at the receiver before a final MPI\_TEST/ MPI\_WAIT on the request itself; the latter represents overall operation completion upon success. A full set of methods for starting and completing partitioned communication is given in the following sections.

Advice to users. Having a large number of receiver-side partitions can increase overheads as the completion mechanism may need to work with finer-grained notifications. Using a small number of receiver-side partitions may provide higher performance.

A large number of sender-side partitions may be aggregated by an MPI implementation, making performance concerns of a large number of sender-side partitions potentially less impactful than receiver-side granularity. (*End of advice to users.*)

Advice to implementors. It is expected that an MPI implementation will attempt to balance latency and aggregation for data transfers for the requested partition counts on the sender-side and receiver-side to allow optimization for different hardware. A high quality implementation may perform significant optimizations to enhance performance in this way; they may, for example, resize the data transfers of the partitions to combine partitions in fractional partition sizes (e.g., 2.5 partitions in a single data transfer). (End of advice to implementors.)

Example 4.1 shows a simple partitioned transfer in which the sender-side and receiver-side partitioning is identical in partition count.

## Example 4.1

```
#include "mpi.h"
#define PARTITIONS 8
#define COUNT 5
int main(int argc, char *argv[])
  double message[PARTITIONS*COUNT];
 MPI_Count partitions = PARTITIONS;
  int source = 0, dest = 1, tag = 1, flag = 0;
  int myrank, i;
  int provided;
  MPI_Request request;
 MPI_Init_thread(&argc, &argv, MPI_THREAD_SERIALIZED, &provided);
                                                                                     12
  if (provided < MPI_THREAD_SERIALIZED)</pre>
                                                                                     13
                                                                                     14
     MPI_Abort(MPI_COMM_WORLD, EXIT_FAILURE);
                                                                                     15
 MPI_Comm_rank(MPI_COMM_WORLD, &myrank);
                                                                                     16
  if (myrank == 0)
  {
     MPI_Psend_init(message, partitions, COUNT, MPI_DOUBLE, dest, tag,
                                                                                     18
                                                                                     19
                MPI_COMM_WORLD, MPI_INFO_NULL, &request);
     MPI_Start(&request);
                                                                                     20
                                                                                    21
     for(i = 0; i < partitions; ++i)</pre>
                                                                                    22
     {
                                                                                    23
        /* compute and fill partition #i, then mark ready: */
                                                                                     24
        MPI_Pready(i, &request);
     }
                                                                                     26
     while(!flag)
                                                                                    27
        /* do useful work #1 */
                                                                                    28
                                                                                    29
        MPI_Test(&request, &flag, MPI_STATUS_IGNORE);
                                                                                    30
        /* do useful work #2 */
     MPI_Request_free(&request);
                                                                                     33
  }
                                                                                    34
  else if (myrank == 1)
                                                                                    35
     MPI_Precv_init(message, partitions, COUNT, MPI_DOUBLE, source, tag,
                                                                                    36
                                                                                    37
                MPI_COMM_WORLD, MPI_INFO_NULL, &request);
     MPI_Start(&request);
                                                                                     39
     while(!flag)
        /* do useful work #1 */
                                                                                     42
        MPI_Test(&request, &flag, MPI_STATUS_IGNORE);
        /* do useful work #2 */
                                                                                     43
                                                                                     44
     }
                                                                                     45
     MPI_Request_free(&request);
                                                                                     46
 MPI_Finalize();
  return 0;
```

}

1

3

5

6

9

10

11

12

13 14

15 16

17

18

19

20

21

22

23

242526

27

28

29 30

31

32

33

34

35

36

37

38 39

40 41

42

43

44

45

46

47

Rationale. Partitioned communication is designed to provide opportunities for MPI implementations to optimize data transfers. MPI is free to choose how many transfers to do within a partitioned communication send independent of how many partitions are reported as ready to MPI through MPI\_PREADY calls. Aggregation of partitions is permitted but not required. Ordering of partitions is permitted but not required. A naive implementation can simply wait for the entire message buffer to be marked ready before any transfer(s) occur and could wait until the completion function is called on a request before transferring data. However, this modality of communication gives MPI implementations far more flexibility in data movement than non-partitioned communications. (End of rationale.)

## 4.2.1 Communication Initialization and Starting with Partitioning

Initialization of partitioned communication operations use the initialization calls described below. Subsequent to initialization, MPI\_START/MPI\_STARTALL are used as the first indication to MPI that a message transfer will occur. For send-side operations, neither initializing nor starting the operation enables transfer of any part of the user buffer. Freeing or canceling a partitioned communication request that is active (i.e., initialized and started) and not completed is erroneous. After the partitioned communication operation is started, individual partitions of a message are indicated as ready to be sent by MPI via the MPI\_PREADY function, described below.

```
MPI_PSEND_INIT(buf, partitions, count, datatype, dest, tag, comm, info, request)
```

```
IN
           buf
                                           initial address of send buffer (choice) (choice)
IN
           partitions
                                           number of partitions (non-negative integer)
IN
           count
                                           number of elements send per partition (non-negative
                                           integer)
                                           type of each element (handle)
IN
           datatype
IN
           dest
                                           rank of destination (integer)
ĺΝ
           tag
                                           message tag (integer)
IN
                                           communicator (handle)
           comm
IN
           info
                                           info argument (handle)
OUT
           request
                                           communication request (handle)
```

#### C binding

#### Fortran 2008 binding

13

14

15 16

17

18

19

20

21

22

23 24

26

27

28

29 30 31

```
TYPE(*), DIMENSION(..), INTENT(IN) :: buf
INTEGER, INTENT(IN) :: partitions, dest, tag
INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
TYPE(MPI_Datatype), INTENT(IN) :: datatype
TYPE(MPI_Comm), INTENT(IN) :: comm
TYPE(MPI_Info), INTENT(IN) :: info
TYPE(MPI_Request), INTENT(OUT) :: request
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_PSEND_INIT(BUF, PARTITIONS, COUNT, DATATYPE, DEST, TAG, COMM, INFO,
             REQUEST, IERROR)
```

<type> BUF(\*)

INTEGER PARTITIONS, DATATYPE, DEST, TAG, COMM, INFO, REQUEST, IERROR INTEGER(KIND=MPI\_COUNT\_KIND) COUNT

MPI\_PSEND\_INIT creates a partitioned communication request and binds to it all the arguments of a partitioned send operation. Matching follows the same MPI matching rules as for point-to-point communication (see Chapter 3) with communicator, tag and source dictating message matching. In the event that the communicator, tag and source do not uniquely identify a message, the order in which partitioned communication initialization calls are made is the order in which they will eventually match. This operation can only match with partitioned communication initialization operations, therefore it is required to be matched with a corresponding MPI\_PRECV\_INIT call. Partitioned communication initialization calls are local. It is erroneous to provide a partitions value < 0. Send-side and receive-side buffers must be identical in size.

Advice to implementors. Unlike MPI\_SEND\_INIT, MPI\_PSEND\_INIT can be matched as early as the initialization call. Also, unlike MPI\_SEND\_INIT, MPI\_PSEND\_INIT takes an info argument. (End of advice to implementors.)

## MPI\_PRECV\_INIT(buf, partitions, count, datatype, dest, tag, comm, info, request)

IN	buf	initial address of recv buffer (choice) (choice)
IN	partitions	number of partitions (non-negative integer)
IN	count	number of elements send per partition (non-negative integer) $$
IN	datatype	type of each element (handle)
IN	dest	rank of destination (integer)
IN	tag	message tag (integer)
IN	comm	communicator (handle)
IN	info	info argument (handle)
OUT	request	communication request (handle)

## C binding

```
1
     int MPI_Precv_init(void *buf, int partitions, MPI_Count count,
2
                   MPI_Datatype datatype, int dest, int tag, MPI_Comm comm,
3
                   MPI_Info info, MPI_Request *request)
4
     Fortran 2008 binding
5
     MPI_Precv_init(buf, partitions, count, datatype, dest, tag, comm, info,
6
                   request, ierror)
         TYPE(*), DIMENSION(...), INTENT(IN) :: buf
         INTEGER, INTENT(IN) :: partitions, dest, tag
9
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
10
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
11
         TYPE(MPI_Comm), INTENT(IN) :: comm
12
         TYPE(MPI_Info), INTENT(IN) :: info
13
         TYPE(MPI_Request), INTENT(OUT) :: request
14
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
15
16
     Fortran binding
17
     MPI_PRECV_INIT(BUF, PARTITIONS, COUNT, DATATYPE, DEST, TAG, COMM, INFO,
18
                   REQUEST, IERROR)
19
         <type> BUF(*)
20
         INTEGER PARTITIONS, DATATYPE, DEST, TAG, COMM, INFO, REQUEST, IERROR
21
         INTEGER(KIND=MPI_COUNT_KIND) COUNT
22
23
          Rationale. The info argument is provided in order to support per-operation imple-
24
          mentation-defined info keys. (End of rationale.)
         MPI_PRECV_INIT creates a partitioned communication receive request and binds to it
26
27
```

all the arguments of a partitioned receive operation. This operation can only match with partitioned communication initialization operations, therefore the MPI library is required to match MPI\_PRECV\_INIT calls only with a corresponding MPI\_PSEND\_INIT call. Matching follows the same MPI matching rules as for point-to-point communication (see Chapter 3) with communicator, tag and source dictating message matching. In the event that the communicator, tag and source do not uniquely identify a message, the order in which partitioned communication initialization calls are made is the order in which they will eventually match. Partitioned communication initialization calls are local. That is,

MPI\_PRECV\_INIT may return before the operation completes. It is erroneous to provide a partitions value  $\leq 0$ . Wildcards for source and tag are not allowed.

Advice to implementors. Unlike MPI\_RECV\_INIT, MPI\_PRECV\_INIT may communicate. Also unlike MPI\_RECV\_INIT, MPI\_PRECV\_INIT takes an info argument. (End of advice to implementors.)

```
42
      MPI_PREADY(partition, request)
```

```
IN
           partition
                                           partition to mark ready for transfer (non-negative
                                           integer)
INOUT
                                           partitioned communication request (handle)
           request
```

#### C binding

28

29

30

31

32

34

35

36 37

39

41

43

44

45

46 47 48

```
int MPI_Pready(int partition, MPI_Request *request)
```

#### Fortran 2008 binding

```
MPI_Pready(partition, request, ierror)
    INTEGER, INTENT(IN) :: partition
    TYPE(MPI_Request), INTENT(INOUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_PREADY(PARTITION, REQUEST, IERROR)
INTEGER PARTITION, REQUEST, IERROR
```

MPI\_PREADY is a send-side call that indicates that a given partition is ready to be transferred. It is erroneous to use MPI\_PREADY on any request object that does not correspond to a partitioned send operation. The partitioning is defined by the MPI\_PSEND\_INIT call. Partition numbering starts at zero and ranges to one less than the number of partitions declared in the MPI\_PSEND\_INIT call. Specifying a partition number that is equal to or larger than the number of partitions is erroneous. After a call to MPI\_START/MPI\_STARTALL, all partitions associated with that operation are inactive. A call to MPI\_PREADY marks the indicated partition as active. Calling MPI\_PREADY on an active partition is erroneous.

#### MPI\_PREADY\_RANGE(partition\_low, partition\_high, request)

IN	partition_low	partition to mark lowest partition ready for transfer
		(non-negative integer)
IN	partition_high	partition to mark highest partition ready for transfer (non-negative integer)
INOUT	request	partitioned communication request (handle)

#### C binding

#### Fortran 2008 binding

```
MPI_Pready_range(partition_low, partition_high, request, ierror)
    INTEGER, INTENT(IN) :: partition_low, partition_high
    TYPE(MPI_Request), INTENT(INOUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_PREADY_RANGE(PARTITION_LOW, PARTITION_HIGH, REQUEST, IERROR)
INTEGER PARTITION_LOW, PARTITION_HIGH, REQUEST, IERROR
```

A call to MPI\_PREADY\_RANGE has the same effect as calls to MPI\_PREADY, executed for i=partition\_low ,..., partition\_high, in some arbitrary order. Calls to MPI\_PREADY\_RANGE follow the same rules as those for MPI\_PREADY calls.

3

4 5

6 7

8

9

11

18

19

20

21

22

23

24 25 26

27

28

29

30

31

32

34

35

36

37

38

39

```
MPI_PREADY_LIST(length, array_of_partitions, request)
       IN
                length
                                            list length (integer)
       INOUT
                array_of_partitions
                                            array of partitions (array of non-negative integers)
       INOUT
                request
                                            partitioned communication request (handle)
     C binding
     int MPI_Pready_list(int length, int array_of_partitions[],
                    MPI_Request *request)
10
     Fortran 2008 binding
     MPI_Pready_list(length, array_of_partitions, request, ierror)
12
         INTEGER, INTENT(IN) :: length
13
         INTEGER, INTENT(INOUT) :: array_of_partitions(length)
14
         TYPE(MPI_Request), INTENT(INOUT) :: request
15
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
16
17
     Fortran binding
```

MPI\_PREADY\_LIST(LENGTH, ARRAY\_OF\_PARTITIONS, REQUEST, IERROR) INTEGER LENGTH, ARRAY\_OF\_PARTITIONS(\*), REQUEST, IERROR

A call to MPI\_PREADY\_LIST has the same effect as calls to MPI\_PREADY, executed for the partitions specified in the range  $array\_of\_partitions[0]$ ...,  $array\_of\_partitions[count-1]$  of the array\\_of\\_partitions, executed in some arbitrary order. Calls to MPI\_PREADY\_LIST follow the same rules as those for MPI\_PREADY calls.

#### Communication Completion under Partitioning 4.2.2

The functions MPI\_WAIT and MPI\_TEST (and variants) are used to complete a partitioned communication operation. The completion of a partitioned send operation indicates that the sender is now free to call MPI\_START/MPI\_STARTALL to restart the operation and subsequently MPI\_PREADY, MPI\_PREADY\_RANGE or MPI\_PREADY\_LIST. Alternatively, the user can safely free the partitioned communication request after the completion of the partitioned operation. For the sending process, completion of the partitioned send operation does not indicate that the partitions of the message have all been received.

The completion of a partitioned receive operation through MPI\_WAIT or MPI\_TEST indicates that the receive buffer contains all of the partitions. A function for probing the partial completion of the receive buffer is provided by MPI\_PARRIVED. The MPI\_PARRIVED function can be used to determine if the message data for the indicated partition has been received into the receive buffer. Upon success, the receiver becomes free to access the indicated partition (as well as any others that previously completed for that operation).

# MPI\_PARRIVED(request, partition, flag) INOUT request partitioned communication request (handle) IN partition partition to be tested (non-negative integer) OUT flag true if operation completed on the specified partition, false if not (boolean)

#### C binding

```
int MPI_Parrived(MPI_Request *request, int partition, int *flag)
```

#### Fortran 2008 binding

```
MPI_Parrived(request, partition, flag, ierror)
    TYPE(MPI_Request), INTENT(INOUT) :: request
    INTEGER, INTENT(IN) :: partition
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_PARRIVED(REQUEST, PARTITION, FLAG, IERROR)
INTEGER REQUEST, PARTITION, IERROR
LOGICAL FLAG
```

The function MPI\_PARRIVED can be used to test partial completion of partitioned receive operations. A call to MPI\_PARRIVED on an active partitioned communications request returns flag = true if the operation identified by request for the specified partition is complete. The request is not marked as complete/inactive by this operation. A subsequent MPI\_TEST/MPI\_WAIT operation is required to complete the message, as described in Chapter 3. MPI\_PARRIVED may be called multiple times for a partition. MPI\_PARRIVED may be called with a null or inactive request argument. In either case, the operation returns with flag = true. Calling MPI\_PARRIVED on a request that does not correspond to a partitioned receive operation is erroneous.

#### 4.2.3 Semantics of Communications in Partitioned Mode

The semantics of nonblocking partitioned communication are defined by suitably extending the definitions in Section 3.5.

Interpretation of count and datatype for partitioned communication. Partitioned communication uses the count and datatype arguments in the partitioned communication initialization functions to describe a single partition. The argument partitions specifies how many equal partitions of a number (count) of datatypes make up the entire buffer to be transferred in the partitioned communication. As partitioned communication describes many partitions, using absolute displacements in datatypes (e.g., MPI\_BOTTOM) is not supported. Partitions are contiguous in memory, there is no padding in between partitions. Once a partitioned send operation is started, each partition must be marked as ready using MPI\_PREADY and the operation must be completed using a completion function, such as MPI\_TEST or MPI\_WAIT.

Order Matching follows the same MPI matching rules as for point-to-point communication (see Chapter 3) with communicator, tag and source dictating message matching. In the event that the communicator, tag and source do not uniquely identify the message, the order in which partitioned communication initialization calls are made is the order in which they will eventually match.

6 7

1

2

3

4

5

8 9

10

## 4.3 Partitioned Communication Examples

This section provides concrete examples of the utility of partitioned communication in realistic settings.

11 12 13

14

15

16

17

18

19

20 21

#### 4.3.1 Partition Communication with Threads/Tasks Using OpenMP 4.0 and greater

The equal partitioning on send-side and receive-side in Example 4.1 is shown using threads. In this case, the receive-side uses the same number of partitions as the sending-side like the previous example, but this example uses multiple threads on the sending-side. Note that the MPI\_PSEND\_INIT and MPI\_PRECV\_INIT functions match each other like in the previous example.

Example 4.2

```
#include "mpi.h"
22
     #define NUM_THREADS 8
23
     #define PARTITIONS 8
24
     #define PARTLENGTH 16
25
     int main( int argc, char *argv[]) /* same send/recv partitioning */
27
       double message[PARTITIONS*PARTLENGTH];
28
       int partitions = PARTITIONS;
29
       int partlength = PARTLENGTH;
30
       int count = 1, source = 0, dest = 1, tag = 1, flag = 0;
31
       int myrank;
32
       int provided;
33
       MPI_Request request;
34
       MPI_Info info = MPI_INFO_NULL;
35
       MPI_Datatype xfer_type;
36
       MPI_Init_thread(&argc, &argv, MPI_THREAD_MULTIPLE, &provided);
37
       if (provided < MPI_THREAD_SERIALIZED)</pre>
38
          MPI_Abort(MPI_COMM_WORLD, EXIT_FAILURE);
39
       MPI_Comm_rank( MPI_COMM_WORLD, &myrank );
       MPI_Type_contiguous(partlength, MPI_DOUBLE, &xfer_type);
41
       MPI_Type_commit(&xfer_type);
42
       if (myrank == 0)
                            /* code for process zero */
43
       {
44
          MPI_Psend_init(message, partitions, count, xfer_type, dest, tag,
45
               info, MPI_COMM_WORLD, &request);
          MPI_Start(&request);
47
```

48

13 14

15

16

18

19

20 21

22

23

26

27

28 29

30

34

35

36 37

38

```
#pragma omp parallel for shared(request) num_threads(NUM_THREADS)
     for (int i=0; i<partitions; i++)
        /* compute and fill partition #i, then mark ready: */
       MPI_Pready(i, &request);
    while(!flag)
        /* Do useful work */
       MPI_Test(&request, &flag, MPI_STATUS_IGNORE);
        /* Do useful work */
     }
    MPI_Request_free(&request);
 }
 else if (myrank == 1) /* code for process one */
    MPI_Precv_init(message, partitions, count, xfer_type, source, tag,
           info, MPI_COMM_WORLD, &request);
    MPI_Start(&request);
     while(!flag)
     {
        /* Do useful work */
       MPI_Test(&request, &flag, MPI_STATUS_IGNORE);
        /* Do useful work */
     }
    MPI_Request_free(&request);
 MPI_Finalize();
 return 0;
}
```

#### 4.3.2 Send-only Partitioning Example with Tasks and OpenMP version 4.0 and greater

The previous example is tailored specifically for send-side partitioning using threads. This is an example where parallel task producers produce input to part of an overall buffer; they complete in any order and contribute to the overall buffer.

#### Example 4.3

```
1
           send_partlength = PARTLENGTH,
2
           recv_partitions = 1,
           recv_partlength = PARTITIONS*PARTLENGTH;
       int count = 1, source = 0, dest = 1, tag = 1, flag = 0;
       int myrank;
       int provided;
       MPI_Request request;
       MPI_Info info = MPI_INFO_NULL;
       MPI_Datatype send_type;
10
       MPI_Init_thread(&argc, &argv, MPI_THREAD_MULTIPLE, &provided);
11
       if (provided < MPI_THREAD_SERIALIZED)</pre>
12
          MPI_Abort(MPI_COMM_WORLD, EXIT_FAILURE);
13
       MPI_Comm_rank( MPI_COMM_WORLD, &myrank );
14
       MPI_Type_contiguous(send_partlength, MPI_DOUBLE, &send_type);
15
       MPI_Type_commit(&send_type);
16
17
       if (myrank == 0)
                           /* code for process zero */
18
       {
19
          MPI_Psend_init(message, send_partitions, count, send_type, dest, tag,
20
                    info, MPI_COMM_WORLD, &request);
21
          MPI_Start(&request);
23
          #pragma omp parallel shared(request) num_threads(NUM_THREADS)
             #pragma omp single
27
               /* single thread creates 64 tasks to be executed by 8 threads */
               for (int partition_num=0; partition_num<NUM_TASKS; partition_num++)
                  #pragma omp task firstprivate(partition_num)
                   /* compute and fill partition #partition_num, then mark
33
                      ready: */
34
                   /* buffer is filled in arbitrary order from each task */
35
                   MPI_Pready(partition_num, &request);
36
                  } /*end task*/
37
               } /* end for */
             } /* end single */
          } /* end parallel */
          while(!flag)
          {
             /* Do useful work */
43
             MPI_Test(&request, &flag, MPI_STATUS_IGNORE);
44
             /* Do useful work */
45
          MPI_Request_free(&request);
47
       }
       else if (myrank == 1) /* code for process one */
```

12

13 14

15

16 17 18

19

20

21

22

23

24

26

27 28

29

30 31

33

34

35 36 37

38

39

42

43 44

45

46

### 4.3.3 Send and Receive Partitioning Example with OpenMP version 4.0 and greater


This example demonstrates receive-side partial completion notification using more than one partition per receive-side thread. It uses a naive flag based method to test for multiple completed partitions per thread. Note that this means that some threads may be busy polling for completion of assigned partitions when partitions are available to work on that were not assigned to the polling threads in this example. More advanced work stealing methods could be employed for greater efficiency. Like previous examples, it also demonstrates send-side production of input to part of an overall buffer. This example also uses different send-side and receive-side partitioning.

#### Example 4.4

```
#include "mpi.h"
#define NUM_THREADS 64
#define PARTITIONS NUM_THREADS
#define PARTLENGTH 16
#define MESSAGE_LENGTH PARTITIONS*PARTLENGTH
int main( int argc, char *argv[]) /* send-side partitioning */
  double message[MESSAGE_LENGTH];
  int send_partitions = PARTITIONS,
      send_partlength = PARTLENGTH,
      recv_partitions = PARTITIONS*2,
      recv_partlength = PARTLENGTH/2;
  int source = 0, dest = 1, tag = 1, flag = 0;
  int myrank;
  int provided;
 MPI_Request request;
  MPI_Info info = MPI_INFO_NULL;
  MPI_Datatype send_type;
  MPI_Init_thread(&argc, &argv, MPI_THREAD_MULTIPLE, &provided);
```

```
1
       if (provided < MPI_THREAD_SERIALIZED)</pre>
2
          MPI_Abort(MPI_COMM_WORLD, EXIT_FAILURE);
       MPI_Comm_rank( MPI_COMM_WORLD, &myrank );
       MPI_Type_contiguous(send_partlength, MPI_DOUBLE, &send_type);
5
       MPI_Type_commit(&send_type);
6
7
       if (myrank == 0)
                            /* code for process zero */
       {
9
          MPI_Psend_init(message, send_partitions, 1, send_type, dest, tag,
10
                     info, MPI_COMM_WORLD, &request);
11
          MPI_Start(&request);
12
          #pragma omp parallel for shared(request) num_threads(NUM_THREADS)
13
          for (int i=0; i<send_partitions; i++)</pre>
14
          {
15
             /* compute and fill partition #i, then mark ready: */
16
             MPI_Pready(i, &request);
          }
          while(!flag)
19
20
             /* Do useful work */
21
             MPI_Test(&request, &flag, MPI_STATUS_IGNORE);
22
             /* Do useful work */
23
          }
24
          MPI_Request_free(&request);
       }
26
       else if (myrank == 1) /* code for process one */
27
       {
28
          MPI_Precv_init(message, recv_partitions, recv_partlength, MPI_DOUBLE,
29
                    source, tag, info, MPI_COMM_WORLD, &request);
30
          MPI_Start(&request);
          #pragma omp parallel for shared(request) num_threads(NUM_THREADS)
          for (int j=0; j<recv_partitions; j+=2)</pre>
33
34
             int part1_complete = 0;
35
             int part2_complete = 0;
36
             while(part1_complete == 0 || part2_complete == 0)
37
                 /* test partition #j and #j+1 */
                MPI_Parrived(&request, j, &flag);
                 if(flag && part1_complete == 0)
41
                 {
42
                    part1_complete++;
43
                    /* Do work using partition j data */
44
                 }
45
                 if (j+1 < recv_partitions) {</pre>
                   MPI_Parrived(&request, j+1, &flag);
47
                   if(flag && part2_complete == 0)
                   {
```

```
part2_complete++;
              /* Do work using partition j+1 */
           }
         }
         else {
             part2_complete++;
      }
   while(!flag)
      /* Do useful work */
      MPI_Test(&request, &flag, MPI_STATUS_IGNORE);
      /* Do useful work */
   }
   MPI_Request_free(&request);
}
MPI_Finalize();
return 0;
```



## Chapter 5

# **Datatypes**

Basic datatypes were introduced in Section 3.2.2 and in Section 3.3. In this chapter, this model is extended to describe any data layout. We consider general datatypes that allow one to transfer efficiently heterogeneous and noncontiguous data. We conclude with the description of calls for explicit packing and unpacking of messages.

#### 5.1 Derived Datatypes

Up to here, all point to point communications have involved only buffers containing a sequence of identical basic datatypes. This is too constraining on two accounts. One often wants to pass messages that contain values with different datatypes (e.g., an integer count, followed by a sequence of real numbers); and one often wants to send noncontiguous data (e.g., a sub-block of a matrix). One solution is to pack noncontiguous data into a contiguous buffer at the sender site and unpack it at the receiver site. This has the disadvantage of requiring additional memory-to-memory copy operations at both sites, even when the communication subsystem has scatter-gather capabilities. Instead, MPI provides mechanisms to specify more general, mixed, and noncontiguous communication buffers. It is up to the implementation to decide whether data should be first packed in a contiguous buffer before being transmitted, or whether it can be collected directly from where it resides.

The general mechanisms provided here allow one to transfer directly, without copying, objects of various shapes and sizes. It is not assumed that the MPI library is cognizant of the objects declared in the host language. Thus, if one wants to transfer a structure, or an array section, it will be necessary to provide in MPI a definition of a communication buffer that mimics the definition of the structure or array section in question. These facilities can be used by library designers to define communication functions that can transfer objects defined in the host language—by decoding their definitions as available in a symbol table or a dope vector. Such higher-level communication functions are not part of MPI.

More general communication buffers are specified by replacing the basic datatypes that have been used so far with derived datatypes that are constructed from basic datatypes using the constructors described in this section. These methods of constructing derived datatypes can be applied recursively.

A general datatype is an opaque object that specifies two things:

- A sequence of basic datatypes
- A sequence of integer (byte) displacements

The displacements are not required to be positive, distinct, or in increasing order. Therefore, the order of items need not coincide with their order in store, and an item may appear more than once. We call such a pair of sequences (or sequence of pairs) a **type** map. The sequence of basic datatypes (displacements ignored) is the **type signature** of the datatype.

Let

$$Typemap = \{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1})\},\$$

be such a type map, where  $type_i$  are basic types, and  $disp_i$  are displacements. Let

$$Typesig = \{type_0, \dots, type_{n-1}\}$$

be the associated type signature. This type map, together with a base address buf, specifies a communication buffer: the communication buffer that consists of n entries, where the i-th entry is at address buf +  $disp_i$  and has type  $type_i$ . A message assembled from such a communication buffer will consist of n values, of the types defined by Typesiq.

Most datatype constructors have replication count or block length arguments. Allowed values are non-negative integers. If the value is zero, no elements are generated in the type map and there is no effect on datatype bounds or extent.

We can use a handle to a general datatype as an argument in a send or receive operation, instead of a basic datatype argument. The operation MPI\_SEND(buf, 1, datatype,...) will use the send buffer defined by the base address buf and the general datatype associated with datatype; it will generate a message with the type signature determined by the datatype argument. MPI\_RECV(buf, 1, datatype,...) will use the receive buffer defined by the base address buf and the general datatype associated with datatype.

General datatypes can be used in all send and receive operations. We discuss, in Section 5.1.11, the case where the second argument count has value > 1.

The basic datatypes presented in Section 3.2.2 are particular cases of a general datatype, and are predefined. Thus, MPI\_INT is a predefined handle to a datatype with type map  $\{(\mathtt{int},0)\}$ , with one entry of type  $\mathtt{int}$  and displacement zero. The other basic datatypes are similar.

The **extent** of a datatype is defined to be the span from the first byte to the last byte occupied by entries in this datatype, rounded up to satisfy alignment requirements. That is, if

$$Typemap = \{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1})\},\$$

then

$$lb(Typemap) = \min_{j} disp_{j},$$

$$ub(Typemap) = \max_{j} (disp_{j} + \text{sizeof}(type_{j})) + \epsilon, \text{ and}$$

$$extent(Typemap) = ub(Typemap) - lb(Typemap). \tag{5.1}$$

If  $type_j$  requires alignment to a byte address that is a multiple of  $k_j$ , then  $\epsilon$  is the least non-negative increment needed to round extent(Typemap) to the next multiple of  $\max_j k_j$ . In Fortran, it is implementation dependent whether the MPI implementation computes the alignments  $k_j$  according to the alignments used by the compiler in common blocks, SEQUENCE derived types, BIND(C) derived types, or derived types that are neither SEQUENCE nor BIND(C). The complete definition of **extent** is given by Equation 5.1 Section 5.1.

**Example 5.1** Assume that  $Type = \{(\texttt{double}, 0), (\texttt{char}, 8)\}$  (a double at displacement zero, followed by a **char** at displacement eight). Assume, furthermore, that doubles have to be strictly aligned at addresses that are multiples of eight. Then, the extent of this datatype is 16 (9 rounded to the next multiple of 8). A datatype that consists of a character immediately followed by a double will also have an extent of 16.

Rationale. The definition of extent is motivated by the assumption that the amount of padding added at the end of each structure in an array of structures is the least needed to fulfill alignment constraints. More explicit control of the extent is provided in Section 5.1.6. Such explicit control is needed in cases where the assumption does not hold, for example, where union types are used. In Fortran, structures can be expressed with several language features, e.g., common blocks, SEQUENCE derived types, or BIND(C) derived types. The compiler may use different alignments, and therefore, it is recommended to use MPI\_TYPE\_CREATE\_RESIZED for arrays of structures if an alignment may cause an alignment-gap at the end of a structure as described in Section 5.1.6 and in Section 19.1.15. (End of rationale.)

#### 5.1.1 Type Constructors with Explicit Addresses

In Fortran, the functions MPI\_TYPE\_CREATE\_HVECTOR,
MPI\_TYPE\_CREATE\_HINDEXED, MPI\_TYPE\_CREATE\_HINDEXED\_BLOCK,
MPI\_TYPE\_CREATE\_STRUCT, and MPI\_GET\_ADDRESS accept arguments of type
INTEGER(KIND=MPI\_ADDRESS\_KIND), wherever arguments of type MPI\_Aint are used in C.
For Fortran compilers that do not support the Fortran 90 KIND notation, and where addresses are 64 bits whereas default INTEGERs are 32 bits, these arguments will be of type
INTEGER\*8 (assuming the Fortran compiler accepts the common extension of INTEGER\*8 for eight-byte integers).

For the large count versions of three datatype constructors with explicit addresses, MPI\_TYPE\_CREATE\_HINDEXED, MPI\_TYPE\_CREATE\_HINDEXED\_BLOCK, and MPI\_TYPE\_CREATE\_STRUCT, absolute addresses shall not be used to specify byte displacements since the parameter is of type MPI\_COUNT instead of type MPI\_AINT.

#### 5.1.2 Datatype Constructors

Contiguous The simplest datatype constructor is MPI\_TYPE\_CONTIGUOUS which allows replication of a datatype into contiguous locations.

#### MPI\_TYPE\_CONTIGUOUS(count, oldtype, newtype)

IN	count	replication count (non-negative integer)
IN	oldtype	old datatype (handle)
OUT	newtype	new datatype (handle)

#### C binding

37

38

39

```
1
      int MPI_Type_contiguous_c(MPI_Count count, MPI_Datatype oldtype,
2
                     MPI_Datatype *newtype)
3
     Fortran 2008 binding
      MPI_Type_contiguous(count, oldtype, newtype, ierror)
5
          INTEGER, INTENT(IN) :: count
6
          TYPE(MPI_Datatype), INTENT(IN) :: oldtype
          TYPE(MPI_Datatype), INTENT(OUT) :: newtype
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
9
10
     MPI_Type_contiguous(count, oldtype, newtype, ierror)
11
          INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
12
          TYPE(MPI_Datatype), INTENT(IN) :: oldtype
13
          TYPE(MPI_Datatype), INTENT(OUT) :: newtype
14
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
15
      Fortran binding
16
     MPI_TYPE_CONTIGUOUS(COUNT, OLDTYPE, NEWTYPE, IERROR)
17
          INTEGER COUNT, OLDTYPE, NEWTYPE, IERROR
18
19
          newtype is the datatype obtained by concatenating count copies of
20
      oldtype. Concatenation is defined using extent as the size of the concatenated copies.
21
     Example 5.2 Let oldtype have type map {(double, 0), (char, 8)}, with extent 16, and let
22
     count = 3. The type map of the datatype returned by newtype is
23
24
           \{(double, 0), (char, 8), (double, 16), (char, 24), (double, 32), (char, 40)\};
25
26
     i.e., alternating double and char elements, with displacements 0, 8, 16, 24, 32, 40.
27
          In general, assume that the type map of oldtype is
28
29
           \{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1})\},\
30
      with extent ex. Then newtype has a type map with count \cdot n entries defined by:
31
32
         \{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1}), (type_0, disp_0 + ex), \dots, (type_{n-1}, disp_{n-1} + ex), \}
33
34
        \ldots, (type_0, disp_0 + ex \cdot (count - 1)), \ldots, (type_{n-1}, disp_{n-1} + ex \cdot (count - 1)).
35
```

Vector The function MPI\_TYPE\_VECTOR is a more general constructor that allows replication of a datatype into locations that consist of equally spaced blocks. Each block is obtained by concatenating the same number of copies of the old datatype. The spacing between blocks is a multiple of the extent of the old datatype.

12

13

14 15

16

17 18

19

24

26

27

28

45

46 47

```
MPI_TYPE_VECTOR(count, blocklength, stride, oldtype, newtype)
  IN
           count
                                       number of blocks (non-negative integer)
  IN
           blocklength
                                       number of elements in each block (non-negative
                                       integer)
  IN
           stride
                                       number of elements between start of each block
                                       (integer)
  IN
           oldtype
                                       old datatype (handle)
  OUT
           newtype
                                       new datatype (handle)
C binding
int MPI_Type_vector(int count, int blocklength, int stride,
               MPI_Datatype oldtype, MPI_Datatype *newtype)
int MPI_Type_vector_c(MPI_Count count, MPI_Count blocklength,
               MPI_Count stride, MPI_Datatype oldtype, MPI_Datatype *newtype)
Fortran 2008 binding
MPI_Type_vector(count, blocklength, stride, oldtype, newtype, ierror)
    INTEGER, INTENT(IN) :: count, blocklength, stride
                                                                                         20
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                        21
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                         22
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                         23
MPI_Type_vector(count, blocklength, stride, oldtype, newtype, ierror)
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count, blocklength, stride
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                         29
                                                                                         30
Fortran binding
MPI_TYPE_VECTOR(COUNT, BLOCKLENGTH, STRIDE, OLDTYPE, NEWTYPE, IERROR)
                                                                                         31
    INTEGER COUNT, BLOCKLENGTH, STRIDE, OLDTYPE, NEWTYPE, IERROR
                                                                                         33
                                                                                        34
Example 5.3 Assume, again, that oldtype has type map {(double, 0), (char, 8)}, with
                                                                                         35
extent 16. A call to MPI_TYPE_VECTOR(2, 3, 4, oldtype, newtype) will create the datatype
                                                                                         36
with type map,
                                                                                        37
                                                                                         38
     \{(double, 0), (char, 8), (double, 16), (char, 24), (double, 32), (char, 40), \}
                                                                                         39
     (double, 64), (char, 72), (double, 80), (char, 88), (double, 96), (char, 104)}.
That is, two blocks with three copies each of the old type, with a stride of 4 elements (4 \cdot 16)
                                                                                         42
bytes) between the start of each block.
                                                                                         43
                                                                                         44
Example 5.4 A call to MPI_TYPE_VECTOR(3, 1, -2, oldtype, newtype) will create the
datatype,
     \{(double, 0), (char, 8), (double, -32), (char, -24), (double, -64), (char, -56)\}.
```

```
1
            In general, assume that oldtype has type map,
2
             \{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1})\},\
3
       with extent ex. Let bl be the blocklength. The newly created datatype has a type map with
5
       count \cdot bl \cdot n  entries:
6
             \{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1}), \}
7
             (type_0, disp_0 + ex), \dots, (type_{n-1}, disp_{n-1} + ex), \dots,
9
10
             (type_0, disp_0 + (bl - 1) \cdot ex), \dots, (type_{n-1}, disp_{n-1} + (bl - 1) \cdot ex),
11
12
             (type_0, disp_0 + stride \cdot ex), \dots, (type_{n-1}, disp_{n-1} + stride \cdot ex), \dots,
13
14
             (type_0, disp_0 + (\mathsf{stride} + \mathsf{bl} - 1) \cdot ex), \dots, (type_{n-1}, disp_{n-1} + (\mathsf{stride} + \mathsf{bl} - 1) \cdot ex), \dots,
15
16
             (type_0, disp_0 + stride \cdot (count - 1) \cdot ex), \ldots,
17
18
             (type_{n-1}, disp_{n-1} + stride \cdot (count - 1) \cdot ex), \ldots,
19
             (type_0, disp_0 + (stride \cdot (count - 1) + bl - 1) \cdot ex), \dots,
20
21
             (type_{n-1}, disp_{n-1} + (stride \cdot (count - 1) + bl - 1) \cdot ex).
22
23
            A call to MPI_TYPE_CONTIGUOUS(count, oldtype, newtype) is equivalent to a call to
24
       MPI_TYPE_VECTOR(count, 1, 1, oldtype, newtype), or to a call to MPI_TYPE_VECTOR(1,
25
       count, n, oldtype, newtype), n arbitrary.
26
27
       Hvector The function MPI_TYPE_CREATE_HVECTOR is identical to
28
       MPI_TYPE_VECTOR, except that stride is given in bytes, rather than in elements. The
29
       use for both types of vector constructors is illustrated in Section 5.1.14. (H stands for
30
31
       "heterogeneous").
32
33
       MPI_TYPE_CREATE_HVECTOR(count, blocklength, stride, oldtype, newtype)
34
         ĪN
35
                     count
                                                        number of blocks (non-negative integer)
36
         IN
                     blocklength
                                                        number of elements in each block (non-negative
37
                                                        integer)
38
         IN
                     stride
                                                        number of bytes between start of each block (integer)
39
         IN
                     oldtype
                                                        old datatype (handle)
```

#### C binding

OUT

newtype

41

42

44

45

46 47

48

new datatype (handle)

MPI\_Count stride, MPI\_Datatype oldtype, MPI\_Datatype \*newtype)

```
Fortran 2008 binding
MPI_Type_create_hvector(count, blocklength, stride, oldtype, newtype,
                 ierror)
     INTEGER, INTENT(IN) :: count, blocklength
     INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: stride
     TYPE(MPI_Datatype), INTENT(IN) :: oldtype
     TYPE(MPI_Datatype), INTENT(OUT) :: newtype
     INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Type_create_hvector(count, blocklength, stride, oldtype, newtype,
                 ierror)
     INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count, blocklength, stride
                                                                                                       12
     TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                                       13
     TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                                       14
     INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                                       15
                                                                                                       16
Fortran binding
MPI_TYPE_CREATE_HVECTOR(COUNT, BLOCKLENGTH, STRIDE, OLDTYPE, NEWTYPE,
                                                                                                       18
                 IERROR)
                                                                                                       19
     INTEGER COUNT, BLOCKLENGTH, OLDTYPE, NEWTYPE, IERROR
     INTEGER(KIND=MPI_ADDRESS_KIND) STRIDE
                                                                                                       20
                                                                                                      21
     Assume that oldtype has type map,
                                                                                                       22
                                                                                                       23
      \{(type_0, disp_0), \ldots, (type_{n-1}, disp_{n-1})\},\
                                                                                                       24
with extent ex. Let bl be the blocklength. The newly created datatype has a type map with
count \cdot bl \cdot n entries:
                                                                                                       26
                                                                                                       27
      \{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1}), \}
                                                                                                       28
                                                                                                       29
      (type_0, disp_0 + ex), \dots, (type_{n-1}, disp_{n-1} + ex), \dots,
                                                                                                       30
      (type_0, disp_0 + (bl - 1) \cdot ex), \dots, (type_{n-1}, disp_{n-1} + (bl - 1) \cdot ex),
      (type_0, disp_0 + \mathsf{stride}), \dots, (type_{n-1}, disp_{n-1} + \mathsf{stride}), \dots,
                                                                                                      34
                                                                                                      35
      (type_0, disp_0 + stride + (bl - 1) \cdot ex), \ldots,
                                                                                                       36
      (type_{n-1}, disp_{n-1} + stride + (bl - 1) \cdot ex), \dots,
                                                                                                       37
      (type_0, disp_0 + \mathsf{stride} \cdot (\mathsf{count} - 1)), \dots, (type_{n-1}, disp_{n-1} + \mathsf{stride} \cdot (\mathsf{count} - 1)), \dots,
      (type_0, disp_0 + stride \cdot (count - 1) + (bl - 1) \cdot ex), \dots,
                                                                                                       42
      (type_{n-1}, disp_{n-1} + stride \cdot (count - 1) + (bl - 1) \cdot ex).
                                                                                                       43
                                                                                                       44
                                                                                                       45
                                                                                                       46
```

2

3

4

5 6

14

15

16 17

18

19 20

21

22

23

24 25

26

27

28

29

30

31

32

33

34

35

36

37

39

41

42

43

44

45

46

47

Indexed The function MPI\_TYPE\_INDEXED allows replication of an old datatype into a sequence of blocks (each block is a concatenation of the old datatype), where each block can contain a different number of copies and have a different displacement. All block displacements are multiples of the old type extent.

MPI\_TYPE\_INDEXED(count, array\_of\_blocklengths, array\_of\_displacements, oldtype, newtype)

Substitute in Latex source " --- " by "---"

```
IN
                                           number of blocks – also number of entries in
           count
                                           array_of_displacements and array_of_blocklengths
                                           (non-negative integer)
IN
           array_of_blocklengths
                                           number of elements per block (array of non-negative
                                           integers)
           array_of_displacements
                                           displacement for each block, in multiples of oldtype
IN
                                           (array of integers)
IN
           oldtype
                                           old datatype (handle)
OUT
           newtype
                                           new datatype (handle)
```

#### C binding

#### Fortran 2008 binding

#### Fortran binding

```
MPI_TYPE_INDEXED(COUNT, ARRAY_OF_BLOCKLENGTHS, ARRAY_OF_DISPLACEMENTS, OLDTYPE, NEWTYPE, IERROR)
```

INTEGER, OPTIONAL, INTENT(OUT) :: ierror

**Example 5.5** Let oldtype have type map {(double, 0), (char, 8)}, with extent 16. Let B = (3, 1) and let D = (4, 0). A call to MPI\_TYPE\_INDEXED(2, B, D, oldtype, newtype) returns a datatype with type map,

$$\{(double, 64), (char, 72), (double, 80), (char, 88), (double, 96), (char, 104), (double, 0), (char, 8)\}.$$

That is, three copies of the old type starting at displacement 64, and one copy starting at displacement 0.

In general, assume that oldtype has type map,

$$\{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1})\},\$$

with extent ex. Let B be the array\_of\_blocklengths argument and D be the array\_of\_displacements argument. The newly created datatype has  $n \cdot \sum_{i=0}^{\mathsf{count}-1} \mathsf{B}[\mathsf{i}]$  entries:

$$\begin{split} &\{(type_0, disp_0 + \mathsf{D}[0] \cdot ex), \dots, (type_{n-1}, disp_{n-1} + \mathsf{D}[0] \cdot ex), \dots, \\ &(type_0, disp_0 + (\mathsf{D}[0] + \mathsf{B}[0] - 1) \cdot ex), \dots, \\ &(type_{n-1}, disp_{n-1} + (\mathsf{D}[0] + \mathsf{B}[0] - 1) \cdot ex), \dots, \\ &(type_0, disp_0 + \mathsf{D}[\mathsf{count-1}] \cdot ex), \dots, (type_{n-1}, disp_{n-1} + \mathsf{D}[\mathsf{count-1}] \cdot ex), \dots, \\ &(type_0, disp_0 + (\mathsf{D}[\mathsf{count-1}] + \mathsf{B}[\mathsf{count-1}] - 1) \cdot ex), \dots, \\ &(type_{n-1}, disp_{n-1} + (\mathsf{D}[\mathsf{count-1}] + \mathsf{B}[\mathsf{count-1}] - 1) \cdot ex)\}. \end{split}$$

A call to MPI\_TYPE\_VECTOR(count, blocklength, stride, oldtype, newtype) is equivalent to a call to MPI\_TYPE\_INDEXED(count, B, D, oldtype, newtype) where

$$D[j] = j \cdot \mathsf{stride}, \ j = 0, \dots, \mathsf{count} - 1,$$

and

$$B[j] = blocklength, j = 0, ..., count - 1.$$

Hindexed The function MPI\_TYPE\_CREATE\_HINDEXED is identical to MPI\_TYPE\_INDEXED, except that block displacements in array\_of\_displacements are specified in bytes, rather than in multiples of the oldtype extent.

#-405

Done

```
MPI_TYPE_CREATE_HINDEXED(count, array_of_blocklengths, array_of_displacements,
                               oldtype, newtype)
                                                 Substitute in Latex source " --- " by "---"
                                                       number of blocks - also number of entries in
#-update1
                  IN
                           count
                                                       array_of_displacements and array_of_blocklengths
                                                       (non-negative integer)
#-PR427
                  IN
                           array_of_blocklengths
                                                       number of elements in each block (array of
                                                       non-negative integers)
                  IN
                           array_of_displacements
                                                       byte displacement of each block (array of integers)
           10
                  IN
                           oldtype
                                                       old datatype (handle)
           11
                  OUT
                                                       new datatype (handle)
                           newtype
          12
          13
          14
                C binding
                int MPI_Type_create_hindexed(int count, const int array_of_blocklengths[],
           15
           16
                               const MPI_Aint array_of_displacements[], MPI_Datatype oldtype,
           17
                               MPI_Datatype *newtype)
           18
                int MPI_Type_create_hindexed_c(MPI_Count count,
           19
                               const MPI_Count array_of_blocklengths[],
          20
                               const MPI_Count array_of_displacements[],
          21
                               MPI_Datatype oldtype, MPI_Datatype *newtype)
          22
          23
                Fortran 2008 binding
          24
                MPI_Type_create_hindexed(count, array_of_blocklengths,
          25
                               array_of_displacements, oldtype, newtype, ierror)
           26
                    INTEGER, INTENT(IN) :: count, array_of_blocklengths(count)
          27
                    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) ::
                                array_of_displacements(count)
          28
                    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
          29
                    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
           30
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
          31
                MPI_Type_create_hindexed(count, array_of_blocklengths,
          33
                               array_of_displacements, oldtype, newtype, ierror)
          34
                    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count,
          35
                                array_of_blocklengths(count), array_of_displacements(count)
          36
                    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
          37
                    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
          38
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
          39
          40
                Fortran binding
          41
                MPI_TYPE_CREATE_HINDEXED(COUNT, ARRAY_OF_BLOCKLENGTHS,
          42
                               ARRAY_OF_DISPLACEMENTS, OLDTYPE, NEWTYPE, IERROR)
          43
                    INTEGER COUNT, ARRAY_OF_BLOCKLENGTHS(*), OLDTYPE, NEWTYPE, IERROR
          44
                    INTEGER(KIND=MPI_ADDRESS_KIND) ARRAY_OF_DISPLACEMENTS(*)
           45
                    Assume that oldtype has type map,
           46
           47
                     \{(type_0, disp_0), \ldots, (type_{n-1}, disp_{n-1})\},\
```

#-update1

#-405 #-PR427

Done

with extent ex. Let B be the array\_of\_blocklengths argument and D be the array\_of\_displacements argument. The newly created datatype has a type map with  $n \cdot \sum_{i=0}^{\mathsf{count}-1} \mathsf{B}[i]$  entries:

```
 \{(type_0, disp_0 + \mathsf{D}[0]), \dots, (type_{n-1}, disp_{n-1} + \mathsf{D}[0]), \dots, \\ (type_0, disp_0 + \mathsf{D}[0] + (\mathsf{B}[0] - 1) \cdot ex), \dots, \\ (type_{n-1}, disp_{n-1} + \mathsf{D}[0] + (\mathsf{B}[0] - 1) \cdot ex), \dots, \\ (type_0, disp_0 + \mathsf{D}[\mathsf{count-1}]), \dots, (type_{n-1}, disp_{n-1} + \mathsf{D}[\mathsf{count-1}]), \dots, \\ (type_0, disp_0 + \mathsf{D}[\mathsf{count-1}] + (\mathsf{B}[\mathsf{count-1}] - 1) \cdot ex), \dots, \\ (type_{n-1}, disp_{n-1} + \mathsf{D}[\mathsf{count-1}] + (\mathsf{B}[\mathsf{count-1}] - 1) \cdot ex) \}.
```

Indexed\_block This function is the same as MPI\_TYPE\_INDEXED except that the block-length is the same for all blocks. There are many codes using indirect addressing arising from unstructured grids where the blocksize is always 1 (gather/scatter). The following convenience function allows for constant blocksize and arbitrary displacements.

```
MPI_TYPE_CREATE_INDEXED_BLOCK(count, blocklength, array_of_displacements, oldtype, newtype)

Note that the second second
```

```
integer) Substitute in Latex source " --- " by "---"

IN blocklength size of block (non-negative integer)

IN array_of_displacements array of displacements (array of integers)

IN oldtype old datatype (handle)
```

OUT newtype new datatype (handle)

#### C binding

#### Fortran 2008 binding

#-405

#-PR427

Done

```
1
                MPI_Type_create_indexed_block(count, blocklength, array_of_displacements,
           2
                               oldtype, newtype, ierror)
           3
                    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count, blocklength,
                                array_of_displacements(count)
                    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                Fortran binding
           9
                MPI_TYPE_CREATE_INDEXED_BLOCK(COUNT, BLOCKLENGTH, ARRAY_OF_DISPLACEMENTS,
           10
                               OLDTYPE, NEWTYPE, IERROR)
           11
                    INTEGER COUNT, BLOCKLENGTH, ARRAY_OF_DISPLACEMENTS(*), OLDTYPE,
          12
                                NEWTYPE, IERROR
           13
          14
           15
                Hindexed_block The function MPI_TYPE_CREATE_HINDEXED_BLOCK is identical to
           16
                MPI_TYPE_CREATE_INDEXED_BLOCK, except that block displacements in
           17
                array_of_displacements are specified in bytes, rather than in multiples of the oldtype extent.
           18
           19
                MPI_TYPE_CREATE_HINDEXED_BLOCK(count, blocklength, array_of_displacements,
          20
                                                 Was already modified into: number of blocks --- also number of
          21
                               oldtype, newtype)
                                                 entries in array_of_displacements
#-update1 122
                                                       length of array of displacements (non-negative
                  IN
                           count
          23
                                                       integer) Substitute in Latex source " --- " by "---"
                  IN
                           blocklength
                                                       size of block (non-negative integer)
           26
                  IN
                           array_of_displacements
                                                       byte displacement of each block (array of integers)
          27
                  IN
                           oldtype
                                                       old datatype (handle)
          28
                  OUT
                                                       new datatype (handle)
                           newtype
          29
          30
                C binding
          31
                int MPI_Type_create_hindexed_block(int count, int blocklength,
          32
                               const MPI_Aint array_of_displacements[], MPI_Datatype oldtype,
          33
                               MPI_Datatype *newtype)
          34
          35
                int MPI_Type_create_hindexed_block_c(MPI_Count count,
          36
                               MPI_Count blocklength,
          37
                               const MPI_Count array_of_displacements[],
          38
                               MPI_Datatype oldtype, MPI_Datatype *newtype)
          39
                Fortran 2008 binding
                MPI_Type_create_hindexed_block(count, blocklength, array_of_displacements,
          41
                               oldtype, newtype, ierror)
          42
                    INTEGER, INTENT(IN) :: count, blocklength
          43
                    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) ::
          44
                                array_of_displacements(count)
           45
                    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
           46
                    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
           47
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
MPI_Type_create_hindexed_block(count, blocklength, array_of_displacements,
               oldtype, newtype, ierror)
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count, blocklength,
               array_of_displacements(count)
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_TYPE_CREATE_HINDEXED_BLOCK(COUNT, BLOCKLENGTH, ARRAY_OF_DISPLACEMENTS,
              OLDTYPE, NEWTYPE, IERROR)
    INTEGER COUNT, BLOCKLENGTH, OLDTYPE, NEWTYPE, IERROR
                                                                                        12
    INTEGER(KIND=MPI_ADDRESS_KIND) ARRAY_OF_DISPLACEMENTS(*)
                                                                                        13
                                                                                        14
                                                                                        15
Struct MPI_TYPE_CREATE_STRUCT is the most general type constructor. It further
                                                                                        16
generalizes MPI_TYPE_CREATE_HINDEXED in that it allows each block to consist of repli-
                                                                                        17
cations of different datatypes.
                                                                                        18
                                                                                       19
                                                                                           #-update1
MPI_TYPE_CREATE_STRUCT(count, array_of_blocklengths, array_of_displacements,
                                                                                       20
              array_of_types, new Was already modified into: number of blocks --- also number of
                                                                                           #-405
                                                                                       21
                                 entries in arrays ...
                                                                                           #-PR427
                                                                                       22
  IN
                                      number of blocks also number of entries in arrays
           count
                                                                                       23
                                      array_of_types, array_of_displacements, and
                                                                                            Done
                                                                                       24
                                      array_of_blocklengths (non-negative integer)
                                      number of elements in each block (array or
  IN
           array_of_blocklengths
                                      non-negative integers)
                                                                                       27
  IN
           array_of_displacements
                                      byte displacement of each block (array of integers)
                                                                                       28
                                                                                        29
           array_of_types
  IN
                                      types of elements in each block (array of handles)
                                                                                        30
  OUT
           newtype
                                      new datatype (handle)
C binding
int MPI_Type_create_struct(int count, const int array_of_blocklengths[],
                                                                                       34
               const MPI_Aint array_of_displacements[],
                                                                                       35
               const MPI_Datatype array_of_types[], MPI_Datatype *newtype)
                                                                                       36
                                                                                       37
int MPI_Type_create_struct_c(MPI_Count count,
               const MPI_Count array_of_blocklengths[],
               const MPI_Count array_of_displacements[],
               const MPI_Datatype array_of_types[], MPI_Datatype *newtype)
Fortran 2008 binding
                                                                                        42
MPI_Type_create_struct(count, array_of_blocklengths,
                                                                                        43
               array_of_displacements, array_of_types, newtype, ierror)
                                                                                       44
    INTEGER, INTENT(IN) :: count, array_of_blocklengths(count)
                                                                                        45
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) ::
                                                                                        46
               array_of_displacements(count)
    TYPE(MPI_Datatype), INTENT(IN) :: array_of_types(count)
```

47

48

```
1
            TYPE(MPI_Datatype), INTENT(OUT) :: newtype
2
            INTEGER, OPTIONAL, INTENT(OUT) :: ierror
      MPI_Type_create_struct(count, array_of_blocklengths,
                         array_of_displacements, array_of_types, newtype, ierror)
5
            INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count,
6
                          array_of_blocklengths(count), array_of_displacements(count)
            TYPE(MPI_Datatype), INTENT(IN) :: array_of_types(count)
            TYPE(MPI_Datatype), INTENT(OUT) :: newtype
9
            INTEGER, OPTIONAL, INTENT(OUT) :: ierror
10
11
      Fortran binding
12
      MPI_TYPE_CREATE_STRUCT(COUNT, ARRAY_OF_BLOCKLENGTHS,
13
                         ARRAY_OF_DISPLACEMENTS, ARRAY_OF_TYPES, NEWTYPE, IERROR)
14
            INTEGER COUNT, ARRAY_OF_BLOCKLENGTHS(*), ARRAY_OF_TYPES(*), NEWTYPE,
15
                          IERROR
16
            INTEGER(KIND=MPI_ADDRESS_KIND) ARRAY_OF_DISPLACEMENTS(*)
17
18
      Example 5.6 Let type 1 have type map,
19
20
             \{(double, 0), (char, 8)\},\
21
       with extent 16. Let B = (2, 1, 3), D = (0, 16, 26), and T = (MPI_FLOAT, type1, MPI_CHAR).
22
       Then a call to MPI_TYPE_CREATE_STRUCT(3, B, D, T, newtype) returns a datatype with
23
      type map,
24
25
             {(float, 0), (float, 4), (double, 16), (char, 24), (char, 26), (char, 27), (char, 28)}.
26
       That is, two copies of MPI_FLOAT starting at 0, followed by one copy of type1 starting at
27
       16, followed by three copies of MPI_CHAR, starting at 26. (We assume that a float occupies
28
       four bytes.)
29
           In general, let T be the array_of_types argument, where T[i] is a handle to,
30
31
             typemap_i = \{(type_0^i, disp_0^i), \dots, (type_{n_i-1}^i, disp_{n_i-1}^i)\},\
32
33
      with extent ex_i. Let B be the array_of_blocklength argument and D be the
34
       array_of_displacements argument. Let c be the count argument. Then the newly created
      datatype has a type map with \sum_{i=0}^{\mathsf{C}-1} \mathsf{B}[i] \cdot n_i entries:
35
36
             \{(type_0^0, disp_0^0 + D[0]), \dots, (type_{n_0}^0, disp_{n_0}^0 + D[0]), \dots, \}
37
38
             (type_0^0, disp_0^0 + D[0] + (B[0] - 1) \cdot ex_0), \dots, (type_{n_0}^0, disp_{n_0}^0 + D[0] + (B[0] - 1) \cdot ex_0), \dots,
39
             (type_0^{\mathsf{C}-1}, disp_0^{\mathsf{C}-1} + \mathsf{D[c-1]}), \dots, (type_{n_{\mathsf{C}-1}-1}^{\mathsf{C}-1}, disp_{n_{\mathsf{C}-1}-1}^{\mathsf{C}-1} + \mathsf{D[c-1]}), \dots,
41
42
             (type_0^{\mathsf{C}-1}, disp_0^{\mathsf{C}-1} + \mathsf{D[c-1]} + (\mathsf{B[c-1]} - 1) \cdot ex_{\mathsf{C}-1}), \dots,
43
             (type_{n_{\mathsf{C}-1}-1}^{\mathsf{C}-1}, disp_{n_{\mathsf{C}-1}-1}^{\mathsf{C}-1} + \mathsf{D[c-1]} + (\mathsf{B[c-1]-1}) \cdot ex_{\mathsf{C}-1})\}.
44
```

A call to MPI\_TYPE\_CREATE\_HINDEXED(count, B, D, oldtype, newtype) is equivalent to a call to MPI\_TYPE\_CREATE\_STRUCT(count, B, D, T, newtype), where each entry of T is equal to oldtype.

```
5.1.3 Subarray Datatype Constructor
MPI_TYPE_CREATE_SUBARRAY(ndims, array_of_sizes, array_of_subsizes, array_of_starts,
              order, oldtype, newtype)
  IN
           ndims
                                      number of array dimensions (positive integer)
           array_of_sizes
  IN
                                      number of elements of type oldtype in each dimension
                                      of the full array (array of positive integers)
           array_of_subsizes
                                      number of elements of type oldtype in each dimension
  IN
                                      of the subarray (array of positive integers)
                                                                                       12
  IN
           array_of_starts
                                      starting coordinates of the subarray in each
                                                                                       13
                                      dimension (array of non-negative integers)
                                                                                       14
  IN
           order
                                      array storage order flag (state)
                                                                                       15
                                                                                       16
  IN
           oldtype
                                      old datatype (handle)
  OUT
                                      new datatype (handle)
           newtype
                                                                                       18
                                                                                       19
C binding
                                                                                       20
int MPI_Type_create_subarray(int ndims, const int array_of_sizes[],
                                                                                       21
              const int array_of_subsizes[], const int array_of_starts[],
                                                                                       22
              int order, MPI_Datatype oldtype, MPI_Datatype *newtype)
                                                                                       23
                                                                                       24
int MPI_Type_create_subarray_c(int ndims, const MPI_Count array_of_sizes[],
              const MPI_Count array_of_subsizes[],
                                                                                       26
              const MPI_Count array_of_starts[], int order,
                                                                                       27
              MPI_Datatype oldtype, MPI_Datatype *newtype)
                                                                                       28
Fortran 2008 binding
                                                                                       29
MPI_Type_create_subarray(ndims, array_of_sizes, array_of_subsizes,
                                                                                       30
              array_of_starts, order, oldtype, newtype, ierror)
                                                                                       31
    INTEGER, INTENT(IN) :: ndims, array_of_sizes(ndims),
               array_of_subsizes(ndims), array_of_starts(ndims), order
                                                                                       33
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                       34
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                       35
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       36
                                                                                       37
MPI_Type_create_subarray(ndims, array_of_sizes, array_of_subsizes,
              array_of_starts, order, oldtype, newtype, ierror)
    INTEGER, INTENT(IN) :: ndims, order
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: array_of_sizes(ndims),
               array_of_subsizes(ndims), array_of_starts(ndims)
                                                                                       42
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                       43
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                       44
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       45
Fortran binding
                                                                                       46
MPI_TYPE_CREATE_SUBARRAY(NDIMS, ARRAY_OF_SIZES, ARRAY_OF_SUBSIZES,
              ARRAY_OF_STARTS, ORDER, OLDTYPE, NEWTYPE, IERROR)
```

The subarray type constructor creates an MPI datatype describing an n-dimensional subarray of an n-dimensional array. The subarray may be situated anywhere within the full array, and may be of any nonzero size up to the size of the larger array as long as it is confined within this array. This type constructor facilitates creating filetypes to access arrays distributed in blocks among processes to a single file that contains the global array, see MPI I/O, especially Section 14.1.1.

This type constructor can handle arrays with an arbitrary number of dimensions and works for both C and Fortran ordered matrices (i.e., row-major or column-major). Note that a C program may use Fortran order and a Fortran program may use C order.

The ndims parameter specifies the number of dimensions in the full data array and gives the number of elements in array\_of\_sizes, array\_of\_subsizes, and array\_of\_starts.

The number of elements of type oldtype in each dimension of the *n*-dimensional array and the requested subarray are specified by array\_of\_sizes and array\_of\_subsizes, respectively. For any dimension i, it is erroneous to specify array\_of\_subsizes[i] < 1 or array\_of\_subsizes[i] > array\_of\_sizes[i].

The array\_of\_starts contains the starting coordinates of each dimension of the subarray. Arrays are assumed to be indexed starting from zero. For any dimension i, it is erroneous to specify array\_of\_starts[i] < 0 or array\_of\_starts[i] > (array\_of\_sizes[i] - array\_of\_subsizes[i]).

Advice to users. In a Fortran program with arrays indexed starting from 1, if the starting coordinate of a particular dimension of the subarray is n, then the entry in array\_of\_starts for that dimension is n-1. (End of advice to users.)

The order argument specifies the storage order for the subarray as well as the full array. It must be set to one of the following:

MPI\_ORDER\_C The ordering used by C arrays, (i.e., row-major order)

MPI\_ORDER\_FORTRAN The ordering used by Fortran arrays, (i.e., column-major order)

A  $\operatorname{\sf ndims\text{-}dimensional}$  subarray ( $\operatorname{\sf newtype}$ ) with no extra padding can be defined by the function Subarray() as follows:

```
newtype = Subarray(ndims, {size_0, size_1, ..., size_{ndims-1}}, {subsize_0, subsize_1, ..., subsize_{ndims-1}}, {start_0, start_1, ..., start_{ndims-1}}, oldtype)
```

Let the typemap of oldtype have the form:

```
\{(type_0, disp_0), (type_1, disp_1), \dots, (type_{n-1}, disp_{n-1})\}
```

where  $type_i$  is a predefined MPI datatype, and let ex be the extent of oldtype. Then we define the Subarray() function recursively using the following three equations. Equation 5.2 defines the base step. Equation 5.3 defines the recursion step when order = MPI\_ORDER\_FORTRAN, and Equation 5.4 defines the recursion step when order = MPI\_ORDER\_C. These equations use the conceptual datatypes lb\_marker and ub\_marker; see Section 5.1.6 for details.

35

36 37

38

39

40 41

42

43

44

45

46

47

48

```
Subarray(1, \{size_0\}, \{subsize_0\}, \{start_0\}, \}
                                                                                                          (5.2)
           \{(type_0, disp_0), (type_1, disp_1), \dots, (type_{n-1}, disp_{n-1})\}
  = \{(\mathsf{lb}_{\mathsf{marker}}, 0),
        (type_0, disp_0 + start_0 \times ex), \dots, (type_{n-1}, disp_{n-1} + start_0 \times ex),
        (type_0, disp_0 + (start_0 + 1) \times ex), \dots, (type_{n-1},
                 disp_{n-1} + (start_0 + 1) \times ex), \dots
                                                                                                                      10
        (tupe_0, disp_0 + (start_0 + subsize_0 - 1) \times ex), \dots,
                                                                                                                      11
                  (type_{n-1}, disp_{n-1} + (start_0 + subsize_0 - 1) \times ex),
                                                                                                                      12
        \{\mathsf{ub\_marker}, size_0 \times ex\}
                                                                                                                      13
                                                                                                                      14
                                                                                                                      15
Subarray(ndims, {size_0, size_1, ..., size_{ndims-1}},
                                                                                                          (5.3)
                                                                                                                      16
           \{subsize_0, subsize_1, \dots, subsize_{ndims-1}\},\
                                                                                                                      17
           \{start_0, start_1, \dots, start_{ndims-1}\}, \mathsf{oldtype}\}
                                                                                                                      18
  = Subarray(ndims - 1, {size_1, size_2, \dots, size_{ndims-1}},
                                                                                                                      19
           \{subsize_1, subsize_2, \dots, subsize_{ndims-1}\},\
                                                                                                                      20
                                                                                                                      21
           \{start_1, start_2, \dots, start_{ndims-1}\},\
                                                                                                                      22
                 Subarray(1, \{size_0\}, \{subsize_0\}, \{start_0\}, oldtype))
                                                                                                                      23
                                                                                                                      24
Subarray(ndims, {size_0, size_1, ..., size_{ndims-1}},
                                                                                                          (5.4)
                                                                                                                      25
                                                                                                                      26
           \{subsize_0, subsize_1, \dots, subsize_{ndims-1}\},\
                                                                                                                      27
           \{start_0, start_1, \dots, start_{ndims-1}\}, oldtype)
                                                                                                                      28
  = Subarray(ndims - 1, {size_0, size_1, ..., size_{ndims-2}},
                                                                                                                      29
           \{subsize_0, subsize_1, \dots, subsize_{ndims-2}\},\
                                                                                                                      30
           \{start_0, start_1, \dots, start_{ndims-2}\},\
                                                                                                                      31
                 Subarray(1, \{size_{ndims-1}\}, \{subsize_{ndims-1}\}, \{start_{ndims-1}\}, oldtype))
                                                                                                                      33
```

For an example use of MPI\_TYPE\_CREATE\_SUBARRAY in the context of I/O see Section 14.9.2.

#### 5.1.4 Distributed Array Datatype Constructor

The distributed array type constructor supports HPF-like [47] data distributions. However, unlike in HPF, the storage order may be specified for C arrays as well as for Fortran arrays.

Advice to users. One can create an HPF-like file view using this type constructor as follows. Complementary filetypes are created by having every process of a group call this constructor with identical arguments (with the exception of rank which should be set appropriately). These filetypes (along with identical disp and etype) are then used to define the view (via MPI\_FILE\_SET\_VIEW), see MPI I/O, especially Section 14.1.1 and Section 14.3. Using this view, a collective data access operation (with identical offsets) will yield an HPF-like distribution pattern. (End of advice to users.)

```
1
     MPI_TYPE_CREATE_DARRAY(size, rank, ndims, array_of_gsizes, array_of_distribs,
2
                    array_of_dargs, array_of_psizes, order, oldtype, newtype)
3
       IN
                 size
                                             size of process group (positive integer)
                                             rank in process group (non-negative integer)
       IN
                 rank
6
       IN
                 ndims
                                             number of array dimensions as well as process grid
                                             dimensions (positive integer)
       IN
                 array_of_gsizes
                                             number of elements of type oldtype in each dimension
                                             of global array (array of positive integers)
10
       IN
                 array_of_distribs
                                             distribution of array in each dimension (array of
11
                                             states)
12
13
       IN
                 array_of_dargs
                                             distribution argument in each dimension (array of
14
                                             positive integers)
15
       IN
                 array_of_psizes
                                             size of process grid in each dimension (array of
16
                                             positive integers)
17
                 order
                                             array storage order flag (state)
       IN
19
       IN
                 oldtype
                                             old datatype (handle)
20
       OUT
                 newtype
                                             new datatype (handle)
21
22
     C binding
23
     int MPI_Type_create_darray(int size, int rank, int ndims,
24
                    const int array_of_gsizes[], const int array_of_distribs[],
25
                    const int array_of_dargs[], const int array_of_psizes[],
26
                    int order, MPI_Datatype oldtype, MPI_Datatype *newtype)
27
     int MPI_Type_create_darray_c(int size, int rank, int ndims,
28
                    const MPI_Count array_of_gsizes[],
29
30
                    const int array_of_distribs[], const int array_of_dargs[],
31
                    const int array_of_psizes[], int order, MPI_Datatype oldtype,
32
                    MPI_Datatype *newtype)
33
     Fortran 2008 binding
34
     MPI_Type_create_darray(size, rank, ndims, array_of_gsizes,
35
                    array_of_distribs, array_of_dargs, array_of_psizes, order,
36
                    oldtype, newtype, ierror)
37
          INTEGER, INTENT(IN) :: size, rank, ndims, array_of_gsizes(ndims),
38
                     array_of_distribs(ndims), array_of_dargs(ndims),
39
                     array_of_psizes(ndims), order
          TYPE(MPI_Datatype), INTENT(IN) :: oldtype
41
          TYPE(MPI_Datatype), INTENT(OUT) :: newtype
42
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
43
44
     MPI_Type_create_darray(size, rank, ndims, array_of_gsizes,
45
                    array_of_distribs, array_of_dargs, array_of_psizes, order,
46
                    oldtype, newtype, ierror)
47
          INTEGER, INTENT(IN) :: size, rank, ndims, array_of_distribs(ndims),
                     array_of_dargs(ndims), array_of_psizes(ndims), order
```

```
INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: array_of_gsizes(ndims)
TYPE(MPI_Datatype), INTENT(IN) :: oldtype
TYPE(MPI_Datatype), INTENT(OUT) :: newtype
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_TYPE_CREATE_DARRAY(SIZE, RANK, NDIMS, ARRAY_OF_GSIZES,

ARRAY_OF_DISTRIBS, ARRAY_OF_DARGS, ARRAY_OF_PSIZES, ORDER,

OLDTYPE, NEWTYPE, IERROR)

INTEGER SIZE, RANK, NDIMS, ARRAY_OF_GSIZES(*), ARRAY_OF_DISTRIBS(*),

ARRAY_OF_DARGS(*), ARRAY_OF_PSIZES(*), ORDER, OLDTYPE,

NEWTYPE, IERROR
```

MPI\_TYPE\_CREATE\_DARRAY can be used to generate the data types corresponding to the distribution of an ndims-dimensional array of old type elements onto an ndims-dimensional grid of logical processes. Unused dimensions of <code>array\_of\_psizes</code> should be set to 1. (See Example 5.7.) For a call to MPI\_TYPE\_CREATE\_DARRAY to be correct, the equation  $\prod_{i=0}^{ndims-1} array\_of\_psizes[i] = size$  must be satisfied. The ordering of processes in the process grid is assumed to be row-major, as in the case of virtual Cartesian process topologies.

Advice to users. For both Fortran and C arrays, the ordering of processes in the process grid is assumed to be row-major. This is consistent with the ordering used in virtual Cartesian process topologies in MPI. To create such virtual process topologies, or to find the coordinates of a process in the process grid, etc., users may use the corresponding process topology functions, see Chapter 8. (End of advice to users.)

Each dimension of the array can be distributed in one of three ways:

- MPI\_DISTRIBUTE\_BLOCK Block distribution
- MPI\_DISTRIBUTE\_CYCLIC Cyclic distribution
- MPI\_DISTRIBUTE\_NONE Dimension not distributed.

The constant MPI\_DISTRIBUTE\_DFLT\_DARG specifies a default distribution argument. The distribution argument for a dimension that is not distributed is ignored. For any dimension i in which the distribution is MPI\_DISTRIBUTE\_BLOCK, it is erroneous to specify array\_of\_dargs[i] \* array\_of\_psizes[i] < array\_of\_gsizes[i].

For example, the HPF layout ARRAY(CYCLIC(15)) corresponds to MPI\_DISTRIBUTE\_CYCLIC with a distribution argument of 15, and the HPF layout ARRAY(BLOCK) corresponds to MPI\_DISTRIBUTE\_BLOCK with a distribution argument of MPI\_DISTRIBUTE\_DFLT\_DARG.

The order argument is used as in MPI\_TYPE\_CREATE\_SUBARRAY to specify the storage order. Therefore, arrays described by this type constructor may be stored in Fortran (column-major) or C (row-major) order. Valid values for order are MPI\_ORDER\_FORTRAN and MPI\_ORDER\_C.

This routine creates a new MPI datatype with a typemap defined in terms of a function called "cyclic()" (see below).

```
1
          Without loss of generality, it suffices to define the typemap for the
2
     MPI_DISTRIBUTE_CYCLIC case where MPI_DISTRIBUTE_DFLT_DARG is not used.
3
          MPI_DISTRIBUTE_BLOCK and MPI_DISTRIBUTE_NONE can be reduced to the
4
     MPI_DISTRIBUTE_CYCLIC case for dimension i as follows.
          MPI_DISTRIBUTE_BLOCK with array_of_dargs[i] equal to MPI_DISTRIBUTE_DFLT_DARG
5
6
     is equivalent to MPI_DISTRIBUTE_CYCLIC with array_of_dargs[i] set to
7
           (array\_of\_gsizes[i] + array\_of\_psizes[i] - 1)/array\_of\_psizes[i].
8
9
     If array_of_dargs[i] is not MPI_DISTRIBUTE_DFLT_DARG, then MPI_DISTRIBUTE_BLOCK and
10
     MPI_DISTRIBUTE_CYCLIC are equivalent.
11
          MPI_DISTRIBUTE_NONE is equivalent to MPI_DISTRIBUTE_CYCLIC with
12
     array_of_dargs[i] set to array_of_gsizes[i].
13
          Finally, MPI_DISTRIBUTE_CYCLIC with array_of_dargs[i] equal to
14
     MPI_DISTRIBUTE_DFLT_DARG is equivalent to MPI_DISTRIBUTE_CYCLIC with
15
     array_of_dargs[i] set to 1.
16
          For MPI_ORDER_FORTRAN, an ndims-dimensional distributed array (newtype) is defined
17
     by the following code fragment:
18
19
          oldtypes[0] = oldtype;
20
          for (i = 0; i < ndims; i++) {
21
              oldtypes[i+1] = cyclic(array_of_dargs[i],
22
                                         array_of_gsizes[i],
23
                                         r[i],
24
                                         array_of_psizes[i],
                                         oldtypes[i]);
26
          }
27
          newtype = oldtypes[ndims];
28
29
          For MPI_ORDER_C, the code is:
30
          oldtypes[0] = oldtype;
          for (i = 0; i < ndims; i++) {
              oldtypes[i + 1] = cyclic(array_of_dargs[ndims - i - 1],
33
34
                                           array_of_gsizes[ndims - i - 1],
35
                                           r[ndims - i - 1],
36
                                           array_of_psizes[ndims - i - 1],
37
                                           oldtypes[i]);
          newtype = oldtypes[ndims];
41
     where r[i] is the position of the process (with rank rank) in the process grid at dimension
42
     i. The values of r[i] are given by the following code fragment:
43
44
          t_rank = rank;
45
          t_size = 1;
46
          for (i = 0; i < ndims; i++)
47
              t_size *= array_of_psizes[i];
```

```
for (i = 0; i < ndims; i++) {
            t_size = t_size / array_of_psizes[i];
            r[i] = t_rank / t_size;
            t_rank = t_rank % t_size;
      }
Let the typemap of oldtype have the form:
       \{(type_0, disp_0), (type_1, disp_1), \dots, (type_{n-1}, disp_{n-1})\}
where type_i is a predefined MPI datatype, and let ex be the extent of
oldtype. The following function uses the conceptual datatypes lb_marker and ub_marker, see
                                                                                                                            11
Section 5.1.6 for details.
                                                                                                                            12
      Given the above, the function cyclic() is defined as follows:
                                                                                                                            13
       \operatorname{cyclic}(darg, gsize, r, psize, \mathsf{oldtype})
                                                                                                                            14
          = \{(\mathsf{lb}_{\mathsf{marker}}, 0),
                                                                                                                            15
               (type_0, disp_0 + r \times darq \times ex), \ldots,
                                                                                                                            16
                                                                                                                            17
                         (type_{n-1}, disp_{n-1} + r \times darg \times ex),
                                                                                                                            18
               (type_0, disp_0 + (r \times darq + 1) \times ex), \dots,
                                                                                                                            19
                         (type_{n-1}, disp_{n-1} + (r \times darq + 1) \times ex)
                                                                                                                            20
                                                                                                                            21
               (type_0, disp_0 + ((r+1) \times darg - 1) \times ex), \dots,
                                                                                                                            22
                        (type_{n-1}, disp_{n-1} + ((r+1) \times darg - 1) \times ex),
                                                                                                                            23
                                                                                                                            24
                                                                                                                            25
               (type_0, disp_0 + r \times darg \times ex + psize \times darg \times ex), \dots,
                                                                                                                            26
                         (type_{n-1}, disp_{n-1} + r \times darg \times ex + psize \times darg \times ex),
                                                                                                                            27
                                                                                                                            28
               (type_0, disp_0 + (r \times darg + 1) \times ex + psize \times darg \times ex), \dots,
                                                                                                                            29
                        (type_{n-1}, disp_{n-1} + (r \times darg + 1) \times ex + psize \times darg \times ex),
                                                                                                                            30
                                                                                                                            31
               (type_0, disp_0 + ((r+1) \times darg - 1) \times ex + psize \times darg \times ex), \ldots,
                                                                                                                            32
                         (type_{n-1}, disp_{n-1} + ((r+1) \times darg - 1) \times ex + psize \times darg \times ex),
                                                                                                                            33
                                                                                                                            34
                                                                                                                            35
               (type_0, disp_0 + r \times darg \times ex + psize \times darg \times ex \times (count - 1)), \ldots,
                                                                                                                            36
                         (type_{n-1}, disp_{n-1} + r \times darg \times ex + psize \times darg \times ex \times (count - 1)),
                                                                                                                            37
                                                                                                                            38
               (type_0, disp_0 + (r \times darg + 1) \times ex + psize \times darg \times ex \times (count - 1)), \dots,
                                                                                                                            39
                      (type_{n-1}, disp_{n-1} + (r \times darg + 1) \times ex
                                   +psize \times darg \times ex \times (count - 1)),
                                                                                                                            41
                                                                                                                            42
               (type_0, disp_0 + (r \times darg + darg_{last} - 1) \times ex
                                                                                                                            43
                                                                                                                            44
                                   +psize \times darg \times ex \times (count - 1)), \dots,
                                                                                                                            45
                         (type_{n-1}, disp_{n-1} + (r \times darg + darg_{last} - 1) \times ex
                                                                                                                            46
                                   +psize \times darg \times ex \times (count - 1)),
                                                                                                                            47
               \{ub\_marker, gsize * ex\}
```

```
where count is defined by this code fragment:
2
         nblocks = (gsize + (darg - 1)) / darg;
         count = nblocks / psize;
         left_over = nblocks - count * psize;
         if (r < left_over)</pre>
              count = count + 1;
     Here, nblocks is the number of blocks that must be distributed among the processors.
9
     Finally, darg_{last} is defined by this code fragment:
10
11
         if ((num_in_last_cyclic = gsize % (psize * darg)) == 0)
12
              darg_last = darg;
13
         else {
14
              darg_last = num_in_last_cyclic - darg * r;
15
              if (darg_last > darg)
16
                  darg_last = darg;
17
              if (darg_last <= 0)</pre>
18
                  darg_last = darg;
19
              }
20
21
     Example 5.7 Consider generating the filetypes corresponding to the HPF distribution:
22
23
            <oldtype> FILEARRAY(100, 200, 300)
24
     !HPF$ PROCESSORS PROCESSES(2, 3)
     !HPF$ DISTRIBUTE FILEARRAY(CYCLIC(10), *, BLOCK) ONTO PROCESSES
26
     This can be achieved by the following Fortran code, assuming there will be six processes
27
     attached to the run:
28
29
     ndims = 3
30
     array_of_gsizes(1) = 100
31
     array_of_distribs(1) = MPI_DISTRIBUTE_CYCLIC
32
     array_of_dargs(1) = 10
     array_of_gsizes(2) = 200
34
     array_of_distribs(2) = MPI_DISTRIBUTE_NONE
35
     array_of_dargs(2) = 0
36
     array_of_gsizes(3) = 300
37
     array_of_distribs(3) = MPI_DISTRIBUTE_BLOCK
38
     array_of_dargs(3) = MPI_DISTRIBUTE_DFLT_DARG
39
     array_of_psizes(1) = 2
40
     array_of_psizes(2) = 1
41
     array_of_psizes(3) = 3
     call MPI_COMM_SIZE(MPI_COMM_WORLD, size, ierr)
43
     call MPI_COMM_RANK(MPI_COMM_WORLD, rank, ierr)
44
     call MPI_TYPE_CREATE_DARRAY(size, rank, ndims, array_of_gsizes, &
45
           array_of_distribs, array_of_dargs, array_of_psizes,
                                                                            &
46
```

MPI\_ORDER\_FORTRAN, oldtype, newtype, ierr)

 $\frac{44}{45}$ 

#### 5.1.5 Address and Size Functions

The displacements in a general datatype are relative to some initial buffer address. **Absolute addresses** can be substituted for these displacements: we treat them as displacements relative to "address zero," the start of the address space. This initial address zero is indicated by the constant MPI\_BOTTOM. Thus, a datatype can specify the absolute address of the entries in the communication buffer, in which case the **buf** argument is passed the value MPI\_BOTTOM. Note that in Fortran MPI\_BOTTOM is not usable for initialization or assignment, see Section 2.5.4.

The address of a location in memory can be found by invoking the function MPI\_GET\_ADDRESS. The **relative displacement** between two absolute addresses can be calculated with the function MPI\_AINT\_DIFF. A new absolute address as sum of an absolute base address and a relative displacement can be calculated with the function MPI\_AINT\_ADD. To ensure portability, arithmetic on absolute addresses should not be performed with the intrinsic operators "-" and "+". See also Sections 2.5.6 and 5.1.12 on pages 20 and 152.

Rationale. Address sized integer values, i.e., MPI\_Aint or INTEGER(KIND=MPI\_ADDRESS\_KIND) values, are signed integers, while absolute addresses are unsigned quantities. Direct arithmetic on addresses stored in address sized signed variables can cause overflows, resulting in undefined behavior. (End of rationale.)

```
MPI_GET_ADDRESS(location, address)
```

IN location location in caller memory (choice)
OUT address address of location (integer)

#### C binding

int MPI\_Get\_address(const void \*location, MPI\_Aint \*address)

#### Fortran 2008 binding

```
MPI_Get_address(location, address, ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: location
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: address
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

Returns the (byte) address of location.

Rationale. In the mpi\_f08 module, the location argument is not defined with INTENT(IN) because existing applications may use MPI\_GET\_ADDRESS as a substitute for MPI\_F\_SYNC\_REG, which was not defined before MPI-3.0. (End of rationale.)

```
1
     Example 5.8 Using MPI_GET_ADDRESS for an array.
2
3
     REAL A(100,100)
     INTEGER(KIND=MPI_ADDRESS_KIND) I1, I2, DIFF
4
     CALL MPI_GET_ADDRESS(A(1,1), I1, IERROR)
5
     CALL MPI_GET_ADDRESS(A(10,10), I2, IERROR)
6
     DIFF = MPI_AINT_DIFF(I2, I1)
7
     ! The value of DIFF is 909*SIZEOF(REAL); the values of I1 and I2 are
     ! implementation dependent.
9
10
          Advice to users.
                             C users may be tempted to avoid the usage of
11
          MPI_GET_ADDRESS and rely on the availability of the address operator &. Note,
12
          however, that & cast-expression is a pointer, not an address. ISO C does not require
13
          that the value of a pointer (or the pointer cast to int) be the absolute address of
14
          the object pointed at—although this is commonly the case. Furthermore, referencing
15
          may not have a unique definition on machines with a segmented address space. The
16
          use of MPI_GET_ADDRESS to "reference" C variables guarantees portability to such
          machines as well. (End of advice to users.)
18
```

Advice to users. To prevent problems with the argument copying and register optimization done by Fortran compilers, please note the hints in Sections 19.1.10–19.1.20. (End of advice to users.)

To ensure portability, arithmetic on MPI addresses must be performed using the MPI\_AINT\_ADD and MPI\_AINT\_DIFF functions.

```
MPI_AINT_ADD(base, disp)
```

```
IN base base address (integer)IN disp displacement (integer)
```

#### C binding

19

20

21

22 23

24

252627

28

29

30

31 32

33

34

35

36

37

39

40

41

42

43

44

45

46

47

48

MPI\_Aint MPI\_Aint\_add(MPI\_Aint base, MPI\_Aint disp)

#### Fortran 2008 binding

```
INTEGER(KIND=MPI_ADDRESS_KIND) MPI_Aint_add(base, disp)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: base, disp
```

#### Fortran binding

```
INTEGER(KIND=MPI_ADDRESS_KIND) MPI_AINT_ADD(BASE, DISP)
    INTEGER(KIND=MPI_ADDRESS_KIND) BASE, DISP
```

MPI\_AINT\_ADD produces a new MPI\_Aint value that is equivalent to the sum of the base and disp arguments, where base represents a base address returned by a call to MPI\_GET\_ADDRESS and disp represents a signed integer displacement. The resulting address is valid only at the process that generated base, and it must correspond to a location in the same object referenced by base, as described in Section 5.1.12. The addition is performed in a manner that results in the correct MPI\_Aint representation of the output address, as if the process that originally produced base had called:

12

13

14 15

16

17

18

26

30

31

33

38

39

42

43 44

45

46

```
MPI_Get_address((char *) base + disp, &result);
MPI_AINT_DIFF(addr1, addr2)
  IN
           addr1
                                      minuend address (integer)
  IN
           addr2
                                      subtrahend address (integer)
C binding
MPI_Aint MPI_Aint_diff(MPI_Aint addr1, MPI_Aint addr2)
Fortran 2008 binding
INTEGER(KIND=MPI_ADDRESS_KIND) MPI_Aint_diff(addr1, addr2)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: addr1, addr2
Fortran binding
INTEGER(KIND=MPI_ADDRESS_KIND) MPI_AINT_DIFF(ADDR1, ADDR2)
    INTEGER(KIND=MPI_ADDRESS_KIND) ADDR1, ADDR2
    MPI_AINT_DIFF produces a new MPI_Aint value that is equivalent to the difference
                                                                                       19
between addr1 and addr2 arguments, where addr1 and addr2 represent addresses returned
                                                                                       20
by calls to MPI_GET_ADDRESS. The resulting address is valid only at the process that
                                                                                       21
generated addr1 and addr2, and addr1 and addr2 must correspond to locations in the same
                                                                                       22
object in the same process, as described in Section 5.1.12. The difference is calculated in
                                                                                       23
a manner that results in the signed difference from addr1 to addr2, as if the process that
                                                                                       24
originally produced the addresses had called (char *) addr1 - (char *) addr2 on the
addresses initially passed to MPI_GET_ADDRESS.
    The following auxiliary functions provide useful information on derived datatypes.
                                                                                       27
                                                                                       28
                                                                                       29
MPI_TYPE_SIZE(datatype, size)
  IN
           datatype
                                      datatype (handle)
  OUT
                                      datatype size (integer)
           size
                                                                                       34
C binding
                                                                                       35
int MPI_Type_size(MPI_Datatype datatype, int *size)
                                                                                       36
int MPI_Type_size_c(MPI_Datatype datatype, MPI_Count *size)
                                                                                       37
Fortran 2008 binding
MPI_Type_size(datatype, size, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Type_size(datatype, size, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

23

24

25

26

27

28

29 30

31 32

33

34

35

36

37

38

39

40

41

42

43

44

45

46 47

48

```
1
     Fortran binding
2
     MPI_TYPE_SIZE(DATATYPE, SIZE, IERROR)
3
         INTEGER DATATYPE, SIZE, IERROR
4
5
6
     MPI_TYPE_SIZE_X(datatype, size)
                datatype
       IN
                                           datatype (handle)
8
       OUT
9
                size
                                           datatype size (integer)
10
11
     C binding
12
     int MPI_Type_size_x(MPI_Datatype datatype, MPI_Count *size)
13
     Fortran 2008 binding
14
     MPI_Type_size_x(datatype, size, ierror)
15
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
16
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: size
17
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
18
19
     Fortran binding
20
     MPI_TYPE_SIZE_X(DATATYPE, SIZE, IERROR)
21
         INTEGER DATATYPE, IERROR
22
         INTEGER(KIND=MPI_COUNT_KIND) SIZE
```

MPI\_TYPE\_SIZE and MPI\_TYPE\_SIZE\_X set the value of size to the total size, in bytes, of the entries in the type signature associated with datatype; i.e., the total size of the data in a message that would be created with this datatype. Entries that occur multiple times in the datatype are counted with their multiplicity. For both functions, if the OUT parameter cannot express the value to be returned (e.g., if the parameter is too small to hold the output value), it is set to MPI\_UNDEFINED.

#### Lower-Bound and Upper-Bound Markers 5.1.6

It is often convenient to define explicitly the lower bound and upper bound of a type map, and override the definition given on page 141. This allows one to define a datatype that has "holes" at its beginning or its end, or a datatype with entries that extend above the upper bound or below the lower bound. Examples of such usage are provided in Section 5.1.14. Also, the user may want to overide the alignment rules that are used to compute upper bounds and extents. E.g., a C compiler may allow the user to overide default alignment rules for some of the structures within a program. The user has to specify explicitly the bounds of the datatypes that match these structures.

To achieve this, we add two additional conceptual datatypes, lb\_marker and **ub\_marker**, that represent the lower bound and upper bound of a datatype. These conceptual datatypes occupy no space  $(extent(lb_marker) = extent(ub_marker) = 0)$ . They do not affect the size or count of a datatype, and do not affect the content of a message created with this datatype. However, they do affect the definition of the extent of a datatype and, therefore, affect the outcome of a replication of this datatype by a datatype constructor.

Example 5.9 A call to MPI\_TYPE\_CREATE\_RESIZED(MPI\_INT, -3, 9, type1) creates a

new datatype that has an extent of 9 (from -3 to 5, 5 included), and contains an integer at displacement 0. This is the datatype defined by the typemap {(lb\_marker, -3), (int, 0), (ub\_marker, 6)}. If this type is replicated twice by a call to MPI\_TYPE\_CONTIGUOUS(2, type1, type2) then the newly created type can be described by the typemap {(lb\_marker, -3), (int, 0), (int,9), (ub\_marker, 15)}. (An entry of type ub\_marker can be deleted if there is another entry of type ub\_marker with a higher displacement; an entry of type lb\_marker can be deleted if there is another entry of type lb\_marker with a lower displacement.)

In general, if

$$Typemap = \{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1})\},\$$

then the **lower bound** of *Typemap* is defined to be

$$lb(Typemap) = \left\{ \begin{array}{ll} \min_{j} disp_{j} & \text{if no entry has type} \\ \min_{j} \{ disp_{j} \text{ such that } type_{j} = \mathsf{lb\_marker} \} & \text{otherwise} \end{array} \right.$$

Similarly, the **upper bound** of *Typemap* is defined to be

$$ub(Typemap) = \begin{cases} \max_{j} (disp_{j} + sizeof(type_{j})) + \epsilon & \text{if no entry has type} \\ \max_{j} \{disp_{j} \text{ such that } type_{j} = \text{ub\_marker} \} & \text{otherwise} \end{cases}$$

Then

$$extent(Typemap) = ub(Typemap) - lb(Typemap)$$

If  $type_i$  requires alignment to a byte address that is a multiple of  $k_i$ , then  $\epsilon$  is the least non-negative increment needed to round extent(Typemap) to the next multiple of  $\max_i k_i$ . In Fortran, it is implementation dependent whether the MPI implementation computes the alignments  $k_i$  according to the alignments used by the compiler in common blocks, SEQUENCE derived types, BIND(C) derived types, or derived types that are neither SEQUENCE nor BIND(C).

The formal definitions given for the various datatype constructors apply now, with the amended definition of **extent**.

Rationale. Before Fortran 2003, MPI\_TYPE\_CREATE\_STRUCT could be applied to Fortran common blocks and SEQUENCE derived types. With Fortran 2003, this list was extended by BIND(C) derived types and MPI implementors have implemented the alignments  $k_i$  differently, i.e., some based on the alignments used in SEQUENCE derived types, and others according to BIND(C) derived types. (End of rationale.)

Advice to implementors. In Fortran, it is generally recommended to use BIND(C) derived types instead of common blocks or SEQUENCE derived types. Therefore it is recommended to calculate the alignments  $k_i$  based on BIND(C) derived types. (End of advice to implementors.)

Advice to users. Structures combining different basic datatypes should be defined so that there will be no gaps based on alignment rules. If such a datatype is used to create an array of structures, users should also avoid an alignment-gap at the end of the structure. In MPI communication, the content of such gaps would not be communicated into the receiver's buffer. For example, such an alignment-gap

may occur between an odd number of floats or REALs before a double or DOUBLE PRECISION data. Such gaps may be added explicitly to both the structure and the MPI derived datatype handle because the communication of a contiguous derived datatype may be significantly faster than the communication of one that is non-contiguous because of such alignment-gaps.

Example: Instead of

END TYPE

```
TYPE, BIND(C) :: my_data

REAL, DIMENSION(3) :: x
! there may be a gap of the size of one REAL
! if the alignment of a DOUBLE PRECISION is
! two times the size of a REAL
DOUBLE PRECISION :: p
END TYPE

one should define

TYPE, BIND(C) :: my_data
REAL, DIMENSION(3) :: x
REAL :: gap1
DOUBLE PRECISION :: p
```

and also include gap1 in the matching MPI derived datatype. It is required that all processes in a communication add the same gaps, i.e., defined with the same basic datatype. Both the original and the modified structures are portable, but may have different performance implications for the communication and memory accesses during computation on systems with different alignment values.

In principle, a compiler may define an additional alignment rule for structures, e.g., to use at least 4 or 8 byte alignment, although the content may have a  $\max_i k_i$  alignment less than this structure alignment. To maintain portability, users should always resize structure derived datatype handles if used in an array of structures, see the Example in Section 19.1.15. (End of advice to users.)

#### 5.1.7 Extent and Bounds of Datatypes

```
MPI_TYPE_GET_EXTENT(datatype, lb, extent)

IN datatype datatype to get information on (handle)

OUT lb lower bound of datatype (integer)

OUT extent extent of datatype (integer)

C binding
int MPI_Type_get_extent(MPI_Datatype datatype, MPI_Aint *lb,

MPI_Aint *extent)
```

```
int MPI_Type_get_extent_c(MPI_Datatype datatype, MPI_Count *lb,
              MPI_Count *extent)
Fortran 2008 binding
MPI_Type_get_extent(datatype, lb, extent, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: lb, extent
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Type_get_extent(datatype, lb, extent, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                       11
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: lb, extent
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       12
                                                                                       13
Fortran binding
                                                                                       14
MPI_TYPE_GET_EXTENT(DATATYPE, LB, EXTENT, IERROR)
                                                                                       15
    INTEGER DATATYPE, IERROR
                                                                                       16
    INTEGER(KIND=MPI_ADDRESS_KIND) LB, EXTENT
                                                                                       18
                                                                                       19
MPI_TYPE_GET_EXTENT_X(datatype, lb, extent)
                                                                                       20
                                                                                       21
  IN
                                      datatype to get information on (handle)
           datatype
                                                                                       22
  OUT
           lb
                                      lower bound of datatype (integer)
                                                                                       23
  OUT
                                      extent of datatype (integer)
           extent
                                                                                       26
C binding
int MPI_Type_get_extent_x(MPI_Datatype datatype, MPI_Count *lb,
                                                                                       27
                                                                                       28
              MPI_Count *extent)
                                                                                       29
Fortran 2008 binding
                                                                                       30
MPI_Type_get_extent_x(datatype, lb, extent, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: lb, extent
                                                                                       33
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       34
                                                                                       35
Fortran binding
                                                                                       36
MPI_TYPE_GET_EXTENT_X(DATATYPE, LB, EXTENT, IERROR)
                                                                                       37
    INTEGER DATATYPE, IERROR
    INTEGER(KIND=MPI_COUNT_KIND) LB, EXTENT
    Returns the lower bound and the extent of datatype (as defined in Equation 5.1).
    For both functions, if either OUT parameter cannot express the value to be returned
(e.g., if the parameter is too small to hold the output value), it is set to MPI_UNDEFINED.
    MPI allows one to change the extent of a datatype, using lower bound and upper bound
                                                                                       43
markers. This provides control over the stride of successive datatypes that are replicated
                                                                                       44
by datatype constructors, or are replicated by the count argument in a send or receive call.
                                                                                       45
```

#-error!

Done

```
"input" datatype is correct. After the release
                                                                             of this RC 40 document, somebody changed
             MPI_TYPE_CREATE_RESIZED(oldtype, lb, extent, newtype)
                                                                             it to "old" datatype, which is incorrect and
#-other 12
               IN
                         oldtype
                                                      input datatype (handle)
                                                                             must be reverted.
               IN
                         lb
                                                      new lower bound of datatype (integer)
        5
               IN
                         extent
                                                      new extent of datatype (integer)
        6
               OUT
                         newtype
                                                      output datatype (handle)
        7
                   https://github.com/mpi-forum/mpi-standard/commit/06d0e8b00679dae3af201a1594f67bfb1db1899e#diff-23137ee8f54746beeeb2ec2383c079a5bf30723d60fc080fc861ff8b8dbe70d2
                   See chap-datatypes/datatypes.tex, line 1800
             C binding
        9
             int MPI_Type_create_resized(MPI_Datatype oldtype, MPI_Aint lb,
        10
                             MPI_Aint extent, MPI_Datatype *newtype)
        11
       12
             int MPI_Type_create_resized_c(MPI_Datatype oldtype, MPI_Count 1b,
        13
                             MPI_Count extent, MPI_Datatype *newtype)
       14
             Fortran 2008 binding
        15
             MPI_Type_create_resized(oldtype, lb, extent, newtype,
                                                                            ierror)
        16
                  TYPE(MPI_Datatype), INTENT(IN) :: oldtype
        17
                  INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: 1b, extent
        18
                  TYPE(MPI_Datatype), INTENT(OUT) :: newtype
        19
                  INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       20
       21
             MPI_Type_create_resized(oldtype, lb, extent, newtype, ierror)
       22
                  TYPE(MPI_Datatype), INTENT(IN) :: oldtype
       23
                  INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: lb, extent
       24
                  TYPE(MPI_Datatype), INTENT(OUT) :: newtype
        25
                  INTEGER, OPTIONAL, INTENT(OUT) :: ierror
        26
             Fortran binding
       27
             MPI_TYPE_CREATE_RESIZED(OLDTYPE, LB, EXTENT, NEWTYPE, IERROR)
       28
                  INTEGER OLDTYPE, NEWTYPE, IERROR
       29
                  INTEGER (KIND=MPI ADDRESS KIND) LB, EXTENT
       30
```

Returns in newtype a handle to a new datatype that is identical to oldtype, except that the lower bound of this new datatype is set to be lb, and its upper bound is set to be lb + extent. Any previous lb and ub markers are erased, and a new pair of lower bound and upper bound markers are put in the positions indicated by the lb and extent arguments. This affects the behavior of the datatype when used in communication operations, with count > 1, and when used in the construction of new derived datatypes.

## True Extent of Datatypes

Suppose we implement gather (see also Section 6.5) as a spanning tree implemented on top of point-to-point routines. Since the receive buffer is only valid on the root process, one will need to allocate some temporary space for receiving data on intermediate nodes. However, the datatype extent cannot be used as an estimate of the amount of space that needs to be allocated, if the user has modified the extent, for example by using MPI\_TYPE\_CREATE\_RESIZED. The functions MPI\_TYPE\_GET\_TRUE\_EXTENT and MPI\_TYPE\_GET\_TRUE\_EXTENT\_X are provided which return the true extent of the datatype.

47

31

32

33

34

35

36

37 38

39

41 42

43

44

45

46

MPI_TYPE_GET_TRUE_EXTENT(datatype, true_lb, true_extent)   1			
IN	datatype	datatype to get information on (handle)	2
OUT	true_lb	true lower bound of datatype (integer)	4
OUT	true_extent	true size of datatype (integer)	5
			6
C bindin	_		7 8
int MPI_7	· - •	Datatype datatype, MPI_Aint *true_lb,	9
	MPI_Aint *true_exten	t)	10
int MPI_7	<pre>Sype_get_true_extent_c(MP: MPI_Count *true_exte</pre>	<pre>I_Datatype datatype, MPI_Count *true_lb, nt)</pre>	11 12
Fontman (			13
	2008 binding get true extent(datatype	, true_lb, true_extent, ierror)	14
	(MPI_Datatype), INTENT(IN		15
INTEC	GER(KIND=MPI_ADDRESS_KIND)	), INTENT(OUT) :: true_lb, true_extent	16 17
INTEC	GER, OPTIONAL, INTENT(OUT)	) :: ierror	18
MPI_Type_	_get_true_extent(datatype	, true_lb, true_extent, ierror)	19
	(MPI_Datatype), INTENT(IN		20
		<pre>INTENT(OUT) :: true_lb, true_extent</pre>	21
INTEC	GER, OPTIONAL, INTENT(OUT)	) :: ierror	22
Fortran l	oinding		23
MPI_TYPE_	_GET_TRUE_EXTENT(DATATYPE	, TRUE_LB, TRUE_EXTENT, IERROR)	24 25
	GER DATATYPE, IERROR		26
INTEC	GER(KIND=MPI_ADDRESS_KIND)	) TRUE_LB, TRUE_EXTENT	27
			28
MDI TVDI	E_GET_TRUE_EXTENT_X(da	tatype true lb true extent)	29
			30
IN	datatype	datatype to get information on (handle)	31 32
OUT	true_lb	true lower bound of datatype (integer)	33
OUT	true_extent	true size of datatype (integer)	34
	, in the second second		35
C bindin			36
int MPI_7		<pre>I_Datatype datatype, MPI_Count *true_lb,</pre>	37
	MPI_Count *true_exte	nt)	38 39
	2008 binding		40
	-	pe, true_lb, true_extent, ierror)	41
	(MPI_Datatype), INTENT(IN	V-	42
	GER, OPTIONAL, INTENT(OUT)	INTENT(OUT) :: true_lb, true_extent ) :: ierror	43
·			44
Fortran b	•		45
	_GET_TRUE_EXTENT_X(DATATY) GER_DATATYPE,	PE, TRUE_LB, TRUE_EXTENT, IERROR)	46 47
	GER(KIND=MPI_COUNT_KIND)	TRUE I.B. TRUE EXTENT	48
111111		,	-

2

3

4

5

6

7 8

9 10

11

12 13

14 15

16 17

18

19

20

21

22

23 24

25

26

27

28 29 30

31

32 33 34

35 36

37

38

39

40 41

42

43

44

45

46

47

48

and

true\_lb returns the offset of the lowest unit of store which is addressed by the datatype, i.e., the lower bound of the corresponding typemap, ignoring explicit lower bound markers. true\_extent returns the true size of the datatype, i.e., the extent of the corresponding typemap, ignoring explicit lower bound and upper bound markers, and performing no rounding for alignment. If the typemap associated with datatype is

```
Typemap = \{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1})\}
Then
      true\_lb(Typemap) = min_i \{ disp_i : type_i \neq lb\_marker, ub\_marker \},
      true\_ub(Typemap) = max_i \{ disp_i + sizeof(type_i) : type_i \neq lb\_marker, ub\_marker \},
```

 $true\_extent(Typemap) = true\_ub(Typemap) - true\_lb(typemap).$ 

(Readers should compare this with the definitions in Section 5.1.6 and Section 5.1.7, which describe the function MPI\_TYPE\_GET\_EXTENT.)

The true\_extent is the minimum number of bytes of memory necessary to hold a datatype, uncompressed.

For both functions, if either OUT parameter cannot express the value to be returned (e.g., if the parameter is too small to hold the output value), it is set to MPI\_UNDEFINED.

# 5.1.9 Commit and Free

INTEGER DATATYPE, IERROR

A datatype object has to be **committed** before it can be used in a communication. As an argument in datatype constructors, uncommitted and also committed datatypes can be used. There is no need to commit basic datatypes. They are "pre-committed."

```
MPI_TYPE_COMMIT(datatype)
 INOUT datatype
                                   datatype that is committed (handle)
C binding
int MPI_Type_commit(MPI_Datatype *datatype)
Fortran 2008 binding
MPI_Type_commit(datatype, ierror)
    TYPE(MPI_Datatype), INTENT(INOUT) :: datatype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_TYPE_COMMIT(DATATYPE, IERROR)
```

The commit operation commits the datatype, that is, the formal description of a communication buffer, not the content of that buffer. Thus, after a datatype has been committed, it can be repeatedly reused to communicate the changing content of a buffer or, indeed, the content of different buffers, with different starting addresses.

6

9

11

12

13

14

15

16

17

18

19

20

21

22 23 24

25 26

27 28

29

30

33

34 35

36

37

38

41

42

43 44

45

46

47

Advice to implementors. The system may "compile" at commit time an internal representation for the datatype that facilitates communication, e.g., change from a compacted representation to a flat representation of the datatype, and select the most convenient transfer mechanism. (End of advice to implementors.)

MPI\_TYPE\_COMMIT will accept a committed datatype; in this case, it is equivalent to a no-op.

**Example 5.10** The following code fragment gives examples of using MPI\_TYPE\_COMMIT.

```
INTEGER type1, type2
CALL MPI_TYPE_CONTIGUOUS(5, MPI_REAL, type1, ierr)
              ! new type object created
CALL MPI_TYPE_COMMIT(type1, ierr)
              ! now type1 can be used for communication
type2 = type1
              ! type2 can be used for communication
              ! (it is a handle to same object as type1)
CALL MPI_TYPE_VECTOR(3, 5, 4, MPI_REAL, type1, ierr)
              ! new uncommitted type object created
CALL MPI_TYPE_COMMIT(type1, ierr)
              ! now type1 can be used anew for communication
MPI_TYPE_FREE(datatype)
                                    datatype that is freed (handle)
 INOUT
          datatype
C binding
int MPI_Type_free(MPI_Datatype *datatype)
Fortran 2008 binding
MPI_Type_free(datatype, ierror)
    TYPE(MPI_Datatype), INTENT(INOUT) :: datatype
```

INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding

MPI\_TYPE\_FREE(DATATYPE, IERROR)

INTEGER DATATYPE, IERROR

Marks the datatype object associated with datatype for deallocation and sets datatype to MPI\_DATATYPE\_NULL. Any communication that is currently using this datatype will complete normally. Freeing a datatype does not affect any other datatype that was built from the freed datatype. The system behaves as if input datatype arguments to derived datatype constructors are passed by value.

Advice to implementors. The implementation may keep a reference count of active communications that use the datatype, in order to decide when to free it. Also, one may implement constructors of derived datatypes so that they keep pointers to their datatype arguments, rather then copying them. In this case, one needs to keep track

of active datatype definition references in order to know when a datatype object can be freed. (*End of advice to implementors.*)

# 5.1.10 Duplicating a Datatype

```
MPI_TYPE_DUP(oldtype, newtype)
```

```
IN oldtype datatype (handle)
OUT newtype copy of oldtype (handle)
```

# C binding

```
int MPI_Type_dup(MPI_Datatype oldtype, MPI_Datatype *newtype)
```

## Fortran 2008 binding

```
MPI_Type_dup(oldtype, newtype, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_TYPE_DUP(OLDTYPE, NEWTYPE, IERROR)
INTEGER OLDTYPE, NEWTYPE, IERROR
```

MPI\_TYPE\_DUP is a type constructor which duplicates the existing oldtype with associated key values. For each key value, the respective copy callback function determines the attribute value associated with this key in the new communicator; one particular action that a copy callback may take is to delete the attribute from the new datatype. Returns in newtype a new datatype with exactly the same properties as oldtype and any copied cached information, see Section 7.7.4. The new datatype has identical upper bound and lower bound and yields the same net result when fully decoded with the functions in Section 5.1.13. The newtype has the same committed state as the old oldtype.

## 5.1.11 Use of General Datatypes in Communication

Handles to derived datatypes can be passed to a communication call wherever a datatype argument is required. A call of the form MPI\_SEND(buf, count, datatype, ...), where count > 1, is interpreted as if the call was passed a new datatype which is the concatenation of count copies of datatype. Thus, MPI\_SEND(buf, count, datatype, dest, tag, comm) is equivalent to,

```
MPI_TYPE_CONTIGUOUS(count, datatype, newtype)
MPI_TYPE_COMMIT(newtype)
MPI_SEND(buf, 1, newtype, dest, tag, comm)
MPI_TYPE_FREE(newtype).
```

Similar statements apply to all other communication functions that have a **count** and **datatype** argument.

Suppose that a send operation MPI\_SEND(buf, count, datatype, dest, tag, comm) is executed, where datatype has type map,

```
\{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1})\},\
```

and extent extent. (Explicit lower bound and upper bound markers are not listed in the type map, but they affect the value of extent.) The send operation sends  $n \cdot \text{count}$  entries, where entry  $i \cdot n + j$  is at location  $addr_{i,j} = \text{buf} + extent \cdot i + disp_j$  and has type  $type_j$ , for  $i = 0, \ldots, \text{count} - 1$  and  $j = 0, \ldots, n - 1$ . These entries need not be contiguous, nor distinct; their order can be arbitrary.

The variable stored at address  $addr_{i,j}$  in the calling program should be of a type that matches  $type_j$ , where type matching is defined as in Section 3.3.1. The message sent contains  $n \cdot \text{count}$  entries, where entry  $i \cdot n + j$  has type  $type_j$ .

Similarly, suppose that a receive operation MPI\_RECV(buf, count, datatype, source, tag, comm, status) is executed, where datatype has type map,

```
\{(type_0, disp_0), \ldots, (type_{n-1}, disp_{n-1})\},\
```

with extent extent. (Again, explicit lower bound and upper bound markers are not listed in the type map, but they affect the value of extent.) This receive operation receives  $n \cdot \text{count}$  entries, where entry  $i \cdot n + j$  is at location  $\text{buf} + extent \cdot i + disp_j$  and has type  $type_j$ . If the incoming message consists of k elements, then we must have  $k \leq n \cdot \text{count}$ ; the  $i \cdot n + j$ -th element of the message should have a type that matches  $type_j$ .

**Type matching** is defined according to the type signature of the corresponding datatypes, that is, the sequence of basic type components. Type matching does not depend on some aspects of the datatype definition, such as the displacements (layout in memory) or the intermediate types used.

**Example 5.11** This example shows that type matching is defined in terms of the basic types that a derived type consists of.

```
CALL MPI_TYPE_CONTIGUOUS(2, MPI_REAL, type2, ...)

CALL MPI_TYPE_CONTIGUOUS(4, MPI_REAL, type4, ...)

CALL MPI_TYPE_CONTIGUOUS(2, type2, type22, ...)

...

CALL MPI_SEND(a, 4, MPI_REAL, ...)

CALL MPI_SEND(a, 2, type2, ...)

CALL MPI_SEND(a, 1, type22, ...)

CALL MPI_SEND(a, 1, type4, ...)

...

CALL MPI_RECV(a, 4, MPI_REAL, ...)

CALL MPI_RECV(a, 2, type2, ...)

CALL MPI_RECV(a, 1, type22, ...)

CALL MPI_RECV(a, 1, type22, ...)

CALL MPI_RECV(a, 1, type4, ...)
```

Each of the sends matches any of the receives.

A datatype may specify overlapping entries. The use of such a datatype in a receive operation is erroneous. (This is erroneous even if the actual message received is short enough not to write any entry more than once.)

Suppose that MPI\_RECV(buf, count, datatype, dest, tag, comm, status) is executed, where datatype has type map,

```
\{(type_0, disp_0), \dots, (type_{n-1}, disp_{n-1})\}.
```

```
1
     The received message need not fill all the receive buffer, nor does it need to fill a number of
2
     locations which is a multiple of n. Any number, k, of basic elements can be received, where
3
     0 \le k \le \text{count} \cdot n. The number of basic elements received can be retrieved from status using
4
     the guery functions MPI_GET_ELEMENTS or MPI_GET_ELEMENTS_X.
5
6
     MPI_GET_ELEMENTS(status, datatype, count)
7
       IN
                                             return status of receive operation (Status)
                status
9
       IN
                                             datatype used by receive operation (handle)
                datatype
10
                                             number of received basic elements (integer)
       OUT
                count
11
12
13
     C binding
     int MPI_Get_elements(const MPI_Status *status, MPI_Datatype datatype,
14
15
                    int *count)
16
     int MPI_Get_elements_c(const MPI_Status *status, MPI_Datatype datatype,
17
                    MPI_Count *count)
18
19
     Fortran 2008 binding
     MPI_Get_elements(status, datatype, count, ierror)
20
21
         TYPE(MPI_Status), INTENT(IN) :: status
22
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
23
         INTEGER, INTENT(OUT) :: count
24
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Get_elements(status, datatype, count, ierror)
26
         TYPE(MPI_Status), INTENT(IN) :: status
27
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
28
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: count
29
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
30
31
     Fortran binding
32
     MPI_GET_ELEMENTS(STATUS, DATATYPE, COUNT, IERROR)
33
          INTEGER STATUS(MPI_STATUS_SIZE), DATATYPE, COUNT, IERROR
34
35
36
     MPI_GET_ELEMENTS_X(status, datatype, count)
37
       IN
                 status
                                             return status of receive operation (Status)
38
39
       IN
                 datatype
                                             datatype used by receive operation (handle)
40
       OUT
                count
                                             number of received basic elements (integer)
41
42
     C binding
43
     int MPI_Get_elements_x(const MPI_Status *status, MPI_Datatype datatype,
44
                    MPI_Count *count)
45
^{46}
     Fortran 2008 binding
47
     MPI_Get_elements_x(status, datatype, count, ierror)
         TYPE(MPI_Status), INTENT(IN) :: status
```

12

13

14

15

16

17

18

19

20

21

22 23 24

26 27

28

29

31

34

35

36

37

38

42

43

44

45 46

47

```
TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: count
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI_GET_ELEMENTS_X(STATUS, DATATYPE, COUNT, IERROR)
    INTEGER STATUS(MPI_STATUS_SIZE), DATATYPE, IERROR
    INTEGER(KIND=MPI_COUNT_KIND) COUNT
```

The datatype argument should match the argument provided by the receive call that set the status variable. For both functions, if the OUT parameter cannot express the value to be returned (e.g., if the parameter is too small to hold the output value), it is set to MPI\_UNDEFINED.

The previously defined function MPI\_GET\_COUNT (Section 3.2.5), has a different behavior. It returns the number of "top-level entries" received, i.e. the number of "copies" of type datatype. In the previous example, MPI\_GET\_COUNT may return any integer value k, where  $0 \le k \le \text{count}$ . If MPI\_GET\_COUNT returns k, then the number of basic elements received (and the value returned by MPI\_GET\_ELEMENTS or MPI\_GET\_ELEMENTS\_X) is  $n \cdot k$ . If the number of basic elements received is not a multiple of n, that is, if the receive operation has not received an integral number of datatype "copies," then MPI\_GET\_COUNT sets the value of count to MPI\_UNDEFINED.

Example 5.12 Usage of MPI\_GET\_COUNT and MPI\_GET\_ELEMENTS.

```
CALL MPI_TYPE_CONTIGUOUS(2, MPI_REAL, Type2, ierr)
CALL MPI_TYPE_COMMIT(Type2, ierr)
CALL MPI_COMM_RANK(comm, rank, ierr)
IF (rank.EQ.0) THEN
   CALL MPI_SEND(a, 2, MPI_REAL, 1, 0, comm, ierr)
   CALL MPI_SEND(a, 3, MPI_REAL, 1, 0, comm, ierr)
ELSE IF (rank.EQ.1) THEN
   CALL MPI_RECV(a, 2, Type2, 0, 0, comm, stat, ierr)
   CALL MPI_GET_COUNT(stat, Type2, i, ierr)
                                                ! returns i=1
  CALL MPI_GET_ELEMENTS(stat, Type2, i, ierr) ! returns i=2
   CALL MPI_RECV(a, 2, Type2, 0, 0, comm, stat, ierr)
   CALL MPI_GET_COUNT(stat, Type2, i, ierr)
                                                ! returns i=MPI_UNDEFINED
   CALL MPI_GET_ELEMENTS(stat, Type2, i, ierr) ! returns i=3
END IF
```

The functions MPI\_GET\_ELEMENTS and MPI\_GET\_ELEMENTS\_X can also be used after a probe to find the number of elements in the probed message. Note that the MPI\_GET\_COUNT, MPI\_GET\_ELEMENTS, and MPI\_GET\_ELEMENTS\_X return the same values when they are used with basic datatypes as long as the limits of their respective count arguments are not exceeded.

Rationale. The extension given to the definition of MPI\_GET\_COUNT seems natural: one would expect this function to return the value of the count argument, when the receive buffer is filled. Sometimes datatype represents a basic unit of data one wants

 to transfer, for example, a record in an array of records (structures). One should be able to find out how many components were received without bothering to divide by the number of elements in each component. However, on other occasions, datatype is used to define a complex layout of data in the receiver memory, and does not represent a basic unit of data for transfers. In such cases, one needs to use the function MPI\_GET\_ELEMENTS or MPI\_GET\_ELEMENTS\_X. (End of rationale.)

Advice to implementors. The definition implies that a receive cannot change the value of storage outside the entries defined to compose the communication buffer. In particular, the definition implies that padding space in a structure should not be modified when such a structure is copied from one process to another. This would prevent the obvious optimization of copying the structure, together with the padding, as one contiguous block. The implementation is free to do this optimization when it does not impact the outcome of the computation. The user can "force" this optimization by explicitly including padding as part of the message. (End of advice to implementors.)

#### 5.1.12 Correct Use of Addresses

Successively declared variables in C or Fortran are not necessarily stored at contiguous locations. Thus, care must be exercised that displacements do not cross from one variable to another. Also, in machines with a segmented address space, addresses are not unique and address arithmetic has some peculiar properties. Thus, the use of **addresses**, that is, displacements relative to the start address MPI\_BOTTOM, has to be restricted.

Variables belong to the same **sequential storage** if they belong to the same array, to the same COMMON block in Fortran, or to the same structure in C. Valid addresses are defined recursively as follows:

- 1. The function MPI\_GET\_ADDRESS returns a valid address, when passed as argument a variable of the calling program.
- 2. The buf argument of a communication function evaluates to a valid address, when passed as argument a variable of the calling program.
- 3. If v is a valid address, and i is an integer, then v+i is a valid address, provided v and v+i are in the same sequential storage.

A correct program uses only valid addresses to identify the locations of entries in communication buffers. Furthermore, if u and v are two valid addresses, then the (integer) difference u-v can be computed only if both u and v are in the same sequential storage. No other arithmetic operations can be meaningfully Aexecuted on addresses.

The rules above impose no constraints on the use of derived datatypes, as long as they are used to define a communication buffer that is wholly contained within the same sequential storage. However, the construction of a communication buffer that contains variables that are not within the same sequential storage must obey certain restrictions. Basically, a communication buffer with variables that are not within the same sequential storage can be used only by specifying in the communication call buf = MPI\_BOTTOM, count = 1, and using a datatype argument where all displacements are valid (absolute) addresses.

Advice to users. It is not expected that MPI implementations will be able to detect erroneous, "out of bound" displacements—unless those overflow the user address

space—since the MPI call may not know the extent of the arrays and records in the host program. (*End of advice to users*.)

Advice to implementors. There is no need to distinguish (absolute) addresses and (relative) displacements on a machine with contiguous address space: MPI\_BOTTOM is zero, and both addresses and displacements are integers. On machines where the distinction is required, addresses are recognized as expressions that involve MPI\_BOTTOM. (End of advice to implementors.)

## 5.1.13 Decoding a Datatype

MPI datatype objects allow users to specify an arbitrary layout of data in memory. There are several cases where accessing the layout information in opaque datatype objects would be useful. The opaque datatype object has found a number of uses outside MPI. Furthermore, a number of tools wish to display internal information about a datatype. To achieve this, datatype decoding functions are provided. The two functions in this section are used together to decode datatypes to recreate the calling sequence used in their initial definition. These can be used to allow a user to determine the type map and type signature of a datatype.

MPI\_TYPE\_GET\_ENVELOPE(datatype, num\_integers, num\_addresses, num\_large\_counts, num\_datatypes, combiner)

IN	datatype	datatype to access (handle)
OUT	num_integers	number of input integers used in call constructing combiner (non-negative integer)
OUT	num_addresses	number of input addresses used in call constructing combiner (non-negative integer)
OUT	num_large_counts	number of input large counts used in call constructing combiner (non-negative integer, only present for large count variants)
OUT	num_datatypes	number of input datatypes used in call constructing combiner (non-negative integer)
OUT	combiner	combiner (state)

## C binding

#### Fortran 2008 binding

2

3

5

6

9

11 12

13

14

15

16

17

18

19

20

21

22

23 24

26

27

28

29

30

31

32

33 34

35

36

37

38

39

40 41

42

43

44

45 46

47

48

```
INTEGER, INTENT(OUT) :: num_integers, num_addresses, num_datatypes,
                   combiner
        INTEGER, OPTIONAL, INTENT(OUT) :: ierror
    MPI_Type_get_envelope(datatype, num_integers, num_addresses,
                  num_large_counts, num_datatypes, combiner, ierror)
        TYPE(MPI_Datatype), INTENT(IN) :: datatype
        INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: num_integers,
                  num_addresses, num_large_counts, num_datatypes
        INTEGER, INTENT(OUT) :: combiner
10
        INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

MPI\_TYPE\_GET\_ENVELOPE(DATATYPE, NUM\_INTEGERS, NUM\_ADDRESSES, NUM\_DATATYPES, COMBINER, IERROR)

INTEGER DATATYPE, NUM\_INTEGERS, NUM\_ADDRESSES, NUM\_DATATYPES, COMBINER, **IERROR** 

For the given datatype, MPI\_TYPE\_GET\_ENVELOPE returns information on the number and type of input arguments used in the call that created the datatype. The number-ofarguments values returned can be used to provide sufficiently large arrays in the decoding routine MPI\_TYPE\_GET\_CONTENTS. This call and the meaning of the returned values is described below. The combiner reflects the MPI datatype constructor call that was used in creating datatype.

Rationale. By requiring that the combiner reflect the constructor used in the creation of the datatype, the decoded information can be used to effectively recreate the calling sequence used in the original creation. This is the most useful information and was felt to be reasonable even though it constrains implementations to remember the original constructor sequence even if the internal representation is different.

The decoded information keeps track of datatype duplications. This is important as one needs to distinguish between a predefined datatype and a dup of a predefined datatype. The former is a constant object that cannot be freed, while the latter is a derived datatype that can be freed. (End of rationale.)

The list in Table 5.1 has the values that can be returned in combiner on the left and the call associated with them on the right.

If combiner is MPI\_COMBINER\_NAMED then datatype is a named predefined datatype.

If the MPI\_TYPE\_GET\_ENVELOPE variant without num\_large\_counts is invoked with a datatype that requires an output value of num\_large\_counts > 0, then an error of class MPI\_ERR\_TYPE is raised.

Rationale. The large count variant of this MPI procedure was added in MPI-4. It contains a new num\_large\_counts parameter. The other variant—the variant that existed before MPI-4—was not changed in order to preserve backwards compatibility. (End of rationale.)


The actual arguments used in the creation call for a datatype can be obtained using MPI\_TYPE\_GET\_CONTENTS.

MPI\_TYPE\_GET\_ENVELOPE and MPI\_TYPE\_GET\_CONTENTS also support large

MPI_COMBINER_NAMED	a named predefined datatype	1
MPI_COMBINER_DUP	MPI_TYPE_DUP	2
MPI_COMBINER_CONTIGUOUS	MPI_TYPE_CONTIGUOUS	3
MPI_COMBINER_VECTOR	MPI_TYPE_VECTOR	4
MPI_COMBINER_HVECTOR	MPI_TYPE_CREATE_HVECTOR	5
MPI_COMBINER_INDEXED	MPI_TYPE_INDEXED	6
MPI_COMBINER_HINDEXED	MPI_TYPE_CREATE_HINDEXED	7
MPI_COMBINER_INDEXED_BLOCK	MPI_TYPE_CREATE_INDEXED_BLOCK	8
MPI_COMBINER_HINDEXED_BLOCK	MPI_TYPE_CREATE_HINDEXED_BLOCK	9
MPI_COMBINER_STRUCT	MPI_TYPE_CREATE_STRUCT	10
MPI_COMBINER_SUBARRAY	MPI_TYPE_CREATE_SUBARRAY	11
MPI_COMBINER_DARRAY	MPI_TYPE_CREATE_DARRAY	12
MPI_COMBINER_F90_REAL	MPI_TYPE_CREATE_F90_REAL	13
MPI_COMBINER_F90_COMPLEX	MPI_TYPE_CREATE_F90_COMPLEX	14
MPI_COMBINER_F90_INTEGER	MPI_TYPE_CREATE_F90_INTEGER	15
MPI_COMBINER_RESIZED	MPI_TYPE_CREATE_RESIZED	16
		17

Table 5.1: combiner values returned from MPI\_TYPE\_GET\_ENVELOPE

count types in separate additional MPI procedures in C (suffixed with the " $\_c$ ") and interface polymorphism in Fortran when using USE mpi $\_f08$ .



```
1
     MPI_TYPE_GET_CONTENTS(datatype, max_integers, max_addresses, max_large_counts,
2
                     max_datatypes, array_of_integers, array_of_addresses,
3
                     array_of_large_counts, array_of_datatypes)
       IN
                 datatype
                                              datatype to access (handle)
5
       IN
                 max_integers
                                              number of elements in array_of_integers
6
                                              (non-negative integer)
       IN
                 max_addresses
                                              number of elements in array_of_addresses
9
                                              (non-negative integer)
10
       IN
                 max_large_counts
                                              number of elements in array_of_large_counts
11
                                              (non-negative integer, only present for large
12
                                              count variants)
13
       IN
                 max_datatypes
                                              number of elements in array_of_datatypes
14
                                              (non-negative integer)
15
16
       OUT
                 array_of_integers
                                              contains integer arguments used in constructing
17
                                              datatype (array of integers)
18
       OUT
                 array_of_addresses
                                              contains address arguments used in constructing
19
                                              datatype (array of integers)
20
       OUT
                 array_of_large_counts
                                              contains large count arguments used in constructing
21
                                              datatype (array of integers, only present for large
22
                                              count variants)
23
24
       OUT
                 array_of_datatypes
                                              contains datatype arguments used in constructing
                                              datatype (array of handles)
26
27
     C binding
28
     int MPI_Type_get_contents(MPI_Datatype datatype, int max_integers,
29
                     int max_addresses, int max_datatypes, int array_of_integers[],
30
                     MPI_Aint array_of_addresses[],
31
                     MPI_Datatype array_of_datatypes[])
32
     int MPI_Type_get_contents_c(MPI_Datatype datatype, MPI_Count max_integers,
33
                     MPI_Count max_addresses, MPI_Count max_large_counts,
34
                     MPI_Count max_datatypes, int array_of_integers[],
35
                     MPI_Aint array_of_addresses[],
36
                     MPI_Count array_of_large_counts[],
37
                     MPI_Datatype array_of_datatypes[])
38
39
     Fortran 2008 binding
     MPI_Type_get_contents(datatype, max_integers, max_addresses, max_datatypes,
41
                     array_of_integers, array_of_addresses, array_of_datatypes,
42
                     ierror)
43
          TYPE(MPI_Datatype), INTENT(IN) :: datatype
44
          INTEGER, INTENT(IN) :: max_integers, max_addresses, max_datatypes
45
          INTEGER, INTENT(OUT) :: array_of_integers(max_integers)
46
          INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) ::
47
                      array_of_addresses(max_addresses)
```

13

14

15

16

18

19

20 21

22

23 24

25

27

28

29

30

33

34 35

36

37

38

42

43

44

45 46

47

```
TYPE(MPI_Datatype), INTENT(OUT) :: array_of_datatypes(max_datatypes)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Type_get_contents(datatype, max_integers, max_addresses,
             max_large_counts, max_datatypes, array_of_integers,
             array_of_addresses, array_of_large_counts, array_of_datatypes,
             ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: max_integers,
              max_addresses, max_large_counts, max_datatypes
    INTEGER, INTENT(OUT) :: array_of_integers(max_integers)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) ::
              array_of_addresses(max_addresses)
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) ::
              array_of_large_counts(max_large_counts)
    TYPE(MPI_Datatype), INTENT(OUT) :: array_of_datatypes(max_datatypes)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

## Fortran binding

MPI\_TYPE\_GET\_CONTENTS(DATATYPE, MAX\_INTEGERS, MAX\_ADDRESSES, MAX\_DATATYPES, ARRAY\_OF\_INTEGERS, ARRAY\_OF\_ADDRESSES, ARRAY\_OF\_DATATYPES, IERROR)

datatype must be a predefined unnamed or a derived datatype; the call is erroneous if datatype is a predefined named datatype.

The values given for max\_integers, max\_addresses, max\_large\_counts, and max\_datatypes must be at least as large as the value returned in num\_integers, num\_addresses, num\_large\_counts, and num\_datatypes, respectively, in the call MPI\_TYPE\_GET\_ENVELOPE for the same datatype argument.

Rationale. The arguments max\_integers, max\_addresses, max\_large\_counts, and max\_datatypes allow for error checking in the call. (End of rationale.)

If the MPI\_TYPE\_GET\_CONTENTS variant without max\_large\_counts is invoked with a datatype that requires > 0 values in array\_of\_large\_counts, then an error of class MPI\_ERR\_TYPE is raised.

Rationale. The large count variant of this MPI procedure was added in MPI-4. It contains new max\_large\_counts and array\_of\_large\_counts parameters. The other variant—the variant that existed before MPI-4—was not changed in order to preserve backwards compatibility. (End of rationale.)

The datatypes returned in array\_of\_datatypes are handles to datatype objects that are equivalent to the datatypes used in the original construction call. If these were derived datatypes, then the returned datatypes are new datatype objects, and the user is responsible for freeing these datatypes with MPI\_TYPE\_FREE. If these were predefined datatypes, then the returned datatype is equal to that (constant) predefined datatype and cannot be freed.

The committed state of returned derived datatypes is undefined, i.e., the datatypes may or may not be committed. Furthermore, the content of attributes of returned datatypes is undefined.

Note that MPI\_TYPE\_GET\_CONTENTS can be invoked with a datatype argument that was constructed using MPI\_TYPE\_CREATE\_F90\_REAL, MPI\_TYPE\_CREATE\_F90\_INTEGER, or MPI\_TYPE\_CREATE\_F90\_COMPLEX (an unnamed predefined datatype). In such a case, an empty array\_of\_datatypes is returned.

Rationale. The definition of datatype equivalence implies that equivalent predefined datatypes are equal. By requiring the same handle for named predefined datatypes, it is possible to use the == or .EQ. comparison operator to determine the datatype involved. (End of rationale.)

Advice to implementors. The datatypes returned in array\_of\_datatypes must appear to the user as if each is an equivalent copy of the datatype used in the type constructor call. Whether this is done by creating a new datatype or via another mechanism such as a reference count mechanism is up to the implementation as long as the semantics are preserved. (End of advice to implementors.)

Rationale. The committed state and attributes of the returned datatype is deliberately left vague. The datatype used in the original construction may have been modified since its use in the constructor call. Attributes can be added, removed, or modified as well as having the datatype committed. The semantics given allow for a reference count implementation without having to track these changes. (End of rationale.)

In the deprecated datatype constructor calls, the address arguments in Fortran are of type INTEGER. In the preferred calls, the address arguments are of type INTEGER(KIND=MPI\_ADDRESS\_KIND). The call MPI\_TYPE\_GET\_CONTENTS returns all addresses in an argument of type INTEGER(KIND=MPI\_ADDRESS\_KIND). This is true even if the deprecated calls were used. Thus, the location of values returned can be thought of as being returned by the C bindings. It can also be determined by examining the preferred calls for datatype constructors for the deprecated calls that involve addresses.

Rationale. By having all address arguments returned in the array\_of\_addresses argument, the result from a C and Fortran decoding of a datatype gives the result in the same argument. It is assumed that an integer of type INTEGER(KIND=MPI\_ADDRESS\_KIND) will be at least as large as the INTEGER argument used in datatype construction with the old MPI-1 calls so no loss of information will occur. (End of rationale.)

The following defines what values are placed in each entry of the returned arrays depending on the datatype constructor used for datatype. It also specifies the size of the arrays needed which is the values returned by MPI\_TYPE\_GET\_ENVELOPE. In Fortran, the following calls were made:

```
PARAMETER (LARGE = 1000)
INTEGER TYPE, NI, NA, ND, COMBINER, I(LARGE), D(LARGE), IERROR
INTEGER (KIND=MPI_ADDRESS_KIND) A(LARGE)
```

! CONSTRUCT DATATYPE TYPE (NOT SHOWN)

11

12

13

14

15

16

18

19

20

21

22

23

24

26

27

28

29 30

33

34

35 36 37

```
CALL MPI_ABORT(MPI_COMM_WORLD, 99, IERROR)
ENDIF
CALL MPI_TYPE_GET_CONTENTS(TYPE, NI, NA, ND, I, A, D, IERROR)
or in C the analogous calls of:
#define LARGE 1000
int ni, na, nd, combiner, i[LARGE];
MPI_Aint a[LARGE];
MPI_Datatype type, d[LARGE];
/* construct datatype type (not shown) */
MPI_Type_get_envelope(type, &ni, &na, &nd, &combiner);
if ((ni > LARGE) || (na > LARGE) || (nd > LARGE)) {
    fprintf(stderr, "ni, na, or nd = %d %d %d returned by ", ni, na, nd);
    fprintf(stderr, "MPI_Type_get_envelope is larger than LARGE = %d\n",
            LARGE);
    MPI_Abort(MPI_COMM_WORLD, 99);
};
MPI_Type_get_contents(type, ni, na, nd, i, a, d);
```

CALL MPI\_TYPE\_GET\_ENVELOPE(TYPE, NI, NA, ND, COMBINER, IERROR)

WRITE (\*, \*) "NI, NA, OR ND = ", NI, NA, ND, &

IF ((NI .GT. LARGE) .OR. (NA .GT. LARGE) .OR. (ND .GT. LARGE)) THEN

" RETURNED BY MPI\_TYPE\_GET\_ENVELOPE IS LARGER THAN LARGE = ", LARGE

MPI\_TYPE\_GET\_CONTENTS.

If combiner is MPI\_COMBINER\_DUP then

Constructor argument	С	Fortran location
oldtype	d[0]	D(1)

In the descriptions that follow, the lower case name of arguments is used.

If combiner is MPI\_COMBINER\_NAMED then it is erroneous to call

and ni = 0, na = 0, nd = 1.

If combiner is MPI\_COMBINER\_CONTIGUOUS then

Constructor argument	С	Fortran location
count	i[0]	I(1)
oldtype	d[0]	D(1)

and ni = 1, na = 0, nd = 1.

If combiner is MPI\_COMBINER\_VECTOR then

Constructor argument	$\mathbf{C}$	Fortran location
count	i[0]	<u>I(1)</u>
blocklength	i[1]	I(2)
stride	i[2]	I(3)
oldtype	d[0]	D(1)

and ni = 3, na = 0, nd = 1. If combiner is MPI\_COMBINER\_HVECTOR then

2 3

1

9

10 11

12 13

14 1516

17

18 19

20 21

22 23 24

26

27 28

29 30

31 32

33 34

35 36

38 39

37

41 42 43

44 45

46 47

С Constructor argument Fortran location i[0]count I(1)blocklength i[1] I(2)a[0]A(1)stride d[0]D(1)oldtype

and ni = 2, na = 1, nd = 1.

If combiner is  $\mathsf{MPI\_COMBINER\_INDEXED}$  then

Constructor argument	$\mathbf{C}$	Fortran location
count	i[0]	I(1)
$array\_of\_blocklengths$	i[1] to $i[i[0]]$	I(2)  to  I(I(1)+1)
array_of_displacements	i[i[0]+1] to $i[2*i[0]]$	I(I(1)+2) to $I(2*I(1)+1)$
oldtype	d[0]	D(1)

and ni = 2\*count+1, na = 0, nd = 1.

If combiner is MPI\_COMBINER\_HINDEXED then

Constructor argument	C	Fortran location
count	i[0]	I(1)
$array\_of\_blocklengths$	i[1] to i[i[0]]	I(2)  to  I(I(1)+1)
array_of_displacements	a[0]  to  a[i[0]-1]	A(1) to $A(I(1))$
oldtype	d[0]	D(1)

and ni = count+1, na = count, nd = 1.

If combiner is MPI\_COMBINER\_INDEXED\_BLOCK then

Constructor argument	C	Fortran location
count	i[0]	I(1)
blocklength	i[1]	I(2)
array_of_displacements	i[2]  to  i[i[0]+1]	I(3)  to  I(I(1)+2)
oldtype	d[0]	D(1)

and ni = count + 2, na = 0, nd = 1.

If combiner is MPI\_COMBINER\_HINDEXED\_BLOCK then

Constructor argument	С	Fortran location
count	i[0]	I(1)
blocklength	i[1]	I(2)
array_of_displacements	a[0]  to  a[i[0]-1]	A(1) to $A(I(1))$
oldtype	d[0]	D(1)

and ni = 2, na = count, nd = 1.

If combiner is MPI\_COMBINER\_STRUCT then

Constructor argument	С	Fortran location
count	i[0]	I(1)
$array\_of\_blocklengths$	i[1] to $i[i[0]]$	I(2)  to  I(I(1)+1)
array_of_displacements	a[0]  to  a[i[0]-1]	A(1) to $A(I(1))$
array_of_types	d[0]  to  d[i[0]-1]	D(1) to $D(I(1))$

and ni = count+1, na = count, nd = count.

If combiner is MPI\_COMBINER\_SUBARRAY then

Constructor argument	С	Fortran location
ndims	i[0]	I(1)
$array\_of\_sizes$	i[1] to $i[i[0]]$	I(2)  to  I(I(1)+1)
$array\_of\_subsizes$	i[i[0]+1]  to  i[2*i[0]]	I(I(1)+2) to $I(2*I(1)+1)$
array_of_starts	i[2*i[0]+1] to $i[3*i[0]]$	I(2*I(1)+2) to $I(3*I(1)+1)$
order	i[3*i[0]+1]	I(3*I(1)+2]
oldtype	d[0]	D(1)

and ni = 3\*ndims+2, na = 0, nd = 1.

If combiner is MPI\_COMBINER\_DARRAY then

Constructor argument	С	Fortran location
size	i[0]	I(1)
$\operatorname{rank}$	i[1]	I(2)
ndims	i[2]	I(3)
array_of_gsizes	i[3] to i[i[2]+2]	I(4)  to  I(I(3)+3)
array_of_distribs	i[i[2]+3] to $i[2*i[2]+2]$	I(I(3)+4) to $I(2*I(3)+3)$
array_of_dargs	i[2*i[2]+3] to $i[3*i[2]+2]$	I(2*I(3)+4) to $I(3*I(3)+3)$
array_of_psizes	i[3*i[2]+3] to $i[4*i[2]+2]$	I(3*I(3)+4) to $I(4*I(3)+3)$
order	i[4*i[2]+3]	I(4*I(3)+4)
oldtype	d[0]	D(1)

and ni = 4\*ndims+4, na = 0, nd = 1.

If combiner is MPI\_COMBINER\_F90\_REAL then

Constructor argumen	nt C	Fortran location
р	i[0]	I(1)
r	i[1]	I(2)

and ni = 2, na = 0, nd = 0.

If combiner is MPI\_COMBINER\_F90\_COMPLEX then

Constructor argument	$\mathbf{C}$	Fortran location
p	i[0]	I(1)
r	i[1]	I(2)

and ni = 2, na = 0, nd = 0.

If combiner is MPI\_COMBINER\_F90\_INTEGER then

Constructor argument	С	Fortran location
r	i[0]	I(1)

```
and ni = 1, na = 0, nd = 0.

If combiner is MPI_COMBINER_RESIZED then
```

```
\begin{array}{c|cccc} \hline Constructor\ argument & C & Fortran\ location \\ \hline lb & a[0] & A(1) \\ extent & a[1] & A(2) \\ oldtype & d[0] & D(1) \\ \hline \end{array}
```

```
and ni = 0, na = 2, nd = 1.
```

# 5.1.14 Examples

The following examples illustrate the use of derived datatypes.

**Example 5.13** Send and receive a section of a 3D array.

```
15
16
     REAL a(100,100,100), e(9,9,9)
17
     INTEGER oneslice, twoslice, threeslice, myrank, ierr
18
     INTEGER (KIND=MPI_ADDRESS_KIND) lb, sizeofreal
19
     INTEGER status(MPI_STATUS_SIZE)
20
21
     ! extract the section a(1:17:2, 3:11, 2:10)
22
     ! and store it in e(:,:,:).
23
^{24}
     CALL MPI_COMM_RANK(MPI_COMM_WORLD, myrank, ierr)
25
26
     CALL MPI_TYPE_GET_EXTENT(MPI_REAL, lb, sizeofreal, ierr)
27
28
     ! create datatype for a 1D section
29
     CALL MPI_TYPE_VECTOR(9, 1, 2, MPI_REAL, oneslice, ierr)
30
31
     ! create datatype for a 2D section
32
     CALL MPI_TYPE_CREATE_HVECTOR(9, 1, 100*sizeofreal, oneslice, &
33
                                          twoslice, ierr)
34
35
     ! create datatype for the entire section
36
     CALL MPI_TYPE_CREATE_HVECTOR(9, 1, 100*100*sizeofreal, twoslice, &
37
                                   threeslice, ierr)
38
39
     CALL MPI_TYPE_COMMIT(threeslice, ierr)
40
     CALL MPI_SENDRECV(a(1,3,2), 1, threeslice, myrank, 0, e, 9*9*9, &
41
                        MPI_REAL, myrank, 0, MPI_COMM_WORLD, status, ierr)
```

**Example 5.14** Copy the (strictly) lower triangular part of a matrix.

```
REAL a(100,100), b(100,100)
INTEGER disp(100), blocklen(100), ltype, myrank, ierr
INTEGER status(MPI_STATUS_SIZE)
! copy lower triangular part of array a
! onto lower triangular part of array b
CALL MPI_COMM_RANK(MPI_COMM_WORLD, myrank, ierr)
! compute start and size of each column
DO i=1,100
   disp(i) = 100*(i-1) + i
                                                                                  12
   blocklen(i) = 100-i
                                                                                  13
END DO
                                                                                  14
                                                                                  15
! create datatype for lower triangular part
                                                                                  16
CALL MPI_TYPE_INDEXED(100, blocklen, disp, MPI_REAL, ltype, ierr)
                                                                                  18
                                                                                  19
CALL MPI_TYPE_COMMIT(ltype, ierr)
CALL MPI_SENDRECV(a, 1, ltype, myrank, 0, b, 1, &
                                                                                  20
                                                                                  21
                   ltype, myrank, 0, MPI_COMM_WORLD, status, ierr)
                                                                                  22
                                                                                  23
Example 5.15 Transpose a matrix.
                                                                                  24
REAL a(100,100), b(100,100)
INTEGER row, xpose, myrank, ierr
                                                                                  26
INTEGER (KIND=MPI_ADDRESS_KIND) lb, sizeofreal
                                                                                  27
INTEGER status(MPI_STATUS_SIZE)
                                                                                  28
                                                                                  29
! transpose matrix a onto b
                                                                                  30
CALL MPI_COMM_RANK(MPI_COMM_WORLD, myrank, ierr)
CALL MPI_TYPE_GET_EXTENT(MPI_REAL, lb, sizeofreal, ierr)
                                                                                  34
                                                                                  35
! create datatype for one row
                                                                                  36
CALL MPI_TYPE_VECTOR(100, 1, 100, MPI_REAL, row, ierr)
                                                                                  37
! create datatype for matrix in row-major order
CALL MPI_TYPE_CREATE_HVECTOR(100, 1, sizeofreal, row, xpose, ierr)
CALL MPI_TYPE_COMMIT(xpose, ierr)
                                                                                  42
                                                                                  43
! send matrix in row-major order and receive in column major order
                                                                                  44
CALL MPI_SENDRECV(a, 1, xpose, myrank, 0, b, 100*100, &
                                                                                  45
                   MPI_REAL, myrank, 0, MPI_COMM_WORLD, status, ierr)
                                                                                  46
```

**Example 5.16** Another approach to the transpose problem:

```
1
     REAL a(100,100), b(100,100)
2
     INTEGER row, row1
3
     INTEGER (KIND=MPI_ADDRESS_KIND) disp(2), lb, sizeofreal
4
     INTEGER myrank, ierr
5
     INTEGER status(MPI_STATUS_SIZE)
6
7
     CALL MPI_COMM_RANK(MPI_COMM_WORLD, myrank, ierr)
8
9
     ! transpose matrix a onto b
10
11
     CALL MPI_TYPE_GET_EXTENT(MPI_REAL, lb, sizeofreal, ierr)
12
13
     ! create datatype for one row
14
     CALL MPI_TYPE_VECTOR(100, 1, 100, MPI_REAL, row, ierr)
15
16
     ! create datatype for one row, with the extent of one real number
17
     1b = 0
18
     CALL MPI_TYPE_CREATE_RESIZED(row, lb, sizeofreal, row1, ierr)
19
20
     CALL MPI_TYPE_COMMIT(row1, ierr)
21
22
     ! send 100 rows and receive in column major order
23
     CALL MPI_SENDRECV(a, 100, row1, myrank, 0, b, 100*100, &
^{24}
                        MPI_REAL, myrank, 0, MPI_COMM_WORLD, status, ierr)
25
26
     Example 5.17 Use of MPI datatypes to manipulate an array of structures.
27
28
     struct Partstruct
29
30
                type; /* particle type */
        int
31
        double d[6];
                      /* particle coordinates */
        char b[7]; /* some additional information */
33
     };
34
35
     struct Partstruct
                           particle[1000];
36
37
     int
                   i, dest, tag;
38
     MPI_Comm
                   comm;
39
40
41
     /* build datatype describing structure */
42
43
     MPI_Datatype Particlestruct, Particletype;
44
     MPI_Datatype type[3] = {MPI_INT, MPI_DOUBLE, MPI_CHAR};
45
     int
                  blocklen[3] = \{1, 6, 7\};
^{46}
     MPI_Aint
                  disp[3];
47
     MPI_Aint
                  base, lb, sizeofentry;
```

```
/* compute displacements of structure components */
MPI_Get_address(particle, disp);
MPI_Get_address(particle[0].d, disp+1);
MPI_Get_address(particle[0].b, disp+2);
base = disp[0];
for (i=0; i < 3; i++) disp[i] = MPI_Aint_diff(disp[i], base);</pre>
MPI_Type_create_struct(3, blocklen, disp, type, &Particlestruct);
/* Since the compiler may pad the structure, it is best to explicitly
                                                                                    12
   set the extent of the MPI datatype for a structure element using
                                                                                    13
   MPI_Type_create_resized */
                                                                                    14
                                                                                    15
                                                                                    16
/* compute extent of the structure */
MPI_Get_address(particle+1, &sizeofentry);
                                                                                    18
sizeofentry = MPI_Aint_diff(sizeofentry, base);
                                                                                    19
/* build datatype describing structure */
                                                                                    20
                                                                                   21
MPI_Type_create_resized(Particlestruct, 0, sizeofentry, &Particletype);
                                                                                    22
                                                                                   23
                                                                                    24
/* 4.1: send the entire array */
                                                                                    26
MPI_Type_commit(&Particletype);
MPI_Send(particle, 1000, Particletype, dest, tag, comm);
                                                                                    27
                                                                                    28
                                                                                    29
                                                                                    30
/* 4.2: send only the entries of type zero particles,
        preceded by the number of such entries */
                                                                                    33
MPI_Datatype Zparticles;
                            /* datatype describing all particles
                                                                                   34
                               with type zero (needs to be recomputed
                               if types change) */
                                                                                   35
MPI_Datatype Ztype;
                                                                                    36
                                                                                   37
              zdisp[1000];
                                                                                    38
int
                                                                                    39
             zblock[1000], j, k;
int
             zzblock[2] = \{1,1\};
int
MPI\_Aint
             zzdisp[2];
                                                                                    42
MPI_Datatype zztype[2];
                                                                                    43
                                                                                    44
/* compute displacements of type zero particles */
                                                                                    45
j = 0;
for (i=0; i < 1000; i++)
                                                                                    46
   if (particle[i].type == 0)
      {
```

```
1
             zdisp[j] = i;
2
             zblock[j] = 1;
             j++;
           }
5
6
     /* create datatype for type zero particles */
7
     MPI_Type_indexed(j, zblock, zdisp, Particletype, &Zparticles);
8
9
     /* prepend particle count */
10
     MPI_Get_address(&j, zzdisp);
11
     MPI_Get_address(particle, zzdisp+1);
12
     zztype[0] = MPI_INT;
13
     zztype[1] = Zparticles;
14
     MPI_Type_create_struct(2, zzblock, zzdisp, zztype, &Ztype);
15
16
     MPI_Type_commit(&Ztype);
17
     MPI_Send(MPI_BOTTOM, 1, Ztype, dest, tag, comm);
18
19
20
     /* A probably more efficient way of defining Zparticles */
21
22
     /* consecutive particles with index zero are handled as one block */
23
     j=0;
^{24}
     for (i=0; i < 1000; i++)
        if (particle[i].type == 0)
26
27
              for (k=i+1; (k < 1000) && (particle[k].type == 0); k++);
28
              zdisp[j] = i;
              zblock[j] = k-i;
30
              j++;
31
              i = k;
32
     MPI_Type_indexed(j, zblock, zdisp, Particletype, &Zparticles);
33
34
35
36
     /* 4.3: send the first two coordinates of all entries */
37
38
     MPI_Datatype Allpairs;
                                  /* datatype for all pairs of coordinates */
39
40
     MPI_Type_get_extent(Particletype, &lb, &sizeofentry);
41
42
     /* sizeofentry can also be computed by subtracting the address
43
        of particle[0] from the address of particle[1] */
44
45
     MPI_Type_create_hvector(1000, 2, sizeofentry, MPI_DOUBLE, &Allpairs);
^{46}
     MPI_Type_commit(&Allpairs);
47
     MPI_Send(particle[0].d, 1, Allpairs, dest, tag, comm);
```

```
/* an alternative solution to 4.3 */
MPI_Datatype Twodouble;
MPI_Type_contiguous(2, MPI_DOUBLE, &Twodouble);
MPI_Datatype Onepair;
                         /* datatype for one pair of coordinates, with
                            the extent of one particle entry */
MPI_Type_create_resized(Twodouble, 0, sizeofentry, &Onepair );
MPI_Type_commit(&Onepair);
MPI_Send(particle[0].d, 1000, Onepair, dest, tag, comm);
                                                                                    12
                                                                                    13
                                                                                    14
                                                                                    15
Example 5.18 The same manipulations as in the previous example, but use absolute
                                                                                    16
addresses in datatypes.
                                                                                    18
struct Partstruct
                                                                                    19
                                                                                    20
    int
            type;
                                                                                    21
    double d[6];
                                                                                    22
    char
           b[7];
                                                                                    23
};
                                                                                    24
                                                                                    25
struct Partstruct particle[1000];
                                                                                    26
                                                                                    27
/* build datatype describing first array entry */
                                                                                    28
                                                                                    29
MPI_Datatype Particletype;
                                                                                    30
MPI_Datatype type[3] = {MPI_INT, MPI_DOUBLE, MPI_CHAR};
                                                                                    31
              block[3] = \{1, 6, 7\};
int
MPI_Aint
              disp[3];
                                                                                    33
                                                                                    34
MPI_Get_address(particle, disp);
                                                                                    35
MPI_Get_address(particle[0].d, disp+1);
                                                                                    36
MPI_Get_address(particle[0].b, disp+2);
                                                                                    37
MPI_Type_create_struct(3, block, disp, type, &Particletype);
                                                                                    38
                                                                                    39
/* Particletype describes first array entry -- using absolute
   addresses */
                                                                                    41
                                                                                    42
/* 5.1: send the entire array */
                                                                                    43
                                                                                    44
MPI_Type_commit(&Particletype);
                                                                                    45
MPI_Send(MPI_BOTTOM, 1000, Particletype, dest, tag, comm);
                                                                                    46
                                                                                    47
```

```
1
     /* 5.2: send the entries of type zero,
2
             preceded by the number of such entries */
3
4
     MPI_Datatype Zparticles, Ztype;
5
6
                   zdisp[1000];
     int
7
     int
                   zblock[1000], i, j, k;
8
                   zzblock[2] = \{1,1\};
     int
9
     MPI_Datatype zztype[2];
10
     MPI_Aint
                   zzdisp[2];
11
12
     j=0;
13
     for (i=0; i < 1000; i++)
14
         if (particle[i].type == 0)
15
16
                  for (k=i+1; (k < 1000)\&\&(particle[k].type == 0); k++);
                  zdisp[j] = i;
                  zblock[j] = k-i;
19
                  j++;
20
                  i = k;
21
             }
22
     MPI_Type_indexed(j, zblock, zdisp, Particletype, &Zparticles);
23
     /* Zparticles describe particles with type zero, using
^{24}
        their absolute addresses*/
25
26
     /* prepend particle count */
27
     MPI_Get_address(&j, zzdisp);
28
     zzdisp[1] = (MPI_Aint)0;
29
     zztype[0] = MPI_INT;
30
     zztype[1] = Zparticles;
31
     MPI_Type_create_struct(2, zzblock, zzdisp, zztype, &Ztype);
32
33
     MPI_Type_commit(&Ztype);
34
     MPI_Send(MPI_BOTTOM, 1, Ztype, dest, tag, comm);
35
36
37
     Example 5.19 This example shows how datatypes can be used to handle unions.
38
39
     union {
40
        int
                 ival;
        float
                 fval;
           } u[1000];
43
44
     int
             i, utype;
45
46
     /* All entries of u have identical type; variable
47
        utype keeps track of their current type */
```

```
MPI_Datatype
                mpi_utype[2];
                ubase, extent;
MPI_Aint
/* compute an MPI datatype for each possible union type;
   assume values are left-aligned in union storage. */
MPI_Get_address(u, &ubase);
MPI_Get_address(u+1, &extent);
extent = MPI_Aint_diff(extent, ubase);
MPI_Type_create_resized(MPI_INT, 0, extent, &mpi_utype[0]);
                                                                                     12
                                                                                     13
                                                                                     14
MPI_Type_create_resized(MPI_FLOAT, 0, extent, &mpi_utype[1]);
                                                                                     15
                                                                                     16
for(i=0; i<2; i++) MPI_Type_commit(&mpi_utype[i]);</pre>
                                                                                     18
/* actual communication */
                                                                                     19
MPI_Send(u, 1000, mpi_utype[utype], dest, tag, comm);
                                                                                     20
                                                                                    21
Example 5.20 This example shows how a datatype can be decoded. The routine
                                                                                    22
printdatatype prints out the elements of the datatype. Note the use of MPI_Type_free for
                                                                                    23
datatypes that are not predefined.
                                                                                     24
                                                                                     25
                                                                                     26
  Example of decoding a datatype.
                                                                                     27
  Returns 0 if the datatype is predefined, 1 otherwise
                                                                                    28
                                                                                    29
 */
                                                                                     30
#include <stdio.h>
#include <stdlib.h>
#include "mpi.h"
int printdatatype(MPI_Datatype datatype)
                                                                                    34
    int *array_of_ints;
                                                                                    35
                                                                                    36
    MPI_Aint *array_of_adds;
                                                                                    37
    MPI_Datatype *array_of_dtypes;
    int num_ints, num_adds, num_dtypes, combiner;
    int i;
    MPI_Type_get_envelope(datatype,
                                                                                    42
                            &num_ints, &num_adds, &num_dtypes, &combiner);
    switch (combiner) {
                                                                                    43
                                                                                     44
    case MPI_COMBINER_NAMED:
                                                                                     45
        printf("Datatype is named:");
                                                                                     46
        /* To print the specific type, we can match against the
            predefined forms. We can NOT use a switch statement here
            We could also use MPI_TYPE_GET_NAME if we preferred to use
```

```
1
                names that the user may have changed.
2
              */
                                                 printf("MPI_INT\n");
             if
                      (datatype == MPI_INT)
             else if (datatype == MPI_DOUBLE) printf("MPI_DOUBLE\n");
              ... else test for other types ...
             return 0;
             break;
         case MPI_COMBINER_STRUCT:
         case MPI_COMBINER_STRUCT_INTEGER:
             printf("Datatype is struct containing");
11
                              = (int *)malloc(num_ints * sizeof(int));
             array_of_ints
12
             array_of_adds
13
                         (MPI_Aint *) malloc(num_adds * sizeof(MPI_Aint));
14
             array_of_dtypes = (MPI_Datatype *)
15
                 malloc(num_dtypes * sizeof(MPI_Datatype));
16
             MPI_Type_get_contents(datatype, num_ints, num_adds, num_dtypes,
                                  array_of_ints, array_of_adds, array_of_dtypes);
18
             printf(" %d datatypes:\n", array_of_ints[0]);
19
             for (i=0; i<array_of_ints[0]; i++) {</pre>
20
                 printf("blocklength %d, displacement %ld, type:\n",
21
                          array_of_ints[i+1], (long)array_of_adds[i]);
22
                  if (printdatatype(array_of_dtypes[i])) {
23
                      /* Note that we free the type ONLY if it
24
                         is not predefined */
                      MPI_Type_free(&array_of_dtypes[i]);
26
                  }
27
28
             free(array_of_ints);
29
             free(array_of_adds);
30
             free(array_of_dtypes);
31
             break;
32
                 other combiner values ...
33
         default:
34
             printf("Unrecognized combiner type\n");
35
36
         return 1;
37
     }
38
```

# 5.2 Pack and Unpack

39

40 41

42

43

44

45

46

47

Some existing communication libraries provide pack/unpack functions for sending noncontiguous data. In these, the user explicitly packs data into a contiguous buffer before sending it, and unpacks it from a contiguous buffer after receiving it. Derived datatypes, which are described in Section 5.1, allow one, in most cases, to avoid explicit packing and unpacking. The user specifies the layout of the data to be sent or received, and the communication library directly accesses a noncontiguous buffer. The pack/unpack routines are provided for compatibility with previous libraries. Also, they provide some functionality that is not

otherwise available in MPI. For instance, a message can be received in several parts, where the receive operation done on a later part may depend on the content of a former part. Another use is that outgoing messages may be explicitly buffered in user supplied space, thus overriding the system buffering policy. Finally, the availability of pack and unpack operations facilitates the development of additional communication libraries layered on top of MPI.

# MPI\_PACK(inbuf, incount, datatype, outbuf, outsize, position, comm)

IN	inbuf	input buffer start (choice)
IN	incount	number of input data items (non-negative integer)
IN	datatype	datatype of each input data item (handle)
OUT	outbuf	output buffer start (choice)
IN	outsize	output buffer size, in bytes (non-negative integer)
INOUT	position	current position in buffer, in bytes (integer)
IN	comm	communicator for packed message (handle)

#### C binding

## Fortran 2008 binding

```
MPI_Pack(inbuf, incount, datatype, outbuf, outsize, position, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
    INTEGER, INTENT(IN) :: incount, outsize
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(*), DIMENSION(..) :: outbuf
    INTEGER, INTENT(INOUT) :: position
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
MPI_Pack(inbuf, incount, datatype, outbuf, outsize, position, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: incount, outsize
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(*), DIMENSION(..) :: outbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(INOUT) :: position
    TYPE(MPI_Comm), INTENT(IN) :: comm
```

## Fortran binding

INTEGER, OPTIONAL, INTENT(OUT) :: ierror

INTEGER INCOUNT, DATATYPE, OUTSIZE, POSITION, COMM, IERROR

Packs the message in the send buffer specified by inbuf, incount, datatype into the buffer space specified by outbuf and outsize. The input buffer can be any communication buffer allowed in MPI\_SEND. The output buffer is a contiguous storage area containing outsize bytes, starting at the address outbuf (length is counted in *bytes*, not elements, as if it were a communication buffer for a message of type MPI\_PACKED).

The input value of position is the first location in the output buffer to be used for packing. position is incremented by the size of the packed message, and the output value of position is the first location in the output buffer following the locations occupied by the packed message. The comm argument is the communicator that will be subsequently used for sending the packed message.

# MPI\_UNPACK(inbuf, insize, position, outbuf, outcount, datatype, comm)

IN	inbuf	input buffer start (choice)
IN	insize	size of input buffer, in bytes (non-negative integer)
INOUT	position	current position in bytes (integer)
OUT	outbuf	output buffer start (choice)
IN	outcount	number of items to be unpacked (integer)
IN	datatype	datatype of each output data item (handle)
IN	comm	communicator for packed message (handle)

## C binding

## Fortran 2008 binding

INTEGER(KIND=MPI\_COUNT\_KIND), INTENT(INOUT) :: position

```
TYPE(*), DIMENSION(..) :: outbuf
TYPE(MPI_Datatype), INTENT(IN) :: datatype
TYPE(MPI_Comm), INTENT(IN) :: comm
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

INTEGER INSIZE, POSITION, OUTCOUNT, DATATYPE, COMM, IERROR

Unpacks a message into the receive buffer specified by outbuf, outcount, datatype from the buffer space specified by inbuf and insize. The output buffer can be any communication buffer allowed in MPI\_RECV. The input buffer is a contiguous storage area containing insize bytes, starting at address inbuf. The input value of position is the first location in the input buffer occupied by the packed message. position is incremented by the size of the packed message, so that the output value of position is the first location in the input buffer after the locations occupied by the message that was unpacked. comm is the communicator used to receive the packed message.

Advice to users. Note the difference between MPI\_RECV and MPI\_UNPACK: in MPI\_RECV, the count argument specifies the maximum number of items that can be received. The actual number of items received is determined by the length of the incoming message. In MPI\_UNPACK, the count argument specifies the actual number of items that are unpacked; the "size" of the corresponding message is the increment in position. The reason for this change is that the "incoming message size" is not predetermined since the user decides how much to unpack; nor is it easy to determine the "message size" from the number of items to be unpacked. In fact, in a heterogeneous system, this number may not be determined a priori. (End of advice to users.)

To understand the behavior of pack and unpack, it is convenient to think of the data part of a message as being the sequence obtained by concatenating the successive values sent in that message. The pack operation stores this sequence in the buffer space, as if sending the message to that buffer. The unpack operation retrieves this sequence from buffer space, as if receiving a message from that buffer. (It is helpful to think of internal Fortran files or sscanf in C, for a similar function.)

Several messages can be successively packed into one **packing unit**. This is effected by several successive **related** calls to MPI\_PACK, where the first call provides **position** = 0, and each successive call inputs the value of **position** that was output by the previous call, and the same values for **outbuf**, **outcount** and **comm**. This packing unit now contains the equivalent information that would have been stored in a message by one send call with a send buffer that is the "concatenation" of the individual send buffers.

A packing unit can be sent using type MPI\_PACKED. Any point to point or collective communication function can be used to move the sequence of bytes that forms the packing unit from one process to another. This packing unit can now be received using any receive operation, with any datatype: the type matching rules are relaxed for messages sent with type MPI\_PACKED.

A message sent with any type (including MPI\_PACKED) can be received using the type MPI\_PACKED. Such a message can then be unpacked by calls to MPI\_UNPACK.

A packing unit (or a message created by a regular, "typed" send) can be unpacked into several successive messages. This is effected by several successive related calls to MPI\_UNPACK, where the first call provides position = 0, and each successive call inputs the value of position that was output by the previous call, and the same values for inbuf, insize and comm.

The concatenation of two packing units is not necessarily a packing unit; nor is a substring of a packing unit necessarily a packing unit. Thus, one cannot concatenate two packing units and then unpack the result as one packing unit; nor can one unpack a substring of a packing unit as a separate packing unit. Each packing unit, that was created by a related sequence of pack calls, or by a regular send, must be unpacked as a unit, by a sequence of related unpack calls.

13 14 15

16

17

1

2

3

4

5

6

7

8

9

10

11

12

The restriction on "atomic" packing and unpacking of packing units Rationale. allows the implementation to add at the head of packing units additional information, such as a description of the sender architecture (to be used for type conversion, in a heterogeneous environment) (End of rationale.)

18 19 20

The following call allows the user to find out how much space is needed to pack a message and, thus, manage space allocation for buffers.

22 23 24

25 26

27

28

29

21

# MPI\_PACK\_SIZE(incount, datatype, comm, size)

```
count argument to packing call (non-negative integer)
IN
           incount
IN
                                          datatype argument to packing call (handle)
          datatype
IN
          comm
                                          communicator argument to packing call (handle)
OUT
                                          upper bound on size of packed message, in bytes
          size
                                          (non-negative integer)
```

30 31 32

33

34

35

36

37 38

48

#### C binding

```
int MPI_Pack_size(int incount, MPI_Datatype datatype, MPI_Comm comm,
             int *size)
int MPI_Pack_size_c(MPI_Count incount, MPI_Datatype datatype,
```

## Fortran 2008 binding

```
39
     MPI_Pack_size(incount, datatype, comm, size, ierror)
40
         INTEGER, INTENT(IN) :: incount
41
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
42
         TYPE(MPI_Comm), INTENT(IN) :: comm
43
         INTEGER, INTENT(OUT) :: size
44
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
     MPI_Pack_size(incount, datatype, comm, size, ierror)
46
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: incount
47
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
```

MPI\_Comm comm, MPI\_Count \*size)

11

12

13

14

15 16 17

18

```
TYPE(MPI_Comm), INTENT(IN) :: comm
INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: size
INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI_PACK_SIZE(INCOUNT, DATATYPE, COMM, SIZE, IERROR)
INTEGER INCOUNT, DATATYPE, COMM, SIZE, IERROR
```

A call to MPI\_PACK\_SIZE(incount, datatype, comm, size) returns in size an upper bound on the increment in position that is effected by a call to MPI\_PACK(inbuf, incount, datatype, outbuf, outcount, position, comm). If the packed size of the datatype cannot be expressed by the size parameter, then MPI\_PACK\_SIZE sets the value of size to MPI\_UNDEFINED.

Rationale. The call returns an upper bound, rather than an exact bound, since the exact amount of space needed to pack the message may depend on the context (e.g., first message packed in a packing unit may take more space). (End of rationale.)

```
Example 5.21 An example using MPI_PACK.
```

```
19
int
            position, i, j, a[2];
            buff[1000];
                                                                                     20
char
                                                                                     21
                                                                                     22
MPI_Comm_rank(MPI_COMM_WORLD, &myrank);
                                                                                     23
if (myrank == 0)
                                                                                     24
{
                                                                                     25
    /* SENDER CODE */
                                                                                     26
                                                                                     27
    position = 0;
    MPI_Pack(&i, 1, MPI_INT, buff, 1000, &position, MPI_COMM_WORLD);
                                                                                     28
                                                                                     29
    MPI_Pack(&j, 1, MPI_INT, buff, 1000, &position, MPI_COMM_WORLD);
    MPI_Send(buff, position, MPI_PACKED, 1, 0, MPI_COMM_WORLD);
                                                                                     30
else /* RECEIVER CODE */
    MPI_Recv(a, 2, MPI_INT, 0, 0, MPI_COMM_WORLD, MPI_STATUS_IGNORE);
                                                                                     33
                                                                                     34
                                                                                     35
Example 5.22 An elaborate example.
                                                                                     36
                                                                                     37
      position, i;
                                                                                     38
float a[1000];
                                                                                     39
      buff[1000];
char
MPI_Comm_rank(MPI_COMM_WORLD, &myrank);
                                                                                     42
if (myrank == 0)
{
                                                                                     43
                                                                                     44
    /* SENDER CODE */
                                                                                     45
                                                                                     46
    int len[2];
    MPI_Aint disp[2];
    MPI_Datatype type[2], newtype;
```

48

```
1
2
         /* build datatype for i followed by a[0]...a[i-1] */
         len[0] = 1;
         len[1] = i;
6
         MPI_Get_address(&i, disp);
         MPI_Get_address(a, disp+1);
         type[0] = MPI_INT;
         type[1] = MPI_FLOAT;
10
         MPI_Type_create_struct(2, len, disp, type, &newtype);
11
         MPI_Type_commit(&newtype);
12
         /* Pack i followed by a[0]...a[i-1]*/
13
14
15
         position = 0;
16
         MPI_Pack(MPI_BOTTOM, 1, newtype, buff, 1000, &position, MPI_COMM_WORLD);
18
         /* Send */
19
20
         MPI_Send(buff, position, MPI_PACKED, 1, 0,
21
                   MPI_COMM_WORLD);
22
23
     /* ****
24
        One can replace the last three lines with
        MPI_Send(MPI_BOTTOM, 1, newtype, 1, 0, MPI_COMM_WORLD);
26
        **** */
27
28
     else if (myrank == 1)
29
30
         /* RECEIVER CODE */
31
         MPI_Status status;
33
34
         /* Receive */
35
36
         MPI_Recv(buff, 1000, MPI_PACKED, 0, 0, MPI_COMM_WORLD, &status);
37
         /* Unpack i */
         position = 0;
41
         MPI_Unpack(buff, 1000, &position, &i, 1, MPI_INT, MPI_COMM_WORLD);
42
         /* Unpack a[0]...a[i-1] */
43
44
         MPI_Unpack(buff, 1000, &position, a, i, MPI_FLOAT, MPI_COMM_WORLD);
45
     }
46
```

**Example 5.23** Each process sends a count, followed by count characters to the root; the

```
root concatenates all characters into one string.
int count, gsize, counts[64], totalcount, k1, k2, k,
     displs[64], position, concat_pos;
char chr[100], *lbuf, *rbuf, *cbuf;
MPI_Comm_size(comm, &gsize);
MPI_Comm_rank(comm, &myrank);
      /* allocate local pack buffer */
MPI_Pack_size(1, MPI_INT, comm, &k1);
                                                                                    11
MPI_Pack_size(count, MPI_CHAR, comm, &k2);
                                                                                    12
k = k1+k2;
                                                                                    13
lbuf = (char *)malloc(k);
                                                                                    14
                                                                                    15
      /* pack count, followed by count characters
                                                                                    16
position = 0;
                                                                                    17
MPI_Pack(&count, 1, MPI_INT, lbuf, k, &position, comm);
                                                                                    18
MPI_Pack(chr, count, MPI_CHAR, lbuf, k, &position, comm);
                                                                                    19
                                                                                    20
if (myrank != root) {
                                                                                   21
    /* gather at root sizes of all packed messages */
                                                                                   22
    MPI_Gather(&position, 1, MPI_INT, NULL, 0,
                                                                                   23
               MPI_DATATYPE_NULL, root, comm);
                                                                                    24
                                                                                   25
    /* gather at root packed messages */
                                                                                    26
    MPI_Gatherv(lbuf, position, MPI_PACKED, NULL,
                                                                                   27
                 NULL, NULL, MPI_DATATYPE_NULL, root, comm);
                                                                                   28
                                                                                   29
} else {
           /* root code */
                                                                                   30
    /* gather sizes of all packed messages */
                                                                                    31
    MPI_Gather(&position, 1, MPI_INT, counts, 1,
               MPI_INT, root, comm);
                                                                                   34
    /* gather all packed messages */
                                                                                   35
    displs[0] = 0;
                                                                                   36
    for (i=1; i < gsize; i++)
                                                                                   37
        displs[i] = displs[i-1] + counts[i-1];
                                                                                   38
    totalcount = displs[gsize-1] + counts[gsize-1];
    rbuf = (char *)malloc(totalcount);
    cbuf = (char *)malloc(totalcount);
    MPI_Gatherv(lbuf, position, MPI_PACKED, rbuf,
                                                                                   42
                 counts, displs, MPI_PACKED, root, comm);
                                                                                   43
                                                                                    44
    /* unpack all messages and concatenate strings */
                                                                                    45
    concat_pos = 0;
                                                                                    46
    for (i=0; i < gsize; i++) {
                                                                                    47
        position = 0;
```

11 12

13

14

15

16 17

18

19

20

21

23

24

30

31

32 33

34

35

36 37

39 40

41

42

43

44 45

46

47

## 5.3 Canonical MPI\_PACK and MPI\_UNPACK

These functions read/write data to/from the buffer in the "external32" data format specified in Section 14.5.2, and calculate the size needed for packing. Their first arguments specify the data format, for future extensibility, but currently the only valid value of the datarep argument is "external32".

Advice to users. These functions could be used, for example, to send typed data in a portable format from one MPI implementation to another. (End of advice to users.)

The buffer will contain exactly the packed data, without headers. MPI\_BYTE should be used to send and receive data that is packed using MPI\_PACK\_EXTERNAL.

Rationale. MPI\_PACK\_EXTERNAL specifies that there is no header on the message and further specifies the exact format of the data. Since MPI\_PACK may (and is allowed to) use a header, the datatype MPI\_PACKED cannot be used for data packed with MPI\_PACK\_EXTERNAL. (End of rationale.)

MPI\_PACK\_EXTERNAL(datarep, inbuf, incount, datatype, outbuf, outsize, position)

```
IN
           datarep
                                            data representation (string)
IN
           inbuf
                                            input buffer start (choice)
IN
                                            number of input data items (integer)
           incount
IN
           datatype
                                            datatype of each input data item (handle)
OUT
           outbuf
                                            output buffer start (choice)
IN
           outsize
                                            output buffer size, in bytes (integer)
INOUT
           position
                                            current position in buffer, in bytes (integer)
```

#### C binding

MPI\_Count incount, MPI\_Datatype datatype, void \*outbuf,

MPI\_Count outsize, MPI\_Count \*position)

```
Fortran 2008 binding
MPI_Pack_external(datarep, inbuf, incount, datatype, outbuf, outsize,
              position, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: datarep
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
    INTEGER, INTENT(IN) :: incount
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(*), DIMENSION(..) :: outbuf
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: outsize
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(INOUT) :: position
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      12
MPI_Pack_external(datarep, inbuf, incount, datatype, outbuf, outsize,
                                                                                      13
              position, ierror)
                                                                                      14
    CHARACTER(LEN=*), INTENT(IN) :: datarep
                                                                                      15
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
                                                                                      16
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: incount, outsize
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      18
    TYPE(*), DIMENSION(..) :: outbuf
                                                                                      19
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(INOUT) :: position
                                                                                      20
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      21
                                                                                      22
Fortran binding
                                                                                      23
MPI_PACK_EXTERNAL(DATAREP, INBUF, INCOUNT, DATATYPE, OUTBUF, OUTSIZE,
              POSITION, IERROR)
    CHARACTER*(*) DATAREP
                                                                                      26
    <type> INBUF(*), OUTBUF(*)
                                                                                      27
    INTEGER INCOUNT, DATATYPE, IERROR
                                                                                      28
    INTEGER(KIND=MPI_ADDRESS_KIND) OUTSIZE, POSITION
                                                                                      29
                                                                                      30
MPI_UNPACK_EXTERNAL(datarep, inbuf, insize, position, outbuf, outcount, datatype)
  IN
           datarep
                                      data representation (string)
                                                                                      34
  IN
           inbuf
                                      input buffer start (choice)
                                                                                      35
  IN
           insize
                                      input buffer size, in bytes (integer)
                                                                                      36
  INOUT
           position
                                      current position in buffer, in bytes (integer)
                                                                                      37
  OUT
           outbuf
                                      output buffer start (choice)
                                                                                      38
  IN
           outcount
                                      number of output data items (integer)
  IN
           datatype
                                      datatype of output data item (handle)
                                                                                      42
C binding
                                                                                      43
int MPI_Unpack_external(const char datarep[], const void *inbuf,
                                                                                      44
              MPI_Aint insize, MPI_Aint *position, void *outbuf,
                                                                                      45
              int outcount, MPI_Datatype datatype)
                                                                                      46
```

```
1
     int MPI_Unpack_external_c(const char datarep[], const void *inbuf,
2
                   MPI_Count insize, MPI_Count *position, void *outbuf,
3
                   MPI_Count outcount, MPI_Datatype datatype)
     Fortran 2008 binding
5
     MPI_Unpack_external(datarep, inbuf, insize, position, outbuf, outcount,
6
                   datatype, ierror)
         CHARACTER(LEN=*), INTENT(IN) :: datarep
         TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
9
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: insize
10
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(INOUT) :: position
         TYPE(*), DIMENSION(..) :: outbuf
12
         INTEGER, INTENT(IN) :: outcount
13
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
14
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
15
16
     MPI_Unpack_external(datarep, inbuf, insize, position, outbuf, outcount,
17
                   datatype, ierror)
18
         CHARACTER(LEN=*), INTENT(IN) :: datarep
19
         TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
20
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: insize, outcount
21
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(INOUT) :: position
22
         TYPE(*), DIMENSION(..) :: outbuf
23
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
24
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
26
     MPI_UNPACK_EXTERNAL(DATAREP, INBUF, INSIZE, POSITION, OUTBUF, OUTCOUNT,
27
                   DATATYPE, IERROR)
28
         CHARACTER*(*) DATAREP
29
         <type> INBUF(*), OUTBUF(*)
30
         INTEGER(KIND=MPI_ADDRESS_KIND) INSIZE, POSITION
31
         INTEGER OUTCOUNT, DATATYPE, IERROR
33
34
     MPI_PACK_EXTERNAL_SIZE(datarep, incount, datatype, size)
35
36
       IN
                datarep
                                          data representation (string)
37
       IN
                incount
                                          number of input data items (integer)
38
       IN
                datatype
                                          datatype of each input data item (handle)
39
       OUT
                                          output buffer size, in bytes (integer)
                size
41
42
     C binding
43
     int MPI_Pack_external_size(const char datarep[], int incount,
44
                   MPI_Datatype datatype, MPI_Aint *size)
45
     int MPI_Pack_external_size_c(const char datarep[], MPI_Count incount,
46
47
                   MPI_Datatype datatype, MPI_Count *size)
```

Fortran 2008 binding  MPI_Pack_external_size(datarep, incount, datatype, size, ierror)  CHARACTER(LEN=*), INTENT(IN) :: datarep  INTEGER, INTENT(IN) :: incount  TYPE(MPI_Datatype), INTENT(IN) :: datatype  INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: size  INTEGER, OPTIONAL, INTENT(OUT) :: ierror
<pre>MPI_Pack_external_size(datarep, incount, datatype, size, ierror)     CHARACTER(LEN=*), INTENT(IN) :: datarep     INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: incount     TYPE(MPI_Datatype), INTENT(IN) :: datatype     INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: size     INTEGER, OPTIONAL, INTENT(OUT) :: ierror</pre>
Fortran binding MPI_PACK_EXTERNAL_SIZE(DATAREP, INCOUNT, DATATYPE, SIZE, IERROR) CHARACTER*(*) DATAREP INTEGER INCOUNT, DATATYPE, IERROR INTEGER(KIND=MPI_ADDRESS_KIND) SIZE



# Chapter 6

# Collective Communication

#### 6.1 Introduction and Overview

Collective communication is defined as communication that involves a group or groups of processes. The functions of this type provided by MPI are the following:

- MPI\_BARRIER, MPI\_IBARRIER: Barrier synchronization across all members of a group (Section 6.3 and Section 6.12.1).
- MPI\_BCAST, MPI\_IBCAST: Broadcast from one member to all members of a group (Section 6.4 and Section 6.12.2). This is shown as "broadcast" in Figure 6.1.
- MPI\_GATHER, MPI\_IGATHER, MPI\_GATHERV, MPI\_IGATHERV: Gather data from all members of a group to one member (Section 6.5 and Section 6.12.3). This is shown as "gather" in Figure 6.1.
- MPI\_SCATTER, MPI\_ISCATTER, MPI\_SCATTERV, MPI\_ISCATTERV: Scatter data from one member to all members of a group (Section 6.6 and Section 6.12.4). This is shown as "scatter" in Figure 6.1.
- MPI\_ALLGATHER, MPI\_IALLGATHER, MPI\_ALLGATHERV, MPI\_IALLGATHERV: A variation on Gather where all members of a group receive the result (Section 6.7 and Section 6.12.5). This is shown as "allgather" in Figure 6.1.
- MPI\_ALLTOALL, MPI\_IALLTOALL, MPI\_ALLTOALLV, MPI\_IALLTOALLV, MPI\_ALLTOALLW, MPI\_IALLTOALLW: Scatter/Gather data from all members to all members of a group (also called complete exchange) (Section 6.8 and Section 6.12.6). This is shown as "complete exchange" in Figure 6.1.
- MPI\_ALLREDUCE, MPI\_IALLREDUCE, MPI\_REDUCE, MPI\_IREDUCE: Global reduction operations such as sum, max, min, or user-defined functions, where the result is returned to all members of a group (Section 6.9.6 and Section 6.12.8) and a variation where the result is returned to only one member (Section 6.9 and Section 6.12.7).
- MPI\_REDUCE\_SCATTER\_BLOCK, MPI\_IREDUCE\_SCATTER\_BLOCK, MPI\_REDUCE\_SCATTER, MPI\_IREDUCE\_SCATTER: A combined reduction and scatter operation (Section 6.10, Section 6.12.9, and Section 6.12.10).

• MPI\_SCAN, MPI\_ISCAN, MPI\_EXSCAN, MPI\_IEXSCAN: Scan across all members of a group (also called prefix) (Section 6.11, Section 6.11.2, Section 6.12.11, and Section 6.12.12).

One of the key arguments in a call to a collective routine is a communicator that defines the group or groups of participating processes and provides a context for the operation. This is discussed further in Section 6.2. The syntax and semantics of the collective operations are defined to be consistent with the syntax and semantics of the point-to-point operations. Thus, general datatypes are allowed and must match between sending and receiving processes as specified in Chapter 5. Several collective routines such as broadcast and gather have a single originating or receiving process. Such a process is called the *root*. Some arguments in the collective functions are specified as "significant only at root," and are ignored for all participants except the root. The reader is referred to Chapter 5 for information concerning communication buffers, general datatypes and type matching rules, and to Chapter 7 for information on how to define groups and create communicators.

The type-matching conditions for the collective operations are more strict than the corresponding conditions between sender and receiver in point-to-point. Namely, for collective operations, the amount of data sent must exactly match the amount of data specified by the receiver. Different type maps (the layout in memory, see Section 5.1) between sender and receiver are still allowed.

Collective operations can (but are not required to) complete as soon as the caller's participation in the collective communication is finished. A blocking operation is complete as soon as the call returns. A nonblocking (immediate) call requires a separate completion call (cf. Section 3.7). The completion of a collective operation indicates that the caller is free to modify locations in the communication buffer. It does not indicate that other processes in the group have completed or even started the operation (unless otherwise implied by the description of the operation). Thus, a collective communication operation may, or may not, have the effect of synchronizing all participating MPI processes.

Collective communication calls may use the same communicators as point-to-point communication; MPI guarantees that messages generated on behalf of collective communication calls will not be confused with messages generated by point-to-point communication. The collective operations do not have a message tag argument. A more detailed discussion of correct use of collective routines is found in Section 6.14.

Rationale. The equal-data restriction (on type matching) was made so as to avoid the complexity of providing a facility analogous to the status argument of MPI\_RECV for discovering the amount of data sent. Some of the collective routines would require an array of status values.

The statements about synchronization are made so as to allow a variety of implementations of the collective functions.

(End of rationale.)

Advice to users. It is dangerous to rely on synchronization side-effects of the collective operations for program correctness. For example, even though a particular implementation may provide a broadcast routine with a side-effect of synchronization, the standard does not require this, and a program that relies on this will not be portable.




Figure 6.1: Collective move functions illustrated for a group of six processes. In each case, each row of boxes represents data locations in one process. Thus, in the broadcast, initially just the first process contains the data  $A_0$ , but after the broadcast all processes contain it.

 On the other hand, a correct, portable program must allow for the fact that a collective call may be synchronizing. Though one cannot rely on any synchronization side-effect, one must program so as to allow it. These issues are discussed further in Section 6.14. (*End of advice to users.*)

Advice to implementors. While vendors may write optimized collective routines matched to their architectures, a complete library of the collective communication routines can be written entirely using the MPI point-to-point communication functions and a few auxiliary functions. If implementing on top of point-to-point, a hidden, special communicator might be created for the collective operation so as to avoid interference with any on-going point-to-point communication at the time of the collective call. This is discussed further in Section 6.14. (End of advice to implementors.)

Many of the descriptions of the collective routines provide illustrations in terms of blocking MPI point-to-point routines. These are intended solely to indicate what data is sent or received by what process. Many of these examples are *not* correct MPI programs; for purposes of simplicity, they often assume infinite buffering.

## 6.2 Communicator Argument

The key concept of the collective functions is to have a group or groups of participating processes. The routines do not have group identifiers as explicit arguments. Instead, there is a communicator argument. Groups and communicators are discussed in full detail in Chapter 7. For the purposes of this chapter, it is sufficient to know that there are two types of communicators: *intra-communicators* and *inter-communicators*. An intra-communicator can be thought of as an identifier for a single group of processes linked with a context. An inter-communicator identifies two distinct groups of processes linked with a context.

## 6.2.1 Specifics for Intra-Communicator Collective Operations

All processes in the group identified by the intra-communicator must call the collective routine.

In many cases, collective communication can occur "in place" for intra-communicators, with the output buffer being identical to the input buffer. This is specified by providing a special argument value, MPI\_IN\_PLACE, instead of the send buffer or the receive buffer argument, depending on the operation performed.

Rationale. The "in place" operations are provided to reduce unnecessary memory motion by both the MPI implementation and by the user. Note that while the simple check of testing whether the send and receive buffers have the same address will work for some cases (e.g., MPI\_ALLREDUCE), they are inadequate in others (e.g., MPI\_GATHER, with root not equal to zero). Further, Fortran explicitly prohibits aliasing of arguments; the approach of using a special value to denote "in place" operation eliminates that difficulty. (End of rationale.)

Advice to users. By allowing the "in place" option, the receive buffer in many of the collective calls becomes a send-and-receive buffer. For this reason, a Fortran binding that includes INTENT must mark these as INOUT, not OUT.

Note that MPI\_IN\_PLACE is a special kind of value; it has the same restrictions on its use that MPI\_BOTTOM has. (*End of advice to users.*)

13

14

15

16

18

19 20

21

22 23

24

25 26

27

28 29

30

31

34

35

36

37

38

40

41

42 43

44

45 46

47

## 6.2.2 Applying Collective Operations to Inter-Communicators

To understand how collective operations apply to inter-communicators, we can view most MPI intra-communicator collective operations as fitting one of the following categories (see, for instance, [63]):

All-To-All All processes contribute to the result. All processes receive the result.

- MPI\_ALLGATHER, MPI\_IALLGATHER, MPI\_ALLGATHERV, MPI\_IALLGATHERV
- MPI\_ALLTOALL, MPI\_IALLTOALL, MPI\_ALLTOALLV, MPI\_IALLTOALLV, MPI\_ALLTOALLW, MPI\_IALLTOALLW
- MPI\_ALLREDUCE, MPI\_IALLREDUCE, MPI\_REDUCE\_SCATTER\_BLOCK, MPI\_IREDUCE\_SCATTER\_BLOCK, MPI\_REDUCE\_SCATTER, MPI\_IREDUCE\_SCATTER
- MPI\_BARRIER, MPI\_IBARRIER

All-To-One All processes contribute to the result. One process receives the result.

- MPI\_GATHER, MPI\_IGATHERV, MPI\_IGATHERV
- MPI\_REDUCE, MPI\_IREDUCE

One-To-All One process contributes to the result. All processes receive the result.

- MPI\_BCAST, MPI\_IBCAST
- MPI\_SCATTER, MPI\_ISCATTER, MPI\_SCATTERV, MPI\_ISCATTERV

Other Collective operations that do not fit into one of the above categories.

MPI\_SCAN, MPI\_ISCAN, MPI\_EXSCAN, MPI\_IEXSCAN

The data movement patterns of MPI\_SCAN, MPI\_ISCAN, MPI\_EXSCAN, and MPI\_IEXSCAN do not fit this taxonomy.

The application of collective communication to inter-communicators is best described in terms of two groups. For example, an all-to-all MPI\_ALLGATHER operation can be described as collecting data from all members of one group with the result appearing in all members of the other group (see Figure 6.2). As another example, a one-to-all

MPI\_BCAST operation sends data from one member of one group to all members of the other group. Collective computation operations such as MPI\_REDUCE\_SCATTER have a similar interpretation (see Figure 6.3). For intra-communicators, these two groups are the same. For inter-communicators, these two groups are distinct. For the all-to-all operations, each such operation is described in two phases, so that it has a symmetric, full-duplex behavior.

The following collective operations also apply to inter-communicators:

- MPI\_BARRIER, MPI\_IBARRIER
- MPI\_BCAST, MPI\_IBCAST
- MPI\_GATHER, MPI\_IGATHER, MPI\_GATHERV, MPI\_IGATHERV,
- MPI\_SCATTER, MPI\_ISCATTER, MPI\_SCATTERV, MPI\_ISCATTERV,

- MPI\_ALLGATHER, MPI\_IALLGATHER, MPI\_ALLGATHERV, MPI\_IALLGATHERV,
- MPI\_ALLTOALL, MPI\_IALLTOALL, MPI\_ALLTOALLV, MPI\_IALLTOALLV, MPI\_ALLTOALLW, MPI\_IALLTOALLW,
- MPI\_ALLREDUCE, MPI\_IALLREDUCE, MPI\_REDUCE, MPI\_IREDUCE,
- MPI\_REDUCE\_SCATTER\_BLOCK, MPI\_IREDUCE\_SCATTER\_BLOCK, MPI\_REDUCE\_SCATTER, MPI\_IREDUCE\_SCATTER.




Figure 6.2: Inter-communicator allgather. The focus of data to one process is represented, not mandated by the semantics. The two phases do allgathers in both directions.

## 6.2.3 Specifics for Inter-Communicator Collective Operations

All processes in both groups identified by the inter-communicator must call the collective routine.

Note that the "in place" option for intra-communicators does not apply to inter-communicators since in the inter-communicator case there is no communication from a process to itself.

For inter-communicator collective communication, if the operation is in the All-To-One or One-To-All categories, then the transfer is unidirectional. The direction of the transfer is indicated by a special value of the root argument. In this case, for the group containing the root process, all processes in the group must call the routine using a special argument for the root. For this, the root process uses the special root value MPI\_ROOT; all other processes in the same group as the root use MPI\_PROC\_NULL. All processes in the other group (the group that is the remote group relative to the root process) must call the collective routine and provide the rank of the root. If the operation is in the All-To-All category, then the transfer is bidirectional.

Rationale. Operations in the All-To-One and One-To-All categories are unidirectional by nature, and there is a clear way of specifying direction. Operations in the All-To-All




Figure 6.3: Inter-communicator reduce-scatter. The focus of data to one process is represented, not mandated by the semantics. The two phases do reduce-scatters in both directions.

category will often occur as part of an exchange, where it makes sense to communicate in both directions at once. ( $End\ of\ rationale.$ )

# 6.3 Barrier Synchronization

Fortran binding

MPI\_BARRIER(COMM, IERROR)

INTEGER COMM, IERROR

```
MPI_BARRIER(comm)

IN comm communicator (handle)

C binding
int MPI_Barrier(MPI_Comm comm)

Fortran 2008 binding

MPI_Barrier(comm, ierror)

    TYPE(MPI_Comm), INTENT(IN) :: comm

    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

If comm is an intra-communicator, MPI\_BARRIER blocks the caller until all group members have called it. The call returns at any process only after all group members have entered the call.

If comm is an inter-communicator, MPI\_BARRIER involves two groups. The call returns at processes in one group (group A) of the inter-communicator only after all members of

the other group (group B) have entered the call (and vice versa). A process may return from the call before all processes in its own group have entered the call.

## 6.4 Broadcast

```
MPI_BCAST(buffer, count, datatype, root, comm)
```

```
INOUT buffer starting address of buffer (choice)

IN count number of entries in buffer (non-negative integer)

IN datatype data type of buffer (handle)

IN root rank of broadcast root (integer)

IN comm communicator (handle)
```

## C binding

#### Fortran 2008 binding

```
MPI_Bcast(buffer, count, datatype, root, comm, ierror)
    TYPE(*), DIMENSION(..) :: buffer
    INTEGER, INTENT(IN) :: count, root
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

MPI_Bcast(buffer, count, datatype, root, comm, ierror)
    TYPE(*), DIMENSION(..) :: buffer
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: root
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

If comm is an intra-communicator, MPI\_BCAST broadcasts a message from the process with rank root to all processes of the group, itself included. It is called by all members of the group using the same arguments for comm and root. On return, the content of root's buffer is copied to all other processes.

General, derived datatypes are allowed for datatype. The type signature of count, datatype on any process must be equal to the type signature of count, datatype at the root.

This implies that the amount of data sent must be equal to the amount received, pairwise between each process and the root. MPI\_BCAST and all other data-movement collective routines make this restriction. Distinct type maps between sender and receiver are still allowed.

The "in place" option is not meaningful here.

If comm is an inter-communicator, then the call involves all processes in the inter-communicator, but with one group (group A) defining the root process. All processes in the other group (group B) pass the same value in argument root, which is the rank of the root in group A. The root passes the value MPI\_ROOT in root. All other processes in group A pass the value MPI\_PROC\_NULL in root. Data is broadcast from the root to all processes in group B. The buffer arguments of the processes in group B must be consistent with the buffer argument of the root.

## 6.4.1 Example using MPI\_BCAST

The examples in this section use intra-communicators.

**Example 6.1** Broadcast 100 ints from process 0 to every process in the group.

```
MPI_Comm comm;
int array[100];
int root=0;
...
MPI_Bcast(array, 100, MPI_INT, root, comm);
```

As in many of our example code fragments, we assume that some of the variables (such as comm in the above) have been assigned appropriate values.

## 6.5 Gather

MPI\_GATHER(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, root, comm)

IN	sendbuf	starting address of send buffer (choice)
IN	sendcount	number of elements in send buffer (non-negative integer) $$
IN	sendtype	data type of send buffer elements (handle)
OUT	recvbuf	address of receive buffer (choice, significant only at root)
IN	recvcount	number of elements for any single receive (non-negative integer, significant only at root)
IN	recvtype	data type of recv buffer elements (handle, significant only at root)
IN	root	rank of receiving process (integer)
IN	comm	communicator (handle)

```
1
     int MPI_Gather(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
2
                    void *recvbuf, int recvcount, MPI_Datatype recvtype, int root,
3
                    MPI_Comm comm)
4
     int MPI_Gather_c(const void *sendbuf, MPI_Count sendcount,
5
                    MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
6
                    MPI_Datatype recvtype, int root, MPI_Comm comm)
7
     Fortran 2008 binding
9
     MPI_Gather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
10
                   root, comm, ierror)
11
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
12
         INTEGER, INTENT(IN) :: sendcount, recvcount, root
13
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
14
         TYPE(*), DIMENSION(..) :: recvbuf
15
         TYPE(MPI_Comm), INTENT(IN) :: comm
16
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
17
     MPI_Gather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
18
                    root, comm, ierror)
19
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
20
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
21
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
22
         TYPE(*), DIMENSION(..) :: recvbuf
23
         INTEGER, INTENT(IN) :: root
24
         TYPE(MPI_Comm), INTENT(IN) :: comm
25
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
27
     Fortran binding
28
     MPI_GATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
29
                    ROOT, COMM, IERROR)
30
         <type> SENDBUF(*), RECVBUF(*)
31
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, IERROR
32
         If comm is an intra-communicator, each process (root process included) sends the con-
     tents of its send buffer to the root process. The root process receives the messages and stores
34
     them in rank order. The outcome is as if each of the n processes in the group (including
35
     the root process) had executed a call to
36
37
        MPI_Send(sendbuf, sendcount, sendtype, root, ...),
38
39
     and the root had executed n calls to
40
41
        MPI_Recv(recvbuf+i· recvcount· extent(recvtype), recvcount, recvtype, i,...),
42
43
     where extent(recvtype) is the type extent obtained from a call to MPI_Type_get_extent.
         An alternative description is that the n messages sent by the processes in the group
44
45
     are concatenated in rank order, and the resulting message is received by the root as if by a
46
     call to MPI_RECV(recvbuf, recvcount·n, recvtype, ...).
```

The receive buffer is ignored for all non-root processes.

General, derived datatypes are allowed for both sendtype and recvtype. The type signature of sendcount, sendtype on each process must be equal to the type signature of recvcount, recvtype at the root. This implies that the amount of data sent must be equal to the amount of data received, pairwise between each process and the root. Distinct type maps between sender and receiver are still allowed.

All arguments to the function are significant on process root, while on other processes, only arguments sendbuf, sendcount, sendtype, root, and comm are significant. The arguments root and comm must have identical values on all processes.

The specification of counts and types should not cause any location on the root to be written more than once. Such a call is erroneous.

Note that the recvcount argument at the root indicates the number of items it receives from *each* process, not the total number of items it receives.

The "in place" option for intra-communicators is specified by passing MPI\_IN\_PLACE as the value of sendbuf at the root. In such a case, sendcount and sendtype are ignored, and the contribution of the root to the gathered vector is assumed to be already in the correct place in the receive buffer.

If comm is an inter-communicator, then the call involves all processes in the inter-communicator, but with one group (group A) defining the root process. All processes in the other group (group B) pass the same value in argument root, which is the rank of the root in group A. The root passes the value MPI\_ROOT in root. All other processes in group A pass the value MPI\_PROC\_NULL in root. Data is gathered from all processes in group B to the root. The send buffer arguments of the processes in group B must be consistent with the receive buffer argument of the root.

```
1
     MPI_GATHERV(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs, recvtype, root,
2
                     comm)
3
       IN
                 sendbuf
                                             starting address of send buffer (choice)
       IN
                 sendcount
                                              number of elements in send buffer (non-negative
5
                                             integer)
6
7
       IN
                 sendtype
                                              data type of send buffer elements (handle)
       OUT
                 recvbuf
                                             address of receive buffer (choice, significant only at
9
                                              root)
10
       IN
                 recvcounts
                                             non-negative integer array (of length group size)
11
                                              containing the number of elements that are received
12
                                              from each process (significant only at root)
13
14
                                             integer array (of length group size). Entry i specifies
       IN
                 displs
15
                                              the displacement relative to recybuf at which to place
16
                                              the incoming data from process i (significant only at
17
18
       IN
                                              data type of recv buffer elements (handle, significant
                 recvtype
19
                                              only at root)
20
       IN
                                             rank of receiving process (integer)
                 root
21
22
       IN
                                              communicator (handle)
                 comm
23
24
     C binding
25
     int MPI_Gatherv(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
26
                     void *recvbuf, const int recvcounts[], const int displs[],
27
                     MPI_Datatype recvtype, int root, MPI_Comm comm)
28
     int MPI_Gatherv_c(const void *sendbuf, MPI_Count sendcount,
29
                     MPI_Datatype sendtype, void *recvbuf,
30
                     const MPI_Count recvcounts[], const MPI_Aint displs[],
31
                     MPI_Datatype recvtype, int root, MPI_Comm comm)
32
33
     Fortran 2008 binding
34
     MPI_Gatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
35
                     recvtype, root, comm, ierror)
36
          TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
37
          INTEGER, INTENT(IN) :: sendcount, recvcounts(*), displs(*), root
38
          TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
39
          TYPE(*), DIMENSION(..) :: recvbuf
          TYPE(MPI_Comm), INTENT(IN) :: comm
41
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
42
     MPI_Gatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
43
                     recvtype, root, comm, ierror)
44
          TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
45
          INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcounts(*)
46
          TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
47
          TYPE(*), DIMENSION(..) :: recvbuf
```

```
INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: displs(*)
INTEGER, INTENT(IN) :: root
TYPE(MPI_Comm), INTENT(IN) :: comm
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_GATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS,

RECVTYPE, ROOT, COMM, IERROR)

<type> SENDBUF(*), RECVBUF(*)

INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, ROOT,

COMM, IERROR
```

MPI\_GATHERV extends the functionality of MPI\_GATHER by allowing a varying count of data from each process, since recvcounts is now an array. It also allows more flexibility as to where the data is placed on the root, by providing the new argument, displs.

If **comm** is an intra-communicator, the outcome is *as if* each process, including the root process, sends a message to the root,

```
MPI_Send(sendbuf, sendcount, sendtype, root, ...),
```

and the root executes n receives,

```
MPI_Recv(recvbuf+displs[j]· extent(recvtype), recvcounts[j], recvtype, i, ...).
```

The data received from process j is placed into recvbuf of the root process beginning at offset displs[j] elements (in terms of the recvtype).

The receive buffer is ignored for all non-root processes.

The type signature implied by sendcount, sendtype on process i must be equal to the type signature implied by recvcounts[i], recvtype at the root. This implies that the amount of data sent must be equal to the amount of data received, pairwise between each process and the root. Distinct type maps between sender and receiver are still allowed, as illustrated in Example 6.6.

All arguments to the function are significant on process root, while on other processes, only arguments sendbuf, sendcount, sendtype, root, and comm are significant. The arguments root and comm must have identical values on all processes.

The specification of counts, types, and displacements should not cause any location on the root to be written more than once. Such a call is erroneous.

The "in place" option for intra-communicators is specified by passing MPI\_IN\_PLACE as the value of sendbuf at the root. In such a case, sendcount and sendtype are ignored, and the contribution of the root to the gathered vector is assumed to be already in the correct place in the receive buffer.

If comm is an inter-communicator, then the call involves all processes in the inter-communicator, but with one group (group A) defining the root process. All processes in the other group (group B) pass the same value in argument root, which is the rank of the root in group A. The root passes the value MPI\_ROOT in root. All other processes in group A pass the value MPI\_PROC\_NULL in root. Data is gathered from all processes in group B to the root. The send buffer arguments of the processes in group B must be consistent with the receive buffer argument of the root.




Figure 6.4: The root process gathers 100 ints from each process in the group.

## 6.5.1 Examples using MPI\_GATHER, MPI\_GATHERV

The examples in this section use intra-communicators.

**Example 6.2** Gather 100 ints from every process in group to root. See Figure 6.4.

```
MPI_Comm comm;
int gsize,sendarray[100];
int root, *rbuf;
...
MPI_Comm_size(comm, &gsize);
rbuf = (int *)malloc(gsize*100*sizeof(int));
MPI_Gather(sendarray, 100, MPI_INT, rbuf, 100, MPI_INT, root, comm);
```

**Example 6.3** Previous example modified—only the root allocates memory for the receive buffer.

```
MPI_Comm comm;
int gsize,sendarray[100];
int root, myrank, *rbuf;
...
MPI_Comm_rank(comm, &myrank);
if (myrank == root) {
    MPI_Comm_size(comm, &gsize);
    rbuf = (int *)malloc(gsize*100*sizeof(int));
}
MPI_Gather(sendarray, 100, MPI_INT, rbuf, 100, MPI_INT, root, comm);
```

**Example 6.4** Do the same as the previous example, but use a derived datatype. Note that the type cannot be the entire set of gsize\*100 ints since type matching is defined pairwise between the root and each process in the gather.




Figure 6.5: The root process gathers 100 ints from each process in the group, each set is placed stride ints apart.

```
MPI_Comm comm;
int gsize,sendarray[100];
int root, *rbuf;
MPI_Datatype rtype;
...
MPI_Comm_size(comm, &gsize);
MPI_Type_contiguous(100, MPI_INT, &rtype);
MPI_Type_commit(&rtype);
rbuf = (int *)malloc(gsize*100*sizeof(int));
MPI_Gather(sendarray, 100, MPI_INT, rbuf, 1, rtype, root, comm);
```

**Example 6.5** Now have each process send 100 ints to root, but place each set (of 100) stride ints apart at receiving end. Use MPI\_GATHERV and the displs argument to achieve this effect. Assume  $stride \ge 100$ . See Figure 6.5.

```
MPI_Comm comm;
int gsize,sendarray[100];
int root, *rbuf, stride;
int *displs,i,*rcounts;

...

MPI_Comm_size(comm, &gsize);
rbuf = (int *)malloc(gsize*stride*sizeof(int));
displs = (int *)malloc(gsize*sizeof(int));
rcounts = (int *)malloc(gsize*sizeof(int));
for (i=0; i < gsize; ++i) {
    displs[i] = i*stride;
    rcounts[i] = 100;
}
MPI_Gatherv(sendarray, 100, MPI_INT, rbuf, rcounts, displs, MPI_INT,
    root, comm);</pre>
```

**Example 6.6** Same as Example 6.5 on the receiving side, but send the 100 ints from the 0th column of a  $100 \times 150$  int array, in C. See Figure 6.6.

Note that the program is erroneous if stride < 100.




Figure 6.6: The root process gathers column 0 of a  $100 \times 150$  C array, and each set is placed stride ints apart.

```
MPI_Comm comm;
14
         int gsize,sendarray[100][150];
15
         int root, *rbuf, stride;
16
         MPI_Datatype stype;
         int *displs,i,*rcounts;
18
19
         . . .
20
21
         MPI_Comm_size(comm, &gsize);
22
         rbuf = (int *)malloc(gsize*stride*sizeof(int));
23
         displs = (int *)malloc(gsize*sizeof(int));
24
         rcounts = (int *)malloc(gsize*sizeof(int));
         for (i=0; i<gsize; ++i) {</pre>
26
             displs[i] = i*stride;
27
             rcounts[i] = 100;
28
         }
29
         /* Create datatype for 1 column of array
30
31
         MPI_Type_vector(100, 1, 150, MPI_INT, &stype);
32
         MPI_Type_commit(&stype);
33
         MPI_Gatherv(sendarray, 1, stype, rbuf, rcounts, displs, MPI_INT,
34
                      root, comm);
35
```

**Example 6.7** Process i sends (100-i) ints from the i-th column of a  $100 \times 150$  int array, in C. It is received into a buffer with stride, as in the previous two examples. See Figure 6.7.

```
MPI_Comm comm;
int gsize,sendarray[100][150],*sptr;
int root, *rbuf, stride, myrank;
MPI_Datatype stype;
int *displs,i,*rcounts;
...
```




Figure 6.7: The root process gathers 100-i ints from column i of a 100×150 C array, and each set is placed stride ints apart.

12 13

14

15

16

18

19

20

21

22

23

24

26

27 28

29

30

31

33 34

35

36

37

```
MPI_Comm_size(comm, &gsize);
MPI_Comm_rank(comm, &myrank);
rbuf = (int *)malloc(gsize*stride*sizeof(int));
displs = (int *)malloc(gsize*sizeof(int));
rcounts = (int *)malloc(gsize*sizeof(int));
for (i=0; i<gsize; ++i) {
    displs[i] = i*stride;
                            /* note change from previous example */
    rcounts[i] = 100-i;
}
/* Create datatype for the column we are sending
 */
MPI_Type_vector(100-myrank, 1, 150, MPI_INT, &stype);
MPI_Type_commit(&stype);
/* sptr is the address of start of "myrank" column
sptr = &sendarray[0][myrank];
MPI_Gatherv(sptr, 1, stype, rbuf, rcounts, displs, MPI_INT,
            root, comm);
```

Note that a different amount of data is received from each process.

**Example 6.8** Same as Example 6.7, but done in a different way at the sending end. We create a datatype that causes the correct striding at the sending end so that we read a column of a C array. A similar thing was done in Example 5.16, Section 5.1.14.

```
MPI_Comm comm;
                                                                                38
                                                                                39
int gsize, sendarray[100][150], *sptr;
int root, *rbuf, stride, myrank;
                                                                                41
MPI_Datatype stype;
                                                                                42
int *displs, i, *rcounts;
                                                                                43
                                                                                44
                                                                                45
                                                                                46
MPI_Comm_size(comm, &gsize);
MPI_Comm_rank(comm, &myrank);
rbuf = (int *)malloc(gsize*stride*sizeof(int));
```

```
1
         displs = (int *)malloc(gsize*sizeof(int));
2
         rcounts = (int *)malloc(gsize*sizeof(int));
         for (i=0; i<gsize; ++i) {
             displs[i] = i*stride;
             rcounts[i] = 100-i;
         }
         /* Create datatype for one int, with extent of entire row
          */
         MPI_Type_create_resized(MPI_INT, 0, 150*sizeof(int), &stype);
         MPI_Type_commit(&stype);
11
         sptr = &sendarray[0][myrank];
12
         MPI_Gatherv(sptr, 100-myrank, stype, rbuf, rcounts, displs, MPI_INT,
13
                      root, comm);
14
15
     Example 6.9 Same as Example 6.7 at sending side, but at receiving side we make the
16
     stride between received blocks vary from block to block. See Figure 6.8.
17
18
         MPI_Comm comm;
19
         int gsize,sendarray[100][150],*sptr;
20
         int root, *rbuf, *stride, myrank, bufsize;
21
         MPI_Datatype stype;
22
         int *displs,i,*rcounts,offset;
23
24
         . . .
26
         MPI_Comm_size(comm, &gsize);
27
         MPI_Comm_rank(comm, &myrank);
28
29
         stride = (int *)malloc(gsize*sizeof(int));
30
         /* stride[i] for i = 0 to gsize-1 is set somehow
          */
33
34
         /* set up displs and rcounts vectors first
35
36
         displs = (int *)malloc(gsize*sizeof(int));
37
         rcounts = (int *)malloc(gsize*sizeof(int));
         offset = 0;
39
         for (i=0; i<gsize; ++i) {
             displs[i] = offset;
             offset += stride[i];
             rcounts[i] = 100-i;
43
         }
44
         /* the required buffer size for rbuf is now easily obtained
45
          */
46
         bufsize = displs[gsize-1]+rcounts[gsize-1];
         rbuf = (int *)malloc(bufsize*sizeof(int));
```




Figure 6.8: The root process gathers 100-i ints from column i of a 100×150 C array, and each set is placed stride[i] ints apart (a varying stride).

12 13

14

15

16

18

19

20 21 22

24

26

**Example 6.10** Process i sends num ints from the i-th column of a  $100 \times 150$  int array, in C. The complicating factor is that the various values of num are not known to root, so a separate gather must first be run to find these out. The data is placed contiguously at the receiving end.

```
MPI_Comm comm;
                                                                                27
int gsize, sendarray[100][150], *sptr;
                                                                                28
                                                                                29
int root, *rbuf, myrank;
                                                                                30
MPI_Datatype stype;
                                                                                31
int *displs,i,*rcounts,num;
                                                                                33
                                                                               34
MPI_Comm_size(comm, &gsize);
                                                                               35
                                                                               36
MPI_Comm_rank(comm, &myrank);
                                                                               37
/* First, gather nums to root
 */
rcounts = (int *)malloc(gsize*sizeof(int));
MPI_Gather(&num, 1, MPI_INT, rcounts, 1, MPI_INT, root, comm);
                                                                               42
/* root now has correct rounts, using these we set displs[] so
 * that data is placed contiguously (or concatenated) at receive end
                                                                                43
                                                                                44
 */
displs = (int *)malloc(gsize*sizeof(int));
                                                                                45
                                                                                46
displs[0] = 0;
for (i=1; i<gsize; ++i) {
    displs[i] = displs[i-1]+rcounts[i-1];
```

```
1
          }
2
          /* And, create receive buffer
          rbuf = (int *)malloc(gsize*(displs[gsize-1]+rcounts[gsize-1])
                                                                           *sizeof(int));
6
          /* Create datatype for one int, with extent of entire row
           */
          MPI_Type_create_resized(MPI_INT, 0, 150*sizeof(int), &stype);
          MPI_Type_commit(&stype);
10
          sptr = &sendarray[0][myrank];
11
          MPI_Gatherv(sptr, num, stype, rbuf, rcounts, displs, MPI_INT,
12
                       root, comm);
13
14
          Scatter
     6.6
15
16
17
     MPI_SCATTER(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, root, comm)
18
19
       IN
                 sendbuf
                                             address of send buffer (choice, significant only at
20
                                             root)
21
       IN
                 sendcount
                                             number of elements sent to each process
22
                                             (non-negative integer, significant only at root)
23
24
       IN
                                             data type of send buffer elements (handle, significant
                 sendtype
                                             only at root)
26
       OUT
                                             address of receive buffer (choice)
                 recvbuf
27
       IN
                 recvcount
                                             number of elements in receive buffer (non-negative
28
                                             integer)
29
30
       IN
                                             data type of receive buffer elements (handle)
                 recvtype
31
       IN
                                             rank of sending process (integer)
                 root
32
       IN
                                             communicator (handle)
                 comm
33
34
     C binding
35
     int MPI_Scatter(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
36
37
                    void *recvbuf, int recvcount, MPI_Datatype recvtype, int root,
                    MPI_Comm comm)
38
39
     int MPI_Scatter_c(const void *sendbuf, MPI_Count sendcount,
40
                    MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
41
                    MPI_Datatype recvtype, int root, MPI_Comm comm)
42
     Fortran 2008 binding
43
44
     MPI_Scatter(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
45
                    root, comm, ierror)
46
          TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
47
          INTEGER, INTENT(IN) :: sendcount, recvcount, root
          TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
```

6.6. SCATTER 203

#### Fortran binding

```
MPI_SCATTER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE, ROOT, COMM, IERROR)
```

```
<type> SENDBUF(*), RECVBUF(*)
```

INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, IERROR

MPI\_SCATTER is the inverse operation to MPI\_GATHER.

If comm is an intra-communicator, the outcome is as if the root executed n send operations,

```
MPI_Send(sendbuf+i· sendcount· extent(sendtype), sendcount, sendtype, i,...),
```

and each process executed a receive,

```
MPI_Recv(recvbuf, recvcount, recvtype, i,...).
```

An alternative description is that the root sends a message with MPI\_Send(sendbuf, sendcount·n, sendtype, . . .). This message is split into n equal segments, the *i*-th segment is sent to the *i*-th process in the group, and each process receives this message as above.

The send buffer is ignored for all non-root processes.

The type signature associated with sendcount, sendtype at the root must be equal to the type signature associated with recvcount, recvtype at all processes (however, the type maps may be different). This implies that the amount of data sent must be equal to the amount of data received, pairwise between each process and the root. Distinct type maps between sender and receiver are still allowed.

All arguments to the function are significant on process root, while on other processes, only arguments recvbuf, recvcount, recvtype, root, and comm are significant. The arguments root and comm must have identical values on all processes.

The specification of counts and types should not cause any location on the root to be read more than once.

Rationale. Though not needed, the last restriction is imposed so as to achieve symmetry with MPI\_GATHER, where the corresponding restriction (a multiple-write restriction) is necessary. (*End of rationale*.)

The "in place" option for intra-communicators is specified by passing MPI\_IN\_PLACE as the value of recvbuf at the root. In such a case, recvcount and recvtype are ignored, and

root "sends" no data to itself. The scattered vector is still assumed to contain n segments, where n is the group size; the root-th segment, which root should "send to itself," is not

If comm is an inter-communicator, then the call involves all processes in the intercommunicator, but with one group (group A) defining the root process. All processes in the other group (group B) pass the same value in argument root, which is the rank of the root in group A. The root passes the value MPI\_ROOT in root. All other processes in group A pass the value MPI\_PROC\_NULL in root. Data is scattered from the root to all processes in group B. The receive buffer arguments of the processes in group B must be consistent with the send buffer argument of the root.

1.

```
MPI_SCATTERV(sendbuf, sendcounts, displs, sendtype, recybuf, recycount, recytype, root,
               comm)
```

15 16	IN	sendbuf	address of send buffer (choice, significant only at root)
17 18	IN	sendcounts	non-negative integer array (of length group size)
19 20			specifying the number of elements to send to each rank (significant only at root)
21	IN	displs	integer array (of length group size). Entry i specifies
22			the displacement (relative to sendbuf) from which to
23			take the outgoing data to process i (significant only
24			at root)
25	IN	sendtype	data type of send buffer elements (handle, significant
26			only at root)
27 28	OUT	recvbuf	address of receive buffer (choice)
29	IN	recvcount	number of elements in receive buffer (non-negative
30			integer)
31	IN	recvtype	data type of receive buffer elements (handle)
32	IN	root	rank of sending process (integer)
33		1000	, , , , , , , , , , , , , , , , , , ,
34	IN	comm	communicator (handle)

#### C binding

```
int MPI_Scatterv(const void *sendbuf, const int sendcounts[],
             const int displs[], MPI_Datatype sendtype, void *recvbuf,
             int recvcount, MPI_Datatype recvtype, int root, MPI_Comm comm)
int MPI_Scatterv_c(const void *sendbuf, const MPI_Count sendcounts[],
             const MPI_Aint displs[], MPI_Datatype sendtype, void *recvbuf,
             MPI_Count recvcount, MPI_Datatype recvtype, int root,
             MPI_Comm comm)
Fortran 2008 binding
MPI_Scatterv(sendbuf, sendcounts, displs, sendtype, recvbuf, recvcount,
             recvtype, root, comm, ierror)
```

TYPE(\*), DIMENSION(..), INTENT(IN) :: sendbuf

6.6. SCATTER 205

12

13

14

15

16

19

20 21

22

23

24

27

28

29

30 31

34 35

36

37

43

44

45

46

47

#### Fortran binding

MPI\_SCATTERV(SENDBUF, SENDCOUNTS, DISPLS, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE, ROOT, COMM, IERROR)

<type> SENDBUF(\*), RECVBUF(\*)

INTEGER SENDCOUNTS(\*), DISPLS(\*), SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, IERROR

MPI\_SCATTERV is the inverse operation to MPI\_GATHERV.

MPI\_SCATTERV extends the functionality of MPI\_SCATTER by allowing a varying count of data to be sent to each process, since sendcounts is now an array. It also allows more flexibility as to where the data is taken from on the root, by providing an additional argument, displs.

If comm is an intra-communicator, the outcome is as if the root executed n send operations,

```
MPI_Send(sendbuf+displs[i] extent(sendtype), sendcounts[i], sendtype, i,...),
```

and each process executed a receive,

```
MPI_Recv(recvbuf, recvcount, recvtype, i,...).
```

The send buffer is ignored for all non-root processes.

The type signature implied by sendcount[i], sendtype at the root must be equal to the type signature implied by recvcount, recvtype at process i (however, the type maps may be different). This implies that the amount of data sent must be equal to the amount of data received, pairwise between each process and the root. Distinct type maps between sender and receiver are still allowed.

All arguments to the function are significant on process root, while on other processes, only arguments recvbuf, recvcount, recvtype, root, and comm are significant. The arguments root and comm must have identical values on all processes.

The specification of counts, types, and displacements should not cause any location on the root to be read more than once.




Figure 6.9: The root process scatters sets of 100 ints to each process in the group.

The "in place" option for intra-communicators is specified by passing MPI\_IN\_PLACE as the value of recvbuf at the root. In such a case, recvcount and recvtype are ignored, and root "sends" no data to itself. The scattered vector is still assumed to contain n segments, where n is the group size; the root-th segment, which root should "send to itself," is not moved.

If comm is an inter-communicator, then the call involves all processes in the inter-communicator, but with one group (group A) defining the root process. All processes in the other group (group B) pass the same value in argument root, which is the rank of the root in group A. The root passes the value MPI\_ROOT in root. All other processes in group A pass the value MPI\_PROC\_NULL in root. Data is scattered from the root to all processes in group B. The receive buffer arguments of the processes in group B must be consistent with the send buffer argument of the root.

# 6.6.1 Examples using MPI\_SCATTER, MPI\_SCATTERV

The examples in this section use intra-communicators.

**Example 6.11** The reverse of Example 6.2. Scatter sets of 100 ints from the root to each process in the group. See Figure 6.9.

```
MPI_Comm comm;
int gsize,*sendbuf;
int root, rbuf[100];
...
MPI_Comm_size(comm, &gsize);
sendbuf = (int *)malloc(gsize*100*sizeof(int));
...
MPI_Scatter(sendbuf, 100, MPI_INT, rbuf, 100, MPI_INT, root, comm);
```

**Example 6.12** The reverse of Example 6.5. The root process scatters sets of 100 ints to the other processes, but the sets of 100 are *stride ints* apart in the sending buffer. Requires use of MPI\_SCATTERV. Assume  $stride \ge 100$ . See Figure 6.10.

6.6. SCATTER 207




Figure 6.10: The root process scatters sets of 100 ints, moving by stride ints from send to send in the scatter.

```
MPI_Comm comm;
int gsize,*sendbuf;
int root, rbuf[100], i, *displs, *scounts;

...

MPI_Comm_size(comm, &gsize);
sendbuf = (int *)malloc(gsize*stride*sizeof(int));
...
displs = (int *)malloc(gsize*sizeof(int));
scounts = (int *)malloc(gsize*sizeof(int));
for (i=0; i<gsize; ++i) {
    displs[i] = i*stride;
    scounts[i] = 100;
}
MPI_Scatterv(sendbuf, scounts, displs, MPI_INT, rbuf, 100, MPI_INT,
    root, comm);</pre>
```

**Example 6.13** The reverse of Example 6.9. We have a varying stride between blocks at sending (root) side, at the receiving side we receive into the i-th column of a  $100 \times 150$  C array. See Figure 6.11.

```
MPI_Comm comm;
                                                                                35
int gsize,recvarray[100][150],*rptr;
                                                                                36
int root, *sendbuf, myrank, *stride;
                                                                                37
                                                                                38
MPI_Datatype rtype;
                                                                                39
int i, *displs, *scounts, offset;
                                                                                41
MPI_Comm_size(comm, &gsize);
                                                                                42
MPI_Comm_rank(comm, &myrank);
                                                                                43
                                                                                44
stride = (int *)malloc(gsize*sizeof(int));
                                                                                45
                                                                                46
/* stride[i] for i = 0 to gsize-1 is set somehow
 * sendbuf comes from elsewhere
 */
```




Figure 6.11: The root scatters blocks of 100-i ints into column i of a 100×150 C array. At the sending side, the blocks are stride[i] ints apart.

```
displs = (int *)malloc(gsize*sizeof(int));
scounts = (int *)malloc(gsize*sizeof(int));
offset = 0;
for (i=0; i<gsize; ++i) {
    displs[i] = offset;
    offset += stride[i];
    scounts[i] = 100 - i;
}
/* Create datatype for the column we are receiving
    */
MPI_Type_vector(100-myrank, 1, 150, MPI_INT, &rtype);
MPI_Type_commit(&rtype);
rptr = &recvarray[0][myrank];
MPI_Scatterv(sendbuf, scounts, displs, MPI_INT, rptr, 1, rtype, root, comm);</pre>
```

Gather-to-all

6 7

#### MPI\_ALLGATHER(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, comm) sendbuf IN starting address of send buffer (choice) IN sendcount number of elements in send buffer (non-negative integer) IN sendtype data type of send buffer elements (handle) OUT recvbuf address of receive buffer (choice) number of elements received from any process 12 IN recvcount 13 (non-negative integer) 14 IN recvtype data type of receive buffer elements (handle) 15 IN communicator (handle) comm 16 C binding 18 int MPI\_Allgather(const void \*sendbuf, int sendcount, 19 MPI\_Datatype sendtype, void \*recvbuf, int recvcount, 20 MPI\_Datatype recvtype, MPI\_Comm comm) 21 22 int MPI\_Allgather\_c(const void \*sendbuf, MPI\_Count sendcount, MPI\_Datatype sendtype, void \*recvbuf, MPI\_Count recvcount, MPI\_Datatype recvtype, MPI\_Comm comm) 26 Fortran 2008 binding MPI\_Allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, 27 comm, ierror) 28 TYPE(\*), DIMENSION(..), INTENT(IN) :: sendbuf 29 INTEGER, INTENT(IN) :: sendcount, recvcount 30 TYPE(MPI\_Datatype), INTENT(IN) :: sendtype, recvtype TYPE(\*), DIMENSION(..) :: recvbuf TYPE(MPI\_Comm), INTENT(IN) :: comm INTEGER, OPTIONAL, INTENT(OUT) :: ierror 34 35 MPI\_Allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, 36 comm, ierror) 37 TYPE(\*), DIMENSION(..), INTENT(IN) :: sendbuf INTEGER(KIND=MPI\_COUNT\_KIND), INTENT(IN) :: sendcount, recvcount TYPE(MPI\_Datatype), INTENT(IN) :: sendtype, recvtype TYPE(\*), DIMENSION(..) :: recvbuf TYPE(MPI\_Comm), INTENT(IN) :: comm 42 INTEGER, OPTIONAL, INTENT(OUT) :: ierror 43 Fortran binding 44 MPI\_ALLGATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE, 45 COMM, IERROR) <type> SENDBUF(\*), RECVBUF(\*) INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, IERROR

tl b

MPI\_ALLGATHER can be thought of as MPI\_GATHER, but where all processes receive the result, instead of just the root. The block of data sent from the j-th process is received by every process and placed in the j-th block of the buffer recvbuf.

The type signature associated with sendcount, sendtype, at a process must be equal to the type signature associated with recvcount, recvtype at any other process.

If comm is an intra-communicator, the outcome of a call to MPI\_ALLGATHER(...) is as if all processes executed n calls to

for  $\mathtt{root} = 0$ , ...,  $\mathtt{n-1}$ . The rules for correct usage of MPI\_ALLGATHER are easily found from the corresponding rules for MPI\_GATHER.

The "in place" option for intra-communicators is specified by passing the value MPI\_IN\_PLACE to the argument sendbuf at all processes. sendcount and sendtype are ignored. Then the input data of each process is assumed to be in the area where that process would receive its own contribution to the receive buffer.

If comm is an inter-communicator, then each process of one group (group A) contributes sendcount data items; these data are concatenated and the result is stored at each process in the other group (group B). Conversely the concatenation of the contributions of the processes in group B is stored at each process in group A. The send buffer arguments in group A must be consistent with the receive buffer arguments in group B, and vice versa.

Advice to users. The communication pattern of MPI\_ALLGATHER executed on an intercommunication domain need not be symmetric. The number of items sent by processes in group A (as specified by the arguments sendcount, sendtype in group A and the arguments recvcount, recvtype in group B), need not equal the number of items sent by processes in group B (as specified by the arguments sendcount, sendtype in group B and the arguments recvcount, recvtype in group A). In particular, one can move data in only one direction by specifying sendcount = 0 for the communication in the reverse direction. (End of advice to users.)

```
MPI_ALLGATHERV(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs, recvtype,
              comm)
  IN
           sendbuf
                                       starting address of send buffer (choice)
  IN
           sendcount
                                       number of elements in send buffer (non-negative
                                       integer)
  IN
           sendtype
                                       data type of send buffer elements (handle)
  OUT
           recvbuf
                                       address of receive buffer (choice)
                                       non-negative integer array (of length group size)
  IN
           recvcounts
                                       containing the number of elements that are received
                                       from each process
                                                                                        12
  IN
                                       integer array (of length group size). Entry i specifies
                                                                                        13
           displs
                                                                                        14
                                       the displacement (relative to recvbuf) at which to
                                                                                        15
                                       place the incoming data from process i
                                                                                        16
  IN
                                       data type of receive buffer elements (handle)
           recvtype
  IN
                                       communicator (handle)
           comm
                                                                                        18
                                                                                        19
C binding
                                                                                        20
int MPI_Allgatherv(const void *sendbuf, int sendcount,
                                                                                        21
              MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
                                                                                        22
               const int displs[], MPI_Datatype recvtype, MPI_Comm comm)
                                                                                        23
int MPI_Allgatherv_c(const void *sendbuf, MPI_Count sendcount,
              MPI_Datatype sendtype, void *recvbuf,
                                                                                        26
               const MPI_Count recvcounts[], const MPI_Aint displs[],
                                                                                        27
              MPI_Datatype recvtype, MPI_Comm comm)
                                                                                        28
Fortran 2008 binding
                                                                                        29
MPI_Allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
                                                                                        30
              recvtype, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    INTEGER, INTENT(IN) :: sendcount, recvcounts(*), displs(*)
                                                                                        33
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                        34
    TYPE(*), DIMENSION(..) :: recvbuf
                                                                                        35
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                        36
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                        37
MPI_Allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
              recvtype, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcounts(*)
                                                                                        42
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                        43
    TYPE(*), DIMENSION(..) :: recvbuf
                                                                                        44
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: displs(*)
                                                                                        45
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                        46
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
```

```
MPI_ALLGATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS,

RECVTYPE, COMM, IERROR)

<type> SENDBUF(*), RECVBUF(*)

INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, COMM,

IERROR
```

MPI\_ALLGATHERV can be thought of as MPI\_GATHERV, but where all processes receive the result, instead of just the root. The block of data sent from the j-th process is received by every process and placed in the j-th block of the buffer recvbuf. These blocks need not all be the same size.

The type signature associated with sendcount, sendtype, at process j must be equal to the type signature associated with recvcounts[j], recvtype at any other process.

If comm is an intra-communicator, the outcome is as if all processes executed calls to

for root = 0, ..., n-1. The rules for correct usage of MPI\_ALLGATHERV are easily found from the corresponding rules for MPI\_GATHERV.

The "in place" option for intra-communicators is specified by passing the value MPI\_IN\_PLACE to the argument sendbuf at all processes. In such a case, sendcount and sendtype are ignored, and the input data of each process is assumed to be in the area where that process would receive its own contribution to the receive buffer.

If comm is an inter-communicator, then each process of one group (group A) contributes sendcount data items; these data are concatenated and the result is stored at each process in the other group (group B). Conversely the concatenation of the contributions of the processes in group B is stored at each process in group A. The send buffer arguments in group A must be consistent with the receive buffer arguments in group B, and vice versa.

## 6.7.1 Example using MPI\_ALLGATHER

The example in this section uses intra-communicators.

**Example 6.14** The all-gather version of Example 6.2. Using MPI\_ALLGATHER, we will gather 100 ints from every process in the group to every process.

```
MPI_Comm comm;
int gsize,sendarray[100];
int *rbuf;
...
MPI_Comm_size(comm, &gsize);
rbuf = (int *)malloc(gsize*100*sizeof(int));
MPI_Allgather(sendarray, 100, MPI_INT, rbuf, 100, MPI_INT, comm);
```

After the call, every process has the group-wide concatenation of the sets of data.

#### 6.8 All-to-All Scatter/Gather MPI\_ALLTOALL(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, comm) sendbuf IN starting address of send buffer (choice) IN sendcount number of elements sent to each process (non-negative integer) IN sendtype data type of send buffer elements (handle) OUT recvbuf address of receive buffer (choice) IN number of elements received from any process 12 recvcount 13 (non-negative integer) 14 data type of receive buffer elements (handle) IN recvtype 15 IN communicator (handle) comm 16 C binding 18 int MPI\_Alltoall(const void \*sendbuf, int sendcount, MPI\_Datatype sendtype, 19 void \*recvbuf, int recvcount, MPI\_Datatype recvtype, 20 MPI\_Comm comm) 21 22 int MPI\_Alltoall\_c(const void \*sendbuf, MPI\_Count sendcount, 23 MPI\_Datatype sendtype, void \*recvbuf, MPI\_Count recvcount, MPI\_Datatype recvtype, MPI\_Comm comm) 26 Fortran 2008 binding MPI\_Alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, 27 comm, ierror) 28 TYPE(\*), DIMENSION(..), INTENT(IN) :: sendbuf 29 INTEGER, INTENT(IN) :: sendcount, recvcount 30 TYPE(MPI\_Datatype), INTENT(IN) :: sendtype, recvtype TYPE(\*), DIMENSION(..) :: recvbuf TYPE(MPI\_Comm), INTENT(IN) :: comm INTEGER, OPTIONAL, INTENT(OUT) :: ierror 34 35 MPI\_Alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, 36 comm, ierror) 37 TYPE(\*), DIMENSION(..), INTENT(IN) :: sendbuf INTEGER(KIND=MPI\_COUNT\_KIND), INTENT(IN) :: sendcount, recvcount TYPE(MPI\_Datatype), INTENT(IN) :: sendtype, recvtype TYPE(\*), DIMENSION(..) :: recvbuf TYPE(MPI\_Comm), INTENT(IN) :: comm 42 INTEGER, OPTIONAL, INTENT(OUT) :: ierror 43 44 Fortran binding MPI\_ALLTOALL(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE, 45

#### **Unofficial Draft for Comment Only**

INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, IERROR

COMM, IERROR)
<type> SENDBUF(\*), RECVBUF(\*)

sene

 MPI\_ALLTOALL is an extension of MPI\_ALLGATHER to the case where each process sends distinct data to each of the receivers. The j-th block sent from process i is received by process j and is placed in the i-th block of recvbuf.

The type signature associated with sendcount, sendtype, at a process must be equal to the type signature associated with recvcount, recvtype at any other process. This implies that the amount of data sent must be equal to the amount of data received, pairwise between every pair of processes. As usual, however, the type maps may be different.

If comm is an intra-communicator, the outcome is as if each process executed a send to each process (itself included) with a call to,

r

MPI\_Send(sendbuf+i· sendcount· extent(sendtype),sendcount,sendtype,i, ...),

and a receive from every other process with a call to,

MPI\_Recv(recvbuf+i· recvcount· extent(recvtype),recvcount,recvtype,i,...).

All arguments on all processes are significant. The argument comm must have identical values on all processes.

The "in place" option for intra-communicators is specified by passing MPI\_IN\_PLACE to the argument sendbuf at *all* processes. In such a case, sendcount and sendtype are ignored. The data to be sent is taken from the recvbuf and replaced by the received data. Data sent and received must have the same type map as specified by recvcount and recvtype.

Rationale. For large MPI\_ALLTOALL instances, allocating both send and receive buffers may consume too much memory. The "in place" option effectively halves the application memory consumption and is useful in situations where the data to be sent will not be used by the sending process after the MPI\_ALLTOALL exchange (e.g., in parallel Fast Fourier Transforms). (End of rationale.)

Advice to implementors. Users may opt to use the "in place" option in order to conserve memory. Quality MPI implementations should thus strive to minimize system buffering. (End of advice to implementors.)

If comm is an inter-communicator, then the outcome is as if each process in group A sends a message to each process in group B, and vice versa. The j-th send buffer of process i in group A should be consistent with the i-th receive buffer of process j in group B, and vice versa.

Advice to users. When a complete exchange is executed on an intercommunication domain, then the number of data items sent from processes in group A to processes in group B need not equal the number of items sent in the reverse direction. In particular, one can have unidirectional communication by specifying sendcount = 0 in the reverse direction. (End of advice to users.)

MPI_ALLT(	OALLV(sendbuf, sendcounts, so recvtype, comm)	lispls, sendtype, recvbuf, recvcounts, rdispls,	1 2		
IN	sendbuf	starting address of send buffer (choice)	3		
IN	sendcounts	non-negative integer array (of length group size) specifying the number of elements to send to each rank	4 5 6 7		
IN	sdispls	integer array (of length group size). Entry j specifies the displacement (relative to sendbuf) from which to take the outgoing data destined for process j	8 9 10		
IN	sendtype	data type of send buffer elements (handle)	11		
OUT	recvbuf	address of receive buffer (choice)	12 13		
IN	recvcounts	non-negative integer array (of length group size) specifying the number of elements that can be received from each rank	14 15 16 17		
IN	rdispls	integer array (of length group size). Entry i specifies the displacement (relative to recvbuf) at which to place the incoming data from process i	18 19 20		
IN	recvtype	data type of receive buffer elements (handle)	21		
IN	comm	communicator (handle)	22		
			23		
C binding			24 25		
int MPI_A.		<pre>lbuf, const int sendcounts[], MPI_Datatype sendtype, void *recvbuf,</pre>	26		
			27		
	<pre>const int recvcounts[], const int rdispls[], MPI_Datatype recvtype, MPI_Comm comm)</pre>				
int MPT Δ	lltoally c(const void *se	endbuf, const MPI_Count sendcounts[],	29 30		
ino mi_n.		Ls[], MPI_Datatype sendtype,	31		
	-	MPI_Count recvcounts[],	32		
	const MPI_Aint rdisp	ls[], MPI_Datatype recvtype,	33		
MPI_Comm comm)					
Fortran 2	008 binding		35		
MPI_Allto	allv(sendbuf, sendcounts,	sdispls, sendtype, recvbuf, recvcounts,	36 37		
rdispls, recvtype, comm, ierror)					
TYPE(*), DIMENSION(), INTENT(IN) :: sendbuf					
<pre>INTEGER, INTENT(IN) :: sendcounts(*), sdispls(*), recvcounts(*),</pre>					
rdispls(*) TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype					
TYPE(*), DIMENSION() :: recvbuf					
TYPE(MPI_Comm), INTENT(IN) :: comm					
INTEGER, OPTIONAL, INTENT(OUT) :: ierror					
MPI_Alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf, recvcounts,					
rdispls, recvtype, comm, ierror)					
TYPE(*), DIMENSION(), INTENT(IN) :: sendbuf					

15

16

17

18

19

20

21

22

23

24

25

26

27 28

29 30

31 32

33

34

35

36

37

38

39 40

41

42

43

44

45

46

47

```
INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcounts(*),
2
                   recvcounts(*)
3
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: sdispls(*), rdispls(*)
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
5
         TYPE(*), DIMENSION(..) :: recvbuf
6
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
9
    MPI_ALLTOALLV(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE, RECVBUF, RECVCOUNTS,
10
                  RDISPLS, RECVTYPE, COMM, IERROR)
11
         <type> SENDBUF(*), RECVBUF(*)
12
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*),
13
                   RECVTYPE, COMM, IERROR
14
```

MPI\_ALLTOALLV adds flexibility to MPI\_ALLTOALL in that the location of data for the send is specified by sdispls and the location of the placement of the data on the receive side is specified by rdispls.

If comm is an intra-communicator, then the j-th block sent from process i is received by process j and is placed in the i-th block of recvbuf. These blocks need not all have the same size.

The type signature associated with sendcounts[i], sendtype at process i must be equal to the type signature associated with recvounts[i], recvtype at process j. This implies that the amount of data sent must be equal to the amount of data received, pairwise between every pair of processes. Distinct type maps between sender and receiver are still allowed.

The outcome is as if each process sent a message to every other process with,

```
MPI_Send(sendbuf+sdispls[i] extent(sendtype),sendcounts[i],sendtype,i,...),
and received a message from every other process with a call to
   MPI_Recv(recvbuf+rdispls[i] extent(recvtype),recvcounts[i],recvtype,i,...).
```

All arguments on all processes are significant. The argument comm must have identical values on all processes.

The "in place" option for intra-communicators is specified by passing MPI\_IN\_PLACE to the argument sendbuf at all processes. In such a case, sendcounts, sdispls and sendtype are ignored. The data to be sent is taken from the recybuf and replaced by the received data. Data sent and received must have the same type map as specified by the recvounts array and the recvtype, and is taken from the locations of the receive buffer specified by rdispls.

Specifying the "in place" option (which must be given on all Advice to users. processes) implies that the same amount and type of data is sent and received between any two processes in the group of the communicator. Different pairs of processes can exchange different amounts of data. Users must ensure that recvcounts[j] and recvtype on process i match recvcounts[i] and recvtype on process j. This symmetric exchange can be useful in applications where the data to be sent will not be used by the sending process after the MPI\_ALLTOALLV exchange. (End of advice to users.)

If comm is an inter-communicator, then the outcome is as if each process in group A sends a message to each process in group B, and vice versa. The j-th send buffer of process i in group A should be consistent with the i-th receive buffer of process j in group B, and vice versa.

Rationale. The definitions of MPI\_ALLTOALL and MPI\_ALLTOALLV give as much flexibility as one would achieve by specifying n independent, point-to-point communications, with two exceptions: all messages use the same datatype, and messages are scattered from (or gathered to) sequential storage. (*End of rationale*.)

Advice to implementors. Although the discussion of collective communication in terms of point-to-point operation implies that each message is transferred directly from sender to receiver, implementations may use a tree communication pattern. Messages can be forwarded by intermediate nodes where they are split (for scatter) or concatenated (for gather), if this is more efficient. (End of advice to implementors.)

MPI\_ALLTOALLW(sendbuf, sendcounts, sdispls, sendtypes, recvbuf, recvcounts, rdispls, recvtypes, comm)

IN	sendbuf	starting address of send buffer (choice)
IN	sendcounts	non-negative integer array (of length group size) specifying the number of elements to send to each rank
IN	sdispls	integer array (of length group size). Entry j specifies the displacement in bytes (relative to sendbuf) from which to take the outgoing data destined for process j (array of integers)
IN	sendtypes	array of datatypes (of length group size). Entry j specifies the type of data to send to process j (array of handles)
OUT	recvbuf	address of receive buffer (choice)
ÎN	recvcounts	non-negative integer array (of length group size) specifying the number of elements that can be received from each rank
IN	rdispls	integer array (of length group size). Entry i specifies the displacement in bytes (relative to recvbuf) at which to place the incoming data from process i (array of integers)
IN	recvtypes	array of datatypes (of length group size). Entry i specifies the type of data received from process i (array of handles)
IN	comm	communicator (handle)

C binding

44

45

46

47

48

```
1
     int MPI_Alltoallw(const void *sendbuf, const int sendcounts[],
2
                   const int sdispls[], const MPI_Datatype sendtypes[],
3
                   void *recvbuf, const int recvcounts[], const int rdispls[],
4
                   const MPI_Datatype recvtypes[], MPI_Comm comm)
5
     int MPI_Alltoallw_c(const void *sendbuf, const MPI_Count sendcounts[],
6
                   const MPI_Aint sdispls[], const MPI_Datatype sendtypes[],
7
                   void *recvbuf, const MPI_Count recvcounts[],
                   const MPI_Aint rdispls[], const MPI_Datatype recvtypes[],
9
                   MPI_Comm comm)
10
11
     Fortran 2008 binding
12
     MPI_Alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf, recvcounts,
13
                   rdispls, recvtypes, comm, ierror)
14
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
15
         INTEGER, INTENT(IN) :: sendcounts(*), sdispls(*), recvcounts(*),
16
                   rdispls(*)
17
         TYPE(MPI_Datatype), INTENT(IN) :: sendtypes(*), recvtypes(*)
18
         TYPE(*), DIMENSION(..) :: recvbuf
19
         TYPE(MPI_Comm), INTENT(IN) :: comm
20
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
21
     MPI_Alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf, recvcounts,
22
                   rdispls, recvtypes, comm, ierror)
23
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
24
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcounts(*),
                   recvcounts(*)
26
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: sdispls(*), rdispls(*)
27
         TYPE(MPI_Datatype), INTENT(IN) :: sendtypes(*), recvtypes(*)
28
         TYPE(*), DIMENSION(..) :: recvbuf
29
         TYPE(MPI_Comm), INTENT(IN) :: comm
30
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
31
32
     Fortran binding
33
     MPI_ALLTOALLW(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPES, RECVBUF, RECVCOUNTS,
34
                   RDISPLS, RECVTYPES, COMM, IERROR)
35
         <type> SENDBUF(*), RECVBUF(*)
36
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPES(*), RECVCOUNTS(*),
37
                   RDISPLS(*), RECVTYPES(*), COMM, IERROR
38
         MPI_ALLTOALLW is the most general form of complete exchange. Like
39
     MPI_TYPE_CREATE_STRUCT, the most general type constructor, MPI_ALLTOALLW al-
40
41
```

lows separate specification of count, displacement and datatype. In addition, to allow maximum flexibility, the displacement of blocks within the send and receive buffers is specified in bytes.

If comm is an intra-communicator, then the j-th block sent from process i is received by process j and is placed in the i-th block of recvbuf. These blocks need not all have the same size.

The type signature associated with sendcounts[i], sendtypes[i] at process i must be equal to the type signature associated with recvcounts[i], recvtypes[i] at process j. This implies that

the amount of data sent must be equal to the amount of data received, pairwise between every pair of processes. Distinct type maps between sender and receiver are still allowed.

The outcome is as if each process sent a message to every other process with

```
MPI_Send(sendbuf+sdispls[i],sendcounts[i],sendtypes[i],i,...),
```

and received a message from every other process with a call to

```
MPI_Recv(recvbuf+rdispls[i],recvcounts[i],recvtypes[i],i,...).
```

All arguments on all processes are significant. The argument comm must describe the same communicator on all processes.

Like for MPI\_ALLTOALLV, the "in place" option for intra-communicators is specified by passing MPI\_IN\_PLACE to the argument sendbuf at *all* processes. In such a case, sendcounts, sdispls and sendtypes are ignored. The data to be sent is taken from the received and replaced by the received data. Data sent and received must have the same type map as specified by the receive and receives arrays, and is taken from the locations of the receive buffer specified by rdispls.

If comm is an inter-communicator, then the outcome is as if each process in group A sends a message to each process in group B, and vice versa. The j-th send buffer of process i in group A should be consistent with the i-th receive buffer of process j in group B, and vice versa.

Rationale. The MPI\_ALLTOALLW function generalizes several MPI functions by carefully selecting the input arguments. For example, by making all but one process have sendcounts[i] = 0, this achieves an MPI\_SCATTERW function. (End of rationale.)

# 6.9 Global Reduction Operations

The functions in this section perform a global reduce operation (for example sum, maximum, and logical and) across all members of a group. The reduction operation can be either one of a predefined list of operations, or a user-defined operation. The global reduction functions come in several flavors: a reduce that returns the result of the reduction to one member of a group, an all-reduce that returns this result to all members of a group, and two scan (parallel prefix) operations. In addition, a reduce-scatter operation combines the functionality of a reduce and of a scatter operation.

```
1
     6.9.1 Reduce
2
3
4
     MPI_REDUCE(sendbuf, recvbuf, count, datatype, op, root, comm)
5
                sendbuf
       IN
                                           address of send buffer (choice)
6
       OUT
                recvbuf
                                           address of receive buffer (choice, significant only at
7
                                           root)
9
       IN
                count
                                           number of elements in send buffer (non-negative
10
                                           integer)
11
                                           data type of elements of send buffer (handle)
       IN
                datatype
12
       IN
                                           reduce operation (handle)
13
                op
14
       IN
                                           rank of root process (integer)
                root
15
       IN
                                            communicator (handle)
                comm
16
17
     C binding
18
     int MPI_Reduce(const void *sendbuf, void *recvbuf, int count,
19
                    MPI_Datatype datatype, MPI_Op op, int root, MPI_Comm comm)
20
21
     int MPI_Reduce_c(const void *sendbuf, void *recvbuf, MPI_Count count,
22
                    MPI_Datatype datatype, MPI_Op op, int root, MPI_Comm comm)
23
     Fortran 2008 binding
24
     MPI_Reduce(sendbuf, recvbuf, count, datatype, op, root, comm, ierror)
25
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
26
         TYPE(*), DIMENSION(..) :: recvbuf
27
         INTEGER, INTENT(IN) :: count, root
28
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
29
         TYPE(MPI_Op), INTENT(IN) :: op
30
         TYPE(MPI_Comm), INTENT(IN) :: comm
31
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
32
33
     MPI_Reduce(sendbuf, recvbuf, count, datatype, op, root, comm, ierror)
34
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
35
         TYPE(*), DIMENSION(..) :: recvbuf
36
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
37
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
         INTEGER, INTENT(IN) :: root
         TYPE(MPI_Comm), INTENT(IN) :: comm
41
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
42
     Fortran binding
43
     MPI_REDUCE(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, ROOT, COMM, IERROR)
44
          <type> SENDBUF(*), RECVBUF(*)
45
          INTEGER COUNT, DATATYPE, OP, ROOT, COMM, IERROR
46
```

If comm is an intra-communicator, MPI\_REDUCE combines the elements provided in the input buffer of each process in the group, using the operation op, and returns the combined value in the output buffer of the process with rank root. The input buffer is defined by the arguments sendbuf, count and datatype; the output buffer is defined by the arguments recvbuf, count and datatype; both have the same number of elements, with the same type. The routine is called by all group members using the same arguments for count, datatype, op, root and comm. Thus, all processes provide input buffers of the same length, with elements of the same type as the output buffer at the root. Each process can provide one element, or a sequence of elements, in which case the combine operation is executed element-wise on each entry of the sequence. For example, if the operation is MPI\_MAX and the send buffer contains two elements that are floating point numbers (count = 2 and datatype = MPI\_FLOAT), then recvbuf(1) =  $global \max(sendbuf(1))$  and  $recvbuf(2) = global \max(sendbuf(2))$ .

Section 6.9.2, lists the set of predefined operations provided by MPI. That section also enumerates the datatypes to which each operation can be applied.

In addition, users may define their own operations that can be overloaded to operate on several datatypes, either basic or derived. This is further explained in Section 6.9.5.

The operation op is always assumed to be associative. All predefined operations are also assumed to be commutative. Users may define operations that are assumed to be associative, but not commutative. The "canonical" evaluation order of a reduction is determined by the ranks of the processes in the group. However, the implementation can take advantage of associativity, or associativity and commutativity in order to change the order of evaluation. This may change the result of the reduction for operations that are not strictly associative and commutative, such as floating point addition.

Advice to implementors. It is strongly recommended that MPI\_REDUCE be implemented so that the same result be obtained whenever the function is applied on the same arguments, appearing in the same order. Note that this may prevent optimizations that take advantage of the physical location of ranks. (End of advice to implementors.)

Advice to users. Some applications may not be able to ignore the non-associative nature of floating-point operations or may use user-defined operations (see Section 6.9.5) that require a special reduction order and cannot be treated as associative. Such applications should enforce the order of evaluation explicitly. For example, in the case of operations that require a strict left-to-right (or right-to-left) evaluation order, this could be done by gathering all operands at a single process (e.g., with MPI\_GATHER), applying the reduction operation in the desired order (e.g., with MPI\_REDUCE\_LOCAL), and if needed, broadcast or scatter the result to the other processes (e.g., with MPI\_BCAST). (End of advice to users.)

The datatype argument of MPI\_REDUCE must be compatible with op. Predefined operators work only with the MPI types listed in Section 6.9.2 and Section 6.9.4. Furthermore, the datatype and op given for predefined operators must be the same on all processes.

Note that it is possible for users to supply different user-defined operations to MPI\_REDUCE in each process. MPI does not define which operations are used on which operands in this case. User-defined operators may operate on general, derived datatypes. In this case, each argument that the reduce operation is applied to is one element described

3

5

6

9

10

11

12

13

14

15

16

17

18 19

20 21

22

23

24

25 26

27 28

29

30

31

32

34

35

36

37

38

39

40

41

42

43

44 45 46

47

by such a datatype, which may contain several basic values. This is further explained in Section 6.9.5.

Advice to users. Users should make no assumptions about how MPI\_REDUCE is implemented. It is safest to ensure that the same function is passed to MPI\_REDUCE by each process. (End of advice to users.)

Overlapping datatypes are permitted in "send" buffers. Overlapping datatypes in "receive" buffers are erroneous and may give unpredictable results.

The "in place" option for intra-communicators is specified by passing the value MPI\_IN\_PLACE to the argument sendbuf at the root. In such a case, the input data is taken at the root from the receive buffer, where it will be replaced by the output data.

If comm is an inter-communicator, then the call involves all processes in the inter-communicator, but with one group (group A) defining the root process. All processes in the other group (group B) pass the same value in argument root, which is the rank of the root in group A. The root passes the value MPI\_ROOT in root. All other processes in group A pass the value MPI\_PROC\_NULL in root. Only send buffer arguments are significant in group B and only receive buffer arguments are significant at the root.

## 6.9.2 Predefined Reduction Operations

The following predefined operations are supplied for MPI\_REDUCE and related functions MPI\_ALLREDUCE, MPI\_REDUCE\_SCATTER\_BLOCK, MPI\_REDUCE\_SCATTER, MPI\_SCAN, MPI\_EXSCAN, all nonblocking variants of those (see Section 6.12), and MPI\_REDUCE\_LOCAL. These operations are invoked by placing the following in op.

Name Meaning MPI\_MAX maximum MPI\_MIN minimum MPI\_SUM  $\operatorname{sum}$ MPI\_PROD product MPI\_LAND logical and MPI\_BAND bit-wise and logical or MPI\_LOR MPI\_BOR bit-wise or MPI\_LXOR logical exclusive or (xor) MPI\_BXOR bit-wise exclusive or (xor) MPI\_MAXLOC max value and location MPI\_MINLOC min value and location

The two operations MPI\_MINLOC and MPI\_MAXLOC are discussed separately in Section 6.9.4. For the other predefined operations, we enumerate below the allowed combinations of op and datatype arguments. First, define groups of MPI basic datatypes in the following way.

C integer: MPI\_INT, MPI\_LONG, MPI\_SHORT, MPI\_UNSIGNED, SHORT, MPI\_UNSIGNED,

	MPI_UNSIGNED_LONG,	1
	MPI_LONG_LONG_INT,	2
	MPI_LONG_LONG (as synonym),	3
	MPI_UNSIGNED_LONG_LONG,	4
	MPI_SIGNED_CHAR,	5
	MPI_UNSIGNED_CHAR,	6
	MPI_INT8_T, MPI_INT16_T,	7
	MPI_INT32_T, MPI_INT64_T,	8
	MPI_UINT8_T, MPI_UINT16_T,	9
	$MPI\_UINT32\_T$ , and $MPI\_UINT64\_T$	10
Fortran integer:	MPI_INTEGER	11
	and handles returned from	12
	MPI_TYPE_CREATE_F90_INTEGER	13
	and, if available, MPI_INTEGER1,	14
	MPI_INTEGER2, MPI_INTEGER4,	15
	MPI_INTEGER8, and MPI_INTEGER16	16
Floating point:	MPI_FLOAT, MPI_DOUBLE, MPI_REAL,	17
	MPI_DOUBLE_PRECISION,	18
	MPI_LONG_DOUBLE,	19
	and handles returned from	20
	MPI_TYPE_CREATE_F90_REAL	21
	and, if available, MPI_REAL2,	22
	MPI_REAL4, MPI_REAL8, and MPI_REAL16	23
Logical:	MPI_LOGICAL, MPI_C_BOOL,	24
	and MPI_CXX_BOOL	25
Complex:	MPI_COMPLEX, MPI_C_COMPLEX,	26
	MPI_C_FLOAT_COMPLEX (as synonym),	27
	MPI_C_DOUBLE_COMPLEX,	28
	MPI_C_LONG_DOUBLE_COMPLEX,	29
	MPI_CXX_FLOAT_COMPLEX,	30
	MPI_CXX_DOUBLE_COMPLEX, MPI_CXX_LONG_DOUBLE_COMPLEX,	
	and handles returned from	31
	MPI_TYPE_CREATE_F90_COMPLEX	32
	and, if available, MPI_DOUBLE_COMPLEX,	33
	MPI_COMPLEX4, MPI_COMPLEX8,	34
	MPI_COMPLEX16, and MPI_COMPLEX32	35
Byte:	MPI_BYTE	36
Multi-language types:	MPI_AINT, MPI_OFFSET, and MPI_COUNT	37
		38
Now, the valid datatypes for each	operation are specified below.	39
<b>*</b>		40
	411 1.77	41
Op	Allowed Types	42
MDI MAY MDI MIN		43
MPI_MAX, MPI_MIN	C integer, Fortran integer, Floating point,	44
MDI CIIM MDI DDOD	Multi-language types	45
MPI_SUM, MPI_PROD	C integer, Fortran integer, Floating point, Complex,	46
MDI LAND MDI LOD MDI LVOD	Multi-language types	47
MPI_LAND, MPI_LOR, MPI_LXOR	C integer, Logical	48

**END** 

```
1
       MPI_BAND, MPI_BOR, MPI_BXOR
                                             C integer, Fortran integer, Byte, Multi-language types
2
          These operations together with all listed datatypes are valid in all supported program-
3
     ming languages, see also Reduce Operations on page 834 in Section 19.3.6.
          The following examples use intra-communicators.
5
6
     Example 6.15 A routine that computes the dot product of two vectors that are distributed
7
     across a group of processes and returns the answer at node zero.
8
9
     SUBROUTINE PAR_BLAS1(m, a, b, c, comm)
     REAL a(m), b(m)
10
                              ! local slice of array
11
     REAL c
                              ! result (at node zero)
12
     REAL sum
13
     INTEGER m, comm, i, ierr
14
15
     ! local sum
16
     sum = 0.0
17
     DO i = 1, m
18
         sum = sum + a(i)*b(i)
19
     END DO
20
21
     ! global sum
     CALL MPI_REDUCE(sum, c, 1, MPI_REAL, MPI_SUM, 0, comm, ierr)
22
23
     RETURN
24
     END
25
26
     Example 6.16 A routine that computes the product of a vector and an array that are
27
     distributed across a group of processes and returns the answer at node zero.
28
     SUBROUTINE PAR_BLAS2(m, n, a, b, c, comm)
29
30
                             ! local slice of array
     REAL a(m), b(m,n)
31
     REAL c(n)
                              ! result
32
     REAL sum(n)
33
     INTEGER n, comm, i, j, ierr
34
35
     ! local sum
36
     DO j=1,n
37
        sum(j) = 0.0
38
        DO i=1,m
39
            sum(j) = sum(j) + a(i)*b(i,j)
40
        END DO
41
     END DO
42
43
     ! global sum
44
     CALL MPI_REDUCE(sum, c, n, MPI_REAL, MPI_SUM, 0, comm, ierr)
45
46
     ! return result at node zero (and garbage at the other nodes)
47
     RETURN
```

### 6.9.3 Signed Characters and Reductions

The types MPI\_SIGNED\_CHAR and MPI\_UNSIGNED\_CHAR can be used in reduction operations. MPI\_CHAR, MPI\_WCHAR, and MPI\_CHARACTER (which represent printable characters) cannot be used in reduction operations. In a heterogeneous environment, MPI\_CHAR, MPI\_WCHAR, and MPI\_CHARACTER will be translated so as to preserve the printable character, whereas MPI\_SIGNED\_CHAR and MPI\_UNSIGNED\_CHAR will be translated so as to preserve the integer value.

Advice to users. The types MPI\_CHAR, MPI\_WCHAR, and MPI\_CHARACTER are intended for characters, and so will be translated to preserve the printable representation, rather than the integer value, if sent between machines with different character codes. The types MPI\_SIGNED\_CHAR and MPI\_UNSIGNED\_CHAR should be used in C if the integer value should be preserved. (*End of advice to users*.)

#### 6.9.4 MINLOC and MAXLOC

The operator MPI\_MINLOC is used to compute a global minimum and also an index attached to the minimum value. MPI\_MAXLOC similarly computes a global maximum and index. One application of these is to compute a global minimum (maximum) and the rank of the process containing this value.

The operation that defines MPI\_MAXLOC is:

$$\left(\begin{array}{c} u\\i \end{array}\right) \circ \left(\begin{array}{c} v\\j \end{array}\right) = \left(\begin{array}{c} w\\k \end{array}\right)$$

where

$$w = \max(u, v)$$

and

$$k = \begin{cases} i & \text{if } u > v \\ \min(i, j) & \text{if } u = v \\ j & \text{if } u < v \end{cases}$$

MPI\_MINLOC is defined similarly:

$$\left(\begin{array}{c} u\\i \end{array}\right) \circ \left(\begin{array}{c} v\\j \end{array}\right) = \left(\begin{array}{c} w\\k \end{array}\right)$$

where

$$w = \min(u, v)$$

and

$$k = \begin{cases} i & \text{if } u < v \\ \min(i, j) & \text{if } u = v \\ j & \text{if } u > v \end{cases}$$

Both operations are associative and commutative. Note that if MPI\_MAXLOC is applied to reduce a sequence of pairs  $(u_0, 0), (u_1, 1), \ldots, (u_{n-1}, n-1)$ , then the value returned is

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

(u,r), where  $u=\max_i u_i$  and r is the index of the first global maximum in the sequence. Thus, if each process supplies a value and its rank within the group, then a reduce operation with  $\mathsf{op} = \mathsf{MPI\_MAXLOC}$  will return the maximum value and the rank of the first process with that value. Similarly,  $\mathsf{MPI\_MINLOC}$  can be used to return a minimum and its index. More generally,  $\mathsf{MPI\_MINLOC}$  computes a  $\mathit{lexicographic minimum}$ , where elements are ordered according to the first component of each pair, and ties are resolved according to the second component.

The reduce operation is defined to operate on arguments that consist of a pair: value and index. For both Fortran and C, types are provided to describe the pair. The potentially mixed-type nature of such arguments is a problem in Fortran. The problem is circumvented, for Fortran, by having the MPI-provided type consist of a pair of the same type as value, and coercing the index to this type also. In C, the MPI-provided pair type has distinct types and the index is an int.

In order to use MPI\_MINLOC and MPI\_MAXLOC in a reduce operation, one must provide a datatype argument that represents a pair (value and index). MPI provides nine such predefined datatypes. The operations MPI\_MAXLOC and MPI\_MINLOC can be used with each of the following datatypes.

```
Fortran:
19
       Name
                                              Description
20
                                              pair of REALs
       MPI_2REAL
21
       MPI_2DOUBLE_PRECISION
                                              pair of DOUBLE PRECISION variables
22
                                              pair of INTEGERS
       MPI_2INTEGER
23
24
25
26
       C:
27
       Name
                                             Description
       MPI_FLOAT_INT
                                              float and int
28
       MPI_DOUBLE_INT
                                              double and int
29
       MPI_LONG_INT
                                              long and int
30
       MPI_2INT
                                              pair of int
31
                                              short and int
       MPI_SHORT_INT
32
       MPI_LONG_DOUBLE_INT
                                              long double and int
33
34
          The datatype MPI_2REAL is as if defined by the following (see Section 5.1).
35
36
     MPI_Type_contiguous(2, MPI_REAL, MPI_2REAL);
37
38
          Similar statements apply for MPI_2INTEGER, MPI_2DOUBLE_PRECISION, and MPI_2INT.
39
          The datatype MPI_SHORT_INT is as if defined by the following sequence of instructions.
     struct mystruct {
41
          short val;
42
          int rank;
43
     };
44
     type[0] = MPI_SHORT;
45
     type[1] = MPI_INT;
46
     disp[0] = 0;
47
     disp[1] = offsetof(struct mystruct, rank);
48
```

```
block[0] = 1;
block[1] = 1;
MPI_Type_create_struct(2, block, disp, type, MPI_SHORT_INT);
Similar statements apply for MPI_FLOAT_INT, MPI_LONG_INT and MPI_DOUBLE_INT.
    The following examples use intra-communicators.
Example 6.17 Each process has an array of 30 doubles, in C. For each of the 30 locations,
compute the value and rank of the process containing the largest value.
                                                                                       11
    /* each process has an array of 30 double: ain[30]
                                                                                       12
                                                                                       13
    double ain[30], aout[30];
                                                                                       14
    int ind[30];
                                                                                       15
    struct {
                                                                                       16
        double val;
                                                                                       17
        int
               rank;
                                                                                       18
    } in[30], out[30];
                                                                                       19
    int i, myrank, root;
                                                                                       20
                                                                                       21
    MPI_Comm_rank(comm, &myrank);
                                                                                       22
    for (i=0; i<30; ++i) {
                                                                                       23
        in[i].val = ain[i];
                                                                                       24
        in[i].rank = myrank;
    }
                                                                                       26
    MPI_Reduce(in, out, 30, MPI_DOUBLE_INT, MPI_MAXLOC, root, comm);
                                                                                       27
    /* At this point, the answer resides on process root
                                                                                       28
     */
                                                                                       29
    if (myrank == root) {
                                                                                       30
        /* read ranks out
        for (i=0; i<30; ++i) {
                                                                                       33
             aout[i] = out[i].val;
                                                                                       34
             ind[i] = out[i].rank;
                                                                                       35
                                                                                       36
    }
                                                                                       37
Example 6.18 Same example, in Fortran.
                                                                                       39
                                                                                       42
! each process has an array of 30 double: ain(30)
                                                                                       43
DOUBLE PRECISION ain(30), aout(30)
                                                                                       44
INTEGER ind(30)
                                                                                       45
DOUBLE PRECISION in(2,30), out(2,30)
                                                                                       46
INTEGER i, myrank, root, ierr
```

```
1
     CALL MPI_COMM_RANK(comm, myrank, ierr)
2
     D0 i=1,30
3
        in(1,i) = ain(i)
4
        in(2,i) = myrank
                              ! myrank is coerced to a double
5
     END DO
6
7
     CALL MPI_REDUCE(in, out, 30, MPI_2DOUBLE_PRECISION, MPI_MAXLOC, root,&
8
                      comm, ierr)
9
     ! At this point, the answer resides on process root
10
11
     IF (myrank .EQ. root) THEN
12
        ! read ranks out
13
        D0 i=1,30
14
           aout(i) = out(1,i)
15
           ind(i) = out(2,i) ! rank is coerced back to an integer
16
        END DO
17
     END IF
18
19
     Example 6.19 Each process has a non-empty array of values. Find the minimum global
20
     value, the rank of the process that holds it and its index on this process.
21
22
     #define LEN
                     1000
23
24
                              /* local array of values */
     float val[LEN];
                              /* local number of values */
     int count;
     int myrank, minrank, minindex;
27
     float minval;
28
29
     struct {
30
         float value;
31
         int
              index;
32
     } in, out;
34
         /* local minloc
35
     in.value = val[0];
36
     in.index = 0;
37
     for (i=1; i < count; i++)
38
         if (in.value > val[i]) {
39
              in.value = val[i];
              in.index = i;
         }
43
         /* global minloc */
44
     MPI_Comm_rank(comm, &myrank);
45
     in.index = myrank*LEN + in.index;
46
     MPI_Reduce(&in, &out, 1, MPI_FLOAT_INT, MPI_MINLOC, root, comm);
47
         /* At this point, the answer resides on process root
```

```
*/
                                                                                        2
if (myrank == root) {
    /* read answer out
     */
                                     By assigning a value other than \code{myrank} to the
    minval = out.value;
                                     \code{in.index} field, a programmer can provide a different
    minrank = out.index / LEN;
                                     definition of \const{MPI\_MAXLOC} and \const{MPI
    minindex = out.index % LEN;
                                     \_MINLOC}, if so desired.
}
     Rationale.
                  The definition of MPI_MINLOC and MPI_MAXLOC given here has the
                                                                                        10
     advantage that it does not require any special-case handling of these two operations:
                                                                                          #-error!
     they are handled like any other reduce operation. A programmer can provide his or
                                                                                        12
                                                                                        13 #-PR415
     her own definition of MPI_MAXLOC and MPI_MINLOC, if so desired. The disadvantage
     is that values and indices have to be first interleaved, and that indices and values have
                                                                                        <sup>14</sup> #-update5
     to be coerced to the same type, in Fortran. (End of rationale.)
                                                                                          Done
                                                                                        16
                                                                                          in
                                                                                           PR415
                                                                                        17
6.9.5 User-Defined Reduction Operations
                                                                                        18
                                                                                        19
                                                                                        20
MPI_OP_CREATE(user_fn, commute, op)
                                                                                        21
 IN
           user_fn
                                      user defined function (function)
                                                                                        22
 IN
           commute
                                      true if commutative; false otherwise.
                                                                                        23
 OUT
                                       operation (handle)
           op
C binding
                                                                                        27
int MPI_Op_create(MPI_User_function *user_fn, int commute, MPI_Op *op)
                                                                                        28
int MPI_Op_create_c(MPI_User_function_c *user_fn, int commute, MPI_Op *op)
                                                                                        29
                                                                                        30
Fortran 2008 binding
                                                                                        31
MPI_Op_create(user_fn, commute, op, ierror)
    PROCEDURE(MPI_User_function), INTENT(IN) :: user_fn
    LOGICAL, INTENT(IN) :: commute
                                                                                        34
    TYPE(MPI_Op), INTENT(OUT) :: op
                                                                                        35
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                        36
                                                                                        37
MPI_Op_create_c(user_fn, commute, op, ierror)
    PROCEDURE (MPI_User_function_c), INTENT(IN) :: user_fn
    LOGICAL, INTENT(IN) :: commute
    TYPE(MPI_Op), INTENT(OUT) :: op
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                        42
Fortran binding
                                                                                        43
MPI_OP_CREATE(USER_FN, COMMUTE, OP, IERROR)
                                                                                        44
    EXTERNAL USER_FN
                                                                                        45
    LOGICAL COMMUTE
                                                                                        46
    INTEGER OP, IERROR
```

```
230
             1
                        MPI_OP_CREATE binds a user-defined reduction operation to an
             2
             3
             4
             5
             6
             7
             8
             9
             10
            11
            12
  #-error! 13
  #-other 14
This is a callback
prototype, use
correct macro!
            19
   PR449
            20
            21
            22
            23
            24
            25
             26
            27
            28
            29
            30
            31
            32
```

Done

33

34

35 36

37

38

39

40

41

42

43

44

45

46

47

48

INTEGER LEN, DATATYPE

in

```
op handle that can subsequently be used in MPI_REDUCE, MPI_ALLREDUCE,
MPI_REDUCE_SCATTER_BLOCK, MPI_REDUCE_SCATTER, MPI_SCAN,
MPI_EXSCAN, all nonblocking variants of those (see Section 6.12), and
MPI_REDUCE_LOCAL. The user-defined operation is assumed to be associative. If commute
= true, then the operation should be both commutative and associative. If commute = false,
then the order of operands is fixed and is defined to be in ascending, process rank order,
beginning with process zero. The order of evaluation can be changed, talking advantage of
the associativity of the operation. If commute = true then the order of evaluation can be
changed, taking advantage of commutativity and associativity.
    The argument user_fn is the user-defined function, which must have the following four
arguments: invec, inoutvec, len, and datatype.
    MPI_USER_FUNCTION also supports large count types in separate additional MPI
procedures in C (suffixed with the "_c") and interface polymorphism in Fortran when using
USE mpi_f08.
    The ISO C prototypes for the functions are the following.
typedef void MPI_User_function(void *invec, void *inoutvec, int *len,
              MPI_Datatype *datatype);
typedef void MPI_User_function_c(void *invec, void *inoutvec,
              MPI_Count *len, MPI_Datatype *datatype);
    The Fortran declarations of the user-defined function user_fn appear below.
ABSTRACT INTERFACE
  SUBROUTINE MPI_User_function(invec, inoutvec, len, datatype)
    USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
    TYPE(C_PTR), VALUE :: invec, inoutvec
    INTEGER :: len
    TYPE(MPI_Datatype) :: datatype
ABSTRACT INTERFACE
  SUBROUTINE MPI_User_function_c(invec, inoutvec, len, datatype)
    USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
    TYPE(C_PTR), VALUE :: invec, inoutvec
    INTEGER(KIND=MPI_COUNT_KIND) :: len
    TYPE(MPI_Datatype) :: datatype
SUBROUTINE USER_FUNCTION(INVEC, INOUTVEC, LEN, DATATYPE)
    <type> INVEC(LEN), INOUTVEC(LEN)
```

The datatype argument is a handle to the data type that was passed into the call to MPI\_REDUCE. The user reduce function should be written such that the following holds: Let u[0], ..., u[len-1] be the len elements in the communication buffer described by the arguments invec, len and datatype when the function is invoked; let  $v[0], \ldots, v[len-1]$  be len elements in the communication buffer described by the arguments inoutvec, len and datatype when the function is invoked; let  $w[0], \ldots, w[len-1]$  be len elements in the communication buffer described by the arguments inoutvec, len and datatype when the function returns; then  $w[i] = u[i] \circ v[i]$ , for  $i=0, \ldots$ , len-1, where  $\circ$  is the reduce operation that the function computes.

Informally, we can think of invec and inoutvec as arrays of len elements that user\_fn is combining. The result of the reduction over-writes values in inoutvec, hence the name. Each invocation of the function results in the pointwise evaluation of the reduce operator on len elements: i.e., the function returns in inoutvec[i] the value invec[i]  $\circ$  inoutvec[i], for i=0, ..., count-1, where  $\circ$  is the combining operation computed by the function.

Rationale. The len argument allows MPI\_REDUCE to avoid calling the function for each element in the input buffer. Rather, the system can choose to apply the function to chunks of input. In C, it is passed in as a reference for reasons of compatibility with Fortran.

By internally comparing the value of the datatype argument to known, global handles, it is possible to overload the use of a single user-defined function for several, different data types. (*End of rationale*.)

When calling any reduction or prefix scan MPI procedure with a user-defined MPI operator, the type of the count parameter in the call to the reduction or prefix scan MPI procedure does not need to be identical to the type of the len parameter in the user function associated with the user-defined MPI operator. If the count parameter has a type of int in C or INTEGER in Fortran and the len parameter has a type of MPI\_COUNT, then MPI will perform the appropriate widening type conversion of the len parameter. If the count parameter has a type of MPI\_COUNT and the len parameter has a type of int in C or INTEGER in Fortran, then MPI will perform the appropriate narrowing type conversion of the len parameter. If this narrowing conversion would result in truncation of the len value, then MPI will call the user function multiple times with a sequence of values for len that sum to the value of count.

Advice to implementors. If the number of data items cannot be represented in len, the implementation may need to invoke user\_fn multiple times. (End of advice to implementors.)

General datatypes may be passed to the user function. However, use of datatypes that are not contiguous is likely to lead to inefficiencies.

No MPI communication function may be called inside the user function. MPI\_ABORT may be called inside the function in case of an error.

Advice to users. Suppose one defines a library of user-defined reduce functions that are overloaded: the datatype argument is used to select the right execution path at each invocation, according to the types of the operands. The user-defined reduce function cannot "decode" the datatype argument that it is passed, and cannot identify, by itself, the correspondence between the datatype handles and the datatype they represent. This correspondence was established when the datatypes were created. Before the library is used, a library initialization preamble must be executed. This preamble code will define the datatypes that are used by the library, and store handles to these datatypes in global, static variables that are shared by the user code and the library code.

The Fortran version of MPI\_REDUCE will invoke a user-defined reduce function using the Fortran calling conventions and will pass a Fortran-type datatype argument; the C version will use C calling convention and the C representation of a datatype handle.

 Users who plan to mix languages should define their reduction functions accordingly. (End of advice to users.)

Advice to implementors. We outline below a naive and inefficient implementation of MPI\_REDUCE not supporting the "in place" option.

```
MPI_Comm_size(comm, &groupsize);
MPI_Comm_rank(comm, &rank);
if (rank > 0) {
    MPI_Recv(tempbuf, count, datatype, rank-1,...);
    User_reduce(tempbuf, sendbuf, count, datatype);
}
if (rank < groupsize-1) {
    MPI_Send(sendbuf, count, datatype, rank+1, ...);
}
/* answer now resides in process groupsize-1 ... now send to root
 */
if (rank == root) {
    MPI_Irecv(recvbuf, count, datatype, groupsize-1,..., &req);
if (rank == groupsize-1) {
    MPI_Send(sendbuf, count, datatype, root, ...);
}
if (rank == root) {
    MPI_Wait(&req, &status);
}
```

The reduction computation proceeds, sequentially, from process 0 to process groupsize-1. This order is chosen so as to respect the order of a possibly non-commutative operator defined by the function User\_reduce(). A more efficient implementation is achieved by taking advantage of associativity and using a logarithmic tree reduction. Commutativity can be used to advantage, for those cases in which the commute argument to MPI\_OP\_CREATE is true. Also, the amount of temporary buffer required can be reduced, and communication can be pipelined with computation, by transferring and reducing the elements in chunks of size len <count.

The predefined reduce operations can be implemented as a library of user-defined operations. However, better performance might be achieved if MPI\_REDUCE handles these functions as a special case. (*End of advice to implementors*.)

```
MPI_OP_FREE(op)

INOUT op operation (handle)

C binding
int MPI_Op_free(MPI_Op *op)

Fortran 2008 binding
```

```
MPI_Op_free(op, ierror)
    TYPE(MPI_Op), INTENT(INOUT) :: op
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_OP_FREE(OP, IERROR)
    INTEGER OP, IERROR
    Marks a user-defined reduction operation for deallocation and sets op to MPI_OP_NULL.
Example of User-Defined Reduce
It is time for an example of user-defined reduction. The example in this section uses an
                                                                                       12
intra-communicator.
                                                                                       13
                                                                                       14
Example 6.20 Compute the product of an array of complex numbers, in C.
                                                                                       15
                                                                                       16
typedef struct {
    double real, imag;
                                                                                       18
} Complex;
                                                                                       19
/* the user-defined function
                                                                                       20
                                                                                       21
 */
void myProd(void *inP, void *inoutP, int *len, MPI_Datatype *dptr)
                                                                                       22
                                                                                       23
                                                                                       24
    int i;
    Complex c;
                                                                                       26
    Complex *in = (Complex *)inP, *inout = (Complex *)inoutP;
                                                                                       27
    for (i=0; i< *len; ++i) {
                                                                                       28
                                                                                       29
         c.real = inout->real*in->real -
                                                                                       30
                     inout->imag*in->imag;
         c.imag = inout->real*in->imag +
                     inout->imag*in->real;
                                                                                       33
         *inout = c;
                                                                                       34
         in++; inout++;
                                                                                       35
}
                                                                                       36
                                                                                       37
/* and, to call it.
 */
                                                                                       42
    /* each process has an array of 100 Complexes
                                                                                       43
                                                                                       44
    Complex a[100], answer[100];
                                                                                       45
    MPI_Op myOp;
                                                                                       46
    MPI_Datatype ctype;
    /* explain to MPI how type Complex is defined
```

```
1
          */
2
         MPI_Type_contiguous(2, MPI_DOUBLE, &ctype);
         MPI_Type_commit(&ctype);
         /* create the complex-product user-op
          */
         MPI_Op_create(myProd, 1, &myOp);
         MPI_Reduce(a, answer, 100, ctype, myOp, root, comm);
         /* At this point, the answer, which consists of 100 Complexes,
11
          * resides on process root
12
          */
13
14
     Example 6.21 How to use the mpi_f08 interface of the Fortran MPI_User_function.
15
16
     subroutine my_user_function(invec, inoutvec, len, type)
                                                                  bind(c)
17
        use, intrinsic :: iso_c_binding, only : c_ptr, c_f_pointer
18
        use mpi_f08
19
        type(c_ptr), value :: invec, inoutvec
20
        integer :: len
21
        type(MPI_Datatype) :: type
22
        real, pointer :: invec_r(:), inoutvec_r(:)
23
        if (type%MPI_VAL == MPI_REAL%MPI_VAL) then
24
           call c_f_pointer(invec, invec_r, (/ len /))
           call c_f_pointer(inoutvec, inoutvec_r, (/ len /))
26
           inoutvec_r = invec_r + inoutvec_r
27
        end if
28
     end subroutine
29
30
```

#### 6.9.6 All-Reduce

31

32

34 35 36

37 38 39

48

MPI includes a variant of the reduce operations where the result is returned to all processes in a group. MPI requires that all processes from the same group participating in these operations receive identical results.

#### MPI\_ALLREDUCE(sendbuf, recvbuf, count, datatype, op, comm)

IN	sendbut	starting address of send buffer (choice)
OUT	recvbuf	starting address of receive buffer (choice)
IN	count	number of elements in send buffer (non-negative integer) $$
IN	datatype	data type of elements of send buffer (handle)
IN	ор	operation (handle)
IN	comm	communicator (handle)

#### C binding

12 13

14

15

16

18

19

20

21

22

23 24

26

27

28

29

34 35

36

37

38

42 43

44

45

46

```
int MPI_Allreduce(const void *sendbuf, void *recvbuf, int count,
             MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
int MPI_Allreduce_c(const void *sendbuf, void *recvbuf, MPI_Count count,
             MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
Fortran 2008 binding
MPI_Allreduce(sendbuf, recvbuf, count, datatype, op, comm, ierror)
   TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
   TYPE(*), DIMENSION(..) :: recvbuf
   INTEGER, INTENT(IN) :: count
   TYPE(MPI_Datatype), INTENT(IN) :: datatype
   TYPE(MPI_Op), INTENT(IN) :: op
   TYPE(MPI_Comm), INTENT(IN) :: comm
   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Allreduce(sendbuf, recvbuf, count, datatype, op, comm, ierror)
   TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
   TYPE(*), DIMENSION(..) :: recvbuf
   INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
   TYPE(MPI_Datatype), INTENT(IN) :: datatype
   TYPE(MPI_Op), INTENT(IN) :: op
   TYPE(MPI_Comm), INTENT(IN) :: comm
   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_ALLREDUCE(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
   INTEGER COUNT, DATATYPE, OP, COMM, IERROR
```

If comm is an intra-communicator, MPI\_ALLREDUCE behaves the same as MPI\_REDUCE except that the result appears in the receive buffer of all the group members.

Advice to implementors. The all-reduce operations can be implemented as a reduce, followed by a broadcast. However, a direct implementation can lead to better performance. (End of advice to implementors.)

The "in place" option for intra-communicators is specified by passing the value MPI\_IN\_PLACE to the argument sendbuf at all processes. In this case, the input data is taken at each process from the receive buffer, where it will be replaced by the output data.

If comm is an inter-communicator, then the result of the reduction of the data provided by processes in group A is stored at each process in group B, and vice versa. Both groups should provide count and datatype arguments that specify the same type signature.

The following example uses an intra-communicator.

**Example 6.22** A routine that computes the product of a vector and an array that are distributed across a group of processes and returns the answer at all nodes (see also Example 6.16).

```
1
     SUBROUTINE PAR_BLAS2(m, n, a, b, c, comm)
2
     REAL a(m), b(m,n)
                            ! local slice of array
3
     REAL c(n)
                            ! result
4
     REAL sum(n)
5
     INTEGER n, comm, i, j, ierr
6
7
     ! local sum
     DO j=1,n
8
9
        sum(j) = 0.0
10
        DO i=1,m
11
            sum(j) = sum(j) + a(i)*b(i,j)
12
13
     END DO
14
15
     ! global sum
16
     CALL MPI_ALLREDUCE(sum, c, n, MPI_REAL, MPI_SUM, comm, ierr)
17
18
     ! return result at all nodes
19
     RETURN
20
     F.ND
21
```

#### 6.9.7 Process-Local Reduction

The functions in this section are of importance to library implementors who may want to implement special reduction patterns that are otherwise not easily covered by the standard MPI operations.

The following function applies a reduction operator to local arguments.

27 28 29

30

31 32

33

34

35

36

37 38

39 40

22

23

24

25

## MPI\_REDUCE\_LOCAL(inbuf, inoutbuf, count, datatype, op)

```
IN
           inbuf
                                           input buffer (choice)
INOUT
           inoutbuf
                                           combined input and output buffer (choice)
IN
           count
                                           number of elements in inbuf and inoutbuf buffers
                                           (non-negative integer)
IN
                                           data type of elements of inbuf and inoutbuf buffers
           datatype
                                           (handle)
IN
                                           operation (handle)
```

#### C binding

```
41
     int MPI_Reduce_local(const void *inbuf, void *inoutbuf, int count,
42
                  MPI_Datatype datatype, MPI_Op op)
43
     int MPI_Reduce_local_c(const void *inbuf, void *inoutbuf, MPI_Count count,
44
                  MPI_Datatype datatype, MPI_Op op)
45
46
     Fortran 2008 binding
47
     MPI_Reduce_local(inbuf, inoutbuf, count, datatype, op, ierror)
```

INTEGER OP, IERROR

LOGICAL COMMUTE

12

13

14 15

16

18

19

20

21

22

23

26 27

28

29

30

33

34

35

36

37

42

43

44 45 46

```
TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
    TYPE(*), DIMENSION(..) :: inoutbuf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Reduce_local(inbuf, inoutbuf, count, datatype, op, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
    TYPE(*), DIMENSION(..) :: inoutbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_REDUCE_LOCAL(INBUF, INOUTBUF, COUNT, DATATYPE, OP, IERROR)
    <type> INBUF(*), INOUTBUF(*)
    INTEGER COUNT, DATATYPE, OP, IERROR
    The function applies the operation given by op element-wise to the elements of inbuf
and inoutbuf with the result stored element-wise in inoutbuf, as explained for user-defined
operations in Section 6.9.5. Both inbuf and inoutbuf (input as well as result) have the
same number of elements given by count and the same datatype given by datatype. The
MPI_IN_PLACE option is not allowed.
    Reduction operations can be queried for their commutativity.
MPI_OP_COMMUTATIVE(op, commute)
 IN
                                     operation (handle)
           op
```

#### Reduce-Scatter 6.10 1 2 MPI includes variants of the reduce operations where the result is scattered to all processes 3 in a group on return. One variant scatters equal-sized blocks to all processes, while another 4 variant scatters blocks that may vary in size for each process. 5 6 6.10.1 MPI\_REDUCE\_SCATTER\_BLOCK 7 8 9 10 MPI\_REDUCE\_SCATTER\_BLOCK(sendbuf, recvbuf, recvcount, datatype, op, comm) 11 IN sendbuf starting address of send buffer (choice) 12 OUT recvbuf starting address of receive buffer (choice) 13 14 IN element count per block (non-negative integer) recvcount 15 IN datatype data type of elements of send and receive buffers 16 (handle) 17 IN operation (handle) 18 op 19 IN comm communicator (handle) 20 21 C binding 22 int MPI\_Reduce\_scatter\_block(const void \*sendbuf, void \*recvbuf, 23 int recvcount, MPI\_Datatype datatype, MPI\_Op op, 24 MPI\_Comm comm) 25 26 int MPI\_Reduce\_scatter\_block\_c(const void \*sendbuf, void \*recvbuf, MPI\_Count recvcount, MPI\_Datatype datatype, MPI\_Op op, 27 MPI\_Comm comm) 28 29 Fortran 2008 binding 30 MPI\_Reduce\_scatter\_block(sendbuf, recvbuf, recvcount, datatype, op, comm, 31 ierror) 32 TYPE(\*), DIMENSION(..), INTENT(IN) :: sendbuf 33 TYPE(\*), DIMENSION(..) :: recvbuf 34 INTEGER, INTENT(IN) :: recvcount 35 TYPE(MPI\_Datatype), INTENT(IN) :: datatype 36 TYPE(MPI\_Op), INTENT(IN) :: op 37 TYPE(MPI\_Comm), INTENT(IN) :: comm 38 INTEGER, OPTIONAL, INTENT(OUT) :: ierror 39 40 MPI\_Reduce\_scatter\_block(sendbuf, recvbuf, recvcount, datatype, op, comm, 41 ierror) 42 TYPE(\*), DIMENSION(..), INTENT(IN) :: sendbuf TYPE(\*), DIMENSION(..) :: recvbuf 43 44 INTEGER(KIND=MPI\_COUNT\_KIND), INTENT(IN) :: recvcount 45 TYPE(MPI\_Datatype), INTENT(IN) :: datatype

TYPE(MPI\_Op), INTENT(IN) :: op

TYPE(MPI\_Comm), INTENT(IN) :: comm

INTEGER, OPTIONAL, INTENT(OUT) :: ierror

47

#### Fortran binding

MPI\_REDUCE\_SCATTER\_BLOCK(SENDBUF, RECVBUF, RECVCOUNT, DATATYPE, OP, COMM, IERROR)

<type> SENDBUF(\*), RECVBUF(\*)
INTEGER RECVCOUNT, DATATYPE, OP, COMM, IERROR

If comm is an intra-communicator, MPI\_REDUCE\_SCATTER\_BLOCK first performs a global, element-wise reduction on vectors of count = n\*recvcount elements in the send buffers defined by sendbuf, count and datatype, using the operation op, where n is the number of processes in the group of comm. The routine is called by all group members using the same arguments for recvcount, datatype, op and comm. The resulting vector is treated as n consecutive blocks of recvcount elements that are scattered to the processes of the group. The i-th block is sent to process i and stored in the receive buffer defined by recvbuf, recvcount, and datatype.

Advice to implementors. The MPI\_REDUCE\_SCATTER\_BLOCK routine is functionally equivalent to: an MPI\_REDUCE collective operation with count equal to recvcount\*n, followed by an MPI\_SCATTER with sendcount equal to recvcount. However, a direct implementation may run faster. (End of advice to implementors.)

The "in place" option for intra-communicators is specified by passing MPI\_IN\_PLACE in the sendbuf argument on *all* processes. In this case, the input data is taken from the receive buffer.

If comm is an inter-communicator, then the result of the reduction of the data provided by processes in one group (group A) is scattered among processes in the other group (group B) and vice versa. Within each group, all processes provide the same value for the recvcount argument, and provide input vectors of count = n\*recvcount elements stored in the send buffers, where n is the size of the group. The number of elements count must be the same for the two groups. The resulting vector from the other group is scattered in blocks of recvcount elements among the processes in the group.

Rationale. The last restriction is needed so that the length of the send buffer of one group can be determined by the local recvcount argument of the other group. Otherwise, a communication is needed to figure out how many elements are reduced. (End of rationale.)

#### 6.10.2 MPI\_REDUCE\_SCATTER

MPI\_REDUCE\_SCATTER extends the functionality of MPI\_REDUCE\_SCATTER\_BLOCK such that the scattered blocks can vary in size. Block sizes are determined by the recvcounts array, such that the i-th block contains recvcounts[i] elements.

```
1
     MPI_REDUCE_SCATTER(sendbuf, recvbuf, recvcounts, datatype, op, comm)
2
       IN
                sendbuf
                                            starting address of send buffer (choice)
3
       OUT
                recvbuf
                                           starting address of receive buffer (choice)
5
       IN
                                            non-negative integer array (of length group size)
                recvcounts
6
                                           specifying the number of elements of the result
                                            distributed to each process.
       IN
                                            data type of elements of send and receive buffers
                datatype
                                            (handle)
10
       IN
                                           operation (handle)
                op
11
12
       IN
                comm
                                            communicator (handle)
13
14
     C binding
15
     int MPI_Reduce_scatter(const void *sendbuf, void *recvbuf,
16
                    const int recvcounts[], MPI_Datatype datatype, MPI_Op op,
17
                    MPI_Comm comm)
18
     int MPI_Reduce_scatter_c(const void *sendbuf, void *recvbuf,
19
                    const MPI_Count recvcounts[], MPI_Datatype datatype,
20
                    MPI_Op op, MPI_Comm comm)
21
22
     Fortran 2008 binding
23
     MPI_Reduce_scatter(sendbuf, recvbuf, recvcounts, datatype, op, comm,
24
                    ierror)
25
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
26
         TYPE(*), DIMENSION(..) :: recvbuf
27
         INTEGER, INTENT(IN) :: recvcounts(*)
28
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
30
         TYPE(MPI_Comm), INTENT(IN) :: comm
31
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
32
     MPI_Reduce_scatter(sendbuf, recvbuf, recvcounts, datatype, op, comm,
33
34
                    ierror)
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
35
         TYPE(*), DIMENSION(..) :: recvbuf
36
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: recvcounts(*)
37
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
38
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
41
42
     Fortran binding
43
     MPI_REDUCE_SCATTER(SENDBUF, RECVBUF, RECVCOUNTS, DATATYPE, OP, COMM,
44
                    IERROR)
45
          <type> SENDBUF(*), RECVBUF(*)
46
         INTEGER RECVCOUNTS(*), DATATYPE, OP, COMM, IERROR
47
```

6.11. SCAN 241

If comm is an intra-communicator, MPI\_REDUCE\_SCATTER first performs a global, element-wise reduction on vectors of count =  $\sum_{i=0}^{n-1}$  recvcounts[i] elements in the send buffers defined by sendbuf, count and datatype, using the operation op, where n is the number of processes in the group of comm. The routine is called by all group members using the same arguments for recvcounts, datatype, op and comm. The resulting vector is treated as n consecutive blocks where the number of elements of the i-th block is recvcounts[i]. The blocks are scattered to the processes of the group. The i-th block is sent to process i and stored in the receive buffer defined by recvbuf, recvcounts[i] and datatype.

Advice to implementors. The MPI\_REDUCE\_SCATTER routine is functionally equivalent to: an MPI\_REDUCE collective operation with count equal to the sum of recvcounts[i] followed by MPI\_SCATTERV with sendcounts equal to recvcounts. However, a direct implementation may run faster. (*End of advice to implementors*.)

The "in place" option for intra-communicators is specified by passing MPI\_IN\_PLACE in the sendbuf argument. In this case, the input data is taken from the receive buffer. It is not required to specify the "in place" option on all processes, since the processes for which recvcounts[i] ==0 may not have allocated a receive buffer.

If comm is an inter-communicator, then the result of the reduction of the data provided by processes in one group (group A) is scattered among processes in the other group (group B), and vice versa. Within each group, all processes provide the same recvcounts argument, and provide input vectors of count =  $\sum_{i=0}^{n-1} \text{recvcounts}[i]$  elements stored in the send buffers, where n is the size of the group. The resulting vector from the other group is scattered in blocks of recvcounts[i] elements among the processes in the group. The number of elements count must be the same for the two groups.

Rationale. The last restriction is needed so that the length of the send buffer can be determined by the sum of the local recvcounts entries. Otherwise, a communication is needed to figure out how many elements are reduced. (*End of rationale*.)

#### 6.11 Scan

#### 6.11.1 Inclusive Scan

#### MPI\_SCAN(sendbuf, recvbuf, count, datatype, op, comm)

IN	sendbuf	starting address of send buffer (choice)
OUT	recvbuf	starting address of receive buffer (choice)
IN	count	number of elements in input buffer (non-negative integer)
IN	datatype	data type of elements of input buffer (handle)
IN	ор	operation (handle)
IN	comm	communicator (handle)

#### C binding

2

3

5 6

7

8

9

11

18

21

28

29

30

31

32

34

35

36

37

38

39

```
int MPI_Scan(const void *sendbuf, void *recvbuf, int count,
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
     int MPI_Scan_c(const void *sendbuf, void *recvbuf, MPI_Count count,
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
     Fortran 2008 binding
     MPI_Scan(sendbuf, recvbuf, count, datatype, op, comm, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
         TYPE(*), DIMENSION(..) :: recvbuf
10
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
12
         TYPE(MPI_Op), INTENT(IN) :: op
13
         TYPE(MPI_Comm), INTENT(IN) :: comm
14
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
15
     MPI_Scan(sendbuf, recvbuf, count, datatype, op, comm,
                                                            ierror)
16
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
17
         TYPE(*), DIMENSION(..) :: recvbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
19
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
20
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
22
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
23
24
     Fortran binding
25
     MPI_SCAN(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, IERROR)
26
         <type> SENDBUF(*), RECVBUF(*)
27
```

```
INTEGER COUNT, DATATYPE, OP, COMM, IERROR
```

If comm is an intra-communicator, MPI\_SCAN is used to perform a prefix reduction on data distributed across the group. The operation returns, in the receive buffer of the process with rank i, the reduction of the values in the send buffers of processes with ranks 0,..., i (inclusive). The routine is called by all group members using the same arguments for count, datatype, op and comm, except that for user-defined operations, the same rules apply as for MPI\_REDUCE. The type of operations supported, their semantics, and the constraints on send and receive buffers are as for MPI\_REDUCE.

The "in place" option for intra-communicators is specified by passing MPI\_IN\_PLACE in the sendbuf argument. In this case, the input data is taken from the receive buffer, and replaced by the output data.

This operation is invalid for inter-communicators.

6.11. SCAN 243

#### 6.11.2 Exclusive Scan

```
MPI_EXSCAN(sendbuf, recvbuf, count, datatype, op, comm)
 IN
           sendbuf
                                     starting address of send buffer (choice)
 OUT
           recvbuf
                                     starting address of receive buffer (choice)
 IN
                                     number of elements in input buffer (non-negative
          count
 IN
                                     data type of elements of input buffer (handle)
          datatype
                                     operation (handle)
 IN
           op
 IN
           comm
                                     intra-communicator (handle)
C binding
int MPI_Exscan(const void *sendbuf, void *recvbuf, int count,
              MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
int MPI_Exscan_c(const void *sendbuf, void *recvbuf, MPI_Count count,
              MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
Fortran 2008 binding
MPI_Exscan(sendbuf, recvbuf, count, datatype, op, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    TYPE(*), DIMENSION(..) :: recvbuf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Exscan(sendbuf, recvbuf, count, datatype, op, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    TYPE(*), DIMENSION(..) :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_EXSCAN(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER COUNT, DATATYPE, OP, COMM, IERROR
```

11

12 13

14 15

16

18

19

20 21

22

23

24

26

27

28

29

30

33

34

35

36

37

42

43

44

45

46 47

If comm is an intra-communicator, MPI\_EXSCAN is used to perform a prefix reduction on data distributed across the group. The value in recvbuf on the process with rank 0 is undefined, and recvbuf is not significant on process 0. The value in recvbuf on the process with rank 1 is defined as the value in sendbuf on the process with rank 0. For processes with rank i > 1, the operation returns, in the receive buffer of the process with rank i, the

reduction of the values in the send buffers of processes with ranks  $0, \ldots, i-1$  (inclusive). The routine is called by all group members using the same arguments for count, datatype, op and comm, except that for user-defined operations, the same rules apply as for MPI\_REDUCE. The type of operations supported, their semantics, and the constraints on send and receive buffers, are as for MPI\_REDUCE.

The "in place" option for intra-communicators is specified by passing MPI\_IN\_PLACE in the sendbuf argument. In this case, the input data is taken from the receive buffer, and replaced by the output data. The receive buffer on rank 0 is not changed by this operation.

This operation is invalid for inter-communicators.

Rationale. The exclusive scan is more general than the inclusive scan. Any inclusive scan operation can be achieved by using the exclusive scan and then locally combining the local contribution. Note that for non-invertable operations such as MPI\_MAX, the exclusive scan cannot be computed with the inclusive scan. (End of rationale.)

### 6.11.3 Example using MPI\_SCAN

The example in this section uses an intra-communicator.

**Example 6.23** This example uses a user-defined operation to produce a *segmented scan*. A segmented scan takes, as input, a set of values and a set of logicals, and the logicals delineate the various segments of the scan. For example:

The operator that produces this effect is

$$\left(egin{array}{c} u \ i \end{array}
ight)\circ \left(egin{array}{c} v \ j \end{array}
ight)= \left(egin{array}{c} w \ j \end{array}
ight).$$

where

$$w = \left\{ \begin{array}{ll} u + v & \text{if } i = j \\ v & \text{if } i \neq j \end{array} \right..$$

Note that this is a non-commutative operator. C code that implements it is given below.

6.11. SCAN 245

```
typedef struct {
    double val;
    int log;
} SegScanPair;
/* the user-defined function
*/
void segScan(SegScanPair *in, SegScanPair *inout, int *len,
             MPI_Datatype *dptr)
{
    int i;
    SegScanPair c;
    for (i=0; i< *len; ++i) {
        if (in->log == inout->log)
            c.val = in->val + inout->val;
        else
            c.val = inout->val;
        c.log = inout->log;
        *inout = c;
        in++; inout++;
    }
}
```

11

12 13 14

15

16

18

19

20 21

22

23

26

27

Note that the inout argument to the user-defined function corresponds to the right-hand operand of the operator. When using this operator, we must be careful to specify that it is non-commutative, as in the following.

```
28
int i, base;
                                                                                29
SegScanPair a, answer;
                                                                                30
MPI_Op
             myOp;
MPI_Datatype type[2] = {MPI_DOUBLE, MPI_INT};
                                                                                31
MPI_Aint
             disp[2];
                                                                                33
int
              blocklen[2] = { 1, 1};
                                                                                34
MPI_Datatype sspair;
                                                                                35
                                                                                36
/* explain to MPI how type SegScanPair is defined
*/
                                                                                37
MPI_Get_address(&a, disp);
                                                                                38
                                                                                39
MPI_Get_address(&a.log, disp+1);
base = disp[0];
                                                                                41
for (i=0; i<2; ++i) disp[i] -= base;
                                                                                42
MPI_Type_create_struct(2, blocklen, disp, type, &sspair);
MPI_Type_commit(&sspair);
                                                                                43
                                                                                44
/* create the segmented-scan user-op
                                                                                45
 */
                                                                                46
MPI_Op_create(segScan, 0, &myOp);
MPI_Scan(&a, &answer, 1, sspair, myOp, comm);
```

## 6.12 Nonblocking Collective Operations

As described in Section 3.7, performance of many applications can be improved by overlapping communication and computation, and many systems enable this. Nonblocking collective operations combine the potential benefits of nonblocking point-to-point operations, to exploit overlap and to avoid synchronization, with the optimized implementation and message scheduling provided by collective operations [34, 38]. One way of doing this would be to perform a blocking collective operation in a separate thread. An alternative mechanism that often leads to better performance (e.g., avoids context switching, scheduler overheads, and thread management) is to use nonblocking collective communication [36].

The nonblocking collective communication model is similar to the model used for non-blocking point-to-point communication. A nonblocking call initiates a collective operation, which must be completed in a separate completion call. Once initiated, the operation may progress independently of any computation or other communication at participating processes. In this manner, nonblocking collective operations can mitigate possible synchronizing effects of collective operations by running them in the "background." In addition to enabling communication-computation overlap, nonblocking collective operations can perform collective operations on overlapping communicators, which would lead to deadlocks with blocking operations. Their semantic advantages can also be useful in combination with point-to-point communication.

As in the nonblocking point-to-point case, all calls are local and return immediately, irrespective of the status of other processes. The call initiates the operation, which indicates that the system may start to copy data out of the send buffer and into the receive buffer. Once initiated, all associated send buffers and buffers associated with input arguments (such as arrays of counts, displacements, or datatypes in the vector versions of the collectives) should not be modified, and all associated receive buffers should not be accessed, until the collective operation completes. The call returns a request handle, which must be passed to a completion call.

All completion calls (e.g., MPI\_WAIT) described in Section 3.7.3 are supported for nonblocking collective operations. Similarly to the blocking case, nonblocking collective operations are considered to be complete when the local part of the operation is finished, i.e., for the caller, the semantics of the operation are guaranteed and all buffers can be safely accessed and modified. Completion does not indicate that other processes have completed or even started the operation (unless otherwise implied by the description of the operation). Completion of a particular nonblocking collective operation also does not indicate completion of any other posted nonblocking collective (or send-receive) operations, whether they are posted before or after the completed operation.

Advice to users. Users should be aware that implementations are allowed, but not required (with exception of MPI\_IBARRIER), to synchronize processes during the completion of a nonblocking collective operation. (End of advice to users.)

Upon returning from a completion call in which a nonblocking collective operation completes, the values of the MPI\_SOURCE and MPI\_TAG fields in the associated status object, if any, are undefined. The value of MPI\_ERROR may be defined, if appropriate, according to the specification in Section 3.2.5. It is valid to mix different request types (i.e., any combination of collective requests, I/O requests, generalized requests, or point-to-point requests) in functions that enable multiple completions (e.g., MPI\_WAITALL). It is erroneous

to call MPI\_REQUEST\_FREE or MPI\_CANCEL for a request associated with a nonblocking collective operation. Nonblocking collective requests created using the APIs described in this section are not persistent. However, persistent collective requests can be created using persistent collective operations described in Sections 6.13 and 8.8.

Rationale. Freeing an active nonblocking collective request could cause similar problems as discussed for point-to-point requests (see Section 3.7.3). Cancelling a request is not supported because the semantics of this operation are not well-defined. (End of rationale.)

Multiple nonblocking collective operations can be outstanding on a single communicator. If the nonblocking call causes some system resource to be exhausted, then it will fail and raise an error. Quality implementations of MPI should ensure that this happens only in pathological cases. That is, an MPI implementation should be able to support a large number of pending nonblocking operations.

Unlike point-to-point operations, nonblocking collective operations do not match with blocking collective operations, and collective operations do not have a tag argument. All processes must call collective operations (blocking and nonblocking) in the same order per communicator. In particular, once a process calls a collective operation, all other processes in the communicator must eventually call the same collective operation, and no other collective operation with the same communicator in between. This is consistent with the ordering rules for blocking collective operations in threaded environments.

Rationale. Matching blocking and nonblocking collective operations is not allowed because the implementation might use different communication algorithms for the two cases. Blocking collective operations may be optimized for minimal time to completion, while nonblocking collective operations may balance time to completion with CPU overhead and asynchronous progression.

The use of tags for collective operations can prevent certain hardware optimizations. (End of rationale.)

Advice to users. If program semantics require matching blocking and nonblocking collective operations, then a nonblocking collective operation can be initiated and immediately completed with a blocking wait to emulate blocking behavior. (End of advice to users.)

In terms of data movement, each nonblocking collective operation has the same effect as its blocking counterpart for intra-communicators and inter-communicators after completion. Likewise, upon completion, nonblocking collective reduction operations have the same effect as their blocking counterparts, and the same restrictions and recommendations on reduction orders apply.

The use of the "in place" option is allowed exactly as described for the corresponding blocking collective operations. When using the "in place" option, message buffers function as both send and receive buffers. Such buffers should not be modified or accessed until the operation completes.

Progression rules for nonblocking collective operations are similar to progression of nonblocking point-to-point operations, refer to Section 3.7.4.

Advice to implementors. Nonblocking collective operations can be implemented with local execution schedules [37] using nonblocking point-to-point communication and a reserved tag-space. (End of advice to implementors.)

### 6.12.1 Nonblocking Barrier Synchronization

```
2
3
4
```

5

6

7

10

11

12

13

14

15

16 17

18

19

20

21

22

23

24

25

26

27 28

29

30

31

32

33 34

1

```
MPI_IBARRIER(comm, request)
```

```
IN comm communicator (handle)
OUT request communication request (handle)
```

9

#### C binding

```
int MPI_Ibarrier(MPI_Comm comm, MPI_Request *request)
```

### Fortran 2008 binding

```
MPI_Ibarrier(comm, request, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_IBARRIER(COMM, REQUEST, IERROR)
    INTEGER COMM, REQUEST, IERROR
```

MPI\_IBARRIER is a nonblocking version of MPI\_BARRIER. By calling MPI\_IBARRIER, a process notifies that it has reached the barrier. The call returns immediately, independent of whether other processes have called MPI\_IBARRIER. The usual barrier semantics are enforced at the corresponding completion operation (test or wait), which in the intracommunicator case will complete only after all other processes in the communicator have called MPI\_IBARRIER. In the inter-communicator case, it will complete when all processes in the remote group have called MPI\_IBARRIER.

Advice to users. A nonblocking barrier can be used to hide latency. Moving independent computations between the MPI\_IBARRIER and the subsequent completion call can overlap the barrier latency and therefore shorten possible waiting times. The semantic properties are also useful when mixing collective operations and point-to-point messages. (End of advice to users.)

## 6.12.2 Nonblocking Broadcast

35 36 37

38 39

41

42

43

44

45

#### MPI\_IBCAST(buffer, count, datatype, root, comm, request)

```
INOUT
           buffer
                                          starting address of buffer (choice)
IN
           count
                                           number of entries in buffer (non-negative integer)
IN
          datatype
                                           data type of buffer (handle)
IN
           root
                                          rank of broadcast root (integer)
IN
                                           communicator (handle)
           comm
OUT
           request
                                          communication request (handle)
```

46 47

#### C binding

14

15

16

18

19

20

21

22 23

26

27

28 29

30

33

34

35

36 37

38

42

43 44

45 46

```
int MPI_Ibcast(void *buffer, int count, MPI_Datatype datatype, int root,
             MPI_Comm comm, MPI_Request *request)
int MPI_Ibcast_c(void *buffer, MPI_Count count, MPI_Datatype datatype,
             int root, MPI_Comm comm, MPI_Request *request)
Fortran 2008 binding
MPI_Ibcast(buffer, count, datatype, root, comm, request, ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
    INTEGER, INTENT(IN) :: count, root
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Ibcast(buffer, count, datatype, root, comm, request, ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: root
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_IBCAST(BUFFER, COUNT, DATATYPE, ROOT, COMM, REQUEST, IERROR)
    <type> BUFFER(*)
    INTEGER COUNT, DATATYPE, ROOT, COMM, REQUEST, IERROR
    This call starts a nonblocking variant of MPI_BCAST (see Section 6.4).
```

## Example using MPI\_IBCAST

The example in this section uses an intra-communicator.

**Example 6.24** Start a broadcast of 100 ints from process 0 to every process in the group, perform some computation on independent data, and then complete the outstanding broadcast operation.

```
MPI_Comm comm;
int array1[100], array2[100];
int root=0;
MPI_Request req;
...
MPI_Ibcast(array1, 100, MPI_INT, root, comm, &req);
compute(array2, 100);
MPI_Wait(&req, MPI_STATUS_IGNORE);
```

```
1
     6.12.3 Nonblocking Gather
2
3
4
     MPI_IGATHER(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, root, comm,
5
                    request)
6
       IN
                 sendbuf
                                            starting address of send buffer (choice)
       IN
                 sendcount
                                             number of elements in send buffer (non-negative
9
                                            integer)
10
       IN
                                            data type of send buffer elements (handle)
                 sendtype
11
       OUT
                 recvbuf
                                            address of receive buffer (choice, significant only at
12
                                             root)
13
       IN
                                             number of elements for any single receive
14
                 recvcount
                                             (non-negative integer, significant only at root)
15
16
       IN
                                             data type of recv buffer elements (handle, significant
                 recvtype
17
                                             only at root)
18
       IN
                                            rank of receiving process (integer)
                 root
19
       IN
                                             communicator (handle)
20
                 comm
21
       OUT
                                            communication request (handle)
                 request
22
23
     C binding
24
     int MPI_Igather(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
25
                    void *recvbuf, int recvcount, MPI_Datatype recvtype, int root,
26
                    MPI_Comm comm, MPI_Request *request)
27
     int MPI_Igather_c(const void *sendbuf, MPI_Count sendcount,
28
                    MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
29
30
                    MPI_Datatype recvtype, int root, MPI_Comm comm,
31
                    MPI_Request *request)
32
     Fortran 2008 binding
     MPI_Igather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
34
                    root, comm, request, ierror)
35
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
36
          INTEGER, INTENT(IN) :: sendcount, recvcount, root
37
          TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
38
          TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
          TYPE(MPI_Comm), INTENT(IN) :: comm
          TYPE(MPI_Request), INTENT(OUT) :: request
41
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
42
43
     MPI_Igather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
44
                    root, comm, request, ierror)
45
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
46
          INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
47
          TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
          TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
```

```
INTEGER, INTENT(IN) :: root
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_IGATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
               ROOT, COMM, REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, REQUEST,
                IERROR
    This call starts a nonblocking variant of MPI_GATHER (see Section 6.5).
                                                                                              12
                                                                                              13
                                                                                              14
MPI_IGATHERV(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs, recvtype, root,
                                                                                              15
               comm, request)
                                                                                              16
  IN
            sendbuf
                                         starting address of send buffer (choice)
                                                                                              18
  IN
            sendcount
                                         number of elements in send buffer (non-negative
                                                                                              19
                                         integer)
                                                                                              20
  IN
            sendtype
                                         data type of send buffer elements (handle)
                                                                                             21
                                                                                             22
  OUT
            recvbuf
                                         address of receive buffer (choice, significant only at
                                                                                             23
                                         root)
                                                                                              24
  IN
            recvcounts
                                         non-negative integer array (of length group size)
                                         containing the number of elements that are received
                                                                                              26
                                         from each process (significant only at root)
                                                                                             27
  IN
            displs
                                         integer array (of length group size). Entry i specifies
                                                                                             28
                                         the displacement relative to recvbuf at which to place
                                                                                             29
                                         the incoming data from process i (significant only at
                                                                                             30
                                         root)
                                                                                              31
  IN
                                         data type of recv buffer elements (handle, significant
            recvtype
                                                                                              33
                                         only at root)
                                                                                             34
  IN
            root
                                         rank of receiving process (integer)
                                                                                             35
  IN
            comm
                                         communicator (handle)
                                                                                             36
                                                                                             37
  OUT
            request
                                         communication request (handle)
                                                                                             38
                                                                                              39
C binding
int MPI_Igatherv(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
               void *recvbuf, const int recvcounts[], const int displs[],
                                                                                             42
               MPI_Datatype recvtype, int root, MPI_Comm comm,
                                                                                             43
               MPI_Request *request)
                                                                                              44
int MPI_Igatherv_c(const void *sendbuf, MPI_Count sendcount,
                                                                                              45
               MPI_Datatype sendtype, void *recvbuf,
                                                                                              46
                const MPI_Count recvcounts[], const MPI_Aint displs[],
                                                                                              47
```

43 44 45

47

```
1
                  MPI_Datatype recvtype, int root, MPI_Comm comm,
2
                  MPI_Request *request)
     Fortran 2008 binding
     MPI_Igatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
                  recvtype, root, comm, request, ierror)
6
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         INTEGER, INTENT(IN) :: sendcount, root
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
10
         INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*), displs(*)
         TYPE(MPI_Comm), INTENT(IN) :: comm
12
         TYPE(MPI_Request), INTENT(OUT) :: request
13
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
14
15
    MPI_Igatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
16
                  recvtype, root, comm, request, ierror)
17
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
18
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
19
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
20
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
21
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
23
         INTEGER, INTENT(IN) :: root
24
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
26
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
27
     Fortran binding
28
     MPI_IGATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS,
29
                  RECVTYPE, ROOT, COMM, REQUEST, IERROR)
30
         <type> SENDBUF(*), RECVBUF(*)
31
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, ROOT,
                   COMM, REQUEST, IERROR
33
34
         This call starts a nonblocking variant of MPI_GATHERV (see Section 6.5).
35
```

**Unofficial Draft for Comment Only** 

```
6.12.4 Nonblocking Scatter
MPI_ISCATTER(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, root, comm,
               request)
  IN
           sendbuf
                                      address of send buffer (choice, significant only at
                                      root)
  IN
           sendcount
                                       number of elements sent to each process
                                       (non-negative integer, significant only at root)
  IN
           sendtype
                                       data type of send buffer elements (handle, significant
                                                                                        12
                                       only at root)
                                                                                        13
  OUT
           recybuf
                                      address of receive buffer (choice)
                                                                                        14
                                       number of elements in receive buffer (non-negative
  IN
           recvcount
                                                                                        15
                                      integer)
                                                                                        16
  IN
           recvtype
                                      data type of receive buffer elements (handle)
                                                                                        18
  IN
                                      rank of sending process (integer)
           root
                                                                                        19
  IN
                                      communicator (handle)
           comm
                                                                                        20
                                                                                        21
  OUT
                                      communication request (handle)
           request
                                                                                        22
                                                                                        23
C binding
int MPI_Iscatter(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
               void *recvbuf, int recvcount, MPI_Datatype recvtype, int root,
              MPI_Comm comm, MPI_Request *request)
                                                                                        27
int MPI_Iscatter_c(const void *sendbuf, MPI_Count sendcount,
                                                                                        28
              MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
                                                                                        29
              MPI_Datatype recvtype, int root, MPI_Comm comm,
                                                                                        30
              MPI_Request *request)
Fortran 2008 binding
MPI_Iscatter(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
                                                                                        34
              root, comm, request, ierror)
                                                                                        35
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                        36
    INTEGER, INTENT(IN) :: sendcount, recvcount, root
                                                                                        37
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                        42
MPI_Iscatter(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
                                                                                        43
                                                                                        44
              root, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                        45
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
                                                                                        46
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
```

```
1
          INTEGER, INTENT(IN) :: root
2
          TYPE(MPI_Comm), INTENT(IN) :: comm
          TYPE(MPI_Request), INTENT(OUT) :: request
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
6
     MPI_ISCATTER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
                     ROOT, COMM, REQUEST, IERROR)
          <type> SENDBUF(*), RECVBUF(*)
9
          INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, REQUEST,
10
                      IERROR
11
12
          This call starts a nonblocking variant of MPI_SCATTER (see Section 6.6).
13
14
     MPI_ISCATTERV(sendbuf, sendcounts, displs, sendtype, recybuf, recycount, recytype, root,
15
                     comm, request)
16
17
       IN
                 sendbuf
                                              address of send buffer (choice, significant only at
18
                                              root)
19
       IN
                 sendcounts
                                              non-negative integer array (of length group size)
20
                                              specifying the number of elements to send to each
21
                                              rank (significant only at root)
22
       IN
                 displs
                                              integer array (of length group size). Entry i specifies
23
                                              the displacement (relative to sendbuf) from which to
24
                                              take the outgoing data to process i (significant only
                                              at root)
26
27
       IN
                 sendtype
                                              data type of send buffer elements (handle, significant
28
                                              only at root)
29
       OUT
                 recvbuf
                                              address of receive buffer (choice)
30
       IN
                 recvcount
                                              number of elements in receive buffer (non-negative
31
                                              integer)
32
33
       IN
                 recvtype
                                              data type of receive buffer elements (handle)
34
       IN
                 root
                                              rank of sending process (integer)
35
       IN
                 comm
                                              communicator (handle)
36
37
       OUT
                 request
                                              communication request (handle)
38
39
     C binding
     int MPI_Iscatterv(const void *sendbuf, const int sendcounts[],
41
                     const int displs[], MPI_Datatype sendtype, void *recvbuf,
42
                     int recvcount, MPI_Datatype recvtype, int root, MPI_Comm comm,
43
                     MPI_Request *request)
44
     int MPI_Iscatterv_c(const void *sendbuf, const MPI_Count sendcounts[],
45
                     const MPI_Aint displs[], MPI_Datatype sendtype, void *recvbuf,
46
                     MPI_Count recvcount, MPI_Datatype recvtype, int root,
47
                     MPI_Comm comm, MPI_Request *request)
```

```
Fortran 2008 binding
MPI_Iscatterv(sendbuf, sendcounts, displs, sendtype, recvbuf, recvcount,
             recvtype, root, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), displs(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER, INTENT(IN) :: recvcount, root
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 12
MPI_Iscatterv(sendbuf, sendcounts, displs, sendtype, recvbuf, recvcount,
                                                                                 13
             recvtype, root, comm, request, ierror)
                                                                                 14
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 15
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: sendcounts(*)
                                                                                 16
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 19
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: recvcount
                                                                                 20
    INTEGER, INTENT(IN) :: root
                                                                                 21
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 22
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
                                                                                 26
MPI_ISCATTERV(SENDBUF, SENDCOUNTS, DISPLS, SENDTYPE, RECVBUF, RECVCOUNT,
             RECVTYPE, ROOT, COMM, REQUEST, IERROR)
                                                                                 27
                                                                                 28
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNTS(*), DISPLS(*), SENDTYPE, RECVCOUNT, RECVTYPE, ROOT,
              COMM, REQUEST, IERROR
                                                                                 30
    This call starts a nonblocking variant of MPI_SCATTERV (see Section 6.6).
```

```
1
     6.12.5
            Nonblocking Gather-to-all
2
3
4
     MPI_IALLGATHER(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, comm,
5
                    request)
6
       IN
                sendbuf
                                            starting address of send buffer (choice)
       IN
                                            number of elements in send buffer (non-negative
                sendcount
                                            integer)
9
10
       IN
                sendtype
                                            data type of send buffer elements (handle)
11
       OUT
                recvbuf
                                            address of receive buffer (choice)
12
                                            number of elements received from any process
       IN
                 recvcount
13
                                            (non-negative integer)
14
15
                                            data type of receive buffer elements (handle)
       IN
                 recvtype
16
                                            communicator (handle)
       IN
                comm
17
       OUT
                request
                                            communication request (handle)
18
19
     C binding
20
     int MPI_Iallgather(const void *sendbuf, int sendcount,
21
                    MPI_Datatype sendtype, void *recvbuf, int recvcount,
22
                    MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
23
24
     int MPI_Iallgather_c(const void *sendbuf, MPI_Count sendcount,
25
                    MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
26
                    MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
27
     Fortran 2008 binding
28
     MPI_Iallgather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
29
30
                    comm, request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
31
32
         INTEGER, INTENT(IN) :: sendcount, recvcount
33
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
34
          TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
35
36
         TYPE(MPI_Request), INTENT(OUT) :: request
37
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
38
     MPI_Iallgather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
39
                    comm, request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
41
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
42
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
43
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
44
         TYPE(MPI_Comm), INTENT(IN) :: comm
45
         TYPE(MPI_Request), INTENT(OUT) :: request
46
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
47
48
     Fortran binding
```

```
MPI_IALLGATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
               COMM, REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, REQUEST, IERROR
    This call starts a nonblocking variant of MPI_ALLGATHER (see Section 6.7).
MPI_IALLGATHERV(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs, recvtype,
               comm, request)
  IN
           sendbuf
                                       starting address of send buffer (choice)
  IN
           sendcount
                                       number of elements in send buffer (non-negative
                                                                                          12
                                       integer)
                                                                                          13
                                                                                          14
  IN
           sendtype
                                       data type of send buffer elements (handle)
                                                                                          15
           recvbuf
  OUT
                                       address of receive buffer (choice)
                                                                                          16
  IN
            recvcounts
                                       non-negative integer array (of length group size)
                                                                                          17
                                       containing the number of elements that are received
                                                                                          18
                                       from each process
                                                                                          19
                                                                                          20
  IN
           displs
                                       integer array (of length group size). Entry i specifies
                                                                                          21
                                       the displacement (relative to recvbuf) at which to
                                                                                          22
                                       place the incoming data from process i
                                                                                          23
                                       data type of receive buffer elements (handle)
  IN
            recvtype
                                                                                          24
                                       communicator (handle)
  IN
                                                                                          25
           comm
                                                                                          26
  OUT
                                       communication request (handle)
            request
                                                                                          27
                                                                                          28
C binding
                                                                                          29
int MPI_Iallgatherv(const void *sendbuf, int sendcount,
                                                                                          30
               MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
                                                                                          31
               const int displs[], MPI_Datatype recvtype, MPI_Comm comm,
               MPI_Request *request)
                                                                                          33
                                                                                          34
int MPI_Iallgatherv_c(const void *sendbuf, MPI_Count sendcount,
               MPI_Datatype sendtype, void *recvbuf,
                                                                                          35
               const MPI_Count recvcounts[], const MPI_Aint displs[],
                                                                                          36
               MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
                                                                                          37
                                                                                          38
Fortran 2008 binding
MPI_Iallgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
               recvtype, comm, request, ierror)
    TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                          42
    INTEGER, INTENT(IN) :: sendcount
                                                                                          43
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                          44
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                          45
    INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*), displs(*)
                                                                                          46
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                          47
    TYPE(MPI_Request), INTENT(OUT) :: request
```

```
1
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
2
     MPI_Iallgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
3
                    recvtype, comm, request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
          INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
6
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
9
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
10
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
12
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
14
     Fortran binding
15
     MPI_IALLGATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS,
16
                    RECVTYPE, COMM, REQUEST, IERROR)
17
          <type> SENDBUF(*), RECVBUF(*)
18
          INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, COMM,
19
                     REQUEST, IERROR
20
         This call starts a nonblocking variant of MPI_ALLGATHERV (see Section 6.7).
21
22
     6.12.6 Nonblocking All-to-All Scatter/Gather
23
24
25
     MPI_IALLTOALL(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, comm, request)
26
27
28
       IN
                sendbuf
                                            starting address of send buffer (choice)
29
       IN
                sendcount
                                            number of elements sent to each process
30
                                            (non-negative integer)
31
       IN
                 sendtype
                                            data type of send buffer elements (handle)
32
33
       OUT
                                            address of receive buffer (choice)
                 recvbuf
34
       IN
                 recvcount
                                            number of elements received from any process
35
                                            (non-negative integer)
36
       IN
                 recytype
                                            data type of receive buffer elements (handle)
37
38
       IN
                 comm
                                            communicator (handle)
       OUT
                 request
                                            communication request (handle)
41
     C binding
     int MPI_Ialltoall(const void *sendbuf, int sendcount,
43
                    MPI_Datatype sendtype, void *recvbuf, int recvcount,
44
                    MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
45
46
     int MPI_Ialltoall_c(const void *sendbuf, MPI_Count sendcount,
47
                    MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
                    MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
```

Fortran 2008 binding	1		
MPI_Ialltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,			
comm, request, ierror)	3		
TYPE(*), DIMENSION(), INTENT(IN), ASYNCHRONOUS :: sendbuf	4		
<pre>INTEGER, INTENT(IN) :: sendcount, recvcount</pre>	5		
TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype	6		
TYPE(*), DIMENSION(), ASYNCHRONOUS :: recvbuf	7		
TYPE(MPI_Comm), INTENT(IN) :: comm	8		
TYPE(MPI_Request), INTENT(OUT) :: request	9		
INTEGER, OPTIONAL, INTENT(OUT) :: ierror	10		
MDT Talltaall(sandhuf sandaaunt sandtuna maarhuf maaraunt maartuna	11		
MPI_Ialltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,	12		
comm, request, ierror)	13		
TYPE(*), DIMENSION(), INTENT(IN), ASYNCHRONOUS :: sendbuf	14		
INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount			
TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype	16		
TYPE(*), DIMENSION(), ASYNCHRONOUS :: recvbuf	17		
TYPE(MPI_Comm), INTENT(IN) :: comm	18		
TYPE(MPI_Request), INTENT(OUT) :: request	19		
INTEGER, OPTIONAL, INTENT(OUT) :: ierror	20		
Fortran binding	21		
MPI_IALLTOALL(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,	22		
COMM, REQUEST, IERROR)	23		
<type> SENDBUF(*), RECVBUF(*)</type>	24		
INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, REQUEST, IERROR	25		
This call stants a month align assignt of MDL ALLTONIA (see Cartin CO)			
This call starts a nonblocking variant of MPI_ALLTOALL (see Section 6.8).	27		

```
1
     MPI_IALLTOALLV(sendbuf, sendcounts, sdispls, sendtype, recvbuf, recvcounts, rdispls,
2
                     recvtype, comm, request)
3
       IN
                 sendbuf
                                              starting address of send buffer (choice)
       IN
                 sendcounts
                                              non-negative integer array (of length group size)
                                              specifying the number of elements to send to each
6
                                              rank
       IN
                 sdispls
                                              integer array (of length group size). Entry j specifies
                                              the displacement (relative to sendbuf) from which to
10
                                              take the outgoing data destined for process j
11
       IN
                                              data type of send buffer elements (handle)
                 sendtype
12
       OUT
                 recvbuf
                                              address of receive buffer (choice)
13
14
                                              non-negative integer array (of length group size)
       IN
                 recvcounts
15
                                              specifying the number of elements that can be
16
                                              received from each rank
17
       IN
                 rdispls
                                              integer array (of length group size). Entry i specifies
18
                                              the displacement (relative to recvbuf) at which to
19
                                              place the incoming data from process i
20
       IN
                                              data type of receive buffer elements (handle)
                 recvtype
21
22
       IN
                                              communicator (handle)
                 comm
23
       OUT
                 request
                                              communication request (handle)
24
25
     C binding
     int MPI_Ialltoallv(const void *sendbuf, const int sendcounts[],
27
                     const int sdispls[], MPI_Datatype sendtype, void *recvbuf,
28
                     const int recvcounts[], const int rdispls[],
29
                     MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
30
31
     int MPI_Ialltoallv_c(const void *sendbuf, const MPI_Count sendcounts[],
32
                     const MPI_Aint sdispls[], MPI_Datatype sendtype,
33
                     void *recvbuf, const MPI_Count recvcounts[],
34
                     const MPI_Aint rdispls[], MPI_Datatype recvtype,
35
                     MPI_Comm comm, MPI_Request *request)
36
     Fortran 2008 binding
37
     MPI_Ialltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf, recvcounts,
38
                     rdispls, recvtype, comm, request, ierror)
39
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
          INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),
41
                     recvcounts(*), rdispls(*)
42
          TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
43
          TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
44
          TYPE(MPI_Comm), INTENT(IN) :: comm
45
          TYPE(MPI_Request), INTENT(OUT) :: request
46
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
47
```

```
MPI_Ialltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf, recvcounts,
             rdispls, recvtype, comm, request, ierror)
    TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
              sendcounts(*), recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
              rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  11
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  12
                                                                                  13
Fortran binding
                                                                                  14
MPI_IALLTOALLV(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE, RECVBUF, RECVCOUNTS,
                                                                                  15
             RDISPLS, RECVTYPE, COMM, REQUEST, IERROR)
                                                                                  16
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*),
              RECVTYPE, COMM, REQUEST, IERROR
                                                                                  19
    This call starts a nonblocking variant of MPI_ALLTOALLV (see Section 6.8).
                                                                                  20
```

y can start a nonorsening variant of im i\_nell to the interest of the interest

```
1
      MPI_IALLTOALLW(sendbuf, sendcounts, sdispls, sendtypes, recvbuf, recvcounts, rdispls,
2
                      recvtypes, comm, request)
3
       IN
                  sendbuf
                                                starting address of send buffer (choice)
       IN
                  sendcounts
                                                integer array (of length group size) specifying the
                                                number of elements to send to each rank (array of
6
                                                non-negative integers)
       IN
                  sdispls
                                                integer array (of length group size). Entry j specifies
9
                                                the displacement in bytes (relative to sendbuf) from
10
                                                which to take the outgoing data destined for process
11
                                               i (array of integers)
12
       IN
                  sendtypes
                                                array of datatypes (of length group size). Entry j
13
                                                specifies the type of data to send to process j (array
14
                                                of handles)
15
                                                address of receive buffer (choice)
        OUT
                  recvbuf
16
17
       IN
                                                integer array (of length group size) specifying the
                  recvcounts
18
                                                number of elements that can be received from each
19
                                                rank (array of non-negative integers)
20
       IN
                  rdispls
                                                integer array (of length group size). Entry i specifies
21
                                                the displacement in bytes (relative to recvbuf) at
22
                                                which to place the incoming data from process i
23
                                                (array of integers)
24
       IN
                                                array of datatypes (of length group size). Entry i
                  recvtypes
25
                                                specifies the type of data received from process i
26
                                                (array of handles)
27
28
       IN
                                                communicator (handle)
                  comm
29
        OUT
                  request
                                                communication request (handle)
30
31
      C binding
32
      int MPI_Ialltoallw(const void *sendbuf, const int sendcounts[],
33
                      const int sdispls[], const MPI_Datatype sendtypes[],
34
                      void *recvbuf, const int recvcounts[], const int rdispls[],
35
                      const MPI_Datatype recvtypes[], MPI_Comm comm,
36
                     MPI_Request *request)
37
38
      int MPI_Ialltoallw_c(const void *sendbuf, const MPI_Count sendcounts[],
39
                      const MPI_Aint sdispls[], const MPI_Datatype sendtypes[],
                     void *recvbuf, const MPI_Count recvcounts[],
41
                      const MPI_Aint rdispls[], const MPI_Datatype recvtypes[],
42
                     MPI_Comm comm, MPI_Request *request)
43
     Fortran 2008 binding
44
     MPI_Ialltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
45
                     recvcounts, rdispls, recvtypes, comm, request, ierror)
46
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
47
```

```
INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),
              recvcounts(*), rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
              recvtypes(*)
    TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Ialltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
              recvcounts, rdispls, recvtypes, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                  12
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
                                                                                  13
              sendcounts(*), recvcounts(*)
                                                                                  14
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
                                                                                  15
              rdispls(*)
                                                                                  16
    TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*)
              recvtypes(*)
                                                                                  18
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                  19
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  20
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  21
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  22
                                                                                  23
Fortran binding
MPI IALLTOALLW(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPES, RECVBUF,
              RECVCOUNTS, RDISPLS, RECVTYPES, COMM, REQUEST, IERROR)
                                                                                  26
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPES(*), RECVCOUNTS(*),
                                                                                  27
              RDISPLS(*), RECVTYPES(*), COMM, REQUEST, IERROR
                                                                                  28
                                                                                  29
    This call starts a nonblocking variant of MPI_ALLTOALLW (see Section 6.8).
                                                                                  30
```

```
1
     6.12.7 Nonblocking Reduce
2
3
4
     MPI_IREDUCE(sendbuf, recvbuf, count, datatype, op, root, comm, request)
5
       IN
                sendbuf
                                            address of send buffer (choice)
6
       OUT
                recvbuf
7
                                            address of receive buffer (choice, significant only at
                                            root)
9
       IN
                count
                                            number of elements in send buffer (non-negative
10
                                            integer)
11
                                            data type of elements of send buffer (handle)
       IN
                datatype
12
       IN
                                            reduce operation (handle)
13
                op
14
       IN
                root
                                            rank of root process (integer)
15
       IN
                comm
                                            communicator (handle)
16
17
       OUT
                                            communication request (handle)
                request
18
19
     C binding
20
     int MPI_Ireduce(const void *sendbuf, void *recvbuf, int count,
21
                    MPI_Datatype datatype, MPI_Op op, int root, MPI_Comm comm,
22
                    MPI_Request *request)
23
     int MPI_Ireduce_c(const void *sendbuf, void *recvbuf, MPI_Count count,
24
                    MPI_Datatype datatype, MPI_Op op, int root, MPI_Comm comm,
25
                    MPI_Request *request)
26
27
     Fortran 2008 binding
28
     MPI_Ireduce(sendbuf, recvbuf, count, datatype, op, root, comm, request,
29
                    ierror)
30
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
31
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: count, root
33
          TYPE(MPI_Datatype), INTENT(IN) :: datatype
34
         TYPE(MPI_Op), INTENT(IN) :: op
35
         TYPE(MPI_Comm), INTENT(IN) :: comm
36
         TYPE(MPI_Request), INTENT(OUT) :: request
37
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
38
     MPI_Ireduce(sendbuf, recvbuf, count, datatype, op, root, comm, request,
39
                    ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
43
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
44
         TYPE(MPI_Op), INTENT(IN) :: op
45
         INTEGER, INTENT(IN) :: root
46
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_IREDUCE(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, ROOT, COMM, REQUEST, IERROR)
```

```
<type> SENDBUF(*), RECVBUF(*)
```

INTEGER COUNT, DATATYPE, OP, ROOT, COMM, REQUEST, IERROR

This call starts a nonblocking variant of MPI\_REDUCE (see Section 6.9.1).

Advice to implementors. The implementation is explicitly allowed to use different algorithms for blocking and nonblocking reduction operations that might change the order of evaluation of the operations. However, as for MPI\_REDUCE, it is strongly recommended that MPI\_IREDUCE be implemented so that the same result be obtained whenever the function is applied on the same arguments, appearing in the same order. Note that this may prevent optimizations that take advantage of the physical location of processes. (End of advice to implementors.)

Advice to users. For operations which are not truly associative, the result delivered upon completion of the nonblocking reduction may not exactly equal the result delivered by the blocking reduction, even when specifying the same arguments in the same order. (End of advice to users.)

# 6.12.8 Nonblocking All-Reduce

#### MPI\_IALLREDUCE(sendbuf, recvbuf, count, datatype, op, comm, request)

IN	sendbuf	starting address of send buffer (choice)
OUT	recvbuf	starting address of receive buffer (choice)
IN	count	number of elements in send buffer (non-negative integer)
IN	datatype	data type of elements of send buffer (handle)
IN	ор	operation (handle)
IN	comm	communicator (handle)
OUT	request	communication request (handle)

## C binding

#### Fortran 2008 binding

```
1
     MPI_Iallreduce(sendbuf, recvbuf, count, datatype, op, comm, request,
2
                    ierror)
3
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: count
6
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
10
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
11
     MPI_Iallreduce(sendbuf, recvbuf, count, datatype, op, comm, request,
12
                    ierror)
13
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
14
         TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
15
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
16
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
17
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
19
         TYPE(MPI_Request), INTENT(OUT) :: request
20
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
21
22
     Fortran binding
23
     MPI_IALLREDUCE(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, REQUEST,
24
                    IERROR)
          <type> SENDBUF(*), RECVBUF(*)
26
          INTEGER COUNT, DATATYPE, OP, COMM, REQUEST, IERROR
27
         This call starts a nonblocking variant of MPI_ALLREDUCE (see Section 6.9.6).
28
29
             Nonblocking Reduce-Scatter with Equal Blocks
30
31
32
     MPI_IREDUCE_SCATTER_BLOCK(sendbuf, recvbuf, recvcount, datatype, op, comm,
33
34
                    request)
35
                sendbuf
       IN
                                            starting address of send buffer (choice)
36
       OUT
                recybuf
                                            starting address of receive buffer (choice)
37
38
       IN
                 recvcount
                                            element count per block (non-negative integer)
                datatype
                                            data type of elements of send and receive buffers
       IN
                                            (handle)
41
       IN
                ор
                                            operation (handle)
42
43
       IN
                comm
                                            communicator (handle)
44
       OUT
                 request
                                            communication request (handle)
45
46
     C binding
47
```

```
int MPI_Ireduce_scatter_block(const void *sendbuf, void *recvbuf,
             int recvcount, MPI_Datatype datatype, MPI_Op op,
             MPI_Comm comm, MPI_Request *request)
int MPI_Ireduce_scatter_block_c(const void *sendbuf, void *recvbuf,
             MPI_Count recvcount, MPI_Datatype datatype, MPI_Op op,
             MPI_Comm comm, MPI_Request *request)
Fortran 2008 binding
MPI_Ireduce_scatter_block(sendbuf, recvbuf, recvcount, datatype, op, comm,
             request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                  12
                                                                                  13
    INTEGER, INTENT(IN) :: recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                  14
                                                                                  15
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                  16
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  18
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  19
MPI_Ireduce_scatter_block(sendbuf, recvbuf, recvcount, datatype, op, comm,
                                                                                  20
             request, ierror)
                                                                                 21
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                  22
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                  23
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: recvcount
                                                                                  24
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  27
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_IREDUCE_SCATTER_BLOCK(SENDBUF, RECVBUF, RECVCOUNT, DATATYPE, OP, COMM,
             REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
                                                                                 34
    INTEGER RECVCOUNT, DATATYPE, OP, COMM, REQUEST, IERROR
                                                                                 35
    This call starts a nonblocking variant of MPI_REDUCE_SCATTER_BLOCK (see Sec-
                                                                                 36
tion 6.10.1).
                                                                                 37
                                                                                  38
                                                                                  39
```

Fortran binding

```
1
     6.12.10 Nonblocking Reduce-Scatter
2
3
4
     MPI_IREDUCE_SCATTER(sendbuf, recvbuf, recvcounts, datatype, op, comm, request)
5
       IN
                sendbuf
                                            starting address of send buffer (choice)
6
       OUT
                recvbuf
7
                                            starting address of receive buffer (choice)
       IN
                                            non-negative integer array specifying the number of
                recvcounts
                                            elements in result distributed to each process. This
10
                                            array must be identical on all calling processes.
11
                                            data type of elements of input buffer (handle)
       IN
                datatype
12
       IN
                                            operation (handle)
13
                op
14
       IN
                comm
                                            communicator (handle)
15
                                            communication request (handle)
       OUT
                request
16
17
     C binding
18
     int MPI_Ireduce_scatter(const void *sendbuf, void *recvbuf,
19
                    const int recvcounts[], MPI_Datatype datatype, MPI_Op op,
20
                    MPI_Comm comm, MPI_Request *request)
21
22
     int MPI_Ireduce_scatter_c(const void *sendbuf, void *recvbuf,
23
                    const MPI_Count recvcounts[], MPI_Datatype datatype,
24
                    MPI_Op op, MPI_Comm comm, MPI_Request *request)
25
     Fortran 2008 binding
26
     MPI_Ireduce_scatter(sendbuf, recvbuf, recvcounts, datatype, op, comm,
27
                    request, ierror)
28
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
29
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
30
         INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
31
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
33
          TYPE(MPI_Comm), INTENT(IN) :: comm
34
         TYPE(MPI_Request), INTENT(OUT) :: request
35
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
36
37
     MPI_Ireduce_scatter(sendbuf, recvbuf, recvcounts, datatype, op, comm,
38
                    request, ierror)
39
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
41
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
42
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
43
         TYPE(MPI_Op), INTENT(IN) :: op
44
         TYPE(MPI_Comm), INTENT(IN) :: comm
45
         TYPE(MPI_Request), INTENT(OUT) :: request
46
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
47
```

```
MPI_IREDUCE_SCATTER(SENDBUF, RECVBUF, RECVCOUNTS, DATATYPE, OP, COMM,
              REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER RECVCOUNTS(*), DATATYPE, OP, COMM, REQUEST, IERROR
    This call starts a nonblocking variant of MPI_REDUCE_SCATTER (see Section 6.10.2).
6.12.11 Nonblocking Inclusive Scan
MPI_ISCAN(sendbuf, recvbuf, count, datatype, op, comm, request)
                                                                                      12
           sendbuf
  IN
                                      starting address of send buffer (choice)
                                                                                      13
  OUT
           recvbuf
                                      starting address of receive buffer (choice)
                                                                                      14
  IN
           count
                                      number of elements in input buffer (non-negative
                                                                                      15
                                      integer)
                                                                                      16
  IN
           datatype
                                      data type of elements of input buffer (handle)
                                                                                      18
  IN
                                      operation (handle)
           op
                                                                                      19
  IN
                                      communicator (handle)
           comm
                                                                                      20
                                                                                      21
  OUT
                                      communication request (handle)
           request
                                                                                      22
                                                                                      23
C binding
                                                                                      24
int MPI_Iscan(const void *sendbuf, void *recvbuf, int count,
              MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
                                                                                      26
              MPI_Request *request)
                                                                                      27
int MPI_Iscan_c(const void *sendbuf, void *recvbuf, MPI_Count count,
                                                                                      28
              MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
                                                                                      29
              MPI_Request *request)
                                                                                      30
Fortran 2008 binding
MPI_Iscan(sendbuf, recvbuf, count, datatype, op, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                      34
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                      35
    INTEGER, INTENT(IN) :: count
                                                                                      36
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      37
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      42
MPI_Iscan(sendbuf, recvbuf, count, datatype, op, comm, request, ierror)
    TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                      43
                                                                                      44
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                      45
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      46
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
1
         TYPE(MPI_Request), INTENT(OUT) :: request
2
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
3
     Fortran binding
     MPI_ISCAN(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, REQUEST, IERROR)
         <type> SENDBUF(*), RECVBUF(*)
6
         INTEGER COUNT, DATATYPE, OP, COMM, REQUEST, IERROR
8
         This call starts a nonblocking variant of MPI_SCAN (see Section 6.11).
9
10
     6.12.12 Nonblocking Exclusive Scan
11
12
13
     MPI_IEXSCAN(sendbuf, recvbuf, count, datatype, op, comm, request)
14
       IN
                sendbuf
                                           starting address of send buffer (choice)
15
16
       OUT
                                           starting address of receive buffer (choice)
                recvbuf
17
                                           number of elements in input buffer (non-negative
       IN
                count
18
                                           integer)
19
       IN
                datatype
                                           data type of elements of input buffer (handle)
20
21
       IN
                op
                                           operation (handle)
22
       IN
                                           intra-communicator (handle)
                comm
23
                                           communication request (handle)
       OUT
                request
24
25
26
     C binding
     int MPI_Iexscan(const void *sendbuf, void *recvbuf, int count,
27
                    MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
28
                    MPI_Request *request)
29
30
     int MPI_Iexscan_c(const void *sendbuf, void *recvbuf, MPI_Count count,
31
                    MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
32
                    MPI_Request *request)
33
34
     Fortran 2008 binding
35
     MPI_Iexscan(sendbuf, recvbuf, count, datatype, op, comm, request, ierror)
36
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
37
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
41
         TYPE(MPI_Comm), INTENT(IN) :: comm
42
         TYPE(MPI_Request), INTENT(OUT) :: request
43
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
44
     MPI_Iexscan(sendbuf, recvbuf, count, datatype, op, comm, request, ierror)
45
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
46
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
47
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
```

```
TYPE(MPI_Datatype), INTENT(IN) :: datatype
TYPE(MPI_Op), INTENT(IN) :: op
TYPE(MPI_Comm), INTENT(IN) :: comm
TYPE(MPI_Request), INTENT(OUT) :: request
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_IEXSCAN(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, REQUEST, IERROR)
<type> SENDBUF(*), RECVBUF(*)
   INTEGER COUNT, DATATYPE, OP, COMM, REQUEST, IERROR
```

This call starts a nonblocking variant of MPI\_EXSCAN (see Section 6.11.2).

# 6.13 Persistent Collective Operations

Many parallel computation algorithms involve repetitively executing a collective communication operation with the same arguments each time. As with persistent point-to-point operations (see Section 3.9), persistent collective operations allow the MPI programmer to specify operations that will be reused frequently (with fixed arguments). MPI can be designed to select a more efficient way to perform the collective operation based on the parameters specified when the operation is initialized. This "planned-transfer" approach [52, 41] can offer significant performance benefits for programs with repetitive communication patterns.

In terms of data movement, each persistent collective operation has the same effect as its blocking and nonblocking counterparts for intra-communicators and inter-communicators after completion. Likewise, upon completion, persistent collective reduction operations perform the same operation as their blocking and nonblocking counterparts, and the same restrictions and recommendations on reduction orders apply (see also Section 6.9.1).

Initialization calls for MPI persistent collective operations are non-local and follow all the existing rules for collective operations, in particular ordering; programs that do not conform to these restrictions are erroneous. After initialization, all arrays associated with input arguments (such as arrays of counts, displacements, and datatypes in the vector versions of the collectives) must not be modified until the corresponding persistent request is freed with MPI\_REQUEST\_FREE.

According to the definitions in Section 2.4.2, the persistent collective initialization procedures are incomplete. They are also non-local procedures because they may or may not return before they are called in all MPI processes of the process group associated with the specified communicator.

Advice to users. This is one of the exceptions in which incomplete procedures are non-local and therefore blocking. (End of advice to users.)

The request argument is an output argument that can be used zero or more times with MPI\_START or MPI\_STARTALL in order to start the collective operation. The request is initially inactive after the initialization call. Once initialized, persistent collective operations can be started in any order and the order can differ among processes in the communicator.

Rationale. All ordering requirements that an implementation may need to match up collective operations across the communicator are achieved through the ordering

requirements of the initialization functions. This enables out-of-order starts for the persistent operations, and particularly supports their use in MPI\_STARTALL. (End of rationale.)

3 5

6

9

10

1

2

Advice to implementors. An MPI implementation should do no worse than duplicating the communicator during the initialization function, caching the input arguments, and calling the appropriate nonblocking collective function, using the cached arguments, during MPI\_START. High-quality implementations should be able to amortize setup costs and further optimize by taking advantage of early-binding, such as efficient and effective pre-allocation of certain resources and algorithm selection. (End of advice to implementors.)

11 12 13

14

15

16

17

21

23

24

25

26

27

28

31

32

33

A request must be inactive when it is started. Starting the operation makes the request active. Once any process starts a persistent collective operation, it must complete that operation and all other processes in the communicator must eventually start (and complete) the same persistent collective operation. Persistent collective operations cannot be matched with blocking or nonblocking collective operations. Completion of a persistent collective operation makes the corresponding request inactive. After starting a persistent collective operation, all associated send buffers must not be modified and all associated receive buffers must not be accessed until the corresponding persistent request is completed.

Completing a persistent collective request, for example using MPI\_TEST or MPI\_WAIT, makes it inactive, but does not free the request. This is the same behavior as for persistent point-to-point requests. Inactive persistent collective requests can be freed using MPI\_REQUEST\_FREE. It is erroneous to free an active persistent collective request. Persistent collective operations cannot be canceled; it is erroneous to use MPI CANCEL on a persistent collective request.

#-other 29

#-error!

Done

For every nonblocking collective communication operation in MPI, there is a corresponding persistent collective operation with the analogous API signature. \mpicdeck\mpi\ Info\ info

The collective persistent API signatures include an MPI\_INFO object in order to support optimization hints and other information that may be non-standard. Persistent collective operations may be optimized during communicator creation or by the initialization operation of an individual persistent collective. Note that communicator-scoped hints should be provided using MPI\_COMM\_SET\_INFO while, for operation-scoped hints, they are supplied to the persistent collective communication initialization functions using the info argument.

34 35

# Persistent Barrier Synchronization

37 38 39

40

41

42 43

36

```
MPI_BARRIER_INIT(comm, info, request)
```

```
IN
                                         communicator (handle)
          comm
IN
          info
                                         info argument (handle)
OUT
          request
                                         communication request (handle)
```

45 46 47

48

44

#### C binding

int MPI\_Barrier\_init(MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request)

# Fortran 2008 binding

```
MPI_Barrier_init(comm, info, request, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_BARRIER_INIT(COMM, INFO, REQUEST, IERROR)
    INTEGER COMM, INFO, REQUEST, IERROR
    Creates a persistent collective communication request for the barrier operation.
                                                                                      12
6.13.2 Persistent Broadcast
                                                                                      13
                                                                                      14
                                                                                      15
MPI_BCAST_INIT(buffer, count, datatype, root, comm, info, request)
                                                                                      16
  INOUT
           buffer
                                      starting address of buffer (choice)
                                                                                      18
  IN
           count
                                      number of entries in buffer (non-negative integer)
                                                                                      19
                                      data type of buffer (handle)
  IN
           datatype
                                                                                      20
  IN
           root
                                      rank of broadcast root (integer)
                                                                                      21
                                                                                      22
  IN
           comm
                                      communicator (handle)
                                                                                      23
                                      info argument (handle)
  IN
           info
                                                                                      24
  OUT
                                      communication request (handle)
           request
                                                                                      26
C binding
                                                                                      27
int MPI_Bcast_init(void *buffer, int count, MPI_Datatype datatype,
                                                                                      28
              int root, MPI_Comm comm, MPI_Info info, MPI_Request *request)
                                                                                      29
                                                                                      30
int MPI_Bcast_init_c(void *buffer, MPI_Count count, MPI_Datatype datatype,
              int root, MPI_Comm comm, MPI_Info info, MPI_Request *request)
Fortran 2008 binding
                                                                                      34
MPI_Bcast_init(buffer, count, datatype, root, comm, info, request, ierror)
                                                                                      35
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
                                                                                      36
    INTEGER, INTENT(IN) :: count, root
                                                                                      37
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      42
MPI_Bcast_init(buffer, count, datatype, root, comm, info, request, ierror)
                                                                                      43
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
                                                                                      44
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                      45
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      46
    INTEGER, INTENT(IN) :: root
    TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
1
          TYPE(MPI_Info), INTENT(IN) :: info
2
          TYPE(MPI_Request), INTENT(OUT) :: request
3
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
5
     MPI_BCAST_INIT(BUFFER, COUNT, DATATYPE, ROOT, COMM, INFO, REQUEST, IERROR)
6
          <type> BUFFER(*)
          INTEGER COUNT, DATATYPE, ROOT, COMM, INFO, REQUEST, IERROR
9
          Creates a persistent collective communication request for the broadcast operation.
10
11
     6.13.3 Persistent Gather
12
13
14
     MPI_GATHER_INIT(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, root, comm,
15
                     info, request)
16
       IN
                 sendbuf
                                             starting address of send buffer (choice)
17
18
       IN
                 sendcount
                                             number of elements in send buffer (non-negative
19
                                              integer)
20
                                              data type of send buffer elements (handle)
       IN
                 sendtype
21
       OUT
                 recvbuf
                                              address of receive buffer (choice, significant only at
22
                                              root)
23
24
                                              number of elements for any single receive
       IN
                 recvcount
                                              (non-negative integer, significant only at root)
26
       IN
                                              data type of recv buffer elements (handle, significant
                 recvtype
27
                                              only at root)
28
       IN
                                              rank of receiving process (integer)
                 root
29
30
       IN
                                              communicator (handle)
                 comm
31
       IN
                 info
                                             info argument (handle)
32
       OUT
                 request
                                              communication request (handle)
33
34
     C binding
35
36
     int MPI_Gather_init(const void *sendbuf, int sendcount,
37
                     MPI_Datatype sendtype, void *recvbuf, int recvcount,
38
                     MPI_Datatype recvtype, int root, MPI_Comm comm, MPI_Info info,
39
                     MPI_Request *request)
     int MPI_Gather_init_c(const void *sendbuf, MPI_Count sendcount,
41
                     MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
42
                     MPI_Datatype recvtype, int root, MPI_Comm comm, MPI_Info info,
43
                     MPI_Request *request)
44
45
     Fortran 2008 binding
46
     MPI_Gather_init(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
47
                     root, comm, info, request, ierror)
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
```

13

14

15

16

18

19

20

26

29 30

```
INTEGER, INTENT(IN) :: sendcount, recvcount, root
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Gather_init(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
             root, comm, info, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER, INTENT(IN) :: root
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_GATHER_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
                                                                                 22
             ROOT, COMM, INFO, REQUEST, IERROR)
                                                                                 23
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, INFO,
              REQUEST, IERROR
    Creates a persistent collective communication request for the gather operation.
                                                                                 27
                                                                                 28
```

```
1
     MPI_GATHERV_INIT(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs, recvtype,
2
                     root, comm, info, request)
3
       IN
                 sendbuf
                                              starting address of send buffer (choice)
       IN
                 sendcount
                                              number of elements in send buffer (non-negative
5
                                              integer)
6
7
       IN
                 sendtype
                                              data type of send buffer elements (handle)
       OUT
                 recvbuf
                                              address of receive buffer (choice, significant only at
                                              root)
10
       IN
                                              non-negative integer array (of length group size)
                 recvcounts
11
                                              containing the number of elements that are received
12
                                              from each process (significant only at root)
13
14
                                              integer array (of length group size). Entry i specifies
       IN
                 displs
15
                                              the displacement relative to recybuf at which to place
16
                                              the incoming data from process i (significant only at
17
18
       IN
                 recvtype
                                              data type of recv buffer elements (handle, significant
19
                                              only at root)
20
       IN
                                              rank of receiving process (integer)
                 root
21
22
       IN
                                              communicator (handle)
                 comm
23
       IN
                 info
                                              info argument (handle)
24
       OUT
                 request
                                              communication request (handle)
25
26
     C binding
27
     int MPI_Gatherv_init(const void *sendbuf, int sendcount,
28
                     MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
29
                     const int displs[], MPI_Datatype recvtype, int root,
30
                     MPI_Comm comm, MPI_Info info, MPI_Request *request)
31
32
     int MPI_Gatherv_init_c(const void *sendbuf, MPI_Count sendcount,
33
                     MPI_Datatype sendtype, void *recvbuf,
34
                     const MPI_Count recvcounts[], const MPI_Aint displs[],
35
                     MPI_Datatype recvtype, int root, MPI_Comm comm, MPI_Info info,
36
                     MPI_Request *request)
37
38
     Fortran 2008 binding
     MPI_Gatherv_init(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
39
                     recvtype, root, comm, info, request, ierror)
41
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
42
          INTEGER, INTENT(IN) :: sendcount, root
          TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
43
          TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
44
45
          INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*), displs(*)
          TYPE(MPI_Comm), INTENT(IN) :: comm
47
          TYPE(MPI_Info), INTENT(IN) :: info
          TYPE(MPI_Request), INTENT(OUT) :: request
```

46

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Gatherv_init(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
               recvtype, root, comm, info, request, ierror)
    TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
    INTEGER, INTENT(IN) :: root
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                         12
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                         13
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                         14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                         15
                                                                                         16
Fortran binding
                                                                                         17
MPI_GATHERV_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS,
               RECVTYPE, ROOT, COMM, INFO, REQUEST, IERROR)
                                                                                         19
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, ROOT,
                                                                                         20
                                                                                         21
               COMM, INFO, REQUEST, IERROR
                                                                                         22
    Creates a persistent collective communication request for the gathery operation.
                                                                                         23
6.13.4 Persistent Scatter
                                                                                         26
                                                                                         27
MPI_SCATTER_INIT(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, root,
                                                                                         28
               comm, info, request)
 IN
           sendbuf
                                       address of send buffer (choice, significant only at
                                       root)
 IN
           sendcount
                                       number of elements sent to each process
                                       (non-negative integer, significant only at root)
                                                                                         34
  1N
                                       data type of send buffer elements (handle, significant
           sendtype
                                                                                         35
                                       only at root)
                                                                                         36
                                                                                         37
  OUT
           recvbuf
                                       address of receive buffer (choice)
 IN
           recvcount
                                       number of elements in receive buffer (non-negative
                                       integer)
 IN
                                       data type of receive buffer elements (handle)
           recvtype
                                                                                         42
 IN
           root
                                       rank of sending process (integer)
                                                                                         43
 IN
           comm
                                       communicator (handle)
                                                                                         44
 IN
           info
                                       info argument (handle)
```

C binding

request

OUT

communication request (handle)

43 44 45

47

```
1
     int MPI_Scatter_init(const void *sendbuf, int sendcount,
2
                  MPI_Datatype sendtype, void *recvbuf, int recvcount,
3
                  MPI_Datatype recvtype, int root, MPI_Comm comm, MPI_Info info,
                  MPI_Request *request)
5
     int MPI_Scatter_init_c(const void *sendbuf, MPI_Count sendcount,
6
                  MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
                  MPI_Datatype recvtype, int root, MPI_Comm comm, MPI_Info info,
8
                  MPI_Request *request)
9
10
     Fortran 2008 binding
11
     MPI_Scatter_init(sendbuf, sendcount, sendtype, recvbuf, recvcount,
12
                  recvtype, root, comm, info, request, ierror)
13
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
14
         INTEGER, INTENT(IN) :: sendcount, recvcount, root
15
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
16
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
18
         TYPE(MPI_Info), INTENT(IN) :: info
19
         TYPE(MPI_Request), INTENT(OUT) :: request
20
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
21
     MPI_Scatter_init(sendbuf, sendcount, sendtype, recvbuf, recvcount,
22
                  recvtype, root, comm, info, request, ierror)
23
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
24
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
26
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
27
         INTEGER, INTENT(IN) :: root
28
         TYPE(MPI_Comm), INTENT(IN) :: comm
29
         TYPE(MPI_Info), INTENT(IN) :: info
30
         TYPE(MPI_Request), INTENT(OUT) :: request
31
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
32
33
     Fortran binding
34
     MPI_SCATTER_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT,
35
                  RECVTYPE, ROOT, COMM, INFO, REQUEST, IERROR)
36
         <type> SENDBUF(*), RECVBUF(*)
37
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, INFO,
                   REQUEST, IERROR
```

Creates a persistent collective communication request for the scatter operation.

```
MPI_SCATTERV_INIT(sendbuf, sendcounts, displs, sendtype, recvbuf, recvcount, recvtype,
               root, comm, info, request)
 IN
           sendbuf
                                        address of send buffer (choice, significant only at
                                        root)
 IN
           sendcounts
                                        non-negative integer array (of length group size)
                                        specifying the number of elements to send to each
                                        rank (significant only at root)
 IN
           displs
                                        integer array (of length group size). Entry i specifies
                                        the displacement (relative to sendbuf) from which to
                                                                                            11
                                        take the outgoing data to process i (significant only
                                        at root)
                                                                                            12
                                                                                            13
 IN
           sendtype
                                        data type of send buffer elements (handle, significant
                                                                                            14
                                        only at root)
                                                                                            15
  OUT
            recvbuf
                                        address of receive buffer (choice, significant only at
                                                                                            16
                                        root)
                                                                                            18
                                        number of elements in receive buffer (non-negative
 IN
            recvcount
                                                                                            19
                                        integer)
                                                                                            20
                                        data type of receive buffer elements (handle)
 IN
            recvtype
                                                                                           21
 IN
            root
                                        rank of sending process (integer)
                                                                                            22
                                                                                            23
 IN
                                        communicator (handle)
           comm
                                                                                            24
 IN
           info
                                        info argument (handle)
 OUT
                                        communication request (handle)
           request
                                                                                            26
                                                                                            27
C binding
                                                                                            28
int MPI_Scatterv_init(const void *sendbuf, const int sendcounts[],
                                                                                            29
               const int displs[], MPI_Datatype sendtype, void *recvbuf,
                                                                                            30
               int recvcount, MPI_Datatype recvtype, int root, MPI_Comm comm,
               MPI_Info info, MPI_Request *request)
int MPI_Scatterv_init_c(const void *sendbuf, const MPI_Count sendcounts[],
                                                                                           34
               const MPI_Aint displs[], MPI_Datatype sendtype, void *recvbuf,
                                                                                            35
               MPI_Count recvcount, MPI_Datatype recvtype, int root,
                                                                                            36
               MPI_Comm comm, MPI_Info info, MPI_Request *request)
                                                                                            37
Fortran 2008 binding
                                                                                            38
MPI_Scatterv_init(sendbuf, sendcounts, displs, sendtype, recvbuf,
                                                                                            39
               recvcount, recvtype, root, comm, info, request, ierror)
                                                                                            41
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                            42
    INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), displs(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                            43
    TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
                                                                                            44
    INTEGER, INTENT(IN) :: recvcount, root
                                                                                            45
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                            46
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
```

```
1
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
2
     MPI_Scatterv_init(sendbuf, sendcounts, displs, sendtype, recvbuf,
3
                    recvcount, recvtype, root, comm, info, request, ierror)
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
5
          INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: sendcounts(*)
6
          INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
          TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
          TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
9
          INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: recvcount
10
          INTEGER, INTENT(IN) :: root
11
          TYPE(MPI_Comm), INTENT(IN) :: comm
12
          TYPE(MPI_Info), INTENT(IN) :: info
13
          TYPE(MPI_Request), INTENT(OUT) :: request
14
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
15
16
     Fortran binding
17
     MPI_SCATTERV_INIT(SENDBUF, SENDCOUNTS, DISPLS, SENDTYPE, RECVBUF,
18
                    RECVCOUNT, RECVTYPE, ROOT, COMM, INFO, REQUEST, IERROR)
19
          <type> SENDBUF(*), RECVBUF(*)
20
          INTEGER SENDCOUNTS(*), DISPLS(*), SENDTYPE, RECVCOUNT, RECVTYPE, ROOT,
21
                     COMM, INFO, REQUEST, IERROR
22
          Creates a persistent collective communication request for the scattery operation.
23
24
     6.13.5 Persistent Gather-to-all
25
26
27
     MPI_ALLGATHER_INIT(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, comm,
28
29
                    info, request)
30
       IN
                 sendbuf
                                            starting address of send buffer (choice)
31
       IN
                 sendcount
                                            number of elements in send buffer (non-negative
32
                                            integer)
33
34
       IN
                 sendtype
                                            data type of send buffer elements (handle)
35
       OUT
                 recvbuf
                                            address of receive buffer (choice)
36
       IN
                 recvcount
                                            number of elements received from any process
37
                                            (non-negative integer)
38
39
       IN
                                            data type of receive buffer elements (handle)
                 recvtype
       IN
                comm
                                            communicator (handle)
41
       IN
                 info
                                            info argument (handle)
42
       OUT
43
                 request
                                            communication request (handle)
44
45
     C binding
46
     int MPI_Allgather_init(const void *sendbuf, int sendcount,
47
                    MPI_Datatype sendtype, void *recvbuf, int recvcount,
```

14

15

16

18

19

24

37

```
MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
             MPI_Request *request)
int MPI_Allgather_init_c(const void *sendbuf, MPI_Count sendcount,
             MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
             MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
             MPI_Request *request)
Fortran 2008 binding
MPI_Allgather_init(sendbuf, sendcount, sendtype, recvbuf, recvcount,
             recvtype, comm, info, request, ierror)
    TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Allgather_init(sendbuf, sendcount, sendtype, recvbuf, recvcount,
                                                                                20
             recvtype, comm, info, request, ierror)
                                                                                21
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                22
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
                                                                                23
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                27
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_ALLGATHER_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT,
             RECVTYPE, COMM, INFO, REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST,
                                                                                35
              IERROR
                                                                                36
```

Creates a persistent collective communication request for the allgather operation.

```
1
     MPI_ALLGATHERV_INIT(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs, recvtype,
2
                    comm, info, request)
3
       IN
                 sendbuf
                                             starting address of send buffer (choice)
       IN
                 sendcount
                                             number of elements in send buffer (non-negative
5
                                             integer)
6
7
       IN
                 sendtype
                                             data type of send buffer elements (handle)
       OUT
                 recvbuf
                                             address of receive buffer (choice)
9
                                             non-negative integer array (of length group size)
       IN
                 recvcounts
10
                                             containing the number of elements that are received
11
                                             from each process
12
       IN
                                             integer array (of length group size). Entry i specifies
13
                 displs
14
                                             the displacement (relative to recvbuf) at which to
15
                                             place the incoming data from process i
16
                 recvtype
                                             data type of receive buffer elements (handle)
       IN
17
                                             communicator (handle)
       IN
                 comm
18
                                             info argument (handle)
19
       IN
                 info
20
       OUT
                                             communication request (handle)
                 request
21
22
     C binding
23
     int MPI_Allgatherv_init(const void *sendbuf, int sendcount,
24
                    MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
25
                    const int displs[], MPI_Datatype recvtype, MPI_Comm comm,
26
                    MPI_Info info, MPI_Request *request)
27
     int MPI_Allgatherv_init_c(const void *sendbuf, MPI_Count sendcount,
28
                    MPI_Datatype sendtype, void *recvbuf,
29
30
                    const MPI_Count recvcounts[], const MPI_Aint displs[],
31
                    MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
32
                    MPI_Request *request)
33
     Fortran 2008 binding
34
     MPI_Allgatherv_init(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
35
                    displs, recvtype, comm, info, request, ierror)
36
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
37
          INTEGER, INTENT(IN) :: sendcount
38
          TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
39
          TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
          INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*), displs(*)
41
          TYPE(MPI_Comm), INTENT(IN) :: comm
42
          TYPE(MPI_Info), INTENT(IN) :: info
43
          TYPE(MPI_Request), INTENT(OUT) :: request
44
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
46
     MPI_Allgatherv_init(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
47
                    displs, recvtype, comm, info, request, ierror)
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
```

```
INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_ALLGATHERV_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS,
                                                                                        12
              DISPLS, RECVTYPE, COMM, INFO, REQUEST, IERROR)
                                                                                        13
    <type> SENDBUF(*), RECVBUF(*)
                                                                                        14
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, COMM,
                                                                                        15
               INFO, REQUEST, IERROR
                                                                                        16
    Creates a persistent collective communication request for the allgathery operation.
                                                                                        18
                                                                                        19
6.13.6 Persistent All-to-All Scatter/Gather
                                                                                        20
                                                                                        21
                                                                                        22
MPI_ALLTOALL_INIT(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, comm,
                                                                                        23
              info, request)
  IN
           sendbuf
                                       starting address of send buffer (choice)
                                                                                        26
  IN
           sendcount
                                       number of elements sent to each process
                                                                                        27
                                       (non-negative integer)
                                                                                        28
           sendtype
                                       data type of send buffer elements (handle)
  IN
                                                                                        29
  OUT
           recvbuf
                                       address of receive buffer (choice)
                                                                                        30
                                       number of elements received from any process
  IN
           recvcount
                                       (non-negative integer)
                                                                                        33
  IN
                                       data type of receive buffer elements (handle)
           recvtype
                                                                                        34
  1N
           comm
                                       communicator (handle)
                                                                                        35
  IN
           info
                                       info argument (handle)
                                                                                        36
                                                                                        37
  OUT
           request
                                       communication request (handle)
                                                                                        38
C binding
int MPI_Alltoall_init(const void *sendbuf, int sendcount,
              MPI_Datatype sendtype, void *recvbuf, int recvcount,
                                                                                        42
              MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
                                                                                        43
              MPI_Request *request)
                                                                                        44
                                                                                        45
int MPI_Alltoall_init_c(const void *sendbuf, MPI_Count sendcount,
              MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
                                                                                        46
              MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
              MPI_Request *request)
```

```
1
     Fortran 2008 binding
2
     MPI_Alltoall_init(sendbuf, sendcount, sendtype, recybuf, recycount,
3
                   recvtype, comm, info, request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
5
         INTEGER, INTENT(IN) :: sendcount, recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
10
         TYPE(MPI_Request), INTENT(OUT) :: request
11
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
12
     MPI_Alltoall_init(sendbuf, sendcount, sendtype, recvbuf, recvcount,
13
                   recvtype, comm, info, request, ierror)
14
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
15
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
16
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
19
         TYPE(MPI_Info), INTENT(IN) :: info
20
         TYPE(MPI_Request), INTENT(OUT) :: request
21
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
22
23
     Fortran binding
24
     MPI_ALLTOALL_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT,
25
                   RECVTYPE, COMM, INFO, REQUEST, IERROR)
26
         <type> SENDBUF(*), RECVBUF(*)
27
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST,
28
                   IERROR
         Creates a persistent collective communication request for the alltoall operation.
30
```

36 37

35

43 44 45

MPI_ALLT	OALLV_INIT(sendbuf, sendco recvtype, comm, info, re	unts, sdispls, sendtype, recvbuf, recvcounts, rdispls, quest)	1 2			
IN	sendbuf	starting address of send buffer (choice)	3			
IN	sendcounts	non-negative integer array (of length group size) specifying the number of elements to send to each rank	4 5 6 7			
IN	sdispls	Integer array (of length group size). Entry j specifies the displacement (relative to sendbuf) from which to take the outgoing data destined for process j	8 9 10			
IN	sendtype	data type of send buffer elements (handle)	11			
OUT	recvbuf	address of receive buffer (choice)	12 13			
IN	recvcounts	non-negative integer array (of length group size) specifying the number of elements that can be received from each rank	14 15 16 17			
IN	rdispls	integer array (of length group size). Entry i specifies the displacement (relative to recvbuf) at which to place the incoming data from process i	18 19 20			
IN	recvtype	data type of receive buffer elements (handle)	21			
IN	comm	communicator (handle)	22			
IN	info	info argument (handle)	23 24			
OUT	request	communication request (handle)	25			
			26			
C binding						
int MPI_A		! *sendbuf, const int sendcounts[],	28 29			
		<pre>, MPI_Datatype sendtype, void *recvbuf, s[], const int rdispls[],</pre>	30			
		pe, MPI_Comm comm, MPI_Info info,	31			
	MPI_Request *reques		32			
int MPT A	Alltoally init c(const yo	oid *sendbuf, const MPI_Count sendcounts[],	33			
1110 111 1_1		pls[], MPI_Datatype sendtype,	34			
		t MPI_Count recvcounts[],	35 36			
	const MPI_Aint rdisp	pls[], MPI_Datatype recvtype,	37			
	MPI_Comm comm, MPI_	Info info, MPI_Request *request)	38			
Fortran 2008 binding						
MPI_Alltoallv_init(sendbuf, sendcounts, sdispls, sendtype, recvbuf,						
recvcounts, rdispls, recvtype, comm, info, request, ierror)						
TYPE(*), DIMENSION(), INTENT(IN), ASYNCHRONOUS :: sendbuf						
<pre>INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),</pre>						
TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype						
TYPE(*), DIMENSION(), ASYNCHRONOUS :: recvbuf TYPE(MPI_Comm), INTENT(IN) :: comm						
						TYPE(MPI_Info), INTENT(IN) :: info

```
1
         TYPE(MPI_Request), INTENT(OUT) :: request
2
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Alltoallv_init(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
                  recvcounts, rdispls, recvtype, comm, info, request, ierror)
5
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
6
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
                   sendcounts(*), recvcounts(*)
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
9
                   rdispls(*)
10
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
11
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
12
         TYPE(MPI_Comm), INTENT(IN) :: comm
13
         TYPE(MPI_Info), INTENT(IN) :: info
14
         TYPE(MPI_Request), INTENT(OUT) :: request
15
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
16
17
     Fortran binding
18
     MPI_ALLTOALLV_INIT(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE, RECVBUF,
19
                  RECVCOUNTS, RDISPLS, RECVTYPE, COMM, INFO, REQUEST, IERROR)
20
         <type> SENDBUF(*), RECVBUF(*)
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*),
21
22
                   RECVTYPE, COMM, INFO, REQUEST, IERROR
```

Creates a persistent collective communication request for the alltoally operation.

MPI_ALLTOALLW_INIT(sendbuf, sendcounts, sdispls, sendtypes, recvbuf, recvcounts, rdispls, recvtypes, comm, info, request)						
IN	sendbuf	starting address of send buffer (choice)	3			
IN	sendcounts	integer array (of length group size) specifying the number of elements to send to each rank (array of non-negative integers)	4 5 6 7			
IN	sdispls	which to take the outgoing data destined for process	8 9 10 11			
IN	sendtypes	Array of datatypes (of length group size). Entry j specifies the type of data to send to process j (array of handles)	12 13 14 15			
OUT	recvbuf	11 ( ' 1 ( (1 ' )	16			
IN	recvcounts	number of elements that can be received from each rank (array of non-negative integers)	17 18 19			
IN	rdispls	integer array (of length group size). Entry i specifies the displacement in bytes (relative to recvbuf) at which to place the incoming data from process i (array of integers)	<ul><li>20</li><li>21</li><li>22</li><li>23</li><li>24</li></ul>			
IN	recvtypes	specifies the type of data received from process i	25 26 27			
IN	comm	communicator (handle)	28			
IN	info	info argument (handle)	29 30			
OUT	request	communication request (handle)	31			
C binding int MPI_Alltoallw_init(const void *sendbuf, const int sendcounts[],						
<pre>const MPI_Aint sdisp void *recvbuf, const const MPI_Aint rdisp</pre>		<pre>d *sendbuf, const MPI_Count sendcounts[], ls[], const MPI_Datatype sendtypes[], MPI_Count recvcounts[], ls[], const MPI_Datatype recvtypes[], nfo info, MPI Request *request)</pre>	39 40 41 42 43 44			
Fortran 2008 binding  MPI_Alltoallw_init(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,						

47

```
1
         INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),
2
                   recvcounts(*), rdispls(*)
         TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
                   recvtypes(*)
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
9
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
10
     MPI_Alltoallw_init(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
11
                   recvcounts, rdispls, recvtypes, comm, info, request, ierror)
12
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
13
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
14
                   sendcounts(*), recvcounts(*)
15
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
16
                   rdispls(*)
         TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
                   recvtypes(*)
19
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
20
         TYPE(MPI_Comm), INTENT(IN) :: comm
21
         TYPE(MPI_Info), INTENT(IN) :: info
22
         TYPE(MPI_Request), INTENT(OUT) :: request
23
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
24
25
     Fortran binding
26
     MPI_ALLTOALLW_INIT(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPES, RECVBUF,
27
                   RECVCOUNTS, RDISPLS, RECVTYPES, COMM, INFO, REQUEST, IERROR)
28
         <type> SENDBUF(*), RECVBUF(*)
29
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPES(*), RECVCOUNTS(*),
30
                   RDISPLS(*), RECVTYPES(*), COMM, INFO, REQUEST, IERROR
         Creates a persistent collective communication request for the alltoally operation.
```

**Unofficial Draft for Comment Only** 

```
6.13.7 Persistent Reduce
MPI_REDUCE_INIT(sendbuf, recvbuf, count, datatype, op, root, comm, info, request)
 IN
           sendbuf
                                      address of send buffer (choice)
 OUT
           recvbuf
                                      address of receive buffer (choice, significant only at
                                      root)
 IN
           count
                                      number of elements in send buffer (non-negative
                                      data type of elements of send buffer (handle)
 IN
           datatype
                                                                                       12
                                      reduce operation (handle)
 IN
           op
                                                                                       13
                                                                                       14
 IN
           root
                                      rank of root process (integer)
                                                                                       15
 IN
           comm
                                      communicator (handle)
                                                                                       16
           info
                                      info argument (handle)
 IN
                                                                                       18
 OUT
           request
                                      communication request (handle)
                                                                                       19
                                                                                       20
C binding
                                                                                      21
int MPI_Reduce_init(const void *sendbuf, void *recvbuf, int count,
                                                                                      22
              MPI_Datatype datatype, MPI_Op op, int root, MPI_Comm comm,
                                                                                      23
              MPI_Info info, MPI_Request *request)
int MPI_Reduce_init_c(const void *sendbuf, void *recvbuf, MPI_Count count,
              MPI_Datatype datatype, MPI_Op op, int root, MPI_Comm comm,
                                                                                       26
              MPI_Info info, MPI_Request *request)
                                                                                      27
                                                                                      28
Fortran 2008 binding
                                                                                      29
MPI_Reduce_init(sendbuf, recvbuf, count, datatype, op, root, comm, info,
                                                                                      30
              request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER, INTENT(IN) :: count, root
                                                                                      34
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      35
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                      36
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                      37
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Reduce_init(sendbuf, recvbuf, count, datatype, op, root, comm, info,
                                                                                      42
              request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                      43
                                                                                       44
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                       45
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                       46
    TYPE(MPI_Op), INTENT(IN) :: op
    INTEGER, INTENT(IN) :: root
```

```
1
         TYPE(MPI_Comm), INTENT(IN) :: comm
2
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
6
     MPI_REDUCE_INIT(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, ROOT, COMM, INFO.
                    REQUEST, IERROR)
          <type> SENDBUF(*), RECVBUF(*)
9
         INTEGER COUNT, DATATYPE, OP, ROOT, COMM, INFO, REQUEST, IERROR
10
11
         Creates a persistent collective communication request for the reduce operation.
12
13
     6.13.8 Persistent All-Reduce
14
15
16
     MPI_ALLREDUCE_INIT(sendbuf, recvbuf, count, datatype, op, comm, info, request)
17
       IN
                sendbuf
                                            starting address of send buffer (choice)
18
19
       OUT
                recvbuf
                                            starting address of receive buffer (choice)
20
       IN
                count
                                            number of elements in send buffer (non-negative
21
                                            integer)
22
                                            data type of elements of send buffer (handle)
       IN
                datatype
23
24
       IN
                op
                                            operation (handle)
       IN
                comm
                                            communicator (handle)
                info
       IN
                                            info argument (handle)
27
28
       OUT
                                            communication request (handle)
                request
29
30
     C binding
31
     int MPI_Allreduce_init(const void *sendbuf, void *recvbuf, int count,
32
                    MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
33
                    MPI_Info info, MPI_Request *request)
34
     int MPI_Allreduce_init_c(const void *sendbuf, void *recvbuf,
35
                    MPI_Count count, MPI_Datatype datatype, MPI_Op op,
36
                    MPI_Comm comm, MPI_Info info, MPI_Request *request)
37
38
     Fortran 2008 binding
39
     MPI_Allreduce_init(sendbuf, recvbuf, count, datatype, op, comm, info,
40
                    request, ierror)
41
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
42
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
43
         INTEGER, INTENT(IN) :: count
44
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
45
         TYPE(MPI_Op), INTENT(IN) :: op
46
         TYPE(MPI_Comm), INTENT(IN) :: comm
47
         TYPE(MPI_Info), INTENT(IN) :: info
```

```
TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Allreduce_init(sendbuf, recvbuf, count, datatype, op, comm, info,
              request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                       12
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                       13
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       14
                                                                                       15
Fortran binding
                                                                                       16
MPI_ALLREDUCE_INIT(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, INFO,
              REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
                                                                                       19
    INTEGER COUNT, DATATYPE, OP, COMM, INFO, REQUEST, IERROR
                                                                                       20
    Creates a persistent collective communication request for the allreduce operation.
                                                                                       21
                                                                                       22
6.13.9 Persistent Reduce-Scatter with Equal Blocks
                                                                                       23
                                                                                       24
MPI_REDUCE_SCATTER_BLOCK_INIT(sendbuf, recvbuf, recvcount, datatype, op, comm,
                                                                                       26
              info, request)
                                                                                       27
                                                                                       28
  IN
           sendbuf
                                      starting address of send buffer (choice)
                                                                                       29
  OUT
           recvbuf
                                      starting address of receive buffer (choice)
                                                                                       30
  IN
                                      element count per block (non-negative integer)
           recvcount
  IN
                                      data type of elements of send and receive buffers
           datatype
                                                                                       33
                                      (handle)
                                                                                       34
  IN
           op
                                      operation (handle)
                                                                                       35
  IN
                                      communicator (handle)
                                                                                       36
           comm
                                                                                       37
  IN
           info
                                      info argument (handle)
  OUT
           request
                                      communication request (handle)
C binding
int MPI_Reduce_scatter_block_init(const void *sendbuf, void *recvbuf,
                                                                                       42
              int recvcount, MPI_Datatype datatype, MPI_Op op,
                                                                                       43
              MPI_Comm comm, MPI_Info info, MPI_Request *request)
                                                                                       44
                                                                                       45
int MPI_Reduce_scatter_block_init_c(const void *sendbuf, void *recvbuf,
                                                                                       46
              MPI_Count recvcount, MPI_Datatype datatype, MPI_Op op,
              MPI_Comm comm, MPI_Info info, MPI_Request *request)
```

47

```
1
     Fortran 2008 binding
2
     MPI_Reduce_scatter_block_init(sendbuf, recvbuf, recvcount, datatype, op,
3
                   comm, info, request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
5
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
11
         TYPE(MPI_Request), INTENT(OUT) :: request
12
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
     MPI_Reduce_scatter_block_init(sendbuf, recvbuf, recvcount, datatype, op,
14
                   comm, info, request, ierror)
15
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
16
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
19
         TYPE(MPI_Op), INTENT(IN) :: op
20
         TYPE(MPI_Comm), INTENT(IN) :: comm
21
         TYPE(MPI_Info), INTENT(IN) :: info
22
         TYPE(MPI_Request), INTENT(OUT) :: request
23
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
24
25
     Fortran binding
26
     MPI_REDUCE_SCATTER_BLOCK_INIT(SENDBUF, RECVBUF, RECVCOUNT, DATATYPE, OP,
27
                   COMM, INFO, REQUEST, IERROR)
28
         <type> SENDBUF(*), RECVBUF(*)
29
         INTEGER RECVCOUNT, DATATYPE, OP, COMM, INFO, REQUEST, IERROR
30
         Creates a persistent collective communication request for the reduce-scatter with equal
31
     blocks operation.
32
33
```

```
6.13.10 Persistent Reduce-Scatter
MPI_REDUCE_SCATTER_INIT(sendbuf, recvbuf, recvcounts, datatype, op, comm, info,
              request)
  IN
           sendbuf
                                      starting address of send buffer (choice)
  OUT
           recvbuf
                                      starting address of receive buffer (choice)
  IN
           recvcounts
                                      non-negative integer array specifying the number of
                                      elements in result distributed to each process. This
                                      array must be identical on all calling processes.
                                                                                       12
  IN
           datatype
                                      data type of elements of input buffer (handle)
                                                                                       13
  IN
           op
                                      operation (handle)
                                                                                       14
                                                                                       15
  IN
           comm
                                      communicator (handle)
                                                                                       16
  IN
           info
                                      info argument (handle)
  OUT
           request
                                      communication request (handle)
                                                                                       18
                                                                                       19
C binding
                                                                                       20
                                                                                       21
int MPI_Reduce_scatter_init(const void *sendbuf, void *recvbuf,
                                                                                       22
              const int recvcounts[], MPI_Datatype datatype, MPI_Op op,
                                                                                       23
              MPI_Comm comm, MPI_Info info, MPI_Request *request)
int MPI_Reduce_scatter_init_c(const void *sendbuf, void *recvbuf,
              const MPI_Count recvcounts[], MPI_Datatype datatype,
              MPI_Op op, MPI_Comm comm, MPI_Info info, MPI_Request *request)
                                                                                       27
                                                                                       28
Fortran 2008 binding
                                                                                       29
MPI_Reduce_scatter_init(sendbuf, recvbuf, recvcounts, datatype, op, comm,
                                                                                       30
              info, request, ierror)
                                                                                       31
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
                                                                                       34
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                       35
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                       36
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                       37
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Reduce_scatter_init(sendbuf, recvbuf, recvcounts, datatype, op, comm,
              info, request, ierror)
                                                                                       42
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                       43
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                       44
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
                                                                                       45
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                       46
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                       47
    TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
1
         TYPE(MPI_Info), INTENT(IN) :: info
2
         TYPE(MPI_Request), INTENT(OUT) :: request
3
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
     MPI_REDUCE_SCATTER_INIT(SENDBUF, RECVBUF, RECVCOUNTS, DATATYPE, OP, COMM,
6
                    INFO, REQUEST, IERROR)
          <type> SENDBUF(*), RECVBUF(*)
         INTEGER RECVCOUNTS(*), DATATYPE, OP, COMM, INFO, REQUEST, IERROR
9
10
         Creates a persistent collective communication request for the reduce-scatter operation.
11
12
     6.13.11 Persistent Inclusive Scan
13
14
15
     MPI_SCAN_INIT(sendbuf, recvbuf, count, datatype, op, comm, info, request)
16
                sendbuf
                                            starting address of send buffer (choice)
       IN
17
18
       OUT
                 recvbuf
                                            starting address of receive buffer (choice)
19
       IN
                                            number of elements in input buffer (non-negative
                count
20
                                            integer)
21
       IN
                datatype
                                            data type of elements of input buffer (handle)
22
23
       IN
                                            operation (handle)
                op
24
       IN
                 comm
                                            communicator (handle)
       IN
                 info
                                            info argument (handle)
26
27
       OUT
                                            communication request (handle)
                 request
28
29
     C binding
30
     int MPI_Scan_init(const void *sendbuf, void *recvbuf, int count,
31
                    MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
32
                    MPI_Info info, MPI_Request *request)
33
     int MPI_Scan_init_c(const void *sendbuf, void *recvbuf, MPI_Count count,
34
                    MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
35
                    MPI_Info info, MPI_Request *request)
36
37
     Fortran 2008 binding
38
     MPI_Scan_init(sendbuf, recvbuf, count, datatype, op, comm, info, request,
39
                    ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
41
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
42
         INTEGER, INTENT(IN) :: count
43
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
44
         TYPE(MPI_Op), INTENT(IN) :: op
45
         TYPE(MPI_Comm), INTENT(IN) :: comm
46
         TYPE(MPI_Info), INTENT(IN) :: info
47
         TYPE(MPI_Request), INTENT(OUT) :: request
```

13 14

15 16

18

19

24

26

45

46

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Scan_init(sendbuf, recvbuf, count, datatype, op, comm, info, request,
               ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_SCAN_INIT(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, INFO, REQUEST,
               IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER COUNT, DATATYPE, OP, COMM, INFO, REQUEST, IERROR
    Creates a persistent collective communication request for the inclusive scan operation.
                                                                                       20
                                                                                       21
6.13.12 Persistent Exclusive Scan
                                                                                       22
                                                                                       23
MPI_EXSCAN_INIT(sendbuf, recvbuf, count, datatype, op, comm, info, request)
  IN
           sendbuf
                                      starting address of send buffer (choice)
                                                                                       27
  OUT
           recybuf
                                      starting address of receive buffer (choice)
                                                                                       28
  IN
                                      number of elements in input buffer (non-negative
                                                                                       29
           count
                                      integer)
                                                                                       30
  IN
                                      data type of elements of input buffer (handle)
           datatype
  IN
           op
                                      operation (handle)
                                                                                       34
  IN
                                      intra-communicator (handle)
           comm
                                                                                       35
  IN
           info
                                      info argument (handle)
                                                                                       36
  OUT
           request
                                      communication request (handle)
                                                                                       37
C binding
int MPI_Exscan_init(const void *sendbuf, void *recvbuf, int count,
              MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
              MPI_Info info, MPI_Request *request)
                                                                                       42
                                                                                       43
int MPI_Exscan_init_c(const void *sendbuf, void *recvbuf, MPI_Count count,
                                                                                       44
              MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
              MPI_Info info, MPI_Request *request)
```

Fortran 2008 binding

```
1
    MPI_Exscan_init(sendbuf, recvbuf, count, datatype, op, comm, info, request,
2
                   ierror)
3
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: count
6
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
11
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
12
     MPI_Exscan_init(sendbuf, recvbuf, count, datatype, op, comm, info, request,
13
14
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
15
         TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
16
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
17
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
19
         TYPE(MPI_Comm), INTENT(IN) :: comm
20
         TYPE(MPI_Info), INTENT(IN) :: info
21
         TYPE(MPI_Request), INTENT(OUT) :: request
22
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
23
24
     Fortran binding
25
     MPI_EXSCAN_INIT(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, INFO, REQUEST,
26
                   IERROR)
27
         <type> SENDBUF(*), RECVBUF(*)
28
         INTEGER COUNT, DATATYPE, OP, COMM, INFO, REQUEST, IERROR
29
         Creates a persistent collective communication request for the exclusive scan operation.
30
```

6.14 Correctness

31 32

33 34

35

36 37

38

A correct, portable program must invoke collective communications so that deadlock will not occur, whether collective communications are synchronizing or not. The following examples illustrate dangerous use of collective routines on intra-communicators.

**Example 6.25** The following is erroneous.

}

We assume that the group of comm is  $\{0,1\}$ . Two processes execute two broadcast operations in reverse order. If the operation is synchronizing then a deadlock will occur.

Collective operations must be executed in the same order at all members of the communication group.

#### **Example 6.26** The following is erroneous.

```
switch(rank) {
    case 0:
        MPI_Bcast(buf1, count, type, 0, comm0);
        MPI_Bcast(buf2, count, type, 2, comm2);
        break;
    case 1:
        MPI_Bcast(buf1, count, type, 1, comm1);
        MPI_Bcast(buf2, count, type, 0, comm0);
        break;
    case 2:
        MPI_Bcast(buf1, count, type, 2, comm2);
        MPI_Bcast(buf2, count, type, 1, comm1);
        break;
}
```

Assume that the group of comm0 is  $\{0,1\}$ , of comm1 is  $\{1,2\}$  and of comm2 is  $\{2,0\}$ . If the broadcast is a synchronizing operation, then there is a cyclic dependency: the broadcast in comm2 completes only after the broadcast in comm0; the broadcast in comm0 completes only after the broadcast in comm1; and the broadcast in comm1 completes only after the broadcast in comm2. Thus, the code will deadlock.

Collective operations must be executed in an order so that no cyclic dependencies occur. Nonblocking collective operations can alleviate this issue.

#### **Example 6.27** The following is erroneous.

```
switch(rank) {
   case 0:
        MPI_Bcast(buf1, count, type, 0, comm);
        MPI_Send(buf2, count, type, 1, tag, comm);
        break;
   case 1:
        MPI_Recv(buf2, count, type, 0, tag, comm, status);
        MPI_Bcast(buf1, count, type, 0, comm);
        break;
}
```

Process zero executes a broadcast, followed by a blocking send operation. Process one first executes a blocking receive that matches the send, followed by broadcast call that matches the broadcast of process zero. This program may deadlock. The broadcast call on process zero may block until process one executes the matching broadcast call, so that the send is not executed. Process one will definitely block on the receive and so, in this case, never executes the broadcast.

The relative order of execution of collective operations and point-to-point operations should be such, so that even if the collective operations and the point-to-point operations are synchronizing, no deadlock will occur.

#### **Example 6.28** An unsafe, non-deterministic program.

```
switch(rank) {
   case 0:
       MPI_Bcast(buf1, count, type, 0, comm);
       MPI_Send(buf2, count, type, 1, tag, comm);
       break;
   case 1:
       MPI_Recv(buf2, count, type, MPI_ANY_SOURCE, tag, comm, status);
       MPI_Bcast(buf1, count, type, 0, comm);
                                                     tag, comm, status);
       MPI_Recv(buf2, count, type, MPI_ANY_SOURCE,
       break;
   case 2:
       MPI_Send(buf2, count, type, 1, tag, comm);
       MPI_Bcast(buf1, count, type, 0, comm);
       break:
}
```

All three processes participate in a broadcast. Process 0 sends a message to process 1 after the broadcast, and process 2 sends a message to process 1 before the broadcast. Process 1 receives before and after the broadcast, with a wildcard source argument.

Two possible executions of this program, with different matchings of sends and receives, are illustrated in Figure 6.12. Note that the second execution has the peculiar effect that a send executed after the broadcast is received at another node before the broadcast. This example illustrates the fact that one should not rely on collective communication functions to have particular synchronization effects. A program that works correctly only when the first execution occurs (only when broadcast is synchronizing) is erroneous.

Finally, in multithreaded implementations, one can have more than one, concurrently executing, collective communication call at a process. In these situations, it is the user's responsibility to ensure that the same communicator is not used concurrently by two different collective communication calls at the same process.

Advice to implementors. Assume that broadcast is implemented using point-to-point MPI communication. Suppose the following two rules are followed.

- 1. All receives specify their source explicitly (no wildcards).
- 2. Each process sends all messages that pertain to one collective call before sending any message that pertain to a subsequent collective call.

Then, messages belonging to successive broadcasts cannot be confused, as the order of point-to-point messages is preserved.

It is the implementor's responsibility to ensure that point-to-point messages are not confused with collective messages. One way to accomplish this is, whenever a communicator is created, to also create a "hidden communicator" for collective communication. One could achieve a similar effect more cheaply, for example, by using a hidden




Figure 6.12: A race condition causes non-deterministic matching of sends and receives. One cannot rely on synchronization from a broadcast to make the program deterministic.

tag or context bit to indicate whether the communicator is used for point-to-point or collective communication. (End of advice to implementors.)

**Example 6.29** Blocking and nonblocking collective operations can be interleaved, i.e., a blocking collective operation can be posted even if there is a nonblocking collective operation outstanding.

```
MPI_Request req;
MPI_Ibarrier(comm, &req);
MPI_Bcast(buf1, count, type, 0, comm);
MPI_Wait(&req, MPI_STATUS_IGNORE);
```

Each process starts a nonblocking barrier operation, participates in a blocking broadcast and then waits until every other process started the barrier operation. This effectively turns the broadcast into a synchronizing broadcast with possible communication/communication overlap (MPI\_Bcast is allowed, but not required to synchronize).

**Example 6.30** The starting order of collective operations on a particular communicator defines their matching. The following example shows an erroneous matching of different collective operations on the same communicator.

18

19

20 21

37

38

39

41 42 43

44

45

46 47

```
1
    MPI_Request req;
2
     switch(rank) {
3
         case 0:
4
             /* erroneous matching */
5
             MPI_Ibarrier(comm, &req);
6
             MPI_Bcast(buf1, count, type, 0, comm);
             MPI_Wait(&req, MPI_STATUS_IGNORE);
             break;
9
         case 1:
10
             /* erroneous matching */
11
             MPI_Bcast(buf1, count, type, 0, comm);
12
             MPI_Ibarrier(comm, &req);
13
             MPI_Wait(&req, MPI_STATUS_IGNORE);
14
             break;
15
     }
16
```

This ordering would match MPI\_lbarrier on rank 0 with MPI\_Bcast on rank 1 which is erroneous and the program behavior is undefined. However, if such an order is required, the user must create different duplicate communicators and perform the operations on them. If started with two processes, the following program would be correct:

```
MPI_Request req;
22
     MPI_Comm dupcomm;
23
     MPI_Comm_dup(comm, &dupcomm);
24
     switch(rank) {
25
         case 0:
26
              MPI_Ibarrier(comm, &req);
27
             MPI_Bcast(buf1, count, type, 0, dupcomm);
28
             MPI_Wait(&req, MPI_STATUS_IGNORE);
29
              break;
30
         case 1:
31
              MPI_Bcast(buf1, count, type, 0, dupcomm);
              MPI_Ibarrier(comm, &req);
33
             MPI_Wait(&req, MPI_STATUS_IGNORE);
34
              break;
35
     }
36
```

Advice to users. The use of different communicators offers some flexibility regarding the matching of nonblocking collective operations. In this sense, communicators could be used as an equivalent to tags. However, communicator construction might induce overheads so that this should be used carefully. (End of advice to users.)

**Example 6.31** Nonblocking collective operations can rely on the same progression rules as nonblocking point-to-point messages. Thus, if started with two processes, the following program is a valid MPI program and is guaranteed to terminate:

case 1:

```
MPI_Request req;
switch(rank) {
    case 0:
      MPI_Ibarrier(comm, &req);
      MPI_Wait(&req, MPI_STATUS_IGNORE);
      MPI_Send(buf, count, dtype, 1, tag, comm);
      break;
    case 1:
      MPI_Ibarrier(comm, &req);
      MPI_Recv(buf, count, dtype, 0, tag, comm, MPI_STATUS_IGNORE);
      MPI_Wait(&req, MPI_STATUS_IGNORE);
                                                                                       12
                                                                                       13
      break;
}
                                                                                       14
                                                                                       15
    The MPI library must progress the barrier in the MPI_Recv call. Thus, the MPI_Wait
                                                                                       16
call in rank 0 will eventually complete, which enables the matching MPI_Send so all calls
eventually return.
                                                                                       18
                                                                                       19
Example 6.32 Blocking and nonblocking collective operations do not match. The fol-
                                                                                       20
lowing example is erroneous.
                                                                                       21
                                                                                       22
MPI_Request req;
                                                                                       23
                                                                                       24
switch(rank) {
    case 0:
                                                                                       26
      /* erroneous false matching of Alltoall and Ialltoall */
                                                                                       27
      MPI_Ialltoall(sbuf, scnt, stype, rbuf, rcnt, rtype, comm, &req);
                                                                                       28
      MPI_Wait(&req, MPI_STATUS_IGNORE);
                                                                                       29
      break;
                                                                                       30
    case 1:
                                                                                       31
      /* erroneous false matching of Alltoall and Ialltoall */
      MPI_Alltoall(sbuf, scnt, stype, rbuf, rcnt, rtype, comm);
                                                                                       33
      break;
                                                                                       34
35
                                                                                       36
                                                                                       37
Example 6.33 Collective and point-to-point requests can be mixed in functions that
                                                                                       38
enable multiple completions. If started with two processes, the following program is valid.
MPI_Request reqs[2];
                                                                                       42
switch(rank) {
    case 0:
                                                                                       43
                                                                                       44
      MPI_Ibarrier(comm, &reqs[0]);
      MPI_Send(buf, count, dtype, 1, tag, comm);
                                                                                       45
      MPI_Wait(&reqs[0], MPI_STATUS_IGNORE);
                                                                                       46
      break;
```

```
MPI_Irecv(buf, count, dtype, 0, tag, comm, &reqs[0]);
MPI_Ibarrier(comm, &reqs[1]);
MPI_Waitall(2, reqs, MPI_STATUSES_IGNORE);
break;
break;
```

The MPI\_Waitall call returns only after the barrier and the receive completed.

**Example 6.34** Multiple nonblocking collective operations can be outstanding on a single communicator and match in order.

```
MPI_Request reqs[3];
12
13
     compute(buf1);
14
     MPI_Ibcast(buf1, count, type, 0, comm, &reqs[0]);
15
     compute(buf2);
16
     MPI_Ibcast(buf2, count, type, 0, comm, &reqs[1]);
17
     compute(buf3);
18
     MPI_Ibcast(buf3, count, type, 0, comm, &reqs[2]);
19
     MPI_Waitall(3, reqs, MPI_STATUSES_IGNORE);
20
```

Advice to users. Pipelining and double-buffering techniques can efficiently be used to overlap computation and communication. However, having too many outstanding requests might have a negative impact on performance. (End of advice to users.)

Advice to implementors. The use of pipelining may generate many outstanding requests. A high-quality hardware-supported implementation with limited resources should be able to fall back to a software implementation if its resources are exhausted. In this way, the implementation could limit the number of outstanding requests only by the available memory. (End of advice to implementors.)

31 Example (

**Example 6.35** Nonblocking collective operations can also be used to enable simultaneous collective operations on multiple overlapping communicators (see Figure 6.13). The following example is started with three processes and three communicators. The first communicator comm1 includes ranks 0 and 1, comm2 includes ranks 1 and 2, and comm3 spans ranks 0 and 2. It is not possible to perform a blocking collective operation on all communicators because there exists no deadlock-free order to invoke them. However, nonblocking collective operations can easily be used to achieve this task.

```
39
     MPI_Request reqs[2];
40
41
42
     switch(rank) {
         case 0:
43
           MPI_Iallreduce(sbuf1, rbuf1, count, dtype, MPI_SUM, comm1, &reqs[0]);
44
           MPI_Iallreduce(sbuf3, rbuf3, count, dtype, MPI_SUM, comm3, &reqs[1]);
45
           break;
46
47
         case 1:
           MPI_Iallreduce(sbuf1, rbuf1, count, dtype, MPI_SUM, comm1, &reqs[0]);
```




Figure 6.13: Example with overlapping communicators.

```
MPI_Iallreduce(sbuf2, rbuf2, count, dtype, MPI_SUM, comm2, &reqs[1]);
    break;
    case 2:
        MPI_Iallreduce(sbuf2, rbuf2, count, dtype, MPI_SUM, comm2, &reqs[0]);
        MPI_Iallreduce(sbuf3, rbuf3, count, dtype, MPI_SUM, comm3, &reqs[1]);
        break;
}
MPI_Waitall(2, reqs, MPI_STATUSES_IGNORE);
```


Advice to users. This method can be useful if overlapping neighboring regions (halo or ghost zones) are used in collective operations. The sequence of the two calls in each process is irrelevant because the two nonblocking operations are performed on different communicators. (End of advice to users.)

**Example 6.36** The progress of multiple outstanding nonblocking collective operations is completely independent.

```
MPI_Request reqs[2];

compute(buf1);
MPI_Ibcast(buf1, count, type, 0, comm, &reqs[0]);
compute(buf2);
MPI_Ibcast(buf2, count, type, 0, comm, &reqs[1]);
MPI_Wait(&reqs[1], MPI_STATUS_IGNORE);
/* nothing is known about the status of the first bcast here */
MPI_Wait(&reqs[0], MPI_STATUS_IGNORE);
```

Finishing the second MPI\_IBCAST is completely independent of the first one. This means that it is not guaranteed that the first broadcast operation is finished or even started after the second one is completed via reqs[1].



## Chapter 7

# Groups, Contexts, Communicators, and Caching

#### 7.1 Introduction

This chapter introduces MPI features that support the development of parallel libraries. Parallel libraries are needed to encapsulate the distracting complications inherent in parallel implementations of key algorithms. They help to ensure consistent correctness of such procedures, and provide a "higher level" of portability than MPI itself can provide. As such, libraries prevent each programmer from repeating the work of defining consistent data structures, data layouts, and methods that implement key algorithms (such as matrix operations). Since the best libraries come with several variations on parallel systems (different data layouts, different strategies depending on the size of the system or problem, or type of floating point), this too needs to be hidden from the user.

We refer the reader to [62] and [4] for further information on writing libraries in MPI, using the features described in this chapter.

#### 7.1.1 Features Needed to Support Libraries

The key features needed to support the creation of robust parallel libraries are as follows:

- Safe communication space, that guarantees that libraries can communicate as they need to, without conflicting with communication extraneous to the library,
- Group scope for collective operations, that allow libraries to avoid unnecessarily synchronizing uninvolved processes (potentially running unrelated code),
- Abstract process naming to allow libraries to describe their communication in terms suitable to their own data structures and algorithms,
- The ability to "adorn" a set of communicating processes with additional user-defined attributes, such as extra collective operations. This mechanism should provide a means for the user or library writer effectively to extend a message-passing notation.

In addition, a unified mechanism or object is needed for conveniently denoting communication context, the group of communicating processes, to house abstract process naming, and to store adornments.

#### 7.1.2 MPI's Support for Libraries

The corresponding concepts that MPI provides, specifically to support robust libraries, are as follows:

- Contexts of communication,
- Groups of processes,
- Virtual topologies,
- Attribute caching.
- Communicators.

Communicators (see [22, 60, 64]) encapsulate all of these ideas in order to provide the appropriate scope for all communication operations in MPI. Communicators are divided into two kinds: intra-communicators for operations within a single group of processes and inter-communicators for operations between two groups of processes.

Caching. Communicators (see below) provide a "caching" mechanism that allows one to associate new attributes with communicators, on par with MPI built-in features. This can be used by advanced users to adorn communicators further, and by MPI to implement some communicator functions. For example, the virtual-topology functions described in Chapter 8 are likely to be supported this way.

Groups. Groups define an ordered collection of processes, each with a rank, and it is this group that defines the low-level names for inter-process communication (ranks are used for sending and receiving). Thus, groups define a scope for process names in point-to-point communication. In addition, groups define the scope of collective operations. Groups may be manipulated separately from communicators in MPI, but only communicators can be used in communication operations.

Intra-Communicators. The most commonly used means for message passing in MPI is via intra-communicators. Intra-communicators contain an instance of a group, contexts of communication for both point-to-point and collective communication, and the ability to include virtual topology and other attributes. These features work as follows:

- Contexts provide the ability to have separate safe "universes" of message-passing in MPI. A context is akin to an additional tag that differentiates messages. The system manages this differentiation process. The use of separate communication contexts by distinct libraries (or distinct library invocations) insulates communication internal to the library execution from external communication. This allows the invocation of the library even if there are pending communications on "other" communicators, and avoids the need to synchronize entry or exit into library code. Pending point-to-point communications are also guaranteed not to interfere with collective communications within a single communicator.
- Groups define the participants in the communication (see above) of a communicator.

- A virtual topology defines a special mapping of the ranks in a group to and from a topology. Special constructors for communicators are defined in Chapter 8 to provide this feature. Intra-communicators as described in this chapter do not have topologies.
- Attributes define the local information that the user or library has added to a communicator for later reference.

Advice to users. The practice in many communication libraries is that there is a unique, predefined communication universe that includes all processes available when the parallel program is initiated; the processes are assigned consecutive ranks. Participants in a point-to-point communication are identified by their rank; a collective communication (such as broadcast) always involves all processes. When using the World Model (Section 11.2), this practice can be followed in MPI by using the predefined communicator MPI\_COMM\_WORLD. Users who are satisfied with this practice can plug in MPI\_COMM\_WORLD wherever a communicator argument is required, and can consequently disregard the rest of this chapter. (End of advice to users.)

Inter-Communicators. The discussion has dealt so far with intra-communication: communication within a group. MPI also supports inter-communication: communication between two non-overlapping groups. When an application is built by composing several parallel modules, it is convenient to allow one module to communicate with another using local ranks for addressing within the second module. This is especially convenient in a client-server computing paradigm, where either client or server are parallel. The support of inter-communication also provides a mechanism for the extension of MPI to a dynamic model where not all processes are preallocated at initialization time. In such a situation, it becomes necessary to support communication across "universes." Inter-communication is supported by objects called inter-communicators. These objects bind two groups together with communication contexts shared by both groups. For inter-communicators, these features work as follows:

- Contexts provide the ability to have a separate safe "universe" of message-passing between the two groups. A send in the local group is always a receive in the remote group, and vice versa. The system manages this differentiation process. The use of separate communication contexts by distinct libraries (or distinct library invocations) insulates communication internal to the library execution from external communication. This allows the invocation of the library even if there are pending communications on "other" communicators, and avoids the need to synchronize entry or exit into library code.
- A local and remote group specify the recipients and destinations for an inter-communicator.
- Virtual topology is undefined for an inter-communicator.
- As before, attributes cache defines the local information that the user or library has added to a communicator for later reference.

MPI provides mechanisms for creating and manipulating inter-communicators. They are used for point-to-point and collective communication in an related manner to intra-communicators. Users who do not need inter-communication in their applications can safely

ignore this extension. Users who require inter-communication between overlapping groups must layer this capability on top of MPI.

## 7.2 Basic Concepts

In this section, we turn to a more formal definition of the concepts introduced above.

## 7.2.1 Groups

A group is an ordered set of process identifiers (henceforth processes); processes are implementation-dependent objects. Each process in a group is associated with an integer rank. Ranks are contiguous and start from zero. Groups are represented by opaque group objects, and hence cannot be directly transferred from one process to another. A group is used within a communicator to describe the participants in a communication "universe" and to rank such participants (thus giving them unique names within that "universe" of communication).

There is a special pre-defined group: MPI\_GROUP\_EMPTY, which is a group with no members. The predefined constant MPI\_GROUP\_NULL is the value used for invalid group handles.

Advice to users. MPI\_GROUP\_EMPTY, which is a valid handle to an empty group, should not be confused with MPI\_GROUP\_NULL, which in turn is an invalid handle. The former may be used as an argument to group operations; the latter, which is returned when a group is freed, is not a valid argument. (*End of advice to users*.)

Advice to implementors. A group may be represented by a virtual-to-real process-address-translation table. Each communicator object (see below) would have a pointer to such a table.

Simple implementations of MPI will enumerate groups, such as in a table. However, more advanced data structures make sense in order to improve scalability and memory usage with large numbers of processes. Such implementations are possible with MPI. (End of advice to implementors.)

## 7.2.2 Contexts

A **context** is a property of communicators (defined next) that allows partitioning of the communication space. A message sent in one context cannot be received in another context. Furthermore, where permitted, collective operations are independent of pending point-to-point operations. Contexts are not explicit MPI objects; they appear only as part of the realization of communicators (below).

Advice to implementors. Distinct communicators in the same process have distinct contexts. A context is essentially a system-managed tag (or tags) needed to make a communicator safe for point-to-point and MPI-defined collective communication. Safety means that collective and point-to-point communication within one communicator do not interfere, and that communication over distinct communicators don't interfere.

A possible implementation for a context is as a supplemental tag attached to messages on send and matched on receive. Each intra-communicator stores the value of its two tags (one for point-to-point and one for collective communication). Communicator-generating functions use a collective communication to agree on a new group-wide unique context.

Analogously, in inter-communication, two context tags are stored per communicator, one used by group A to send and group B to receive, and a second used by group B to send and for group A to receive.

Since contexts are not explicit objects, other implementations are also possible. (End of advice to implementors.)

#### 7.2.3 Intra-Communicators

Intra-communicators bring together the concepts of group and context. To support implementation-specific optimizations, and application topologies (defined in the next chapter, Chapter 8), communicators may also "cache" additional information (see Section 7.7). MPI communication operations reference communicators to determine the scope and the "communication universe" in which a point-to-point or collective operation is to operate.

Each communicator contains a group of valid participants; this group always includes the local process. The source and destination of a message is identified by process rank within that group.

For collective communication, the intra-communicator specifies the set of processes that participate in the collective operation (and their order, when significant). Thus, the communicator restricts the "spatial" scope of communication, and provides machine-independent process addressing through ranks.

Intra-communicators are represented by opaque **intra-communicator objects**, and hence cannot be directly transferred from one process to another.

#### 7.2.4 Predefined Intra-Communicators

When using the World Model for MPI initialization, an initial intra-communicator MPI\_COMM\_WORLD of all processes the local process can communicate with after initialization (itself included) is defined once MPI\_INIT or MPI\_INIT\_THREAD has been called. In addition, the communicator MPI\_COMM\_SELF is provided, which includes only the process itself. When using the Sessions Model (Section 11.3) for initialization of MPI resources, MPI\_COMM\_WORLD and MPI\_COMM\_SELF are not valid for use as a communicator. See the discussion concerning use of MPI named constants in 2.5.4 for valid uses of MPI\_COMM\_WORLD and MPI\_COMM\_SELF prior to initialization of MPI.

The predefined constant MPI\_COMM\_NULL is the value used for invalid communicator handles.

In a static-process-model implementation of MPI, all processes that participate in the computation are available after MPI is initialized. For this case, MPI\_COMM\_WORLD is a communicator of all processes available for the computation; this communicator has the same value in all processes. In an implementation of MPI where processes can dynamically join an MPI execution, it may be the case that a process starts an MPI computation without having access to all other processes. In such situations, MPI\_COMM\_WORLD is a communicator incorporating all processes with which the joining process can immediately

communicate. Therefore,  $\mathsf{MPI\_COMM\_WORLD}$  may simultaneously represent disjoint groups in different processes.

All MPI implementations are required to provide the MPI\_COMM\_WORLD communicator. It cannot be deallocated during the life of a process. The group corresponding to this communicator does not appear as a pre-defined constant, but it may be accessed using MPI\_COMM\_GROUP (see below). MPI does not specify the correspondence between the process rank in MPI\_COMM\_WORLD and its (machine-dependent) absolute address. Neither does MPI specify the function of the host process, if any. Other implementation-dependent, predefined communicators may also be provided.

## 7.3 Group Management

This section describes the manipulation of process groups in MPI. These operations are local and their execution does not require interprocess communication.

```
7.3.1 Group Accessors
```

```
MPI_GROUP_SIZE(group, size)
 IN
                                    group (handle)
          group
 OUT
                                     number of processes in the group (integer)
          size
C binding
int MPI_Group_size(MPI_Group group, int *size)
Fortran 2008 binding
MPI_Group_size(group, size, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_GROUP_SIZE(GROUP, SIZE, IERROR)
    INTEGER GROUP, SIZE, IERROR
```

```
MPI_GROUP_RANK(group, rank)
```

```
IN group group (handle)

OUT rank rank of the calling process in group, or MPI_UNDEFINED if the process is not a member (integer)
```

```
C binding
```

```
int MPI_Group_rank(MPI_Group group, int *rank)
```

Fortran 2008 binding

C binding

```
MPI_Group_rank(group, rank, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group
    INTEGER, INTENT(OUT) :: rank
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_GROUP_RANK(GROUP, RANK, IERROR)
    INTEGER GROUP, RANK, IERROR
MPI_GROUP_TRANSLATE_RANKS(group1, n, ranks1, group2, ranks2)
                                                                                         12
  IN
                                       group1 (handle)
           group1
                                                                                         13
  IN
                                       number of ranks in ranks1 and ranks2 arrays (integer)
           n
                                                                                         14
  IN
           ranks1
                                       array of zero or more valid ranks in group1
                                                                                         15
                                                                                         16
                                       group2 (handle)
  IN
           group2
                                       array of corresponding ranks in group2,
  OUT
            ranks2
                                                                                         18
                                       MPI_UNDEFINED when no correspondence exists.
                                                                                         19
                                                                                         20
C binding
                                                                                         21
int MPI_Group_translate_ranks(MPI_Group group1, int n, const int ranks1[],
                                                                                         22
               MPI_Group group2, int ranks2[])
                                                                                         23
                                                                                         24
Fortran 2008 binding
MPI_Group_translate_ranks(group1, n, ranks1, group2, ranks2, ierror)
                                                                                         26
    TYPE(MPI_Group), INTENT(IN) :: group1, group2
                                                                                         27
    INTEGER, INTENT(IN) :: n, ranks1(n)
    INTEGER, INTENT(OUT) :: ranks2(n)
                                                                                         28
                                                                                         29
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                         30
Fortran binding
MPI_GROUP_TRANSLATE_RANKS(GROUP1, N, RANKS1, GROUP2, RANKS2, IERROR)
    INTEGER GROUP1, N, RANKS1(*), GROUP2, RANKS2(*), IERROR
                                                                                         33
                                                                                         34
    This function is important for determining the relative numbering of the same processes
                                                                                         35
in two different groups. For instance, if one knows the ranks of certain processes in the group
                                                                                         36
of MPI_COMM_WORLD, one might want to know their ranks in a subset of that group.
                                                                                         37
    MPI_PROC_NULL is a valid rank for input to MPI_GROUP_TRANSLATE_RANKS, which
returns MPI_PROC_NULL as the translated rank.
                                                                                         39
MPI_GROUP_COMPARE(group1, group2, result)
                                                                                         41
                                                                                         42
  IN
           group1
                                       first group (handle)
                                                                                         43
  IN
           group2
                                       second group (handle)
                                                                                         44
  OUT
           result
                                       result (integer)
                                                                                         45
                                                                                         46
```

#### **Unofficial Draft for Comment Only**

int MPI\_Group\_compare(MPI\_Group group1, MPI\_Group group2, int \*result)

```
Fortran 2008 binding
```

```
MPI_Group_compare(group1, group2, result, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group1, group2
    INTEGER, INTENT(OUT) :: result
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_GROUP_COMPARE(GROUP1, GROUP2, RESULT, IERROR)
    INTEGER GROUP1, GROUP2, RESULT, IERROR
```

MPI\_IDENT results if the group members and group order is exactly the same in both groups. This happens for instance if group1 and group2 are the same handle. MPI\_SIMILAR results if the group members are the same but the order is different. MPI\_UNEQUAL results otherwise.

## 7.3.2 Group Constructors

MPI provides two approaches to constructing groups. In the first approach, MPI procedures are provided to subset and superset existing groups. These constructors construct new groups from existing groups. In the second approach, a group is created using a session handle and associated process set. This second approach is available when using the Sessions Model. With both approaches, these are local operations, and distinct groups may be defined on different processes; a process may also define a group that does not include itself. Consistent definitions are required when groups are used as arguments in communicator-building functions. When using the World Model for initializing MPI, the base group, upon which all other groups are defined, is the group associated with the initial communicator MPI\_COMM\_WORLD (accessible through the function MPI\_COMM\_GROUP).

Rationale. In what follows, there is no group duplication function analogous to MPI\_COMM\_DUP, defined later in this chapter. There is no need for a group duplicator. A group, once created, can have several references to it by making copies of the handle. The following constructors address the need for subsets and supersets of existing groups. (End of rationale.)

Advice to implementors. Each group constructor behaves as if it returned a new group object. When this new group is a copy of an existing group, then one can avoid creating such new objects, using a reference-count mechanism. (End of advice to implementors.)

```
MPI_COMM_GROUP(comm, group)
```

```
IN comm communicator (handle)

OUT group group corresponding to comm (handle)
```

#### C binding

```
int MPI_Comm_group(MPI_Comm comm, MPI_Group *group)
```

#### Fortran 2008 binding

```
MPI_Comm_group(comm, group, ierror)
```

```
TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Group), INTENT(OUT) :: group
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_COMM_GROUP(COMM, GROUP, IERROR)
    INTEGER COMM, GROUP, IERROR
    MPI_COMM_GROUP returns in group a handle to the group of comm.
MPI_GROUP_UNION(group1, group2, newgroup)
                                     first group (handle)
                                                                                     12
 IN
           group1
                                                                                     13
 IN
           group2
                                     second group (handle)
                                                                                     14
 OUT
           newgroup
                                     union group (handle)
                                                                                     15
                                                                                     16
C binding
                                                                                     18
int MPI_Group_union(MPI_Group group1, MPI_Group group2,
              MPI_Group *newgroup)
                                                                                     19
                                                                                     20
Fortran 2008 binding
                                                                                     21
MPI_Group_union(group1, group2, newgroup, ierror)
                                                                                     22
    TYPE(MPI_Group), INTENT(IN) :: group1, group2
                                                                                     23
    TYPE(MPI_Group), INTENT(OUT) :: newgroup
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                     26
Fortran binding
MPI_GROUP_UNION(GROUP1, GROUP2, NEWGROUP, IERROR)
                                                                                     27
    INTEGER GROUP1, GROUP2, NEWGROUP, IERROR
                                                                                     28
                                                                                     29
                                                                                     30
MPI_GROUP_INTERSECTION(group1, group2, newgroup)
 IN
                                     first group (handle)
           group1
 IN
                                     second group (handle)
                                                                                     34
           group2
                                                                                     35
 OUT
           newgroup
                                     intersection group (handle)
                                                                                     36
                                                                                     37
C binding
                                                                                     38
int MPI_Group_intersection(MPI_Group group1, MPI_Group group2,
              MPI_Group *newgroup)
Fortran 2008 binding
                                                                                     42
MPI_Group_intersection(group1, group2, newgroup, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group1, group2
                                                                                     43
    TYPE(MPI_Group), INTENT(OUT) :: newgroup
                                                                                     44
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                     45
                                                                                     46
Fortran binding
MPI_GROUP_INTERSECTION(GROUP1, GROUP2, NEWGROUP, IERROR)
```

1 INTEGER GROUP1, GROUP2, NEWGROUP, IERROR 2 3 4 MPI\_GROUP\_DIFFERENCE(group1, group2, newgroup) 5 IN group1 first group (handle) 6 IN group2 second group (handle) 7 OUT newgroup difference group (handle) 9 10 C binding 11 int MPI\_Group\_difference(MPI\_Group group1, MPI\_Group group2, 12 MPI\_Group \*newgroup) 13 Fortran 2008 binding 14 MPI\_Group\_difference(group1, group2, newgroup, ierror) 15TYPE(MPI\_Group), INTENT(IN) :: group1, group2 16 TYPE(MPI\_Group), INTENT(OUT) :: newgroup 17 INTEGER, OPTIONAL, INTENT(OUT) :: ierror 18 19 Fortran binding 20 MPI\_GROUP\_DIFFERENCE(GROUP1, GROUP2, NEWGROUP, IERROR) 21 INTEGER GROUP1, GROUP2, NEWGROUP, IERROR 22 23 The set-like operations are defined as follows: 24 union All elements of the first group (group1), followed by all elements of second group 25 (group2) not in the first group. 26 intersect all elements of the first group that are also in the second group, ordered as in 27 the first group. 28 29 difference all elements of the first group that are not in the second group, ordered as in 30 the first group. 31 32 Note that for these operations the order of processes in the output group is determined primarily by order in the first group (if possible) and then, if necessary, by order in the 33 34 second group. Neither union nor intersection are commutative, but both are associative. The new group can be empty, that is, equal to MPI\_GROUP\_EMPTY. 35 36 37 MPI\_GROUP\_INCL(group, n, ranks, newgroup) 38 39 IN group (handle) group IN number of elements in array ranks (and size of n 41 newgroup) (integer) 42 IN ranks of processes in group to appear in newgroup

47

OUT

C binding

43

44

45

46

48

ranks

newgroup

(array of integers)

by ranks (handle)

new group derived from above, in the order defined

#### Fortran 2008 binding

```
MPI_Group_incl(group, n, ranks, newgroup, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group
    INTEGER, INTENT(IN) :: n, ranks(n)
    TYPE(MPI_Group), INTENT(OUT) :: newgroup
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_GROUP_INCL(GROUP, N, RANKS, NEWGROUP, IERROR)
INTEGER GROUP, N, RANKS(*), NEWGROUP, IERROR
```

The function MPI\_GROUP\_INCL creates a group newgroup that consists of the n processes in group with ranks  $ranks[0], \ldots, ranks[n-1]$ ; the process with rank i in newgroup is the process with rank ranks[i] in group. Each of the n elements of ranks must be a valid rank in group and all elements must be distinct, or else the program is erroneous. If n=0, then newgroup is MPI\_GROUP\_EMPTY. This function can, for instance, be used to reorder the elements of a group. See also MPI\_GROUP\_COMPARE.

#### MPI\_GROUP\_EXCL(group, n, ranks, newgroup)

IN	group	group (handle)
IN	n	number of elements in array ranks (integer)
IN	ranks	array of integer ranks of processes in group not to
		appear in newgroup
OUT	newgroup	new group derived from above, preserving the order
		defined by group (handle)

#### C binding

#### Fortran 2008 binding

```
MPI_Group_excl(group, n, ranks, newgroup, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group
    INTEGER, INTENT(IN) :: n, ranks(n)
    TYPE(MPI_Group), INTENT(OUT) :: newgroup
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_GROUP_EXCL(GROUP, N, RANKS, NEWGROUP, IERROR)
    INTEGER GROUP, N, RANKS(*), NEWGROUP, IERROR
```

The function MPI\_GROUP\_EXCL creates a group of processes newgroup that is obtained by deleting from group those processes with ranks ranks[0],..., ranks[n-1]. The ordering of processes in newgroup is identical to the ordering in group. Each of the n elements of ranks

must be a valid rank in group and all elements must be distinct; otherwise, the program is erroneous. If n = 0, then newgroup is identical to group.

3 4 5

6

7

8

9

10

11

12

1

2

```
MPI_GROUP_RANGE_INCL(group, n, ranges, newgroup)
```

```
IN
                                           group (handle)
           group
IN
                                            number of triplets in array ranges (integer)
           n
IN
           ranges
                                            a one-dimensional array of integer triplets, of the
                                            form (first rank, last rank, stride) indicating ranks in
                                            group of processes to be included in newgroup
                                            new group derived from above, in the order defined
OUT
           newgroup
                                            by ranges (handle)
```

13 1415

16

17

18

19

20

21

22

23

24 25

26

27

28

33

34 35

40

41

42

43

44

45

#### C binding

```
int MPI_Group_range_incl(MPI_Group group, int n, int ranges[][3],
            MPI_Group *newgroup)
```

#### Fortran 2008 binding

```
MPI_Group_range_incl(group, n, ranges, newgroup, ierror)
   TYPE(MPI_Group), INTENT(IN) :: group
   INTEGER, INTENT(IN) :: n, ranges(3, n)
   TYPE(MPI_Group), INTENT(OUT) :: newgroup
   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

## Fortran binding

```
MPI_GROUP_RANGE_INCL(GROUP, N, RANGES, NEWGROUP, IERROR)
    INTEGER GROUP, N, RANGES(3, *), NEWGROUP, IERROR
```

If ranges consists of the triplets 
$$(first_1, last_1, stride_1), \dots, (first_n, last_n, stride_n)$$

then newgroup consists of the sequence of processes in group with ranks

$$first_1, first_1 + stride_1, \dots, first_1 + \left\lfloor \frac{last_1 - first_1}{stride_1} \right\rfloor stride_1, \dots,$$
  $first_n, first_n + stride_n, \dots, first_n + \left\lfloor \frac{last_n - first_n}{stride_n} \right\rfloor stride_n.$ 

Each computed rank must be a valid rank in group and all computed ranks must be distinct, or else the program is erroneous. Note that we may have  $first_i > last_i$ , and  $stride_i$ may be negative, but cannot be zero.

The functionality of this routine is specified to be equivalent to expanding the array of ranges to an array of the included ranks and passing the resulting array of ranks and other arguments to MPI\_GROUP\_INCL. A call to MPI\_GROUP\_INCL is equivalent to a call to MPI\_GROUP\_RANGE\_INCL with each rank i in ranks replaced by the triplet (i,i,1) in the argument ranges.

46 47 48

MPI\_GROUP\_RANGE\_EXCL(group, n, ranges, newgroup)

11 12

13

14

15 16

17

18

19

20

21

22

23

24

26

27

28

29

30

31

33 34

35 36

37

38

39

#### IN group (handle) group IN number of triplets in array ranges (integer) n IN ranges a one-dimensional array of integer triplets, of the form (first rank, last rank, stride) indicating ranks in group of processes to be excluded from the output group newgroup (array of integers) OUT new group derived from above, preserving the order newgroup in group (handle)

#### C binding

#### Fortran 2008 binding

```
MPI_Group_range_excl(group, n, ranges, newgroup, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group
    INTEGER, INTENT(IN) :: n, ranges(3, n)
    TYPE(MPI_Group), INTENT(OUT) :: newgroup
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_GROUP_RANGE_EXCL(GROUP, N, RANGES, NEWGROUP, IERROR)
    INTEGER GROUP, N, RANGES(3, *), NEWGROUP, IERROR
```

Each computed rank must be a valid rank in group and all computed ranks must be distinct, or else the program is erroneous.

The functionality of this routine is specified to be equivalent to expanding the array of ranges to an array of the excluded ranks and passing the resulting array of ranks and other arguments to MPI\_GROUP\_EXCL. A call to MPI\_GROUP\_EXCL is equivalent to a call to MPI\_GROUP\_RANGE\_EXCL with each rank i in ranks replaced by the triplet (i,i,1) in the argument ranges.

Advice to users. The range operations do not explicitly enumerate ranks, and therefore are more scalable if implemented efficiently. Hence, we recommend MPI programmers to use them whenever possible, as high-quality implementations will take advantage of this fact. (End of advice to users.)

Advice to implementors. The range operations should be implemented, if possible, without enumerating the group members, in order to obtain better scalability (time and space). (End of advice to implementors.)

```
MPI_GROUP_FROM_SESSION_PSET(session, pset_name, newgroup)
2
       IN
                session
                                            session (handle)
3
       IN
                                            name of process set to use to create the new group
                pset_name
5
6
       OUT
                                            new group derived from supplied session and process
                newgroup
                                            set (handle)
9
     C binding
10
     int MPI_Group_from_session_pset(MPI_Session session, const char *pset_name,
11
                    MPI_Group *newgroup)
12
     Fortran 2008 binding
13
     MPI_Group_from_session_pset(session, pset_name, newgroup, ierror)
14
         TYPE(MPI_Session), INTENT(IN) :: session
15
         CHARACTER(LEN=*), INTENT(IN) :: pset_name
16
         TYPE(MPI_Group), INTENT(OUT) :: newgroup
17
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
18
19
     Fortran binding
20
     MPI_GROUP_FROM_SESSION_PSET(SESSION, PSET_NAME, NEWGROUP, IERROR)
21
          INTEGER SESSION, NEWGROUP, IERROR
22
         CHARACTER*(*) PSET_NAME
23
         The function MPI_GROUP_FROM_SESSION_PSET creates a group newgroup using the
24
     provided session handle and process set. The process set name must be one returned from
25
     an invocation of MPI_SESSION_GET_NTH_PSET using the supplied session handle. If the
26
     pset_name does not exist, MPI_GROUP_NULL will be returned in the newgroup argument.
27
     As with other group constructors, MPI_GROUP_FROM_SESSION_PSET is a local function.
28
     See Section 11.3 for more information on sessions and process sets.
29
30
31
     7.3.3 Group Destructors
32
33
34
     MPI_GROUP_FREE(group)
35
       INOUT group
                                            group (handle)
36
37
     C binding
38
     int MPI_Group_free(MPI_Group *group)
39
     Fortran 2008 binding
41
     MPI_Group_free(group, ierror)
42
         TYPE(MPI_Group), INTENT(INOUT) :: group
43
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
44
     Fortran binding
45
     MPI_GROUP_FREE(GROUP, IERROR)
46
         INTEGER GROUP, IERROR
47
```

This operation marks a group object for deallocation. The handle group is set to MPI\_GROUP\_NULL by the call. Any on-going operation using this group will complete normally.

Advice to implementors. One can keep a reference count that is incremented for each call to MPI\_COMM\_GROUP, MPI\_COMM\_CREATE, MPI\_COMM\_DUP, and MPI\_COMM\_IDUP, and decremented for each call to MPI\_GROUP\_FREE or MPI\_COMM\_FREE; the group object is ultimately deallocated when the reference count drops to zero. (End of advice to implementors.)

## 7.4 Communicator Management

This section describes the manipulation of communicators in MPI. Operations that access communicators are local and their execution does not require interprocess communication. Operations that create communicators are collective and may require interprocess communication.

Advice to implementors. High-quality implementations should amortize the overheads associated with the creation of communicators (for the same group, or subsets thereof) over several calls, by allocating multiple contexts with one collective communication. (End of advice to implementors.)

#### 7.4.1 Communicator Accessors

The following are all local operations.

```
MPI_COMM_SIZE(comm, size)
```

IN comm communicator (handle)

OUT size number of processes in the group of comm (integer)

#### C binding

int MPI\_Comm\_size(MPI\_Comm comm, int \*size)

#### Fortran 2008 binding

```
MPI_Comm_size(comm, size, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_COMM_SIZE(COMM, SIZE, IERROR)
INTEGER COMM, SIZE, IERROR
```

Rationale. This function is equivalent to accessing the communicator's group with MPI\_COMM\_GROUP (see above), computing the size using MPI\_GROUP\_SIZE, and then freeing the temporary group via MPI\_GROUP\_FREE. However, this function is so commonly used that this shortcut was introduced. (*End of rationale*.)

Advice to users. This function indicates the number of processes involved in a communicator. For MPI\_COMM\_WORLD, it indicates the total number of processes available unless the number of processes has been changed by using the functions described in Chapter 11; note that the number of processes in MPI\_COMM\_WORLD does not change during the life of an MPI program.

This call is often used with the next call to determine the amount of concurrency available for a specific library or program. The following call, MPI\_COMM\_RANK indicates the rank of the process that calls it in the range from 0,..., size-1, where size is the return value of MPI\_COMM\_SIZE.(End of advice to users.)

## MPI\_COMM\_RANK(comm, rank)

```
IN comm communicator (handle)OUT rank rank of the calling process in group of comm (integer)
```

## C binding

```
int MPI_Comm_rank(MPI_Comm comm, int *rank)
```

#### Fortran 2008 binding

```
MPI_Comm_rank(comm, rank, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(OUT) :: rank
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_COMM_RANK(COMM, RANK, IERROR)
INTEGER COMM, RANK, IERROR
```

Rationale. This function is equivalent to accessing the communicator's group with MPI\_COMM\_GROUP (see above), computing the rank using MPI\_GROUP\_RANK, and then freeing the temporary group via MPI\_GROUP\_FREE. However, this function is so commonly used that this shortcut was introduced. (*End of rationale*.)

Advice to users. This function gives the rank of the process in the particular communicator's group. It is useful, as noted above, in conjunction with MPI\_COMM\_SIZE.

Many programs will be written with the supervisor/executor or manager/worker model, where one process (such as the rank-zero process) will play a supervisory role, and the other processes will serve as compute nodes. In this framework, the two preceding calls are useful for determining the roles of the various processes of a communicator. (End of advice to users.)

## MPI\_COMM\_COMPARE(comm1, comm2, result)

```
IN comm1 first communicator (handle)
IN comm2 second communicator (handle)
OUT result result (integer)
```

#### C binding

```
int MPI_Comm_compare(MPI_Comm comm1, MPI_Comm comm2, int *result)
```

#### Fortran 2008 binding

```
MPI_Comm_compare(comm1, comm2, result, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm1, comm2
    INTEGER, INTENT(OUT) :: result
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_COMM_COMPARE(COMM1, COMM2, RESULT, IERROR)
    INTEGER COMM1, COMM2, RESULT, IERROR
```

MPI\_IDENT results if and only if comm1 and comm2 are handles for the same object (identical groups and same contexts). MPI\_CONGRUENT results if the underlying groups are identical in constituents and rank order; these communicators differ only by context. MPI\_SIMILAR results if the group members of both communicators are the same but the rank order differs. MPI\_UNEQUAL results otherwise.

#### 7.4.2 Communicator Constructors

The following are collective functions that are invoked by all processes in the group or groups associated with comm, with the exception of MPI\_COMM\_CREATE\_GROUP, MPI\_COMM\_CREATE\_FROM\_GROUP, and MPI\_INTERCOMM\_CREATE\_FROM\_GROUPS. MPI\_COMM\_CREATE\_GROUP and MPI\_COMM\_CREATE\_FROM\_GROUP are invoked only by the processes in the group of the new communicator being constructed.

MPI\_INTERCOMM\_CREATE\_FROM\_GROUPS is invoked by all the processes in the local and remote groups of the new communicator being constructed. See the discussion below for the definition of local and remote groups.

Rationale. Note that, when using the World Model, there is a chicken-and-egg aspect to MPI in that a communicator is needed to create a new communicator. In the World Model, the base communicator for all MPI communicators is predefined outside of MPI, and is MPI\_COMM\_WORLD. The World Model was arrived at after considerable debate, and was chosen to increase "safety" of programs written in MPI. (End of rationale.)

```
This chapter presents the following communicator construction routines: MPI_COMM_CREATE, MPI_COMM_DUP, MPI_COMM_IDUP, MPI_COMM_DUP, MPI_COMM_DUP_WITH_INFO and MPI_COMM_SPLIT can be used to create both intra-communicators and inter-communicators; MPI_COMM_CREATE_GROUP, MPI_COMM_CREATE_FROM_GROUP, and MPI_INTERCOMM_MERGE (see Section 7.6.2) can be used to create intra-communicators;
```

MPI\_INTERCOMM\_CREATE and MPI\_INTERCOMM\_CREATE\_FROM\_GROUPS (see Section 7.6.2) can be used to create inter-communicators.

An intra-communicator involves a single group while an inter-communicator involves two groups. Where the following discussions address inter-communicator semantics, the two groups in an inter-communicator are called the *left* and *right* groups. A process in an inter-communicator is a member of either the left or the right group. From the point of view of that process, the group that the process is a member of is called the *local group*; the other group (relative to that process) is the *remote group*. The left and right group labels give us a way to describe the two groups in an inter-communicator that is not relative to any particular process (as the local and remote groups are).

```
MPI_COMM_DUP(comm, newcomm)
```

```
IN comm communicator (handle)
OUT newcomm copy of comm (handle)
```

#### C binding

```
int MPI_Comm_dup(MPI_Comm comm, MPI_Comm *newcomm)
```

#### Fortran 2008 binding

```
MPI_Comm_dup(comm, newcomm, ierror)
   TYPE(MPI_Comm), INTENT(IN) :: comm
   TYPE(MPI_Comm), INTENT(OUT) :: newcomm
   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_COMM_DUP(COMM, NEWCOMM, IERROR)
INTEGER COMM, NEWCOMM, IERROR
```

MPI\_COMM\_DUP duplicates the existing communicator comm with associated key values and topology information. For each key value, the respective copy callback function determines the attribute value associated with this key in the new communicator; one particular action that a copy callback may take is to delete the attribute from the new communicator. MPI\_COMM\_DUP returns in newcomm a new communicator with the same group or groups, same topology, and any copied cached information, but a new context (see Section 7.7.1).

Advice to users. This operation is used to provide a parallel library with a duplicate communication space that has the same properties as the original communicator. This includes any attributes (see below) and topologies (see Chapter 8). This call is valid even if there are pending point-to-point communications involving the communicator comm. A typical call might involve a MPI\_COMM\_DUP at the beginning of the parallel call, and an MPI\_COMM\_FREE of that duplicated communicator at the end of the call. Other models of communicator management are also possible.

This call applies to both intra- and inter-communicators. (End of advice to users.)

Advice to implementors. One need not actually copy the group information, but only add a new reference and increment the reference count. Copy on write can be used for the cached information. (End of advice to implementors.)

```
MPI_COMM_DUP_WITH_INFO(comm, info, newcomm)
  IN
           comm
                                      communicator (handle)
  IN
           info
                                      info object (handle)
  OUT
           newcomm
                                      copy of comm (handle)
C binding
int MPI_Comm_dup_with_info(MPI_Comm comm, MPI_Info info, MPI_Comm *newcomm)
Fortran 2008 binding
MPI_Comm_dup_with_info(comm, info, newcomm, ierror)
                                                                                      11
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                      12
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                      13
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
                                                                                      14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      15
                                                                                      16
Fortran binding
MPI_COMM_DUP_WITH_INFO(COMM, INFO, NEWCOMM, IERROR)
                                                                                      18
    INTEGER COMM, INFO, NEWCOMM, IERROR
                                                                                      19
    MPI_COMM_DUP_WITH_INFO behaves exactly as MPI_COMM_DUP except that the
                                                                                      20
hints provided by the argument info are associated with the output communicator newcomm.
                                                                                      21
                                                                                      22
     Rationale. It is expected that some hints will only be valid at communicator creation
     time. However, for legacy reasons, most communicator creation calls do not provide
                                                                                      24
     an info argument. One may associate info hints with a duplicate of any communicator
     at creation time through a call to MPI_COMM_DUP_WITH_INFO. (End of rationale.)
                                                                                      26
                                                                                      27
                                                                                      28
                                                                                      29
MPI_COMM_IDUP(comm, newcomm, request)
                                                                                      30
  IN
                                      communicator (handle)
           comm
  OUT
                                      copy of comm (handle)
           newcomm
  OUT
           request
                                      communication request (handle)
                                                                                      34
                                                                                      35
C binding
                                                                                      36
int MPI_Comm_idup(MPI_Comm comm, MPI_Comm *newcomm, MPI_Request *request)
                                                                                      37
Fortran 2008 binding
                                                                                      38
                                                                                      39
MPI_Comm_idup(comm, newcomm, request, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Comm), INTENT(OUT), ASYNCHRONOUS :: newcomm
                                                                                      42
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      43
                                                                                      44
Fortran binding
                                                                                      45
MPI_COMM_IDUP(COMM, NEWCOMM, REQUEST, IERROR)
                                                                                      46
    INTEGER COMM, NEWCOMM, REQUEST, IERROR
```

 MPI\_COMM\_IDUP is a nonblocking variant of MPI\_COMM\_DUP. With the exception of its nonblocking behavior, the semantics of MPI\_COMM\_IDUP are as if MPI\_COMM\_DUP was executed at the time that MPI\_COMM\_IDUP is called. For example, attributes changed after MPI\_COMM\_IDUP will not be copied to the new communicator. All restrictions and assumptions for nonblocking collective operations (see Section 6.12) apply to MPI\_COMM\_IDUP and the returned request.

It is erroneous to use the communicator newcomm as an input argument to other MPI functions before the MPI\_COMM\_IDUP operation completes.

## MPI\_COMM\_IDUP\_WITH\_INFO(comm, info, newcomm, request)

```
      IN
      comm
      communicator (handle)

      IN
      info
      info object (handle)

      OUT
      newcomm
      copy of comm (handle)

      OUT
      request
      communication request (handle)
```

#### C binding

#### Fortran 2008 binding

```
MPI_Comm_idup_with_info(comm, info, newcomm, request, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Comm), INTENT(OUT), ASYNCHRONOUS :: newcomm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_COMM_IDUP_WITH_INFO(COMM, INFO, NEWCOMM, REQUEST, IERROR)
INTEGER COMM, INFO, NEWCOMM, REQUEST, IERROR
```

MPI\_COMM\_IDUP\_WITH\_INFO is a nonblocking variant of MPI\_COMM\_DUP\_WITH\_INFO. With the exception of its nonblocking behavior, the semantics of MPI\_COMM\_IDUP\_WITH\_INFO are as if MPI\_COMM\_DUP\_WITH\_INFO was executed at the time that MPI\_COMM\_IDUP\_WITH\_INFO is called. For example, attributes or info hints changed after MPI\_COMM\_IDUP\_WITH\_INFO will not be copied to the new communicator. All restrictions and assumptions for nonblocking collective operations (see Section 6.12) apply to MPI\_COMM\_IDUP\_WITH\_INFO and the returned request.

It is erroneous to use the communicator newcomm as an input argument to other MPI functions before the MPI\_COMM\_IDUP\_WITH\_INFO operation completes.

Rationale. The MPI\_COMM\_IDUP and MPI\_COMM\_IDUP\_WITH\_INFO functions are crucial for the development of purely nonblocking libraries (see [40]). (End of rationale.)

```
MPI_COMM_CREATE(comm, group, newcomm)
```

```
\begin{array}{lll} \mbox{IN} & \mbox{comm} & \mbox{communicator (handle)} \\ \mbox{IN} & \mbox{group} & \mbox{group, which is a subset of the group of comm} \\ \mbox{(handle)} \\ \mbox{OUT} & \mbox{newcomm} & \mbox{new communicator (handle)} \\ \end{array}
```

#### C binding

int MPI\_Comm\_create(MPI\_Comm comm, MPI\_Group group, MPI\_Comm \*newcomm)

#### Fortran 2008 binding

```
MPI_Comm_create(comm, group, newcomm, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Group), INTENT(IN) :: group
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_COMM_CREATE(COMM, GROUP, NEWCOMM, IERROR)
INTEGER COMM, GROUP, NEWCOMM, IERROR
```

If comm is an intra-communicator, this function returns a new communicator newcomm with communication group defined by the group argument. No cached information propagates from comm to newcomm and no virtual topology information is added to the created communicator. Each process must call MPI\_COMM\_CREATE with a group argument that is a subgroup of the group associated with comm; this could be MPI\_GROUP\_EMPTY. The processes may specify different values for the group argument. If a process calls with a nonempty group then all processes in that group must call the function with the same group as argument, that is the same processes in the same order. Otherwise, the call is erroneous. This implies that the set of groups specified across the processes must be disjoint. If the calling process is a member of the group given as group argument, then newcomm is a communicator with group as its associated group. In the case that a process calls with a group to which it does not belong, e.g., MPI\_GROUP\_EMPTY, then MPI\_COMM\_NULL is returned as newcomm. The function is collective and must be called by all processes in the group of comm.

Rationale. The interface supports the original mechanism from MPI-1.1, which required the same group in all processes of comm. It was extended in MPI-2.2 to allow the use of disjoint subgroups in order to allow implementations to eliminate unnecessary communication that MPI\_COMM\_SPLIT would incur when the user already knows the membership of the disjoint subgroups. (End of rationale.)

Rationale. The requirement that the entire group of comm participate in the call stems from the following considerations:

- It allows the implementation to layer MPI\_COMM\_CREATE on top of regular collective communications.
- It provides additional safety, in particular in the case where partially overlapping groups are used to create new communicators.

1

5

6 9

11 12 13

14

15

10

20 21 22

24 25 26

27

28

33 34

23

35 36 37

38 39

40

41

42

43 44

45 46

47

 It permits implementations to sometimes avoid communication related to context creation.

(End of rationale.)

Advice to users. MPI\_COMM\_CREATE provides a means to subset a group of processes for the purpose of separate MIMD computation, with separate communication space. newcomm, which emerges from MPI\_COMM\_CREATE, can be used in subsequent calls to MPI\_COMM\_CREATE (or other communicator constructors) to further subdivide a computation into parallel sub-computations. A more general service is provided by MPI\_COMM\_SPLIT, below. (End of advice to users.)

Advice to implementors. When calling MPI\_COMM\_DUP, all processes call with the same group (the group associated with the communicator). When calling MPI\_COMM\_CREATE, the processes provide the same group or disjoint subgroups. For both calls, it is theoretically possible to agree on a group-wide unique context with no communication. However, local execution of these functions requires use of a larger context name space and reduces error checking. Implementations may strike various compromises between these conflicting goals, such as bulk allocation of multiple contexts in one collective operation.

Important: If new communicators are created without synchronizing the processes involved then the communication system must be able to cope with messages arriving in a context that has not yet been allocated at the receiving process. (End of advice to implementors.)

If comm is an inter-communicator, then the output communicator is also an inter-communicator where the local group consists only of those processes contained in group (see Figure 7.1). The group argument should only contain those processes in the local group of the input inter-communicator that are to be a part of newcomm. All processes in the same local group of comm must specify the same value for group, i.e., the same members in the same order. If either group does not specify at least one process in the local group of the inter-communicator, or if the calling process is not included in the group, MPI\_COMM\_NULL is returned.

Rationale. In the case where either the left or right group is empty, a null communicator is returned instead of an inter-communicator with MPI\_GROUP\_EMPTY because the side with the empty group must return MPI\_COMM\_NULL. (End of rationale.)

#### **Example 7.1** Inter-communicator creation.

The following example illustrates how the first node in the left side of an inter-communicator could be joined with all members on the right side of an inter-communicator to form a new inter-communicator.

2425

26

27

28

29 30

31

34

35

36

37

38

39

42 43

44




Figure 7.1: Inter-communicator creation using MPI\_COMM\_CREATE extended to inter-communicators. The input groups are those in the grey circle.

```
MPI_Comm inter_comm, new_inter_comm;
MPI_Group local_group, group;
          rank = 0; /* rank on left side to include in
int
                       new inter-comm */
/* Construct the original inter-communicator: "inter_comm" */
. . .
/* Construct the group of processes to be in new
   inter-communicator */
if (/* I'm on the left side of the inter-communicator */) {
  MPI_Comm_group(inter_comm, &local_group);
  MPI_Group_incl(local_group, 1, &rank, &group);
  MPI_Group_free(&local_group);
}
else
  MPI_Comm_group(inter_comm, &group);
MPI_Comm_create(inter_comm, group, &new_inter_comm);
MPI_Group_free(&group);
```

7

21

22

23 24

25

26

27

28

29

30

31

32

33

34

35

36

37

38

39

40 41

42

43

44

45

46

47

```
MPI_COMM_CREATE_GROUP(comm, group, tag, newcomm)
2
       IN
                                           intra-communicator (handle)
                comm
3
       IN
                                           group, which is a subset of the group of comm
                group
4
                                           (handle)
5
6
       IN
                                           tag (integer)
                tag
       OUT
                newcomm
                                           new communicator (handle)
8
9
     C binding
10
     int MPI_Comm_create_group(MPI_Comm comm, MPI_Group group, int tag,
11
                   MPI_Comm *newcomm)
12
13
     Fortran 2008 binding
14
     MPI_Comm_create_group(comm, group, tag, newcomm, ierror)
15
         TYPE(MPI_Comm), INTENT(IN) :: comm
16
         TYPE(MPI_Group), INTENT(IN) :: group
17
         INTEGER, INTENT(IN) :: tag
18
         TYPE(MPI_Comm), INTENT(OUT) :: newcomm
19
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
20
```

### Fortran binding

MPI\_COMM\_CREATE\_GROUP(COMM, GROUP, TAG, NEWCOMM, IERROR) INTEGER COMM, GROUP, TAG, NEWCOMM, IERROR

MPI\_COMM\_CREATE\_GROUP is similar to MPI\_COMM\_CREATE; however, MPI\_COMM\_CREATE must be called by all processes in the group of comm, whereas MPI\_COMM\_CREATE\_GROUP must be called by all processes in group, which is a subgroup of the group of comm. In addition, MPI\_COMM\_CREATE\_GROUP requires that comm is an intra-communicator. MPI\_COMM\_CREATE\_GROUP returns a new intra-communicator, newcomm, for which the group argument defines the communication group. No cached information propagates from comm to newcomm and no virtual topology information is added to the created communicator. Each process must provide a group argument that is a subgroup of the group associated with comm; this could be MPI\_GROUP\_EMPTY. If a nonempty group is specified, then all processes in that group must call the function, and each of these processes must provide the same arguments, including a group that contains the same members with the same ordering. Otherwise the call is erroneous. If the calling process is a member of the group given as the group argument, then newcomm is a communicator with group as its associated group. If the calling process is not a member of group, e.g., group is MPI\_GROUP\_EMPTY, then the call is a local operation and MPI\_COMM\_NULL is returned as newcomm.

Functionality similar to MPI\_COMM\_CREATE\_GROUP can be imple-Rationale. mented through repeated MPI\_INTERCOMM\_CREATE and MPI\_INTERCOMM\_MERGE calls that start with the MPI\_COMM\_SELF communicators at each process in group and build up an intra-communicator with group group [17]. Such an algorithm requires the creation of many intermediate communicators; MPI\_COMM\_CREATE\_GROUP can provide a more efficient implementation that avoids this overhead. (End of rationale.)

Advice to users. An inter-communicator can be created collectively over processes in the union of the local and remote groups by creating the local communicator using MPI\_COMM\_CREATE\_GROUP and using that communicator as the local communicator argument to MPI\_INTERCOMM\_CREATE. (End of advice to users.)

The tag argument does not conflict with tags used in point-to-point communication and is not permitted to be a wildcard. If multiple threads at a given process perform concurrent MPI\_COMM\_CREATE\_GROUP operations, the user must distinguish these operations by providing different tag or comm arguments.

Advice to users. MPI\_COMM\_CREATE may provide lower overhead than MPI\_COMM\_CREATE\_GROUP because it can take advantage of collective communication on comm when constructing newcomm. (End of advice to users.)

#### MPI\_COMM\_SPLIT(comm, color, key, newcomm)

```
      IN
      comm
      communicator (handle)

      IN
      color
      control of subset assignment (integer)

      IN
      key
      control of rank assignment (integer)

      OUT
      newcomm
      new communicator (handle)
```

#### C binding

int MPI\_Comm\_split(MPI\_Comm comm, int color, int key, MPI\_Comm \*newcomm)

#### Fortran 2008 binding

```
MPI_Comm_split(comm, color, key, newcomm, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: color, key
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_COMM_SPLIT(COMM, COLOR, KEY, NEWCOMM, IERROR)
INTEGER COMM, COLOR, KEY, NEWCOMM, IERROR
```

This function partitions the group associated with comm into disjoint subgroups, one for each value of color. Each subgroup contains all processes of the same color. Within each subgroup, the processes are ranked in the order defined by the value of the argument key, with ties broken according to their rank in the old group. A new communicator is created for each subgroup and returned in newcomm. A process may supply the color value MPI\_UNDEFINED, in which case newcomm returns MPI\_COMM\_NULL. This is a collective call, but each process is permitted to provide different values for color and key. No cached information propagates from comm to newcomm and no virtual topology information is added to the created communicators.

With an intra-communicator comm, a call to MPI\_COMM\_CREATE(comm, group, new-comm) is equivalent to a call to MPI\_COMM\_SPLIT(comm, color, key, newcomm), where processes that are members of their group argument provide color = number of the group

(based on a unique numbering of all disjoint groups) and key = rank in group, and all processes that are not members of their group argument provide color = MPI\_UNDEFINED.

The value of color must be non-negative or MPI\_UNDEFINED.

Advice to users. This is an extremely powerful mechanism for dividing a single communicating group of processes into k subgroups, with k chosen implicitly by the user (by the number of colors asserted over all the processes). Each resulting communicator will be non-overlapping. Such a division could be useful for defining a hierarchy of computations, such as for multigrid, or linear algebra. For intra-communicators, MPI\_COMM\_SPLIT provides similar capability as MPI\_COMM\_CREATE to split a communicating group into disjoint subgroups. MPI\_COMM\_SPLIT is useful when some processes do not have complete information of the other members in their group, but all processes know (the color of) the group to which they belong. In this case, the MPI implementation discovers the other group members via communication. MPI\_COMM\_CREATE is useful when all processes have complete information of the members of their group. In this case, MPI can avoid the extra communication required to discover group membership. MPI\_COMM\_CREATE\_GROUP is useful when all processes in a given group have complete information of the members of their group and synchronization with processes outside the group can be avoided.

Multiple calls to MPI\_COMM\_SPLIT can be used to overcome the requirement that any call have no overlap of the resulting communicators (each process is of only one color per call). In this way, multiple overlapping communication structures can be created. Creative use of the color and key in such splitting operations is encouraged.


Note that, for a fixed color, the keys need not be unique. It is MPI\_COMM\_SPLIT's responsibility to sort processes in ascending order according to this key, and to break ties in a consistent way. If all the keys are specified in the same way, then all the processes in a given color will have the relative rank order as they did in their parent group.

Essentially, making the key value zero for all processes of a given color means that one does not really care about the rank-order of the processes in the new communicator. (*End of advice to users.*)


Rationale. color is restricted to be non-negative, so as not to confict with the value assigned to MPI\_UNDEFINED. (End of rationale.)

The result of MPI\_COMM\_SPLIT on an inter-communicator is that those processes on the left with the same color as those processes on the right combine to create a new inter-communicator. The key argument describes the relative rank of processes on each side of the inter-communicator (see Figure 7.2). For those colors that are specified only on one side of the inter-communicator, MPI\_COMM\_NULL is returned. MPI\_COMM\_NULL is also returned to those processes that specify MPI\_UNDEFINED as the color.

Advice to users. For inter-communicators, MPI\_COMM\_SPLIT is more general than MPI\_COMM\_CREATE. A single call to MPI\_COMM\_SPLIT can create a set of disjoint inter-communicators, while a call to MPI\_COMM\_CREATE creates only one. (End of advice to users.)



## Input Intercommunicator (comm)



Disjoint output communicators (newcomm) (one per color)

Figure 7.2: Inter-communicator construction achieved by splitting an existing inter-communicator with MPI\_COMM\_SPLIT extended to inter-communicators.

```
1
     Example 7.2 Parallel client-server model.
2
     The following client code illustrates how clients on the left side of an inter-communicator
3
     could be assigned to a single server from a pool of servers on the right side of an inter-
4
     communicator.
5
              /* Client code */
6
             MPI_Comm multiple_server_comm;
             MPI_Comm
                        single_server_comm;
              int
                        color, rank, num_servers;
10
              /* Create inter-communicator with clients and servers:
11
                 multiple_server_comm */
12
13
14
              /* Find out the number of servers available */
15
             MPI_Comm_remote_size(multiple_server_comm, &num_servers);
16
              /* Determine my color */
             MPI_Comm_rank(multiple_server_comm, &rank);
19
              color = rank % num_servers;
20
21
              /* Split the inter-communicator */
22
             MPI_Comm_split(multiple_server_comm, color, rank,
23
                              &single_server_comm);
24
25
     The following is the corresponding server code:
26
27
              /* Server code */
             MPI_Comm multiple_client_comm;
28
29
             MPI_Comm single_server_comm;
30
              int
                        rank;
              /* Create inter-communicator with clients and servers:
33
                 multiple_client_comm */
34
35
36
              /* Split the inter-communicator for a single server per group
37
                of clients */
             MPI_Comm_rank(multiple_client_comm, &rank);
             MPI_Comm_split(multiple_client_comm, rank, 0,
                              &single_server_comm);
```

Fortran binding

11

12 13

14

15

16

18

19

20

21

22

23 24

27

28

31

34

35

36 37

38

42

43

44

45

46 47

```
MPI_COMM_SPLIT_TYPE(comm, split_type, key, info, newcomm)
 IN
           comm
                                      communicator (handle)
 IN
           split_type
                                     type of processes to be grouped together (integer)
 IN
           key
                                     control of rank assignment (integer)
 INOUT
           info
                                     info argument (handle)
 OUT
           newcomm
                                     new communicator (handle)
C binding
int MPI_Comm_split_type(MPI_Comm comm, int split_type, int key,
              MPI_Info info, MPI_Comm *newcomm)
Fortran 2008 binding
MPI_Comm_split_type(comm, split_type, key, info, newcomm, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: split_type, key
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

This function partitions the group associated with comm into disjoint subgroups such that each subgroup contains all MPI processes in the same grouping referred to by split\_type. Within each subgroup, the MPI processes are ranked in the order defined by the value of the argument key, with ties broken according to their rank in the old group. A new communicator is created for each subgroup and returned in newcomm. This is a collective call. All MPI processes in the group associated with comm must provide the same split\_type, but each MPI process is permitted to provide different values for key. An exception to this rule is that an MPI process may supply the type value MPI\_UNDEFINED, in which case MPI\_COMM\_NULL is returned in newcomm for such MPI process. No cached information propagates from comm to newcomm and no virtual topology information is added to the created communicators.

MPI\_COMM\_SPLIT\_TYPE(COMM, SPLIT\_TYPE, KEY, INFO, NEWCOMM, IERROR)

INTEGER COMM, SPLIT\_TYPE, KEY, INFO, NEWCOMM, IERROR

For split\_type, the following values are defined by MPI:

MPI\_COMM\_TYPE\_SHARED—all MPI processes in newcomm can create a shared memory segment (e.g., with a successful call to MPI\_WIN\_ALLOCATE\_SHARED). This segment can subsequently be used for load/store accesses by all MPI processes in newcomm.

Advice to users. Since the location of some of the MPI processes may change during the application execution, the communicators created with the value MPI\_COMM\_TYPE\_SHARED before this change may not reflect an actual ability to share memory between MPI processes after this change. (End of advice to users.)

MPI\_COMM\_TYPE\_HW\_GUIDED—this value specifies that the communicator comm is split according to a hardware resource type (for example a computing core or an L3

cache) specified by the "mpi\_hw\_resource\_type" info key. Each output communicator newcomm corresponds to a single instance of the specified hardware resource type. The MPI processes in the group associated with the output communicator newcomm utilize that specific hardware resource type instance, and no other instance of the same hardware resource type.

If an MPI process does not meet the above criteria, then MPI\_COMM\_NULL is returned in newcomm for such process.

MPI\_COMM\_NULL is also returned in newcomm in the following cases:

- No info key is provided.
- The info handle does not include the key "mpi\_hw\_resource\_type".
- The MPI implementation neither recognizes nor supports the info key "mpi\_hw\_resource\_type".
- The MPI implementation does not recognize the value associated with the info key "mpi\_hw\_resource\_type".

The MPI implementation will return in the group of the output communicator newcomm the largest subset of MPI processes that match the splitting criterion.

The processes in the group associated with newcomm are ranked in the order defined by the value of the argument key with ties broken according to their rank in the group associated with comm.

Advice to users. The set of hardware resources that an MPI process is able to utilize may change during the application execution (e.g., because of the relocation of an MPI process), in which case the communicators created with the value MPI\_COMM\_TYPE\_HW\_GUIDED before this change may not reflect the utilization of hardware resources of such process at any time after the communicator creation. (End of advice to users.)

The user explicitly constrains with the info argument the splitting of the input communicator comm. To this end, the info key "mpi\_hw\_resource\_type" is reserved and its associated value is an implementation-defined string designating the type of the requested hardware resource (e.g., "NUMANode", "Package" or "L3Cache").

The value "mpi\_shared\_memory" is reserved and its use is equivalent to using MPI\_COMM\_TYPE\_SHARED for the split\_type parameter.

Rationale. The value "mpi\_shared\_memory" is defined in order to ensure consistency between the use of MPI\_COMM\_TYPE\_SHARED and the use of MPI\_COMM\_TYPE\_HW\_GUIDED. (End of rationale.)

All MPI processes must provide the same value for the info key "mpi\_hw\_resource\_type".

**Example 7.3** Splitting MPI\_COMM\_WORLD into NUMANode subcommunicators.

MPI\_COMM\_TYPE\_HW\_UNGUIDED—the group of MPI processes associated with newcomm must be a *strict* subset of the group associated with comm and each newcomm corresponds to a single instance of a **hardware resource type** (for example a computing core or an L3 cache).

All MPI processes in the group associated with comm which utilize that specific hardware resource type instance – and no other instance of the same hardware resource type – are included in the group of newcomm.

If a given MPI process cannot be a member of a communicator that forms such a strict subset, or does not meet the above criteria, then MPI\_COMM\_NULL is returned in newcomm for this process.

Advice to implementors. In a high-quality MPI implementation, the number of different new valid communicators newcomm produced by this splitting operation should be minimal unless the user provides a key/value pair that modifies this behavior. The sets of hardware resource types used for the splitting operation are implementation-dependent, but should reflect the hardware of the actual system on which the application is currently executing. (End of advice to implementors.)

Rationale. If the hardware resources are hierarchically organized, calling this routine several times using as its input communicator comm the output communicator newcomm of the previous call creates a sequence of newcomm communicators in each MPI process, which exposes a hierarchical view of the hardware platform, as shown in Example 7.4. This sequence of returned newcomm communicators may differ from the sets of hardware resource types, as shown in the second splitting operation in Figure 7.3. (End of rationale.)

Advice to users. Each output communicator newcomm can represent a different hardware resource type (see Figure 7.3 for an example). The set of hardware resources an MPI process utilizes may change during the application execution (e.g., because of process relocation), in which case the communicators created with the value MPI\_COMM\_TYPE\_HW\_UNGUIDED before this change may not reflect the utilization of hardware resources for such process at any time after the communicator creation. (End of advice to users.)

If a valid info handle is provided as an argument, the MPI implementation sets the info key "mpi\_hw\_resource\_type" for each MPI process in the group associated with a

2

6

9 10

11

12 13

14 15

16

18

19

20

21

22

23

returned newcomm communicator and the info key value is an implementation-defined string that indicates the hardware resource type represented by newcomm. The same hardware resource type must be set in all MPI processes in the group associated with newcomm.

#### **Example 7.4** Recursive splitting of MPI\_COMM\_WORLD.

```
#define MAX_NUM_LEVELS 32
MPI_Comm hwcomm[MAX_NUM_LEVELS];
int rank, level_num = 0;
hwcomm[level_num] = MPI_COMM_WORLD;
while((hwcomm[level_num] != MPI_COMM_NULL)
      && (level_num < MAX_NUM_LEVELS-1)){
 MPI_Comm_rank(hwcomm[level_num],&rank);
 MPI_Comm_split_type(hwcomm[level_num],
                      MPI_COMM_TYPE_HW_UNGUIDED,
                      rank,
                      MPI_INFO_NULL,
                      &hwcomm[level_num+1]);
level_num++;
}
```

26 27

28

29

30

31

32

33

Implementations can define their own split\_type values, or Advice to implementors. use the info argument, to assist in creating communicators that help expose platformspecific information to the application. The concept of hardware-based communicators was first described by Träff [67] for SMP systems. Guided and unguided modes description as well as an implementation path are introduced by Goglin et al. [27]. (End of advice to implementors.)

34 35 36

37

41

47

#### MPI\_COMM\_CREATE\_FROM\_GROUP(group, stringtag, info, errhandler, newcomm)

```
IN
                    group
                                                     group (handle)
38
        IN
                    stringtag
                                                     unique identifier for this operation (string)
39
                    info
        IN
                                                    info object (handle)
        IN
                    errhandler
                                                    error handler to be attached to new
42
                                                    intra-communicator (handle)
43
        OUT
                    newcomm
                                                    new communicator (handle)
44
45
46
```

#### C binding

```
int MPI_Comm_create_from_group(MPI_Group group, const char *stringtag,
             MPI_Info info, MPI_Errhandler errhandler, MPI_Comm *newcomm)
```




Figure 7.3: Recursive splitting of MPI\_COMM\_WORLD with MPI\_COMM\_SPLIT\_TYPE and MPI\_COMM\_TYPE\_HW\_UNGUIDED. Dashed lines represent communicators whilst solid lines represent hardware resources. MPI processes (P0 to P11) utilize exclusively their respective core, except for P6 and P7 which utilize CPU #3 of Rack #0 and can therefore use Cores #6 and #7 indifferently. The second splitting operation yields two subcommunicators corresponding to NUMANodes in Rack #0 and to CPUs in Rack #1 because Rack #1 features only one NUMANode which corresponds to the whole portion of the Rack that is included in MPI\_COMM\_WORLD and hwcomm[1]. For the first splitting operation, the hardware resource type returned in the info argument is "Rack" on the processes on Rack #0, whereas on Rack #1, it can be either "Rack" or "NUMANode".

22

23

24

25

31

32

35

36

37

38

42

44

47

#-other

#-error!

Done

PR400

in

Is PR400 incomplete? 34

Done

PR461

remove new linebreak that there is

no overfull

lin

Done

PR486 45

line

in

#-update59

```
1
     Fortran 2008 binding
2
     MPI_Comm_create_from_group(group, stringtag, info, errhandler, newcomm,
3
                   ierror)
4
         TYPE(MPI_Group), INTENT(IN) :: group
5
         CHARACTER(LEN=*), INTENT(IN) :: stringtag
6
         TYPE(MPI_Info), INTENT(IN) :: info
7
         TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
         TYPE(MPI_Comm), INTENT(OUT) :: newcomm
9
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
10
     Fortran binding
11
     MPI_COMM_CREATE_FROM_GROUP(GROUP, STRINGTAG, INFO, ERRHANDLER, NEWCOMM,
12
                   IERROR)
13
         INTEGER GROUP, INFO, ERRHANDLER, NEWCOMM, IERROR
14
         CHARACTER*(*) STRINGTAG
15
16
         MPI_COMM_CREATE_FROM_GROUP is similar to MPI_COMM_CREATE_GROUP, ex-
17
18
19
20
```

cept that the set of MPI processes involved in the creation of the new intra-communicator is specified by a group argument, rather than the group associated with a pre-existing communicator. If a non-empty group is specified, then all MPI processes in that group must call the function and each of these MPI processes must provide the same arguments, including a group that contains the same members with the same ordering, and identical stringtag value. In the event that MPI\_GROUP\_EMPTY is supplied as the group argument, then the call is a local operation and MPI\_COMM\_NULL is returned as newcomm. The stringtag argument is analogous to the tag used for MPI\_COMM\_CREATE\_GROUP. If multiple threads at a given MPI process perform concurrent MPI\_COMM\_CREATE\_FROM\_GROUP operations, the user must distinguish these operations by providing different stringtag arguments. The stringtag shall not exceed MPI\_MAX\_FROM\_GROUP\_TAG characters in length. For C, this includes space for a null terminating character. The errhandler argument specifies an error handler to be attached to the new intra-communicator. This error handler will also be invoked if the MPI\_COMM\_CREATE\_FROM\_GROUP function encounters an error. The info argument provides hints and assertions, possibly MPI implementation dependent, which indicate desired characteristics and guide communicator creation.

The stringtag argument is used to distinguish concurrent commu-Advice to users. nicator construction operations issued by different entities. As such, it is important to ensure that this argument is unique for each concurrent call to MPI\_COMM\_CREATE\_FROM\_GROUP. Reverse domain name notation convention [1] is one approach to constructing unique stringtag arguments. See also example 11.8. (End of advice to users.)

#### 7.4.3 Communicator Destructors

```
MPI_COMM_FREE(comm)
 INOUT
          comm
                                     communicator to be destroyed (handle)
```

C binding

```
int MPI_Comm_free(MPI_Comm *comm)
Fortran 2008 binding
MPI_Comm_free(comm, ierror)
        TYPE(MPI_Comm), INTENT(INOUT) :: comm
        INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_COMM_FREE(COMM, IERROR)
        INTEGER COMM, IERROR
```

This collective operation marks the communication object for deallocation. The handle is set to MPI\_COMM\_NULL. Any pending operations that use this communicator will complete normally; the object is actually deallocated only if there are no other active references to it. This call applies to intra- and inter-communicators. The delete callback functions for all cached attributes (see Section 7.7) are called in arbitrary order.

Advice to implementors. Though collective, it is anticipated that this operation will normally be implemented to be local, though a debugging version of an MPI library might choose to synchronize. (End of advice to implementors.)

#### 7.4.4 Communicator Info

Hints specified via info (see Chapter 10) allow a user to provide information to direct optimization. Providing hints may enable an implementation to deliver increased performance or minimize use of system resources. An implementation is free to ignore all hints; however, applications must comply with any info hints they provide that are used by the MPI implementation (i.e., are returned by a call to MPI\_COMM\_GET\_INFO) and that place a restriction on the behavior of the application. Hints are specified on a per communicator basis, in MPI\_COMM\_DUP\_WITH\_INFO, MPI\_COMM\_IDUP\_WITH\_INFO, MPI\_COMM\_SET\_INFO, MPI\_COMM\_SPLIT\_TYPE, MPI\_DIST\_GRAPH\_CREATE, and MPI\_DIST\_GRAPH\_CREATE\_ADJACENT, via the opaque info object. When an info object that specifies a subset of valid hints is passed to MPI\_COMM\_SET\_INFO, there will be no effect on previously set or defaulted hints that the info does not specify.

Advice to implementors. It may happen that a program is coded with hints for one system, and later executes on another system that does not support these hints. In general, unsupported hints should simply be ignored. Needless to say, no hint can be mandatory. However, for each hint used by a specific implementation, a default value must be provided when the user does not specify a value for this hint. (End of advice to implementors.)

Info hints are not propagated by MPI from one communicator to another. The following info keys are valid for all communicators.

- "mpi\_assert\_no\_any\_tag" (boolean, default: "false"): If set to "true", then the implementation may assume that the process will not use the MPI\_ANY\_TAG wildcard on the given communicator.
- "mpi\_assert\_no\_any\_source" (boolean, default: "false"): If set to "true", then the implementation may assume that the process will not use the MPI\_ANY\_SOURCE wildcard on the given communicator.

"mpi\_assert\_exact\_length" (boolean, default: "false"): If set to "true", then the implementation may assume that the lengths of messages received by the process are equal to the lengths of the corresponding receive buffers, for point-to-point communication operations on the given communicator.

"mpi\_assert\_allow\_overtaking" (boolean, default: "false"): If set to "true", then the implementation may assume that point-to-point communications on the given communicator do not rely on the non-overtaking rule specified in Section 3.5. In other words, the application asserts that send operations are not required to be matched at the receiver in the order in which the send operations were posted by the sender, and receive operations are not required to be matched in the order in which they were posted by the receiver.

Advice to users. Use of the "mpi\_assert\_allow\_overtaking" info key can result in nondeterminism in the message matching order. (End of advice to users.)

Advice to users. Some optimizations may only be possible when all processes in the group of the communicator provide a given info key with the same value. (End of advice to users.)

```
MPI_COMM_SET_INFO(comm, info)
```

```
INOUT comm communicator (handle)

IN info info object (handle)
```

#### C binding

```
int MPI_Comm_set_info(MPI_Comm comm, MPI_Info info)
```

#### Fortran 2008 binding

```
MPI_Comm_set_info(comm, info, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_COMM_SET_INFO(COMM, INFO, IERROR)
INTEGER COMM, INFO, IERROR
```

MPI\_COMM\_SET\_INFO updates the hints of the communicator associated with comm using the hints provided in info. This operation has no effect on previously set or defaulted hints that are not specified by info. It also has no effect on previously set or defaulted hints that are specified by info, but are ignored by the MPI implementation in this call to MPI\_COMM\_SET\_INFO. MPI\_COMM\_SET\_INFO is a collective routine. The info object may be different on each process, but any info entries that an implementation requires to be the same on all processes must appear with the same value in each process's info object.

Advice to users. Some info items that an implementation can use when it creates a communicator cannot easily be changed once the communicator has been created. Thus, an implementation may ignore hints issued in this call that it would have

11 12 13

15

16 17

18 19

20

21

22

23

24

26 27

28

29

30

33

34

35

36

37

39

41 42

43

44 45

46

accepted in a creation call. An implementation may also be unable to update certain info hints in a call to MPI\_COMM\_SET\_INFO. MPI\_COMM\_GET\_INFO can be used to determine whether updates to existing info hints were ignored by the implementation. (*End of advice to users*.)

Advice to users. Setting info hints on the predefined communicators MPI\_COMM\_WORLD and MPI\_COMM\_SELF may have unintended effects, as changes to these global objects may affect all components of the application, including libraries and tools. Users must ensure that all components of the application that use a given communicator, including libraries and tools, can comply with any info hints associated with that communicator. (End of advice to users.)

```
MPI_COMM_GET_INFO(comm, info_used)
                                    communicator object (handle)
 IN
          comm
 OUT
          info_used
                                    new info object (handle)
C binding
int MPI_Comm_get_info(MPI_Comm comm, MPI_Info *info_used)
Fortran 2008 binding
MPI_Comm_get_info(comm, info_used, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(OUT) :: info_used
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_COMM_GET_INFO(COMM, INFO_USED, IERROR)
    INTEGER COMM, INFO_USED, IERROR
```

MPI\_COMM\_GET\_INFO returns a new info object containing the hints of the communicator associated with comm. The current setting of all hints related to this communicator is returned in info\_used. An MPI implementation is required to return all hints that are supported by the implementation and have default values specified; any user-supplied hints that were not ignored by the implementation; and any additional hints that were set by the implementation. If no such hints exist, a handle to a newly created info object is returned that contains no key/value pair. The user is responsible for freeing info\_used via MPI\_INFO\_FREE.

## 7.5 Motivating Examples

## 7.5.1 Current Practice #1

```
Example #1a:
   int main(int argc, char *argv[])
   {
     int me, size;
```

```
1
2
           MPI_Init(&argc, &argv);
           MPI_Comm_rank(MPI_COMM_WORLD, &me);
           MPI_Comm_size(MPI_COMM_WORLD, &size);
6
           (void)printf("Process %d size %d\n", me, size);
           MPI_Finalize();
           return 0;
10
        }
11
     Example #1a is a do-nothing program that initializes itself, and refers to the "all" commu-
12
     nicator, and prints a message. It terminates itself too. This example does not imply that
13
     MPI supports printf-like communication itself.
14
     Example #1b: Message exchange (supposing that size is even)
15
16
          int main(int argc, char *argv[])
          {
18
             int me, size;
19
             int SOME_TAG = 0;
20
21
             MPI_Init(&argc, &argv);
22
23
             MPI_Comm_rank(MPI_COMM_WORLD, &me);
                                                       /* local */
             MPI_Comm_size(MPI_COMM_WORLD, &size); /* local */
26
             if((me \% 2) == 0)
27
28
                /* send unless highest-numbered process */
29
                if((me + 1) < size)
30
                    MPI_Send(..., me + 1, SOME_TAG, MPI_COMM_WORLD);
             }
             else
33
                                    - 1, SOME_TAG, MPI_COMM_WORLD, &status);
                MPI_Recv(..., me
34
35
36
             MPI_Finalize();
37
             return 0;
38
          }
39
40
     Example #1b schematically illustrates message exchanges between "even" and "odd" pro-
41
     cesses in the "all" communicator.
42
43
            Current Practice #2
     7.5.2
44
        int main(int argc, char *argv[])
45
46
           int me, count;
47
           void *data;
```

```
. . .
     MPI_Init(&argc, &argv);
     MPI_Comm_rank(MPI_COMM_WORLD, &me);
     if(me == 0)
     ₹
         /* get input, create buffer 'data' */
     }
                                                                                    11
     MPI_Bcast(data, count, MPI_BYTE, 0, MPI_COMM_WORLD);
                                                                                    12
                                                                                    13
                                                                                    14
                                                                                    15
     MPI_Finalize();
                                                                                    16
     return 0;
   }
                                                                                    18
This example illustrates the use of a collective communication.
                                                                                    19
                                                                                    20
7.5.3 (Approximate) Current Practice #3
                                                                                    21
                                                                                    22
  int main(int argc, char *argv[])
                                                                                    23
  {
                                                                                    24
    int me, count, count2;
    void *send_buf, *recv_buf, *send_buf2, *recv_buf2;
                                                                                    26
    MPI_Group group_world, grprem;
                                                                                    27
    MPI_Comm commWorker;
                                                                                    28
    static int ranks[] = {0};
                                                                                    29
                                                                                    30
    MPI_Init(&argc, &argv);
    MPI_Comm_group(MPI_COMM_WORLD, &group_world);
    MPI_Comm_rank(MPI_COMM_WORLD, &me); /* local */
                                                                                    34
    MPI_Group_excl(group_world, 1, ranks, &grprem); /* local */
                                                                                    35
    MPI_Comm_create(MPI_COMM_WORLD, grprem, &commWorker);
                                                                                    36
                                                                                    37
    if(me != 0)
      /* compute on worker */
      MPI_Reduce(send_buf,recv_buf,count, MPI_INT, MPI_SUM, 1, commWorker);
                                                                                    43
      MPI_Comm_free(&commWorker);
                                                                                    44
                                                                                    45
    /* zero falls through immediately to this reduce, others do later... */
    MPI_Reduce(send_buf2, recv_buf2, count2,
                                                                                    47
                MPI_INT, MPI_SUM, 0, MPI_COMM_WORLD);
```

8

9

10

11

12

13

14

15 16 17

18

19

20

21

```
MPI_Group_free(&group_world);
MPI_Group_free(&grprem);
MPI_Finalize();
return 0;
}
```

This example illustrates how a group consisting of all but the zeroth process of the "all" group is created, and then how a communicator is formed (commWorker) for that new group. The new communicator is used in a collective call, and all processes execute a collective call in the MPI\_COMM\_WORLD context. This example illustrates how the two communicators (that inherently possess distinct contexts) protect communication. That is, communication in MPI\_COMM\_WORLD is insulated from communication in commWorker, and vice versa.

In summary, "group safety" is achieved via communicators because distinct contexts within communicators are enforced to be unique on any process.

#### 7.5.4 Example #4

The following example is meant to illustrate "safety" between point-to-point and collective communication. MPI guarantees that a single communicator can do safe point-to-point and collective communication.

```
22
        #define TAG_ARBITRARY 12345
23
        #define SOME_COUNT
24
        int main(int argc, char *argv[])
26
27
          int me;
28
          MPI_Request request[2];
29
          MPI_Status status[2];
30
          MPI_Group group_world, subgroup;
31
          int ranks[] = \{2, 4, 6, 8\};
32
          MPI_Comm the_comm;
33
           ...
34
          MPI_Init(&argc, &argv);
35
          MPI_Comm_group(MPI_COMM_WORLD, &group_world);
36
37
          MPI_Group_incl(group_world, 4, ranks, &subgroup); /* local */
          MPI_Group_rank(subgroup, &me);
                                                /* local */
39
          MPI_Comm_create(MPI_COMM_WORLD, subgroup, &the_comm);
41
42
          if(me != MPI_UNDEFINED)
43
          {
44
               MPI_Irecv(buff1, count, MPI_DOUBLE, MPI_ANY_SOURCE, TAG_ARBITRARY,
45
                                  the_comm, request);
46
               MPI_Isend(buff2, count, MPI_DOUBLE, (me+1)%4, TAG_ARBITRARY,
47
                                  the_comm, request+1);
               for(i = 0; i < SOME_COUNT; i++)</pre>
```

```
MPI_Reduce(..., the_comm);
          MPI_Waitall(2, request, status);
         MPI_Comm_free(&the_comm);
     }
     MPI_Group_free(&group_world);
     MPI_Group_free(&subgroup);
     MPI_Finalize();
     return 0;
   }
                                                                                        11
                                                                                        12
                                                                                        13
      Library Example #1
                                                                                        14
The main program:
                                                                                        15
                                                                                        16
   int main(int argc, char *argv[])
                                                                                        18
     int done = 0;
                                                                                        19
     user_lib_t *libh_a, *libh_b;
                                                                                        20
     void *dataset1, *dataset2;
                                                                                        21
                                                                                        22
     MPI_Init(&argc, &argv);
                                                                                        23
                                                                                        24
     init_user_lib(MPI_COMM_WORLD, &libh_a);
                                                                                        25
     init_user_lib(MPI_COMM_WORLD, &libh_b);
                                                                                        26
                                                                                        27
     user_start_op(libh_a, dataset1);
                                                                                        28
     user_start_op(libh_b, dataset2);
                                                                                        29
                                                                                        30
     while(!done)
     {
         /* work */
                                                                                        33
                                                                                        34
        MPI_Reduce(..., MPI_COMM_WORLD);
                                                                                        35
                                                                                        36
         /* see if done */
                                                                                        37
                                                                                        38
     }
                                                                                        39
     user_end_op(libh_a);
     user_end_op(libh_b);
                                                                                        42
     uninit_user_lib(libh_a);
                                                                                        43
     uninit_user_lib(libh_b);
                                                                                        44
     MPI_Finalize();
                                                                                        45
     return 0;
                                                                                        46
   }
The user library initialization code:
```

```
1
        void init_user_lib(MPI_Comm comm, user_lib_t **handle)
2
          user_lib_t *save;
          user_lib_initsave(&save); /* local */
          MPI_Comm_dup(comm, &(save->comm));
          /* other inits */
10
11
          *handle = save;
12
        }
13
     User start-up code:
14
15
        void user_start_op(user_lib_t *handle, void *data)
16
        {
17
          MPI_Irecv( ..., handle->comm, &(handle->irecv_handle) );
18
          MPI_Isend( ..., handle->comm, &(handle->isend_handle) );
19
        }
20
     User communication clean-up code:
21
22
        void user_end_op(user_lib_t *handle)
23
24
          MPI_Status status;
          MPI_Wait(&handle->isend_handle, &status);
26
          MPI_Wait(&handle->irecv_handle, &status);
27
        }
28
29
     User object clean-up code:
30
        void uninit_user_lib(user_lib_t *handle)
31
        {
32
          MPI_Comm_free(&(handle->comm));
33
          free(handle);
34
       }
35
36
     7.5.6 Library Example #2
37
38
     The main program:
39
        int main(int argc, char *argv[])
41
42
          int ma, mb;
43
          MPI_Group group_world, group_a, group_b;
44
          MPI_Comm comm_a, comm_b;
45
46
          static int list_a[] = \{0, 1\};
47
     #if defined(EXAMPLE_2B) || defined(EXAMPLE_2C)
          static int list_b[] = \{0, 2, 3\};
```

```
#else/* EXAMPLE_2A */
     static int list_b[] = \{0, 2\};
#endif
     int size_list_a = sizeof(list_a)/sizeof(int);
     int size_list_b = sizeof(list_b)/sizeof(int);
     MPI_Init(&argc, &argv);
     MPI_Comm_group(MPI_COMM_WORLD, &group_world);
     MPI_Group_incl(group_world, size_list_a, list_a, &group_a);
     MPI_Group_incl(group_world, size_list_b, list_b, &group_b);
                                                                                     12
                                                                                     13
     MPI_Comm_create(MPI_COMM_WORLD, group_a, &comm_a);
                                                                                     14
                                                                                     15
     MPI_Comm_create(MPI_COMM_WORLD, group_b, &comm_b);
                                                                                     16
     if(comm_a != MPI_COMM_NULL)
                                                                                     18
        MPI_Comm_rank(comm_a, &ma);
                                                                                     19
     if(comm_b != MPI_COMM_NULL)
                                                                                     20
        MPI_Comm_rank(comm_b, &mb);
                                                                                     21
     if(comm_a != MPI_COMM_NULL)
                                                                                     22
                                                                                     23
        lib_call(comm_a);
                                                                                     24
     if(comm_b != MPI_COMM_NULL)
                                                                                     26
       lib_call(comm_b);
                                                                                     27
       lib_call(comm_b);
                                                                                     28
                                                                                     29
     }
                                                                                     30
     if(comm_a != MPI_COMM_NULL)
       MPI_Comm_free(&comm_a);
                                                                                     33
     if(comm_b != MPI_COMM_NULL)
                                                                                     34
       MPI_Comm_free(&comm_b);
     MPI_Group_free(&group_a);
                                                                                     35
     MPI_Group_free(&group_b);
                                                                                     36
                                                                                     37
     MPI_Group_free(&group_world);
     MPI_Finalize();
                                                                                     39
     return 0;
   }
The library:
                                                                                     42
   void lib_call(MPI_Comm comm)
                                                                                     43
                                                                                     44
     int me, done = 0;
                                                                                     45
                                                                                     46
     MPI_Status status;
     MPI_Comm_rank(comm, &me);
     if(me == 0)
```

```
1
              while(!done)
2
              {
3
                 MPI_Recv(..., MPI_ANY_SOURCE, MPI_ANY_TAG, comm, &status);
4
5
              }
6
           else
           {
             /* work */
9
             MPI_Send(..., 0, ARBITRARY_TAG, comm);
10
11
           }
12
     #ifdef EXAMPLE_2C
13
           /* include (resp, exclude) for safety (resp, no safety): */
14
          MPI_Barrier(comm);
15
     #endif
16
        }
```

The above example is really three examples, depending on whether or not one includes rank 3 in list\_b, and whether or not a synchronize is included in lib\_call. This example illustrates that, despite contexts, subsequent calls to lib\_call with the same context need not be safe from one another (colloquially, "back-masking"). Safety is realized if the MPI\_Barrier is added. What this demonstrates is that libraries have to be written carefully, even with contexts. When rank 3 is excluded, then the synchronize is not needed to get safety from back-masking.

Algorithms like "reduce" and "allreduce" have strong enough source selectivity properties so that they are inherently okay (no back-masking), provided that MPI provides basic guarantees. So are multiple calls to a typical tree-broadcast algorithm with the same root or different roots (see [64]). Here we rely on two guarantees of MPI: pairwise ordering of messages between processes in the same context, and source selectivity—deleting either feature removes the guarantee that back-masking cannot be required.

Algorithms that try to do non-deterministic broadcasts or other calls that include wild-card operations will not generally have the good properties of the deterministic implementations of "reduce," "allreduce," and "broadcast." Such algorithms would have to utilize the monotonically increasing tags (within a communicator scope) to keep things straight.

All of the foregoing is a supposition of "collective calls" implemented with point-to-point operations. MPI implementations may or may not implement collective calls using point-to-point operations. These algorithms are used to illustrate the issues of correctness and safety, independent of how MPI implements its collective calls. See also Section 7.9.

#### 7.6 Inter-Communication

This section introduces the concept of inter-communication and describes the portions of MPI that support it. It describes support for writing programs that contain user-level servers.

All communication described thus far has involved communication between processes that are members of the same group. This type of communication is called "intra-communication" and the communicator used is called an "intra-communicator," as we have noted earlier in the chapter.

In modular and multi-disciplinary applications, different process groups execute distinct modules and processes within different modules communicate with one another in a pipeline or a more general module graph. In these applications, the most natural way for a process to specify a target process is by the rank of the target process within the target group. In applications that contain internal user-level servers, each server may be a process group that provides services to one or more clients, and each client may be a process group that uses the services of one or more servers. It is again most natural to specify the target process by rank within the target group in these applications. This type of communication is called "inter-communication" and the communicator used is called an "inter-communicator," as introduced earlier.

An **inter-communication** is a point-to-point communication between processes in different groups. The group containing a process that initiates an inter-communication operation is called the "local group," that is, the sender in a send and the receiver in a receive. The group containing the target process is called the "remote group," that is, the receiver in a send and the sender in a receive. As in intra-communication, the target process is specified using a (communicator, rank) pair. Unlike intra-communication, the rank is relative to a second, remote group.

All inter-communicator constructors are blocking except for MPI\_COMM\_IDUP and require that the local and remote groups be disjoint.

Advice to users. The groups must be disjoint for several reasons. Primarily, this is the intent of the inter-communicators—to provide a communicator for communication between disjoint groups. This is reflected in the definition of MPI\_INTERCOMM\_MERGE, which allows the user to control the ranking of the processes in the created intra-communicator; this ranking makes little sense if the groups are not disjoint. In addition, the natural extension of collective operations to intercommunicators makes the most sense when the groups are disjoint. (End of advice to users.)

Here is a summary of the properties of inter-communication and inter-communicators:

- The syntax of point-to-point and collective communication is the same for both interand intra-communication. The same communicator can be used both for send and for receive operations.
- A target process is addressed by its rank in the remote group, both for sends and for receives.
- Communications using an inter-communicator are guaranteed not to conflict with any communications that use a different communicator.
- A communicator will provide either intra- or inter-communication, never both.

The routine MPI\_COMM\_TEST\_INTER may be used to determine if a communicator is an inter- or intra-communicator. Inter-communicators can be used as arguments to some of the other communicator access routines. Inter-communicators cannot be used as input to some of the constructor routines for intra-communicators (for instance, MPI\_CART\_CREATE).

Advice to implementors. For the purpose of point-to-point communication, communicators can be represented in each process by a tuple consisting of:

group send\_context receive\_context

source

For inter-communicators, group describes the remote group, and source is the rank of the process in the local group. For intra-communicators, group is the communicator group (remote=local), source is the rank of the process in this group, and send context and receive context are identical. A group can be represented by a rank-to-absolute-address translation table.

The inter-communicator cannot be discussed sensibly without considering processes in both the local and remote groups. Imagine a process  $\mathbf{P}$  in group  $\mathcal{P}$ , which has an inter-communicator  $\mathbf{C}_{\mathcal{P}}$ , and a process  $\mathbf{Q}$  in group  $\mathcal{Q}$ , which has an inter-communicator  $\mathbf{C}_{\mathcal{Q}}$ . Then

- $C_{\mathcal{P}}$ .group describes the group  $\mathcal{Q}$  and  $C_{\mathcal{Q}}$ .group describes the group  $\mathcal{P}$ .
- $C_{\mathcal{P}}$ .send\_context =  $C_{\mathcal{Q}}$ .receive\_context and the context is unique in  $\mathcal{Q}$ ;  $C_{\mathcal{P}}$ .receive\_context =  $C_{\mathcal{Q}}$ .send\_context and this context is unique in  $\mathcal{P}$ .
- $C_{\mathcal{P}}$ .source is rank of **P** in  $\mathcal{P}$  and  $C_{\mathcal{Q}}$ .source is rank of **Q** in  $\mathcal{Q}$ .

Assume that **P** sends a message to **Q** using the inter-communicator. Then **P** uses the **group** table to find the absolute address of **Q**; **source** and **send\_context** are appended to the message.

Assume that  $\mathbf{Q}$  posts a receive with an explicit source argument using the inter-communicator. Then  $\mathbf{Q}$  matches **receive\_context** to the message context and source argument to the message source.

The same algorithm is appropriate for intra-communicators as well.

In order to support inter-communicator accessors and constructors, it is necessary to supplement this model with additional structures, that store information about the local communication group, and additional safe contexts. (*End of advice to implementors.*)

#### 7.6.1 Inter-Communicator Accessors

```
MPI_COMM_TEST_INTER(comm, flag)
```

```
IN comm communicator (handle)

OUT flag true if comm is an inter-communicator (logical)
```

#### C binding

```
int MPI_Comm_test_inter(MPI_Comm comm, int *flag)
```

#### Fortran 2008 binding

```
MPI_Comm_test_inter(comm, flag, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
```

18

19 20

21

22

24

26

27 28 29

30

34

35

36 37

38

42

43 44

45 46

```
LOGICAL, INTENT(OUT) :: flag
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
```

MPI\_COMM\_TEST\_INTER(COMM, FLAG, IERROR)
INTEGER COMM, IERROR
LOGICAL FLAG

This local routine allows the calling process to determine if a communicator is an inter-communicator or an intra-communicator. It returns true if it is an inter-communicator, otherwise false.

When an inter-communicator is used as an input argument to the communicator accessors described above under intra-communication, the following table describes behavior.

MPI_COMM_SIZE	returns the size of the local group.	
MPI_COMM_GROUP	returns the local group.	
MPI_COMM_RANK	returns the rank in the local group	

Table 7.1: MPI\_COMM\_\* Function Behavior (in Inter-Communication Mode)

Furthermore, the operation MPI\_COMM\_COMPARE is valid for inter-communicators. Both communicators must be either intra- or inter-communicators, or else MPI\_UNEQUAL results. Both corresponding local and remote groups must compare correctly to get the results MPI\_CONGRUENT or MPI\_SIMILAR. In particular, it is possible for MPI\_SIMILAR to result because either the local or remote groups were similar but not identical.

The following accessors provide consistent access to the remote group of an intercommunicator. The following are all local operations.

```
MPI_COMM_REMOTE_SIZE(comm, size)
```

```
IN comm inter-communicator (handle)

OUT size number of processes in the remote group of comm (integer)
```

#### C binding

```
int MPI_Comm_remote_size(MPI_Comm comm, int *size)
```

#### Fortran 2008 binding

```
MPI_Comm_remote_size(comm, size, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_COMM_REMOTE_SIZE(COMM, SIZE, IERROR)
INTEGER COMM, SIZE, IERROR
```

```
1
     MPI_COMM_REMOTE_GROUP(comm, group)
2
       IN
                                          inter-communicator (handle)
                comm
3
       OUT
                                          remote group corresponding to comm (handle)
                group
4
5
6
     C binding
7
     int MPI_Comm_remote_group(MPI_Comm comm, MPI_Group *group)
8
     Fortran 2008 binding
9
     MPI_Comm_remote_group(comm, group, ierror)
10
         TYPE(MPI_Comm), INTENT(IN) :: comm
11
         TYPE(MPI_Group), INTENT(OUT) :: group
12
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
14
     Fortran binding
     MPI_COMM_REMOTE_GROUP(COMM, GROUP, IERROR)
15
16
         INTEGER COMM, GROUP, IERROR
```

Rationale. Symmetric access to both the local and remote groups of an inter-communicator is important, so this function, as well as MPI\_COMM\_REMOTE\_SIZE have been provided. (*End of rationale*.)

## 7.6.2 Inter-Communicator Operations

This section introduces five blocking inter-communicator operations.

MPI\_INTERCOMM\_CREATE is used to bind two intra-communicators into an inter-communicator; the function MPI\_INTERCOMM\_CREATE\_FROM\_GROUPS constructs an inter-communicator from two previously defined disjoint groups; the function

MPI\_INTERCOMM\_MERGE creates an intra-communicator by merging the local and remote groups of an inter-communicator. The functions MPI\_COMM\_DUP and MPI\_COMM\_FREE, introduced previously, duplicate and free an inter-communicator, respectively.

Overlap of local and remote groups that are bound into an inter-communicator is prohibited. If there is overlap, then the program is erroneous and is likely to deadlock. (If a process is multithreaded, and MPI calls block only a thread, rather than a process, then "dual membership" can be supported. It is then the user's responsibility to make sure that calls on behalf of the two "roles" of a process are executed by two independent threads.)

The function MPI\_INTERCOMM\_CREATE can be used to create an inter-communicator from two existing intra-communicators, in the following situation: At least one selected member from each group (the "group leader") has the ability to communicate with the selected member from the other group; that is, a "peer" communicator exists to which both leaders belong, and each leader knows the rank of the other leader in this peer communicator. Furthermore, members of each group know the rank of their leader.

Construction of an inter-communicator from two intra-communicators requires separate collective operations in the local group and in the remote group, as well as a point-to-point communication between a process in the local group and a process in the remote group.

When using the World Model, the MPI\_COMM\_WORLD communicator (or preferably a dedicated duplicate thereof) can be this peer communicator. For applications that have used the Sessions Model, spawn, or join it may be necessary to first create an intra-communicator to be used as peer.

communicators. Users that require this capability should utilize MPI\_INTERCOMM\_MERGE to build an intra-communicator, then apply the graph or cartesian topology capabilities to that intra-communicator, creating an appropriate topology-oriented intra-communicator. Alternatively, it may be reasonable to devise one's own application topology mechanisms for this case, without loss of generality.

The application topology functions described in Chapter 8 do not apply to inter-

# MPI\_INTERCOMM\_CREATE(local\_comm, local\_leader, peer\_comm, remote\_leader, tag, newintercomm)

IN	local_comm	local intra-communicator (handle)
IN	local_leader	${\rm rank\ of\ local\ group\ leader\ in\ } {\sf local\_comm\ (integer)}$
IN	peer_comm	"peer" communicator; significant only at the local_leader (handle)
IN	remote_leader	rank of remote group leader in peer_comm; significant only at the local_leader (integer)
IN	tag	tag (integer)
OUT	newintercomm	new inter-communicator (handle)

#### C binding

#### Fortran 2008 binding

#### Fortran binding

```
MPI_INTERCOMM_CREATE(LOCAL_COMM, LOCAL_LEADER, PEER_COMM, REMOTE_LEADER, TAG, NEWINTERCOMM, IERROR)

INTEGER LOCAL_COMM, LOCAL_LEADER, PEER_COMM, REMOTE_LEADER, TAG, NEWINTERCOMM, IERROR
```

This call creates an inter-communicator. It is collective over the union of the local and remote groups. MPI processes should provide identical local\_comm and local\_leader arguments within each group. Wildcards are not permitted for remote\_leader, local\_leader, and tag.

```
1
     MPI_INTERCOMM_CREATE_FROM_GROUPS(local_group, local_leader, remote_group,
2
                    remote_leader, stringtag, info, errhandler, newintercomm)
3
       IN
                 local_group
                                             local group (handle)
       IN
                 local_leader
                                             rank of local group leader in local_group (integer)
5
6
       IN
                 remote_group
                                             remote group, significant only at local_leader (handle)
                 remote_leader
                                             rank of remote group leader in remote_group,
       IN
                                             significant only at local_leader (integer)
9
                 stringtag
                                             unique idenitifier for this operation (string)
       IN
10
11
                 info
       IN
                                             info object (handle)
12
       IN
                 errhandler
                                             error handler to be attached to new
13
                                             inter-communicator (handle)
14
       OUT
                 newintercomm
                                             new inter-communicator (handle)
15
16
17
     C binding
     int MPI_Intercomm_create_from_groups(MPI_Group local_group,
18
                    int local_leader, MPI_Group remote_group, int remote_leader,
19
                    const char *stringtag, MPI_Info info,
20
                    MPI_Errhandler errhandler, MPI_Comm *newintercomm)
21
22
     Fortran 2008 binding
23
     MPI_Intercomm_create_from_groups(local_group, local_leader, remote_group,
24
                    remote_leader, stringtag, info, errhandler, newintercomm,
25
                    ierror)
26
          TYPE(MPI_Group), INTENT(IN) :: local_group, remote_group
27
          INTEGER, INTENT(IN) :: local_leader, remote_leader
28
          CHARACTER(LEN=*), INTENT(IN) :: stringtag
29
          TYPE(MPI_Info), INTENT(IN) :: info
30
          TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
31
          TYPE(MPI_Comm), INTENT(OUT) :: newintercomm
32
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
33
34
     Fortran binding
     MPI_INTERCOMM_CREATE_FROM_GROUPS(LOCAL_GROUP, LOCAL_LEADER, REMOTE_GROUP,
35
                    REMOTE_LEADER, STRINGTAG, INFO, ERRHANDLER, NEWINTERCOMM,
36
37
                    IERROR)
          INTEGER LOCAL_GROUP, LOCAL_LEADER, REMOTE_GROUP, REMOTE_LEADER, INFO,
38
                     ERRHANDLER, NEWINTERCOMM, IERROR
39
40
          CHARACTER*(*) STRINGTAG
41
     This call creates an inter-communicator. Unlike MPI_INTERCOMM_CREATE, this function
42
     uses as input previously defined, disjoint local and remote groups. The calling MPI process
43
     must be a member of the local group. The call is collective over the union of the local
44
     and remote groups. All involved MPI processes shall provide an identical value for the
45
     stringtag argument. Within each group, all MPI processes shall provide identical
46
     local_group, local_leader arguments. Wildcards are not permitted for the
47
     remote_leader or local_leader arguments. The stringtag argument serves the same purpose
```

as the stringtag used in the MPI\_COMM\_CREATE\_FROM\_GROUP function; it differentiates concurrent calls in a multithreaded environment. The stringtag shall not exceed MPI\_MAX\_FROM\_GROUP\_STRINGTAG characters in length. For C, this includes space for a null terminating character. In the event that MPI\_GROUP\_EMPTY is supplied as the local\_group or remote\_group or both, then the call is a local operation and MPI\_COMM\_NULL is returned as the newintercomm.

### MPI\_INTERCOMM\_MERGE(intercomm, high, newintracomm)

IN intercomm inter-communicator (handle)

IN high ordering of the local and remote groups in the new intra-communicator (logical)

OUT newintracomm new intra-communicator (handle)

#### C binding

#### Fortran 2008 binding

```
MPI_Intercomm_merge(intercomm, high, newintracomm, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: intercomm
    LOGICAL, INTENT(IN) :: high
    TYPE(MPI_Comm), INTENT(OUT) :: newintracomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_INTERCOMM_MERGE(INTERCOMM, HIGH, NEWINTRACOMM, IERROR)
INTEGER INTERCOMM, NEWINTRACOMM, IERROR
LOGICAL HIGH
```

This function creates an intra-communicator from the union of the two groups that are associated with intercomm. All processes should provide the same high value within each of the two groups. If processes in one group provided the value high = false and processes in the other group provided the value high = true then the union orders the "low" group before the "high" group. If all processes provided the same high argument then the order of the union is arbitrary. This call is blocking and collective within the union of the two groups.

The error handler on the new inter-communicator in each process is inherited from the communicator that contributes the local group. Note that this can result in different processes in the same communicator having different error handlers.

Advice to implementors. The implementation of MPI\_INTERCOMM\_MERGE, MPI\_COMM\_FREE, and MPI\_COMM\_DUP are similar to the implementation of MPI\_INTERCOMM\_CREATE, except that contexts private to the input inter-communicator are used for communication between group leaders rather than contexts inside a bridge communicator. (End of advice to implementors.)

#-other #-error! #-update5 Done in PR400

12

13

14 15

16

18 19

20

21

22

23

26

27

28

29

34

35

36

37

38

39

41

42

43

44

45




Figure 7.4: Three-group pipeline

11

12

13

14

15 16

2

### 7.6.3 Inter-Communication Examples

#### Example 1: Three-Group "Pipeline"

Groups 0 and 1 communicate. Groups 1 and 2 communicate. Therefore, group 0 requires one inter-communicator, group 1 requires two inter-communicators, and group 2 requires 1 inter-communicator.

```
int main(int argc, char *argv[])
17
        {
                                    /* intra-communicator of local sub-group */
          MPI_Comm
                      myComm;
19
          MPI_Comm
                     myFirstComm;
                                    /* inter-communicator */
20
          MPI_Comm
                      mySecondComm; /* second inter-communicator (group 1 only) */
21
          int membershipKey;
22
          int rank;
23
          MPI_Init(&argc, &argv);
          MPI_Comm_rank(MPI_COMM_WORLD, &rank);
27
          /* User code must generate membershipKey in the range [0, 1, 2] */
28
          membershipKey = rank % 3;
29
30
          /* Build intra-communicator for local sub-group */
          MPI_Comm_split(MPI_COMM_WORLD, membershipKey, rank, &myComm);
33
          /* Build inter-communicators.
                                          Tags are hard-coded. */
34
          if (membershipKey == 0)
35
                                 /* Group 0 communicates with group 1. */
36
            MPI_Intercomm_create(myComm, 0, MPI_COMM_WORLD, 1,
37
                                  1, &myFirstComm);
          else if (membershipKey == 1)
                          /* Group 1 communicates with groups 0 and 2. */
            MPI_Intercomm_create(myComm, 0, MPI_COMM_WORLD, 0,
                                  1, &myFirstComm);
43
            MPI_Intercomm_create(myComm, 0, MPI_COMM_WORLD, 2,
44
                                  12, &mySecondComm);
45
          }
          else if (membershipKey == 2)
                                 /* Group 2 communicates with group 1. */
```

13 14

15 16

18

19

20

21

22

23

24

26

27

28

29 30

34




Figure 7.5: Three-group ring

# Example 2: Three-Group "Ring"

Groups 0 and 1 communicate. Groups 1 and 2 communicate. Groups 0 and 2 communicate. Therefore, each requires two inter-communicators.

```
int main(int argc, char *argv[])
                                                                                 35
{
                                                                                 36
 MPI_Comm
                           /* intra-communicator of local sub-group */
             myComm;
                                                                                 37
 MPI_Comm
             myFirstComm; /* inter-communicators */
                                                                                 38
 MPI_Comm
             mySecondComm;
                                                                                 39
  int membershipKey;
  int rank;
                                                                                 42
 MPI_Init(&argc, &argv);
                                                                                 43
 MPI_Comm_rank(MPI_COMM_WORLD, &rank);
                                                                                 44
                                                                                 45
                                                                                 46
  /* User code must generate membershipKey in the range [0, 1, 2] */
 membershipKey = rank % 3;
```

```
1
2
          /* Build intra-communicator for local sub-group */
          MPI_Comm_split(MPI_COMM_WORLD, membershipKey, rank, &myComm);
          /* Build inter-communicators. Tags are hard-coded. */
          if (membershipKey == 0)
          {
                         /* Group 0 communicates with groups 1 and 2. */
            MPI_Intercomm_create(myComm, 0, MPI_COMM_WORLD, 1,
                                   1, &myFirstComm);
10
            MPI_Intercomm_create(myComm, 0, MPI_COMM_WORLD, 2,
11
                                  2, &mySecondComm);
12
          }
13
          else if (membershipKey == 1)
14
                     /* Group 1 communicates with groups 0 and 2.
15
            MPI_Intercomm_create(myComm, 0, MPI_COMM_WORLD, 0,
16
                                   1, &myFirstComm);
            MPI_Intercomm_create(myComm, 0, MPI_COMM_WORLD, 2,
18
                                  12, &mySecondComm);
19
          }
20
          else if (membershipKey == 2)
21
                    /* Group 2 communicates with groups 0 and 1. */
22
            MPI_Intercomm_create(myComm, 0, MPI_COMM_WORLD, 0,
23
                                  2, &myFirstComm);
24
            MPI_Intercomm_create(myComm, 0, MPI_COMM_WORLD, 1,
                                   12, &mySecondComm);
26
          }
27
28
          /* Do some work ...
29
          /* Then free communicators before terminating... */
30
          MPI_Comm_free(&myFirstComm);
          MPI_Comm_free(&mySecondComm);
33
          MPI_Comm_free(&myComm);
34
          MPI_Finalize();
35
          return 0;
36
        }
37
38
```

# 7.7 Caching

39

41

42

43

44 45

46

47

MPI provides a "caching" facility that allows an application to attach arbitrary pieces of information, called **attributes**, to three kinds of MPI objects, communicators, windows, and datatypes. More precisely, the caching facility allows a portable library to do the following:

- pass information between calls by associating it with an MPI intra- or inter-communicator, window, or datatype,
- quickly retrieve that information, and

• be guaranteed that out-of-date information is never retrieved, even if the object is freed and its handle subsequently reused by MPI.

The caching capabilities, in some form, are required by built-in MPI routines such as collective communication and application topology. Defining an interface to these capabilities as part of the MPI standard is valuable because it permits routines like collective communication and application topologies to be implemented as portable code, and also because it makes MPI more extensible by allowing user-written routines to use standard MPI calling sequences.

Advice to users. The communicator MPI\_COMM\_SELF is a suitable choice for posting process-local attributes, via this attribute-caching mechanism. (*End of advice to users.*)

Rationale. In one extreme one can allow caching on all opaque handles. The other extreme is to only allow it on communicators. Caching has a cost associated with it and should only be allowed when it is clearly needed and the increased cost is modest. This is the reason that windows and datatypes were added but not other handles. (End of rationale.)

One difficulty is the potential for size differences between Fortran integers and C pointers. For this reason, the Fortran versions of these routines use integers of kind MPI\_ADDRESS\_KIND.

Advice to implementors. High-quality implementations should raise an error when a keyval that was created by a call to MPI\_XXX\_CREATE\_KEYVAL is used with an object of the wrong type with a call to MPI\_YYY\_GET\_ATTR, MPI\_YYY\_SET\_ATTR, MPI\_YYY\_DELETE\_ATTR, or MPI\_YYY\_FREE\_KEYVAL. To do so, it is necessary to maintain, with each keyval, information on the type of the associated user function. (End of advice to implementors.)

# 7.7.1 Functionality

Attributes can be attached to communicators, windows, and datatypes. Attributes are local to the process and specific to the communicator to which they are attached. Attributes are not propagated by MPI from one communicator to another except when the communicator is duplicated using MPI\_COMM\_DUP or MPI\_COMM\_IDUP (and even then the application must give specific permission through callback functions for the attribute to be copied).

Advice to users. Attributes in C are of type void\*. Typically, such an attribute will be a pointer to a structure that contains further information, or a handle to an MPI object. In Fortran, attributes are of type INTEGER. Such attribute can be a handle to an MPI object, or just an integer-valued attribute. (End of advice to users.)

Advice to implementors. Attributes are scalar values, equal in size to, or larger than a C-language pointer. Attributes can always hold an MPI handle. (End of advice to implementors.)

The caching interface defined here requires that attributes be stored by MPI opaquely within a communicator, window, or datatype. Accessor functions include the following:

- obtain a key value (used to identify an attribute); the user specifies "callback" functions by which MPI informs the application when the communicator is destroyed or copied.
- store and retrieve the value of an attribute;

Advice to implementors. Caching and callback functions are only called synchronously, in response to explicit application requests. This avoids problems that result from repeated crossings between user and system space. (This synchronous calling rule is a general property of MPI.)

The choice of key values is under control of MPI. This allows MPI to optimize its implementation of attribute sets. It also avoids conflict between independent modules caching information on the same communicators.

A much smaller interface, consisting of just a callback facility, would allow the entire caching facility to be implemented by portable code. However, with the minimal callback interface, some form of table searching is implied by the need to handle arbitrary communicators. In contrast, the more complete interface defined here permits rapid access to attributes through the use of pointers in communicators (to find the attribute table) and cleverly chosen key values (to retrieve individual attributes). In light of the efficiency "hit" inherent in the minimal interface, the more complete interface defined here is seen to be superior. (End of advice to implementors.)

MPI provides the following services related to caching. They are all process local.

### 7.7.2 Communicators

Functions for caching on communicators are:

```
\label{eq:mpi_comm_copy_attr_fn, comm_delete_attr_fn, comm_keyval, extra_state)} \\ \text{MPI_COMM\_CREATE\_KEYVAL}(comm\_copy\_attr\_fn, comm\_delete\_attr\_fn, comm\_keyval, extra_state)}
```

```
IN comm_copy_attr_fn copy callback function for comm_keyval (function)
IN comm_delete_attr_fn delete callback function for comm_keyval (function)
OUT comm_keyval key value for future access (integer)
IN extra_state extra state for callback function
```

# C binding

### Fortran 2008 binding

```
INTEGER, INTENT(OUT) :: comm_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_COMM_CREATE_KEYVAL(COMM_COPY_ATTR_FN, COMM_DELETE_ATTR_FN, COMM_KEYVAL,
              EXTRA_STATE, IERROR)
    EXTERNAL COMM_COPY_ATTR_FN, COMM_DELETE_ATTR_FN
    INTEGER COMM_KEYVAL, IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
    Generates a new attribute key. Keys are locally unique in a process, and opaque to
user, though they are explicitly stored in integers. Once allocated, the key value can be
                                                                                    12
                                                                                    13
used to associate attributes and access them on any locally defined communicator.
                                                                                    14
The C callback functions are:
                                                                                    15
typedef int MPI_Comm_copy_attr_function(MPI_Comm oldcomm, int comm_keyval,
              void *extra_state, void *attribute_val_in,
              void *attribute_val_out, int *flag);
                                                                                    19
typedef int MPI_Comm_delete_attr_function(MPI_Comm comm, int comm_keyval,
                                                                                    20
              void *attribute_val, void *extra_state);
                                                                                    21
                                                                                    22
which are the same as the MPI-1.1 calls but with a new name. The old names are deprecated.
With the mpi_f08 module, the Fortran callback functions are:
                                                                                    24
ABSTRACT INTERFACE
  SUBROUTINE MPI_Comm_copy_attr_function(oldcomm, comm_keyval, extra_state,
                                                                                    26
               attribute_val_in, attribute_val_out, flag, ierror)
                                                                                    27
    TYPE(MPI_Comm) :: oldcomm
                                                                                    28
    INTEGER :: comm_keyval, ierror
                                                                                    29
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
                                                                                    30
               attribute_val_out
    LOGICAL :: flag
and
                                                                                    33
ABSTRACT INTERFACE
                                                                                    34
 SUBROUTINE MPI_Comm_delete_attr_function(comm, comm_keyval,
                                                                                    35
               attribute_val, extra_state, ierror)
                                                                                    36
    TYPE(MPI_Comm) :: comm
                                                                                    37
    INTEGER :: comm_keyval, ierror
    INTEGER(KIND=MPI_ADDRESS_KIND) :: attribute_val, extra_state
With the mpi module and mpif.h, the Fortran callback functions are:
SUBROUTINE COMM_COPY_ATTR_FUNCTION(OLDCOMM, COMM_KEYVAL, EXTRA_STATE,
                                                                                    42
              ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)
                                                                                    43
    INTEGER OLDCOMM, COMM_KEYVAL, IERROR
                                                                                    44
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
                                                                                    45
               ATTRIBUTE_VAL_OUT
                                                                                    46
    LOGICAL FLAG
```

and

SUBROUTINE COMM\_DELETE\_ATTR\_FUNCTION(COMM, COMM\_KEYVAL, ATTRIBUTE\_VAL, EXTRA\_STATE, IERROR)

INTEGER COMM, COMM\_KEYVAL, IERROR
INTEGER(KIND=MPI\_ADDRESS\_KIND) ATTRIBUTE\_VAL, EXTRA\_STATE

The comm\_copy\_attr\_fn function is invoked when a communicator is duplicated by MPI\_COMM\_DUP or MPI\_COMM\_IDUP. comm\_copy\_attr\_fn should be of type MPI\_Comm\_copy\_attr\_function. The copy callback function is invoked for each key value in oldcomm in arbitrary order. Each call to the copy callback is made with a key value and its corresponding attribute. If it returns flag = 0 or .FALSE., then the attribute is deleted in the duplicated communicator. Otherwise (flag = 1 or .TRUE.), the new attribute value is set to the value returned in attribute\_val\_out. The function returns MPI\_SUCCESS on success and an error code on failure (in which case MPI\_COMM\_DUP or MPI\_COMM\_IDUP will fail).

The argument comm\_copy\_attr\_fn may be specified as MPI\_COMM\_NULL\_COPY\_FN or MPI\_COMM\_DUP\_FN from either C or Fortran. MPI\_COMM\_NULL\_COPY\_FN is a function that does nothing other than returning flag = 0 or .FALSE. (depending on whether the keyval was created with a C or Fortran binding to MPI\_COMM\_CREATE\_KEYVAL) and MPI\_SUCCESS. MPI\_COMM\_DUP\_FN is a simple-minded copy function that sets flag = 1 or .TRUE., returns the value of attribute\_val\_in in attribute\_val\_out, and returns MPI\_SUCCESS. These replace the MPI-1 predefined callbacks MPI\_NULL\_COPY\_FN and MPI\_DUP\_FN, whose use is deprecated.

Advice to users. Even though both formal arguments attribute\_val\_in and attribute\_val\_out are of type void\*, their usage differs. The C copy function is passed by MPI in attribute\_val\_in the value of the attribute, and in attribute\_val\_out the address of the attribute, so as to allow the function to return the (new) attribute value. The use of type void\* for both is to avoid messy type casts.

A valid copy function is one that completely duplicates the information by making a full duplicate copy of the data structures implied by an attribute; another might just make another reference to that data structure, while using a reference-count mechanism. Other types of attributes might not copy at all (they might be specific to oldcomm only). (End of advice to users.)

Advice to implementors. A C interface should be assumed for copy and delete functions associated with key values created in C; a Fortran calling interface should be assumed for key values created in Fortran. (End of advice to implementors.)

Analogous to comm\_copy\_attr\_fn is a callback deletion function, defined as follows. The comm\_delete\_attr\_fn function is invoked when a communicator is deleted by MPI\_COMM\_FREE or when a call is made explicitly to MPI\_COMM\_DELETE\_ATTR. comm\_delete\_attr\_fn should be of type MPI\_Comm\_delete\_attr\_function.

This function is called by MPI\_COMM\_FREE, MPI\_COMM\_DELETE\_ATTR, and MPI\_COMM\_SET\_ATTR to do whatever is needed to remove an attribute. The function returns MPI\_SUCCESS on success and an error code on failure (in which case MPI\_COMM\_FREE will fail).

The argument comm\_delete\_attr\_fn may be specified as MPI\_COMM\_NULL\_DELETE\_FN from either C or Fortran.

MPI\_COMM\_NULL\_DELETE\_FN is a function that does nothing, other than returning MPI\_SUCCESS. MPI\_COMM\_NULL\_DELETE\_FN replaces MPI\_NULL\_DELETE\_FN, whose use is deprecated.

If an attribute copy function or attribute delete function returns other than MPI\_SUCCESS, then the call that caused it to be invoked (for example, MPI\_COMM\_FREE), is erroneous.

The special key value MPI\_KEYVAL\_INVALID is never returned by MPI\_COMM\_CREATE\_KEYVAL. Therefore, it can be used for static initialization of key values.

Advice to implementors. The predefined Fortran functions MPI\_COMM\_NULL\_COPY\_FN, MPI\_COMM\_DUP\_FN, and MPI\_COMM\_NULL\_DELETE\_FN are defined in the mpi module (and mpif.h) and the mpi\_f08 module with the same name, but with different interfaces. Each function can coexist twice with the same name in the same MPI library, one routine as an implicit interface outside of the mpi module, i.e., declared as EXTERNAL, and the other routine within mpi\_f08 declared with CONTAINS. These routines have different link names, which are also different to the link names used for the routines used in C. (End of advice to implementors.)

Advice to users. Callbacks, including the predefined Fortran functions MPI\_COMM\_NULL\_COPY\_FN, MPI\_COMM\_DUP\_FN, and MPI\_COMM\_NULL\_DELETE\_FN should not be passed from one application routine that uses the mpi\_f08 module to another application routine that uses the mpi module or mpif.h, and vice versa; see also the advice to users on page 836. (End of advice to users.)

```
MPI_COMM_FREE_KEYVAL(comm_keyval)
```

INOUT comm\_keyval key value (integer)

# C binding

int MPI\_Comm\_free\_keyval(int \*comm\_keyval)

### Fortran 2008 binding

MPI\_Comm\_free\_keyval(comm\_keyval, ierror)
 INTEGER, INTENT(INOUT) :: comm\_keyval
 INTEGER, OPTIONAL, INTENT(OUT) :: ierror

### Fortran binding

MPI\_COMM\_FREE\_KEYVAL(COMM\_KEYVAL, IERROR)
INTEGER COMM\_KEYVAL, IERROR

Frees an extant attribute key. This function sets the value of keyval to MPI\_KEYVAL\_INVALID. Note that it is not erroneous to free an attribute key that is in use, because the actual free does not transpire until after all references (in other communicators on the process) to the key have been freed. These references need to be explictly freed by the program, either via calls to MPI\_COMM\_DELETE\_ATTR that free one attribute instance,

or by calls to MPI\_COMM\_FREE that free all attribute instances associated with the freed communicator.

```
MPI_COMM_SET_ATTR(comm, comm_keyval, attribute_val)
```

```
INOUT comm communicator to which attribute will be attached (handle)

IN comm_keyval key value (integer)

IN attribute_val attribute value
```

# C binding

```
int MPI_Comm_set_attr(MPI_Comm comm, int comm_keyval, void *attribute_val)
```

# Fortran 2008 binding

```
MPI_Comm_set_attr(comm, comm_keyval, attribute_val, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: comm_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

```
MPI_COMM_SET_ATTR(COMM, COMM_KEYVAL, ATTRIBUTE_VAL, IERROR)
INTEGER COMM, COMM_KEYVAL, IERROR
INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
```

This function stores the stipulated attribute value attribute\_val for subsequent retrieval by MPI\_COMM\_GET\_ATTR. If the value is already present, then the outcome is as if MPI\_COMM\_DELETE\_ATTR was first called to delete the previous value (and the callback function comm\_delete\_attr\_fn was executed), and a new value was next stored. The call is erroneous if there is no key with value keyval; in particular MPI\_KEYVAL\_INVALID is an erroneous key value. The call will fail if the comm\_delete\_attr\_fn function returned an error code other than MPI\_SUCCESS.

# MPI\_COMM\_GET\_ATTR(comm, comm\_keyval, attribute\_val, flag)

```
IN comm communicator to which the attribute is attached (handle)

IN comm_keyval key value (integer)

OUT attribute_val attribute value, unless flag = false

OUT flag false if no attribute is associated with the key (logical)
```

# C binding

### Fortran 2008 binding

```
MPI_Comm_get_attr(comm, comm_keyval, attribute_val, flag, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: comm_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI_COMM_GET_ATTR(COMM, COMM_KEYVAL, ATTRIBUTE_VAL, FLAG, IERROR)
    INTEGER COMM, COMM_KEYVAL, IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
    LOGICAL FLAG
```

Retrieves attribute value by key. The call is erroneous if there is no key with value keyval. On the other hand, the call is correct if the key value exists, but no attribute is attached on comm for that key; in such case, the call returns flag = false. In particular MPI\_KEYVAL\_INVALID is an erroneous key value.

Advice to users. The call to MPI\_Comm\_set\_attr passes in attribute\_val the value of the attribute; the call to MPI\_Comm\_get\_attr passes in attribute\_val the address of the location where the attribute value is to be returned. Thus, if the attribute value itself is a pointer of type void\*, then the actual attribute\_val parameter to MPI\_Comm\_set\_attr will be of type void\* and the actual attribute\_val parameter to MPI\_Comm\_get\_attr will be of type void\*\*. (End of advice to users.)

Rationale. The use of a formal parameter attribute\_val of type void\* (rather than void\*\*) avoids the messy type casting that would be needed if the attribute value is declared with a type other than void\*. (End of rationale.)

```
MPI_COMM_DELETE_ATTR(comm, comm_keyval)
```

```
INOUT comm communicator from which the attribute is deleted (handle)

IN comm_keyval key value (integer)
```

### C binding

int MPI\_Comm\_delete\_attr(MPI\_Comm comm, int comm\_keyval)

# Fortran 2008 binding

```
MPI_Comm_delete_attr(comm, comm_keyval, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: comm_keyval
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

```
MPI_COMM_DELETE_ATTR(COMM, COMM_KEYVAL, IERROR)
    INTEGER COMM, COMM_KEYVAL, IERROR
```

Delete attribute from cache by key. This function invokes the attribute delete function comm\_delete\_attr\_fn specified when the keyval was created. The call will fail if the comm\_delete\_attr\_fn function returns an error code other than MPI\_SUCCESS.

Whenever a communicator is replicated using the function MPI\_COMM\_DUP or MPI\_COMM\_IDUP, all call-back copy functions for attributes that are currently set are invoked (in arbitrary order). Whenever a communicator is deleted using the function MPI\_COMM\_FREE all callback delete functions for attributes that are currently set are invoked.

# 7.7.3 Windows

The functions for caching on windows are:

```
MPI_WIN_CREATE_KEYVAL(win_copy_attr_fn, win_delete_attr_fn, win_keyval, extra_state)
```

```
IN win_copy_attr_fn copy callback function for win_keyval (function)
IN win_delete_attr_fn delete callback function for win_keyval (function)
OUT win_keyval key value for future access (integer)
IN extra_state extra state for callback function
```

# C binding

### Fortran 2008 binding

# Fortran binding

```
MPI_WIN_CREATE_KEYVAL(WIN_COPY_ATTR_FN, WIN_DELETE_ATTR_FN, WIN_KEYVAL, EXTRA_STATE, IERROR)

EXTERNAL WIN_COPY_ATTR_FN, WIN_DELETE_ATTR_FN

INTEGER WIN_KEYVAL, IERROR

INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
```

The argument win\_copy\_attr\_fn may be specified as MPI\_WIN\_NULL\_COPY\_FN or MPI\_WIN\_DUP\_FN from either C or Fortran. MPI\_WIN\_NULL\_COPY\_FN is a function that does nothing other than returning flag = 0 and MPI\_SUCCESS. MPI\_WIN\_DUP\_FN is a simple-minded copy function that sets flag = 1, returns the value of attribute\_val\_in in attribute\_val\_out, and returns MPI\_SUCCESS.

```
The argument win_delete_attr_fn may be specified as MPI_WIN_NULL_DELETE_FN
from either C or Fortran. MPI_WIN_NULL_DELETE_FN is a function that does nothing,
other than returning MPI_SUCCESS.
The C callback functions are:
typedef int MPI_Win_copy_attr_function(MPI_Win oldwin, int win_keyval,
              void *extra_state, void *attribute_val_in,
              void *attribute_val_out, int *flag);
and
typedef int MPI_Win_delete_attr_function(MPI_Win win, int win_keyval,
              void *attribute_val, void *extra_state);
With the mpi_f08 module, the Fortran callback functions are:
                                                                                    12
                                                                                    13
ABSTRACT INTERFACE
                                                                                    14
  SUBROUTINE MPI_Win_copy_attr_function(oldwin, win_keyval, extra_state,
                                                                                    15
               attribute_val_in, attribute_val_out, flag, ierror)
                                                                                    16
    TYPE(MPI_Win) :: oldwin
    INTEGER :: win_keyval, ierror
                                                                                    18
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
                                                                                    19
               attribute_val_out
                                                                                    20
    LOGICAL :: flag
                                                                                    21
and
                                                                                    22
ABSTRACT INTERFACE
                                                                                    23
  SUBROUTINE MPI_Win_delete_attr_function(win, win_keyval, attribute_val,
                                                                                    24
               extra_state, ierror)
    TYPE(MPI_Win) :: win
                                                                                    26
    INTEGER :: win_keyval, ierror
                                                                                    27
    INTEGER(KIND=MPI_ADDRESS_KIND) :: attribute_val, extra_state
                                                                                    28
                                                                                    29
With the mpi module and mpif.h, the Fortran callback functions are:
                                                                                    30
SUBROUTINE WIN_COPY_ATTR_FUNCTION(OLDWIN, WIN_KEYVAL, EXTRA_STATE,
              ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)
    INTEGER OLDWIN, WIN_KEYVAL, IERROR
                                                                                    33
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
                                                                                    34
               ATTRIBUTE_VAL_OUT
                                                                                    35
    LOGICAL FLAG
                                                                                    36
and
                                                                                    37
SUBROUTINE WIN_DELETE_ATTR_FUNCTION(WIN, WIN_KEYVAL, ATTRIBUTE_VAL,
              EXTRA_STATE, IERROR)
    INTEGER WIN, WIN_KEYVAL, IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
                                                                                    42
    If an attribute copy function or attribute delete function returns other than
                                                                                    43
MPI_SUCCESS, then the call that caused it to be invoked (for example, MPI_WIN_FREE), is
                                                                                    44
erroneous.
                                                                                    45
```

```
MPI_WIN_FREE_KEYVAL(win_keyval)
2
       INOUT
                 win_keyval
                                             key value (integer)
3
     C binding
     int MPI_Win_free_keyval(int *win_keyval)
6
     Fortran 2008 binding
     MPI_Win_free_keyval(win_keyval, ierror)
9
          INTEGER, INTENT(INOUT) :: win_keyval
10
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
11
     Fortran binding
12
     MPI_WIN_FREE_KEYVAL(WIN_KEYVAL, IERROR)
13
          INTEGER WIN_KEYVAL, IERROR
14
15
16
     MPI_WIN_SET_ATTR(win, win_keyval, attribute_val)
17
18
                                             window to which attribute will be attached (handle)
       INOUT
19
       IN
                 win_keyval
                                             key value (integer)
20
21
       IN
                 attribute_val
                                             attribute value
22
23
     C binding
24
     int MPI_Win_set_attr(MPI_Win win, int win_keyval, void *attribute_val)
     Fortran 2008 binding
26
     MPI_Win_set_attr(win, win_keyval, attribute_val, ierror)
27
          TYPE(MPI_Win), INTENT(IN) :: win
28
          INTEGER, INTENT(IN) :: win_keyval
29
          INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val
30
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
31
32
     Fortran binding
33
     MPI_WIN_SET_ATTR(WIN, WIN_KEYVAL, ATTRIBUTE_VAL, IERROR)
34
          INTEGER WIN, WIN_KEYVAL, IERROR
35
          INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
36
37
38
     MPI_WIN_GET_ATTR(win, win_keyval, attribute_val, flag)
39
       IN
                 win
                                             window to which the attribute is attached (handle)
41
                 win_keyval
       IN
                                             key value (integer)
42
       OUT
                 attribute_val
                                             attribute value, unless flag = false
43
       OUT
                 flag
                                             false if no attribute is associated with the key
44
                                             (logical)
45
46
```

# C binding

```
int MPI_Win_get_attr(MPI_Win win, int win_keyval, void *attribute_val,
              int *flag)
Fortran 2008 binding
MPI_Win_get_attr(win, win_keyval, attribute_val, flag, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, INTENT(IN) :: win_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_WIN_GET_ATTR(WIN, WIN_KEYVAL, ATTRIBUTE_VAL, FLAG, IERROR)
                                                                                     12
                                                                                     13
    INTEGER WIN, WIN_KEYVAL, IERROR
                                                                                     14
    INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
                                                                                     15
    LOGICAL FLAG
                                                                                     16
                                                                                     18
MPI_WIN_DELETE_ATTR(win, win_keyval)
                                                                                     19
  INOUT
                                     window from which the attribute is deleted (handle)
           win
                                                                                     20
  IN
           win_keyval
                                     key value (integer)
                                                                                     21
                                                                                     22
                                                                                     23
C binding
                                                                                     24
int MPI_Win_delete_attr(MPI_Win win, int win_keyval)
Fortran 2008 binding
MPI_Win_delete_attr(win, win_keyval, ierror)
                                                                                     27
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                     28
    INTEGER, INTENT(IN) :: win_keyval
                                                                                     29
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                     30
Fortran binding
MPI_WIN_DELETE_ATTR(WIN, WIN_KEYVAL, IERROR)
                                                                                     33
    INTEGER WIN, WIN_KEYVAL, IERROR
                                                                                     34
                                                                                     35
7.7.4 Datatypes
                                                                                     36
                                                                                     37
The new functions for caching on datatypes are:
                                                                                     42
                                                                                     43
                                                                                     44
                                                                                     45
```

```
1
     MPI_TYPE_CREATE_KEYVAL(type_copy_attr_fn, type_delete_attr_fn, type_keyval,
2
                    extra_state)
3
       IN
                type_copy_attr_fn
                                           copy callback function for type_keyval (function)
       IN
                type_delete_attr_fn
                                           delete callback function for type_keyval (function)
5
6
       OUT
                type_keyval
                                           key value for future access (integer)
       IN
                extra_state
                                           extra state for callback function
8
9
     C binding
10
     int MPI_Type_create_keyval(MPI_Type_copy_attr_function *type_copy_attr_fn,
11
                    MPI_Type_delete_attr_function *type_delete_attr_fn,
12
                    int *type_keyval, void *extra_state)
13
14
     Fortran 2008 binding
15
     MPI_Type_create_keyval(type_copy_attr_fn, type_delete_attr_fn, type_keyval,
16
                    extra_state, ierror)
17
         PROCEDURE(MPI_Type_copy_attr_function), INTENT(IN) :: type_copy_attr_fn
18
         PROCEDURE(MPI_Type_delete_attr_function), INTENT(IN) ::
19
                    type_delete_attr_fn
20
         INTEGER, INTENT(OUT) :: type_keyval
21
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
22
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
23
     Fortran binding
24
     MPI_TYPE_CREATE_KEYVAL(TYPE_COPY_ATTR_FN, TYPE_DELETE_ATTR_FN, TYPE_KEYVAL,
25
                    EXTRA_STATE, IERROR)
26
         EXTERNAL TYPE_COPY_ATTR_FN, TYPE_DELETE_ATTR_FN
27
         INTEGER TYPE_KEYVAL, IERROR
28
         INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
29
30
         The argument type_copy_attr_fn may be specified as MPI_TYPE_NULL_COPY_FN or
31
     MPI_TYPE_DUP_FN from either C or Fortran. MPI_TYPE_NULL_COPY_FN is a function
32
     that does nothing other than returning flag = 0 and MPI_SUCCESS. MPI_TYPE_DUP_FN
33
     is a simple-minded copy function that sets flag = 1, returns the value of attribute_val_in in
34
     attribute_val_out, and returns MPI_SUCCESS.
35
         The argument type_delete_attr_fn may be specified as MPI_TYPE_NULL_DELETE_FN
36
     from either C or Fortran. MPI_TYPE_NULL_DELETE_FN is a function that does nothing,
37
     other than returning MPI_SUCCESS.
38
     The C callback functions are:
39
     typedef int MPI_Type_copy_attr_function(MPI_Datatype oldtype,
                    int type_keyval, void *extra_state, void *attribute_val_in,
41
                    void *attribute_val_out, int *flag);
42
     and
43
     typedef int MPI_Type_delete_attr_function(MPI_Datatype datatype,
44
                    int type_keyval, void *attribute_val, void *extra_state);
45
46
     With the mpi_f08 module, the Fortran callback functions are:
47
     ABSTRACT INTERFACE
```

```
SUBROUTINE MPI_Type_copy_attr_function(oldtype, type_keyval, extra_state,
              attribute_val_in, attribute_val_out, flag, ierror)
    TYPE(MPI_Datatype) :: oldtype
    INTEGER :: type_keyval, ierror
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
              attribute_val_out
    LOGICAL :: flag
and
ABSTRACT INTERFACE
  SUBROUTINE MPI_Type_delete_attr_function(datatype, type_keyval,
              attribute_val, extra_state, ierror)
                                                                                    12
    TYPE(MPI_Datatype) :: datatype
                                                                                    13
    INTEGER :: type_keyval, ierror
                                                                                    14
    INTEGER(KIND=MPI_ADDRESS_KIND) :: attribute_val, extra_state
                                                                                    15
                                                                                    16
With the mpi module and mpif.h, the Fortran callback functions are:
SUBROUTINE TYPE_COPY_ATTR_FUNCTION(OLDTYPE, TYPE_KEYVAL, EXTRA_STATE,
                                                                                    18
              ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)
                                                                                    19
    INTEGER OLDTYPE, TYPE_KEYVAL, IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
                                                                                   20
                                                                                   21
              ATTRIBUTE_VAL_OUT
                                                                                   22
    LOGICAL FLAG
                                                                                   23
and
SUBROUTINE TYPE_DELETE_ATTR_FUNCTION(DATATYPE, TYPE_KEYVAL, ATTRIBUTE_VAL,
              EXTRA_STATE, IERROR)
                                                                                    26
    INTEGER DATATYPE, TYPE_KEYVAL, IERROR
                                                                                   27
    INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
                                                                                   28
                                                                                   29
    If an attribute copy function or attribute delete function returns other than
                                                                                   30
MPI_SUCCESS, then the call that caused it to be invoked (for example, MPI_TYPE_FREE),
is erroneous.
MPI_TYPE_FREE_KEYVAL(type_keyval)
                                                                                   34
                                                                                   35
 INOUT type_keyval
                                     key value (integer)
                                                                                   36
                                                                                   37
C binding
int MPI_Type_free_keyval(int *type_keyval)
Fortran 2008 binding
MPI_Type_free_keyval(type_keyval, ierror)
    INTEGER, INTENT(INOUT) :: type_keyval
                                                                                   42
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    43
                                                                                    44
Fortran binding
                                                                                    45
MPI_TYPE_FREE_KEYVAL(TYPE_KEYVAL, IERROR)
                                                                                    46
    INTEGER TYPE_KEYVAL, IERROR
```

```
MPI_TYPE_SET_ATTR(datatype, type_keyval, attribute_val)
2
       INOUT
                datatype
                                            datatype to which attribute will be attached (handle)
3
                type_keyval
       IN
                                            key value (integer)
5
                attribute_val
       IN
                                            attribute value
6
7
     C binding
     int MPI_Type_set_attr(MPI_Datatype datatype, int type_keyval,
9
                    void *attribute_val)
10
     Fortran 2008 binding
11
     MPI_Type_set_attr(datatype, type_keyval, attribute_val, ierror)
12
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
13
         INTEGER, INTENT(IN) :: type_keyval
14
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val
15
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
16
17
     Fortran binding
18
     MPI_TYPE_SET_ATTR(DATATYPE, TYPE_KEYVAL, ATTRIBUTE_VAL, IERROR)
19
         INTEGER DATATYPE, TYPE_KEYVAL, IERROR
20
         INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
21
22
23
     MPI_TYPE_GET_ATTR(datatype, type_keyval, attribute_val, flag)
24
                                            datatype to which the attribute is attached (handle)
       IN
                datatype
25
26
       IN
                type_keyval
                                            key value (integer)
27
       OUT
                attribute_val
                                            attribute value, unless flag = false
28
       OUT
                flag
                                            false if no attribute is associated with the key
29
                                            (logical)
30
31
32
     C binding
33
     int MPI_Type_get_attr(MPI_Datatype datatype, int type_keyval,
34
                    void *attribute_val, int *flag)
35
     Fortran 2008 binding
36
     MPI_Type_get_attr(datatype, type_keyval, attribute_val, flag, ierror)
37
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, INTENT(IN) :: type_keyval
39
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val
         LOGICAL, INTENT(OUT) :: flag
41
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
42
43
     Fortran binding
44
     MPI_TYPE_GET_ATTR(DATATYPE, TYPE_KEYVAL, ATTRIBUTE_VAL, FLAG, IERROR)
45
         INTEGER DATATYPE, TYPE_KEYVAL, IERROR
46
         INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
47
         LOGICAL FLAG
```

```
MPI_TYPE_DELETE_ATTR(datatype, type_keyval)
  INOUT
           datatype
                                      datatype from which the attribute is deleted (handle)
  IN
           type_keyval
                                      key value (integer)
C binding
int MPI_Type_delete_attr(MPI_Datatype datatype, int type_keyval)
Fortran 2008 binding
MPI_Type_delete_attr(datatype, type_keyval, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: type_keyval
                                                                                       12
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       13
Fortran binding
                                                                                       14
MPI_TYPE_DELETE_ATTR(DATATYPE, TYPE_KEYVAL, IERROR)
                                                                                       15
    INTEGER DATATYPE, TYPE_KEYVAL, IERROR
                                                                                       16
                                                                                       18
7.7.5 Error Class for Invalid Keyval
                                                                                       19
                                                                                       20
Key values for attributes are system-allocated, by
                                                                                      21
MPI_{XXX}_CREATE_KEYVAL. Only such values can be passed to the functions that use
                                                                                      22
key values as input arguments. In order to signal that an erroneous key value has been
                                                                                      23
passed to one of these functions, there is a new MPI error class: MPI_ERR_KEYVAL. It can
                                                                                       24
be returned by MPI_ATTR_PUT, MPI_ATTR_GET, MPI_ATTR_DELETE,
MPI_KEYVAL_FREE,
                                                                                       26
MPI_{XXX}_DELETE_ATTR,
                                                                                       27
MPI_{XXX}_SET_ATTR,
                                                                                       28
MPI_{XXX}_GET_ATTR,
                                                                                       29
MPI_{XXX}_FREE_KEYVAL, MPI_COMM_DUP, MPI_COMM_IDUP,
                                                                                       30
MPI_COMM_DISCONNECT, and MPI_COMM_FREE. The last four are included because
                                                                                       31
keyval is an argument to the copy and delete functions for attributes.
                                                                                       33
7.7.6 Attributes Example
                                                                                      34
     Advice to users.
                        This example shows how to write a collective communication
                                                                                      35
     operation that uses caching to be more efficient after the first call. (End of advice to
                                                                                      36
     users.)
                                                                                      37
                                                                                       38
   /* key for this module's stuff: */
   static int gop_key = MPI_KEYVAL_INVALID;
                                                                                       42
   typedef struct
                                                                                       43
   {
                                                                                       44
                                 /* reference count */
      int ref_count;
                                                                                       45
      /* other stuff, whatever else we want */
```

} gop\_stuff\_type;

```
1
        void Efficient_Collective_Op(MPI_Comm comm, ...)
2
          gop_stuff_type *gop_stuff;
          MPI_Group
                           group;
5
          int
                           foundflag;
6
7
          MPI_Comm_group(comm, &group);
          if (gop_key == MPI_KEYVAL_INVALID) /* get a key on first call ever */
          {
11
            if ( ! MPI_Comm_create_keyval(gop_stuff_copier,
12
                                      gop_stuff_destructor,
13
                                      &gop_key, (void *)0)) {
14
            /* get the key while assigning its copy and delete callback
15
               behavior. */
16
            } else
                MPI_Abort(comm, 99);
          }
19
20
          MPI_Comm_get_attr(comm, gop_key, &gop_stuff, &foundflag);
21
          if (foundflag)
          { /* This module has executed in this group before.
23
               We will use the cached information */
24
          }
          else
          { /* This is a group that we have not yet cached anything in.
27
               We will now do so.
28
            */
29
            /* First, allocate storage for the stuff we want,
               and initialize the reference count */
33
            gop_stuff = (gop_stuff_type *) malloc(sizeof(gop_stuff_type));
34
            if (gop_stuff == NULL) { /* abort on out-of-memory error */ }
35
36
            gop_stuff->ref_count = 1;
37
            /* Second, fill in *gop_stuff with whatever we want.
               This part isn't shown here */
            /* Third, store gop_stuff as the attribute value */
            MPI_Comm_set_attr(comm, gop_key, gop_stuff);
43
44
          /* Then, in any case, use contents of *gop_stuff
45
             to do the global op ... */
46
        }
47
        /* The following routine is called by MPI when a group is freed */
```

13 14

15

16

18

19

20

21

22

23 24

26

27

28 29

30

33 34

35

36

37

38

39

42

43

44

45 46

```
int gop_stuff_destructor(MPI_Comm comm, int keyval, void *gop_stuffP,
                         void *extra)
{
  gop_stuff_type *gop_stuff = (gop_stuff_type *)gop_stuffP;
  if (keyval != gop_key) { /* abort -- programming error */ }
  /* The group's being freed removes one reference to gop_stuff */
  gop_stuff->ref_count -= 1;
  /* If no references remain, then free the storage */
  if (gop_stuff->ref_count == 0) {
    free((void *)gop_stuff);
  }
  return MPI_SUCCESS;
}
/* The following routine is called by MPI when a group is copied */
int gop_stuff_copier(MPI_Comm comm, int keyval, void *extra,
               void *gop_stuff_inP, void *gop_stuff_outP, int *flag)
{
  gop_stuff_type *gop_stuff_in = (gop_stuff_type *)gop_stuff_inP;
  gop_stuff_type **gop_stuff_out = (gop_stuff_type **)gop_stuff_outP;
  if (keyval != gop_key) { /* abort -- programming error */ }
  /* The new group adds one reference to this gop_stuff */
  gop_stuff_in->ref_count += 1;
  *gop_stuff_out = gop_stuff_in;
  return MPI_SUCCESS;
}
```

# 7.8 Naming Objects

There are many occasions on which it would be useful to allow a user to associate a printable identifier with an MPI communicator, window, or datatype, for instance error reporting, debugging, and profiling. The names attached to opaque objects do not propagate when the object is duplicated or copied by MPI routines. For communicators this can be achieved using the following two functions.

```
MPI_COMM_SET_NAME(comm, comm_name)

INOUT comm communicator whose identifier is to be set (handle)

IN comm_name the character string which is remembered as the name (string)

C binding
```

int MPI\_Comm\_set\_name(MPI\_Comm comm, const char \*comm\_name)

```
Fortran 2008 binding
```

```
MPI_Comm_set_name(comm, comm_name, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    CHARACTER(LEN=*), INTENT(IN) :: comm_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

```
MPI_COMM_SET_NAME(COMM, COMM_NAME, IERROR)
    INTEGER COMM, IERROR
    CHARACTER*(*) COMM_NAME
```

MPI\_COMM\_SET\_NAME allows a user to associate a name string with a communicator. The character string which is passed to MPI\_COMM\_SET\_NAME will be saved inside the MPI library (so it can be freed by the caller immediately after the call, or allocated on the stack). Leading spaces in name are significant but trailing ones are not.

MPI\_COMM\_SET\_NAME is a local (non-collective) operation, which only affects the name of the communicator as seen in the process which made the MPI\_COMM\_SET\_NAME call. There is no requirement that the same (or any) name be assigned to a communicator in every process where it exists.

Advice to users. Since MPI\_COMM\_SET\_NAME is provided to help debug code, it is sensible to give the same name to a communicator in all of the processes where it exists, to avoid confusion. (*End of advice to users.*)

The length of the name which can be stored is limited to the value of MPI\_MAX\_OBJECT\_NAME in Fortran and MPI\_MAX\_OBJECT\_NAME-1 in C to allow for the null terminator. Attempts to put names longer than this will result in truncation of the name. MPI\_MAX\_OBJECT\_NAME must have a value of at least 64.

Advice to users. Under circumstances of store exhaustion an attempt to put a name of any length could fail, therefore the value of MPI\_MAX\_OBJECT\_NAME should be viewed only as a strict upper bound on the name length, not a guarantee that setting names of less than this length will always succeed. (*End of advice to users*.)

Advice to implementors. Implementations which pre-allocate a fixed size space for a name should use the length of that allocation as the value of MPI\_MAX\_OBJECT\_NAME. Implementations which allocate space for the name from the heap should still define MPI\_MAX\_OBJECT\_NAME to be a relatively small value, since the user has to allocate space for a string of up to this size when calling MPI\_COMM\_GET\_NAME. (End of advice to implementors.)

# 

# MPI\_COMM\_GET\_NAME(comm, comm\_name, resultlen)

IN	comm	communicator whose name is to be returned (handle)
OUT	comm_name	the name previously stored on the communicator, or
		an empty string if no such name exists (string)
OUT	resultlen	length of returned name (integer)

# C binding

```
int MPI_Comm_get_name(MPI_Comm comm, char *comm_name, int *resultlen)
Fortran 2008 binding
MPI_Comm_get_name(comm, comm_name, resultlen, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    CHARACTER(LEN=MPI_MAX_OBJECT_NAME), INTENT(OUT) :: comm_name
    INTEGER, INTENT(OUT) :: resultlen
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

```
MPI_COMM_GET_NAME(COMM, COMM_NAME, RESULTLEN, IERROR)
INTEGER COMM, RESULTLEN, IERROR
CHARACTER*(*) COMM_NAME
```

MPI\_COMM\_GET\_NAME returns the last name which has previously been associated with the given communicator. The name may be set and retrieved from any language. The same name will be returned independent of the language used. name should be allocated so that it can hold a resulting string of length MPI\_MAX\_OBJECT\_NAME characters.

MPI\_COMM\_GET\_NAME returns a copy of the set name in name.

In C, a null character is additionally stored at name[resultlen]. The value of resultlen cannot be larger than MPI\_MAX\_OBJECT\_NAME-1. In Fortran, name is padded on the right with blank characters. The value of resultlen cannot be larger than MPI\_MAX\_OBJECT\_NAME.

If the user has not associated a name with a communicator, or an error occurs, MPI\_COMM\_GET\_NAME will return an empty string (all spaces in Fortran, "" in C). The three predefined communicators will have predefined names associated with them. Thus, the names of MPI\_COMM\_WORLD, MPI\_COMM\_SELF, and the communicator returned by MPI\_COMM\_GET\_PARENT (if not MPI\_COMM\_NULL) will have the default of MPI\_COMM\_WORLD, MPI\_COMM\_SELF, and MPI\_COMM\_PARENT. The fact that the system may have chosen to give a default name to a communicator does not prevent the user from setting a name on the same communicator; doing this removes the old name and assigns the new one.

Rationale. We provide separate functions for setting and getting the name of a communicator, rather than simply providing a predefined attribute key for the following reasons:

- It is not, in general, possible to store a string as an attribute from Fortran.
- It is not easy to set up the delete function for a string attribute unless it is known to have been allocated from the heap.
- To make the attribute key useful additional code to call strdup is necessary. If this is not standardized then users have to write it. This is extra unneeded work which we can easily eliminate.
- The Fortran binding is not trivial to write (it will depend on details of the Fortran compilation system), and will not be portable. Therefore it should be in the library rather than in user code.

(End of rationale.)

 Advice to users. The above definition means that it is safe simply to print the string returned by MPI\_COMM\_GET\_NAME, as it is always a valid string even if there was no name.

Note that associating a name with a communicator has no effect on the semantics of an MPI program, and will (necessarily) increase the store requirement of the program, since the names must be saved. Therefore there is no requirement that users use these functions to associate names with communicators. However debugging and profiling MPI applications may be made easier if names are associated with communicators, since the debugger or profiler should then be able to present information in a less cryptic manner. (*End of advice to users*.)

The following functions are used for setting and getting names of datatypes. The constant MPI\_MAX\_OBJECT\_NAME also applies to these names.

# MPI\_TYPE\_SET\_NAME(datatype, type\_name)

```
INOUT datatype datatype whose identifier is to be set (handle)

IN type_name the character string which is remembered as the name (string)
```

# C binding

```
int MPI_Type_set_name(MPI_Datatype datatype, const char *type_name)
```

# Fortran 2008 binding

```
MPI_Type_set_name(datatype, type_name, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    CHARACTER(LEN=*), INTENT(IN) :: type_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

```
MPI_TYPE_SET_NAME(DATATYPE, TYPE_NAME, IERROR)
INTEGER DATATYPE, IERROR
CHARACTER*(*) TYPE_NAME
```

# MPI\_TYPE\_GET\_NAME(datatype, type\_name, resultlen)

```
OUT type_name datatype whose name is to be returned (handle)
the name previously stored on the datatype, or an empty string if no such name exists (string)

OUT resultlen length of returned name (integer)
```

# 43 C binding

### Fortran 2008 binding

```
MPI_Type_get_name(datatype, type_name, resultlen, ierror)
```

```
TYPE(MPI_Datatype), INTENT(IN) :: datatype
    CHARACTER(LEN=MPI_MAX_OBJECT_NAME), INTENT(OUT) :: type_name
    INTEGER, INTENT(OUT) :: resultlen
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_TYPE_GET_NAME(DATATYPE, TYPE_NAME, RESULTLEN, IERROR)
    INTEGER DATATYPE, RESULTLEN, IERROR
    CHARACTER*(*) TYPE_NAME
    Named predefined datatypes have the default names of the datatype name. For exam-
ple, MPI_WCHAR has the default name of "MPI_WCHAR".
    The following functions are used for setting and getting names of windows. The con-
                                                                                        12
stant MPI_MAX_OBJECT_NAME also applies to these names.
                                                                                        13
                                                                                        14
                                                                                        15
MPI_WIN_SET_NAME(win, win_name)
                                                                                        16
  INOUT
           win
                                      window whose identifier is to be set (handle)
                                                                                        18
  IN
           win_name
                                      the character string which is remembered as the
                                                                                        19
                                      name (string)
                                                                                        20
                                                                                       21
C binding
                                                                                        22
int MPI_Win_set_name(MPI_Win win,
                                     const char *win_name)
                                                                                        23
Fortran 2008 binding
MPI_Win_set_name(win, win_name, ierror)
                                                                                        26
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                        27
    CHARACTER(LEN=*), INTENT(IN) :: win_name
                                                                                        28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                        29
Fortran binding
                                                                                        30
MPI_WIN_SET_NAME(WIN, WIN_NAME, IERROR)
    INTEGER WIN, IERROR
    CHARACTER*(*) WIN_NAME
                                                                                        33
                                                                                        34
                                                                                        35
MPI_WIN_GET_NAME(win, win_name, resultlen)
                                                                                        36
                                                                                        37
  IN
           win
                                      window whose name is to be returned (handle)
  OUT
                                      the name previously stored on the window, or an
           win_name
                                      empty string if no such name exists (string)
  OUT
           resultlen
                                      length of returned name (integer)
                                                                                        42
                                                                                        43
C binding
                                                                                        44
int MPI_Win_get_name(MPI_Win win, char *win_name, int *resultlen)
                                                                                        45
Fortran 2008 binding
                                                                                        46
MPI_Win_get_name(win, win_name, resultlen, ierror)
```

TYPE(MPI\_Win), INTENT(IN) :: win

```
CHARACTER(LEN=MPI_MAX_OBJECT_NAME), INTENT(OUT) :: win_name
    INTEGER, INTENT(OUT) :: resultlen
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI_WIN_GET_NAME(WIN, WIN_NAME, RESULTLEN, IERROR)
```

# 7.9 Formalizing the Loosely Synchronous Model

INTEGER WIN, RESULTLEN, IERROR

CHARACTER\*(\*) WIN\_NAME

In this section, we make further statements about the loosely synchronous model, with particular attention to intra-communication.

# 7.9.1 Basic Statements

When a caller passes a communicator (that contains a context and group) to a callee, that communicator must be free of side effects throughout execution of the subprogram: there should be no active operations on that communicator that might involve the process. This provides one model in which libraries can be written, and work "safely." For libraries so designated, the callee has permission to do whatever communication it likes with the communicator, and under the above guarantee knows that no other communications will interfere. Since we permit good implementations to create new communicators without synchronization (such as by preallocated contexts on communicators), this does not impose a significant overhead.

This form of safety is analogous to other common computer-science usages, such as passing a descriptor of an array to a library routine. The library routine has every right to expect such a descriptor to be valid and modifiable.

# 7.9.2 Models of Execution

In the loosely synchronous model, transfer of control to a **parallel procedure** is effected by having each executing process invoke the procedure. The invocation is a collective operation: it is executed by all processes in the execution group, and invocations are similarly ordered at all processes. However, the invocation need not be synchronized.

We say that a parallel procedure is *active* in a process if the process belongs to a group that may collectively execute the procedure, and some member of that group is currently executing the procedure code. If a parallel procedure is active in a process, then this process may be receiving messages pertaining to this procedure, even if it does not currently execute the code of this procedure.

#### Static Communicator Allocation

This covers the case where, at any point in time, at most one invocation of a parallel procedure can be active at any process, and the group of executing processes is fixed. For example, all invocations of parallel procedures involve all processes, processes are single-threaded, and there are no recursive invocations.

In such a case, a communicator can be statically allocated to each procedure. The static allocation can be done in a preamble, as part of initialization code. If the parallel procedures can be organized into libraries, so that only one procedure of each library can be concurrently active in each processor, then it is sufficient to allocate one communicator per library.

# Dynamic Communicator Allocation

Calls of parallel procedures are well-nested if a new parallel procedure is always invoked in a subset of a group executing the same parallel procedure. Thus, processes that execute the same parallel procedure have the same execution stack.

In such a case, a new communicator needs to be dynamically allocated for each new invocation of a parallel procedure. The allocation is done by the caller. A new communicator can be generated by a call to MPI\_COMM\_DUP, if the callee execution group is identical to the caller execution group, or by a call to MPI\_COMM\_SPLIT if the caller execution group is split into several subgroups executing distinct parallel routines. The new communicator is passed as an argument to the invoked routine.

The need for generating a new communicator at each invocation can be alleviated or avoided altogether in some cases: If the execution group is not split, then one can allocate a stack of communicators in a preamble, and next manage the stack in a way that mimics the stack of recursive calls.

One can also take advantage of the well-ordering property of communication to avoid confusing caller and callee communication, even if both use the same communicator. To do so, one needs to abide by the following two rules:

- messages sent before a procedure call (or before a return from the procedure) are also received before the matching call (or return) at the receiving end;
- messages are always selected by source (no use is made of MPI\_ANY\_SOURCE).

# The General Case

In the general case, there may be multiple concurrently active invocations of the same parallel procedure within the same group; invocations may not be well-nested. A new communicator needs to be created for each invocation. It is the user's responsibility to make sure that, should two distinct parallel procedures be invoked concurrently on overlapping sets of processes, communicator creation is properly coordinated.



#-... all changes
#-nnn by issue nnn
#-PRnnn by pull request
Non problematic fomatting-changes and typo-corrections are not listed
Embiggening: only new \_c versions are marked, all other is not listed
New or changed content
Problematic fomatting-changes are listed
#-error
Errors in RC 40 - also marked with #-error
B.m.n: i. - refers to Change-Log section B.m.n, Item i

Chapter 8

# **Process Topologies**

# 8.1 Introduction

This chapter discusses the MPI topology mechanism. A topology is an extra, optional attribute that one can give to an intra-communicator; topologies cannot be added to inter-communicators. A topology can provide a convenient naming mechanism for the processes of a group (within a communicator), and additionally, may assist the runtime system in mapping the processes onto hardware.

As stated in Chapter 7, a process group in MPI is a collection of n processes. Each process in the group is assigned a rank between 0 and n-1. In many parallel applications a linear ranking of processes does not adequately reflect the logical communication pattern of the processes (which is usually determined by the underlying problem geometry and the numerical algorithm used). Often the processes are arranged in topological patterns such as two- or three-dimensional grids. More generally, the logical process arrangement is described by a graph. In this chapter we will refer to this logical process arrangement as the "virtual topology."

A clear distinction must be made between the virtual process topology and the topology of the underlying, physical hardware. The virtual topology can be exploited by the system in the assignment of processes to physical processors, if this helps to improve the communication performance on a given machine. How this mapping is done, however, is outside the scope of MPI. The description of the virtual topology, on the other hand, depends only on the application, and is machine-independent. The functions that are described in this chapter deal with machine-independent mapping and communication on virtual process topologies.

Rationale. Though physical mapping is not discussed, the existence of the virtual topology information may be used as advice by the runtime system. There are well-known techniques for mapping grid/torus structures to hardware topologies such as hypercubes or grids. For more complicated graph structures good heuristics often yield nearly optimal results [49]. On the other hand, if there is no way for the user to specify the logical process arrangement as a "virtual topology," a random mapping is most likely to result. On some machines, this will lead to unnecessary contention in the interconnection network. Some details about predicted and measured performance improvements that result from good process-to-processor mapping on modern wormhole-routing architectures can be found in [12, 13].

4

1

2

5

7

9

10

6

11 12 13

19

20

21

22

23 24

27 28

25

26

29 30

31 32

33 34

35 36

37

38

40

42

43

44

45

46

47

48

#-314

Besides possible performance benefits, the virtual topology can function as a convenient, process-naming structure, with significant benefits for program readability and notational power in message-passing programming. (End of rationale.)

#### 8.2 Virtual Topologies

The communication pattern of a set of processes can be represented by a graph. nodes represent processes, and the edges connect processes that communicate with each other. MPI provides message-passing between any pair of processes in a group. There is no requirement for opening a channel explicitly. Therefore, a "missing link" in the user-defined process graph does not prevent the corresponding processes from exchanging messages. It means rather that this connection is neglected in the virtual topology. This strategy implies that the topology gives no convenient way of naming this pathway of communication. Another possible consequence is that an automatic mapping tool (if one exists for the runtime environment) will not take account of this edge when mapping.

Specifying the virtual topology in terms of a graph is sufficient for all applications. However, in many applications the graph structure is regular, and the detailed set-up of the graph would be inconvenient for the user and might be less efficient at run time. A large fraction of all parallel applications use process topologies like rings, two- or higher-dimensional grids, or tori. These structures are completely defined by the number of dimensions and the numbers of processes in each coordinate direction. Also, the mapping of grids and tori is generally an easier problem than that of general graphs. Thus, it is desirable to address these cases explicitly.

Process coordinates in a Cartesian structure begin their numbering at 0. Row-major numbering is always used for the processes in a Cartesian structure. This means that, for example, the relation between group rank and coordinates for four processes in a  $(2 \times 2)$ grid is as follows.

> $\operatorname{coord}(0.0)$ : rank 0  $\operatorname{coord}(0,1)$ : rank 1  $\operatorname{coord}(1.0)$ : rank 2 coord (1,1): rank 3

# Embedding in MPI

The support for virtual topologies as defined in this chapter is consistent with other parts of MPI, and, whenever possible, makes use of functions that are defined elsewhere. Topology information is associated with communicators. It is added to communicators using the caching mechanism described in Chapter 7.

Information representing an MPI virtual topology may be added to a communicator at the time of its creation. If a communicator creation function adds information representing an MPI virtual topology to the output communicator it creates, then it either propagates the topology representation from the input communicator to the output communicator, or adds a new topology representation generated from the input parameters that describe a virtual topology. The description of every MPI communicator creation function explicitly states how topology information is handled. Communicator creation functions that create new topology representations are described in Section 8.5.

# 8.4 Overview of the Functions

MPI supports three topology types: Cartesian, graph, and distributed graph. The function MPI\_CART\_CREATE can be used to create Cartesian topologies, the function MPI\_GRAPH\_CREATE can be used to create graph topologies, and the functions MPI\_DIST\_GRAPH\_CREATE\_ADJACENT and MPI\_DIST\_GRAPH\_CREATE can be used to create distributed graph topologies. These topology creation functions are collective. As with other collective calls, the program must be written to work correctly, whether the call synchronizes or not.

The above topology creation functions take as input an existing communicator comm\_old, which defines the set of processes on which the topology is to be mapped. For MPI\_GRAPH\_CREATE and MPI\_CART\_CREATE, all input arguments must have identical values on all processes of the group of comm\_old. When calling MPI\_GRAPH\_CREATE, each process specifies all nodes and edges in the graph. In contrast, the functions MPI\_DIST\_GRAPH\_CREATE\_ADJACENT or MPI\_DIST\_GRAPH\_CREATE are used to specify the graph in a distributed fashion, whereby each process only specifies a subset of the edges in the graph such that the entire graph structure is defined collectively across the set of processes. Therefore the processes provide different values for the arguments specifying the graph. However, all processes must give the same value for reorder and the info argument. In all cases, a new communicator comm\_topol is created that carries the topological structure as cached information (see Chapter 7). In analogy to function MPI\_COMM\_CREATE, no cached information propagates from comm\_old to comm\_topol.

MPI\_CART\_CREATE can be used to describe Cartesian structures of arbitrary dimension. For each coordinate direction one specifies whether the process structure is periodic or not. Note that an n-dimensional hypercube is an n-dimensional torus with 2 processes per coordinate direction. Thus, special support for hypercube structures is not necessary. The local auxiliary function MPI\_DIMS\_CREATE can be used to compute a balanced distribution of processes among a given number of dimensions.

MPI\_defines functions to query a communicator for topology information. The function MPI\_TOPO\_TEST is used to query for the type of topology associated with a communicator. Depending on the topology type, different information can be extracted. For a graph topology, the functions MPI\_GRAPHDIMS\_GET and MPI\_GRAPH\_GET retrieve the graph-topology information that is associated with the communicator. Additionally, the functions MPI\_GRAPH\_NEIGHBORS\_COUNT and MPI\_GRAPH\_NEIGHBORS can be used to obtain the neighbors of an arbitrary node in the graph. For a distributed graph topology, the functions MPI\_DIST\_GRAPH\_NEIGHBORS\_COUNT and MPI\_DIST\_GRAPH\_NEIGHBORS can be used to obtain the neighbors of the calling process. For a Cartesian topology, the function MPI\_CARTDIM\_GET returns the number of dimensions and MPI\_MPI\_MPI\_CART\_GET returns the numbers of processes in each dimension and periodicity of the associated Cartesian topology. Additionally, the functions MPI\_CART\_RANK and MPI\_CART\_COORDS translate Cartesian coordinates into a group rank, and vice-versa. The function MPI\_CART\_SHIFT provides the information needed to communicate with neighbors along a Cartesian dimension. All of these query functions are local.

For Cartesian topologies, the function MPI\_CART\_SUB can be used to extract a Cartesian subspace (analogous to MPI\_COMM\_SPLIT). This function is collective over the input communicator's group.

The two additional functions, MPI\_GRAPH\_MAP and MPI\_CART\_MAP, are, in general, not called by the user directly. However, together with the communicator manipulation

#-314

**#-314** 

#-error

Done in ... + PR439 functions presented in Chapter 7, they are sufficient to implement all other topology functions. Section 8.5.8 outlines such an implementation.

The neighborhood collective communication routines MPI\_NEIGHBOR\_ALLGATHER, MPI\_NEIGHBOR\_ALLGATHERV, MPI\_NEIGHBOR\_ALLTOALL,

MPI\_NEIGHBOR\_ALLTOALLV, and MPI\_NEIGHBOR\_ALLTOALLW communicate with the nearest neighbors on the topology associated with the communicator. The nonblocking variants are MPI\_INEIGHBOR\_ALLGATHER, MPI\_INEIGHBOR\_ALLGATHERV,

MPI\_INEIGHBOR\_ALLTOALL, MPI\_INEIGHBOR\_ALLTOALLV, and MPI\_INEIGHBOR\_ALLTOALLW.

 IN

# 8.5 Topology Constructors

comm\_old

# 8.5.1 Cartesian Constructor

```
MPI_CART_CREATE(comm_old, ndims, dims, periods, reorder, comm_cart)
```

IN	ndims	number of dimensions of Cartesian grid (integer)
IN	dims	integer array of size ndims specifying the number of
		processes in each dimension
IN	periods	logical array of size ndims specifying whether the grid
		is periodic (true) or not (false) in each dimension
IN	reorder	ranking may be reordered (true) or not (false)

input communicator (handle)

IN reorder ranking may be reordered (true) or not (false) (logical)

OUT comm\_cart

communicator with new Cartesian topology (handle)

# C binding

# Fortran 2008 binding

```
MPI_Cart_create(comm_old, ndims, dims, periods, reorder, comm_cart, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm_old
    INTEGER, INTENT(IN) :: ndims, dims(ndims)
    LOGICAL, INTENT(IN) :: periods(ndims), reorder
    TYPE(MPI_Comm), INTENT(OUT) :: comm_cart
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

```
MPI_CART_CREATE(COMM_OLD, NDIMS, DIMS, PERIODS, REORDER, COMM_CART, IERROR)
    INTEGER COMM_OLD, NDIMS, DIMS(*), COMM_CART, IERROR
    LOGICAL PERIODS(*), REORDER
```

MPI\_CART\_CREATE returns a handle to a new communicator to which the Cartesian topology information is attached. If reorder = false then the rank of each process in the new group is identical to its rank in the old group. Otherwise, the function may reorder

Sometimes, = is used, somtimes ==. Is there a general rule for test of

#-27746

the processes (possibly so as to choose a good embedding of the virtual topology onto the physical machine). If the total size of the Cartesian grid is smaller than the size of the group of comm\_old, then some processes are returned MPI\_COMM\_NULL, in analogy to MPI\_COMM\_SPLIT. If ndims is zero then a zero-dimensional Cartesian topology is created. The call is erroneous if it specifies a grid that is larger than the group size or if ndims is negative. MPI\_CART\_CREATE will associate information representing a Cartesian topology with the specified number of dimensions, numbers of processes in each coordinate direction, and periodicity with the new communicator. MPI

#### 8.5.2 Cartesian Convenience Function: MPI\_DIMS\_CREATE

For Cartesian topologies, the function MPI\_DIMS\_CREATE helps the user select a balanced distribution of processes per coordinate direction, depending on the number of processes in the group to be balanced and optional constraints that can be specified by the user. One use is to partition all the processes (the size of MPI\_COMM\_WORLD's group) into an n-dimensional topology.

# MPI\_DIMS\_CREATE(nnodes, ndims, dims)

number of nodes in a grid (integer) IN nnodes IN ndims number of Cartesian dimensions (integer) **INOUT** integer array of size ndims specifying the number of dims nodes in each dimension

### C binding

int MPI\_Dims\_create(int nnodes, int ndims, int dims[])

### Fortran 2008 binding


```
MPI_Dims_create(nnodes, ndims, dims, ierror)
    INTEGER, INTENT(IN) :: nnodes, ndims
    INTEGER, INTENT(INOUT) :: dims(ndims)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

```
MPI_DIMS_CREATE(NNODES, NDIMS, DIMS, IERROR)
    INTEGER NNODES, NDIMS, DIMS(*), IERROR
```

The entries in the array dims are set to describe a Cartesian grid with ndims dimensions and a total of nnodes nodes. The dimensions are set to be as close to each other as possible, using an appropriate divisibility algorithm. The caller may further constrain the operation of this routine by specifying elements of array dims. If dims[i] is set to a positive number, the routine will not modify the number of nodes in dimension i; only those entries where dims[i] = 0 are modified by the call.

Negative input values of dims[i] are erroneous. An error will occur if nnodes is not a multiple of



\$\$\prod\_{i, {\sf dims}[i]\neq 0} \mpicode{dims[\$i\$]}.\$\$



4

11

12

13

14

15

16 17 18

19

20 21

22

23

24 25

26

27 28

29

30

33

34

35

36 37

38

40

42

43

44

45 #-error

#-72 | 3 B.2.2: 10 4

6

18

19

20 21

22

23

24

25 26

27 28

29

30

31

32

33

34

35

36

37

38

39 40

41

42

43

44

45

46

47

For dims[i] set by the call, dims[i] will be ordered in non-increasing order. Array dims is suitable for use as input to routine MPI\_CART\_CREATE. MPI\_DIMS\_CREATE is local. If ndims is zero and nnodes is one, MPI\_DIMS\_CREATE returns MPI\_SUCCESS.

# Example 8.1

dims	function call	dims
before call		on return
(0,0)	MPI_DIMS_CREATE(6, 2, dims)	(3,2)
(0,0)	MPI_DIMS_CREATE(7, 2, dims)	(7,1)
(0,3,0)	MPI_DIMS_CREATE(6, 3, dims)	(2,3,1)
(0,3,0)	MPI_DIMS_CREATE(7, 3, dims)	erroneous call

# 8.5.3 Graph Constructor

```
MPI_GRAPH_CREATE(comm_old, nnodes, index, edges, reorder, comm_graph)
```

```
IN
          comm_old
                                          input communicator (handle)
IN
           nnodes
                                          number of nodes in graph (integer)
IN
           index
                                          array of integers describing node degrees (see below)
                                          array of integers describing graph edges (see below)
IN
          edges
                                          ranking may be reordered (true) or not (false)
IN
           reorder
                                          (logical)
OUT
                                          communicator with graph topology added (handle)
          comm_graph
```

# C binding

### Fortran 2008 binding

# Fortran binding

```
MPI_GRAPH_CREATE(COMM_OLD, NNODES, INDEX, EDGES, REORDER, COMM_GRAPH, IERROR)

INTEGER COMM_OLD, NNODES, INDEX(*), EDGES(*), COMM_GRAPH, IERROR LOGICAL REORDER
```

MPI\_GRAPH\_CREATE returns a handle to a new communicator to which the graph topology information is attached. If reorder = false then the rank of each process in the new group is identical to its rank in the old group. Otherwise, the function may reorder the

processes. If the size, nnodes, of the graph is smaller than the size of the group of comm\_old, then some processes are returned MPI\_COMM\_NULL, in analogy to MPI\_CART\_CREATE and MPI\_COMM\_SPLIT. If the graph is empty, i.e., nnodes == 0, then MPI\_COMM\_NULL is returned in all processes. The call is erroneous if it specifies a graph that is larger than the group size of the input communicator.

The three parameters nnodes, index and edges define the graph structure. nnodes is the number of nodes of the graph. The nodes are numbered from 0 to nnodes-1. The i-th entry of array index stores the total number of neighbors of the first i graph nodes. The lists of neighbors of nodes 0, 1, ..., nnodes-1 are stored in consecutive locations in array edges. The array edges is a flattened representation of the edge lists. The total number of entries in index is nnodes and the total number of entries in edges is equal to the number of graph edges.

The definitions of the arguments nnodes, index, and edges are illustrated with the following simple example.

**Example 8.2** Assume there are four processes 0, 1, 2, 3 with the following adjacency matrix:

process	neighbors
0	1, 3
1	0
2	3
3	0, 2

Then, the input arguments are:

$$nnodes = 4$$
  
 $index = 2, 3, 4, 6$   
 $edges = 1, 3, 0, 3, 0, 2$ 

Thus, in C, index[0] is the degree of node zero, and index[i] - index[i-1] is the degree of node i, i=1, ..., nnodes-1; the list of neighbors of node zero is stored in edges[j], for  $0 \le j \le index[0] - 1$  and the list of neighbors of node i, i > 0, is stored in edges[j], index[i-1]  $\le j \le index[i] - 1$ .

In Fortran, index(1) is the degree of node zero, and index(i+1) - index(i) is the degree of node i, i=1, ..., nnodes-1; the list of neighbors of node zero is stored in edges(j), for  $1 \le j \le index(1)$  and the list of neighbors of node i, i > 0, is stored in edges(j), index(i)+1  $\le j \le index(i+1)$ .

A single process is allowed to be defined multiple times in the list of neighbors of a process (i.e., there may be multiple edges between two processes). A process is also allowed to be a neighbor to itself (i.e., a self loop in the graph). The adjacency matrix is allowed to be non-symmetric.

Advice to users. Performance implications of using multiple edges or a non-symmetric adjacency matrix are not defined. The definition of a node-neighbor edge does not imply a direction of the communication. (End of advice to users.)

Advice to implementors. The following topology information is likely to be stored with a communicator:

- 1 2 5 6

- 9 10 11
- 12 13 14

- 16 17 18
- 19 20

21

22

23

24

25

26

27

28

29

30

- 31 32 33 34 35 36

37

38 39

- 41 42 43
- 44 45 46
- 47

- Type of topology (Cartesian/graph),
- For a Cartesian topology:
  - 1. ndims (number of dimensions),
  - 2. dims (numbers of processes per coordinate direction),
  - 3. periods (periodicity information),
  - 4. own\_position (own position in grid, could also be computed from rank and dims)
- For a graph topology:
  - 1. index.
  - 2. edges.

which are the vectors defining the graph structure.

For a graph structure the number of nodes is equal to the number of processes in the group. Therefore, the number of nodes does not have to be stored explicitly. An additional zero entry at the start of array index simplifies access to the topology information. (End of advice to implementors.)

#### Distributed Graph Constructor 8.5.4

MPI\_GRAPH\_CREATE requires that each process passes the full (global) communication graph to the call. This limits the scalability of this constructor. With the distributed graph interface, the communication graph is specified in a fully distributed fashion. Each process specifies only the part of the communication graph of which it is aware. Typically, this could be the set of processes from which the process will eventually receive or get data, or the set of processes to which the process will send or put data, or some combination of such edges. Two different interfaces can be used to create a distributed graph topology. MPI\_DIST\_GRAPH\_CREATE\_ADJACENT creates a distributed graph communicator with each process specifying each of its incoming and outgoing (adjacent) edges in the logical communication graph and thus requires minimal communication during creation.

MPI\_DIST\_GRAPH\_CREATE provides full flexibility such that any process can indicate that communication will occur between any pair of processes in the graph.

To provide better possibilities for optimization by the MPI library, the distributed graph constructors permit weighted communication edges and take an info argument that can further influence process reordering or other optimizations performed by the MPI library. For example, hints can be provided on how edge weights are to be interpreted, the quality of the reordering, and/or the time permitted for the MPI library to process the graph.

MPI_DIST		T(comm_old, indegree, sources, sourceweights, estweights, info, reorder, comm_dist_graph)	1 2			
IN	comm_old	input communicator (handle)	3			
IN	indegree	size of sources and sourceweights arrays (non-negative	4 5			
		integer)	6			
IN	sources	ranks of processes for which the calling process is a destination (array of non-negative integers)	7 8			
IN	sourceweights	weights of the edges into the calling process (array of non-negative integers)	9 10 11			
IN	outdegree	size of destinations and destweights arrays (non-negative integer)	12 13			
IN	destinations	ranks of processes for which the calling process is a source (array of non-negative integers)	14 15			
IN	destweights	weights of the edges out of the calling process (array of non-negative integers)	16 17 18			
IN	info	hints on optimization and interpretation of weights (handle)	19 20			
IN	reorder	the ranks may be reordered (true) or not (false) (logical)	21 22			
OUT	comm_dist_graph	communicator with distributed graph topology (handle)	23 24 25			
C binding int MPI_Dist_graph_create_adjacent(MPI_Comm comm_old, int indegree,						
Fortran 2008 binding  MPI_Dist_graph_create_adjacent(comm_old, indegree, sources, sourceweights, outdegree, destinations, destweights, info, reorder, comm_dist_graph, ierror)  TYPE(MPI_Comm), INTENT(IN) :: comm_old  INTEGER, INTENT(IN) :: indegree, sources(indegree), sourceweights(*), outdegree, destinations(outdegree), destweights(*)  TYPE(MPI_Info), INTENT(IN) :: info  LOGICAL, INTENT(IN) :: reorder  TYPE(MPI_Comm), INTENT(OUT) :: comm_dist_graph  INTEGER, OPTIONAL, INTENT(OUT) :: ierror						
Fortran binding MPI_DIST_GRAPH_CREATE_ADJACENT(COMM_OLD, INDEGREE, SOURCES, SOURCEWEIGHTS, OUTDEGREE, DESTINATIONS, DESTWEIGHTS, INFO, REORDER, COMM_DIST_GRAPH, IERROR)						

 $\frac{45}{46}$ 

#-error

Done

PR439

in

LOGICAL REORDER

MPI\_DIST\_GRAPH\_CREATE\_ADJACENT returns a handle to a new communicator to which the distributed graph topology information is attached. Each process passes all information about its incoming and outgoing edges in the virtual distributed graph topology. The calling processes must ensure that each edge of the graph is described in the source and in the destination process with the same weights. If there are multiple edges for a given (source,dest) pair, then the sequence of the weights of these edges does not matter. The complete communication topology is the combination of all edges shown in the sources arrays of all processes in comm\_old, which must be identical to the combination of all edges shown in the destinations arrays. Source and destination ranks must be process ranks of comm\_old. This allows a fully distributed specification of the communication graph. Isolated processes (i.e., processes with no outgoing or incoming edges, that is, processes that have specified indegree and outdegree as zero and thus do not occur as source or destination rank in the graph specification) are allowed.

The call creates a new communicator <code>comm\_dist\_graph</code> of distributed graph topology type to which topology information has been attached. The number of processes in <code>comm\_dist\_graph</code> is identical to the number of processes in <code>comm\_old</code>. The call to <code>MPI\_DIST\_GRAPH\_CREATE\_ADJACENT</code> is collective.

Weights are specified as non-negative integers and can be used to influence the process remapping strategy and other internal MPI optimizations. For instance, approximate count arguments of later communication calls along specific edges could be used as their edge weights. Multiplicity of edges can likewise indicate more intense communication between pairs of processes. However, the exact meaning of edge weights is not specified by the MPI standard and is left to the implementation. In C or Fortran, an application can supply the special value MPI\_UNWEIGHTED for the weight array to indicate that all edges have the same (effectively no) weight. It is erroneous to supply MPI\_UNWEIGHTED for some but not all processes of comm\_old. If the graph is weighted but indegree or outdegree is zero, then MPI\_WEIGHTS\_EMPTY or any arbitrary array may be passed to sourceweights or destweights respectively. Note that MPI\_UNWEIGHTED and MPI\_WEIGHTS\_EMPTY are not special weight values; rather they are special values for the total array argument. In Fortran, MPI\_UNWEIGHTED and MPI\_WEIGHTS\_EMPTY are objects like MPI\_BOTTOM (not usable for initialization or assignment). See Section 2.5.4.

Advice to users. In the case of an empty weights array argument passed while constructing a weighted graph, one should not pass NULL because the value of MPI\_UNWEIGHTED may be equal to NULL. The value of this argument would then be indistinguishable from MPI\_UNWEIGHTED to the implementation. In this case MPI\_WEIGHTS\_EMPTY should be used instead. (End of advice to users.)

Advice to implementors. It is recommended that MPI\_UNWEIGHTED not be implemented as NULL. (End of advice to implementors.)

Rationale. To ensure backward compatibility, MPI\_UNWEIGHTED may still be implemented as NULL. See Annex B.4. (End of rationale.)

\constmain{MPI\\_UNWEIGHTED}

\constmain{MPI\\_WEIGHTS\\_EMPTY}

\code{NULL}

The meaning of the info and reorder arguments is defined in the description of the following routine. MPI\_DIST\_GRAPH\_CREATE(comm\_old, n, sources, degrees, destinations, weights, info, reorder, comm\_dist\_graph) IN comm\_old input communicator (handle) IN number of source nodes for which this process n specifies edges (non-negative integer) IN array containing the n source nodes for which this sources process specifies edges (array of non-negative 12 integers) 13 14IN degrees array specifying the number of destinations for each 15 source node in the source node array (array of 16 non-negative integers) IN destinations destination nodes for the source nodes in the source node array (array of non-negative integers) 19 IN weights weights for source to destination edges (array of 20 non-negative integers) 21 info hints on optimization and interpretation of weights 22 IN 23 (handle) 24 IN reorder the ranks may be reordered (true) or not (false) (logical) 26 OUT comm\_dist\_graph communicator with distributed graph topology 27 added (handle) 28 29 C binding 30 int MPI\_Dist\_graph\_create(MPI\_Comm comm\_old, int n, const int sources[], 31 const int degrees[], const int destinations[], const int weights[], MPI\_Info info, int reorder, MPI\_Comm \*comm\_dist\_graph) 34 35 Fortran 2008 binding MPI\_Dist\_graph\_create(comm\_old, n, sources, degrees, destinations, weights, 37 info, reorder, comm\_dist\_graph, ierror) TYPE(MPI\_Comm), INTENT(IN) :: comm\_old INTEGER, INTENT(IN) :: n, sources(n), degrees(n), destinations(\*), weights(\*) TYPE(MPI\_Info), INTENT(IN) :: info 42 LOGICAL, INTENT(IN) :: reorder 43 TYPE(MPI\_Comm), INTENT(OUT) :: comm\_dist\_graph 44 INTEGER, OPTIONAL, INTENT(OUT) :: ierror 45 Fortran binding 46 MPI\_DIST\_GRAPH\_CREATE(COMM\_OLD, N, SOURCES, DEGREES, DESTINATIONS, WEIGHTS,

INFO, REORDER, COMM\_DIST\_GRAPH, IERROR)

MPI\_DIST\_GRAPH\_CREATE returns a handle to a new communicator to which the distributed graph topology information is attached. Concretely, each process calls the constructor with a set of directed (source, destination) communication edges as described below. Every process passes an array of n source nodes in the sources array. For each source node, a non-negative number of destination nodes is specified in the degrees array. The destination nodes are stored in the corresponding consecutive segment of the destinations array. More precisely, if the i-th node in sources is s, this specifies degrees[i] edges (s,d) with d of the j-th such edge stored in destinations[degrees[0]+...+degrees[i-1]+j]. The weight of this edge is stored in weights[degrees[0]+...+degrees[i-1]+i]. Both the sources and the destinations arrays may contain the same node more than once, and the order in which nodes are listed as destinations or sources is not significant. Similarly, different processes may specify edges with the same source and destination nodes. Source and destination nodes must be process ranks of comm\_old. Different processes may specify different numbers of source and destination nodes, as well as different source to destination edges. This allows a fully distributed specification of the communication graph. Isolated processes (i.e., processes with no outgoing or incoming edges, that is, processes that do not occur as source or destination node in the graph specification) are allowed.

The call creates a new communicator comm\_dist\_graph of distributed graph topology type to which topology information has been attached. The number of processes in comm\_dist\_graph is identical to the number of processes in comm\_old. The call to MPI\_DIST\_GRAPH\_CREATE is collective.

If reorder = false, all processes will have the same rank in comm\_dist\_graph as in comm\_old. If reorder = true then the MPI library is free to remap to other processes (of comm\_old) in order to improve communication on the edges of the communication graph. The weight associated with each edge is a hint to the MPI library about the amount or intensity of communication on that edge, and may be used to compute a "best" reordering.

Weights are specified as non-negative integers and can be used to influence the process remapping strategy and other internal MPI optimizations. For instance, approximate count arguments of later communication calls along specific edges could be used as their edge weights. Multiplicity of edges can likewise indicate more intense communication between pairs of processes. However, the exact meaning of edge weights is not specified by the MPI standard and is left to the implementation. In C or Fortran, an application can supply the special value MPI\_UNWEIGHTED for the weight array to indicate that all edges have the same (effectively no) weight. It is erroneous to supply MPI\_UNWEIGHTED for some but not all processes of comm\_old. If the graph is weighted but n = 0, then MPI\_WEIGHTS\_EMPTY or any arbitrary array may be passed to weights. Note that MPI\_UNWEIGHTED and MPI\_WEIGHTS\_EMPTY are not special weight values; rather they are special values for the total array argument. In Fortran, MPI\_UNWEIGHTED and MPI\_WEIGHTS\_EMPTY are objects like MPI\_BOTTOM (not usable for initialization or assignment). See Section 2.5.4.

Advice to users. In the case of an empty weights array argument passed while constructing a weighted graph, one should not pass NULL because the value of MPI\_UNWEIGHTED may be equal to NULL. The value of this argument would then be indistinguishable from MPI\_UNWEIGHTED to the implementation.

MPI\_WEIGHTS\_EMPTY should be used instead. (End of advice to users.)

PR439

Advice to implementors. It is recommended that MPI\_UNWEIGHTED not be implemented as NULL. (End of advice to implementors.)

Rationale. To ensure backward compatibility, MPI\_UNWEIGHTED may still be impleword as NULL. See Annex B.4. (End of rationale.)

The meaning of the weights argument can be influenced by the info argument. Info arguments can be used to guide the mapping; possible options include minimizing the maximum number of edges between processes on different SMP nodes, or minimizing the sum of all such edges. An MPI implementation is not obliged to follow specific hints, and it is valid for an MPI implementation not to do any reordering. An MPI implementation may specify more info key-value pairs. All processes must specify the same set of key-value info pairs.

Advice to implementors. MPI implementations must document any additionally supported key-value info pairs. MPI\_INFO\_NULL is always valid, and may indicate the default creation of the distributed graph topology to the MPI library.

An implementation does not explicitly need to construct the topology from its distributed parts. However, all processes can construct the full topology from the distributed specification and use this in a call to MPI\_GRAPH\_CREATE to create the topology. This may serve as a reference implementation of the functionality, and may be acceptable for small communicators. However, a scalable high-quality implementation would save the topology graph in a distributed way. (*End of advice to implementors*.)

**Example 8.3** As for Example 8.2, assume there are four processes 0, 1, 2, 3 with the following adjacency matrix and unit edge weights:

т.		
	process	neighbors
	0	1, 3
	1	0
	2	3
	3	0, 2

With MPI\_DIST\_GRAPH\_CREATE, this graph could be constructed in many different ways. One way would be that each process specifies its outgoing edges. The arguments per process would be:

process	n	sources	degrees	destinations	weights
0	1	0	2	1,3	1,1
1	1	1	1	0	1
2	1	2	1	3	1
3	1	3	2	0,2	1,1

Another way would be to pass the whole graph on process 0, which could be done with the following arguments per process:

process	n	sources	degrees	destinations	weights
0	4	0,1,2,3	2,1,1,2	1,3,0,3,0,2	1,1,1,1,1,1
1	0	-	_	-	-
2	0	_	-	-	-
3	0	-	_	-	

2

3

4

5 6 7

13

14

15

16

17

In both cases above, the application could supply MPI\_UNWEIGHTED instead of explicitly providing identical weights.

MPI\_DIST\_GRAPH\_CREATE\_ADJACENT could be used to specify this graph using the following arguments:

process	indegree	sources	sourceweights	outdegree	destinations	destweights
0	2	1,3	1,1	2	1,3	1,1
1	1	0	1	1	0	1
2	1	3	1	1	3	1
3	2	0,2	1,1	2	0,2	1,1

**Example 8.4** A two-dimensional PxQ torus where all processes communicate along the dimensions and along the diagonal edges. This cannot be modeled with Cartesian topologies, but can easily be captured with MPI\_DIST\_GRAPH\_CREATE as shown in the following code. In this example, the communication along the dimensions is twice as heavy as the communication along the diagonals:

```
18
     /*
19
     Input:
                 dimensions P, Q
20
     Condition: number of processes equal to P*Q; otherwise only
21
                ranks smaller than P*Q participate
22
     */
23
     int rank, x, y;
^{24}
     int sources[1], degrees[1];
     int destinations[8], weights[8];
26
     MPI_Comm comm_dist_graph;
27
28
     MPI_Comm_rank(MPI_COMM_WORLD, &rank);
29
30
     /* get x and y dimension */
31
     y=rank/P; x=rank%P;
32
33
     /* get my communication partners along x dimension */
34
     destinations[0] = P*y+(x+1)%P; weights[0] = 2;
     destinations[1] = P*y+(P+x-1)%P; weights[1] = 2;
35
36
37
     /* get my communication partners along y dimension */
38
     destinations[2] = P*((y+1)\%Q)+x; weights[2] = 2;
39
     destinations[3] = P*((Q+y-1)%Q)+x; weights[3] = 2;
40
41
     /* get my communication partners along diagonals */
42
     destinations[4] = P*((y+1)\%Q)+(x+1)\%P; weights[4] = 1;
43
     destinations[5] = P*((Q+y-1)%Q)+(x+1)%P; weights[5] = 1;
     destinations[6] = P*((y+1)\%Q)+(P+x-1)\%P; weights[6] = 1;
44
45
     destinations[7] = P*((Q+y-1)%Q)+(P+x-1)%P; weights[7] = 1;
^{46}
47
     sources[0] = rank;
48
     degrees[0] = 8;
```

13 14

15

16

18

19

20

21 22

23

24

26

27

28

30

34

35

36 37 38

42 43

44

45 46

MPI\_Dist\_graph\_create(MPI\_COMM\_WORLD, 1, sources, degrees, destinations, weights, MPI\_INFO\_NULL, 1, &comm\_dist\_graph);

#### 8.5.5 Topology Inquiry Functions

If a topology has been defined with one of the above functions, then the topology information can be looked up using inquiry functions. They all are local calls.

# MPI\_TOPO\_TEST(comm, status)

IN comm communicator (handle) OUT topology type of communicator comm (state) status

# C binding

int MPI\_Topo\_test(MPI\_Comm comm, int \*status)

# Fortran 2008 binding

MPI\_Topo\_test(comm, status, ierror) TYPE(MPI\_Comm), INTENT(IN) :: comm INTEGER, INTENT(OUT) :: status INTEGER, OPTIONAL, INTENT(OUT) :: ierror

# Fortran binding

MPI\_TOPO\_TEST(COMM, STATUS, IERROR) INTEGER COMM, STATUS, IERROR

The function MPI\_TOPO\_TEST returns the type of topology that is assigned to a communicator.

The output value status is one of the following:

# \constmainitem{....}

MPI\_GRAPH graph topology MPI\_CART Cartesian topology distributed graph topology MPI\_DIST\_GRAPH MPI\_UNDEFINED no topology

There seems to be no main index entry for MPI\_UNDEFINED

# MPI\_GRAPHDIMS\_GET(comm, nnodes, nedges)

IN	comm	communicator for group with graph structure (handle)
OUT	nnodes	number of nodes in graph (same as number of processes in the group) (integer)
OUT	nedges	number of edges in graph (integer)

### C binding

int MPI\_Graphdims\_get(MPI\_Comm comm, int \*nnodes, int \*nedges)

#### Fortran 2008 binding

MPI\_Graphdims\_get(comm, nnodes, nedges, ierror)

29 #-error #-update 3 31



#-314

#-error

Done

PR439

48

lin

```
1
          TYPE(MPI_Comm), INTENT(IN) :: comm
2
          INTEGER, INTENT(OUT) :: nnodes, nedges
3
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
5
     MPI_GRAPHDIMS_GET(COMM, NNODES, NEDGES, IERROR)
6
          INTEGER COMM, NNODES, NEDGES, IERROR
         The functions MPI_GRAPHDIMS_GET and MPI_GRAPH_GET retrieve the graph-topol-
     ogy information that is associated with the communicator. No linebreak
10
          The information provided by MPI_GRAPHDIMS_GET can be used to dimension the
11
     vectors index and edges correctly for the following call to MPI_GRAPH_GET.
12
     \mpiarg{index} and \mpiarg{edges}
     (instead of \mpicode)
13
     MPI_GRAPH_GET(comm, maxindex, maxedges, index, edges)
14
15
                                             communicator with graph structure (handle)
16
       IN
                 maxindex
                                             length of vector index in the calling program (integer)
17
       IN
                                             length of vector edges in the calling program (integer)
                 maxedges
18
19
       OUT
                 index
                                             array of integers containing the graph structure (for
20
                                             details see the definition of MPI_GRAPH_CREATE)
21
       OUT
                 edges
                                             array of integers containing the graph structure
22
23
     C binding
24
     int MPI_Graph_get(MPI_Comm comm, int maxindex, int maxedges, int index[],
25
                    int edges[])
26
27
     Fortran 2008 binding
28
     MPI_Graph_get(comm, maxindex, maxedges, index, edges, ierror)
29
          TYPE(MPI_Comm), INTENT(IN) :: comm
30
          INTEGER, INTENT(IN) :: maxindex, maxedges
31
          INTEGER, INTENT(OUT) :: index(maxindex), edges(maxedges)
32
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
33
     Fortran binding
34
     MPI_GRAPH_GET(COMM, MAXINDEX, MAXEDGES, INDEX, EDGES, IERROR)
35
          INTEGER COMM, MAXINDEX, MAXEDGES, INDEX(*), EDGES(*), IERROR
36
37
38
     MPI_CARTDIM_GET(comm, ndims)
39
40
       IN
                                             communicator with Cartesian structure (handle)
                 comm
41
       OUT
                 ndims
                                             number of dimensions of the Cartesian structure
42
                                             (integer)
43
44
     C binding
45
     int MPI_Cartdim_get(MPI_Comm comm, int *ndims)
46
47
     Fortran 2008 binding
```

INTEGER COMM, NDIMS, IERROR

```
MPI_Cartdim_get(comm, ndims, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(OUT) :: ndims
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI_CARTDIM_GET(COMM, NDIMS, IERROR)
```

The functions MPI\_CARTDIM\_GET and MPI\_CART\_GET return the Cartesian topology information that is associated with the communicator. If comm is associated with a zero-dimensional Cartesian topology, MPI\_CARTDIM\_GET returns ndims = 0 and MPI\_CART\_GET will keep all output arguments unchanged.

# MPI\_CART\_GET(comm, maxdims, dims, periods, coords)

IN	comm	communicator with Cartesian structure (handle)
IN	maxdims	length of vectors dims, periods, and coords in the calling program (integer)
OUT	dims	number of processes for each Cartesian dimension (array of integers)
OUT	periods	periodicity (true/false) for each Cartesian dimension (array of logicals)
OUT	coords	coordinates of calling process in Cartesian structure (array of integers)

# C binding

# Fortran 2008 binding

```
MPI_Cart_get(comm, maxdims, dims, periods, coords, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: maxdims
    INTEGER, INTENT(OUT) :: dims(maxdims), coords(maxdims)
    LOGICAL, INTENT(OUT) :: periods(maxdims)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

```
MPI_CART_GET(COMM, MAXDIMS, DIMS, PERIODS, COORDS, IERROR)
    INTEGER COMM, MAXDIMS, DIMS(*), COORDS(*), IERROR
    LOGICAL PERIODS(*)
```

#-314

communicator with Cartesian structure (handle)

coordinates of a process

integer array (of size ndims) specifying the Cartesian

IN

IN

2

3

#-311

#-error

#-update3

Done

PR439

41 42

43

44

45

46

47

C binding

Fortran 2008 binding

MPI\_CART\_RANK(comm, coords, rank)

comm

coords

```
6
                  OUT
                                         rank
                                                                                                            rank of specified process (integer)
              C binding
              int MPI_Cart_rank(MPI_Comm comm, const int coords[], int *rank)
10
              Fortran 2008 binding
11
             MPI_Cart_rank(comm, coords, rank, ierror)
12
                        TYPE(MPI_Comm), INTENT(IN) :: comm
13
                        INTEGER, INTENT(IN) :: coords(*)
14
                        INTEGER, INTENT(OUT) :: rank
15
                        INTEGER, OPTIONAL, INTENT(OUT) :: ierror
16
17
              Fortran binding
18
             MPI_CART_RANK(COMM, COORDS, RANK, IERROR)
19
                        INTEGER COMM, COORDS(*), RANK, IERROR
20
                       For a communicator with an associated Cartesian topology, the function
21
              MPI_CART_RANK translates the logical process coordinates to process ranks as they are
22
            used by the point-to-point routines. No linebreak
23
24
                       For dimension i with periods(i) = true, if the coordinate, coords(i), is out of range, that
             is, coords(i) < 0 or coords(i) \ge dims(i), it is shifted back to the interval \big| \big| \mbox{\lambda \cond} \cond \lambda \lamb
25
              0 \leq coords(i) < dims(i) automatically. Out-of-range coordinates are erroneous for non-
26
              periodic dimensions.
27
                        If comm is associated with a zero-dimensional Cartesian topology, coords is not signif-
28
              icant and 0 is returned in rank.
29
30
31
              MPI_CART_COORDS(comm, rank, maxdims, coords)
32
                  IN
                                                                                                             communicator with Cartesian structure (handle)
33
                                         comm
34
                  IN
                                          rank
                                                                                                            rank of a process within group of comm (integer)
35
                  IN
                                          maxdims
                                                                                                             length of vector coords in the calling program
36
                                                                                                             (integer)
37
                  OUT
                                                                                                             integer array (of size maxdims) containing the
38
                                          coords
                                                                                                             Cartesian coordinates of specified process (array of
39
                                                                                                             integers)
```

int MPI\_Cart\_coords(MPI\_Comm comm, int rank, int maxdims, int coords[])

MPI\_Cart\_coords(comm, rank, maxdims, coords, ierror)

TYPE(MPI\_Comm), INTENT(IN) :: comm

INTEGER, INTENT(IN) :: rank, maxdims

```
INTEGER, INTENT(OUT) :: coords(maxdims)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_CART_COORDS(COMM, RANK, MAXDIMS, COORDS, IERROR)
    INTEGER COMM, RANK, MAXDIMS, COORDS(*), IERROR
    The inverse mapping, rank-to-coordinates translation is provided by
                                                                                          #-error
MPI_CART_COORDS. No linebreak
                                                                                           #-353
    If comm is associated with a zero-dimensional Cartesian topology,
                                                                                           PR332
coords will be unchanged.
                                                                                           Done
                                                                                           in
                                                                                           PR439
                                                                                        12
MPI_GRAPH_NEIGHBORS_COUNT(comm, rank, nneighbors)
                                                                                        13
                                                                                        14
  IN
                                       communicator with graph topology (handle)
           comm
                                                                                        15
  IN
                                       rank of process in group of comm (integer)
           rank
                                                                                        16
  OUT
           nneighbors
                                       number of neighbors of specified process (integer)
C binding
                                                                                        19
int MPI_Graph_neighbors_count(MPI_Comm comm, int rank, int *nneighbors)
                                                                                        20
                                                                                        21
Fortran 2008 binding
                                                                                        22
MPI_Graph_neighbors_count(comm, rank, nneighbors, ierror)
                                                                                        23
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                        24
    INTEGER, INTENT(IN) :: rank
    INTEGER, INTENT(OUT) :: nneighbors
                                                                                        26
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                        27
                                                                                        28
Fortran binding
                                                                                        29
MPI_GRAPH_NEIGHBORS_COUNT(COMM, RANK, NNEIGHBORS, IERROR)
    INTEGER COMM, RANK, NNEIGHBORS, IERROR
                                                                                        30
                                                                                        33
MPI_GRAPH_NEIGHBORS(comm, rank, maxneighbors, neighbors)
                                                                                        34
  1M
                                       communicator with graph topology (handle)
           comm
                                                                                        35
  IN
           rank
                                       rank of process in group of comm (integer)
                                                                                        36
                                                                                        37
  IN
           maxneighbors
                                       size of array neighbors (integer)
  OUT
           neighbors
                                       ranks of processes that are neighbors to specified
                                       process (array of integers)
C binding
                                                                                        42
int MPI_Graph_neighbors(MPI_Comm comm, int rank, int maxneighbors,
                                                                                        43
              int neighbors[])
                                                                                        44
                                                                                        45
Fortran 2008 binding
                                                                                        46
MPI_Graph_neighbors(comm, rank, maxneighbors, neighbors, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
6
7
8
9
10
11
```

14

19

20

21

22

23

24

31

32

33

34

35 36

37 38 39

41

42

43 |44

45

46

47

1

2

3

5

```
15
16
17
#-error | 18
```

```
#-353
(PR332)
Done
in
PR439
```

in PR439

Done

```
INTEGER, INTENT(IN) :: rank, maxneighbors
INTEGER, INTENT(OUT) :: neighbors(maxneighbors)
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

MPI\_GRAPH\_NEIGHBORS(COMM, RANK, MAXNEIGHBORS, NEIGHBORS, IERROR)
INTEGER COMM, RANK, MAXNEIGHBORS, NEIGHBORS(\*), IERROR

MPI\_GRAPH\_NEIGHBORS\_COUNT and MPI\_GRAPH\_NEIGHBORS provide adjacency information for a graph topology. The returned count and array of neighbors for the queried rank will both include *all* neighbors and reflect the same edge ordering as was specified by the original call to MPI\_GRAPH\_CREATE. Specifically, MPI\_GRAPH\_NEIGHBORS\_COUNT and MPI\_GRAPH\_NEIGHBORS will return values based on the original index and edges array passed to MPI\_GRAPH\_CREATE (for the purpose of this example, we assume that index[-1] is zero):

- The number of neighbors (nneighbors) returned from MPI\_GRAPH\_NEIGHBORS\_COUNT will be (index[rank] - index[rank-1]).
- The neighbors array returned from MPI\_GRAPH\_NEIGHBORS will be edges[index[rank-1]] through edges[index[rank]-1].

**Example 8.5** Assume there are four processes 0, 1, 2, 3 with the following adjacency matrix (note that some neighbors are listed multiple times):

process	neighbors
0	1, 1, 3
1	0, 0
2	3
3	0, 2, 2

Thus, the input arguments to MPI\_GRAPH\_CREATE are:

$$\begin{array}{ll} \text{nnodes} = & 4 \\ \text{index} = & 3, 5, 6, 9 \\ \text{edges} = & 1, 1, 3, 0, 0, 3, 0, 2, 2 \end{array}$$

Therefore, calling MPI\_GRAPH\_NEIGHBORS\_COUNT and MPI\_GRAPH\_NEIGHBORS for each of the 4 processes will return:

Input rank	Count	Neighbors
0	3	1, 1, 3
1	2	0, 0
2	1	3
3	3	0, 2, 2

I would prefere to use this "Lightgray lines on top and bottom, with vertical ticks:" https://github.com/mpi-forum/mpi-issues/ files/4697966/mpi40-report-extopbottom.pdf (page 341[printed], 381[pdf])

#-error #-343 #-285 #-PR417 Done

PR417

**Example 8.6** Suppose that comm is a communicator with a shuffle-exchange topology. The group has  $2^n$  members. Each process is labeled by  $a_1, \ldots, a_n$  with  $a_i \in \{0, 1\}$ , and has three neighbors: exchange  $(a_1, \ldots, a_n) = a_1, \ldots, a_{n-1}, \bar{a}_n$  ( $\bar{a} = 1 - a$ ), shuffle  $(a_1, \ldots, a_n) = a_2, \ldots, a_n, a_1$ , and unshuffle  $(a_1, \ldots, a_n) = a_n, a_1, \ldots, a_{n-1}$ . The graph adjacency list is illustrated below for n = 3.

#### **Unofficial Draft for Comment Only**

#-error #-343 #-285

node		exchange	shuffle	unshuffle
		neighbors(1)	neighbors(2)	neighbors(3)
0	(000)	1	0	0
1	(001)	0	2	4
2	(010)	3	4	1
3	(011)	2	6	5
4	(100)	5	1	2
5	(101)	4	3	6
6	(110)	7	5	3
7	(111)	6	7	7

Suppose that the communicator comm has this topology associated with it. The following code fragment cycles through the three types of neighbors and performs an appropriate permutation for each.

MPI\_DIST\_GRAPH\_NEIGHBORS\_COUNT and MPI\_DIST\_GRAPH\_NEIGHBORS provide adjacency information for a distributed graph topology.

# MPI\_DIST\_GRAPH\_NEIGHBORS\_COUNT(comm, indegree, outdegree, weighted)

IN	comm	communicator with distributed graph topology (handle)
OUT	indegree	number of edges into this process (non-negative integer)
OUT	outdegree	number of edges out of this process (non-negative integer)
OUT	weighted	false if MPI_UNWEIGHTED was supplied during creation, true otherwise (logical)

# C binding

#### Fortran 2008 binding

```
1
     MPI_Dist_graph_neighbors_count(comm, indegree, outdegree, weighted, ierror)
2
          TYPE(MPI_Comm), INTENT(IN) :: comm
3
          INTEGER, INTENT(OUT) :: indegree, outdegree
          LOGICAL, INTENT(OUT) :: weighted
5
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
     Fortran binding
     MPI_DIST_GRAPH_NEIGHBORS_COUNT(COMM, INDEGREE, OUTDEGREE, WEIGHTED, IERROR)
          INTEGER COMM, INDEGREE, OUTDEGREE, IERROR
9
          LOGICAL WEIGHTED
10
11
12
     MPI_DIST_GRAPH_NEIGHBORS(comm, maxindegree, sources, sourceweights,
13
                    maxoutdegree, destinations, destweights)
14
15
       IN
                 comm
                                             communicator with distributed graph topology
16
                                             (handle)
17
       IN
                                             size of sources and sourceweights arrays
                 maxindegree
18
                                             (non-negative integer)
19
                                             processes for which the calling process is a
       OUT
                 sources
20
                                             destination (array of non-negative integers)
21
       OUT
                                             weights of the edges into the calling process (array of
22
                 sourceweights
23
                                             non-negative integers)
24
       IN
                 maxoutdegree
                                             size of destinations and destweights arrays
                                             (non-negative integer)
26
       OUT
                 destinations
                                             processes for which the calling process is a source
27
                                             (array of non-negative integers)
28
                                             weights of the edges out of the calling process (array
       OUT
                 destweights
29
                                             of non-negative integers)
30
31
32
     C binding
33
     int MPI_Dist_graph_neighbors(MPI_Comm comm, int maxindegree, int sources[],
34
                    int sourceweights[], int maxoutdegree, int destinations[],
35
                     int destweights[])
36
     Fortran 2008 binding
37
     MPI_Dist_graph_neighbors(comm, maxindegree, sources, sourceweights,
38
                    maxoutdegree, destinations, destweights, ierror)
39
          TYPE(MPI_Comm), INTENT(IN) :: comm
40
          INTEGER, INTENT(IN) :: maxindegree, maxoutdegree
          INTEGER, INTENT(OUT) :: sources(maxindegree),
42
                     destinations (maxoutdegree)
43
          INTEGER :: sourceweights(*), destweights(*)
44
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
46
     Fortran binding
47
     MPI_DIST_GRAPH_NEIGHBORS(COMM, MAXINDEGREE, SOURCES, SOURCEWEIGHTS,
                    MAXOUTDEGREE, DESTINATIONS, DESTWEIGHTS, IERROR)
```

INTEGER COMM, MAXINDEGREE, SOURCES(\*), SOURCEWEIGHTS(\*), MAXOUTDEGREE, DESTINATIONS(\*), DESTWEIGHTS(\*), IERROR

These calls are local. The number of edges into and out of the process returned by MPI\_DIST\_GRAPH\_NEIGHBORS\_COUNT are the total number of such edges given in the call to MPI\_DIST\_GRAPH\_CREATE\_ADJACENT or MPI\_DIST\_GRAPH\_CREATE (potentially by processes other than the calling process in the case of MPI\_DIST\_GRAPH\_CREATE). Multiply-defined edges are all counted and returned by MPI\_DIST\_GRAPH\_NEIGHBORS in some order. If MPI\_UNWEIGHTED is supplied for sourceweights or destweights or both, or if MPI\_UNWEIGHTED was supplied during the construction of the graph then no weight information is returned in that array or those arrays. If the communicator was created with MPI\_DIST\_GRAPH\_CREATE\_ADJACENT then for each rank in comm, the order of the values in sources and destinations is identical to the input that was used by the process with the same rank in comm old in the creation call. If the communicator was created with MPI\_DIST\_GRAPH\_CREATE then the only requirement on the order of values in sources and destinations is that two calls to the routine with same input argument comm will return the same sequence of edges. If maxindegree or maxoutdegree is smaller than the numbers returned by MPI\_DIST\_GRAPH\_NEIGHBORS\_COUNT, then only the first part of the full list is returned.

Advice to implementors. Since the query calls are defined to be local, each process needs to store the list of its neighbors with incoming and outgoing edges. Communication is required at the collective MPI\_DIST\_GRAPH\_CREATE call in order to compute the neighbor lists for each process from the distributed graph specification. (End of advice to implementors.)

#### 8.5.6 Cartesian Shift Coordinates

If the process topology is a Cartesian structure, an MPI\_SENDRECV operation may be used along a coordinate direction to perform a shift of data. As input, MPI\_SENDRECV takes the rank of a source process for the receive, and the rank of a destination process for the send. If the function MPI\_CART\_SHIFT is called for a Cartesian process group, it provides the calling process with the above identifiers, which then can be passed to MPI\_SENDRECV. The user specifies the coordinate direction and the size of the step (positive or negative).

The function is local.

MPI\_CART\_SHIFT(comm, direction, disp, rank\_source, rank\_dest)

IN	comm	communicator with Cartesian structure (handle)
IN	direction	coordinate dimension of shift (integer)
IN	disp	displacement (> 0: upwards shift, < 0: downwards shift) (integer)
OUT	rank_source	rank of source process (integer)
OUT	rank_dest	rank of destination process (integer)

#### C binding

20

21

22

23

24

25 26

27 28

29

Done in PR439 not zero

but not zero

33 question in

75 #-343 86 #-error!

```
1
     int MPI_Cart_shift(MPI_Comm comm, int direction, int disp,
2
                   int *rank_source, int *rank_dest)
3
     Fortran 2008 binding
4
     MPI_Cart_shift(comm, direction, disp, rank_source, rank_dest, ierror)
5
         TYPE(MPI_Comm), INTENT(IN) :: comm
6
         INTEGER, INTENT(IN) :: direction, disp
         INTEGER, INTENT(OUT) :: rank_source, rank_dest
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
9
10
     Fortran binding
11
     MPI_CART_SHIFT(COMM, DIRECTION, DISP, RANK_SOURCE, RANK_DEST, IERROR)
12
         INTEGER COMM, DIRECTION, DISP, RANK_SOURCE, RANK_DEST, IERROR
13
14
```

The direction argument indicates the coordinate dimension to be traversed by the shift. The dimensions are numbered from 0 to ndims-1, where ndims is the number of dimensions.

Depending on the periodicity of the Cartesian group in the specified coordinate direction, MPI\_CART\_SHIFT provides the identifiers for a circular or an end-off shift. In the case of an end-off shift, the value MPI\_PROC\_NULL may be returned in rank\_source or rank\_dest, indicating that the source or the destination for the shift is out of range.

It is erroneous to call MPI\_CART\_SHIFT with a direction that is either negative or greater than or equal to the number of dimensions in the Cartesian communicator. This implies that it is erroneous to call MPI\_CART\_SHIFT with a comm that is associated with a zero-dimensional Cartesian topology.

**Example 8.7** The communicator, comm, has a two-dimensional, periodic, Cartesian topology associated with it. A two-dimensional array of REALs is stored one element per process, in variable A. One wishes to skew this array, by shifting column i (vertically, i.e., along the column) by i steps.

```
! find process rank
CALL MPI_COMM_RANK(comm, rank, ierr)
! find Cartesian coordinates
CALL MPI_CART_COORDS(comm, rank, maxdims, coords, ierr)
! compute shift source and destination
CALL MPI_CART_SHIFT(comm, 0, coords(2), source, dest, ierr)
! skew array
CALL MPI_SENDRECV_REPLACE(A, 1, MPI_REAL, dest, 0, source, 0, comm, & status, ierr)
```

Advice to users. In Fortran, the dimension indicated by DIRECTION = i has DIMS(i+1) nodes, where DIMS is the array that was used to create the grid. In C, the dimension indicated by direction = i is the dimension specified by dims[i]. (End of advice to users.)

# 8.5.7 Partitioning of Cartesian Structures

# MPI\_CART\_SUB(comm, remain\_dims, newcomm)

IN comm communicator with Cartesian structure (handle)

IN remain\_dims the i-th entry of remain\_dims specifies whether the i-th dimension is kept in the subgrid (true) or is dropped (false) (array of logicals)

OUT newcomm communicator containing the subgrid that includes

the calling process (handle)

# C binding

int MPI\_Cart\_sub(MPI\_Comm comm, const int remain\_dims[], MPI\_Comm \*newcomm)

# Fortran 2008 binding

```
MPI_Cart_sub(comm, remain_dims, newcomm, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    LOGICAL, INTENT(IN) :: remain_dims(*)
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

```
MPI_CART_SUB(COMM, REMAIN_DIMS, NEWCOMM, IERROR)
INTEGER COMM, NEWCOMM, IERROR
LOGICAL REMAIN_DIMS(*)
```

MPI\_CART\_SUB can be used to partition the group associated with a communicator that has an associated Cartesian topology into subgroups that form lower-dimensional Cartesian subgrids, and to build for each subgroup a communicator with the associated subgrid Cartesian topology. The topologies of the new communicators describe the subgrids. The number of dimensions of the subgrids is the number of remaining dimensions, i.e., the number of true values in remain\_dims. The numbers of processes in each coordinate direction of the subgrids are the remaining numbers of processes in each coordinate direction of the grid associated with the original communicator, i.e., the values of the original grid dimensions for which the corresponding entry in remain\_dims is true. The periodicity for the remaining dimensions in the new communicator is preserved from the original communicator. If all entries in remain\_dims are false or comm is already associated with a zero-dimensional Cartesian topology. (This function is closely related to MPI\_COMM\_SPLIT.)

**Example 8.8** Assume that MPI\_Cart\_create(..., comm) has defined a  $(2 \times 3 \times 4)$  grid. Let remain\_dims = (true, false, true). Then a call to

```
MPI_Cart_sub(comm, remain_dims, newcomm)
```

will create three communicators each with eight processes in a  $2 \times 4$  Cartesian topology. If remain\_dims = (false, false, true) then the call to

<sup>27</sup> #-314

<sup>30</sup> **#-315** 

```
MPI_Cart_sub(comm, remain_dims, newcomm)
```

will create six non-overlapping communicators, each with four processes, in a one-dimensional

Cartesian topology.

# 8.5.8 Low-Level Topology Functions

The two additional functions introduced in this section can be used to implement all other topology functions. In general they will not be called by the user directly, unless he or she is creating additional virtual topology capability other than that provided by MPI. The two calls are both local.

# MPI\_CART\_MAP(comm, ndims, dims, periods, newrank)

IN	comm	input communicator (handle)
IN	ndims	number of dimensions of Cartesian structure (integer)
IN	dims	integer array of size ndims specifying the number of processes in each coordinate direction
IN	periods	logical array of size ndims specifying the periodicity specification in each coordinate direction
OUT	newrank	reordered rank of the calling process;  MPI_UNDEFINED if calling process does not belong to grid (integer)

#### C binding

# Fortran 2008 binding

```
MPI_Cart_map(comm, ndims, dims, periods, newrank, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: ndims, dims(ndims)
    LOGICAL, INTENT(IN) :: periods(ndims)
    INTEGER, INTENT(OUT) :: newrank
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

```
MPI_CART_MAP(COMM, NDIMS, DIMS, PERIODS, NEWRANK, IERROR)
    INTEGER COMM, NDIMS, DIMS(*), NEWRANK, IERROR
    LOGICAL PERIODS(*)
```

MPI\_CART\_MAP computes an "optimal" placement for the calling process on the physical machine. A possible implementation of this function is to always return the rank of the calling process, that is, not to perform any reordering.

Advice to implementors. The function MPI\_CART\_CREATE(comm, ndims, dims, periods, reorder, comm\_cart), with reorder = true can be implemented by calling MPI\_CART\_MAP(comm, ndims, dims, periods, newrank), then calling

MPI\_COMM\_SPLIT(comm, color, key, comm\_cart), with color = 0 if newrank  $\neq$  MPI\_UNDEFINED, color = MPI\_UNDEFINED otherwise, and key = newrank. If ndims is zero then a zero-dimensional Cartesian topology is created.

The function MPI\_CART\_SUB(comm, remain\_dims, comm\_new) can be implemented by a call to MPI\_COMM\_SPLIT(comm, color, key, comm\_new), using a single number encoding of the lost dimensions as color and a single number encoding of the preserved dimensions as key.

All other Cartesian topology functions can be implemented locally, using the topology information that is cached with the communicator. (End of advice to implementors.)

The corresponding function for graph structures is as follows.

# MPI\_GRAPH\_MAP(comm, nnodes, index, edges, newrank)

IN	comm	input communicator (handle)
IN	nnodes	number of graph nodes (integer)
IN	index	integer array specifying the graph structure, see $MPI\_GRAPH\_CREATE$
IN	edges	integer array specifying the graph structure
OUT	newrank	reordered rank of the calling process;  MPI_UNDEFINED if the calling process does not belong to graph (integer)

#### C binding

# Fortran 2008 binding

```
MPI_Graph_map(comm, nnodes, index, edges, newrank, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: nnodes, index(nnodes), edges(*)
    INTEGER, INTENT(OUT) :: newrank
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_GRAPH_MAP(COMM, NNODES, INDEX, EDGES, NEWRANK, IERROR)
INTEGER COMM, NNODES, INDEX(*), EDGES(*), NEWRANK, IERROR
```

Advice to implementors. The function MPI\_GRAPH\_CREATE(comm, nnodes, index, edges, reorder, comm\_graph), with reorder = true can be implemented by calling MPI\_GRAPH\_MAP(comm, nnodes, index, edges, newrank), then calling MPI\_COMM\_SPLIT(comm, color, key, comm\_graph), with color = 0 if newrank  $\neq$  MPI\_UNDEFINED, color = MPI\_UNDEFINED otherwise, and key = newrank.

All other graph topology functions can be implemented locally, using the topology information that is cached with the communicator. (End of advice to implementors.)

8.6

MPI process topologies specify a communication graph, but they implement no communication function themselves. Many applications require sparse nearest neighbor communications that can be expressed as graph topologies. We now describe several collective operations that perform communication along the edges of a process topology. All of these functions are collective; i.e., they must be called by all processes in the specified communicator. See Section 6 for an overview of other dense (global) collective communication operations and the semantics of collective operations.

Neighborhood Collective Communication on Process Topologies

If the graph was created with MPI\_DIST\_GRAPH\_CREATE\_ADJACENT with sources and destinations containing 0, ..., n-1, where n is the number of processes in the group of comm\_old (i.e., the graph is fully connected and also includes an edge from each node to itself), then the sparse neighborhood communication routine performs the same data exchange as the corresponding dense (fully-connected) collective operation. In the case of a Cartesian communicator, only nearest neighbor communication is provided, corresponding to rank\_source and rank\_dest in MPI\_CART\_SHIFT with input disp = 1.

Rationale. Neighborhood collective communications enable communication on a process topology. This high-level specification of data exchange among neighboring processes enables optimizations in the MPI library because the communication pattern is known statically (the topology). Thus, the implementation can compute optimized message schedules during creation of the topology [39]. This functionality can significantly simplify the implementation of neighbor exchanges [35]. (End of rationale.)

For a distributed graph topology, created with MPI\_DIST\_GRAPH\_CREATE, the sequence of neighbors in the send and receive buffers at each process is defined as the sequence returned by MPI\_DIST\_GRAPH\_NEIGHBORS for destinations and sources, respectively. For a general graph topology, created with MPI\_GRAPH\_CREATE, the use of neighborhood collective communication is restricted to adjacency matrices, where the number of edges between any two processes is defined to be the same for both processes (i.e., with a symmetric adjacency matrix). In this case, the order of neighbors in the send and receive buffers is defined as the sequence of neighbors as returned by MPI\_GRAPH\_NEIGHBORS. Note that general graph topologies should generally be replaced by the distributed graph topologies.

For a Cartesian topology, created with MPI\_CART\_CREATE, the sequence of neighbors in the send and receive buffers at each process is defined by order of the dimensions, first the neighbor in the negative direction and then in the positive direction with displacement 1. The numbers of sources and destinations in the communication routines are 2\*ndims with ndims defined in MPI\_CART\_CREATE. If a neighbor does not exist, i.e., at the border of a Cartesian topology in the case of a non-periodic virtual grid dimension (i.e., periods[...]==false), then this neighbor is defined to be MPI\_PROC\_NULL.

If a neighbor in any of the functions is MPI\_PROC\_NULL, then the neighborhood collective communication behaves like a point-to-point communication with MPI\_PROC\_NULL in this direction. That is, the buffer is still part of the sequence of neighbors but it is neither communicated nor updated.

#### 8.6.1 Neighborhood Gather

In this function, each process i gathers data items from each process j if an edge (j, i) exists in the topology graph, and each process i sends the same data items to all processes j where

an edge (i,j) exists. The send buffer is sent to each neighboring process and the l-th block

47

in the receive buffer is received from the *l*-th neighbor. MPI\_NEIGHBOR\_ALLGATHER(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, comm) IN sendbuf starting address of send buffer (choice) IN sendcount number of elements sent to each neighbor (non-negative integer) IN sendtype data type of send buffer elements (handle) OUT recvbuf starting address of receive buffer (choice) 12 13 IN recvcount number of elements received from each neighbor 14 (non-negative integer) 15 data type of receive buffer elements (handle) IN recvtype 16 17 communicator with topology structure (handle) IN comm 18 19 C binding 20 int MPI\_Neighbor\_allgather(const void \*sendbuf, int sendcount, 21 MPI\_Datatype sendtype, void \*recvbuf, int recvcount, 22 MPI\_Datatype recvtype, MPI\_Comm comm) 23 <sub>24</sub> #-... int MPI\_Neighbor\_allgather\_c(const void \*sendbuf, MPI\_Count sendcount, MPI\_Datatype sendtype, void \*recvbuf, MPI\_Count recvcount, 25 MPI\_Datatype recvtype, MPI\_Comm comm) 26 27 Fortran 2008 binding 28 MPI\_Neighbor\_allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount, 29 recvtype, comm, ierror) 30 TYPE(\*), DIMENSION(..), INTENT(IN) :: sendbuf INTEGER, INTENT(IN) :: sendcount, recvcount TYPE(MPI\_Datatype), INTENT(IN) :: sendtype, recvtype TYPE(\*), DIMENSION(..) :: recvbuf 34 TYPE(MPI\_Comm), INTENT(IN) :: comm 35 INTEGER, OPTIONAL, INTENT(OUT) :: ierror 36 MPI\_Neighbor\_allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount, 37 #-... recvtype, comm, ierror) 38 TYPE(\*), DIMENSION(..), INTENT(IN) :: sendbuf 39 INTEGER(KIND=MPI\_COUNT\_KIND), INTENT(IN) :: sendcount, recvcount 40 TYPE(MPI\_Datatype), INTENT(IN) :: sendtype, recvtype 41 TYPE(\*), DIMENSION(..) :: recvbuf 42 TYPE(MPI\_Comm), INTENT(IN) :: comm 43 INTEGER, OPTIONAL, INTENT(OUT) :: ierror 44 45 Fortran binding 46 MPI\_NEIGHBOR\_ALLGATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT,

RECVTYPE, COMM, IERROR)

question in 6

#-343

```
<type> SENDBUF(*), RECVBUF(*)
INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, IERROR
```

This function supports Cartesian communicators, graph communicators, and distributed graph communicators as described in Section 8.6. If comm is a distributed graph communicator, the outcome is as if each process executed sends to each of its outgoing neighbors and receives from each of its incoming neighbors:

Figure 8.1 shows the neighborhood gather communication of one process with outgoing neighbors  $d_0 ldots d_3$  and incoming neighbors  $s_0 ldots s_5$ . The process will send its sendbuf to all four destinations (outgoing neighbors) and it will receive the contribution from all six sources (incoming neighbors) into separate locations of its receive buffer.




Figure 8.1: Neighborhood gather communication example.

11

12

14

15

16 17

All arguments are significant on all processes and the argument comm must have identical values on all processes.

The type signature associated with sendcount, sendtype, at a process must be equal to the type signature associated with recvount, recvtype at all other processes. This implies that the amount of data sent must be equal to the amount of data received, pairwise between every pair of communicating processes. Distinct type maps between sender and receiver are still allowed.

For optimization reasons, the same type signature is required indepen-Rationale. dently of whether the topology graph is connected or not. (End of rationale.)

The "in place" option is not meaningful for this operation.

**Example 8.9** On a Cartesian virtual grid, the buffer usage in a given direction d with dims[d]==3 and 1, respectively during creation of the communicator is described in Figure 8.2.



Figure 8.2: Cartesian neighborhood allgather example for 3 and 1 processes in a dimension.

The figure may apply to any (or multiple) directions in the Cartesian topology. The grey buffers are required in all cases but are only accessed if during creation of the communicator, periods[d] was defined as **1** (in C) or .TRUE. (in Fortran).

The vector variant of MPI\_NEIGHBOR\_ALLGATHER allows one to gather different numbers of elements from each neighbor.

MPI\_NEIGHBOR\_ALLGATHERV(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs, recvtype, comm)

IN	sendbuf	starting address of send buffer (choice)
IN	sendcount	number of elements sent to each neighbor (non-negative integer)
IN	sendtype	data type of send buffer elements (handle)
OUT	recvbuf	starting address of receive buffer (choice)
IN	recvcounts	non-negative integer array (of length indegree) containing the number of elements that are received from each neighbor
IN	displs	integer array (of length indegree). Entry i specifies the displacement (relative to recvbuf) at which to place the incoming data from neighbor i
IN	recvtype	data type of receive buffer elements (handle)
IN	comm	communicator with topology structure (handle)

C binding

non-zero

13 #-153 B.2.1: 1

18 19 20

21 22

23

24

25

26

27

28

29

30

#-error! #-343 (PR332)

Done in PR439

```
1
          int MPI_Neighbor_allgatherv(const void *sendbuf, int sendcount,
     2
                        MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
                        const int displs[], MPI_Datatype recvtype, MPI_Comm comm)
          int MPI_Neighbor_allgatherv_c(const void *sendbuf, MPI_Count sendcount,
#-...
                        MPI_Datatype sendtype, void *recvbuf,
                        const MPI_Count recvcounts[], const MPI_Aint displs[],
     7
                        MPI_Datatype recvtype, MPI_Comm comm)
     8
     9
          Fortran 2008 binding
     10
          MPI_Neighbor_allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
     11
                        displs, recvtype, comm, ierror)
     12
              TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
     13
              INTEGER, INTENT(IN) :: sendcount, recvcounts(*), displs(*)
     14
              TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
     15
              TYPE(*), DIMENSION(..) :: recvbuf
              TYPE(MPI_Comm), INTENT(IN) :: comm
     17
              INTEGER, OPTIONAL, INTENT(OUT) :: ierror
          MPI_Neighbor_allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
     19
#-...
                        displs, recvtype, comm, ierror)
     20
              TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
     21
              INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcounts(*)
     22
              TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
     23
              TYPE(*), DIMENSION(..) :: recvbuf
     24
              INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: displs(*)
     25
              TYPE(MPI_Comm), INTENT(IN) :: comm
     26
              INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     27
     28
          Fortran binding
     29
          MPI_NEIGHBOR_ALLGATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS,
     30
                        DISPLS, RECVTYPE, COMM, IERROR)
     31
              <type> SENDBUF(*), RECVBUF(*)
              INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, COMM,
     33
                         IERROR
     34
              This function supports Cartesian communicators, graph communicators, and distributed
     35
          graph communicators as described in Section 8.6. If comm is a distributed graph commu-
     36
          nicator, the outcome is as if each process executed sends to each of its outgoing neighbors
     37
          and receives from each of its incoming neighbors:
     38
     39
          MPI_Dist_graph_neighbors_count(comm, &indegree, &outdegree, &weighted);
     40
          int *srcs=(int*)malloc(indegree*sizeof(int));
     41
          int *dsts=(int*)malloc(outdegree*sizeof(int));
          MPI_Dist_graph_neighbors(comm, indegree, srcs, MPI_UNWEIGHTED,
     43
                                     outdegree, dsts, MPI_UNWEIGHTED);
     44
          int k;
     45
     46
          /* assume sendbuf and recvbuf are of type (char*) */
     47
          for(k=0; k<outdegree; ++k)</pre>
```

#-...

The type signature associated with sendcount, sendtype, at process j must be equal to the type signature associated with recvcounts[l], recvtype at any other process with srcs[l]==j. This implies that the amount of data sent must be equal to the amount of data received, pairwise between every pair of communicating processes. Distinct type maps between sender and receiver are still allowed. The data received from the l-th neighbor is placed into recvbuf beginning at offset displs[l] elements (in terms of the recvtype).

The "in place" option is not meaningful for this operation.

All arguments are significant on all processes and the argument comm must have identical values on all processes.

# 8.6.2 Neighbor Alltoall

In this function, each process i receives data items from each process j if an edge (j,i) exists in the topology graph or Cartesian topology. Similarly, each process i sends data items to all processes j where an edge (i,j) exists. This call is more general than MPI\_NEIGHBOR\_ALLGATHER in that different data items can be sent to each neighbor. The k-th block in send buffer is sent to the k-th neighboring process and the l-th block in the receive buffer is received from the l-th neighbor.

MPI\_NEIGHBOR\_ALLTOALL(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, comm)

IN	sendbuf	starting address of send buffer (choice)
IN	sendcount	number of elements sent to each neighbor (non-negative integer)
IN	sendtype	data type of send buffer elements (handle)
OUT	recvbuf	starting address of receive buffer (choice)
IN	recvcount	number of elements received from each neighbor (non-negative integer)
IN	recvtype	data type of receive buffer elements (handle)
IN	comm	communicator with topology structure (handle)

#### C binding

```
int MPI_Neighbor_alltoall_c(const void *sendbuf, MPI_Count sendcount,
                        MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
                        MPI_Datatype recvtype, MPI_Comm comm)
          Fortran 2008 binding
          MPI_Neighbor_alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount,
     6
                        recvtype, comm, ierror)
              TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
              INTEGER, INTENT(IN) :: sendcount, recvcount
     9
              TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
     10
              TYPE(*), DIMENSION(..) :: recvbuf
              TYPE(MPI_Comm), INTENT(IN) :: comm
     12
              INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     13
    14
          MPI_Neighbor_alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount,
#-...
     15
                        recvtype, comm, ierror)
     16
              TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
     17
              INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
              TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
     19
              TYPE(*), DIMENSION(..) :: recvbuf
     20
              TYPE(MPI_Comm), INTENT(IN) :: comm
     21
              INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     22
          Fortran binding
     23
          MPI_NEIGHBOR_ALLTOALL(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT,
     24
                        RECVTYPE, COMM, IERROR)
     25
              <type> SENDBUF(*), RECVBUF(*)
     26
              INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, IERROR
     27
     28
              This function supports Cartesian communicators, graph communicators, and distributed
     29
          graph communicators as described in Section 8.6. If comm is a distributed graph commu-
     30
          nicator, the outcome is as if each process executed sends to each of its outgoing neighbors
     31
          and receives from each of its incoming neighbors:
     32
     33
          MPI_Dist_graph_neighbors_count(comm, &indegree, &outdegree, &weighted);
     34
          int *srcs=(int*)malloc(indegree*sizeof(int));
     35
          int *dsts=(int*)malloc(outdegree*sizeof(int));
     36
          MPI_Dist_graph_neighbors(comm, indegree, srcs, MPI_UNWEIGHTED,
     37
                                     outdegree, dsts, MPI_UNWEIGHTED);
     38
          int k;
     39
          /* assume sendbuf and recvbuf are of type (char*) */
     41
          for(k=0; k<outdegree; ++k)</pre>
     42
            MPI_Isend(sendbuf+k*sendcount*extent(sendtype), sendcount, sendtype,
     43
                       dsts[k],...);
     44
     45
          for(k=0; k<indegree; ++k)</pre>
            MPI_Irecv(recvbuf+k*recvcount*extent(recvtype), recvcount, recvtype,
     47
                       srcs[k],...);
```

```
MPI_Waitall(...);
```

non-zero

The type signature associated with sendcount, sendtype, at a process must be equal to the type signature associated with recvount, recvtype at any other process. This implies that the amount of data sent must be equal to the amount of data received, pairwise between every pair of communicating processes. Distinct type maps between sender and receiver are still allowed.

The "in place" option is not meaningful for this operation.

All arguments are significant on all processes and the argument comm must have identical values on all processes.

**Example 8.10** For a halo communication on a Cartesian grid, the buffer usage in a given direction d with dims[d]==3 and 1, respectively during creation of the communicator is described in Figure 8.3.




Figure 8.3: Cartesian neighborhood alltoall example for 3 and 1 processes in a dimension.

The figure may apply to any (or multiple) directions in the Cartesian topology. The grey buffers are required in all cases but are only accessed if during creation of the communicator, periods[d] was defined as 1 (in C) or .TRUE. (in Fortran).

If each array element of sendbuf and recybuf are described by sendcount, sendtype and recvbuf, recvtype, then after MPI\_NEIGHBOR\_ALLTOALL on a Cartesian communicator \mpiarg returned, the content of the recybuf is as if the following code is executed:

```
MPI_Cartdim_get(comm, &ndims);
for( /*direction*/ d=0; d < ndims; d++) {</pre>
 MPI_Cart_shift(comm, /*direction*/ d, /*disp*/ 1, &rank_source, &rank_dest);
 MPI_Sendrecv(sendbuf[d*2+0], sendcount, sendtype, rank_source, /*sendtag*/d*2,
                recvbuf[d*2+1],recvcount,recvtype,rank_dest, /*recvtag*/ d*2,
                comm,&status);/*communication in direction of displacment -1*/
 MPI_Sendrecv(sendbuf[d*2+1], sendcount, sendtype, rank_dest, /*sendtag*/ d*2+1,
                recvbuf[d*2+0],recvcount,recvtype,rank_source,/*recvtag*/d*2+1,
                comm, &status); /*communication in direction of displacment +1*/
}
    The first call to MPI_Sendrecv implements the upper (solid arrows) communication
```

**Unofficial Draft for Comment Only** 

solid arrows'

12 #-153 B.2.1: 1

10

13

23

24 25

30 31

33

34

35

36

37

38

39

40

41

42

43

44

45

 $^{46}$ 

#-error! #-343 (PR332)

Done PR439

#-error! #-343

Done PR439

#-error! #-343 Done in PR439

#-153

#-error! #-343 (PR332) Done in PR439

#-...

pattern in each diagram of Figure 8.3, whereas the second call is for the lower (dashed arrows) pattern. dashed arrows'

Advice to implementors. For a Cartesian topology, if the virtual grid in a direction d 1 or 2 is periodic and dims[d] is equal to for f, then rank\_source and rank\_dest are identical, but still all ndims send and ndims receive operations use different buffers. If in this case, the two send and receive operations per direction or of all directions are internally parallelized, then the several send and receive operations for the same sender-receiver process pair must be initiated in the same sequence on sender and receiver side or they shall be distinguished by different tags. The code above shows a valid sequence of operations and tags. (End of advice to implementors.)

The vector variant of MPI\_NEIGHBOR\_ALLTOALL allows sending/receiving different numbers of elements to and from each neighbor.

# MPI\_NEIGHBOR\_ALLTOALLV(sendbuf, sendcounts, sdispls, sendtype, recvbuf, recvcounts, rdispls, recvtype, comm)

IN	sendbuf	starting address of send buffer (choice)
IN	sendcounts	non-negative integer array (of length outdegree)
		specifying the number of elements to send to each
		neighbor
IN	sdispls	integer array (of length outdegree). Entry j specifies
		the displacement (relative to sendbuf) from which to
		send the outgoing data to neighbor <b>j</b>
IN	sendtype	data type of send buffer elements (handle)
OUT	recvbuf	starting address of receive buffer (choice)
IN	recvcounts	non-negative integer array (of length indegree)
		specifying the number of elements that are received
		from each neighbor
IN	rdispls	integer array (of length indegree). Entry i specifies
		the displacement (relative to recvbuf) at which to
		place the incoming data from neighbor i
IN	recvtype	data type of receive buffer elements (handle)
IN	comm	communicator with topology structure (handle)

### C binding

```
Fortran 2008 binding
MPI_Neighbor_alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
              recvcounts, rdispls, recvtype, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    INTEGER, INTENT(IN) :: sendcounts(*), sdispls(*), recvcounts(*),
               rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..) :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Neighbor_alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
                                                                                    12
              recvcounts, rdispls, recvtype, comm, ierror)
                                                                                    13
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
                                                                                    14
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcounts(*),
                                                                                    15
               recvcounts(*)
                                                                                    16
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: sdispls(*), rdispls(*)
                                                                                    17
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                    18
    TYPE(*), DIMENSION(..) :: recvbuf
                                                                                    19
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                    20
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    21
                                                                                    22
Fortran binding
                                                                                    23
MPI_NEIGHBOR_ALLTOALLV(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE, RECVBUF,
                                                                                    24
              RECVCOUNTS, RDISPLS, RECVTYPE, COMM, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
                                                                                    26
    INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*),
               RECVTYPE, COMM, IERROR
                                                                                    27
                                                                                    28
    This function supports Cartesian communicators, graph communicators, and distributed
graph communicators as described in Section 8.6. If comm is a distributed graph commu-
nicator, the outcome is as if each process executed sends to each of its outgoing neighbors
                                                                                    31
and receives from each of its incoming neighbors:
                                                                                    33
MPI_Dist_graph_neighbors_count(comm, &indegree, &outdegree, &weighted);
                                                                                    34
int *srcs=(int*)malloc(indegree*sizeof(int));
                                                                                    35
int *dsts=(int*)malloc(outdegree*sizeof(int));
                                                                                    36
MPI_Dist_graph_neighbors(comm, indegree, srcs, MPI_UNWEIGHTED,
                                                                                    37
                          outdegree, dsts, MPI_UNWEIGHTED);
                                                                                    38
int k;
                                                                                    40
/* assume sendbuf and recvbuf are of type (char*) */
                                                                                    41
for(k=0; k<outdegree; ++k)</pre>
                                                                                    42
  MPI_Isend(sendbuf+sdispls[k]*extent(sendtype), sendcounts[k], sendtype,
                                                                                    43
            dsts[k],...);
                                                                                    44
                                                                                    45
for(k=0; k<indegree; ++k)</pre>
                                                                                    46
  MPI_Irecv(recvbuf+rdispls[k]*extent(recvtype), recvcounts[k], recvtype,
                                                                                    47
             srcs[k],...);
```

# MPI\_Waitall(...);

The type signature associated with sendcounts[k], sendtype with dsts[k]==j at process i must be equal to the type signature associated with recvcounts[l], recvtype with srcs[l]==i at process j. This implies that the amount of data sent must be equal to the amount of data received, pairwise between every pair of communicating processes. Distinct type maps between sender and receiver are still allowed. The data in the sendbuf beginning at offset sdispls[k] elements (in terms of the sendtype) is sent to the k-th outgoing neighbor. The data received from the l-th incoming neighbor is placed into recvbuf beginning at offset rdispls[l] elements (in terms of the recvtype).

The "in place" option is not meaningful for this operation.

All arguments are significant on all processes and the argument comm must have identical values on all processes.

MPI\_NEIGHBOR\_ALLTOALLW allows one to send and receive with different datatypes to and from each neighbor.

IN

sendbuf

MPI\_NEIGHBOR\_ALLTOALLW(sendbuf, sendcounts, sdispls, sendtypes, recvbuf, recvcounts, rdispls, recvtypes, comm)

starting address of send buffer (choice)

IN	sendcounts	non-negative integer array (of length outdegree) specifying the number of elements to send to each neighbor
IN	sdispls	integer array (of length outdegree). Entry j specifies the displacement in bytes (relative to sendbuf) from which to take the outgoing data destined for neighbor j (array of integers)
IN	sendtypes	array of data types (of length outdegree). Entry j specifies the type of data to send to neighbor j (array of handles)
OUT	recvbuf	starting address of receive buffer (choice)
IN	recvcounts	non-negative integer array (of length indegree) specifying the number of elements that are received from each neighbor
IN	rdispls	integer array (of length indegree). Entry i specifies the displacement in bytes (relative to recvbuf) at which to place the incoming data from neighbor i (array of integers)
IN	recvtypes	array of datatypes (of length indegree). Entry i specifies the type of data received from neighbor i (array of handles)
IN	comm	communicator with topology structure (handle)

```
int MPI_Neighbor_alltoallw(const void *sendbuf, const int sendcounts[],
              const MPI_Aint sdispls[], const MPI_Datatype sendtypes[],
              void *recvbuf, const int recvcounts[],
              const MPI_Aint rdispls[], const MPI_Datatype recvtypes[],
              MPI Comm comm)
int MPI_Neighbor_alltoallw_c(const void *sendbuf,
              const MPI_Count sendcounts[], const MPI_Aint sdispls[],
                                                                                   8
              const MPI_Datatype sendtypes[], void *recvbuf,
                                                                                   9
              const MPI_Count recvcounts[], const MPI_Aint rdispls[],
                                                                                   10
              const MPI_Datatype recvtypes[], MPI_Comm comm)
Fortran 2008 binding
                                                                                   12
                                                                                   13
MPI_Neighbor_alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
                                                                                   14
              recvcounts, rdispls, recvtypes, comm, ierror)
                                                                                   15
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    INTEGER, INTENT(IN) :: sendcounts(*), recvcounts(*)
                                                                                   16
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: sdispls(*), rdispls(*)
                                                                                   18
    TYPE(MPI_Datatype), INTENT(IN) :: sendtypes(*), recvtypes(*)
                                                                                   19
    TYPE(*), DIMENSION(..) :: recvbuf
                                                                                   20
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                   21
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   22
MPI_Neighbor_alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
                                                                                   23 #-...
              recvcounts, rdispls, recvtypes, comm, ierror)
                                                                                   24
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
                                                                                   25
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcounts(*),
                                                                                   26
               recvcounts(*)
                                                                                   27
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: sdispls(*), rdispls(*)
                                                                                   28
    TYPE(MPI_Datatype), INTENT(IN) :: sendtypes(*), recvtypes(*)
                                                                                   29
    TYPE(*), DIMENSION(..) :: recvbuf
                                                                                   30
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                   31
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   32
Fortran binding
                                                                                   34
MPI_NEIGHBOR_ALLTOALLW(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPES, RECVBUF,
                                                                                   35
              RECVCOUNTS, RDISPLS, RECVTYPES, COMM, IERROR)
                                                                                   36
    <type> SENDBUF(*), RECVBUF(*)
                                                                                   37
    INTEGER SENDCOUNTS(*), SENDTYPES(*), RECVCOUNTS(*), RECVTYPES(*), COMM,
                                                                                   38
               IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) SDISPLS(*), RDISPLS(*)
    This function supports Cartesian communicators, graph communicators, and distributed
graph communicators as described in Section 8.6. If comm is a distributed graph commu-
nicator, the outcome is as if each process executed sends to each of its outgoing neighbors
                                                                                   43
and receives from each of its incoming neighbors:
                                                                                   44
                                                                                   45
MPI_Dist_graph_neighbors_count(comm, &indegree, &outdegree, &weighted);
                                                                                   46
int *srcs=(int*)malloc(indegree*sizeof(int));
```

int \*dsts=(int\*)malloc(outdegree\*sizeof(int));

The type signature associated with sendcounts[k], sendtypes[k] with dsts[k]==j at process i must be equal to the type signature associated with recvcounts[l], recvtypes[l] with srcs[l]==i at process j. This implies that the amount of data sent must be equal to the amount of data received, pairwise between every pair of communicating processes. Distinct type maps between sender and receiver are still allowed.

The "in place" option is not meaningful for this operation.

All arguments are significant on all processes and the argument comm must have identical values on all processes.

# 8.7 Nonblocking Neighborhood Communication on Process Topologies

Nonblocking variants of the neighborhood collective operations allow relaxed synchronization and overlapping of computation and communication. The semantics are similar to nonblocking collective operations as described in Section 6.12.

# 8.7.1 Nonblocking Neighborhood Gather

# MPI\_INEIGHBOR\_ALLGATHER(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, comm, request)

1N	sendbuf	starting address of send buffer (choice)
IN	sendcount	number of elements sent to each neighbor (non-negative integer)
IN	sendtype	data type of send buffer elements (handle)
OUT	recvbuf	starting address of receive buffer (choice)
IN	recvcount	$\begin{array}{l} {\rm number\ of\ elements\ received\ from\ each\ neighbor} \\ {\rm (non-negative\ integer)} \end{array}$
IN	recvtype	data type of receive buffer elements (handle)
IN	comm	communicator with topology structure (handle)
OUT	request	communication request (handle)
	•	1 ( )

C binding

```
int MPI_Ineighbor_allgather(const void *sendbuf, int sendcount,
             MPI_Datatype sendtype, void *recvbuf, int recvcount,
             MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
int MPI_Ineighbor_allgather_c(const void *sendbuf, MPI_Count sendcount,
                                                                                  5 #-...
             MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
             MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
Fortran 2008 binding
MPI_Ineighbor_allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount,
             recvtype, comm, request, ierror)
    TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN) :: sendcount, recvcount
                                                                                  12
                                                                                  13
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                  14
    TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
                                                                                  15
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  16
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  17
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  18
MPI_Ineighbor_allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount,
                                                                                  19 #-...
             recvtype, comm, request, ierror)
                                                                                  20
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                  21
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
                                                                                  22
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                  23
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                  ^{24}
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  25
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  26
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  27
                                                                                  28
Fortran binding
                                                                                  29
MPI_INEIGHBOR_ALLGATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT,
             RECVTYPE, COMM, REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, REQUEST, IERROR
    This call starts a nonblocking variant of MPI_NEIGHBOR_ALLGATHER.
                                                                                  34
                                                                                  35
                                                                                  36
                                                                                  37
                                                                                  42
                                                                                  43
                                                                                  44
                                                                                  45
```

#-...

```
1
     MPI_INEIGHBOR_ALLGATHERV(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
2
                    recvtype, comm, request)
3
       IN
                sendbuf
                                            starting address of send buffer (choice)
       IN
                sendcount
                                            number of elements sent to each neighbor
5
                                            (non-negative integer)
6
7
       IN
                sendtype
                                            data type of send buffer elements (handle)
       OUT
                 recvbuf
                                            starting address of receive buffer (choice)
9
       IN
                                            non-negative integer array (of length indegree)
                 recvcounts
10
                                            containing the number of elements that are received
11
                                            from each neighbor
12
13
       IN
                 displs
                                            integer array (of length indegree). Entry i specifies
14
                                            the displacement (relative to recvbuf) at which to
15
                                            place the incoming data from neighbor i
16
                                            data type of receive buffer elements (handle)
       IN
                 recvtype
17
       IN
                 comm
                                            communicator with topology structure (handle)
18
19
                                            communication request (handle)
       OUT
                 request
20
21
     C binding
22
     int MPI_Ineighbor_allgatherv(const void *sendbuf, int sendcount,
23
                    MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
24
                    const int displs[], MPI_Datatype recvtype, MPI_Comm comm,
25
                    MPI_Request *request)
     int MPI_Ineighbor_allgatherv_c(const void *sendbuf, MPI_Count sendcount,
27
                    MPI_Datatype sendtype, void *recvbuf,
28
                    const MPI_Count recvcounts[], const MPI_Aint displs[],
29
                    MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
30
31
     Fortran 2008 binding
32
     MPI_Ineighbor_allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
33
                    displs, recvtype, comm, request, ierror)
34
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
35
          INTEGER, INTENT(IN) :: sendcount
36
          TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
37
          TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
38
          INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*), displs(*)
          TYPE(MPI_Comm), INTENT(IN) :: comm
          TYPE(MPI_Request), INTENT(OUT) :: request
41
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
42
     MPI_Ineighbor_allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
43
                    displs, recvtype, comm, request, ierror)
44
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
45
          INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
46
          TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
47
          TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
```

39 #-..

```
INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
TYPE(MPI_Comm), INTENT(IN) :: comm
TYPE(MPI_Request), INTENT(OUT) :: request
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

MPI\_INEIGHBOR\_ALLGATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS, RECVTYPE, COMM, REQUEST, IERROR)

<type> SENDBUF(\*), RECVBUF(\*)

INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(\*), DISPLS(\*), RECVTYPE, COMM, REQUEST, IERROR

This call starts a nonblocking variant of MPI\_NEIGHBOR\_ALLGATHERV.

# 8.7.2 Nonblocking Neighborhood Alltoall

MPI\_INEIGHBOR\_ALLTOALL(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype, comm, request)

IN	sendbuf	starting address of send buffer (choice)
IN	sendcount	number of elements sent to each neighbor (non-negative integer)
IN	sendtype	data type of send buffer elements (handle)
OUT	recvbuf	starting address of receive buffer (choice)
IN	recvcount	number of elements received from each neighbor (non-negative integer)
IN	recvtype	data type of receive buffer elements (handle)
IN	comm	communicator with topology structure (handle)
OUT	request	communication request (handle)

#### C binding

# Fortran 2008 binding

```
1
                TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
      2
                TYPE(MPI_Comm), INTENT(IN) :: comm
                TYPE(MPI_Request), INTENT(OUT) :: request
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
            MPI_Ineighbor_alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount,
#-...
                           recvtype, comm, request, ierror)
      7
                TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
      8
                INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
      9
                TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
      10
                TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
      11
                TYPE(MPI_Comm), INTENT(IN) :: comm
      12
                TYPE(MPI_Request), INTENT(OUT) :: request
      13
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
      14
      15
            Fortran binding
      16
            MPI_INEIGHBOR_ALLTOALL(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT,
      17
                           RECVTYPE, COMM, REQUEST, IERROR)
      18
                <type> SENDBUF(*), RECVBUF(*)
      19
                INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, REQUEST, IERROR
      20
                This call starts a nonblocking variant of MPI_NEIGHBOR_ALLTOALL.
      21
      22
      23
            MPI_INEIGHBOR_ALLTOALLV(sendbuf, sendcounts, sdispls, sendtype, recvbuf, recvcounts,
      24
                           rdispls, recvtype, comm, request)
      25
              IN
                       sendbuf
                                                     starting address of send buffer (choice)
      26
      27
              IN
                       sendcounts
                                                     non-negative integer array (of length outdegree)
                                                     specifying the number of elements to send to each
      28
      29
                                                     neighbor
      30
              IN
                        sdispls
                                                     integer array (of length outdegree). Entry i specifies
      31
                                                     the displacement (relative to sendbuf) from which
      32
                                                     send the outgoing data to neighbor j
      33
              IN.
                       sendtype
                                                     data type of send buffer elements (handle)
      34
              OUT
      35
                        recvbuf
                                                     starting address of receive buffer (choice)
      36
              IN
                        recvcounts
                                                     non-negative integer array (of length indegree)
      37
                                                     specifying the number of elements that are received
      38
                                                     from each neighbor
      39
              IN
                        rdispls
                                                     integer array (of length indegree). Entry i specifies
      40
                                                     the displacement (relative to recvbuf) at which to
      41
                                                     place the incoming data from neighbor i
      42
              IN
      43
                        recvtype
                                                     data type of receive buffer elements (handle)
      44
              IN
                        comm
                                                     communicator with topology structure (handle)
      45
              OUT
                                                     communication request (handle)
                        request
      46
      47
            C binding
      48
```

```
int MPI_Ineighbor_alltoallv(const void *sendbuf, const int sendcounts[],
              const int sdispls[], MPI_Datatype sendtype, void *recvbuf,
              const int recvcounts[], const int rdispls[],
             MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
int MPI_Ineighbor_alltoallv_c(const void *sendbuf,
                                                                                  6 #-...
             const MPI_Count sendcounts[], const MPI_Aint sdispls[],
                                                                                  7
             MPI_Datatype sendtype, void *recvbuf,
                                                                                  8
             const MPI_Count recvcounts[], const MPI_Aint rdispls[],
             MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
                                                                                  10
Fortran 2008 binding
MPI_Ineighbor_alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
                                                                                  12
             recvcounts, rdispls, recvtype, comm, request, ierror)
                                                                                  13
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                  14
                                                                                  15
    INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),
                                                                                  16
              recvcounts(*), rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                  18
    TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
                                                                                  19
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  20
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  21
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  22
MPI_Ineighbor_alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
                                                                                  23 #-...
             recvcounts, rdispls, recvtype, comm, request, ierror)
                                                                                  24
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                  25
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
                                                                                  26
              sendcounts(*), recvcounts(*)
                                                                                  27
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
                                                                                  28
              rdispls(*)
                                                                                  29
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                  30
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                  31
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  32
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  33
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  35
Fortran binding
                                                                                  36
MPI_INEIGHBOR_ALLTOALLV(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE, RECVBUF,
                                                                                  37
             RECVCOUNTS, RDISPLS, RECVTYPE, COMM, REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*),
              RECVTYPE, COMM, REQUEST, IERROR
    This call starts a nonblocking variant of MPI_NEIGHBOR_ALLTOALLV.
                                                                                  42
                                                                                  43
                                                                                  44
                                                                                  45
```

```
1
      MPI_INEIGHBOR_ALLTOALLW(sendbuf, sendcounts, sdispls, sendtypes, recvbuf, recvcounts,
2
                      rdispls, recvtypes, comm, request)
3
        IN
                  sendbuf
                                                starting address of send buffer (choice)
        IN
                  sendcounts
                                                non-negative integer array (of length outdegree)
                                                specifying the number of elements to send to each
6
                                                neighbor
        IN
                  sdispls
                                               integer array (of length outdegree). Entry j specifies
9
                                                the displacement in bytes (relative to sendbuf) from
10
                                                which to take the outgoing data destined for
11
                                                neighbor i (array of integers)
12
        IN
                  sendtypes
                                                array of datatypes (of length outdegree). Entry i
13
                                                specifies the type of data to send to neighbor i (array
14
                                                of handles)
15
                                               starting address of receive buffer (choice)
        OUT
                  recvbuf
16
17
        IN
                                                non-negative integer array (of length indegree)
                  recvcounts
18
                                                specifying the number of elements that are received
19
                                                from each neighbor
20
        IN
                  rdispls
                                                integer array (of length indegree). Entry i specifies
21
                                                the displacement in bytes (relative to recvbuf) at
22
                                                which to place the incoming data from neighbor i
23
                                                (array of integers)
24
        IN
                                                array of datatypes (of length indegree). Entry i
                  recvtypes
25
                                                specifies the type of data received from neighbor i
26
                                                (array of handles)
27
28
        IN
                                                communicator with topology structure (handle)
                  comm
29
        OUT
                  request
                                                communication request (handle)
30
31
      C binding
32
      int MPI_Ineighbor_alltoallw(const void *sendbuf, const int sendcounts[],
33
                      const MPI_Aint sdispls[], const MPI_Datatype sendtypes[],
34
                      void *recvbuf, const int recvcounts[],
35
                      const MPI_Aint rdispls[], const MPI_Datatype recvtypes[],
36
                     MPI_Comm comm, MPI_Request *request)
37
38
      int MPI_Ineighbor_alltoallw_c(const void *sendbuf,
39
                      const MPI_Count sendcounts[], const MPI_Aint sdispls[],
40
                      const MPI_Datatype sendtypes[], void *recvbuf,
41
                      const MPI_Count recvcounts[], const MPI_Aint rdispls[],
42
                      const MPI_Datatype recvtypes[], MPI_Comm comm,
43
                     MPI_Request *request)
44
      Fortran 2008 binding
45
      MPI_Ineighbor_alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
46
                     recvcounts, rdispls, recvtypes, comm, request, ierror)
47
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
48
```

<sup>11</sup> #-...

12

13

14

15

16

17

18

19

20

21

22

23 24

26

27

28

29

30 31

32

34

35

36

37

38 39

```
INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
              rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
              recvtypes(*)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Ineighbor_alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
             recvcounts, rdispls, recvtypes, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
              sendcounts(*), recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
              rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
              recvtypes(*)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

This call starts a nonblocking variant of MPI\_NEIGHBOR\_ALLTOALLW.

## 8.8 Persistent Neighborhood Communication on Process Topologies

Persistent variants of the neighborhood collective operations can offer significant performance benefits for programs with repetitive communication patterns. The semantics are similar to persistent collective operations as described in Section 6.13.

#-25 B.2.2: 3 8.8.1 Persistent Neighborhood Gather

```
#-25 <sup>1</sup>
     3
          MPI_NEIGHBOR_ALLGATHER_INIT(sendbuf, sendcount, sendtype, recvbuf, recvcount,
     5
                         recvtype, comm, info, request)
     6
            IN
                      sendbuf
                                                 starting address of send buffer (choice)
            IN
                      sendcount
                                                 number of elements sent to each neighbor
                                                 (non-negative integer)
     10
            IN
                      sendtype
                                                 data type of send buffer elements (handle)
            OUT
                      recvbuf
                                                 starting address of receive buffer (choice)
     12
     13
            IN
                                                 number of elements received from each neighbor
                      recvcount
     14
                                                 (non-negative integer)
     15
            IN
                      recvtype
                                                 data type of receive buffer elements (handle)
     16
                                                 communicator with topology structure (handle)
            IN
                      comm
     17
     18
            IN
                      info
                                                 info argument (handle)
     19
            OUT
                      request
                                                 communication request (handle)
     20
     ^{21}
          C binding
     22
          int MPI_Neighbor_allgather_init(const void *sendbuf, int sendcount,
     23
                         MPI_Datatype sendtype, void *recvbuf, int recvcount,
     ^{24}
                         MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
     25
                         MPI_Request *request)
     26
     27
          int MPI_Neighbor_allgather_init_c(const void *sendbuf, MPI_Count sendcount,
     28
                         MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
     29
                         MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
     30
                         MPI_Request *request)
     31
          Fortran 2008 binding
     32
          MPI_Neighbor_allgather_init(sendbuf, sendcount, sendtype, recvbuf,
     33
                         recvcount, recvtype, comm, info, request, ierror)
     34
               TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
     35
               INTEGER, INTENT(IN) :: sendcount, recvcount
     36
               TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
     37
               TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
     38
               TYPE(MPI_Comm), INTENT(IN) :: comm
     39
               TYPE(MPI_Info), INTENT(IN) :: info
     40
               TYPE(MPI_Request), INTENT(OUT) :: request
     41
               INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     42
     43
          MPI_Neighbor_allgather_init(sendbuf, sendcount, sendtype, recvbuf,
     44
                         recvcount, recvtype, comm, info, request, ierror)
     45
               TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
     46
               INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
     47
               TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
               TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
```

#-25

43

44

45

46

```
431
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                             3
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                             4
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_NEIGHBOR_ALLGATHER_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF,
               RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST,
                                                                                             10
                IERROR
                                                                                             12
    Creates a persistent collective communication request for the neighborhood allgather
                                                                                             13
operation.
                                                                                             14
                                                                                             15
MPI_NEIGHBOR_ALLGATHERV_INIT(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
                                                                                             16
               displs, recvtype, comm, info, request)
                                                                                             17
                                                                                             18
  IN
            sendbuf
                                         starting address of send buffer (choice)
                                                                                             19
  IN
            sendcount
                                         number of elements sent to each neighbor
                                                                                             20
                                         (non-negative integer)
                                                                                             21
  IN
            sendtype
                                         data type of send buffer elements (handle)
                                                                                             22
  OUT
            recvbuf
                                         starting address of receive buffer (choice)
                                                                                             23
                                                                                             ^{24}
  IN
            recvcounts
                                         non-negative integer array (of length indegree)
                                                                                             25
                                         containing the number of elements that are received
                                                                                             26
                                         from each neighbor
                                                                                             27
  IN
            displs
                                         integer array (of length indegree). Entry i specifies
                                                                                             28
                                         the displacement (relative to recvbuf) at which to
                                                                                             29
                                         place the incoming data from neighbor i
                                                                                             30
  IN
                                         data type of receive buffer elements (handle)
            recvtype
                                                                                             31
                                                                                             32
  IN
            comm
                                         communicator with topology structure (handle)
                                                                                             33
  IN
            info
                                         info argument (handle)
                                                                                             34
  OUT
            request
                                         communication request (handle)
                                                                                             35
                                                                                             36
                                                                                             37
int MPI_Neighbor_allgatherv_init(const void *sendbuf, int sendcount,
                                                                                             38
                                                                                             39
               MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
                                                                                             40
               const int displs[], MPI_Datatype recvtype, MPI_Comm comm,
               MPI_Info info, MPI_Request *request)
                                                                                             42
```

#### C binding

```
int MPI_Neighbor_allgatherv_init_c(const void *sendbuf,
             MPI_Count sendcount, MPI_Datatype sendtype, void *recvbuf,
             const MPI_Count recvcounts[], const MPI_Aint displs[],
             MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
             MPI_Request *request)
```

#### Fortran 2008 binding

```
MPI_Neighbor_allgatherv_init(sendbuf, sendcount, sendtype, recvbuf,
#-25 <sup>1</sup>
                        recvcounts, displs, recvtype, comm, info, request, ierror)
     3
              TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
              INTEGER, INTENT(IN) :: sendcount, displs(*)
              TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
     6
              TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
              INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
              TYPE(MPI_Comm), INTENT(IN) :: comm
              TYPE(MPI_Info), INTENT(IN) :: info
     10
              TYPE(MPI_Request), INTENT(OUT) :: request
     11
              INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     12
          MPI_Neighbor_allgatherv_init(sendbuf, sendcount, sendtype, recvbuf,
     13
                        recvcounts, displs, recvtype, comm, info, request, ierror)
     14
              TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
     15
              INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
     16
              TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
     17
              TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
              INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
     19
              INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: displs(*)
     20
              TYPE(MPI_Comm), INTENT(IN) :: comm
     ^{21}
              TYPE(MPI_Info), INTENT(IN) :: info
     22
              TYPE(MPI_Request), INTENT(OUT) :: request
     23
              INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     ^{24}
     25
          Fortran binding
     26
          MPI_NEIGHBOR_ALLGATHERV_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF,
     ^{27}
                        RECVCOUNTS, DISPLS, RECVTYPE, COMM, INFO, REQUEST, IERROR)
     28
              <type> SENDBUF(*), RECVBUF(*)
     29
              INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, COMM,
     30
                         INFO, REQUEST, IERROR
     31
              Creates a persistent collective communication request for the neighborhood allgathery
     32
          operation.
     33
     34
     35
     36
     37
     38
```

#-25

#### 8.8.2 Persistent Neighborhood Alltoall

```
3
                                                                                        4
MPI_NEIGHBOR_ALLTOALL_INIT(sendbuf, sendcount, sendtype, recvbuf, recvcount,
               recvtype, comm, info, request)
  IN
           sendbuf
                                      starting address of send buffer (choice)
  IN
           sendcount
                                      number of elements sent to each neighbor
                                      (non-negative integer)
                                      data type of send buffer elements (handle)
  IN
           sendtype
  OUT
           recvbuf
                                      starting address of receive buffer (choice)
                                                                                        12
  IN
                                      number of elements received from each neighbor
                                                                                        13
           recvcount
                                      (non-negative integer)
                                                                                        14
                                                                                        15
  IN
           recvtype
                                      data type of receive buffer elements (handle)
                                      communicator with topology structure (handle)
  IN
           comm
                                                                                        17
  IN
           info
                                      info argument (handle)
                                                                                        18
                                                                                        19
  OUT
           request
                                      communication request (handle)
                                                                                        20
                                                                                        21
C binding
                                                                                        22
int MPI_Neighbor_alltoall_init(const void *sendbuf, int sendcount,
                                                                                        23
              MPI_Datatype sendtype, void *recvbuf, int recvcount,
                                                                                        ^{24}
              MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
                                                                                        25
              MPI_Request *request)
                                                                                        26
int MPI_Neighbor_alltoall_init_c(const void *sendbuf, MPI_Count sendcount,
                                                                                        27
              MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
                                                                                        28
              MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
                                                                                        29
              MPI_Request *request)
                                                                                        30
                                                                                        31
Fortran 2008 binding
                                                                                        32
MPI_Neighbor_alltoall_init(sendbuf, sendcount, sendtype, recvbuf,
                                                                                        33
              recvcount, recvtype, comm, info, request, ierror)
                                                                                        34
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                        35
    INTEGER, INTENT(IN) :: sendcount, recvcount
                                                                                        36
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                        37
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                        38
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                        39
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                        42
                                                                                        43
MPI_Neighbor_alltoall_init(sendbuf, sendcount, sendtype, recvbuf,
                                                                                        44
              recvcount, recvtype, comm, info, request, ierror)
                                                                                        45
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                        46
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
```

TYPE(\*), DIMENSION(..), ASYNCHRONOUS :: recvbuf

```
#-25
                TYPE(MPI_Comm), INTENT(IN) :: comm
                TYPE(MPI_Info), INTENT(IN) :: info
      3
                TYPE(MPI_Request), INTENT(OUT) :: request
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
      5
           Fortran binding
      6
           MPI_NEIGHBOR_ALLTOALL_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF,
                           RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST, IERROR)
                <type> SENDBUF(*), RECVBUF(*)
      9
                INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST,
      10
                            IERROR
      11
     12
                Creates a persistent collective communication request for the neighborhood alltoall
     13
           operation.
     14
     15
           MPI_NEIGHBOR_ALLTOALLV_INIT(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
     16
                           recvcounts, rdispls, recvtype, comm, info, request)
     17
     18
             IN
                       sendbuf
                                                     starting address of send buffer (choice)
      19
             IN
                       sendcounts
                                                     non-negative integer array (of length outdegree)
     20
                                                     specifying the number of elements to send to each
     ^{21}
                                                     neighbor
     22
             IN
                       sdispls
                                                     integer array (of length outdegree). Entry i specifies
     23
                                                     the displacement (relative to sendbuf) from which
     24
                                                     send the outgoing data to neighbor j
     25
     26
             IN
                       sendtype
                                                     data type of send buffer elements (handle)
     27
                       recvbuf
                                                     starting address of receive buffer (choice)
             OUT
     28
             IN
                        recvcounts
                                                     non-negative integer array (of length indegree)
     29
                                                     specifying the number of elements that are received
     30
                                                     from each neighbor
     31
     32
             IN
                        rdispls
                                                     integer array (of length indegree). Entry i specifies
     33
                                                     the displacement (relative to recvbuf) at which to
     34
                                                     place the incoming data from neighbor i
     35
                                                     data type of receive buffer elements (handle)
             IN
                        recvtype
     36
             IN
                        comm
                                                     communicator with topology structure (handle)
     37
     38
             IN
                        info
                                                     info argument (handle)
     39
             OUT
                        request
                                                     communication request (handle)
      40
     41
           C binding
     42
           int MPI_Neighbor_alltoallv_init(const void *sendbuf,
     43
                           const int sendcounts[], const int sdispls[],
     44
                           MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
     45
                           const int rdispls[], MPI_Datatype recvtype, MPI_Comm comm,
     46
```

MPI\_Info info, MPI\_Request \*request)

 $45 \\ 46$ 

```
int MPI_Neighbor_alltoallv_init_c(const void *sendbuf,
                                                                                    #-25
              const MPI_Count sendcounts[], const MPI_Aint sdispls[],
             MPI_Datatype sendtype, void *recvbuf,
                                                                                  4
              const MPI_Count recvcounts[], const MPI_Aint rdispls[],
             MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
                                                                                  6
             MPI_Request *request)
Fortran 2008 binding
MPI_Neighbor_alltoallv_init(sendbuf, sendcounts, sdispls, sendtype,
             recvbuf, recvcounts, rdispls, recvtype, comm, info, request,
              ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                  12
    INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),
                                                                                  13
              recvcounts(*), rdispls(*)
                                                                                  14
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                  15
    TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
                                                                                  16
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  17
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                  18
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  19
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  20
                                                                                  21
MPI_Neighbor_alltoallv_init(sendbuf, sendcounts, sdispls, sendtype,
                                                                                  22
             recvbuf, recvcounts, rdispls, recvtype, comm, info, request,
                                                                                  23
              ierror)
                                                                                  ^{24}
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                  25
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
                                                                                  26
              sendcounts(*), recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
                                                                                  ^{27}
                                                                                  28
              rdispls(*)
                                                                                  29
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                  30
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                  31
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  32
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                  33
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  35
Fortran binding
                                                                                  36
MPI_NEIGHBOR_ALLTOALLV_INIT(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE,
                                                                                  37
             RECVBUF, RECVCOUNTS, RDISPLS, RECVTYPE, COMM, INFO, REQUEST,
                                                                                  38
             IERROR)
                                                                                  39
    <type> SENDBUF(*), RECVBUF(*)
                                                                                  40
    INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*),
              RECVTYPE, COMM, INFO, REQUEST, IERROR
                                                                                  42
                                                                                  43
    Creates a persistent collective communication request for the neighborhood alltoally
                                                                                  44
operation.
```

```
MPI_NEIGHBOR_ALLTOALLW_INIT(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
#-25 <sup>1</sup>
                            recvcounts, rdispls, recvtypes, comm, info, request)
      3
             IN
                        sendbuf
                                                       starting address of send buffer (choice)
             IN
                        sendcounts
                                                       non-negative integer array (of length outdegree)
                                                       specifying the number of elements to send to each
      6
                                                       neighbor
      8
             IN
                        sdispls
                                                       integer array (of length outdegree). Entry j specifies
      9
                                                       the displacement in bytes (relative to sendbuf) from
      10
                                                       which to take the outgoing data destined for
      11
                                                       neighbor i (array of integers).
      12
             IN
                        sendtypes
                                                       array of datatypes (of length outdegree). Entry i
      13
                                                       specifies the type of data to send to neighbor j (array
      14
                                                       of handles)
      15
                                                       starting address of receive buffer (choice)
              OUT
                        recvbuf
      16
      17
             IN
                                                       non-negative integer array (of length indegree)
                        recvcounts
      18
                                                       specifying the number of elements that are received
      19
                                                       from each neighbor
      20
             IN
                        rdispls
                                                       integer array (of length indegree). Entry i specifies
      ^{21}
                                                       the displacement in bytes (relative to recvbuf) at
      22
                                                       which to place the incoming data from neighbor i
      23
                                                       (array of integers)
      ^{24}
             IN
                                                       array of datatypes (of length indegree). Entry i
                        recvtypes
      25
                                                       specifies the type of data received from neighbor i
      26
                                                       (array of handles)
      27
      28
             IN
                                                       communicator with topology structure (handle)
                        comm
      29
                        info
             IN
                                                       info argument (handle)
      30
             OUT
                                                       communication request (handle)
                        request
      31
      32
      33
            C binding
      ^{34}
            int MPI_Neighbor_alltoallw_init(const void *sendbuf,
      35
                            const int sendcounts[], const MPI_Aint sdispls[],
                            const MPI_Datatype sendtypes[], void *recvbuf,
      36
                            const int recvcounts[], const MPI_Aint rdispls[],
      37
                            const MPI_Datatype recvtypes[], MPI_Comm comm, MPI_Info info,
      38
      39
                            MPI_Request *request)
      40
            int MPI_Neighbor_alltoallw_init_c(const void *sendbuf,
      41
                            const MPI_Count sendcounts[], const MPI_Aint sdispls[],
      42
                            const MPI_Datatype sendtypes[], void *recvbuf,
      43
                            const MPI_Count recvcounts[], const MPI_Aint rdispls[],
      44
                            const MPI_Datatype recvtypes[], MPI_Comm comm, MPI_Info info,
      45
                            MPI_Request *request)
      46
      47
           Fortran 2008 binding
```

47

```
MPI_Neighbor_alltoallw_init(sendbuf, sendcounts, sdispls, sendtypes,
                                                                                     #-25
              recvbuf, recvcounts, rdispls, recvtypes, comm, info, request,
              ierror)
                                                                                   4
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
                                                                                   6
              rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
                                                                                   9
              recvtypes(*)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                   10
                                                                                   11
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                   12
                                                                                   13
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                   14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   15
MPI_Neighbor_alltoallw_init(sendbuf, sendcounts, sdispls, sendtypes,
                                                                                   16
              recvbuf, recvcounts, rdispls, recvtypes, comm, info, request,
                                                                                   17
              ierror)
                                                                                   18
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                   19
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
                                                                                   20
              sendcounts(*), recvcounts(*)
                                                                                   21
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
                                                                                   22
              rdispls(*)
                                                                                   23
    TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
                                                                                   ^{24}
              recvtypes(*)
                                                                                   25
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                   26
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                   27
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                   28
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                   29
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   30
                                                                                   31
Fortran binding
                                                                                   32
MPI_NEIGHBOR_ALLTOALLW_INIT(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPES,
                                                                                   33
              RECVBUF, RECVCOUNTS, RDISPLS, RECVTYPES, COMM, INFO, REQUEST,
                                                                                   34
              IERROR)
                                                                                   35
    <type> SENDBUF(*), RECVBUF(*)
                                                                                   36
    INTEGER SENDCOUNTS(*), SENDTYPES(*), RECVCOUNTS(*), RECVTYPES(*), COMM,
                                                                                   37
              INFO, REQUEST, IERROR
                                                                                   38
    INTEGER(KIND=MPI_ADDRESS_KIND) SDISPLS(*), RDISPLS(*)
                                                                                   39
    Creates a persistent collective communication request for the neighborhood alltoallw
                                                                                   40
operation.
                                                                                   42
                                                                                   43
```

## 8.9 An Application Example

**Example 8.11** The example in Figures 8.4-8.7 shows how the grid definition and inquiry functions can be used in an application program. A partial differential equation, for instance the Poisson equation, is to be solved on a rectangular domain. First, the processes organize

t i k

themselves in a two-dimensional structure. Each process then inquires about the ranks of its neighbors in the four directions (up, down, right, left). The numerical problem is solved by an iterative method, the details of which are hidden in the subroutine relax.

In each relaxation step each process computes new values for the solution grid function at the points u(1:100,1:100) owned by the process. Then the values at inter-process boundaries have to be exchanged with neighboring processes. For example, the newly calculated values in u(1,1:100) must be sent into the halo cells u(101,1:100) of the left-hand neighbor with coordinates (own\_coord(1)-1,own\_coord(2)).



35 36 37

```
INTEGER ndims, num_neigh
LOGICAL reorder
                                                                                   2
PARAMETER (ndims=2, num_neigh=4, reorder=.true.)
INTEGER comm, comm_size, comm_cart, dims(ndims), ierr
                                                                                  4 #-...
INTEGER neigh_rank(num_neigh), own_coords(ndims), i, j, it
                                                                                  5
LOGICAL periods(ndims)
                                                                                   6
REAL u(0:101,0:101), f(0:101,0:101)
DATA dims / ndims * 0 /
comm = MPI_COMM_WORLD
CALL MPI_COMM_SIZE(comm, comm_size, ierr)
                                                                                  10
    Set process grid size and periodicity
                                                                                  11
CALL MPI_DIMS_CREATE(comm_size, ndims, dims, ierr)
                                                                                  12
periods(1) = .TRUE.
                                                                                  13
periods(2) = .TRUE.
                                                                                  14
    Create a grid structure in WORLD group and inquire about own position
CALL MPI_CART_CREATE(comm, ndims, dims, periods, reorder, &
                                                                                  16
                      comm_cart, ierr)
CALL MPI_CART_GET(comm_cart, ndims, dims, periods, own_coords, ierr)
i = own_coords(1)
                                                                                  19
j = own_coords(2)
                                                                                  20
! Look up the ranks for the neighbors. Own process coordinates are (i,j).
                                                                                  21
! Neighbors are (i-1,j), (i+1,j), (i,j-1), (i,j+1) modulo (dims(1),dims(2))
                                                                                  22
CALL MPI_CART_SHIFT(comm_cart, 0,1, neigh_rank(1), neigh_rank(2), ierr)
                                                                                  23
CALL MPI_CART_SHIFT(comm_cart, 1,1, neigh_rank(3), neigh_rank(4), ierr)
                                                                                  24
! Initialize the grid functions and start the iteration
CALL init(u, f)
                                                                                  26
DO it=1,100
                                                                                  27
   CALL relax(u, f)
                                                                                  28
       Exchange data with neighbor processes
                                                                                  29
   CALL exchange(u, comm_cart, neigh_rank, num_neigh)
                                                                                  30
END DO
CALL output(u)
```

Figure 8.4: Set-up of process structure for two-dimensional parallel Poisson solver.

35 36 37

47

```
SUBROUTINE exchange(u, comm_cart, neigh_rank, num_neigh)
       1
           REAL u(0:101,0:101)
       2
           INTEGER comm_cart, num_neigh, neigh_rank(num_neigh)
       3
           REAL sndbuf(100,num_neigh), rcvbuf(100,num_neigh)
           INTEGER ierr
           sndbuf(1:100,1) = u(1,1:100)
       6
           sndbuf(1:100,2) = u(100,1:100)
           sndbuf(1:100,3) = u(1:100, 1)
           sndbuf(1:100,4) = u(1:100,100)
       9
           CALL MPI_NEIGHBOR_ALLTOALL(sndbuf, 100, MPI_REAL, rcvbuf, 100, MPI_REAL, &
      10
                                       comm_cart, ierr)
           ! instead of
#-153 <sub>13</sub>
           ! CALL MPI_IRECV(rcvbuf(1,1),100,MPI_REAL, neigh_rank(1),..., rq(1), ierr)
           ! CALL MPI_ISEND(sndbuf(1,2),100,MPI_REAL, neigh_rank(2),..., rq(2), ierr)
B.2.1: 1 14
               Always pairing a receive from rank_source with a send to rank_dest
       15
               of the same direction in MPI_CART_SHIFT!
           ! CALL MPI_IRECV(rcvbuf(1,2),100,MPI_REAL, neigh_rank(2),..., rq(3), ierr)
       17
           ! CALL MPI_ISEND(sndbuf(1,1),100,MPI_REAL, neigh_rank(1),..., rq(4), ierr)
           ! CALL MPI_IRECV(rcvbuf(1,3),100,MPI_REAL, neigh_rank(3),..., rq(5), ierr)
       19
           ! CALL MPI_ISEND(sndbuf(1,4),100,MPI_REAL, neigh_rank(4),..., rq(6), ierr)
      20
           ! CALL MPI_IRECV(rcvbuf(1,4),100,MPI_REAL, neigh_rank(4),..., rq(7), ierr)
      21
           ! CALL MPI_ISEND(sndbuf(1,3),100,MPI_REAL, neigh_rank(3),..., rq(8), ierr)
      22
               Of course, one can first start all four IRECV and then all four ISEND,
      23
           (!)
               Or vice versa, but both in the sequence shown above. Otherwise, the
      ^{24}
               matching would be wrong for 2 or only 1 processes in a direction.
      25
           ! CALL MPI_WAITALL(2*num_neigh, rq, statuses, ierr)
           u(0,1:100) = rcvbuf(1:100,1)
      27
           u(101,1:100) = rcvbuf(1:100,2)
      28
           u(1:100, 0) = rcvbuf(1:100,3)
      29
           u(1:100,101) = rcvbuf(1:100,4)
      30
           END
      31
      32
      33
```

Figure 8.5: Communication routine with local data copying and sparse neighborhood all-to-all.

13

14

15

16

18

19

20

21

22

23

24

26

27

28

29

30

33 34 35

36

37 38 39

```
SUBROUTINE exchange(u, comm_cart, neigh_rank, num_neigh)
IMPLICIT NONE
USE MPI
REAL u(0:101,0:101)
INTEGER comm_cart, num_neigh, neigh_rank(num_neigh)
INTEGER sndcounts(num_neigh), sndtypes(num_neigh)
INTEGER rcvcounts(num_neigh), rcvtypes(num_neigh)
INTEGER (KIND=MPI_ADDRESS_KIND) lb, sizeofreal
INTEGER (KIND=MPI_ADDRESS_KIND) sdispls(num_neigh), rdispls(num_neigh)
INTEGER type_vec, ierr
! The following initialization need to be done only once
! before the first call of exchange.
CALL MPI_TYPE_GET_EXTENT(MPI_REAL, lb, sizeofreal, ierr)
CALL MPI_TYPE_VECTOR(100, 1, 102, MPI_REAL, type_vec, ierr)
CALL MPI_TYPE_COMMIT(type_vec, ierr)
sndtypes(1:2) = type_vec
sndcounts(1:2) = 1
sndtypes(3:4) = MPI_REAL
sndcounts(3:4) = 100
rcvtypes = sndtypes
rcvcounts = sndcounts
sdispls(1) = (1 + 1*102) * size of real! first element of u(1)
                                                                        1:100)
                    1*102) * sizeofreal ! first element of u(100
sdispls(2) = (100 +
sdispls(3) = (1 +
                    1*102) * sizeofreal ! first element of u( 1:100,
sdispls(4) = (1 + 100*102) * size of real! first element of u(
                                                                1:100,100
rdispls(1) = (0 +
                    1*102) * sizeofreal ! first element of u( 0
                     1*102) * sizeofreal ! first element of u(101
rdispls(2) = (101 +
rdispls(3) = (1 +
                     0*102) * sizeofreal ! first element of u( 1:100, 0
rdispls(4) = (1 + 101*102) * size of real! first element of u(1:100,101)
! the following communication has to be done in each call of exchange
CALL MPI_NEIGHBOR_ALLTOALLW(u, sndcounts, sdispls, sndtypes, &
                           u, rcvcounts, rdispls, rcvtypes, &
                            comm_cart, ierr)
! The following finalizing need to be done only once
! after the last call of exchange.
CALL MPI_TYPE_FREE(type_vec, ierr)
END
```

Figure 8.6: Communication routine with sparse neighborhood all-to-all-w and without local data copying.

```
INTEGER ndims, num_neigh
#-25
         LOGICAL reorder
         PARAMETER (ndims=2, num_neigh=4, reorder=.true.)
         INTEGER comm, comm_size, comm_cart, dims(ndims), it, ierr
         LOGICAL periods(ndims)
         REAL u(0:101,0:101), f(0:101,0:101)
     6
         DATA dims / ndims * 0 /
         INTEGER sndcounts(num_neigh), sndtypes(num_neigh)
         INTEGER rcvcounts(num_neigh), rcvtypes(num_neigh)
         INTEGER (KIND=MPI_ADDRESS_KIND) lb, sizeofreal
    10
         INTEGER (KIND=MPI_ADDRESS_KIND) sdispls(num_neigh), rdispls(num_neigh)
    11
         INTEGER type_vec, request, status
    12
         comm = MPI_COMM_WORLD
    13
         CALL MPI_COMM_SIZE(comm, comm_size, ierr)
    14
              Set process grid size and periodicity
    15
         CALL MPI_DIMS_CREATE(comm_size, ndims, dims, ierr)
     16
         periods(1) = .TRUE.
    ^{17}
         periods(2) = .TRUE.
    18
              Create a grid structure in WORLD group
    19
         CALL MPI_CART_CREATE(comm, ndims, dims, periods, reorder, &
    20
                                comm_cart, ierr)
    ^{21}
          ! Create datatypes for the neighborhood communication
    22
    23
          ! Insert code from example in Figure 7.4 to create and initialize
    ^{24}
          ! sndcounts, sdispls, sndtypes, rcvcounts, rdispls, and rcvtypes
    25
    26
          ! Initialize the neighborhood all-to-all-w operation
    27
         CALL MPI_NEIGHBOR_ALLTOALLW_INIT(u, sndcounts, sdispls, sndtypes, &
    28
                                            u, rcvcounts, rdispls, rcvtypes, &
    29
                                            comm_cart, info, request, ierr)
    30
          ! Initialize the grid functions and start the iteration
    31
         CALL init(u, f)
    32
         DO it=1,100
    33
                 Start data exchange with neighbor processes
    34
            CALL MPI_START(request, ierr)
    35
                 Compute inner cells
    36
             CALL relax_inner (u, f)
    37
                 Check on completion of neighbor exchange
    38
             CALL MPI_WAIT(request, status, ierr)
    39
                 Compute edge cells
    40
             CALL relax_edges(u, f)
    41
         END DO
    42
         CALL output(u)
    43
         CALL MPI_REQUEST_FREE(request, ierr)
    44
         CALL MPI_TYPE_FREE(type_vec, ierr)
    45
    46
    ^{47}
```

Figure 8.7: Two-dimensional parallel Poisson solver with persistent sparse neighborhood all-to-all-w and without local data copying.

## Chapter 9

# **MPI** Environmental Management

This chapter discusses routines for getting and, where appropriate, setting various parameters that relate to the MPI implementation and the execution environment (such as error handling). The procedures for entering and leaving the MPI execution environment are also described here.

## 9.1 Implementation Information

#### 9.1.1 Version Inquiries

In order to cope with changes to the MPI Standard, there are both compile-time and runtime ways to determine which version of the standard is in use in the environment one is using.

The "version" will be represented by two separate integers, for the version and subversion: In C,

```
#define MPI_VERSION 3
#define MPI_SUBVERSION 1
```

in Fortran,

```
INTEGER :: MPI_VERSION, MPI_SUBVERSION
PARAMETER (MPI_VERSION = 3)
PARAMETER (MPI_SUBVERSION = 1)
```

For runtime determination,

#### MPI\_GET\_VERSION(version, subversion)

```
OUT version version number (integer)
OUT subversion subversion number (integer)
```

#### C binding

```
int MPI_Get_version(int *version, int *subversion)
```

#### Fortran 2008 binding

MPI\_Get\_version(version, subversion, ierror)

12 13 14

15

18 19

20 21

22

26

27 28

29

30

34

35 36

37

42

43

```
INTEGER, INTENT(OUT) :: version, subversion
INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI_GET_VERSION(VERSION, SUBVERSION, IERROR)
INTEGER VERSION, SUBVERSION, IERROR
```

MPI\_GET\_VERSION can be called at any time in an MPI program. This function must always be thread-safe, as defined in Section 11.6. Valid (MPI\_VERSION, MPI\_SUBVERSION) pairs in this and previous versions of the MPI standard are (4,0), (3,1), (3,0), (2,2), (2,1), (2,0), and (1,2).

#### MPI\_GET\_LIBRARY\_VERSION(version, resultlen)

```
OUT version version number (string)
OUT resultlen Length (in printable characters) of the result returned in version (integer)
```

#### C binding

```
int MPI_Get_library_version(char *version, int *resultlen)
```

#### Fortran 2008 binding

```
MPI_Get_library_version(version, resultlen, ierror)
    CHARACTER(LEN=MPI_MAX_LIBRARY_VERSION_STRING), INTENT(OUT) :: version
    INTEGER, INTENT(OUT) :: resultlen
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_GET_LIBRARY_VERSION(VERSION, RESULTLEN, IERROR)
CHARACTER*(*) VERSION
INTEGER RESULTLEN, IERROR
```

This routine returns a string representing the version of the MPI library. The version argument is a character string for maximum flexibility.

Advice to implementors. An implementation of MPI should return a different string for every change to its source code or build that could be visible to the user. (End of advice to implementors.)

The argument version must represent storage that is

MPI\_MAX\_LIBRARY\_VERSION\_STRING characters long. MPI\_GET\_LIBRARY\_VERSION may write up to this many characters into version.

The number of characters actually written is returned in the output argument, resultlen. In C, a null character is additionally stored at version[resultlen]. The value of resultlen cannot be larger than MPI\_MAX\_LIBRARY\_VERSION\_STRING - 1. In Fortran, version is padded on the right with blank characters. The value of resultlen cannot be larger than MPI\_MAX\_LIBRARY\_VERSION\_STRING.

MPI\_GET\_LIBRARY\_VERSION can be called at any time in an MPI program. This function must always be thread-safe, as defined in Section 11.6.

#### 9.1.2 Environmental Inquiries

When using the World Model (Section 11.2), a set of attributes that describe the execution environment is attached to the communicator MPI\_COMM\_WORLD when MPI is initialized. The values of these attributes can be inquired by using the function

MPI\_COMM\_GET\_ATTR described in Section 7.7 and in Section 19.3.7. It is erroneous to delete these attributes, free their keys, or change their values.

The list of predefined attribute keys include

MPI\_TAG\_UB Upper bound for tag value.

MPI\_HOST Host process rank, if such exists, MPI\_PROC\_NULL, otherwise.

MPI\_IO rank of a node that has regular I/O facilities (possibly myrank). Nodes in the same communicator may return different values for this parameter.

MPI\_WTIME\_IS\_GLOBAL Boolean variable that indicates whether clocks are synchronized.

When using the Sessions Model (Section 11.3), only the MPI\_TAG\_UB attribute is available.

Vendors may add implementation-specific parameters (such as node number, real memory size, virtual memory size, etc.)

These predefined attributes do not change value between MPI initialization (MPI\_INIT) and MPI completion (MPI\_FINALIZE), and cannot be updated or deleted by users.

Advice to users. Note that in the C binding, the value returned by these attributes is a pointer to an int containing the requested value. (End of advice to users.)

The required parameter values are discussed in more detail below:

#### Tag Values

Tag values range from 0 to the value returned for MPI\_TAG\_UB, inclusive. These values are guaranteed to be unchanging during the execution of an MPI program. In addition, the tag upper bound value must be at least 32767. An MPI implementation is free to make the value of MPI\_TAG\_UB larger than this; for example, the value  $2^{30} - 1$  is also a valid value for MPI\_TAG\_UB.

In the Sessions Model, the attribute  $MPI\_TAG\_UB$  is attached to all communicators created by  $MPI\_COMM\_CREATE\_FROM\_GROUP$  and

MPI\_INTERCOMM\_CREATE\_FROM\_GROUPS, with the same value on all MPI processes in the communicator. In the World Model, the attribute MPI\_TAG\_UB has the same value on all processes of MPI\_COMM\_WORLD.

#### Host Rank

The value returned for MPI\_HOST gets the rank of the HOST process in the group associated with communicator MPI\_COMM\_WORLD, if there is such. MPI\_PROC\_NULL is returned if there is no host. MPI does not specify what it means for a process to be a HOST, nor does it requires that a HOST exists.

The attribute MPI\_HOST has the same value on all processes of MPI\_COMM\_WORLD.

IO Rank

 The value returned for MPI\_IO is the rank of a processor that can provide language-standard I/O facilities. For Fortran, this means that all of the Fortran I/O operations are supported (e.g., OPEN, REWIND, WRITE). For C, this means that all of the ISO C I/O operations are supported (e.g., fopen, fprintf, lseek).

If every process can provide language-standard I/O, then the value MPI\_ANY\_SOURCE will be returned. Otherwise, if the calling process can provide language-standard I/O, then its rank will be returned. Otherwise, if some process can provide language-standard I/O then the rank of one such process will be returned. The same value need not be returned by all processes. If no process can provide language-standard I/O, then the value MPI\_PROC\_NULL will be returned.

Advice to users. Note that input is not collective, and this attribute does not indicate which process can or does provide input. (End of advice to users.)

#### Clock Synchronization

The value returned for MPI\_WTIME\_IS\_GLOBAL is 1 if clocks at all processes in MPI\_COMM\_WORLD are synchronized, 0 otherwise. A collection of clocks is considered synchronized if explicit effort has been taken to synchronize them. The expectation is that the variation in time, as measured by calls to MPI\_WTIME, will be less then one half the round-trip time for an MPI message of length zero. If time is measured at a process just before a send and at another process just after a matching receive, the second time should be always higher than the first one.

The attribute MPI\_WTIME\_IS\_GLOBAL need not be present when the clocks are not synchronized (however, the attribute key MPI\_WTIME\_IS\_GLOBAL is always valid). This attribute may be associated with communicators other than MPI\_COMM\_WORLD.

The attribute  $MPI\_WTIME\_IS\_GLOBAL$  has the same value on all processes of  $MPI\_COMM\_WORLD$ .

Inquire Processor Name

#### MPI\_GET\_PROCESSOR\_NAME(name, resultlen)

OUT name A unique specifier for the actual (as opposed to virtual) node.

OUT resultlen Length (in printable characters) of the result returned in name

#### C binding

```
int MPI_Get_processor_name(char *name, int *resultlen)
```

#### Fortran 2008 binding

```
MPI_Get_processor_name(name, resultlen, ierror)
    CHARACTER(LEN=MPI_MAX_PROCESSOR_NAME), INTENT(OUT) :: name
    INTEGER, INTENT(OUT) :: resultlen
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
Fortran binding
MPI_GET_PROCESSOR_NAME(NAME, RESULTLEN, IERROR)
CHARACTER*(*) NAME
```

INTEGER RESULTLEN, IERROR

This routine returns the name of the processor on which it was called at the moment of the call. The name is a character string for maximum flexibility. From this value it must be possible to identify a specific piece of hardware; possible values include "processor 9 in rack 4 of mpp.cs.org" and "231" (where 231 is the actual processor number in the running homogeneous system). The argument name must represent storage that is at least MPI\_MAX\_PROCESSOR\_NAME characters long. MPI\_GET\_PROCESSOR\_NAME may write up to this many characters into name.

The number of characters actually written is returned in the output argument, resultlen. In C, a null character is additionally stored at name[resultlen]. The value of resultlen cannot be larger than MPI\_MAX\_PROCESSOR\_NAME-1. In Fortran, name is padded on the right with blank characters. The value of resultlen cannot be larger than MPI\_MAX\_PROCESSOR\_NAME.

Rationale. This function allows MPI implementations that do process migration to return the current processor. Note that nothing in MPI requires or defines process migration; this definition of MPI\_GET\_PROCESSOR\_NAME simply allows such an implementation. (End of rationale.)

Advice to users. The user must provide at least MPI\_MAX\_PROCESSOR\_NAME space to write the processor name—processor names can be this long. The user should examine the output argument, resultlen, to determine the actual length of the name. (End of advice to users.)

## 9.2 Memory Allocation

In some systems, message-passing and remote-memory-access (RMA) operations run faster when accessing specially allocated memory (e.g., memory that is shared by the other processes in the communicating group on an SMP). MPI provides a mechanism for allocating and freeing such special memory. The use of such memory for message-passing or RMA is not mandatory, and this memory can be used without restrictions as any other dynamically allocated memory. However, implementations may restrict the use of some RMA functionality as defined in Section 12.5.3.

#### MPI\_ALLOC\_MEM(size, info, baseptr)

IN	size	size of memory segment in bytes (non-negative integer)
IN	info	info argument (handle)
OUT	baseptr	pointer to beginning of memory segment allocated

#### C binding

int MPI\_Alloc\_mem(MPI\_Aint size, MPI\_Info info, void \*baseptr)

#### Fortran 2008 binding

31

32

33

34

35

36

37

38

39

40

41

42

43

```
2
         USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
3
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
4
         TYPE(MPI_Info), INTENT(IN) :: info
5
         TYPE(C_PTR), INTENT(OUT) :: baseptr
6
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
     MPI_ALLOC_MEM(SIZE, INFO, BASEPTR, IERROR)
9
         INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
10
         INTEGER INFO, IERROR
11
12
         If the Fortran compiler provides TYPE(C_PTR), then the following generic interface must
13
     be provided in the mpi module and should be provided in mpif.h through overloading,
14
     i.e., with the same routine name as the routine with INTEGER(KIND=MPI_ADDRESS_KIND)
15
     BASEPTR, but with a different specific procedure name:
16
17
     INTERFACE MPI_ALLOC_MEM
18
         SUBROUTINE MPI_ALLOC_MEM(SIZE, INFO, BASEPTR, IERROR)
19
             IMPORT :: MPI_ADDRESS_KIND
             INTEGER INFO, IERROR
20
21
             INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
22
         END SUBROUTINE
23
         SUBROUTINE MPI_ALLOC_MEM_CPTR(SIZE, INFO, BASEPTR, IERROR)
24
             USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
             IMPORT :: MPI_ADDRESS_KIND
26
             INTEGER :: INFO, IERROR
27
             INTEGER(KIND=MPI_ADDRESS_KIND) ::
                                                   SIZE
             TYPE(C_PTR) ::
                              BASEPTR
28
29
         END SUBROUTINE
30
     END INTERFACE
```

MPI\_Alloc\_mem(size, info, baseptr, ierror)

The base procedure name of this overloaded function is MPI\_ALLOC\_MEM\_CPTR. The implied specific procedure names are described in Section 19.1.5.

By default, the allocated memory shall be aligned to at least the alignment required for load/store accesses of any datatype corresponding to a predefined MPI datatype. The info argument may be used to specify a desired alternative minimum alignment in bytes for the allocated memory by setting the value of the key "mpi\_minimum\_memory\_alignment" to an integral number equal to a power of two. An implementation may ignore values smaller than the default required alignment. The info argument can also be used to provide directives that control the desired location of the allocated memory. Such a directive does not affect the semantics of the call. The corresponding info values are implementation-dependent. A null directive value of info = MPI\_INFO\_NULL is always valid.

The function MPI\_ALLOC\_MEM may return an error code of class MPI\_ERR\_NO\_MEM to indicate it failed because memory is exhausted.

```
MPI_FREE_MEM(base)

IN base initial address of memory segment allocated by MPI_ALLOC_MEM (choice)

C binding int MPI_Free_mem(void *base)

Fortran 2008 binding 
MPI_Free_mem(base, ierror) 
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: base INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding 
MPI_FREE_MEM(BASE, IERROR) 
    <type> BASE(*) 
    INTEGER IERROR
```

The function MPI\_FREE\_MEM may return an error code of class MPI\_ERR\_BASE to indicate an invalid base argument.

Rationale. The C bindings of MPI\_ALLOC\_MEM and MPI\_FREE\_MEM are similar to the bindings for the malloc and free C library calls: a call to MPI\_Alloc\_mem(..., &base) should be paired with a call to MPI\_Free\_mem(base) (one less level of indirection). Both arguments are declared to be of same type void\* so as to facilitate type casting. The Fortran binding is consistent with the C bindings: the Fortran MPI\_ALLOC\_MEM call returns in baseptr the TYPE(C\_PTR) pointer or the (integer valued) address of the allocated memory. The base argument of MPI\_FREE\_MEM is a choice argument, which passes (a reference to) the variable stored at that location. (End of rationale.)

Advice to implementors. If MPI\_ALLOC\_MEM allocates special memory, then a design similar to the design of C malloc and free functions has to be used, in order to find out the size of a memory segment, when the segment is freed. If no special memory is used, MPI\_ALLOC\_MEM simply invokes malloc, and MPI\_FREE\_MEM invokes free.

A call to MPI\_ALLOC\_MEM can be used in shared memory systems to allocate memory in a shared memory segment. (*End of advice to implementors*.)

**Example 9.1** Example of use of MPI\_ALLOC\_MEM, in Fortran with TYPE(C\_PTR) pointers. We assume 4-byte REALs.

```
size = 4 * shape(1) * shape(2) ! assuming 4 bytes per REAL

CALL MPI_Alloc_mem(size,MPI_INFO_NULL,p,ierr) ! memory is allocated and

CALL C_F_POINTER(p, a, shape) ! intrinsic ! now accessible via a(i,j)

! in ISO_C_BINDING

a(3,5) = 2.71

CALL MPI_Free_mem(a, ierr) ! memory is freed
```

**Example 9.2** Example of use of MPI\_ALLOC\_MEM, in Fortran with non-standard *Cray-pointers*. We assume 4-byte REALs, and assume that these pointers are address-sized.

```
REAL A

POINTER (P, A(100,100)) ! no memory is allocated

INTEGER(KIND=MPI_ADDRESS_KIND) SIZE

SIZE = 4*100*100

CALL MPI_ALLOC_MEM(SIZE, MPI_INFO_NULL, P, IERR)
! memory is allocated
...

A(3,5) = 2.71
...

CALL MPI_FREE_MEM(A, IERR) ! memory is freed
```

This code is not Fortran 77 or Fortran 90 code. Some compilers may not support this code or need a special option, e.g., the GNU gFortran compiler needs -fcray-pointer.

Advice to implementors. Some compilers map Cray-pointers to address-sized integers, some to TYPE(C\_PTR) pointers (e.g., Cray Fortran, version 7.3.3). From the user's viewpoint, this mapping is irrelevant because Examples 9.2 should work correctly with an MPI-3.0 (or later) library if Cray-pointers are available. (End of advice to implementors.)

#### Example 9.3 Same example, in C.

```
float (* f)[100][100];
/* no memory is allocated */
MPI_Alloc_mem(sizeof(float)*100*100, MPI_INFO_NULL, &f);
/* memory allocated */
...
(*f)[5][3] = 2.71;
...
MPI_Free_mem(f);
```

## 9.3 Error Handling

An MPI implementation may be unable or choose not to handle some failures that occur during MPI calls. These can include failures that generate exceptions or traps, such as floating point errors or access violations. The set of failures that are handled by MPI is implementation-dependent. Each such failure causes an error to be raised.

The above text takes precedence over any text on error handling within this document. Specifically, text that states that errors will be handled should be read as may be handled. More background information about how MPI treats errors can be found in Section 2.8.

A user can associate error handlers to four types of objects: communicators, windows, files, and sessions. The specified error handling routine will be used for any error that occurs during a call to MPI for the respective object. MPI calls that are not related to any MPI objects are considered to be attached to the communicator MPI\_COMM\_SELF. When MPI\_COMM\_SELF is not initialized (i.e., before MPI\_INIT / MPI\_INIT\_THREAD or after MPI\_FINALIZE) the error raises the initial error handler (set during the launch operation, see 11.8.4). The attachment of error handlers to objects is purely local: different processes may attach different error handlers to corresponding objects.

Several predefined error handlers are available in MPI:

- MPI\_ERRORS\_ARE\_FATAL The handler, when called, causes the program to abort all connected MPI processes. This is similar to calling MPI\_ABORT using a communicator containing all connected processes with an implementation-specific value as the errorcode argument.
- MPI\_ERRORS\_ABORT The handler, when called, is invoked on a communicator in a manner similar to calling MPI\_ABORT on that communicator. If the error handler is invoked on an window or file, it is similar to calling MPI\_ABORT using a communicator containing the group of MPI processes associated with the window or file, respectively. If the error handler is invoked on a session, the operation aborts only the local MPI process. In all cases, the value that would be provided as the errorcode argument to MPI\_ABORT is implementation-specific.
- MPI\_ERRORS\_RETURN The handler has no effect other than returning the error code to the user.

Advice to implementors. The implementation-specific error information resulting from MPI\_ERRORS\_ARE\_FATAL and MPI\_ERRORS\_ABORT provided to the invoking environment should be meaningful to the end-user, for example a predefined error class. (End of advice to implementors.)

Implementations may provide additional predefined error handlers and programmers can code their own error handlers.

Unless otherwise requested, the error handler MPI\_ERRORS\_ARE\_FATAL is set as the default initial error handler and associated with predefined communicators. Thus, if the user chooses not to control error handling, every error that MPI handles is treated as fatal. Since (almost) all MPI calls return an error code, a user may choose to handle errors in its main code, by testing the return code of MPI calls and executing a suitable recovery code when the call was not successful. In this case, the error handler MPI\_ERRORS\_RETURN will be used. Usually it is more convenient and more efficient not to test for errors after each MPI call, and have such error handled by a non-trivial MPI error handler. Note that unlike predefined communicators, windows and files do not inherit from the initial error handler, as defined in Sections 12.6 and 14.7 respectively.

When an error is raised, MPI will provide the user information about that error using an error code. Some errors might prevent MPI from completing further API calls successfully and those functions will continue to report errors until the cause of the error is corrected

or the user terminates the application. The user can make the determination of whether or not to attempt to continue when handling such an error.

Advice to users. For example, users may be unable to correct errors corresponding to some error classes, such as MPI\_ERR\_INTERN. Such errors may cause subsequent MPI calls to complete in error. (End of advice to users.)

Advice to implementors. A high-quality implementation will, to the greatest possible extent, circumscribe the impact of an error, so that normal processing can continue after an error handler was invoked. The implementation documentation will provide information on the possible effect of each class of errors and available recovery actions. (End of advice to implementors.)

An MPI error handler is an opaque object, which is accessed by a handle. MPI calls are provided to create new error handlers, to associate error handlers with objects, and to test which error handler is associated with an object. C has distinct typedefs for user defined error handling callback functions that accept communicator, file, window, and session arguments. In Fortran there are four user routines.

An error handler object is created by a call to MPI\_XXX\_CREATE\_ERRHANDLER, where XXX is, respectively, COMM, WIN, FILE, or SESSION.

An error handler is attached to a communicator, window, file, or session by a call to MPI\_XXX\_SET\_ERRHANDLER. The error handler must be either a predefined error handler, or an error handler that was created by a call to MPI\_XXX\_CREATE\_ERRHANDLER, with matching XXX. An error handler can also be attached to a session using the errorhandler argument to MPI\_SESSION\_INIT. The predefined error handlers MPI\_ERRORS\_RETURN and MPI\_ERRORS\_ARE\_FATAL can be attached to communicators, windows, files, or sessions.

The error handler currently associated with a communicator, window, file, or session can be retrieved by a call to MPI\_XXX\_GET\_ERRHANDLER.

The MPI function MPI\_ERRHANDLER\_FREE can be used to free an error handler that was created by a call to MPI\_XXX\_CREATE\_ERRHANDLER.

MPI\_XXX\_GET\_ERRHANDLER behave as if a new error handler object is created. That is, once the error handler is no longer needed, MPI\_ERRHANDLER\_FREE should be called with the error handler returned from MPI\_XXX\_GET\_ERRHANDLER to mark the error handler for deallocation. This provides behavior similar to that of MPI\_COMM\_GROUP and MPI\_GROUP\_FREE.

Advice to implementors. High-quality implementations should raise an error when an error handler that was created by a call to MPI\_XXX\_CREATE\_ERRHANDLER is attached to an object of the wrong type with a call to MPI\_YYY\_SET\_ERRHANDLER. To do so, it is necessary to maintain, with each error handler, information on the typedef of the associated user function. (End of advice to implementors.)

The syntax for these calls is given below.

13

14

15

16

18

19 20

22

24

26

27

31

38

39

41

42

43

44

45

46

#### 9.3.1 Error Handlers for Communicators

```
MPI_COMM_CREATE_ERRHANDLER(comm_errhandler_fn, errhandler)
 IN
           comm_errhandler_fn
                                      user defined error handling procedure (function)
 OUT
           errhandler
                                      MPI error handler (handle)
C binding
int MPI_Comm_create_errhandler(
              MPI_Comm_errhandler_function *comm_errhandler_fn,
              MPI_Errhandler *errhandler)
Fortran 2008 binding
MPI_Comm_create_errhandler(comm_errhandler_fn, errhandler, ierror)
    PROCEDURE(MPI_Comm_errhandler_function), INTENT(IN) ::
               comm_errhandler_fn
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
                                                                                       21
MPI_COMM_CREATE_ERRHANDLER(COMM_ERRHANDLER_FN, ERRHANDLER, IERROR)
    EXTERNAL COMM_ERRHANDLER_FN
                                                                                       23
    INTEGER ERRHANDLER, IERROR
    Creates an error handler that can be attached to communicators.
    The user routine should be, in C, a function of type MPI_Comm_errhandler_function, which
is defined as
typedef void MPI_Comm_errhandler_function(MPI_Comm *comm, int *error_code,
                                                                                       28
                                                                                       29
                                                                                       30
    The first argument is the communicator in use. The second is the error code to be
returned by the MPI routine that raised the error. If the routine would have returned
MPI_ERR_IN_STATUS, it is the error code returned in the status for the request that caused
                                                                                      33
the error handler to be invoked. The remaining arguments are "varargs" arguments whose
                                                                                      34
number and meaning is implementation-dependent. An implementation should clearly doc-
                                                                                       35
ument these arguments. Addresses are used so that the handler may be written in Fortran.
                                                                                       36
With the Fortran mpi_f08 module, the user routine comm_errhandler_fn should be of the
                                                                                       37
form:
ABSTRACT INTERFACE
  SUBROUTINE MPI_Comm_errhandler_function(comm, error_code)
    TYPE(MPI_Comm) :: comm
    INTEGER :: error_code
With the Fortran mpi module and mpif.h, the user routine COMM_ERRHANDLER_FN
should be of the form:
```

SUBROUTINE COMM\_ERRHANDLER\_FUNCTION(COMM, ERROR\_CODE)

INTEGER COMM, ERROR\_CODE

47

48

Fortran binding

The variable argument list is provided because it provides an ISO-Rationale. 2 standard hook for providing additional information to the error handler; without this hook, ISO C prohibits additional arguments. (End of rationale.) A newly created communicator inherits the error handler that Advice to users. is associated with the "parent" communicator. In particular, the user can specify a "global" error handler for all communicators by associating this handler with the communicator MPI\_COMM\_WORLD immediately after initialization. (End of advice to users.) 10 11 12 MPI\_COMM\_SET\_ERRHANDLER(comm, errhandler) 13 **INOUT** comm communicator (handle) 14 15 new error handler for communicator (handle) IN errhandler 16 17 C binding 18 int MPI\_Comm\_set\_errhandler(MPI\_Comm comm, MPI\_Errhandler errhandler) 19 Fortran 2008 binding 20 MPI\_Comm\_set\_errhandler(comm, errhandler, ierror) 21 TYPE(MPI\_Comm), INTENT(IN) :: comm 22 TYPE(MPI\_Errhandler), INTENT(IN) :: errhandler 23 INTEGER, OPTIONAL, INTENT(OUT) :: ierror 24 25 Fortran binding 26 MPI\_COMM\_SET\_ERRHANDLER(COMM, ERRHANDLER, IERROR) 27 INTEGER COMM, ERRHANDLER, IERROR 28 Attaches a new error handler to a communicator. The error handler must be either 29 a predefined error handler, or an error handler created by a call to 30 31 MPI\_COMM\_CREATE\_ERRHANDLER. 32 33 MPI\_COMM\_GET\_ERRHANDLER(comm, errhandler) 34 ĪN 35 communicator (handle) comm 36 OUT errhandler error handler currently associated with 37 communicator (handle) 38 39 C binding 40 int MPI\_Comm\_get\_errhandler(MPI\_Comm comm, MPI\_Errhandler \*errhandler) 41 42 Fortran 2008 binding 43 MPI\_Comm\_get\_errhandler(comm, errhandler, ierror) 44 TYPE(MPI\_Comm), INTENT(IN) :: comm 45 TYPE(MPI\_Errhandler), INTENT(OUT) :: errhandler 46 INTEGER, OPTIONAL, INTENT(OUT) :: ierror

be of the form:

INTEGER WIN, ERROR\_CODE

44

45

46

```
MPI_COMM_GET_ERRHANDLER(COMM, ERRHANDLER, IERROR)
    INTEGER COMM, ERRHANDLER, IERROR
    Retrieves the error handler currently associated with a communicator.
    For example, a library function may register at its entry point the current error handler
for a communicator, set its own private error handler for this communicator, and restore
before exiting the previous error handler.
9.3.2 Error Handlers for Windows
MPI_WIN_CREATE_ERRHANDLER(win_errhandler_fn, errhandler)
                                                                                        12
                                                                                        13
  IN
           win_errhandler_fn
                                       user defined error handling procedure (function)
                                                                                        14
  OUT
           errhandler
                                       MPI error handler (handle)
                                                                                        15
                                                                                        16
C binding
int MPI_Win_create_errhandler(
                                                                                        18
               MPI_Win_errhandler_function *win_errhandler_fn,
                                                                                        19
               MPI_Errhandler *errhandler)
                                                                                        20
                                                                                        21
Fortran 2008 binding
                                                                                        22
MPI_Win_create_errhandler(win_errhandler_fn, errhandler, ierror)
    PROCEDURE(MPI_Win_errhandler_function), INTENT(IN) :: win_errhandler_fn
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                        26
Fortran binding
                                                                                        27
MPI_WIN_CREATE_ERRHANDLER(WIN_ERRHANDLER_FN, ERRHANDLER, IERROR)
                                                                                        28
    EXTERNAL WIN_ERRHANDLER_FN
                                                                                        29
    INTEGER ERRHANDLER, IERROR
                                                                                        30
    Creates an error handler that can be attached to a window object. The user routine
should be, in C, a function of type MPI_Win_errhandler_function which is defined as
typedef void MPI_Win_errhandler_function(MPI_Win *win, int *error_code,
                                                                                        34
               ...);
                                                                                        35
    The first argument is the window in use, the second is the error code to be returned.
                                                                                        36
With the Fortran mpi_f08 module, the user routine win_errhandler_fn should be of the form:
                                                                                        37
ABSTRACT INTERFACE
  SUBROUTINE MPI_Win_errhandler_function(win, error_code)
    TYPE(MPI_Win) :: win
    INTEGER :: error_code
                                                                                        41
                                                                                        42
With the Fortran mpi module and mpif.h, the user routine WIN_ERRHANDLER_FN should
                                                                                        43
```

SUBROUTINE WIN\_ERRHANDLER\_FUNCTION(WIN, ERROR\_CODE)

```
MPI_WIN_SET_ERRHANDLER(win, errhandler)
2
       INOUT
                                           window object (handle)
                win
3
       IN
                errhandler
                                           new error handler for window (handle)
5
6
     C binding
     int MPI_Win_set_errhandler(MPI_Win win, MPI_Errhandler errhandler)
7
     Fortran 2008 binding
9
     MPI_Win_set_errhandler(win, errhandler, ierror)
10
         TYPE(MPI_Win), INTENT(IN) :: win
11
         TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
12
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
14
     Fortran binding
15
     MPI_WIN_SET_ERRHANDLER(WIN, ERRHANDLER, IERROR)
16
         INTEGER WIN, ERRHANDLER, IERROR
17
         Attaches a new error handler to a window. The error handler must be either a pre-
     defined error handler, or an error handler created by a call to
19
     MPI_WIN_CREATE_ERRHANDLER.
20
21
22
     MPI_WIN_GET_ERRHANDLER(win, errhandler)
23
       IN
                                           window object (handle)
                win
24
       OUT
                errhandler
                                           error handler currently associated with window
25
26
                                           (handle)
27
28
     C binding
29
     int MPI_Win_get_errhandler(MPI_Win win, MPI_Errhandler *errhandler)
30
     Fortran 2008 binding
31
     MPI_Win_get_errhandler(win, errhandler, ierror)
32
         TYPE(MPI_Win), INTENT(IN) :: win
         TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
34
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
35
36
     Fortran binding
37
     MPI_WIN_GET_ERRHANDLER(WIN, ERRHANDLER, IERROR)
38
         INTEGER WIN, ERRHANDLER, IERROR
39
         Retrieves the error handler currently associated with a window.
```

```
9.3.3
      Error Handlers for Files
MPI_FILE_CREATE_ERRHANDLER(file_errhandler_fn, errhandler)
           file_errhandler_fn
 IN
                                      user defined error handling procedure (function)
 OUT
           errhandler
                                       MPI error handler (handle)
C binding
int MPI_File_create_errhandler(
              MPI_File_errhandler_function *file_errhandler_fn,
                                                                                        12
              MPI_Errhandler *errhandler)
                                                                                        13
Fortran 2008 binding
                                                                                        14
MPI_File_create_errhandler(file_errhandler_fn, errhandler, ierror)
    PROCEDURE(MPI_File_errhandler_function), INTENT(IN) ::
                                                                                        16
               file_errhandler_fn
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
                                                                                        18
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                        19
                                                                                        20
Fortran binding
                                                                                        21
MPI_FILE_CREATE_ERRHANDLER(FILE_ERRHANDLER_FN, ERRHANDLER, IERROR)
                                                                                        22
    EXTERNAL FILE_ERRHANDLER_FN
                                                                                        23
    INTEGER ERRHANDLER, IERROR
    Creates an error handler that can be attached to a file object. The user routine should
be, in C, a function of type MPI_File_errhandler_function, which is defined as
typedef void MPI_File_errhandler_function(MPI_File *file, int *error_code,
                                                                                        27
               ...);
                                                                                        28
                                                                                        29
    The first argument is the file in use, the second is the error code to be returned.
                                                                                        30
With the Fortran mpi_f08 module, the user routine file_errhandler_fn should be of the form:
ABSTRACT INTERFACE
  SUBROUTINE MPI_File_errhandler_function(file, error_code)
    TYPE(MPI_File) :: file
                                                                                        34
    INTEGER :: error_code
                                                                                        35
With the Fortran mpi module and mpif.h, the user routine FILE_ERRHANDLER_FN should
                                                                                        36
be of the form:
                                                                                        37
SUBROUTINE FILE_ERRHANDLER_FUNCTION(FILE, ERROR_CODE)
                                                                                        38
    INTEGER FILE, ERROR_CODE
                                                                                        39
                                                                                        42
MPI_FILE_SET_ERRHANDLER(file, errhandler)
                                                                                        43
 INOUT
           file
                                       file (handle)
                                                                                        44
           errhandler
 IN
                                      new error handler for file (handle)
                                                                                        45
                                                                                        46
C binding
int MPI_File_set_errhandler(MPI_File file, MPI_Errhandler errhandler)
```

```
1
     Fortran 2008 binding
2
     MPI_File_set_errhandler(file, errhandler, ierror)
3
         TYPE(MPI_File), INTENT(IN) :: file
4
         TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
     Fortran binding
     MPI_FILE_SET_ERRHANDLER(FILE, ERRHANDLER, IERROR)
         INTEGER FILE, ERRHANDLER, IERROR
9
10
         Attaches a new error handler to a file. The error handler must be either a predefined
11
     error handler, or an error handler created by a call to MPI_FILE_CREATE_ERRHANDLER.
12
13
     MPI_FILE_GET_ERRHANDLER(file, errhandler)
14
15
       IN
16
       OUT
                errhandler
                                            error handler currently associated with file (handle)
17
18
     C binding
19
     int MPI_File_get_errhandler(MPI_File file, MPI_Errhandler *errhandler)
20
21
     Fortran 2008 binding
22
     MPI_File_get_errhandler(file, errhandler, ierror)
23
         TYPE(MPI_File), INTENT(IN) :: file
24
         TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
25
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
     Fortran binding
27
     MPI_FILE_GET_ERRHANDLER(FILE, ERRHANDLER, IERROR)
28
         INTEGER FILE, ERRHANDLER, IERROR
29
30
         Retrieves the error handler currently associated with a file.
31
32
     9.3.4 Error Handlers for Sessions
33
34
35
     MPI_SESSION_CREATE_ERRHANDLER(session_errhandler_fn, errhandler)
36
37
       IN
                session_errhandler_fn
                                            user defined error handling procedure (function)
       OUT
                errhandler
                                            MPI error handler (handle)
39
     C binding
41
     int MPI_Session_create_errhandler(
42
                    MPI_Session_errhandler_function *session_errhandler_fn,
43
                    MPI_Errhandler *errhandler)
44
45
     Fortran 2008 binding
46
     MPI_Session_create_errhandler(session_errhandler_fn, errhandler, ierror)
47
         PROCEDURE (MPI_Session_errhandler_function), INTENT(IN) ::
                     session_errhandler_fn
```

```
TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_SESSION_CREATE_ERRHANDLER(SESSION_ERRHANDLER_FN, ERRHANDLER, IERROR)
    EXTERNAL SESSION_ERRHANDLER_FN
    INTEGER ERRHANDLER, IERROR
    Creates an error handler that can be attached to a session object. In C, the
session_errhandler_fn argument should be a function of type MPI_Session_errhandler_function,
which is defined as
typedef void MPI_Session_errhandler_function(MPI_Session *session,
              int *error_code, ...);
                                                                                      12
                                                                                      13
    The first argument is the session in use, the second is the error code to be returned.
With the Fortran mpi_f08 module, the session_errhandler_fn argument should be of the
                                                                                      15
form:
                                                                                      16
ABSTRACT INTERFACE
  SUBROUTINE MPI_Session_errhandler_function(session, error_code)
    TYPE(MPI_Session) :: session
                                                                                      19
    INTEGER :: error_code
                                                                                     20
                                                                                     21
With the Fortran mpi module and mpif.h, the SESSION_ERRHANDLER_FN argument
                                                                                     22
should be of the form:
                                                                                     23
SUBROUTINE SESSION_ERRHANDLER_FUNCTION(SESSION, ERROR_CODE)
                                                                                      24
    INTEGER SESSION, ERROR_CODE
                                                                                     27
MPI_SESSION_SET_ERRHANDLER(session, errhandler)
                                                                                     28
 INOUT
           session
                                     (handle)
 IN
           errhandler
                                     new error handler for session (handle)
C binding
int MPI_Session_set_errhandler(MPI_Session session,
                                                                                     34
              MPI_Errhandler errhandler)
                                                                                     35
Fortran 2008 binding
                                                                                     36
MPI_Session_set_errhandler(session, errhandler, ierror)
                                                                                     37
    TYPE(MPI_Session), INTENT(IN) :: session
    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_SESSION_SET_ERRHANDLER(SESSION, ERRHANDLER, IERROR)
                                                                                      43
    INTEGER SESSION, ERRHANDLER, IERROR
    Attaches a new error handler to a session. The error handler must be either a pre-
                                                                                      45
defined error handler, or an error handler created by a call to
MPI_SESSION_CREATE_ERRHANDLER.
```

41

```
MPI_SESSION_GET_ERRHANDLER(session, errhandler)
2
       IN
                session
                                            (handle)
3
       OUT
                errhandler
                                            error handler currently associated with session
                                            (handle)
5
6
     C binding
7
     int MPI_Session_get_errhandler(MPI_Session session,
9
                    MPI_Errhandler *errhandler)
10
     Fortran 2008 binding
11
     MPI_Session_get_errhandler(session, errhandler, ierror)
12
         TYPE(MPI_Session), INTENT(IN) :: session
13
         TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
14
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
15
16
     Fortran binding
17
     MPI_SESSION_GET_ERRHANDLER(SESSION, ERRHANDLER, IERROR)
18
          INTEGER SESSION, ERRHANDLER, IERROR
19
         Retrieves the error handler currently associated with a session.
20
21
     9.3.5 Freeing Errorhandlers and Retrieving Error Strings
22
23
24
     MPI_ERRHANDLER_FREE(errhandler)
25
26
       INOUT
                errhandler
                                            MPI error handler (handle)
27
28
     C binding
29
     int MPI_Errhandler_free(MPI_Errhandler *errhandler)
30
31
     Fortran 2008 binding
     MPI_Errhandler_free(errhandler, ierror)
32
33
         TYPE(MPI_Errhandler), INTENT(INOUT) :: errhandler
34
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
35
     Fortran binding
36
     MPI_ERRHANDLER_FREE(ERRHANDLER, IERROR)
37
          INTEGER ERRHANDLER, IERROR
38
39
```

Marks the error handler associated with errhandler for deallocation and sets errhandler to MPI\_ERRHANDLER\_NULL. The error handler will be deallocated after all the objects associated with it (communicator, window, or file) have been deallocated.

## MPI\_ERROR\_STRING(errorcode, string, resultlen)

```
    IN errorcode Error code returned by an MPI routine
    OUT string Text that corresponds to the errorcode
    OUT resultlen Length (in printable characters) of the result returned in string
```

#### C binding

int MPI\_Error\_string(int errorcode, char \*string, int \*resultlen)

#### Fortran 2008 binding

```
MPI_Error_string(errorcode, string, resultlen, ierror)
    INTEGER, INTENT(IN) :: errorcode
    CHARACTER(LEN=MPI_MAX_ERROR_STRING), INTENT(OUT) :: string
    INTEGER, INTENT(OUT) :: resultlen
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_ERROR_STRING(ERRORCODE, STRING, RESULTLEN, IERROR)
INTEGER ERRORCODE, RESULTLEN, IERROR
CHARACTER*(*) STRING
```

Returns the error string associated with an error code or class. The argument string must represent storage that is at least MPI\_MAX\_ERROR\_STRING characters long.

The number of characters actually written is returned in the output argument, resultlen. This function must always be thread-safe, as defined in Section 11.6. It is one of the few routines that may be called before MPI is initialized or after MPI is finalized.

Rationale. The form of this function was chosen to make the Fortran and C bindings similar. A version that returns a pointer to a string has two difficulties. First, the return string must be statically allocated and different for each error message (allowing the pointers returned by successive calls to MPI\_ERROR\_STRING to point to the correct message). Second, in Fortran, a function declared as returning CHARACTER\*(\*) can not be referenced in, for example, a PRINT statement. (End of rationale.)

## 9.4 Error Codes and Classes

The error codes returned by MPI are left entirely to the implementation (with the exception of MPI\_SUCCESS). This is done to allow an implementation to provide as much information as possible in the error code (for use with MPI\_ERROR\_STRING).

All MPI function calls shall return MPI\_SUCCESS if and only if the specification of that function has been fulfilled at the point of return. For multiple completion functions, if the function returns MPI\_ERR\_IN\_STATUS, the error code in each status object shall be set to MPI\_SUCCESS if and only if the specification of the operation represented by the corresponding MPI\_Request has been fulfilled at the point of return.

When an operation raises an error, it may not satisfy its specification (for example, a synchronizing operation may not have synchronized) and the content of the output buffers, targeted memory, or output parameters is undefined. However, a valid error code shall

always be set when an operation raises an error, whether in the return value, error field in the status object, or element in an array of error codes.

To make it possible for an application to interpret an error code, the routine MPI\_ERROR\_CLASS converts any error code into one of a small set of standard error codes, called *error classes*. Valid error classes are shown in Table 9.1 and Table 9.2.

The error classes are a subset of the error codes: an MPI function may return an error class number; and the function MPI\_ERROR\_STRING can be used to compute the error string associated with an error class. The values defined for MPI error classes are valid MPI error codes.

The error codes satisfy,

```
0 = \mathsf{MPI\_SUCCESS} < \mathsf{MPI\_ERR\_...} \le \mathsf{MPI\_ERR\_LASTCODE}.
```

Rationale. The difference between MPI\_ERR\_UNKNOWN and MPI\_ERR\_OTHER is that MPI\_ERROR\_STRING can return useful information about MPI\_ERR\_OTHER.

Note that MPI\_SUCCESS = 0 is necessary to be consistent with C practice; the separation of error classes and error codes allows us to define the error classes this way. Having a known LASTCODE is often a nice sanity check as well. (*End of rationale*.)

#### MPI\_ERROR\_CLASS(errorcode, errorclass)

```
IN errorcode Error code returned by an MPI routine
OUT errorclass Error class associated with errorcode
```

#### C binding

```
int MPI_Error_class(int errorcode, int *errorclass)
```

#### Fortran 2008 binding

```
MPI_Error_class(errorcode, errorclass, ierror)
    INTEGER, INTENT(IN) :: errorcode
    INTEGER, INTENT(OUT) :: errorclass
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_ERROR_CLASS(ERRORCODE, ERRORCLASS, IERROR)
INTEGER ERRORCODE, ERRORCLASS, IERROR
```

The function  $\mathsf{MPI\_ERROR\_CLASS}$  maps each standard error code (error class) onto itself.

This function must always be thread-safe, as defined in Section 11.6. It is one of the few routines that may be called before MPI is initialized or after MPI is finalized.

## 9.5 Error Classes, Error Codes, and Error Handlers

Users may want to write a layered library on top of an existing MPI implementation, and this library may have its own set of error codes and classes. An example of such a library is an I/O library based on MPI, see Chapter 14. For this purpose, functions are needed to:

MPI_SUCCESS	No error	1
MPI_ERR_ACCESS	Permission denied	2
MPI_ERR_AMODE	Error related to the amode passed to	3
	MPI_FILE_OPEN	4
MPI_ERR_ARG	Invalid argument of some other kind	5
MPI_ERR_ASSERT	Invalid assert argument	6
MPI_ERR_BAD_FILE	Invalid file name (e.g., path name too long)	7
MPI_ERR_BASE	Invalid base passed to MPI_FREE_MEM	8
MPI_ERR_BUFFER	Invalid buffer pointer	9
MPI_ERR_COMM	Invalid communicator	10
MPI_ERR_CONVERSION	An error occurred in a user supplied data	11
	conversion function.	12
MPI_ERR_COUNT	Invalid count argument	13
MPI_ERR_DIMS	Invalid dimension argument	14
MPI_ERR_DISP	Invalid disp argument	15
MPI_ERR_DUP_DATAREP	Conversion functions could not be regis-	16
	tered because a data representation identi-	17
	fier that was already defined was passed to	18
	MPI_REGISTER_DATAREP	19
MPI_ERR_FILE	Invalid file handle	20
MPI_ERR_FILE_EXISTS	File exists	21
MPI_ERR_FILE_IN_USE	File operation could not be completed, as	22
	the file is currently open by some process	23
MPI_ERR_GROUP	Invalid group	24
MPI_ERR_INFO	Invalid info argument	25
MPI_ERR_INFO_KEY	Key longer than MPI_MAX_INFO_KEY	26
MPI_ERR_INFO_NOKEY	Invalid key passed to MPI_INFO_DELETE	27
MPI_ERR_INFO_VALUE	Value longer than MPI_MAX_INFO_VAL	28
MPI_ERR_IN_STATUS	Error code is in status	29
MPI_ERR_INTERN	Internal MPI (implementation) error	30
MPI_ERR_IO	Other I/O error	31
MPI_ERR_KEYVAL	Invalid keyval has been passed	32
MPI_ERR_LOCKTYPE	Invalid locktype argument	33
MPI_ERR_NAME	Invalid service name passed to	34
	MPI_LOOKUP_NAMÉ	35
MPI_ERR_NO_MEM	MPI_ALLOC_MEM failed because memory	36
	is exhausted	37
MPI_ERR_NO_SPACE	Not enough space	38
MPI_ERR_NO_SUCH_FILE	File does not exist	39
MPI_ERR_NOT_SAME	Collective argument not identical on all	40
	processes, or collective routines called in	41
	a different order by different processes	42
	r	43
		44

Table 9.1: Error classes (Part 1)

47

1	MPI_ERR_OP	Invalid operation
2	MPI_ERR_OTHER	Known error not in this list
3	MPI_ERR_PENDING	Pending request
4	MPI_ERR_PORT	Invalid port name passed to
5		MPI_COMM_CONNECT
6	MPI_ERR_PROC_ABORTED	Operation failed because a peer process has
7		aborted
8	MPI_ERR_QUOTA	Quota exceeded
9	MPI_ERR_RANK	Invalid rank
10	MPI_ERR_READ_ONLY	Read-only file or file system
11	MPI_ERR_REQUEST	Invalid request (handle)
12	MPI_ERR_RMA_ATTACH	Memory cannot be attached (e.g., because
13		of resource exhaustion)
14	MPI_ERR_RMA_CONFLICT	Conflicting accesses to window
15	MPI_ERR_RMA_FLAVOR	Passed window has the wrong flavor for the
16		called function
17	MPI_ERR_RMA_RANGE	Target memory is not part of the win-
18		dow (in the case of a window created
19		with MPI_WIN_CREATE_DYNAMIC, tar-
20		get memory is not attached)
21	MPI_ERR_RMA_SHARED	Memory cannot be shared (e.g., some pro-
22		cess in the group of the specified commu-
23		nicator cannot expose shared memory)
24	MPI_ERR_RMA_SYNC	Wrong synchronization of RMA calls
25	MPI_ERR_ROOT	Invalid root
26	MPI_ERR_SERVICE	Invalid service name passed to
27		MPI_UNPUBLISH_NAME
28	MPI_ERR_SESSION	Invalid session argument
29	MPI_ERR_SIZE	Invalid size argument
30	MPI_ERR_SPAWN	Error in spawning processes
31	MPI_ERR_TAG	Invalid tag argument
32	MPI_ERR_TOPOLOGY	Invalid topology
33	MPI_ERR_TRUNCATE	Message truncated on receive
34	MPI_ERR_TYPE	Invalid datatype argument
35	MPI_ERR_UNKNOWN	Unknown error
36 37	MPI_ERR_UNSUPPORTED_DATAREP	Unsupported datarep passed to MPI_FILE_SET_VIEW
38	MPI_ERR_UNSUPPORTED_OPERATION	Unsupported operation, such as seeking on
39	WITERIA ON SOLITOR TEDEST ENATION	a file which supports sequential access only
40	MPI_ERR_VALUE_TOO_LARGE	Value is too large to store
41	MPI_ERR_WIN	Invalid win argument
42	MPI_ERR_LASTCODE	Last error code
43		
44		
	Table 9.2: Err	or classes (Part 2)

Table 9.2: Error classes (Part 2)

- 1. add a new error class to the ones an MPI implementation already knows.
- 2. associate error codes with this error class, so that MPI\_ERROR\_CLASS works.
- 3. associate strings with these error codes, so that MPI\_ERROR\_STRING works.
- 4. invoke the error handler associated with a communicator, window, or object.

Several functions are provided to do this. They are all local. No functions are provided to free error classes or codes: it is not expected that an application will generate them in significant numbers.

## MPI\_ADD\_ERROR\_CLASS(errorclass)

OUT errorclass

value for the new error class (integer)

#### C binding

int MPI\_Add\_error\_class(int \*errorclass)

#### Fortran 2008 binding

```
MPI_Add_error_class(errorclass, ierror)
    INTEGER, INTENT(OUT) :: errorclass
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_ADD_ERROR_CLASS(ERRORCLASS, IERROR)
    INTEGER ERRORCLASS, IERROR
```

Creates a new error class and returns the value for it.

Rationale. To avoid conflicts with existing error codes and classes, the value is set by the implementation and not by the user. (End of rationale.)

Advice to users. Since a call to MPI\_ADD\_ERROR\_CLASS is local, the same errorclass may not be returned on all processes that make this call. Thus, it is not safe to assume that registering a new error on a set of processes at the same time will yield the same errorclass on all of the processes. Getting the "same" error on multiple processes may not cause the same value of error code to be generated. (*End of advice to users*.)

The value of MPI\_ERR\_LASTCODE is a constant value and is not affected by new user-defined error codes and classes. Instead, a predefined attribute key MPI\_LASTUSEDCODE is associated with MPI\_COMM\_WORLD. The attribute value corresponding to this key is the current maximum error class including the user-defined ones. This is a local value and may be different on different processes. The value returned by this key is always greater than or equal to MPI\_ERR\_LASTCODE.

Advice to users. The value returned by the key MPI\_LASTUSEDCODE will not change unless the user calls a function to explicitly add an error class/code. In a multithreaded environment, the user must take extra care in assuming this value has not changed. Note that error codes and error classes are not necessarily dense. A user may not assume that each error class below MPI\_LASTUSEDCODE is valid. (End of advice to users.)

44

45

46

47

48

```
MPI_ADD_ERROR_CODE(errorclass, errorcode)
2
       IN
                 errorclass
                                             error class (integer)
3
       OUT
                 errorcode
                                             new error code to be associated with errorclass
                                             (integer)
5
6
     C binding
7
     int MPI_Add_error_code(int errorclass, int *errorcode)
9
     Fortran 2008 binding
10
     MPI_Add_error_code(errorclass, errorcode, ierror)
11
          INTEGER, INTENT(IN) :: errorclass
12
          INTEGER, INTENT(OUT) :: errorcode
13
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
14
15
     Fortran binding
16
     MPI_ADD_ERROR_CODE(ERRORCLASS, ERRORCODE, IERROR)
17
          INTEGER ERRORCLASS, ERRORCODE, IERROR
18
          Creates new error code associated with errorclass and returns its value in errorcode.
19
20
                      To avoid conflicts with existing error codes and classes, the value of the
21
           new error code is set by the implementation and not by the user. (End of rationale.)
22
23
24
25
     MPI_ADD_ERROR_STRING(errorcode, string)
26
       IN
                                             error code or class (integer)
                 errorcode
27
       IN
                 string
                                             text corresponding to errorcode (string)
28
29
     C binding
30
     int MPI_Add_error_string(int errorcode, const char *string)
31
32
     Fortran 2008 binding
33
     MPI_Add_error_string(errorcode, string, ierror)
34
          INTEGER, INTENT(IN) :: errorcode
35
          CHARACTER(LEN=*), INTENT(IN) :: string
36
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
37
     Fortran binding
38
     MPI_ADD_ERROR_STRING(ERRORCODE, STRING, IERROR)
39
          INTEGER ERRORCODE, IERROR
41
          CHARACTER*(*) STRING
42
```

Associates an error string with an error code or class. The string must be no more than MPI\_MAX\_ERROR\_STRING characters long. The length of the string is as defined in the calling language. The length of the string does not include the null terminator in C. Trailing blanks will be stripped in Fortran. Calling MPI\_ADD\_ERROR\_STRING for an errorcode that already has a string will replace the old string with the new string. It is erroneous to call MPI\_ADD\_ERROR\_STRING for an error code or class with a value  $\leq$  MPI\_ERR\_LASTCODE.

13 14

15

16

18

19

20

21

22 23

24

26

27 28

29 30

31

33

34

35 36

37

42

43

44 45

47

If MPI\_ERROR\_STRING is called when no string has been set, it will return a empty string (all spaces in Fortran, "" in C).

Section 9.3 describes the methods for creating and associating error handlers with communicators, files, windows, and sessions.

#### MPI\_COMM\_CALL\_ERRHANDLER(comm, errorcode)

```
IN comm communicator with error handler (handle)
IN error code (integer)
```

#### C binding

int MPI\_Comm\_call\_errhandler(MPI\_Comm comm, int errorcode)

#### Fortran 2008 binding

```
MPI_Comm_call_errhandler(comm, errorcode, ierror)
   TYPE(MPI_Comm), INTENT(IN) :: comm
   INTEGER, INTENT(IN) :: errorcode
   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_COMM_CALL_ERRHANDLER(COMM, ERRORCODE, IERROR)
INTEGER COMM, ERRORCODE, IERROR
```

This function invokes the error handler assigned to the communicator with the error code supplied. This function returns MPI\_SUCCESS in C and the same value in IERROR if the error handler was successfully called (assuming the process is not aborted and the error handler returns).

#### MPI\_WIN\_CALL\_ERRHANDLER(win, errorcode)

```
IN win window with error handler (handle)
IN errorcode error code (integer)
```

#### C binding

```
int MPI_Win_call_errhandler(MPI_Win win, int errorcode)
```

#### Fortran 2008 binding

```
MPI_Win_call_errhandler(win, errorcode, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, INTENT(IN) :: errorcode
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_WIN_CALL_ERRHANDLER(WIN, ERRORCODE, IERROR)
INTEGER WIN, ERRORCODE, IERROR
```

This function invokes the error handler assigned to the window with the error code supplied. This function returns MPI\_SUCCESS in C and the same value in IERROR if the

```
error handler was successfully called (assuming the process is not aborted and the error
2
     handler returns).
3
           Advice to users.
                              In contrast to communicators, the error handler
           MPI_ERRORS_ARE_FATAL is associated with a window when it is created. (End of
           advice to users.)
9
     MPI_FILE_CALL_ERRHANDLER(fh, errorcode)
10
                                             file with error handler (handle)
       IN
11
12
       IN
                 errorcode
                                             error code (integer)
13
14
     C binding
15
     int MPI_File_call_errhandler(MPI_File fh, int errorcode)
16
     Fortran 2008 binding
17
     MPI_File_call_errhandler(fh, errorcode, ierror)
18
          TYPE(MPI_File), INTENT(IN) :: fh
19
          INTEGER, INTENT(IN) :: errorcode
20
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
21
22
     Fortran binding
23
     MPI_FILE_CALL_ERRHANDLER(FH, ERRORCODE, IERROR)
24
          INTEGER FH, ERRORCODE, IERROR
25
         This function invokes the error handler assigned to the file with the error code supplied.
26
     This function returns MPI_SUCCESS in C and the same value in IERROR if the error handler
27
     was successfully called (assuming the process is not aborted and the error handler returns).
28
29
           Advice to users.
                           The default error handler for files is MPI_ERRORS_RETURN. (End of
30
           advice to users.)
31
32
33
34
     MPI_SESSION_CALL_ERRHANDLER(session, errorcode)
35
       IN
                 session
                                             session with error handler (handle)
36
       IN
                 errorcode
                                             error code (integer)
37
38
39
     C binding
     int MPI_Session_call_errhandler(MPI_Session session, int errorcode)
41
     Fortran 2008 binding
42
     MPI_Session_call_errhandler(session, errorcode, ierror)
43
          TYPE(MPI_Session), INTENT(IN) :: session
44
          INTEGER, INTENT(IN) :: errorcode
45
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
46
47
     Fortran binding
48
     MPI_SESSION_CALL_ERRHANDLER(SESSION, ERRORCODE, IERROR)
```

#### INTEGER SESSION, ERRORCODE, IERROR

This function invokes the error handler assigned to the session with the error code supplied. This function returns MPI\_SUCCESS in C and the same value in IERROR if the error handler was successfully called (assuming the process is not aborted and the error handler returns).

Advice to users. Users are warned that handlers should not be called recursively with MPI\_COMM\_CALL\_ERRHANDLER, MPI\_FILE\_CALL\_ERRHANDLER,

MPI\_WIN\_CALL\_ERRHANDLER, or MPI\_SESSION\_CALL\_ERRHANDLER. Doing this can create a situation where an infinite recursion is created. This can occur if MPI\_COMM\_CALL\_ERRHANDLER, MPI\_FILE\_CALL\_ERRHANDLER.

MPI\_WIN\_CALL\_ERRHANDLER, or MPI\_SESSION\_CALL\_ERRHANDLER is called inside an error handler.

Error codes and classes are associated with a process. As a result, they may be used in any error handler. Error handlers should be prepared to deal with any error code they are given. Furthermore, it is good practice to only call an error handler with the appropriate error codes. For example, file errors would normally be sent to the file error handler. (*End of advice to users.*)

# 9.6 Timers and Synchronization

MPI defines a timer. A timer is specified even though it is not "message-passing," because timing parallel programs is important in "performance debugging" and because existing timers (both in POSIX 1003.1-1988 and 1003.4D 14.1 and in Fortran 90) are either inconvenient or do not provide adequate access to high resolution timers. See also Section 2.6.4.

```
MPI_WTIME()

C binding
double MPI_Wtime(void)

Fortran 2008 binding
DOUBLE PRECISION MPI_Wtime()

Fortran binding
DOUBLE PRECISION MPI_WTIME()
```

MPI\_WTIME returns a floating-point number of seconds, representing elapsed wall-clock time since some time in the past.

The "time in the past" is guaranteed not to change during the life of the process. The user is responsible for converting large numbers of seconds to other units if they are preferred.

This function is portable (it returns seconds, not "ticks"), it allows high-resolution, and carries no unnecessary baggage. One would use it like this:

```
{
  double starttime, endtime;
  starttime = MPI_Wtime();
```

The times returned are local to the node that called them. There is no requirement that different nodes return "the same time." (But see also the discussion of MPI\_WTIME\_IS\_GLOBAL in Section 9.1.2).

MPI\_WTICK()

C binding


double MPI\_Wtick(void)

Fortran 2008 binding
DOUBLE PRECISION MPI\_Wtick()

Fortran binding

DOUBLE PRECISION MPI\_WTICK()

MPI\_WTICK returns the resolution of MPI\_WTIME in seconds. That is, it returns, as a double precision value, the number of seconds between successive clock ticks. For example, if the clock is implemented by the hardware as a counter that is incremented every millisecond, the value returned by MPI\_WTICK should be  $(10^{-3})$ .



# Chapter 10

# The Info Object

Many of the routines in MPI take an argument info. info is an opaque object with a handle of type MPI\_Info in C and Fortran with the mpi\_f08 module, and INTEGER in Fortran with the mpi module or the include file mpif.h. It stores an unordered set of (key,value) pairs (both key and value are strings). A key can have only one value. MPI reserves several keys and requires that if an implementation uses a reserved key, it must provide the specified functionality. An implementation is not required to support these keys and may support any others not reserved by MPI.

Some info hints allow the MPI library to restrict its support for certain operations in order to improve performance or resource utilization. If an application provides such an info hint, it must be compatible with any changes in the behavior of the MPI library that are allowed by the info hint.

An implementation must support info objects as caches for arbitrary (key,value) pairs, regardless of whether it recognizes the key. Each function that takes hints in the form of an MPI\_Info must be prepared to ignore any key it does not recognize. This description of info objects does not attempt to define how a particular function should react if it recognizes a key but not the associated value. MPI\_INFO\_GET\_NKEYS, MPI\_INFO\_GET\_NTHKEY, MPI\_INFO\_GET\_VALUELEN, MPI\_INFO\_GET, and MPI\_INFO\_GET\_STRING must retain all (key,value) pairs so that layered functionality can also use the Info object.

Keys have an implementation-defined maximum length of MPI\_MAX\_INFO\_KEY, which is at least 32 and at most 255. Values have an implementation-defined maximum length of MPI\_MAX\_INFO\_VAL. In Fortran, leading and trailing spaces are stripped from both. Returned values will never be larger than these maximum lengths. Both key and value are case sensitive.

Rationale. Keys have a maximum length because the set of known keys—will always be finite and known to the implementation and because there is no reason for keys to be complex. The small maximum size allows applications to declare keys of size MPI\_MAX\_INFO\_KEY. The limitation on value sizes is so that an implementation is not forced to deal with arbitrarily long strings. (End of rationale.)

Advice to users. MPI\_MAX\_INFO\_VAL might be very large, so it might not be wise to declare a string of that size. (End of advice to users.)

When info is used as an IN or INOUT argument to any MPI routine, it is parsed before that routine returns, so that it may be read, modified or freed immediately after return.

to be removed, because the routines are moved to the deprecated chapter



12 13 14

15

17

18

19

20

21

22

24

26

27

28

37

38

42

43

44

45 46

When the descriptions refer to a key or value as being a boolean, an integer, or a list, they mean the string representation of these types. An implementation may define its own rules for how info value strings are converted to other types, but to ensure portability, every implementation must support the following representations. Valid values for a boolean must include the strings "true" and "false" (all lowercase). For integers, valid values must include string representations of decimal values of integers that are within the range of a standard integer type in the program. (However it is possible that not every integer is a valid value for a given key.) On positive numbers, + signs are optional. No space may appear between a + or - sign and the leading digit of a number. For comma separated lists, the string must contain valid elements separated by commas. Leading and trailing spaces are stripped automatically from the types of info values described above and for each element of a comma separated list. These rules apply to all info values of these types. Implementations are free to specify a different interpretation for values of other info keys.

```
MPI_INFO_CREATE(info)
OUT info info object created (handle)

C binding
int MPI_Info_create(MPI_Info *info)

Fortran 2008 binding
MPI_Info_create(info, ierror)
    TYPE(MPI_Info), INTENT(OUT) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

MPI\_INFO\_CREATE(INFO, IERROR)
INTEGER INFO, IERROR

MPI\_INFO\_CREATE creates a new info object. The newly created object contains no key/value pairs.

```
MPI_INFO_SET(info, key, value)
```

```
INOUT info info object (handle)
IN key key (string)
IN value value (string)
```

#### C binding

int MPI\_Info\_set(MPI\_Info info, const char \*key, const char \*value)

#### Fortran 2008 binding

```
MPI_Info_set(info, key, value, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    CHARACTER(LEN=*), INTENT(IN) :: key, value
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

12

13

14 15 16

17

18

19

20

21

22

23 24

26

27

28

29

30 31

34

35

36

37

38 39

40

42

43

44

45

 $^{46}$ 

```
MPI_INFO_SET(INFO, KEY, VALUE, IERROR)
    INTEGER INFO, IERROR
    CHARACTER*(*) KEY, VALUE
```

MPI\_INFO\_SET adds the (key,value) pair to info, and overrides the value if a value for the same key was previously set. key and value are null-terminated strings in C. In Fortran, leading and trailing spaces in key and value are stripped. If either key or value are larger than the allowed maximums, the errors MPI\_ERR\_INFO\_KEY or MPI\_ERR\_INFO\_VALUE are raised, respectively.

```
MPI_INFO_DELETE(info, key)
```

```
INOUT
           info
                                           info object (handle)
IN
           key
                                           key (string)
```

#### C binding

int MPI\_Info\_delete(MPI\_Info info, const char \*key)

#### Fortran 2008 binding

```
MPI_Info_delete(info, key, ierror)
   TYPE(MPI_Info), INTENT(IN) :: info
   CHARACTER(LEN=*), INTENT(IN) :: key
   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_INFO_DELETE(INFO, KEY, IERROR)
    INTEGER INFO, IERROR
    CHARACTER*(*) KEY
```

MPI\_INFO\_DELETE deletes a (key,value) pair from info. If key is not defined in info, the call raises an error of class MPI\_ERR\_INFO\_NOKEY.

#### MPI\_INFO\_GET(info, key, valuelen, value, flag)

PI_INFO_	GET(info, key, valuelen, value,	flag)	Deprecated function
IN	info	THIO ODIECT (Handle)	descriptions must be moved from the
IN	key		original chapter to the
IN	valuelen	rength of value arg (integer)	Deprecated Interfaces chapter !!!
OUT	value	value (string)	

true if key defined, false if not (boolean)

#### C binding

OUT

```
int MPI_Info_get(MPI_Info info, const char *key, int valuelen, char *value,
             int *flag)
```

#### Fortran 2008 binding

flag

```
MPI_Info_get(info, key, valuelen, value, flag, ierror)
   TYPE(MPI_Info), INTENT(IN) :: info
   CHARACTER(LEN=*), INTENT(IN) :: key
```

#-other #-error #-364 Done PR443

#-other #-error #-364

Done in PR443

> 10 11

> 12

13

14

15

16

 $^{17}$ 

18 19

20

 $^{21}$ 

22

23

 $^{24}$ 

 $^{25}$ 

26 27

28

29

30 31

32

33 34

35

36

37 38

39

40

41

42

43 44

45

46

47

48

```
INTEGER, INTENT(IN) :: valuelen
CHARACTER(LEN=valuelen), INTENT(OUT) :: value
LOGICAL, INTENT(OUT) :: flag
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_INFO_GET(INFO, KEY, VALUELEN, VALUE, FLAG, IERROR)
INTEGER INFO, VALUELEN, IERROR
CHARACTER*(*) KEY, VALUE
LOGICAL FLAG
```

This function retrieves the value associated with key in a previous call to MPI\_INFO\_SET. If such a key exists, it sets flag to true and returns the value in value, otherwise it sets flag to false and leaves value unchanged. valuelen is the number of characters available in value. If it is less than the actual size of the value, the value is truncated. In C, valuelen should be one less than the amount of allocated space to allow for the null terminator.

If key is larger than MPI\_MAX\_INFO\_KEY, the call is erroneous.

#### MPI\_INFO\_GET\_VALUELEN(info, key, valuelen, flag)

 IN
 info
 info object (handle)

 IN
 key
 key (string)

 OUT
 valuelen
 length of value arg (integer)

descriptions must be moved from the original chapter to the Deprecated Interfaces chapter !!!

Deprecated function

OUT flag true if key defined, false if not (boolean)

#### C binding

#### Fortran 2008 binding

```
MPI_Info_get_valuelen(info, key, valuelen, flag, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    CHARACTER(LEN=*), INTENT(IN) :: key
    INTEGER, INTENT(OUT) :: valuelen
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_INFO_GET_VALUELEN(INFO, KEY, VALUELEN, FLAG, IERROR)
INTEGER INFO, VALUELEN, IERROR
CHARACTER*(*) KEY
LOGICAL FLAG
```

Retrieves the length of the value associated with key. If key is defined, valuelen is set to the length of its associated value and flag is set to true. If key is not defined, valuelen is not touched and flag is set to false. The length returned in C does not include the end-of-string character.

If key is larger than MPI\_MAX\_INFO\_KEY, the call is erroneous.

12 13

14

15

16

17

18

19

20

21

22

23 24

26

27

28

35

36

37

38

```
MPI_INFO_GET_STRING(info, key, buflen, value, flag)
 IN
           info
                                      info object (handle)
 IN
           key
                                     key (string)
 INOUT
           buflen
                                     length of buffer (integer)
  OUT
           value
                                     value (string)
 OUT
           flag
                                     true if key defined, false if not (boolean)
C binding
int MPI_Info_get_string(MPI_Info info, const char *key, int *buflen,
              char *value, int *flag)
Fortran 2008 binding
MPI_Info_get_string(info, key, buflen, value, flag, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    CHARACTER(LEN=*), INTENT(IN) :: key
    INTEGER, INTENT(INOUT) :: buflen
    CHARACTER(LEN=*), INTENT(OUT) :: value
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_INFO_GET_STRING(INFO, KEY, BUFLEN, VALUE, FLAG,
    INTEGER INFO, BUFLEN, IERROR
    CHARACTER*(*) KEY, VALUE
```

This function retrieves the value associated with key in a previous call to MPI\_INFO\_SET. If such a key exists, it sets flag to true and returns the value in value, otherwise it sets flag to false and leaves value unchanged. buflen on input is the size of the provided buffer, for the output of buflen it is the size of the buffer needed to store the value string. If the buflen passed into the function is less than the actual size needed to store the value string (including null terminator in C), the value is truncated. On return, the value of buflen will be set to the required buffer size to hold the value string. If buflen is set to 0, value is not changed. In C, buflen includes the required space for the null terminator. In C, this function returns a null terminated string in all cases where the buflen input value is greater than 0.

If key is larger than MPI\_MAX\_INFO\_KEY, the call is erroneous.

LOGICAL FLAG

Advice to users. The MPI\_INFO\_GET\_STRING function can be used to obtain the size of the required buffer for a value string by setting the buflen to 0. The returned buflen can then be used to allocate memory before calling MPI\_INFO\_GET\_STRING again to obtain the value string. (End of advice to users.)

```
MPI_INFO_GET_NKEYS(info, nkeys)
2
       IN
                info
                                            info object (handle)
3
       OUT
                nkeys
                                            number of defined keys (integer)
5
6
     C binding
7
     int MPI_Info_get_nkeys(MPI_Info info, int *nkeys)
     Fortran 2008 binding
9
     MPI_Info_get_nkeys(info, nkeys, ierror)
10
         TYPE(MPI_Info), INTENT(IN) :: info
11
         INTEGER, INTENT(OUT) :: nkeys
12
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
14
     Fortran binding
15
     MPI_INFO_GET_NKEYS(INFO, NKEYS, IERROR)
16
         INTEGER INFO, NKEYS, IERROR
17
         MPI_INFO_GET_NKEYS returns the number of currently defined keys in info.
18
19
20
     MPI_INFO_GET_NTHKEY(info, n, key)
21
       IN
                info
                                            info object (handle)
22
       IN
                                            key number (integer)
23
                 n
24
       OUT
                key
                                            key (string)
25
26
     C binding
27
     int MPI_Info_get_nthkey(MPI_Info info, int n, char *key)
28
     Fortran 2008 binding
29
     MPI_Info_get_nthkey(info, n, key, ierror)
30
31
         TYPE(MPI_Info), INTENT(IN) :: info
32
         INTEGER, INTENT(IN) :: n
         CHARACTER(LEN=*), INTENT(OUT) :: key
33
34
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
35
     Fortran binding
36
     MPI_INFO_GET_NTHKEY(INFO, N, KEY, IERROR)
37
         INTEGER INFO, N, IERROR
38
         CHARACTER*(*) KEY
39
         This function returns the nth defined key in info. Keys are numbered 0 \dots N-1 where
41
```

This function returns the nth defined key in info. Keys are numbered 0 ... N-1 where N is the value returned by MPI\_INFO\_GET\_NKEYS. All keys between 0 and N-1 are guaranteed to be defined. The number of a given key does not change as long as info is not modified with MPI\_INFO\_SET or MPI\_INFO\_DELETE.

```
MPI_INFO_DUP(info, newinfo)
  IN
           info
                                       info object (handle)
  OUT
           newinfo
                                       info object (handle)
C binding
int MPI_Info_dup(MPI_Info info, MPI_Info *newinfo)
Fortran 2008 binding
MPI_Info_dup(info, newinfo, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Info), INTENT(OUT) :: newinfo
                                                                                         12
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                         13
Fortran binding
                                                                                         14
MPI_INFO_DUP(INFO, NEWINFO, IERROR)
                                                                                         15
                                                                                         16
    INTEGER INFO, NEWINFO, IERROR
    MPI_INFO_DUP duplicates an existing info object, creating a new object, with the
                                                                                         18
same (key, value) pairs and the same ordering of keys.
                                                                                         19
                                                                                         20
                                                                                        21
MPI_INFO_FREE(info)
                                                                                         22
  INOUT
           info
                                       info object (handle)
                                                                                         23
                                                                                         24
C binding
int MPI_Info_free(MPI_Info *info)
                                                                                         26
                                                                                         27
Fortran 2008 binding
                                                                                         28
MPI_Info_free(info, ierror)
                                                                                         29
    TYPE(MPI_Info), INTENT(INOUT) :: info
                                                                                         30
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_INFO_FREE(INFO, IERROR)
    INTEGER INFO, IERROR
                                                                                        34
                                                                                        35
    This function frees info and sets it to MPI_INFO_NULL.
                                                                                        36
    The value of an info argument is interpreted each time the info is passed to a routine.
                                                                                        37
Changes to an info after return from a routine do not affect that interpretation.
                                                                                         38
                                                                                         39
MPI_INFO_CREATE_ENV(info)
                                                                                         41
  OUT
           info
                                       info object (handle)
                                                                                         42
                                                                                         43
C binding
                                                                                         44
int MPI_Info_create_env(int argc, char argv[], MPI_Info *info)
                                                                                         45
                                                                                         46
Fortran 2008 binding
MPI_Info_create_env(info, ierror)
```

```
TYPE(MPI_Info), INTENT(OUT) :: info
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
```

MPI\_INFO\_CREATE\_ENV(INFO, IERROR)
INTEGER INFO, IERROR

This routine produces an output object info with the same construction as MPI\_INFO\_ENV as created during MPI\_INIT or MPI\_INIT\_THREAD when the same arguments are used. This construction is described in Section 11.2.1; however, this function can be called when not using the World Model, e.g., when using the Sessions Model. This object is not a direct copy or alias of the MPI\_INFO\_ENV object and could contain different values based on the input arguments and other sources. Multiple calls to this procedure that are given the same input arguments will produce info objects consistent with the definition of MPI\_INFO\_ENV. The version for ISO C accepts the argc and argv that are provided by the arguments to main or 0 for argc and NULL for argv. The user is responsible for freeing the info object via MPI\_INFO\_FREE. This procedure is local.

This procedure must always be thread-safe, as defined in Section 11.6. It is one of the few routines that may be called before MPI is initialized or after MPI is finalized.

Advice to users.

In some circumstances (e.g., when passing 0 to argc and NULL to argv in C or in Fortran where such arguments do not exist), the info object may not be populated or may be populated incompletely because this procedure is local and the implementation may not be able to determine the correct values. Note that this could result in different values in the resulting info object at different MPI processes.

(End of advice to users.)



# Chapter 11

# Process Initialization, Creation, and Management

#### 11.1 Introduction

MPI is primarily concerned with communication rather than process or resource management. However, it is necessary to address these issues to some degree in order to define a useful framework for communication. This chapter presents a set of MPI interfaces that allows for several approaches to MPI initialization and process management while placing minimal restrictions on the execution environment.

One goal of MPI is to achieve source code portability. By this we mean that a program written using MPI and complying with the relevant language standards is portable as written, and must not require any source code changes when moved from one system to another. This explicitly does not say anything about how an MPI program is started or launched from the command line, nor what the user must do to set up the environment in which an MPI program will run. However, an implementation may require some setup or initialization procedure to be performed before the complete set of MPI routines may be called.

To this end, MPI presents two models for MPI process initialization. In the World Model, an initial set of processes is created that are related by their membership in a common MPI\_COMM\_WORLD (see Section 11.2) communicator. In the Sessions Model (Section 11.3), an initial set of processes is also created, but the application must explicitly manage the creation of MPI groups, and hence MPI communicators. MPI\_COMM\_WORLD is only valid for use as a communicator in the World Model, i.e., after a successful call to MPI\_INIT\_THREAD and before a call to MPI\_FINALIZE. An application can employ both of these Process Models concurrently. In multi-component MPI applications, for example, a component such as a library can make use of the Sessions Model to instantiate MPI resources without impacting the rest of the application.

Both of these models also support the *Dynamic Process Model* (see Section 11.7), which provides for the creation and management of additional processes after an MPI application has been started. A major impetus for the *Dynamic Process Model* comes from the PVM [25] research effort. This work has provided a wealth of experience with process management and resource control that illustrates their benefits and potential pitfalls.

In developing the *Dynamic Process Model*, the MPI Forum decided not to address resource control because it was not able to design a portable interface that would be ap-

propriate for the broad spectrum of existing and potential resource and process controllers. MPI assumes that resource control is provided externally.

Process management functionality is included in MPI to enable its use in classes of message-passing applications requiring process control. These include task farms, serial applications with parallel modules, and problems that require a run-time assessment of the number and type of processes that should be started.

The following goals are central to the design of MPI process management:

• The MPI process model must apply to the vast majority of current parallel environments.

• MPI must not take over operating system responsibilities. It should instead provide a clean interface between an application and system software.

• MPI must guarantee communication determinism in the presense of dynamic processes, i.e., dynamic process management must not introduce unavoidable race conditions.

• MPI must not contain features that compromise performance.

The *Dynamic Process Model* addresses these issues in two ways. First, MPI remains primarily a communication library. It does not manage the parallel environment in which a parallel program executes, though it provides a minimal interface between an application and external resource and process managers.

Second, MPI maintains a consistent concept of a communicator, regardless of how its members came into existence. A communicator is never changed once created, and it is always created using deterministic collective operations.

#### 11.2 The World Model

## 11.2.1 Starting MPI Processes

When using the World Model, MPI is initialized by calling either MPI\_INIT or MPI\_INIT\_THREAD.

MPI\_INIT()

#### C binding

```
int MPI_Init(int *argc, char ***argv)
```

#### Fortran 2008 binding

MPI\_Init(ierror)

INTEGER, OPTIONAL, INTENT(OUT) :: ierror

#### Fortran binding

MPI\_INIT(IERROR)

INTEGER IERROR

In the World Model, an MPI program must contain exactly one call to an MPI initialization routine: MPI\_INIT or MPI\_INIT\_THREAD. MPI\_COMM\_WORLD and MPI\_COMM\_SELF are not valid for use as communicators prior to invocation of MPI\_INIT or

MPI\_INIT\_THREAD. Subsequent calls to either of these initialization routines are erroneous. A subset of MPI functions may be invoked before MPI initialization routines are called. See Section 11.4. MPI\_INIT accepts the argc and argv that are provided by the arguments to main or NULL:

```
int main(int argc, char *argv[])
{
    MPI_Init(&argc, &argv);

    /* parse arguments */
    /* main program */

    MPI_Finalize();    /* see below */
    return 0;
}
```

The Fortran version takes only IERROR.

Conforming implementations of MPI are required to allow applications to pass NULL for both the argc and arguments of main in C.

Failures may disrupt the execution of the program before or during MPI initialization. A high-quality implementation shall not deadlock during MPI initialization, even in the presence of failures. Except for functions with the MPI\_T\_ prefix, failures in MPI operations prior to or during MPI initialization are reported by invoking the initial error handler. Users can use the "mpi\_initial\_errhandler" info key during the launch of MPI processes (e.g., MPI\_COMM\_SPAWN / MPI\_COMM\_SPAWN\_MULTIPLE, or mpiexec) to set a non-fatal initial error handler before MPI initialization. When the initial error handler is set to MPI\_ERRORS\_ABORT, raising an error before or during initialization aborts the local MPI process (i.e., it is similar to calling MPI\_ABORT on MPI\_COMM\_SELF). An implementation may not always be capable of determining, before MPI initialization, what constitutes the local MPI process, or the set of connected processes. In this case, errors before initialization may cause a different set of MPI processes to abort than specified. While MPI initialization, the initial error handler is associated with MPI\_COMM\_WORLD, MPI\_COMM\_SELF, and the communicator returned by MPI\_COMM\_GET\_PARENT (if any).

Advice to implementors. Some failures may leave MPI in an undefined state, or raise an error before the error handling capabilities are fully operational, in which cases the implementation may be incapable of providing the desired error handling behavior. Of note, in some implementations, the notion of an MPI process is not clearly established in the early stages of MPI initialization (for example, when the implementation considers threads that called MPI\_INIT as independent MPI processes); in this case, before MPI is initialized, the MPI\_ERRORS\_ABORT error handler may abort what would have become multiple MPI processes.

When a failure occurs during MPI initialization, the implementation may decide to return MPI\_SUCCESS from the MPI initialization function instead of raising an error. It is recommended that an implementation masks an initialization error only when it expects that later MPI calls will result in well-specified behavior (i.e., barring additional failures, either the outcome of any call will be correct, or the call will raise an appropriate error). For example, it may be difficult for an implementation to avoid

unspecified behavior when the group of MPI\_COMM\_WORLD does not contain the same set of MPI processes at all members of the communicator, or if the communicator returned from MPI\_COMM\_GET\_PARENT was not initialized correctly. (*End of advice to implementors.*)

After MPI is initialized, the application can access information about the execution environment by querying the predefined info object MPI\_INFO\_ENV. The following keys are predefined for this object, corresponding to the arguments of MPI\_COMM\_SPAWN or of mpiexec:

"command" Name of program executed.

 $\mbox{"argv"}$  Space separated arguments to command.

"maxprocs" Maximum number of MPI processes to start.

"mpi\_initial\_errhandler" Name of the initial errhandler.

"soft" Allowed values for number of processors.

"host" Hostname.

"arch" Architecture name.

"wdir" Working directory of the MPI process.

"file" Value is the name of a file in which additional information is specified.

 "thread\_level" Requested level of thread support, if requested before the program started execution.

Note that all values are strings. Thus, the maximum number of processes is represented by a string such as ''1024'' and the requested level is represented by a string such as ''MPI\_THREAD\_SINGLE''.

Advice to users. If one of the "argv" arguments contains a space, there is no way to tell from the value of the "argv" info key whether a space is part of the argument or is separating different arguments. (End of advice to users.)

The info object MPI\_INFO\_ENV need not contain a (key,value) pair for each of these predefined keys; the set of (key,value) pairs provided is implementation-dependent. Implementations may provide additional, implementation specific, (key,value) pairs.

In cases where the MPI processes were started with MPI\_COMM\_SPAWN\_MULTIPLE or, equivalently, with a startup mechanism that supports multiple process specifications, then the values stored in the info object MPI\_INFO\_ENV at a process are those values that affect the local MPI process.

 $\frac{45}{46}$ 

Example 11.1 If MPI is started with a call to

mpiexec -n 5 -arch x86\_64 ocean : -n 10 -arch power9 atmos

Then the first 5 processes will have in their MPI\_INFO\_ENV object the pairs (command, ocean), (maxprocs, 5), and (arch, x86\_64). The next 10 processes will have in MPI\_INFO\_ENV (command, atmos), (maxprocs, 10), and (arch, power9)

Advice to users. The values passed in MPI\_INFO\_ENV are the values of the arguments passed to the mechanism that started the MPI execution—not the actual value provided. Thus, the value associated with "maxprocs" is the number of MPI processes requested; it can be larger than the actual number of processes obtained, if the soft option was used. (End of advice to users.)

Advice to implementors. High-quality implementations will provide a (key,value) pair for each parameter that can be passed to the command that starts an MPI program. (End of advice to implementors.)

The following function may be used to initialize MPI, and to initialize the MPI thread environment, instead of MPI\_INIT.

#### MPI\_INIT\_THREAD(required, provided)

```
IN required desired level of thread support (integer)OUT provided provided level of thread support (integer)
```

#### C binding

```
int MPI_Init_thread(int *argc, char ***argv, int required, int *provided)
```

#### Fortran 2008 binding

```
MPI_Init_thread(required, provided, ierror)
    INTEGER, INTENT(IN) :: required
    INTEGER, INTENT(OUT) :: provided
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_INIT_THREAD(REQUIRED, PROVIDED, IERROR)
    INTEGER REQUIRED, PROVIDED, IERROR
```

This call initializes MPI in the same way that a call to MPI\_INIT would. In addition, it initializes the thread environment. The argument required is used to specify the desired level of thread support. The possible values are listed in increasing order of thread support.

MPI\_THREAD\_SINGLE Only one thread will execute.

- MPI\_THREAD\_FUNNELED The process may be multithreaded, but the application must ensure that only the main thread makes MPI calls (for the definition of main thread, see MPI\_IS\_THREAD\_MAIN on page 485).
- MPI\_THREAD\_SERIALIZED The process may be multithreaded, and multiple threads may make MPI calls, but only one at a time: MPI calls are not made concurrently from two distinct threads (all MPI calls are "serialized").

MPI\_THREAD\_MULTIPLE Multiple threads may call MPI, with no restrictions.

These values are monotonic; i.e., MPI\_THREAD\_SINGLE < MPI\_THREAD\_FUNNELED < MPI\_THREAD\_SERIALIZED < MPI\_THREAD\_MULTIPLE.

Different processes in MPI\_COMM\_WORLD may require different levels of thread support.

The call returns in **provided** information about the actual level of thread support that will be provided by MPI. It can be one of the four values listed above.

The level(s) of thread support that can be provided by MPI\_INIT\_THREAD will depend on the implementation, and may depend on information provided by the user before the program started to execute (e.g., with arguments to mpiexec). If possible, the call will return provided = required. Failing this, the call will return the least supported level such that provided > required (thus providing a stronger level of support than required by the user). Finally, if the user requirement cannot be satisfied, then the call will return in provided the highest supported level.

A thread compliant MPI implementation will be able to return provided = MPI\_THREAD\_MULTIPLE. Such an implementation may always return provided = MPI\_THREAD\_MULTIPLE, irrespective of the value of required.

An MPI library that is not thread compliant must always return provided = MPI\_THREAD\_SINGLE, even if MPI\_INIT\_THREAD is called on a multithreaded process. The library should also return correct values for the MPI calls that can be executed before initialization, even if multiple threads have been spawned.

Rationale. Such code is erroneous, but if the MPI initialization is performed by a library, the error cannot be detected until MPI\_INIT\_THREAD is called. The requirements in the previous paragraph ensure that the error can be properly detected. (*End of rationale*.)

A call to MPI\_INIT has the same effect as a call to MPI\_INIT\_THREAD with a required = MPI\_THREAD\_SINGLE.

Vendors may provide (implementation dependent) means to specify the level(s) of thread support available when the MPI program is started, e.g., with arguments to mpiexec. This will affect the outcome of calls to MPI\_INIT and MPI\_INIT\_THREAD. Suppose, for example, that an MPI program has been started so that only MPI\_THREAD\_MULTIPLE is available. Then MPI\_INIT\_THREAD will return provided = MPI\_THREAD\_MULTIPLE, irrespective of the value of required; a call to MPI\_INIT will also initialize the MPI thread support level to MPI\_THREAD\_MULTIPLE. Suppose, instead, that an MPI program has been started so that all four levels of thread support are available. Then, a call to MPI\_INIT\_THREAD will return provided = required; alternatively, a call to MPI\_INIT will initialize the MPI thread support level to MPI\_THREAD\_SINGLE.

Rationale. Various optimizations are possible when MPI code is executed single-threaded, or is executed on multiple threads, but not concurrently: mutual exclusion code may be omitted. Furthermore, if only one thread executes, then the MPI library can use library functions that are not thread safe, without risking conflicts with user threads. Also, the model of one communication thread, multiple computation threads fits many applications well, e.g., if the process code is a sequential Fortran/C program with MPI calls that has been parallelized by a compiler for execution on an SMP node, in a cluster of SMPs, then the process computation is multithreaded, but MPI calls will likely execute on a single thread.

The design accommodates a static specification of the thread support level, for environments that require static binding of libraries, and for compatibility for current multithreaded MPI codes. (*End of rationale*.)

11

12 13

14

15

16 17 18

19

20 21

22

23 24

26

27

28

29

30

33

34

35

36

37

38 39

42

43 44

45

46

Advice to implementors. If provided is not MPI\_THREAD\_SINGLE then the MPI library should not invoke C or Fortran library calls that are not thread safe, e.g., in an environment where malloc is not thread safe, then malloc should not be used by the MPI library.

Some implementors may want to use different MPI libraries for different levels of thread support. They can do so using dynamic linking and selecting which library will be linked when MPI\_INIT\_THREAD is invoked. If this is not possible, then optimizations for lower levels of thread support will occur only when the level of thread support required is specified at link time.

Note that required need not be the same value on all processes of MPI\_COMM\_WORLD. (End of advice to implementors.)

As with MPI\_INIT, discussed in Section 11.2.1, the version for ISO C accepts the argc and argv that are provided by the arguments to main or NULL for both arguments.

The following function can be used to query the current level of thread support.

### MPI\_QUERY\_THREAD(provided)

OUT provided

provided level of thread support (integer)

#### C binding

int MPI\_Query\_thread(int \*provided)

#### Fortran 2008 binding

```
MPI_Query_thread(provided, ierror)
    INTEGER, INTENT(OUT) :: provided
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

MPI\_QUERY\_THREAD(PROVIDED, IERROR)
INTEGER PROVIDED, IERROR

The call returns in provided the current level of thread support, which will be the value returned in provided by MPI\_INIT\_THREAD, if MPI was initialized by a call to MPI\_INIT\_THREAD(). This function is only applicable when using the World Model to initialize MPI. In the case of applications using both the World Model and the Sessions Model, this function only returns the thread support level returned in provided by MPI\_INIT\_THREAD.

#### MPI\_IS\_THREAD\_MAIN(flag)

OUT flag true if calling thread is main thread, false otherwise (logical)

#### C binding

int MPI\_Is\_thread\_main(int \*flag)

#### Fortran 2008 binding

MPI\_Is\_thread\_main(flag, ierror)

```
LOGICAL, INTENT(OUT) :: flag
INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI_IS_THREAD_MAIN(FLAG, IERROR)
LOGICAL FLAG
INTEGER IERROR
```

This function can be called by a thread to determine if it is the main thread (the thread that called MPI\_INIT or MPI\_INIT\_THREAD). This function is only applicable when using the World Model to initialize MPI. In the case of applications using both the World Model and the Sessions Model, this function only returns the thread support level returned in provided by MPI\_INIT\_THREAD.

All routines listed in this section must be supported by all MPI implementations.

Rationale. MPI libraries are required to provide these calls even if they do not support threads, so that portable code that contains invocations to these functions can link correctly. MPI\_INIT continues to be supported so as to provide compatibility with current MPI codes. (End of rationale.)

Advice to users. It is possible to spawn threads before MPI is initialized, but MPI\_COMM\_WORLD and MPI\_COMM\_SELF cannot be used until the World Model is active, i.e. until MPI\_INIT\_THREAD is invoked by one thread (which, thereby, becomes the main thread). In particular, it is possible to enter the MPI execution with a multithreaded process.

In the World Model, the level of thread support provided is a global property of the MPI process that can be specified only once, when MPI is initialized on that process (or before). Portable third party libraries have to be written so as to accommodate any provided level of thread support. Otherwise, their usage will be restricted to specific level(s) of thread support. If such a library can run only with specific level(s) of thread support, e.g., only with MPI\_THREAD\_MULTIPLE, then MPI\_QUERY\_THREAD can be used to check whether the user initialized MPI to the correct level of thread support and. (End of advice to users.)

11.2.2 Finalizing MPI

```
MPI_FINALIZE()
```

C binding
int MPI\_Finalize(void)
Fortran 2008 binding

MPI\_Finalize(ierror)

INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI\_FINALIZE(IERROR)
INTEGER IERROR

This routine cleans up all MPI state associated with the World Model. If an MPI program terminates normally (i.e., not due to a call to MPI\_ABORT or an unrecoverable error) then each process must call MPI\_FINALIZE before it exits.

Before an MPI process invokes MPI\_FINALIZE, the process must perform all MPI calls needed to complete its involvement in MPI communications associated with the World Model. It must locally complete all MPI operations that it initiated and must execute matching calls needed to complete MPI communications initiated by other processes. For example, if the process executed a nonblocking send, it must eventually call MPI\_WAIT, MPI\_TEST, MPI\_REQUEST\_FREE, or any derived function; if the process is the target of a send, then it must post the matching receive; if it is part of a group executing a collective operation, then it must have completed its participation in the operation.

The call to MPI\_FINALIZE does not clean up MPI state associated with objects created using MPI\_SESSION\_INIT and other Sessions Model methods, nor objects created using the communicator returned by MPI\_COMM\_GET\_PARENT. See Sections 11.3 and 11.8.

The call to  $\mathsf{MPI\_FINALIZE}$  does not free objects created by  $\mathsf{MPI}$  calls; these objects are freed using  $\mathsf{MPI\_XXX\_FREE}$  calls.

MPI\_FINALIZE is collective over all connected processes. If no processes were spawned, accepted or connected then this means over MPI\_COMM\_WORLD; otherwise it is collective over the union of all processes that have been and continue to be connected, as explained in Section 11.10.4.

The following examples illustrate these rules.

**Example 11.2** The following code is correct

Example 11.3 Without a matching receive, the program is erroneous

**Example 11.4** This program is correct: Process 0 calls MPI\_Finalize after it has executed the MPI calls that complete the send operation. Likewise, process 1 executes the MPI call that completes the matching receive operation before it calls MPI\_Finalize.

```
42
Process 0
                                 Process 1
                                                                                    43
                                                                                    44
MPI_Init();
                                 MPI_Init();
                                 MPI_Recv(src=0);
                                                                                    45
MPI_Isend(dest=1);
                                                                                    46
MPI_Request_free();
                                 MPI_Finalize();
MPI_Finalize();
                                 exit();
exit();
```

**Example 11.5** This program is correct. The attached buffer is a resource allocated by the user, not by MPI; it is available to the user after MPI is finalized.

**Example 11.6** This program is correct. The cancel operation must succeed, since the send cannot complete normally. The wait operation, after the call to MPI\_Cancel, is local—no matching MPI call is required on process 1. Cancelling a send request by calling MPI\_CANCEL is deprecated.

Advice to implementors. Even though a process has executed all MPI calls needed to complete the communications it is involved with, such communication may not yet be completed from the viewpoint of the underlying MPI system. For example, a blocking send may have returned, even though the data is still buffered at the sender in an MPI buffer; an MPI process may receive a cancel request for a message it has completed receiving. The MPI implementation must ensure that a process has completed any involvement in MPI communication before MPI\_FINALIZE returns. Thus, if a process exits after the call to MPI\_FINALIZE, this will not cause an ongoing communication to fail. The MPI implementation should also complete freeing all objects marked for deletion by MPI calls that freed them. (End of advice to implementors.)

Failures may disrupt MPI operations during and after MPI finalization. A high quality implementation shall not deadlock in MPI finalization, even in the presence of failures. The normal rules for MPI error handling continue to apply. After MPI\_COMM\_SELF has been "freed" (see Section 11.2.4), errors that are not associated with a communicator, window, or file raise the initial error handler (set during the launch operation, see 11.8.4).

Although it is not required that all processes return from MPI\_FINALIZE, it is required that, when it has not failed or aborted, at least the MPI process that was assigned rank 0 in MPI\_COMM\_WORLD returns, so that users can know that the MPI portion of the computation is over. In addition, in a POSIX environment, users may desire to supply an exit code for each process that returns from MPI\_FINALIZE.

Note that a failure may terminate the MPI process that was assigned rank 0 in MPI\_COMM\_WORLD, in which case it is possible that no MPI process returns from MPI\_FINALIZE.

Advice to users. Applications that handle errors are encouraged to implement all rank-specific code before the call to MPI\_FINALIZE. In Example 11.7 below, the process with rank 0 in MPI\_COMM\_WORLD may have been terminated before, during, or after the call to MPI\_FINALIZE, possibly leading to the code after MPI\_FINALIZE never being executed. (End of advice to users.)

**Example 11.7** The following illustrates the use of requiring that at least one process return and that it be known that process 0 is one of the processes that return. One wants code like the following to work no matter how many processes return.

```
MPI_Comm_rank(MPI_COMM_WORLD, &myrank);
...
MPI_Finalize();
if (myrank == 0) {
    resultfile = fopen("outfile", "w");
    dump_results(resultfile);
    fclose(resultfile);
}
exit(0);
```

## 11.2.3 Determining Whether MPI Has Been Initialized When Using the World Model

One of the goals of MPI is to allow for layered libraries. For a library using the World Model, it needs to know if MPI has been initialized using MPI\_INIT or MPI\_INIT\_THREAD. In MPI the function MPI\_INITIALIZED is provided to tell if MPI had been initialized using the World Model. In the World Model, once MPI has been finalized it cannot be restarted. A library needs to be able to determine this to act accordingly. To achieve this the function MPI\_FINALIZED is needed.

```
MPI_INITIALIZED(flag)

OUT flag Flag is true if MPI_INIT has been called and false otherwise (logical)

C binding
int MPI_Initialized(int *flag)

Fortran 2008 binding

MPI_Initialized(flag, ierror)

LOGICAL, INTENT(OUT) :: flag
INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding

MPI_INITIALIZED(FLAG, IERROR)

LOGICAL FLAG
INTEGER IERROR
```

This routine may be used to determine whether MPI\_INIT or MPI\_INIT\_THREAD has been called. MPI\_INITIALIZED returns true if the calling process has called either of these MPI procedures. Whether MPI\_FINALIZE has been called does not affect the behavior of MPI\_INITIALIZED. This function must always be thread-safe, as defined in Section 11.6. This function returns false for applications using the Sessions Model exclusively.

```
MPI_FINALIZED(flag)
```

true if MPI was finalized (logical)

#### C binding

OUT

int MPI\_Finalized(int \*flag)

flag

#### Fortran 2008 binding

```
MPI_Finalized(flag, ierror)
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

MPI\_FINALIZED(FLAG, IERROR)
LOGICAL FLAG
INTEGER IERROR

This routine returns true if MPI\_FINALIZE has completed. It is valid to call MPI\_FINALIZED before MPI\_INIT and after MPI\_FINALIZE. This function must always be thread-safe, as defined in Section 11.6.

#### 11.2.4 Allowing User Functions at MPI Finalization

In the context of the World Model, there are times in which it would be convenient to have actions happen when an MPI process finalizes MPI. For example, a routine may do initializations that are useful until the MPI job (or that part of the job that is being terminated in the case of dynamically created processes) finalizes MPI. This can be accomplished in MPI by attaching an attribute to MPI\_COMM\_SELF with a callback function. When MPI\_FINALIZE is called, it will first execute the equivalent of an MPI\_COMM\_FREE on MPI\_COMM\_SELF. This will cause the delete callback function to be executed on all keys associated with MPI\_COMM\_SELF, in the reverse order that they were set on MPI\_COMM\_SELF. If no key has been attached to MPI\_COMM\_SELF, then no callback is invoked. The "freeing" of MPI\_COMM\_SELF occurs before any other parts of MPI are affected. Thus, for example, calling MPI\_FINALIZED will return false in any of these callback functions. Once done with MPI\_COMM\_SELF, the order and rest of the actions taken by MPI\_FINALIZE is not specified.

Advice to implementors. Since attributes can be added from any supported language, the MPI implementation needs to remember the creating language so the correct callback is made. Implementations that use the attribute delete callback on MPI\_COMM\_SELF internally should register their internal callbacks before returning from MPI\_INIT / MPI\_INIT\_THREAD, so that libraries or applications will not have portions of the MPI implementation shut down before the application-level callbacks are made. (End of advice to implementors.)

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

31

34

35

36

37

#### 11.3 The Sessions Model

There are a number of limitations with the World Model described in the preceding section. Among these are the following: MPI cannot be initialized from different application components without a priori knowledge or coordination; MPI cannot be initialized more than once; and MPI cannot be reinitialized after MPI\_FINALIZE has been called. This section describes an alternative approach to MPI initialization—the Sessions Model. With this approach, an MPI application, or components of the application, can instantiate MPI resources for the specific communication needs of this component. MPI\_COMM\_WORLD is not valid for use as a communicator. MPI\_INFO\_ENV is not valid for use as an info object when only using the Sessions Model. As described in Section 11.2.1, MPI must be initialized using the World Model to use this info object.

In the Sessions Model, MPI resources can be allocated and freed multiple times in an MPI process.

As shown in Figure 11.1, when using the Sessions Model, an MPI process instantiates an MPI Session handle, which can be used to query the runtime system about characteristics of the job within which the process is running, as well as other system resources. Using this information, the MPI process can then create an MPI Group based on application requirements and available resources, which in turn can be used to create an MPI Communicator, Window, or File. By judicious creation of communicators, an application only needs to allocate MPI resources based on its communication requirements. Although there are existing MPI interfaces for creating communicators which can, in principle, allow for resource optimizations within an MPI implementation, this can only be done following initialization of MPI.

For multithreaded applications the Sessions Model provides fine-grain control of the thread support level for MPI objects. It is possible to specify different thread support levels when creating different MPI Session handles. Thus different components of an application can use different thread support levels.

The Sessions Model introduces a concept of isolation. MPI objects derived from different MPI Session handles shall not be intermixed with each other in a single MPI procedure call. MPI objects derived from the Sessions Model shall not be intermixed in a single MPI procedure call with MPI objects derived from the World Model. MPI objects derived from the Sessions Model shall not be intermixed in a single MPI procedure call with MPI objects derived from the communicator obtained from a call to MPI\_COMM\_GET\_PARENT or MPI\_COMM\_JOIN.

This restriction does not apply to generalized requests (Section 13.2) as such requests are not associated directly with communicators or other MPI objects. Note however, the Sessions Model does not otherwise change the semantics or behavior of MPI objects.


**Unofficial Draft for Comment Only** 

38 39

42 43 44

> 46 47

45






Figure 11.1: Steps to creating an MPI Communicator from an MPI Session handle.

#### 11.3.1 Session Creation and Destruction Methods

#### MPI\_SESSION\_INIT(info, errhandler, session)

IN	info	info object to specify thread support level and MPI
		implementation specific resources (handle)
IN	errhandler	error handler to invoke in the event that an error is encountered during this function call (handle)
OUT	session	new session (handle)

#### C binding

#### Fortran 2008 binding

```
MPI_Session_init(info, errhandler, session, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
    TYPE(MPI_Session), INTENT(OUT) :: session
```

MPI\_Session and TYPE(MPI\_Session) as primary reference in the Declarations Index

43

44

45

#-error #-update5

Done

PR449

in

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
```

MPI\_SESSION\_INIT(INFO, ERRHANDLER, SESSION, IERROR)
INTEGER INFO, ERRHANDLER, SESSION, IERROR

The info argument is used to request MPI functionality requirements and possible MPI implementation specific capabilities. The following info key is predefined:

"mpi\_thread\_support\_level" used to request the thread support level required for MPI objects derived from the Session. Allowed values are "MPI\_THREAD\_SINGLE", "MPI\_THREAD\_FUNNELED", "MPI\_THREAD\_SERIALIZED", and "MPI\_THREAD\_MULTIPLE". Note that the thread support value is specified by a string rather than the integer values supplied to MPI\_INIT\_THREAD. The thread support level actually provided by the MPI implementation can be determined via a subsequent call to MPI\_SESSION\_GET\_INFO to return the info object associated with the Session. The default thread support level is MPI implementation dependent.

The errhandler argument specifies an error handler to invoke in the event that the Session instantiation call encounters an error. The error handler shall be either a pre-defined error handler (see 9.3) or one created using MPI\_SESSION\_CREATE\_ERRHANDLER. Session instantiation is intended to be a lightweight operation. An MPI process may instantiate multiple Sessions. MPI\_SESSION\_INIT is always thread safe; multiple threads within an application may invoke it concurrently.

Advice to users. Requesting "MPI\_THREAD\_SINGLE" thread support level is generally not recommended, because this will conflict with other components of an application requesting higher levels of thread support. (End of advice to users.)

Advice to implementors. Owing to the restrictions of the MPI\_THREAD\_SINGLE thread support level, implementators are discouraged from making this the default thread support level for Sessions. (End of advice to implementors.)

```
MPI_SESSION_FINALIZE(session)
```

IN session session to be finalized (handle)

#### C binding

int MPI\_Session\_finalize(MPI\_Session \*session)

#### Fortran 2008 binding

MPI\_Session\_finalize(session, ierror)
 TYPE(MPI\_Session), INTENT(INOUT) :: session
 INTEGER, OPTIONAL, INTENT(OUT) :: ierror

#### Fortran binding

MPI\_SESSION\_FINALIZE(SESSION, IERROR)
INTEGER SESSION, IERROR

This routine cleans up all MPI state associated with the supplied session. Every instantiated Session must be finalized using MPI\_SESSION\_FINALIZE. The handle session is set to MPI\_SESSION\_NULL by the call.

Before an MPI process invokes MPI\_SESSION\_FINALIZE, the process must perform all MPI calls needed to complete its involvement in MPI communications: it must locally complete all MPI operations that it initiated and it must execute matching calls needed to complete MPI communications initiated by other processes.

The call to MPI\_SESSION\_FINALIZE does not free objects created by MPI calls; these objects are freed using MPI\_XXX\_FREE calls.

MPI\_SESSION\_FINALIZE is collective over all MPI processes that are connected via MPI Communicators, Windows, or Files that were created as part of the Session and still exist. If processes were spawned, accepted, or connected using MPI Communicators created as part of this session, this operation is collective over the union of all processes that have been and continue to be connected via those objects, as explained in Section 11.10.4.

Advice to implementors. An MPI implementation should be able to implement the semantics of MPI\_SESSION\_FINALIZE without synchronization with other MPI processes, provided an application frees all MPI windows, closes all MPI files, and uses MPI\_COMM\_DISCONNECT to free all MPI communicators associated with a session prior to invoking MPI\_SESSION\_FINALIZE on the corresponding session handle. (End of advice to implementors.)

#### 11.3.2 Processes Sets

Process sets are the mechanism for MPI applications to query the runtime. Process sets are identified by process set names. Process set names have a *Uniform Resource Identifier* (URI) format. Two process set names are mandated: "mpi://WORLD" and

"mpi://SELF". Additional process set names may be defined, for example,

"mpix://UNIVERSE" and "hwloc://L3Cache" may be defined by the MPI implementation. The "mpi://" namespace is reserved for exclusive use by the MPI standard. Figure 11.2 depicts process sets that the runtime could associate with an instance of an MPI job. In this example, the two mandated process sets are defined, in addition to optional, implementation specific ones.

Mechanisms for defining process sets and how system resources are assigned to these sets is considered to be implementation dependent.

A process set caches key/value tuples that are accessible to the application via an MPI\_Info object. The "mpi\_size" key is mandatory for all process sets.




Figure 11.2: Examples of process sets. Illustrated are the two mandated process sets - "mpi://WORLD" and "mpi://SELF" - along with several optional ones that a runtime could define. In this example, MPI\_SESSION\_GET\_NUM\_PSETS would return five at each MPI process.

#### 11.3.3 Runtime Query Functions

#### MPI\_SESSION\_GET\_NUM\_PSETS(session, info, npset\_names)

IN	session	session (handle)
IN	info	info object (handle)
OUT	npset_names	number of available process sets (non-negative
		integer)

#### C binding

#### Fortran 2008 binding

```
MPI_Session_get_num_psets(session, info, npset_names, ierror)
    TYPE(MPI_Session), INTENT(IN) :: session
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, INTENT(OUT) :: npset_names
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

MPI\_SESSION\_GET\_NUM\_PSETS(SESSION, INFO, NPSET\_NAMES, IERROR)

#### INTEGER SESSION, INFO, NPSET\_NAMES, IERROR

This function is used to query the runtime for the number of available process sets in which the calling MPI process is a member. An MPI implementation is allowed to increase the number of available process sets during the execution of an MPI application when new process sets become available. However, MPI implementations are not allowed to change the index of a particular process set name, or to change the name of the process set at a particular index, or to delete a process set name once it has been added. When a process set becomes invalid, for example, when some processes become unreachable due to failures in the communication system, subsequent usage of the process set name should raise an error. For example, creating an MPI\_Group from such a process set might succeed because it is a local operation, but creating an MPI\_Comm from that group and attempting collective communication should raise an error.

Advice to implementors. It is anticipated that an MPI implementation may be relying on an external runtime system to provide process sets. Such runtime systems may have the ability to dynamically create process sets during the course of application execution. Requiring the number of process sets returned by

MPI\_SESSION\_GET\_NUM\_PSETS to be constant over the course of application execution would prevent an application from taking advantage of such capabilities. (*End of advice to implementors.*)

## MPI\_SESSION\_GET\_NTH\_PSET(session, info, n, pset\_len, pset\_name)

```
IN session session (handle)

IN info info object (handle)

IN n index of the desired process set name (integer)

INOUT pset_len length of the pset_name argument (integer)

OUT pset_name name of the nth process set (string)
```

#### C binding

#### Fortran 2008 binding

```
MPI_Session_get_nth_pset(session, info, n, pset_len, pset_name, ierror)
    TYPE(MPI_Session), INTENT(IN) :: session
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, INTENT(IN) :: n
    INTEGER, INTENT(INOUT) :: pset_len
    CHARACTER(LEN=*), INTENT(OUT) :: pset_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_SESSION_GET_NTH_PSET(SESSION, INFO, N, PSET_LEN, PSET_NAME, IERROR)
INTEGER SESSION, INFO, N, PSET_LEN, IERROR
CHARACTER*(*) PSET_NAME
```

This function returns the name of the nth process set in the supplied pset\_name buffer. pset\_len is the size of the buffer needed to store the nth process set name. If the pset\_len passed into the function is less than the actual buffer size needed for the process set name, then the string value returned in pset\_name is truncated. If pset\_len is set to 0, pset\_name is not changed. On return, the value of pset\_len will be set to the required buffer size to hold the process set name. In C, pset\_len includes the required space for the null terminator. In C, this function returns a null terminated string in all cases where the pset\_len input value is greater than 0.

If two MPI processes get the same process set name, then the intersection of the two process sets shall either be the empty set or identical to the union of the two process sets.

After a successful call to MPI\_SESSION\_GET\_NTH\_PSET, subsequent calls to routines that query information about the same process set name and same session handle must return the same information. An MPI implementation is not allowed to alter any of the returned process set names.

Process set names have an implementation-defined maximum length of MPI\_MAX\_PSET\_NAME\_LEN.

Advice to users. MPI\_MAX\_PSET\_NAME\_LEN might be very large, so it might not be wise to declare a string of that size. Users are encouraged to use MPI\_SESSION\_GET\_NTH\_PSET both for obtaining the length of a pset\_name and the process set name. (End of advice to users.)

```
MPI_SESSION_GET_INFO(session, info_used)
```

```
IN session session (handle)
OUT info_used see explanation below (handle)
```

#### C binding

```
int MPI_Session_get_info(MPI_Session session, MPI_Info *info_used)
```

#### Fortran 2008 binding

```
MPI_Session_get_info(session, info_used, ierror)
    TYPE(MPI_Session), INTENT(IN) :: session
    TYPE(MPI_Info), INTENT(OUT) :: info_used
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_SESSION_GET_INFO(SESSION, INFO_USED, IERROR)
INTEGER SESSION, INFO_USED, IERROR
```

MPI\_SESSION\_GET\_INFO returns a new info object containing the hints of the MPI Session associated with session. The current setting of all hints related to this MPI Session is returned in info\_used. An MPI implementation is required to return all hints that are supported by the implementation and have default values specified; any user-supplied hints that were not ignored by the implementation; and any additional hints that were set by the implementation. If no such hints exist, a handle to a newly created info object is returned that contains no key/value pair. The user is responsible for freeing info\_used via MPI\_INFO\_FREE.

```
MPI_SESSION_GET_PSET_INFO(session, pset_name, info)
2
       IN
                 session
                                             session (handle)
3
       IN
                 pset_name
                                             name of process set (string)
4
5
       OUT
                 info
                                             info object containing information about the given
6
                                             process set (handle)
7
     C binding
9
     int MPI_Session_get_pset_info(MPI_Session session, const char *pset_name,
10
                    MPI_Info *info)
11
     Fortran 2008 binding
12
     MPI_Session_get_pset_info(session, pset_name, info, ierror)
13
          TYPE(MPI_Session), INTENT(IN) :: session
14
          CHARACTER(LEN=*), INTENT(IN) :: pset_name
15
          TYPE(MPI_Info), INTENT(OUT) :: info
16
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
17
18
     Fortran binding
19
     MPI_SESSION_GET_PSET_INFO(SESSION, PSET_NAME, INFO, IERROR)
20
          INTEGER SESSION, INFO, IERROR
21
          CHARACTER*(*) PSET_NAME
22
          This function is used to query properties of a specific process set. The returned info
23
     object can be queried with existing MPI info object query functions. One key/value pair
24
     must be defined, "mpi_size". The value of the "mpi_size" key specifies the number of MPI
25
     processes in the process set. The user is responsible for freeing the returned MPI_Info object.
26
27
     11.3.4 Sessions Model Examples
28
29
     This section presents several examples of how to use MPI Sessions to create MPI Groups
30
     and MPI Communicators.
31
32
     Example 11.8 Simple example illustrating creation of an MPI communicator using the
33
     Sessions Model.
34
35
     #include <stdio.h>
36
     #include <stdlib.h>
37
     #include <string.h>
38
     #include "mpi.h"
39
40
     static MPI_Session lib_shandle = MPI_SESSION_NULL;
41
     static MPI_Comm lib_comm = MPI_COMM_NULL;
42
43
     int library_foo_init(void)
44
45
         int rc, flag;
46
         int ret = 0;
```

const char pset\_name[] = "mpi://WORLD";

const char mt\_key[] = "mpi\_thread\_support\_level";

47

```
const char mt_value[] = "MPI_THREAD_MULTIPLE";
char out_value[100];
                        /* large enough */
MPI_Group wgroup = MPI_GROUP_NULL;
MPI_Info sinfo = MPI_INFO_NULL;
MPI_Info tinfo = MPI_INFO_NULL;
MPI_Info_create(&sinfo);
MPI_Info_set(sinfo, mt_key, mt_value);
rc = MPI_Session_init(sinfo, MPI_ERRORS_RETURN,
                        &lib_shandle);
                                                                                 11
if (rc != MPI_SUCCESS) {
   ret = -1;
                                                                                 12
                                                                                 13
   goto fn_exit;
}
                                                                                 14
                                                                                 15
                                                                                 16
                                                                                 17
 * check we got thread support level foo library needs
                                                                                 18
                                                                                 19
rc = MPI_Session_get_info(lib_shandle, &tinfo);
if (rc != MPI_SUCCESS) {
                                                                                 20
                                                                                 21
   ret = -1;
   goto fn_exit;
                                                                                 22
}
                                                                                 23
                                                                                 24
                                                                                 25
MPI_Info_get(tinfo, mt_key, sizeof(out_value);
                                                                                 26
              out_value, &flag);
if (flag != 1) {
                                                                                 27
   printf("Could not find key %s\n", mt_key);
                                                                                 28
                                                                                 29
   ret = -1;
                                                                                 30
   goto fn_exit;
}
                                                                                 33
if (strcmp(out_value, mt_value)) {
                                                                                 34
   printf("Did not get thread multiple support, got %s\n",
          out_value);
                                                                                 35
   ret = -1;
                                                                                 36
                                                                                 37
   goto fn_exit;
}
                                                                                 38
                                                                                 39
/*
 * create a group from the WORLD process set
                                                                                 42
rc = MPI_Group_from_session_pset(lib_shandle,
                                                                                 43
                                                                                 44
                                   pset_name,
                                                                                 45
                                   &wgroup);
                                                                                 46
if (rc != MPI_SUCCESS) {
   ret = -1;
   goto fn_exit;
```

```
1
        }
2
         /*
          * get a communicator
          */
6
        rc = MPI_Comm_create_from_group(wgroup,
                                             "org.mpi-forum.mpi-v4_0.example-ex10_8",
                                             MPI_INFO_NULL,
9
                                             MPI_ERRORS_RETURN,
10
                                             &lib_comm);
11
        if (rc != MPI_SUCCESS) {
12
            ret = -1;
13
            goto fn_exit;
14
        }
15
16
         /*
17
          * free group, library doesn't need it.
18
19
20
     fn_exit:
21
        MPI_Group_free(&wgroup);
22
23
         if (sinfo != MPI_INFO_NULL) {
24
            MPI_Info_free(&sinfo);
        }
26
27
         if (tinfo != MPI_INFO_NULL) {
28
            MPI_Info_free(&tinfo);
29
        }
30
         if (ret != 0) {
            MPI_Session_finalize(&lib_shandle);
33
        }
34
35
        return ret;
36
37
         Example 11.8 shows how the pre-defined "mpi://WORLD" process set can be used to
38
     first create a local MPI group and then subsequently to create an MPI communicator from
39
     this group.
40
41
     Example 11.9 This example illustrates the use of Process Set query functions to select a
     Process Set to use for MPI Group creation.
43
44
     #include <stdio.h>
45
     #include <stdlib.h>
^{46}
     #include <string.h>
47
     #include "mpi.h"
```

```
int main(int argc, char *argv[])
   int i, n_psets, psetlen, rc, ret;
   int valuelen;
   int flag = 0;
   char *pset_name = NULL;
   char *info_val = NULL;
   MPI_Session shandle = MPI_SESSION_NULL;
   MPI_Info sinfo = MPI_INFO_NULL;
   MPI_Group pgroup = MPI_GROUP_NULL;
                                                                                    11
   if (argc < 2) {
                                                                                    12
      fprintf(stderr, "A process set name fragment is required\n");
                                                                                    13
                                                                                    14
      return -1;
                                                                                    15
   }
                                                                                    16
   rc = MPI_Session_init(MPI_INFO_NULL, MPI_ERRORS_RETURN, &shandle);
                                                                                    18
   if (rc != MPI_SUCCESS) {
      fprintf(stderr, "Could not initialize session, bailing out\n");
                                                                                    19
      return -1;
                                                                                    20
   }
                                                                                    21
                                                                                    22
   MPI_Session_get_num_psets(shandle, MPI_INFO_NULL, &n_psets);
                                                                                    23
                                                                                    24
   for (i=0, pset_name=NULL; i<n_psets; i++) {</pre>
                                                                                    25
                                                                                    26
       psetlen = 0;
       MPI_Session_get_nth_pset(shandle, MPI_INFO_NULL, i,
                                                                                    27
                                                                                    28
                                  &psetlen, NULL);
                                                                                    29
       pset_name = (char *)malloc(sizeof(char) * psetlen);
                                                                                    30
       MPI_Session_get_nth_pset(shandle, MPI_INFO_NULL, i,
                                                                                    31
                                  &psetlen, pset_name);
       if (strstr(pset_name, argv[1]) != NULL) break;
                                                                                    33
                                                                                    34
       free(pset_name);
       pset_name = NULL;
                                                                                    35
   }
                                                                                    36
                                                                                    37
   /*
                                                                                    39
    * get instance of an info object for this Session
                                                                                    42
   MPI_Session_get_pset_info(shandle, pset_name, &sinfo);
   MPI_Info_get_valuelen(sinfo, "mpi_size", &valuelen, &flag);
                                                                                    43
                                                                                    44
   info_val = (char *)malloc(valuelen+1);
   MPI_Info_get(sinfo, "mpi_size", valuelen, info_val, &flag);
                                                                                    45
                                                                                    46
   free(info_val);
                                                                                    47
   /*
```

```
1
         * create a group from the process set
2
         */
        rc = MPI_Group_from_session_pset(shandle, pset_name,
                                            &pgroup);
6
        ret = (rc == MPI_SUCCESS) ? 0 : -1;
        free(pset_name);
9
        MPI_Group_free(&pgroup);
10
        MPI_Info_free(&sinfo);
11
        MPI_Session_finalize(&shandle);
12
13
        fprintf(stderr, "Test completed ret = %d\n", ret);
14
        return ret;
15
16
     }
17
```

19

20

21 22

23

24

25

48

Example 11.9 illustrates several aspects of the Sessions Model. First, the default error handler can be specified when instantiating a Session instance. Second, there must be at least two process sets associated with a Session. Third, the example illustrates use of the Sessions info object and the one required key: "mpi\_size".

**Example 11.10** A Fortran 2008 example illustrating how to obtain information about available process sets, create an MPI Group from a process set, and subsequently create an MPI Communicator.

```
26
     PROGRAM MAIN
27
         USE mpi_f08
28
         IMPLICIT NONE
29
         INTEGER :: pset_len, ierror, n_psets
30
         CHARACTER(LEN=:), ALLOCATABLE :: pset_name
         TYPE(MPI_Session) :: shandle
         TYPE(MPI_Group) :: pgroup
33
         TYPE(MPI_Comm) :: pcomm
34
35
         CALL MPI_Session_init(MPI_INFO_NULL, MPI_ERRORS_RETURN, &
36
                               shandle, ierror)
37
         IF (ierror .NE. MPI_SUCCESS) THEN
            WRITE(*,*) "MPI_Session_init failed"
            ERROR STOP
         END IF
41
42
         CALL MPI_Session_get_num_psets(shandle, MPI_INFO_NULL, n_psets)
43
         IF (n_psets .LT. 2) THEN
44
            WRITE(*,*) "MPI_Session_get_num_psets didn't return at least 2 psets"
45
            ERROR STOP
46
         END IF
47
```

14

15

16

18

19

20 21 22

23

26

27 28 29

30

33 34

35

36 37

42

43

44

45

46 47

```
Just get the second pset's length and name
    Note that index values are zero-based, even in Fortran
    pset_len = 0
    CALL MPI_Session_get_nth_pset(shandle, MPI_INFO_NULL, 1,
                                  pset_len, pset_name)
    ALLOCATE(CHARACTER(LEN=pset_len)::pset_name)
    CALL MPI_Session_get_nth_pset(shandle, MPI_INFO_NULL, 1,
                                  pset_len, pset_name)
!
    create a group from the pset
!
    CALL MPI_Group_from_session_pset(shandle, pset_name, pgroup)
    free the buffer used for the pset name
ļ
    DEALLOCATE(pset_name)
!
    create a MPI communicator from the group
                                             "session_example",
    CALL MPI_Comm_create_from_group(pgroup,
                                             MPI_INFO_NULL,
                                             MPI_ERRORS_RETURN,
                                             pcomm)
    CALL MPI_Barrier(pcomm, ierror)
    IF (ierror .NE. MPI_SUCCESS) THEN
        WRITE(*,*) "Barrier call on communicator failed"
        ERROR STOP
    END IF
    CALL MPI_Comm_free(pcomm)
    CALL MPI_Group_free(pgroup)
    CALL MPI_Session_finalize(shandle, ierror)
END PROGRAM MAIN
```

Note in this example that the call to MPI\_SESSION\_FINALIZE may block in order to ensure that the calling MPI process has completed its involvement in the preceding MPI\_BARRIER operation. If MPI\_COMM\_DISCONNECT had been used instead of MPI\_COMM\_FREE, the example would have blocked in MPI\_COMM\_DISCONNECT rather than MPI\_SESSION\_FINALIZE.

# 11.4 Common Elements of Both Process Models

### 11.4.1 MPI Functionality that is Always Available

Some MPI functions may be invoked at any time, including prior to calling MPI\_INIT or MPI\_SESSION\_INIT, and following MPI finalization, independent of whether the World Model, Sessions Model, or both are used. These functions can be called concurrently by multiple threads within an MPI Process. Table 11.1 lists the applicable MPI functions.

MPI_INITIALIZED
MPI_FINALIZED
MPI_GET_VERSION
MPI_GET_LIBRARY_VERSION
MPI_INFO_CREATE
MPI_INFO_CREATE_ENV
MPI_INFO_SET
MPI_INFO_DELETE
MPI_INFO_GET
MPI_INFO_GET_VALUELEN
MPI_INFO_GET_NKEYS
MPI_INFO_GET_NTHKEY
MPI_INFO_DUP
MPI_INFO_FREE
MPI_INFO_F2C
MPI_INFO_C2F
MPI_SESSION_CREATE_ERRHANDLER
MPI_SESSION_CALL_ERRHANDLER
MPI_ERRHANDLER_FREE
MPI_ERRHANDLER_F2C
MPI_ERRHANDLER_C2F
MPI_ERROR_STRING
MPI_ERROR_CLASS

Table 11.1: List of MPI Functions that can be called at any time within an MPI program, including prior to MPI initialization and following MPI finalization

In addition to the functions listed in Table 11.1, any function with the prefix MPI\_T\_ (within the constraints for functions with this prefix listed in Section 15.3.4) may also be called prior to MPI initialization and after MPI finalization.

### 11.4.2 Aborting MPI Processes

# MPI\_ABORT(comm, errorcode)

IN comm communicator of tasks to abort (handle)

IN errorcode error code to return to invoking environment (integer)

### C binding

int MPI\_Abort(MPI\_Comm comm, int errorcode)

#### Fortran 2008 binding

```
MPI_Abort(comm, errorcode, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: errorcode
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

```
MPI_ABORT(COMM, ERRORCODE, IERROR)
INTEGER COMM, ERRORCODE, IERROR
```

This routine makes a "best attempt" to abort all MPI processes in the group of comm. This function does not require that the invoking environment take any action with the error code. However, a Unix or POSIX environment should handle this as a return errorcode from the main program.

It may not be possible for an MPI implementation to abort only the processes represented by comm if this is a subset of the processes. In this case, the MPI implementation should attempt to abort all the connected processes but should not abort any unconnected processes. When using the World Model, and if no processes were spawned, accepted, or connected then this has the effect of aborting all the processes associated with MPI\_COMM\_WORLD. In the case of the Sessions Model, if an MPI process has instantiated multiple sessions, the union of the process sets in these sessions are considered connected processes. Thus invoking MPI\_ABORT on a communicator derived from one of these sessions will result in all MPI processes in this union being aborted.

Advice to implementors. After aborting a subset of processes, a high quality implementation should be able to provide error handling for communicators, windows, and files involving both aborted and non-aborted processes. As an example, if the user changes the error handler for MPI\_COMM\_WORLD to MPI\_ERRORS\_RETURN or a custom error handler, when a subset of MPI\_COMM\_WORLD is aborted, the remaining processes in MPI\_COMM\_WORLD should be able to continue communicating with each other and receive an appropriate error code when attempting communication with an aborted process (e.g., an error of class MPI\_ERR\_PROC\_ABORTED). A high quality implementation should support equivalent behavior for communicators derived from sessions. (End of advice to implementors.)

Advice to users. Whether the errorcode is returned from the executable or from the MPI process startup mechanism (e.g., mpiexec), is an aspect of quality of the MPI library but not mandatory. (End of advice to users.)

Advice to implementors. Where possible, a high-quality implementation will try to return the errorcode from the MPI process startup mechanism (e.g. mpiexec or singleton init). (End of advice to implementors.)

# 11.5 Portable MPI Process Startup

A number of implementations of MPI provide a startup command for MPI programs that is of the form

```
mpirun <mpirun arguments> <program> <program arguments>
```

Separating the command to start the program from the program itself provides flexibility, particularly for network and heterogeneous implementations. For example, the startup script need not run on one of the machines that will be executing the MPI program itself.

Having a standard startup mechanism also extends the portability of MPI programs one step further, to the command lines and scripts that manage them. For example, a validation suite script that runs hundreds of programs can be a portable script if it is written using such a standard startup mechanism. In order that the "standard" command not be confused with existing practice, which is not standard and not portable among implementations, instead of mpirun MPI specifies mpiexec.

While a standardized startup mechanism improves the usability of MPI, the range of environments is so diverse (e.g., there may not even be a command line interface) that MPI cannot mandate such a mechanism. Instead, MPI specifies an mpiexec startup command and recommends but does not require it, as advice to implementors. However, if an implementation does provide a command called mpiexec, it must be of the form described below.

It is suggested that

```
mpiexec -n <numprocs>   program>
```

be at least one way to start cprogram> with an initial set of <numprocs> processes, which will be accessible as the process set named "mpi://world" in the Sessions Model and/or used to the form the group associated with the built-in communicator, MPI\_COMM\_WORLD in the World Model. Other arguments to mpiexec may be implementation-dependent.

Advice to implementors. Implementors, if they do provide a special startup command for MPI programs, are advised to give it the following form. The syntax is chosen in order that mpiexec be able to be viewed as a command-line version of MPI\_COMM\_SPAWN (See Section 11.8.4).

Analogous to MPI\_COMM\_SPAWN, we have

mpiexec -n	<maxj< th=""><th>procs&gt;</th></maxj<>	procs>
-soft	<	>
-host	<	>
-arch	<	>
-wdir	<	>
-path	<	>
-file	<	>
-initial-errhandler	<	>

<command line>

for the case where a single command line for the application program and its arguments will suffice. See Section 11.8.4 for the meanings of these arguments. For the case corresponding to MPI\_COMM\_SPAWN\_MULTIPLE there are two possible formats:

Form A:

```
mpiexec { <above arguments> } : { ... } : { ... } : ... ;
```

As with MPI\_COMM\_SPAWN, all the arguments are optional. (Even the -n x argument is optional; the default is implementation dependent. It might be 1, it might be taken from an environment variable, or it might be specified at compile time.) The names and meanings of the arguments are taken from the keys in the info argument to MPI\_COMM\_SPAWN. There may be other, implementation-dependent arguments as well.

Note that Form A, though convenient to type, prevents colons from being program arguments. Therefore an alternate, file-based form is allowed:

Form B:

```
mpiexec -configfile <filename>
```

where the lines of <filename> are of the form separated by the colons in Form A. Lines beginning with '#' are comments, and lines may be continued by terminating the partial line with '\'.

**Example 11.11** Start 16 instances of myprog on the current or default machine:

```
mpiexec -n 16 myprog
```

Example 11.12 Start 10 instances of myprog on the machine called ferrari:

```
mpiexec -n 10 -host ferrari myprog
```

**Example 11.13** Start 3 instances of the same program myprog with different command-line arguments:

```
mpiexec myprog infile1: myprog infile2: myprog infile3
```

**Example 11.14** Start 5 instances of the ocean program on x86\_64 hosts and 10 instances of the atmos program on Power9 hosts (Form B):

```
mpiexec -n 5 -arch x86_64 ocean : -n 10 -arch power9 atmos
```

It is assumed that the implementation in this case has a method for choosing hosts of the appropriate type. Their ranks are in the order specified.

**Example 11.15** Start the ocean program on five Suns and the atmos program on 10 RS/6000's (Form B):

```
mpiexec -configfile myfile
where myfile contains
-n 5 -arch sun ocean
-n 10 -arch rs6000 atmos
```

(End of advice to implementors.)

# 11.6 MPI and Threads

 This section specifies the interaction between MPI calls and threads. Although thread compliance is not required, the standard specifies how threads are to work if they are provided. The section lists minimal requirements for **thread compliant** MPI implementations and defines functions that can be used for initializing the thread environment. MPI may be implemented in environments where threads are not supported or perform poorly. Therefore, MPI implementations are not required to be thread compliant as defined in this section. Regardless of whether or not the MPI implementation is thread compliant, a subset of MPI functions must always be thread safe. A complete list of such MPI functions is given in Table 11.1. When a thread is executing one of these routines, if another concurrently running thread also makes an MPI call, the outcome will be as if the calls executed in some order.

This section generally assumes a thread package similar to POSIX threads [44], but the syntax and semantics of thread calls are not specified here—these are beyond the scope of this document.

# 11.6.1 General

In a thread-compliant implementation, an MPI process is a process that may be multithreaded. Each thread can issue MPI calls; however, threads are not separately addressable: a rank in a send or receive call identifies a process, not a thread. A message sent to a process can be received by any thread in this process.

Rationale. This model corresponds to the POSIX model of interprocess communication: the fact that a process is multithreaded, rather than single-threaded, does not affect the external interface of this process. MPI implementations in which MPI 'processes' are POSIX threads inside a single POSIX process are not thread-compliant by this definition (indeed, their "processes" are single-threaded). (End of rationale.)

Advice to users. It is the user's responsibility to prevent races when threads within the same application post conflicting communication calls. The user can make sure that two threads in the same process will not issue conflicting communication calls by using distinct communicators at each thread. (End of advice to users.)

The two main requirements for a thread-compliant implementation are listed below.

- 1. All MPI calls are *thread-safe*, i.e., two concurrently running threads may make MPI calls and the outcome will be as if the calls executed in some order, even if their execution is interleaved.
- 2. Blocking MPI calls will block the calling thread only, allowing another thread to execute, if available. The calling thread will be blocked until the event on which it is waiting occurs. Once the blocked communication is enabled and can proceed, then the call will complete and the thread will be marked runnable, within a finite time. A blocked thread will not prevent progress of other runnable threads on the same process, and will not prevent them from executing MPI calls.

Example 11.16 Process 0 consists of two threads. The first thread executes a blocking send call MPI\_Send(buff1, count, type, 0, 0, comm), whereas the second thread executes a blocking receive call MPI\_Recv(buff2, count, type, 0, 0, comm, &status), i.e., the first thread sends a message that is received by the second thread. This communication should always succeed. According to the first requirement, the execution will correspond to some interleaving of the two calls. According to the second requirement, a call can only block the calling thread and cannot prevent progress of the other thread. If the send call went ahead of the receive call, then the sending thread may block, but this will not prevent the receiving thread from executing. Thus, the receive call will occur. Once both calls occur, the communication is enabled and both calls will complete. On the other hand, a single-threaded process that posts a send, followed by a matching receive, may deadlock. The progress requirement for multithreaded implementations is stronger, as a blocked call cannot prevent progress in other threads.

Advice to implementors. MPI calls can be made thread-safe by executing only one at a time, e.g., by protecting MPI code with one process-global lock. However, blocked operations cannot hold the lock, as this would prevent progress of other threads in the process. The lock is held only for the duration of an atomic, locally-completing suboperation such as posting a send or completing a send, and is released in between. Finer locks can provide more concurrency, at the expense of higher locking overheads. Concurrency can also be achieved by having some of the MPI protocol executed by separate server threads. (End of advice to implementors.)

### 11.6.2 Clarifications

Initialization and Completion When using the World Model, the call to MPI\_FINALIZE should occur on the same thread that initialized MPI. We call this thread the **main thread**. The call should occur only after all process threads have completed their MPI calls, and have no pending communications or I/O operations.

Rationale. This constraint simplifies implementation. (End of rationale.)

Threads and the Sessions Model The Sessions Model provides a finer-grain approach to controlling the interaction between MPI calls and threads. When using this model, the desired level of thread support is specified at Session initialization time. See Section 11.3. Thus it is possible for communicators and other MPI objects derived from one Session

to provide a different level of thread support than those created from another Session for which a different level of thread support was requested. Depending on the level of thread support requested at Session initialization time, different threads in a MPI process can make concurrent calls to MPI when using MPI objects derived from different session handles. Note that the requested and provided level of thread support when creating a Session may influence the granted level of thread support in a subsequent invocation of MPI\_SESSION\_INIT. Likewise, if the application at some point calls

MPI\_INIT\_THREAD, the requested and granted level of thread support may influence the granted level of thread support for subsequent calls to MPI\_SESSION\_INIT. Similarly, if the application calls MPI\_INIT\_THREAD after a call to MPI\_SESSION\_INIT, the level of thread support returned from MPI\_INIT\_THREAD may be similarly influenced by the requested level of thread support in the prior call to MPI\_SESSION\_INIT.

In addition, if an MPI application is only using the Sessions Model, the provided thread support level returned by MPI\_QUERY\_THREAD is the same as that returned prior to invocation of MPI\_INIT\_THREAD or MPI\_INIT. If the application also used the World Model in some component of the application, MPI\_QUERY\_THREAD will return the level of thread support returned by the original call to MPI\_INIT\_THREAD.

Multiple threads completing the same request. A program in which two threads block, waiting on the same request, is erroneous. Similarly, the same request cannot appear in the array of requests of two concurrent MPI\_{WAIT|TEST}\_{ANY|SOME|ALL} calls. In MPI, a request can only be completed once. Any combination of wait or test that violates this rule is erroneous.

Rationale. This restriction is consistent with the view that a multithreaded execution corresponds to an interleaving of the MPI calls. In a single threaded implementation, once a wait is posted on a request the request handle will be nullified before it is possible to post a second wait on the same handle. With threads, an MPI\_WAIT{ANY|SOME|ALL} may be blocked without having nullified its request(s) so it becomes the user's responsibility to avoid using the same request in an MPI\_WAIT on another thread. This constraint also simplifies implementation, as only one thread will be blocked on any communication or I/O event. (End of rationale.)

Probe A receive call that uses source and tag values returned by a preceding call to MPI\_PROBE or MPI\_IPROBE will receive the message matched by the probe call only if there was no other matching receive after the probe and before that receive. In a multi-threaded environment, it is up to the user to enforce this condition using suitable mutual exclusion logic. This can be enforced by making sure that each communicator is used by only one thread on each process. Alternatively, MPI\_MPROBE or MPI\_IMPROBE can be used.

Collective calls Matching of collective calls on a communicator, window, or file handle is done according to the order in which the calls are issued at each process. If concurrent threads issue such calls on the same communicator, window or file handle, it is up to the user to make sure the calls are correctly ordered, using interthread synchronization.

Advice to users. With three concurrent threads in each MPI process of a communicator comm, it is allowed that thread A in each MPI process calls a collective operation

on comm, thread B calls a file operation on an existing filehandle that was formerly opened on comm, and thread C invokes one-sided operations on an existing window handle that was also formerly created on comm. (*End of advice to users.*)

Rationale. As specified in MPI\_FILE\_OPEN and MPI\_WIN\_CREATE, a file handle and a window handle inherit only the group of processes of the underlying communicator, but not the communicator itself. Accesses to communicators, window handles and file handles cannot affect one another. (*End of rationale*.)

Advice to implementors. If the implementation of file or window operations internally uses MPI communication then a duplicated communicator may be cached on the file or window object. (End of advice to implementors.)

Error handlers An error handler does not necessarily execute in the context of the thread that made the error-raising MPI call; the error handler may be executed by a thread that is distinct from the thread that will return the error code.

Rationale. The MPI implementation may be multithreaded, so that part of the communication protocol may execute on a thread that is distinct from the thread that made the MPI call. The design allows the error handler to be executed on the thread where the error is raised. (End of rationale.)

Interaction with signals and cancellations The outcome is undefined if a thread that executes an MPI call is cancelled (by another thread), or if a thread catches a signal while executing an MPI call. However, a thread of an MPI process may terminate, and may catch signals or be cancelled by another thread when not executing MPI calls.

Rationale. Few C library functions are signal safe, and many have cancellation points—points at which the thread executing them may be cancelled. The above restriction simplifies implementation (no need for the MPI library to be "async-cancelsafe" or "async-signal-safe"). (End of rationale.)

Advice to users. Users can catch signals in separate, non-MPI threads (e.g., by masking signals on MPI calling threads, and unmasking them in one or more non-MPI threads). A good programming practice is to have a distinct thread blocked in a call to signal to each user expected signal that may occur. Users must not catch signals used by the MPI implementation; as each MPI implementation is required to document the signals used internally, users can avoid these signals. (End of advice to users.)

Advice to implementors. The MPI library should not invoke library calls that are not thread safe, if multiple threads execute. (End of advice to implementors.)

# 11.7 The Dynamic Process Model

The dynamic process model allows for the creation and cooperative termination of processes after an MPI application has started. It provides a mechanism to establish communication between the newly created processes and the existing MPI application. It also provides a mechanism to establish communication between two existing MPI applications, even when one did not "start" the other.

### 11.7.1 Starting Processes

MPI applications may start new processes through an interface to an external process manager.

MPI\_COMM\_SPAWN starts MPI processes and establishes communication with them, returning an inter-communicator. MPI\_COMM\_SPAWN\_MULTIPLE starts several different binaries (or the same binary with different arguments), placing them in the same MPI\_COMM\_WORLD and returning an inter-communicator.

MPI uses the group abstraction to represent processes. A process is identified by a (group, rank) pair.

### 11.7.2 The Runtime Environment

The MPI\_COMM\_SPAWN and MPI\_COMM\_SPAWN\_MULTIPLE routines provide an interface between MPI and the *runtime environment* of an MPI application. The difficulty is that there is an enormous range of runtime environments and application requirements, and MPI must not be tailored to any particular one.

MPI assumes, implicitly, the existence of an environment in which an application runs. It does not provide "operating system" services, such as a general ability to query what processes are running, to kill arbitrary processes, to find out properties of the runtime environment (how many processors, how much memory, etc.). Complex interaction of an MPI application with its runtime environment should be done through an environment-specific API.

At some low level, obviously, MPI must be able to interact with the runtime system, but the interaction is not visible at the application level and the details of the interaction are not specified by the MPI standard.

In many cases, it is impossible to keep environment-specific information out of the MPI interface without seriously compromising MPI functionality. To permit applications to take advantage of environment-specific functionality, many MPI routines take an info argument that allows an application to specify environment-specific information. There is a tradeoff between functionality and portability: applications that make use of environment-specific info are not portable.

MPI does not require the existence of an underlying "virtual machine" model, in which there is a consistent global view of an MPI application and an implicit "operating system" managing resources and processes. For instance, processes spawned by one task may not be visible to another; additional hosts added to the runtime environment by one process may not be visible in another process; tasks spawned by different processes may not be automatically distributed over available resources.

Interaction between MPI and the runtime environment is limited to the following areas:

- A process may start new processes with MPI\_COMM\_SPAWN and MPI\_COMM\_SPAWN\_MULTIPLE.
- When a process spawns a child process, it may optionally use an info argument to tell the runtime environment where or how to start the process. This extra information may be opaque to MPI.
- An attribute MPI\_UNIVERSE\_SIZE (See Section 11.10.1) on MPI\_COMM\_WORLD tells a program how "large" the initial runtime environment is, namely how many processes

can usefully be started in all. One can subtract the size of MPI\_COMM\_WORLD from this value to find out how many processes might usefully be started in addition to those already running.

# 11.8 Process Manager Interface

#### 11.8.1 Processes in MPI

A process is represented in MPI by a (group, rank) pair. A (group, rank) pair specifies a unique process but a process does not determine a unique (group, rank) pair, since a process may belong to several groups.

## 11.8.2 Starting Processes and Establishing Communication

The following routine starts a number of MPI processes and establishes communication with them, returning an inter-communicator.

Advice to users. It is possible in MPI to start an SPMD or MPMD application with a fixed number of processes after initialization by first starting one process and having that process start its siblings with MPI\_COMM\_SPAWN. This practice is discouraged primarily for reasons of performance. If possible, it is preferable to start all processes at once, as a single MPI application. (End of advice to users.)

# MPI\_COMM\_SPAWN(command, argv, maxprocs, info, root, comm, intercomm, array\_of\_errcodes)

IN	command	name of program to be spawned (string, significant only at root)
IN	argv	arguments to ${\sf command}$ (array of strings, significant only at root)
IN	maxprocs	maximum number of processes to start (integer, significant only at root)
IN	info	a set of key-value pairs telling the runtime system where and how to start the processes (handle, significant only at root)
IN	root	rank of process in which previous arguments are examined (integer)
IN	comm	intra-communicator containing group of spawning processes (handle)
OUT	intercomm	inter-communicator between original group and the newly spawned group (handle)
OUT	array_of_errcodes	one code per process (array of integer)

### C binding

```
int MPI_Comm_spawn(const char *command, char *argv[], int maxprocs,
             MPI_Info info, int root, MPI_Comm comm, MPI_Comm *intercomm,
             int array_of_errcodes[])
Fortran 2008 binding
MPI_Comm_spawn(command, argv, maxprocs, info, root, comm, intercomm,
             array_of_errcodes, ierror)
   CHARACTER(LEN=*), INTENT(IN) :: command, argv(*)
   INTEGER, INTENT(IN) :: maxprocs, root
   TYPE(MPI_Info), INTENT(IN) :: info
   TYPE(MPI_Comm), INTENT(IN) :: comm
   TYPE(MPI_Comm), INTENT(OUT) :: intercomm
    INTEGER :: array_of_errcodes(*)
   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_COMM_SPAWN(COMMAND, ARGV, MAXPROCS, INFO, ROOT, COMM, INTERCOMM,
             ARRAY_OF_ERRCODES, IERROR)
   CHARACTER*(*) COMMAND, ARGV(*)
   INTEGER MAXPROCS, INFO, ROOT, COMM, INTERCOMM, ARRAY_OF_ERRCODES(*),
              IERROR
```

MPI\_COMM\_SPAWN tries to start maxprocs identical copies of the MPI program specified by command, establishing communication with them and returning an inter-communicator. The spawned processes are referred to as children. The children have their own MPI\_COMM\_WORLD, which is separate from that of the parents. MPI\_COMM\_SPAWN is collective over comm, and also may not return until MPI\_INIT has been called in the children. Similarly, MPI\_INIT in the children may not return until all parents have called MPI\_COMM\_SPAWN. In this sense, MPI\_COMM\_SPAWN in the parents and MPI\_INIT in the children form a collective operation over the union of parent and child processes. The inter-communicator returned by MPI\_COMM\_SPAWN contains the parent processes in the local group and the child processes in the remote group. The ordering of processes in the local and remote groups is the same as the ordering of the group of the comm in the parents and of MPI\_COMM\_WORLD of the children, respectively. This inter-communicator can be obtained in the children through the function MPI\_COMM\_GET\_PARENT.

Advice to users. An implementation may automatically establish communication before MPI\_INIT is called by the children. Thus, completion of MPI\_COMM\_SPAWN in the parent does not necessarily mean that MPI\_INIT has been called in the children (although the returned inter-communicator can be used immediately). (End of advice to users.)

The command argument The command argument is a string containing the name of a program to be spawned. The string is null-terminated in C. In Fortran, leading and trailing spaces are stripped. MPI does not specify how to find the executable or how the working directory is determined. These rules are implementation-dependent and should be appropriate for the runtime environment.

Advice to implementors. The implementation should use a natural rule for finding executables and determining working directories. For instance, a homogeneous system

with a global file system might look first in the working directory of the spawning process, or might search the directories in a PATH environment variable as do Unix shells. An implementation should document its rules for finding executables and determining working directories, and a high-quality implementation should give the user some control over these rules. (*End of advice to implementors*.)

If the program named in command does not call MPI\_INIT, but instead forks a process that calls MPI\_INIT, the results are undefined. Implementations may allow this case to work but are not required to.

Advice to users. MPI does not say what happens if the program you start is a shell script and that shell script starts a program that calls MPI\_INIT. Though some implementations may allow you to do this, they may also have restrictions, such as requiring that arguments supplied to the shell script be supplied to the program, or requiring that certain parts of the environment not be changed. (*End of advice to users.*)

The argu argument argv is an array of strings containing arguments that are passed to the program. The first element of argv is the first argument passed to command, not, as is conventional in some contexts, the command itself. The argument list is terminated by NULL in C and an empty string in Fortran. In Fortran, leading and trailing spaces are always stripped, so that a string consisting of all spaces is considered an empty string. The constant MPI\_ARGV\_NULL may be used in C and Fortran to indicate an empty argument list. In C this constant is the same as NULL.

### **Example 11.17** Examples of argv in C and Fortran

To run the program "ocean" with arguments "-gridfile" and "ocean1.grd" in C:

```
char command[] = "ocean";
char *argv[] = {"-gridfile", "ocean1.grd", NULL};
MPI_Comm_spawn(command, argv, ...);
```

or, if not everything is known at compile time:

```
char *command;
char **argv;
command = "ocean";
argv=(char **)malloc(3 * sizeof(char *));
argv[0] = "-gridfile";
argv[1] = "ocean1.grd";
argv[2] = NULL;
MPI_Comm_spawn(command, argv, ...);
```

In Fortran:

```
CHARACTER*25 command, argv(3)
command = 'ocean'
argv(1) = '-gridfile'
argv(2) = 'ocean1.grd'
argv(3) = ' '
call MPI_COMM_SPAWN(command, argv, ...)
```

Arguments are supplied to the program if this is allowed by the operating system. In C, the MPI\_COMM\_SPAWN argument argv differs from the argv argument of main in two respects. First, it is shifted by one element. Specifically, argv[0] of main is provided by the implementation and conventionally contains the name of the program (given by command). argv[1] of main corresponds to argv[0] in MPI\_COMM\_SPAWN, argv[2] of main to argv[1] of MPI\_COMM\_SPAWN, etc. Passing an argv of MPI\_ARGV\_NULL to MPI\_COMM\_SPAWN results in main receiving argc of 1 and an argv whose element 0 is (conventionally) the name of the program. Second, argv of MPI\_COMM\_SPAWN must be null-terminated, so that its length can be determined.

If a Fortran implementation supplies routines that allow a program to obtain its arguments, the arguments may be available through that mechanism. In C, if the operating system does not support arguments appearing in argv of main(), the MPI implementation may add the arguments to the argv that is passed to MPI\_INIT.

The maxprocs argument MPI tries to spawn maxprocs processes. If it is unable to spawn maxprocs processes, it raises an error of class MPI\_ERR\_SPAWN.

An implementation may allow the info argument to change the default behavior, such that if the implementation is unable to spawn all maxprocs processes, it may spawn a smaller number of processes instead of raising an error. In principle, the info argument may specify an arbitrary set  $\{m_i: 0 \leq m_i \leq \text{maxprocs}\}\$  of allowed values for the number of processes spawned. The set  $\{m_i\}$  does not necessarily include the value maxprocs. If an implementation is able to spawn one of these allowed numbers of processes,

MPI\_COMM\_SPAWN returns successfully and the number of spawned processes, m, is given by the size of the remote group of intercomm. If m is less than maxproc, reasons why the other processes were not spawned are given in array\_of\_errcodes as described below. If it is not possible to spawn one of the allowed numbers of processes, MPI\_COMM\_SPAWN raises an error of class MPI\_ERR\_SPAWN.

A spawn call with the default behavior is called *hard*. A spawn call for which fewer than maxprocs processes may be returned is called "soft". See Section 11.8.4 for more information on the "soft" key for info.

Advice to users. By default, requests are hard and MPI errors are fatal. This means that by default there will be a fatal error if MPI cannot spawn all the requested processes. If you want the behavior "spawn as many processes as possible, up to N," you should do a soft spawn, where the set of allowed values  $\{m_i\}$  is  $\{0, \ldots, N\}$ . However, this is not completely portable, as implementations are not required to support soft spawning. (End of advice to users.)

The info argument The info argument to all of the routines in this chapter is an opaque handle of type MPI\_Info in C and Fortran with the mpi\_f08 module and INTEGER in Fortran with the mpi module or the include file mpif.h. It is a container for a number of user-specified (key,value) pairs. key and value are strings (null-terminated char\* in C, character\*(\*) in Fortran). Routines to create and manipulate the info argument are described in Chapter 10.

For the SPAWN calls, info provides additional (and possibly implementation-dependent) instructions to MPI and the runtime system on how to start processes. An application may pass MPI\_INFO\_NULL in C or Fortran. Portable programs not requiring detailed control over process locations should use MPI\_INFO\_NULL.

MPI does not specify the content of the info argument, except to reserve a number of special key values (see Section 11.8.4). The info argument is quite flexible and could even be used, for example, to specify the executable and its command-line arguments. In this case the command argument to MPI\_COMM\_SPAWN could be empty. The ability to do this follows from the fact that MPI does not specify how an executable is found, and the info argument can tell the runtime system where to "find" the executable "" (empty string). Of course a program that does this will not be portable across MPI implementations.

The root argument All arguments before the root argument are examined only on the process whose rank in comm is equal to root. The value of these arguments on other processes is ignored.

The array\_of\_errcodes argument The array\_of\_errcodes is an array of length maxprocs in which MPI reports the status of each process that MPI was requested to start. If all maxprocs processes were spawned, array\_of\_errcodes is filled in with the value MPI\_SUCCESS. If only m ( $0 \le m < \text{maxprocs}$ ) processes are spawned, m of the entries will contain MPI\_SUCCESS and the rest will contain an implementation-specific error code indicating the reason MPI could not start the process. MPI does not specify which entries correspond to failed processes. An implementation may, for instance, fill in error codes in one-to-one correspondence with a detailed specification in the info argument. These error codes all belong to the error class MPI\_ERR\_SPAWN if there was no error in the argument list. In C or Fortran, an application may pass MPI\_ERRCODES\_IGNORE if it is not interested in the error codes.

Advice to implementors. MPI\_ERRCODES\_IGNORE in Fortran is a special type of constant, like MPI\_BOTTOM. See the discussion in Section 2.5.4. (*End of advice to implementors.*)

```
MPI_COMM_GET_PARENT(parent)
```

OUT parent the parent communicator (handle)

### C binding

int MPI\_Comm\_get\_parent(MPI\_Comm \*parent)

### Fortran 2008 binding

```
MPI_Comm_get_parent(parent, ierror)
    TYPE(MPI_Comm), INTENT(OUT) :: parent
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

If a process was started with MPI\_COMM\_SPAWN or MPI\_COMM\_SPAWN\_MULTIPLE, MPI\_COMM\_GET\_PARENT returns the "parent" inter-communicator of the current process. This parent inter-communicator is created implicitly inside of MPI\_INIT and is the same inter-communicator returned by SPAWN in the parents.

If the process was not spawned, MPI\_COMM\_GET\_PARENT returns MPI\_COMM\_NULL.

After the parent communicator is freed or disconnected, MPI\_COMM\_GET\_PARENT returns MPI\_COMM\_NULL.

Advice to users. MPI\_COMM\_GET\_PARENT returns a handle to a single inter-communicator. Calling MPI\_COMM\_GET\_PARENT a second time returns a handle to the same inter-communicator. Freeing the handle with MPI\_COMM\_DISCONNECT or MPI\_COMM\_FREE will cause other references to the inter-communicator to become invalid (dangling). Note that calling MPI\_COMM\_FREE on the parent communicator is not useful. (End of advice to users.)

Rationale. The desire of the Forum was to create a constant MPI\_COMM\_PARENT similar to MPI\_COMM\_WORLD. Unfortunately such a constant cannot be used (syntactically) as an argument to MPI\_COMM\_DISCONNECT, which is explicitly allowed. (End of rationale.)

# 11.8.3 Starting Multiple Executables and Establishing Communication

While MPI\_COMM\_SPAWN is sufficient for most cases, it does not allow the spawning of multiple binaries, or of the same binary with multiple sets of arguments. The following routine spawns multiple binaries or the same binary with multiple sets of arguments, establishing communication with them and placing them in the same MPI\_COMM\_WORLD.

```
MPI_COMM_SPAWN_MULTIPLE(count, array_of_commands, array_of_argv, array_of_maxprocs, array_of_info, root, comm, intercomm, array_of_errcodes)
```

26 27 28	IN	count	number of commands (positive integer, significant only at root)
29 30	IN	array_of_commands	programs to be executed (array of strings, significant only at root) $$
31 32	IN	array_of_argv	arguments for commands (array of array of strings, significant only at root)
33 34	IN	array_of_maxprocs	maximum number of processes to start for each command (array of integers, significant only at root)
35 36 37 38	IN	array_of_info	info objects telling the runtime system where and how to start processes (array of handles, significant only at root)
39 40	IN	root	rank of process in which previous arguments are examined (integer)
41 42	IN	comm	intra-communicator containing group of spawning processes (handle)
43 44 45	OUT	intercomm	inter-communicator between original group and the newly spawned group (handle)

# C binding

OUT

array\_of\_errcodes

one error code per process (array of integers)

12

13

14

15

16

17 18

19

20

21

22

23 24

25

27

28

29

30

31

34

35

36

37

39 40

43

44

45

46 47

```
char **array_of_argv[], const int array_of_maxprocs[],
             const MPI_Info array_of_info[], int root, MPI_Comm comm,
             MPI_Comm *intercomm, int array_of_errcodes[])
Fortran 2008 binding
MPI_Comm_spawn_multiple(count, array_of_commands, array_of_argv,
             array_of_maxprocs, array_of_info, root, comm, intercomm,
             array_of_errcodes, ierror)
    INTEGER, INTENT(IN) :: count, array_of_maxprocs(*), root
    CHARACTER(LEN=*), INTENT(IN) :: array_of_commands(*),
              array_of_argv(count, *)
    TYPE(MPI_Info), INTENT(IN) :: array_of_info(*)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Comm), INTENT(OUT) :: intercomm
    INTEGER :: array_of_errcodes(*)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
```

int MPI\_Comm\_spawn\_multiple(int count, char \*array\_of\_commands[],

```
MPI_COMM_SPAWN_MULTIPLE(COUNT, ARRAY_OF_COMMANDS, ARRAY_OF_ARGV,

ARRAY_OF_MAXPROCS, ARRAY_OF_INFO, ROOT, COMM, INTERCOMM,

ARRAY_OF_ERRCODES, IERROR)

INTEGER COUNT, ARRAY_OF_MAXPROCS(*), ARRAY_OF_INFO(*), ROOT, COMM,
```

INTEGER COUNT, ARRAY\_OF\_MAXPROCS(\*), ARRAY\_OF\_INFO(\*), ROUT, COMM,
INTERCOMM, ARRAY\_OF\_ERRCODES(\*), IERROR
CHARACTER\*(\*) ARRAY\_OF\_COMMANDS(\*), ARRAY\_OF\_ARGV(COUNT, \*)

MPI\_COMM\_SPAWN\_MULTIPLE is identical to MPI\_COMM\_SPAWN except that there are multiple executable specifications. The first argument, count, gives the number of specifications. Each of the next four arguments are simply arrays of the corresponding arguments in MPI\_COMM\_SPAWN. For the Fortran version of array\_of\_argv, the element array\_of\_argv(i,j) is the j-th argument to command number i.

Rationale. This may seem backwards to Fortran programmers who are familiar with Fortran's column-major ordering. However, it is necessary to do it this way to allow MPI\_COMM\_SPAWN to sort out arguments. Note that the leading dimension of array\_of\_argv must be the same as count. Also note that Fortran rules for sequence association allow a different value in the first dimension; in this case, the sequence of array elements is interpreted by MPI\_COMM\_SPAWN\_MULTIPLE as if the sequence is stored in an array defined with the first dimension set to count. This Fortran feature allows an implementor to define MPI\_ARGVS\_NULL (see below) with fixed dimensions, e.g., (1,1), or only with one dimension, e.g., (1). (End of rationale.)

Advice to users. The argument count is interpreted by MPI only at the root, as is array\_of\_argv. Since the leading dimension of array\_of\_argv is count, a non-positive value of count at a non-root node could theoretically cause a runtime bounds check error, even though array\_of\_argv should be ignored by the subroutine. If this happens, you should explicitly supply a reasonable value of count on the non-root nodes. (End of advice to users.)

In any language, an application may use the constant MPI\_ARGVS\_NULL (which is likely to be (char \*\*\*)0 in C) to specify that no arguments should be passed to any commands.

The effect of setting individual elements of array\_of\_argv to MPI\_ARGV\_NULL is not defined. To specify arguments for some commands but not others, the commands without arguments should have a corresponding argv whose first element is null ((char \*)0 in C and empty string in Fortran). In Fortran at non-root processes, the count argument must be set to a value that is consistent with the provided array\_of\_argv although the content of these arguments has no meaning for this operation.

All of the spawned processes have the same MPI\_COMM\_WORLD. Their ranks in MPI\_COMM\_WORLD correspond directly to the order in which the commands are specified in MPI\_COMM\_SPAWN\_MULTIPLE. Assume that  $m_1$  processes are generated by the first command,  $m_2$  by the second, etc. The processes corresponding to the first command have ranks  $0, 1, \ldots, m_1 - 1$ . The processes in the second command have ranks  $m_1, m_1 + 1, \ldots, m_1 + m_2 - 1$ . The processes in the third have ranks  $m_1 + m_2 + m_3 + 1, \ldots, m_1 + m_2 + m_3 - 1$ , etc.

Advice to users. Calling MPI\_COMM\_SPAWN multiple times would create many sets of children with different MPI\_COMM\_WORLDs whereas

MPI\_COMM\_SPAWN\_MULTIPLE creates children with a single MPI\_COMM\_WORLD, so the two methods are not completely equivalent. There are also two performance-related reasons why, if you need to spawn multiple executables, you may want to use MPI\_COMM\_SPAWN\_MULTIPLE instead of calling MPI\_COMM\_SPAWN several times. First, spawning several things at once may be faster than spawning them sequentially. Second, in some implementations, communication between processes spawned at the same time may be faster than communication between processes spawned separately. (End of advice to users.)

 The array\_of\_errcodes argument is a 1-dimensional array of size  $\sum_{i=1}^{count} n_i$ , where  $n_i$  is the *i*-th element of array\_of\_maxprocs. Command number *i* corresponds to the  $n_i$  contiguous slots in this array from element  $\sum_{j=1}^{i-1} n_j$  to  $\left[\sum_{j=1}^{i} n_j\right] - 1$ . Error codes are treated as for MPI\_COMM\_SPAWN.

# Example 11.18 Examples of array\_of\_argv in C and Fortran

To run the program "ocean" with arguments "-gridfile" and "ocean1.grd" and the program "atmos" with argument "atmos.grd" in C:

```
char *array_of_commands[2] = {"ocean", "atmos"};
char **array_of_argv[2];
char *argv0[] = {"-gridfile", "ocean1.grd", (char *)0};
char *argv1[] = {"atmos.grd", (char *)0};
array_of_argv[0] = argv0;
array_of_argv[1] = argv1;
MPI_Comm_spawn_multiple(2, array_of_commands, array_of_argv, ...);
```

Here is how you do it in Fortran:

```
CHARACTER*25 commands(2), array_of_argv(2, 3)
commands(1) = 'ocean'
array_of_argv(1, 1) = '-gridfile'
array_of_argv(1, 2) = 'ocean1.grd'
array_of_argv(1, 3) = ' '

commands(2) = 'atmos'
array_of_argv(2, 1) = 'atmos.grd'
array_of_argv(2, 2) = ' '
call MPI_COMM_SPAWN_MULTIPLE(2, commands, array_of_argv, ...)
```

### 11.8.4 Reserved Keys

behavior.

The following keys are reserved. An implementation is not required to interpret these keys, but if it does interpret the key, it must provide the functionality described.

- "host" Value is a hostname. The format of the hostname is determined by the implementation.
- "arch" Value is an architecture name. Valid architecture names and what they mean are determined by the implementation.
- "wdir" Value is the name of a directory on a machine on which the spawned process(es) execute(s). This directory is made the working directory of the executing process(es). The format of the directory name is determined by the implementation.
- "path" Value is a directory or set of directories where the implementation should look for the executable. The format of "path" is determined by the implementation.
- "file" Value is the name of a file in which additional information is specified. The format of the filename and internal format of the file are determined by the implementation.
- "mpi\_initial\_errhandler" Value is the name of an errhandler that will be set as the initial error handler. The "mpi\_initial\_errhandler" key can take the case insensitive values "mpi\_errors\_are\_fatal", "mpi\_errors\_abort", and "mpi\_errors\_return" representing the predefined MPI error handlers (MPI\_ERRORS\_ARE\_FATAL—the default, MPI\_ERRORS\_ABORT, and MPI\_ERRORS\_RETURN, respectively). Other, non-standard values may be supported by the implementation, which should document the resultant
- "soft" Value specifies a set of numbers which are allowed values for the number of processes that MPI\_COMM\_SPAWN (et al.) may create. The format of the value is a comma-separated list of Fortran-90 triplets each of which specifies a set of integers and which together specify the set formed by the union of these sets. Negative values in this set and values greater than maxprocs are ignored. MPI will spawn the largest number of processes it can, consistent with some number in the set. The order in which triplets are given is not significant.

By Fortran-90 triplets, we mean:

```
1. a means a
```

```
1
            2. a:b means a, a + 1, a + 2, \dots, b
2
            3. a:b:c means a, a + c, a + 2c, \ldots, a + ck, where for c > 0, k is the largest integer
               for which a + ck < b and for c < 0, k is the largest integer for which a + ck > b.
               If b > a then c must be positive. If b < a then c must be negative.
6
          Examples:
            1. a:b gives a range between a and b
            2. 0:N gives full "soft" functionality
10
            3. 1,2,4,8,16,32,64,128,256,512,1024,2048,4096 allows a power-of-two num-
11
               ber of processes.
12
            4. 2:10000:2 allows an even number of processes.
13
            5. 2:10:2,7 allows 2, 4, 6, 7, 8, or 10 processes.
14
15
     11.8.5 Spawn Example
16
17
18
     Example 11.19 Manager-worker Example Using MPI_COMM_SPAWN
19
20
     /* manager */
21
     #include "mpi.h"
22
     int main(int argc, char *argv[])
23
24
        int world_size, universe_size, *universe_sizep, flag;
        MPI_Comm everyone;
                                        /* inter-communicator */
26
        char worker_program[100];
27
28
        MPI_Init(&argc, &argv);
29
        MPI_Comm_size(MPI_COMM_WORLD, &world_size);
30
        if (world_size != 1)
                                   error("Top heavy with management");
33
        MPI_Comm_get_attr(MPI_COMM_WORLD, MPI_UNIVERSE_SIZE,
34
                            &universe_sizep, &flag);
35
        if (!flag) {
36
              printf("This MPI does not support UNIVERSE_SIZE. How many\n\
37
     processes total?");
              scanf("%d", &universe_size);
39
        } else universe_size = *universe_sizep;
40
        if (universe_size == 1) error("No room to start workers");
41
42
43
         * Now spawn the workers. Note that there is a run-time determination
44
         * of what type of worker to spawn, and presumably this calculation must
45
         * be done at run time and cannot be calculated before starting
         * the program. If everything is known when the application is
47
         * first started, it is generally better to start them all at once
         * in a single MPI_COMM_WORLD.
```

15

16

18 19

20

21

22

23

24

25

26

27

28

29 30

34

35 36 37

38

39

42 43 44

45

47

```
*/
   choose_worker_program(worker_program);
  MPI_Comm_spawn(worker_program, MPI_ARGV_NULL, universe_size-1,
             MPI_INFO_NULL, O, MPI_COMM_SELF, &everyone,
             MPI_ERRCODES_IGNORE);
   /*
    * Parallel code here. The communicator "everyone" can be used
    * to communicate with the spawned processes, which have ranks 0,...
    * MPI_UNIVERSE_SIZE-1 in the remote group of the inter-communicator
    * "everyone".
    */
  MPI_Finalize();
  return 0;
}
/* worker */
#include "mpi.h"
int main(int argc, char *argv[])
{
   int size;
  MPI_Comm parent;
  MPI_Init(&argc, &argv);
  MPI_Comm_get_parent(&parent);
   if (parent == MPI_COMM_NULL) error("No parent!");
  MPI_Comm_remote_size(parent, &size);
   if (size != 1) error("Something's wrong with the parent");
   /*
    * Parallel code here.
    st The manager is represented as the process with rank 0 in (the remote
    * group of) the parent communicator. If the workers need to communicate
    * among themselves, they can use MPI_COMM_WORLD.
  MPI_Finalize();
  return 0:
}
```

# 11.9 Establishing Communication

This section provides functions that establish communication between two sets of MPI processes that do not share a communicator.

Some situations in which these functions are useful are:

- 1. Two parts of an application that are started independently need to communicate.
- 2. A visualization tool wants to attach to a running process.

 3. A server wants to accept connections from multiple clients. Both clients and server may be parallel programs.

In each of these situations, MPI must establish communication channels where none existed before, and there is no parent/child relationship. The routines described in this section establish communication between the two sets of processes by creating an MPI inter-communicator, where the two groups of the inter-communicator are the original sets of processes.

Establishing contact between two groups of processes that do not share an existing communicator is a collective but asymmetric process. One group of processes indicates its willingness to accept connections from other groups of processes. We will call this group the (parallel) *server*, even if this is not a client/server type of application. The other group connects to the server; we will call it the *client*.

Advice to users. While the names client and server are used throughout this section, MPI does not guarantee the traditional robustness of client/server systems. The functionality described in this section is intended to allow two cooperating parts of the same application to communicate with one another. For instance, a client that gets a segmentation fault and dies, or one that does not participate in a collective operation may cause a server to crash or hang. (End of advice to users.)

### 11.9.1 Names, Addresses, Ports, and All That

Almost all of the complexity in MPI client/server routines addresses the question "how does the client find out how to contact the server?" The difficulty, of course, is that there is no existing communication channel between them, yet they must somehow agree on a rendezvous point where they will establish communication.

Agreeing on a rendezvous point always involves a third party. The third party may itself provide the rendezvous point or may communicate rendezvous information from server to client. Complicating matters might be the fact that a client does not really care what server it contacts, only that it be able to get in touch with one that can handle its request.

Ideally, MPI can accommodate a wide variety of run-time systems while retaining the ability to write simple, portable code. The following should be compatible with MPI:

- The server resides at a well-known internet address host:port.
- The server prints out an address to the terminal; the user gives this address to the client program.
- The server places the address information on a nameserver, where it can be retrieved with an agreed-upon name.
- The server to which the client connects is actually a broker, acting as a middleman between the client and the real server.

5 6

9 10

11

12

13 14

15

16

17

18

19 20

21

22

23

24

26

27 28 29

30

31

33 34

38 39

41

42

43

44

45

46

MPI does not require a nameserver, so not all implementations will be able to support all of the above scenarios. However, MPI provides an optional nameserver interface, and is compatible with external name servers.

A port\_name is a system-supplied string that encodes a low-level network address at which a server can be contacted. Typically this is an IP address and a port number, but an implementation is free to use any protocol. The server establishes a port\_name with the MPI\_OPEN\_PORT routine. It accepts a connection to a given port with MPI\_COMM\_ACCEPT. A client uses port\_name to connect to the server.

By itself, the port\_name mechanism is completely portable, but it may be clumsy to use because of the necessity to communicate port\_name to the client. It would be more convenient if a server could specify that it be known by an application-supplied service\_name so that the client could connect to that service\_name without knowing the port\_name.

An MPI implementation may allow the server to publish a (port\_name, service\_name) pair with MPI\_PUBLISH\_NAME and the client to retrieve the port name from the service name with MPI\_LOOKUP\_NAME. This allows three levels of portability, with increasing levels of functionality.

- 1. Applications that do not rely on the ability to publish names are the most portable. Typically the port\_name must be transferred "by hand" from server to client.
- 2. Applications that use the MPI\_PUBLISH\_NAME mechanism are completely portable among implementations that provide this service. To be portable among all implementations, these applications should have a fall-back mechanism that can be used when names are not published.
- 3. Applications may ignore MPI's name publishing functionality and use their own mechanism (possibly system-supplied) to publish names. This allows arbitrary flexibility but is not portable.

#### 11.9.2 Server Routines

A server makes itself available with two routines. First it must call MPI\_OPEN\_PORT to establish a port at which it may be contacted. Secondly it must call MPI\_COMM\_ACCEPT to accept connections from clients.

```
35
MPI_OPEN_PORT(info, port_name)
                                                                                       36
 IN
                                      implementation-specific information on how to
                                                                                       37
                                      establish an address (handle)
 OUT
                                      newly established port (string)
           port_name
C binding
int MPI_Open_port(MPI_Info info, char *port_name)
Fortran 2008 binding
MPI_Open_port(info, port_name, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    CHARACTER(LEN=MPI_MAX_PORT_NAME), INTENT(OUT) :: port_name
```

INTEGER, OPTIONAL, INTENT(OUT) :: ierror

### Fortran binding

MPI\_OPEN\_PORT(INFO, PORT\_NAME, IERROR)
 INTEGER INFO, IERROR
 CHARACTER\*(\*) PORT\_NAME

This function establishes a network address, encoded in the port\_name string, at which the server will be able to accept connections from clients. port\_name is supplied by the system, possibly using information in the info argument.

MPI copies a system-supplied port name into port\_name. port\_name identifies the newly opened port and can be used by a client to contact the server. The maximum size string that may be supplied by the system is MPI\_MAX\_PORT\_NAME.

Advice to users. The system copies the port name into port\_name. The application must pass a buffer of sufficient size to hold this value. (End of advice to users.)

port\_name is essentially a network address. It is unique within the communication universe to which it belongs (determined by the implementation), and may be used by any client within that communication universe. For instance, if it is an internet (host:port) address, it will be unique on the internet. If it is a low level switch address on an IBM SP, it will be unique to that SP.

Advice to implementors. These examples are not meant to constrain implementations. A port\_name could, for instance, contain a user name or the name of a batch job, as long as it is unique within some well-defined communication domain. The larger the communication domain, the more useful MPI's client/server functionality will be. (End of advice to implementors.)

The precise form of the address is implementation-defined. For instance, an internet address may be a host name or IP address, or anything that the implementation can decode into an IP address. A port name may be reused after it is freed with MPI\_CLOSE\_PORT and released by the system.

Advice to implementors. Since the user may type in port\_name by hand, it is useful to choose a form that is easily readable and does not have embedded spaces. (End of advice to implementors.)

info may be used to tell the implementation how to establish the address. It may, and usually will, be MPI\_INFO\_NULL in order to get the implementation defaults.

```
MPI_CLOSE_PORT(port_name)

IN port_name a port (string)

C binding
int MPI_Close_port(const char *port_name)

Fortran 2008 binding

MPI_Close_port(port_name, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: port_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

44 45

46

```
Fortran binding
MPI_CLOSE_PORT(PORT_NAME, IERROR)
    CHARACTER*(*) PORT_NAME
    INTEGER IERROR
    This function releases the network address represented by port_name.
MPI_COMM_ACCEPT(port_name, info, root, comm, newcomm)
 IN
                                       port name (string, significant only at root)
           port_name
 IN
           info
                                       implementation-dependent information (handle,
                                                                                         11
                                       significant only at root)
                                                                                         12
                                                                                         13
 IN
           root
                                       rank in comm of root node (integer)
                                                                                         14
 IN
           comm
                                       intra-communicator over which call is collective
                                                                                         15
                                       (handle)
                                                                                         16
 OUT
                                       inter-communicator with client as remote group
           newcomm
                                                                                         18
                                       (handle)
                                                                                         19
                                                                                         20
C binding
                                                                                         21
int MPI_Comm_accept(const char *port_name, MPI_Info info, int root,
                                                                                         22
               MPI_Comm comm, MPI_Comm *newcomm)
                                                                                         23
Fortran 2008 binding
                                                                                         24
MPI_Comm_accept(port_name, info, root, comm, newcomm, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: port_name
                                                                                         26
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                         27
    INTEGER, INTENT(IN) :: root
                                                                                         28
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                         29
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
                                                                                         30
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
                                                                                         33
MPI_COMM_ACCEPT(PORT_NAME, INFO, ROOT, COMM, NEWCOMM, IERROR)
                                                                                         34
    CHARACTER*(*) PORT_NAME
                                                                                         35
    INTEGER INFO, ROOT, COMM, NEWCOMM, IERROR
                                                                                         36
    MPI_COMM_ACCEPT establishes communication with a client. It is collective over the
                                                                                         37
calling communicator. It returns an inter-communicator that allows communication with
the client.
    The port_name must have been established through a call to MPI_OPEN_PORT.
    info can be used to provide directives that may influence the behavior of the ACCEPT
call.
                                                                                         42
```

### 11.9.3 Client Routines

There is only one routine on the client side.

```
1
     MPI_COMM_CONNECT(port_name, info, root, comm, newcomm)
2
       IN
                                             network address (string, significant only at root)
                 port_name
3
       IN
                 info
                                             implementation-dependent information (handle,
4
                                             significant only at root)
5
6
       IN
                 root
                                             rank in comm of root node (integer)
       IN
                                             intra-communicator over which call is collective
                 comm
                                             (handle)
9
       OUT
                 newcomm
                                             inter-communicator with server as remote group
10
                                             (handle)
11
12
13
     C binding
14
     int MPI_Comm_connect(const char *port_name, MPI_Info info, int root,
                    MPI_Comm comm, MPI_Comm *newcomm)
15
16
     Fortran 2008 binding
17
     MPI_Comm_connect(port_name, info, root, comm, newcomm, ierror)
18
          CHARACTER(LEN=*), INTENT(IN) :: port_name
19
          TYPE(MPI_Info), INTENT(IN) :: info
20
          INTEGER, INTENT(IN) :: root
21
          TYPE(MPI_Comm), INTENT(IN) :: comm
22
          TYPE(MPI_Comm), INTENT(OUT) :: newcomm
23
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
24
25
     Fortran binding
26
     MPI_COMM_CONNECT(PORT_NAME, INFO, ROOT, COMM, NEWCOMM, IERROR)
27
          CHARACTER*(*) PORT_NAME
          INTEGER INFO, ROOT, COMM, NEWCOMM, IERROR
28
29
         This routine establishes communication with a server specified by port_name. It is
30
31
```

collective over the calling communicator and returns an inter-communicator in which the remote group participated in an MPI\_COMM\_ACCEPT.

If the named port does not exist (or has been closed), MPI\_COMM\_CONNECT raises an error of class MPI\_ERR\_PORT.

32

33

34

35

36

37

38 39

40

41

42

43

44

45 46

47

If the port exists, but does not have a pending MPI\_COMM\_ACCEPT, the connection attempt will eventually time out after an implementation-defined time, or succeed when the server calls MPI\_COMM\_ACCEPT. In the case of a time out, MPI\_COMM\_CONNECT raises an error of class MPI\_ERR\_PORT.

Advice to implementors. The time out period may be arbitrarily short or long. However, a high-quality implementation will try to queue connection attempts so that a server can handle simultaneous requests from several clients. A high-quality implementation may also provide a mechanism, through the info arguments to MPI\_OPEN\_PORT, MPI\_COMM\_ACCEPT, and/or MPI\_COMM\_CONNECT, for the user to control timeout and queuing behavior. (End of advice to implementors.)

MPI provides no guarantee of fairness in servicing connection attempts. That is, connection attempts are not necessarily satisfied in the order they were initiated and competition

from other connection attempts may prevent a particular connection attempt from being satisfied.

port\_name is the address of the server. It must be the same as the name returned by MPI\_OPEN\_PORT on the server. Some freedom is allowed here. If there are equivalent forms of port\_name, an implementation may accept them as well. For instance, if port\_name is (hostname:port), an implementation may accept (ip\_address:port) as well.

### 11.9.4 Name Publishing

The routines in this section provide a mechanism for publishing names. A (service\_name, port\_name) pair is published by the server, and may be retrieved by a client using the service\_name only. An MPI implementation defines the *scope* of the service\_name, that is, the domain over which the service\_name can be retrieved. If the domain is the empty set, that is, if no client can retrieve the information, then we say that name publishing is not supported. Implementations should document how the scope is determined. High-quality implementations will give some control to users through the info arguments to name publishing functions. Examples are given in the descriptions of individual functions.

### MPI\_PUBLISH\_NAME(service\_name, info, port\_name)

```
IN service_name a service name to associate with the port (string)

IN info implementation-specific information (handle)

IN port_name a port_name (string)
```

#### C binding

### Fortran 2008 binding

```
MPI_Publish_name(service_name, info, port_name, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: service_name, port_name
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_PUBLISH_NAME(SERVICE_NAME, INFO, PORT_NAME, IERROR)
CHARACTER*(*) SERVICE_NAME, PORT_NAME
INTEGER INFO, IERROR
```

This routine publishes the pair (port\_name, service\_name) so that an application may retrieve a system-supplied port\_name using a well-known service\_name.

The implementation must define the *scope* of a published service name, that is, the domain over which the service name is unique, and conversely, the domain over which the (port name, service name) pair may be retrieved. For instance, a service name may be unique to a job (where job is defined by a distributed operating system or batch scheduler), unique to a machine, or unique to a Kerberos realm. The scope may depend on the info argument to MPI\_PUBLISH\_NAME.

MPI permits publishing more than one service\_name for a single port\_name. On the other hand, if service\_name has already been published within the scope determined by info,

the behavior of MPI\_PUBLISH\_NAME is undefined. An MPI implementation may, through a mechanism in the info argument to MPI\_PUBLISH\_NAME, provide a way to allow multiple servers with the same service in the same scope. In this case, an implementation-defined policy will determine which of several port names is returned by MPI\_LOOKUP\_NAME.

Note that while service\_name has a limited scope, determined by the implementation, port\_name always has global scope within the communication universe used by the implementation (i.e., it is globally unique).

port\_name should be the name of a port established by MPI\_OPEN\_PORT and not yet released by MPI\_CLOSE\_PORT. If it is not, the result is undefined.

Advice to implementors. In some cases, an MPI implementation may use a name service that a user can also access directly. In this case, a name published by MPI could easily conflict with a name published by a user. In order to avoid such conflicts, MPI implementations should mangle service names so that they are unlikely to conflict with user code that makes use of the same service. Such name mangling will of course be completely transparent to the user.

The following situation is problematic but unavoidable, if we want to allow implementations to use nameservers. Suppose there are multiple instances of "ocean" running on a machine. If the scope of a service name is confined to a job, then multiple oceans can coexist. If an implementation provides site-wide scope, however, multiple instances are not possible as all calls to MPI\_PUBLISH\_NAME after the first may fail. There is no universal solution to this.

To handle these situations, a high-quality implementation should make it possible to limit the domain over which names are published. (*End of advice to implementors.*)

```
MPI_UNPUBLISH_NAME(service_name, info, port_name)
```

```
IN service_name a service name (string)

IN info implementation-specific information (handle)

IN port_name a port name (string)
```

#### C binding

### Fortran 2008 binding

```
MPI_Unpublish_name(service_name, info, port_name, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: service_name, port_name
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

```
MPI_UNPUBLISH_NAME(SERVICE_NAME, INFO, PORT_NAME, IERROR)
CHARACTER*(*) SERVICE_NAME, PORT_NAME
INTEGER INFO, IERROR
```

This routine unpublishes a service name that has been previously published. Attempting to unpublish a name that has not been published or has already been unpublished is erroneous and is indicated by the error class MPI\_ERR\_SERVICE.

All published names must be unpublished before the corresponding port is closed and before the publishing process exits. The behavior of MPI\_UNPUBLISH\_NAME is implementation dependent when a process tries to unpublish a name that it did not publish.

If the info argument was used with MPI\_PUBLISH\_NAME to tell the implementation how to publish names, the implementation may require that info passed to MPI\_UNPUBLISH\_NAME contain information to tell the implementation how to unpublish a name.

### MPI\_LOOKUP\_NAME(service\_name, info, port\_name)

```
IN service_name a service name (string)

IN info implementation-specific information (handle)

OUT port_name a port_name (string)
```

### C binding

#### Fortran 2008 binding

```
MPI_Lookup_name(service_name, info, port_name, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: service_name
    TYPE(MPI_Info), INTENT(IN) :: info
    CHARACTER(LEN=MPI_MAX_PORT_NAME), INTENT(OUT) :: port_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

```
MPI_LOOKUP_NAME(SERVICE_NAME, INFO, PORT_NAME, IERROR)
CHARACTER*(*) SERVICE_NAME, PORT_NAME
INTEGER INFO, IERROR
```

This function retrieves a port\_name published by MPI\_PUBLISH\_NAME with service\_name. If service\_name has not been published, it raises an error in the error class MPI\_ERR\_NAME. The application must supply a port\_name buffer large enough to hold the largest possible port name (see discussion above under MPI\_OPEN\_PORT).

If an implementation allows multiple entries with the same service\_name within the same scope, a particular port\_name is chosen in a way determined by the implementation.

If the info argument was used with MPI\_PUBLISH\_NAME to tell the implementation how to publish names, a similar info argument may be required for MPI\_LOOKUP\_NAME.

### 11.9.5 Reserved Key Values

The following key values are reserved. An implementation is not required to interpret these key values, but if it does interpret the key value, it must provide the functionality described.

```
"ip_port" Value contains IP port number at which to establish a port. (Reserved for MPI_OPEN_PORT only).
```

```
1
     "ip_address" Value contains IP address at which to establish a port. If the address is not a
2
          valid IP address of the host on which the MPI_OPEN_PORT call is made, the results
3
          are undefined. (Reserved for MPI_OPEN_PORT only).
4
5
     11.9.6 Client/Server Examples
6
7
     Example 11.20 Simplest Example—Completely Portable.
     The following example shows the simplest way to use the client/server interface. It does
9
     not use service names at all.
10
     On the server side:
11
12
13
         char myport[MPI_MAX_PORT_NAME];
14
         MPI_Comm intercomm;
15
         /* ... */
16
         MPI_Open_port(MPI_INFO_NULL, myport);
         printf("port name is: %s\n", myport);
18
19
         MPI_Comm_accept(myport, MPI_INFO_NULL, 0, MPI_COMM_SELF, &intercomm);
20
         /* do something with intercomm */
21
     The server prints out the port name to the terminal and the user must type it in when
22
     starting up the client (assuming the MPI implementation supports stdin such that this
23
     works). On the client side:
24
         MPI_Comm intercomm;
26
         char name[MPI_MAX_PORT_NAME];
27
         printf("enter port name: ");
28
         gets(name);
29
         MPI_Comm_connect(name, MPI_INFO_NULL, 0, MPI_COMM_SELF, &intercomm);
30
31
     Example 11.21 Ocean/Atmosphere—Relies on Name Publishing
32
         In this example, the "ocean" application is the "server" side of a coupled ocean-
33
     atmosphere climate model. It assumes that the MPI implementation publishes names.
34
35
36
         MPI_Open_port(MPI_INFO_NULL, port_name);
37
         MPI_Publish_name("ocean", MPI_INFO_NULL, port_name);
39
         MPI_Comm_accept(port_name, MPI_INFO_NULL, 0, MPI_COMM_SELF, &intercomm);
         /* do something with intercomm */
         MPI_Unpublish_name("ocean", MPI_INFO_NULL, port_name);
42
43
44
     On the client side:
45
46
         MPI_Lookup_name("ocean", MPI_INFO_NULL, port_name);
47
         MPI_Comm_connect(port_name, MPI_INFO_NULL, 0, MPI_COMM_SELF,
```

&intercomm);

### Example 11.22 Simple Client-Server Example

This is a simple example; the server accepts only a single connection at a time and serves that connection until the client requests to be disconnected. The server is a single process.

Here is the server. It accepts a single connection and then processes data until it receives a message with tag 1. A message with tag 0 tells the server to exit.

```
#include "mpi.h"
int main(int argc, char *argv[])
    MPI_Comm client;
    MPI_Status status;
                                                                                      11
    char port_name[MPI_MAX_PORT_NAME];
                                                                                      12
    double buf[MAX_DATA];
                                                                                      13
    int
            size, again;
                                                                                      14
                                                                                      15
    MPI_Init(&argc, &argv);
                                                                                      16
    MPI_Comm_size(MPI_COMM_WORLD, &size);
                                                                                      17
    if (size != 1) error(FATAL, "Server too big");
                                                                                      18
    MPI_Open_port(MPI_INFO_NULL, port_name);
                                                                                      19
    printf("server available at %s\n", port_name);
                                                                                      20
    while (1) {
                                                                                      21
        MPI_Comm_accept(port_name, MPI_INFO_NULL, 0, MPI_COMM_WORLD,
                                                                                      22
                          &client);
                                                                                      23
        again = 1;
                                                                                      24
        while (again) {
                                                                                      25
             MPI_Recv(buf, MAX_DATA, MPI_DOUBLE,
                                                                                      26
                       MPI_ANY_SOURCE, MPI_ANY_TAG, client, &status);
                                                                                      27
             switch (status.MPI_TAG) {
                                                                                      28
                case 0: MPI_Comm_free(&client);
                                                                                      29
                          MPI_Close_port(port_name);
                                                                                      30
                          MPI_Finalize();
                                                                                      31
                          return 0;
                 case 1: MPI_Comm_disconnect(&client);
                                                                                      33
                          again = 0;
                                                                                      34
                          break;
                                                                                      35
                 case 2: /* do something */
                                                                                      36
                                                                                      37
                 default:
                                                                                      38
                          /* Unexpected message type */
                                                                                      39
                          MPI_Abort(MPI_COMM_WORLD, 1);
                 }
                                                                                      41
             }
                                                                                      42
        }
                                                                                      43
}
                                                                                      44
                                                                                      45
Here is the client.
```

```
1
     #include "mpi.h"
2
     int main(int argc, char **argv)
3
4
         MPI_Comm server;
5
         double buf [MAX_DATA];
6
         char port_name[MPI_MAX_PORT_NAME];
         MPI_Init(&argc, &argv);
         strcpy(port_name, argv[1]);/* assume server's name is cmd-line arg */
10
11
         MPI_Comm_connect(port_name, MPI_INFO_NULL, 0, MPI_COMM_WORLD,
12
                            &server);
13
14
         while (!done) {
15
             tag = 2; /* Action to perform */
16
             MPI_Send(buf, n, MPI_DOUBLE, 0, tag, server);
             /* etc */
18
             }
19
         MPI_Send(buf, 0, MPI_DOUBLE, 0, 1, server);
20
         MPI_Comm_disconnect(&server);
21
         MPI_Finalize();
22
         return 0;
23
     }
24
```

# 11.10 Other Functionality

#### 11.10.1 Universe Size

26 27

28

29

30

31

32

33 34

35

36

37

38

39

41

42

43

44 45

46 47 Many "dynamic" MPI applications are expected to exist in a static runtime environment, in which resources have been allocated before the application is run. When a user (or possibly a batch system) runs one of these quasi-static applications, she will usually specify a number of processes to start and a total number of processes that are expected. An application simply needs to know how many slots there are, i.e., how many processes it should spawn.

MPI provides an attribute on MPI\_COMM\_WORLD, MPI\_UNIVERSE\_SIZE, that allows the application to obtain this information in a portable manner. This attribute indicates the total number of processes that are expected. In Fortran, the attribute is the integer value. In C, the attribute is a pointer to the integer value. An application typically subtracts the size of MPI\_COMM\_WORLD from MPI\_UNIVERSE\_SIZE to find out how many processes it should spawn. MPI\_UNIVERSE\_SIZE is initialized in MPI\_INIT and is not changed by MPI. If defined, it has the same value on all processes of MPI\_COMM\_WORLD. MPI\_UNIVERSE\_SIZE is determined by the application startup mechanism in a way not specified by MPI. (The size of MPI\_COMM\_WORLD is another example of such a parameter.)

Possibilities for how MPI\_UNIVERSE\_SIZE might be set include

- A -universe\_size argument to a program that starts MPI processes.
- Automatic interaction with a batch scheduler to figure out how many processors have been allocated to an application.

- An environment variable set by the user.
- Extra information passed to MPI\_COMM\_SPAWN through the info argument.

An implementation must document how MPI\_UNIVERSE\_SIZE is set. An implementation may not support the ability to set MPI\_UNIVERSE\_SIZE, in which case the attribute MPI\_UNIVERSE\_SIZE is not set.

MPI\_UNIVERSE\_SIZE is a recommendation, not necessarily a hard limit. For instance, some implementations may allow an application to spawn 50 processes per processor, if they are requested. However, it is likely that the user only wants to spawn one process per processor.

MPI\_UNIVERSE\_SIZE is assumed to have been specified when an application was started, and is in essence a portable mechanism to allow the user to pass to the application (through the MPI process startup mechanism, such as mpiexec) a piece of critical runtime information. Note that no interaction with the runtime environment is required. If the runtime environment changes size while an application is running, MPI\_UNIVERSE\_SIZE is not updated, and the application must find out about the change through direct communication with the runtime system.

## 11.10.2 Singleton MPI Initialization

A high-quality implementation will allow any process (including those not started with a "parallel application" mechanism) to become an MPI process by calling MPI\_INIT, MPI\_INIT\_THREAD, or MPI\_SESSION\_INIT. Such a process can then connect to other MPI processes using the MPI\_COMM\_ACCEPT and MPI\_COMM\_CONNECT routines, or spawn other MPI processes. MPI does not mandate this behavior, but strongly encourages it where technically feasible.

Advice to implementors. Special coordination is required to start MPI processes belonging to the same MPI\_COMM\_WORLD in the case of the World Model, or the same "mpi://world" process set in the Sessions Model. The processes must be started at the "same" time, they must have a mechanism to establish communication, etc. Either the user or the operating system must take special steps beyond simply starting processes.

Considering the World Model, when an application enters MPI\_INIT, clearly it must be able to determine if these special steps were taken. If a process enters MPI\_INIT and determines that no special steps were taken (i.e., it has not been given the information to form an MPI\_COMM\_WORLD with other processes) it succeeds and forms a singleton MPI program, that is, one in which MPI\_COMM\_WORLD has size 1.

In some implementations, MPI may not be able to function without an "MPI environment." For example, MPI may require that daemons be running or MPI may not be able to work at all on the front-end of an MPP. In this case, an MPI implementation may either

- 1. Create the environment (e.g., start a daemon) or
- 2. Raise an error if it cannot create the environment and the environment has not been started independently.

A high-quality implementation will try to create a singleton MPI process and not raise an error.

(End of advice to implementors.)

### 11.10.3 MPI\_APPNUM

 There is a predefined attribute MPI\_APPNUM of MPI\_COMM\_WORLD. In Fortran, the attribute is an integer value. In C, the attribute is a pointer to an integer value. If a process was spawned with MPI\_COMM\_SPAWN\_MULTIPLE, MPI\_APPNUM is the command number that generated the current process. Numbering starts from zero. If a process was spawned with MPI\_COMM\_SPAWN, it will have MPI\_APPNUM equal to zero.

Additionally, if the process was not started by a spawn call, but by an implementation-specific startup mechanism that can handle multiple process specifications, MPI\_APPNUM should be set to the number of the corresponding process specification. In particular, if it is started with

```
mpiexec spec0 [: spec1 : spec2 : ...]
```

MPI\_APPNUM should be set to the number of the corresponding specification.

If an application was not spawned with MPI\_COMM\_SPAWN or MPI\_COMM\_SPAWN\_MULTIPLE, and MPI\_APPNUM does not make sense in the context of the implementation-specific startup mechanism, MPI\_APPNUM is not set.

MPI implementations may optionally provide a mechanism to override the value of MPI\_APPNUM through the info argument. MPI reserves the following key for all SPAWN calls.

"appnum" Value contains an integer that overrides the default value for MPI\_APPNUM in the child.

Rationale. When a single application is started, it is able to figure out how many processes there are by looking at the size of MPI\_COMM\_WORLD. An application consisting of multiple SPMD sub-applications has no way to find out how many sub-applications there are and to which sub-application the process belongs. While there are ways to figure it out in special cases, there is no general mechanism. MPI\_APPNUM provides such a general mechanism. (End of rationale.)

### 11.10.4 Releasing Connections

Before a client and server connect, they are independent MPI applications. An error in one does not affect the other. After establishing a connection with MPI\_COMM\_CONNECT and MPI\_COMM\_ACCEPT, an error in one may affect the other. It is desirable for a client and server to be able to disconnect, so that an error in one will not affect the other. Similarly, it might be desirable for a parent and child to disconnect, so that errors in the child do not affect the parent, or vice-versa.

- Two processes are **connected** if there is a communication path (direct or indirect) between them. More precisely:
  - 1. Two processes are connected if

- (a) they both belong to the same communicator (inter- or intra-, including MPI\_COMM\_WORLD) or
- (b) they have previously belonged to a communicator that was freed with MPI\_COMM\_FREE instead of MPI\_COMM\_DISCONNECT or
- (c) they both belong to the group of the same window or filehandle.
- 2. If A is connected to B and B to C, then A is connected to C.
- Two processes are **disconnected** (also **independent**) if they are not connected.
- By the above definitions, connectivity is a transitive property, and divides the universe of MPI processes into disconnected (independent) sets (equivalence classes) of processes.
- Processes which are connected, but do not share the same MPI\_COMM\_WORLD, may become disconnected (independent) if the communication path between them is broken by using MPI\_COMM\_DISCONNECT.

The following additional rules apply to MPI routines in other chapters:

- MPI\_FINALIZE is collective over a set of connected processes.
- MPI\_ABORT does not abort independent processes. It may abort all processes in the caller's MPI\_COMM\_WORLD (ignoring its comm argument). Additionally, it may abort connected processes as well, though it makes a "best attempt" to abort only the processes in comm.
- If a process terminates without calling MPI\_FINALIZE, independent processes are not affected but the effect on connected processes is not defined.

Advice to implementors. In practice, it may be difficult to distinguish between an MPI process failure and an erroneous program that terminates without calling an MPI finalization function: an implementation that defines semantics for process failure management may have to exhibit the behavior defined for MPI process failures with such erroneous programs. A high quality implementation should exhibit a different behavior for erroneous programs and MPI process failures. (End of advice to implementors.)

```
MPI_COMM_DISCONNECT(comm)

INOUT comm communicator (handle)
```

# C binding

int MPI\_Comm\_disconnect(MPI\_Comm \*comm)

#### Fortran 2008 binding

```
MPI_Comm_disconnect(comm, ierror)
    TYPE(MPI_Comm), INTENT(INOUT) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

```
MPI_COMM_DISCONNECT(COMM, IERROR)
INTEGER COMM, IERROR
```

This function waits for all pending communication on comm to complete internally, deallocates the communicator object, and sets the handle to MPI\_COMM\_NULL. It is a collective operation.

It may not be called with the communicator MPI\_COMM\_WORLD or MPI\_COMM\_SELF. MPI\_COMM\_DISCONNECT may be called only if all communication is complete and matched, so that buffered data can be delivered to its destination. This requirement is the same as for MPI\_FINALIZE.

MPI\_COMM\_DISCONNECT has the same action as MPI\_COMM\_FREE, except that it waits for pending communication to finish internally and enables the guarantee about the behavior of disconnected processes.

Advice to users. To disconnect two processes you may need to call MPI\_COMM\_DISCONNECT, MPI\_WIN\_FREE, and MPI\_FILE\_CLOSE to remove all communication paths between the two processes. Note that it may be necessary to disconnect several communicators (or to free several windows or files) before two processes are completely independent. (End of advice to users.)

Rationale. It would be nice to be able to use MPI\_COMM\_FREE instead, but that function explicitly does not wait for pending communication to complete. (End of rationale.)

# 11.10.5 Another Way to Establish MPI Communication

```
MPI_COMM_JOIN(fd, intercomm)
 IN
                                    socket file descriptor
 OUT
                                    new inter-communicator (handle)
          intercomm
C binding
int MPI_Comm_join(int fd, MPI_Comm *intercomm)
Fortran 2008 binding
MPI_Comm_join(fd, intercomm, ierror)
    INTEGER, INTENT(IN) :: fd
    TYPE(MPI_Comm), INTENT(OUT) :: intercomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_COMM_JOIN(FD, INTERCOMM, IERROR)
    INTEGER FD, INTERCOMM, IERROR
```

MPI\_COMM\_JOIN is intended for MPI implementations that exist in an environment supporting the Berkeley Socket interface [50, 56]. Implementations that exist in an environment not supporting Berkeley Sockets should provide the entry point for MPI\_COMM\_JOIN and should return MPI\_COMM\_NULL.

This call creates an inter-communicator from the union of two MPI processes which are connected by a socket. MPI\_COMM\_JOIN should normally succeed if the local and remote processes have access to the same implementation-defined MPI communication universe.

Advice to users. An MPI implementation may require a specific communication medium for MPI communication, such as a shared memory segment or a special switch. In this case, it may not be possible for two processes to successfully join even if there is a socket connecting them and they are using the same MPI implementation. (End of advice to users.)

Advice to implementors. A high-quality implementation will attempt to establish communication over a slow medium if its preferred one is not available. If implementations do not do this, they must document why they cannot do MPI communication over the medium used by the socket (especially if the socket is a TCP connection). (End of advice to implementors.)

fd is a file descriptor representing a socket of type SOCK\_STREAM (a two-way reliable byte-stream connection). Nonblocking I/O and asynchronous notification via SIGIO must not be enabled for the socket. The socket must be in a connected state. The socket must be quiescent when MPI\_COMM\_JOIN is called (see below). It is the responsibility of the application to create the socket using standard socket API calls.

MPI\_COMM\_JOIN must be called by the process at each end of the socket. It does not return until both processes have called MPI\_COMM\_JOIN. The two processes are referred to as the local and remote processes.

MPI uses the socket to bootstrap creation of the inter-communicator, and for nothing else. Upon return from MPI\_COMM\_JOIN, the file descriptor will be open and quiescent (see below).


If MPI is unable to create an inter-communicator, but is able to leave the socket in its original state, with no pending communication, it succeeds and sets intercomm to MPI\_COMM\_NULL.

The socket must be quiescent before MPI\_COMM\_JOIN is called and after MPI\_COMM\_JOIN returns. More specifically, on entry to MPI\_COMM\_JOIN, a read on the socket will not read any data that was written to the socket before the remote process called MPI\_COMM\_JOIN. On exit from MPI\_COMM\_JOIN, a read will not read any data that was written to the socket before the remote process returned from MPI\_COMM\_JOIN. It is the responsibility of the application to ensure the first condition, and the responsibility of the MPI implementation to ensure the second. In a multithreaded application, the application must ensure that one thread does not access the socket while another is calling MPI\_COMM\_JOIN, or call MPI\_COMM\_JOIN concurrently.

Advice to implementors. MPI is free to use any available communication path(s) for MPI messages in the new communicator; the socket is only used for the initial handshaking. (End of advice to implementors.)

MPI\_COMM\_JOIN uses non-MPI communication to do its work. The interaction of non-MPI communication with pending MPI communication is not defined. Therefore, the result of calling MPI\_COMM\_JOIN on two connected processes (see Section 11.10.4 for the definition of connected) is undefined.

The returned communicator may be used to establish MPI communication with additional processes, through the usual MPI communicator creation mechanisms.



# Chapter 12

# **One-Sided Communications**

# 12.1 Introduction

Remote Memory Access (RMA) extends the communication mechanisms of MPI by allowing one process to specify all communication parameters, both for the sending side and for the receiving side. This mode of communication facilitates the coding of some applications with dynamically changing data access patterns where the data distribution is fixed or slowly changing. In such a case, each process can compute what data it needs to access or to update at other processes. However, the programmer may not be able to easily determine which data in a process may need to be accessed or to be updated by operations executed by a different process, and may not even know which processes may perform such updates. Thus, the transfer parameters are all available only on one side. Regular send/receive communication requires matching operations by sender and receiver. In order to issue the matching operations, an application needs to distribute the transfer parameters. This distribution may require all processes to participate in a time-consuming global computation, or to poll for potential communication requests to receive and upon which to act periodically. The use of RMA communication mechanisms avoids the need for global computations or explicit polling. A generic example of this nature is the execution of an assignment of the form A = B(map), where map is a permutation vector, and A, B, and map are distributed in the same manner.

Message-passing communication achieves two effects: *communication* of data from sender to receiver and *synchronization* of sender with receiver. The RMA design separates these two functions. The following communication calls are provided:

- Remote write: MPI\_PUT, MPI\_RPUT
- Remote read: MPI\_GET, MPI\_RGET
- Remote update: MPI\_ACCUMULATE, MPI\_RACCUMULATE
- Remote read and update: MPI\_GET\_ACCUMULATE, MPI\_RGET\_ACCUMULATE, and MPI\_FETCH\_AND\_OP
- Remote atomic swap operations: MPI\_COMPARE\_AND\_SWAP

This chapter refers to an operations set that includes all remote update, remote read and update, and remote atomic swap operations as "accumulate" operations.

11 12 13

15 16

17

18

19

20

21

22

23

24

26

27

28

29

30

31

33

34

35

36

37 38

39

42

43 44

45 46

47

MPI supports two fundamentally different memory models: separate and unified. The separate model makes no assumption about memory consistency and is highly portable. This model is similar to that of weakly coherent memory systems: the user must impose correct ordering of memory accesses through synchronization calls. The unified model can exploit cache-coherent hardware and hardware-accelerated, one-sided operations that are commonly available in high-performance systems. The two different models are discussed in detail in Section 12.4. Both models support several synchronization calls to support different synchronization styles.

The design of the RMA functions allows implementors to take advantage of fast or asynchronous communication mechanisms provided by various platforms, such as coherent or noncoherent shared memory, DMA engines, hardware-supported put/get operations, and communication coprocessors. The most frequently used RMA communication mechanisms can be layered on top of message-passing. However, certain RMA functions might need support for asynchronous communication agents in software (handlers, threads, etc.) in a distributed memory environment.

We shall denote by **origin** the process that performs the call, and by **target** the process in which the memory is accessed. Thus, in a put operation, source = origin and destination = target; in a get operation, source = target and destination = origin.

The use of terms such as nonblocking and local in this chapter follow the usage in MPI-3.1, and this chapter has not been updated to follow the definitions in Section 2.4. The MPI Forum intends to update this chapter in a subsequent version of the MPI standard to follow the definitions in Section 2.4.

# 12.2 Initialization

MPI provides the following window initialization functions: MPI\_WIN\_CREATE,

MPI\_WIN\_ALLOCATE, MPI\_WIN\_ALLOCATE\_SHARED, and

MPI\_WIN\_CREATE\_DYNAMIC, which are collective on an intra-communicator.

MPI\_WIN\_CREATE allows each process to specify a "window" in its memory that is made accessible to accesses by remote processes. The call returns an opaque object that represents the group of processes that own and access the set of windows, and the attributes of each window, as specified by the initialization call. MPI\_WIN\_ALLOCATE differs from

MPI\_WIN\_CREATE in that the user does not pass allocated memory;

MPI\_WIN\_ALLOCATE returns a pointer to memory allocated by the MPI implementation. MPI\_WIN\_ALLOCATE\_SHARED differs from MPI\_WIN\_ALLOCATE in that the allocated memory can be accessed from all processes in the window's group with direct load/store instructions. Some restrictions may apply to the specified communicator.

MPI\_WIN\_CREATE\_DYNAMIC creates a window that allows the user to dynamically control which memory is exposed by the window.

14 15

16

17

18

19

20

22

23

24

26

27

28

29

30

33

34

35

36

37

41

42

43

4546

47

# 12.2.1 Window Creation

```
MPI_WIN_CREATE(base, size, disp_unit, info, comm, win)
  IN
           base
                                     initial address of window (choice)
  IN
           size
                                     size of window in bytes (non-negative integer)
  IN
           disp_unit
                                     local unit size for displacements, in bytes (positive
                                     integer)
  IN
           info
                                     info argument (handle)
  IN
                                     intra-communicator (handle)
           comm
  OUT
           win
                                     window object (handle)
C binding
int MPI_Win_create(void *base, MPI_Aint size, int disp_unit, MPI_Info info,
              MPI_Comm comm, MPI_Win *win)
int MPI_Win_create_c(void *base, MPI_Aint size, MPI_Aint disp_unit,
              MPI_Info info, MPI_Comm comm, MPI_Win *win)
                                                                                    21
Fortran 2008 binding
MPI_Win_create(base, size, disp_unit, info, comm, win, ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: base
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
    INTEGER, INTENT(IN) :: disp_unit
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Win), INTENT(OUT) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Win_create(base, size, disp_unit, info, comm, win, ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: base
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size, disp_unit
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Win), INTENT(OUT) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_WIN_CREATE(BASE, SIZE, DISP_UNIT, INFO, COMM, WIN, IERROR)
    <type> BASE(*)
```

This is a collective call executed by all processes in the group of comm. It returns a window object that can be used by these processes to perform RMA operations. Each process specifies a window of existing memory that it exposes to RMA accesses by the processes in the group of comm. The window consists of size bytes, starting at address base. In C, base is the starting address of a memory region. In Fortran, one can pass the

INTEGER(KIND=MPI\_ADDRESS\_KIND) SIZE

INTEGER DISP\_UNIT, INFO, COMM, WIN, IERROR

first element of a memory region or a whole array, which must be 'simply contiguous' (for 'simply contiguous,' see also Section 19.1.12). A process may elect to expose no memory by specifying size = 0.

The displacement unit argument is provided to facilitate address arithmetic in RMA operations: the target displacement argument of an RMA operation is scaled by the factor disp\_unit specified by the target process, at window creation.

Rationale. The window size is specified using an address-sized integer, rather than a basic integer type, to allow windows that span more memory than can be described with a basic integer type. (End of rationale.)

Advice to users. Common choices for disp\_unit are 1 (no scaling), and (in C syntax) sizeof(type), for a window that consists of an array of elements of type type. The latter choice will allow one to use array indices in RMA calls, and have those scaled correctly to byte displacements, even in a heterogeneous environment. (End of advice to users.)

The info argument provides optimization hints to the runtime about the expected usage pattern of the window. The following info keys are predefined:

- "no\_locks"—if set to true, then the implementation may assume that passive target synchronization (i.e., MPI\_WIN\_LOCK, MPI\_WIN\_LOCK\_ALL) will not be used on the given window. This implies that this window is not used for 3-party communication, and RMA can be implemented with no (less) asynchronous agent activity at this process.
- "accumulate\_ordering"—controls the ordering of accumulate operations at the target. See Section 12.7.2 for details.
- "accumulate\_ops"—if set to "same\_op", the implementation will assume that all concurrent accumulate calls to the same target address will use the same operation. If set to "same\_op\_no\_op", then the implementation will assume that all concurrent accumulate calls to the same target address will use the same operation or MPI\_NO\_OP. This can eliminate the need to protect access for certain operation types where the hardware can guarantee atomicity. The default is "same\_op\_no\_op".
- "same\_size"—if set to true, then the implementation may assume that the argument size is identical on all processes, and that all processes have provided this info key with the same value.
- "same\_disp\_unit"—if set to true, then the implementation may assume that the argument disp\_unit is identical on all processes, and that all processes have provided this info key with the same value.

Advice to users. The info query mechanism described in Section 12.2.7 can be used to query the specified info arguments for windows that have been passed to a library. It is recommended that libraries check attached info keys for each passed window. (End of advice to users.)

The various processes in the group of comm may specify completely different target windows, in location, size, displacement units, and info arguments. As long as all the get,

put and accumulate accesses to a particular process fit their specific target window this should pose no problem. The same area in memory may appear in multiple windows, each associated with a different window object. However, concurrent communications to distinct, overlapping windows may lead to undefined results.

Rationale. The reason for specifying the memory that may be accessed from another process in an RMA operation is to permit the programmer to specify what memory can be a target of RMA operations and for the implementation to enforce that specification. For example, with this definition, a server process can safely allow a client process to use RMA operations, knowing that (under the assumption that the MPI implementation does enforce the specified limits on the exposed memory) an error in the client cannot affect any memory other than what was explicitly exposed. (End of rationale.)

Advice to users. A window can be created in any part of the process memory. However, on some systems, the performance of windows in memory allocated by MPI\_ALLOC\_MEM (Section 9.2) will be better. Also, on some systems, performance is improved when window boundaries are aligned at "natural" boundaries (word, double-word, cache line, page frame, etc.). (End of advice to users.)

Advice to implementors. In cases where RMA operations use different mechanisms in different memory areas (e.g., load/store in a shared memory segment, and an asynchronous handler in private memory), the MPI\_WIN\_CREATE call needs to figure out which type of memory is used for the window. To do so, MPI maintains, internally, the list of memory segments allocated by MPI\_ALLOC\_MEM, or by other, implementation-specific, mechanisms, together with information on the type of memory segment allocated. When a call to MPI\_WIN\_CREATE occurs, then MPI checks which segment contains each window, and decides, accordingly, which mechanism to use for RMA operations.

Vendors may provide additional, implementation-specific mechanisms to allocate or to specify memory regions that are preferable for use in one-sided communication. In particular, such mechanisms can be used to place static variables into such preferred regions.

Implementors should document any performance impact of window alignment. (End of advice to implementors.)

47

48

```
1
     12.2.2 Window That Allocates Memory
2
3
4
     MPI_WIN_ALLOCATE(size, disp_unit, info, comm, baseptr, win)
5
       IN
                size
                                           size of window in bytes (non-negative integer)
6
       IN
                disp_unit
                                           local unit size for displacements, in bytes (positive
7
                                           integer)
9
       IN
                info
                                           info argument (handle)
10
       IN
                comm
                                           intra-communicator (handle)
11
       OUT
                                           initial address of window (choice)
                baseptr
12
13
       OUT
                                           window object returned by call (handle)
                win
14
15
     C binding
16
     int MPI_Win_allocate(MPI_Aint size, int disp_unit, MPI_Info info,
17
                    MPI_Comm comm, void *baseptr, MPI_Win *win)
18
     int MPI_Win_allocate_c(MPI_Aint size, MPI_Aint disp_unit, MPI_Info info,
19
                    MPI_Comm comm, void *baseptr, MPI_Win *win)
20
21
     Fortran 2008 binding
22
     MPI_Win_allocate(size, disp_unit, info, comm, baseptr, win, ierror)
23
         USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
24
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
         INTEGER, INTENT(IN) :: disp_unit
26
         TYPE(MPI_Info), INTENT(IN) :: info
27
         TYPE(MPI_Comm), INTENT(IN) :: comm
28
         TYPE(C_PTR), INTENT(OUT) :: baseptr
29
         TYPE(MPI_Win), INTENT(OUT) :: win
30
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
31
32
     MPI_Win_allocate(size, disp_unit, info, comm, baseptr, win, ierror)
33
         USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
34
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size, disp_unit
         TYPE(MPI_Info), INTENT(IN) :: info
35
         TYPE(MPI_Comm), INTENT(IN) :: comm
36
         TYPE(C_PTR), INTENT(OUT) :: baseptr
37
         TYPE(MPI_Win), INTENT(OUT) :: win
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
39
     Fortran binding
41
     MPI_WIN_ALLOCATE(SIZE, DISP_UNIT, INFO, COMM, BASEPTR, WIN, IERROR)
42
         INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
43
         INTEGER DISP_UNIT, INFO, COMM, WIN, IERROR
44
45
         This is a collective call executed by all processes in the group of comm. On each
```

Unofficial Draft for Comment Only

process, it allocates memory of at least size bytes, returns a pointer to it, and returns a

window object that can be used by all processes in comm to perform RMA operations. The

returned memory consists of size bytes local to each process, starting at address baseptr

5

11

12

13

14

15

16

17

18

19

20

21

22

23

24

26

27 28

29

30

34

35

36

37 38

39

42

and is associated with the window as if the user called MPI\_WIN\_CREATE on existing memory. The size argument may be different at each process and size = 0 is valid; however, a library might allocate and expose more memory in order to create a fast, globally symmetric allocation. The discussion of and rationales for MPI\_ALLOC\_MEM and MPI\_FREE\_MEM in Section 9.2 also apply to MPI\_WIN\_ALLOCATE; in particular, see the rationale in Section 9.2 for an explanation of the type used for baseptr.

If the Fortran compiler provides TYPE(C\_PTR), then the following generic interface must be provided in the mpi module and should be provided in mpif.h through overloading, i.e., with the same routine name as the routine with INTEGER(KIND=MPI\_ADDRESS\_KIND) BASEPTR, but with a different specific procedure name:

```
INTERFACE MPI_WIN_ALLOCATE
   SUBROUTINE MPI_WIN_ALLOCATE(SIZE, DISP_UNIT, INFO, COMM, BASEPTR, &
                                WIN, IERROR)
       IMPORT :: MPI_ADDRESS_KIND
       INTEGER DISP_UNIT, INFO, COMM, WIN, IERROR
       INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
   END SUBROUTINE
   SUBROUTINE MPI_WIN_ALLOCATE_CPTR(SIZE, DISP_UNIT, INFO, COMM, BASEPTR, &
                                     WIN, IERROR)
       USE, INTRINSIC ::
                          ISO_C_BINDING, ONLY : C_PTR
       IMPORT :: MPI_ADDRESS_KIND
       INTEGER :: DISP_UNIT, INFO, COMM, WIN, IERROR
       INTEGER(KIND=MPI_ADDRESS_KIND) :: SIZE
       TYPE(C_PTR) :: BASEPTR
   END SUBROUTINE
END INTERFACE
```

The base procedure name of this overloaded function is MPI\_WIN\_ALLOCATE\_CPTR. The implied specific procedure names are described in Section 19.1.5.

Rationale. By allocating (potentially aligned) memory instead of allowing the user to pass in an arbitrary buffer, this call can improve the performance for systems with remote direct memory access. This also permits the collective allocation of memory and supports what is sometimes called the "symmetric allocation" model that can be more scalable (for example, the implementation can arrange to return an address for the allocated memory that is the same on all processes). (End of rationale.)

The info argument can be used to specify hints similar to the info argument for MPI\_WIN\_CREATE and MPI\_ALLOC\_MEM.

The default memory alignment requirements and the "mpi\_minimum\_memory\_alignment" info key described for MPI\_ALLOC\_MEM in Section 9.2 apply to all processes with non-zero size argument.

48

```
1
     12.2.3 Window That Allocates Shared Memory
2
3
4
     MPI_WIN_ALLOCATE_SHARED(size, disp_unit, info, comm, baseptr, win)
5
       IN
                size
                                           size of local window in bytes (non-negative integer)
6
       IN
                disp_unit
                                           local unit size for displacements, in bytes (positive
7
                                           integer)
9
       IN
                info
                                           info argument (handle)
10
                                           intra-communicator (handle)
       IN
                comm
11
       OUT
                baseptr
                                           address of local allocated window segment (choice)
12
13
       OUT
                                           window object returned by the call (handle)
                win
14
15
     C binding
16
     int MPI_Win_allocate_shared(MPI_Aint size, int disp_unit, MPI_Info info,
17
                    MPI_Comm comm, void *baseptr, MPI_Win *win)
18
     int MPI_Win_allocate_shared_c(MPI_Aint size, MPI_Aint disp_unit,
19
                    MPI_Info info, MPI_Comm comm, void *baseptr, MPI_Win *win)
20
21
     Fortran 2008 binding
22
     MPI_Win_allocate_shared(size, disp_unit, info, comm, baseptr, win, ierror)
23
         USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
24
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
         INTEGER, INTENT(IN) :: disp_unit
26
         TYPE(MPI_Info), INTENT(IN) :: info
27
         TYPE(MPI_Comm), INTENT(IN) :: comm
28
         TYPE(C_PTR), INTENT(OUT) :: baseptr
29
         TYPE(MPI_Win), INTENT(OUT) :: win
30
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
31
32
     MPI_Win_allocate_shared(size, disp_unit, info, comm, baseptr, win, ierror)
33
         USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
34
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size, disp_unit
         TYPE(MPI_Info), INTENT(IN) :: info
35
         TYPE(MPI_Comm), INTENT(IN) :: comm
36
37
         TYPE(C_PTR), INTENT(OUT) :: baseptr
         TYPE(MPI_Win), INTENT(OUT) :: win
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
39
     Fortran binding
41
     MPI_WIN_ALLOCATE_SHARED(SIZE, DISP_UNIT, INFO, COMM, BASEPTR, WIN, IERROR)
42
         INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
43
         INTEGER DISP_UNIT, INFO, COMM, WIN, IERROR
44
45
         This is a collective call executed by all processes in the group of comm. On each
46
     process, it allocates memory of at least size bytes that is shared among all processes in
```

**Unofficial Draft for Comment Only** 

comm, and returns a pointer to the locally allocated segment in baseptr that can be used

for load/store accesses on the calling process. The locally allocated memory can be the

6 7

11

12

13

14 15

16

17

18

19

20

21

22

23

24

26

27

28

29

30

31

33

34 35

36

37

38

42 43

44

45

46

47

target of load/store accesses by remote processes; the base pointers for other processes can be queried using the function MPI\_WIN\_SHARED\_QUERY. The call also returns a window object that can be used by all processes in comm to perform RMA operations. The size argument may be different at each process and size = 0 is valid. It is the user's responsibility to ensure that the communicator comm represents a group of processes that can create a shared memory segment that can be accessed by all processes in the group. The discussions of rationales for MPI\_ALLOC\_MEM and MPI\_FREE\_MEM in Section 9.2 also apply to MPI\_WIN\_ALLOCATE\_SHARED; in particular, see the rationale in Section 9.2 for an explanation of the type used for baseptr. The allocated memory is contiguous across process ranks unless the info key "alloc\_shared\_noncontig" is specified. Contiguous across process ranks means that the first address in the memory segment of process i is consecutive with the last address in the memory segment of process i 1. This may enable the user to calculate remote address offsets with local information only.

If the Fortran compiler provides TYPE(C\_PTR), then the following generic interface must be provided in the mpi module and should be provided in mpif.h through overloading, i.e., with the same routine name as the routine with INTEGER(KIND=MPI\_ADDRESS\_KIND) BASEPTR, but with a different specific procedure name:

```
INTERFACE MPI_WIN_ALLOCATE_SHARED
   SUBROUTINE MPI_WIN_ALLOCATE_SHARED(SIZE, DISP_UNIT, INFO, COMM, &
                                       BASEPTR, WIN, IERROR)
        IMPORT :: MPI_ADDRESS_KIND
        INTEGER DISP_UNIT, INFO, COMM, WIN, IERROR
        INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
   END SUBROUTINE
   SUBROUTINE MPI_WIN_ALLOCATE_SHARED_CPTR(SIZE, DISP_UNIT, INFO, COMM, &
                                            BASEPTR, WIN, IERROR)
       USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
        IMPORT :: MPI_ADDRESS_KIND
        INTEGER :: DISP_UNIT, INFO, COMM, WIN, IERROR
        INTEGER(KIND=MPI_ADDRESS_KIND) ::
       TYPE(C_PTR) ::
                       BASEPTR
   END SUBROUTINE
END INTERFACE
```

The base procedure name of this overloaded function is MPI\_WIN\_ALLOCATE\_SHARED\_CPTR. The implied specific procedure names are described in Section 19.1.5.

The info argument can be used to specify hints similar to the info argument for MPI\_WIN\_CREATE, MPI\_WIN\_ALLOCATE, and MPI\_ALLOC\_MEM. The additional info key "alloc\_shared\_noncontig" allows the library to optimize the layout of the shared memory segments in memory.

Advice to users. If the info key "alloc\_shared\_noncontig" is not set to true, the allocation strategy is to allocate contiguous memory across process ranks. This may limit the performance on some architectures because it does not allow the implementation to modify the data layout (e.g., padding to reduce access latency). (End of advice to users.)

Advice to implementors. If the user sets the info key "alloc\_shared\_noncontig" to true, the implementation can allocate the memory requested by each process in a location that is close to this process. This can be achieved by padding or allocating memory in special memory segments. Both techniques may make the address space across consecutive ranks noncontiguous. (End of advice to implementors.)

For contiguous shared memory allocations, the default alignment requirements outlined for MPI\_ALLOC\_MEM in Section 9.2 and the "mpi\_minimum\_memory\_alignment" info key apply to the start of the contiguous memory that is returned in baseptr to the first process with non-zero size argument. For noncontiguous memory allocations, the default alignment requirements and the "mpi\_minimum\_memory\_alignment" info key apply to all processes with non-zero size argument.

Advice to users. If the info key "alloc\_shared\_noncontig" is not set to true (or ignored by the MPI implementation), the alignment of the memory returned in baseptr to all but the first process with non-zero size argument depends on the value of the size argument provided by other processes. It is thus the user's responsibility to control the alignment of contiguous memory allocated for these processes by ensuring that each process provides a size argument that is an integral multiple of the alignment required for the application. (End of advice to users.)

The consistency of load/store accesses from/to the shared memory as observed by the user program depends on the architecture. A consistent view can be created in the *unified memory model* (see Section 12.4) by utilizing the window synchronization functions (see Section 12.5) or explicitly completing outstanding store accesses (e.g., by calling MPI\_WIN\_FLUSH). MPI does not define semantics for accessing shared memory windows in the *separate memory model*.

# MPI\_WIN\_SHARED\_QUERY(win, rank, size, disp\_unit, baseptr)

IN	win	shared memory window object (handle)
IN	rank	rank in the group of window win or MPI_PROC_NULL (non-negative integer)
OUT	size	size of the window segment (non-negative integer) $$
OUT	disp_unit	local unit size for displacements, in bytes (positive integer) $$
OUT	baseptr	address for load/store access to window segment (choice)

#### C binding

13

14

15 16

18

19

20

21

22

27

28

29

30

34 35

36

37

38

42

43

44

45

46

```
USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, INTENT(IN) :: rank
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: size
    INTEGER, INTENT(OUT) :: disp_unit
    TYPE(C_PTR), INTENT(OUT) :: baseptr
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Win_shared_query(win, rank, size, disp_unit, baseptr, ierror)
    USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, INTENT(IN) :: rank
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: size, disp_unit
    TYPE(C_PTR), INTENT(OUT) :: baseptr
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_WIN_SHARED_QUERY(WIN, RANK, SIZE, DISP_UNIT, BASEPTR, IERROR)
    INTEGER WIN, RANK, DISP_UNIT, IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
```

This function queries the process-local address for remote memory segments created with MPI\_WIN\_ALLOCATE\_SHARED. This function can return different process-local addresses for the same physical memory on different processes. The returned memory can be used for load/store accesses subject to the constraints defined in Section 12.7. This function can only be called with windows of flavor MPI\_WIN\_FLAVOR\_SHARED. If the passed window is not of flavor MPI\_WIN\_FLAVOR\_SHARED, the error MPI\_ERR\_RMA\_FLAVOR is raised. When rank is MPI\_PROC\_NULL, the pointer, disp\_unit, and size returned are the pointer, disp\_unit, and size of the memory segment belonging the lowest rank that specified size > 0. If all processes in the group attached to the window specified size = 0, then the call returns size = 0 and a baseptr as if MPI\_ALLOC\_MEM was called with size = 0.

If the Fortran compiler provides TYPE(C\_PTR), then the following generic interface must be provided in the mpi module and should be provided in mpif.h through overloading, i.e., with the same routine name as the routine with INTEGER(KIND=MPI\_ADDRESS\_KIND) BASEPTR, but with a different specific procedure name:

```
INTERFACE MPI_WIN_SHARED_QUERY

SUBROUTINE MPI_WIN_SHARED_QUERY(WIN, RANK, SIZE, DISP_UNIT, & BASEPTR, IERROR)

IMPORT :: MPI_ADDRESS_KIND

INTEGER WIN, RANK, DISP_UNIT, IERROR

INTEGER (KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR

END SUBROUTINE

SUBROUTINE MPI_WIN_SHARED_QUERY_CPTR(WIN, RANK, SIZE, DISP_UNIT, & BASEPTR, IERROR)

USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR

IMPORT :: MPI_ADDRESS_KIND

INTEGER :: WIN, RANK, DISP_UNIT, IERROR

INTEGER(KIND=MPI_ADDRESS_KIND) :: SIZE
```

```
TYPE(C_PTR) :: BASEPTR
END SUBROUTINE
END INTERFACE
```

The base procedure name of this overloaded function is MPI\_WIN\_SHARED\_QUERY\_CPTR. The implied specific procedure names are described in Section 19.1.5.

# 12.2.4 Window of Dynamically Attached Memory

The MPI-2 RMA model requires the user to identify the local memory that may be a target of RMA calls at the time the window is created. This has advantages for both the programmer (only this memory can be updated by one-sided operations and provides greater safety) and the MPI implementation (special steps may be taken to make one-sided access to such memory more efficient). However, consider implementing a modifiable linked list using RMA operations; as new items are added to the list, memory must be allocated. In a C or C++ program, this memory is typically allocated using malloc or new respectively. In MPI-2 RMA, the programmer must create a window with a predefined amount of memory and then implement routines for allocating memory from within the window's memory. In addition, there is no easy way to handle the situation where the predefined amount of memory turns out to be inadequate. To support this model, the routine MPI\_WIN\_CREATE\_DYNAMIC creates a window that makes it possible to expose memory without remote synchronization. It must be used in combination with the local routines MPI\_WIN\_ATTACH and MPI\_WIN\_DETACH.

```
MPI_WIN_CREATE_DYNAMIC(info, comm, win)
```

```
IN info info argument (handle)

IN comm intra-communicator (handle)

OUT win window object returned by the call (handle)
```

#### C binding

```
int MPI_Win_create_dynamic(MPI_Info info, MPI_Comm comm, MPI_Win *win)
```

#### Fortran 2008 binding

```
MPI_Win_create_dynamic(info, comm, win, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Win), INTENT(OUT) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_WIN_CREATE_DYNAMIC(INFO, COMM, WIN, IERROR)
INTEGER INFO, COMM, WIN, IERROR
```

This is a collective call executed by all processes in the group of comm. It returns a window win without memory attached. Existing process memory can be attached as described below. This routine returns a window object that can be used by these processes to

perform RMA operations on attached memory. Because this window has special properties, it will sometimes be referred to as a *dynamic* window.

The info argument can be used to specify hints similar to the info argument for MPI\_WIN\_CREATE.

In the case of a window created with MPI\_WIN\_CREATE\_DYNAMIC, the target\_disp for all RMA functions is the address at the target; i.e., the effective window\_base is MPI\_BOTTOM and the disp\_unit is one. For dynamic windows, the target\_disp argument to RMA communication operations is not restricted to non-negative values. Users should use MPI\_GET\_ADDRESS at the target process to determine the address of a target memory location and communicate this address to the origin process.

Advice to users. Users are cautioned that displacement arithmetic can overflow in variables of type MPI\_Aint and result in unexpected values on some platforms. The MPI\_AINT\_ADD and MPI\_AINT\_DIFF functions can be used to safely perform address arithmetic with MPI\_Aint displacements. (End of advice to users.)

Advice to implementors. In environments with heterogeneous data representations, care must be exercised in communicating addresses between processes. For example, it is possible that an address valid at the target process (for example, a 64-bit pointer) cannot be expressed as an address at the origin (for example, the origin uses 32-bit pointers). For this reason, a portable MPI implementation should ensure that the type MPI\_AINT (see Table 3.3) is able to store addresses from any process. (End of advice to implementors.)

Memory at the target cannot be accessed with this window until that memory has been attached using the function MPI\_WIN\_ATTACH. That is, in addition to using MPI\_WIN\_CREATE\_DYNAMIC to create an MPI window, the user must use MPI\_WIN\_ATTACH before any local memory may be the target of an MPI RMA operation. Only memory that is currently accessible may be attached.

# MPI\_WIN\_ATTACH(win, base, size)

IN	win	window object (handle)
IN	base	initial address of memory to be attached (choice)
IN	size	size of memory to be attached in bytes (non-negative
		integer)

# C binding

```
int MPI_Win_attach(MPI_Win win, void *base, MPI_Aint size)
```

## Fortran 2008 binding

```
MPI_Win_attach(win, base, size, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: base
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

```
MPI_WIN_ATTACH(WIN, BASE, SIZE, IERROR)
    INTEGER WIN, IERROR
    <type> BASE(*)
    INTEGER(KIND=MPI_ADDRESS_KIND) SIZE
```

Attaches a local memory region beginning at base for remote access within the given window. The memory region specified must not contain any part that is already attached to the window win, that is, attaching overlapping memory concurrently within the same window is erroneous. The argument win must be a window that was created with MPI\_WIN\_CREATE\_DYNAMIC. The local memory region attached to the window consists of size bytes, starting at address base. In C, base is the starting address of a memory region. In Fortran, one can pass the first element of a memory region or a whole array, which must be 'simply contiguous' (for 'simply contiguous,' see Section 19.1.12). Multiple (but non-overlapping) memory regions may be attached to the same window.

Rationale. Requiring that memory be explicitly attached before it is exposed to one-sided access by other processes can simplify implementations and improve performance. The ability to make memory available for RMA operations without requiring a collective MPI\_WIN\_CREATE call is needed for some one-sided programming models. (End of rationale.)

Advice to users. Attaching memory to a window may require the use of scarce resources; thus, attaching large regions of memory is not recommended in portable programs. Attaching memory to a window may fail if sufficient resources are not available; this is similar to the behavior of MPI\_ALLOC\_MEM.

The user is also responsible for ensuring that MPI\_WIN\_ATTACH at the target has returned before a process attempts to target that memory with an MPI RMA call.

Performing an RMA operation to memory that has not been attached to a window created with MPI\_WIN\_CREATE\_DYNAMIC is erroneous. (*End of advice to users.*)

Advice to implementors. A high-quality implementation will attempt to make as much memory available for attaching as possible. Any limitations should be documented by the implementor. (End of advice to implementors.)

Attaching memory is a local operation as defined by MPI, which means that the call is not collective and completes without requiring any MPI routine to be called in any other process. Memory may be detached with the routine MPI\_WIN\_DETACH. After memory has been detached, it may not be the target of an MPI RMA operation on that window (unless the memory is re-attached with MPI\_WIN\_ATTACH).

```
MPI_WIN_DETACH(win, base)
```

```
IN win window object (handle)
IN base initial address of memory to be detached (choice)
```

## C binding

```
int MPI_Win_detach(MPI_Win win, const void *base)
```

```
Fortran 2008 binding
MPI_Win_detach(win, base, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: base
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI_WIN_DETACH(WIN, BASE, IERROR)
    INTEGER WIN, IERROR
    <type> BASE(*)
```

Detaches a previously attached memory region beginning at base. The arguments base and win must match the arguments passed to a previous call to MPI\_WIN\_ATTACH.

Advice to users. Detaching memory may permit the implementation to make more efficient use of special memory or provide memory that may be needed by a subsequent MPI\_WIN\_ATTACH. Users are encouraged to detach memory that is no longer needed. Memory should be detached before it is freed by the user. (End of advice to users.)

Memory becomes detached when the associated dynamic memory window is freed, see Section 12.2.5.

## 12.2.5 Window Destruction

```
MPI_WIN_FREE(win)

INOUT win window object (handle)

C binding
int MPI_Win_free(MPI_Win *win)

Fortran 2008 binding

MPI_Win_free(win, ierror)
    TYPE(MPI_Win), INTENT(INOUT) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding

MPI_WIN_FREE(WIN, IERROR)
    INTEGER WIN, IERROR
```

Frees the window object win and returns a null handle (equal to MPI\_WIN\_NULL). This is a collective call executed by all processes in the group associated with win. MPI\_WIN\_FREE(win) can be invoked by a process only after it has completed its involvement in RMA communications on window win: e.g., the process has called MPI\_WIN\_FENCE, or called MPI\_WIN\_WAIT to match a previous call to MPI\_WIN\_START or called MPI\_WIN\_COMPLETE to match a previous call to MPI\_WIN\_START or called MPI\_WIN\_UNLOCK to match a previous call to MPI\_WIN\_LOCK. The memory associated with windows created by a call to MPI\_WIN\_CREATE may be freed after the call returns. If the window was created with MPI\_WIN\_ALLOCATE, MPI\_WIN\_FREE will free the window

memory that was allocated in MPI\_WIN\_ALLOCATE. If the window was created with MPI\_WIN\_ALLOCATE\_SHARED, MPI\_WIN\_FREE will free the window memory that was allocated in MPI\_WIN\_ALLOCATE\_SHARED.

Freeing a window that was created with a call to MPI\_WIN\_CREATE\_DYNAMIC detaches all associated memory; i.e., it has the same effect as if all attached memory was detached by calls to MPI\_WIN\_DETACH.

Advice to implementors. MPI\_WIN\_FREE requires a barrier synchronization: no process can return from free until all processes in the group of win call free. This ensures that no process will attempt to access a remote window (e.g., with lock/unlock) after it was freed. The only exception to this rule is when the user sets the "no\_locks" info key to "true" when creating the window. In that case, an MPI implementation may free the local window without barrier synchronization. (End of advice to implementors.)

# 12.2.6 Window Attributes

The following attributes are cached with a window when the window is created.

MPI\_WIN\_BASE window base address.

MPI\_WIN\_SIZE window size, in bytes.

MPI\_WIN\_DISP\_UNIT displacement unit associated with the window.

MPI\_WIN\_CREATE\_FLAVOR how the window was created.

MPI\_WIN\_MODEL memory model for window.

In C, calls to MPI\_Win\_get\_attr(win, MPI\_WIN\_BASE, &base, &flag), MPI\_Win\_get\_attr(win, MPI\_WIN\_SIZE, &size, &flag),

MPI\_Win\_get\_attr(win, MPI\_WIN\_DISP\_UNIT, &disp\_unit, &flag),

MPI\_Win\_get\_attr(win, MPI\_WIN\_CREATE\_FLAVOR, &create\_kind, &flag), and

MPI\_Win\_get\_attr(win, MPI\_WIN\_MODEL, &memory\_model, &flag) will return in base a pointer to the start of the window win, and will return in size, disp\_unit, create\_kind, and memory\_model pointers to the size, displacement unit of the window, the kind of routine used to create the window, and the memory model, respectively. A detailed listing of the type of the pointer in the attribute value argument to MPI\_WIN\_GET\_ATTR and MPI\_WIN\_SET\_ATTR is shown in Table 12.1.

Attribute	C Type
MPI_WIN_BASE	void *
MPI_WIN_SIZE	MPI_Aint *
MPI_WIN_DISP_UNIT	int *
MPI_WIN_CREATE_FLAVOR	int *
MPI_WIN_MODEL	int *

Table 12.1: C types of attribute value argument to  $\mathsf{MPI\_WIN\_GET\_ATTR}$  and  $\mathsf{MPI\_WIN\_SET\_ATTR}$ .

```
In Fortran, calls to MPI_WIN_GET_ATTR(win, MPI_WIN_BASE, base, flag, ierror), MPI_WIN_GET_ATTR(win, MPI_WIN_SIZE, size, flag, ierror), MPI_WIN_GET_ATTR(win, MPI_WIN_DISP_UNIT, disp_unit, flag, ierror), MPI_WIN_GET_ATTR(win, MPI_WIN_CREATE_FLAVOR, create_kind, flag, ierror), and
```

MPI\_WIN\_GET\_ATTR(win, MPI\_WIN\_MODEL, memory\_model, flag, ierror) will return in base, size, disp\_unit, create\_kind, and memory\_model the (integer representation of) the base address, the size, the displacement unit of the window win, the kind of routine used to create the window, and the memory model, respectively.

The values of create\_kind are

MPI\_WIN\_FLAVOR\_CREATE
MPI\_WIN\_FLAVOR\_ALLOCATE
MPI\_WIN\_FLAVOR\_DYNAMIC
MPI\_WIN\_FLAVOR\_SHARED
Window was created with MPI\_WIN\_ALLOCATE.
Window was created with
MPI\_WIN\_CREATE\_DYNAMIC.
Window was created with
MPI\_WIN\_ALLOCATE\_SHARED.

The values of memory\_model are MPI\_WIN\_SEPARATE and MPI\_WIN\_UNIFIED. The meaning of these is described in Section 12.4.

In the case of windows created with MPI\_WIN\_CREATE\_DYNAMIC, the base address is MPI\_BOTTOM and the size is 0. In C, pointers are returned, and in Fortran, the values are returned, for the respective attributes. (The window attribute access functions are defined in Section 7.7.3.) The value returned for an attribute on a window is constant over the lifetime of the window.

The other "window attribute," namely the group of processes attached to the window, can be retrieved using the call below.

# MPI\_WIN\_GET\_GROUP(win, group)

IN win window object (handle)

OUT group group group of processes which share access to the window (handle)

#### C binding

int MPI\_Win\_get\_group(MPI\_Win win, MPI\_Group \*group)

#### Fortran 2008 binding

```
MPI_Win_get_group(win, group, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Group), INTENT(OUT) :: group
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

## Fortran binding

```
MPI_WIN_GET_GROUP(WIN, GROUP, IERROR)
    INTEGER WIN, GROUP, IERROR
```

MPI\_WIN\_GET\_GROUP returns a duplicate of the group of the communicator used to create the window associated with win. The group is returned in group.

# 12.2.7 Window Info

Hints specified via info (see Section 10) allow a user to provide information to direct optimization. Providing hints may enable an implementation to deliver increased performance or use system resources more efficiently. An implementation is free to ignore all hints;

however, applications must comply with any info hints they provide that are used by the MPI implementation (i.e., are returned by a call to MPI\_WIN\_GET\_INFO) and that place a restriction on the behavior of the application. Hints are specified on a per window basis, in window creation functions and MPI\_WIN\_SET\_INFO, via the opaque info object. When an info object that specifies a subset of valid hints is passed to MPI\_WIN\_SET\_INFO there will be no effect on previously set or default hints that the info does not specify.

Advice to implementors. It may happen that a program is coded with hints for one system, and later executes on another system that does not support these hints. In general, unsupported hints should simply be ignored. Needless to say, no hint can be mandatory. However, for each hint used by a specific implementation, a default value must be provided when the user does not specify a value for the hint. (End of advice to implementors.)

```
14
15
16
```

```
MPI_WIN_SET_INFO(win, info)

INOUT win window object (handle)

IN info info argument (handle)
```

# C binding

```
int MPI_Win_set_info(MPI_Win win, MPI_Info info)
```

# Fortran 2008 binding

```
MPI_Win_set_info(win, info, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding

```
MPI_WIN_SET_INFO(WIN, INFO, IERROR)
INTEGER WIN, INFO, IERROR
```

MPI\_WIN\_SET\_INFO updates the hints of the window associated with win using the hints provided in info. This operation has no effect on previously set or defaulted hints that are not specified by info. It also has no effect on previously set or defaulted hints that are specified by info, but are ignored by the MPI implementation in this call to MPI\_WIN\_SET\_INFO. The call is collective on the group of win. The info object may be different on each process, but any info entries that an implementation requires to be the same on all processes must appear with the same value in each process's info object.

Advice to users. Some info items that an implementation can use when it creates a window cannot easily be changed once the window has been created. Thus, an implementation may ignore hints issued in this call that it would have accepted in a creation call. An implementation may also be unable to update certain info hints in a call to MPI\_WIN\_SET\_INFO. MPI\_WIN\_GET\_INFO can be used to determine whether info changes were ignored by the implementation. (*End of advice to users*.)

12

13

14 15

16 17

18

19

20

21

22

23

24

26 27

28

29

30

31

33

34

35

36

37

38

39

40

41

42

43

44

45

46

47

```
MPI_WIN_GET_INFO(win, info_used)
 IN
                                    window object (handle)
          win
 OUT
          info_used
                                    new info object (handle)
C binding
int MPI_Win_get_info(MPI_Win win, MPI_Info *info_used)
Fortran 2008 binding
MPI_Win_get_info(win, info_used, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Info), INTENT(OUT) :: info_used
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_WIN_GET_INFO(WIN, INFO_USED, IERROR)
```

MPI\_WIN\_GET\_INFO returns a new info object containing the hints of the window associated with win. The current setting of all hints related to this window is returned in info\_used. An MPI implementation is required to return all hints that are supported by the implementation and have default values specified; any user-supplied hints that were not ignored by the implementation; and any additional hints that were set by the implementation. If no such hints exist, a handle to a newly created info object is returned that contains no key/value pair. The user is responsible for freeing info\_used via MPI\_INFO\_FREE.

# 12.3 Communication Calls

INTEGER WIN, INFO\_USED, IERROR

MPI supports the following RMA communication calls: MPI\_PUT and MPI\_RPUT transfer data from the caller memory (origin) to the target memory; MPI\_GET and MPI\_RGET transfer data from the target memory to the caller memory; MPI\_ACCUMULATE and MPI\_RACCUMULATE update locations in the target memory, e.g., by adding to these locations values sent from the caller memory; MPI\_GET\_ACCUMULATE,

MPI\_RGET\_ACCUMULATE, and MPI\_FETCH\_AND\_OP perform atomic read-modify-write and return the data before the accumulate operation; and MPI\_COMPARE\_AND\_SWAP performs a remote atomic compare and swap operation. These operations are *nonblocking*: the call initiates the transfer, but the transfer may continue after the call returns. The transfer is completed, at the origin or both the origin and the target, when a subsequent *synchronization* call is issued by the caller on the involved window object. These synchronization calls are described in Section 12.5. Transfers can also be completed with calls to flush routines; see Section 12.5.4 for details. For the MPI\_RPUT, MPI\_RGET, MPI\_RACCUMULATE, and MPI\_RGET\_ACCUMULATE calls, the transfer can be locally completed by using the MPI test or wait operations described in Section 3.7.3.

The local communication buffer of an RMA call should not be updated, and the local communication buffer of a get call should not be accessed after the RMA call until the operation completes at the origin.

The resulting data values, or outcome, of concurrent conflicting accesses to the same memory locations is undefined; if a location is updated by a put or accumulate operation, then the outcome of loads or other RMA operations is undefined until the updating operation

 has completed at the target. There is one exception to this rule; namely, the same location can be updated by several concurrent accumulate calls, the outcome being as if these updates occurred in some order. In addition, the outcome of concurrent load/store and RMA updates to the same memory location is undefined. These restrictions are described in more detail in Section 12.7.

The calls use general datatype arguments to specify communication buffers at the origin and at the target. Thus, a transfer operation may also gather data at the source and scatter it at the destination. However, all arguments specifying both communication buffers are provided by the caller.

For all RMA calls, the target process may be identical with the origin process; i.e., a process may use an RMA operation to move data in its memory.

Rationale. The choice of supporting "self-communication" is the same as for message-passing. It simplifies some coding, and is very useful with accumulate operations, to allow atomic updates of local variables. (*End of rationale*.)

MPI\_PROC\_NULL is a valid target rank in all MPI RMA communication calls. The effect is the same as for MPI\_PROC\_NULL in MPI point-to-point communication. After any RMA operation with rank MPI\_PROC\_NULL, it is still necessary to finish the RMA epoch with the synchronization method that started the epoch.

#### 12.3.1 Put

The execution of a put operation is similar to the execution of a send by the origin process and a matching receive by the target process. The obvious difference is that all arguments are provided by one call—the call executed by the origin process.

MPI\_PUT(origin\_addr, origin\_count, origin\_datatype, target\_rank, target\_disp, target\_count, target\_datatype, win)

IN	origin_addr	initial address of origin buffer (choice)
IN	origin_count	number of entries in origin buffer (non-negative integer)
IN	origin_datatype	data type of each entry in origin buffer (handle)
IN	target_rank	rank of target (non-negative integer)
IN	target_disp	displacement from start of window to target buffer (non-negative integer)
IN	target_count	number of entries in target buffer (non-negative integer)
IN	target_datatype	data type of each entry in target buffer (handle)
IN	win	window object used for communication (handle)

# C binding

12 13

14

15

16

18

19

20

21

22

23

24

26 27

28

29

30

33

34

35

36

37

38

43

44

45

46

47

```
MPI_Aint target_disp, int target_count,
             MPI_Datatype target_datatype, MPI_Win win)
int MPI_Put_c(const void *origin_addr, MPI_Count origin_count,
             MPI_Datatype origin_datatype, int target_rank,
             MPI_Aint target_disp, MPI_Count target_count,
             MPI_Datatype target_datatype, MPI_Win win)
Fortran 2008 binding
MPI_Put(origin_addr, origin_count, origin_datatype, target_rank,
             target_disp, target_count, target_datatype, win, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
    INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Put(origin_addr, origin_count, origin_datatype, target_rank,
             target_disp, target_count, target_datatype, win, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, target_count
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
    INTEGER, INTENT(IN) :: target_rank
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_PUT(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK,
             TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, WIN, IERROR)
    <type> ORIGIN_ADDR(*)
```

```
INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK, TARGET_COUNT,
          TARGET_DATATYPE, WIN, IERROR
INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
```

Transfers origin\_count successive entries of the type specified by the origin\_datatype, starting at address origin\_addr on the origin node, to the target node specified by the win, target\_rank pair. The data are written in the target buffer at address target\_addr = window\_base + target\_disp × disp\_unit, where window\_base and disp\_unit are the base address and window displacement unit specified at window initialization, by the target process.

The target buffer is specified by the arguments target\_count and target\_datatype.

The data transfer is the same as that which would occur if the origin process executed a send operation with arguments origin\_addr, origin\_count, origin\_datatype, target\_rank, tag, comm, and the target process executed a receive operation with arguments target\_addr, target\_count, target\_datatype, source, tag, comm, where target\_addr is the target buffer address computed as explained above, the values of tag are arbitrary valid matching tag values, and comm is a communicator for the group of win.

The communication must satisfy the same constraints as for a similar message-passing communication. The target\_datatype may not specify overlapping entries in the target buffer. The message sent must fit, without truncation, in the target buffer. Furthermore, the target buffer must fit in the target window or in attached memory in a dynamic window.

The target\_datatype argument is a handle to a datatype object defined at the origin process. However, this object is interpreted at the target process: the outcome is as if the target datatype object was defined at the target process by the same sequence of calls used to define it at the origin process. The target datatype must contain only relative displacements, not absolute addresses. The same holds for get and accumulate operations.

Advice to users. The target\_datatype argument is a handle to a datatype object that is defined at the origin process, even though it defines a data layout in the target process memory. This causes no problems in a homogeneous environment, or in a heterogeneous environment if only portable datatypes are used (portable datatypes are defined in Section 2.4).

The performance of a put transfer can be significantly affected, on some systems, by the choice of window location and the shape and location of the origin and target buffer: transfers to a target window in memory allocated by MPI\_ALLOC\_MEM or MPI\_WIN\_ALLOCATE may be much faster on shared memory systems; transfers from contiguous buffers will be faster on most, if not all, systems; the alignment of the communication buffers may also impact performance. (*End of advice to users*.)

Advice to implementors. A high-quality implementation will attempt to prevent remote accesses to memory outside the window that was exposed by the process. This is important both for debugging purposes and for protection with client-server codes that use RMA. That is, a high-quality implementation will check, if possible, window bounds on each RMA call, and raise an error at the origin call if an out-of-bound situation occurs. Note that the condition can be checked at the origin. Of course, the added safety achieved by such checks has to be weighed against the added cost of such checks. (End of advice to implementors.)

```
12.3.2 Get
MPI_GET(origin_addr, origin_count, origin_datatype, target_rank, target_disp, target_count,
              target_datatype, win)
  OUT
           origin_addr
                                      initial address of origin buffer (choice)
           origin_count
  IN
                                       number of entries in origin buffer (non-negative
                                      integer)
                                      datatype of each entry in origin buffer (handle)
  IN
           origin_datatype
           target_rank
  IN
                                      rank of target (non-negative integer)
                                                                                        12
  IN
           target_disp
                                       displacement from window start to the beginning of
                                                                                        13
                                       the target buffer (non-negative integer)
                                                                                        14
                                                                                        15
  IN
           target_count
                                       number of entries in target buffer (non-negative
                                                                                        16
                                      integer)
  IN
           target_datatype
                                      datatype of each entry in target buffer (handle)
                                                                                        18
  IN
           win
                                       window object used for communication (handle)
                                                                                        19
                                                                                        20
                                                                                        21
C binding
                                                                                        22
int MPI_Get(void *origin_addr, int origin_count,
                                                                                        23
              MPI_Datatype origin_datatype, int target_rank,
                                                                                        24
              MPI_Aint target_disp, int target_count,
              MPI_Datatype target_datatype, MPI_Win win)
                                                                                        26
int MPI_Get_c(void *origin_addr, MPI_Count origin_count,
                                                                                        27
              MPI_Datatype origin_datatype, int target_rank,
                                                                                        28
              MPI_Aint target_disp, MPI_Count target_count,
                                                                                        29
              MPI_Datatype target_datatype, MPI_Win win)
                                                                                        30
Fortran 2008 binding
MPI_Get(origin_addr, origin_count, origin_datatype, target_rank,
                                                                                        33
              target_disp, target_count, target_datatype, win, ierror)
                                                                                        34
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: origin_addr
                                                                                        35
    INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
                                                                                        36
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
                                                                                        37
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Get(origin_addr, origin_count, origin_datatype, target_rank,
               target_disp, target_count, target_datatype, win, ierror)
                                                                                        42
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: origin_addr
                                                                                        43
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, target_count
                                                                                        44
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
                                                                                        45
    INTEGER, INTENT(IN) :: target_rank
                                                                                        46
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
    TYPE(MPI_Win), INTENT(IN) :: win
```

Similar to MPI\_PUT, except that the direction of data transfer is reversed. Data are copied from the target memory to the origin. The origin\_datatype may not specify overlapping entries in the origin buffer. The target buffer must be contained within the target window or within attached memory in a dynamic window, and the copied data must fit, without truncation, in the origin buffer.

# 12.3.3 Examples for Communication Calls

INTEGER(KIND=MPI\_ADDRESS\_KIND) TARGET\_DISP

These examples show the use of the MPI\_GET function. As all MPI RMA communication functions are nonblocking, they must be completed. In the following, this is accomplished with the routine MPI\_WIN\_FENCE, introduced in Section 12.5.

**Example 12.1** We show how to implement the generic indirect assignment A = B(map), where A, B, and map have the same distribution, and map is a permutation. To simplify, we assume a block distribution with equal size blocks.

```
SUBROUTINE MAPVALS(A, B, map, m, comm, p)
INTEGER m, map(m), comm, p
REAL A(m), B(m)
INTEGER otype(p), oindex(m),
                               &! used to construct origin datatypes
     ttype(p), tindex(m),
                               & ! used to construct target datatypes
     count(p), total(p),
     disp_int, win, ierr
INTEGER (KIND=MPI_ADDRESS_KIND) lowerbound, size, realextent, disp_aint
! This part does the work that depends on the locations of B.
! Can be reused while this does not change
CALL MPI_TYPE_GET_EXTENT(MPI_REAL, lowerbound, realextent, ierr)
disp_int = realextent
size = m * realextent
CALL MPI_WIN_CREATE(B, size, disp_int, MPI_INFO_NULL,
                    comm, win, ierr)
! This part does the work that depends on the value of map and
! the locations of the arrays.
! Can be reused while these do not change
```

```
! Compute number of entries to be received from each process
D0 i=1,p
   count(i) = 0
END DO
DO i=1,m
   j = map(i)/m+1
   count(j) = count(j)+1
END DO
                                                                                     11
total(1) = 0
                                                                                     12
                                                                                     13
DO i=2,p
   total(i) = total(i-1) + count(i-1)
                                                                                     14
                                                                                     15
END DO
                                                                                     16
                                                                                     17
DO i=1,p
                                                                                     18
   count(i) = 0
                                                                                     19
END DO
                                                                                    20
                                                                                    21
! compute origin and target indices of entries.
! entry i at current process is received from location
                                                                                    22
                                                                                    23
! k at process (j-1), where map(i) = (j-1)*m + (k-1),
                                                                                     24
! j = 1..p and k = 1..m
                                                                                    25
                                                                                     26
DO i=1,m
   j = map(i)/m+1
                                                                                    27
   k = MOD(map(i), m) + 1
                                                                                    28
                                                                                    29
   count(j) = count(j)+1
                                                                                    30
   oindex(total(j) + count(j)) = i
   tindex(total(j) + count(j)) = k
END DO
                                                                                    33
                                                                                    34
! create origin and target datatypes for each get operation
DO i=1,p
                                                                                    35
   CALL MPI_TYPE_CREATE_INDEXED_BLOCK(count(i), 1, &
                                                                                    36
                                                                                    37
                                      oindex(total(i)+1:total(i)+count(i)), &
                                                                                    38
                                      MPI_REAL, otype(i), ierr)
   CALL MPI_TYPE_COMMIT(otype(i), ierr)
                                                                                    39
   CALL MPI_TYPE_CREATE_INDEXED_BLOCK(count(i), 1, &
                                      tindex(total(i)+1:total(i)+count(i)), &
                                                                                    42
                                      MPI_REAL, ttype(i), ierr)
   CALL MPI_TYPE_COMMIT(ttype(i), ierr)
                                                                                    43
                                                                                    44
END DO
                                                                                     45
                                                                                     46
! this part does the assignment itself
CALL MPI_WIN_FENCE(0, win, ierr)
disp_aint = 0
```

```
1
     DO i=1,p
2
        CALL MPI_GET(A, 1, otype(i), i-1, disp_aint, 1, ttype(i), win, ierr)
3
     END DO
4
     CALL MPI_WIN_FENCE(0, win, ierr)
5
6
     CALL MPI_WIN_FREE(win, ierr)
7
     DO i=1,p
8
        CALL MPI_TYPE_FREE(otype(i), ierr)
9
        CALL MPI_TYPE_FREE(ttype(i), ierr)
10
     END DO
11
     RETURN
12
     END
13
14
     Example 12.2 A simpler version can be written that does not require that a datatype
15
     be built for the target buffer. But, one then needs a separate get call for each entry, as
16
     illustrated below. This code is much simpler, but usually much less efficient, for large arrays.
17
18
     SUBROUTINE MAPVALS(A, B, map, m, comm, p)
19
     USE MPI
20
     INTEGER m, map(m), comm, p
21
     REAL A(m), B(m)
22
     INTEGER disp_int, win, ierr
23
     INTEGER (KIND=MPI_ADDRESS_KIND) lowerbound, size, realextent, disp_aint
24
25
     CALL MPI_TYPE_GET_EXTENT(MPI_REAL, lowerbound, realextent, ierr)
     disp_int = realextent
27
     size = m * realextent
28
     CALL MPI_WIN_CREATE(B, size, disp_int, MPI_INFO_NULL,
29
                           comm, win, ierr)
30
31
     CALL MPI_WIN_FENCE(0, win, ierr)
32
     DO i=1,m
33
        j = map(i)/m
34
       disp_aint = MOD(map(i),m)
35
        CALL MPI_GET(A(i), 1, MPI_REAL, j, disp_aint, 1, MPI_REAL, win, ierr)
36
     END DO
37
     CALL MPI_WIN_FENCE(0, win, ierr)
38
     CALL MPI_WIN_FREE(win, ierr)
39
     RETURN
40
     END
41
42
```

## 12.3.4 Accumulate Functions

43 44

45

46

47

It is often useful in a put operation to combine the data moved to the target process with the data that resides at that process, rather than replacing it. This will allow, for example, the accumulation of a sum by having all involved processes add their contributions to the sum variable in the memory of one process. The accumulate functions have slightly different

semantics with respect to overlapping data accesses than the put and get functions; see Section 12.7 for details.

#### Accumulate Function

MPI\_ACCUMULATE(origin\_addr, origin\_count, origin\_datatype, target\_rank, target\_disp, target\_count, target\_datatype, op, win)

IN	origin_addr	initial address of buffer (choice)
IN	origin_count	number of entries in buffer (non-negative integer)
IN	origin_datatype	datatype of each entry (handle)
IN	target_rank	rank of target (non-negative integer)
IN	target_disp	displacement from start of window to beginning of target buffer (non-negative integer)
IN	target_count	number of entries in target buffer (non-negative integer)
IN	target_datatype	datatype of each entry in target buffer (handle)
IN	ор	reduce operation (handle)
IN	win	window object (handle)

#### C binding

#### Fortran 2008 binding

14 15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

32

33

34

35

36 37

38 39

40

41 42

43

44

45

46

47

```
TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
2
         INTEGER, INTENT(IN) :: target_rank
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
         TYPE(MPI_Op), INTENT(IN) :: op
5
         TYPE(MPI_Win), INTENT(IN) :: win
6
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
    Fortran binding
    MPI_ACCUMULATE(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK,
9
                  TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, OP, WIN, IERROR)
10
         <type> ORIGIN_ADDR(*)
11
         INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK, TARGET_COUNT,
12
                   TARGET_DATATYPE, OP, WIN, IERROR
13
```

INTEGER(KIND=MPI\_ADDRESS\_KIND) TARGET\_DISP

Accumulate the contents of the origin buffer (as defined by origin\_addr, origin\_count, and origin\_datatype) to the buffer specified by arguments target\_count and target\_datatype, at offset target\_disp, in the target window specified by target\_rank and win, using the operation op. This is like MPI\_PUT except that data is combined into the target area instead of overwriting it.

Any of the predefined operations for MPI\_REDUCE can be used. User-defined functions cannot be used. For example, if op is MPI\_SUM, each element of the origin buffer is added to the corresponding element in the target, replacing the former value in the target.

Each datatype argument must be a predefined datatype or a derived datatype, where all basic components are of the same predefined datatype. Both datatype arguments must be constructed from the same predefined datatype. The operation op applies to elements of that predefined type. The parameter target\_datatype must not specify overlapping entries, and the target buffer must fit in the target window.

A new predefined operation, MPI\_REPLACE, is defined. It corresponds to the associative function f(a,b) = b; i.e., the current value in the target memory is replaced by the value supplied by the origin.

MPI\_REPLACE can be used only in MPI\_ACCUMULATE, MPI\_RACCUMULATE, MPI\_GET\_ACCUMULATE, MPI\_FETCH\_AND\_OP, and MPI\_RGET\_ACCUMULATE, but not in collective reduction operations such as MPI\_REDUCE.

MPI\_PUT is a special case of MPI\_ACCUMULATE, with the op-Advice to users. eration MPI\_REPLACE. Note, however, that MPI\_PUT and MPI\_ACCUMULATE have different constraints on concurrent updates. (End of advice to users.)

**Example 12.3** We want to compute  $B(j) = \sum_{map(i)=j} A(i)$ . The arrays A, B, and map are distributed in the same manner. We write the simple version.

```
SUBROUTINE SUM(A, B, map, m, comm, p)
USE MPI
INTEGER m, map(m), comm, p, win, ierr, disp_int
REAL A(m), B(m)
INTEGER (KIND=MPI_ADDRESS_KIND) lowerbound, size, realextent, disp_aint
```

```
CALL MPI_TYPE_GET_EXTENT(MPI_REAL, lowerbound, realextent, ierr)
size = m * realextent
disp_int = realextent
CALL MPI_WIN_CREATE(B, size, disp_int, MPI_INFO_NULL,
                    comm, win, ierr)
CALL MPI_WIN_FENCE(0, win, ierr)
DO i=1,m
   j = map(i)/m
   disp_aint = MOD(map(i),m)
   CALL MPI_ACCUMULATE(A(i), 1, MPI_REAL, j, disp_aint, 1, MPI_REAL,
                       MPI_SUM, win, ierr)
END DO
CALL MPI_WIN_FENCE(0, win, ierr)
CALL MPI_WIN_FREE(win, ierr)
RETURN
END
```

This code is identical to the code in Example 12.2, except that a call to get has been replaced by a call to accumulate. (Note that, if map is one-to-one, the code computes  $B = A(map^{-1})$ , which is the reverse assignment to the one computed in that previous example.) In a similar manner, we can replace in Example 12.1, the call to get by a call to accumulate, thus performing the computation with only one communication between any two processes.

#### Get Accumulate Function

It is often useful to have fetch-and-accumulate semantics such that the remote data is returned to the caller before the sent data is accumulated into the remote data. The get and accumulate steps are executed atomically for each basic element in the datatype (see Section 12.7 for details). The predefined operation MPI\_REPLACE provides fetch-and-set behavior.

```
1
     MPI_GET_ACCUMULATE(origin_addr, origin_count, origin_datatype, result_addr,
2
                    result_count, result_datatype, target_rank, target_disp, target_count,
3
                    target_datatype, op, win)
       IN
                 origin_addr
                                             initial address of buffer (choice)
5
                 origin_count
       IN
                                             number of entries in origin buffer (non-negative
6
                                             integer)
       IN
                 origin_datatype
                                             datatype of each entry in origin buffer (handle)
9
       OUT
                 result_addr
                                             initial address of result buffer (choice)
10
                 result_count
                                             number of entries in result buffer (non-negative
       IN
11
                                             integer)
12
       IN
                 result_datatype
                                             datatype of each entry in result buffer (handle)
13
14
       IN
                 target_rank
                                             rank of target (non-negative integer)
15
       IN
                 target_disp
                                             displacement from start of window to beginning of
16
                                             target buffer (non-negative integer)
17
       IN
                 target_count
                                             number of entries in target buffer (non-negative
18
                                             integer)
19
20
       IN
                 target_datatype
                                             datatype of each entry in target buffer (handle)
21
       IN
                                             reduce operation (handle)
                 op
22
       IN
                 win
                                             window object (handle)
23
24
25
     C binding
26
     int MPI_Get_accumulate(const void *origin_addr, int origin_count,
27
                    MPI_Datatype origin_datatype, void *result_addr,
28
                    int result_count, MPI_Datatype result_datatype,
                    int target_rank, MPI_Aint target_disp, int target_count,
29
30
                    MPI_Datatype target_datatype, MPI_Op op, MPI_Win win)
31
     int MPI_Get_accumulate_c(const void *origin_addr, MPI_Count origin_count,
32
                    MPI_Datatype origin_datatype, void *result_addr,
33
                    MPI_Count result_count, MPI_Datatype result_datatype,
34
                    int target_rank, MPI_Aint target_disp, MPI_Count target_count,
35
                    MPI_Datatype target_datatype, MPI_Op op, MPI_Win win)
36
37
     Fortran 2008 binding
38
     MPI_Get_accumulate(origin_addr, origin_count, origin_datatype, result_addr,
39
                    result_count, result_datatype, target_rank, target_disp,
                    target_count, target_datatype, op, win, ierror)
41
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
42
          INTEGER, INTENT(IN) :: origin_count, result_count, target_rank,
43
                     target_count
44
          TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, result_datatype,
45
                     target_datatype
46
          TYPE(*), DIMENSION(...), ASYNCHRONOUS :: result_addr
47
          INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
          TYPE(MPI_Op), INTENT(IN) :: op
```

12

13

14

15

16

17 18

19

20 21

22

23 24

26

27

28

34

36

42

43

45

46

47

```
TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Get_accumulate(origin_addr, origin_count, origin_datatype, result_addr,
             result_count, result_datatype, target_rank, target_disp,
             target_count, target_datatype, op, win, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, result_count,
              target_count
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, result_datatype,
              target_datatype
    TYPE(*), DIMENSION(...), ASYNCHRONOUS :: result_addr
    INTEGER, INTENT(IN) :: target_rank
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

Accumulate origin\_count elements of type origin\_datatype from the origin buffer (origin\_addr) to the buffer at offset target\_disp, in the target window specified by target\_rank and win, using the operation op and return in the result buffer result\_addr the content of the target buffer before the accumulation, specified by target\_disp, target\_count, and target\_datatype. The data transferred from origin to target must fit, without truncation, in the target buffer. Likewise, the data copied from target to origin must fit, without truncation, in the result buffer.

The origin and result buffers (origin\_addr and result\_addr) must be disjoint. Each datatype argument must be a predefined datatype or a derived datatype where all basic components are of the same predefined datatype. All datatype arguments must be constructed from the same predefined datatype. The operation op applies to elements of that predefined type. target\_datatype must not specify overlapping entries, and the target buffer must fit in the target window or in attached memory in a dynamic window. The operation is executed atomically for each basic datatype; see Section 12.7 for details.

Any of the predefined operations for MPI\_REDUCE, as well as MPI\_NO\_OP or MPI\_REPLACE can be specified as op. User-defined functions cannot be used. A new predefined operation, MPI\_NO\_OP, is defined. It corresponds to the associative function f(a,b)=a; i.e., the current value in the target memory is returned in the result buffer at the origin and no operation is performed on the target buffer. When MPI\_NO\_OP is specified as the operation, the origin\_addr, origin\_count, and origin\_datatype arguments are ignored. MPI\_NO\_OP can be used only in MPI\_GET\_ACCUMULATE, MPI\_RGET\_ACCUMULATE,

2

3 4

5

6

8

9

10

11

12

13 14 15

16 17

18

20

21

22

23

24

26

27

28 29

30

31

32

33 34

35

36

37

39

41

42

43

44

45

46

47

```
and MPI_FETCH_AND_OP. MPI_NO_OP cannot be used in MPI_ACCUMULATE,
     MPI_RACCUMULATE, or collective reduction operations, such as MPI_REDUCE and others.
          Advice to users. MPI_GET is similar to MPI_GET_ACCUMULATE, with the opera-
          tion MPI_NO_OP. Note, however, that MPI_GET and MPI_GET_ACCUMULATE have
          different constraints on concurrent updates. (End of advice to users.)
     Fetch and Op Function
     The generic functionality of MPI_GET_ACCUMULATE might limit the performance of fetch-
     and-increment or fetch-and-add calls that might be supported by special hardware oper-
     ations. MPI_FETCH_AND_OP thus allows for a fast implementation of a commonly used
     subset of the functionality of MPI_GET_ACCUMULATE.
     MPI_FETCH_AND_OP(origin_addr, result_addr, datatype, target_rank, target_disp, op, win)
       IN
                origin_addr
                                            initial address of buffer (choice)
19
       OUT
                result_addr
                                           initial address of result buffer (choice)
       IN
                                            datatype of the entry in origin, result, and target
                datatype
                                           buffers (handle)
       IN
                target_rank
                                           rank of target (non-negative integer)
                                            displacement from start of window to beginning of
       IN
                target_disp
                                            target buffer (non-negative integer)
       IN
                                            reduce operation (handle)
                op
       IN
                                            window object (handle)
                win
     C binding
     int MPI_Fetch_and_op(const void *origin_addr, void *result_addr,
                    MPI_Datatype datatype, int target_rank, MPI_Aint target_disp,
                    MPI_Op op, MPI_Win win)
     Fortran 2008 binding
     MPI_Fetch_and_op(origin_addr, result_addr, datatype, target_rank,
                    target_disp, op, win, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: result_addr
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, INTENT(IN) :: target_rank
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
         TYPE(MPI_Op), INTENT(IN) :: op
```

# Fortran binding

TYPE(MPI\_Win), INTENT(IN) :: win

INTEGER, OPTIONAL, INTENT(OUT) :: ierror

MPI\_FETCH\_AND\_OP(ORIGIN\_ADDR, RESULT\_ADDR, DATATYPE, TARGET\_RANK, TARGET\_DISP, OP, WIN, IERROR)

```
<type> ORIGIN_ADDR(*), RESULT_ADDR(*)
INTEGER DATATYPE, TARGET_RANK, OP, WIN, IERROR
INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
```

Accumulate one element of type datatype from the origin buffer (origin\_addr) to the buffer at offset target\_disp, in the target window specified by target\_rank and win, using the operation op and return in the result buffer result\_addr the content of the target buffer before the accumulation.

The origin and result buffers (origin\_addr and result\_addr) must be disjoint. Any of the predefined operations for MPI\_REDUCE, as well as MPI\_NO\_OP or MPI\_REPLACE, can be specified as op; user-defined functions cannot be used. The datatype argument must be a predefined datatype. The operation is executed atomically.

## Compare and Swap Function

Another useful operation is an atomic compare and swap where the value at the origin is compared to the value at the target, which is atomically replaced by a third value only if the values at origin and target are equal.

MPI\_COMPARE\_AND\_SWAP(origin\_addr, compare\_addr, result\_addr, datatype, target\_rank, target\_disp, win)

IN	origin_addr	initial address of buffer (choice)
IN	compare_addr	initial address of compare buffer (choice)
OUT	result_addr	initial address of result buffer (choice)
IN	datatype	datatype of the element in all buffers (handle)
IN	target_rank	rank of target (non-negative integer)
IN	target_disp	displacement from start of window to beginning of
		target buffer (non-negative integer)
IN	win	window object (handle)

#### C binding

#### Fortran 2008 binding

### Fortran binding

This function compares one element of type datatype in the compare buffer compare\_addr with the buffer at offset target\_disp in the target window specified by target\_rank and win and replaces the value at the target with the value in the origin buffer origin\_addr if the compare buffer and the target buffer are identical. The original value at the target is returned in the buffer result\_addr. The parameter datatype must belong to one of the following categories of predefined datatypes: C integer, Fortran integer, Logical, Multi-language types, or Byte as specified in Section 6.9.2. The origin and result buffers (origin\_addr and result\_addr) must be disjoint.

## 12.3.5 Request-based RMA Communication Operations

Request-based RMA communication operations allow the user to associate a request handle with the RMA operations and test or wait for the completion of these requests using the functions described in Section 3.7.3. Request-based RMA operations are only valid within a passive target epoch (see Section 12.5).

Upon returning from a completion call in which an RMA operation completes, all fields of the status object, if any, and the results of status query functions (e.g., MPI\_GET\_COUNT) are undefined with the exception of MPI\_ERROR if appropriate (see Section 3.2.5). It is valid to mix different request types (e.g., any combination of RMA)

requests, collective requests, I/O requests, generalized requests, or point-to-point requests) in functions that enable multiple completions (e.g., MPI\_WAITALL). It is erroneous to call MPI\_REQUEST\_FREE or MPI\_CANCEL for a request associated with an RMA operation.

RMA requests are not persistent.

The end of the epoch, or explicit bulk synchronization using MPI\_WIN\_FLUSH, MPI\_WIN\_FLUSH\_ALL, MPI\_WIN\_FLUSH\_LOCAL, or MPI\_WIN\_FLUSH\_LOCAL\_ALL, also indicates completion of the RMA operations. However, users must still wait or test on the request handle to allow the MPI implementation to clean up any resources associated with these requests; in such cases the wait operation will complete locally.

```
MPI_RPUT(origin_addr, origin_count, origin_datatype, target_rank, target_disp,
                                                                                         2
               target_count, target_datatype, win, request)
  IN
           origin_addr
                                       initial address of origin buffer (choice)
  IN
           origin_count
                                       number of entries in origin buffer (non-negative
                                       integer)
  IN
           origin_datatype
                                       datatype of each entry in origin buffer (handle)
  IN
           target_rank
                                       rank of target (non-negative integer)
                                       displacement from start of window to target buffer
  IN
           target_disp
                                       (non-negative integer)
                                                                                        11
  IN
           target_count
                                       number of entries in target buffer (non-negative
                                                                                        12
                                                                                        13
                                       integer)
                                                                                        14
           target_datatype
  IN
                                       datatype of each entry in target buffer (handle)
                                                                                        15
  IN
           win
                                       window object used for communication (handle)
                                                                                        16
  OUT
                                       RMA request (handle)
           request
                                                                                        18
                                                                                        19
C binding
                                                                                        20
int MPI_Rput(const void *origin_addr, int origin_count,
                                                                                        21
              MPI_Datatype origin_datatype, int target_rank,
                                                                                        22
              MPI_Aint target_disp, int target_count,
                                                                                        23
              MPI_Datatype target_datatype, MPI_Win win,
                                                                                        24
              MPI_Request *request)
int MPI_Rput_c(const void *origin_addr, MPI_Count origin_count,
                                                                                        26
              MPI_Datatype origin_datatype, int target_rank,
                                                                                        27
              MPI_Aint target_disp, MPI_Count target_count,
                                                                                        28
              MPI_Datatype target_datatype, MPI_Win win,
                                                                                        29
              MPI_Request *request)
                                                                                        30
Fortran 2008 binding
MPI_Rput(origin_addr, origin_count, origin_datatype, target_rank,
                                                                                        33
              target_disp, target_count, target_datatype, win, request,
                                                                                        34
               ierror)
                                                                                        35
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
                                                                                        36
    INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
                                                                                        37
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
                                                                                        39
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                        42
MPI_Rput(origin_addr, origin_count, origin_datatype, target_rank,
                                                                                        43
              target_disp, target_count, target_datatype, win, request,
                                                                                        44
               ierror)
                                                                                        45
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
                                                                                        46
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, target_count
                                                                                        47
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
```

```
1
         INTEGER, INTENT(IN) :: target_rank
2
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
         TYPE(MPI_Win), INTENT(IN) :: win
         TYPE(MPI_Request), INTENT(OUT) :: request
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
     Fortran binding
     MPI_RPUT(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK,
                  TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, WIN, REQUEST,
9
                  IERROR)
10
         <type> ORIGIN_ADDR(*)
11
         INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK, TARGET_COUNT,
12
                   TARGET_DATATYPE, WIN, REQUEST, IERROR
13
         INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
14
```

MPI\_RPUT is similar to MPI\_PUT (Section 12.3.1), except that it allocates a communication request object and associates it with the request handle (the argument request). The completion of an MPI\_RPUT operation (i.e., after the corresponding test or wait) indicates that the sender is now free to update the locations in the origin buffer. It does not indicate that the data is available at the target window. If remote completion is required, MPI\_WIN\_FLUSH, MPI\_WIN\_FLUSH\_ALL, MPI\_WIN\_UNLOCK, or MPI\_WIN\_UNLOCK\_ALL can be used.

MPI\_RGET(origin\_addr, origin\_count, origin\_datatype, target\_rank, target\_disp, target\_count, target\_datatype, win, request)

OUT	origin_addr	initial address of origin buffer (choice)
IN	origin_count	number of entries in origin buffer (non-negative integer)
IN	origin_datatype	data type of each entry in origin buffer (handle)
IN	target_rank	rank of target (non-negative integer)
IN	target_disp	displacement from window start to the beginning of the target buffer (non-negative integer)
1N	target_count	number of entries in target buffer (non-negative integer)
IN	target_datatype	data type of each entry in target buffer (handle)
IN	win	window object used for communication (handle)
OUT	request	RMA request (handle)

## C binding

13

14

15

16

18

19

20

21

22

23

26

27

28

29

30

34

35

36

37

42

```
int MPI_Rget_c(void *origin_addr, MPI_Count origin_count,
             MPI_Datatype origin_datatype, int target_rank,
             MPI_Aint target_disp, MPI_Count target_count,
             MPI_Datatype target_datatype, MPI_Win win,
             MPI_Request *request)
Fortran 2008 binding
MPI_Rget(origin_addr, origin_count, origin_datatype, target_rank,
             target_disp, target_count, target_datatype, win, request,
             ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: origin_addr
    INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Rget(origin_addr, origin_count, origin_datatype, target_rank,
             target_disp, target_count, target_datatype, win, request,
             ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: origin_addr
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, target_count
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
    INTEGER, INTENT(IN) :: target_rank
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_RGET(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK,
             TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, WIN, REQUEST,
             IERROR)
    <type> ORIGIN_ADDR(*)
    INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK, TARGET_COUNT,
              TARGET_DATATYPE, WIN, REQUEST, IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
    MPI_RGET is similar to MPI_GET (Section 12.3.2), except that it allocates a commu-
```

MPI\_RGET is similar to MPI\_GET (Section 12.3.2), except that it allocates a communication request object and associates it with the request handle (the argument request) that can be used to wait or test for completion. The completion of an MPI\_RGET operation indicates that the data is available in the origin buffer. If origin\_addr points to memory attached to a window, then the data becomes available in the private copy of this window.

```
1
     MPI_RACCUMULATE(origin_addr, origin_count, origin_datatype, target_rank, target_disp,
2
                    target_count, target_datatype, op, win, request)
3
       IN
                origin_addr
                                            initial address of buffer (choice)
       IN
                origin_count
                                            number of entries in buffer (non-negative integer)
6
                origin_datatype
                                            datatype of each entry in origin buffer (handle)
       IN
       IN
                target_rank
                                            rank of target (non-negative integer)
       IN
                target_disp
                                            displacement from start of window to beginning of
9
                                            target buffer (non-negative integer)
10
11
       IN
                                            number of entries in target buffer (non-negative
                target_count
12
                                            integer)
13
       IN
                target_datatype
                                            datatype of each entry in target buffer (handle)
14
       IN
                                            reduce operation (handle)
                op
15
16
       IN
                win
                                            window object (handle)
17
                                            RMA request (handle)
       OUT
                request
18
19
     C binding
20
     int MPI_Raccumulate(const void *origin_addr, int origin_count,
21
                    MPI_Datatype origin_datatype, int target_rank,
22
                    MPI_Aint target_disp, int target_count,
23
                    MPI_Datatype target_datatype, MPI_Op op, MPI_Win win,
24
                    MPI_Request *request)
25
26
     int MPI_Raccumulate_c(const void *origin_addr, MPI_Count origin_count,
27
                    MPI_Datatype origin_datatype, int target_rank,
                    MPI_Aint target_disp, MPI_Count target_count,
28
                    MPI_Datatype target_datatype, MPI_Op op, MPI_Win win,
29
30
                    MPI_Request *request)
31
     Fortran 2008 binding
32
     MPI_Raccumulate(origin_addr, origin_count, origin_datatype, target_rank,
33
                    target_disp, target_count, target_datatype, op, win, request,
34
                    ierror)
35
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
36
         INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
37
         TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
39
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Win), INTENT(IN) :: win
         TYPE(MPI_Request), INTENT(OUT) :: request
42
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
43
44
     MPI_Raccumulate(origin_addr, origin_count, origin_datatype, target_rank,
45
                    target_disp, target_count, target_datatype, op, win, request,
46
                    ierror)
47
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, target_count
```

```
TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
INTEGER, INTENT(IN) :: target_rank
INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
TYPE(MPI_Op), INTENT(IN) :: op
TYPE(MPI_Win), INTENT(IN) :: win
TYPE(MPI_Request), INTENT(OUT) :: request
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

MPI\_RACCUMULATE(ORIGIN\_ADDR, ORIGIN\_COUNT, ORIGIN\_DATATYPE, TARGET\_RANK, TARGET\_DISP, TARGET\_COUNT, TARGET\_DATATYPE, OP, WIN, REQUEST, IERROR)

<type> ORIGIN\_ADDR(\*)

MPI\_RACCUMULATE is similar to MPI\_ACCUMULATE (Section 12.3.4), except that it allocates a communication request object and associates it with the request handle (the argument request) that can be used to wait or test for completion. The completion of an MPI\_RACCUMULATE operation indicates that the origin buffer is free to be updated. It does not indicate that the operation has completed at the target window.

```
1
     MPI_RGET_ACCUMULATE(origin_addr, origin_count, origin_datatype, result_addr,
2
                     result_count, result_datatype, target_rank, target_disp, target_count,
3
                     target_datatype, op, win, request)
4
       IN
                 origin_addr
                                              initial address of buffer (choice)
5
       IN
                 origin_count
                                              number of entries in origin buffer (non-negative
6
                                              integer)
       IN
                 origin_datatype
                                              datatype of each entry in origin buffer (handle)
9
       OUT
                 result_addr
                                              initial address of result buffer (choice)
10
                 result_count
                                              number of entries in result buffer (non-negative
       IN
11
                                              integer)
12
13
       IN
                 result_datatype
                                              datatype of entries in result buffer (handle)
14
       IN
                 target_rank
                                              rank of target (non-negative integer)
15
       IN
                 target_disp
                                              displacement from start of window to beginning of
16
                                              target buffer (non-negative integer)
17
18
                                              number of entries in target buffer (non-negative
       IN
                 target_count
19
                                              integer)
20
       IN
                 target_datatype
                                              datatype of each entry in target buffer (handle)
21
       IN
                 op
                                              reduce operation (handle)
22
23
       IN
                                              window object (handle)
                 win
24
       OUT
                                              RMA request (handle)
                 request
25
26
     C binding
27
     int MPI_Rget_accumulate(const void *origin_addr, int origin_count,
28
                     MPI_Datatype origin_datatype, void *result_addr,
29
                     int result_count, MPI_Datatype result_datatype,
30
                     int target_rank, MPI_Aint target_disp, int target_count,
31
                     MPI_Datatype target_datatype, MPI_Op op, MPI_Win win,
32
                     MPI_Request *request)
33
34
     int MPI_Rget_accumulate_c(const void *origin_addr, MPI_Count origin_count,
35
                     MPI_Datatype origin_datatype, void *result_addr,
36
                     MPI_Count result_count, MPI_Datatype result_datatype,
37
                     int target_rank, MPI_Aint target_disp, MPI_Count target_count,
38
                     MPI_Datatype target_datatype, MPI_Op op, MPI_Win win,
39
                     MPI_Request *request)
40
     Fortran 2008 binding
41
     MPI_Rget_accumulate(origin_addr, origin_count, origin_datatype,
42
                     result_addr, result_count, result_datatype, target_rank,
43
                     target_disp, target_count, target_datatype, op, win, request,
44
                     ierror)
45
          TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
46
          INTEGER, INTENT(IN) :: origin_count, result_count, target_rank,
47
                      target_count
```

13

14

15

16

18

19

20

21

22

23

24

26

27 28

29 30

33

34

35

36

42 43

44 45

46

47

```
TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, result_datatype,
              target_datatype
    TYPE(*), DIMENSION(...), ASYNCHRONOUS :: result_addr
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Rget_accumulate(origin_addr, origin_count, origin_datatype,
             result_addr, result_count, result_datatype, target_rank,
             target_disp, target_count, target_datatype, op, win, request,
             ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, result_count,
              target_count
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, result_datatype,
              target_datatype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: result_addr
    INTEGER, INTENT(IN) :: target_rank
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_RGET_ACCUMULATE(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE,
             RESULT_ADDR, RESULT_COUNT, RESULT_DATATYPE, TARGET_RANK,
             TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, OP, WIN, REQUEST,
             IERROR)
    <type> ORIGIN_ADDR(*), RESULT_ADDR(*)
```

INTEGER ORIGIN\_COUNT, ORIGIN\_DATATYPE, RESULT\_COUNT, RESULT\_DATATYPE,

TARGET\_RANK, TARGET\_COUNT, TARGET\_DATATYPE, OP, WIN, REQUEST,

IERROR

INTEGER(KIND=MPI\_ADDRESS\_KIND) TARGET\_DISP

MPI\_RGET\_ACCUMULATE is similar to MPI\_GET\_ACCUMULATE (Section 12.3.4), except that it allocates a communication request object and associates it with the request handle (the argument request) that can be used to wait or test for completion. The completion of an MPI\_RGET\_ACCUMULATE operation indicates that the data is available in the result buffer and the origin buffer is free to be updated. It does not indicate that the operation has been completed at the target window.

# 12.4 Memory Model

The memory semantics of RMA are best understood by using the concept of *public* and *private* window copies. We assume that systems have a public memory region that is addressable by all processes (e.g., the shared memory in shared memory machines or the




Figure 12.1: Schematic description of the public/private window operations in the MPI\_WIN\_SEPARATE memory model for two overlapping windows.

exposed main memory in distributed memory machines). In addition, most machines have fast private buffers (e.g., transparent caches or explicit communication buffers) local to each process where copies of data elements from the main memory can be stored for faster access. Such buffers are either coherent, i.e., all updates to main memory are reflected in all private copies consistently, or non-coherent, i.e., conflicting accesses to main memory need to be synchronized and updated in all private copies explicitly. Coherent systems allow direct updates to remote memory without any participation of the remote side. Non-coherent systems, however, need to call RMA functions in order to reflect updates to the public window in their private memory. Thus, in coherent memory, the public and the private window are identical while they remain logically separate in the non-coherent case. MPI thus differentiates between two memory models called RMA unified, if public and private window are logically identical, and RMA separate, otherwise.

In the RMA separate model, there is only one instance of each variable in process memory, but a distinct *public* copy of the variable for each window that contains it. A load accesses the instance in process memory (this includes MPI sends). A local store accesses and updates the instance in process memory (this includes MPI receives), but the update may affect other public copies of the same locations. A get on a window accesses the public copy of that window. A put or accumulate on a window accesses and updates the public copy of that window, but the update may affect the private copy of the same locations in process memory, and public copies of other overlapping windows. This is illustrated in Figure 12.1.

In the RMA unified model, public and private copies are identical and updates via put or accumulate calls are eventually observed by load operations without additional RMA calls. A store access to a window is eventually visible to remote get or accumulate calls without additional RMA calls. These stronger semantics of the RMA unified model allow the user to omit some synchronization calls and potentially improve performance.

Advice to users. If accesses in the RMA unified model are not synchronized (with

locks or flushes, see Section 12.5.3), load and store operations might observe changes to the memory while they are in progress. The order in which data is written is not specified unless further synchronization is used. This might lead to inconsistent views on memory and programs that assume that a transfer is complete by only checking parts of the message are erroneous. (*End of advice to users*.)

The memory model for a particular RMA window can be determined by accessing the attribute MPI\_WIN\_MODEL. If the memory model is the unified model, the value of this attribute is MPI\_WIN\_UNIFIED; otherwise, the value is MPI\_WIN\_SEPARATE.

## 12.5 Synchronization Calls

RMA communications fall in two categories:

- active target communication, where data is moved from the memory of one process to the memory of another, and both are explicitly involved in the communication. This communication pattern is similar to message passing, except that all the data transfer arguments are provided by one process, and the second process only participates in the synchronization.
- passive target communication, where data is moved from the memory of one process to the memory of another, and only the origin process is explicitly involved in the transfer. Thus, two origin processes may communicate by accessing the same location in a target window. The process that owns the target window may be distinct from the two communicating processes, in which case it does not participate explicitly in the communication. This communication paradigm is closest to a shared memory model, where shared data can be accessed by all processes, irrespective of location.

RMA communication calls with argument win must occur at a process only within an access epoch for win. Such an epoch starts with an RMA synchronization call on win; it proceeds with zero or more RMA communication calls (e.g., MPI\_PUT, MPI\_GET or MPI\_ACCUMULATE) on win; it completes with another synchronization call on win. This allows users to amortize one synchronization with multiple data transfers and provide implementors more flexibility in the implementation of RMA operations.

Distinct access epochs for win at the same process must be disjoint. On the other hand, epochs pertaining to different win arguments may overlap. Local operations or other MPI calls may also occur during an epoch.

In active target communication, a target window can be accessed by RMA operations only within an **exposure epoch**. Such an epoch is started and completed by RMA synchronization calls executed by the target process. Distinct exposure epochs at a process on the same window must be disjoint, but such an exposure epoch may overlap with exposure epochs on other windows or with access epochs for the same or other win arguments. There is a one-to-one matching between access epochs at origin processes and exposure epochs on target processes: RMA operations issued by an origin process for a target window will access that target window during the same exposure epoch if and only if they were issued during the same access epoch.

In passive target communication the target process does not execute RMA synchronization calls, and there is no concept of an exposure epoch.

MPI provides three synchronization mechanisms:

1. The MPI\_WIN\_FENCE collective synchronization call supports a simple synchronization pattern that is often used in parallel computations: namely a loosely-synchronous model, where global computation phases alternate with global communication phases. This mechanism is most useful for loosely synchronous algorithms where the graph of communicating processes changes very frequently, or where each process communicates with many others.

This call is used for active target communication. An access epoch at an origin process or an exposure epoch at a target process are started and completed by calls to MPI\_WIN\_FENCE. A process can access windows at all processes in the group of win during such an access epoch, and the local window can be accessed by all processes in the group of win during such an exposure epoch.

2. The four functions MPI\_WIN\_START, MPI\_WIN\_COMPLETE, MPI\_WIN\_POST, and MPI\_WIN\_WAIT can be used to restrict synchronization to the minimum: only pairs of communicating processes synchronize, and they do so only when a synchronization is needed to order correctly RMA accesses to a window with respect to local accesses to that same window. This mechanism may be more efficient when each process communicates with few (logical) neighbors, and the communication graph is fixed or changes infrequently.

These calls are used for active target communication. An access epoch is started at the origin process by a call to MPI\_WIN\_START and is terminated by a call to MPI\_WIN\_COMPLETE. The start call has a group argument that specifies the group of target processes for that epoch. An exposure epoch is started at the target process by a call to MPI\_WIN\_POST and is completed by a call to MPI\_WIN\_WAIT. The post call has a group argument that specifies the set of origin processes for that epoch.

3. Finally, shared lock access is provided by the functions MPI\_WIN\_LOCK, MPI\_WIN\_LOCK\_ALL, MPI\_WIN\_UNLOCK, and MPI\_WIN\_UNLOCK\_ALL. MPI\_WIN\_LOCK and MPI\_WIN\_UNLOCK also provide exclusive lock capability. Lock synchronization is useful for MPI applications that emulate a shared memory model via MPI calls; e.g., in a "bulletin board" model, where processes can, at random times, access or update different parts of the bulletin board.

These four calls provide passive target communication. An access epoch is started by a call to MPI\_WIN\_LOCK or MPI\_WIN\_LOCK\_ALL and terminated by a call to MPI\_WIN\_UNLOCK or MPI\_WIN\_UNLOCK\_ALL, respectively.

Figure 12.2 illustrates the general synchronization pattern for active target communication. The synchronization between post and start ensures that the put call of the origin process does not start until the target process exposes the window (with the post call); the target process will expose the window only after preceding local accesses to the window have completed. The synchronization between complete and wait ensures that the put call of the origin process completes before the window is unexposed (with the wait call). The target process will execute following local accesses to the target window only after the wait returned.

Figure 12.2 shows operations occurring in the natural temporal order implied by the synchronizations: the post occurs before the matching start, and complete occurs before the matching wait. However, such strong synchronization is more than needed for




Figure 12.2: Active target communication. Dashed arrows represent synchronizations (ordering of events).

correct ordering of window accesses. The semantics of MPI calls allow **weak synchronization**, as illustrated in Figure 12.3. The access to the target window is delayed until the window is exposed, after the post. However the start may complete earlier; the put and complete may also terminate earlier, if put data is buffered by the implementation. The synchronization calls order correctly window accesses, but do not necessarily synchronize other operations. This weaker synchronization semantic allows for more efficient implementations.

Figure 12.4 illustrates the general synchronization pattern for passive target communication. The first origin process communicates data to the second origin process, through the memory of the target process; the target process is not explicitly involved in the communication. The lock and unlock calls ensure that the two RMA accesses do not occur concurrently. However, they do *not* ensure that the put by origin 1 will precede the get by origin 2.

Rationale. RMA does not define fine-grained mutexes in memory (only logical coarse-grained process locks). MPI provides the primitives (compare and swap, accumulate, send/receive, etc.) needed to implement high-level synchronization operations. (*End of rationale.*)




Figure 12.3: Active target communication, with weak synchronization. Dashed arrows represent synchronizations (ordering of events)

### 12.5.1 Fence

```
MPI_WIN_FENCE(assert, win)

IN assert program assertion (integer)

IN win window object (handle)

C binding
int MPI_Win_fence(int assert, MPI_Win win)
```

## Fortran 2008 binding

```
MPI_Win_fence(assert, win, ierror)
    INTEGER, INTENT(IN) :: assert
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

## Fortran binding

```
MPI_WIN_FENCE(ASSERT, WIN, IERROR)
INTEGER ASSERT, WIN, IERROR
```

The MPI call MPI\_WIN\_FENCE(assert, win) synchronizes RMA calls on win. The call




Figure 12.4: Passive target communication. Dashed arrows represent synchronizations (ordering of events).

is collective on the group of win. All RMA operations on win originating at a given process and started before the fence call will complete at that process before the fence call returns. They will be completed at their target before the fence call returns at the target. RMA operations on win started by a process after the fence call returns will access their target window only after MPI\_WIN\_FENCE has been called by the target process.

The call completes an RMA access epoch if it was preceded by another fence call and the local process issued RMA communication calls on win between these two calls. The call completes an RMA exposure epoch if it was preceded by another fence call and the local window was the target of RMA accesses between these two calls. The call starts an RMA access epoch if it is followed by another fence call and by RMA communication calls issued between these two fence calls. The call starts an exposure epoch if it is followed by another fence call and the local window is the target of RMA accesses between these two fence calls. Thus, the fence call is equivalent to calls to a subset of post, start, complete, wait.

A fence call usually entails a barrier synchronization: a process completes a call to MPI\_WIN\_FENCE only after all other processes in the group entered their matching call.

However, a call to MPI\_WIN\_FENCE that is known not to end any epoch (in particular, a call with assert equal to MPI\_MODE\_NOPRECEDE) does not necessarily act as a barrier.

The assert argument is used to provide assertions on the context of the call that may be used for various optimizations. This is described in Section 12.5.5. A value of assert = 0 is always valid.

Advice to users. Calls to MPI\_WIN\_FENCE should both precede and follow calls to RMA communication functions that are synchronized with fence calls. (*End of advice to users.*)

## 12.5.2 General Active Target Synchronization

## MPI\_WIN\_START(group, assert, win)

```
INgroupgroup of target processes (handle)INassertprogram assertion (integer)INwinwindow object (handle)
```

### C binding

int MPI\_Win\_start(MPI\_Group group, int assert, MPI\_Win win)

## Fortran 2008 binding

```
MPI_Win_start(group, assert, win, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group
    INTEGER, INTENT(IN) :: assert
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_WIN_START(GROUP, ASSERT, WIN, IERROR)
INTEGER GROUP, ASSERT, WIN, IERROR
```

Starts an RMA access epoch for win. RMA calls issued on win during this epoch must access only windows at processes in group. Each process in group must issue a matching call to MPI\_WIN\_POST. RMA accesses to each target window will be delayed, if necessary, until the target process executed the matching call to MPI\_WIN\_POST. MPI\_WIN\_START is allowed to block until the corresponding MPI\_WIN\_POST calls are executed, but is not required to.

The assert argument is used to provide assertions on the context of the call that may be used for various optimizations. This is described in Section 12.5.5. A value of assert = 0 is always valid.

```
MPI_WIN_COMPLETE(win)
```

```
IN window object (handle)
```

#### C binding

```
int MPI_Win_complete(MPI_Win win)
Fortran 2008 binding
MPI_Win_complete(win, ierror)
        TYPE(MPI_Win), INTENT(IN) :: win
        INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_WIN_COMPLETE(WIN, IERROR)
        INTEGER WIN, IERROR
```

Completes an RMA access epoch on win started by a call to MPI\_WIN\_START. All RMA communication calls issued on win during this epoch will have completed at the origin when the call returns.

MPI\_WIN\_COMPLETE enforces completion of preceding RMA calls at the origin, but not at the target. A put or accumulate call may not have completed at the target when it has completed at the origin.

Consider the sequence of calls in the example below.

## Example 12.4 Use of MPI\_WIN\_START and MPI\_WIN\_COMPLETE.

```
MPI_Win_start(group, flag, win);
MPI_Put(..., win);
MPI_Win_complete(win);
```

The call to MPI\_WIN\_COMPLETE does not return until the put call has completed at the origin; and the target window will be accessed by the put operation only after the call to MPI\_WIN\_START has matched a call to MPI\_WIN\_POST by the target process. This still leaves much choice to implementors. The call to MPI\_WIN\_START can block until the matching call to MPI\_WIN\_POST occurs at all target processes. One can also have implementations where the call to MPI\_WIN\_START is nonblocking, but the call to MPI\_PUT blocks until the matching call to MPI\_WIN\_POST occurs; or implementations where the first two calls are nonblocking, but the call to MPI\_WIN\_COMPLETE blocks until the call to MPI\_WIN\_POST occurred; or even implementations where all three calls can complete before any target process has called MPI\_WIN\_POST—the data put must be buffered, in this last case, so as to allow the put to complete at the origin ahead of its completion at the target. However, once the call to MPI\_WIN\_POST is issued, the sequence above must complete, without further dependencies.

## MPI\_WIN\_POST(group, assert, win)

IN	group	group of origin processes (handle)
IN	assert	program assertion (integer)
IN	win	window object (handle)

### C binding

```
int MPI_Win_post(MPI_Group group, int assert, MPI_Win win)
```

#### Fortran 2008 binding

```
MPI_Win_post(group, assert, win, ierror)
```

26

27

28

29

30

31

32

33 34

35

36

37

38 39

40 41

42

43 44

45 46

47

48

```
TYPE(MPI_Group), INTENT(IN) :: group
2
         INTEGER, INTENT(IN) :: assert
         TYPE(MPI_Win), INTENT(IN) :: win
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
5
     Fortran binding
6
     MPI_WIN_POST(GROUP, ASSERT, WIN, IERROR)
         INTEGER GROUP, ASSERT, WIN, IERROR
9
         Starts an RMA exposure epoch for the local window associated with win. Only processes
10
     in group should access the window with RMA calls on win during this epoch. Each process
11
     in group must issue a matching call to MPI_WIN_START. MPI_WIN_POST does not block.
12
13
     MPI_WIN_WAIT(win)
14
15
       IN
                win
                                            window object (handle)
16
17
     C binding
18
     int MPI_Win_wait(MPI_Win win)
19
     Fortran 2008 binding
20
21
     MPI_Win_wait(win, ierror)
         TYPE(MPI_Win), INTENT(IN) :: win
22
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
23
24
     Fortran binding
25
     MPI_WIN_WAIT(WIN, IERROR)
```

INTEGER WIN, IERROR

Completes an RMA exposure epoch started by a call to MPI\_WIN\_POST on win. This call matches calls to MPI\_WIN\_COMPLETE(win) issued by each of the origin processes that were granted access to the window during this epoch. The call to MPI\_WIN\_WAIT will block until all matching calls to MPI\_WIN\_COMPLETE have occurred. This guarantees that all these origin processes have completed their RMA accesses to the local window. When the call returns, all these RMA accesses will have completed at the target window.

Figure 12.5 illustrates the use of these four functions. Process 0 puts data in the windows of processes 1 and 2 and process 3 puts data in the window of process 2. Each start call lists the ranks of the processes whose windows will be accessed; each post call lists the ranks of the processes that access the local window. The figure illustrates a possible timing for the events, assuming strong synchronization; in a weak synchronization, the start, put or complete calls may occur ahead of the matching post calls.

```
MPI_WIN_TEST(win, flag)
 IN
           win
                                        window object (handle)
 OUT
           flag
                                       success flag (logical)
C binding
int MPI_Win_test(MPI_Win win, int *flag)
```




Figure 12.5: Active target communication. Dashed arrows represent synchronizations and solid arrows represent data transfer.

## Fortran 2008 binding

```
MPI_Win_test(win, flag, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

```
MPI_WIN_TEST(WIN, FLAG, IERROR)
INTEGER WIN, IERROR
LOGICAL FLAG
```

This is the nonblocking version of MPI\_WIN\_WAIT. It returns flag = true if all accesses to the local window by the group to which it was exposed by the corresponding MPI\_WIN\_POST call have been completed as signalled by matching MPI\_WIN\_COMPLETE calls, and flag = false otherwise. In the former case MPI\_WIN\_WAIT would have returned immediately. The effect of return of MPI\_WIN\_TEST with flag = true is the same as the effect of a return of MPI\_WIN\_WAIT. If flag = false is returned, then the call has no visible effect.

MPI\_WIN\_TEST should be invoked only where MPI\_WIN\_WAIT can be invoked. Once the call has returned flag = true, it must not be invoked anew, until the window is posted anew.

Assume that window win is associated with a "hidden" communicator wincomm, used for communication by the processes of win. The rules for matching of post and start calls and for matching complete and wait calls can be derived from the rules for matching sends and receives, by considering the following (partial) model implementation.

MPI\_WIN\_POST(group,0,win) initiates a nonblocking send with tag tag0 to each process in group, using wincomm. There is no need to wait for the completion of these sends.

MPI\_WIN\_START(group,0,win) initiates a nonblocking receive with tag tag0 from each process in group, using wincomm. An RMA access to a window in target process i is delayed until the receive from i is completed.

MPI\_WIN\_COMPLETE(win) initiates a nonblocking send with tag tag1 to each process in the group of the preceding start call. No need to wait for the completion of these sends.

MPI\_WIN\_WAIT(win) initiates a nonblocking receive with tag tag1 from each process in the group of the preceding post call. Wait for the completion of all receives.

 No races can occur in a correct program: each of the sends matches a unique receive, and vice versa.

Rationale. The design for general active target synchronization requires the user to provide complete information on the communication pattern, at each end of a communication link: each origin specifies a list of targets, and each target specifies a list of origins. This provides maximum flexibility (hence, efficiency) for the implementor: each synchronization can be initiated by either side, since each "knows" the identity of the other. This also provides maximum protection from possible races. On the other hand, the design requires more information than RMA needs: in general, it is sufficient for the origin to know the rank of the target, but not vice versa. Users that want more "anonymous" communication will be required to use the fence or lock mechanisms. (End of rationale.)

Advice to users. Assume a communication pattern that is represented by a directed graph  $G = \langle V, E \rangle$ , where  $V = \{0, \ldots, n-1\}$  and  $ij \in E$  if origin process i accesses the window at target process j. Then each process i issues a call to MPI\_WIN\_POST( $ingroup_i, \ldots$ ), followed by a call to

MPI\_WIN\_START(outgroup<sub>i</sub>,...), where  $outgroup_i = \{j : ij \in E\}$  and  $ingroup_i = \{j : ji \in E\}$ . A call is a noop, and can be skipped, if the group argument is empty. After the communications calls, each process that issued a start will issue a complete. Finally, each process that issued a post will issue a wait.

Note that each process may call with a group argument that has different members. (*End of advice to users.*)

12.5.3 Lock

## MPI\_WIN\_LOCK(lock\_type, rank, assert, win)

```
IN lock_type either MPI_LOCK_EXCLUSIVE or MPI_LOCK_SHARED (state)

IN rank rank of locked window (non-negative integer)

IN assert program assertion (integer)

IN win window object (handle)
```

## C binding

```
int MPI_Win_lock(int lock_type, int rank, int assert, MPI_Win win)
```

## Fortran 2008 binding

```
MPI_Win_lock(lock_type, rank, assert, win, ierror)
```

```
INTEGER, INTENT(IN) :: lock_type, rank, assert
TYPE(MPI_Win), INTENT(IN) :: win
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

```
MPI_WIN_LOCK(LOCK_TYPE, RANK, ASSERT, WIN, IERROR)
INTEGER LOCK_TYPE, RANK, ASSERT, WIN, IERROR
```

Starts an RMA access epoch. The window at the process with rank rank can be accessed by RMA operations on win during that epoch. Multiple RMA access epochs (with calls to MPI\_WIN\_LOCK) can occur simultaneously; however, each access epoch must target a different process.

## MPI\_WIN\_LOCK\_ALL(assert, win)

```
IN assert program assertion (integer)
IN win window object (handle)
```

## C binding

```
int MPI_Win_lock_all(int assert, MPI_Win win)
```

### Fortran 2008 binding

```
MPI_Win_lock_all(assert, win, ierror)
    INTEGER, INTENT(IN) :: assert
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

```
MPI_WIN_LOCK_ALL(ASSERT, WIN, IERROR)
INTEGER ASSERT, WIN, IERROR
```

Starts an RMA access epoch to all processes in win, with a lock type of MPI\_LOCK\_SHARED. During the epoch, the calling process can access the window memory on all processes in win by using RMA operations. A window locked with MPI\_WIN\_LOCK\_ALL must be unlocked with MPI\_WIN\_UNLOCK\_ALL. This routine is not collective—the ALL refers to a lock on all members of the group of the window.

Advice to users. There may be additional overheads associated with using MPI\_WIN\_LOCK and MPI\_WIN\_LOCK\_ALL concurrently on the same window. These overheads could be avoided by specifying the assertion MPI\_MODE\_NOCHECK when possible (see Section 12.5.5). (End of advice to users.)

### MPI\_WIN\_UNLOCK(rank, win)

```
IN rank rank of window (non-negative integer)
IN win window object (handle)
```

#### C binding

2

4

5

7

12

13

14 15 16

17

18 19

20 21

22

23

24

25

26 27

28

29 30

31

32

33 34

35

36

37

38

39

40

41

42

43

44

45 46

47

```
int MPI_Win_unlock(int rank, MPI_Win win)
    Fortran 2008 binding
3
     MPI_Win_unlock(rank, win, ierror)
         INTEGER, INTENT(IN) :: rank
         TYPE(MPI_Win), INTENT(IN) :: win
6
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
9
     MPI_WIN_UNLOCK(RANK, WIN, IERROR)
10
         INTEGER RANK, WIN, IERROR
11
```

Completes an RMA access epoch started by a call to MPI\_WIN\_LOCK on window win. RMA operations issued during this period will have completed both at the origin and at the target when the call returns.

```
MPI_WIN_UNLOCK_ALL(win)
                                    window object (handle)
 IN
          win
C binding
int MPI_Win_unlock_all(MPI_Win win)
Fortran 2008 binding
MPI_Win_unlock_all(win, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

## Fortran binding

```
MPI_WIN_UNLOCK_ALL(WIN, IERROR)
    INTEGER WIN, IERROR
```

Completes a shared RMA access epoch started by a call to MPI\_WIN\_LOCK\_ALL on window win. RMA operations issued during this epoch will have completed both at the origin and at the target when the call returns.

Locks are used to protect accesses to the locked target window effected by RMA calls issued between the lock and unlock calls, and to protect load/store accesses to a locked local or shared memory window executed between the lock and unlock calls. Accesses that are protected by an exclusive lock will not be concurrent at the window site with other accesses to the same window that are lock protected. Accesses that are protected by a shared lock will not be concurrent at the window site with accesses protected by an exclusive lock to the same window.

It is erroneous to have a window locked and exposed (in an exposure epoch) concurrently. For example, a process may not call MPI\_WIN\_LOCK to lock a target window if the target process has called MPI\_WIN\_POST and has not yet called MPI\_WIN\_WAIT; it is erroneous to call MPI\_WIN\_POST while the local window is locked.

Rationale. An alternative is to require MPI to enforce mutual exclusion between exposure epochs and locking periods. But this would entail additional overheads when locks or active target synchronization do not interact in support of those rare

interactions between the two mechanisms. The programming style that we encourage here is that a set of windows is used with only one synchronization mechanism at a time, with shifts from one mechanism to another being rare and involving global synchronization. (*End of rationale*.)

Advice to users. Users need to use explicit synchronization code in order to enforce mutual exclusion between locking periods and exposure epochs on a window. (End of advice to users.)

Implementors may restrict the use of RMA communication that is synchronized by lock calls to windows in memory allocated by MPI\_ALLOC\_MEM (Section 9.2), MPI\_WIN\_ALLOCATE (Section 12.2.2), MPI\_WIN\_ALLOCATE\_SHARED (Section 12.2.3), or attached with MPI\_WIN\_ATTACH (Section 12.2.4). Locks can be used portably only in such memory.

Rationale. The implementation of passive target communication when memory is not shared may require an asynchronous software agent. Such an agent can be implemented more easily, and can achieve better performance, if restricted to specially allocated memory. It can be avoided altogether if shared memory is used. It seems natural to impose restrictions that allows one to use shared memory for third party communication in shared memory machines.

```
(End of rationale.)
```

Consider the sequence of calls in the example below.

## Example 12.5 Use of MPI\_WIN\_LOCK and MPI\_WIN\_UNLOCK.

```
MPI_Win_lock(MPI_LOCK_EXCLUSIVE, rank, assert, win);
MPI_Put(..., rank, ..., win);
MPI_Win_unlock(rank, win);
```

The call to MPI\_WIN\_UNLOCK will not return until the put transfer has completed at the origin and at the target. This still leaves much freedom to implementors. The call to MPI\_WIN\_LOCK may block until an exclusive lock on the window is acquired; or, the first two calls may not block, while MPI\_WIN\_UNLOCK blocks until a lock is acquired—the update of the target window is then postponed until the call to MPI\_WIN\_UNLOCK occurs. However, if the call to MPI\_WIN\_LOCK is used to lock a local window, then the call must block until the lock is acquired, since the lock may protect local load/store accesses to the window issued after the lock call returns.

## 12.5.4 Flush and Sync

All flush and sync functions can be called only within passive target epochs.

#### MPI\_WIN\_FLUSH(rank, win)

```
IN rank rank of target window (non-negative integer)IN win window object (handle)
```

#### C binding

3

6

9

11

```
int MPI_Win_flush(int rank, MPI_Win win)
     Fortran 2008 binding
     MPI_Win_flush(rank, win, ierror)
          INTEGER, INTENT(IN) :: rank
          TYPE(MPI_Win), INTENT(IN) :: win
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
     MPI_WIN_FLUSH(RANK, WIN, IERROR)
10
          INTEGER RANK, WIN, IERROR
         MPI_WIN_FLUSH completes all outstanding RMA operations initiated by the calling
12
     process to the target rank on the specified window. The operations are completed both at
13
     the origin and at the target.
14
15
16
     MPI_WIN_FLUSH_ALL(win)
17
                                            window object (handle)
       IN
                win
18
19
     C binding
20
21
     int MPI_Win_flush_all(MPI_Win win)
22
     Fortran 2008 binding
23
     MPI_Win_flush_all(win, ierror)
24
          TYPE(MPI_Win), INTENT(IN) :: win
25
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
27
     Fortran binding
     MPI_WIN_FLUSH_ALL(WIN, IERROR)
28
          INTEGER WIN, IERROR
29
30
          All RMA operations issued by the calling process to any target on the specified window
31
     prior to this call and in the specified window will have completed both at the origin and at
32
     the target when this call returns.
34
35
     MPI_WIN_FLUSH_LOCAL(rank, win)
36
       IN
                                            rank of target window (non-negative integer)
                 rank
37
       IN
                 win
                                            window object (handle)
38
39
     C binding
41
     int MPI_Win_flush_local(int rank, MPI_Win win)
42
     Fortran 2008 binding
43
     MPI_Win_flush_local(rank, win, ierror)
44
          INTEGER, INTENT(IN) :: rank
45
          TYPE(MPI_Win), INTENT(IN) :: win
46
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
47
```

```
Fortran binding
MPI_WIN_FLUSH_LOCAL(RANK, WIN, IERROR)
INTEGER RANK, WIN, IERROR
```

Locally completes at the origin all outstanding RMA operations initiated by the calling process to the target process specified by rank on the specified window. For example, after this routine completes, the user may reuse any buffers provided to put, get, or accumulate operations.

```
MPI_WIN_FLUSH_LOCAL_ALL(win)

IN win window object (handle)

C binding
int MPI_Win_flush_local_all(MPI_Win win)

Fortran 2008 binding

MPI_Win_flush_local_all(win, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding

MPI_WIN_FLUSH_LOCAL_ALL(WIN, IERROR)
    INTEGER WIN, IERROR
```

All RMA operations issued to any target prior to this call in this window will have completed at the origin when MPI\_WIN\_FLUSH\_LOCAL\_ALL returns.

```
MPI_WIN_SYNC(win)

IN win window object (handle)

C binding
int MPI_Win_sync(MPI_Win win)
```

## Fortran 2008 binding

```
MPI_Win_sync(win, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_WIN_SYNC(WIN, IERROR)
INTEGER WIN, IERROR
```

The call MPI\_WIN\_SYNC synchronizes the private and public window copies of win. For the purposes of synchronizing the private and public window, MPI\_WIN\_SYNC has the effect of ending and reopening an access and exposure epoch on the window (note that it does not actually end an epoch or complete any pending MPI RMA operations).

## 12.5.5 Assertions

The assert argument in the calls MPI\_WIN\_POST, MPI\_WIN\_START, MPI\_WIN\_FENCE, MPI\_WIN\_LOCK, and MPI\_WIN\_LOCK\_ALL is used to provide assertions on the context of the call that may be used to optimize performance. The assert argument does not change program semantics if it provides correct information on the program—it is erroneous to provide incorrect information. Users may always provide assert = 0 to indicate a general case where no guarantees are made.

Advice to users. Many implementations may not take advantage of the information in assert; some of the information is relevant only for noncoherent shared memory machines. Users should consult their implementation's manual to find which information is useful on each system. On the other hand, applications that provide correct assertions whenever applicable are portable and will take advantage of assertion specific optimizations whenever available. (End of advice to users.)

Advice to implementors. Implementations can always ignore the assert argument. Implementors should document which assert values are significant on their implementation. (End of advice to implementors.)

assert is the bit vector OR of zero or more of the following integer constants: MPI\_MODE\_NOCHECK, MPI\_MODE\_NOSTORE, MPI\_MODE\_NOPUT, MPI\_MODE\_NOPRECEDE, and MPI\_MODE\_NOSUCCEED. The significant options are listed below for each call.

Advice to users. C/C++ users can use bit vector OR (|) to combine these constants; Fortran 90 users can use the bit vector IOR intrinsic. Alternatively, Fortran users can portably use integer addition to OR the constants (each constant should appear at most once in the addition!). (End of advice to users.)

### MPI\_WIN\_START:

MPI\_MODE\_NOCHECK—the matching calls to MPI\_WIN\_POST have already completed on all target processes when the call to MPI\_WIN\_START is made. The nocheck option can be specified in a start call if and only if it is specified in each matching post call. This is similar to the optimization of "ready-send" that may save a handshake when the handshake is implicit in the code. However, ready-send is matched by a regular receive, whereas both start and post must specify the nocheck option.

## MPI\_WIN\_POST:

- MPI\_MODE\_NOCHECK—the matching calls to MPI\_WIN\_START have not yet occurred on any origin processes when the call to MPI\_WIN\_POST is made. The nocheck option can be specified by a post call if and only if it is specified by each matching start call.
- MPI\_MODE\_NOSTORE—the local window was not updated by stores (or local get or receive calls) since last synchronization. This may avoid the need for cache synchronization at the post call.

MPI\_MODE\_NOPUT—the local window will not be updated by put or accumulate calls after the post call, until the ensuing (wait) synchronization. This may avoid the need for cache synchronization at the wait call.

### MPI\_WIN\_FENCE:

- MPI\_MODE\_NOSTORE—the local window was not updated by stores (or local get or receive calls) since last synchronization.
- MPI\_MODE\_NOPUT—the local window will not be updated by put or accumulate calls after the fence call, until the ensuing (fence) synchronization.
- MPI\_MODE\_NOPRECEDE—the fence does not complete any sequence of locally issued RMA calls. If this assertion is given by any process in the window group, then it must be given by all processes in the group.
- MPI\_MODE\_NOSUCCEED—the fence does not start any sequence of locally issued RMA calls. If the assertion is given by any process in the window group, then it must be given by all processes in the group.

### MPI\_WIN\_LOCK, MPI\_WIN\_LOCK\_ALL:

MPI\_MODE\_NOCHECK—no other process holds, or will attempt to acquire, a conflicting lock, while the caller holds the window lock. This is useful when mutual exclusion is achieved by other means, but the coherence operations that may be attached to the lock and unlock calls are still required.

Advice to users. Note that the nostore and noprecede flags provide information on what happened before the call; the noput and nosucceed flags provide information on what will happen after the call. (End of advice to users.)

#### 12.5.6 Miscellaneous Clarifications

Once an RMA routine completes, it is safe to free any opaque objects passed as arguments to that routine. For example, the datatype argument of a MPI\_PUT call can be freed as soon as the call returns, even though the communication may not be complete.

As in message-passing, datatypes must be committed before they can be used in RMA communication.

# 12.6 Error Handling

#### 12.6.1 Error Handlers

Errors occurring during calls to routines that create MPI windows (e.g., MPI\_WIN\_CREATE (...,comm,...)) cause the error handler currently associated with comm to be invoked. All other RMA calls have an input win argument. When an error occurs during such a call, the error handler currently associated with win is invoked.

The error handler MPI\_ERRORS\_ARE\_FATAL is associated with win during its creation. Users may change this default by explicitly associating a new error handler with win (see Section 9.3).

12.6.2

Error Classes

## 

The error classes for one-sided communication are defined in Table 12.2. RMA routines may (and almost certainly will) use other MPI error classes, such as MPI\_ERR\_OP or MPI\_ERR\_RANK.

MPI_ERR_WIN	invalid win argument
MPI_ERR_BASE	invalid base argument
MPI_ERR_SIZE	invalid size argument
MPI_ERR_DISP	invalid disp argument
MPI_ERR_LOCKTYPE	invalid locktype argument
MPI_ERR_ASSERT	invalid assert argument
MPI_ERR_RMA_CONFLICT	conflicting accesses to window
MPI_ERR_RMA_SYNC	invalid synchronization of RMA calls
MPI_ERR_RMA_RANGE	target memory is not part of the window (in the case
	of a window created with
	MPI_WIN_CREATE_DYNAMIC, target memory is not
	attached)
MPI_ERR_RMA_ATTACH	memory cannot be attached (e.g., because of resource
	exhaustion)
MPI_ERR_RMA_SHARED	memory cannot be shared (e.g., some process in the
	group of the specified communicator cannot expose
	shared memory)
MPI_ERR_RMA_FLAVOR	passed window has the wrong flavor for the called

Table 12.2: Error classes in one-sided communication routines

function

## 

## 12.7 Semantics and Correctness

The following rules specify the latest time at which an operation must complete at the origin or the target. The update performed by a get call in the origin process memory is visible when the get operation is complete at the origin (or earlier); the update performed by a put or accumulate call in the public copy of the target window is visible when the put or accumulate has completed at the target (or earlier). The rules also specify the latest time at which an update of one window copy becomes visible in another overlapping copy.

- 1. An RMA operation is completed at the origin by the ensuing call to MPI\_WIN\_COMPLETE, MPI\_WIN\_FENCE, MPI\_WIN\_FLUSH, MPI\_WIN\_FLUSH\_ALL, MPI\_WIN\_FLUSH\_LOCAL, MPI\_WIN\_FLUSH\_LOCAL\_ALL, MPI\_WIN\_UNLOCK, or MPI\_WIN\_UNLOCK\_ALL that synchronizes this access at the origin.
- 2. If an RMA operation is completed at the origin by a call to MPI\_WIN\_FENCE then the operation is completed at the target by the matching call to MPI\_WIN\_FENCE by the target process.

- 3. If an RMA operation is completed at the origin by a call to MPI\_WIN\_COMPLETE then the operation is completed at the target by the matching call to MPI\_WIN\_WAIT by the target process.
- 4. If an RMA operation is completed at the origin by a call to MPI\_WIN\_UNLOCK, MPI\_WIN\_UNLOCK\_ALL, MPI\_WIN\_FLUSH(rank=target), or MPI\_WIN\_FLUSH\_ALL, then the operation is completed at the target by that same call.
- 5. An update of a location in a private window copy in process memory becomes visible in the public window copy at latest when an ensuing call to MPI\_WIN\_POST, MPI\_WIN\_FENCE, MPI\_WIN\_UNLOCK, MPI\_WIN\_UNLOCK\_ALL, or MPI\_WIN\_SYNC is executed on that window by the window owner. In the RMA unified memory model, an update of a location in a private window in process memory becomes visible without additional RMA calls.
- 6. An update by a put or accumulate call to a public window copy becomes visible in the private copy in process memory at latest when an ensuing call to MPI\_WIN\_WAIT, MPI\_WIN\_FENCE, MPI\_WIN\_LOCK, MPI\_WIN\_LOCK\_ALL, or MPI\_WIN\_SYNC is executed on that window by the window owner. In the RMA unified memory model, an update by a put or accumulate call to a public window copy eventually becomes visible in the private copy in process memory without additional RMA calls.

The MPI\_WIN\_FENCE or MPI\_WIN\_WAIT call that completes the transfer from public copy to private copy (6) is the same call that completes the put or accumulate operation in the window copy (2, 3). If a put or accumulate access was synchronized with a lock, then the update of the public window copy is complete as soon as the updating process executed MPI\_WIN\_UNLOCK or MPI\_WIN\_UNLOCK\_ALL. In the RMA separate memory model, the update of a private copy in the process memory may be delayed until the target process executes a synchronization call on that window (6). Thus, updates to process memory can always be delayed in the RMA separate memory model until the process executes a suitable synchronization call, while they must complete in the RMA unified model without additional synchronization calls. If fence or post-start-complete-wait synchronization is used, updates to a public window copy can be delayed in both memory models until the window owner executes a synchronization call. When passive target synchronization is used, it is necessary to update the public window copy even if the window owner does not execute any related synchronization call.

The rules above also define, by implication, when an update to a public window copy becomes visible in another overlapping public window copy. Consider, for example, two overlapping windows, win1 and win2. A call to MPI\_WIN\_FENCE(0, win1) by the window owner makes visible in the process memory previous updates to window win1 by remote processes. A subsequent call to MPI\_WIN\_FENCE(0, win2) makes these updates visible in the public copy of win2.

The behavior of some MPI RMA operations may be *undefined* in certain situations. For example, the result of several origin processes performing concurrent MPI\_PUT operations to the same target location is undefined. In addition, the result of a single origin process performing multiple MPI\_PUT operations to the same target location within the same access epoch is also undefined. The result at the target may have all of the data from one of the MPI\_PUT operations (the "last" one, in some sense), bytes from some of each of the

5 6 7

8

9

10

1

11 12 13

14

15

16 17

18 19

20 21

24 25 26

27

28

22 23

29 30 31

32

33

34

35 36 37

38

39

41

42 43 44

45 46 47 operations, or something else. In MPI-2, such operations were erroneous. That meant that an MPI implementation was permitted to raise an error. Thus, user programs or tools that used MPI RMA could not portably permit such operations, even if the application code could function correctly with such an undefined result. Starting with MPI-3, these operations are not erroneous, but do not have a defined behavior.

As discussed in [7], requiring operations such as overlapping puts to Rationale. be erroneous makes it difficult to use MPI RMA to implement programming models such as Unified Parallel C (UPC) or SHMEM—that permit these operations. Further, while MPI-2 defined these operations as erroneous, the MPI Forum is unaware of any implementation that enforces this rule, as it would require significant overhead. Thus, relaxing this condition does not impact existing implementations or applications. (End of rationale.)

Advice to implementors. Overlapping accesses are undefined. However, to assist users in debugging code, implementations may wish to provide a mode in which such operations are detected and reported to the user. Note, however, that starting with MPI-3, such operations must not raise an error. (End of advice to implementors.)

A program with a well-defined outcome in the MPI\_WIN\_SEPARATE memory model must obey the following rules.

- S1. A location in a window must not be accessed with load/store operations once an update to that location has started, until the update becomes visible in the private window copy in process memory.
- S2. A location in a window must not be accessed as a target of an RMA operation once an update to that location has started, until the update becomes visible in the public window copy. There is one exception to this rule, in the case where the same variable is updated by two concurrent accumulates with the same predefined datatype, on the same window. Additional restrictions on the operation apply, see the info key accumulate\_ops in Section 12.2.1.
- S3. A put or accumulate must not access a target window once a store or a put or accumulate update to another (overlapping) target window has started on a location in the target window, until the update becomes visible in the public copy of the window. Conversely, a store to process memory to a location in a window must not start once a put or accumulate update to that target window has started, until the put or accumulate update becomes visible in process memory. In both cases, the restriction applies to operations even if they access disjoint locations in the window.

The last constraint on correct RMA accesses may seem unduly restrictive, as it forbids concurrent accesses to nonoverlapping locations in a window. The reason for this constraint is that, on some architectures, explicit coherence restoring operations may be needed at synchronization points. A different operation may be needed for locations that were updated by stores and for locations that were remotely updated by put or accumulate operations. Without this constraint, the MPI library would have to track precisely which locations in a window were updated by a put or accumulate call. The additional overhead of maintaining such information is considered prohibitive. (End of rationale.)

Note that MPI\_WIN\_SYNC may be used within a passive target epoch to synchronize the private and public window copies (that is, updates to one are made visible to the other).

In the MPI\_WIN\_UNIFIED memory model, the rules are simpler because the public and private windows are the same. However, there are restrictions to avoid concurrent access to the same memory locations by different processes. The rules that a program with a well-defined outcome must obey in this case are:

- U1. A location in a window must not be accessed with load/store operations once an update to that location has started, until the update is complete, subject to the following special case.
- U2. Accessing a location in the window that is also the target of a remote update is valid (not erroneous) but the precise result will depend on the behavior of the implementation. Updates from a remote process will appear in the memory of the target, but there are no atomicity or ordering guarantees if more than one byte is updated. Updates are stable in the sense that once data appears in memory of the target, the data remains until replaced by another update. This permits polling on a location for a change from zero to non-zero or for a particular value, but not polling and comparing the relative magnitude of values. Users are cautioned that polling on one memory location and then accessing a different memory location has defined behavior only if the other rules given here and in this chapter are followed.

Advice to users. Some compiler optimizations can result in code that maintains the sequential semantics of the program, but violates this rule by introducing temporary values into locations in memory. Most compilers only apply such transformations under very high levels of optimization and users should be aware that such aggressive optimization may produce unexpected results. (End of advice to users.)

- U3. Updating a location in the window with a store operation that is also the target of a remote read (but not update) is valid (not erroneous) but the precise result will depend on the behavior of the implementation. Store updates will appear in memory, but there are no atomicity or ordering guarantees if more than one byte is updated. Updates are stable in the sense that once data appears in memory, the data remains until replaced by another update. This permits updates to memory with store operations without requiring an RMA epoch. Users are cautioned that remote accesses to a window that is updated by the local process has defined behavior only if the other rules given here and elsewhere in this chapter are followed.
- U4. A location in a window must not be accessed as a target of an RMA operation once an update to that location has started and until the update completes at the target. There is one exception to this rule: in the case where the same location is updated by two concurrent accumulates with the same predefined datatype on the same window. Additional restrictions on the operation apply; see the info key accumulate\_ops in Section 12.2.1.
- U5. A put or accumulate must not access a target window once a store, put, or accumulate update to another (overlapping) target window has started on the same location in the target window and until the update completes at the target window. Conversely,

a store operation to a location in a window must not start once a put or accumulate update to the same location in that target window has started and until the put or accumulate update completes at the target.

Advice to users. In the unified memory model, in the case where the window is in shared memory, MPI\_WIN\_SYNC can be used to order store operations and make store updates to the window visible to other processes and threads. Use of this routine is necessary to ensure portable behavior when point-to-point, collective, or shared memory synchronization is used in place of an RMA synchronization routine. MPI\_WIN\_SYNC should be called by the writer before the non-RMA synchronization operation and by the reader after the non-RMA synchronization, as shown in Example 12.21. (End of advice to users.)

A program that violates these rules has undefined behavior.

Advice to users. A user can write correct programs by following the following rules:

- fence: During each period between fence calls, each window is either updated by put or accumulate calls, or updated by stores, but not both. Locations updated by put or accumulate calls should not be accessed during the same period (with the exception of concurrent updates to the same location by accumulate calls). Locations accessed by get calls should not be updated during the same period.
- post-start-complete-wait: A window should not be updated with store operations while posted if it is being updated by put or accumulate calls. Locations updated by put or accumulate calls should not be accessed while the window is posted (with the exception of concurrent updates to the same location by accumulate calls). Locations accessed by get calls should not be updated while the window is posted.

With the post-start synchronization, the target process can tell the origin process that its window is now ready for RMA access; with the complete-wait synchronization, the origin process can tell the target process that it has finished its RMA accesses to the window.

- **lock:** Updates to the window are protected by exclusive locks if they may conflict. Nonconflicting accesses (such as read-only accesses or accumulate accesses) are protected by shared locks, both for load/store accesses and for RMA accesses.
- changing window or synchronization mode: One can change synchronization mode, or change the window used to access a location that belongs to two overlapping windows, when the process memory and the window copy are guaranteed to have the same values. This is true after a local call to MPI\_WIN\_FENCE, if RMA accesses to the window are synchronized with fences; after a local call to MPI\_WIN\_WAIT, if the accesses are synchronized with post-start-complete-wait; after the call at the origin (local or remote) to MPI\_WIN\_UNLOCK or MPI\_WIN\_UNLOCK\_ALL if the accesses are synchronized with locks.

In addition, a process should not access the local buffer of a get operation until the operation is complete, and should not update the local buffer of a put or accumulate operation until that operation is complete.

The RMA synchronization operations define when updates are guaranteed to become visible in public and private windows. Updates may become visible earlier, but such behavior is implementation dependent. (*End of advice to users.*)

The semantics are illustrated by the following examples:

**Example 12.6** The following example demonstrates updating a memory location inside a window for the separate memory model, according to Rule 5. The MPI\_WIN\_LOCK and MPI\_WIN\_UNLOCK calls around the store to X in process B are necessary to ensure consistency between the public and private copies of the window.

```
Process B:
window location X

MPI_Win_lock(EXCLUSIVE, B)
store X /* local update to private copy of B */
MPI_Win_unlock(B)
/* now visible in public window copy */

MPI_Barrier

MPI_Barrier

MPI_Win_lock(EXCLUSIVE, B)
MPI_Get(X) /* ok, read from public window */
MPI_Win_unlock(B)
```

**Example 12.7** In the RMA unified model, although the public and private copies of the windows are synchronized, caution must be used when combining load/stores and multiprocess synchronization. Although the following example appears correct, the compiler or hardware may delay the store to X after the barrier, possibly resulting in the MPI\_GET returning an incorrect value of X.

```
Process A:

window location X

store X /* update to private & public copy of B */
MPI_Barrier

MPI_Win_lock_all

MPI_Get(X) /* ok, read from window */
MPI_Win_flush_local(B)

/* read value in X */
MPI_Win_unlock_all
```

MPI\_BARRIER provides process synchronization, but not memory synchronization. The example could potentially be made safe through the use of compiler- and hardware-specific notations to ensure the store to X occurs before process B enters the MPI\_BARRIER. The use of one-sided synchronization calls, as shown in Example 12.6, also ensures the correct result.

2

3

4

5

6

7

8 9

11

20

21

22

23

24

25

26

27

28

29

30

31

32

33 34

35

36

37

38

39 40

41

42

43 44 45

46

47

48

**Example 12.8** The following example demonstrates the reading of a memory location updated by a remote process (Rule 6) in the RMA separate memory model. Although the MPI\_WIN\_UNLOCK on process A and the MPI\_BARRIER ensure that the public copy on process B reflects the updated value of X, the call to MPI\_WIN\_LOCK by process B is necessary to synchronize the private copy with the public copy.

```
Process B:
     Process A:
                                  window location X
     MPI_Win_lock(EXCLUSIVE, B)
10
     MPI_Put(X) /* update to public window */
     MPI_Win_unlock(B)
12
13
     MPI_Barrier
                                  MPI_Barrier
14
15
                                  MPI_Win_lock(EXCLUSIVE, B)
16
                                  /* now visible in private copy of B */
17
                                  load X
18
                                  MPI_Win_unlock(B)
19
```

Note that in this example, the barrier is not critical to the semantic correctness. The use of exclusive locks guarantees a remote process will not modify the public copy after MPI\_WIN\_LOCK synchronizes the private and public copies. A polling implementation looking for changes in X on process B would be semantically correct. The barrier is required to ensure that process A performs the put operation before process B performs the load of Χ.

**Example 12.9** Similar to Example 12.7, the following example is unsafe even in the unified model, because the load of X can not be guaranteed to occur after the MPI\_BARRIER. While Process B does not need to explicitly synchronize the public and private copies through MPI\_WIN\_LOCK as the MPI\_PUT will update both the public and private copies of the window, the scheduling of the load could result in old values of X being returned. Compiler and hardware specific notations could ensure the load occurs after the data is updated, or explicit one-sided synchronization calls can be used to ensure the proper result.

```
Process A:
                            Process B:
                            window location X
MPI_Win_lock_all
MPI_Put(X) /* update to window */
MPI_Win_flush(B)
MPI_Barrier
                            MPI_Barrier
                            load X
MPI_Win_unlock_all
```

Example 12.10 The following example further clarifies Rule 5. MPI\_WIN\_LOCK and MPI\_WIN\_LOCK\_ALL do not update the public copy of a window with changes to the private copy. Therefore, there is no guarantee that process A in the following sequence will see the value of X as updated by the local store by process B before the lock.

14

15

16

19

20

21

22 23

24

25

26 27

28

29

30

33

34

35

36 37

41

42

43 44

45

46 47

```
Process B:
window location X

store X /* update to private copy of B */
MPI_Win_lock(SHARED, B)

MPI_Barrier

MPI_Win_lock(SHARED, B)

MPI_Get(X) /* X may be the X before the store */
MPI_Win_unlock(B)

MPI_Win_unlock(B)

/* update on X now visible in public window */
```

The addition of an MPI\_WIN\_SYNC before the call to MPI\_BARRIER by process B would guarantee process A would see the updated value of X, as the public copy of the window would be explicitly synchronized with the private copy.

**Example 12.11** Similar to the previous example, Rule 5 can have unexpected implications for general active target synchronization with the RMA separate memory model. It is *not* guaranteed that process B reads the value of X as per the local update by process A, because neither MPI\_WIN\_WAIT nor MPI\_WIN\_COMPLETE calls by process A ensure visibility in the public window copy.

```
Process A:
                           Process B:
window location X
window location Y
store Y
MPI_Win_post(A, B) /* Y visible in public window */
                           MPI_Win_start(A)
MPI_Win_start(A)
store X /* update to private window */
MPI_Win_complete
                            MPI_Win_complete
MPI_Win_wait
/* update on X may not yet visible in public window */
                           MPI_Barrier
MPI_Barrier
                           MPI_Win_lock(EXCLUSIVE, A)
                           MPI_Get(X) /* may return an obsolete value */
                           MPI_Get(Y)
                           MPI_Win_unlock(A)
```

To allow process B to read the value of X stored by A the local store must be replaced by a local MPI\_PUT that updates the public window copy. Note that by this replacement X may become visible in the private copy of process A only after the MPI\_WIN\_WAIT call in process A. The update to Y made before the MPI\_WIN\_POST call is visible in the public window after the MPI\_WIN\_POST call and therefore process B will read the proper value

of Y. The MPI\_GET(Y) call could be moved to the epoch started by the MPI\_WIN\_START operation, and process B would still get the value stored by process A.

**Example 12.12** The following example demonstrates the interaction of general active target synchronization with local read operations with the RMA separate memory model. Rules 5 and 6 do *not* guarantee that the private copy of X at process B has been updated before the load takes place.

```
Process A:
                                   Process B:
9
                                   window location X
10
11
     MPI_Win_lock(EXCLUSIVE, B)
12
     MPI_Put(X) /* update to public window */
13
     MPI_Win_unlock(B)
14
15
     MPI_Barrier
                                   MPI_Barrier
16
17
                                   MPI_Win_post(B)
18
                                   MPI_Win_start(B)
19
20
                                   load X /* access to private window */
21
                                         /* may return an obsolete value */
22
23
                                   MPI_Win_complete
24
                                   MPI_Win_wait
25
```

To ensure that the value put by process A is read, the local load must be replaced with a local MPI\_GET operation, or must be placed after the call to MPI\_WIN\_WAIT.

## 12.7.1 Atomicity

The outcome of concurrent accumulate operations to the same location with the same predefined datatype is as if the accumulates were done at that location in some serial order. Additional restrictions on the operation apply; see the info key accumulate\_ops in Section 12.2.1. Concurrent accumulate operations with different origin and target pairs are not ordered. Thus, there is no guarantee that the entire call to an accumulate operation is executed atomically. The effect of this lack of atomicity is limited: The previous correctness conditions imply that a location updated by a call to an accumulate operation cannot be accessed by a load or an RMA call other than accumulate until the accumulate operation has completed (at the target). Different interleavings can lead to different results only to the extent that computer arithmetics are not truly associative or commutative. The outcome of accumulate operations with overlapping types of different sizes or target displacements is undefined.

#### 12.7.2 Ordering

Accumulate calls enable element-wise atomic read and write to remote memory locations. MPI specifies ordering between accumulate operations from an origin process to the same (or overlapping) memory locations at a target process on a per-datatype granularity. The

4

5

6 7

9 10

11

12

13

14

15

16

17

18

19

20

21

22

23 24

25

26 27

28

29

30

35

36

37

38

42

43

44

45

46

47

default ordering is strict ordering, which guarantees that overlapping updates from the same origin to a remote location are committed in program order and that reads (e.g., with MPI\_GET\_ACCUMULATE) and writes (e.g., with MPI\_ACCUMULATE) are executed and committed in program order. Ordering only applies to operations originating at the same origin that access overlapping target memory regions. MPI does not provide any guarantees for accesses or updates from different origin processes to overlapping target memory regions.

The default strict ordering may incur a significant performance penalty. MPI specifies the info key "accumulate\_ordering" to allow relaxation of the ordering semantics when specified to any window creation function. The values for this key are as follows. If set to "none", then no ordering will be guaranteed for accumulate calls. This was the behavior for RMA in MPI-2 but has not been the default since MPI-3. The key can be set to a comma-separated list of required access orderings at the target. Allowed values in the comma-separated list are "rar", "war", "raw", and "waw" for read-after-read, write-after-read, read-after-write, and write-after-write ordering, respectively. These indicate whether operations of the specified type complete in the order they were issued. For example, "raw" means that any writes must complete at the target before subsequent reads. These ordering requirements apply only to operations issued by the same origin process and targeting the same target process. The default value for "accumulate\_ordering" is rar,raw,war,waw, which implies that writes complete at the target in the order in which they were issued, reads complete at the target before any writes that are issued after the reads, and writes complete at the target before any reads that are issued after the writes. Any subset of these four orderings can be specified. For example, if only read-after-read and write-after-write ordering is required, then the value of the "accumulate\_ordering" key could be set to rar, waw. The order of values is not significant.

Note that the above ordering semantics apply only to accumulate operations, not put and get. Put and get within an epoch are unordered.

# 12.7.3 Progress

One-sided communication has the same progress requirements as point-to-point communication: once a communication is enabled it is guaranteed to complete. RMA calls must have local semantics, except when required for synchronization with other RMA calls.

There is some fuzziness in the definition of the time when a RMA communication becomes enabled. This fuzziness provides to the implementor more flexibility than with point-to-point communication. Access to a target window becomes enabled once the corresponding synchronization (such as MPI\_WIN\_FENCE or MPI\_WIN\_POST) has executed. On the origin process, an RMA communication may become enabled as soon as the corresponding put, get or accumulate call has executed, or as late as when the ensuing synchronization call is issued. Once the communication is enabled both at the origin and at the target, the communication must complete.

Consider the code fragment in Example 12.4. Some of the calls may block if the target window is not posted. However, if the target window is posted, then the code fragment must complete. The data transfer may start as soon as the put call occurs, but may be delayed until the ensuing complete call occurs.

Consider the code fragment in Example 12.5. Some of the calls may block if another process holds a conflicting lock. However, if no conflicting lock is held, then the code fragment must complete.

Consider the code illustrated in Figure 12.6. Each process updates the window of the other process using a put operation, then accesses its own window. The post calls are

24

25 26

27

28

29

34

35

36

37

38

43

44

45

46

47

PROCESS 0 PROCESS 1 post(1) post(0) start(1) start(0) **put(1)** put(0)complete complete wait wait load load

Figure 12.6: Symmetric communication




Figure 12.7: Deadlock situation

nonblocking, and should complete. Once the post calls occur, RMA access to the windows is enabled, so that each process should complete the sequence of calls start-put-complete. Once these are done, the wait calls should complete at both processes. Thus, this communication should not deadlock, irrespective of the amount of data transferred.

Assume, in the last example, that the order of the post and start calls is reversed at each process. Then, the code may deadlock, as each process may block on the start call, waiting for the matching post to occur. Similarly, the program will deadlock if the order of the complete and wait calls is reversed at each process.

The following two examples illustrate the fact that the synchronization between complete and wait is not symmetric: the wait call blocks until the complete executes, but not vice versa. Consider the code illustrated in Figure 12.7. This code will deadlock: the wait of process 1 blocks until process 0 calls complete, and the receive of process 0 blocks until process 1 calls send. Consider, on the other hand, the code illustrated in Figure 12.8. This code will not deadlock. Once process 1 calls post, then the sequence start, put, complete on process 0 can proceed to completion. Process 0 will reach the send call, allowing the receive call of process 1 to complete.

Rationale. MPI implementations must guarantee that a process makes progress on all enabled communications it participates in, while blocked on an MPI call. This is true for send-receive communication and applies to RMA communication as well. Thus, in the example in Figure 12.8, the put and complete calls of process 0 should complete while process 1 is blocked on the receive call. This may require the involvement of process 1, e.g., to transfer the data put, while it is blocked on the receive call.




Figure 12.8: No deadlock

A similar issue is whether such progress must occur while a process is busy computing, or blocked in a non-MPI call. Suppose that in the last example the send-receive pair is replaced by a write-to-socket/read-from-socket pair. Then MPI does not specify whether deadlock is avoided. Suppose that the blocking receive of process 1 is replaced by a very long compute loop. Then, according to one interpretation of the MPI standard, process 0 must return from the complete call after a bounded delay, even if process 1 does not reach any MPI call in this period of time. According to another interpretation, the complete call may block until process 1 reaches the wait call, or reaches another MPI call. The qualitative behavior is the same, under both interpretations, unless a process is caught in an infinite compute loop, in which case the difference may not matter. However, the quantitative expectations are different. Different MPI implementations reflect these different interpretations. While this ambiguity is unfortunate, the MPI Forum decided not to define which interpretation of the standard is the correct one, since the issue is contentious. (*End of rationale*.)

### 12.7.4 Registers and Compiler Optimizations

Advice to users. All the material in this section is an advice to users. (End of advice to users.)

A coherence problem exists between variables kept in registers and the memory values of these variables. An RMA call may access a variable in memory (or cache), while the up-to-date value of this variable is in register. A get will not return the latest variable value, and a put may be overwritten when the register is stored back in memory. Note that these issues are unrelated to the RMA memory model; that is, these issues apply even if the memory model is MPI\_WIN\_UNIFIED.

The problem is illustrated by the following code:

Source of Process 1	Source of Process 2	Executed in Process 2
bbbb = 777	buff = 999	reg_A:=999
call MPI_WIN_FENCE	call MPI_WIN_FENCE	
call MPI_PUT(bbbb		stop appl.thread
into buff of process 2)		buff:=777 in PUT handler
		continue appl.thread
call MPI_WIN_FENCE	call MPI_WIN_FENCE	
	ccc = buff	ccc:=reg_A

In this example, variable buff is allocated in the register reg\_A and therefore ccc will have the old value of buff and not the new value 777.

This problem, which also afflicts in some cases send/receive communication, is discussed more at length in Section 19.1.16.

Programs written in C avoid this problem, because of the semantics of C. Many Fortran compilers will avoid this problem, without disabling compiler optimizations. However, in order to avoid register coherence problems in a completely portable manner, users should restrict their use of RMA windows to variables stored in modules or COMMON blocks. To prevent problems with the argument copying and register optimization done by Fortran compilers, please note the hints in Sections 19.1.10–19.1.20. Sections 19.1.17 to 19.1.17 discuss several solutions for the problem in this example.

# 12.8 Examples

**Example 12.13** The following example shows a generic loosely synchronous, iterative code, using fence synchronization. The window at each process consists of array A, which contains the origin and target buffers of the put calls.

The same code could be written with get rather than put. Note that, during the communication phase, each window is concurrently read (as origin buffer of puts) and written (as target buffer of puts). This is OK, provided that there is no overlap between the target buffer of a put and another communication buffer.

**Example 12.14** Same generic example, with more computation/communication overlap. We assume that the update phase is broken into two subphases: the first, where the "boundary," which is involved in communication, is updated, and the second, where the "core," which neither uses nor provides communicated data, is updated.

12.8. EXAMPLES 613

The get communication can be concurrent with the core update, since they do not access the same locations, and the local update of the origin buffer by the get call can be concurrent with the local update of the core by the update\_core call. In order to get similar overlap with put communication we would need to use separate windows for the core and for the boundary. This is required because we do not allow local stores to be concurrent with puts on the same, or on overlapping, windows.

3

4

5

11

12

13

14

15

16

17

18

19

20 21

22 23 24

25

26

27

28

29

30

31

33

34

35 36 37

38

42

43

44

45

46

**Example 12.15** Same code as in Example 12.13, rewritten using post-start-complete-wait.

```
while (!converged(A)) {
 update(A);
 MPI_Win_post(fromgroup, 0, win);
 MPI_Win_start(togroup, 0, win);
  for(i=0; i < toneighbors; i++)</pre>
    MPI_Put(&frombuf[i], 1, fromtype[i], toneighbor[i],
            todisp[i], 1, totype[i], win);
 MPI_Win_complete(win);
  MPI_Win_wait(win);
}
Example 12.16 Same example, with split phases, as in Example 12.14.
while (!converged(A)) {
 update_boundary(A);
  MPI_Win_post(togroup, MPI_MODE_NOPUT, win);
 MPI_Win_start(fromgroup, 0, win);
  for(i=0; i < fromneighbors; i++)</pre>
    MPI_Get(&tobuf[i], 1, totype[i], fromneighbor[i],
            fromdisp[i], 1, fromtype[i], win);
  update_core(A);
 MPI_Win_complete(win);
  MPI_Win_wait(win);
}
```

**Example 12.17** A checkerboard, or double buffer communication pattern, that allows more computation/communication overlap. Array A0 is updated using values of array A1, and vice versa. We assume that communication is symmetric: if process A gets data from process B, then process B gets data from process A. Window wini consists of array Ai.

```
if (!converged(AO,A1))
   MPI_Win_post(neighbors, (MPI_MODE_NOCHECK | MPI_MODE_NOPUT), win0);
MPI_Barrier(comm0);
/* the barrier is needed because the start call inside the
loop uses the nocheck option */
while (!converged(AO, A1)) {
```

27

28

29

30

31

32

33

34

35

36

37 38

39 40

41

42

43 44

45

46

47

```
1
       /* communication on AO and computation on A1 */
2
       update2(A1, A0); /* local update of A1 that depends on A0 (and A1) */
3
       MPI_Win_start(neighbors, MPI_MODE_NOCHECK, win0);
       for(i=0; i < fromneighbors; i++)</pre>
5
         MPI_Get(&tobuf0[i], 1, totype0[i], neighbor[i],
6
                     fromdisp0[i], 1, fromtype0[i], win0);
7
       update1(A1); /* local update of A1 that is
                        concurrent with communication that updates AO */
9
       MPI_Win_post(neighbors, (MPI_MODE_NOCHECK | MPI_MODE_NOPUT), win1);
10
       MPI_Win_complete(win0);
11
       MPI_Win_wait(win0);
12
       /* communication on A1 and computation on A0 */
13
14
       update2(A0, A1); /* local update of A0 that depends on A1 (and A0) */
15
       MPI_Win_start(neighbors, MPI_MODE_NOCHECK, win1);
16
       for(i=0; i < fromneighbors; i++)</pre>
17
         MPI_Get(&tobuf1[i], 1, totype1[i], neighbor[i],
18
                      fromdisp1[i], 1, fromtype1[i], win1);
19
       update1(A0); /* local update of A0 that depends on A0 only,
                       concurrent with communication that updates A1 */
20
21
       if (!converged(A0,A1))
22
         MPI_Win_post(neighbors, (MPI_MODE_NOCHECK | MPI_MODE_NOPUT), win0);
23
       MPI_Win_complete(win1);
24
       MPI_Win_wait(win1);
25
     }
```

A process posts the local window associated with win0 before it completes RMA accesses to the remote windows associated with win1. When the wait(win1) call returns, then all neighbors of the calling process have posted the windows associated with win0. Conversely, when the wait(win0) call returns, then all neighbors of the calling process have posted the windows associated with win1. Therefore, the nocheck option can be used with the calls to MPI\_WIN\_START.

Put calls can be used, instead of get calls, if the area of array AO (resp. A1) used by the update(A1, A0) (resp. update(A0, A1)) call is disjoint from the area modified by the RMA communication. On some systems, a put call may be more efficient than a get call, as it requires information exchange only in one direction.

In the next several examples, for conciseness, the expression

```
z = MPI_Get_accumulate(...)
```

means to perform an MPI\_GET\_ACCUMULATE with the result buffer (given by result\_addr in the description of MPI\_GET\_ACCUMULATE) on the left side of the assignment, in this case, z. This format is also used with MPI\_COMPARE\_AND\_SWAP and MPI\_COMM\_SIZE. Process B... refers to any process other than A.

**Example 12.18** The following example implements a naive, non-scalable counting semaphore. The example demonstrates the use of MPI\_WIN\_SYNC to manipulate the public copy of X, as well as MPI\_WIN\_FLUSH to complete operations without ending the access epoch opened with MPI\_WIN\_LOCK\_ALL. To avoid the rules regarding synchronization of the

12.8. EXAMPLES 615

public and private copies of windows, MPI\_ACCUMULATE and MPI\_GET\_ACCUMULATE are used to write to or read from the local public copy.

```
Process A:
                                           Process B...:
MPI_Win_lock_all
                                           MPI_Win_lock_all
window location X
X=MPI_Comm_size()
MPI_Win_sync
MPI_Barrier
                                           MPI_Barrier
MPI_Accumulate(X, MPI_SUM, -1)
                                           MPI_Accumulate(X, MPI_SUM, -1)
stack variable z
                                           stack variable z
                                           do
                                             z = MPI_Get_accumulate(X,
  z = MPI_Get_accumulate(X,
       MPI_NO_OP, 0)
                                                  MPI_NO_OP, 0)
  MPI_Win_flush(A)
                                             MPI_Win_flush(A)
while(z!=0)
                                            while(z!=0)
MPI_Win_unlock_all
                                           MPI_Win_unlock_all
```

12

13

14

15

16

18 19

20 21 22

24

26

27

28

**Example 12.19** Implementing a critical region between two processes (Peterson's algorithm). Despite their appearance in the following example, MPI\_WIN\_LOCK\_ALL and MPI\_WIN\_UNLOCK\_ALL are not collective calls, but it is frequently useful to start shared access epochs to all processes from all other processes in a window. Once the access epochs are established, accumulate communication operations and flush and sync synchronization operations can be used to read from or write to the public copy of the window.

```
Process A:
                                         Process B:
                                                                                      29
window location X
                                         window location Y
                                                                                      30
window location T
MPI_Win_lock_all
                                         MPI_Win_lock_all
                                                                                      33
X=1
                                         Y=1
                                                                                      34
MPI_Win_sync
                                         MPI_Win_sync
                                                                                      35
MPI_Barrier
                                         MPI_Barrier
                                                                                      36
MPI_Accumulate(T, MPI_REPLACE, 1)
                                         MPI_Accumulate(T, MPI_REPLACE, 0)
                                                                                      37
stack variables t,y
                                         stack variable t,x
                                                                                      38
t=1
                                         t=0
                                                                                      39
                                         x=MPI_Get_accumulate(X,
y=MPI_Get_accumulate(Y,
   MPI_NO_OP, 0)
                                            MPI_NO_OP, 0)
                                                                                      41
while (y==1 \&\& t==1) do
                                         while (x==1 \&\& t==0) do
                                                                                      42
  y=MPI_Get_accumulate(Y,
                                           x=MPI_Get_accumulate(X,
                                                                                      43
     MPI_NO_OP, 0)
                                              MPI_NO_OP, 0)
                                                                                      44
                                           t=MPI_Get_accumulate(T,
  t=MPI_Get_accumulate(T,
                                                                                      45
     MPI_NO_OP, 0)
                                              MPI_NO_OP, 0)
                                                                                      46
  MPI_Win_flush_all
                                           MPI_Win_flush(A)
done
                                         done
```

```
// critical region // critical region
MPI_Accumulate(X, MPI_REPLACE, 0) MPI_Accumulate(Y, MPI_REPLACE, 0)
MPI_Win_unlock_all MPI_Win_unlock_all
```

6

9

10

11

26 27

28

29

30

31

32

33

34

35

36

37

38

39

40

41 42

43

44

 $\frac{45}{46}$ 

47

**Example 12.20** Implementing a critical region between multiple processes with compare and swap. The call to MPI\_WIN\_SYNC is necessary on Process A after local initialization of A to guarantee the public copy has been updated with the initialization value found in the private copy. It would also be valid to call MPI\_ACCUMULATE with MPI\_REPLACE to directly initialize the public copy. A call to MPI\_WIN\_FLUSH would be necessary to assure A in the public copy of Process A had been updated before the barrier.

```
12
     Process A:
                                               Process B...:
     MPI_Win_lock_all
                                               MPI_Win_lock_all
13
14
     atomic location A
15
     A=0
16
     MPI_Win_sync
17
                                               MPI_Barrier
     MPI_Barrier
                                               stack variable r=1
18
     stack variable r=1
19
     while(r != 0) do
                                               while(r != 0) do
                                                 r = MPI_Compare_and_swap(A, 0, 1)
       r = MPI_Compare_and_swap(A, 0, 1)
20
       MPI_Win_flush(A)
                                                 MPI_Win_flush(A)
21
22
     done
                                               done
                                               // critical region
23
     // critical region
^{24}
     r = MPI_Compare_and_swap(A, 1, 0)
                                               r = MPI_Compare_and_swap(A, 1, 0)
     MPI_Win_unlock_all
                                               MPI_Win_unlock_all
25
```

Example 12.21 The following example demonstrates the proper synchronization in the unified memory model when a data transfer is implemented with load and store in the case of windows in shared memory (instead of MPI\_PUT or MPI\_GET) and the synchronization between processes is performed using point-to-point communication. The synchronization between processes must be supplemented with a memory synchronization through calls to MPI\_WIN\_SYNC, which act locally as a processor-memory barrier. In Fortran, if MPI\_ASYNC\_PROTECTS\_NONBLOCKING is .FALSE. or the variable X is not declared as ASYNCHRONOUS, reordering of the accesses to the variable X must be prevented with MPI\_F\_SYNC\_REG operations. (No equivalent function is needed in C.)

The variable X is contained within a shared memory window and X corresponds to the same memory location at both processes. The MPI\_WIN\_SYNC operation performed by process A ensures completion of the load/store operations issued by process A. The MPI\_WIN\_SYNC operation performed by process B ensures that process A's updates to X are visible to process B.

```
Process A:

MPI_WIN_LOCK_ALL(

MPI_MODE_NOCHECK,win)

DO ...

X=...
```

12.8. EXAMPLES 617

```
MPI_F_SYNC_REG(X)
  MPI_WIN_SYNC(win)
  MPI_SEND
                                    MPI_RECV
                                    MPI_WIN_SYNC(win)
                                    MPI_F_SYNC_REG(X)
                                    print X
                                    MPI_F_SYNC_REG(X)
  MPI_RECV
                                    MPI_SEND
  MPI_F_SYNC_REG(X)
END DO
                                  END DO
                                                                                   14
MPI_WIN_UNLOCK_ALL(win)
                                  MPI_WIN_UNLOCK_ALL(win)
```

11

12 13

15 16

17

18

19

Example 12.22 The following example shows how request-based operations can be used to overlap communication with computation. Each process fetches, processes, and writes the result for NSTEPS chunks of data. Instead of a single buffer, M local buffers are used to allow up to M communication operations to overlap with computation.

```
20
                                                                                     21
int
             i, j;
                                                                                     22
MPI_Win
             win;
MPI_Request put_req[M] = { MPI_REQUEST_NULL };
                                                                                     23
                                                                                     24
MPI_Request get_req;
double
             *baseptr;
                                                                                     26
double
             data[M][N];
                                                                                     27
MPI_Win_allocate(NSTEPS*N*sizeof(double), sizeof(double), MPI_INFO_NULL,
                                                                                     28
                                                                                     29
  MPI_COMM_WORLD, &baseptr, &win);
                                                                                     30
                                                                                     31
MPI_Win_lock_all(0, win);
                                                                                     33
for (i = 0; i < NSTEPS; i+
                                                                                     34
 if (i<M)
                                                                                     35
   j=i;
                                                                                     36
 else
                                                                                     37
   MPI_Waitany(M, put_req, &j, MPI_STATUS_IGNORE);
                                                                                     38
                                                                                     39
 MPI_Rget(data[i], N, MPI_DOUBLE, target, i*N, N, MPI_DOUBLE, win,
           &get_req);
                                                                                     41
 MPI_Wait(&get_req,MPI_STATUS_IGNORE);
                                                                                     42
 compute(i, data[j], ...);
 MPI_Rput(data[j], N, MPI_DOUBLE, target, i*N, N, MPI_DOUBLE, win,
                                                                                     43
                                                                                     44
           &put_req[j]);
}
                                                                                     45
                                                                                     46
MPI_Waitall(M, put_req, MPI_STATUSES_IGNORE);
MPI_Win_unlock_all(win);
```

2

3

4

5

6

7

8

**Example 12.23** The following example constructs a distributed shared linked list using dynamic windows. Initially process 0 creates the head of the list, attaches it to the window, and broadcasts the pointer to all processes. All processes then concurrently append N new elements to the list. When a process attempts to attach its element to the tail of the list it may discover that its tail pointer is stale and it must chase ahead to the new tail before the element can be attached. This example requires some modification to work in an environment where the layout of the structures is different on different processes.

```
9
10
     #define NUM_ELEMS 10
11
     #define LLIST_ELEM_NEXT_RANK ( offsetof(llist_elem_t, next) + \
12
                                      offsetof(llist_ptr_t, rank) )
13
     #define LLIST_ELEM_NEXT_DISP ( offsetof(llist_elem_t, next) 
14
                                      offsetof(llist_ptr_t,
15
                                                             disp))
16
17
     /* Linked list pointer */
     typedef struct {
18
19
       MPI_Aint disp;
20
       int
                rank;
     } llist_ptr_t;
21
22
23
     /* Linked list element */
24
     typedef struct {
25
       llist_ptr_t next;
26
       int value;
     } llist_elem_t;
27
28
     const llist_ptr_t nil = { (MPI_Aint) MPI_BOTTOM, -1 };
29
30
     /* List of locally allocated list elements. */
31
     static llist_elem_t **my_elems = NULL;
32
     static int my_elems_size = 0;
33
34
     static int my_elems_count = 0;
35
     /* Allocate a new shared linked list element */
36
     MPI_Aint alloc_elem(int value, MPI_Win win) {
37
38
       MPI_Aint disp;
       llist_elem_t *elem_ptr;
39
       /* Allocate the new element and register it with the window */
41
42
       MPI_Alloc_mem(sizeof(llist_elem_t), MPI_INFO_NULL, &elem_ptr);
       elem_ptr->value = value;
43
       elem_ptr->next = nil;
44
       MPI_Win_attach(win, elem_ptr, sizeof(llist_elem_t));
45
46
47
       /* Add the element to the list of local elements so we can free
```

it later. \*/

12.8. EXAMPLES 619

```
if (my_elems_size == my_elems_count) {
   my_elems_size += 100;
   my_elems = realloc(my_elems, my_elems_size*sizeof(void*));
 }
 my_elems[my_elems_count] = elem_ptr;
 my_elems_count++;
 MPI_Get_address(elem_ptr, &disp);
 return disp;
}
int main(int argc, char *argv[]) {
                                                                                  12
                                                                                  13
 int
                procid, nproc, i;
                                                                                  14
 MPI_Win
                llist_win;
                                                                                  15
 llist_ptr_t
                head_ptr, tail_ptr;
                                                                                  16
 MPI_Init(&argc, &argv);
                                                                                  18
                                                                                  19
 MPI_Comm_rank(MPI_COMM_WORLD, &procid);
 MPI_Comm_size(MPI_COMM_WORLD, &nproc);
                                                                                  20
                                                                                  21
 MPI_Win_create_dynamic(MPI_INFO_NULL, MPI_COMM_WORLD, &llist_win);
                                                                                  22
                                                                                  23
 /* Process 0 creates the head node */
                                                                                  24
 if (procid == 0)
   head_ptr.disp = alloc_elem(-1, llist_win);
                                                                                  27
 /* Broadcast the head pointer to everyone */
                                                                                  28
                                                                                  29
 head_ptr.rank = 0;
                                                                                  30
 MPI_Bcast(&head_ptr.disp, 1, MPI_AINT, 0, MPI_COMM_WORLD);
 tail_ptr = head_ptr;
  /* Lock the window for shared access to all targets */
                                                                                  34
 MPI_Win_lock_all(0, llist_win);
                                                                                  35
  /* All processes concurrently append NUM_ELEMS elements to the list */
                                                                                  36
                                                                                  37
 for (i = 0; i < NUM_ELEMS; i++) {</pre>
   llist_ptr_t new_elem_ptr;
   int success;
   /* Create a new list element and attach it to the window */
                                                                                  42
   new_elem_ptr.rank = procid;
   new_elem_ptr.disp = alloc_elem(procid, llist_win);
                                                                                  43
                                                                                  44
                                                                                  45
   /* Append the new node to the list. This might take multiple
                                                                                  46
       attempts if others have already appended and our tail pointer
       is stale. */
   do {
```

```
1
           llist_ptr_t next_tail_ptr = nil;
2
           MPI_Compare_and_swap((void*) &new_elem_ptr.rank, (void*) &nil.rank,
                (void*)&next_tail_ptr.rank, MPI_INT, tail_ptr.rank,
               MPI_Aint_add(tail_ptr.disp, LLIST_ELEM_NEXT_RANK),
               llist_win);
           MPI_Win_flush(tail_ptr.rank, llist_win);
           success = (next_tail_ptr.rank == nil.rank);
10
11
           if (success) {
12
             MPI_Accumulate(&new_elem_ptr.disp, 1, MPI_AINT, tail_ptr.rank,
13
                 MPI_Aint_add(tail_ptr.disp, LLIST_ELEM_NEXT_DISP), 1,
14
                 MPI_AINT, MPI_REPLACE, llist_win);
15
16
             MPI_Win_flush(tail_ptr.rank, llist_win);
             tail_ptr = new_elem_ptr;
19
           } else {
20
             /* Tail pointer is stale, fetch the displacement.
                                                                   May take
21
                multiple tries if it is being updated. */
22
             do {
23
               MPI_Get_accumulate(NULL, 0, MPI_AINT, &next_tail_ptr.disp,
24
                   1, MPI_AINT, tail_ptr.rank,
                   MPI_Aint_add(tail_ptr.disp, LLIST_ELEM_NEXT_DISP),
                   1, MPI_AINT, MPI_NO_OP, 1list_win);
27
28
               MPI_Win_flush(tail_ptr.rank, llist_win);
             } while (next_tail_ptr.disp == nil.disp);
30
             tail_ptr = next_tail_ptr;
         } while (!success);
33
       }
34
       MPI_Win_unlock_all(llist_win);
35
36
       MPI_Barrier(MPI_COMM_WORLD);
37
38
       /* Free all the elements in the list */
       for ( ; my_elems_count > 0; my_elems_count--) {
         MPI_Win_detach(llist_win,my_elems[my_elems_count-1]);
41
         MPI_Free_mem(my_elems[my_elems_count-1]);
42
43
       MPI_Win_free(&llist_win);
44
45
46
```

# Chapter 13

# **External Interfaces**

### 13.1 Introduction

This chapter contains calls used to create **generalized requests**, which allow users to create new nonblocking operations with an interface similar to what is present in MPI. These calls can be used to layer new functionality on top of MPI. Next, Section 13.3 deals with setting the information found in **status**. This functionality is needed for generalized requests.

# 13.2 Generalized Requests

The goal of generalized requests is to allow users to define new nonblocking operations. Such an outstanding nonblocking operation is represented by a (generalized) request. A fundamental property of nonblocking operations is that progress toward the completion of this operation occurs asynchronously, i.e., concurrently with normal program execution. Typically, this requires execution of code concurrently with the execution of the user code, e.g., in a separate thread or in a signal handler. Operating systems provide a variety of mechanisms in support of concurrent execution. MPI does not attempt to standardize or to replace these mechanisms: it is assumed programmers who wish to define new asynchronous operations will use the mechanisms provided by the underlying operating system. Thus, the calls in this section only provide a means for defining the effect of MPI calls such as MPI\_WAIT or MPI\_CANCEL when they apply to generalized requests, and for signaling to MPI the completion of a generalized operation.

Rationale. It is tempting to also define an MPI standard mechanism for achieving concurrent execution of user-defined nonblocking operations. However, it is difficult to define such a mechanism without consideration of the specific mechanisms used in the operating system. The Forum feels that concurrency mechanisms are a proper part of the underlying operating system and should not be standardized by MPI; the MPI standard should only deal with the interaction of such mechanisms with MPI. (End of rationale.)

For a regular request, the operation associated with the request is performed by the MPI implementation, and the operation completes without intervention by the application. For a generalized request, the operation associated with the request is performed by the application; therefore, the application must notify MPI through a call to MPI\_GREQUEST\_COMPLETE when the operation completes. MPI maintains the "completion" status of generalized requests. Any other request state has to be maintained by the user.

A new generalized request is started with

# MPI\_GREQUEST\_START(query\_fn, free\_fn, cancel\_fn, extra\_state, request)

IN	query_fn	callback function invoked when request status is queried (function)
IN	free_fn	callback function invoked when request is freed
		(function)
IN	cancel_fn	callback function invoked when request is cancelled
		(function)
IN	extra_state	extra state
OUT	request	generalized request (handle)

# C binding

### Fortran 2008 binding

### Fortran binding

INTEGER REQUEST, IERROR

```
MPI_GREQUEST_START(QUERY_FN, FREE_FN, CANCEL_FN, EXTRA_STATE, REQUEST, IERROR)

EXTERNAL QUERY_FN, FREE_FN, CANCEL_FN
INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
```

 Advice to users. Note that a generalized request is of the same type as regular requests, in C and Fortran. (End of advice to users.)

The call starts a generalized request and returns a handle to it in request.

The syntax and meaning of the callback functions are listed below. All callback functions are passed the extra\_state argument that was associated with the request by the starting call MPI\_GREQUEST\_START; extra\_state can be used to maintain user-defined state for the request.

 $\frac{44}{45}$ 

The query\_fn function computes the status that should be returned for the generalized request. The status also includes information about successful/unsuccessful cancellation of the request (result to be returned by MPI\_TEST\_CANCELLED).

The query\_fn callback is invoked by the MPI\_{WAIT|TEST}\_{ANY|SOME|ALL} call that completed the generalized request associated with this callback. The callback function is also invoked by calls to MPI\_REQUEST\_GET\_STATUS, if the request is complete when the call occurs. In both cases, the callback is passed a reference to the corresponding status variable passed by the user to the MPI call; the status set by the callback function is returned by the MPI call. If the user provided MPI\_STATUS\_IGNORE or

MPI\_STATUSES\_IGNORE to the MPI function that causes query\_fn to be called, then MPI will pass a valid status object to query\_fn, and this status will be ignored upon return of the callback function. Note that query\_fn is invoked only after MPI\_GREQUEST\_COMPLETE is called on the request; it may be invoked several times for the same generalized request, e.g., if the user calls MPI\_REQUEST\_GET\_STATUS several times for this request. Note also that a call to MPI\_{WAIT|TEST}{SOME|ALL} may cause multiple invocations of query\_fn callback functions, one for each generalized request that is completed by the MPI call. The order of these invocations is not specified by MPI.

```
In C, the free function is
typedef int MPI_Grequest_free_function(void *extra_state);
in Fortran with the mpi_f08 module
ABSTRACT INTERFACE
   SUBROUTINE MPI_Grequest_free_function(extra_state, ierror)
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state
    INTEGER :: ierror
in Fortran with the mpi module and mpif.h
SUBROUTINE GREQUEST_FREE_FUNCTION(EXTRA_STATE, IERROR)
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
   INTEGER IERROR
```

The free\_fn function is invoked to clean up user-allocated resources when the generalized request is freed.

The free\_fn callback is invoked by the MPI\_{WAIT|TEST}\_{ANY|SOME|ALL} call that completed the generalized request associated with this callback. free\_fn is invoked after the call to query\_fn for the same request. However, if the MPI call completed multiple generalized requests, the order in which free\_fn callback functions are invoked is not specified by MPI.

The free\_fn callback is also invoked for generalized requests that are freed by a call to MPI\_REQUEST\_FREE (no call to MPI\_{WAIT|TEST}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|SOME|ALL}\_{ANY|S

Advice to users. Calling MPI\_REQUEST\_FREE(request) will cause the request handle to be set to MPI\_REQUEST\_NULL. This handle to the generalized request is no longer valid. However, user copies of this handle are valid until after free\_fn completes since MPI does not deallocate the object until then. Since free\_fn is not called until after MPI\_GREQUEST\_COMPLETE, the user copy of the handle can be used to make this call. Users should note that MPI will deallocate the object after free\_fn executes. At this point, user copies of the request handle no longer point to a valid request. MPI will not set user copies to MPI\_REQUEST\_NULL in this case, so it is up to the user to avoid accessing this stale handle. This is a special case in which MPI defers deallocating the object until a later time that is known by the user. (End of advice to users.)

```
26
27
```

INTEGER IERROR

```
In C, the cancel function is
typedef int MPI_Grequest_cancel_function(void *extra_state, int complete);
in Fortran with the mpi_f08 module
ABSTRACT INTERFACE
SUBROUTINE MPI_Grequest_cancel_function(extra_state, complete, ierror)
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state
    LOGICAL :: complete
    INTEGER :: ierror
in Fortran with the mpi module and mpif.h
SUBROUTINE GREQUEST_CANCEL_FUNCTION(EXTRA_STATE, COMPLETE, IERROR)
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
    LOGICAL COMPLETE
```

The cancel\_fn function is invoked to start the cancelation of a generalized request. It is called by MPI\_CANCEL(request). MPI passes complete = true to the callback function if MPI\_GREQUEST\_COMPLETE was already called on the request, and complete = false otherwise.

All callback functions return an error code. The code is passed back and dealt with as appropriate for the error code by the MPI function that invoked the callback function. For example, if error codes are returned then the error code returned by the callback function will be returned by the MPI function that invoked the callback function. In the case of an MPI\_{WAIT|TEST}{ANY} call that invokes both query\_fn and free\_fn, the MPI call will

 $\frac{44}{45}$ 

return the error code returned by the last callback, namely free\_fn. If one or more of the requests in a call to MPI\_{WAIT|TEST}{SOME|ALL} failed, then the MPI call will return MPI\_ERR\_IN\_STATUS. In such a case, if the MPI call was passed an array of statuses, then MPI will return in each of the statuses that correspond to a completed generalized request the error code returned by the corresponding invocation of its free\_fn callback function. However, if the MPI function was passed MPI\_STATUSES\_IGNORE, then the individual error codes returned by each callback functions will be lost.

Advice to users. query\_fn must not set the error field of status since query\_fn may be called by MPI\_WAIT or MPI\_TEST, in which case the error field of status should not change. The MPI library knows the "context" in which query\_fn is invoked and can decide correctly when to put the returned error code in the error field of status. (End of advice to users.)

The call informs MPI that the operations represented by the generalized request request are complete (see definitions in Section 2.4). A call to MPI\_WAIT(request, status) will return and a call to MPI\_TEST(request, flag, status) will return flag = true only after a call to MPI\_GREQUEST\_COMPLETE has declared that these operations are complete.

MPI imposes no restrictions on the code executed by the callback functions. However, new nonblocking operations should be defined so that the general semantic rules about MPI calls such as MPI\_TEST, MPI\_REQUEST\_FREE, or MPI\_CANCEL still hold. For example, these calls are supposed to be local and nonblocking. Therefore, the callback functions query\_fn, free\_fn, or cancel\_fn should invoke blocking MPI communication calls only if the context is such that these calls are guaranteed to return in finite time. Once MPI\_CANCEL is invoked, the cancelled operation should complete in finite time, irrespective of the state of other processes (the operation has acquired "local" semantics). It should either succeed, or fail without side-effects. The user should guarantee these same properties for newly defined operations.

Advice to implementors. A call to MPI\_GREQUEST\_COMPLETE may unblock a blocked user process/thread. The MPI library should ensure that the blocked user computation will resume. (*End of advice to implementors.*)

2

```
13.2.1 Examples
```

```
3
     Example 13.1 This example shows the code for a user-defined reduce operation on an
4
     int using a binary tree: each non-root node receives two messages, sums them, and sends
5
     them up. We assume that no status is returned and that the operation cannot be cancelled.
6
7
     typedef struct {
8
        MPI_Comm comm;
9
        int tag;
10
        int root;
11
        int valin;
12
        int *valout;
13
        MPI_Request request;
14
        } ARGS;
15
16
17
     int myreduce(MPI_Comm comm, int tag, int root,
18
                   int valin, int *valout, MPI_Request *request)
19
     {
20
        ARGS *args;
21
        pthread_t thread;
22
23
        /* start request */
24
        MPI_Grequest_start(query_fn, free_fn, cancel_fn, NULL, request);
26
        args = (ARGS*)malloc(sizeof(ARGS));
27
        args->comm = comm;
28
        args->tag = tag;
29
        args->root = root;
30
        args->valin = valin;
31
        args->valout = valout;
        args->request = *request;
33
34
        /* spawn thread to handle request */
35
        /* The availability of the pthread_create call is system dependent */
36
        pthread_create(&thread, NULL, reduce_thread, args);
37
38
        return MPI_SUCCESS;
39
     }
40
41
     /* thread code */
42
     void* reduce_thread(void *ptr)
43
44
        int lchild, rchild, parent, lval, rval, val;
45
        MPI_Request req[2];
46
        ARGS *args;
47
        args = (ARGS*)ptr;
```

```
/* compute left and right child and parent in tree; set
      to MPI_PROC_NULL if does not exist */
   /* code not shown */
  MPI_Irecv(&lval, 1, MPI_INT, lchild, args->tag, args->comm, &req[0]);
  MPI_Irecv(&rval, 1, MPI_INT, rchild, args->tag, args->comm, &req[1]);
  MPI_Waitall(2, req, MPI_STATUSES_IGNORE);
  val = lval + args->valin + rval;
  MPI_Send(&val, 1, MPI_INT, parent, args->tag, args->comm);
   if (parent == MPI_PROC_NULL) *(args->valout) = val;
                                                                                  12
  MPI_Grequest_complete((args->request));
                                                                                  13
                                                                                  14
  free(ptr);
                                                                                  15
  return(NULL);
                                                                                  16
}
                                                                                  18
int query_fn(void *extra_state, MPI_Status *status)
                                                                                  19
   /* always send just one int */
                                                                                  20
                                                                                  21
  MPI_Status_set_elements(status, MPI_INT, 1);
   /* can never cancel so always true */
                                                                                  22
                                                                                  23
  MPI_Status_set_cancelled(status, 0);
                                                                                  24
  /* choose not to return a value for this */
   status->MPI_SOURCE = MPI_UNDEFINED;
                                                                                  26
   /* tag has no meaning for this generalized request */
   status->MPI_TAG = MPI_UNDEFINED;
                                                                                  27
  /* this generalized request never fails */
                                                                                  28
                                                                                  29
  return MPI_SUCCESS;
}
                                                                                  30
                                                                                  33
int free_fn(void *extra_state)
                                                                                  34
   /* this generalized request does not need to do any freeing */
                                                                                  35
   /* as a result it never fails here */
                                                                                  36
                                                                                  37
  return MPI_SUCCESS;
}
int cancel_fn(void *extra_state, int complete)
                                                                                  42
   /* This generalized request does not support cancelling.
                                                                                  43
      Abort if not already done. If done then treat as if cancel failed.*/
                                                                                  45
   if (!complete) {
                                                                                  46
     fprintf(stderr,
             "Cannot cancel generalized request - aborting program\n");
     MPI_Abort(MPI_COMM_WORLD, 99);
```

```
}
return MPI_SUCCESS;
}
```

# 13.3 Associating Information with Status

MPI supports several different types of requests besides those for point-to-point operations. These range from MPI calls for I/O to generalized requests. It is desirable to allow these calls to use the same request mechanism, which allows one to wait or test on different types of requests. However, MPI\_{TEST|WAIT}{ANY|SOME|ALL} returns a status with information about the request. With the generalization of requests, one needs to define what information will be returned in the status object.

Each MPI call fills in the appropriate fields in the status object. Any unused fields will have undefined values. A call to MPI\_{TEST|WAIT}{ANY|SOME|ALL} can modify any of the fields in the status object. Specifically, it can modify fields that are undefined. The fields with meaningful values for a given request are defined in the sections with the new request.

Generalized requests raise additional considerations. Here, the user provides the functions to deal with the request. Unlike other MPI calls, the user needs to provide the information to be returned in the status. The status argument is provided directly to the callback function where the status needs to be set. Users can directly set the values in 3 of the 5 status values. The count and cancel fields are opaque. To overcome this, these calls are provided:

## MPI\_STATUS\_SET\_ELEMENTS(status, datatype, count)

```
INOUT status status with which to associate count (Status)

IN datatype associated with count (handle)

IN count number of elements to associate with status (integer)
```

### C binding

### Fortran 2008 binding

```
MPI_Status_set_elements(status, datatype, count, ierror)
    TYPE(MPI_Status), INTENT(INOUT) :: status
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: count
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

```
MPI_STATUS_SET_ELEMENTS(STATUS, DATATYPE, COUNT, IERROR)
INTEGER STATUS(MPI_STATUS_SIZE), DATATYPE, COUNT, IERROR
```

12

13

14

15

16

18

19

20

24

39

41 42

43

44

45 46

47

### MPI\_STATUS\_SET\_ELEMENTS\_X(status, datatype, count) **INOUT** status with which to associate count (Status) status IN datatype datatype associated with count (handle) IN count number of elements to associate with status (integer) C binding int MPI\_Status\_set\_elements\_x(MPI\_Status \*status, MPI\_Datatype datatype, MPI\_Count count) Fortran 2008 binding MPI\_Status\_set\_elements\_x(status, datatype, count, ierror) TYPE(MPI\_Status), INTENT(INOUT) :: status TYPE(MPI\_Datatype), INTENT(IN) :: datatype INTEGER(KIND=MPI\_COUNT\_KIND), INTENT(IN) :: count INTEGER, OPTIONAL, INTENT(OUT) :: ierror Fortran binding MPI\_STATUS\_SET\_ELEMENTS\_X(STATUS, DATATYPE, COUNT, IERROR) INTEGER STATUS(MPI\_STATUS\_SIZE), DATATYPE, IERROR INTEGER(KIND=MPI\_COUNT\_KIND) COUNT 21 These functions modify the opaque part of status so that a call to 22 MPI\_GET\_ELEMENTS or MPI\_GET\_ELEMENTS\_X will return count. MPI\_GET\_COUNT 23 will return a compatible value. The number of elements is set instead of the count because the former 26 can deal with a nonintegral number of datatypes. (End of rationale.) 27 28 A subsequent call to MPI\_GET\_COUNT(status, datatype, count), 29 MPI\_GET\_ELEMENTS(status, datatype, count), or 30 MPI\_GET\_ELEMENTS\_X(status, datatype, count) must use a datatype argument that has 31 the same type signature as the datatype argument that was used in the call to MPI\_STATUS\_SET\_ELEMENTS or MPI\_STATUS\_SET\_ELEMENTS\_X. 33 34 Rationale. The requirement of matching type signatures for these calls is similar 35 to the restriction that holds when count is set by a receive operation: in that case, 36 the calls to MPI\_GET\_COUNT, MPI\_GET\_ELEMENTS, and MPI\_GET\_ELEMENTS\_X must use a datatype with the same signature as the datatype used in the receive call. 38 (End of rationale.) MPI\_STATUS\_SET\_CANCELLED(status, flag) **INOUT** status status with which to associate cancel flag (Status) IN flag if true, indicates request was cancelled (logical)

int MPI\_Status\_set\_cancelled(MPI\_Status \*status, int flag)


C binding

#### Fortran 2008 binding MPI\_Status\_set\_cancelled(status, flag, ierror) TYPE(MPI\_Status), INTENT(INOUT) :: status LOGICAL, INTENT(IN) :: flag INTEGER, OPTIONAL, INTENT(OUT) :: ierror Fortran binding MPI\_STATUS\_SET\_CANCELLED(STATUS, FLAG, IERROR) INTEGER STATUS(MPI\_STATUS\_SIZE), IERROR LOGICAL FLAG

If flag is set to true then a subsequent call to MPI\_TEST\_CANCELLED(status, flag) will also return flag = true, otherwise it will return false.

Advice to users. Users are advised not to reuse the status fields for values other than those for which they were intended. Doing so may lead to unexpected results when using the status object. For example, calling MPI\_GET\_ELEMENTS may cause an error if the value is out of range or it may be impossible to detect such an error. The extra\_state argument provided with a generalized request can be used to return information that does not logically belong in status. Furthermore, modifying the values in a status set internally by MPI, e.g., MPI\_RECV, may lead to unpredictable results and is strongly discouraged. (End of advice to users.)





# Chapter 14

# I/O

# 14.1 Introduction

POSIX provides a model of a widely portable file system, but the portability and optimization needed for parallel I/O cannot be achieved with the POSIX interface.

The significant optimizations required for efficiency (e.g., grouping [54], collective buffering [8, 16, 55, 59, 66], and disk-directed I/O [48]) can only be implemented if the parallel I/O system provides a high-level interface supporting partitioning of file data among processes and a collective interface supporting complete transfers of global data structures between process memories and files. In addition, further efficiencies can be gained via support for asynchronous I/O, strided accesses, and control over physical file layout on storage devices (disks). The I/O environment described in this chapter provides these facilities.

Instead of defining I/O access modes to express the common patterns for accessing a shared file (broadcast, reduction, scatter, gather), we chose another approach in which data partitioning is expressed using derived datatypes. Compared to a limited set of predefined access patterns, this approach has the advantage of added flexibility and expressiveness.

### 14.1.1 Definitions

file An MPI file is an ordered collection of typed data items. MPI supports random or sequential access to any integral set of these items. A file is opened collectively by a group of processes. All collective I/O calls on a file are collective over this group.

**displacement** A file *displacement* is an absolute byte position relative to the beginning of a file. The displacement defines the location where a *view* begins. Note that a "file displacement" is distinct from a "typemap displacement."

etype An etype (elementary datatype) is the unit of data access and positioning. It can be any MPI predefined or derived datatype. Derived etypes can be constructed using any of the MPI datatype constructor routines, provided all resulting typemap displacements are non-negative and monotonically nondecreasing. Data access is performed in etype units, reading or writing whole data items of type etype. Offsets are expressed as a count of etypes; file pointers point to the beginning of etypes. Depending on context, the term "etype" is used to describe one of three aspects of an elementary datatype: a particular MPI type, a data item of that type, or the extent of that type.

filetype A filetype is the basis for partitioning a file among processes and defines a template for accessing the file. A filetype is either a single etype or a derived MPI datatype constructed from multiple instances of the same etype. In addition, the extent of any hole in the filetype must be a multiple of the etype's extent. The displacements in the typemap of the filetype are not required to be distinct, but they must be non-negative and monotonically nondecreasing.

view A view defines the current set of data visible and accessible from an open file as an ordered set of etypes. Each process has its own view of the file, defined by three quantities: a displacement, an etype, and a filetype. The pattern described by a filetype is repeated, beginning at the displacement, to define the view. The pattern of repetition is defined to be the same pattern that MPI\_TYPE\_CONTIGUOUS would produce if it were passed the filetype and an arbitrarily large count. Figure 14.1 shows how the tiling works; note that the filetype in this example must have explicit lower and upper bounds set in order for the initial and final holes to be repeated in the view. Views can be changed by the user during program execution. The default view is a linear byte stream (displacement is zero, etype and filetype equal to MPI\_BYTE).




Figure 14.1: Etypes and filetypes

A group of processes can use complementary views to achieve a global data distribution such as a scatter/gather pattern (see Figure 14.2).




Figure 14.2: Partitioning a file among parallel processes

offset An offset is a position in the file relative to the current view, expressed as a count of etypes. Holes in the view's filetype are skipped when calculating this position. Offset 0 is the location of the first etype visible in the view (after skipping the displacement and any initial holes in the view). For example, an offset of 2 for process 1 in Figure 14.2 is the position of the eighth etype in the file after the displacement. An "explicit offset" is an offset that is used as an argument in explicit data access routines.

 $\frac{44}{45}$ 

file size and end of file The *size* of an MPI file is measured in bytes from the beginning of the file. A newly created file has a size of zero bytes. Using the size as an absolute displacement gives the position of the byte immediately following the last byte in the file. For any given view, the *end of file* is the offset of the first etype accessible in the current view starting after the last byte in the file.

file pointer A file pointer is an implicit offset maintained by MPI. "Individual file pointers" are file pointers that are local to each process that opened the file. A "shared file pointer" is a file pointer that is shared by the group of processes that opened the file.

file handle A file handle is an opaque object created by MPI\_FILE\_OPEN and freed by MPI\_FILE\_CLOSE. All operations on an open file reference the file through the file handle.

# 14.2 File Manipulation

# 14.2.1 Opening a File

### MPI\_FILE\_OPEN(comm, filename, amode, info, fh)

IN	comm	communicator (handle)
IN	filename	name of file to open (string)
IN	amode	file access mode (integer)
IN	info	info object (handle)
OUT	fh	new file handle (handle)

### C binding

### Fortran 2008 binding

```
MPI_File_open(comm, filename, amode, info, fh, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    CHARACTER(LEN=*), INTENT(IN) :: filename
    INTEGER, INTENT(IN) :: amode
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_File), INTENT(OUT) :: fh
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

```
MPI_FILE_OPEN(COMM, FILENAME, AMODE, INFO, FH, IERROR)
INTEGER COMM, AMODE, INFO, FH, IERROR
CHARACTER*(*) FILENAME
```

MPI\_FILE\_OPEN opens the file identified by the file name filename on all processes in the comm communicator group. MPI\_FILE\_OPEN is a collective routine: all processes must provide the same value for amode, and all processes must provide filenames that reference

the same file. (Values for info may vary.) comm must be an intra-communicator; it is erroneous to pass an inter-communicator to MPI\_FILE\_OPEN. Errors in MPI\_FILE\_OPEN are raised using the default file error handler (see Section 14.7). When using the World Model (Section 11.1), a process can open a file independently of other processes by using the MPI\_COMM\_SELF communicator. Applications using the Sessions Model (Section 11.3) can achieve the same result using communicators created from the "mpi://SELF" process set. The file handle returned, fh, can be subsequently used to access the file until the file is closed using MPI\_FILE\_CLOSE. Before calling MPI\_FINALIZE, the user is required to close (via MPI\_FILE\_CLOSE) all files that were opened with MPI\_FILE\_OPEN. Note that the communicator comm is unaffected by MPI\_FILE\_OPEN and continues to be usable in all MPI routines (e.g., MPI\_SEND). Furthermore, the use of comm will not interfere with I/O behavior.

The format for specifying the file name in the filename argument is implementation dependent and must be documented by the implementation.

Advice to implementors. An implementation may require that filename include a string or strings specifying additional information about the file. Examples include the type of filesystem (e.g., a prefix of ufs:), a remote hostname (e.g., a prefix of machine.univ.edu:), or a file password (e.g., a suffix of /PASSWORD=SECRET). (End of advice to implementors.)

Advice to users. On some implementations of MPI, the file namespace may not be identical from all processes of all applications. For example, "/tmp/foo" may denote different files on different processes, or a single file may have many names, dependent on process location. The user is responsible for ensuring that a single file is referenced by the filename argument, as it may be impossible for an implementation to detect this type of namespace error. (End of advice to users.)

Initially, all processes view the file as a linear byte stream, and each process views data in its own native representation (no data representation conversion is performed). (POSIX files are linear byte streams in the native representation.) The file view can be changed via the MPI\_FILE\_SET\_VIEW routine.

The following access modes are supported (specified in amode, a bit vector OR of the following integer constants):

- MPI\_MODE\_RDONLY—read only,
- MPI\_MODE\_RDWR—reading and writing,
- MPI\_MODE\_WRONLY—write only,
- MPI\_MODE\_CREATE—create the file if it does not exist.
- MPI\_MODE\_EXCL—error if creating file that already exists,
- MPI\_MODE\_DELETE\_ON\_CLOSE—delete file on close,
- MPI\_MODE\_UNIQUE\_OPEN—file will not be concurrently opened elsewhere,
- MPI\_MODE\_SEQUENTIAL—file will only be accessed sequentially,
- MPI\_MODE\_APPEND—set initial position of all file pointers to end of file.

Advice to users. C users can use bit vector OR (|) to combine these constants; Fortran 90 users can use the bit vector IOR intrinsic. Fortran 77 users can use (nonportably) bit vector IOR on systems that support it. Alternatively, Fortran users can portably use integer addition to OR the constants (each constant should appear at most once in the addition.). (End of advice to users.)

Advice to implementors. The values of these constants must be defined such that the bitwise OR and the sum of any distinct set of these constants is equivalent. (End of advice to implementors.)

The modes MPI\_MODE\_RDONLY, MPI\_MODE\_RDWR, MPI\_MODE\_WRONLY, MPI\_MODE\_CREATE, and MPI\_MODE\_EXCL have identical semantics to their POSIX counterparts [44]. Exactly one of MPI\_MODE\_RDONLY, MPI\_MODE\_RDWR, or MPI\_MODE\_WRONLY, must be specified. It is erroneous to specify MPI\_MODE\_CREATE or MPI\_MODE\_EXCL in conjunction with MPI\_MODE\_RDONLY; it is erroneous to specify MPI\_MODE\_SEQUENTIAL together with MPI\_MODE\_RDWR.

The MPI\_MODE\_DELETE\_ON\_CLOSE mode causes the file to be deleted (equivalent to performing an MPI\_FILE\_DELETE) when the file is closed.

The MPI\_MODE\_UNIQUE\_OPEN mode allows an implementation to optimize access by eliminating the overhead of file locking. It is erroneous to open a file in this mode unless the file will not be concurrently opened elsewhere.

Advice to users. For MPI\_MODE\_UNIQUE\_OPEN, not opened elsewhere includes both inside and outside the MPI environment. In particular, one needs to be aware of potential external events which may open files (e.g., automated backup facilities). When MPI\_MODE\_UNIQUE\_OPEN is specified, the user is responsible for ensuring that no such external events take place. (End of advice to users.)

The MPI\_MODE\_SEQUENTIAL mode allows an implementation to optimize access to some sequential devices (tapes and network streams). It is erroneous to attempt nonsequential access to a file that has been opened in this mode.

Specifying MPI\_MODE\_APPEND only guarantees that all shared and individual file pointers are positioned at the initial end of file when MPI\_FILE\_OPEN returns. Subsequent positioning of file pointers is application dependent. In particular, the implementation does not ensure that all writes are appended.

Errors related to the access mode are raised in the class MPI\_ERR\_AMODE.

The info argument is used to provide information regarding file access patterns and file system specifics (see Section 14.2.8). The constant MPI\_INFO\_NULL can be used when no info needs to be specified.

Advice to users. Some file attributes are inherently implementation dependent (e.g., file permissions). These attributes must be set using either the info argument or facilities outside the scope of MPI. (End of advice to users.)

Files are opened by default using nonatomic mode file consistency semantics (see Section 14.6.1). The more stringent atomic mode consistency semantics, required for atomicity of conflicting accesses, can be set using MPI\_FILE\_SET\_ATOMICITY.

```
1
     14.2.2 Closing a File
2
3
4
     MPI_FILE_CLOSE(fh)
5
       INOUT
                                              file handle (handle)
6
     C binding
8
     int MPI_File_close(MPI_File *fh)
9
10
     Fortran 2008 binding
11
     MPI_File_close(fh, ierror)
12
          TYPE(MPI_File), INTENT(INOUT) :: fh
13
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
14
     Fortran binding
15
16
     MPI_FILE_CLOSE(FH, IERROR)
17
          INTEGER FH, IERROR
18
          MPI_FILE_CLOSE first synchronizes file state (equivalent to performing an
19
     MPI_FILE_SYNC), then closes the file associated with fh. The file is deleted if it was
20
     opened with access mode MPI_MODE_DELETE_ON_CLOSE (equivalent to performing an
21
     MPI_FILE_DELETE). MPI_FILE_CLOSE is a collective routine.
22
23
           Advice to users. If the file is deleted on close, and there are other processes currently
24
           accessing the file, the status of the file and the behavior of future accesses by these
           processes are implementation dependent. (End of advice to users.)
26
27
          The user is responsible for ensuring that all outstanding nonblocking requests and
28
     split collective operations associated with fh made by a process have completed before that
29
     process calls MPI_FILE_CLOSE.
30
          The MPI_FILE_CLOSE routine deallocates the file handle object and sets fh to
31
     MPI_FILE_NULL.
32
33
     14.2.3 Deleting a File
34
35
36
     MPI_FILE_DELETE(filename, info)
37
       IN
                 filename
                                              name of file to delete (string)
38
39
       IN
                 info
                                              info object (handle)
41
     C binding
42
     int MPI_File_delete(const char *filename, MPI_Info info)
43
     Fortran 2008 binding
44
     MPI_File_delete(filename, info, ierror)
45
46
          CHARACTER(LEN=*), INTENT(IN) :: filename
47
          TYPE(MPI_Info), INTENT(IN) :: info
```

INTEGER, OPTIONAL, INTENT(OUT) :: ierror

13

14

15 16

17 18 19

20 21

22

23 24

26 27

28

29

30

31

33

34

35

36 37

42

43

44

45

46

47

```
Fortran binding
MPI_FILE_DELETE(FILENAME, INFO, IERROR)
CHARACTER*(*) FILENAME
INTEGER INFO, IERROR
```

MPI\_FILE\_DELETE deletes the file identified by the file name filename. If the file does not exist, MPI\_FILE\_DELETE raises an error in the class MPI\_ERR\_NO\_SUCH\_FILE.

The info argument can be used to provide information regarding file system specifics (see Section 14.2.8). The constant MPI\_INFO\_NULL refers to the null info, and can be used when no info needs to be specified.

If a process currently has the file open, the behavior of any access to the file (as well as the behavior of any outstanding accesses) is implementation dependent. In addition, whether an open file is deleted or not is also implementation dependent. If the file is not deleted, an error in the class MPI\_ERR\_FILE\_IN\_USE or MPI\_ERR\_ACCESS will be raised. Errors are raised using the default file error handler (see Section 14.7).

## 14.2.4 Resizing a File

```
MPI_FILE_SET_SIZE(fh, size)
 INOUT
          fh
                                     file handle (handle)
 IN
                                     size to truncate or expand file (integer)
          size
C binding
int MPI_File_set_size(MPI_File fh, MPI_Offset size)
Fortran 2008 binding
MPI_File_set_size(fh, size, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_FILE_SET_SIZE(FH, SIZE, IERROR)
    INTEGER FH, IERROR
    INTEGER(KIND=MPI_OFFSET_KIND) SIZE
```

MPI\_FILE\_SET\_SIZE resizes the file associated with the file handle fh. size is measured in bytes from the beginning of the file. MPI\_FILE\_SET\_SIZE is collective; all processes in the group must pass identical values for size.

If size is smaller than the current file size, the file is truncated at the position defined by size. The implementation is free to deallocate file blocks located beyond this position.

If size is larger than the current file size, the file size becomes size. Regions of the file that have been previously written are unaffected. The values of data in the new regions in the file (those locations with displacements between old file size and size) are undefined. It is implementation dependent whether the MPI\_FILE\_SET\_SIZE routine allocates file space—use MPI\_FILE\_PREALLOCATE to force file space to be reserved.

MPI\_FILE\_SET\_SIZE does not affect the individual file pointers or the shared file

pointer. If MPI\_MODE\_SEQUENTIAL mode was specified when the file was opened, it is erroneous to call this routine.

Advice to users. It is possible for the file pointers to point beyond the end of file after a MPI\_FILE\_SET\_SIZE operation truncates a file. This is valid, and equivalent to seeking beyond the current end of file. (End of advice to users.)

All nonblocking requests and split collective operations on fh must be completed before calling MPI\_FILE\_SET\_SIZE. Otherwise, calling MPI\_FILE\_SET\_SIZE is erroneous. As far as consistency semantics are concerned, MPI\_FILE\_SET\_SIZE is a write operation that conflicts with operations that access bytes at displacements between the old and new file sizes (see Section 14.6.1).

# 14.2.5 Preallocating Space for a File

```
MPI_FILE_PREALLOCATE(fh, size)
```

```
INOUT fh file handle (handle)

IN size size to preallocate file (integer)
```

### C binding

```
int MPI_File_preallocate(MPI_File fh, MPI_Offset size)
```

# Fortran 2008 binding

```
MPI_File_preallocate(fh, size, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

### Fortran binding

```
MPI_FILE_PREALLOCATE(FH, SIZE, IERROR)
INTEGER FH, IERROR
INTEGER(KIND=MPI_OFFSET_KIND) SIZE
```

MPI\_FILE\_PREALLOCATE ensures that storage space is allocated for the first size bytes of the file associated with fh. MPI\_FILE\_PREALLOCATE is collective; all processes in the group must pass identical values for size. Regions of the file that have previously been written are unaffected. For newly allocated regions of the file, MPI\_FILE\_PREALLOCATE has the same effect as writing undefined data. If size is larger than the current file size, the file size increases to size. If size is less than or equal to the current file size, the file size is unchanged.

The treatment of file pointers, pending nonblocking accesses, and file consistency is the same as with MPI\_FILE\_SET\_SIZE. If MPI\_MODE\_SEQUENTIAL mode was specified when the file was opened, it is erroneous to call this routine.

Advice to users. In some implementations, file preallocation may be time-consuming. (End of advice to users.)

freeing group.

```
14.2.6 Querying the Size of a File
MPI_FILE_GET_SIZE(fh, size)
           fh
  IN
                                       file handle (handle)
  OUT
           size
                                       size of the file in bytes (integer)
C binding
int MPI_File_get_size(MPI_File fh, MPI_Offset *size)
Fortran 2008 binding
                                                                                         12
MPI_File_get_size(fh, size, ierror)
                                                                                         13
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                         14
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: size
                                                                                         15
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                         16
Fortran binding
                                                                                         18
MPI_FILE_GET_SIZE(FH, SIZE, IERROR)
                                                                                         19
    INTEGER FH, IERROR
                                                                                         20
    INTEGER(KIND=MPI_OFFSET_KIND) SIZE
                                                                                         21
    MPI_FILE_GET_SIZE returns, in size, the current size in bytes of the file associated with
the file handle fh. As far as consistency semantics are concerned, MPI_FILE_GET_SIZE is a
data access operation (see Section 14.6.1).
                                                                                         24
14.2.7 Querying File Parameters
                                                                                         26
                                                                                         27
                                                                                         28
MPI_FILE_GET_GROUP(fh, group)
  IN
           fh
                                       file handle (handle)
  OUT
                                       group which opened the file (handle)
           group
C binding
                                                                                         34
int MPI_File_get_group(MPI_File fh, MPI_Group *group)
                                                                                         35
                                                                                         36
Fortran 2008 binding
                                                                                         37
MPI_File_get_group(fh, group, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(MPI_Group), INTENT(OUT) :: group
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                         42
Fortran binding
MPI_FILE_GET_GROUP(FH, GROUP, IERROR)
                                                                                         43
                                                                                         44
    INTEGER FH, GROUP, IERROR
                                                                                         45
    MPI_FILE_GET_GROUP returns a duplicate of the group of the communicator used to
                                                                                         46
open the file associated with fh. The group is returned in group. The user is responsible for
                                                                                         47
```

48

```
MPI_FILE_GET_AMODE(fh, amode)
2
       IN
                fh
                                           file handle (handle)
3
       OUT
                amode
                                           file access mode used to open the file (integer)
5
6
     C binding
7
     int MPI_File_get_amode(MPI_File fh, int *amode)
     Fortran 2008 binding
9
     MPI_File_get_amode(fh, amode, ierror)
10
         TYPE(MPI_File), INTENT(IN) :: fh
11
         INTEGER, INTENT(OUT) :: amode
12
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
14
     Fortran binding
     MPI_FILE_GET_AMODE(FH, AMODE, IERROR)
15
16
         INTEGER FH, AMODE, IERROR
17
         MPI_FILE_GET_AMODE returns, in amode, the access mode of the file associated with
18
     fh.
19
20
     Example 14.1 In Fortran 77, decoding an amode bit vector will require a routine such as
21
     the following:
22
23
     SUBROUTINE BIT_QUERY(TEST_BIT, MAX_BIT, AMODE, BIT_FOUND)
24
         TEST IF THE INPUT TEST BIT IS SET IN THE INPUT AMODE
26
         IF SET, RETURN 1 IN BIT_FOUND, O OTHERWISE
27
28
         INTEGER TEST_BIT, AMODE, BIT_FOUND, CP_AMODE, HIFOUND
29
         BIT_FOUND = 0
30
         CP\_AMODE = AMODE
31
     100 CONTINUE
32
         LBIT = 0
33
         HIFOUND = 0
34
         DO L = MAX_BIT, 0, -1
35
             MATCHER = 2**L
36
             IF (CP_AMODE .GE. MATCHER .AND. HIFOUND .EQ. 0) THEN
37
                 HIFOUND = 1
                LBIT = MATCHER
39
                CP_AMODE = CP_AMODE - MATCHER
             END IF
41
         END DO
42
         IF (HIFOUND .EQ. 1 .AND. LBIT .EQ. TEST_BIT) BIT_FOUND = 1
43
         IF (BIT_FOUND .EQ. O .AND. HIFOUND .EQ. 1 .AND. &
44
              CP_AMODE .GT. 0) GO TO 100
45
     END
46
```

This routine could be called successively to decode amode, one bit at a time. For example, the following code fragment would check for MPI\_MODE\_RDONLY.

13

14

15

16

17

18

19

20 21

22

23

24

26

31

33

35 36

37

38

39

41

42 43

44

45

46

```
CALL BIT_QUERY(MPI_MODE_RDONLY, 30, AMODE, BIT_FOUND)

IF (BIT_FOUND .EQ. 1) THEN

PRINT *, 'FOUND READ-ONLY BIT IN AMODE=', AMODE

ELSE

PRINT *, 'READ-ONLY BIT NOT FOUND IN AMODE=', AMODE

END IF
```

### 14.2.8 File Info

Hints specified via info (see Chapter 10) allow a user to provide information such as file access patterns and file system specifics to direct optimization. Providing hints may enable an implementation to deliver increased I/O performance or minimize the use of system resources. An implementation is free to ignore all hints; however, applications must comply with any info hints they provide that are used by the MPI implementation (i.e., are returned by a call to MPI\_FILE\_GET\_INFO) and that place a restriction on the behavior of the application. Hints are specified on a per file basis, in MPI\_FILE\_OPEN, MPI\_FILE\_DELETE, MPI\_FILE\_SET\_VIEW, and MPI\_FILE\_SET\_INFO, via the opaque info object. When an info object that specifies a subset of valid hints is passed to MPI\_FILE\_SET\_VIEW or MPI\_FILE\_SET\_INFO, there will be no effect on previously set or defaulted hints that the info does not specify.

Advice to implementors. It may happen that a program is coded with hints for one system, and later executes on another system that does not support these hints. In general, unsupported hints should simply be ignored. Needless to say, no hint can be mandatory. However, for each hint used by a specific implementation, a default value must be provided when the user does not specify a value for this hint. (End of advice to implementors.)

```
MPI_FILE_SET_INFO(fh, info)
 INOUT
                                     file handle (handle)
           fh
 IN
          info
                                     info object (handle)
C binding
int MPI_File_set_info(MPI_File fh, MPI_Info info)
Fortran 2008 binding
MPI_File_set_info(fh, info, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_FILE_SET_INFO(FH, INFO, IERROR)
```

INTEGER FH, INFO, IERROR

MPI\_FILE\_SET\_INFO updates the hints of the file associated with fh using the hints provided in info. This operation has no effect on previously set or defaulted hints that are not

specified by info. It also has no effect on previously set or defaulted hints that are specified by info, but are ignored by the MPI implementation in this call to MPI\_FILE\_SET\_INFO. MPI\_FILE\_SET\_INFO is a collective routine. The info object may be different on each process, but any info entries that an implementation requires to be the same on all processes must appear with the same value in each process's info object.

Advice to users. Many info items that an implementation can use when it creates or opens a file cannot easily be changed once the file has been created or opened. Thus, an implementation may ignore hints issued in this call that it would have accepted in an open call. An implementation may also be unable to update certain info hints in a call to MPI\_FILE\_SET\_VIEW or MPI\_FILE\_SET\_INFO. MPI\_FILE\_GET\_INFO can be used to determine whether info changes were ignored by the implementation. (End of advice to users.)

MPI\_FILE\_GET\_INFO(FH, INFO\_USED, IERROR)

INTEGER FH, INFO\_USED, IERROR

MPI\_FILE\_GET\_INFO returns a new info object containing the hints of the file associated with fh. The current setting of all hints related to this file is returned in info\_used. An MPI implementation is required to return all hints that are supported by the implementation and have default values specified; any user-supplied hints that were not ignored by the implementation; and any additional hints that were set by the implementation. If no such hints exist, a handle to a newly created info object is returned that contains no (key,value) pairs. The user is responsible for freeing info\_used via MPI\_INFO\_FREE.

### Reserved File Hints

Fortran binding

Some potentially useful hints (info key values) are outlined below. The following key values are reserved. An implementation is not required to interpret these key values, but if it does interpret the key value, it must provide the functionality described. (For more details on "info," see Chapter 10.)

These hints mainly affect access patterns and the layout of data on parallel I/O devices. For each hint name introduced, we describe the purpose of the hint, and the type of the hint

value. The "[SAME]" annotation specifies that the hint values provided by all participating processes must be identical; otherwise the program is erroneous. In addition, some hints are context dependent, and are only used by an implementation at specific times (e.g., "file\_perm" is only useful during file creation).

- "access\_style" (comma separated list of strings): This hint specifies the manner in which the file will be accessed until the file is closed or until the "access\_style" key value is altered. The hint value is a comma separated list of the following: "read\_once", "write\_once", "read\_mostly", "write\_mostly", "sequential", "reverse\_sequential", and "random".
- "collective\_buffering" (boolean) [SAME]: This hint specifies whether the application may benefit from collective buffering. Collective buffering is an optimization performed on collective accesses. Accesses to the file are performed on behalf of all processes in the group by a number of target nodes. These target nodes coalesce small requests into large disk accesses. Valid values for this key are "true" and "false". Collective buffering parameters are further directed via additional hints: "cb\_block\_size", "cb\_buffer\_size", and "cb\_nodes".
- "cb\_block\_size" (integer) [SAME]: This hint specifies the block size to be used for collective buffering file access. *Target nodes* access data in chunks of this size. The chunks are distributed among target nodes in a round-robin (cyclic) pattern.
- "cb\_buffer\_size" (integer) [SAME]: This hint specifies the total buffer space that can be used for collective buffering on each target node, usually a multiple of "cb\_block\_size".
- "cb\_nodes" (integer) [SAME]: This hint specifies the number of target nodes to be used for collective buffering.
- "chunked" (comma separated list of integers) [SAME]: This hint specifies that the file consists of a multidimentional array that is often accessed by subarrays. The value for this hint is a comma separated list of array dimensions, starting from the most significant one (for an array stored in row-major order, as in C, the most significant dimension is the first one; for an array stored in column-major order, as in Fortran, the most significant dimension is the last one, and array dimensions should be reversed).
- "chunked\_item" (comma separated list of integers) [SAME]: This hint specifies the size of each array entry, in bytes.
- "chunked\_size" (comma separated list of integers) [SAME]: This hint specifies the dimensions of the subarrays. This is a comma separated list of array dimensions, starting from the most significant one.
- "filename" (string): This hint specifies the file name used when the file was opened. If the implementation is capable of returning the file name of an open file, it will be returned using this key by MPI\_FILE\_GET\_INFO. This key is ignored when passed to MPI\_FILE\_OPEN, MPI\_FILE\_SET\_VIEW, MPI\_FILE\_SET\_INFO, and MPI\_FILE\_DELETE.
- "file\_perm" (string) [SAME]: This hint specifies the file permissions to use for file creation. Setting this hint is only useful when passed to MPI\_FILE\_OPEN with an amode

1 that includes MPI\_MODE\_CREATE. The set of valid values for this key is implementa-2 tion dependent. 3 "io\_node\_list" (comma separated list of strings) [SAME]: This hint specifies the list 4 of I/O devices that should be used to store the file. This hint is most relevant when 5 the file is created. 6 7 "nb\_proc" (integer) [SAME]: This hint specifies the number of parallel processes that 8 will typically be assigned to run programs that access this file. This hint is most 9 relevant when the file is created. 10 11 "num\_io\_nodes" (integer) [SAME]: This hint specifies the number of I/O devices in the system. This hint is most relevant when the file is created. 12 13 "striping\_factor" (integer) [SAME]: This hint specifies the number of I/O devices that 14 the file should be striped across, and is relevant only when the file is created. 15 16 "striping\_unit" (integer) [SAME]: This hint specifies the suggested striping unit to be 17 used for this file. The striping unit is the amount of consecutive data assigned to one 18 I/O device before progressing to the next device, when striping across a number of 19 devices. It is expressed in bytes. This hint is relevant only when the file is created. 20 21 14.3 File Views 22 23 24 25 MPI\_FILE\_SET\_VIEW(fh, disp, etype, filetype, datarep, info) 26 **INOUT** fh file handle (handle) 27 28 IN disp displacement (integer) 29 elementary datatype (handle) IN etype 30 filetype (handle) IN filetype 31 32 IN datarep data representation (string) 33 IN info info object (handle) 34 35 C binding 36 int MPI\_File\_set\_view(MPI\_File fh, MPI\_Offset disp, MPI\_Datatype etype, 37 MPI\_Datatype filetype, const char \*datarep, MPI\_Info info) 38 39 Fortran 2008 binding 40 MPI\_File\_set\_view(fh, disp, etype, filetype, datarep, info, ierror) 41 TYPE(MPI\_File), INTENT(IN) :: fh 42 INTEGER(KIND=MPI\_OFFSET\_KIND), INTENT(IN) :: disp

### Fortran binding

43

44

45

46

47

48

TYPE(MPI\_Datatype), INTENT(IN) :: etype, filetype

CHARACTER(LEN=\*), INTENT(IN) :: datarep

INTEGER, OPTIONAL, INTENT(OUT) :: ierror

TYPE(MPI\_Info), INTENT(IN) :: info

14.3. FILE VIEWS 645

MPI\_FILE\_SET\_VIEW(FH, DISP, ETYPE, FILETYPE, DATAREP, INFO, IERROR)
INTEGER FH, ETYPE, FILETYPE, INFO, IERROR
INTEGER(KIND=MPI\_OFFSET\_KIND) DISP
CHARACTER\*(\*) DATAREP

The MPI\_FILE\_SET\_VIEW routine changes the process's view of the data in the file. The start of the view is set to disp; the type of data is set to etype; the distribution of data to processes is set to filetype; and the representation of data in the file is set to datarep. In addition, MPI\_FILE\_SET\_VIEW resets the individual file pointers and the shared file pointer to zero. MPI\_FILE\_SET\_VIEW is collective; the values for datarep and the extents of etype in the file data representation must be identical on all processes in the group; values for disp, filetype, and info may vary. The datatypes passed in etype and filetype must be committed.

The etype always specifies the data layout in the file. If etype is a portable datatype (see Section 2.4), the extent of etype is computed by scaling any displacements in the datatype to match the file data representation. If etype is not a portable datatype, no scaling is done when computing the extent of etype. The user must be careful when using nonportable etypes in heterogeneous environments; see Section 14.5.1 for further details.

If MPI\_MODE\_SEQUENTIAL mode was specified when the file was opened, the special displacement MPI\_DISPLACEMENT\_CURRENT must be passed in disp. This sets the displacement to the current position of the shared file pointer. MPI\_DISPLACEMENT\_CURRENT is invalid unless the amode for the file has MPI\_MODE\_SEQUENTIAL set.

Rationale. For some sequential files, such as those corresponding to magnetic tapes or streaming network connections, the *displacement* may not be meaningful. MPI\_DISPLACEMENT\_CURRENT allows the view to be changed for these types of files. (*End of rationale*.)

Advice to implementors. It is expected that a call to MPI\_FILE\_SET\_VIEW will immediately follow MPI\_FILE\_OPEN in numerous instances. A high-quality implementation will ensure that this behavior is efficient. (*End of advice to implementors*.)

The disp displacement argument specifies the position (absolute offset in bytes from the beginning of the file) where the view begins.

Advice to users. disp can be used to skip headers or when the file includes a sequence of data segments that are to be accessed in different patterns (see Figure 14.3). Separate views, each using a different displacement and filetype, can be used to access each segment.




Figure 14.3: Displacements

(End of advice to users.)

 An etype (elementary datatype) is the unit of data access and positioning. It can be any MPI predefined or derived datatype. Derived etypes can be constructed by using any of the MPI datatype constructor routines, provided all resulting typemap displacements are non-negative and monotonically nondecreasing. Data access is performed in etype units, reading or writing whole data items of type etype. Offsets are expressed as a count of etypes; file pointers point to the beginning of etypes.

Advice to users. In order to ensure interoperability in a heterogeneous environment, additional restrictions must be observed when constructing the etype (see Section 14.5). (End of advice to users.)

A filetype is either a single etype or a derived MPI datatype constructed from multiple instances of the same etype. In addition, the extent of any hole in the filetype must be a multiple of the etype's extent. These displacements are not required to be distinct, but they cannot be negative, and they must be monotonically nondecreasing.

If the file is opened for writing, neither the etype nor the filetype is permitted to contain overlapping regions. This restriction is equivalent to the "datatype used in a receive cannot specify overlapping regions" restriction for communication. Note that filetypes from different processes may still overlap each other.

If a filetype has holes in it, then the data in the holes is inaccessible to the calling process. However, the disp, etype, and filetype arguments can be changed via future calls to MPI\_FILE\_SET\_VIEW to access a different part of the file.

It is erroneous to use absolute addresses in the construction of the etype and filetype.

The info argument is used to provide information regarding file access patterns and file system specifics to direct optimization (see Section 14.2.8). The constant MPI\_INFO\_NULL refers to the null info and can be used when no info needs to be specified.

The datarep argument is a string that specifies the representation of data in the file. See the file interoperability section (Section 14.5) for details and a discussion of valid values.

The user is responsible for ensuring that all nonblocking requests and split collective operations on fh have been completed before calling MPI\_FILE\_SET\_VIEW—otherwise, the call to MPI\_FILE\_SET\_VIEW is erroneous.

# MPI\_FILE\_GET\_VIEW(fh, disp, etype, filetype, datarep)

1N	fh	file handle (handle)
OUT	disp	displacement (integer)
OUT	etype	elementary datatype (handle)
OUT	filetype	filetype (handle)
OUT	datarep	data representation (string)

# C binding

## Fortran 2008 binding

```
INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: disp
TYPE(MPI_Datatype), INTENT(OUT) :: etype, filetype
CHARACTER(LEN=*), INTENT(OUT) :: datarep
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_FILE_GET_VIEW(FH, DISP, ETYPE, FILETYPE, DATAREP, IERROR)
INTEGER FH, ETYPE, FILETYPE, IERROR
INTEGER(KIND=MPI_OFFSET_KIND) DISP
CHARACTER*(*) DATAREP
```

MPI\_FILE\_GET\_VIEW returns the process's view of the data in the file. The current value of the displacement is returned in disp. The etype and filetype are new datatypes with typemaps equal to the typemaps of the current etype and filetype, respectively.

The data representation is returned in datarep. The user is responsible for ensuring that datarep is large enough to hold the returned data representation string. The length of a data representation string is limited to the value of MPI\_MAX\_DATAREP\_STRING.

In addition, if a portable datatype was used to set the current view, then the corresponding datatype returned by MPI\_FILE\_GET\_VIEW is also a portable datatype. If etype or filetype are derived datatypes, the user is responsible for freeing them. The etype and filetype returned are both in a committed state.

# 14.4 Data Access

#### 14.4.1 Data Access Routines

Data is moved between files and processes by issuing read and write calls. There are three orthogonal aspects to data access: positioning (explicit offset vs. implicit file pointer), synchronism (blocking vs. nonblocking and split collective), and coordination (noncollective vs. collective). The following combinations of these data access routines, including two types of file pointers (individual and shared) are provided in Table 14.1.

positioning	synchronism	coordination	
		noncollective	collective
explicit	blocking	MPI_FILE_READ_AT	MPI_FILE_READ_AT_ALL
offsets		MPI_FILE_WRITE_AT	MPI_FILE_WRITE_AT_ALL
	nonblocking	MPI_FILE_IREAD_AT	MPI_FILE_IREAD_AT_ALL
		MPI_FILE_IWRITE_AT	MPI_FILE_IWRITE_AT_ALL
	split collective	N/A	MPI_FILE_READ_AT_ALL_BEGIN
			MPI_FILE_READ_AT_ALL_END
			MPI_FILE_WRITE_AT_ALL_BEGIN
			MPI_FILE_WRITE_AT_ALL_END
individual	blocking	MPI_FILE_READ	MPI_FILE_READ_ALL
file pointers		MPI_FILE_WRITE	MPI_FILE_WRITE_ALL
	nonblocking	MPI_FILE_IREAD	MPI_FILE_IREAD_ALL
		MPI_FILE_IWRITE	MPI_FILE_IWRITE_ALL
	split collective	N/A	MPI_FILE_READ_ALL_BEGIN
			MPI_FILE_READ_ALL_END
Y			MPI_FILE_WRITE_ALL_BEGIN
			MPI_FILE_WRITE_ALL_END
shared	blocking	MPI_FILE_READ_SHARED	MPI_FILE_READ_ORDERED
file pointer		MPI_FILE_WRITE_SHARED	MPI_FILE_WRITE_ORDERED
	nonblocking	MPI_FILE_IREAD_SHARED	N/A
		MPI_FILE_IWRITE_SHARED	
	split collective	N/A	MPI_FILE_READ_ORDERED_BEGIN
			MPI_FILE_READ_ORDERED_END
			MPI_FILE_WRITE_ORDERED_BEGIN
			MPI_FILE_WRITE_ORDERED_END

Table 14.1: Data access routines

POSIX read()/fread() and write()/fwrite() are blocking, noncollective operations and use individual file pointers. The MPI equivalents are MPI\_FILE\_READ and MPI\_FILE\_WRITE.

Implementations of data access routines may buffer data to improve performance. This does not affect reads, as the data is always available in the user's buffer after a read operation completes. For writes, however, the MPI\_FILE\_SYNC routine provides the only guarantee that data has been transferred to the storage device.

#### Positioning

MPI provides three types of positioning for data access routines: **explicit offsets**, **individual file pointers**, and **shared file pointers**. The different positioning methods may be mixed within the same program and do not affect each other.

The data access routines that accept explicit offsets contain \_AT in their name (e.g., MPI\_FILE\_WRITE\_AT). Explicit offset operations perform data access at the file position given directly as an argument—no file pointer is used nor updated. Note that this is not equivalent to an atomic seek-and-read or seek-and-write operation, as no "seek" is issued. Operations with explicit offsets are described in Section 14.4.2.

The names of the individual file pointer routines contain no positional qualifier (e.g., MPI\_FILE\_WRITE). Operations with individual file pointers are described in Section 14.4.3. The data access routines that use shared file pointers contain \_SHARED or \_ORDERED in their name (e.g., MPI\_FILE\_WRITE\_SHARED). Operations with shared file pointers are described in Section 14.4.4.

The main semantic issues with MPI-maintained file pointers are how and when they are updated by I/O operations. In general, each I/O operation leaves the file pointer pointing to the next data item after the last one that is accessed by the operation. In a nonblocking or split collective operation, the pointer is updated by the call that initiates the I/O, possibly before the access completes.

More formally,

$$new\_file\_offset = old\_file\_offset + \frac{elements(datatype)}{elements(etupe)} \times count$$

where count is the number of datatype items to be accessed, elements(X) is the number of predefined datatypes in the typemap of X, and  $old\_file\_offset$  is the value of the implicit offset before the call. The file position,  $new\_file\_offset$ , is in terms of a count of etypes relative to the current view.

#### Synchronism

MPI supports blocking and nonblocking I/O routines.

A blocking I/O call will not return until the I/O request is completed.

A nonblocking I/O call initiates an I/O operation, but does not wait for it to complete. Given suitable hardware, this allows the transfer of data out of and into the user's buffer to proceed concurrently with computation. A separate request complete call (MPI\_WAIT, MPI\_TEST, or any of their variants) is needed to complete the I/O request, i.e., to confirm that the data has been read or written and that it is safe for the user to reuse the buffer. The nonblocking versions of the routines are named MPI\_FILE\_IXXX, where the I stands for immediate.

It is erroneous to access the local buffer of a nonblocking data access operation, or to use that buffer as the source or target of other communications, between the initiation and completion of the operation.

The split collective routines support a restricted form of "nonblocking" operations for collective data access (see Section 14.4.5).

#### Coordination

Every noncollective data access routine MPI\_FILE\_XXX has a collective counterpart. For most routines, this counterpart is MPI\_FILE\_XXX\_ALL or a pair of MPI\_FILE\_XXX\_BEGIN and MPI\_FILE\_XXX\_END. The counterparts to the MPI\_FILE\_XXX\_SHARED routines are MPI\_FILE\_XXX\_ORDERED.

The completion of a noncollective call only depends on the activity of the calling process. However, the completion of a collective call (which must be called by all members of the process group) may depend on the activity of the other processes participating in the collective call. See Section 14.6.4 for rules on semantics of collective calls.

Collective operations may perform much better than their noncollective counterparts, as global data accesses have significant potential for automatic optimization.

#### **Data Access Conventions**

Data is moved between files and processes by calling read and write routines. Read routines move data from a file into memory. Write routines move data from memory into a file. The file is designated by a file handle, fh. The location of the file data is specified by an offset into the current view. The data in memory is specified by a triple: buf, count, and datatype. Upon completion, the amount of data accessed by the calling process is returned in a status.

An offset designates the starting position in the file for an access. The offset is always in etype units relative to the current view. Explicit offset routines pass offset as an argument (negative values are erroneous). The file pointer routines use implicit offsets maintained by MPI.

A data access routine attempts to transfer (read or write) count data items of type datatype between the user's buffer buf and the file. The datatype passed to the routine must be a committed datatype. The layout of data in memory corresponding to buf, count, datatype is interpreted the same way as in MPI communication functions; see Section 3.2.2 and Section 5.1.11. The data is accessed from those parts of the file specified by the current view (Section 14.3). The type signature of datatype must match the type signature of some number of contiguous copies of the etype of the current view. As in a receive, it is erroneous to specify a datatype for reading that contains overlapping regions (areas of memory which would be stored into more than once).

The nonblocking data access routines indicate that MPI can start a data access and associate a request handle, request, with the I/O operation. Nonblocking operations are completed via MPI\_TEST, MPI\_WAIT, or any of their variants.

Data access operations, when completed, return the amount of data accessed in status.

Advice to users. To prevent problems with the argument copying and register optimization done by Fortran compilers, please note the hints in Sections 19.1.10–19.1.20. (End of advice to users.)

2

3

4

5

6

7

8

9

10

11

12

13

14

1516

17

18

19 20 21

22

23 24

26

27

28 29

30 31

32

33

34 35

36

37

41

For blocking routines, status is returned directly. For nonblocking routines and split collective routines, status is returned when the operation is completed. The number of datatype entries and predefined elements accessed by the calling process can be extracted from status by using MPI\_GET\_COUNT and MPI\_GET\_ELEMENTS (or

MPI\_GET\_ELEMENTS\_X), respectively. The interpretation of the MPI\_ERROR field is the same as for other operations—normally undefined, but meaningful if an MPI routine returns MPI\_ERR\_IN\_STATUS. The user can pass (in C and Fortran) MPI\_STATUS\_IGNORE in the status argument if the return value of this argument is not needed. The status can be passed to MPI\_TEST\_CANCELLED to determine if the operation was cancelled. All other fields of status are undefined.

When reading, a program can detect the end of file by noting that the amount of data read is less than the amount requested. Writing past the end of file increases the file size. The amount of data accessed will be the amount requested, unless an error is raised (or a read reaches the end of file).

# 14.4.2 Data Access with Explicit Offsets

If MPI\_MODE\_SEQUENTIAL mode was specified when the file was opened, it is erroneous to call the routines in this section.

```
MPI_FILE_READ_AT(fh, offset, buf, count, datatype, status)
```

```
fh
IN
                                            file handle (handle)
IN
           offset
                                            file offset (integer)
OUT
           buf
                                            initial address of buffer (choice)
IN
           count
                                            number of elements in buffer (integer)
IN
                                            datatype of each buffer element (handle)
           datatype
OUT
           status
                                            status object (Status)
```

#### C binding

```
int MPI_File_read_at(MPI_File fh, MPI_Offset offset, void *buf, int count,
             MPI_Datatype datatype, MPI_Status *status)
```

```
int MPI_File_read_at_c(MPI_File fh, MPI_Offset offset, void *buf,
             MPI_Count count, MPI_Datatype datatype, MPI_Status *status)
```

#### Fortran 2008 binding

```
38
     MPI_File_read_at(fh, offset, buf, count, datatype, status, ierror)
39
         TYPE(MPI_File), INTENT(IN) :: fh
40
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
         TYPE(*), DIMENSION(..) :: buf
42
         INTEGER, INTENT(IN) :: count
43
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
44
         TYPE(MPI_Status) :: status
45
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
46
47
     MPI_File_read_at(fh, offset, buf, count, datatype, status, ierror)
48
         TYPE(MPI_File), INTENT(IN) :: fh
```

```
INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..) :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_FILE_READ_AT(FH, OFFSET, BUF, COUNT, DATATYPE, STATUS, IERROR)
    INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
    INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
    <type> BUF(*)
                                                                                     12
                                                                                     13
    MPI_FILE_READ_AT reads a file beginning at the position specified by offset.
                                                                                     14
                                                                                     15
MPI_FILE_READ_AT_ALL(fh, offset, buf, count, datatype, status)
                                                                                     16
           fh
                                     file handle (handle)
 IN
                                                                                     18
 IN
          offset
                                     file offset (integer)
                                                                                     19
 OUT
          buf
                                     initial address of buffer (choice)
                                                                                     20
                                                                                     21
 IN
                                     number of elements in buffer (integer)
          count
                                                                                     22
                                     datatype of each buffer element (handle)
 IN
          datatype
                                                                                     23
                                     status object (Status)
 OUT
          status
                                                                                     24
                                                                                     26
C binding
int MPI_File_read_at_all(MPI_File fh, MPI_Offset offset, void *buf,
                                                                                     27
              int count, MPI_Datatype datatype, MPI_Status *status)
                                                                                     28
                                                                                     29
int MPI_File_read_at_all_c(MPI_File fh, MPI_Offset offset, void *buf,
              MPI_Count count, MPI_Datatype datatype, MPI_Status *status)
Fortran 2008 binding
                                                                                     33
MPI_File_read_at_all(fh, offset, buf, count, datatype, status, ierror)
                                                                                     34
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                     35
                                                                                     36
    TYPE(*), DIMENSION(..) :: buf
                                                                                     37
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_read_at_all(fh, offset, buf, count, datatype, status, ierror)
                                                                                     42
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                     43
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                     44
    TYPE(*), DIMENSION(..) :: buf
                                                                                     45
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                     46
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
```

```
1
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
2
     Fortran binding
3
     MPI_FILE_READ_AT_ALL(FH, OFFSET, BUF, COUNT, DATATYPE, STATUS, IERROR)
         INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
         INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
6
         <type> BUF(*)
         MPI_FILE_READ_AT_ALL is a collective version of the blocking MPI_FILE_READ_AT
9
     interface.
10
11
     MPI_FILE_WRITE_AT(fh, offset, buf, count, datatype, status)
12
13
       INOUT
                fh
                                           file handle (handle)
14
       IN
                offset
                                           file offset (integer)
15
       IN
                buf
                                           initial address of buffer (choice)
16
17
       IN
                count
                                           number of elements in buffer (integer)
18
       IN
                                           datatype of each buffer element (handle)
                datatype
19
       OUT
                status
                                           status object (Status)
20
21
     C binding
22
     int MPI_File_write_at(MPI_File fh, MPI_Offset offset, const void *buf,
23
^{24}
                   int count, MPI_Datatype datatype, MPI_Status *status)
     int MPI_File_write_at_c(MPI_File fh, MPI_Offset offset, const void *buf,
26
                   MPI_Count count, MPI_Datatype datatype, MPI_Status *status)
27
28
     Fortran 2008 binding
     MPI_File_write_at(fh, offset, buf, count, datatype, status, ierror)
29
30
         TYPE(MPI_File), INTENT(IN) :: fh
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
31
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
33
         INTEGER, INTENT(IN) :: count
34
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
35
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
36
37
     MPI_File_write_at(fh, offset, buf, count, datatype, status, ierror)
38
         TYPE(MPI_File), INTENT(IN) :: fh
39
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
41
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
42
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
43
         TYPE(MPI_Status) :: status
44
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
46
     Fortran binding
47
     MPI_FILE_WRITE_AT(FH, OFFSET, BUF, COUNT, DATATYPE, STATUS, IERROR)
         INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
```

```
INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
    <type> BUF(*)
    MPI_FILE_WRITE_AT writes a file beginning at the position specified by offset.
MPI_FILE_WRITE_AT_ALL(fh, offset, buf, count, datatype, status)
  INOUT
           fh
                                     file handle (handle)
  IN
           offset
                                     file offset (integer)
                                     initial address of buffer (choice)
           buf
  IN
  IN
                                     number of elements in buffer (integer)
           count
                                                                                      12
  IN
           datatype
                                     datatype of each buffer element (handle)
                                                                                      13
                                                                                      14
  OUT
                                     status object (Status)
           status
                                                                                      15
                                                                                      16
C binding
int MPI_File_write_at_all(MPI_File fh, MPI_Offset offset, const void *buf,
              int count, MPI_Datatype datatype, MPI_Status *status)
                                                                                      19
int MPI_File_write_at_all_c(MPI_File fh, MPI_Offset offset,
                                                                                      20
              const void *buf, MPI_Count count, MPI_Datatype datatype,
                                                                                     21
              MPI_Status *status)
                                                                                     22
                                                                                      23
Fortran 2008 binding
MPI_File_write_at_all(fh, offset, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                      26
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                      27
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                      28
    INTEGER, INTENT(IN) :: count
                                                                                      29
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      30
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_write_at_all(fh, offset, buf, count, datatype, status, ierror)
                                                                                      33
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                     34
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                     35
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                      36
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                     37
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
                                                                                      42
MPI_FILE_WRITE_AT_ALL(FH, OFFSET, BUF, COUNT, DATATYPE, STATUS, IERROR)
                                                                                      43
    INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
                                                                                      44
    INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
                                                                                      45
    <type> BUF(*)
                                                                                      46
    MPI_FILE_WRITE_AT_ALL is a collective version of the blocking
```

MPI\_FILE\_WRITE\_AT interface.

```
MPI_FILE_IREAD_AT(fh, offset, buf, count, datatype, request)
2
       IN
                fh
                                           file handle (handle)
3
                offset
       IN
                                           file offset (integer)
4
5
       OUT
                buf
                                           initial address of buffer (choice)
6
       IN
                count
                                           number of elements in buffer (integer)
       IN
                datatype
                                           datatype of each buffer element (handle)
9
       OUT
                request
                                           request object (handle)
10
11
     C binding
12
     int MPI_File_iread_at(MPI_File fh, MPI_Offset offset, void *buf, int count,
13
                   MPI_Datatype datatype, MPI_Request *request)
14
     int MPI_File_iread_at_c(MPI_File fh, MPI_Offset offset, void *buf,
15
                   MPI_Count count, MPI_Datatype datatype, MPI_Request *request)
16
17
     Fortran 2008 binding
18
     MPI_File_iread_at(fh, offset, buf, count, datatype, request, ierror)
19
         TYPE(MPI_File), INTENT(IN) :: fh
20
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
21
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
22
         INTEGER, INTENT(IN) :: count
23
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
24
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
     MPI_File_iread_at(fh, offset, buf, count, datatype, request, ierror)
27
         TYPE(MPI_File), INTENT(IN) :: fh
28
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
29
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
30
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
31
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Request), INTENT(OUT) :: request
33
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
35
     Fortran binding
36
     MPI_FILE_IREAD_AT(FH, OFFSET, BUF, COUNT, DATATYPE, REQUEST, IERROR)
37
         INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
38
         INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
39
         <type> BUF(*)
         MPI_FILE_IREAD_AT is a nonblocking version of the MPI_FILE_READ_AT interface.
41
42
```

```
MPI_FILE_IREAD_AT_ALL(fh, offset, buf, count, datatype, request)
  IN
           fh
                                      file handle (handle)
           offset
  IN
                                      file offset (integer)
  OUT
           buf
                                      initial address of buffer (choice)
  IN
                                      number of elements in buffer (integer)
           count
  IN
           datatype
                                      datatype of each buffer element (handle)
  OUT
           request
                                      request object (handle)
C binding
                                                                                      12
int MPI_File_iread_at_all(MPI_File fh, MPI_Offset offset, void *buf,
                                                                                      13
              int count, MPI_Datatype datatype, MPI_Request *request)
                                                                                      14
int MPI_File_iread_at_all_c(MPI_File fh, MPI_Offset offset, void *buf,
                                                                                      15
              MPI_Count count, MPI_Datatype datatype, MPI_Request *request)
                                                                                      16
Fortran 2008 binding
                                                                                      18
MPI_File_iread_at_all(fh, offset, buf, count, datatype, request, ierror)
                                                                                      19
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                      20
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                      21
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
                                                                                      22
    INTEGER, INTENT(IN) :: count
                                                                                      23
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      26
MPI_File_iread_at_all(fh, offset, buf, count, datatype, request, ierror)
                                                                                      27
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                      28
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                      29
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
                                                                                      30
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                      33
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      34
                                                                                      35
Fortran binding
                                                                                      36
MPI_FILE_IREAD_AT_ALL(FH, OFFSET, BUF, COUNT, DATATYPE, REQUEST, IERROR)
                                                                                      37
    INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
    INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
                                                                                      39
    <type> BUF(*)
    MPI_FILE_IREAD_AT_ALL is a nonblocking version of MPI_FILE_READ_AT_ALL. See
Section 14.6.5 for semantics of nonblocking collective file operations.
                                                                                      42
                                                                                      43
```

```
1
     MPI_FILE_IWRITE_AT(fh, offset, buf, count, datatype, request)
2
       INOUT
                fh
                                           file handle (handle)
3
                offset
       IN
                                           file offset (integer)
4
5
                buf
                                           initial address of buffer (choice)
       IN
6
       IN
                count
                                           number of elements in buffer (integer)
       IN
                datatype
                                           datatype of each buffer element (handle)
9
       OUT
                request
                                           request object (handle)
10
11
     C binding
12
     int MPI_File_iwrite_at(MPI_File fh, MPI_Offset offset, const void *buf,
13
                    int count, MPI_Datatype datatype, MPI_Request *request)
14
     int MPI_File_iwrite_at_c(MPI_File fh, MPI_Offset offset, const void *buf,
15
                   MPI_Count count, MPI_Datatype datatype, MPI_Request *request)
16
17
     Fortran 2008 binding
18
     MPI_File_iwrite_at(fh, offset, buf, count, datatype, request, ierror)
19
         TYPE(MPI_File), INTENT(IN) :: fh
20
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
21
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
22
         INTEGER, INTENT(IN) :: count
23
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
24
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
     MPI_File_iwrite_at(fh, offset, buf, count, datatype, request, ierror)
27
         TYPE(MPI_File), INTENT(IN) :: fh
28
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
29
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
30
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
31
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Request), INTENT(OUT) :: request
33
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
35
     Fortran binding
36
     MPI_FILE_IWRITE_AT(FH, OFFSET, BUF, COUNT, DATATYPE, REQUEST, IERROR)
37
         INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
38
         INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
39
         <type> BUF(*)
         MPI_FILE_IWRITE_AT is a nonblocking version of the MPI_FILE_WRITE_AT interface.
41
```

```
MPI_FILE_IWRITE_AT_ALL(fh, offset, buf, count, datatype, request)
 INOUT
           fh
                                      file handle (handle)
           offset
 IN
                                      file offset (integer)
           buf
                                     initial address of buffer (choice)
 IN
                                     number of elements in buffer (integer)
 IN
           count
 IN
           datatype
                                     datatype of each buffer element (handle)
 OUT
           request
                                     request object (handle)
C binding
                                                                                      12
int MPI_File_iwrite_at_all(MPI_File fh, MPI_Offset offset, const void *buf,
                                                                                      13
              int count, MPI_Datatype datatype, MPI_Request *request)
                                                                                      14
int MPI_File_iwrite_at_all_c(MPI_File fh, MPI_Offset offset,
                                                                                      15
              const void *buf, MPI_Count count, MPI_Datatype datatype,
                                                                                      16
              MPI_Request *request)
                                                                                      18
Fortran 2008 binding
                                                                                      19
MPI_File_iwrite_at_all(fh, offset, buf, count, datatype, request, ierror)
                                                                                      20
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                     21
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                      22
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                      23
    INTEGER, INTENT(IN) :: count
                                                                                      24
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                      26
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      27
MPI_File_iwrite_at_all(fh, offset, buf, count, datatype, request, ierror)
                                                                                      28
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                      29
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                      30
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      33
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                     34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      35
                                                                                      36
Fortran binding
                                                                                      37
MPI_FILE_IWRITE_AT_ALL(FH, OFFSET, BUF, COUNT, DATATYPE, REQUEST, IERROR)
    INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
    INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
    <type> BUF(*)
    MPI_FILE_IWRITE_AT_ALL is a nonblocking version of MPI_FILE_WRITE_AT_ALL.
                                                                                      42
                                                                                      43
14.4.3 Data Access with Individual File Pointers
                                                                                      44
                                                                                      45
MPI maintains one individual file pointer per process per file handle. The current value
```

of this pointer implicitly specifies the offset in the data access routines described in this

section. These routines only use and update the individual file pointers maintained by MPI. The shared file pointer is not used nor updated.

The individual file pointer routines have the same semantics as the data access with explicit offset routines described in Section 14.4.2, with the following modification:

• the offset is defined to be the current value of the MPI-maintained individual file pointer.

After an individual file pointer operation is initiated, the individual file pointer is updated to point to the next etype after the last one that will be accessed. The file pointer is updated relative to the current view of the file.

If MPI\_MODE\_SEQUENTIAL mode was specified when the file was opened, it is erroneous to call the routines in this section, with the exception of MPI\_FILE\_GET\_BYTE\_OFFSET.

```
MPI_FILE_READ(fh, buf, count, datatype, status)
```

```
INOUT fh file handle (handle)
OUT buf initial address of buffer (choice)
IN count number of elements in buffer (integer)
IN datatype datatype of each buffer element (handle)
OUT status status object (Status)
```

# C binding

#### Fortran 2008 binding

```
MPI_File_read(fh, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

MPI_File_read(fh, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..) :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_FILE_READ(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
```

<type> BUF(\*)

```
MPI_FILE_READ reads a file using the individual file pointer.
Example 14.2 The following Fortran code fragment is an example of reading a file until
the end of file is reached:
    Read a preexisting input file until all data has been read.
    Call routine "process_input" if all requested data is read.
    The Fortran 90 "exit" statement exits the loop.
           bufsize, numread, totprocessed, status(MPI_STATUS_SIZE)
                                                                                       11
parameter (bufsize=100)
                                                                                       12
           localbuffer(bufsize)
                                                                                       13
real
                                                                                       14
integer (kind=MPI_OFFSET_KIND) zero
                                                                                       15
                                                                                       16
zero = 0
                                                                                       18
call MPI_FILE_OPEN(MPI_COMM_WORLD, 'myoldfile', &
                     MPI_MODE_RDONLY, MPI_INFO_NULL, myfh, ierr)
                                                                                       19
call MPI_FILE_SET_VIEW(myfh, zero, MPI_REAL, MPI_REAL, 'native', &
                                                                                       20
                         MPI_INFO_NULL, ierr)
                                                                                       21
totprocessed = 0
                                                                                       22
                                                                                       23
do
   call MPI_FILE_READ(myfh, localbuffer, bufsize, MPI_REAL, &
                                                                                       24
                        status, ierr)
                                                                                       26
   call MPI_GET_COUNT(status, MPI_REAL, numread, ierr)
   call process_input(localbuffer, numread)
                                                                                       27
   totprocessed = totprocessed + numread
                                                                                       28
   if (numread < bufsize) exit
                                                                                       29
end do
                                                                                       30
write(6, 1001) numread, bufsize, totprocessed
                                                                                       33
1001 format("No more data: read", I3, "and expected", I3, &
              "Processed total of", I6, "before terminating job.")
                                                                                       34
                                                                                       35
call MPI_FILE_CLOSE(myfh, ierr)
                                                                                       36
                                                                                       37
                                                                                       38
MPI_FILE_READ_ALL(fh, buf, count, datatype, status)
 INOUT
           fh
                                      file handle (handle)
 OUT
                                                                                       42
           buf
                                      initial address of buffer (choice)
                                                                                       43
 IN
           count
                                      number of elements in buffer (integer)
                                                                                       44
           datatype
 IN
                                      datatype of each buffer element (handle)
                                                                                       45
 OUT
                                      status object (Status)
           status
                                                                                       46
C binding
```

```
1
     int MPI_File_read_all(MPI_File fh, void *buf, int count,
2
                   MPI_Datatype datatype, MPI_Status *status)
3
     int MPI_File_read_all_c(MPI_File fh, void *buf, MPI_Count count,
                   MPI_Datatype datatype, MPI_Status *status)
5
6
     Fortran 2008 binding
7
     MPI_File_read_all(fh, buf, count, datatype, status, ierror)
         TYPE(MPI_File), INTENT(IN) :: fh
9
         TYPE(*), DIMENSION(..) :: buf
10
         INTEGER, INTENT(IN) :: count
11
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
12
         TYPE(MPI_Status) :: status
13
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
14
     MPI_File_read_all(fh, buf, count, datatype, status, ierror)
15
         TYPE(MPI_File), INTENT(IN) :: fh
16
         TYPE(*), DIMENSION(..) :: buf
17
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
19
         TYPE(MPI_Status) :: status
20
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
21
22
     Fortran binding
23
     MPI_FILE_READ_ALL(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
24
         INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
         <type> BUF(*)
26
         MPI_FILE_READ_ALL is a collective version of the blocking MPI_FILE_READ interface.
27
28
29
     MPI_FILE_WRITE(fh, buf, count, datatype, status)
30
                                           file handle (handle)
       INOUT
31
32
       IN
                buf
                                           initial address of buffer (choice)
33
       IN
                                           number of elements in buffer (integer)
                count
34
       1N
                datatype
                                           datatype of each buffer element (handle)
35
36
       OUT
                status
                                           status object (Status)
37
38
     C binding
39
     int MPI_File_write(MPI_File fh, const void *buf, int count,
40
                   MPI_Datatype datatype, MPI_Status *status)
41
     int MPI_File_write_c(MPI_File fh, const void *buf, MPI_Count count,
42
                   MPI_Datatype datatype, MPI_Status *status)
43
44
     Fortran 2008 binding
45
     MPI_File_write(fh, buf, count, datatype, status, ierror)
46
         TYPE(MPI_File), INTENT(IN) :: fh
47
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
```

```
INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_write(fh, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                     12
                                                                                     13
Fortran binding
                                                                                     14
MPI_FILE_WRITE(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
                                                                                     15
    INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
                                                                                     16
    <type> BUF(*)
    MPI_FILE_WRITE writes a file using the individual file pointer.
                                                                                     18
                                                                                     19
                                                                                     20
MPI_FILE_WRITE_ALL(fh, buf, count, datatype, status)
                                                                                     21
 INOUT
           fh
                                     file handle (handle)
                                                                                     22
                                     initial address of buffer (choice)
 IN
           buf
                                                                                     23
                                     number of elements in buffer (integer)
 IN
           count
 IN
                                     datatype of each buffer element (handle)
           datatype
                                                                                     26
 OUT
           status
                                     status object (Status)
                                                                                     27
                                                                                     28
                                                                                     29
C binding
                                                                                     30
int MPI_File_write_all(MPI_File fh, const void *buf, int count,
              MPI_Datatype datatype, MPI_Status *status)
int MPI_File_write_all_c(MPI_File fh, const void *buf, MPI_Count count,
                                                                                     33
              MPI_Datatype datatype, MPI_Status *status)
                                                                                     34
                                                                                     35
Fortran 2008 binding
                                                                                     36
MPI_File_write_all(fh, buf, count, datatype, status, ierror)
                                                                                     37
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
                                                                                     42
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                     43
MPI_File_write_all(fh, buf, count, datatype, status, ierror)
                                                                                     44
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                     45
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                     46
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
```

```
1
         TYPE(MPI_Status) :: status
2
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
     MPI_FILE_WRITE_ALL(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
5
         INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
6
         <type> BUF(*)
         MPI_FILE_WRITE_ALL is a collective version of the blocking MPI_FILE_WRITE inter-
9
     face.
10
11
     MPI_FILE_IREAD(fh, buf, count, datatype, request)
12
13
       INOUT
                fh
                                           file handle (handle)
14
       OUT
                buf
                                           initial address of buffer (choice)
15
       IN
                                           number of elements in buffer (integer)
                count
16
17
       IN
                                           datatype of each buffer element (handle)
                datatype
18
       OUT
                                           request object (handle)
                request
19
20
     C binding
21
     int MPI_File_iread(MPI_File fh, void *buf, int count,
22
                   MPI_Datatype datatype, MPI_Request *request)
23
24
     int MPI_File_iread_c(MPI_File fh, void *buf, MPI_Count count,
25
                   MPI_Datatype datatype, MPI_Request *request)
26
     Fortran 2008 binding
27
     MPI_File_iread(fh, buf, count, datatype, request, ierror)
28
         TYPE(MPI_File), INTENT(IN) :: fh
29
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
30
         INTEGER, INTENT(IN) :: count
31
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Request), INTENT(OUT) :: request
33
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
35
     MPI_File_iread(fh, buf, count, datatype, request, ierror)
36
         TYPE(MPI_File), INTENT(IN) :: fh
37
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Request), INTENT(OUT) :: request
41
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
42
     Fortran binding
43
     MPI_FILE_IREAD(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)
44
         INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
45
         <type> BUF(*)
46
47
         MPI_FILE_IREAD is a nonblocking version of the MPI_FILE_READ interface.
```

```
Example 14.3 The following Fortran code fragment illustrates file pointer update seman-
tics:
!
    Read the first twenty real words in a file into two local
    buffers. Note that when the first MPI_FILE_IREAD returns,
    the file pointer has been updated to point to the
    eleventh real word in the file.
          bufsize, req1, req2
integer
integer, dimension(MPI_STATUS_SIZE) :: status1, status2
parameter (bufsize=10)
                                                                                      11
          buf1(bufsize), buf2(bufsize)
real
                                                                                      12
integer (kind=MPI_OFFSET_KIND) zero
                                                                                      13
                                                                                      14
zero = 0
                                                                                      15
call MPI_FILE_OPEN(MPI_COMM_WORLD, 'myoldfile', &
                                                                                      16
                    MPI_MODE_RDONLY, MPI_INFO_NULL, myfh, ierr)
call MPI_FILE_SET_VIEW(myfh, zero, MPI_REAL, MPI_REAL, 'native', &
                                                                                      18
                         MPI_INFO_NULL, ierr)
                                                                                      19
call MPI_FILE_IREAD(myfh, buf1, bufsize, MPI_REAL, &
                                                                                      20
                     req1, ierr)
                                                                                      21
call MPI_FILE_IREAD(myfh, buf2, bufsize, MPI_REAL,
                                                                                      22
                     req2, ierr)
                                                                                      23
                                                                                      24
call MPI_WAIT(req1, status1, ierr)
call MPI_WAIT(req2, status2, ierr)
                                                                                      26
                                                                                      27
call MPI_FILE_CLOSE(myfh, ierr)
                                                                                      28
                                                                                      29
                                                                                      30
MPI_FILE_IREAD_ALL(fh, buf, count, datatype, request)
 INOUT
                                      file handle (handle)
           fh
                                                                                      33
  OUT
           buf
                                      initial address of buffer (choice)
                                                                                      34
                                                                                      35
 ĬΝ
                                      number of elements in buffer (integer)
           count
                                                                                      36
 IN
                                      datatype of each buffer element (handle)
           datatype
                                                                                      37
 OUT
           request
                                      request object (handle)
                                                                                      38
                                                                                      39
C binding
int MPI_File_iread_all(MPI_File fh, void *buf, int count,
                                                                                      42
              MPI_Datatype datatype, MPI_Request *request)
                                                                                      43
int MPI_File_iread_all_c(MPI_File fh, void *buf, MPI_Count count,
                                                                                      44
              MPI_Datatype datatype, MPI_Request *request)
                                                                                      45
                                                                                      46
Fortran 2008 binding
MPI_File_iread_all(fh, buf, count, datatype, request, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
```

```
1
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
2
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Request), INTENT(OUT) :: request
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
     MPI_File_iread_all(fh, buf, count, datatype, request, ierror)
         TYPE(MPI_File), INTENT(IN) :: fh
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
9
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
10
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
11
         TYPE(MPI_Request), INTENT(OUT) :: request
12
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
14
     Fortran binding
15
     MPI_FILE_IREAD_ALL(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)
16
         INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
17
         <type> BUF(*)
18
         MPI_FILE_IREAD_ALL is a nonblocking version of MPI_FILE_READ_ALL.
19
20
21
     MPI_FILE_IWRITE(fh, buf, count, datatype, request)
22
       INOUT
                                           file handle (handle)
23
^{24}
       IN
                buf
                                           initial address of buffer (choice)
       IN
                count
                                           number of elements in buffer (integer)
26
       IN
                                           datatype of each buffer element (handle)
                datatype
27
28
       OUT
                request
                                           request object (handle)
29
30
     C binding
31
     int MPI_File_iwrite(MPI_File fh, const void *buf, int count,
32
                   MPI_Datatype datatype, MPI_Request *request)
33
     int MPI_File_iwrite_c(MPI_File fh, const void *buf, MPI_Count count,
34
                   MPI_Datatype datatype, MPI_Request *request)
35
36
     Fortran 2008 binding
37
     MPI_File_iwrite(fh, buf, count, datatype, request, ierror)
38
         TYPE(MPI_File), INTENT(IN) :: fh
39
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
         INTEGER, INTENT(IN) :: count
41
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
42
         TYPE(MPI_Request), INTENT(OUT) :: request
43
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
44
     MPI_File_iwrite(fh, buf, count, datatype, request, ierror)
45
         TYPE(MPI_File), INTENT(IN) :: fh
46
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
47
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
```

```
TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_FILE_IWRITE(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)
    INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
    <type> BUF(*)
    MPI_FILE_IWRITE is a nonblocking version of the MPI_FILE_WRITE interface.
                                                                                     11
MPI_FILE_IWRITE_ALL(fh, buf, count, datatype, request)
                                                                                     12
                                                                                     13
 INOUT
           fh
                                     file handle (handle)
                                                                                     14
 IN
           buf
                                     initial address of buffer (choice)
                                                                                     15
                                     number of elements in buffer (integer)
 IN
           count
                                                                                     16
 IN
                                     datatype of each buffer element (handle)
           datatype
                                                                                     18
 OUT
           request
                                     request object (handle)
                                                                                     19
                                                                                     20
C binding
                                                                                     21
int MPI_File_iwrite_all(MPI_File fh, const void *buf, int count,
                                                                                     22
              MPI_Datatype datatype, MPI_Request *request)
                                                                                     23
int MPI_File_iwrite_all_c(MPI_File fh, const void *buf, MPI_Count count,
              MPI_Datatype datatype, MPI_Request *request)
                                                                                     26
Fortran 2008 binding
                                                                                     27
MPI_File_iwrite_all(fh, buf, count, datatype, request, ierror)
                                                                                     28
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                     29
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                     30
    INTEGER, INTENT(IN) :: count
                                                                                     31
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                     33
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                     34
                                                                                     35
MPI_File_iwrite_all(fh, buf, count, datatype, request, ierror)
                                                                                     36
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                     37
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                     38
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                     42
Fortran binding
                                                                                     43
MPI_FILE_IWRITE_ALL(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)
                                                                                     44
    INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
                                                                                     45
    <type> BUF(*)
                                                                                     46
    MPI_FILE_IWRITE_ALL is a nonblocking version of MPI_FILE_WRITE_ALL.
```

```
MPI_FILE_SEEK(fh, offset, whence)
2
       INOUT
                                             file handle (handle)
3
                 offset
       IN
                                             file offset (integer)
5
       IN
                 whence
                                             update mode (state)
6
7
     C binding
     int MPI_File_seek(MPI_File fh, MPI_Offset offset, int whence)
9
     Fortran 2008 binding
10
     MPI_File_seek(fh, offset, whence, ierror)
11
          TYPE(MPI_File), INTENT(IN) :: fh
12
          INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
13
          INTEGER, INTENT(IN) :: whence
14
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
15
16
     Fortran binding
17
     MPI_FILE_SEEK(FH, OFFSET, WHENCE, IERROR)
18
          INTEGER FH, WHENCE, IERROR
19
          INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
20
          MPI_FILE_SEEK updates the individual file pointer according to whence, which has the
21
     following possible values:
22
23
        • MPI_SEEK_SET: the pointer is set to offset
24
        • MPI_SEEK_CUR: the pointer is set to the current pointer position plus offset
26
        • MPI_SEEK_END: the pointer is set to the end of file plus offset
27
28
         The offset can be negative, which allows seeking backwards. It is erroneous to seek to
29
     a negative position in the view.
30
31
32
     MPI_FILE_GET_POSITION(fh, offset)
33
       IN
                 fh
                                             file handle (handle)
34
       OUT
                 offset
                                             offset of individual pointer (integer)
35
36
37
     C binding
38
     int MPI_File_get_position(MPI_File fh, MPI_Offset *offset)
39
     Fortran 2008 binding
40
     MPI_File_get_position(fh, offset, ierror)
41
          TYPE(MPI_File), INTENT(IN) :: fh
42
          INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: offset
43
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
44
45
     Fortran binding
46
     MPI_FILE_GET_POSITION(FH, OFFSET, IERROR)
47
          INTEGER FH, IERROR
          INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
```

MPI\_FILE\_GET\_POSITION returns, in offset, the current position of the individual file pointer in etype units relative to the current view.

Advice to users. The offset can be used in a future call to MPI\_FILE\_SEEK using whence = MPI\_SEEK\_SET to return to the current position. To set the displacement to the current file pointer position, first convert offset into an absolute byte position using MPI\_FILE\_GET\_BYTE\_OFFSET, then call MPI\_FILE\_SET\_VIEW with the resulting displacement. (End of advice to users.)

 $\frac{44}{45}$ 

# MPI\_FILE\_GET\_BYTE\_OFFSET(fh, offset, disp)

```
IN fh file handle (handle)
IN offset offset (integer)
OUT disp absolute byte position of offset (integer)
```

#### C binding

# Fortran 2008 binding

```
MPI_File_get_byte_offset(fh, offset, disp, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: disp
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

## Fortran binding

```
MPI_FILE_GET_BYTE_OFFSET(FH, OFFSET, DISP, IERROR)
    INTEGER FH, IERROR
    INTEGER(KIND=MPI_OFFSET_KIND) OFFSET, DISP
```

MPI\_FILE\_GET\_BYTE\_OFFSET converts a view-relative offset into an absolute byte position. The absolute byte position (from the beginning of the file) of offset relative to the current view of fh is returned in disp.

#### 14.4.4 Data Access with Shared File Pointers

MPI maintains exactly one shared file pointer per collective MPI\_FILE\_OPEN (shared among processes in the communicator group). The current value of this pointer implicitly specifies the offset in the data access routines described in this section. These routines only use and update the shared file pointer maintained by MPI. The individual file pointers are not used nor updated.

The shared file pointer routines have the same semantics as the data access with explicit offset routines described in Section 14.4.2, with the following modifications:

- the offset is defined to be the current value of the MPI-maintained shared file pointer,
- the effect of multiple calls to shared file pointer routines is defined to behave as if the calls were serialized, and

• the use of shared file pointer routines is erroneous unless all processes use the same file view.

For the noncollective shared file pointer routines, the serialization ordering is not deterministic. The user needs to use other synchronization means to enforce a specific order.

After a shared file pointer operation is initiated, the shared file pointer is updated to point to the next etype after the last one that will be accessed. The file pointer is updated relative to the current view of the file.

# Noncollective Operations

11 12

47

<type> BUF(\*)

1

2

6

9

```
13
     MPI_FILE_READ_SHARED(fh, buf, count, datatype, status)
14
       INOUT
                fh
                                           file handle (handle)
15
       OUT
                buf
                                           initial address of buffer (choice)
16
17
       IN
                count
                                           number of elements in buffer (integer)
18
       IN
                datatype
                                           datatype of each buffer element (handle)
19
       OUT
                status
                                           status object (Status)
20
21
     C binding
22
     int MPI_File_read_shared(MPI_File fh, void *buf, int count,
23
                   MPI_Datatype datatype, MPI_Status *status)
24
25
     int MPI_File_read_shared_c(MPI_File fh, void *buf, MPI_Count count,
26
                   MPI_Datatype datatype, MPI_Status *status)
27
     Fortran 2008 binding
28
     MPI_File_read_shared(fh, buf, count, datatype, status, ierror)
29
30
         TYPE(MPI_File), INTENT(IN) :: fh
         TYPE(*), DIMENSION(..) :: buf
31
         INTEGER, INTENT(IN) :: count
32
33
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
34
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
35
36
     MPI_File_read_shared(fh, buf, count, datatype, status, ierror)
37
         TYPE(MPI_File), INTENT(IN) :: fh
38
         TYPE(*), DIMENSION(..) :: buf
39
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
41
         TYPE(MPI_Status) :: status
42
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
43
44
     Fortran binding
45
     MPI_FILE_READ_SHARED(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
46
         INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
```

```
MPI_FILE_READ_SHARED reads a file using the shared file pointer.
MPI_FILE_WRITE_SHARED(fh, buf, count, datatype, status)
  INOUT
           fh
                                      file handle (handle)
  IN
           buf
                                      initial address of buffer (choice)
  IN
           count
                                      number of elements in buffer (integer)
                                      datatype of each buffer element (handle)
  IN
           datatype
  OUT
           status
                                      status object (Status)
                                                                                      12
C binding
                                                                                      13
int MPI_File_write_shared(MPI_File fh, const void *buf, int count,
                                                                                      14
              MPI_Datatype datatype, MPI_Status *status)
                                                                                      15
                                                                                      16
int MPI_File_write_shared_c(MPI_File fh, const void *buf, MPI_Count count,
              MPI_Datatype datatype, MPI_Status *status)
                                                                                      18
Fortran 2008 binding
                                                                                      19
MPI_File_write_shared(fh, buf, count, datatype, status, ierror)
                                                                                      20
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                      21
    TYPE(*), DIMENSION(...), INTENT(IN) :: buf
                                                                                      22
    INTEGER, INTENT(IN) :: count
                                                                                      23
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      24
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      26
                                                                                      27
MPI_File_write_shared(fh, buf, count, datatype, status, ierror)
                                                                                      28
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                      29
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                      30
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
                                                                                      33
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      34
Fortran binding
                                                                                      35
MPI_FILE_WRITE_SHARED(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
                                                                                      36
    INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
                                                                                      37
    <type> BUF(*)
    MPI_FILE_WRITE_SHARED writes a file using the shared file pointer.
```

```
MPI_FILE_IREAD_SHARED(fh, buf, count, datatype, request)
2
       INOUT
                fh
                                           file handle (handle)
3
       OUT
                buf
                                           initial address of buffer (choice)
4
5
       IN
                                           number of elements in buffer (integer)
                count
6
       IN
                datatype
                                           datatype of each buffer element (handle)
       OUT
                request
                                           request object (handle)
8
9
10
     C binding
     int MPI_File_iread_shared(MPI_File fh, void *buf, int count,
11
                   MPI_Datatype datatype, MPI_Request *request)
12
13
     int MPI_File_iread_shared_c(MPI_File fh, void *buf, MPI_Count count,
14
                   MPI_Datatype datatype, MPI_Request *request)
15
16
     Fortran 2008 binding
17
     MPI_File_iread_shared(fh, buf, count, datatype, request, ierror)
18
         TYPE(MPI_File), INTENT(IN) :: fh
19
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
         INTEGER, INTENT(IN) :: count
20
21
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Request), INTENT(OUT) :: request
22
23
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
24
     MPI_File_iread_shared(fh, buf, count, datatype, request, ierror)
25
         TYPE(MPI_File), INTENT(IN) :: fh
26
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
27
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
28
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
29
         TYPE(MPI_Request), INTENT(OUT) :: request
30
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
31
32
     Fortran binding
33
     MPI_FILE_IREAD_SHARED(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)
34
         INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
35
         <type> BUF(*)
36
         MPI_FILE_IREAD_SHARED is a nonblocking version of the MPI_FILE_READ_SHARED
37
     interface.
38
39
```

```
MPI_FILE_IWRITE_SHARED(fh, buf, count, datatype, request)
  INOUT
          fh
                                     file handle (handle)
  IN
           buf
                                    initial address of buffer (choice)
                                    number of elements in buffer (integer)
  IN
          count
  IN
                                    datatype of each buffer element (handle)
          datatype
  OUT
          request
                                    request object (handle)
C binding
int MPI_File_iwrite_shared(MPI_File fh, const void *buf, int count,
              MPI_Datatype datatype, MPI_Request *request)
int MPI_File_iwrite_shared_c(MPI_File fh, const void *buf, MPI_Count count,
              MPI_Datatype datatype, MPI_Request *request)
Fortran 2008 binding
MPI_File_iwrite_shared(fh, buf, count, datatype, request, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_iwrite_shared(fh, buf, count, datatype, request, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_FILE_IWRITE_SHARED(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)
    INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
    <type> BUF(*)
    MPI_FILE_IWRITE_SHARED is a nonblocking version of the
MPI_FILE_WRITE_SHARED interface.
```

11

12 13

14

15 16

17 18

19

20

21

22

23 24

26

27

28

29

30

31

33

34

35 36

37

38 39

42

43

44

45

46

47

# Collective Operations

The semantics of a collective access using a shared file pointer is that the accesses to the file will be in the order determined by the ranks of the processes within the group. For each process, the location in the file at which data is accessed is the position at which the shared file pointer would be after all processes whose ranks within the group less than that of this process had accessed their data. In addition, in order to prevent subsequent shared offset accesses by the same processes from interfering with this collective access, the call might return only after all the processes within the group have initiated their accesses. When the

call returns, the shared file pointer points to the next etype accessible, according to the file view used by all processes, after the last etype requested.

2 3

1

There may be some programs in which all processes in the group need to access the file using the shared file pointer, but the program may not require that data be accessed in order of process rank. In such programs, using the shared ordered routines (e.g., MPI\_FILE\_WRITE\_ORDERED rather than MPI\_FILE\_WRITE\_SHARED) may enable an implementation to optimize access, im-

proving performance. (End of advice to users.)

10 11

12

13

14

Advice to implementors. Accesses to the data requested by all processes do not have to be serialized. Once all processes have issued their requests, locations within the file for all accesses can be computed, and accesses can proceed independently from each other, possibly in parallel. (End of advice to implementors.)

15 16

17

18

19

20 21

22

23

24 25 26

27

28 29

30

31

47 48

```
MPI_FILE_READ_ORDERED(fh, buf, count, datatype, status)
                                        file handle (handle)
 INOUT
```

OUT buf initial address of buffer (choice)

IN number of elements in buffer (integer) count

IN datatype of each buffer element (handle) datatype

status object (Status) OUT status

# C binding

```
int MPI_File_read_ordered(MPI_File fh, void *buf, int count,
             MPI_Datatype datatype, MPI_Status *status)
```

int MPI\_File\_read\_ordered\_c(MPI\_File fh, void \*buf, MPI\_Count count, MPI\_Datatype datatype, MPI\_Status \*status)

# Fortran 2008 binding

```
32
33
     MPI_File_read_ordered(fh, buf, count, datatype, status, ierror)
34
         TYPE(MPI_File), INTENT(IN) :: fh
         TYPE(*), DIMENSION(..) :: buf
35
36
         INTEGER, INTENT(IN) :: count
37
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
39
40
     MPI_File_read_ordered(fh, buf, count, datatype, status, ierror)
41
         TYPE(MPI_File), INTENT(IN) :: fh
42
         TYPE(*), DIMENSION(..) :: buf
43
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
44
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
45
         TYPE(MPI_Status) :: status
46
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_FILE_READ_ORDERED(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
    INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
    <type> BUF(*)
    MPI_FILE_READ_ORDERED is a collective version of the MPI_FILE_READ_SHARED
interface.
MPI_FILE_WRITE_ORDERED(fh, buf, count, datatype, status)
  INOUT
                                     file handle (handle)
           fh
  IN
           buf
                                     initial address of buffer (choice)
                                                                                     12
  IN
           count
                                     number of elements in buffer (integer)
                                                                                     13
  IN
           datatype
                                     datatype of each buffer element (handle)
                                                                                     14
  OUT
           status
                                     status object (Status)
                                                                                     15
                                                                                     16
C binding
                                                                                     18
int MPI_File_write_ordered(MPI_File fh, const void *buf, int count,
                                                                                     19
              MPI_Datatype datatype, MPI_Status *status)
                                                                                     20
int MPI_File_write_ordered_c(MPI_File fh, const void *buf, MPI_Count count,
                                                                                     21
              MPI_Datatype datatype, MPI_Status *status)
                                                                                     22
                                                                                     23
Fortran 2008 binding
                                                                                     24
MPI_File_write_ordered(fh, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                     26
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                     27
    INTEGER, INTENT(IN) :: count
                                                                                     28
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                     29
    TYPE(MPI_Status) :: status
                                                                                     30
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_write_ordered(fh, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                     33
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                     34
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                     35
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                     36
    TYPE(MPI_Status) :: status
                                                                                     37
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_FILE_WRITE_ORDERED(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
    INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
                                                                                     42
    <type> BUF(*)
                                                                                     43
    MPI_FILE_WRITE_ORDERED is a collective version of the MPI_FILE_WRITE_SHARED
interface.
                                                                                     45
```

47

C binding

```
1
     Seek
2
     If MPI_MODE_SEQUENTIAL mode was specified when the file was opened, it is erroneous
     to call the following two routines (MPI_FILE_SEEK_SHARED and
     MPI_FILE_GET_POSITION_SHARED).
6
7
     MPI_FILE_SEEK_SHARED(fh, offset, whence)
       INOUT
                 fh
                                              file handle (handle)
9
       IN
                 offset
                                              file offset (integer)
10
11
       IN
                 whence
                                              update mode (state)
12
13
     C binding
14
     int MPI_File_seek_shared(MPI_File fh, MPI_Offset offset, int whence)
15
16
     Fortran 2008 binding
17
     MPI_File_seek_shared(fh, offset, whence, ierror)
18
          TYPE(MPI_File), INTENT(IN) :: fh
19
          INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
20
          INTEGER, INTENT(IN) :: whence
21
          INTEGER, OPTIONAL, INTENT(OUT) :: ierror
22
     Fortran binding
23
     MPI_FILE_SEEK_SHARED(FH, OFFSET, WHENCE, IERROR)
24
          INTEGER FH, WHENCE, IERROR
25
          INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
26
27
          MPI_FILE_SEEK_SHARED updates the shared file pointer according to whence, which
28
     has the following possible values:
29
         • MPI_SEEK_SET: the pointer is set to offset
30
31
         • MPI_SEEK_CUR: the pointer is set to the current pointer position plus offset
33
         • MPI_SEEK_END: the pointer is set to the end of file plus offset
34
         MPI_FILE_SEEK_SHARED is collective; all the processes in the communicator group
35
     associated with the file handle fh must call MPI_FILE_SEEK_SHARED with the same values
36
     for offset and whence.
37
         The offset can be negative, which allows seeking backwards. It is erroneous to seek to
38
     a negative position in the view.
39
41
     MPI_FILE_GET_POSITION_SHARED(fh, offset)
42
       IN
                 fh
                                              file handle (handle)
43
44
       OUT
                 offset
                                             offset of shared pointer (integer)
45
```

int MPI\_File\_get\_position\_shared(MPI\_File fh, MPI\_Offset \*offset)

# Fortran 2008 binding

```
MPI_File_get_position_shared(fh, offset, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: offset
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

## Fortran binding

```
MPI_FILE_GET_POSITION_SHARED(FH, OFFSET, IERROR)
INTEGER FH, IERROR
INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
```

MPI\_FILE\_GET\_POSITION\_SHARED returns, in offset, the current position of the shared file pointer in etype units relative to the current view.

Advice to users. The offset can be used in a future call to MPI\_FILE\_SEEK\_SHARED using whence = MPI\_SEEK\_SET to return to the current position. To set the displacement to the current file pointer position, first convert offset into an absolute byte position using MPI\_FILE\_GET\_BYTE\_OFFSET, then call MPI\_FILE\_SET\_VIEW with the resulting displacement. (End of advice to users.)

# 14.4.5 Split Collective Data Access Routines

MPI provides a restricted form of "nonblocking collective" I/O operations for all data accesses using split collective data access routines. These routines are referred to as "split" collective routines because a single collective operation is split in two: a begin routine and an end routine. The begin routine begins the operation, much like a nonblocking data access (e.g., MPI\_FILE\_IREAD). The end routine completes the operation, much like the matching test or wait (e.g., MPI\_WAIT). As with nonblocking data access operations, the user must not use the buffer passed to a begin routine while the routine is outstanding; the operation must be completed with an end routine before it is safe to free buffers, etc.

Split collective data access operations on a file handle fh are subject to the semantic rules given below.

- On any MPI process, each file handle may have at most one active split collective operation at any time.
- Begin calls are collective over the group of processes that participated in the collective open and follow the ordering rules for collective calls.
- End calls are collective over the group of processes that participated in the collective open and follow the ordering rules for collective calls. Each end call matches the preceding begin call for the same collective operation. When an "end" call is made, exactly one unmatched "begin" call for the same operation must precede it.
- An implementation is free to implement any split collective data access routine using
  the corresponding blocking collective routine when either the begin call (e.g.,
  MPI\_FILE\_READ\_ALL\_BEGIN) or the end call (e.g., MPI\_FILE\_READ\_ALL\_END) is
  issued. The begin and end calls are provided to allow the user and MPI implementation
  to optimize the collective operation.

 According to the definitions in Section 2.4.2, the begin procedures are incomplete. They are also non-local procedures because they may or may not return before they are called in all MPI processes of the process group.

Advice to users. This is one of the exceptions in which incomplete procedures are non-local and therefore blocking. (End of advice to users.)

- Split collective operations do not match the corresponding regular collective operation. For example, in a single collective read operation, an MPI\_FILE\_READ\_ALL on one process does not match an MPI\_FILE\_READ\_ALL\_BEGIN/MPI\_FILE\_READ\_ALL\_END pair on another process.
- Split collective routines must specify a buffer in both the begin and end routines. By specifying the buffer that receives data in the end routine, we can avoid the problems described in "A Problem with Code Movements and Register Optimization," Section 19.1.17, but not all of the problems, such as those described in Sections 19.1.12, 19.1.13, and 19.1.16.
- No collective I/O operations are permitted on a file handle concurrently with a split collective access on that file handle (i.e., between the begin and end of the access). That is

```
MPI_File_read_all_begin(fh, ...);
...
MPI_File_read_all(fh, ...);
...
MPI_File_read_all_end(fh, ...);
```

is erroneous.

• In a multithreaded implementation, any split collective begin and end operation called by a process must be called from the same thread. This restriction is made to simplify the implementation in the multithreaded case. (Note that we have already disallowed having two threads begin a split collective operation on the same file handle since only one split collective operation can be active on a file handle at any time.)

The arguments for these routines have the same meaning as for the equivalent collective versions (e.g., the argument definitions for MPI\_FILE\_READ\_ALL\_BEGIN and MPI\_FILE\_READ\_ALL\_END are equivalent to the arguments for MPI\_FILE\_READ\_ALL). The begin routine (e.g., MPI\_FILE\_READ\_ALL\_BEGIN) begins a split collective operation that, when completed with the matching end routine (i.e., MPI\_FILE\_READ\_ALL\_END) produces the result as defined for the equivalent collective routine (i.e., MPI\_FILE\_READ\_ALL).

For the purpose of consistency semantics (Section 14.6.1), a matched pair of split collective data access operations (e.g., MPI\_FILE\_READ\_ALL\_BEGIN and MPI\_FILE\_READ\_ALL\_END) compose a single data access.

```
MPI_FILE_READ_AT_ALL_BEGIN(fh, offset, buf, count, datatype)
  IN
           fh
                                      file handle (handle)
           offset
  IN
                                      file offset (integer)
  OUT
           buf
                                      initial address of buffer (choice)
  IN
                                      number of elements in buffer (integer)
           count
  IN
           datatype
                                      datatype of each buffer element (handle)
C binding
int MPI_File_read_at_all_begin(MPI_File fh, MPI_Offset offset, void *buf,
              int count, MPI_Datatype datatype)
                                                                                      12
                                                                                      13
int MPI_File_read_at_all_begin_c(MPI_File fh, MPI_Offset offset, void *buf,
                                                                                      14
              MPI_Count count, MPI_Datatype datatype)
                                                                                      15
Fortran 2008 binding
                                                                                      16
                                                                                      17
MPI_File_read_at_all_begin(fh, offset, buf, count, datatype, ierror)
                                                                                      18
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                      19
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
                                                                                      20
    INTEGER, INTENT(IN) :: count
                                                                                      21
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      22
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      23
                                                                                      24
MPI_File_read_at_all_begin(fh, offset, buf, count, datatype, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                      26
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                      27
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
                                                                                      28
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                      29
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      30
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
                                                                                      33
MPI_FILE_READ_AT_ALL_BEGIN(FH, OFFSET, BUF, COUNT, DATATYPE, IERROR)
                                                                                      34
    INTEGER FH, COUNT, DATATYPE, IERROR
    INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
                                                                                      35
                                                                                      36
    <type> BUF(*)
                                                                                      37
MPI_FILE_READ_AT_ALL_END(fh, buf, status)
           fh
  IN
                                      file handle (handle)
  OUT
           buf
                                                                                      42
                                      initial address of buffer (choice)
                                                                                      43
  OUT
           status
                                      status object (Status)
                                                                                      44
                                                                                      45
C binding
int MPI_File_read_at_all_end(MPI_File fh, void *buf, MPI_Status *status)
Fortran 2008 binding
```

```
1
     MPI_File_read_at_all_end(fh, buf, status, ierror)
2
         TYPE(MPI_File), INTENT(IN) :: fh
3
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
         TYPE(MPI_Status) :: status
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
     Fortran binding
     MPI_FILE_READ_AT_ALL_END(FH, BUF, STATUS, IERROR)
         INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR
9
         <type> BUF(*)
10
11
12
     MPI_FILE_WRITE_AT_ALL_BEGIN(fh, offset, buf, count, datatype)
13
14
       INOUT
                fh
                                           file handle (handle)
15
       IN
                offset
                                           file offset (integer)
16
                buf
                                           initial address of buffer (choice)
       IN
17
18
                                          number of elements in buffer (integer)
       IN
                count
19
                                           datatype of each buffer element (handle)
       IN
                datatype
20
21
     C binding
22
     int MPI_File_write_at_all_begin(MPI_File fh, MPI_Offset offset,
23
                   const void *buf, int count, MPI_Datatype datatype)
24
     int MPI_File_write_at_all_begin_c(MPI_File fh, MPI_Offset offset,
26
                   const void *buf, MPI_Count count, MPI_Datatype datatype)
27
     Fortran 2008 binding
28
     MPI_File_write_at_all_begin(fh, offset, buf, count, datatype, ierror)
29
         TYPE(MPI_File), INTENT(IN) :: fh
30
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
31
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
         INTEGER, INTENT(IN) :: count
33
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
34
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
35
36
     MPI_File_write_at_all_begin(fh, offset, buf, count, datatype, ierror)
37
         TYPE(MPI_File), INTENT(IN) :: fh
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
39
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
41
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
42
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
43
     Fortran binding
44
     MPI_FILE_WRITE_AT_ALL_BEGIN(FH, OFFSET, BUF, COUNT, DATATYPE, IERROR)
45
         INTEGER FH, COUNT, DATATYPE, IERROR
46
         INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
47
         <type> BUF(*)
```

```
MPI_FILE_WRITE_AT_ALL_END(fh, buf, status)
  INOUT
           fh
                                      file handle (handle)
  IN
           buf
                                     initial address of buffer (choice)
  OUT
                                      status object (Status)
           status
C binding
int MPI_File_write_at_all_end(MPI_File fh, const void *buf,
              MPI_Status *status)
Fortran 2008 binding
MPI_File_write_at_all_end(fh, buf, status, ierror)
                                                                                      12
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                      13
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                      14
    TYPE(MPI_Status) :: status
                                                                                      15
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      16
Fortran binding
                                                                                      18
MPI_FILE_WRITE_AT_ALL_END(FH, BUF, STATUS, IERROR)
                                                                                      19
    INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR
                                                                                      20
    <type> BUF(*)
                                                                                      21
                                                                                      22
                                                                                      23
MPI_FILE_READ_ALL_BEGIN(fh, buf, count, datatype)
                                      file handle (handle)
  INOUT
           fh
                                                                                      26
  OUT
           buf
                                      initial address of buffer (choice)
                                                                                      27
                                      number of elements in buffer (integer)
  IN
           count
                                                                                      28
  IN
           datatype
                                      datatype of each buffer element (handle)
                                                                                      29
                                                                                      30
C binding
int MPI_File_read_all_begin(MPI_File fh, void *buf, int count,
                                                                                      33
              MPI_Datatype datatype)
                                                                                      34
int MPI_File_read_all_begin_c(MPI_File fh, void *buf, MPI_Count count,
                                                                                      35
              MPI_Datatype datatype)
                                                                                      36
                                                                                      37
Fortran 2008 binding
MPI_File_read_all_begin(fh, buf, count, datatype, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
    INTEGER, INTENT(IN) :: count
                                                                                      42
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      43
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      44
MPI_File_read_all_begin(fh, buf, count, datatype, ierror)
                                                                                      45
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                      46
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
```

```
1
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
2
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     Fortran binding
     MPI_FILE_READ_ALL_BEGIN(FH, BUF, COUNT, DATATYPE, IERROR)
          INTEGER FH, COUNT, DATATYPE, IERROR
6
         <type> BUF(*)
9
     MPI_FILE_READ_ALL_END(fh, buf, status)
10
11
       INOUT
                fh
                                            file handle (handle)
12
       OUT
                                           initial address of buffer (choice)
                buf
13
       OUT
                                           status object (Status)
                status
14
15
16
     C binding
17
     int MPI_File_read_all_end(MPI_File fh, void *buf, MPI_Status *status)
18
     Fortran 2008 binding
19
     MPI_File_read_all_end(fh, buf, status, ierror)
20
         TYPE(MPI_File), INTENT(IN) :: fh
21
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
22
         TYPE(MPI_Status) :: status
23
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
24
25
     Fortran binding
26
     MPI_FILE_READ_ALL_END(FH, BUF, STATUS, IERROR)
27
         INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR
28
          <type> BUF(*)
29
30
31
     MPI_FILE_WRITE_ALL_BEGIN(fh, buf, count, datatype)
32
       INOUT
                                            file handle (handle)
                fh
34
       IN
                buf
                                            initial address of buffer (choice)
35
       IN
                count
                                            number of elements in buffer (integer)
36
       IN
                datatype
                                            datatype of each buffer element (handle)
37
38
     C binding
39
     int MPI_File_write_all_begin(MPI_File fh, const void *buf, int count,
                    MPI_Datatype datatype)
41
42
     int MPI_File_write_all_begin_c(MPI_File fh, const void *buf,
43
                    MPI_Count count, MPI_Datatype datatype)
44
     Fortran 2008 binding
45
     MPI_File_write_all_begin(fh, buf, count, datatype, ierror)
46
47
         TYPE(MPI_File), INTENT(IN) :: fh
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
```

14.4. DATA ACCESS 681

```
INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_write_all_begin(fh, buf, count, datatype, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_FILE_WRITE_ALL_BEGIN(FH, BUF, COUNT, DATATYPE, IERROR)
                                                                                       12
                                                                                       13
    INTEGER FH, COUNT, DATATYPE, IERROR
                                                                                       14
    <type> BUF(*)
                                                                                       15
                                                                                       16
MPI_FILE_WRITE_ALL_END(fh, buf, status)
                                                                                       18
  INOUT
                                      file handle (handle)
                                                                                       19
                                      initial address of buffer (choice)
  IN
           buf
                                                                                       20
                                                                                      21
  OUT
           status
                                      status object (Status)
                                                                                      22
                                                                                      23
C binding
int MPI_File_write_all_end(MPI_File fh, const void *buf,
              MPI_Status *status)
                                                                                       26
Fortran 2008 binding
                                                                                      27
MPI_File_write_all_end(fh, buf, status, ierror)
                                                                                      28
                                                                                      29
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                      30
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       33
Fortran binding
                                                                                      34
MPI_FILE_WRITE_ALL_END(FH, BUF, STATUS, IERROR)
                                                                                      35
    INTEGER FH, STATUS (MPI_STATUS_SIZE), IERROR
                                                                                      36
    <type> BUF(*)
                                                                                      37
MPI_FILE_READ_ORDERED_BEGIN(fh, buf, count, datatype)
  INOUT
           fh
                                      file handle (handle)
                                                                                      42
  OUT
           buf
                                      initial address of buffer (choice)
                                                                                      43
  IN
           count
                                      number of elements in buffer (integer)
                                                                                      44
                                                                                       45
  IN
           datatype
                                      datatype of each buffer element (handle)
                                                                                       46
C binding
```

```
1
     int MPI_File_read_ordered_begin(MPI_File fh, void *buf, int count,
2
                   MPI_Datatype datatype)
3
     int MPI_File_read_ordered_begin_c(MPI_File fh, void *buf, MPI_Count count,
                   MPI_Datatype datatype)
5
6
     Fortran 2008 binding
7
     MPI_File_read_ordered_begin(fh, buf, count, datatype, ierror)
         TYPE(MPI_File), INTENT(IN) :: fh
9
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
10
         INTEGER, INTENT(IN) :: count
11
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
12
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
     MPI_File_read_ordered_begin(fh, buf, count, datatype,
                                                              ierror)
14
         TYPE(MPI_File), INTENT(IN) :: fh
15
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
16
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
17
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
18
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
19
20
     Fortran binding
21
     MPI_FILE_READ_ORDERED_BEGIN(FH, BUF, COUNT, DATATYPE, IERROR)
22
         INTEGER FH, COUNT, DATATYPE, IERROR
23
         <type> BUF(*)
24
26
     MPI_FILE_READ_ORDERED_END(fh, buf, status)
27
       INOUT
                                          file handle (handle)
                fh
28
29
                buf
       OUT
                                          initial address of buffer (choice)
30
       OUT
                                          status object (Status)
                status
31
32
     C binding
33
     int MPI_File_read_ordered_end(MPI_File fh, void *buf, MPI_Status *status)
34
35
     Fortran 2008 binding
36
     MPI_File_read_ordered_end(fh, buf, status, ierror)
37
         TYPE(MPI_File), INTENT(IN) :: fh
38
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
39
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
41
     Fortran binding
42
     MPI_FILE_READ_ORDERED_END(FH, BUF, STATUS, IERROR)
43
         INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR
44
         <type> BUF(*)
45
```

14.4. DATA ACCESS 683

```
MPI_FILE_WRITE_ORDERED_BEGIN(fh, buf, count, datatype)
  INOUT
           fh
                                      file handle (handle)
  IN
           buf
                                     initial address of buffer (choice)
  IN
           count
                                     number of elements in buffer (integer)
  IN
                                      datatype of each buffer element (handle)
           datatype
C binding
int MPI_File_write_ordered_begin(MPI_File fh, const void *buf, int count,
              MPI_Datatype datatype)
int MPI_File_write_ordered_begin_c(MPI_File fh, const void *buf,
                                                                                      12
                                                                                      13
              MPI_Count count, MPI_Datatype datatype)
                                                                                      14
Fortran 2008 binding
                                                                                      15
MPI_File_write_ordered_begin(fh, buf, count, datatype, ierror)
                                                                                      16
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                      18
    INTEGER, INTENT(IN) :: count
                                                                                      19
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      20
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      21
                                                                                      22
MPI_File_write_ordered_begin(fh, buf, count, datatype, ierror)
                                                                                      23
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                      24
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                      26
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      27
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      28
Fortran binding
                                                                                      29
MPI_FILE_WRITE_ORDERED_BEGIN(FH, BUF, COUNT, DATATYPE, IERROR)
                                                                                      30
    INTEGER FH, COUNT, DATATYPE, IERROR
    <type> BUF(*)
                                                                                      33
                                                                                      34
MPI_FILE_WRITE_ORDERED_END(fh, buf, status)
                                                                                      35
                                                                                      36
  INOUT
                                      file handle (handle)
           fh
                                                                                      37
  IN
           buf
                                     initial address of buffer (choice)
  OUT
           status
                                     status object (Status)
C binding
                                                                                      42
int MPI_File_write_ordered_end(MPI_File fh, const void *buf,
                                                                                      43
              MPI_Status *status)
                                                                                      44
Fortran 2008 binding
                                                                                      45
MPI_File_write_ordered_end(fh, buf, status, ierror)
                                                                                      46
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
```

```
TYPE(MPI_Status) :: status
   INTEGER, OPTIONAL, INTENT(OUT) :: ierror

Fortran binding
MPI_FILE_WRITE_ORDERED_END(FH, BUF, STATUS, IERROR)
   INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR
   <type> BUF(*)
```

## 14.5 File Interoperability

At the most basic level, file interoperability is the ability to read the information previously written to a file—not just the bits of data, but the actual information the bits represent. MPI guarantees full interoperability within a single MPI environment, and supports increased interoperability outside that environment through the external data representation (Section 14.5.2) as well as the data conversion functions (Section 14.5.3).

Interoperability within a single MPI environment (which could be considered "operability") ensures that file data written by one MPI process can be read by any other MPI process, subject to the consistency constraints (see Section 14.6.1), provided that it would have been possible to start the two processes simultaneously and have them reside in a single MPI\_COMM\_WORLD. Furthermore, both processes must see the same data values at every absolute byte offset in the file for which data was written.

This single environment file interoperability implies that file data is accessible regardless of the number of processes.

There are three aspects to file interoperability:

- transferring the bits,
- converting between different file structures, and
- converting between different machine representations.

The first two aspects of file interoperability are beyond the scope of this standard, as both are highly machine dependent. However, transferring the bits of a file into and out of the MPI environment (e.g., by writing a file to tape) is required to be supported by all MPI implementations. In particular, an implementation must specify how familiar operations similar to POSIX cp, rm, and mv can be performed on the file. Furthermore, it is expected that the facility provided maintains the correspondence between absolute byte offsets (e.g., after possible file structure conversion, the data bits at byte offset 102 in the MPI environment are at byte offset 102 outside the MPI environment). As an example, a simple off-line conversion utility that transfers and converts files between the native file system and the MPI environment would suffice, provided it maintained the offset coherence mentioned above. In a high-quality implementation of MPI, users will be able to manipulate MPI files using the same or similar tools that the native file system offers for manipulating its files.

The remaining aspect of file interoperability, converting between different machine representations, is supported by the typing information specified in the etype and filetype. This facility allows the information in files to be shared between any two applications, regardless of whether they use MPI, and regardless of the machine architectures on which they run.

MPI supports multiple data representations: "native", "internal", and "external32". An implementation may support additional data representations. MPI also supports user-defined data representations (see Section 14.5.3). The "native" and "internal" data representations are implementation dependent, while the "external32" representation is common to all MPI implementations and facilitates file interoperability. The data representation is specified in the datarep argument to MPI\_FILE\_SET\_VIEW.

Advice to users. MPI is not guaranteed to retain knowledge of what data representation was used when a file is written. Therefore, to correctly retrieve file data, an MPI application is responsible for specifying the same data representation as was used to create the file. (End of advice to users.)

"native" Data in this representation is stored in a file exactly as it is in memory. The advantage of this data representation is that data precision and I/O performance are not lost in type conversions with a purely homogeneous environment. The disadvantage is the loss of transparent interoperability within a heterogeneous MPI environment.

Advice to users. This data representation should only be used in a homogeneous MPI environment, or when the MPI application is capable of performing the data type conversions itself. (*End of advice to users*.)

Advice to implementors. When implementing read and write operations on top of MPI message-passing, the message data should be typed as MPI\_BYTE to ensure that the message routines do not perform any type conversions on the data. (End of advice to implementors.)

"internal" This data representation can be used for I/O operations in a homogeneous or heterogeneous environment; the implementation will perform type conversions if necessary. The implementation is free to store data in any format of its choice, with the restriction that it will maintain constant extents for all predefined datatypes in any one file. The environment in which the resulting file can be reused is implementation-defined and must be documented by the implementation.

Rationale. This data representation allows the implementation to perform I/O efficiently in a heterogeneous environment, though with implementation-defined restrictions on how the file can be reused. (*End of rationale*.)

Advice to implementors. Since "external32" is a superset of the functionality provided by "internal", an implementation may choose to implement "internal" as "external32". (End of advice to implementors.)

"external32" This data representation states that read and write operations convert all data from and to the "external32" representation defined in Section 14.5.2. The data conversion rules for communication also apply to these conversions (see Section 3.3.2). The data on the storage medium is always in this canonical representation, and the data in memory is always in the local process's native representation.

This data representation has several advantages. First, all processes reading the file in a heterogeneous MPI environment will automatically have the data converted to their respective native representations. Second, the file can be exported from one MPI

 environment and imported into any other MPI environment with the guarantee that the second environment will be able to read all the data in the file.

The disadvantage of this data representation is that data precision and I/O performance may be lost in data type conversions.

Advice to implementors. When implementing read and write operations on top of MPI message-passing, the message data should be converted to and from the "external32" representation in the client, and sent as type MPI\_BYTE. This will avoid possible double data type conversions and the associated further loss of precision and performance. (End of advice to implementors.)

## 14.5.1 Datatypes for File Interoperability

If the file data representation is other than "native", care must be taken in constructing etypes and filetypes. Any of the datatype constructor functions may be used; however, for those functions that accept displacements in bytes, the displacements must be specified in terms of their values in the file for the file data representation being used. MPI will interpret these byte displacements as is; no scaling will be done. The function

MPI\_FILE\_GET\_TYPE\_EXTENT can be used to calculate the extents of datatypes in the file. For etypes and filetypes that are portable datatypes (see Section 2.4), MPI will scale any displacements in the datatypes to match the file data representation. Datatypes passed as arguments to read/write routines specify the data layout in memory; therefore, they must always be constructed using displacements corresponding to displacements in memory.

Advice to users. One can logically think of the file as if it were stored in the memory of a file server. The etype and filetype are interpreted as if they were defined at this file server, by the same sequence of calls used to define them at the calling process. If the data representation is "native", then this logical file server runs on the same architecture as the calling process, so that these types define the same data layout on the file as they would define in the memory of the calling process. If the etype and filetype are portable datatypes, then the data layout defined in the file is the same as would be defined in the calling process memory, up to a scaling factor. The routine MPI\_FILE\_GET\_TYPE\_EXTENT can be used to calculate this scaling factor. Thus, two equivalent, portable datatypes will define the same data layout in the file, even in a heterogeneous environment with "internal", "external32", or user defined data representations. Otherwise, the etype and filetype must be constructed so that their typemap and extent are the same on any architecture. This can be achieved if they have an explicit upper bound and lower bound (defined using MPI\_TYPE\_CREATE\_RESIZED). This condition must also be fulfilled by any datatype

MPI\_TYPE\_CREATE\_RESIZED). This condition must also be fulfilled by any datatype that is used in the construction of the etype and filetype, if this datatype is replicated contiguously, either explicitly, by a call to MPI\_TYPE\_CONTIGUOUS, or implicitly, by a blocklength argument that is greater than one. If an etype or filetype is not portable, and has a typemap or extent that is architecture dependent, then the data layout specified by it on a file is implementation dependent.

File data representations other than "native" may be different from corresponding data representations in memory. Therefore, for these file data representations, it is important not to use hardwired byte offsets for file positioning, including the initial displacement that specifies the view. When a portable datatype (see Section 2.4) is

5

11

12 13

14

15 16

18

19 20

21

22

23

24

25

26

27

28 29

30

31

33

34

35

36

37

38

42

43 44

45

46

47

used in a data access operation, any holes in the datatype are scaled to match the data representation. However, note that this technique only works when all the processes that created the file view build their etypes from the same predefined datatypes. For example, if one process uses an etype built from MPI\_INT and another uses an etype built from MPI\_FLOAT, the resulting views may be nonportable because the relative sizes of these types may differ from one data representation to another. (*End of advice to users*.)

```
MPI_FILE_GET_TYPE_EXTENT(fh, datatype, extent)
          fh
 IN
                                    file handle (handle)
 IN
          datatype
                                    datatype (handle)
 OUT
          extent
                                    datatype extent (integer)
C binding
int MPI_File_get_type_extent(MPI_File fh, MPI_Datatype datatype,
             MPI_Aint *extent)
int MPI_File_get_type_extent_c(MPI_File fh, MPI_Datatype datatype,
             MPI_Count *extent)
Fortran 2008 binding
MPI_File_get_type_extent(fh, datatype, extent, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: extent
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_get_type_extent(fh, datatype, extent, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: extent
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_FILE_GET_TYPE_EXTENT(FH, DATATYPE, EXTENT, IERROR)
    INTEGER FH, DATATYPE, IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTENT
```

Returns the extent of datatype in the file fh. This extent will be the same for all processes accessing the file fh. If the current view uses a user-defined data representation (see Section 14.5.3), MPI uses the dtype\_file\_extent\_fn callback to calculate the extent.

If the datatype extent cannot be represented in extent, it is set to MPI\_UNDEFINED.

Advice to implementors. In the case of user-defined data representations, the extent of a derived datatype can be calculated by first determining the extents of the predefined datatypes in this derived datatype using dtype\_file\_extent\_fn (see Section 14.5.3). (End of advice to implementors.)

#### 14.5.2 External Data Representation: "external32"

All MPI implementations are required to support the data representation defined in this section. Support of optional datatypes (e.g., MPI\_INTEGER2) is not required.

All floating point values are in big-endian IEEE format [42] of the appropriate size. Floating point values are represented by one of three IEEE formats. These are the IEEE "Single (binary32)," "Double (binary64)," and "Double Extended (binary128)" formats, requiring 4, 8, and 16 bytes of storage, respectively. For the IEEE "Double Extended (binary128)" formats, MPI specifies a Format Width of 16 bytes, with 15 exponent bits, bias = +16383, 112 fraction bits, and an encoding analogous to the "Double (binary64)" format. All integral values are in two's complement big-endian format. Big-endian means most significant byte at lowest address byte. For C \_Bool, Fortran LOGICAL, and C++ bool, 0 implies false and nonzero implies true. C float \_Complex, double \_Complex, and long double \_Complex, Fortran COMPLEX and DOUBLE COMPLEX, and other complex types are represented by a pair of floating point format values for the real and imaginary components. Characters are in ISO 8859-1 format [43]. Wide characters (of type MPI\_WCHAR) are in Unicode format [68].

All signed numerals (e.g., MPI\_INT, MPI\_REAL) have the sign bit at the most significant bit. MPI\_COMPLEX and MPI\_DOUBLE\_COMPLEX have the sign bit of the real and imaginary parts at the most significant bit of each part.

According to IEEE specifications [42], the "NaN" (not a number) is system dependent. It should not be interpreted within MPI as anything other than "NaN."

Advice to implementors. The MPI treatment of "NaN" is similar to the approach used in XDR [65]. (End of advice to implementors.)

All data is byte aligned, regardless of type. All data items are stored contiguously in the file (if the file view is contiguous).

Advice to implementors. All bytes of LOGICAL and bool must be checked to determine the value. (End of advice to implementors.)

Advice to users. The type MPI\_PACKED is treated as bytes and is not converted. The user should be aware that MPI\_PACK has the option of placing a header in the beginning of the pack buffer. (*End of advice to users.*)

The sizes of the predefined datatypes returned from MPI\_TYPE\_CREATE\_F90\_REAL, MPI\_TYPE\_CREATE\_F90\_COMPLEX, and MPI\_TYPE\_CREATE\_F90\_INTEGER are defined in Section 19.1.9, page 801.

Advice to implementors. When converting a larger size integer to a smaller size integer, only the least significant bytes are moved. Care must be taken to preserve the sign bit value. This allows no conversion errors if the data range is within the range of the smaller size integer. (End of advice to implementors.)

Table 14.2, 14.3, and 14.4 specify the sizes of predefined, optional, and C++ datatypes in "external32" format, respectively.

Predefined Type	Length	1
MPI_PACKED	1	2
MPI_BYTE	1	3
MPI_CHAR	1	4
MPI_UNSIGNED_CHAR	1	5
MPI_SIGNED_CHAR	1	6
MPI_WCHAR	2	7
MPI_SHORT	2	8
MPI_UNSIGNED_SHORT	2	9
MPI_INT	4	10
MPI_LONG	4	11
MPI_UNSIGNED	4	12
MPI_UNSIGNED_LONG	4	13
MPI_LONG_LONG_INT	8	14
MPI_UNSIGNED_LONG_LONG	8	15
MPI_FLOAT	4	16
MPI_DOUBLE	8	17
MPI_LONG_DOUBLE	16	18
MPI_C_BOOL	1	19
MPI_INT8_T	1	20
MPI_INT16_T	2	2
MPI_INT32_T	4	22
MPI_INT64_T	8	23
MPI_UINT8_T	1	24
MPI_UINT16_T	2	25
MPI_UINT32_T	4	26
MPI_UINT64_T	8	27
MPI_AINT	8	28
MPI_COUNT	8	29
MPI_OFFSET	8	30
MPI_C_COMPLEX	2*4	3
MPI_C_FLOAT_COMPLEX	2*4	32
MPI_C_DOUBLE_COMPLEX	2*8	33
MPI_C_LONG_DOUBLE_COMPLEX	2*16	34
MPI_CHARACTER	1	35
MPI_LOGICAL	4	36
MPI_INTEGER	4	37
MPI_REAL	4	38
MPI_DOUBLE_PRECISION	8	39
MPI_COMPLEX	2*4	40
MPI_DOUBLE_COMPLEX	2*8	4
MPI_CXX_BOOL	1	42
MPI_CXX_FLOAT_COMPLEX	2*4	43
MPI_CXX_DOUBLE_COMPLEX	2*8	44
MPI_CXX_LONG_DOUBLE_COMPLEX	2*16	45
		46

Table 14.2: "external 32" sizes of predefined datatypes

1
2
3
4
5
6
7
8
9
10
11
12
13
14

Predefined Type	Length
MPI_INTEGER1	1
MPI_INTEGER2	2
MPI_INTEGER4	4
MPI_INTEGER8	8
MPI_INTEGER16	16
MPI_REAL2	2
MPI_REAL4	4
MPI_REAL8	8
MPI_REAL16	16
MPI_COMPLEX4	2*2
MPI_COMPLEX8	2*4
MPI_COMPLEX16	2*8
MPI_COMPLEX32	2*16
· · · · · · · · · · · · · · · · · · ·	

Table 14.3: "external32" sizes of optional datatypes

C++ Types	Length
MPI_CXX_BOOL	1
MPI_CXX_FLOAT_COMPLEX	2*4
MPI_CXX_DOUBLE_COMPLEX	2*8
MPI_CXX_LONG_DOUBLE_COMPLEX	2*16

Table 14.4: "external32" sizes of C++ datatypes

#### 14.5.3 User-Defined Data Representations

There are two situations that cannot be handled by the required representations:

- 1. a user wants to write a file in a representation unknown to the implementation, and
- 2. a user wants to read a file written in a representation unknown to the implementation.

User-defined data representations allow the user to insert a third party converter into the I/O stream to do the data representation conversion.

```
MPI_REGISTER_DATAREP(datarep, read_conversion_fn, write_conversion_fn, dtype_file_extent_fn, extra_state)
```

IN	datarep	data representation identifier (string)
IN	read_conversion_fn	function invoked to convert from file representation to native representation (function)
IN	write_conversion_fn	function invoked to convert from native representation to file representation (function)
IN	dtype_file_extent_fn	function invoked to get the extent of a data type as represented in the file (function)
IN	extra_state	extra state

#### C binding

#### Fortran 2008 binding

14

15

16

17

18

19

20

21

22

23

24

25 26

27

28

29 30

31

32 33

34

35

36

37

38

39

41

42

43

44 45

46

47

```
PROCEDURE(MPI_Datarep_conversion_function_c), INTENT(IN) ::
2
                   read_conversion_fn, write_conversion_fn
3
         PROCEDURE(MPI_Datarep_extent_function) :: dtype_file_extent_fn
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
     Fortran binding
     MPI_REGISTER_DATAREP(DATAREP, READ_CONVERSION_FN, WRITE_CONVERSION_FN,
8
                  DTYPE_FILE_EXTENT_FN, EXTRA_STATE, IERROR)
9
         CHARACTER*(*) DATAREP
10
         EXTERNAL READ_CONVERSION_FN, WRITE_CONVERSION_FN, DTYPE_FILE_EXTENT_FN
11
         INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
12
         INTEGER IERROR
13
```

The call associates read\_conversion\_fn, write\_conversion\_fn, and dtype\_file\_extent\_fn with the data representation identifier datarep. datarep can then be used as an argument to MPI\_FILE\_SET\_VIEW, causing subsequent data access operations to call the conversion functions to convert all data items accessed between file data representation and native representation. MPI\_REGISTER\_DATAREP is a local operation and only registers the data representation for the calling MPI process. If datarep is already defined, an error in the error class MPI\_ERR\_DUP\_DATAREP is raised using the default file error handler (see Section 14.7). The length of a data representation string is limited to the value of MPI\_MAX\_DATAREP\_STRING. MPI\_MAX\_DATAREP\_STRING must have a value of at least 64. No routines are provided to delete data representations and free the associated resources; it is not expected that an application will generate them in significant numbers.

#### Extent Callback

```
typedef int MPI_Datarep_extent_function(MPI_Datatype datatype,
             MPI_Aint *extent, void *extra_state);
ABSTRACT INTERFACE
 SUBROUTINE MPI_Datarep_extent_function(datatype, extent, extra_state,
    TYPE(MPI_Datatype) :: datatype
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extent, extra_state
   INTEGER :: ierror
SUBROUTINE DATAREP_EXTENT_FUNCTION(DATATYPE, EXTENT, EXTRA_STATE, IERROR)
   INTEGER DATATYPE, IERROR
```

INTEGER(KIND=MPI\_ADDRESS\_KIND) EXTENT, EXTRA\_STATE

The function dtype\_file\_extent\_fn must return, in file\_extent, the number of bytes required to store datatype in the file representation. The function is passed, in extra\_state, the argument that was passed to the MPI\_REGISTER\_DATAREP call. MPI will only call this routine with predefined datatypes employed by the user.

Rationale. This callback does not have a large count variant because it is anticipated that large counts will not be required to represent the extent output value. (End of rationale.)

Done

in PR449

47

\mpicallbackmain{MPI\\_Datarep\\_conversion\\_function}\mpicallbackmainindex{MPI\\_Datarep\\_conversion\\_function\\_c}

```
MPI_DATAREP_CONVERSION_FUNCTION also supports large count types in separate
additional MPI procedures in C (suffixed with the "_c") and interface polymorphism in
                                                                                       #-other
Fortran when using USE mpi_f08.
                                                                                   This is a callback
    If the extent cannot be represented in extent, the callback function shall set extent to
                                                                                   prototype, use
MPI_UNDEFINED. The MPI implementation will then raise an error of class
                                                                                   correct macro!
MPI_ERR_VALUE_TOO_LARGE.
Datarep Conversion Functions
typedef int MPI_Datarep_conversion_function(void *userbuf,
              MPI_Datatype datatype, int count, void *filebuf,
              MPI_Offset position, void *extra_state);
                                                                                     12
                                                                                     13
typedef int MPI_Datarep_conversion_function_c(void *userbuf,
                                                                                     14
              MPI_Datatype datatype, MPI_Count count, void *filebuf,
              MPI_Offset position, void *extra_state);
                                                                                     16
ABSTRACT INTERFACE
  SUBROUTINE MPI_Datarep_conversion_function(userbuf, datatype, count,
                                                                                     18
               filebuf, position, extra_state, ierror)
                                                                                     19
    USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
                                                                                     20
    TYPE(C_PTR), VALUE :: userbuf, filebuf
                                                                                     21
    TYPE(MPI_Datatype) :: datatype
                                                                                     22
    INTEGER :: count, ierror
                                                                                     23
    INTEGER(KIND=MPI_OFFSET_KIND) :: position
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state
                                                                                     26
ABSTRACT INTERFACE
                                                                                     27
  SUBROUTINE MPI_Datarep_conversion_function_c(userbuf, datatype, count,
                                                                                     28
               filebuf, position, extra_state, ierror)
                                                                                     29
    USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
                                                                                     30
    TYPE(C_PTR), VALUE :: userbuf, filebuf
    TYPE(MPI_Datatype) :: datatype
    INTEGER(KIND=MPI_COUNT_KIND) :: count
    INTEGER(KIND=MPI_OFFSET_KIND) :: position
                                                                                     34
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state
                                                                                     35
    INTEGER :: ierror
SUBROUTINE DATAREP_CONVERSION_FUNCTION(USERBUF, DATATYPE, COUNT, FILEBUF,
                                                                                     37
              POSITION, EXTRA_STATE, IERROR)
    <TYPE> USERBUF(*), FILEBUF(*)
    INTEGER DATATYPE, COUNT, IERROR
    INTEGER(KIND=MPI_OFFSET_KIND) POSITION
                                                                                     41
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
                                                                                     42
                                                                                     43
    The function read_conversion_fn must convert from file data representation to na-
                                                                                     44
tive representation. Before calling this routine, MPI allocates and fills filebuf with count
                                                                                     45
contiguous data items. The type of each data item matches the corresponding entry for the
```

predefined datatype in the type signature of datatype. The function is passed, in extra\_state,

the argument that was passed to the MPI\_REGISTER\_DATAREP call. The function must

copy all count data items from filebuf to userbuf in the distribution described by datatype, converting each data item from file representation to native representation. datatype will be equivalent to the datatype that the user passed to the read function. If the size of datatype is less than the size of the count data items, the conversion function must treat datatype as being contiguously tiled over the userbuf. The conversion function must begin storing converted data at the location in userbuf specified by position into the (tiled) datatype.

Advice to users. Although the conversion functions have similarities to MPI\_PACK and MPI\_UNPACK, one should note the differences in the use of the arguments count and position. In the conversion functions, count is a count of data items (i.e., count of typemap entries of datatype), and position is an index into this typemap. In MPI\_PACK, incount refers to the number of whole datatypes, and position is a number of bytes. (End of advice to users.)

Advice to implementors. A converted read operation could be implemented as follows:

- 1. Get file extent of all data items
- 2. Allocate a filebuf large enough to hold all count data items
- 3. Read data from file into filebuf
- 4. Call read\_conversion\_fn to convert data and place it into userbuf
- 5. Deallocate filebuf

(End of advice to implementors.)

If MPI cannot allocate a buffer large enough to hold all the data to be converted from a read operation, it may call the conversion function repeatedly using the same datatype and userbuf, and reading successive chunks of data to be converted in filebuf. For the first call (and in the case when all the data to be converted fits into filebuf), MPI will call the function with position set to zero. Data converted during this call will be stored in the userbuf according to the first count data items in datatype. Then in subsequent calls to the conversion function, MPI will increment the value in position by the count of items converted in the previous call, and the userbuf pointer will be unchanged.

Rationale. Passing the conversion function a position and one datatype for the transfer allows the conversion function to decode the datatype only once and cache an internal representation of it on the datatype. Then on subsequent calls, the conversion function can use the position to quickly find its place in the datatype and continue storing converted data where it left off at the end of the previous call. (End of rationale.)

Advice to users. Although the conversion function may usefully cache an internal representation on the datatype, it should not cache any state information specific to an ongoing conversion operation, since it is possible for the same datatype to be used concurrently in multiple conversion operations. (End of advice to users.)

The function write\_conversion\_fn must convert from native representation to file data representation. Before calling this routine, MPI allocates filebuf of a size large enough to hold count contiguous data items. The type of each data item matches the corresponding

entry for the predefined datatype in the type signature of datatype. The function must copy count data items from userbuf in the distribution described by datatype, to a contiguous distribution in filebuf, converting each data item from native representation to file representation. If the size of datatype is less than the size of count data items, the conversion function must treat datatype as being contiguously tiled over the userbuf.

The function must begin copying at the location in userbuf specified by position into the (tiled) datatype. datatype will be equivalent to the datatype that the user passed to the write function. The function is passed, in extra\_state, the argument that was passed to the MPI\_REGISTER\_DATAREP call.

The predefined constant MPI\_CONVERSION\_FN\_NULL may be used as either write\_conversion\_fn or read\_conversion\_fn. In that case, MPI will not attempt to invoke write\_conversion\_fn or read\_conversion\_fn, respectively, but will perform the requested data access using the native data representation.

An MPI implementation must ensure that all data accessed is converted, either by using a filebuf large enough to hold all the requested data items or else by making repeated calls to the conversion function with the same datatype argument and appropriate values for position.

An implementation will only invoke the callback routines in this section (read\_conversion\_fn, write\_conversion\_fn, and dtype\_file\_extent\_fn) when one of the read or write routines in Section 14.4, or MPI\_FILE\_GET\_TYPE\_EXTENT is called by the user. dtype\_file\_extent\_fn will only be passed predefined datatypes employed by the user. The conversion functions will only be passed datatypes equivalent to those that the user has passed to one of the routines noted above.

The conversion functions must be reentrant. User defined data representations are restricted to use byte alignment for all types. Furthermore, it is erroneous for the conversion functions to call any collective routines or to free datatype.

The conversion functions should return an error code. If the returned error code has a value other than MPI\_SUCCESS, the implementation will raise an error in the class MPI\_ERR\_CONVERSION.

### 14.5.4 Matching Data Representations

It is the user's responsibility to ensure that the data representation used to read data from a file is *compatible* with the data representation that was used to write that data to the file.

In general, using the same data representation name when writing and reading a file does not guarantee that the representation is compatible. Similarly, using different representation names on two different implementations may yield compatible representations.

Compatibility can be obtained when "external32" representation is used, although precision may be lost and the performance may be less than when "native" representation is used. Compatibility is guaranteed using "external32" provided at least one of the following conditions is met.

- The data access routines directly use types enumerated in Section 14.5.2, that are supported by all implementations participating in the I/O. The predefined type used to write a data item must also be used to read a data item.
- In the case of Fortran 90 programs, the programs participating in the data accesses obtain compatible datatypes using MPI routines that specify precision and/or range (Section 19.1.9).

• For any given data item, the programs participating in the data accesses use compatible predefined types to write and read the data item.

User-defined data representations may be used to provide an implementation compatibility with another implementation's "native" or "internal" representation.

Advice to users. Section 19.1.9 defines routines that support the use of matching datatypes in heterogeneous environments and contains examples illustrating their use. (End of advice to users.)

## 14.6 Consistency and Semantics

#### 14.6.1 File Consistency

Consistency semantics define the outcome of multiple accesses to a single file. All file accesses in MPI are relative to a specific file handle created from a collective open. MPI provides three levels of consistency: sequential consistency among all accesses using a single file handle, sequential consistency among all accesses using file handles created from a single collective open with atomic mode enabled, and user-imposed consistency among accesses other than the above. Sequential consistency means the behavior of a set of operations will be as if the operations were performed in some serial order consistent with program order; each access appears atomic, although the exact ordering of accesses is unspecified. User-imposed consistency may be obtained using program order and calls to MPI\_FILE\_SYNC.

Let  $FH_1$  be the set of file handles created from one particular collective open of the file FOO, and  $FH_2$  be the set of file handles created from a different collective open of FOO. Note that nothing restrictive is said about  $FH_1$  and  $FH_2$ : the sizes of  $FH_1$  and  $FH_2$  may be different, the groups of processes used for each open may or may not intersect, the file handles in  $FH_1$  may be destroyed before those in  $FH_2$  are created, etc. Consider the following three cases: a single file handle (e.g.,  $fh_1 \in FH_1$ ), two file handles created from a single collective open (e.g.,  $fh_{1a} \in FH_1$  and  $fh_{1b} \in FH_1$ ), and two file handles from different collective opens (e.g.,  $fh_1 \in FH_1$  and  $fh_2 \in FH_2$ ).

For the purpose of consistency semantics, a matched pair (Section 14.4.5) of split collective data access operations (e.g., MPI\_FILE\_READ\_ALL\_BEGIN and MPI\_FILE\_READ\_ALL\_END) compose a single data access operation. Similarly, a non-blocking data access routine (e.g., MPI\_FILE\_IREAD) and the routine which completes the request (e.g., MPI\_WAIT) also compose a single data access operation. For all cases below, these data access operations are subject to the same constraints as blocking data access operations.

Advice to users. For an MPI\_FILE\_IREAD and MPI\_WAIT pair, the operation begins when MPI\_FILE\_IREAD is called and ends when MPI\_WAIT returns. (End of advice to users.)

Assume that  $A_1$  and  $A_2$  are two data access operations. Let  $D_1$  ( $D_2$ ) be the set of absolute byte displacements of every byte accessed in  $A_1$  ( $A_2$ ). The two data accesses overlap if  $D_1 \cap D_2 \neq \emptyset$ . The two data accesses conflict if they overlap and at least one is a write access.

Let  $SEQ_{fh}$  be a sequence of file operations on a single file handle, bracketed by MPI\_FILE\_SYNCs on that file handle. (Both opening and closing a file implicitly perform

an MPI\_FILE\_SYNC.)  $SEQ_{fh}$  is a "write sequence" if any of the data access operations in the sequence are writes or if any of the file manipulation operations in the sequence change the state of the file (e.g., MPI\_FILE\_SET\_SIZE or MPI\_FILE\_PREALLOCATE). Given two sequences,  $SEQ_1$  and  $SEQ_2$ , we say they are not *concurrent* if one sequence is guaranteed to completely precede the other (temporally).

The requirements for guaranteeing sequential consistency among all accesses to a particular file are divided into the three cases given below. If any of these requirements are not met, then the value of all data in that file is implementation dependent.

Case 1:  $fh_1 \in FH_1$  All operations on  $fh_1$  are sequentially consistent if atomic mode is set. If nonatomic mode is set, then all operations on  $fh_1$  are sequentially consistent if they are either nonconcurrent, nonconflicting, or both.

Case 2:  $fh_{1a} \in FH_1$  and  $fh_{1b} \in FH_1$  Assume  $A_1$  is a data access operation using  $fh_{1a}$ , and  $A_2$  is a data access operation using  $fh_{1b}$ . If for any access  $A_1$ , there is no access  $A_2$  that conflicts with  $A_1$ , then MPI guarantees sequential consistency.

However, unlike POSIX semantics, the default MPI semantics for conflicting accesses do not guarantee sequential consistency. If  $A_1$  and  $A_2$  conflict, sequential consistency can be guaranteed by either enabling atomic mode via the MPI\_FILE\_SET\_ATOMICITY routine, or meeting the condition described in Case 3 below.

Case 3:  $fh_1 \in FH_1$  and  $fh_2 \in FH_2$  Consider access to a single file using file handles from distinct collective opens. In order to guarantee sequential consistency, MPI\_FILE\_SYNC must be used (both opening and closing a file implicitly perform an MPI\_FILE\_SYNC).

Sequential consistency is guaranteed among accesses to a single file if for any write sequence  $SEQ_1$  to the file, there is no sequence  $SEQ_2$  to the file which is *concurrent* with  $SEQ_1$ . To guarantee sequential consistency when there are write sequences,

MPI\_FILE\_SYNC must be used together with a mechanism that guarantees nonconcurrency of the sequences.

See the examples in Section 14.6.11 for further clarification of some of these consistency semantics.

```
MPI_FILE_SET_ATOMICITY(fh, flag)
```

```
INOUT fh file handle (handle)

IN flag true to set atomic mode, false to set nonatomic mode (logical)
```

#### C binding

```
int MPI_File_set_atomicity(MPI_File fh, int flag)
```

#### Fortran 2008 binding

```
MPI_File_set_atomicity(fh, flag, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    LOGICAL, INTENT(IN) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_FILE_SET_ATOMICITY(FH, FLAG, IERROR)
INTEGER FH, IERROR
LOGICAL FLAG
```

Let FH be the set of file handles created by one collective open. The consistency semantics for data access operations using FH is set by collectively calling

MPI\_FILE\_SET\_ATOMICITY on FH. MPI\_FILE\_SET\_ATOMICITY is collective; all processes in the group must pass identical values for fh and flag. If flag is true, atomic mode is set; if flag is false, nonatomic mode is set.

Changing the consistency semantics for an open file only affects new data accesses. All completed data accesses are guaranteed to abide by the consistency semantics in effect during their execution. Nonblocking data accesses and split collective operations that have not completed (e.g., via MPI\_WAIT) are only guaranteed to abide by nonatomic mode consistency semantics.

Advice to implementors. Since the semantics guaranteed by atomic mode are stronger than those guaranteed by nonatomic mode, an implementation is free to adhere to the more stringent atomic mode semantics for outstanding requests. (*End of advice to implementors.*)

```
MPI_FILE_GET_ATOMICITY(fh, flag)
 IN
           fh
                                     file handle (handle)
 OUT
          flag
                                     true if atomic mode, false if nonatomic mode (logical)
C binding
int MPI_File_get_atomicity(MPI_File fh, int *flag)
Fortran 2008 binding
MPI_File_get_atomicity(fh, flag, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_FILE_GET_ATOMICITY(FH, FLAG, IERROR)
```

MPI\_FILE\_GET\_ATOMICITY returns the current consistency semantics for data access operations on the set of file handles created by one collective open. If flag is true, atomic mode is enabled; if flag is false, nonatomic mode is enabled.

```
MPI_FILE_SYNC(fh)
INOUT fh file handle (handle)
```

#### C binding

INTEGER FH, IERROR

LOGICAL FLAG

```
int MPI_File_sync(MPI_File fh)
Fortran 2008 binding
MPI_File_sync(fh, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_FILE_SYNC(FH, IERROR)
INTEGER FH, IERROR
```

Calling MPI\_FILE\_SYNC with fh causes all previous writes to fh by the calling process to be transferred to the storage device. If other processes have made updates to the storage device, then all such updates become visible to subsequent reads of fh by the calling process. MPI\_FILE\_SYNC may be necessary to ensure sequential consistency in certain cases (see above).

MPI\_FILE\_SYNC is a collective operation.

The user is responsible for ensuring that all nonblocking requests and split collective operations on fh have been completed before calling MPI\_FILE\_SYNC—otherwise, the call to MPI\_FILE\_SYNC is erroneous.

#### 14.6.2 Random Access vs. Sequential Files

MPI distinguishes ordinary random access files from sequential stream files, such as pipes and tape files. Sequential stream files must be opened with the MPI\_MODE\_SEQUENTIAL flag set in the amode. For these files, the only permitted data access operations are shared file pointer reads and writes. Filetypes and etypes with holes are erroneous. In addition, the notion of file pointer is not meaningful; therefore, calls to MPI\_FILE\_SEEK\_SHARED and MPI\_FILE\_GET\_POSITION\_SHARED are erroneous, and the pointer update rules specified for the data access routines do not apply. The amount of data accessed by a data access operation will be the amount requested unless the end of file is reached or an error is raised.

Rationale. This implies that reading on a pipe will always wait until the requested amount of data is available or until the process writing to the pipe has issued an end of file. (End of rationale.)

Finally, for some sequential files, such as those corresponding to magnetic tapes or streaming network connections, writes to the file may be destructive. In other words, a write may act as a truncate (a MPI\_FILE\_SET\_SIZE with size set to the current position) followed by the write.

### 14.6.3 Progress

The progress rules of MPI are both a promise to users and a set of constraints on implementors. In cases where the progress rules restrict possible implementation choices more than the interface specification alone, the progress rules take precedence.

All blocking routines must complete in finite time unless an exceptional condition (such as resource exhaustion) causes an error.

Nonblocking data access routines inherit the following progress rule from nonblocking point to point communication: a nonblocking write is equivalent to a nonblocking send for

which a receive is eventually posted, and a nonblocking read is equivalent to a nonblocking receive for which a send is eventually posted.

Finally, an implementation is free to delay progress of collective routines until all processes in the group associated with the collective call have invoked the routine. Once all processes in the group have invoked the routine, the progress rule of the equivalent noncollective routine must be followed.

#### 14.6.4 Collective File Operations

Collective file operations are subject to the same restrictions as collective communication operations. For a complete discussion, please refer to the semantics set forth in Section 6.14.

Collective file operations are collective over a duplicate of the communicator used to open the file—this duplicate communicator is implicitly specified via the file handle argument. Different processes can pass different values for other arguments of a collective routine unless specified otherwise.

#### 14.6.5 Nonblocking Collective File Operations

Nonblocking collective file operations are defined only for data access routines with explicit offsets and individual file pointers but not with shared file pointers.

Nonblocking collective file operations are subject to the same restrictions as blocking collective I/O operations. All processes belonging to the group of the communicator that was used to open the file must call collective I/O operations (blocking and nonblocking) in the same order. This is consistent with the ordering rules for collective operations in threaded environments. For a complete discussion, please refer to the semantics set forth in Section 6.14.

Nonblocking collective I/O operations do not match with blocking collective I/O operations. Multiple nonblocking collective I/O operations can be outstanding on a single file handle. High quality MPI implementations should be able to support a large number of pending nonblocking I/O operations.

All nonblocking collective I/O calls are local and return immediately, irrespective of the status of other processes. The call initiates the operation which may progress independently of any communication, computation, or I/O. The call returns a request handle, which must be passed to a completion call. Input buffers should not be modified and output buffers should not be accessed before the completion call returns. The same progress rules described for nonblocking collective operations apply for nonblocking collective I/O operations. For a complete discussion, please refer to the semantics set forth in Section 6.12.

#### 14.6.6 Type Matching

The type matching rules for I/O mimic the type matching rules for communication with one exception: if etype is MPI\_BYTE, then this matches any datatype in a data access operation. In general, the etype of data items written must match the etype used to read the items, and for each data access operation, the current etype must also match the type declaration of the data access buffer.

Advice to users. In most cases, use of MPI\_BYTE as a wild card will defeat the file interoperability features of MPI. File interoperability can only perform automatic

conversion between heterogeneous data representations when the exact datatypes accessed are explicitly specified. (*End of advice to users.*)

#### 14.6.7 Miscellaneous Clarifications

Once an I/O routine completes, it is safe to free any opaque objects passed as arguments to that routine. For example, the comm and info used in an MPI\_FILE\_OPEN, or the etype and filetype used in an MPI\_FILE\_SET\_VIEW, can be freed without affecting access to the file. Note that for nonblocking routines and split collective operations, the operation must be completed before it is safe to reuse data buffers passed as arguments.

As in communication, datatypes must be committed before they can be used in file manipulation or data access operations. For example, the etype and filetype must be committed before calling MPI\_FILE\_SET\_VIEW, and the datatype must be committed before calling MPI\_FILE\_READ or MPI\_FILE\_WRITE.

### 14.6.8 MPI\_Offset Type

MPI\_Offset is an integer type of size sufficient to represent the size (in bytes) of the largest file supported by MPI. Displacements and offsets are always specified as values of type MPI\_Offset.

In Fortran, the corresponding integer is an integer with kind parameter MPI\_OFFSET\_KIND, which is defined in the mpi\_f08 module, the mpi module and the mpif.h include file.

In Fortran 77 environments that do not support KIND parameters, MPI\_Offset arguments should be declared as an INTEGER of suitable size. The language interoperability implications for MPI\_Offset are similar to those for addresses (see Section 19.3).

#### 14.6.9 Logical vs. Physical File Layout

MPI specifies how the data should be laid out in a virtual file structure (the view), not how that file structure is to be stored on one or more disks. Specification of the physical file structure was avoided because it is expected that the mapping of files to disks will be system specific, and any specific control over file layout would therefore restrict program portability. However, there are still cases where some information may be necessary to optimize file layout. This information can be provided as *hints* specified via info when a file is created (see Section 14.2.8).

#### 14.6.10 File Size

The size of a file may be increased by writing to the file after the current end of file. The size may also be changed by calling MPI *size changing* routines, such as MPI\_FILE\_SET\_SIZE. A call to a size changing routine does not necessarily change the file size. For example, calling MPI\_FILE\_PREALLOCATE with a size less than the current size does not change the size.

Consider a set of bytes that has been written to a file since the most recent call to a size changing routine, or since MPI\_FILE\_OPEN if no such routine has been called. Let the high byte be the byte in that set with the largest displacement. The file size is the larger of

• One plus the displacement of the high byte.

• The size immediately after the size changing routine, or MPI\_FILE\_OPEN, returned.

When applying consistency semantics, calls to MPI\_FILE\_SET\_SIZE and MPI\_FILE\_PREALLOCATE are considered writes to the file (which conflict with operations that access bytes at displacements between the old and new file sizes), and MPI\_FILE\_GET\_SIZE is considered a read of the file (which overlaps with all accesses to the file).

Advice to users. Any sequence of operations containing the collective routines MPI\_FILE\_SET\_SIZE and MPI\_FILE\_PREALLOCATE is a write sequence. As such, sequential consistency in nonatomic mode is not guaranteed unless the conditions in Section 14.6.1 are satisfied. (End of advice to users.)

File pointer update semantics (i.e., file pointers are updated by the amount accessed) are only guaranteed if file size changes are sequentially consistent.

Advice to users. Consider the following example. Given two operations made by separate processes to a file containing 100 bytes: an MPI\_FILE\_READ of 10 bytes and an MPI\_FILE\_SET\_SIZE to 0 bytes. If the user does not enforce sequential consistency between these two operations, the file pointer may be updated by the amount requested (10 bytes) even if the amount accessed is zero bytes. (End of advice to users.)

#### 14.6.11 Examples

The examples in this section illustrate the application of the MPI consistency and semantics guarantees. These address

- conflicting accesses on file handles obtained from a single collective open, and
- all accesses on file handles obtained from two separate collective opens.

The simplest way to achieve consistency for conflicting accesses is to obtain sequential consistency by setting atomic mode. For the code below, process 1 will read either 0 or 10 integers. If the latter, every element of b will be 5. If nonatomic mode is set, the results of the read are undefined.

14

15

16 17

18

19

20

21

22 23

24

26

27

28

29

30

33

34

35

36

37

38

41

42

43 44

45

46 47

A user may guarantee that the write on process 0 precedes the read on process 1 by imposing temporal order with, for example, calls to MPI\_BARRIER.

Advice to users. Routines other than MPI\_BARRIER may be used to impose temporal order. In the example above, process 0 could use MPI\_SEND to send a 0 byte message, received by process 1 using MPI\_RECV. (End of advice to users.)

Alternatively, a user can impose consistency with nonatomic mode set:

```
/* Process 0 */
int i, a[10];
for (i=0;i<10;i++)
   a[i] = 5;
MPI_File_open(MPI_COMM_WORLD, "workfile",
              MPI_MODE_RDWR | MPI_MODE_CREATE, MPI_INFO_NULL, &fh0);
MPI_File_set_view(fh0, 0, MPI_INT, MPI_INT, "native", MPI_INFO_NULL);
MPI_File_write_at(fh0, 0, a, 10, MPI_INT, &status );
MPI_File_sync(fh0);
MPI_Barrier(MPI_COMM_WORLD);
MPI_File_sync(fh0);
/* Process 1 */
int b[10];
MPI_File_open(MPI_COMM_WORLD, "workfile",
              MPI_MODE_RDWR | MPI_MODE_CREATE, MPI_INFO_NULL, &fh1);
MPI_File_set_view(fh1, 0, MPI_INT, MPI_INT, "native", MPI_INFO_NULL);
MPI_File_sync(fh1);
MPI_Barrier(MPI_COMM_WORLD);
MPI_File_sync(fh1);
MPI_File_read_at(fh1, 0, b, 10, MPI_INT, &status);
```

The "sync-barrier-sync" construct is required because:

- The barrier ensures that the write on process 0 occurs before the read on process 1.
- The first sync guarantees that the data written by all processes is transferred to the storage device.
- The second sync guarantees that all data which has been transferred to the storage device is visible to all processes. (This does not affect process 0 in this example.)

2

27

28

29 30

31

33

34

35 36

37 38

39

40 41

42

The following program represents an erroneous attempt to achieve consistency by eliminating the apparently superfluous second "sync" call for each process.

```
/* ----- THIS EXAMPLE IS ERRONEOUS ----- */
     /* Process 0 */
    int i, a[10];
6
    for (i=0;i<10;i++)
       a[i] = 5;
9
    MPI_File_open(MPI_COMM_WORLD, "workfile",
10
                  MPI_MODE_RDWR | MPI_MODE_CREATE, MPI_INFO_NULL, &fh0);
11
    MPI_File_set_view(fh0, 0, MPI_INT, MPI_INT, "native", MPI_INFO_NULL);
12
    MPI_File_write_at(fh0, 0, a, 10, MPI_INT, &status);
13
    MPI_File_sync(fh0);
14
    MPI_Barrier(MPI_COMM_WORLD);
15
16
     /* Process 1 */
17
    int b[10];
18
    MPI_File_open(MPI_COMM_WORLD, "workfile",
19
                  MPI_MODE_RDWR | MPI_MODE_CREATE, MPI_INFO_NULL, &fh1);
20
    MPI_File_set_view(fh1, 0, MPI_INT, MPI_INT, "native", MPI_INFO_NULL);
21
    MPI_Barrier(MPI_COMM_WORLD);
22
    MPI_File_sync(fh1);
23
    MPI_File_read_at(fh1, 0, b, 10, MPI_INT, &status);
24
25
     /* ----- THIS EXAMPLE IS ERRONEOUS ----- */
26
```

The above program also violates the MPI rule against out-of-order collective operations and will deadlock for implementations in which MPI\_FILE\_SYNC blocks.

Advice to users. Some implementations may choose to implement MPI\_FILE\_SYNC as a temporally synchronizing function. When using such an implementation, the "sync-barrier-sync" construct above can be replaced by a single "sync." The results of using such code with an implementation for which MPI\_FILE\_SYNC is not temporally synchronizing is undefined. (End of advice to users.)

#### Asynchronous I/O

The behavior of asynchronous I/O operations is determined by applying the rules specified above for synchronous I/O operations.

The following examples all access a preexisting file "myfile." Word 10 in myfile initially contains the integer 2. Each example writes and reads word 10.

First consider the following code fragment:

```
int a = 4, b, TRUE=1;

MPI_File_open(MPI_COMM_WORLD, "myfile",

MPI_MODE_RDWR, MPI_INFO_NULL, &fh);

MPI_File_set_view(fh, 0, MPI_INT, MPI_INT, "native", MPI_INFO_NULL);

/* MPI_File_set_atomicity(fh, TRUE); Use this to set atomic mode. */
```

11

12 13

14

15

16

17

18

19

20

21

22

23 24

26

27

28

29

30

31

32

33

34 35

36 37

38

41

42

43

 $\frac{44}{45}$ 

46

47

```
MPI_File_iwrite_at(fh, 10, &a, 1, MPI_INT, &reqs[0]);
MPI_File_iread_at(fh, 10, &b, 1, MPI_INT, &reqs[1]);
MPI_Waitall(2, reqs, statuses);
```

For asynchronous data access operations, MPI specifies that the access occurs at any time between the call to the asynchronous data access routine and the return from the corresponding request complete routine. Thus, executing either the read before the write, or the write before the read is consistent with program order. If atomic mode is set, then MPI guarantees sequential consistency, and the program will read either 2 or 4 into b. If atomic mode is not set, then sequential consistency is not guaranteed and the program may read something other than 2 or 4 due to the conflicting data access.

Similarly, the following code fragment does not order file accesses:

If atomic mode is set, either 2 or 4 will be read into b. Again, MPI does not guarantee sequential consistency in nonatomic mode.

On the other hand, the following code fragment:

```
int a = 4, b;
MPI_File_open(MPI_COMM_WORLD, "myfile",
              MPI_MODE_RDWR, MPI_INFO_NULL, &fh);
MPI_File_set_view(fh, 0, MPI_INT, MPI_INT, "native", MPI_INFO_NULL);
MPI_File_iwrite_at(fh, 10, &a, 1, MPI_INT, &reqs[0]);
MPI_Wait(&reqs[0], &status);
MPI_File_iread_at(fh, 10, &b, 1, MPI_INT, &reqs[1]);
MPI_Wait(&reqs[1], &status);
defines the same ordering as:
int a = 4, b;
MPI_File_open(MPI_COMM_WORLD, "myfile",
              MPI_MODE_RDWR, MPI_INFO_NULL, &fh);
MPI_File_set_view(fh, 0, MPI_INT, MPI_INT, "native", MPI_INFO_NULL);
MPI_File_write_at(fh, 10, &a, 1, MPI_INT, &status );
MPI_File_read_at(fh, 10, &b, 1, MPI_INT, &status );
Since
```

- nonconcurrent operations on a single file handle are sequentially consistent, and
- the program fragments specify an order for the operations,

MPI guarantees that both program fragments will read the value 4 into b. There is no need to set atomic mode for this example.

Similar considerations apply to conflicting accesses of the form:

```
MPI_File_iwrite_all(fh,...);
MPI_File_iread_all(fh,...);
MPI_Waitall(...);
```

In addition, as mentioned in Section 14.6.5, nonblocking collective I/O operations have to be called in the same order on the file handle by all processes.

Similar considerations apply to conflicting accesses of the form:

```
MPI_File_write_all_begin(fh,...);
MPI_File_iread(fh,...);
MPI_Wait(fh,...);
MPI_File_write_all_end(fh,...);
```

Recall that constraints governing consistency and semantics are not relevant to the following:

```
MPI_File_write_all_begin(fh,...);
MPI_File_read_all_begin(fh,...);
MPI_File_read_all_end(fh,...);
MPI_File_write_all_end(fh,...);
```

since split collective operations on the same file handle may not overlap (see Section 14.4.5).

## 14.7 I/O Error Handling

By default, communication errors are fatal—MPI\_ERRORS\_ARE\_FATAL is the default error handler associated with MPI\_COMM\_WORLD. I/O errors are usually less catastrophic (e.g., "file not found") than communication errors, and common practice is to catch these errors and continue executing. For this reason, MPI provides additional error facilities for I/O.

Advice to users. MPI does not specify the state of a computation after an erroneous MPI call has occurred. A high-quality implementation will support the I/O error handling facilities, allowing users to write programs using common practice for I/O. (End of advice to users.)

Like communicators, each file handle has an error handler associated with it. The MPI I/O error handling routines are defined in Section 9.3.

When MPI calls a user-defined error handler resulting from an error on a particular file handle, the first two arguments passed to the file error handler are the file handle and the error code. For I/O errors that are not associated with a valid file handle (e.g., in MPI\_FILE\_OPEN or MPI\_FILE\_DELETE), the first argument passed to the error handler is MPI\_FILE\_NULL.

I/O error handling differs from communication error handling in another important aspect. By default, the predefined error handler for file handles is MPI\_ERRORS\_RETURN. The **default file error** handler has two purposes: when a new file handle is created (by MPI\_FILE\_OPEN), the error handler for the new file handle is initially set to the default

file error handler, and I/O routines that have no valid file handle on which to raise an error (e.g., MPI\_FILE\_OPEN or MPI\_FILE\_DELETE) use the default file error handler. The default file error handler can be changed by specifying MPI\_FILE\_NULL as the fh argument to MPI\_FILE\_SET\_ERRHANDLER. The current value of the default file error handler can be determined by passing MPI\_FILE\_NULL as the fh argument to MPI\_FILE\_GET\_ERRHANDLER.

Rationale. For communication, the default error handler is inherited from MPI\_COMM\_WORLD when using the World Model. In I/O, there is no analogous "root" file handle from which default properties can be inherited. Rather than invent a new global file handle, the default file error handler is manipulated as if it were attached to MPI\_FILE\_NULL. (End of rationale.)

## 14.8 I/O Error Classes

The implementation dependent error codes returned by the I/O routines can be converted into the error classes defined in Table 14.5.

In addition, calls to routines in this chapter may raise errors in other MPI classes, such as MPI\_ERR\_TYPE.

MPI_ERR_FILE	Invalid file handle
MPI_ERR_NOT_SAME	Collective argument not identical on all
	processes, or collective routines called in
`	a different order by different processes
MPI_ERR_AMODE	Error related to the amode passed to
	MPI_FILE_OPEN
MPI_ERR_UNSUPPORTED_DATAREP	Unsupported datarep passed to
	MPI_FILE_SET_VIEW
MPI_ERR_UNSUPPORTED_OPERATION	Unsupported operation, such as seeking on
	a file which supports sequential access only
MPI_ERR_NO_SUCH_FILE	File does not exist
MPI_ERR_FILE_EXISTS	File exists
MPI_ERR_BAD_FILE	Invalid file name (e.g., path name too long)
MPI_ERR_ACCESS	Permission denied
MPI_ERR_NO_SPACE	Not enough space
MPI_ERR_QUOTA	Quota exceeded
MPI_ERR_READ_ONLY	Read-only file or file system
MPI_ERR_FILE_IN_USE	File operation could not be completed, as
	the file is currently open by some process
MPI_ERR_DUP_DATAREP	Conversion functions could not be regis-
	tered because a data representation identi-
	fier that was already defined was passed to
	MPI_REGISTER_DATAREP
MPI_ERR_CONVERSION	An error occurred in a user supplied data
	conversion function.
MPI_ERR_IO	Other I/O error

Table 14.5: I/O Error Classes

45

47

buffer2 = (float \*)

write\_buf\_ptr = buffer1;

## 14.9 Examples

```
14.9.1 Double Buffering with Split Collective I/O
3
4
     This example shows how to overlap computation and output. The computation is performed
5
     by the function compute_buffer().
6
7
9
                              double_buffer
      * Function:
10
11
      * Synopsis:
12
             void double_buffer(
13
                      MPI_File fh,
                                                                 ** IN
14
                      MPI_Datatype buftype,
                                                                 ** IN
15
                      int bufcount
                                                                 ** IN
16
             )
18
      * Description:
19
             Performs the steps to overlap computation with a collective write
20
             by using a double-buffering technique.
21
22
      * Parameters:
23
                                 previously opened MPI file handle
             fh
^{24}
                                 MPI datatype for memory layout
             buftype
                                  (Assumes a compatible view has been set on fh)
26
                                  # buftype elements to transfer
             bufcount
27
28
29
     /* this macro switches which buffer "x" is pointing to */
     #define TOGGLE_PTR(x) (((x)==(buffer1)) ? (x=buffer2) : (x=buffer1))
30
31
     void double_buffer(MPI_File fh, MPI_Datatype buftype, int bufcount)
33
     {
34
35
        MPI_Status status;
                                   /* status for MPI calls */
36
        float *buffer1, *buffer2; /* buffers to hold results */
37
        float *compute_buf_ptr;
                                    /* destination buffer */
38
                                     /* for computing */
        float *write_buf_ptr;
                                    /* source for writing */
                                     /* determines when to quit */
        int done;
41
42
        /* buffer initialization */
43
        buffer1 = (float *)
44
```

/\* initially point to buffer1 \*/

malloc(bufcount\*sizeof(float));

malloc(bufcount\*sizeof(float));

compute\_buf\_ptr = buffer1; /\* initially point to buffer1 \*/

14.9. EXAMPLES 709

```
/* DOUBLE-BUFFER prolog:
        compute buffer1; then initiate writing buffer1 to disk
    */
  compute_buffer(compute_buf_ptr, bufcount, &done);
  MPI_File_write_all_begin(fh, write_buf_ptr, bufcount, buftype);
  /* DOUBLE-BUFFER steady state:
      Overlap writing old results from buffer pointed to by write_buf_ptr
      with computing new results into buffer pointed to by compute_buf_ptr.
      There is always one write-buffer and one compute-buffer in use
      during steady state.
   */
  while (!done) {
     TOGGLE_PTR(compute_buf_ptr);
      compute_buffer(compute_buf_ptr, bufcount, &done);
     MPI_File_write_all_end(fh, write_buf_ptr, &status);
     TOGGLE_PTR(write_buf_ptr);
     MPI_File_write_all_begin(fh, write_buf_ptr, bufcount, buftype);
  }
  /* DOUBLE-BUFFER epilog:
       wait for final write to complete.
  MPI_File_write_all_end(fh, write_buf_ptr, &status);
  /* buffer cleanup */
  free(buffer1);
  free(buffer2);
}
```

12

13 14

15

16

18

19

20 21

22 23

26

27 28 29

30

34 35

36

38

39

#### 14.9.2 Subarray Filetype Constructor

Assume we are writing out a  $100 \times 100$  2D array of double precision floating point numbers that is distributed among 4 processes such that each process has a block of 25 columns (e.g., process 0 has columns 0–24, process 1 has columns 25–49, etc.; see Figure 14.4). To create the filetypes for each process one could use the following C program (see Section 5.1.3):

```
double subarray[100][25];
MPI_Datatype filetype;
int sizes[2], subsizes[2], starts[2];
int rank;

MPI_Comm_rank(MPI_COMM_WORLD, &rank);
sizes[0]=100; sizes[1]=100;

42
43
44
45
46
47
48
```




Figure 14.4: Example array file layout




Figure 14.5: Example local array filetype for process 1

14.9. EXAMPLES 711

```
subsizes[0]=100; subsizes[1]=25;
   starts[0]=0; starts[1]=rank*subsizes[1];
   MPI_Type_create_subarray(2, sizes, subsizes, starts, MPI_ORDER_C,
                             MPI_DOUBLE, &filetype);
    Or, equivalently in Fortran:
double precision subarray(100,25)
integer filetype, rank, ierror
integer sizes(2), subsizes(2), starts(2)
call MPI_COMM_RANK(MPI_COMM_WORLD, rank, ierror)
sizes(1)
            = 100
sizes(2)
            = 100
subsizes(1) = 100
subsizes(2) = 25
starts(1)
            = 0
starts(2)
            = rank*subsizes(2)
call MPI_TYPE_CREATE_SUBARRAY(2, sizes, subsizes, starts, &
           MPI_ORDER_FORTRAN, MPI_DOUBLE_PRECISION,
                                                            &
           filetype, ierror)
```

11 12

13

14

15

16

17

18

19 20


21

22

23 24

26

The generated filetype will then describe the portion of the file contained within the process's subarray with holes for the space taken by the other processes. Figure 14.5 shows the filetype created for process 1.



## Chapter 15

# Tool Support

#### 15.1 Introduction

This chapter discusses interfaces that allow debuggers, performance analyzers, and other tools to extract information about the operation of MPI processes. Specifically, this chapter defines both the MPI profiling interface (Section 15.2), which supports the transparent interception and inspection of MPI calls, and the MPI tool information interface (Section 15.3), which supports the inspection and manipulation of MPI control and performance variables, as well as the registration of callbacks for MPI library events. The interfaces described in this chapter are all defined in the context of an MPI process, i.e., are callable from the same code that invokes other MPI functions.

## 15.2 Profiling Interface

## 15.2.1 Requirements

To meet the requirements for the MPI profiling interface, an implementation of the MPI functions must

- 1. provide a mechanism through which all of the MPI defined functions, except those allowed as macros (See Section 2.6.4), may be accessed with a name shift. This requires, in C and Fortran, an alternate entry point name, with the prefix PMPI\_ for each MPI function in each provided language binding and language support method. For routines implemented as macros, it is still required that the PMPI\_ version be supplied and work as expected, but it is not possible to replace at link time the MPI\_ version with a user-defined version.
  - For Fortran, the different support methods cause several specific procedure names. Therefore, several profiling routines (with these specific procedure names) are needed for each Fortran MPI routine, as described in Section 19.1.5.
- 2. ensure that those MPI functions that are not replaced may still be linked into an executable image without causing name clashes.
- 3. document the implementation of different language bindings of the MPI interface if they are layered on top of each other, so that the profiler developer knows whether she must implement the profile interface for each binding, or can economize by implementing it only for the lowest level routines.

2

3

5

6

9

10 11 12

13 14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

36

37

43

44

45 46

47 48 4. where the implementation of different language bindings is done through a layered approach (e.g., the Fortran binding is a set of "wrapper" functions that call the C implementation), ensure that these wrapper functions are separable from the rest of the library.

This separability is necessary to allow a separate profiling library to be correctly implemented, since (at least with Unix linker semantics) the profiling library must contain these wrapper functions if it is to perform as expected. This requirement allows the person who builds the profiling library to extract these functions from the original MPI library and add them into the profiling library without bringing along any other unnecessary code.

5. provide a no-op routine MPI\_PCONTROL in the MPI library.

#### 15.2.2 Discussion

The objective of the MPI profiling interface is to ensure that it is relatively easy for authors of profiling (and other similar) tools to interface their codes to MPI implementations on different machines.

Since MPI is a machine independent standard with many different implementations, it is unreasonable to expect that the authors of profiling tools for MPI will have access to the source code that implements MPI on any particular machine. It is therefore necessary to provide a mechanism by which the implementors of such tools can collect whatever performance information they wish without access to the underlying implementation.

We believe that having such an interface is important if MPI is to be attractive to end users, since the availability of many different tools will be a significant factor in attracting users to the MPI standard.

The profiling interface is just that, an interface. It says nothing about the way in which it is used. There is therefore no attempt to lay down what information is collected through the interface, or how the collected information is saved, filtered, or displayed.

While the initial impetus for the development of this interface arose from the desire to permit the implementation of profiling tools, it is clear that an interface like that specified may also prove useful for other purposes, such as "internetworking" multiple MPI implementations. Since all that is defined is an interface, there is no objection to its being used wherever it is useful.

As the issues being addressed here are intimately tied up with the way in which executable images are built, which may differ greatly on different machines, the examples given below should be treated solely as one way of implementing the objective of the MPI profiling interface. The actual requirements made of an implementation are those detailed in the Requirements section above, the whole of the rest of this section is only present as justification and discussion of the logic for those requirements.

The examples below show one way in which an implementation could be constructed to meet the requirements on a Unix system (there are doubtless others that would be equally valid).

#### 15.2.3 Logic of the Design

Provided that an MPI implementation meets the requirements above, it is possible for the implementor of the profiling system to intercept the MPI calls that are made by the

user program. She can then collect whatever information she requires before calling the underlying MPI implementation (through its name shifted entry points) to achieve the desired effects.

## 15.2.4 Miscellaneous Control of Profiling

There is a clear requirement for the user code to be able to control the profiler dynamically at run time. This capability is normally used for (at least) the purposes of

- Enabling and disabling profiling depending on the state of the calculation.
- Flushing trace buffers at non-critical points in the calculation.
- Adding user events to a trace file.

These requirements are met by use of MPI\_PCONTROL.

```
MPI_PCONTROL(level, ...)

IN level Profiling level (integer)

C binding
int MPI_Pcontrol(const int level, ...)

Fortran 2008 binding
MPI_Pcontrol(level)
    INTEGER, INTENT(IN) :: level

Fortran binding
MPI_PCONTROL(LEVEL)
    INTEGER LEVEL
```

MPI libraries themselves make no use of this routine, and simply return immediately to the user code. However the presence of calls to this routine allows a profiling package to be explicitly called by the user.

Since MPI has no control of the implementation of the profiling code, we are unable to specify precisely the semantics that will be provided by calls to MPI\_PCONTROL. This vagueness extends to the number of arguments to the function, and their datatypes.

However to provide some level of portability of user codes to different profiling libraries, we request the following meanings for certain values of level.

- level==0 Profiling is disabled.
- level==1 Profiling is enabled at a normal default level of detail.
- level==2 Profile buffers are flushed, which may be a no-op in some profilers.
- All other values of level have profile library defined effects and additional arguments.

We also request that the default state after MPI has been initialized is for profiling to be enabled at the normal default level. (i.e., as if MPI\_PCONTROL had just been called with the argument 1). This allows users to link with a profiling library and to obtain profile output without having to modify their source code at all.

The provision of MPI\_PCONTROL as a no-op in the standard MPI library supports the collection of more detailed profiling information with source code that can still link against the standard MPI library.

3 4 5

6

7

1

2

## 15.2.5 Profiler Implementation Example

A profiler can accumulate the total amount of data sent by the MPI\_SEND function, along with the total elapsed time spent in the function as the following example shows:

9 10

11

12

13 14

15

16

17

18

19

20 21

22 23

24

25 26

27

28 29

30

31

32

33

#### Example 15.1

```
static int totalBytes = 0;
static double totalTime = 0.0;
int MPI_Send(const void* buffer, int count, MPI_Datatype datatype,
             int dest, int tag, MPI_Comm comm)
{
  double tstart = MPI_Wtime();
                                      /* Pass on all arguments */
   int size;
                 = PMPI_Send(buffer,count,datatype,dest,tag,comm);
   int result
  totalTime += MPI Wtime() - tstart:
                                                /* and time
                                                                     */
  MPI_Type_size(datatype, &size);
                                    /* Compute size */
  totalBytes += count*size;
  return result;
}
```

## 15.2.6 MPI Library Implementation Example

If the MPI library is implemented in C on a Unix system, then there are various options, including the two presented here, for supporting the name-shift requirement. The choice between these two options depends partly on whether the linker and compiler support weak symbols.

34 35 36

37

38

39 40

41

#### Systems with Weak Symbols

If the compiler and linker support weak external symbols (e.g., Solaris 2.x, other System V.4 machines), then only a single library is required as the following example shows:

#### Example 15.2

```
#pragma weak MPI_Example = PMPI_Example
int PMPI_Example(/* appropriate args */)

{
    /* Useful content */
}
```

The effect of this **#pragma** is to define the external symbol MPI\_Example as a weak definition. This means that the linker will not complain if there is another definition of the symbol (for instance in the profiling library); however if no other definition exists, then the linker will use the weak definition.

#### Systems without Weak Symbols

In the absence of weak symbols then one possible solution would be to use the C macro preprocessor as the following example shows:

#### Example 15.3

```
#ifdef PROFILELIB
# ifdef __STDC__
# define FUNCTION(name) P##name
# else
# define FUNCTION(name) P/**/name
# endif
#else
# define FUNCTION(name) name
#endif
```

Each of the user visible functions in the library would then be declared thus

```
int FUNCTION(MPI_Example)(/* appropriate args */)
{
    /* Useful content */
}
```

The same source file can then be compiled to produce both versions of the library, depending on the state of the PROFILELIB macro symbol.

It is required that the standard MPI library be built in such a way that the inclusion of MPI functions can be achieved one at a time. This is a somewhat unpleasant requirement, since it may mean that each external function has to be compiled from a separate file. However this is necessary so that the author of the profiling library need only define those MPI functions that she wishes to intercept, references to any others being fulfilled by the normal MPI library. Therefore the link step can look something like this

```
% cc ... -lmyprof -lpmpi -lmpi
```

Here libmyprof.a contains the profiler functions that intercept some of the MPI functions, libpmpi.a contains the "name shifted" MPI functions, and libmpi.a contains the normal definitions of the MPI functions.

#### 15.2.7 Complications

#### Multiple Counting

Since parts of the MPI library may themselves be implemented using more basic MPI functions (e.g., a portable implementation of the collective operations implemented using point

to point communications), there is potential for profiling functions to be called from within an MPI function that was called from a profiling function. This could lead to "double counting" of the time spent in the inner routine. Since this effect could actually be useful under some circumstances (e.g., it might allow one to answer the question "How much time is spent in the point to point routines when they are called from collective functions?"), we have decided not to enforce any restrictions on the author of the MPI library that would overcome this. Therefore the author of the profiling library should be aware of this problem, and guard against it. In a single-threaded world this is easily achieved through use of a static variable in the profiling code that remembers if you are already inside a profiling routine. It becomes more complex in a multithreaded environment (as does the meaning of the times recorded).

#### Linker Oddities

The Unix linker traditionally operates in one pass: the effect of this is that functions from libraries are only included in the image if they are needed at the time the library is scanned. When combined with weak symbols, or multiple definitions of the same function, this can cause odd (and unexpected) effects.

Consider, for instance, an implementation of MPI in which the Fortran binding is achieved by using wrapper functions on top of the C implementation. The author of the profile library then assumes that it is reasonable only to provide profile functions for the C binding, since Fortran will eventually call these, and the cost of the wrappers is assumed to be small. However, if the wrapper functions are not in the profiling library, then none of the profiled entry points will be undefined when the profiling library is called. Therefore none of the profiling code will be included in the image. When the standard MPI library is scanned, the Fortran wrappers will be resolved, and will also pull in the base versions of the MPI functions. The overall effect is that the code will link successfully, but will not be profiled.

To overcome this we must ensure that the Fortran wrapper functions are included in the profiling version of the library. We ensure that this is possible by requiring that these be separable from the rest of the base MPI library. This allows them to be copied out of the base library and into the profiling one using a tool such as ar.

# Fortran Support Methods

The different Fortran support methods and possible options for the support of subarrays (depending on whether the compiler can support TYPE(\*), DIMENSION(...) choice buffers) imply different specific procedure names for the same Fortran MPI routine. The rules and implications for the profiling interface are described in Section 19.1.5.

## 15.2.8 Multiple Levels of Interception

The scheme given here does not directly support the nesting of profiling functions, since it provides only a single alternative name for each MPI function. Consideration was given to an implementation that would allow multiple levels of call interception, however we were unable to construct an implementation of this that did not have the following disadvantages

- assuming a particular implementation language,
- imposing a run time cost even when no profiling was taking place.

Since one of the objectives of MPI is to permit efficient, low latency implementations, and it is not the business of a standard to require a particular implementation language, we decided to accept the scheme outlined above.

Note, however, that it is possible to use the scheme above to implement a multi-level system, since the function called by the user may call many different profiling functions before calling the underlying MPI function. This capability has been demonstrated in the  $P^N$ MPI tool infrastructure [58].

#### 15.3 The MPI Tool Information Interface

MPI implementations often use internal variables to control their operation and performance and rely on internal events for their implementation. Understanding and manipulating these variables and tracking these events can provide a more efficient execution environment or improve performance for many applications. This section describes the MPI tool information interface, which provides a mechanism for MPI implementors to expose variables, each of which represents a particular property, setting, or performance measurement from within the MPI implementation, as well as expose events that can be tracked by tools. The interface is split into three parts: the first part provides information about, and supports the setting of, control variables through which the MPI implementation tunes its configuration. The second part provides access to performance variables that can provide insight into internal performance information of the MPI implementation. The third part enables tools to query available events within an MPI implementation and register callbacks for them.

To avoid restrictions on the MPI implementation, the MPI tool information interface allows the implementation to specify which control variables, performance variables, and events exist. Additionally, the user of the MPI tool information interface can obtain metadata about each available variable or event, such as its datatype, and a textual description. The MPI tool information interface provides the necessary routines to find all variables and events that exist in a particular MPI implementation; to query their properties; to retrieve descriptions about their meaning; to access and, if appropriate, to alter their values; and (in case of events) set callbacks triggered by them.

Variables, events, and categories across connected MPI processes with equivalent names are required to have the same meaning (see the definition of "equivalent" as related to strings in Section 15.3.3). Furthermore, enumerations with equivalent names across connected MPI processes are required to have the same meaning, but are allowed to comprise different enumeration items. Enumeration items that have equivalent names across connected MPI processes in enumerations with the same meaning must also have the same meaning. In order for variables and categories to have the same meaning, routines in the tools information interface that return details for those variables and categories have requirements on what parameters must be identical. These requirements are specified in their respective sections.

Rationale. The intent of requiring the same meaning for entities with equivalent names is to enforce consistency across connected MPI processes. For example, variables describing the number of packets sent on different types of network devices should have different names to reflect their potentially different meanings. (End of rationale.)

The MPI tool information interface can be used independently from the MPI communication functionality. In particular, the routines of this interface can be called before MPI is

initialized and after MPI is finalized. In order to support this behavior cleanly, the MPI tool information interface uses separate initialization and finalization routines. All identifiers used in the MPI tool information interface have the prefix MPI\_T\_.

On success, all MPI tool information interface routines return MPI\_SUCCESS, otherwise they return an appropriate and unique return code indicating the reason why the call was not successfully completed. Details on return codes can be found in Section 15.3.10. However, unsuccessful calls to the MPI tool information interface are not fatal and do not impact the execution of subsequent MPI routines.

Since the MPI tool information interface primarily focuses on tools and support libraries, MPI implementations are only required to provide C bindings for functions and constants introduced in this section. Except where otherwise noted, all conventions and principles governing the C bindings of the MPI API also apply to the MPI tool information interface, which is available by including the mpi.h header file. All routines in this interface have local semantics.

Advice to users. The number and type of control variables, performance variables, and events can vary between MPI implementations, platforms and different builds of the same implementation on the same platform as well as between runs. Hence, any application relying on a particular variable will not be portable. Further, there is no guarantee that the number of variables and variable indices are the same across connected MPI processes.

This interface is primarily intended for performance monitoring tools, support tools, and libraries controlling the application's environment. When maximum portability is desired, application programmers should either avoid using the MPI tool information interface or avoid being dependent on the existence of a particular control or performance variable or of a particular event. (*End of advice to users.*)

#### 15.3.1 Verbosity Levels

The MPI tool information interface provides access to internal configuration and performance information through a set of control and performance variables defined by the MPI implementation. Since some implementations may export a large number of variables, variables are classified by a verbosity level that categorizes both their intended audience (end users, performance tuners or MPI implementors) and a relative measure of level of detail (basic, detailed or all). These verbosity levels are described by a single integer. Table 15.1 lists the constants for all possible verbosity levels. The values of the constants are monotonic in the order listed in the table; i.e., MPI\_T\_VERBOSITY\_USER\_BASIC < MPI\_T\_VERBOSITY\_USER\_DETAIL < ... < MPI\_T\_VERBOSITY\_MPIDEV\_ALL.

## 15.3.2 Binding MPI Tool Information Interface Variables to MPI Objects

Each MPI tool information interface variable provides access to a particular control setting or performance property of the MPI implementation. A variable may refer to a specific MPI object such as a communicator, datatype, or one-sided communication window, or the variable may refer more generally to the MPI environment of the process. Except for the last case, the variable must be bound to exactly one MPI object before it can be used. Table 15.2 lists all MPI object types to which an MPI tool information interface variable can be bound, together with the matching constant that MPI tool information interface routines return to identify the object type.

MPI_T_VERBOSITY_USER_BASIC	Basic information of interest to users
MPI_T_VERBOSITY_USER_DETAIL	Detailed information of interest to users
MPI_T_VERBOSITY_USER_ALL	All remaining information of interest to users
MPI_T_VERBOSITY_TUNER_BASIC	Basic information required for tuning
MPI_T_VERBOSITY_TUNER_DETAIL	Detailed information required for tuning
MPI_T_VERBOSITY_TUNER_ALL	All remaining information required for tuning
MPI_T_VERBOSITY_MPIDEV_BASIC	Basic information for MPI implementors
MPI_T_VERBOSITY_MPIDEV_DETAIL	Detailed information for MPI implementors
MPI_T_VERBOSITY_MPIDEV_ALL	All remaining information for MPI implementors

Table 15.1: MPI tool information interface verbosity levels

Constant	MPI object
MPI_T_BIND_NO_OBJECT	N/A; applies globally to entire MPI process
MPI_T_BIND_MPI_COMM	MPI communicators
MPI_T_BIND_MPI_DATATYPE	MPI datatypes
MPI_T_BIND_MPI_ERRHANDLER	MPI error handlers
MPI_T_BIND_MPI_FILE	MPI file handles
MPI_T_BIND_MPI_GROUP	MPI groups
MPI_T_BIND_MPI_OP	MPI reduction operators
MPI_T_BIND_MPI_REQUEST	MPI requests
MPI_T_BIND_MPI_WIN	MPI windows for one-sided communication
MPI_T_BIND_MPI_MESSAGE	MPI message object
MPI_T_BIND_MPI_INFO	MPI info object
MPI_T_BIND_MPI_SESSION	MPI session object

Table 15.2: Constants to identify associations of variables

Rationale. Some variables have meanings tied to a specific MPI object. Examples include the number of send or receive operations that use a particular datatype, the number of times a particular error handler has been called, or the communication protocol and "eager limit" used for a particular communicator. Creating a new MPI tool information interface variable for each MPI object would cause the number of variables to grow without bound, since they cannot be reused to avoid naming conflicts. By associating MPI tool information interface variables with a specific MPI object, the MPI implementation only must specify and maintain a single variable, which can then be applied to as many MPI objects of the respective type as created during the program's execution. (End of rationale.)

#### 15.3.3 Convention for Returning Strings

Several MPI tool information interface functions return one or more strings. These functions have two arguments for each string to be returned: an OUT parameter that identifies a pointer to the buffer in which the string will be returned, and an INOUT parameter to pass the length of the buffer. The user is responsible for the memory allocation of the buffer and must pass the size of the buffer (n) as the length argument. Let n be the length value specified to the function. On return, the function writes at most n-1 of the string's

characters into the buffer, followed by a null terminator. If the returned string's length is greater than or equal to n, the string will be truncated to n-1 characters. In this case, the length of the string plus one (for the terminating null character) is returned in the length argument. If the user passes the null pointer as the buffer argument or passes 0 as the length argument, the function does not return the string and only returns the length of the string plus one in the length argument. If the user passes the null pointer as the length argument, the buffer argument is ignored and nothing is returned.

MPI implementations behave as if they have an internal character array that is copied to the output character array supplied by the user. Such output strings are only defined to be equivalent if their notional source-internal character arrays are identical (up to and including the null terminator), even if the output string is truncated due to a small input length parameter n.

# 15.3.4 Initialization and Finalization

The MPI tool information interface requires a separate set of initialization and finalization routines.

# MPI\_T\_INIT\_THREAD(required, provided)

```
IN required desired level of thread support (integer)

OUT provided provided level of thread support (integer)
```

# C binding

```
int MPI_T_init_thread(int required, int *provided)
```

All programs or tools that use the MPI tool information interface must initialize the MPI tool information interface in the processes that will use the interface before calling any other of its routines. A user can initialize the MPI tool information interface by calling MPI\_T\_INIT\_THREAD, which can be called multiple times. In addition, this routine initializes the thread environment for all routines in the MPI tool information interface. Calling this routine when the MPI tool information interface is already initialized has no effect beyond increasing the reference count of how often the interface has been initialized. The argument required is used to specify the desired level of thread support. The possible values and their semantics are identical to the ones that can be used with MPI\_INIT\_THREAD listed in Section 11.6. The call returns in provided information about the actual level of thread support that will be provided by the MPI implementation for calls to MPI tool information interface routines. It can be one of the four values listed in Section 11.6.

The MPI specification does not require all MPI processes to exist before MPI is initialized. If the MPI tool information interface is used before initialization of MPI, the user is responsible for ensuring that the MPI tool information interface is initialized on all processes it is used in. Processes created by the MPI implementation during initialization inherit the status of the MPI tool information interface (whether it is initialized or not as well as all active sessions and handles) from the process from which they are created.

Processes created at runtime as a result of calls to MPI's dynamic process management require their own initialization before they can use the MPI tool information interface.

Advice to users. If MPI\_T\_INIT\_THREAD is called before MPI\_INIT\_THREAD, the

requested and provided thread level for MPI\_T\_INIT\_THREAD may influence the behavior and return value of MPI\_INIT\_THREAD. The same is true for the reverse order. Likewise, when using the Sessions Model (Section 11.3), the requested and provided thread level for MPI\_T\_INIT\_THREAD may influence the behavior and return values of MPI\_SESSION\_INIT (see Section 11.3), with the same being true for the reverse order. (*End of advice to users*.)

Advice to implementors. MPI implementations should strive to make as many control or performance variables available before MPI initialization (instead of adding them during initialization) to allow tools the most flexibility. In particular, control variables should be available before MPI initialization if their value cannot be changed after MPI initialization. (End of advice to implementors.)

MPI\_T\_FINALIZE()

# C binding

int MPI\_T\_finalize(void)

This routine finalizes the use of the MPI tool information interface and may be called as often as the corresponding MPI\_T\_INIT\_THREAD routine up to the current point of execution. Calling it more times returns a corresponding error code. As long as the number of calls to MPI\_T\_FINALIZE is smaller than the number of calls to MPI\_T\_INIT\_THREAD up to the current point of execution, the MPI tool information interface remains initialized and calls to its routines are permissible. Further, additional calls to MPI\_T\_INIT\_THREAD after one or more calls to MPI\_T\_FINALIZE are permissible.

Once MPI\_T\_FINALIZE is called the same number of times as the routine MPI\_T\_INIT\_THREAD up to the current point of execution, the MPI tool information interface is no longer initialized. The user can reinitialize the interface by a subsequent call to MPI\_T\_INIT\_THREAD.

At the end of the program execution, unless MPI\_ABORT is called, an application must have called MPI\_T\_INIT\_THREAD and MPI\_T\_FINALIZE an equal number of times.

# 15.3.5 Datatype System

All variables managed through the MPI tool information interface represent their values through typed buffers of a given length and type using an MPI datatype (similar to regular send/receive buffers). Since the initialization of the MPI tool information interface is separate from the initialization of MPI, MPI tool information interface routines can be called before MPI initialization. Consequently, these routines can also use MPI datatypes before MPI initialization. Therefore, within the context of the MPI tool information interface, it is permissible to use a subset of MPI datatypes as specified below before MPI initialization.

Rationale. The MPI tool information interface relies mainly on unsigned datatypes for integer values since most variables are expected to represent counters or resource sizes. MPI\_INT is provided for additional flexibility and is expected to be used mainly for control variables and enumeration types (see below).

Providing all basic datatypes, in particular providing all signed and unsigned variants of integer types, would lead to a larger number of types, which tools need to interpret.

11 12 13

14 15

16

17 18

19

20

21

22

23

24

25

26

27 28

29

30

31

32 33

34

35

36

37

38

39

40

41

42

1	MPI_INT
2	MPI_INT32_T
3	MPI_INT64_T
4	MPI_UNSIGNED
5	MPI_UNSIGNED_LONG
6	MPI_UNSIGNED_LONG_LONG
7	MPI_UINT32_T
8	MPI_UINT64_T
9	MPI_COUNT
10	MPI_CHAR
11	MPI_DOUBLE

Table 15.3: MPI datatypes that can be used by the MPI tool information interface

This would cause unnecessary complexity in the implementation of tools based on the MPI tool information interface. (End of rationale.)

The MPI tool information interface only relies on a subset of the basic MPI datatypes and does not use any derived MPI datatypes. Table 15.3 lists all MPI datatypes that can be returned by the MPI tool information interface to represent its variables.

The use of the datatype MPI\_CHAR in the MPI tool information interface implies a nullterminated character array, i.e., a string in the C language. If a variable has type MPI\_CHAR, the value of the count parameter returned by MPI\_T\_CVAR\_HANDLE\_ALLOC and MPI\_T\_PVAR\_HANDLE\_ALLOC must be large enough to include any valid value, including its terminating null character. The contents of returned MPI\_CHAR arrays are only defined from index 0 through the location of the first null character.

The MPI tool information interface requires a significantly simpler type system than MPI itself. Therefore, only its required subset must be present before MPI initialization and MPI implementations do not need to initialize the complete MPI datatype system. (End of rationale.)

For variables of type MPI\_INT, an MPI implementation can provide additional information by associating names with a fixed number of values. We refer to this information in the following as an enumeration. In this case, the respective calls that provide additional metadata for each control or performance variable, i.e., MPI\_T\_CVAR\_GET\_INFO (Section 15.3.6), MPI\_T\_PVAR\_GET\_INFO (Section 15.3.7), and MPI\_T\_EVENT\_GET\_INFO (Section 15.3.8), return a handle of type MPI\_T\_enum that can be passed to the following functions to extract additional information. Thus, the MPI implementation can describe variables with a fixed set of values that each represents a particular state. Each enumeration type can have N different values, with a fixed N that can be queried using MPI\_T\_ENUM\_GET\_INFO.

enumtype

#### MPI\_T\_ENUM\_GET\_INFO(enumtype, num, name, name\_len)

OUT	num	number of discrete values represented by this enumeration (integer)
OUT	name	buffer to return the string containing the name of the enumeration item (string)
INOUT	name_len	length of the string and/or buffer for name (integer)

enumeration to be queried (handle)

#### C binding

IN

If enumtype is a valid enumeration, this routine returns the number of items represented by this enumeration type as well as its name. N must be greater than 0, i.e., the enumeration must represent at least one value.

The arguments name and name\_len are used to return the name of the enumeration as described in Section 15.3.3.

The routine is required to return a name of at least length one. This name must be unique with respect to all other names for enumerations that the MPI implementation uses.

Names associated with individual values in each enumeration enumtype can be queried using MPI\_T\_ENUM\_GET\_ITEM.

# MPI\_T\_ENUM\_GET\_ITEM(enumtype, index, value, name, name\_len)

IN	enumtype	enumeration to be queried (handle)
IN	index	number of the value to be queried in this enumeration (integer)
OUT	value	variable value (integer)
OUT	name	buffer to return the string containing the name of the enumeration item (string)
INOUT	name_len	length of the string and/or buffer for name (integer)

#### C binding

The arguments name and name\_len are used to return the name of the enumeration item as described in Section 15.3.3.

If completed successfully, the routine returns the name/value pair that describes the enumeration at the specified index. The call is further required to return a name of at least length one. This name must be unique with respect to all other names of items for the same enumeration.

3

5 6

9

10

11

12 13

14

15

16

17

18

19

20 21

23 24 25

22

26 27

28 29

30 31

32

33 34

35 36

37

38

39 41

42 43

44

45 46

47

#### Control Variables 15.3.6

The routines described in this section of the MPI tool information interface specification focus on the ability to list, query, and possibly set control variables exposed by the MPI implementation. These variables can typically be used by the user to fine tune properties and configuration settings of the MPI implementation. On many systems, such variables can be set using environment variables, although other configuration mechanisms may be available, such as configuration files or central configuration registries. A typical example that is available in several existing MPI implementations is the ability to specify an "eager limit," i.e., an upper bound on the size of messages sent or received using an eager protocol.

# Control Variable Query Functions

An MPI implementation exports a set of N control variables through the MPI tool information interface. If N is zero, then the MPI implementation does not export any control variables, otherwise the provided control variables are indexed from 0 to N-1. This index number is used in subsequent calls to identify the individual variables.

An MPI implementation is allowed to increase the number of control variables during the execution of an MPI application when new variables become available through dynamic loading. However, MPI implementations are not allowed to change the index of a control variable or to delete a variable once it has been added to the set. When a variable becomes inactive, e.g., through dynamic unloading, accessing its value should return a corresponding error code.

Advice to users. While the MPI tool information interface guarantees that indices or variable properties do not change during a particular run of an MPI program, it does not provide a similar guarantee between runs. (End of advice to users.)

The following function can be used to query the number of control variables, num\_cvar:

```
MPI_T_CVAR_GET_NUM(num_cvar)
```

OUT num\_cvar returns number of control variables (integer)

#### C binding

int MPI\_T\_cvar\_get\_num(int \*num\_cvar)

The function MPI\_T\_CVAR\_GET\_INFO provides access to additional information for each variable

MPI\_T\_CVAR\_GET\_INFO(cvar\_index, name, name\_len, verbosity, datatype, enumtype, desc, desc\_len, bind, scope)

IN	cvar_index	index of the control variable to be queried, value between 0 and $num\_cvar - 1$ (integer)
OUT	name	buffer to return the string containing the name of the control variable (string)
INOUT	name_len	length of the string and/or buffer for name (integer)
OUT	verbosity	verbosity level of this variable (integer)
OUT	datatype	MPI data type of the information stored in the control variable (handle)
OUT	enumtype	optional descriptor for enumeration information (handle)
OUT	desc	buffer to return the string containing a description of the control variable (string)
INOUT	desc_len	length of the string and/or buffer for desc (integer)
OUT	bind	type of MPI object to which this variable must be bound (integer)
OUT	scope	scope of when changes to this variable are possible (integer)

#### C binding

After a successful call to MPI\_T\_CVAR\_GET\_INFO for a particular variable, subsequent calls to this routine that query information about the same variable must return the same information. An MPI implementation is not allowed to alter any of the returned values.

If any OUT parameter to MPI\_T\_CVAR\_GET\_INFO is a NULL pointer, the implementation will ignore the parameter and not return a value for the parameter.

The arguments name and name\_len are used to return the name of the control variable as described in Section 15.3.3.

If completed successfully, the routine is required to return a name of at least length one. The name must be unique with respect to all other names for control variables used by the MPI implementation.

The argument verbosity returns the verbosity level of the variable (see Section 15.3.1). The argument datatype returns the MPI datatype that is used to represent the control variable.

If the variable is of type MPI\_INT, MPI can optionally specify an enumeration for the values represented by this variable and return it in enumtype. In this case, MPI returns an enumeration identifier, which can then be used to gather more information as described in Section 15.3.5. Otherwise, enumtype is set to MPI\_T\_ENUM\_NULL. If the datatype is not MPI\_INT or the argument enumtype is the null pointer, no enumeration type is returned.

The arguments desc and desc\_len are used to return a description of the control variable as described in Section 15.3.3.

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

Returning a description is optional. If an MPI implementation does not return a description, the first character for desc must be set to the null character and desc\_len must be set to one at the return of this call.

The parameter bind returns the type of the MPI object to which the variable must be bound or the value MPI\_T\_BIND\_NO\_OBJECT (see Section 15.3.2).

The scope of a variable determines whether changing a variable's value is either local to the MPI process or must be done by the user across multiple connected MPI processes. The latter is further split into variables that require changes in a group of MPI processes and those that require collective changes among all connected MPI processes. Both cases can require variables on all participating MPI processes either to be set to consistent (but potentially different) values or to equal values. The description provided with the variable must contain an explanation about the requirements and/or restrictions for setting the particular variable.

On successful return from MPI\_T\_CVAR\_GET\_INFO, the argument scope will be set to one of the constants listed in Table 15.4.

If the name of a control variable is equivalent across connected MPI processes, the following OUT parameters must be identical: verbosity, datatype, enumtype, bind, and scope. The returned description must be equivalent.

Scope Constant	Description
MPI_T_SCOPE_CONSTANT	read-only, value is constant
MPI_T_SCOPE_READONLY	read-only, cannot be written, but can change
MPI_T_SCOPE_LOCAL	may be writeable, writing is a local operation
MPI_T_SCOPE_GROUP	may be writeable, must be set to consistent values
	across a group of connected MPI processes
MPI_T_SCOPE_GROUP_EQ	may be writeable, must be set to the same value
	across a group of connected MPI processes
MPI_T_SCOPE_ALL	may be writeable, must be set to consistent values
	across all connected MPI processes
MPI_T_SCOPE_ALL_EQ	may be writeable, must be set to the same value
	across all connected MPI processes

Table 15.4: Scopes for control variables

Advice to users. The scope of a variable only indicates if a variable might be changeable; it is not a guarantee that it can be changed at any time. (End of advice to users.)

```
39
40
41
```

42 43

44

45 46

47

48

34 35 36

37

```
MPI_T_CVAR_GET_INDEX(name, cvar_index)
 IN
                                         name of the control variable (string)
            name
 OUT
            cvar_index
                                         index of the control variable (integer)
```

#### C binding

```
int MPI_T_cvar_get_index(const char *name, int *cvar_index)
```

11

12

13

14

15

16 17

18 19 20

21

22

MPI\_T\_CVAR\_GET\_INDEX is a function for retrieving the index of a control variable given a known variable name. The name parameter is provided by the caller, and cvar\_index is returned by the MPI implementation. The name parameter is a string terminated with a null character.

This routine returns MPI\_SUCCESS on success and returns MPI\_T\_ERR\_INVALID\_NAME if name does not match the name of any control variable provided by the implementation at the time of the call.

Rationale. This routine is provided to enable fast retrieval of control variables by a tool, assuming it knows the name of the variable for which it is looking. The number of variables exposed by the implementation can change over time, so it is not possible for the tool to simply iterate over the list of variables once at initialization. Although using MPI implementation specific variable names is not portable across MPI implementations, tool developers may choose to take this route for lower overhead at runtime because the tool will not have to iterate over the entire set of variables to find a specific one. (End of rationale.)

Example: Printing All Control Variables

**Example 15.4** The following example shows how the MPI tool information interface can be used to query and to print the names of all available control variables.

```
#include <stdio.h>
                                                                                     23
                                                                                     24
#include <stdlib.h>
                                                                                     25
#include <mpi.h>
                                                                                     26
                                                                                     27
int main(int argc, char *argv[]) {
                                                                                     28
  int i, err, num, namelen, bind, verbose, scope;
                                                                                     29
  int threadsupport;
  char name[100];
                                                                                     30
                                                                                     31
 MPI_Datatype datatype;
                                                                                     33
  err=MPI_T_init_thread(MPI_THREAD_SINGLE,&threadsupport);
                                                                                     34
  if (err!=MPI_SUCCESS)
                                                                                     35
    return err;
                                                                                     36
                                                                                     37
  err=MPI_T_cvar_get_num(&num);
                                                                                     38
  if (err!=MPI_SUCCESS)
                                                                                     39
    return err;
  for (i=0; i<num; i++) {
                                                                                     42
    namelen=100;
    err=MPI_T_cvar_get_info(i, name, &namelen,
                                                                                     43
                                                                                     44
            &verbose, &datatype, NULL,
            NULL, NULL, /*no description */
                                                                                     45
                                                                                     46
             &bind, &scope);
    if (err!=MPI_SUCCESS && err!=MPI_T_ERR_INVALID_INDEX) return err;
    printf("Var %i: %s\n", i, name);
```

```
1
       }
2
3
       err=MPI_T_finalize();
4
       if (err!=MPI_SUCCESS)
5
          return 1;
6
       else
7
          return 0;
8
     }
9
```

#### Handle Allocation and Deallocation

Before reading or writing the value of a variable, a user must first allocate a handle of type MPI\_T\_cvar\_handle for the variable by binding it to an MPI object (see also Section 15.3.2).

Rationale. Handles used in the MPI tool information interface are distinct from handles used in the remaining parts of the MPI standard because they must be usable before MPI is initialized and after MPI is finalized. Further, accessing handles, in particular for performance variables, can be time critical and having a separate handle space enables optimizations. (End of rationale.)

# MPI\_T\_CVAR\_HANDLE\_ALLOC(cvar\_index, obj\_handle, handle, count)

IN	cvar_index	index of control variable for which handle is to be
		allocated (index)
IN	obj_handle	reference to a handle of the MPI object to which this variable is supposed to be bound (pointer)
OUT	handle	allocated handle (handle)
OUT	count	number of elements used to represent this variable
		(integer)

#### C binding

This routine binds the control variable specified by the argument index to an MPI object. The object is passed in the argument obj\_handle as an address to a local variable that stores the object's handle. The argument obj\_handle is ignored if the MPI\_T\_CVAR\_GET\_INFO call for this control variable returned MPI\_T\_BIND\_NO\_OBJECT in the argument bind. The handle allocated to reference the variable is returned in the argument handle. Upon successful return, count contains the number of elements (of the datatype returned by a previous MPI\_T\_CVAR\_GET\_INFO call) used to represent this variable.

Advice to users. The count can be different based on the MPI object to which the control variable was bound. For example, variables bound to communicators could have a count that matches the size of the communicator.

It is not portable to pass references to predefined MPI object handles, such as MPI\_COMM\_WORLD to this routine, since their implementation depends on the MPI

11

12 13 14

15

16

17

18

19

20 21

22 23 24

26

27

28

29 30

31

32 33

34

35

36

37

38 39

46

library. Instead, such object handles should be stored in a local variable and the address of this local variable should be passed into MPI\_T\_CVAR\_HANDLE\_ALLOC. (End of advice to users.)

The value of cvar\_index should be in the range 0 to  $num_cvar - 1$ , where  $num_cvar$  is the number of available control variables as determined from a prior call to MPI\_T\_CVAR\_GET\_NUM. The type of the MPI object it references must be consistent with the type returned in the bind argument in a prior call to MPI\_T\_CVAR\_GET\_INFO.

# MPI\_T\_CVAR\_HANDLE\_FREE(handle)

INOUT handle handle to be freed (handle)

#### C binding

int MPI\_T\_cvar\_handle\_free(MPI\_T\_cvar\_handle \*handle)

When a handle is no longer needed, a user of the MPI tool information interface should call MPI\_T\_CVAR\_HANDLE\_FREE to free the handle and the associated resources in the MPI implementation. On a successful return, MPI sets the handle to MPI\_T\_CVAR\_HANDLE\_NULL.

Control Variable Access Functions

#### MPI\_T\_CVAR\_READ(handle, buf)

IN handle

handle to the control variable to be read (handle) OUT buf initial address of storage location for variable value (choice)

#### C binding

int MPI\_T\_cvar\_read(MPI\_T\_cvar\_handle handle, void \*buf)

This routine queries the value of a control variable identified by the argument handle and stores the result in the buffer identified by the parameter buf. The user must ensure that the buffer is of the appropriate size to hold the entire value of the control variable (based on the returned datatype and count from prior corresponding calls to MPI\_T\_CVAR\_GET\_INFO and MPI\_T\_CVAR\_HANDLE\_ALLOC, respectively).

#### MPI\_T\_CVAR\_WRITE(handle, buf)

IN	handle	handle to the control variable to be written (handle)
IN	buf	initial address of storage location for variable value
		(choice)

#### C binding

int MPI\_T\_cvar\_write(MPI\_T\_cvar\_handle handle, const void \*buf)

This routine sets the value of the control variable identified by the argument handle to the data stored in the buffer identified by the parameter buf. The user must ensure that the buffer is of the appropriate size to hold the entire value of the control variable (based on the returned datatype and count from prior corresponding calls to MPI\_T\_CVAR\_GET\_INFO and MPI\_T\_CVAR\_HANDLE\_ALLOC, respectively).

If the variable has a global scope (as returned by a prior corresponding MPI\_T\_CVAR\_GET\_INFO call), any write call to this variable must be issued by the user in all connected (as defined in Section 11.10.4) MPI processes. If the variable has group scope, any write call to this variable must be issued by the user in all MPI processes in the group, which must be described by the MPI implementation in the description by the MPI\_T\_CVAR\_GET\_INFO.

In both cases, the user must ensure that the writes in all participating MPI processes are consistent. If the scope is either MPI\_T\_SCOPE\_ALL\_EQ or MPI\_T\_SCOPE\_GROUP\_EQ this means that the variable in all connected MPI processes or MPI processes of the group, respectively, must be set to the same value.

If it is not possible to change the variable at the time the call is made, the function returns either MPI\_T\_ERR\_CVAR\_SET\_NOT\_NOW, if there may be a later time at which the variable could be set, or MPI\_T\_ERR\_CVAR\_SET\_NEVER, if the variable cannot be set for the remainder of the application's execution.

Example: Reading the Value of a Control Variable

**Example 15.5** The following example shows a routine that can be used to query the value with a control variable with a given index. The example assumes that the variable is intended to be bound to an MPI communicator.

```
27
     int getValue_int_comm(int index, MPI_Comm comm, int *val) {
28
       int err, count;
29
       MPI_T_cvar_handle handle;
30
31
       /* This example assumes that the variable index */
32
       /* can be bound to a communicator */
33
34
       err=MPI_T_cvar_handle_alloc(index, &comm, &handle, &count);
35
       if (err!=MPI_SUCCESS) return err;
36
37
       /* The following assumes that the variable is */
       /* represented by a single integer */
39
40
       err=MPI_T_cvar_read(handle,val);
41
       if (err!=MPI_SUCCESS) return err;
42
43
       err=MPI_T_cvar_handle_free(&handle);
44
       return err;
45
     }
46
```

#### 15.3.7 Performance Variables

The following section focuses on the ability to list and to query performance variables provided by the MPI implementation. Performance variables provide insight into MPI implementation specific internals and can represent information such as the state of the MPI implementation (e.g., waiting blocked, receiving, not active), aggregated timing data for submodules, or queue sizes and lengths.

Rationale. The interface for performance variables is separate from the interface for control variables, since performance variables have different requirements and parameters. By keeping them separate, the interface provides cleaner semantics and allows for more performance optimization opportunities. (*End of rationale*.)

Some performance variables and classes refer to *events*. In general, such events describe state transitions within software or hardware related to the performance of an MPI application. The events offered through the callback-driven event-notification interface described in Section 15.3.8 also refer to such state transitions; however, the set of state transitions referred to by performance variables and events as described in Section 15.3.8 may not be identical.

#### Performance Variable Classes

Each performance variable is associated with a class that describes its basic semantics, possible datatypes, basic behavior, its starting value, whether it can overflow, and when and how an MPI implementation can change the variable's value. The starting value is the value that is assigned to the variable the first time that it is used or whenever it is reset.

Advice to users. If a performance variable belongs to a class that can overflow, it is up to the user to protect against this overflow, e.g., by frequently reading and resetting the variable value. (End of advice to users.)

Advice to implementors. MPI implementations should use large enough datatypes for each performance variable to avoid overflows under normal circumstances. (End of advice to implementors.)

The classes are defined by the following constants:

#### MPI\_T\_PVAR\_CLASS\_STATE

A performance variable in this class represents a set of discrete states. Variables of this class are represented by MPI\_INT and can be set by the MPI implementation at any time. Variables of this type should be described further using an enumeration, as discussed in Section 15.3.5. The starting value is the current state of the implementation at the time that the starting value is set. MPI implementations must ensure that variables of this class cannot overflow.

#### • MPI\_T\_PVAR\_CLASS\_LEVEL

A performance variable in this class represents a value that describes the utilization level of a resource. The value of a variable of this class can change at any time to match the current utilization level of the resource. Values returned from variables in this class are non-negative and represented by one of the following datatypes: MPI\_UNSIGNED,

MPI\_UNSIGNED\_LONG, MPI\_UNSIGNED\_LONG\_LONG, MPI\_DOUBLE. The starting value

is the current utilization level of the resource at the time that the starting value is

A performance variable in this class represents a value that is the size of a resource.

Values returned from variables in this class are non-negative and represented by one

MPI\_UNSIGNED\_LONG\_LONG, MPI\_DOUBLE. The starting value is the current size of

the resource at the time that the starting value is set. MPI implementations must

The value of a performance variable in this class represents the percentage utiliza-

tion of a finite resource. The value of a variable of this class can change at any

time to match the current utilization level of the resource. It will be returned as an

MPI\_DOUBLE datatype. The value must always be between 0.0 (resource not used at

all) and 1.0 (resource completely used). The starting value is the current percent-

age utilization level of the resource at the time that the starting value is set. MPI

A performance variable in this class represents a value that describes the high water-

mark utilization of a resource. The value of a variable of this class is non-negative

and grows monotonically from the initialization or reset of the variable. It can be represented by one of the following datatypes: MPI\_UNSIGNED, MPI\_UNSIGNED\_LONG,

MPI\_UNSIGNED\_LONG\_LONG, MPI\_DOUBLE. The starting value is the current utiliza-

tion level of the resource at the time that the variable is started or reset. MPI imple-

A performance variable in this class represents a value that describes the low water-

mark utilization of a resource. The value of a variable of this class is non-negative

and decreases monotonically from the initialization or reset of the variable. It can be

represented by one of the following datatypes: MPI\_UNSIGNED, MPI\_UNSIGNED\_LONG,

MPI\_UNSIGNED\_LONG\_LONG, MPI\_DOUBLE. The starting value is the current utiliza-

tion level of the resource at the time that the variable is started or reset. MPI imple-

A performance variable in this class counts the number of occurrences of a specific

event (e.g., the number of memory allocations within an MPI library). The value of

a variable of this class increases monotonically from the initialization or reset of the

performance variable by one for each specific event that is observed. Values must

be non-negative and represented by one of the following datatypes: MPI\_UNSIGNED,

MPI\_UNSIGNED\_LONG, MPI\_UNSIGNED\_LONG\_LONG. The starting value for variables

implementations must ensure that variables of this class cannot overflow.

mentations must ensure that variables of this class cannot overflow.

mentations must ensure that variables of this class cannot overflow.

of the following datatypes: MPI\_UNSIGNED, MPI\_UNSIGNED\_LONG,

ensure that variables of this class cannot overflow.

set. MPI implementations must ensure that variables of this class cannot overflow.

MPI\_T\_PVAR\_CLASS\_SIZE

MPI\_T\_PVAR\_CLASS\_PERCENTAGE

• MPI\_T\_PVAR\_CLASS\_HIGHWATERMARK

• MPI\_T\_PVAR\_CLASS\_LOWWATERMARK

2 3

1

5 6

9 10 11

12 13

14

15 16 17

18 19 20

21 22 23

> 24 26 27

28 29 30

31

32 33 34

36 37

39

40

35

45

46 47

The value of a performance variable in this class is an an aggregated value that

• MPI\_T\_PVAR\_CLASS\_AGGREGATE

MPI\_T\_PVAR\_CLASS\_COUNTER

of this class is 0. Variables of this class can overflow.

**Unofficial Draft for Comment Only** 

represents a sum of arguments processed during a specific event (e.g., the amount of memory allocated by all memory allocations). This class is similar to the counter class, but instead of counting individual events, the value can be incremented by arbitrary amounts. The value of a variable of this class increases monotonically from the initialization or reset of the performance variable. It must be non-negative and represented by one of the following datatypes: MPI\_UNSIGNED, MPI\_UNSIGNED\_LONG, MPI\_UNSIGNED\_LONG, MPI\_DOUBLE. The starting value for variables of this class is 0. Variables of this class can overflow.

#### • MPI\_T\_PVAR\_CLASS\_TIMER

The value of a performance variable in this class represents the aggregated time that the MPI implementation spends executing a particular event, type of event, or section of the MPI library. This class has the same basic semantics as MPI\_T\_PVAR\_CLASS\_AGGREGATE, but explicitly records a timing value. The value of a variable of this class increases monotonically from the initialization or reset of the performance variable. It must be non-negative and represented by one of the following datatypes: MPI\_UNSIGNED, MPI\_UNSIGNED\_LONG, MPI\_UNSIGNED\_LONG, MPI\_DOUBLE. The starting value for variables of this class is 0. If the type MPI\_DOUBLE is used, the units that represent time in this datatype must match the units used by MPI\_WTIME. Otherwise, the time units should be documented, e.g., in the description returned by MPI\_T\_PVAR\_GET\_INFO. Variables of this class can overflow.

#### MPI\_T\_PVAR\_CLASS\_GENERIC

This class can be used to describe a variable that does not fit into any of the other classes. For variables in this class, the starting value is variable-specific and implementation-defined.

#### Performance Variable Query Functions

An MPI implementation exports a set of N performance variables through the MPI tool information interface. If N is zero, then the MPI implementation does not export any performance variables; otherwise the provided performance variables are indexed from 0 to N-1. This index number is used in subsequent calls to identify the individual variables.

An MPI implementation is allowed to increase the number of performance variables during the execution of an MPI application when new variables become available through dynamic loading. However, MPI implementations are not allowed to change the index of a performance variable or to delete a variable once it has been added to the set. When a variable becomes inactive, e.g., through dynamic unloading, accessing its value should return a corresponding error code.

The following function can be used to query the number of performance variables, num\_pvar:

```
MPI_T_PVAR_GET_NUM(num_pvar)

OUT num_pvar returns number of performance variables (integer)
```

C binding

int MPI\_T\_pvar\_get\_num(int \*num\_pvar)

The function MPI\_T\_PVAR\_GET\_INFO provides access to additional information for each variable.

5 6

> 34 35

> 36

37

38

39

41

42

43

44

45

46

47

48

1

2

3

4

MPI\_T\_PVAR\_GET\_INFO(pvar\_index, name, name\_len, verbosity, var\_class, datatype, enumtype, desc, desc\_len, bind, readonly, continuous, atomic)

8		enantype, dese, dese_ten	, bind, readonly, continuous, atomic)
9	IN	pvar_index	index of the performance variable to be queried between 0 and $num\_pvar - 1$ (integer)
11 12	OUT	name	buffer to return the string containing the name of the performance variable (string)
13	INOUT	name_len	length of the string and/or buffer for name (integer)
14 15	OUT	verbosity	verbosity level of this variable (integer)
16	OUT	var_class	class of performance variable (integer)
17 18	OUT	datatype	MPI datatype of the information stored in the performance variable (handle)
19 20 21	OUT	enumtype	optional descriptor for enumeration information (handle)
22 23	OUT	desc	buffer to return the string containing a description of the performance variable (string)
24	INOUT	desc_len	length of the string and/or buffer for desc (integer)
25 26 27	OUT	bind	type of MPI object to which this variable must be bound (integer)
28 29	OUT	readonly	flag indicating whether the variable can be written/reset (integer)
30 31	OUT	continuous	flag indicating whether the variable can be started and stopped or is continuously active (integer)
32 33	OUT	atomic	flag indicating whether the variable can be

# C binding

```
int MPI_T_pvar_get_info(int pvar_index, char *name, int *name_len,
             int *verbosity, int *var_class, MPI_Datatype *datatype,
             MPI_T_enum *enumtype, char *desc, int *desc_len, int *bind,
             int *readonly, int *continuous, int *atomic)
```

atomically read and reset (integer)

After a successful call to MPI\_T\_PVAR\_GET\_INFO for a particular variable, subsequent calls to this routine that query information about the same variable must return the same information. An MPI implementation is not allowed to alter any of the returned values.

If any OUT parameter to MPI\_T\_PVAR\_GET\_INFO is a NULL pointer, the implementation will ignore the parameter and not return a value for the parameter.

The arguments name and name\_len are used to return the name of the performance variable as described in Section 15.3.3. If completed successfully, the routine is required to return a name of at least length one.

The argument verbosity returns the verbosity level of the variable (see Section 15.3.1). The class of the performance variable is returned in the parameter var\_class. The class must be one of the constants defined in Section 15.3.7.

The combination of the name and the class of the performance variable must be unique with respect to all other names for performance variables used by the MPI implementation.

Advice to implementors. Groups of variables that belong closely together, but have different classes, can have the same name. This choice is useful, e.g., to refer to multiple variables that describe a single resource (like the level, the total size, as well as high and low watermarks). (End of advice to implementors.)

The argument datatype returns the MPI datatype that is used to represent the performance variable.

If the variable is of type MPI\_INT, MPI can optionally specify an enumeration for the values represented by this variable and return it in enumtype. In this case, MPI returns an enumeration identifier, which can then be used to gather more information as described in Section 15.3.5. Otherwise, enumtype is set to MPI\_T\_ENUM\_NULL. If the datatype is not MPI\_INT or the argument enumtype is the null pointer, no enumeration type is returned.

Returning a description is optional. If an MPI implementation does not return a description, the first character for desc must be set to the null character and desc\_len must be set to one at the return from this function.

The parameter bind returns the type of the MPI object to which the variable must be bound or the value MPI\_T\_BIND\_NO\_OBJECT (see Section 15.3.2).

Upon return, the argument readonly is set to zero if the variable can be written or reset by the user. It is set to one if the variable can only be read.

Upon return, the argument continuous is set to zero if the variable can be started and stopped by the user, i.e., it is possible for the user to control if and when the value of a variable is updated. It is set to one if the variable is always active and cannot be controlled by the user.

Upon return, the argument atomic is set to zero if the variable cannot be read and reset atomically. Only variables for which the call sets atomic to one can be used in a call to MPI\_T\_PVAR\_READRESET.

If a performance variable has an equivalent name and has the same class across connected MPI processes, the following OUT parameters must be identical: verbosity, varclass, datatype, enumtype, bind, readonly, continuous, and atomic. The returned description must be equivalent.

## MPI\_T\_PVAR\_GET\_INDEX(name, var\_class, pvar\_index)

IN	name	the name of the performance variable (string)
IN	var_class	the class of the performance variable (integer)
OUT	pvar_index	the index of the performance variable (integer)

#### C binding

```
int MPI_T_pvar_get_index(const char *name, int var_class, int *pvar_index)
```

MPI\_T\_PVAR\_GET\_INDEX is a function for retrieving the index of a performance variable given a known variable name and class. The name and var\_class parameters are

 provided by the caller, and pvar\_index is returned by the MPI implementation. The name parameter is a string terminated with a null character.

This routine returns MPI\_SUCCESS on success and returns MPI\_T\_ERR\_INVALID\_NAME if name does not match the name of any performance variable of the specified var\_class provided by the implementation at the time of the call.

Rationale. This routine is provided to enable fast retrieval of performance variables by a tool, assuming it knows the name of the variable for which it is looking. The number of variables exposed by the implementation can change over time, so it is not possible for the tool to simply iterate over the list of variables once at initialization. Although using MPI implementation specific variable names is not portable across MPI implementations, tool developers may choose to take this route for lower overhead at runtime because the tool will not have to iterate over the entire set of variables to find a specific one. (End of rationale.)

#### Performance Experiment Sessions

Within a single program, multiple components can use the MPI tool information interface. To avoid collisions with respect to accesses to performance variables, users of the MPI tool information interface must first create a session. Subsequent calls that access performance variables can then be made within the context of this session. Starting, stopping, reading, writing, or resetting a variable in one performance experiment session shall not influence whether a variable is started, stopped, read, written, or reset in another performance experiment session.

#### MPI\_T\_PVAR\_SESSION\_CREATE(session)

OUT session identifier of performance session (handle)

#### C binding

int MPI\_T\_pvar\_session\_create(MPI\_T\_pvar\_session \*session)

This call creates a new session for accessing performance variables and returns a handle for this session in the argument session of type MPI\_T\_pvar\_session.

# MPI\_T\_PVAR\_SESSION\_FREE(session)

INOUT session identifier of performance experiment session (handle)

#### C binding

int MPI\_T\_pvar\_session\_free(MPI\_T\_pvar\_session \*session)

This call frees an existing session. Calls to the MPI tool information interface can no longer be made within the context of a session after it is freed. On a successful return, MPI sets the session identifier to MPI\_T\_PVAR\_SESSION\_NULL.

#### Handle Allocation and Deallocation

Before using a performance variable, a user must first allocate a handle of type MPI\_T\_pvar\_handle for the variable by binding it to an MPI object (see also Section 15.3.2).

# MPI\_T\_PVAR\_HANDLE\_ALLOC(session, pvar\_index, obj\_handle, handle, count)

IN	session	identifier of performance experiment session (handle)
IN	pvar_index	index of performance variable for which handle is to be allocated (integer)
IN	obj_handle	reference to a handle of the MPI object to which this variable is supposed to be bound (pointer)
OUT	handle	allocated handle (handle)
OUT	count	number of elements used to represent this variable (integer)

#### C binding

This routine binds the performance variable specified by the argument index to an MPI object in the session identified by the parameter session. The object is passed in the argument obj\_handle as an address to a local variable that stores the object's handle. The argument obj\_handle is ignored if the MPI\_T\_PVAR\_GET\_INFO call for this performance variable returned MPI\_T\_BIND\_NO\_OBJECT in the argument bind. The handle allocated to reference the variable is returned in the argument handle. Upon successful return, count contains the number of elements (of the datatype returned by a previous MPI\_T\_PVAR\_GET\_INFO call) used to represent this variable.

Advice to users. The count can be different based on the MPI object to which the performance variable was bound. For example, variables bound to communicators could have a count that matches the size of the communicator.

It is not portable to pass references to predefined MPI object handles, such as MPI\_COMM\_WORLD, to this routine, since their implementation depends on the MPI library. Instead, such an object handle should be stored in a local variable and the address of this local variable should be passed into MPI\_T\_PVAR\_HANDLE\_ALLOC. (End of advice to users.)

The value of index should be in the range 0 to num\_pvar - 1, where num\_pvar is the number of available performance variables as determined from a prior call to MPI\_T\_PVAR\_GET\_NUM. The type of the MPI object it references must be consistent with the type returned in the bind argument in a prior call to MPI\_T\_PVAR\_GET\_INFO.

For all routines in the rest of this section that take both handle and session as IN or INOUT arguments, if the handle argument passed in is not associated with the session argument, MPI\_T\_ERR\_INVALID\_HANDLE is returned.

```
MPI_T_PVAR_HANDLE_FREE(session, handle)
```

```
IN session identifier of performance experiment session (handle)

INOUT handle handle to be freed (handle)
```

# C binding

When a handle is no longer needed, a user of the MPI tool information interface should call MPI\_T\_PVAR\_HANDLE\_FREE to free the handle in the session identified by the parameter session and the associated resources in the MPI implementation. On a successful return, MPI sets the handle to MPI\_T\_PVAR\_HANDLE\_NULL.

#### Starting and Stopping of Performance Variables

Performance variables that have the continuous flag set during the query operation are continuously operating once a handle has been allocated. Such variables may be queried at any time, but they cannot be started or stopped by the user. All other variables are in a stopped state after their handle has been allocated; their values are not updated until they have been started by the user.

# MPI\_T\_PVAR\_START(session, handle)

IN	session	identifier of performance experiment session (handle)
IN	handle	handle of a performance variable (handle)

#### C binding

```
int MPI_T_pvar_start(MPI_T_pvar_session session, MPI_T_pvar_handle handle)
```

This functions starts the performance variable with the handle identified by the parameter handle in the session identified by the parameter session.

If the constant MPI\_T\_PVAR\_ALL\_HANDLES is passed in handle, the MPI implementation attempts to start all variables within the session identified by the parameter session for which handles have been allocated. In this case, the routine returns MPI\_SUCCESS if all variables are started successfully (even if there are no non-continuous variables to be started), otherwise MPI\_T\_ERR\_PVAR\_NO\_STARTSTOP is returned. Continuous variables and variables that are already started are ignored when MPI\_T\_PVAR\_ALL\_HANDLES is specified.

#### MPI\_T\_PVAR\_STOP(session, handle)

IN	session	identifier of performance experiment session (handle)
IN	handle	handle of a performance variable (handle)

#### C binding

```
int MPI_T_pvar_stop(MPI_T_pvar_session session, MPI_T_pvar_handle handle)
```

This functions stops the performance variable with the handle identified by the parameter handle in the session identified by the parameter session.

If the constant MPI\_T\_PVAR\_ALL\_HANDLES is passed in handle, the MPI implementation attempts to stop all variables within the session identified by the parameter session for which handles have been allocated. In this case, the routine returns MPI\_SUCCESS if all variables are stopped successfully (even if there are no non-continuous variables to be stopped), otherwise MPI\_T\_ERR\_PVAR\_NO\_STARTSTOP is returned. Continuous variables and variables that are already stopped are ignored when MPI\_T\_PVAR\_ALL\_HANDLES is specified.

Performance Variable Access Functions

#### MPI\_T\_PVAR\_READ(session, handle, buf)

IN	session	$identifier \ of \ performance \ experiment \ session \ (handle)$
IN	handle	handle of a performance variable (handle)
OUT	buf	initial address of storage location for variable value (choice)

#### C binding

The MPI\_T\_PVAR\_READ call queries the value of the performance variable with the handle handle in the session identified by the parameter session and stores the result in the buffer identified by the parameter buf. The user is responsible to ensure that the buffer is of the appropriate size to hold the entire value of the performance variable (based on the datatype and count returned by the corresponding previous calls to MPI\_T\_PVAR\_GET\_INFO and MPI\_T\_PVAR\_HANDLE\_ALLOC, respectively).

The constant  $MPI\_T\_PVAR\_ALL\_HANDLES$  cannot be used as an argument for the function  $MPI\_T\_PVAR\_READ$ .

# MPI\_T\_PVAR\_WRITE(session, handle, buf)

IN sess	ion	identifier of performance experiment session (handle)
IN han	dle	handle of a performance variable (handle)
IN buf		initial address of storage location for variable value (choice)

#### C binding

The MPI\_T\_PVAR\_WRITE call attempts to write the value of the performance variable with the handle identified by the parameter handle in the session identified by the parameter session. The value to be written is passed in the buffer identified by the parameter buf. The user must ensure that the buffer is of the appropriate size to hold the entire value of the per-

formance variable (based on the datatype and count returned by the corresponding previous calls to MPI\_T\_PVAR\_GET\_INFO and MPI\_T\_PVAR\_HANDLE\_ALLOC, respectively).

If it is not possible to change the variable, the function returns MPI\_T\_ERR\_PVAR\_NO\_WRITE.

The constant MPI\_T\_PVAR\_ALL\_HANDLES cannot be used as an argument for the function MPI\_T\_PVAR\_WRITE.

# MPI\_T\_PVAR\_RESET(session, handle)

```
IN session identifier of performance experiment session (handle)IN handle handle of a performance variable (handle)
```

# 

#### C binding

```
int MPI_T_pvar_reset(MPI_T_pvar_session session, MPI_T_pvar_handle handle)
```

The MPI\_T\_PVAR\_RESET call sets the performance variable with the handle identified by the parameter handle to its starting value specified in Section 15.3.7. If it is not possible to change the variable, the function returns MPI\_T\_ERR\_PVAR\_NO\_WRITE.

If the constant MPI\_T\_PVAR\_ALL\_HANDLES is passed in handle, the MPI implementation attempts to reset all variables within the session identified by the parameter session for which handles have been allocated. In this case, the routine returns MPI\_SUCCESS if all variables are reset successfully (even if there are no valid handles or all are read-only), otherwise MPI\_T\_ERR\_PVAR\_NO\_WRITE is returned. Read-only variables are ignored when MPI\_T\_PVAR\_ALL\_HANDLES is specified.

# 

#### MPI\_T\_PVAR\_READRESET(session, handle, buf)

IN	session	identifier of performance experiment session (handle)
IN	handle	handle of a performance variable (handle)
OUT	buf	initial address of storage location for variable value
		(choice)

# 

#### C binding

This call atomically combines the functionality of MPI\_T\_PVAR\_READ and MPI\_T\_PVAR\_RESET with the same semantics as if these two calls were called separately. If atomic operations on this variable are not supported, this routine returns MPI\_T\_ERR\_PVAR\_NO\_ATOMIC.

The constant MPI\_T\_PVAR\_ALL\_HANDLES cannot be used as an argument for the function MPI\_T\_PVAR\_READRESET.

Advice to implementors. Sampling-based tools rely on the ability to call the MPI tool information interface, in particular routines to start, stop, read, write, and reset performance variables, from any program context, including asynchronous contexts such as signal handlers. MPI implementations should strive, if possible in their particular

environment, to enable these usage scenarios for all or a subset of the routines mentioned above. If implementing only a subset, the read, write, and reset routines are typically the most critical for sampling based tools. An MPI implementation should clearly document any restrictions on the program contexts in which the MPI tool information interface can be used. Restrictions might include guaranteeing usage outside of all signals or outside a specific set of signals. Any restrictions could be documented, for example, through the description returned by MPI\_T\_PVAR\_GET\_INFO. (End of advice to implementors.)

Rationale. All routines to read, to write or to reset performance variables require the session argument. This requirement keeps the interface consistent and allows the use of MPI\_T\_PVAR\_ALL\_HANDLES where appropriate. Further, this opens up additional performance optimizations for the implementation of handles. (*End of rationale*.)

Example: Tool to Detect Receives with Long Unexpected Message Queues

**Example 15.6** The following example shows a sample tool to identify receive operations that occur during times with long message queues. This examples assumes that the MPI implementation exports a variable with the name "MPI\_T\_UMQ\_LENGTH" to represent the current length of the unexpected message queue. The tool is implemented as a PMPI tool using the MPI profiling interface.

The tool consists of three parts: (1) the initialization (by intercepting the call to MPI\_INIT), (2) the test for long unexpected message queues (by intercepting calls to MPI\_RECV), and (3) the clean-up phase (by intercepting the call to MPI\_FINALIZE). To capture all receives, the example would have to be extended to have similar wrappers for all receive operations.

Part 1—Initialization: During initialization, the tool searches for the variable and, once the right index is found, allocates a session and a handle for the variable with the found index, and starts the performance variable.

```
#include <stdio.h>
#include <stdib.h>
#include <string.h>
#include <assert.h>
#include <mpi.h>

/* Global variables for the tool */
static MPI_T_pvar_session session;
static MPI_T_pvar_handle handle;

int MPI_Init(int *argc, char ***argv ) {
    int err, num, i, index, namelen, verbosity;
    int var_class, bind, threadsup;
    int readonly, continuous, atomic, count;
    char name[18];
    MPI_Comm comm;
    MPI_Datatype datatype;
```

```
1
           MPI_T_enum enumtype;
2
           err=PMPI_Init(argc, argv);
           if (err!=MPI_SUCCESS) return err;
           err=PMPI_T_init_thread(MPI_THREAD_SINGLE, &threadsup);
           if (err!=MPI_SUCCESS) return err;
           err=PMPI_T_pvar_get_num(&num);
           if (err!=MPI_SUCCESS) return err;
           index=-1;
12
           i=0;
13
           while ((i<num) && (index<0) && (err==MPI_SUCCESS)) {
14
                 /* Pass a buffer that is at least one character longer than */
15
                 /* the name of the variable being searched for to avoid */
16
                 /* finding variables that have a name that has a prefix */
                 /* equal to the name of the variable being searched. */
                 namelen=18;
19
                 err=PMPI_T_pvar_get_info(i, name, &namelen, &verbosity,
20
                          &var_class, &datatype, &enumtype, NULL, NULL, &bind,
21
                          &readonly, &continuous, &atomic);
22
                 if (strcmp(name, "MPI_T_UMQ_LENGTH") == 0) index = i;
23
                 i++; }
           if (err!=MPI_SUCCESS) return err;
           /* this could be handled in a more flexible way for a generic tool */
27
           assert(index>=0);
           assert(var_class==MPI_T_PVAR_CLASS_LEVEL);
           assert(datatype==MPI_INT);
30
           assert(bind==MPI_T_BIND_MPI_COMM);
           /* Create a session */
           err=PMPI_T_pvar_session_create(&session);
34
           if (err!=MPI_SUCCESS) return err;
35
36
           /* Get a handle and bind to MPI_COMM_WORLD */
37
           comm=MPI_COMM_WORLD;
           err=PMPI_T_pvar_handle_alloc(session, index, &comm, &handle, &count);
           if (err!=MPI_SUCCESS) return err;
           /* this could be handled in a more flexible way for a generic tool */
           assert(count==1);
43
44
           /* Start variable */
45
           err=PMPI_T_pvar_start(session, handle);
           if (err!=MPI_SUCCESS) return err;
47
           return MPI_SUCCESS;
```

}

12 13

14

15

16

18

19

20

21

22 23 24

26 27

28

29 30

31

33

34

35

36

37

43

45

46

47

```
Part 2—Testing the Queue Lengths During Receives: During every receive operation, the
tool reads the unexpected queue length through the matching performance variable and
compares it against a predefined threshold.
#define THRESHOLD 5
int MPI_Recv(void *buf, int count, MPI_Datatype datatype, int source,
              int tag, MPI_Comm comm, MPI_Status *status)
{
        int value, err;
        if (comm==MPI_COMM_WORLD) {
                 err=PMPI_T_pvar_read(session, handle, &value);
                 if ((err==MPI_SUCCESS) && (value>THRESHOLD))
                 {
                         /* tool identified receive called with long UMQ */
                         /* execute tool functionality, */
                         /* e.g., gather and print call stack */
                 }
        }
        return PMPI_Recv(buf, count, datatype, source, tag, comm, status);
}
Part 3—Termination: In the wrapper for MPI_FINALIZE, the MPI tool information interface
is finalized.
int MPI_Finalize(void)
{
    int err;
    err=PMPI_T_pvar_handle_free(session, &handle);
    err=PMPI_T_pvar_session_free(&session);
    err=PMPI_T_finalize();
    return PMPI_Finalize();
}
```

#### 15.3.8 Events

During the execution of an MPI application, the MPI implementation can raise events of a specific type to inform the user of a state change in the implementation. Event types describe specific state changes within the MPI implementation. In comparison to aggregate performance variables, events provide per-instance information on such state changes. The MPI implementation is said to raise an event when it invokes a callback function previously registered for the corresponding event type by the user. Each callback invocation for a specific event instance has a timestamp associated with it, which can be queried by the user, describing the time when the event was observed by the implementation. This decouples

the observation of the state change from the communication of this information to the user. A timestamp in this context is a count of clock ticks elapsed since some time in the past and represented as a variable of type MPI\_Count.

#### **Event Sources**

As a means to manage multiple state changes to be observed concurrently by different parts of the software and hardware system, the event interface of the MPI Tool Information Interface uses the concept of *sources*. A source in this context is a concept describing the logical entity raising the event. A source may or may not directly represent a concrete part of the software or hardware system. This concept is used primarily to describe partial ordering of events across different components where total ordering cannot necessarily be determined or is too costly to enforce.

The following function can be used to query the number of event sources, num\_sources:

# MPI\_T\_SOURCE\_GET\_NUM(num\_sources)

OUT num\_sources returns number of event sources (integer)

#### C binding

int MPI\_T\_source\_get\_num(int \*num\_sources)

The number of available event sources can be queried with a call to MPI\_T\_SOURCE\_GET\_NUM. An MPI implementation is allowed to increase the number of sources during the execution of an MPI process. However, MPI implementations are not allowed to change the index of an event source or to delete an event source once it has been made visible to the user (e.g., if new event sources become available via dynamic loading of additional components in the MPI implementation).





MPI_T_SOURCE_GET_INFO(source_index, name	, name_len	, desc, des	c_len, ordering,
ticks_per_second, max_ticks, info	1		

IN	source_index	index of the source to be queried between 0 and $num\_sources - 1$ (integer)
OUT	name	buffer to return the string containing the name of the source (string)
INOUT	name_len	length of the string and/or buffer for name (integer)
OUT	desc	buffer to return the string containing the description of the source (string)
INOUT	desc_len	length of the string and/or buffer for desc (integer)
OUT	ordering	flag indicating chronological ordering guarantees given by the source (integer)
OUT	ticks_per_second	the number of ticks per second for the timer of this source (integer)
OUT	max_ticks	the maximum count of ticks reported by this source before overflow occurs (integer)
OUT	info	optional info object (handle)

#### C binding

A call to MPI\_T\_SOURCE\_GET\_INFO returns additional information on the source identified by the source\_index argument.

The arguments name and name\_len are used to return the name of the source as described in Section 15.3.3.

The arguments desc and desc\_len are used to return the description of the source as described in Section 15.3.3.

The ordering argument returns whether event callbacks of this source will be invoked in chronological order, i.e., the timestamps reported by MPI\_T\_EVENT\_GET\_TIMESTAMP of subsequent events of the same source are monotonically increasing. The value of ordering can be MPI\_T\_SOURCE\_ORDERED or MPI\_T\_SOURCE\_UNORDERED.

The ticks\_per\_seconds argument returns the number of ticks elapsed in one second for the timer used for the specific source.

The max\_ticks argument returns the largest number of ticks reported by this source as a timestamp before the value overflows.

Advice to users. As the size of MPI\_Count is defined in relation to the types MPI\_Aint and MPI\_Offset, the effective size of MPI\_Count may lead to overflows of the timestamp values reported. Users can use the argument max\_ticks to mitigate resulting problems. (End of advice to users.)

MPI can optionally return an info object containing the default hints set for this source. If the argument to info provided by the user is the NULL pointer, this argument is ignored,

otherwise an MPI implementation is required to return all hints that are supported by the implementation for this source and have default values specified; any user-supplied hints that were not ignored by the implementation; and any additional hints that were set by the implementation. If no such hints exist, a handle to a newly created info object is returned that contains no key/value pair. The user is responsible for freeing info via MPI\_INFO\_FREE.

 $\frac{44}{45}$ 

# MPI\_T\_SOURCE\_GET\_TIMESTAMP(source\_index, timestamp)

```
IN source_index index of the source (integer)

OUT timestamp current timestamp from specified source (integer)
```

#### C binding

```
int MPI_T_source_get_timestamp(int source_index, MPI_Count *timestamp)
```

To enable proper query of a reference timestamp for a specific source, a user can obtain a current timestamp using MPI\_T\_SOURCE\_GET\_TIMESTAMP. The argument source\_index identifies the index of the source to query. The call returns MPI\_SUCCESS and a current timestamp in the argument timestamp if the source supports ad-hoc generation of timestamps. The call returns MPI\_T\_ERR\_INVALID\_INDEX if the index does not identify a valid source. The call returns MPI\_T\_ERR\_NOT\_SUPPORTED if the source does not support the ad-hoc generation of timestamps.

#### Callback Safety Requirements

The actions a user is allowed to perform inside a callback function may vary with its execution context. As the user has no control over the execution context of specific callback function invocations, MPI provides a way to communicate this information using callback safety levels.

```
Safety Requirement #335

MPI_T_CB_REQUIRE_NONE #-358+359

MPI_T_CB_REQUIRE_MPI_RESTRICTED #2.2. p 10

MPI_T_CB_REQUIRE_THREAD_SAFE MPI_T_CB_REQUIRE_ASYNC_SIGNAL_SAFE 34 character !!!

Proposal: Change to MPI_T_CB_REQUIRE_ASYNC_SIG_SAFE (31 character)

#-error #335
#-358+359
2.2. p 10
18.1 p.717
19.1.5 p789

B.1.2 p.10318
```

Table 15.5: Hierarchy of safety requirement levels for event callback routines.

Table 15.5 provides the hierarchy of callback safety requirements levels within user-defined callback functions. The MPI implementation provides the safety requirement as an argument to the callback when it is invoked.

The level of MPI\_T\_CB\_REQUIRE\_NONE is the lowest level and does not impose any restrictions on the callback function.

The level of MPI\_T\_CB\_REQUIRE\_MPI\_RESTRICTED restricts the set of MPI functions that can be called from inside the callback to all functions with the prefix MPI\_T as well as MPI\_WTICK and MPI\_WTIME.

Advice to users. While some MPI functions are safe to be called inside a callback

#-error

-335

1 p.7

34 character!!!

12

13

18 19

20

21

22 23

24

26

27

28

29

30

31

33

34

35

36

37

38

41 42 43

44

45

46

47 48

.5<mark>/</mark>p789 9 B.1.2 p.1031ff

function used in the MPI tool information interface—which may in some implementations be issued from asynchronous contexts such as signal handlers—this does not imply that those MPI functions are generally safe to be called in asynchronous contexts such as signal handlers. (End of advice to users.)

The level of MPI\_T\_CB\_REQUIRE\_THREAD\_SAFE includes all the limitations of MPI\_T\_CB\_REQUIRE\_MPI\_RESTRICTED and additionally requires the callback to be reentrant and thread-safe. This means the callback must allow its execution to be interrupted by or happen concurrently with any other callback including itself.

The level of MPI\_T\_CB\_REQUIRE\_ASYNC\_SIGNAL\_SAFE includes all the limitations of MPI\_T\_CB\_REQUIRE\_THREAD\_SAFE and additionally requires the callback to meet the safety requirements needed to support invocations from asynchronous contexts, such as signal handlers.

Advice to users. It is always safe to assume the highest restrictions for a callback invocation (i.e., MPI\_T\_CB\_REQUIRE\_ASYNC\_SIGNAL\_SAFE). By evaluating the spe- [34 character!!! cific requirements at runtime, a tool may obtain more freedom of action within the callback. (End of advice to users.)

A high-quality implementation will strive to set callback Advice to implementors. safety requirements to the most permissive level for a given callback invocation. (Endof advice to implementors.)

All functions with the prefix MPI\_T, except those listed in Table 15.6, may return the error code MPI\_T\_ERR\_NOT\_ACCESSIBLE to indicate that the user may not access this function at this time.

```
MPI_T_EVENT_COPY
                             PMPI_T_EVENT_COPY
MPI_T_EVENT_GET_SOURCE
                             PMPI_T_EVENT_GET_SOURCE
MPI_T_EVENT_GET_TIMESTAMP
                             PMPI_T_EVENT_GET_TIMESTAMP
MPI_T_EVENT_READ
                             PMPI_T_EVENT_READ
MPI_T_PVAR_READ
                             PMPI_T_PVAR_READ
MPI_T_PVAR_READRESET
                             PMPI_T_PVAR_READRESET
MPI_T_PVAR_RESET
                             PMPI_T_PVAR_RESET
MPI_T_PVAR_START
                             PMPI_T_PVAR_START
MPI_T_PVAR_STOP
                             PMPI_T_PVAR_STOP
MPI_T_PVAR_WRITE
                             PMPI_T_PVAR_WRITE
MPI_T_SOURCE_GET_TIMESTAMP
                             PMPI_T_SOURCE_GET_TIMESTAMP
```

Table 15.6: List of MPI functions that when called from within a callback function may not return MPI\_T\_ERR\_NOT\_ACCESSIBLE.

A call may be implemented in a way that is not safe for all execution contexts of a callback function, e.g., inside a signal handler. An MPI implementation therefore needs a way to communicate its inability to perform a certain action due to the execution context of a callback invocation. (End of rationale.)

Advice to implementors. A high-quality implementation shall not return MPI\_T\_ERR\_NOT\_ACCESSIBLE except where absolutely necessary. (End of advice to implementors.)

Advice to users. Users intercepting calls into the MPI tool information interface using the PMPI interface must ensure that the safety requirements for the calling context are met. This means that users may have to implement the wrapper with the highest safety level used by the MPI implementation. (End of advice to users.)

#### **Event Type Query Functions**

An MPI implementation exports a set of N event types through the MPI tool information interface. If N is zero, then the MPI implementation does not export any event types; otherwise, the provided event types are indexed from 0 to N-1. This index number is used in subsequent calls to identify a specific event type.

An MPI implementation is allowed to increase the number of event types during the execution of an MPI process. However, MPI implementations are not allowed to change the index of an event type or to delete an event type once it has been made visible to the user (e.g., if new event types become available via dynamic loading of additional components in the MPI implementation).

The following function can be used to query the number of event types, num\_events:

# MPI\_T\_EVENT\_GET\_NUM(num\_events)

OUT num\_events

returns number of event types (integer)

#### C binding

int MPI\_T\_event\_get\_num(int \*num\_events)

The function MPI\_T\_EVENT\_GET\_INFO provides access to additional information about a specific event type.

MPI\_T\_EVENT\_GET\_INFO(event\_index, name, name\_len, verbosity, array\_of\_datatypes, array\_of\_displacements, num\_elements, enumtype, info, desc, desc\_len, bind)

IN	event_index	index of the event type to be queried between 0 and $num\_events - 1$ (integer)
OUT	name	buffer to return the string containing the name of the event type (string)
INOUT	name_len	length of the string and/or buffer for name (integer)
OUT	verbosity	verbosity level of this event type (integer)
OUT	array_of_datatypes	array of MPI basic data types used to encode the event data (array of handles)
OUT	array_of_displacements	array of byte displacements of the elements in the event buffer (array of non-negative integers)
INOUT	num_elements	length of array_of_datatypes and array_of_displacements arrays (non-negative integer)
OUT	enumtype	optional descriptor for enumeration information (handle)
OUT	info	optional info object (handle)
OUT	desc	buffer to return the string containing a description of the event type (string)
INOUT	desc_len	length of the string and/or buffer for desc (integer)
OUT	bind	type of MPI object to which an event of this type must be bound (integer)

#### C binding

After a successful call to MPI\_T\_EVENT\_GET\_INFO for a particular event type, subsequent calls to this routine that query information about the same event type must return the same information. If any INOUT or OUT argument to MPI\_T\_EVENT\_GET\_INFO is a NULL pointer, the implementation will ignore the argument and not return a value for the specific argument.

The arguments name and name\_len are used to return the name of the event type as described in Section 15.3.3. If completed successfully, the routine is required to return a name of at least length one. The name of the event type must be unique with respect to all other names for event types used by the MPI implementation.

The argument  ${\sf verbosity}$  returns the verbosity level of the event type (see Section 15.3.1).

The argument array\_of\_datatypes returns an array of MPI datatype handles that describe the elements returned for an instance of the event type with index event\_index. The event data can either be queried element by element with MPI\_T\_EVENT\_READ or copied

into a contiguous event buffer with MPI\_T\_EVENT\_COPY. For the latter case, the argument array\_of\_displacements returns an array of byte displacements in the event buffer in ascending order starting with zero.

The user is responsible for the memory allocation for the array\_of\_datatypes and array\_of\_displacements arrays. The number of elements in each array is supplied by the user in num\_elements. If the number of elements used by the event type is larger than the value of num\_elements provided by the user, the number of datatype handles and displacements returned in the corresponding arrays is truncated to the value of num\_elements passed in by the user. If the user passes the NULL pointer for array\_of\_datatypes or array\_of\_displacements, the respective arguments are ignored. Unless the user passes the NULL pointer for num\_elements required for this event type. If the user passes the NULL pointer for num\_elements, the arguments num\_elements, array\_of\_datatypes, and array\_of\_displacements are ignored.

MPI can optionally return an enumeration identifier in the enumtype argument, describing the individual elements in the array\_of\_datatypes argument. Otherwise, enumtype is set to MPI\_T\_ENUM\_NULL. If the argument to enumtype provided by the user is the MPI\_T\_ENUM\_NULL pointer, no enumeration type is returned.

MPI can optionally return an info object containing the default hints set for a registration handle for this event type. If the argument to info provided by the user is the NULL pointer, this argument is ignored, otherwise an MPI implementation is required to return all hints that are supported by the implementation for a registration handle for this event type and have default values specified; any user-supplied hints that were not ignored by the implementation; and any additional hints that were set by the implementation. If no such hints exist, a handle to a newly created info object is returned that contains no key/value pair. The user is responsible for freeing info via MPI\_INFO\_FREE.

The arguments desc and desc\_len are used to return the description of the event type as described in Section 15.3.3. Returning a description is optional. If an MPI implementation does not return a description, the first character for desc must be set to the null character and desc\_len must be set to one at the return from this function.

The parameter bind returns the type of the MPI object to which the event type must be bound or the value MPI\_T\_BIND\_NO\_OBJECT (see Section 15.3.2).

If an event type has an equivalent name across connected MPI processes, the following OUT parameters must be identical: verbosity, array\_of\_datatypes, num\_elements, enumtype, and bind. The returned description must be equivalent. As the argument

array\_of\_displacements is process dependent, it may differ across connected MPI processes.

This routine returns MPI\_SUCCESS on success and returns MPI\_T\_ERR\_INVALID\_INDEX if event\_index does not match a valid event type index provided by the implementation at the time of the call.

```
39
40
41
```

```
MPI_T_EVENT_GET_INDEX(name, event_index)
IN name name of the event type (string)
OUT event_index index of the event type (integer)

C binding
int MPI_T_event_get_index(const char *name, int *event_index)
```

MPI\_T\_EVENT\_GET\_INDEX returns the index of an event type identified by a known event type name. The name parameter is provided by the caller, and event\_index is returned by the MPI implementation. The name parameter is a string terminated with a null character.

This routine returns MPI\_SUCCESS on success and returns MPI\_T\_ERR\_INVALID\_NAME if name does not match the name of any event type provided by the implementation at the time of the call.

Rationale. This routine is provided to enable fast retrieval of an event index by a tool, assuming it knows the name of the event type for which it is looking. The number of event types exposed by the implementation can change over time, so it is not possible for the tool to simply iterate over the list of event types once at initialization. Although using MPI implementation specific event type names is not portable across MPI implementations, tool developers may choose to take this route for lower overhead at runtime because the tool will not have to iterate over the entire set of event types to find a specific one. (End of rationale.)

### Handle Allocation and Deallocation

Before the MPI implementation calls a callback function on the occurrence of a specific event, the user needs to register a callback function to be called for that event type and obtain a handle of type MPI\_T\_event\_registration.

### MPI\_T\_EVENT\_HANDLE\_ALLOC(event\_index, obj\_handle, info, event\_registration)

IN	event_index	index of event type for which the registration handle
		is to be allocated (integer)
IN	obj_handle	reference to a handle of the MPI object to which this
		event is supposed to be bound (pointer)
IN	info	info object (handle)
OUT	event_registration	event registration (handle)

### C binding

MPI\_T\_EVENT\_HANDLE\_ALLOC creates a registration handle for the event type identified by event\_index. Furthermore, if required by the event type, the registration handle is bound to the object referred to by the argument obj\_handle. The argument obj\_handle is ignored if the MPI\_T\_EVENT\_GET\_INFO call for this event type returned MPI\_T\_BIND\_NO\_OBJECT in the argument bind. The user can pass hints for the handle allocation to the MPI implementation via the info argument. The allocated event-registration handle is returned in the argument event\_registration.

2

3

4 5 6

7

9

10

11

12

13

14 15

16

17

18

19

20

21

22 23 24

25 26

27

28 29

30

31

32

33 34

35

36

37

38

39

40

41

```
MPI_T_EVENT_HANDLE_SET_INFO(event_registration, info)
 IN
            event_registration
                                          event registration (handle)
 IN
            info
                                          info object (handle)
```

### C binding

```
int MPI_T_event_handle_set_info(
             MPI_T_event_registration event_registration, MPI_Info info)
```

MPI\_T\_EVENT\_HANDLE\_SET\_INFO updates the hints of the event-registration handle associated with event\_registration using the hints provided in info. This operation has no effect on previously set or defaulted hints that are not specified by info. It also has no effect on previously set or defaulted hints that are specified by info, but are ignored by the MPI implementation in this call to MPI\_T\_EVENT\_HANDLE\_SET\_INFO.

Some info items that an implementation can use when it creates Advice to users. an event-registration handle cannot easily be changed once the registration handle is created. Thus, an implementation may ignore hints issued in this call that it would have accepted in an handle allocation call. An implementation may also be unable to update certain info hints in a call to MPI\_T\_EVENT\_HANDLE\_SET\_INFO. MPI\_T\_EVENT\_HANDLE\_GET\_INFO can be used to determine whether info changes were ignored by the implementation. (End of advice to users.)

### MPI\_T\_EVENT\_HANDLE\_GET\_INFO(event\_registration, info\_used)

```
IN
           event_registration
                                           event registration (handle)
OUT
           info_used
                                           info object (handle)
```

### C binding

```
int MPI_T_event_handle_get_info(
             MPI_T_event_registration event_registration,
             MPI_Info *info_used)
```

MPI\_EVENT\_HANDLE\_GET\_INFO returns a new info object containing the hints of the event-registration handle associated with event\_registration. The current setting of all hints related to this registration handle is returned in info\_used. An MPI implementation is required to return all hints that are supported by the implementation and have default values specified; any user-supplied hints that were not ignored by the implementation; and any additional hints that were set by the implementation. If no such hints exist, a handle to a newly created info object is returned that contains no key/value pairs. The user is responsible for freeing info\_used via MPI\_INFO\_FREE.

```
MPI_T_EVENT_REGISTER_CALLBACK(event_registration, cb_safety, info, user_data, event_cb_function)
```

IN	event_registration	event registration (handle)
IN	cb_safety	maximum callback safety level (integer)
IN	info	info object (handle)
IN	user_data	pointer to a user-controlled buffer
IN	event_cb_function	pointer to user-defined callback function (function)

### C binding

MPI\_T\_EVENT\_REGISTER\_CALLBACK associates a user-defined function pointed to by event\_cb\_function with an allocated event-registration handle. The maximum callback safety level supported by the callback function is passed in the argument cb\_safety. The safety levels are defined in Table 15.5. A user can register multiple callback functions for a given event-registration handle, potentially specifying one for each callback safety level. Registering a callback function for a specific callback safety level overwrites any previously registered callback function pointer and info object associated with the event registration for the specific callback safety level. If event\_cb\_function is the NULL pointer, the association of a callback function for that callback safety level is removed.

When an event is triggered, the implementation will select from all registered callbacks the callback with the lowest safety level valid in the context in which the callback is invoked. In situations where the required callback safety level exceeds the highest level for which a callback function is registered for a given registration handle, the event instance is dropped.

At invocation time, the implementation passes the pointer to a user-defined memory region specified during callback registration with the argument user\_data.

The user can pass hints for the registration of the specified callback function to the MPI implementation via the info argument.

Advice to users. As event instances can be raised as soon as the registration handle is associated with the first callback function, the callback function with the highest callback safety guarantees should be registered before any further registrations for lower callback safety guarantees, to avoid dropped events due to insufficient callback safety guarantees. (End of advice to users.)

The callback function passed to MPI\_T\_EVENT\_REGISTER\_CALLBACK in the argument event\_cb\_function needs to have the following type:

```
typedef void (*MPI_T_event_cb_function)(

MPI_T_event_instance event_instance,

MPI_T_event_registration event_registration,

MPI_T_cb_safety cb_safety,

void *user_data);

MPI_T_cb_safety cb_safety,

Void *user_data);

Unofficial Draft for Comment Only

After the merge of PR409,
the remaining \typedef.. must be checked and may be removed.
```

The argument event\_instance corresponds to a handle for the opaque event-instance object of type MPI\_T\_event\_instance. This handle is only valid inside the corresponding invocation of the function to which it is passed. The argument event\_registration corresponds to the event-registration handle returned by MPI\_T\_EVENT\_HANDLE\_ALLOC for the user function to the same event type and bound object combination. The handle can be used to identify the specific event registration information, such as event type and bound object, or even to deallocate the handle from within the callback invocation. The argument cb\_safety describes the safety requirements the callback function must fulfill in the current invocation. The argument user\_data is the pointer to user-allocated memory that was passed to the MPI implementation during callback registration.

### MPI\_T\_EVENT\_CALLBACK\_SET\_INFO(event\_registration, cb\_safety, info)

```
IN event_registration event registration (handle)
IN cb_safety callback safety level (integer)
IN info info object (handle)
```

### C binding

MPI\_T\_EVENT\_CALLBACK\_SET\_INFO updates the hints of the callback function registered for the callback safety level specified by cb\_safety of the event-registration handle associated with event\_registration using the hints provided in info. This operation has no effect on previously set or defaulted hints that are not specified by info. It also has no effect on previously set or defaulted hints that are specified by info, but are ignored by the MPI implementation in this call to MPI\_T\_EVENT\_CALLBACK\_SET\_INFO.

### MPI\_T\_EVENT\_CALLBACK\_GET\_INFO(event\_registration, cb\_safety, info\_used)

```
IN event_registration event registration (handle)
IN cb_safety callback safety level (integer)
OUT info_used info object (handle)
```

C binding

```
int MPI_T_event_callback_get_info(
```

```
MPI_T_event_registration event_registration,
MPI_T_cb_safety cb_safety, MPI_Info *info_used)
```

MPI\_EVENT\_CALLBACK\_GET\_INFO returns a new info object containing the hints of the callback function registered for the callback safety level specified by cb\_safety of the event-registration handle associated with event\_registration. The current setting of all hints related to this callback safety level of the event-registration handle is returned in info\_used. An MPI implementation is required to return all hints that are supported by the implementation and have default values specified; any user-supplied hints that were not ignored by the implementation; and any additional hints that were set by

14

15

16

17 18

19

20

21

22

23

24

26

27

28 29

30

31

32

Done in

PR449

44

45 46

47

checked and may be removed.

the implementation. If no such hints exist, a handle to a newly created info object is returned that contains no key/value pairs. The user is responsible for freeing info\_used via MPI\_INFO\_FREE.

To stop the MPI implementation from raising events for a specific registration, a user needs to free the corresponding event-registration handle.

### MPI\_T\_EVENT\_HANDLE\_FREE(event\_registration, user\_data, free\_cb\_function)

```
IN event_registration event registration (handle)

IN user_data pointer to a user-controlled buffer

IN free_cb_function pointer to user-defined callback function (function)
```

### C binding

MPI\_T\_EVENT\_HANDLE\_FREE returns MPI\_SUCCESS when deallocation of the handle was initiated successfully and returns MPI\_T\_ERR\_INVALID\_HANDLE if event\_registration does not match a valid allocated event-registration handle at the time of the call. The callback function free\_cb\_function is called by the MPI implementation, when it is able to guarantee that no further event instances for the corresponding event-registration handle will be raised. If the pointer to free\_cb\_function is the NULL pointer, no user function is invoked after successful deallocation of the event registration handle. The pointer to user-controlled memory provided in the user\_data argument will be passed to the function provided in the free\_cb\_function on invocation.

Advice to users. A free-callback function associated with a registration handle should always be prepared to postpone any pending actions, should the provided callback safety requirements exceed those required by the pending actions. (*End of advice to users.*)

The callback function passed to MPI\_T\_EVENT\_HANDLE\_FREE in the argument free\_cb\_function needs to have the following type:

### Handling Dropped Events

Events may occur at times when the MPI implementation cannot invoke the user function corresponding to a matching event handle. An implementation is allowed to buffer such events and delay the callback invocation. If an event occurs at times when the corresponding callback function cannot be called and the corresponding data cannot be buffered, or no callback function meeting the required callback safety level is registered, the event data may be dropped. To discover such data loss, the user can set a handler function for a specific event-registration handle.

Done

IN

```
4
5
6
7
8
9
10
11
12
13
14
15
16
```

#-other #-PR449 #-update10

```
MPI\_T\_EVENT\_SET\_DROPPED\_HANDLER (event\_registration, dropped\_cb\_function)
```

event\_registration valid event registration (handle)

IN dropped\_cb\_function pointer to user-defined callback function (function)

### C binding

MPI\_T\_EVENT\_SET\_DROPPED\_HANDLER registers the function dropped\_cb\_function to be called by the MPI implementation when event information is dropped for the registration handle specified in event\_registration. Subsequent calls to MPI\_T\_EVENT\_SET\_DROPPED\_HANDLER with the same registration handle will replace previously registered callback functions for that registration handle. If the pointer to dropped\_cb\_function is the NULL pointer, no data loss is recorded or reported until a new valid callback function is registered.

Advice to users. The invocation of the dropped handler callback function may not occur close to the time the event was actually lost. (End of advice to users.)

The callback function passed to MPI\_T\_EVENT\_SET\_DROPPED\_HANDLER in the argument dropped\_cb\_function needs to have the following type:

The argument event\_registration corresponds to the event registration handle to which the dropped data corresponds. The argument count provides a best effort estimation of the number of invocations to a registered event callback corresponding to event\_registration that were not executed since the registration of the dropped-callback handler or the last invocation of a registered dropped-callback handler. The source\_index provides the index of the source that dropped the corresponding event information. The argument cb\_safety describes the safety requirements the callback function must fulfill in the current invocation. The possible values for cb\_safety are described in Table 15.5. The argument user\_data is the pointer to user-allocated memory that was passed to the MPI implementation during callback registration.

Advice to users. A callback function for dropped events associated with a registration handle should always be prepared to postpone any pending actions, should the provided callback safety requirements exceed those required by the pending actions. (End of advice to users.)

Advice to implementors. A high-quality implementation will strive to invoke a callback function for dropped events associated with a registration handle at times that provide as much freedom of action to the function as possible. (*End of advice to implementors.*)

If events are dropped for a specific source, the corresponding handler callback function must be called before other events are raised for this source. This means in a sequence of five events E1 to E5 from the same source, where E3 and E4 were dropped, any handler function set through MPI\_T\_EVENT\_SET\_DROPPED\_HANDLER for event-registration handles associated with E3 or E4 must be called before E5 is raised.

### Reading Event Data

In event callbacks, the parameter event\_instance provides access to the per-instance event data, i.e., the data encoded by the specific event type for this instance. The user can obtain event data as well as event meta data, such as a time stamp and the source, by providing this handle to the respective query functions. The event-instance handle is invalid beyond the scope of the current invocation of the callback function to which it is provided.

The callback function argument event\_registration identifies the registration handle that was used to register the callback function.

The callback function argument cb\_safety indicates the requirements for the specific callback invocation. The value is one of the safety requirements levels described in Table 15.5. The argument user\_data passes the pointer provided by the user during callback registration back to the function call.

Advice to users. Depending on the registered event and usage of MPI by the application, a callback function may be invoked with high frequency. Users should therefore strive to minimize the amount of work done inside callback functions. Furthermore, the time spent in a callback function may influence the capability of an implementation to buffer events and long execution times may lead to an increased number of dropped events. (End of advice to users.)

MPI provides the following function calls to access data of a specific event instance and its corresponding meta data (such as its time and source).

### MPI\_T\_EVENT\_READ(event\_instance, element\_index, buffer)

IN	event_instance	event-instance handle provided to the callback function (handle)
IN	element_index	index into the array of datatypes of the item to be queried (integer)
OUT	buffer	pointer to a memory location to store the item data (choice)

### C binding

MPI\_T\_EVENT\_READ allows users to copy one element of the event data to a user-specified buffer at a time.

The event\_instance argument identifies the event instance to query. It is erroneous to provide any other event-instance handle to the call than the one passed by the MPI implementation to the callback function in which the data is read. The buffer argument

user-allocated buffer for event data (choice)

must point to a memory location the MPI implementation can copy the element of the event data to identified by element\_index.

### MPI\_T\_EVENT\_COPY(event\_instance, buffer)

buffer

 $\begin{tabular}{ll} {\sf IN} & {\sf event\_instance} & {\sf event\ instance\ provided\ to\ the\ callback\ function} \\ & (handle) \\ \end{tabular}$ 

### C binding

OUT

int MPI\_T\_event\_copy(MPI\_T\_event\_instance event\_instance, void \*buffer)

MPI\_T\_EVENT\_COPY copies the event data as a whole into the user-provided buffer. The user must assure that the buffer is of at least the size of the extent of the event type, which can be computed from the type and displacement information returned by the corresponding call to MPI\_T\_EVENT\_GET\_INFO. The data may include padding bytes between individual elements of the event data in the buffer. A user can reconstruct the location and size of the data contained in the buffer through the information returned by MPI\_T\_EVENT\_GET\_INFO.

Advice to implementors. An implementation should strive to use an appropriately compact representation when copying event instance data to a user buffer via MPI\_T\_EVENT\_COPY to reduce the amount of memory required for the user buffer. (End of advice to implementors.)

### Reading Event Meta Data

Additional to the specific event data encoded by each event type, supplemental information available across all event types can be queried.

### MPI\_T\_EVENT\_GET\_TIMESTAMP(event\_instance, event\_timestamp)

IN event\_instance event instance provided to the callback function (handle)

OUT event\_timestamp timestamp the event was observed (integer)

### C binding

MPI\_T\_EVENT\_GET\_TIMESTAMP returns the timestamp of when the event was initially observed by the implementation. The event\_instance argument identifies the event instance to query. It is erroneous to provide any other handle to the call than the one passed by the MPI implementation to the callback function in which the timestamp is read.

Advice to users. An MPI implementation may postpone the call to the user's callback function. In this case, the call to MPI\_T\_EVENT\_GET\_TIMESTAMP may yield a timestamp in the past that is closer to the time the event was initially observed, as

opposed to a timestamp captured during callback function invocation. (End of advice to users.)

Advice to implementors. A high-quality implementation will return a timestamp as close as possible to the earliest time the event was observed by the MPI implementation. (End of advice to implementors.)

An event may be raised from different components acting as event sources in the MPI implementation. A source in this context is an abstract concept that helps to define partial ordering of raised events, as each source provides its own ordering guarantees. A source describes the entity that raises the event, rather than the origin of the data.

To identify the source of an event instance, the user can query the index of the source within the corresponding event callback function invocation.

Advice to implementors. An excessive number of event sources may negatively impact performance of a tool due to per-source overhead in event handling. (End of advice to implementors.)

### MPI\_T\_EVENT\_GET\_SOURCE(event\_instance, source\_index)

IN event\_instance event instance provided to the callback function (handle)

OUT source\_index index identifying the source (integer)

### C binding

The event\_instance argument identifies the event instance to query. It is erroneous to provide any other event-instance handle to the call than the one passed by the MPI implementation to the callback function in which the source is queried.

The source\_index argument returns the index of the source of the event instance. It can be used to query more information on the source using MPI\_T\_SOURCE\_GET\_INFO.

Rationale. Event callback function invocations are associated with a source to enable chronological processing of events on the tool side, when required, while retaining low overhead on the side of the MPI implementation. (*End of rationale*.)

### 15.3.9 Variable Categorization

MPI implementations can optionally group performance and control variables into categories to express logical relationships between various variables. For example, an MPI implementation could group all control and performance variables that refer to message transfers in the MPI implementation and thereby distinguish them from variables that refer to local resources such as memory allocations or other interactions with the operating system.

Categories can also contain other categories to form a hierarchical grouping. Categories can never include themselves, either directly or transitively within other included categories. Expanding on the example above, this allows MPI to refine the grouping of variables referring

to message transfers into variables to control and to monitor message queues, message matching activities and communication protocols. Each of these groups of variables would be represented by a separate category and these categories would then be listed in a single category representing variables for message transfers.

The category information may be queried in a fashion similar to the mechanism for querying variable information. The MPI implementation exports a set of N categories via the MPI tool information interface. If N=0, then the MPI implementation does not export any categories, otherwise the provided categories are indexed from 0 to N-1. This index number is used in subsequent calls to functions of the MPI tool information interface to identify the individual categories.

An MPI implementation is permitted to increase the number of categories during the execution of an MPI program when new categories become available through dynamic loading. However, MPI implementations are not allowed to change the index of a category or delete it once it has been added to the set.

Similarly, MPI implementations are allowed to add variables to categories, but they are not allowed to remove variables from categories or change the order in which they are returned.

### Category Query Functions

The following function can be used to query the number of categories, num\_cat.

```
MPI_T_CATEGORY_GET_NUM(num_cat)
```

OUT num\_cat current number of categories (integer)

### C binding

int MPI\_T\_category\_get\_num(int \*num\_cat)

Individual category information can then be queried by calling the following function:

MPI_T_CATEGORY_GET	_INFO(cat_index,	, name, name	_len, desc,	desc_len,	num_cvars,
num_pva	rs, num_categories	<b>(</b> )			

IN	cat_index	index of the category to be queried (integer)
OUT	name	buffer to return the string containing the name of the category (string)
INOUT	name_len	length of the string and/or buffer for ${\sf name}$ (integer)
OUT	desc	buffer to return the string containing the description of the category (string)
INOUT	desc_len	length of the string and/or buffer for <code>desc</code> (integer)
OUT	num_cvars	number of control variables in the category (integer)
OUT	num_pvars	number of performance variables in the category (integer)
OUT	num_categories	number of categories contained in the category (integer)

### C binding

The arguments name and name\_len are used to return the name of the category as described in Section 15.3.3.

The routine is required to return a name of at least length one. This name must be unique with respect to all other names for categories used by the MPI implementation.

If any OUT parameter to MPI\_T\_CATEGORY\_GET\_INFO is the NULL pointer, the implementation will ignore the parameter and not return a value for the parameter.

The arguments desc and desc\_len are used to return the description of the category as described in Section 15.3.3.

Returning a description is optional. If an MPI implementation decides not to return a description, the first character for desc must be set to the null character and desc\_len must be set to one at the return of this call.

The function returns the number of control variables, performance variables and other categories contained in the queried category in the arguments num\_cvars, num\_pvars, and num\_categories, respectively.

If the name of a category is equivalent across connected MPI processes, then the returned description must be equivalent.

### MPI\_T\_CATEGORY\_GET\_NUM\_EVENTS(cat\_index, num\_events)

IN	cat_index	index of the category to be queried (integer)
OUT	num events	number of event types in the category (integer)

### C binding

```
int MPI_T_category_get_num_events(int cat_index, int *num_events)
```

MPI\_T\_CATEGORY\_GET\_NUM\_EVENTS returns the number of event types contained in the queried category.

### MPI\_T\_CATEGORY\_GET\_INDEX(name, cat\_index)

```
IN name the name of the category (string)
OUT cat_index the index of the category (integer)
```

### C binding

```
int MPI_T_category_get_index(const char *name, int *cat_index)
```

MPI\_T\_CATEGORY\_GET\_INDEX is a function for retrieving the index of a category given a known category name. The name parameter is provided by the caller, and cat\_index is returned by the MPI implementation. The name parameter is a string terminated with a null character.

This routine returns MPI\_SUCCESS on success and returns MPI\_T\_ERR\_INVALID\_NAME if name does not match the name of any category provided by the implementation at the time of the call.

Rationale. This routine is provided to enable fast retrieval of a category index by a tool, assuming it knows the name of the category for which it is looking. The number of categories exposed by the implementation can change over time, so it is not possible for the tool to simply iterate over the list of categories once at initialization. Although using MPI implementation specific category names is not portable across MPI implementations, tool developers may choose to take this route for lower overhead at runtime because the tool will not have to iterate over the entire set of categories to find a specific one. (End of rationale.)

### Category Member Query Functions

### MPI\_T\_CATEGORY\_GET\_CVARS(cat\_index, len, indices)

```
IN cat_index index of the category to be queried, in the range 0 and num\_cat - 1 (integer)

IN len the length of the indices array (integer)

OUT indices an integer array of size len, indicating control variable indices (array of integers)
```

### C binding

```
int MPI_T_category_get_cvars(int cat_index, int len, int indices[])
```

MPI\_T\_CATEGORY\_GET\_CVARS can be used to query which control variables are contained in a particular category. A category contains zero or more control variables.

### MPI\_T\_CATEGORY\_GET\_PVARS(cat\_index, len, indices)

IN	cat_index	index of the category to be queried, in the range 0 and $num_cat - 1$ (integer)
IN	len	the length of the indices array (integer)
OUT	indices	an integer array of size len, indicating performance variable indices (array of integers)

### C binding

int MPI\_T\_category\_get\_pvars(int cat\_index, int len, int indices[])

MPI\_T\_CATEGORY\_GET\_PVARS can be used to query which performance variables are contained in a particular category. A category contains zero or more performance variables.

### MPI\_T\_CATEGORY\_GET\_EVENTS(cat\_index, len, indices)

IN	cat_index	index of the category to be queried, in the range 0 and $num_cat - 1$ (integer)
IN	len	the length of the indices array (integer)
OUT	indices	an integer array of size len, indicating event type
		indices (array of integers)

### C binding

int MPI\_T\_category\_get\_events(int cat\_index, int len, int indices[])

MPI\_T\_CATEGORY\_GET\_EVENTS can be used to query which event types are contained in a particular category. A category contains zero or more event types.

### MPI\_T\_CATEGORY\_GET\_CATEGORIES(cat\_index, len, indices)

IN	cat_index	index of the category to be queried, in the range 0
		and $num_cat - 1$ (integer)
IN	len	the length of the indices array (integer)
OUT	indices	an integer array of size len, indicating category
		indices (array of integers)

### C binding

int MPI\_T\_category\_get\_categories(int cat\_index, int len, int indices[])

MPI\_T\_CATEGORY\_GET\_CATEGORIES can be used to query which other categories are contained in a particular category. A category contains zero or more other categories.

As mentioned above, MPI implementations can grow the number of categories as well as the number of variables or other categories within a category. In order to allow users of the MPI tool information interface to check quickly whether new categories have been added or new variables or categories have been added to a category, MPI maintains a

virtual timestamp. This timestamp is monotonically increasing during the execution and is returned by the following function:

### MPI\_T\_CATEGORY\_CHANGED(stamp)

OUT stamp a virtual time stamp to indicate the last change to the categories (integer)

### C binding

```
int MPI_T_category_changed(int *stamp)
```

If two subsequent calls to this routine return the same timestamp, it is guaranteed that the category information has not changed between the two calls. If the timestamp retrieved from the second call is higher, then some categories have been added or expanded.

Advice to users. The timestamp value is purely virtual and only intended to check for changes in the category information. It should not be used for any other purpose. (End of advice to users.)

The index values returned in indices by MPI\_T\_CATEGORY\_GET\_CVARS, MPI\_T\_CATEGORY\_GET\_PVARS and MPI\_T\_CATEGORY\_GET\_CATEGORIES can be used as input to MPI\_T\_CVAR\_GET\_INFO, MPI\_T\_PVAR\_GET\_INFO and MPI\_T\_CATEGORY\_GET\_INFO, respectively.

The user is responsible for allocating the arrays passed into the functions MPI\_T\_CATEGORY\_GET\_CVARS, MPI\_T\_CATEGORY\_GET\_PVARS and MPI\_T\_CATEGORY\_GET\_CATEGORIES. Starting from array index 0, each function writes up to len elements into the array. If the category contains more than len elements, the function returns an arbitrary subset of size len. Otherwise, the entire set of elements is returned in the beginning entries of the array, and any remaining array entries are not modified.

### 15.3.10 Return Codes for the MPI Tool Information Interface

All functions defined as part of the MPI tool information interface return an integer error code (see Table 15.7) to indicate whether the function was completed successfully or was aborted. In the latter case the error code indicates the reason for not completing the routine. Such errors neither impact the execution of the MPI process nor invoke MPI error handlers. The MPI process continues executing regardless of the return code from the call. The MPI implementation is not required to check all user-provided parameters; if a user passes invalid parameter values to any routine the behavior of the implementation is undefined.

All error codes with the prefix MPI\_T\_ must be unique values and cannot overlap with any other error codes or error classes returned by the MPI implementation. Further, they shall be treated as MPI error classes as defined in Section 9.4 and follow the same rules and restrictions. In particular, they must satisfy:

```
0 = \mathsf{MPI\_SUCCESS} < \mathsf{MPI\_T\_ERR\_XXX} \le \mathsf{MPI\_ERR\_LASTCODE}.
```

Rationale. All MPI tool information interface functions must return error classes, because applications cannot portably call MPI\_ERROR\_CLASS before MPI initialization to map an arbitrary error code to an error class. (*End of rationale*.)

### 15.3.11 Profiling Interface

All requirements for the profiling interfaces, as described in Section 15.2, also apply to the MPI tool information interface. All rules, guidelines, and recommendations from Section 15.2 apply equally to calls defined as part of the MPI tool information interface.



1	Return Code	Description	
2	Return Codes for All Functions in the	ne MPI Tool Information Interface	
3	MPI_SUCCESS	Call completed successfully	
4	MPI_T_ERR_INVALID	Invalid or bad parameter value(s)	
5	MPI_T_ERR_MEMORY	Out of memory	
6	MPI_T_ERR_NOT_INITIALIZED	Interface not initialized	
7	MPI_T_ERR_CANNOT_INIT	Interface not in the state to be initialized	
8	MPI_T_ERR_NOT_ACCESSIBLE	Requested functionality not accessible	
9	Return Codes for Datatype Function	ns: MPI_T_ENUM_*	
10	MPI_T_ERR_INVALID_INDEX	The enumeration index is invalid	
11	MPI_T_ERR_INVALID_ITEM	The item index queried is out of range	
12 13		(for MPI_T_ENUM_GET_ITEM only)	
14	Return Codes for Variable, Category	y, and Event Query Functions: MPI_T_*_GET_*	
15	MPI_T_ERR_INVALID_INDEX	The variable or category index is invalid	
16	MPI_T_ERR_INVALID_NAME	The variable or category name is invalid	
17	Return Codes for Handle Functions:	MPI_T_*_{ALLOC FREE}	
18	MPI_T_ERR_INVALID_INDEX	The variable index is invalid	
19	MPI_T_ERR_INVALID_HANDLE	The handle is invalid	
20	MPI_T_ERR_OUT_OF_HANDLES	No more handles available	
21	Return Codes for Session Functions:	MPI_T_PVAR_SESSION_*	
22	MPI_T_ERR_OUT_OF_SESSIONS	No more sessions available	
23	MPI_T_ERR_INVALID_SESSION	Session argument is not a valid session	
24	Return Codes for Control Variable A	Access Functions: MPI_T_CVAR_{READ WRITE}	
25 26	MPI_T_ERR_CVAR_SET_NOT_NOW	Variable cannot be set at this moment	
	MPI_T_ERR_CVAR_SET_NEVER	Variable cannot be set until end of execution	
27 28	MPI_T_ERR_INVALID_HANDLE	The handle is invalid	
29	Return Codes for Performance Varia		
30	MPI_T_PVAR_{START STOP READ		
31	MPI_T_ERR_INVALID_HANDLE	The handle is invalid	
32	MPI_T_ERR_INVALID_SESSION	Session argument is not a valid session	
33	MPI_T_ERR_PVAR_NO_STARTSTOP	Variable cannot be started or stopped (for	
34		MPI_T_PVAR_START and MPI_T_PVAR_STOP)	
35	MPI_T_ERR_PVAR_NO_WRITE	Variable cannot be written or reset (for	
36		MPI_T_PVAR_WRITE and MPI_T_PVAR_RESET)	
37	MPI_T_ERR_PVAR_NO_ATOMIC	Variable cannot be read and written atomically (for	
38		MPI_T_PVAR_READRESET)	
39	Return Codes for Source Functions:		
40	MPI_T_ERR_INVALID_INDEX	The source index is invalid	
41	MPI_T_ERR_NOT_SUPPORTED	Requested functionality not supported	
42	Return Codes for Category Functions: MPI_T_CATEGORY_*		
43	MPI_T_ERR_INVALID_INDEX	The category index is invalid	

Table 15.7: Return codes used in functions of the MPI tool information interface

#-... all changes
#-nnn by issue nnn
#-PRnnn by pull request
Non problematic fomatting-changes and typo-corrections are not listed
Embiggening: only new \_c versions are marked, all other is not listed
New or changed content
Problematic fomatting-changes are listed
#-error
Errors in RC 40 - also marked with #-error
B.m.n: i. - refers to Change-Log section B.m.n, Item i

# Chapter 16

# Deprecated Interfaces

## 16.1 Deprecated since MPI-2.0

The following function is deprecated and is superseded by MPI\_COMM\_CREATE\_KEYVAL in MPI-2.0. The language independent definition of the deprecated function is the same as that of the new function, except for the function name and a different behavior in the C/Fortran language interoperability, see Section 19.3.7. The language bindings are modified.

### MPI\_KEYVAL\_CREATE(copy\_fn, delete\_fn, keyval, extra\_state)

IN	copy_fn	Copy callback function for keyval
IN	delete_fn	Delete callback function for keyval
OUT	keyval	key value for future access (integer)
IN	extra_state	Extra state for callback functions

### C binding

For this routine, an interface within the mpi\_f08 module was never defined.

### Fortran binding

```
MPI_KEYVAL_CREATE(COPY_FN, DELETE_FN, KEYVAL, EXTRA_STATE, IERROR)
EXTERNAL COPY_FN, DELETE_FN
INTEGER KEYVAL, EXTRA_STATE, IERROR
```

Done in #-PR442

And

finally

done

PR449

lin

The copy\_fn function is invoked when a communicator is duplicated by MPI\_COMM\_DUP. copy\_fn should be of type MPI\_Copy\_function, which is defined as follows:

```
In the function index as primary 
typedef int MPI_Copy_f
```

this space before the typdef is lost since RC-40 mm oldcomm, int keyval,

A Fortran declaration for such a function is as follows:

For this routine, an interface within the mpi\_f08 module was never defined.

41 #-error 42 #-update4 43 #-PR442

12 13 14

15

18

19

20 21

22 23

27 28

34

35

37

38

39



3

13

14

15

16

18

19

21

22

23

24

25

26

27

28

29 30

31 32

35

36 37

38

39

40

41 42

43

44

45

46

In the function index as primary

SUBROUTINE COPY\_FUNCTION(OLDCOMM, KEYVAL, EXTRA\_STATE, ATTRIBUTE\_VAL\_IN,

ATTRIBUTE\_VAL\_OUT, FLAG, IERR)

INTEGER OLDCOMM, KEYVAL, EXTRA\_STATE, ATTRIBUTE\_VAL\_IN,

ATTRIBUTE\_VAL\_OUT, IERR

LOGICAL FLAG

Rolf: In MPI-3.1, the first location was completely on line 9 and the second location was line-broken. Bill: I will leave this as is. ==> don't worry

> no linebreak

Proposal in

Issue #-366:

returning --> return

What must

I/do????

-erron

Test \mbox{...}

lin #-PR442

Done

Done in #-PR442

#-error #-366+405 #-update12 #-TODO

10

that MPI\_NULL\_COPY\_FN and MPI\_DUP\_FN are also deprecated. Analogous to copy\_fn is a callback deletion function, defined as follows. The delete\_fn function is invoked when a communicator is deleted by MPI\_COMM\_FREE or when a call is made explicitly to MPI\_ATTR\_DELETE. delete\_fn should be of type MPI\_Delete\_function, which is defined as follows: In the function index as primary typedef int MPI\_Delete\_function (MPI\_Comm comm, int keyval,

copy\_fn may be specified as MPI\_NULL\_COPY\_FN or MPI\_DUP\_FN from either C or

Fortran; MPI\_NULL\_COPY\_FN is a function that does nothing other than returning flag

= 0 and MPI\_SUCCESS. MPI\_DUP\_FN is a simple-minded copy function that sets flag = 1, returns the value of attribute\_val\_in in attribute\_val\_out, and returns MPI\_SUCCESS. Note

void \*attribute\_val, void \*extra\_state);

A Fortran declaration for such a function is as follows:

For this routine, an interface within the mpi\_f08 module was never defined. In the function index as primary

SUBROUTINE DELETE\_FUNCTION(COMM, KEYVAL, ATTRIBUTE\_VAL, EXTRA\_STATE, IERR)

INTEGER COMM, KEYVAL, ATTRIBUTE\_VAL, EXTRA\_STATE, IERR

delete\_fn may be specified as MPI\_NULL\_DELETE\_FN from either C or Fortran; MPI\_NULL\_DELETE\_FN is a function that does nothing, other than returning MPI\_SUCCESS. Note that MPI\_NULL\_DELETE\_FN is also deprecated.

The following function is deprecated and is superseded by MPI\_COMM\_FREE\_KEYVAL in MPI-2.0. The language independent definition of the deprecated function is the same as of the new function, except of the function name. The language bindings are modified.

MPI\_KEYVAL\_FREE(keyval)

INOUT keyval Frees the integer key value (integer)

C binding

int MPI\_Keyval\_free(int \*keyval)

For this routine, an interface within the mpi\_f08 module was never defined.

Fortran binding

MPI\_KEYVAL\_FREE(KEYVAL, IERROR)

INTEGER KEYVAL, IERROR

The following function is deprecated and is superseded by MPI\_COMM\_SET\_ATTR in MPI-2.0. The language independent definition of the deprecated function is the same as of the new function, except of the function name. The language bindings are modified.

> Should one or both "of" be removed?

#-error #-366+405 #-update12 #-TODO

14

15

16

17

19

20

21

27 28

34

35

36

37

42

43

44 45 46 #-error

#-TODO

#-366+405

#-update12

### MPI\_ATTR\_PUT(comm, keyval, attribute\_val)

INOUT comm communicator to which attribute will be attached

(handle)

IN keyval key value, as returned by MPI\_KEYVAL\_CREATE

(integer)

IN attribute\_val attribute value

### C binding

int MPI\_Attr\_put(MPI\_Comm comm, int keyval, void \*attribute\_val)

For this routine, an interface within the mpi\_f08 module was never defined.

### Fortran binding

MPI\_ATTR\_PUT(COMM, KEYVAL, ATTRIBUTE\_VAL, IERROR)
INTEGER COMM, KEYVAL, ATTRIBUTE\_VAL, IERROR

The following function is deprecated and is superseded by MPI\_COMM\_GET\_ATTR in MPI-2.0. The language independent definition of the deprecated function is the same as of the new function, except of the function name. The language bindings are modified.

Should one or both "of" be removed?

### MPI\_ATTR\_GET(comm, keyval, attribute\_val, flag)

IN	comm	communicator to which attribute is attached (handle)
IN	keyval	key value (integer)
OUT	attribute_val	attribute value, unless $flag = false$
OUT	flag	true if an attribute value was extracted; false if no
		attribute is associated with the key

### C binding

int MPI\_Attr\_get(MPI\_Comm comm, int keyval, void \*attribute\_val, int \*flag)

For this routine, an interface within the mpi\_f08 module was never defined.

### Fortran binding

```
MPI_ATTR_GET(COMM, KEYVAL, ATTRIBUTE_VAL, FLAG, IERROR)
INTEGER COMM, KEYVAL, ATTRIBUTE_VAL, IERROR
LOGICAL FLAG
```

The following function is deprecated and is superseded by MPI\_COMM\_DELETE\_ATTR in MPI-2.0. The language independent definition of the deprecated function is the same as of the new function, except of the function name. The language bindings are modified.

Should one or both "of" be removed?

### MPI\_ATTR\_DELETE(comm, keyval)

INOUT	comm	communicator to which attribute is attached (handle)
IN	keyval	The key value of the deleted attribute (integer)

### C binding

#-366+405 #-update12

#-error

#-TODO

```
1
              2
               3
               4
              5
              6
               7
              9
   #-error
              10
             11
   #-366
              12
  Done
              13
  in
  #-PR442
              14
              15
              16
   #-366
              17
  #-error
  Done
              19
  lin
             20
  #-PR442
  #-error
            22
  #-354 Done
  #-...
              24
              25
  B2.2: 2.
  #-error | 27
  #-354 Done
  #-...
              30
  B2.2: 17.
              31
              32
              33
              34
              35
#-PR377
              36
#-error!
              37
#-update4
              39
 Done
              40
 #-PR442
              41
              42
              43
              44
              45
              46
```

int MPI\_Attr\_delete(MPI\_Comm comm, int keyval)
For this routine, an interface within the mpi\_f08 module was never defined.
Fortuge binding

### Fortran binding

MPI\_ATTR\_DELETE(COMM, KEYVAL, IERROR)
INTEGER COMM, KEYVAL, IERROR

### 16.2 Deprecated since MPI-2.2

The entire set of C++ language bindings was deprecated as of MPI-2.2 and removed in MPI-3.0. The entire set of C++ language bindings have been removed. See Chapter 17, Removed Interfaces for more information.

The following function typedefs have been deprecated and are superseded by new names. Other than the typedef names, the function signatures are exactly the same; the names were updated to match conventions of other function typedef names.

```
Deprecated Name

MPI_Comm_errhandler_fn
MPI_File_errhandler_fn
MPI_File_errhandler_fn
MPI_Win_errhandler_fn
MPI_Win_errhandler_fn
MPI_Win_errhandler_function
MPI_win_errhandler_function
MPI_win_errhandler_function
Select them as primary index in the callback function prototypes index

4.0
```

Cancelling a send request by calling MPI\_CANCEL has been deprecated and may be removed in a future version of the MPI specification.

# 16.4 Deprecated since MPI-4.0

The following function is deprecated and is superseded by the new MPI\_INFO\_GET\_STRING call in MPI-4.0.

MPI\_INFO\_GET(info, key, valuelen, value, flag)

```
IN
           info
                                            info object (handle)
IN
           key
                                            key (string)
                                                                associated with \\mpiarg{key}
IN
           valuelen
                                            length of value arg (integer)
OUT
           value
                                            value (string)
OUT
           flag
                                            true if key defined, false if not (boolean)
```

#### C binding

47

48

### Fortran 2008 binding

```
MPI_Info_get(info, key, valuelen, value, flag, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
```

```
CHARACTER(LEN=*), INTENT(IN) :: key
                                                                                                           #-...
                   INTEGER, INTENT(IN) :: valuelen
                                                                                                            B2.2: 17.
                   CHARACTER(LEN=valuelen), INTENT(OUT) :: value
                                                                                                            continued
                   LOGICAL, INTENT(OUT) :: flag
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
              Fortran binding
              MPI_INFO_GET(INFO, KEY, VALUELEN, VALUE, FLAG, IERROR)
                                                                                                         8
                   INTEGER INFO, VALUELEN, IERROR
                                                                                                            #-364
                   CHARACTER*(*) KEY, VALUE
                                                        Textblock page 474 lines 11-16 is missing
                   LOGICAL FLAG
                                                                                                            #-error!
                                                                                                            Done
                   The following function is deprecated and is superseded by the new
                                                                                                         12
                                                                                                         13
              MPI_INFO_GET_STRING call in MPI-4.0.
                                                                                                            #-PR442
                                                                                                         14
                                                                                                         15
              MPI_INFO_GET_VALUELEN(info, key, valuelen, flag)
                                                                                                         16
                                                                                                         17
                IN
                                                      info object (handle)
                          info
                                                                                                            #-PR377
                                                                                                         18
                IN
                          key
                                                      key (string)
                                                                        associated with \mpiarg{key}
                                                                                                            #-error!
                OUT
                          valuelen
                                                      length of value arg (integer)
                                                                                                            #-update4
                                                                                                        21
                                                                                                            Done
                OUT
                                                      true if key defined, false if not (boolean)
                          flag
                                                                                                            in
                                                                                                         22
                                                                                                            #-PR442
                                                                                                         23
              C binding
                                                                                                         24
              int MPI_Info_get_valuelen(MPI_Info info, const char *key, int *valuelen,
                                                                                                         25
                             int *flag)
                                                                                                         26
              Fortran 2008 binding
                                                                                                         27
              MPI_Info_get_valuelen(info, key, valuelen, flag, ierror)
                                                                                                         28
                   TYPE(MPI_Info), INTENT(IN) :: info
                                                                                                         29
                   CHARACTER(LEN=*), INTENT(IN) :: key
                                                                                                         30
                   INTEGER, INTENT(OUT) :: valuelen
                                                                                                         31
                   LOGICAL, INTENT(OUT) :: flag
                                                                                                         32
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                                         34
                                                                                                            Done
              Fortran binding
                                                                                                            in
                                                                                                         35
              MPI_INFO_GET_VALUELEN(INFO, KEY, VALUELEN, FLAG, IERROR)
                                                                                                            #-PR442
                                                                                                         36
                   INTEGER INFO, VALUELEN, IERROR
                                                                                                            #-364
                                                                                                        37
                   CHARACTER*(*) KEY
                                                                                                            #-error!
                                                        Textblock page 474 lines 44-48 is missing
                   LOGICAL FLAG
                                                                                                  #-366 40
                   The following return class has been deprecated and is superseded by a new name
                                                                                                            #-...
                                                                                       in MPI-4.0
                                  return code
                                                                                                         41
                                                                                                  #-366
                                                                                                            B2.2: 9.
                                      Deprecated Name Replacement Name
     This term seems to be still in
                                                                                                            #-error!
                              MPI_T_ERR_INVALID_ITEM
                                                         MPI_T_ERR_INVALID_INDEX
     regular use on page 768
                                                                                                         43
                                                                                                            Done
Page 768 will
                                                                                                            in
                   The following Fortran subroutines are deprecated because the Fortran language
                                                                                                            #-PR442
be fixed
                                                                                                         45
              storage_size() and c_sizeof() intrinsic functions provide similar functionality. Note that while
                                                                                                         46
              MPI_SIZEOF and c_sizeof() return the size in bytes, storage_size() provides the size in bits.
                                                                                                            #-...
                           Done
                                                                                                            B1.2: 2.
                           lin
                           #-PR4??
```

**Unofficial Draft for Comment Only** 

```
MPI_SIZEOF(x, size)
#-...
                 IN
                                                        a Fortran variable of numeric intrinsic type (choice)
B1.2: 2.
                           Χ
                 OUT
continued
                           size
                                                        size of machine representation of that type (integer)
               Fortran 2008 binding
          6
          7
               MPI_Sizeof(x, size, ierror)
          8
                    TYPE(*), DIMENSION(..) :: x
          9
                    INTEGER, INTENT(OUT) :: size
          10
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
          11
               Fortran binding
          12
               MPI_SIZEOF(X, SIZE, IERROR)
          13
                    <type> X
          14
                    INTEGER SIZE, IERROR
         15
 #-364
          16
                                                              Textblock MPI-3.1 page 629 lines 1-10 is missing
 #-error! 17
Done
          19
#-PR442
          20
          21
          22
          23
          24
```

#-... all changes
#-nnn by issue nnn
#-PRnnn by pull request
Non problematic fomatting-changes and typo-corrections are not listed
Embiggening: only new \_c versions are marked, all other is not listed
New or changed content
Problematic fomatting-changes are listed
#-error

#-error

B.m.n: i. - refers to Change-Log section B.m.n, Item i

# Chapter 17

# Removed Interfaces

## 17.1 Removed MPI-1 Bindings

### 17.1.1 Overview

The following MPI-1 bindings were deprecated as of MPI-2 and are removed in MPI-3. They may be provided by an implementation for backwards compatibility, but are not required. Removal of these bindings affects all language-specific definitions thereof. Only the language-neutral bindings are listed when possible.

#### 17.1.2 Removed MPI-1 Functions

Table 17.1 shows the removed MPI-1 functions and their replacements.

Table 17.1: Removed MPI-1 functions and their replacements

Removed MPI-2 Replacement Select it as primary index MPI\_ADDRESS MPI\_GET\_ADDRESS in the MPI\_ERRHANDLER\_CREATE MPI\_COMM\_CREATE\_ERRHANDLER Constants&Handles index MPI\_COMM\_GET\_ERRHANDLER MPI\_ERRHANDLER\_GET MPI\_ERRHANDLER\_SET MPI\_COMM\_SET\_ERRHANDLER MPI\_TYPE\_EXTENT MPI\_TYPE\_GET\_EXTENT MPI\_TYPE\_HINDEXED MPI\_TYPE\_CREATE\_HINDEXED MPI\_TYPE\_HVECTOR MPI\_TYPE\_CREATE\_HVECTOR MPI\_TYPE\_LB MPI\_TYPE\_GET\_EXTENT MPI\_TYPE\_STRUCT MPI\_TYPE\_CREATE\_STRUCT MPI\_TYPE\_UB MPI\_TYPE\_GET\_EXTENT

### 17.1.3 Removed MPI-1 Datatypes

Table 17.2 shows the removed MPI-1 datatypes and their replacements.

### 17.1.4 Removed MPI-1 Constants

"There are no replacements." or <del>"There are no replacements in MPI-2 and later."</del>

Table 17.3 shows the removed MPI-1 constants. There are no MPI-2 replacements.

#-error! #-367

12 13 14

15

19

20

21 22

23 24

26

27 28

30

31

32

33

34

35

36

37

38

39

42

43 44

45

46

#-error

Done

PR441

Done in PR441 #-error
Done
in
PR441

#-error
Done
in
PR441

#-error!
#-367

10 11

12

13

14

15

16

19

20

**2**1

22

23

29

30

31

32

33 34

Table 17.2: Removed MPI-1 datatypes. The indicated routine may be used for changing the lower and upper bound respectively.

Removed MPI-2 Replacement

MPI\_LB MPI\_TYPE\_CREATE\_RESIZED

MPI\_UB MPI\_TYPE\_CREATE\_RESIZED

Table 17.3: Removed MPI-1 constants

Removed MPI-1 Constants

C type: const int (or unnamed enum)
Fortran type: INTEGER

MPI\_COMBINER\_HINDEXED\_INTEGER

MPI\_COMBINER\_HVECTOR\_INTEGER

Select it as primary index in the Constants&Handles index

Select it as primary index

Constants&Handles index

17.1.5 Removed MPI-1 Callback Prototypes

"and their replacements." or "and their replacements since MPI-2."

Table 17.4 shows the removed MPI-1 callback prototypes and their MPI-2 replacements.

MPI\_COMBINER\_STRUCT\_INTEGER

Table 17.4: Removed MPI-1 callback prototypes and their replacements

Select it as primary index in the callback function prototypes index

Removed

MPI\_2 Replacement

MPI\_Comm\_errhandler\_function

#-error

PR441

Done

lin

Done in PR441

# 17.2 C++ Bindings

The C++ bindings were deprecated as of MPI-2.2. The C++ bindings are removed in MPI-3.0. The namespace is still reserved, however, and bindings may only be provided by an implementation as described in the MPI-2.2 standard.

# Chapter 18

# Backward Incompatibilities

....bilities Starting in 4.0

#-error!

# 18.1 Backward Incompatible since MPI-3.2

MPI\_COMM\_DUP and MPI\_COMM\_IDUP no longer propagate info hints from the input communicator to the output communicator. This behavior can be achieved using MPI\_COMM\_DUP\_WITH\_INFO and MPI\_COMM\_IDUP\_WITH\_INFO.

The default communicator where errors are raised when not involving a communicator, window, or file was changed from MPI\_COMM\_WORLD to MPI\_COMM\_SELF.

Proposal: #-error #-335 #-358 + 359 2.2. p10 18.1 p.777 19.1.5 p789 The limit for length of MPI identifiers was removed. Prior to MPI-4.0, MPI identifiers were limited to 30 characters (31 with the profiling interface). This was done to avoid exceeding the limit on some compilation systems.

Rationale. For Fortran, this limit was already relaxed for the Fortran specific function names, see Section 19.1.5, and the Fortran language specification 2003 requires support for a minimum of 63 characters for internal and external identifiers.

18.1 p.777
19.1.5 p789
Starting with the ISO/IEC 9899:1999 C programming language standard, support for a minimum of 63 characters is required for internal identifiers, but only 31 characters are required to be significant for external identifiers. At the time of the release of MPI-4.0, most or nearly all compilers allow external identifiers longer than 31 characters. Therefore, the restriction is removed. (End of rationale.)

in 19.1.5, | PR434 and

32 = MPI\_INTERCOMM\_CREATE\_FROM\_GROUPS 30 = MPI\_TYPE\_CREATE\_HINDEXED\_BLOCK\_C

Done

12

13 14

15

18

19

20

21

Done

```
The maximumm is 72 - 6 (space) - 12 ("SUBROUTINE P") = 54
                                                                  Tables to verify the
                                                                                       31 = MPI_T_EVENT_SET_DROPPED_HANDLER
                                                                  new statements on
                                                                                       31 = MPI TYPE CREATE INDEXED BLOCK C
Note that in mpif.h, the versions with c are not defined.
                                                                  page 789.
                                                                                       31 = MPI REDUCE SCATTER BLOCK INIT C
                                                                                       30 = MPI_TYPE_CREATE_HINDEXED_BLOCK
                                                                  They will be not part
Interfaces that are longer than 54:
                                                                                       30 = MPI_DIST_GRAPH_NEIGHBORS_COUNT
56 = MPI_Neighbor_alltoallw_init_fts(a,b,c,d,e,f,g,h,i,j,k,l)
                                                                  of the standard.
                                                                                       30 = MPI DIST GRAPH CREATE ADJACENT
56 = MPI Neighbor alltoallv init fts(a,b,c,d,e,f,g,h,i,j,k,l)
                                                                                       30 = MPI_NEIGHBOR_ALLGATHERV_INIT_C
55 = MPI Neighbor allgatherv init fts(a,b,c,d,e,f,g,h,i,j,k)
                                                                                       29 = MPI TYPE CREATE INDEXED BLOCK
For these 3 exceptions, fts is shortened to f
                                                                                       29 = MPI SESSION CREATE ERRHANDLER
54 = MPI_Neighbor_alltoallw_init_f(a,b,c,d,e,f,g,h,i,j,j,k)
                                                                                          = MPI REDUCE SCATTER BLOCK INIT
54 = MPI_Neighbor_alltoallv_init_f(a,b,c,d,e,f,g,h,i,j,k,l)
53 = MPI Neighbor allgatherv init f(a,b,c,d,e,f,g,h,i,j,k)
Long routines with fts, but without exceptions
                                                                       and shorter ones, but without fts
52 = MPI_Rget_accumulate_fts(a,b,c,d,e,f,g,h,i,j,k,l,m,n)
                                                                  47 = MPI_Neighbor_alltoall_init(a,b,c,d,e,f,g,h,i,j)
                                                                  46 = MPI Ineighbor_alltoallw(a,b,c,d,e,f,g,h,i,j,k)
52 = MPI Reduce scatter block init fts(a,b,c,d,e,f,g,h,i)
52 = MPI Neighbor allgather init fts(a,b,c,d,e,f,g,h,i,j)
                                                                  46 = MPI Ineighbor alltoallv(a,b,c,d,e,f,g,h,i,j,k)
Same, but without _fts
                                                                    = MPI Type create darray(a,b,c,d,e,f,g,h,i,j,k)
53 = MPI Dist graph create adjacent(a,b,c,d,e,f,g,h,i,j,k)
                                                                     = MPI_Ineighbor_allgatherv(a,b,c,d,e,f,g,h,i,j)
52 = MPI_Neighbor_alltoallw_init(a,b,c,d,e,f,g,h,i,j,k,l)
                                                                    = MPI_Get_accumulate(a,b,c,d,e,f,g,h,i,j,k,l,m)
52 = MPI Neighbor alltoallv init(a,b,c,d,e,f,g,h,i,j,k,l)
                                                                  44 = MPI_Comm_spawn_multiple(a,b,c,d,e,f,g,h,i,j)
51 = MPI Neighbor allgatherv init(a,b,c,d,e,f,g,h,i,j,k)
                                                                  43 = MPI Type create hindexed block(a,b,c,d,e,f)
51 = MPI_Intercomm_create_from_groups(a,b,c,d,e,f,g,h,i)
                                                                  43 = MPI_Neighbor_alltoallw(a,b,c,d,e,f,g,h,i,j)
48 = MPI Rget accumulate(a,b,c,d,e,f,g,h,i,j,k,l,m,n)
                                                                  43 = MPI_Neighbor_alltoallv(a,b,c,d,e,f,g,h,i,j)
48 = MPI Reduce scatter block init(a,b,c,d,e,f,g,h,i)
                                                                  43 = MPI_Alltoallw_init(a,b,c,d,e,f,g,h,i,j,k,l)
48 = MPI_Neighbor_allgather_init(a,b,c,d,e,f,g,h,i,j)
                                                                  43 = MPI_Alltoallv_init(a,b,c,d,e,f,g,h,i,j,k,l)
```

#-error! #-PR429 2

#-TODO in PR429

In the definition of \mpifunc{MPI\\_T\\_CATEGORY\\_CHANGED}, the name of the \OUT/ argument was changed from \mpiarg{timestamp} to \mpiarg{update\\_number}. The type of the argument (\code{int \*}) is unchanged.



# Chapter 19

# Language Bindings

# 19.1 Support for Fortran

### 19.1.1 Overview

The Fortran MPI language bindings have been designed to be compatible with the Fortran 90 standard with additional features from Fortran 2003 and Fortran 2008 [45] + TS 29113 [46].

Rationale. Fortran 90 contains numerous features designed to make it a more "modern" language than Fortran 77. It seems natural that MPI should be able to take advantage of these new features with a set of bindings tailored to Fortran 90. In Fortran 2008 + TS 29113, the major new language features used are the ASYNCHRONOUS attribute to protect nonblocking MPI operations, and assumed-type and assumed-rank dummy arguments for choice buffer arguments. Further requirements for compiler support are listed in Section 19.1.7. (End of rationale.)

MPI defines three methods of Fortran support:

- 1. **USE mpi\_f08:** This method is described in Section 19.1.2. It requires compile-time argument checking with unique MPI handle types and provides techniques to fully solve the optimization problems with nonblocking calls. This is the only Fortran support method that is consistent with the Fortran standard (Fortran 2008 + TS 29113 and later). This method is highly recommended for all MPI applications.
- 2. **USE mpi:** This method is described in Section 19.1.3 and requires compile-time argument checking. Handles are defined as INTEGER. This Fortran support method is inconsistent with the Fortran standard, and its use is therefore not recommended. It exists only for backwards compatibility.
- 3. **INCLUDE 'mpif.h':** This method is described in Section 19.1.4. The use of the include file mpif.h is strongly discouraged starting with MPI-3.0, because this method neither guarantees compile-time argument checking nor provides sufficient techniques to solve the optimization problems with nonblocking calls, and is therefore inconsistent with the Fortran standard. It exists only for backwards compatibility with legacy MPI applications.

Compliant MPI-3 implementations providing a Fortran interface must provide one or both of the following:

- The USE mpi\_f08 Fortran support method.
- The USE mpi and INCLUDE 'mpif.h' Fortran support methods.

Section 19.1.6 describes restrictions if the compiler does not support all the needed features. Application subroutines and functions may use either one of the modules or the mpif.h include file. An implementation may require the use of one of the modules to prevent type mismatch errors.

Advice to users. Users are advised to utilize one of the MPI modules even if mpif.h enforces type checking on a particular system. Using a module provides several potential advantages over using an include file; the mpi\_f08 module offers the most robust and complete Fortran support. (End of advice to users.)

In a single application, it must be possible to link together routines which USE mpi\_f08, USE mpi, and INCLUDE 'mpif.h'.

The LOGICAL compile-time constant MPI\_SUBARRAYS\_SUPPORTED is set to .TRUE. if all buffer choice arguments are defined in explicit interfaces with assumed-type and assumed-rank [46]; otherwise it is set to .FALSE.. The LOGICAL compile-time constant MPI\_ASYNC\_PROTECTS\_NONBLOCKING is set to .TRUE. if the ASYNCHRONOUS attribute was added to the choice buffer arguments of all nonblocking interfaces and the underlying Fortran compiler supports the ASYNCHRONOUS attribute for MPI communication (as part of TS 29113), otherwise it is set to .FALSE.. These constants exist for each Fortran support method, but not in the C header file. The values may be different for each Fortran support method. All other constants and the integer values of handles must be the same for each Fortran support method.

Section 19.1.2 through 19.1.4 define the Fortran support methods. The Fortran interfaces of each MPI routine are shorthands. Section 19.1.5 defines the corresponding full interface specification together with the specific procedure names and implications for the profiling interface. Section 19.1.6 the implementation of the MPI routines for different versions of the Fortran standard. Section 19.1.7 summarizes major requirements for valid MPI-3.0 implementations with Fortran support. Section 19.1.8 and Section 19.1.9 describe additional functionality that is part of the Fortran support. MPI\_F\_SYNC\_REG is needed for one of the methods to prevent register optimization problems. A set of functions provides additional support for Fortran intrinsic numeric types, including parameterized types: MPI\_TYPE\_MATCH\_SIZE, MPI\_TYPE\_CREATE\_F90\_INTEGER,

MPI\_TYPE\_CREATE\_F90\_REAL and MPI\_TYPE\_CREATE\_F90\_COMPLEX. In the context of MPI, parameterized types are Fortran intrinsic types which are specified using KIND type parameters. Sections 19.1.10 through 19.1.19 give an overview and details on known problems when using Fortran together with MPI; Section 19.1.20 compares the Fortran problems with those in C.

### 19.1.2 Fortran Support Through the mpi\_f08 Module

An MPI implementation providing a Fortran interface must provide a module named mpi\_f08 that can be used in a Fortran program. Section 19.1.6 describes restrictions if the compiler does not support all the needed features. Within all MPI function specifications, the first

of the set of two Fortran routine interface specifications is provided by this module. This module must:

- Define all named MPI constants.
- Declare MPI functions that return a value.
- Provide explicit interfaces according to the Fortran routine interface specifications. This module therefore guarantees compile-time argument checking for all arguments which are not TYPE(\*), with the following exception:

Only one Fortran interface is defined for functions that are deprecated as of MPI-3.0. This interface must be provided as an explicit interface according to the rules defined for the mpi module, see Section 19.1.3.

Advice to users. It is strongly recommended that developers substitute calls to deprecated routines when upgrading from mpif.h or the mpi module to the mpi\_f08 module. (End of advice to users.)

- Define the derived type MPI\_Status, and define all MPI handles with uniquely named handle types (instead of INTEGER handles, as in the mpi module). This is reflected in the first Fortran binding in each MPI function definition throughout this document (except for the deprecated routines).
- Overload the operators .EQ. and .NE. to allow the comparison of these MPI handles with .EQ., .NE., == and /=.
- Use the ASYNCHRONOUS attribute to protect the buffers of nonblocking operations, and set the LOGICAL compile-time constant MPI\_ASYNC\_PROTECTS\_NONBLOCKING to .TRUE. if the underlying Fortran compiler supports the ASYNCHRONOUS attribute for MPI communication (as part of TS 29113). See Section 19.1.6 for older compiler versions.
- Set the LOGICAL compile-time constant MPI\_SUBARRAYS\_SUPPORTED to .TRUE. and declare choice buffers using the Fortran 2008 TS 29113 features assumed-type and assumed-rank, i.e., TYPE(\*), DIMENSION(..) in all nonblocking, split collective and persistent communication routines, if the underlying Fortran compiler supports it. With this, non-contiguous sub-arrays can be used as buffers in nonblocking routines.

Rationale. In all blocking routines, i.e., if the choice-buffer is not declared as ASYNCHRONOUS, the TS 29113 feature is not needed for the support of non-contiguous buffers because the compiler can pass the buffer by in-and-out-copy through a contiguous scratch array. (End of rationale.)

- Set the MPI\_SUBARRAYS\_SUPPORTED compile-time constant to .FALSE. and declare choice buffers with a compiler-dependent mechanism that overrides type checking if the underlying Fortran compiler does not support the Fortran 2008 TS 29113 assumed-type and assumed-rank notation. In this case, the use of non-contiguous sub-arrays as buffers in nonblocking calls may be invalid. See Section 19.1.6 for details.
- Declare each argument with an INTENT of IN, OUT, or INOUT as defined in this standard.

#-error!

Done in PR449

#-other

#-TODO Resulting line is 8pt to long. Should a flushline be added? Rationale. For these definitions in the mpi\_f08 bindings, in most cases, INTENT(IN) is used if the C interface uses call-by-value. For all buffer arguments and for OUT and INOUT dummy arguments that allow one of the non-ordinary Fortran constants (see MPI\_BOTTOM, etc. in Section 2.5.4) as input, an INTENT is not specified. (End of rationale.)

Advice to users. If a dummy argument is declared with INTENT(OUT), then the Fortran standard stipulates that the actual argument becomes undefined upon invocation of the MPI routine, i.e., it may be overwritten by some other values, e.g. zeros; according to [45], 12.5.2.4 Ordinary dummy variables, Paragraph 17: "If a dummy argument has INTENT(OUT), the actual argument becomes undefined at the time the association is established, except [...]". For example, if the dummy argument is an assumed-size array and the actual argument is a strided array, the call may be implemented with copy-in and copy-out of the argument. In the case of INTENT(OUT) the copy-in may be suppressed by the optimization and the routine starts execution using an array of undefined values. If the routine stores fewer elements into the dummy argument than is provided in the actual argument, then the remaining locations are overwritten with these undefined values. See also both advices to implementors in Section 19.1.3. (End of advice to users.)

 Declare all ierror output arguments as OPTIONAL, except for user-defined callback functions (e.g., COMM\_COPY\_ATTR\_FUNCTION) and predefined callbacks (e.g., MPI COMM\_NULL\_COPY\_FN).

This is a callback prototype, use correct macro!

(e.g., of type MPI\_Comm\_copy\_attr\_function or COMM\_COPY\_ATTR\_FUNCTION)

Rationale. For user-defined callback functions (e.g., COMM\_COPY\_ATTR\_FUNCTION) and their predefined callbacks (e.g., MPI\_COMM\_NULL\_COPY\_FN), the ierror argument is not optional. The MPI library must always call these routines with an actual ierror argument. Therefore, these user-defined functions need not check whether the MPI library calls these routines with or without an actual ierror output argument. (End of rationale.)

The MPI Fortran bindings in the mpi\_f08 module are designed based on the Fortran 2008 standard [45] together with the Technical Specification "TS 29113 Further Interoperability with C" [46] of the ISO/IEC JTC1/SC22/WG5 (Fortran) working group.

Rationale. The features in TS 29113 on further interoperability with C were decided on by ISO/IEC JTC1/SC22/WG5 and designed by PL22.3 (formerly J3) to support a higher level of integration between Fortran-specific features and C than was provided in the Fortran 2008 standard; part of this design is based on requirements from the MPI Forum to support MPI-3.0. According to [46], "an ISO/IEC TS is reviewed after three years in order to decide whether it will be confirmed for a further three years, revised to become an International Standard, or withdrawn. If the ISO/IEC TS is confirmed, it is reviewed again after a further three years, at which time it must either be transformed into an International Standard or be withdrawn."

The TS 29113 contains the following language features that are needed for the MPI bindings in the mpi\_f08 module: assumed-type and assumed-rank. It is important that any possible actual argument can be used for such dummy arguments, e.g., scalars, arrays, assumed-shape arrays, assumed-size arrays, allocatable arrays, and

with any element type, e.g., REAL, CHARACTER\*5, CHARACTER\*(\*), sequence derived types, or BIND(C) derived types. Especially for backward compatibility reasons, it is important that any possible actual argument in an implicit interface implementation of a choice buffer dummy argument (e.g., with mpif.h without argument-checking) can be used in an implementation with assumed-type and assumed-rank argument in an explicit interface (e.g., with the mpi\_f08 module).

A further feature useful for MPI is the extension of the semantics of the ASYNCHRONOUS attribute: In F2003 and F2008, this attribute could be used only to protect buffers of Fortran asynchronous I/O. With TS 29113, this attribute now also covers asynchronous communication occurring within library routines written in C.

The MPI Forum hereby wishes to acknowledge this important effort by the Fortran PL22.3 and WG5 committee. (*End of rationale.*)

### 19.1.3 Fortran Support Through the mpi Module

An MPI implementation providing a Fortran interface must provide a module named mpi that can be used in a Fortran program. Within all MPI function specifications, the second of the set of two Fortran routine interface specifications is provided by this module. This module must:

- Define all named MPI constants
- Declare MPI functions that return a value.
- Provide explicit interfaces according to the Fortran routine interface specifications. This module therefore guarantees compile-time argument checking and allows positional and keyword-based argument lists. If an implementation is paired with a compiler that either does not support TYPE(\*), DIMENSION(..) from TS 29113, or is otherwise unable to ignore the types of choice buffers, then the implementation must provide explicit interfaces only for MPI routines with no choice buffer arguments. See Section 19.1.6 for more details.
- Define all MPI handles as type INTEGER.
- Define the derived type MPI\_Status and all named handle types that are used in the mpi\_f08 module. For these named handle types, overload the operators .EQ. and .NE. to allow handle comparison via the .EQ., .NE., == and /= operators.

Rationale. They are needed only when the application converts old-style INTEGER handles into new-style handles with a named type. (End of rationale.)

- A high quality MPI implementation may enhance the interface by using the ASYNCHRONOUS attribute in the same way as in the mpi\_f08 module if it is supported by the underlying compiler.
- Set the LOGICAL compile-time constant MPI\_ASYNC\_PROTECTS\_NONBLOCKING to .TRUE. if the ASYNCHRONOUS attribute is used in all nonblocking interfaces and the underlying Fortran compiler supports the ASYNCHRONOUS attribute for MPI communication (as part of TS 29113), otherwise to .FALSE..

1

2

21 22 23

24

25

26

18

19

20

27 28 29

30

31

32 33 34

35

36

37 38 39

41 42 43

For an MPI implementation that fully supports nonblocking calls Advice to users. with the ASYNCHRONOUS attribute for choice buffers, an existing MPI-2.2 application may fail to compile even if it compiled and executed with expected results with an MPI-2.2 implementation. One reason may be that the application uses "contiguous" but not "simply contiguous" ASYNCHRONOUS arrays as actual arguments for choice buffers of nonblocking routines, e.g., by using subscript triplets with stride one or specifying (1:n) for a whole dimension instead of using (:). This should be fixed to fulfill the Fortran constraints for ASYNCHRONOUS dummy arguments. This is not considered a violation of backward compatibility because existing applications can not use the ASYNCHRONOUS attribute to protect nonblocking calls. Another reason may be that the application does not conform either to MPI-2.2, or to MPI-3.0, or to the Fortran standard, typically because the program forces the compiler to perform copy-in/out for a choice buffer argument in a nonblocking MPI call. This is also not a violation of backward compatibility because the application itself is non-conforming. See Section 19.1.12 for more details. (End of advice to users.)

- A high quality MPI implementation may enhance the interface by using TYPE(\*), DIMENSION(..) choice buffer dummy arguments instead of using non-standardized extensions such as !\$PRAGMA IGNORE\_TKR or a set of overloaded functions as described by M. Hennecke in [32], if the compiler supports this TS 29113 language feature. See Section 19.1.6 for further details.
- Set the LOGICAL compile-time constant MPI\_SUBARRAYS\_SUPPORTED to .TRUE. if all choice buffer arguments in all nonblocking, split collective and persistent communication routines are declared with TYPE(\*), DIMENSION(..), otherwise set it to .FALSE.. When MPI\_SUBARRAYS\_SUPPORTED is defined as .TRUE., non-contiguous sub-arrays can be used as buffers in nonblocking routines.
- Set the MPI\_SUBARRAYS\_SUPPORTED compile-time constant to .FALSE. and declare choice buffers with a compiler-dependent mechanism that overrides type checking if the underlying Fortran compiler does not support the TS 29113 assumed-type and assumed-rank features. In this case, the use of non-contiguous sub-arrays in non-blocking calls may be disallowed. See Section 19.1.6 for details.

An MPI implementation may provide other features in the mpi module that enhance the usability of MPI while maintaining adherence to the standard. For example, it may provide INTENT information in these interface blocks.

Advice to implementors. The appropriate INTENT may be different from what is given in the MPI language-neutral bindings. Implementations must choose INTENT so that the function adheres to the MPI standard, e.g., by defining the INTENT as provided in the mpi\_f08 bindings. (End of advice to implementors.)

Rationale. The intent given by the MPI generic interface is not precisely defined and does not in all cases correspond to the correct Fortran INTENT. For instance, receiving into a buffer specified by a datatype with absolute addresses may require associating MPI\_BOTTOM with a dummy OUT argument. Moreover, "constants" such as MPI\_BOTTOM and MPI\_STATUS\_IGNORE are not constants as defined by Fortran, but "special addresses" used in a nonstandard way. Finally, the MPI-1 generic intent

was changed in several places in MPI-2. For instance, MPI\_IN\_PLACE changes the intent of an OUT argument to be INOUT. (*End of rationale*.)

Advice to implementors. The Fortran 2008 standard illustrates in its Note 5.17 that "INTENT(OUT) means that the value of the argument after invoking the procedure is entirely the result of executing that procedure. If an argument should retain its value rather than being redefined, INTENT(INOUT) should be used rather than INTENT(OUT), even if there is no explicit reference to the value of the dummy argument. Furthermore, INTENT(INOUT) is not equivalent to omitting the INTENT attribute, because INTENT(INOUT) always requires that the associated actual argument is definable." Applications that include mpif.h may not expect that INTENT(OUT) is used. In particular, output array arguments are expected to keep their content as long as the MPI routine does not modify them. To keep this behavior, it is recommended that implementations not use INTENT(OUT) in the mpi module and the mpif.h include file, even though INTENT(OUT) is specified in an interface description of the mpi\_fo8 module. (End of advice to implementors.)

### 19.1.4 Fortran Support Through the mpif.h Include File

The use of the mpif.h include file is strongly discouraged and may be deprecated in a future version of MPI.

An MPI implementation providing a Fortran interface must provide an include file named mpif.h that can be used in a Fortran program. Within all MPI function specifications, the second of the set of two Fortran routine interface specifications is supported by this include file. This include file must:

- Define all named MPI constants.
- Declare MPI functions that return a value.
- Define all handles as INTEGER.
- Be valid and equivalent for both fixed and free source form.

For each MPI routine, an implementation can choose to use an implicit or explicit interface for the second Fortran binding (in deprecated routines, the first one may be omitted).

• Set the LOGICAL compile-time constants MPI\_SUBARRAYS\_SUPPORTED and MPI\_ASYNC\_PROTECTS\_NONBLOCKING according to the same rules as for the mpi module. In the case of implicit interfaces for choice buffer or nonblocking routines, the constants must be set to .FALSE..

Advice to users. Instead of using mpif.h, the use of the mpi\_f08 or mpi module is strongly encouraged for the following reasons:

- Most mpif.h implementations do not include compile-time argument checking.
- Therefore, many bugs in MPI applications remain undetected at compile-time, such as:
  - Missing ierror as last argument in most Fortran bindings.

- Declaration of a status as an INTEGER variable instead of an INTEGER array with size MPI\_STATUS\_SIZE.
- Incorrect argument positions; e.g., interchanging the count and datatype arguments.
- Passing incorrect MPI handles; e.g., passing a datatype instead of a communicator.
- The migration from mpif.h to the mpi module should be relatively straightforward (i.e., substituting include 'mpif.h' after an implicit statement by use mpi before that implicit statement) as long as the application syntax is correct.
- Migrating portable and correctly written applications to the mpi module is not expected to be difficult. No compile or runtime problems should occur because an mpif.h include file was always allowed to provide explicit Fortran interfaces.

(End of advice to users.)

Rationale. With MPI-3.0, the mpif.h include file was not deprecated in order to retain strong backward compatibility. Internally, mpif.h and the mpi module may be implemented so that essentialy the same library implementation of the MPI routines can be used. (End of rationale.)

### 19.1.5 Interface Specifications, Procedure Names, and the Profiling Interface

The Fortran interface specification of each MPI routine specifies the routine name that must be called by the application program, and the names and types of the dummy arguments together with additional attributes. The Fortran standard allows a given Fortran interface to be implemented with several methods, e.g., within or outside of a module, with or without BIND(C), or the buffers with or without TS 29113. Such implementation decisions imply different binary interfaces and different specific procedure names. The requirements for several implementation schemes together with the rules for the specific procedure names and its implications for the profiling interface are specified within this section, but not the implementation details.

Rationale. This section was introduced in MPI-3.0 on Sep. 21, 2012. The major goals for implementing the three Fortran support methods have been:

- Portable implementation of the wrappers from the MPI Fortran interfaces to the MPI routines in C.
- Binary backward compatible implementation path when switching MPI\_SUBARRAYS\_SUPPORTED from .FALSE. to .TRUE..
- The Fortran PMPI interface need not be backward compatible, but a method
  must be included that a tools layer can use to examine the MPI library about
  the specific procedure names and interfaces used.
- No performance drawbacks.
- Consistency between all three Fortran support methods.
- Consistent with Fortran 2008 + TS 29113.

Done

	No.	Specific pro-	Calling convention
	110.	cedure name	
	1A	MPI_Isend_f08	Fortran interface and arguments, as in Annex A.4, except
	171	WI I_ISCHU_100	that in routines with a choice buffer dummy argument, this dummy argument is implemented with non-standard extensions like !\$PRAGMA IGNORE_TKR, which provides a call-by-reference argument without type, kind, and dimension checking.
	1B	MPI_Isend_f08ts	Fortran interface and arguments, as in Annex A.4, but only for routines with one or more choice buffer dummy arguments; these dummy arguments are implemented with TYPE(*), DIMENSION().
	2A	MPI_ISEND	Fortran interface and arguments, as in Annex A.5, except that in routines with a choice buffer dummy argument, this dummy argument is implemented with non-standard extensions like !\$PRAGMA IGNORE_TKR, which provides a call-by-reference argument without type, kind, and dimension checking.
	2B	MPI_ISEND_FTS	Fortran interface and arguments, as in Annex A.5, but
In mpif.h only, the postfix "_FTS" for MPI_NEIGHBOR_ALLTOALLW_INIT, MPI_NEIGHBOR_ALLTOALLV_INIT, and MPI_NEIGHBOR_ALLGATHERV_INIT is		stfix "_FTS" for "OALLW_INIT, "OALLV_INIT, and	only for routines with one or more choice buffer dummy arguments; these dummy arguments are implemented with TYPE(*), DIMENSION().
shortened to " F".			

Table 19.1: Specific Fortran procedure names and related calling conventions. MPI\_ISEND is used as an example. For routines without choice buffers, only 1A and 2A apply.

The design expected that all dummy arguments in the MPI Fortran interfaces are interoperable with C according to Fortran 2008 + TS 29113. This expectation was not fulfilled. The LOGICAL arguments are not interoperable with C, mainly because the internal representations for .FALSE. and .TRUE. are compiler dependent. The provided interface was mainly based on BIND(C) interfaces and therefore inconsistent with Fortran. To be consistent with Fortran, the BIND(C) had to be removed from the callback procedure interfaces and the predefined callbacks, e.g., MPI\_COMM\_DUP\_FN. Non-BIND(C) procedures are also not interoperable with C, and therefore the BIND(C) had to be removed from all routines with PROCEDURE arguments, e.g., from MPI\_OP\_CREATE.

Therefore, this section was rewritten as an erratum to MPI-3.0. (End of rationale.)

A Fortran call to an MPI routine shall result in a call to a procedure with one of the specific procedure names and calling conventions, as described in Table 19.1. Case is not significant in the names.

Note that for the deprecated routines in Section 16.1, which are reported only in Annex A.5, scheme 2A is utilized in the mpi module and mpif.h, and also in the mpi\_f08 module.

To set MPI\_SUBARRAYS\_SUPPORTED to .TRUE. within a Fortran support method, it is required that all nonblocking and split-collective routines with buffer arguments are implemented according to 1B and 2B, i.e., with MPI\_Xxxx\_f08ts in the mpi\_f08 module,

and with MPI\_XXXX\_FTS in the mpi module and the mpif.h include file.

The mpi and mpi\_f08 modules and the mpif.h include file will each correspond to exactly one implementation scheme from Table 19.1. However, the MPI library may contain multiple implementation schemes from Table 19.1.

Advice to implementors. This may be desirable for backwards binary compatibility in the scope of a single MPI implementation, for example. (End of advice to implementors.)

Rationale. After a compiler provides the facilities from TS 29113, i.e., TYPE(\*), DIMENSION(..), it is possible to change the bindings within a Fortran support method to support subarrays without recompiling the complete application provided that the previous interfaces with their specific procedure names are still included in the library. Of course, only recompiled routines can benefit from the added facilities. There is no binary compatibility conflict because each interface uses its own specific procedure names and all interfaces use the same constants (except the value of MPI\_SUBARRAYS\_SUPPORTED and MPI\_ASYNC\_PROTECTS\_NONBLOCKING) and type definitions. After a compiler also ensures that buffer arguments of nonblocking MPI operations can be protected through the ASYNCHRONOUS attribute, and the procedure declarations in the mpi\_f08 and mpi module and the mpif.h include file declare choice buffers with the ASYNCHRONOUS attribute, then the value of MPI\_ASYNC\_PROTECTS\_NONBLOCKING can be switched to .TRUE. in the module definition and include file. (End of rationale.)

Advice to users. Partial recompilation of user applications when upgrading MPI implementations is a highly complex and subtle topic. Users are strongly advised to consult their MPI implementation's documentation to see exactly what is—and what is not—supported. (End of advice to users.)

Within the mpi\_f08 and mpi modules and mpif.h, for all MPI procedures, a second procedure with the same calling conventions shall be supplied, except that the name is modified by prefixing with the letter "P", e.g., PMPI\_Isend. The specific procedure names for these PMPI\_Xxxx procedures must be different from the specific procedure names for the MPI\_Xxxx procedures and are not specified by this standard.

A user-written or middleware profiling routine should provide the same specific Fortran procedure names and calling conventions, and therefore can interpose itself as the MPI library routine. The profiling routine can internally call the matching PMPI routine with any of its existing bindings, except for routines that have callback routine dummy arguments, choice buffer arguments, or that are attribute caching routines (MPI\_{COMM|WIN|TYPE}\_{SET|GET}\_ATTR). In this case, the profiling software should invoke the corresponding PMPI routine using the same Fortran support method as used in the calling application program, because the C, mpi\_f08 and mpi callback prototypes are different or the meaning of the choice buffer or attribute\_val arguments are different.

Advice to users. Although for each support method and MPI routine (e.g., MPI\_ISEND in mpi\_f08), multiple routines may need to be provided to intercept the specific procedures in the MPI library (e.g., MPI\_Isend\_f08 and MPI\_Isend\_f08ts), each profiling routine itself uses only one support method (e.g., mpi\_f08) and calls the real MPI routine through the one PMPI routine defined in this support method (i.e., PMPI\_Isend in this example). (End of advice to users.)

12

13 14

15

16

17

18 19

20

21

22

23

24

25

26

27

28

29

30

31

32

33

34

35

36

37

38

39

40

41

42

43

44

45

46

47

Advice to implementors. If all of the following conditions are fulfilled:

- the handles in the mpi\_f08 module occupy one Fortran numerical storage unit (same as an INTEGER handle),
- the internal argument passing mechanism used to pass an actual ierror argument to a non-optional ierror dummy argument is binary compatible to passing an actual ierror argument to an ierror dummy argument that is declared as OPTIONAL,
- the internal argument passing mechanism for ASYNCHRONOUS and non-ASYNCHRONOUS arguments is the same,
- the internal routine call mechanism is the same for the Fortran and the C compilers for which the MPI library is compiled,
- the compiler does not provide TS 29113,

then the implementor may use the same internal routine implementations for all Fortran support methods but with several different specific procedure names. If the accompanying Fortran compiler supports TS 29113, then the new routines are needed only for routines with choice buffer arguments. (End of advice to implementors.)

In the Fortran support method mpif.h, compile-time Advice to implementors. argument checking can be also implemented for all routines. For mpif.h, the argument names are not specified through the MPI standard, i.e., only positional argument lists are defined, and not key-word based lists. Due to the rule that mpif.h must be valid for fixed and free source form, the subroutine declaration is restricted to one line with 72 characters. To keep the argument lists short, each argument name can be shortened to a minimum of one character. With this, the two longest subroutine three declaration statements are

These examples are beased on the tables on page 777

```
SUBROUTINE PMPI DIST GRAPH CREATE ADJACENT(a,b,c,d,e,f,g,h,i,j,k)
SUBROUTINE PMPI NEIGHBOR ALLTOALLW INIT(a,b,c,d,e,f,g,h,i,j,k,l)
SUBROUTINE PMPI NEIGHBOR ALLTOALLV INIT(a,b,c,d,e,f,g,h,i,j,k,l)
```

Some of the each with 71 and 66 characters. With buffers implemented with TS 29113, the specific procedure names have an additional postfix. The longest of such interface definitions

```
are 🔠
```

72, 71, and 70

71 and 70

```
INTERFACE
           PMPI NEIGHBOR ALLTOALLW INIT
SUBROUTINE PMPI NEIGHBOR ALLTOALLW INIT F(a,b,c,d,e,f,g,h,i,j,k)
INTERFACE PMPI NEIGHBOR ALLGATHERV INIT
SUBROUTINE PMPI NEIGHBOR ALLGATHERV INIT_F(a,b,c,d,e,f,g,h,i,j,k)
         PMPI RGET ACCUMULATE
SUBROUTINE PMPI RGET ACCUMULATE FTS(a,b,c,d,e,f,g,h,i,j,k,l,m,n)
```

with 70 characters. In principle, continuation lines would be possible in mpif.h (spaces in columns 73-131, & in column 132, and in column 6 of the continuation line) but this would not be valid if the source line length is extended with a compiler flag to 132 characters. Column 133 is also not available for the continuation character because lines longer than 132 characters are invalid with some compilers by default.

#-error! #-335 #-358 + 359 2.2. p10 18.1 p.777 19.1.5 p789 B.1.2 p.1031ff

The longest specific procedure names are PMPI\_Dist\_graph\_create\_adjacent\_f08 and PMPI\_File\_write\_ordered\_begin\_f08ts both with 35 characters in the mpi\_f08 module.

For example, the interface specifications together with the specific procedure names can be implemented with

The longest specific procedure name is PMPI\_Reduce\_scatter\_block\_init\_c\_f08ts with 38 characters in the mpi\_f08 module.

Unofficial Draft for Comment Only

Done in PR434 #-error #-update2

```
1
           MODULE mpi_f08
2
            TYPE, BIND(C) :: MPI_Comm
               INTEGER :: MPI_VAL
            END TYPE MPI_Comm
            INTERFACE MPI_Comm_rank ! (as defined in Chapter 6)
               SUBROUTINE MPI_Comm_rank_f08(comm, rank, ierror)
                 IMPORT :: MPI_Comm
                 TYPE(MPI_Comm),
                                       INTENT(IN) :: comm
9
                                       INTENT(OUT) :: rank
                 INTEGER,
                 INTEGER, OPTIONAL,
                                       INTENT(OUT) :: ierror
10
               END SUBROUTINE
11
            END INTERFACE
12
           END MODULE mpi_f08
13
14
           MODULE mpi
15
            INTERFACE MPI_Comm_rank ! (as defined in Chapter 6)
16
               SUBROUTINE MPI_Comm_rank(comm, rank, ierror)
                                                 ! The INTENT may be added although
                 INTEGER, INTENT(IN) :: comm
                 INTEGER, INTENT(OUT) :: rank
                                                 ! it is not defined in the
18
                 INTEGER, INTENT(OUT) :: ierror ! official routine definition.
19
               END SUBROUTINE
20
            END INTERFACE
21
           END MODULE mpi
22
23
           And if interfaces are provided in mpif.h, they might look like this (outside of any
24
           module and in fixed source format):
           !2345678901234567890123456789012345678901234567890123456789012
26
                 INTERFACE MPI_Comm_rank ! (as defined in Chapter 6)
27
                  SUBROUTINE MPI_Comm_rank(comm, rank, ierror)
28
                   INTEGER, INTENT(IN) :: comm ! The argument names may be
29
                   INTEGER, INTENT(OUT) :: rank
                                                   ! shortened so that the
30
                   INTEGER, INTENT(OUT) :: ierror ! subroutine line fits to the
31
                  END SUBROUTINE
                                                   ! maximum of 72 characters.
32
                 END INTERFACE
33
34
           (End of advice to implementors.)
35
           Advice to users.
                            The following is an example of how a user-written or middleware
36
           profiling routine can be implemented:
37
           SUBROUTINE MPI_Isend_f08ts(buf,count,datatype,dest,tag,comm,request,ierror)
39
            USE :: mpi_f08, my_noname => MPI_Isend_f08ts
            TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
41
            INTEGER,
                                  INTENT(IN)
                                                   :: count, dest, tag
42
            TYPE(MPI_Datatype), INTENT(IN)
                                                   :: datatype
            TYPE(MPI_Comm),
                                 INTENT(IN)
                                                   :: comm
43
            TYPE(MPI_Request), INTENT(OUT)
                                                   :: request
44
             INTEGER, OPTIONAL,
                                 INTENT(OUT)
                                                   :: ierror
45
               ! ... some code for the begin of profiling
             call PMPI_Isend (buf, count, datatype, dest, tag, comm, request, ierror)
47
               ! ... some code for the end of profiling
           END SUBROUTINE MPI_Isend_f08ts
```

6

10

11

12

13

14

15

16

17

19

20

21

22

23

24

25 26

27

28

29

30 31

32

34

35

36 37

38

39

42

43

44

45 46

47

Note that this routine is used to intercept the existing specific procedure name MPI\_lsend\_f08ts in the MPI library. This routine must not be part of a module. This routine itself calls PMPI\_lsend. The USE of the mpi\_f08 module is needed for definitions of handle types and the interface for PMPI\_lsend. However, this module also contains an interface definition for the specific procedure name MPI\_lsend\_f08ts that conflicts with the definition of this profiling routine (i.e., the name is doubly defined). Therefore, the USE here specifically excludes the interface from the module by renaming the unused routine name in the mpi\_f08 module into "my\_noname" in the scope of this routine. (End of advice to users.)

The PMPI interface allows intercepting MPI routines. For exam-Advice to users. ple, an additional MPI\_ISEND profiling wrapper can be provided that is called by the application and internally calls PMPI\_ISEND. There are two typical use cases: a profiling layer that is developed independently from the application and the MPI library, and profiling routines that are part of the application and have access to the application data. With MPI-3.0, new Fortran interfaces and implementation schemes were introduced that have several implications on how Fortran MPI routines are internally implemented and optimized. For profiling layers, these schemes imply that several internal interfaces with different specific procedure names may need to be intercepted, as shown in the example code above. Therefore, for wrapper routines that are part of a Fortran application, it may be more convenient to make the name shift within the application, i.e., to substitute the call to the MPI routine (e.g., MPI\_ISEND) by a call to a user-written profiling wrapper with a new name (e.g., X\_MPI\_ISEND) and to call the Fortran MPI\_ISEND from this wrapper, instead of using the PMPI interface. (End of advice to users.)

Advice to implementors. An implementation that provides a Fortran interface must provide a combination of MPI library and module or include file that uses the specific procedure names as described in Table 19.1 so that the MPI Fortran routines are interceptable as described above. (End of advice to implementors.)

## 19.1.6 MPI for Different Fortran Standard Versions

This section describes which Fortran interface functionality can be provided for different versions of the Fortran standard.

- For Fortran 77 with some extensions:
  - MPI identifiers may be up to 30 characters (31 with the profiling interface).
  - MPI identifiers may contain underscores after the first character.
  - An MPI subroutine with a choice argument may be called with different argument types.
  - Although not required by the MPI standard, the INCLUDE statement should be available for including mpif.h into the user application source code.

Only MPI-1.1, MPI-1.2, and MPI-1.3 can be implemented. The use of absolute addresses from MPI\_ADDRESS and MPI\_BOTTOM may cause problems if an address does not fit into the memory space provided by an INTEGER. (In MPI-2.0 this problem is solved with MPI\_GET\_ADDRESS, but not for Fortran 77.)

2

9

10 11

12

13

14

15

16 17

18

19

20

21

22 23

24

26

27

28

29 30

31

32

33

34

35

36

37

38

39

41

42

43

44 45

46

47

• For Fortran 90:

The major additional features that are needed from Fortran 90 are:

- The MODULE and INTERFACE concept.
- The KIND= and SELECTED\_XXX\_KIND concept.
- Fortran derived TYPEs and the SEQUENCE attribute.
- The OPTIONAL attribute for dummy arguments.
- Cray pointers, which are a non-standard compiler extension, are needed for the use of MPI\_ALLOC\_MEM.

With these features, MPI-1.1 – MPI-2.2 can be implemented without restrictions. MPI-3.0 can be implemented with some restrictions. The Fortran support methods are abbreviated with S1 = the mpi\_f08 module, S2 = the mpi module, and S3 = the mpif.f include file. If not stated otherwise, restrictions exist for each method which prevent implementing the complete semantics of MPI-3.0.

- MPI\_SUBARRAYS\_SUPPORTED equals .FALSE., i.e., subscript triplets and noncontiguous subarrays cannot be used as buffers in nonblocking routines, RMA, or split-collective I/O.
- S1, S2, and S3 can be implemented, but for S1, only a preliminary implementation is possible.
- In this preliminary interface of \$1, the following changes are necessary:
  - \* TYPE(\*), DIMENSION(..) is substituted by non-standardized extensions like !\$PRAGMA IGNORE\_TKR.
  - \* The ASYNCHRONOUS attribute is omitted.
  - \* PROCEDURE(...) callback declarations are substituted by EXTERNAL.
- The specific procedure names are specified in Section 19.1.5.
- Due to the rules specified in Section 19.1.5, choice buffer declarations should be implemented only with non-standardized extensions like !\$PRAGMA IGNORE\_TKR (as long as F2008+TS 29113 is not available).
  - In S2 and S3: Without such extensions, routines with choice buffers should be provided with an implicit interface, instead of overloading with a different MPI function for each possible buffer type (as mentioned in Section 19.1.11). Such overloading would also imply restrictions for passing Fortran derived types as choice buffer, see also Section 19.1.15.
  - Only in S1: The implicit interfaces for routines with choice buffer arguments imply that the ierror argument cannot be defined as OPTIONAL. For this reason, it is recommended not to provide the mpi\_f08 module if such an extension is not available.
- The ASYNCHRONOUS attribute can **not** be used in applications to protect buffers in nonblocking MPI calls (S1-S3).
- The TYPE(C\_PTR) binding of the MPI\_ALLOC\_MEM and MPI\_WIN\_ALLOCATE routines is not available.

6

11

12 13

14

15 16

17

18

19

20

21 22

23

24

26

27 28

29

30

31

33

34 35

36 37

41

42

43 44

45

46

47

- In S1 and S2, the definition of the handle types (e.g., TYPE(MPI\_Comm) and the status type TYPE(MPI\_Status) must be modified: The SEQUENCE attribute must be used instead of BIND(C) (which is not available in Fortran 90/95). This restriction implies that the application must be fully recompiled if one switches to an MPI library for Fortran 2003 and later because the internal memory size of the handles may have changed. For this reason, an implementor may choose not to provide the mpi\_f08 module for Fortran 90 compilers. In this case, the mpi\_f08 handle types and all routines, constants and types related to TYPE(MPI\_Status) (see Section 19.3.5) are also not available in the mpi module and mpif.h.
- For Fortran 95:

The quality of the MPI interface and the restrictions are the same as with Fortran 90.

• For Fortran 2003:

The major features that are needed from Fortran 2003 are:

- Interoperability with C, i.e.,
  - \* BIND(C) derived types.
  - \* The ISO\_C\_BINDING intrinsic type C\_PTR and routine C\_F\_POINTER.
- The ability to define an ABSTRACT INTERFACE and to use it for PROCEDURE dummy arguments.
- The ability to overload the operators .EQ. and .NE. to allow the comparison of derived types (used in MPI-3.0 for MPI handles).
- The ASYNCHRONOUS attribute is available to protect Fortran asynchronous I/O. This feature is not yet used by MPI, but it is the basis for the enhancement for MPI communication in the TS 29113.

With these features (but still without the features of TS 29113), MPI-1.1 – MPI-2.2 can be implemented without restrictions, but with one enhancement:

 The user application can use TYPE(C\_PTR) together with MPI\_ALLOC\_MEM as long as MPI\_ALLOC\_MEM is defined with an implicit interface because a C\_PTR and an INTEGER(KIND=MPI\_ADDRESS\_KIND) argument must both map to a void \* argument.

MPI-3.0 can be implemented with the following restrictions:

- MPI\_SUBARRAYS\_SUPPORTED equals .FALSE..
- For \$1, only a preliminary implementation is possible. The following changes are necessary:
  - \* TYPE(\*), DIMENSION(..) is substituted by non-standardized extensions like !\$PRAGMA IGNORE\_TKR.
- The specific procedure names are specified in Section 19.1.5.
- With S1, the ASYNCHRONOUS is required as specified in the second Fortran interfaces. With S2 and S3 the implementation can also add this attribute if explicit interfaces are used.

- The ASYNCHRONOUS Fortran attribute can be used in applications to try to protect buffers in nonblocking MPI calls, but the protection can work only if the compiler is able to protect asynchronous Fortran I/O and makes no difference between such asynchronous Fortran I/O and MPI communication.
- The TYPE(C\_PTR) binding of the MPI\_ALLOC\_MEM, MPI\_WIN\_ALLOCATE,
   MPI\_WIN\_ALLOCATE\_SHARED, and MPI\_WIN\_SHARED\_QUERY routines can be used only for Fortran types that are C compatible.
- The same restriction as for Fortran 90 applies if non-standardized extensions like
   !\$PRAGMA IGNORE\_TKR are not available.
- For Fortran 2008 + TS 29113 and later and For Fortran 2003 + TS 29113:

The major feature that are needed from TS 29113 are:

- TYPE(\*), DIMENSION(..) is available.
- The ASYNCHRONOUS attribute is extended to protect also nonblocking MPI communication.
- The array dummy argument of the ISO\_C\_BINDING intrinsic C\_F\_POINTER is not restricted to Fortran types for which a corresponding type in C exists.

Using these features, MPI-3.0 can be implemented without any restrictions.

- With S1, MPI\_SUBARRAYS\_SUPPORTED equals .TRUE.. The ASYNCHRONOUS attribute can be used to protect buffers in nonblocking MPI calls. The TYPE(C\_PTR) binding of the MPI\_ALLOC\_MEM, MPI\_WIN\_ALLOCATE, MPI\_WIN\_ALLOCATE\_SHARED, and MPI\_WIN\_SHARED\_QUERY routines can be used for any Fortran type.
- With S2 and S3, the value of MPI\_SUBARRAYS\_SUPPORTED is implementation dependent. A high quality implementation will also provide
   MPI\_SUBARRAYS\_SUPPORTED set to .TRUE. and will use the ASYNCHRONOUS attribute in the same way as in S1.
- If non-standardized extensions like !\$PRAGMA IGNORE\_TKR are not available then
   S2 must be implemented with TYPE(\*), DIMENSION(..).

Advice to implementors. If MPI\_SUBARRAYS\_SUPPORTED==.FALSE., the choice argument may be implemented with an explicit interface using compiler directives, for example:

```
INTERFACE

SUBROUTINE MPI_...(buf, ...)

!DEC$ ATTRIBUTES NO_ARG_CHECK :: buf

!$PRAGMA IGNORE_TKR buf

!DIR$ IGNORE_TKR buf

!IBM* IGNORE_TKR buf

REAL, DIMENSION(*) :: buf

...! declarations of the other arguments

END SUBROUTINE

END INTERFACE

(End of advice to implementors.)
```

## 19.1.7 Requirements on Fortran Compilers

MPI-3.0 (and later) compliant Fortran bindings are not only a property of the MPI library itself, but rather a property of an MPI library together with the Fortran compiler suite for which it is compiled.

Advice to users. Users must take appropriate steps to ensure that proper options are specified to compilers. MPI libraries must document these options. Some MPI libraries are shipped together with special compilation scripts (e.g., mpif90, mpicc) that set these options automatically. (End of advice to users.)

An MPI library together with the Fortran compiler suite is only compliant with MPI-3.0 (and later), as referred by MPI\_GET\_VERSION, if all the solutions described in Sections 19.1.11 through 19.1.19 work correctly. Based on this rule, major requirements for all three Fortran support methods (i.e., the mpi\_f08 and mpi modules, and mpif.h) are:

- The language features assumed-type and assumed-rank from Fortran 2008 TS 29113 [46] are available. This is required only for mpi\_f08. As long as this requirement is not supported by the compiler, it is valid to build an MPI library that implements the mpi\_f08 module with MPI\_SUBARRAYS\_SUPPORTED set to .FALSE..
- "Simply contiguous" arrays and scalars must be passed to choice buffer dummy arguments of nonblocking routines with call by reference. This is needed only if one of the support methods does not use the ASYNCHRONOUS attribute. See Section 19.1.12 for more details.
- SEQUENCE and BIND(C) derived types are valid as actual arguments passed to choice buffer dummy arguments, and, in the case of MPI\_SUBARRAYS\_SUPPORTED== .FALSE., they are passed with call by reference, and passed by descriptor in the case of .TRUE..
- All actual arguments that are allowed for a dummy argument in an implicitly defined and separately compiled Fortran routine with the given compiler (e.g., CHARACTER(LEN=\*) strings and array of strings) must also be valid for choice buffer dummy arguments with all Fortran support methods.
- The array dummy argument of the ISO\_C\_BINDING intrinsic module procedure C\_F\_POINTER is not restricted to Fortran types for which a corresponding type in C exists.
- The Fortran compiler shall not provide TYPE(\*) unless the ASYNCHRONOUS attribute protects MPI communication as described in TS 29113. Specifically, the TS 29113 must be implemented as a whole.

The following rules are required at least as long as the compiler does not provide the extension of the ASYNCHRONOUS attribute as part of TS 29113 and there still exists a Fortran support method with MPI\_ASYNC\_PROTECTS\_NONBLOCKING set to .FALSE.. Observation of these rules by the MPI application developer is especially recomended for backward compatibility of existing applications that use the mpi module or the mpif.h include file. The rules are as follows:

- Separately compiled empty Fortran routines with implicit interfaces and separately compiled empty C routines with BIND(C) Fortran interfaces (e.g., MPI\_F\_SYNC\_REG on page 818 and Section 19.1.8, and DD on page 819) solve the problems described in Section 19.1.17.
- The problems with temporary data movement (described in detail in Section 19.1.18) are solved as long as the application uses different sets of variables for the nonblocking communication (or nonblocking or split collective I/O) and the computation when overlapping communication and computation.
- Problems caused by automatic and permanent data movement (e.g., within a garbage collection, see Section 19.1.19) are resolved **without** any further requirements on the application program, neither on the usage of the buffers, nor on the declaration of application routines that are involved in invoking MPI procedures.

All of these rules are valid for the mpi\_f08 and mpi modules and independently of whether mpif.h uses explicit interfaces.

Advice to implementors. Some of these rules are already part of the Fortran 2003 standard, some of these requirements require the Fortran TS 29113 [46], and some of these requirements for MPI-3.0 are beyond the scope of TS 29113. (End of advice to implementors.)

# 19.1.8 Additional Support for Fortran Register-Memory-Synchronization

As described in Section 19.1.17, a dummy call may be necessary to tell the compiler that registers are to be flushed for a given buffer or that accesses to a buffer may not be moved across a given point in the execution sequence. Only a Fortran binding exists for this call.

```
MPI_F_SYNC_REG(buf)

INOUT buf initial address of buffer (choice)
```

```
Fortran 2008 binding
MPI_F_sync_reg(buf)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
```

```
Fortran binding
MPI_F_SYNC_REG(BUF)
<type> BUF(*)
```

This routine has no executable statements. It must be compiled in the MPI library in such a manner that a Fortran compiler cannot detect in the module that the routine has an empty body. It is used only to force the compiler to flush a cached register value of a variable or buffer back to memory (when necessary), or to invalidate the register value.

Rationale. This function is not available in other languages because it would not be useful. This routine has no ierror return argument because there is no operation that can fail. (End of rationale.)

Advice to implementors. This routine can be bound to a C routine to minimize the risk that the Fortran compiler can learn that this routine is empty (and that the call to this routine can be removed as part of an optimization). However, it is explicitly allowed to implement this routine within the mpi\_f08 module according to the definition for the mpi module or mpif.h to circumvent the overhead of building the internal dope vector to handle the assumed-type, assumed-rank argument. (End of advice to implementors.)

Rationale. This routine is not defined with TYPE(\*), DIMENSION(\*), i.e., assumed size instead of assumed rank, because this would restrict the usability to "simply contiguous" arrays and would require overloading with another interface for scalar arguments. (End of rationale.)

Advice to users. If only a part of an array (e.g., defined by a subscript triplet) is used in a nonblocking routine, it is recommended to pass the whole array to MPI\_F\_SYNC\_REG anyway to minimize the overhead of this no-operation call. Note that this routine need not be called if MPI\_ASYNC\_PROTECTS\_NONBLOCKING is .TRUE. and the application fully uses the facilities of ASYNCHRONOUS arrays. (End of advice to users.)

## 19.1.9 Additional Support for Fortran Numeric Intrinsic Types

MPI provides a small number of named datatypes that correspond to named intrinsic types supported by C and Fortran. These include MPI\_INTEGER, MPI\_REAL, MPI\_INT, MPI\_DOUBLE, etc., as well as the optional types MPI\_REAL4, MPI\_REAL8, etc. There is a one-to-one correspondence between language declarations and MPI types.

Fortran (starting with Fortran 90) provides so-called KIND-parameterized types. These types are declared using an intrinsic type (one of INTEGER, REAL, COMPLEX, LOGICAL, and CHARACTER) with an optional integer KIND parameter that selects from among one or more variants. The specific meaning of different KIND values themselves are implementation dependent and not specified by the language. Fortran provides the KIND selection functions selected\_real\_kind for REAL and COMPLEX types, and selected\_int\_kind for INTEGER types that allow users to declare variables with a minimum precision or number of digits. These functions provide a portable way to declare KIND-parameterized REAL, COMPLEX, and INTEGER variables in Fortran. This scheme is backward compatible with Fortran 77. REAL and INTEGER Fortran variables have a default KIND if none is specified. Fortran DOUBLE PRECISION variables are of intrinsic type REAL with a non-default KIND. The following two declarations are equivalent:

```
double precision x
real(KIND(0.0d0)) x
```

MPI provides two orthogonal methods for handling communication buffers of numeric intrinsic types. The first method (see the following section) can be used when variables have been declared in a portable way—using default KIND or using KIND parameters obtained with the selected\_int\_kind or selected\_real\_kind functions. With this method, MPI automatically selects the correct data size (e.g., 4 or 8 bytes) and provides representation conversion in heterogeneous environments. The second method (see "Support for size-specific MPI Datatypes" on page 802) gives the user complete control over communication by exposing machine representations.

\_

Parameterized Datatypes with Specified Precision and Exponent Range

MPI provides named datatypes corresponding to standard Fortran 77 numeric types:

MPI\_INTEGER, MPI\_COMPLEX, MPI\_REAL, MPI\_DOUBLE\_PRECISION  $\,\operatorname{and}$ 

MPI\_DOUBLE\_COMPLEX. MPI automatically selects the correct data size and provides representation conversion in heterogeneous environments. The mechanism described in this section extends this model to support portable parameterized numeric types.

The model for supporting portable parameterized types is as follows. Real variables are declared (perhaps indirectly) using selected\_real\_kind(p, r) to determine the KIND parameter, where p is decimal digits of precision and r is an exponent range. Implicitly MPI maintains a two-dimensional array of predefined MPI datatypes D(p, r). D(p, r) is defined for each value of (p, r) supported by the compiler, including pairs for which one value is unspecified. Attempting to access an element of the array with an index (p, r) not supported by the compiler is erroneous. MPI implicitly maintains a similar array of COMPLEX datatypes. For integers, there is a similar implicit array related to selected\_int\_kind and indexed by the requested number of digits r. Note that the predefined datatypes contained in these implicit arrays are not the same as the named MPI datatypes MPI\_REAL, etc., but a new set.

Advice to implementors. The above description is for explanatory purposes only. It is not expected that implementations will have such internal arrays. (End of advice to implementors.)

Advice to users. selected\_real\_kind() maps a large number of (p,r) pairs to a much smaller number of KIND parameters supported by the compiler. KIND parameters are not specified by the language and are not portable. From the language point of view intrinsic types of the same base type and KIND parameter are of the same type. In order to allow interoperability in a heterogeneous environment, MPI is more stringent. The corresponding MPI datatypes match if and only if they have the same (p,r) value (REAL and COMPLEX) or r value (INTEGER). Thus MPI has many more datatypes than there are fundamental language types. (End of advice to users.)

```
31
32
33
```

```
MPI_TYPE_CREATE_F90_REAL(p, r, newtype)
```

```
IN p precision, in decimal digits (integer)
IN r decimal exponent range (integer)
OUT newtype the requested MPI datatype (handle)
```

## C binding

```
int MPI_Type_create_f90_real(int p, int r, MPI_Datatype *newtype)
```

## Fortran 2008 binding

```
MPI_Type_create_f90_real(p, r, newtype, ierror)
    INTEGER, INTENT(IN) :: p, r
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

## Fortran binding

```
MPI_TYPE_CREATE_F90_REAL(P, R, NEWTYPE, IERROR)
INTEGER P, R, NEWTYPE, IERROR
```

This function returns a predefined MPI datatype that matches a REAL variable of KIND selected\_real\_kind(p, r). In the model described above it returns a handle for the element D(p, r). Either p or r may be omitted from calls to selected\_real\_kind(p, r) (but not both). Analogously, either p or r may be set to MPI\_UNDEFINED. In communication, an MPI datatype A returned by MPI\_TYPE\_CREATE\_F90\_REAL matches a datatype B if and only if B was returned by MPI\_TYPE\_CREATE\_F90\_REAL called with the same values for p and r or B is a duplicate of such a datatype. Restrictions on using the returned datatype with the "external32" data representation are given on page 801.

It is erroneous to supply values for p and r not supported by the compiler.

## MPI\_TYPE\_CREATE\_F90\_COMPLEX(p, r, newtype)

```
    IN p precision, in decimal digits (integer)
    IN r decimal exponent range (integer)
    OUT newtype the requested MPI datatype (handle)
```

#### C binding

```
int MPI_Type_create_f90_complex(int p, int r, MPI_Datatype *newtype)
```

#### Fortran 2008 binding

```
MPI_Type_create_f90_complex(p, r, newtype, ierror)
    INTEGER, INTENT(IN) :: p, r
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

#### Fortran binding

```
MPI_TYPE_CREATE_F90_COMPLEX(P, R, NEWTYPE, IERROR)
INTEGER P, R, NEWTYPE, IERROR
```

This function returns a predefined MPI datatype that matches a COMPLEX variable of KIND selected\_real\_kind(p, r). Either p or r may be omitted from calls to selected\_real\_kind(p, r) (but not both). Analogously, either p or r may be set to MPI\_UNDEFINED. Matching rules for datatypes created by this function are analogous to the matching rules for datatypes created by MPI\_TYPE\_CREATE\_F90\_REAL. Restrictions on using the returned datatype with the "external32" data representation are given on page 801.

It is erroneous to supply values for p and r not supported by the compiler.

## MPI\_TYPE\_CREATE\_F90\_INTEGER(r, newtype)

```
IN r decimal exponent range, i.e., number of decimal digits (integer)

OUT newtype the requested MPI datatype (handle)
```

#### C binding

```
int MPI_Type_create_f90_integer(int r, MPI_Datatype *newtype)
```

11

12

13

14

15

16

17

21

28

29

30

31

32

33 34

35

36

37

39

41

42

43 44

45

47

```
1
    Fortran 2008 binding
2
    MPI_Type_create_f90_integer(r, newtype, ierror)
3
        INTEGER, INTENT(IN) :: r
4
        TYPE(MPI_Datatype), INTENT(OUT) :: newtype
5
        INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
    Fortran binding
    MPI_TYPE_CREATE_F90_INTEGER(R, NEWTYPE, IERROR)
        INTEGER R, NEWTYPE, IERROR
9
```

This function returns a predefined MPI datatype that matches a INTEGER variable of KIND selected\_int\_kind(r). Matching rules for datatypes created by this function are analogous to the matching rules for datatypes created by MPI\_TYPE\_CREATE\_F90\_REAL. Restrictions on using the returned datatype with the "external32" data representation are given on page 801.

It is erroneous to supply a value for r that is not supported by the compiler. Example:

```
longtype, quadtype
     integer
18
     integer, parameter :: long = selected_int_kind(15)
19
     integer(long) ii(10)
20
     real(selected_real_kind(30)) x(10)
     call MPI_TYPE_CREATE_F90_INTEGER(15, longtype, ierror)
22
     call MPI_TYPE_CREATE_F90_REAL(30, MPI_UNDEFINED, quadtype, ierror)
23
24
25
     call MPI_SEND(ii, 10, longtype, ...)
26
     call MPI_SEND(x,
                        10, quadtype, ...)
27
```

Advice to users. The datatypes returned by the above functions are predefined datatypes. They cannot be freed; they do not need to be committed; they can be used with predefined reduction operations. There are two situations in which they behave differently syntactically, but not semantically, from the MPI named predefined datatypes.

- 1. MPI\_TYPE\_GET\_ENVELOPE returns special combiners that allow a program to retrieve the values of p and r.
- 2. Because the datatypes are not named, they cannot be used as compile-time initializers or otherwise accessed before a call to one of the MPI\_TYPE\_CREATE\_F90\_XXX routines.

If a variable was declared specifying a non-default KIND value that was not obtained with selected\_real\_kind() or selected\_int\_kind(), the only way to obtain a matching MPI datatype is to use the size-based mechanism described in the next section.

```
(End of advice to users.)
```

Advice to implementors. An application may often repeat a call to MPI\_TYPE\_CREATE\_F90\_XXX with the same combination of (XXX,p,r). The application is not allowed to free the returned predefined, unnamed datatype handles. To

prevent the creation of a potentially huge amount of handles, a high quality MPI implementation should return the same datatype handle for the same (REAL/COMPLEX/INTEGER,p,r) combination. Checking for the combination (p,r) in the preceding call to MPI\_TYPE\_CREATE\_F90\_XXX and using a hash table to find formerly generated handles should limit the overhead of finding a previously generated datatype with same combination of (XXX,p,r). (End of advice to implementors.)

Rationale. The MPI\_TYPE\_CREATE\_F90\_REAL/COMPLEX/INTEGER interface needs as input the original range and precision values to be able to define useful and compiler-independent external (Section 14.5.2) or user-defined (Section 14.5.3) data representations, and in order to be able to perform automatic and efficient data conversions in a heterogeneous environment. (End of rationale.)

We now specify how the datatypes described in this section behave when used with the "external32" external data representation described in Section 14.5.2.

The "external32" representation specifies data formats for integer and floating point values. Integer values are represented in two's complement big-endian format. Floating point values are represented by one of three IEEE formats. These are the IEEE "Single," "Double," and "Double Extended" formats, requiring 4, 8, and 16 bytes of storage, respectively. For the IEEE "Double Extended" formats, MPI specifies a Format Width of 16 bytes, with 15 exponent bits, bias = +10383, 112 fraction bits, and an encoding analogous to the "Double" format.

The "external32" representations of the datatypes returned by MPI\_TYPE\_CREATE\_F90\_REAL/COMPLEX/INTEGER are given by the following rules. For MPI\_TYPE\_CREATE\_F90\_REAL:

```
if (p > 33) or (r > 4931) then external32 representation is undefined else if (p > 15) or (r > 307) then external32_size = 16 else if (p > 6) or (r > 37) then external32_size = 8 external32_size = 4
```

For MPI\_TYPE\_CREATE\_F90\_COMPLEX: twice the size as for MPI\_TYPE\_CREATE\_F90\_REAL. For MPI\_TYPE\_CREATE\_F90\_INTEGER:

```
if (r > 38) then external32 representation is undefined else if (r > 18) then external32_size = 16 else if (r > 9) then external32_size = 8 else if (r > 4) then external32_size = 4 else if (r > 2) then external32_size = 2 external32_size = 1
```

If the "external32" representation of a datatype is undefined, the result of using the datatype directly or indirectly (i.e., as part of another datatype or through a duplicated datatype) in operations that require the "external32" representation is undefined. These operations include MPI\_PACK\_EXTERNAL, MPI\_UNPACK\_EXTERNAL, and many MPI\_FILE functions, when the "external32" data representation is used. The ranges for which the "external32" representation is undefined are reserved for future standardization.

 Support for Size-specific MPI Datatypes

MPI provides named datatypes corresponding to optional Fortran 77 numeric types that contain explicit byte lengths—MPI\_REAL4, MPI\_INTEGER8, etc. This section describes a mechanism that generalizes this model to support all Fortran numeric intrinsic types.

We assume that for each **typeclass** (integer, real, complex) and each word size there is a unique machine representation. For every pair (**typeclass**, **n**) supported by a compiler, MPI must provide a named size-specific datatype. The name of this datatype is of the form MPI\_<TYPE>n in C and Fortran where <TYPE> is one of REAL, INTEGER and COMPLEX, and **n** is the length in bytes of the machine representation. This datatype locally matches all variables of type (**typeclass**, **n**) in Fortran. The list of names for such types includes:

```
MPI_REAL4
12
     MPI_REAL8
13
     MPI_REAL16
14
     MPI_COMPLEX8
15
16
     MPI_COMPLEX16
17
     MPI_COMPLEX32
     MPI_INTEGER1
18
19
     MPI_INTEGER2
     MPI_INTEGER4
20
21
     MPI_INTEGER8
     MPI_INTEGER16
22
```

One datatype is required for each representation supported by the Fortran compiler.

Rationale. Particularly for the longer floating-point types, C and Fortran may use different representations. For example, a Fortran compiler may define a 16-byte REAL type with 33 decimal digits of precision while a C compiler may define a 16-byte long double type that implements an 80-bit (10 byte) extended precision floating point value. Both of these types are 16 bytes long, but they are not interoperable. Thus, these types are defined by Fortran, even though C may define types of the same length. (End of rationale.)

To be backward compatible with the interpretation of these types in MPI-1, we assume that the nonstandard declarations REAL\*n, INTEGER\*n, always create a variable whose representation is of size n. These datatypes may also be used for variables declared with KIND=INT8/16/32/64 or KIND=REAL32/64/128, which are defined in the ISO\_FORTRAN\_ENV intrinsic module. Note that the MPI datatypes and the REAL\*n, INTEGER\*n declarations count bytes whereas the Fortran KIND values count bits. All these datatypes are predefined.

The following function allows a user to obtain a size-specific MPI datatype for any intrinsic Fortran type.

## MPI\_TYPE\_MATCH\_SIZE(typeclass, size, datatype)

```
INtypeclassgeneric type specifier (integer)INsizesize, in bytes, of representation (integer)OUTdatatypedatatype with correct type, size (handle)
```

#### C binding

```
int MPI_Type_match_size(int typeclass, int size, MPI_Datatype *datatype)
Fortran 2008 binding
MPI_Type_match_size(typeclass, size, datatype, ierror)
    INTEGER, INTENT(IN) :: typeclass, size
    TYPE(MPI_Datatype), INTENT(OUT) :: datatype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
Fortran binding
MPI_TYPE_MATCH_SIZE(TYPECLASS, SIZE, DATATYPE, IERROR)
    INTEGER TYPECLASS, SIZE, DATATYPE, IERROR
```

typeclass is one of MPI\_TYPECLASS\_REAL, MPI\_TYPECLASS\_INTEGER and MPI\_TYPECLASS\_COMPLEX, corresponding to the desired **typeclass**. The function returns an MPI datatype matching a local variable of type (**typeclass**, **size**).

This function returns a reference (handle) to one of the predefined named datatypes, not a duplicate. This type cannot be freed. MPI\_TYPE\_MATCH\_SIZE can be used to obtain a size-specific type that matches a Fortran numeric intrinsic type by first calling storage\_size() in order to compute the variable size in bits, dividing it by eight, and then calling MPI\_TYPE\_MATCH\_SIZE to find a suitable datatype. In C, one can use the C function sizeof() (which returns the size in bytes) instead of storage\_size() (which returns the size in bits). In addition, for variables of default kind the variable's size can be computed by a call to MPI\_TYPE\_GET\_EXTENT, if the typeclass is known. It is erroneous to specify a size not supported by the compiler.

Rationale. This is a convenience function. Without it, it can be tedious to find the correct named type. See note to implementors below. (End of rationale.)

Advice to implementors. This function could be implemented as a series of tests.

```
int MPI_Type_match_size(int typeclass, int size, MPI_Datatype *rtype)
{
    switch(typeclass) {
        case MPI_TYPECLASS_REAL: switch(size) {
            case 4: *rtype = MPI_REAL4; return MPI_SUCCESS;
            case 8: *rtype = MPI_REAL8; return MPI_SUCCESS;
            default: error(...);
    }
    case MPI_TYPECLASS_INTEGER: switch(size) {
        case 4: *rtype = MPI_INTEGER4; return MPI_SUCCESS;
        case 8: *rtype = MPI_INTEGER8; return MPI_SUCCESS;
        default: error(...);
    }
    ... etc. ...
}

(End of advice to implementors.)
```

CC

 Communication With Size-specific Types

The usual type matching rules apply to size-specific datatypes: a value sent with datatype MPI\_<TYPE>n can be received with this same datatype on another process. Most modern computers use 2's complement for integers and IEEE format for floating point. Thus, communication using these size-specific datatypes will not entail loss of precision or truncation errors.

Advice to users. Care is required when communicating in a heterogeneous environment. Consider the following code:

This may not work in a heterogeneous environment if the value of size is not the same on process 1 and process 0. There should be no problem in a homogeneous environment. To communicate in a heterogeneous environment, there are at least four options. The first is to declare variables of default type and use the MPI datatypes for these types, e.g., declare a variable of type REAL and use MPI\_REAL. The second is to use selected\_real\_kind or selected\_int\_kind and with the functions of the previous section. The third is to declare a variable that is known to be the same size on all architectures (e.g., selected\_real\_kind(12) on almost all compilers will result in an 8-byte representation). The fourth is to carefully check representation size before communication. This may require explicit conversion to a variable of size that can be communicated and handshaking between sender and receiver to agree on a size.

Note finally that using the "external32" representation for I/O requires explicit attention to the representation sizes. Consider the following code:

endif

If processes 0 and 1 are on different machines, this code may not work as expected if the size is different on the two machines. (*End of advice to users.*)

## 19.1.10 Problems With Fortran Bindings for MPI

This section discusses a number of problems that may arise when using MPI in a Fortran program. It is intended as advice to users, and clarifies how MPI interacts with Fortran. It is intended to clarify, not add to, this standard.

As noted in the original MPI specification, the interface violates the Fortran standard in several ways. While these may cause few problems for Fortran 77 programs, they become more significant for Fortran 90 programs, so that users must exercise care when using new Fortran 90 features. With Fortran 2008 and the new semantics defined in TS 29113, most violations are resolved, and this is hinted at in an addendum to each item. The violations were originally adopted and have been retained because they are important for the usability of MPI. The rest of this section describes the potential problems in detail.

The following MPI features are inconsistent with Fortran 90 and Fortran 77.

- 1. An MPI subroutine with a choice argument may be called with different argument types. When using the mpi\_f08 module together with a compiler that supports Fortran 2008 + TS 29113, this problem is resolved.
- 2. An MPI subroutine with an assumed-size dummy argument may be passed an actual scalar argument. This is only solved for choice buffers through the use of DIMENSION(..).
- 3. Nonblocking and split-collective MPI routines assume that actual arguments are passed by address or descriptor and that arguments and the associated data are not copied on entrance to or exit from the subroutine. This problem is solved with the use of the ASYNCHRONOUS attribute.
- 4. An MPI implementation may read or modify user data (e.g., communication buffers used by nonblocking communications) concurrently with a user program that is executing outside of MPI calls. This problem is resolved by relying on the extended semantics of the ASYNCHRONOUS attribute as specified in TS 29113.

- 5. Several named "constants," such as MPI\_BOTTOM, MPI\_IN\_PLACE, MPI\_STATUS\_IGNORE, MPI\_STATUSES\_IGNORE, MPI\_ERRCODES\_IGNORE, MPI\_UNWEIGHTED, MPI\_WEIGHTS\_EMPTY, MPI\_ARGV\_NULL, and MPI\_ARGVS\_NULL are not ordinary Fortran constants and require a special implementation. See Section 2.5.4 for more information.
- 6. The memory allocation routine MPI\_ALLOC\_MEM cannot be used from Fortran 77/90/95 without a language extension (for example, Cray pointers) that allows the allocated memory to be associated with a Fortran variable. Therefore, address sized integers were used in MPI-2.0 MPI-2.2. In Fortran 2003, TYPE(C\_PTR) entities were added, which allow a standard-conforming implementation of the semantics of MPI\_ALLOC\_MEM. In MPI-3.0 and later, MPI\_ALLOC\_MEM has an additional, overloaded interface to support this language feature. The use of Cray pointers is deprecated. The mpi\_f08 module only supports TYPE(C\_PTR) pointers.

Additionally, MPI is inconsistent with Fortran 77 in a number of ways, as noted below.

- MPI identifiers exceed 6 characters.
- MPI identifiers may contain underscores after the first character.
- MPI requires an include file, mpif.h. On systems that do not support include files, the implementation should specify the values of named constants.
- Many routines in MPI have KIND-parameterized integers (e.g., MPI\_ADDRESS\_KIND and MPI\_OFFSET\_KIND) that hold address information. On systems that do not support Fortran 90-style parameterized types, INTEGER\*8 or INTEGER should be used instead.

MPI-1 contained several routines that take address-sized information as input or return address-sized information as output. In C such arguments were of type MPI\_Aint and in Fortran of type INTEGER. On machines where integers are smaller than addresses, these routines can lose information. In MPI-2 the use of these functions has been deprecated and they have been replaced by routines taking INTEGER arguments of KIND=MPI\_ADDRESS\_KIND. A number of MPI-2 functions also take INTEGER arguments of non-default KIND. See Section 2.6 and Section 5.1.1 for more information.

Sections 19.1.11 through 19.1.19 describe several problems in detail which concern the interaction of MPI and Fortran as well as their solutions. Some of these solutions require special capabilities from the compilers. Major requirements are summarized in Section 19.1.7.

## 19.1.11 Problems Due to Strong Typing

All MPI functions with choice arguments associate actual arguments of different Fortran datatypes with the same dummy argument. This is not allowed by Fortran 77, and in Fortran 90, it is technically only allowed if the function is overloaded with a different function for each type (see also Section 19.1.6). In C, the use of void\* formal arguments avoids these problems. Similar to C, with Fortran 2008 + TS 29113 (and later) together with the mpi\_f08 module, the problem is avoided by declaring choice arguments with TYPE(\*), DIMENSION(..), i.e., as assumed-type and assumed-rank dummy arguments.

Using INCLUDE 'mpif.h', the following code fragment is technically invalid and may generate a compile-time error.

```
integer i(5)
real x(5)
...
call mpi_send(x, 5, MPI_REAL, ...)
call mpi_send(i, 5, MPI_INTEGER, ...)
```

In practice, it is rare for compilers to do more than issue a warning. When using either the mpi\_f08 or mpi module, the problem is usually resolved through the assumed-type and assumed-rank declarations of the dummy arguments, or with a compiler-dependent mechanism that overrides type checking for choice arguments.

It is also technically invalid in Fortran to pass a scalar actual argument to an array dummy argument that is not a choice buffer argument. Thus, when using the mpi\_f08 or mpi module, the following code fragment usually generates an error since the dims and periods arguments to MPI\_CART\_CREATE are declared as assumed size arrays INTEGER:: DIMS(\*) and LOGICAL:: PERIODS(\*).

```
USE mpi_f08  ! or USE mpi
INTEGER size
CALL MPI_Cart_create(comm_old, 1, size, .TRUE., .TRUE., comm_cart, ierror)
```

Although this is a non-conforming MPI call, compiler warnings are not expected (but may occur) when using INCLUDE 'mpif.h' and this include file does not use Fortran explicit interfaces.

## 19.1.12 Problems Due to Data Copying and Sequence Association with Subscript Triplets

Arrays with subscript **triplets** describe Fortran subarrays with or without strides, e.g.,

```
REAL a(100,100,100)
CALL MPI_Send(a(11:17, 12:99:3, 1:100), 7*30*100, MPI_REAL, ...)
```

The handling of subscript triplets depends on the value of the constant MPI\_SUBARRAYS\_SUPPORTED:

• If MPI\_SUBARRAYS\_SUPPORTED equals .TRUE.:

Choice buffer arguments are declared as TYPE(\*), DIMENSION(..). For example, consider the following code fragment:

```
REAL s(100), r(100)

CALL MPI_Isend(s(1:100:5), 3, MPI_REAL, ..., rq, ierror)

CALL MPI_Wait(rq, status, ierror)

CALL MPI_Irecv(r(1:100:5), 3, MPI_REAL, ..., rq, ierror)

CALL MPI_Wait(rq, status, ierror)
```

In this case, the individual elements s(1), s(6), and s(11) are sent between the start of MPI\_ISEND and the end of MPI\_WAIT even though the compiled code will not copy s(1:100:5) to a real contiguous temporary scratch buffer. Instead, the compiled code will pass a descriptor to MPI\_ISEND that allows MPI to operate directly on s(1), s(6),

 s(11),...,s(96). The called MPI\_ISEND routine will take only the first three of these elements due to the type signature "3, MPI\_REAL".

All nonblocking MPI functions (e.g., MPI\_ISEND, MPI\_PUT,

MPI\_FILE\_WRITE\_ALL\_BEGIN) behave as if the user-specified elements of choice buffers are copied to a contiguous scratch buffer in the MPI runtime environment. All datatype descriptions (in the example above, "3, MPI\_REAL") read and store data from and to this virtual contiguous scratch buffer. Displacements in MPI derived datatypes are relative to the beginning of this virtual contiguous scratch buffer. Upon completion of a nonblocking receive operation (e.g., when MPI\_WAIT on a corresponding MPI\_Request returns), it is as if the received data has been copied from the virtual contiguous scratch buffer back to the non-contiguous application buffer. In the example above, r(1), r(6), and r(11) are guaranteed to be defined with the received data when MPI\_WAIT returns.

Note that the above definition does not supercede restrictions about buffers used with nonblocking operations (e.g., those specified in Section 3.7.2).

Advice to implementors. The Fortran descriptor for TYPE(\*), DIMENSION(...) arguments contains enough information that, if desired, the MPI library can make a real contiguous copy of non-contiguous user buffers when the nonblocking operation is started, and release this buffer not before the nonblocking communication has completed (e.g., the MPI\_WAIT routine). Efficient implementations may avoid such additional memory-to-memory data copying. (End of advice to implementors.)

Rationale. If MPI\_SUBARRAYS\_SUPPORTED equals .TRUE., non-contiguous buffers are handled inside the MPI library instead of by the compiler through argument association conventions. Therefore, the scope of MPI library scratch buffers can be from the beginning of a nonblocking operation until the completion of the operation although beginning and completion are implemented in different routines. (End of rationale.)

#### • If MPI\_SUBARRAYS\_SUPPORTED equals .FALSE.:

In this case, the use of Fortran arrays with subscript triplets as actual choice buffer arguments in any nonblocking MPI operation (which also includes persistent request, and split collectives) may cause undefined behavior. They may, however, be used in blocking MPI operations.

Implicit in MPI is the idea of a contiguous chunk of memory accessible through a linear address space. MPI copies data to and from this memory. An MPI program specifies the location of data by providing memory addresses and offsets. In the C language, sequence association rules plus pointers provide all the necessary low-level structure.

In Fortran, array data is not necessarily stored contiguously. For example, the array section A(1:N:2) involves only the elements of A with indices 1, 3, 5, .... The same is true for a pointer array whose target is such a section. Most compilers ensure that an array that is a dummy argument is held in contiguous memory if it is declared with

an explicit shape (e.g., B(N)) or is of assumed size (e.g., B(\*)). If necessary, they do this by making a copy of the array into contiguous memory.<sup>1</sup>

Because MPI dummy buffer arguments are assumed-size arrays if MPI\_SUBARRAYS\_SUPPORTED equals .FALSE., this leads to a serious problem for a nonblocking call: the compiler copies the temporary array back on return but MPI continues to copy data to the memory that held it. For example, consider the following code fragment:

```
real a(100) call MPI_IRECV(a(1:100:2), MPI_REAL, 50, ...)
```

Since the first dummy argument to MPI\_IRECV is an assumed-size array (<type>buf(\*)), the array section a(1:100:2) is copied to a temporary before being passed to MPI\_IRECV, so that it is contiguous in memory. MPI\_IRECV returns immediately, and data is copied from the temporary back into the array a. Sometime later, MPI may write to the address of the deallocated temporary. Copying is also a problem for MPI\_ISEND since the temporary array may be deallocated before the data has all been sent from it.

Most Fortran 90 compilers do not make a copy if the actual argument is the whole of an explicit-shape or assumed-size array or is a "simply contiguous" section such as A(1:N) of such an array. ("Simply contiguous" is defined in the next paragraph.) Also, many compilers treat allocatable arrays the same as they treat explicit-shape arrays in this regard (though we know of one that does not). However, the same is not true for assumed-shape and pointer arrays; since they may be discontiguous, copying is often done. It is this copying that causes problems for MPI as described in the previous paragraph.

According to the Fortran 2008 Standard, Section 6.5.4, a "simply contiguous" array section is

```
name ( [:,]... [<subscript>]:[<subscript>] [,<subscript>]... )
```

That is, there are zero or more dimensions that are selected in full, then one dimension selected without a stride, then zero or more dimensions that are selected with a simple subscript. The compiler can detect from analyzing the source code that the array is contiguous. Examples are

```
A(1:N), A(:,N), A(:,1:N,1), A(1:6,N), A(:,:,1:N)
```

Because of Fortran's column-major ordering, where the first index varies fastest, a "simply contiguous" section of a contiguous array will also be contiguous.

The same problem can occur with a scalar argument. A compiler may make a copy of scalar dummy arguments within a called procedure when passed as an actual argument to a choice buffer routine. That this can cause a problem is illustrated by the example

<sup>&</sup>lt;sup>1</sup>Technically, the Fortran standard is worded to allow non-contiguous storage of any array data, unless the dummy argument has the CONTIGUOUS attribute.

```
real :: a
call user1(a,rq)
call MPI_WAIT(rq,status,ierr)
write (*,*) a

subroutine user1(buf,request)
call MPI_IRECV(buf,...,request,...)
end
```

If a is copied, MPI\_IRECV will alter the copy when it completes the communication and will not alter a itself.

Note that copying will almost certainly occur for an argument that is a non-trivial expression (one with at least one operator or function call), a section that does not select a contiguous part of its parent (e.g., A(1:n:2)), a pointer whose target is such a section, or an assumed-shape array that is (directly or indirectly) associated with such a section.

If a compiler option exists that inhibits copying of arguments, in either the calling or called procedure, this must be employed.

If a compiler makes copies in the calling procedure of arguments that are explicit-shape or assumed-size arrays, "simply contiguous" array sections of such arrays, or scalars, and if no compiler option exists to inhibit such copying, then the compiler cannot be used for applications that use MPI\_GET\_ADDRESS, or any nonblocking MPI routine. If a compiler copies scalar arguments in the called procedure and there is no compiler option to inhibit this, then this compiler cannot be used for applications that use memory references across subroutine calls as in the example above.

## 19.1.13 Problems Due to Data Copying and Sequence Association with Vector Subscripts

Fortran arrays with **vector** subscripts describe subarrays containing a possibly irregular set of elements

```
REAL a(100)
CALL MPI_Send(A((/7,9,23,81,82/)), 5, MPI_REAL, ...)
```

Fortran arrays with a vector subscript must not be used as actual choice buffer arguments in any nonblocking or split collective MPI operations. They may, however, be used in blocking MPI operations.

## 19.1.14 Special Constants

MPI requires a number of special "constants" that cannot be implemented as normal Fortran constants, e.g., MPI\_BOTTOM. The complete list can be found in Section 2.5.4. In C, these are implemented as constant pointers, usually as NULL and are used where the function prototype calls for a pointer to a variable, not the variable itself.

In Fortran, using special values for the constants (e.g., by defining them through parameter statements) is not possible because an implementation cannot distinguish these values from valid data. Typically these constants are implemented as predefined static variables (e.g., a variable in an MPI-declared COMMON block), relying on the fact that the target

4

6

12

13

14

15 16

17

18

19

20

21

22 23

24

25

26 27

28

29

30

33

34

35

36

37 38

39

41

42 43

44

45

46

compiler passes data by address. Inside the subroutine, the address of the actual choice buffer argument can be compared with the address of such a predefined static variable.

These special constants also cause an exception with the usage of Fortran INTENT: with USE mpi\_f08, the attributes INTENT(IN), INTENT(OUT), and INTENT(INOUT) are used in the Fortran interface. In most cases, INTENT(IN) is used if the C interface uses call-by-value. For all buffer arguments and for dummy arguments that may be modified and allow one of these special constants as input, an INTENT is not specified.

## 19.1.15 Fortran Derived Types

MPI supports passing Fortran entities of BIND(C) and SEQUENCE derived types to choice dummy arguments, provided no type component has the ALLOCATABLE or POINTER attribute.

The following code fragment shows some possible ways to send scalars or arrays of interoperable derived type in Fortran. The example assumes that all data is passed by address.

```
type, BIND(C) :: mytype
   integer :: i
  real :: x
  double precision :: d
   logical :: 1
end type mytype
type(mytype) :: foo, fooarr(5)
integer :: blocklen(4), type(4)
integer(KIND=MPI_ADDRESS_KIND) :: disp(4), base, lb, extent
call MPI_GET_ADDRESS(foo%i, disp(1), ierr)
call MPI_GET_ADDRESS(foo%x, disp(2), ierr)
call MPI_GET_ADDRESS(foo%d, disp(3), ierr)
call MPI_GET_ADDRESS(foo%1, disp(4), ierr)
base = disp(1)
disp(1) = disp(1)
disp(2) = disp(2) - base
disp(3) = disp(3) - base
disp(4) = disp(4) - base
blocklen(1) = 1
blocklen(2) = 1
blocklen(3) = 1
blocklen(4) = 1
type(1) = MPI_INTEGER
type(2) = MPI_REAL
type(3) = MPI_DOUBLE_PRECISION
type(4) = MPI_LOGICAL
```

```
1
     call MPI_TYPE_CREATE_STRUCT(4, blocklen, disp, type, newtype, ierr)
2
     call MPI_TYPE_COMMIT(newtype, ierr)
3
4
     call MPI_SEND(foo%i, 1, newtype, dest, tag, comm, ierr)
5
     ! or
6
     call MPI_SEND(foo, 1, newtype, dest, tag, comm, ierr)
7
     ! expects that base == address(foo%i) == address(foo)
8
9
     call MPI_GET_ADDRESS(fooarr(1), disp(1), ierr)
10
     call MPI_GET_ADDRESS(fooarr(2), disp(2), ierr)
11
     extent = disp(2) - disp(1)
12
     1b = 0
13
     call MPI_TYPE_CREATE_RESIZED(newtype, lb, extent, newarrtype, ierr)
14
     call MPI_TYPE_COMMIT(newarrtype, ierr)
15
16
     call MPI_SEND(fooarr, 5, newarrtype, dest, tag, comm, ierr)
```

Using the derived type variable foo instead of its first basic type element foo%i may be impossible if the MPI library implements choice buffer arguments through overloading instead of using TYPE(\*), DIMENSION(..), or through a non-standardized extension such as !\$PRAGMA IGNORE\_TKR; see Section 19.1.6.

To use a derived type in an array requires a correct extent of the datatype handle to take care of the alignment rules applied by the compiler. These alignment rules may imply that there are gaps between the components of a derived type, and also between the subsuquent elements of an array of a derived type. The extent of an interoperable derived type (i.e., defined with BIND(C)) and a SEQUENCE derived type with the same content may be different because C and Fortran may apply different alignment rules. As recommended in the advice to users in Section 5.1.6, one should add an additional fifth structure element with one numerical storage unit at the end of this structure to force in most cases that the array of structures is contiguous. Even with such an additional element, one should keep this resizing due to the special alignment rules that can be used by the compiler for structures, as also mentioned in this advice.

Using the extended semantics defined in TS 29113, it is also possible to use entities or derived types without either the BIND(C) or the SEQUENCE attribute as choice buffer arguments; some additional constraints must be observed, e.g., no ALLOCATABLE or POINTER type components may exist. In this case, the base address in the example must be changed to become the address of foo instead of foo%i, because the Fortran compiler may rearrange type components or add padding. Sending the structure foo should then also be performed by providing it (and not foo%i) as actual argument for MPI\_Send.

#### 19.1.16 Optimization Problems, an Overview

MPI provides operations that may be hidden from the user code and run concurrently with it, accessing the same memory as user code. Examples include the data transfer for an MPI\_IRECV. The optimizer of a compiler will assume that it can recognize periods when a copy of a variable can be kept in a register without reloading from or storing to memory. When the user code is working with a register copy of some variable while the hidden operation reads or writes the memory copy, problems occur. These problems are

14

15 16

17

18 19

20

21222324

33

34 35

36

37

38

39

41 42

43 44

45

47

independent of the Fortran support method; i.e., they occur with the mpi\_f08 module, the mpi module, and the mpif.h include file.

This section shows four problematic usage areas (the abbrevations in parentheses are used in the table below):

- Use of nonblocking routines or persistent requests (Nonbl.).
- Use of one-sided routines (1-sided).
- Use of MPI parallel file I/O split collective operations (Split).
- Use of MPI\_BOTTOM together with absolute displacements in MPI datatypes, or relative displacements between two variables in such datatypes (Bottom).

The following compiler optimization strategies (valid for serial code) may cause problems in MPI applications:

- Code movement and register optimization problems; see Section 19.1.17.
- Temporary data movement and temporary memory modifications; see Section 19.1.18.
- Permanent data movement (e.g., through garbage collection); see Section 19.1.19.

Table 19.2 shows the only usage areas where these optimization problems may occur.

Optimization	may cause a problem in			
	following usage areas			
	Nonbl.	1-sided	Split	Bottom
Code movement	yes	yes	no	yes
and register optimization				
Temporary data movement	yes	yes	yes	no
Permanent data movement	yes	yes	yes	yes

Table 19.2: Occurrence of Fortran optimization problems in several usage areas

The solutions in the following sections are based on compromises:

- to minimize the burden for the application programmer, e.g., as shown in Sections "Solutions" through "The (Poorly Performing) Fortran VOLATILE Attribute" on pages 816–820,
- to minimize the drawbacks on compiler based optimization, and
- to minimize the requirements defined in Section 19.1.7.

## 19.1.17 Problems with Code Movement and Register Optimization

#### Nonblocking Operations

If a variable is local to a Fortran subroutine (i.e., not in a module or a COMMON block), the compiler will assume that it cannot be modified by a called subroutine unless it is an actual argument of the call. In the most common linkage convention, the subroutine is expected

**Example 19.1** Fortran 90 register optimization—extreme.

```
Source
                           compiled as
                                                       or compiled as
REAL :: buf, b1
                           REAL :: buf, b1
                                                       REAL :: buf, b1
call MPI_IRECV(buf,..req)
                           call MPI_IRECV(buf,..req)
                                                       call MPI_IRECV(buf,..reg)
                           register = buf
                                                       b1 = buf
call MPI_WAIT(req,..)
                           call MPI_WAIT(req,..)
                                                       call MPI_WAIT(req,..)
b1 = buf
                           b1 = register
```

12

13

14

15

16

17

18

1

2

4

5

6

7

8

to save and restore certain registers. Thus, the optimizer will assume that a register which held a valid copy of such a variable before the call will still hold a valid copy on return.

Example 19.1 shows extreme, but allowed, possibilities. MPI\_WAIT on a concurrent thread modifies buf between the invocation of MPI\_IRECV and the completion of MPI\_WAIT. But the compiler cannot see any possibility that buf can be changed after MPI\_IRECV has returned, and may schedule the load of buf earlier than typed in the source. The compiler has no reason to avoid using a register to hold buf across the call to MPI\_WAIT. It also may reorder the instructions as illustrated in the rightmost column.

19 20 21

22

23 24

25

26

27

28

29

30

31 32

33 34

35

36

37

38 39

40

41

42

43

44

45

Example 19.2 Similar example with MPI\_ISEND

```
with a possible MPI-internal
Source
                            compiled as
                                                        execution sequence
                            REAL :: buf, copy
REAL :: buf, copy
                                                        REAL :: buf, copy
                                                        buf = val
buf = val
                            buf = val
call MPI_ISEND(buf,..req)
                            call MPI_ISEND(buf,..req)
                                                        addr = &buf
                                                        copy = buf
copy = buf
                            copy= buf
                            buf = val_overwrite
                                                        buf = val_overwrite
                            call MPI_WAIT(req,..)
                                                        call send(*addr) ! within
call MPI_WAIT(req,..)
                                                                          ! MPI_WAIT
buf = val_overwrite
```

Due to valid compiler code movement optimizations in Example 19.2, the content of buf may already have been overwritten by the compiler when the content of buf is sent. The code movement is permitted because the compiler cannot detect a possible access to buf in MPI\_WAIT (or in a second thread between the start of MPI\_ISEND and the end of MPI\_WAIT).

Such register optimization is based on moving code; here, the access to buf was moved from after MPI\_WAIT to before MPI\_WAIT. Note that code movement may also occur across subroutine boundaries when subroutines or functions are inlined.

This register optimization/code movement problem for nonblocking operations does not occur with MPI parallel file I/O split collective operations, because in the MPI\_XXX\_BEGIN and MPI\_XXX\_END calls, the same buffer has to be provided as an actual argument. The register optimization / code movement problem for MPI\_BOTTOM and derived MPI datatypes may occur in each blocking and nonblocking communication call, as well as in each parallel file I/O operation.

46 47

13

14

15

16

17

18

19

20

21 22 23

24

26

27

28

29

30

31

33

34

35

36 37

38

39

41

42

43

44

45 46 47

#### Persistent Operations

With persistent requests, the buffer argument is hidden from the MPI\_START and MPI\_STARTALL calls, i.e., the Fortran compiler may move buffer accesses across the MPI\_START or MPI\_STARTALL call, similar to the MPI\_WAIT call as described in the Nonblocking Operations subsection in Section 19.1.17.

#### One-sided Communication

An example with instruction reordering due to register optimization can be found in Section 12.7.4.

## MPI\_BOTTOM and Combining Independent Variables in Datatypes

This section is only relevant if the MPI program uses a buffer argument to an MPI\_SEND, MPI\_RECV, etc., that hides the actual variables involved in the communication. MPI\_BOTTOM with an MPI\_Datatype containing absolute addresses is one example. Creating a datatype which uses one variable as an anchor and brings along others by using MPI\_GET\_ADDRESS to determine their offsets from the anchor is another. The anchor variable would be the only one referenced in the call. Also attention must be paid if MPI operations are used that run in parallel with the user's application.

Example 19.3 shows what Fortran compilers are allowed to do.

## Example 19.3 Fortran 90 register optimization.

```
This source ...
                                          can be compiled as:
call MPI_GET_ADDRESS(buf,bufaddr,
                                          call MPI_GET_ADDRESS(buf,...)
               ierror)
call MPI_TYPE_CREATE_STRUCT(1,1,
                                          call MPI_TYPE_CREATE_STRUCT(...)
               bufaddr,
               MPI_REAL, type, ierror)
call MPI_TYPE_COMMIT(type,ierror)
                                          call MPI_TYPE_COMMIT(...)
val_old = buf
                                          register = buf
                                          val_old = register
call MPI_RECV(MPI_BOTTOM,1,type,...)
                                          call MPI_RECV(MPI_BOTTOM,...)
val_new = buf
                                          val_new = register
```

In Example 19.3, the compiler does not invalidate the register because it cannot see that MPI\_RECV changes the value of buf. The access to buf is hidden by the use of MPI\_GET\_ADDRESS and MPI\_BOTTOM.

In Example 19.4, several successive assignments to the same variable buf can be combined in a way such that only the last assignment is executed. "Successive" means that no interfering load access to this variable occurs between the assignments. The compiler cannot detect that the call to MPI\_SEND statement is interfering because the load access to buf is hidden by the usage of MPI\_BOTTOM.

## Example 19.4 Similar example with MPI\_SEND

```
This source ...

! buf contains val_old

buf = val_new

call MPI_SEND(MPI_BOTTOM,1,type,...)
! with buf as a displacement in type

! buf=val_new is moved to here
! and detected as dead code
! and therefore removed
!

buf = val_overwrite

buf = val_overwrite
```

#### Solutions

The following sections show in detail how the problems with code movement and register optimization can be portably solved. Application writers can partially or fully avoid these compiler optimization problems by using one or more of the special Fortran declarations with the send and receive buffers used in nonblocking operations, or in operations in which MPI\_BOTTOM is used, or if datatype handles that combine several variables are used:

- Use of the Fortran ASYNCHRONOUS attribute.
- Use of the helper routine MPI\_F\_SYNC\_REG, or an equivalent user-written dummy routine.
- Declare the buffer as a Fortran module variable or within a Fortran common block.
- Use of the Fortran VOLATILE attribute.

Each of these methods solves the problems of code movement and register optimization, but may incur various degrees of performance impact, and may not be usable in every application context. These methods may not be guaranteed by the Fortran standard, but they must be guaranteed by a MPI-3.0 (and later) compliant MPI library and associated compiler suite according to the requirements listed in Section 19.1.7. The performance impact of using MPI\_F\_SYNC\_REG is expected to be low, that of using module variables or the ASYNCHRONOUS attribute is expected to be low to medium, and that of using the VOLATILE attribute is expected to be high or very high. Note that there is one attribute that cannot be used for this purpose: the Fortran TARGET attribute does not solve code movement problems in MPI applications.

#### The Fortran ASYNCHRONOUS Attribute

Declaring an actual buffer argument with the ASYNCHRONOUS Fortran attribute in a scoping unit (or BLOCK) informs the compiler that any statement in the scoping unit may be executed while the buffer is affected by a pending asynchronous Fortran input/output operation (since Fortran 2003) or by an asynchronous communication (TS 29113 extension). Without the extensions specified in TS 29113, a Fortran compiler may totally ignore this attribute if the

Fortran compiler implements asynchronous Fortran input/output operations with blocking I/O. The ASYNCHRONOUS attribute protects the buffer accesses from optimizations through code movements across routine calls, and the buffer itself from temporary and permanent data movements. If the choice buffer dummy argument of a nonblocking MPI routine is declared with ASYNCHRONOUS (which is mandatory for the mpi\_f08 module, with allowable exceptions listed in Section 19.1.6), then the compiler has to guarantee call by reference and should report a compile-time error if call by reference is impossible, e.g., if vector subscripts are used. The MPI\_ASYNC\_PROTECTS\_NONBLOCKING is set to .TRUE. if both the protection of the actual buffer argument through ASYNCHRONOUS according to the TS 29113 extension and the declaration of the dummy argument with ASYNCHRONOUS in the Fortran support method is guaranteed for all nonblocking routines, otherwise it is set to .FALSE..

The ASYNCHRONOUS attribute has some restrictions. Section 5.4.2 of the TS 29113 specifies:

"Asynchronous communication for a Fortran variable occurs through the action of procedures defined by means other than Fortran. It is initiated by execution of an asynchronous communication initiation procedure and completed by execution of an asynchronous communication completion procedure. Between the execution of the initiation and completion procedures, any variable of which any part is associated with any part of the asynchronous communication variable is a pending communication affector. Whether a procedure is an asynchronous communication initiation or completion procedure is processor dependent.

Asynchronous communication is either input communication or output communication. For input communication, a pending communication affector shall not be referenced, become defined, become undefined, become associated with a dummy argument that has the VALUE attribute, or have its pointer association status changed. For output communication, a pending communication affector shall not be redefined, become undefined, or have its pointer association status changed."

In Example 19.5 Case (a) on page 823, the read accesses to b within function(b(i-1), b(i), b(i+1)) cannot be moved by compiler optimizations to before the wait call because b was declared as ASYNCHRONOUS. Note that only the elements 0, 1, 100, and 101 of b are involved in asynchronous communication but by definition, the total variable b is the pending communication affector and is usable for input and output asynchronous communication between the MPI\_IXXX routines and MPI\_Waitall. Case (a) works fine because the read accesses to b occur after the communication has completed.

In Case (b), the read accesses to b(1:100) in the loop i=2,99 are read accesses to a pending communication affector while input communication (i.e., the two MPI\_Irecv calls) is pending. This is a contradiction to the rule that for input communication, a pending communication affector shall not be referenced. The problem can be solved by using separate variables for the halos and the inner array, or by splitting a common array into disjoint subarrays which are passed through different dummy arguments into a subroutine, as shown in Example 19.9.

If one does not overlap communication and computation on the same variable, then all optimization problems can be solved through the ASYNCHRONOUS attribute.

The problems with MPI\_BOTTOM, as shown in Example 19.3 and Example 19.4, can also be solved by declaring the buffer buf with the ASYNCHRONOUS attribute.

In some MPI routines, a buffer dummy argument is defined as ASYNCHRONOUS to guarantee passing by reference, provided that the actual argument is also defined as ASYNCHRONOUS.

Calling MPI\_F\_SYNC\_REG

The compiler may be prevented from moving a reference to a buffer across a call to an MPI subroutine by surrounding the call by calls to an external subroutine with the buffer as an actual argument. The MPI library provides the MPI\_F\_SYNC\_REG routine for this purpose; see Section 19.1.8.

• The problems illustrated by the Examples 19.1 and 19.2 can be solved by calling MPI\_F\_SYNC\_REG(buf) once immediately after MPI\_WAIT.

```
Example 19.1 Example 19.2

can be solved with

call MPI_IRECV(buf,..req) buf = val

call MPI_ISEND(buf,..req)

call MPI_WAIT(req,..)

call MPI_WAIT(req,..)

call MPI_F_SYNC_REG(buf)

b1 = buf

Example 19.2

can be solved with

buf = val

call MPI_ISEND(buf,..req)

call MPI_ISEND(buf,..req)

call MPI_F_SYNC_REG(buf)

buf = val_overwrite
```

The call to MPI\_F\_SYNC\_REG(buf) prevents moving the last line before the MPI\_WAIT call. Further calls to MPI\_F\_SYNC\_REG(buf) are not needed because it is still correct if the additional read access copy=buf is moved below MPI\_WAIT and before buf=val\_overwrite.

• The problems illustrated by the Examples 19.3 and 19.4 can be solved with two additional MPI\_F\_SYNC\_REG(buf) statements; one directly before MPI\_RECV/MPI\_SEND, and one directly after this communication operation.

```
Example 19.3 Example 19.4 can be solved with call MPI_F_SYNC_REG(buf) call MPI_RECV(MPI_BOTTOM,...) call MPI_F_SYNC_REG(buf) call MPI_F_SYNC_REG(buf) call MPI_F_SYNC_REG(buf)
```

The first call to MPI\_F\_SYNC\_REG(buf) is needed to finish all load and store references to buf prior to MPI\_RECV/MPI\_SEND; the second call is needed to assure that any subsequent access to buf is not moved before MPI\_RECV/MPI\_SEND.

• In the example in Section 12.7.4, two asynchronous accesses must be protected: in Process 1, the access to bbbb must be protected similar to Example 19.1, i.e., a call to MPI\_F\_SYNC\_REG(bbbb) is needed after the second MPI\_WIN\_FENCE to guarantee that further accesses to bbbb are not moved ahead of the call to MPI\_WIN\_FENCE. In Process 2, both calls to MPI\_WIN\_FENCE together act as a communication call with MPI\_BOTTOM as the buffer. That is, before the first fence and after the second fence, a call to MPI\_F\_SYNC\_REG(buff) is needed to guarantee that accesses to buff are not moved after or ahead of the calls to MPI\_WIN\_FENCE. Using MPI\_GET instead of MPI\_PUT, the same calls to MPI\_F\_SYNC\_REG are necessary.

 $\frac{23}{24}$ 

```
Source of Process 1

bbbb = 777

buff = 999

call MPI_F_SYNC_REG(buff)

call MPI_PUT(bbbb

into buff of process 2)

call MPI_WIN_FENCE

call MPI_WIN_FENCE

call MPI_WIN_FENCE

call MPI_WIN_FENCE

call MPI_F_SYNC_REG(bbbb)

ccc = buff
```

• The temporary memory modification problem, i.e., Example 19.6, can **not** be solved with this method.

## A User Defined Routine Instead of MPI\_F\_SYNC\_REG

Instead of MPI\_F\_SYNC\_REG, one can also use a user defined external subroutine, which is separately compiled:

```
subroutine DD(buf)
integer buf
end
```

Note that if the INTENT is declared in an explicit interface for the external subroutine, it must be OUT or INOUT. The subroutine itself may have an empty body, but the compiler does not know this and has to assume that the buffer may be altered. For example, a call to MPI\_RECV with MPI\_BOTTOM as buffer might be replaced by

```
call DD(buf)
call MPI_RECV(MPI_BOTTOM,...)
call DD(buf)
```

Such a user-defined routine was introduced in MPI-2.0 and is still included here to document such usage in existing application programs although new applications should prefer MPI\_F\_SYNC\_REG or one of the other possibilities. In an existing application, calls to such a user-written routine should be substituted by a call to MPI\_F\_SYNC\_REG because the user-written routine may not be implemented in accordance with the rules specified in Section 19.1.7.

## Module Variables and COMMON Blocks

An alternative to the previously mentioned methods is to put the buffer or variable into a module or a common block and access it through a USE or COMMON statement in each scope where it is referenced, defined or appears as an actual argument in a call to an MPI routine. The compiler will then have to assume that the MPI procedure may alter the buffer or variable, provided that the compiler cannot infer that the MPI procedure does not reference the module or common block.

• This method solves problems of instruction reordering, code movement, and register optimization related to nonblocking and one-sided communication, or related to the usage of MPI\_BOTTOM and derived datatype handles.

5

6

7

9

10

11

12 13

14 15

16

17

18

1

2

• Unfortunately, this method does **not** solve problems caused by asynchronous accesses between the start and end of a nonblocking or one-sided communication. Specifically, problems caused by temporary memory modifications are not solved.

The (Poorly Performing) Fortran VOLATILE Attribute

The VOLATILE attribute gives the buffer or variable the properties needed to avoid register optimization or code movement problems, but it may inhibit optimization of any code containing references or definitions of the buffer or variable. On many modern systems, the performance impact will be large because not only register, but also cache optimizations will not be applied. Therefore, use of the VOLATILE attribute to enforce correct execution of MPI programs is discouraged.

The Fortran TARGET Attribute

The TARGET attribute does not solve the code movement problem because it is not specified for the choice buffer dummy arguments of nonblocking routines. If the compiler detects that the application program specifies the TARGET attribute for an actual buffer argument used in the call to a nonblocking routine, the compiler may ignore this attribute if no pointer reference to this buffer exists.

19 20 21

22

The Fortran standardization body decided to extend the ASYNCHRONOUS attribute within the TS 29113 to protect buffers in nonblocking calls from all kinds of optimization, instead of extending the TARGET attribute. (End of rationale.)

23 24 25

26

27

28

29

30

31

32

33

34

35

36

37

38

39

40

41

42

43 44

45

46 47

#### 19.1.18 Temporary Data Movement and Temporary Memory Modification

The compiler is allowed to temporarily modify data in memory. Normally, this problem may occur only when overlapping communication and computation, as in Example 19.5, Case (b) on page 823. Example 19.6 also shows a possibility that could be problematic.

In the compiler-generated, possible optimization in Example 19.7, buf(100,100) from Example 19.6 is equivalenced with the 1-dimensional array buf\_1dim(10000). The nonblocking receive may asynchronously receive the data in the boundary buf(1,1:100) while the fused loop is temporarily using this part of the buffer. When the tmp data is written back to buf, the previous data of buf(1,1:100) is restored and the received data is lost. The principle behind this optimization is that the receive buffer data buf(1,1:100) was temporarily moved to tmp.

Example 19.8 shows a second possible optimization. The whole array is temporarily moved to local\_buf.

When storing local\_buf back to the original location buf, then this implies overwriting the section of buf that serves as a receive buffer in the nonblocking MPI call, i.e., this storing back of local\_buf is therefore likely to interfere with asynchronously received data in buf(1,1:100).

Note that this problem may also occur:

- With the local buffer at the origin process, between an RMA communication call and the ensuing synchronization call; see Chapter 12.
- With the window buffer at the target process between two ensuing RMA synchronization calls.

 With the local buffer in MPI parallel file I/O split collective operations between the MPI\_XXX\_BEGIN and MPI\_XXX\_END calls; see Section 14.4.5.

As already mentioned in subsection *The Fortran ASYNCHRONOUS attribute* on page 816 of Section 19.1.17, the ASYNCHRONOUS attribute can prevent compiler optimization with temporary data movement, but only if the receive buffer and the local references are separated into different variables, as shown in Example 19.9 and in Example 19.10.

Note also that the methods

- calling MPI\_F\_SYNC\_REG (or such a user-defined routine),
- using module variables and COMMON blocks, and
- the TARGET attribute

cannot be used to prevent such temporary data movement. These methods influence compiler optimization when library routines are called. They cannot prevent the optimizations of the code fragments shown in Example 19.6 and 19.7.

Note also that compiler optimization with temporary data movement should **not** be prevented by declaring buf as VOLATILE because the VOLATILE implies that all accesses to any storage unit (word) of buf must be directly done in the main memory exactly in the sequence defined by the application program. The VOLATILE attribute prevents all register and cache optimizations. Therefore, VOLATILE may cause a huge performance degradation.

Instead of solving the problem, it is better to **prevent** the problem: when overlapping communication and computation, the nonblocking communication (or nonblocking or split collective I/O) and the computation should be executed **on different variables**, and the communication should be *protected* with the ASYNCHRONOUS attribute. In this case, the temporary memory modifications are done only on the variables used in the computation and cannot have any side effect on the data used in the nonblocking MPI operations.

Rationale. This is a strong restriction for application programs. To weaken this restriction, a new or modified asynchronous feature in the Fortran language would be necessary: an asynchronous attribute that can be used on parts of an array and together with asynchronous operations outside the scope of Fortran. If such a feature becomes available in a future edition of the Fortran standard, then this restriction also may be weakened in a later version of the MPI standard. (End of rationale.)

In Example 19.9 (which is a solution for the problem shown in Example 19.5 and in Example 19.10 (which is a solution for the problem shown in Example 19.8), the array is split into inner and halo part and both disjoint parts are passed to a subroutine separated\_sections. This routine overlaps the receiving of the halo data and the calculations on the inner part of the array. In a second step, the whole array is used to do the calculation on the elements where inner+halo is needed. Note that the halo and the inner area are strided arrays. Those can be used in nonblocking communication only with a TS 29113 based MPI library.

#### 19.1.19 Permanent Data Movement

A Fortran compiler may implement permanent data movement during the execution of a Fortran program. This would require that pointers to such data are appropriately updated. An implementation with automatic garbage collection is one use case. Such permanent data movement is in conflict with MPI in several areas:

- MPI datatype handles with absolute addresses in combination with MPI\_BOTTOM.
- All nonblocking MPI operations if the internally used pointers to the buffers are not
- updated by the Fortran runtime, or if within an MPI process, the data movement is executed in parallel with the MPI operation.

see Section 19.1.7.

operation is pending.

Comparison with C

- This problem can be also solved by using the ASYNCHRONOUS attribute for such buffers.
- This MPI standard requires that the problems with permanent data movement do not

19.1.20

**Unofficial Draft for Comment Only** 

occur by imposing suitable restrictions on the MPI library together with the compiler used;

In C, subroutines which modify variables that are not in the argument list will not cause

register optimization problems. This is because taking pointers to storage objects by using

the & operator and later referencing the objects by indirection on the pointer is an integral

part of the language. A C compiler understands the implications, so that the problem should

not occur, in general. However, some compilers do offer optional aggressive optimization

levels which may not be safe. Problems due to temporary memory modifications can also

occur in C. As above, the best advice is to avoid the problem: use different variables for

buffers in nonblocking MPI operations and computation that is executed while a nonblocking

13

14 15

16

18

19

20

24

26

27

28

29

33

42

43

44

45

46

```
USE mpi_f08
REAL, ASYNCHRONOUS :: b(0:101) ! elements 0 and 101 are halo cells
                               ! elements 1 and 100 are newly computed
REAL :: bnew(0:101)
TYPE(MPI_Request) :: req(4)
INTEGER :: left, right, i
CALL MPI_Cart_shift(...,left,right,...)
CALL MPI_Irecv(b( 0), ..., left, ..., req(1), ...)
CALL MPI_Irecv(b(101), ..., right, ..., req(2), ...)
CALL MPI_Isend(b( 1), ..., left, ..., req(3), ...)
CALL MPI_Isend(b(100), ..., right, ..., req(4), ...)
#ifdef WITHOUT_OVERLAPPING_COMMUNICATION_AND_COMPUTATION
! Case (a)
  CALL MPI_Waitall(4, req, ...)
  DO i=1,100 ! compute all new local data
    bnew(i) = function(b(i-1), b(i), b(i+1))
  END DO
                                                                                 21
#endif
                                                                                 22
                                                                                 23
#ifdef WITH_OVERLAPPING_COMMUNICATION_AND_COMPUTATION
! Case (b)
  DO i=2,99 ! compute only elements for which halo data is not needed
    bnew(i) = function(b(i-1), b(i), b(i+1))
  END DO
  CALL MPI_Waital1(4, req, ...)
  i=1 ! compute leftmost element
                                                                                 30
    bnew(i) = function(b(i-1), b(i), b(i+1))
  i=100 ! compute rightmost element
    bnew(i) = function(b(i-1), b(i), b(i+1))
#endif
                                                                                 34
                                                                                 35
                                                                                 36
Example 19.6 Overlapping Communication and Computation.
                                                                                 37
USE mpi_f08
REAL :: buf(100,100)
CALL MPI_Irecv(buf(1,1:100),..., req,...)
DO j=1,100
  D0 i=2,100
    buf(i,j)=...
  END DO
END DO
CALL MPI_Wait(req,...)
```

Example 19.5 Protecting nonblocking communication with the ASYNCHRONOUS attribute.

```
Example 19.7 The compiler may substitute the nested loops through loop fusion.
```

```
REAL :: buf(100,100), buf_1dim(10000)

EQUIVALENCE (buf(1,1), buf_1dim(1))

CALL MPI_Irecv(buf(1,1:100),..., req,...)

tmp(1:100) = buf(1,1:100)

D0 j=1,10000

buf_1dim(h)=...

END D0

buf(1,1:100) = tmp(1:100)

CALL MPI_Wait(req,...)
```

**Example 19.8** Another optimization is based on the usage of a separate memory storage area, e.g., in a GPU.

13

14 15

16

17

19

20

21

22

23

24

26

27

28 29

30

33

34

35

36 37

**Example 19.9** Using separated variables for overlapping communication and computation to allow the protection of nonblocking communication with the ASYNCHRONOUS attribute.

```
USE mpi_f08
REAL :: b(0:101)
                     ! elements 0 and 101 are halo cells
REAL :: bnew(0:101) ! elements 1 and 100 are newly computed
INTEGER :: i
CALL separated_sections(b(0), b(1:100), b(101), bnew(0:101))
i=1 ! compute leftmost element
  bnew(i) = function(b(i-1), b(i), b(i+1))
i=100 ! compute rightmost element
  bnew(i) = function(b(i-1), b(i), b(i+1))
END
SUBROUTINE separated_sections(b_lefthalo, b_inner, b_righthalo, bnew)
USE mpi_f08
REAL, ASYNCHRONOUS :: b_lefthalo(0:0), b_inner(1:100), b_righthalo(101:101)
REAL :: bnew(0:101) ! elements 1 and 100 are newly computed
TYPE(MPI_Request) :: req(4)
INTEGER :: left, right, i
CALL MPI_Cart_shift(...,left, right,...)
CALL MPI_Irecv(b_lefthalo ( 0), ..., left, ..., req(1), ...)
CALL MPI_Irecv(b_righthalo(101), ..., right, ..., req(2), ...)
! b_lefthalo and b_righthalo is written asynchronously.
! There is no other concurrent access to b_lefthalo and b_righthalo.
CALL MPI_Isend(b_inner( 1),
                                 \ldots, left, \ldots, req(3), \ldots)
CALL MPI_Isend(b_inner(100),
                                  \ldots, right, \ldots, req(4), \ldots)
DO i=2,99 ! compute only elements for which halo data is not needed
  bnew(i) = function(b_inner(i-1), b_inner(i), b_inner(i+1))
  ! b_inner is read and sent at the same time.
  ! This is allowed based on the rules for ASYNCHRONOUS.
END DO
CALL MPI_Waitall(4, req,...)
END SUBROUTINE
```

```
1
     Example 19.10 Protecting GPU optimizations with the ASYNCHRONOUS attribute.
2
3
     USE mpi_f08
4
     REAL :: buf(100,100)
5
     CALL separated_sections(buf(1:1,1:100), buf(2:100,1:100))
6
     END
7
8
     SUBROUTINE separated_sections(buf_halo, buf_inner)
     REAL, ASYNCHRONOUS :: buf_halo(1:1,1:100)
10
     REAL :: buf_inner(2:100,1:100)
11
     REAL :: local_buf(2:100,100)
12
13
     CALL MPI_Irecv(buf_halo(1,1:100),..., req,...)
14
     local_buf = buf_inner
15
     DO j=1,100
16
       D0 i=2,100
17
         local_buf(i,j)=...
18
       END DO
19
     END DO
20
     buf_inner = local_buf ! buf_halo is not touched!!!
21
22
     CALL MPI_Wait(req,...)
23
24
26
27
28
29
30
31
32
33
34
35
36
37
41
42
43
44
45
46
```

13

14 15

16

17

18

19

20

21

22

23 24

#### 19.2 Support for Large Count and Large Byte Displacement in MPI Language Bindings

The following types, which were used prior to MPI-4.0, have been deemed too small to hold values that applications wish to use:

- The C int type and the Fortran INTEGER type were used for *count* parameters.
- The C int type and the Fortran INTEGER type were used for some parameters that represent byte displacement in memory.
- The C MPI\_Aint type and the Fortran INTEGER(KIND=MPI\_ADDRESS\_KIND) type were used for some parameters that represent byte displacement in files (e.g., in constructors of MPI datatypes that can be used with files).

In order to avoid breaking backwards compatibility, this version of MPI supports larger types via separate additional MPI procedures in C (suffixed with "\_c") and via interface polymorphism in Fortran when using USE mpi\_f08. No polymorphic support for larger types is provided in Fortran when using mpif.h and use mpi.

For the large count versions of three datatype constructors, MPI\_TYPE\_CREATE\_HINDEXED, MPI\_TYPE\_CREATE\_HINDEXED\_BLOCK, and MPI\_TYPE\_CREATE\_STRUCT, absolute addresses shall not be used to specify byte displacements since the parameter is of type MPI\_COUNT instead of type MPI\_AINT (see Section 2.5.8).

In addition, the functions MPI\_TYPE\_GET\_ENVELOPE and MPI\_TYPE\_GET\_CONTENTS also support large count types via additional parameters in separate additional MPI procedures in C (suffixed with "\_c") and interface polymorphism in Fortran when using USE mpi\_f08 (see Section 5.1.13). of type MPI\_User\_function and MPI\_Datarep\_

Further, the callbacks MPI\_USER\_FUNCTION and MPI\_DATAREP\_CONVERSION\_FUNCTION also support large count types via separate additional callback prototypes in C (suffixed with "\_c") and multiple abstract interfaces in Fortran when using USE mpi\_f08 (see Sections 6.9.5 and 14.5.3, respectively).

In C bindings, for each MPI procedure that had at least one count or byte displacement parameter that used the int and/or MPI\_Aint types prior to MPI-4.0, an additional MPI procedure is provided, with the same name but suffixed by "\_c". The MPI procedure without the "\_c" token has the same name and parameter types as versions prior to MPI-4.0. The "\_c" suffixed MPI procedure has MPI\_Count for all count parameters, MPI\_Aint for parameters that represent byte displacement in memory, MPI\_Offset for parameters that represent byte displacement in files, and MPI\_Count for parameters that may represent byte displacement in both memory and files.

In Fortran, when using USE mpi\_f08, for each MPI procedure that had at least one count or byte displacement parameter that used the INTEGER or INTEGER (KIND=MPI\_ADDRESS\_KIND) types prior to MPI-4.0, a polymorphic interface containing two specific procedures is provided. One of the specific procedures has the same name and dummy parameter types as in versions prior to MPI-4.0. INTEGER and/or INTEGER (KIND=MPI\_ADDRESS\_KIND) for count and byte displacement parameters. The other specific procedure has the same name followed by "\_c", and then suffixed by the token specified in Table 19.1 for USE mpi\_f08. It also has INTEGER(KIND=MPI\_COUNT\_KIND) for all count parameters, INTEGER(KIND=MPI\_ADDRESS\_KIND) for parameters that represent byte displacement in memory, INTEGER(KIND=MPI\_OFFSET\_KIND) for parameters that

#-other 29 This is a callback prototype, use correct macro! 33 Done

lin

PR449

34

35

36 37

38

42

43 44

4546

47

#-error!

Unofficial Draft for Comment Only

represent byte displacement in files, and INTEGER(KIND=MPI\_COUNT\_KIND) for parameters that may represent byte displacement in both memory and files (for more details on specific Fortran procedure names and related calling conventions, refer to Table 19.1 in Section 19.1.5). There is one exception: if the type signatures of the two specific procedures are identical (e.g., if INTEGER(KIND=MPI\_COUNT\_KIND) is the same type as INTEGER(KIND=MPI\_ADDRESS\_KIND)), then the implementation shall not provide the "\_c" specific procedure.

It is erroneous to directly invoke the "\_c" specific procedures in the Fortran mpi\_f08 module with the exception of the following procedures: MPI\_Op\_create\_c and MPI\_Register\_datarep\_c.

In older Fortran bindings (mpif.h and use mpi), no new interfaces and no new specific procedures for larger types are provided beyond what existed in MPI-4.0; all MPI procedures have the same types as in the versions prior to MPI-4.0.

# 19.3 Language Interoperability

## 19.3.1 Introduction

It is not uncommon for library developers to use one language to develop an application library that may be called by an application program written in a different language. MPI currently supports ISO (previously ANSI) C and Fortran bindings. It should be possible for applications in any of the supported languages to call MPI-related functions in another language.

Moreover, MPI allows the development of client-server code, with MPI communication used between a parallel client and a parallel server. It should be possible to code the server in one language and the clients in another language. To do so, communications should be possible between applications written in different languages.

There are several issues that need to be addressed in order to achieve interoperability.

**Initialization** We need to specify how the MPI environment is initialized for all languages.

Interlanguage passing of MPI opaque objects We need to specify how MPI object handles are passed between languages. We also need to specify what happens when an MPI object is accessed in one language, to retrieve information (e.g., attributes) set in another language.

Interlanguage communication We need to specify how messages sent in one language can be received in another language.

It is highly desirable that the solution for interlanguage interoperability be extensible to new languages, should MPI bindings be defined for such languages.

## 19.3.2 Assumptions

We assume that conventions exist for programs written in one language to call routines written in another language. These conventions specify how to link routines in different languages into one program, how to call functions in a different language, how to pass arguments between languages, and the correspondence between basic data types in different languages. In general, these conventions will be implementation dependent. Furthermore, not every basic datatype may have a matching type in other languages. For example,

C character strings may not be compatible with Fortran CHARACTER variables. However, we assume that a Fortran INTEGER, as well as a (sequence associated) Fortran array of INTEGERs, can be passed to a C program. We also assume that Fortran and C have address-sized integers. This does not mean that the default-size integers are the same size as default-sized pointers, but only that there is some way to hold (and pass) a C address in a Fortran integer. It is also assumed that INTEGER(KIND=MPI\_OFFSET\_KIND) can be passed from Fortran to C as MPI\_Offset.

#### 19.3.3 Initialization

A call to MPI\_INIT or MPI\_INIT\_THREAD, from any language, initializes MPI for execution in all languages.

Advice to users. Certain implementations use the (inout) argc, argv arguments of the C version of MPI\_INIT in order to propagate values for argc and argv to all executing processes. Use of the Fortran version of MPI\_INIT to initialize MPI may result in a loss of this ability. (End of advice to users.)

The function MPI\_INITIALIZED returns the same answer in all languages.

The function MPI\_FINALIZE finalizes the MPI environments for all languages.

The function MPI\_FINALIZED returns the same answer in all languages.

The function MPI\_ABORT kills processes, irrespective of the language used by the caller or by the processes killed.

The MPI environment is initialized in the same manner for all languages by MPI\_INIT. E.g., MPI\_COMM\_WORLD carries the same information regardless of language: same processes, same environmental attributes, same error handlers.

Information can be added to info objects in one language and retrieved in another.

Advice to users. The use of several languages in one MPI program may require the use of special options at compile and/or link time. (End of advice to users.)

Advice to implementors. Implementations may selectively link language specific MPI libraries only to codes that need them, so as not to increase the size of binaries for codes that use only one language. The MPI initialization code need perform initialization for a language only if that language library is loaded. (End of advice to implementors.)

#### 19.3.4 Transfer of Handles

Handles are passed between Fortran and C by using an explicit C wrapper to convert Fortran handles to C handles. There is no direct access to C handles in Fortran.

The type definition MPI\_Fint is provided in C for an integer of the size that matches a Fortran INTEGER; usually, MPI\_Fint will be equivalent to int. With the Fortran mpi module or the mpif.h include file, a Fortran handle is a Fortran INTEGER value that can be used in the following conversion functions. With the Fortran mpi\_f08 module, a Fortran handle is a BIND(C) derived type that contains an INTEGER component named MPI\_VAL. This INTEGER value can be used in the following conversion functions.

The following functions are provided in C to convert from a Fortran communicator handle (which is an integer) to a C communicator handle, and vice versa. See also Section 2.6.4.

```
C binding
2
     MPI_Comm MPI_Comm_f2c(MPI_Fint comm)
         If comm is a valid Fortran handle to a communicator, then MPI_Comm_f2c returns a
4
     valid C handle to that same communicator; if comm = MPI_COMM_NULL (Fortran value),
5
     then MPI_Comm_f2c returns a null C handle; if comm is an invalid Fortran handle, then
6
     MPI_Comm_f2c returns an invalid C handle.
     MPI_Fint MPI_Comm_c2f(MPI_Comm comm)
9
         The function MPI_Comm_c2f translates a C communicator handle into a Fortran handle
10
     to the same communicator; it maps a null handle into a null handle and an invalid handle
11
     into an invalid handle.
12
         Similar functions are provided for the other types of opaque objects.
13
     MPI_Datatype MPI_Type_f2c(MPI_Fint datatype)
14
     MPI_Fint MPI_Type_c2f(MPI_Datatype datatype)
15
16
     MPI_Group_f2c(MPI_Fint group)
17
     MPI_Fint MPI_Group_c2f(MPI_Group group)
18
19
     MPI_Request MPI_Request_f2c(MPI_Fint request)
20
     MPI_Fint MPI_Request_c2f(MPI_Request request)
21
22
     MPI_File MPI_File_f2c(MPI_Fint file)
23
     MPI_Fint MPI_File_c2f(MPI_File file)
^{24}
25
     MPI_Win MPI_Win_f2c(MPI_Fint win)
26
     MPI_Fint MPI_Win_c2f(MPI_Win win)
27
28
     MPI_Op MPI_Op_f2c(MPI_Fint op)
29
     MPI_Fint MPI_Op_c2f(MPI_Op op)
30
31
     MPI_Info MPI_Info_f2c(MPI_Fint info)
32
33
     MPI_Fint MPI_Info_c2f(MPI_Info info)
34
     MPI_Errhandler MPI_Errhandler_f2c(MPI_Fint errhandler)
35
36
     MPI_Fint MPI_Errhandler_c2f(MPI_Errhandler errhandler)
37
     MPI_Message MPI_Message_f2c(MPI_Fint message)
38
39
     MPI_Fint MPI_Message_c2f(MPI_Message message)
40
     MPI_Session MPI_Session_f2c(MPI_Fint session)
41
42
     MPI_Fint MPI_Session_c2f(MPI_Session session)
43
```

**Example 19.11** The example below illustrates how the Fortran MPI function MPI\_TYPE\_COMMIT can be implemented by wrapping the C MPI function MPI\_Type\_commit with a C wrapper to do handle conversions. In this example a Fortran-C interface is assumed where a Fortran function is all upper case when referred to from C and arguments are passed by addresses.

```
! FORTRAN PROCEDURE
SUBROUTINE MPI_TYPE_COMMIT(DATATYPE, IERR)
INTEGER :: DATATYPE, IERR
CALL MPI_X_TYPE_COMMIT(DATATYPE, IERR)
RETURN
END

/* C wrapper */

void MPI_X_TYPE_COMMIT(MPI_Fint *f_handle, MPI_Fint *ierr)
{
    MPI_Datatype datatype;

    datatype = MPI_Type_f2c(*f_handle);
    *ierr = (MPI_Fint)MPI_Type_commit(&datatype);
    *f_handle = MPI_Type_c2f(datatype);
    return;
}
```

The same approach can be used for all other MPI functions. The call to  $MPI_XXX_f2c$  (resp.  $MPI_XXX_c2f$ ) can be omitted when the handle is an OUT (resp. IN) argument, rather than INOUT.

Rationale. The design here provides a convenient solution for the prevalent case, where a C wrapper is used to allow Fortran code to call a C library, or C code to call a Fortran library. The use of C wrappers is much more likely than the use of Fortran wrappers, because it is much more likely that a variable of type INTEGER can be passed to C, than a C handle can be passed to Fortran.

Returning the converted value as a function value rather than through the argument list allows the generation of efficient inlined code when these functions are simple (e.g., the identity). The conversion function in the wrapper does not catch an invalid handle argument. Instead, an invalid handle is passed below to the library function, which, presumably, checks its input arguments. (*End of rationale*.)

#### 19.3.5 Status

The following two procedures are provided in C to convert from a Fortran (with the mpi module or mpif.h) status (which is an array of integers) to a C status (which is a structure), and vice versa. The conversion occurs on all the information in status, including that which is hidden. That is, no status information is lost in the conversion.

```
int MPI_Status_f2c(const MPI_Fint *f_status, MPI_Status *c_status)
```

If f\_status is a valid Fortran status, but not the Fortran value of MPI\_STATUS\_IGNORE or MPI\_STATUSES\_IGNORE, then MPI\_Status\_f2c returns in c\_status a valid C status with the same content. If f\_status is the Fortran value of MPI\_STATUS\_IGNORE or MPI\_STATUSES\_IGNORE, or if f\_status is not a valid Fortran status, then the call is erroneous.

In C, such an f\_status array can be defined with MPI\_Fint f\_status[MPI\_F\_STATUS\_SIZE]. Within this array, one can use in C the indexes MPI\_F\_SOURCE, MPI\_F\_TAG, and MPI\_F\_ERROR, to access the same elements as in Fortran with MPI\_SOURCE, MPI\_TAG and MPI\_ERROR. The C indexes are 1 less than the corresponding indexes in Fortran due to the different default array start indexes in both languages.

The C status has the same source, tag and error code values as the Fortran status, and returns the same answers when queried for count, elements, and cancellation. The conversion function may be called with a Fortran status argument that has an undefined error field, in which case the value of the error field in the C status argument is undefined.

Two global variables of type MPI\_Fint\*, MPI\_F\_STATUS\_IGNORE and MPI\_F\_STATUSES\_IGNORE are declared in mpi.h. They can be used to test, in C, whether f\_status is the Fortran value of MPI\_STATUS\_IGNORE or MPI\_STATUSES\_IGNORE defined in the mpi module or mpif.h. These are global variables, not C constant expressions and cannot be used in places where C requires constant expressions. Their value is defined only between the calls to MPI\_INIT and MPI\_FINALIZE and should not be changed by user code.

To do the conversion in the other direction, we have the following:

```
int MPI_Status_c2f(const MPI_Status *c_status, MPI_Fint *f_status)
```


This call converts a C status into a Fortran status, and has a behavior similar to MPI\_Status\_f2c. That is, the value of c\_status must not be either MPI\_STATUS\_IGNORE or MPI\_STATUSES\_IGNORE.

Advice to users. There exists no separate conversion function for arrays of statuses, since one can simply loop through the array, converting each status with the routines in Figure 19.1. (End of advice to users.)

Rationale. The handling of MPI\_STATUS\_IGNORE is required in order to layer libraries with only a C wrapper: if the Fortran call has passed MPI\_STATUS\_IGNORE, then the C wrapper must handle this correctly. Note that this constant need not have the same value in Fortran and C. If MPI\_Status\_f2c were to handle MPI\_STATUS\_IGNORE, then the type of its result would have to be MPI\_Status\*\*, which was considered an inferior solution. (End of rationale.)

Using the mpi\_f08 Fortran module, a status is declared as TYPE(MPI\_Status). The C type MPI\_F08\_status can be used to pass a Fortran TYPE(MPI\_Status) argument into a C routine. Figure 19.1 illustrates all status conversion routines. Some are only available in C, some in both C and the Fortran mpi and mpi\_f08 interfaces (but not in the mpif.h interface).

This C routine converts a Fortran mpi\_f08 TYPE(MPI\_Status) into a C MPI\_Status.



Fortran types and subroutines

Figure 19.1: Status conversion routines

This C routine converts a C MPI\_Status into a Fortran mpi\_f08 TYPE(MPI\_Status). Two global variables of type MPI\_F08\_status\*, MPI\_F08\_STATUS\_IGNORE and MPI\_F08\_STATUSES\_IGNORE are declared in mpi.h. They can be used to test, in C, whether f\_status is the Fortran value of MPI\_STATUS\_IGNORE or MPI\_STATUSES\_IGNORE defined in the mpi\_f08 module. These are global variables, not C constant expressions and cannot be used in places where C requires constant expressions. Their value is defined only between the calls to MPI\_INIT and MPI\_FINALIZE and should not be changed by user code.

Conversion between the two Fortran versions of a status can be done with:

```
MPI_STATUS_F2F08(f_status, f08_status)
```

IN	t_status	status object declared as array
OUT	f08_status	status object declared as named type

#### C binding

int MPI\_Status\_f2f08(const MPI\_Fint \*f\_status, MPI\_F08\_status \*f08\_status)

#### Fortran 2008 binding

```
MPI_Status_f2f08(f_status, f08_status, ierror)
    INTEGER, INTENT(IN) :: f_status(MPI_STATUS_SIZE)
    TYPE(MPI_Status), INTENT(OUT) :: f08_status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

# Fortran binding (the following procedure is not available with mpif.h)

MPI\_STATUS\_F2F08(F\_STATUS, F08\_STATUS, IERROR)

```
2
          TYPE(MPI_Status) :: F08_STATUS
          This routine converts a Fortran INTEGER, DIMENSION (MPI_STATUS_SIZE) status array
     into a Fortran mpi_f08 TYPE(MPI_Status).
5
6
7
     MPI_STATUS_F082F(f08_status, f_status)
8
       IN
                 f08_status
                                              status object declared as named type
9
       OUT
10
                 f_status
                                              status object declared as array
```

## C binding

int MPI\_Status\_f082f(const MPI\_F08\_status \*f08\_status, MPI\_Fint \*f\_status)

# Fortran 2008 binding

```
MPI_Status_f082f(f08_status, f_status, ierror)
    TYPE(MPI_Status), INTENT(IN) :: f08_status
    INTEGER, INTENT(OUT) :: f_status(MPI_STATUS_SIZE)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

INTEGER :: F\_STATUS(MPI\_STATUS\_SIZE), IERROR

# Fortran binding (the following procedure is not available with mpif.h)

MPI\_STATUS\_F082F(F08\_STATUS, F\_STATUS, IERROR)

```
TYPE(MPI_Status) :: F08_STATUS
INTEGER :: F_STATUS(MPI_STATUS_SIZE), IERROR
```

This routine converts a Fortran mpi\_f08 TYPE(MPI\_Status) into a Fortran INTEGER, DIMENSION(MPI\_STATUS\_SIZE) status array.

#### 19.3.6 MPI Opaque Objects

Unless said otherwise, opaque objects are "the same" in all languages: they carry the same information, and have the same meaning in both languages. The mechanism described in the previous section can be used to pass references to MPI objects from language to language. An object created in one language can be accessed, modified or freed in another language.

We examine below in more detail issues that arise for each type of MPI object.

#### **Datatypes**

Datatypes encode the same information in all languages. E.g., a datatype accessor like MPI\_TYPE\_GET\_EXTENT will return the same information in all languages. If a datatype defined in one language is used for a communication call in another language, then the message sent will be identical to the message that would be sent from the first language: the same communication buffer is accessed, and the same representation conversion is performed, if needed. All predefined datatypes can be used in datatype constructors in any language. If a datatype is committed, it can be used for communication in any language.

The function MPI\_GET\_ADDRESS returns the same value in all languages. Note that we do not require that the constant MPI\_BOTTOM have the same value in all languages (see Section 19.3.9).

12

13 14

15 16

18

19

20

21

22 23

26

27

28

29

30

33

34

35

36

37

42

43 44

45 46

47

```
Example 19.12
! FORTRAN CODE
REAL :: R(5)
INTEGER :: TYPE, IERR, AOBLEN(1), AOTYPE(1)
INTEGER (KIND=MPI_ADDRESS_KIND) :: AODISP(1)
! create an absolute datatype for array R
AOBLEN(1) = 5
CALL MPI_GET_ADDRESS(R, AODISP(1), IERR)
AOTYPE(1) = MPI_REAL
CALL MPI_TYPE_CREATE_STRUCT(1, AOBLEN, AODISP, AOTYPE, TYPE, IERR)
CALL C_ROUTINE(TYPE)
/* C code */
void C_ROUTINE(MPI_Fint *ftype)
   int count = 5;
   int lens[2] = \{1,1\};
  MPI_Aint displs[2];
  MPI_Datatype types[2], newtype;
   /* create an absolute datatype for buffer that consists
                                                              */
   /* of count, followed by R(5)
                                                              */
  MPI_Get_address(&count, &displs[0]);
  displs[1] = 0;
   types[0] = MPI_INT;
   types[1] = MPI_Type_f2c(*ftype);
  MPI_Type_create_struct(2, lens, displs, types, &newtype);
  MPI_Type_commit(&newtype);
  MPI_Send(MPI_BOTTOM, 1, newtype, 1, 0, MPI_COMM_WORLD);
  /* the message sent contains an int count of 5, followed
                                                              */
   /* by the 5 REAL entries of the Fortran array R.
                                                              */
}
```

Advice to implementors. The following implementation can be used: MPI addresses, as returned by MPI\_GET\_ADDRESS, will have the same value in all languages. One obvious choice is that MPI addresses be identical to regular addresses. The address is stored in the datatype, when datatypes with absolute addresses are constructed. When a send or receive operation is performed, then addresses stored in a datatype are interpreted as displacements that are all augmented by a base address. This base address is (the address of) buf, or zero, if buf = MPI\_BOTTOM. Thus, if MPI\_BOTTOM is zero then a send or receive call with buf = MPI\_BOTTOM is implemented exactly as a call with a regular buffer argument: in both cases the base address is buf. On the other hand, if MPI\_BOTTOM is not zero, then the implementation has to be slightly different. A test is performed to check whether buf = MPI\_BOTTOM. If true, then the

base address is zero, otherwise it is buf. In particular, if MPI\_BOTTOM does not have the same value in Fortran and C, then an additional test for buf = MPI\_BOTTOM is needed in at least one of the languages.

It may be desirable to use a value other than zero for MPI\_BOTTOM even in C, so as to distinguish it from a NULL pointer. If MPI\_BOTTOM = c then one can still avoid the test buf = MPI\_BOTTOM, by using the displacement from MPI\_BOTTOM, i.e., the regular address - c, as the MPI address returned by MPI\_GET\_ADDRESS and stored in absolute datatypes. (*End of advice to implementors*.)

#### Callback Functions

MPI calls may associate callback functions with MPI objects: error handlers are associated with communicators, files, windows, and sessions; attribute copy and delete functions are associated with attribute keys; reduce operations are associated with operation objects, etc. In a multilanguage environment, a function passed in an MPI call in one language may be invoked by an MPI call in another language. MPI implementations must make sure that such invocation will use the calling convention of the language the function is bound to.

Advice to implementors. Callback functions need to have a language tag. This tag is set when the callback function is passed in by the library function (which is presumably different for each language and language support method), and is used to generate the right calling sequence when the callback function is invoked. (End of advice to implementors.)

Advice to users. If a subroutine written in one language or Fortran support method wants to pass a callback routine including the predefined Fortran functions (e.g., MPI\_COMM\_NULL\_COPY\_FN) to another application routine written in another language or Fortran support method, then it must be guaranteed that both routines use the callback interface definition that is defined for the argument when passing the callback to an MPI routine (e.g., MPI\_COMM\_CREATE\_KEYVAL); see also the advice to users on page 363. (End of advice to users.)

# Error Handlers

Advice to implementors. Error handlers, have, in C, a variable length argument list. It might be useful to provide to the handler information on the language environment where the error occurred. (End of advice to implementors.)

#### Reduce Operations

All predefined named and unnamed datatypes as listed in Section 6.9.2 can be used in the listed predefined operations independent of the programming language from which the MPI routine is called.

Advice to users. Reduce operations receive as one of their arguments the datatype of the operands. Thus, one can define "polymorphic" reduce operations that work for C and Fortran datatypes. (*End of advice to users*.)

#### 19.3.7 Attributes

Attribute keys can be allocated in one language and freed in another. Similarly, attribute values can be set in one language and accessed in another. To achieve this, attribute keys will be allocated in an integer range that is valid all languages. The same holds true for system-defined attribute values (such as MPI\_TAG\_UB, MPI\_WTIME\_IS\_GLOBAL, etc.).

Attribute keys declared in one language are associated with copy and delete functions in that language (the functions provided by the MPI\_XXX\_CREATE\_KEYVAL call). When a communicator is duplicated, for each attribute, the corresponding copy function is called, using the right calling convention for the language of that function; and similarly, for the delete callback function.

Advice to implementors. This requires that attributes be tagged either as "C" or "Fortran" and that the language tag be checked in order to use the right calling convention for the callback function. (End of advice to implementors.)

The attribute manipulation functions described in Section 7.7 defines attributes arguments to be of type void\* in C, and of type INTEGER, in Fortran. On some systems, INTEGERs will have 32 bits, while C pointers will have 64 bits. This is a problem if communicator attributes are used to move information from a Fortran caller to a C callee, or vice-versa.

MPI behaves as if it stores, internally, address sized attributes. If Fortran INTEGERs are smaller, then the (deprecated) Fortran function MPI\_ATTR\_GET will return the least significant part of the attribute word; the (deprecated) Fortran function MPI\_ATTR\_PUT will set the least significant part of the attribute word, which will be sign extended to the entire word. (These two functions may be invoked explicitly by user code, or implicitly, by attribute copying callback functions.)

As for addresses, new functions are provided that manipulate Fortran address sized attributes, and have the same functionality as the old functions in C. These functions are described in Section 7.7. Users are encouraged to use these new functions.

MPI supports two types of attributes: address-valued (pointer) attributes, and integer-valued attributes. C attribute functions put and get address-valued attributes. Fortran attribute functions put and get integer-valued attributes. When an integer-valued attribute is accessed from C, then MPI\_XXX\_get\_attr will return the address of (a pointer to) the integer-valued attribute, which is a pointer to MPI\_Aint if the attribute was stored with Fortran MPI\_XXX\_SET\_ATTR, and a pointer to int if it was stored with the deprecated Fortran MPI\_ATTR\_PUT. When an address-valued attribute is accessed from Fortran, then MPI\_XXX\_GET\_ATTR will convert the address into an integer and return the result of this conversion. This conversion is lossless if new style attribute functions are used, and an integer of kind MPI\_ADDRESS\_KIND is returned. The conversion may cause truncation if deprecated attribute functions are used. In C, the deprecated routines MPI\_Attr\_put and MPI\_Attr\_get behave identical to MPI\_Comm\_set\_attr and MPI\_Comm\_get\_attr.

#### **Example 19.13**

A. Setting an attribute value in C

```
1
     int set_val = 3;
2
     struct foo set_struct;
3
4
     /* Set a value that is a pointer to an int */
5
6
     MPI_Comm_set_attr(MPI_COMM_WORLD, keyval1, &set_val);
7
     /* Set a value that is a pointer to a struct */
     MPI_Comm_set_attr(MPI_COMM_WORLD, keyval2, &set_struct);
     /* Set an integer value */
10
     MPI_Comm_set_attr(MPI_COMM_WORLD, keyval3, (void *) 17);
11
         B. Reading the attribute value in C
12
13
     int flag, *get_val;
14
     struct foo *get_struct;
15
16
     /* Upon successful return, get_val == &set_val
17
        (and therefore *get_val == 3) */
     MPI_Comm_get_attr(MPI_COMM_WORLD, keyval1, &get_val, &flag);
     /* Upon successful return, get_struct == &set_struct */
20
     MPI_Comm_get_attr(MPI_COMM_WORLD, keyval2, &get_struct, &flag);
21
     /* Upon successful return, get_val == (void*) 17 */
22
               i.e., (MPI_Aint) get_val == 17 */
23
    MPI_Comm_get_attr(MPI_COMM_WORLD, keyval3, &get_val, &flag);
24
         C. Reading the attribute value with (deprecated) Fortran MPI-1 calls
26
27
     LOGICAL FLAG
28
     INTEGER IERR, GET_VAL, GET_STRUCT
29
30
     ! Upon successful return, GET_VAL == &set_val, possibly truncated
31
     CALL MPI_ATTR_GET(MPI_COMM_WORLD, KEYVAL1, GET_VAL, FLAG, IERR)
32
     ! Upon successful return, GET_STRUCT == &set_struct, possibly truncated
33
     CALL MPI_ATTR_GET(MPI_COMM_WORLD, KEYVAL2, GET_STRUCT, FLAG, IERR)
34
     ! Upon successful return, GET_VAL == 17
35
     CALL MPI_ATTR_GET(MPI_COMM_WORLD, KEYVAL3, GET_VAL, FLAG, IERR)
36
37
         D. Reading the attribute value with Fortran MPI-2 calls
38
39
     LOGICAL FLAG
40
     INTEGER IERR
41
     INTEGER (KIND=MPI_ADDRESS_KIND) GET_VAL, GET_STRUCT
42
43
     ! Upon successful return, GET_VAL == &set_val
44
     CALL MPI_COMM_GET_ATTR(MPI_COMM_WORLD, KEYVAL1, GET_VAL, FLAG, IERR)
45
     ! Upon successful return, GET_STRUCT == &set_struct
     CALL MPI_COMM_GET_ATTR(MPI_COMM_WORLD, KEYVAL2, GET_STRUCT, FLAG, IERR)
47
     ! Upon successful return, GET_VAL == 17
     CALL MPI_COMM_GET_ATTR(MPI_COMM_WORLD, KEYVAL3, GET_VAL, FLAG, IERR)
```

```
Example 19.14 A. Setting an attribute value with the (deprecated) Fortran MPI-1 call
INTEGER IERR, VAL
VAL = 7
CALL MPI_ATTR_PUT(MPI_COMM_WORLD, KEYVAL, VAL, IERR)
    B. Reading the attribute value in C
int flag;
int *value;
/* Upon successful return, value points to internal MPI storage and
                                                                                      12
   *value == (int) 7 */
                                                                                      13
MPI_Comm_get_attr(MPI_COMM_WORLD, keyval, &value, &flag);
                                                                                      14
                                                                                      15
    C. Reading the attribute value with (deprecated) Fortran MPI-1 calls
                                                                                      16
LOGICAL FLAG
                                                                                      18
INTEGER IERR, VALUE
                                                                                      19
                                                                                      20
! Upon successful return, VALUE == 7
                                                                                      21
CALL MPI_ATTR_GET(MPI_COMM_WORLD, KEYVAL, VALUE, FLAG, IERR)
                                                                                      22
                                                                                      23
    D. Reading the attribute value with Fortran MPI-2 calls
                                                                                      24
LOGICAL FLAG
                                                                                      26
INTEGER IERR
                                                                                      27
INTEGER (KIND=MPI_ADDRESS_KIND) VALUE
                                                                                      28
                                                                                      29
! Upon successful return, VALUE == 7 (sign extended)
                                                                                      30
CALL MPI_COMM_GET_ATTR(MPI_COMM_WORLD, KEYVAL, VALUE, FLAG, IERR)
Example 19.15 A. Setting an attribute value via a Fortran MPI-2 call
                                                                                      33
                                                                                      34
INTEGER IERR
                                                                                      35
INTEGER(KIND=MPI_ADDRESS_KIND) VALUE1
                                                                                      36
INTEGER(KIND=MPI_ADDRESS_KIND) VALUE2
                                                                                      37
VALUE1 = 42
VALUE2 = INT(2, KIND=MPI_ADDRESS_KIND) ** 40
CALL MPI_COMM_SET_ATTR(MPI_COMM_WORLD, KEYVAL1, VALUE1, IERR)
CALL MPI_COMM_SET_ATTR(MPI_COMM_WORLD, KEYVAL2, VALUE2, IERR)
                                                                                      42
                                                                                      43
    B. Reading the attribute value in C
                                                                                      44
                                                                                      45
```

2

3 4

5

7

8

9

21

31

32

33

34

35

36

37

38

39

41

42

43

44

45

47

```
int flag;
     MPI_Aint *value1, *value2;
     /* Upon successful return, value1 points to internal MPI storage and
        *value1 == 42 */
6
     MPI_Comm_get_attr(MPI_COMM_WORLD, keyval1, &value1, &flag);
     /* Upon successful return, value2 points to internal MPI storage and
        *value2 == 2^40 */
     MPI_Comm_get_attr(MPI_COMM_WORLD, keyval2, &value2, &flag);
10
         C. Reading the attribute value with (deprecated) Fortran MPI-1 calls
11
12
     LOGICAL FLAG
13
     INTEGER IERR, VALUE1, VALUE2
14
15
     ! Upon successful return, VALUE1 == 42
16
     CALL MPI_ATTR_GET(MPI_COMM_WORLD, KEYVAL1, VALUE1, FLAG, IERR)
17
     ! Upon successful return, VALUE2 == 2^40, or 0 if truncation
18
     ! needed (i.e., the least significant part of the attribute word)
19
     CALL MPI_ATTR_GET(MPI_COMM_WORLD, KEYVAL2, VALUE2, FLAG, IERR)
20
         D. Reading the attribute value with Fortran MPI-2 calls
22
     LOGICAL FLAG
23
     INTEGER IERR
24
     INTEGER (KIND=MPI_ADDRESS_KIND) VALUE1, VALUE2
25
26
     ! Upon successful return, VALUE1 == 42
27
     CALL MPI_COMM_GET_ATTR(MPI_COMM_WORLD, KEYVAL1, VALUE1, FLAG, IERR)
28
     ! Upon successful return, VALUE2 == 2^40
29
     CALL MPI_COMM_GET_ATTR(MPI_COMM_WORLD, KEYVAL2, VALUE2, FLAG, IERR)
30
```

The predefined MPI attributes can be integer valued or address-valued. Predefined integer valued attributes, such as MPI\_TAG\_UB, behave as if they were put by a call to the deprecated Fortran routine MPI\_ATTR\_PUT, i.e., in Fortran,

MPI\_COMM\_GET\_ATTR(MPI\_COMM\_WORLD, MPI\_TAG\_UB, val, flag, ierr) will return in val the upper bound for tag value; in C, MPI\_Comm\_get\_attr(MPI\_COMM\_WORLD, MPI\_TAG\_UB, &p, &flag) will return in p a pointer to an int containing the upper bound for tag value.

Address-valued predefined attributes, such as MPI\_WIN\_BASE behave as if they were put by a C call, i.e., in Fortran, MPI\_WIN\_GET\_ATTR(win, MPI\_WIN\_BASE, val, flag, ierror) will return in val the base address of the window, converted to an integer. In C, MPI\_Win\_get\_attr(win, MPI\_WIN\_BASE, &p, &flag) will return in p a pointer to the window base, cast to (void \*).

The design is consistent with the behavior specified for predefined at-Rationale. tributes, and ensures that no information is lost when attributes are passed from language to language. Because the language interoperability for predefined attributes was defined based on MPI\_ATTR\_PUT, this definition is kept for compatibility reasons although the routine itself is now deprecated. (End of rationale.)

Advice to implementors. Implementations should tag attributes either as (1) address attributes, (2) as INTEGER(KIND=MPI\_ADDRESS\_KIND) attributes or (3) as INTEGER attributes, according to whether they were set in (1) C (with MPI\_Attr\_put or MPI\_XXX\_set\_attr), (2) in Fortran with MPI\_XXX\_SET\_ATTR or (3) with the deprecated Fortran routine MPI\_ATTR\_PUT. Thus, the right choice can be made when the attribute is retrieved. (End of advice to implementors.)

#### 19.3.8 Extra-State

Extra-state should not be modified by the copy or delete callback functions. (This is obvious from the C binding, but not obvious from the Fortran binding). However, these functions may update state that is indirectly accessed via extra-state. E.g., in C, extra-state can be a pointer to a data structure that is modified by the copy or callback functions; in Fortran, extra-state can be an index into an entry in a COMMON array that is modified by the copy or callback functions. In a multithreaded environment, users should be aware that distinct threads may invoke the same callback function concurrently: if this function modifies state associated with extra-state, then mutual exclusion code must be used to protect updates and accesses to the shared state.

#### 19.3.9 Constants

MPI constants have the same value in all languages, unless specified otherwise. This does not apply to constant handles (MPI\_INT, MPI\_COMM\_WORLD, MPI\_ERRORS\_RETURN, MPI\_SUM, etc.) These handles need to be converted, as explained in Section 19.3.4. Constants that specify maximum lengths of strings (see Section A.1.1 for a listing) have a value one less in Fortran than C since in C the length includes the null terminating character. Thus, these constants represent the amount of space which must be allocated to hold the largest possible such string, rather than the maximum number of printable characters the string could contain.

Advice to users. This definition means that it is safe in C to allocate a buffer to receive a string using a declaration like

```
char name [MPI_MAX_OBJECT_NAME];
```

(End of advice to users.)

Also constant "addresses," i.e., special values for reference arguments that are not handles, such as MPI\_BOTTOM or MPI\_STATUS\_IGNORE may have different values in different languages.

Rationale. The current MPI standard specifies that MPI\_BOTTOM can be used in initialization expressions in C, but not in Fortran. Since Fortran does not normally support call by value, then MPI\_BOTTOM in Fortran must be the name of a predefined static variable, e.g., a variable in an MPI declared COMMON block. On the other hand, in C, it is natural to take MPI\_BOTTOM = 0 (Caveat: Defining MPI\_BOTTOM = 0 implies that NULL pointer cannot be distinguished from MPI\_BOTTOM; it may be that MPI\_BOTTOM = 1 is better. See the advice to implementors in the Datatypes subsection in Section 19.3.6) Requiring that the Fortran and C values be the same will complicate the initialization process. (End of rationale.)

6

9

10

11

47

48

# 19.3.10 Interlanguage Communication

The type matching rules for communication in MPI are not changed: the datatype specification for each item sent should match, in type signature, the datatype specification used to receive this item (unless one of the types is MPI\_PACKED). Also, the type of a message item should match the type declaration for the corresponding communication buffer location, unless the type is MPI\_BYTE or MPI\_PACKED. Interlanguage communication is allowed if it complies with these rules.


**Example 19.16** In the example below, a Fortran array is sent from Fortran and received in C.


```
! FORTRAN CODE
12
     SUBROUTINE MYEXAMPLE()
13
14
     USE mpi_f08
     REAL :: R(5)
15
16
     INTEGER :: IERR, MYRANK, AOBLEN(1)
17
     TYPE(MPI_Datatype) :: TYPE, AOTYPE(1)
     INTEGER (KIND=MPI_ADDRESS_KIND) :: AODISP(1)
18
19
     ! create an absolute datatype for array R
20
21
     AOBLEN(1) = 5
     CALL MPI_GET_ADDRESS(R, AODISP(1), IERR)
22
     AOTYPE(1) = MPI_REAL
23
     CALL MPI_TYPE_CREATE_STRUCT(1, AOBLEN, AODISP, AOTYPE, TYPE, IERR)
24
     CALL MPI_TYPE_COMMIT(TYPE, IERR)
25
26
     CALL MPI_COMM_RANK(MPI_COMM_WORLD, MYRANK, IERR)
27
     IF (MYRANK.EQ.O) THEN
28
        CALL MPI_SEND(MPI_BOTTOM, 1, TYPE, 1, 0, MPI_COMM_WORLD, IERR)
29
     ELSE
30
        CALL C_ROUTINE(TYPE%MPI_VAL)
31
     END IF
32
     END SUBROUTINE
33
34
35
     /* C code */
36
37
     void C_ROUTINE(MPI_Fint *fhandle)
38
39
        MPI_Datatype type;
        MPI_Status status;
41
42
        type = MPI_Type_f2c(*fhandle);
43
44
        MPI_Recv(MPI_BOTTOM, 1, type, 0, 0, MPI_COMM_WORLD, &status);
45
     }
46
```

MPI implementors may weaken these type matching rules, and allow messages to be sent with Fortran types and received with C types, and vice versa, when those types match. I.e.,

if the Fortran type INTEGER is identical to the C type int, then an MPI implementation may allow data to be sent with datatype MPI\_INTEGER and be received with datatype MPI\_INT. However, such code is not portable.







# Annex A

# Language Bindings Summary

In this section we summarize the specific bindings for C and Fortran. First we present the constants, type definitions, info values and keys. Then we present the routine prototypes separately for each binding. Listings are alphabetical within chapter.

## A.1 Defined Values and Handles

#### A.1.1 Defined Constants

The C and Fortran names are listed below. Constants with the type const int may also be implemented as literal integer constants substituted by the preprocessor.

# Error classes C type: const int (or unnamed enum) Fortran type: INTEGER MPI\_SUCCESS MPI\_ERR\_BUFFER MPI\_ERR\_COUNT MPI\_ERR\_TYPE MPI\_ERR\_TAG MPI\_ERR\_COMM MPI\_ERR\_RANK MPI\_ERR\_REQUEST MPI\_ERR\_ROOT MPI\_ERR\_GROUP MPI\_ERR\_OP MPI\_ERR\_TOPOLOGY MPI\_ERR\_DIMS MPI\_ERR\_ARG MPI\_ERR\_UNKNOWN MPI\_ERR\_TRUNCATE MPI\_ERR\_OTHER MPI\_ERR\_INTERN MPI\_ERR\_PENDING (Continued on next page)

12

18

19 20

21

26

27

28

34

35

37

42

43

1	Error classes (continued)
2	C type: const int (or unnamed enum)
3	Fortran type: INTEGER
4	MPI_ERR_IN_STATUS
5	MPI_ERR_ACCESS
6	MPI_ERR_AMODE
7	MPI_ERR_ASSERT
8	MPI_ERR_BAD_FILE
9	MPI_ERR_BASE
10	MPI_ERR_CONVERSION
11	MPI_ERR_DISP
12	MPI_ERR_DUP_DATAREP
13	MPI_ERR_FILE_EXISTS
14	MPI_ERR_FILE_IN_USE
15	MPI_ERR_FILE
16	MPI_ERR_INFO_KEY
17	MPI_ERR_INFO_NOKEY
18	MPI_ERR_INFO_VALUE
19	MPI_ERR_INFO
20	MPI_ERR_IO
21	MPI_ERR_KEYVAL
22	MPI_ERR_LOCKTYPE
23	MPI_ERR_NAME
24	MPI_ERR_NO_MEM
25	MPI_ERR_NOT_SAME
26	MPI_ERR_NO_SPACE
27	MPI_ERR_NO_SUCH_FILE
28	MPI_ERR_PORT
29	MPI_ERR_PROC_ABORTED
30	MPI_ERR_QUOTA
31	MPI_ERR_READ_ONLY
32	MPI_ERR_RMA_ATTACH
33	MPI_ERR_RMA_CONFLICT
34	MPI_ERR_RMA_RANGE
35	MPI_ERR_RMA_SHARED
36	MPI_ERR_RMA_SYNC
37	MPI_ERR_RMA_FLAVOR
38	MPI_ERR_SERVICE
39	MPI_ERR_SIZE
40	MPI_ERR_SPAWN
41	MPI_ERR_UNSUPPORTED_DATAREP
42	MPI_ERR_UNSUPPORTED_OPERATION
43	MPI_ERR_WIN
44	(Continued on next page)
45	
46	
47	
48	

**Unofficial Draft for Comment Only** 

#-???

	Emmon alogges (continued)	1
	Error classes (continued)	1 2
	C type: const int (or unnamed enum) Fortran type: INTEGER	3
	MPI_T_ERR_CANNOT_INIT	4
_	MPI_T_ERR_NOT_ACCESSIBLE	5
#-???	MPI_T_ERR_NOT_INITIALIZED	6
	MPI_T_ERR_NOT_SUPPORTED	7
	MPI_T_ERR_MEMORY	8
	MPI_T_ERR_INVALID	9
	MPI_T_ERR_INVALID_INDEX	10
	MPI_T_ERR_INVALID_ITEM	11
	MPI_T_ERR_INVALID_SESSION	12
	MPI_T_ERR_INVALID_HANDLE	13
	MPI_T_ERR_INVALID_NAME	14
	MPI_T_ERR_OUT_OF_HANDLES	15
	MPI_T_ERR_OUT_OF_SESSIONS	16
	MPI_T_ERR_CVAR_SET_NOT_NOW	17
	MPI_T_ERR_CVAR_SET_NEVER	18
	MPI_T_ERR_PVAR_NO_WRITE	19
	MPI_T_ERR_PVAR_NO_STARTSTOP	20
	MPI_T_ERR_PVAR_NO_ATOMIC	21
	MPI_ERR_LASTCODE	22
	Buffer Address Constants	23
	C type: void * const	24 25
	Fortran type: (predefined memory location) <sup>1</sup>	26
	MPI_BOTTOM	27
	MPI_IN_PLACE	28
	<sup>1</sup> Note that in Fortran these constants are not usable for initialization	29
	expressions or assignment. See Section 2.5.4.	30
	Assorted Constants	31
	C type: const int (or unnamed enum)	32
	Fortran type: INTEGER	33
	MPI_PROC_NULL	34
	MPI_ANY_SOURCE	35
	MPI_ANY_TAG	36
	MPI_UNDEFINED	37
	MPI_BSEND_OVERHEAD	38
	MPI_KEYVAL_INVALID	39
	MPI_LOCK_EXCLUSIVE	40
	MPI_LOCK_SHARED	41 42
	MPI_ROOT	
		43 44
	No Process Message Handle	45
	C type: MPI_Message	46
	Fortran type: INTEGER or TYPE(MPI_Message)	47
	AADI AAGGA GE NO DDOG	48

MPI\_MESSAGE\_NO\_PROC

	646 ANNEA A. LANGUAGE DINDINGS SUMMARI
1	Fortran Support Method Specific Constants
2	
	Fortran type: LOGICAL
3	MPI_SUBARRAYS_SUPPORTED (Fortran only)
4 5	MPI_ASYNC_PROTECTS_NONBLOCKING (Fortran only)
#- <b>???</b> 6	Status array size and reserved index values (Fortran only)
7	Fortran type: INTEGER
8	MPI_STATUS_SIZE
9	MPI_SOURCE
10	MPI_TAG
11	MPI_ERROR
12	
13	
<b>#-???</b> 14	Fortran status array size and reserved index values (C only)
15	C type: int
16	MPI_F_STATUS_SIZE
17	MPI_F_SOURCE
18	MPI_F_TAG
19	MPI_F_ERROR
20	
21	Variable Address Size (Fortran only)
22	Fortran type: INTEGER
23	MPI_ADDRESS_KIND
24	MPI_COUNT_KIND
25	MPI_INTEGER_KIND
26	MPI_OFFSET_KIND
27	
28	Error-handling specifiers
29	C type: MPI_Errhandler
30	Fortran type: INTEGER or TYPE(MPI_Errhandler)
31	MPI_ERRORS_ARE_FATAL
32	MPI_ERRORS_RETURN
33	
34	Maximum Sizes for Strings
35	C type: const int (or unnamed enum)
36	Fortran type: INTEGER
37	MPI_MAX_DATAREP_STRING
38	MPI_MAX_ERROR_STRING
39	MPI_MAX_INFO_KEY
40	MPI_MAX_INFO_VAL
41	MPI_MAX_LIBRARY_VERSION_STRING
42	MPI_MAX_OBJECT_NAME
43	MPI_MAX_PORT_NAME
#-???	MPI_MAX_PROCESSOR_NAME  Yet unclear, whether there will be
#-error! 45	MPI_MAX_FROM_GROUP_TAG  MPI_MAX_FROM_GROUP_TAG or  MPI_MAX_FROM_GROUP_STRINGTAG
#-382	MPI_MAX_PSET_NAME_LEN or none of them see Issue #-382.
47	Decision in PR 400:
#-PR400 48	MPI_MAX_STRINGTAG_LEN
#-update4	
Done	Unofficial Draft for Comment Only

PR400

Named Predefined Datatypes	C types	1
C type: MPI_Datatype		2
Fortran type: INTEGER		3
or TYPE(MPI_Datatype)		4
MPI_CHAR	char	5
	(treated as printable character)	6
MPI_SHORT	signed short int	7
MPI_INT	signed int	8
MPI_LONG	signed long	9
MPI_LONG_LONG_INT	signed long long	10
MPI_LONG_LONG (as a synonym)	signed long long	11
MPI_SIGNED_CHAR	signed char	12
	(treated as integral value)	13
MPI_UNSIGNED_CHAR	unsigned char	14
	(treated as integral value)	15
MPI_UNSIGNED_SHORT	unsigned short	16
MPI_UNSIGNED	unsigned int	17
MPI_UNSIGNED_LONG	unsigned long	18
MPI_UNSIGNED_LONG_LONG	unsigned long long	19
MPI_FLOAT	float	20
MPI_DOUBLE	double	21
MPI_LONG_DOUBLE	long double	22
MPI_WCHAR	wchar_t	23
	(defined in <stddef.h>)</stddef.h>	24
	(treated as printable character)	25
MPI_C_BOOL	_Bool	26
MPI_INT8_T	int8_t	27
MPI_INT16_T	int16_t	28
MPI_INT32_T	int32_t	29
MPI_INT64_T	int64_t	30
MPI_UINT8_T	uint8_t	31
MPI_UINT16_T	uint16_t	32
MPI_UINT32_T	uint32_t	33
MPI_UINT64_T	uint64_t	34
MPI_AINT	MPI_Aint	35
MPI_COUNT	MPI_Count	36
MPI_OFFSET	MPI_Offset	37
MPI_C_COMPLEX	float _Complex	38
MPI_C_FLOAT_COMPLEX	float _Complex	39
MPI_C_DOUBLE_COMPLEX	double _Complex	40
MPI_C_LONG_DOUBLE_COMPLEX	long double _Complex	41
MPI_BYTE	(any C type)	42
MPI_PACKED	(any C type)	43
	( 0 · · · 0 <b>r</b> · /	44

1	Named Predefined Datatypes	Fortran types
2	C type: MPI_Datatype	
3	Fortran type: INTEGER	
4	or TYPE(MPI_Datatype)	
5	MPI_INTEGER	INTEGER
6	MPI_REAL	REAL
7	MPI_DOUBLE_PRECISION	DOUBLE PRECISION
8	MPI_COMPLEX	COMPLEX
9	MPI_LOGICAL	LOGICAL
10	MPI_CHARACTER	CHARACTER(1)
11	MPI_AINT	INTEGER (KIND=MPI_ADDRESS_KIND)
12	MPI_COUNT	INTEGER (KIND=MPI_COUNT_KIND)
13	MPI_OFFSET	INTEGER (KIND=MPI_OFFSET_KIND)
14	MPI_BYTE	(any Fortran type)
15	MPI_PACKED	(any Fortran type)
16		

Named Predefined Datatypes

C type: MPI\_Datatype
Fortran type: INTEGER
or TYPE(MPI\_Datatype)

MPI\_CXX\_BOOL
MPI\_CXX\_FLOAT\_COMPLEX
MPI\_CXX\_DOUBLE\_COMPLEX
MPI\_CXX\_LONG\_DOUBLE\_COMPLEX
std::complex<double>
std::complex<long double>

<sup>&</sup>lt;sup>1</sup> If an accompanying C++ compiler is missing, then the MPI datatypes in this table are not defined.

Optional datatypes (Fortran)	Fortran types
C type: MPI_Datatype	
Fortran type: INTEGER	
or TYPE(MPI_Datatype)	
MPI_DOUBLE_COMPLEX	DOUBLE COMPLEX
MPI_INTEGER1	INTEGER*1
MPI_INTEGER2	INTEGER*2
MPI_INTEGER4	INTEGER*4
MPI_INTEGER8	INTEGER*8
MPI_INTEGER16	INTEGER*16
MPI_REAL2	REAL*2
MPI_REAL4	REAL*4
MPI_REAL8	REAL*8
MPI_REAL16	REAL*16
MPI_COMPLEX4	COMPLEX*4
MPI_COMPLEX8	COMPLEX*8
MPI_COMPLEX16	COMPLEX*16
MPI_COMPLEX32	COMPLEX*32

Datatypes for reduction functions (C)	1
C type: MPI_Datatype	2
Fortran type: INTEGER or TYPE(MPI_Datatype)	3
MPI_FLOAT_INT	4
MPI_DOUBLE_INT	5
MPI_LONG_INT	6
MPI_2INT	7
MPI_SHORT_INT	8
MPI_LONG_DOUBLE_INT	9
	10
Datatypes for reduction functions (Fortran)	11
C type: MPI_Datatype	12
Fortran type: INTEGER or TYPE(MPI_Datatype)	13
MPI_2REAL	14
MPI_2DOUBLE_PRECISION	15
MPI_2INTEGER	16
Reserved communicators	17
C type: MPI_Comm	18
Fortran type: INTEGER or TYPE(MPI_Comm)	19
MPI_COMM_WORLD	20
MPI_COMM_SELF	21
IVII I_COIVIIVI_SEEI	22
Communicator split type constants	23
C type: const int (or unnamed enum)	24
Fortran type: INTEGER	25
MPI_COMM_TYPE_SHARED	26
MPI_COMM_TYPE_HW_UNGUIDED	27
MPI_COMM_TYPE_HW_GUIDED	28
Results of communicator and group comparisons	29
C type: const int (or unnamed enum)	30
Fortran type: INTEGER	31
· -	32
MPI_IDENT	33
MPI_CONGRUENT	34
MPI_SIMILAR	35
MPI_UNEQUAL	36
Environmental inquiry info key	37
C type: MPI_Info	38
Fortran type: INTEGER or TYPE(MPI_Info)	39
MPI_INFO_ENV	40
	41 42
Environmental inquiry keys	
C type: const int (or unnamed enum)	43 44
Fortran type: INTEGER	
MPI_TAG_UB	45
MPI_IO	46
MPI_HOST	47
MPI_WTIME_IS_GLOBAL	48

#-???

#-??? Done

PR444

	1	Collective Operations
	2	C type: MPI_Op
	3	Fortran type: INTEGER or TYPE(MPI_Op)
	4	MPI_MAX
	5	MPI_MIN
	6	MPI_SUM
	7	MPI_PROD
	8	MPI_MAXLOC
	9	MPI_MINLOC
	10	MPI_BAND
	11	MPI_BOR
	12	MPI_BXOR
	13	MPI_LAND
	14	MPI_LOR
	15	MPI_LXOR
	16	MPI_REPLACE
	17	MPI_NO_OP
	18	- MI 1_110_01
	19	Null Handles
	20	C/Fortran name
	21	C type / Fortran type
	22	MPI_GROUP_NULL
	23	MPI_Group / INTEGER or TYPE(MPI_Group)
	24	MPI_COMM_NULL
	25	MPI_Comm / INTEGER or TYPE(MPI_Comm)
	26	MPI_DATATYPE_NULL
	27	MPI_Datatype / INTEGER or TYPE(MPI_Datatype)
	28	MPI_REQUEST_NULL
	29	MPI_Request / INTEGER or TYPE(MPI_Request)
	30	MPI_OP_NULL
	31	MPI_Op / INTEGER or TYPE(MPI_Op)
	32	MPI_ERRHANDLER_NULL
	33	MPI_Errhandler / INTEGER or TYPE(MPI_Errhandler)
	34	MPI_EITHANDIET / INTEGER OF TITE (MITI_EITHANDIET)
	35	MPI_File / INTEGER or TYPE(MPI_File)
	36	MPI_INFO_NULL
	37	MPI_Info / INTEGER or TYPE(MPI_Info)
#-error!	38	MPI_SESSION_NULL
#-enor: #-???	39	MPI_Session / INTEGER or TYPE(MPI_Session)
	40	MPI_Session / INTEGER OF TTPE(MPI_Session)  MPI_WIN_NULL
Done in	41	
PR444	42	MPI_Win / INTEGER or TYPE(MPI_Win) MPI_MESSAGE_NULL
	43	
	44	MPI_Message / INTEGER or TYPE(MPI_Message)
	45	Franty group
	46	C type: MPI Crown
	47	C type: MPI_Group
	48	Fortran type: INTEGER or TYPE(MPI_Group)  MPI_GROUP_EMPTY
	_	IVIPI_GROUP_EIVIP I Y

**Unofficial Draft for Comment Only** 

```
MPI_GRAPH
                          MPI_CART
                          MPI_DIST_GRAPH
                               Predefined functions
C/Fortran name
   C type
   / Fortran type with mpi module
                                        / Fortran type with mpi_f08 module
                                                                                           12
MPI_COMM_NULL_COPY_FN
                                  All old-style Fortran callback prototypes also
   MPI_Comm_copy_attr_function
                                  referenced in the callback prototype index
                                                                                             #-error!
                                  PROCEDURE (MPI_Comm_copy_attr_function) 1)
   / COMM_COPY_ATTR_FUNCTION
                                                                                              Done
                                                                                           15
MPI_COMM_DUP_FN
                                                                                              lin
   MPI_Comm_copy_attr_function
                                                                                              PR449
                                 / PROCEDURE(MPI_Comm_copy_attr_function)
   / COMM_COPY_ATTR_FUNCTION
                                                                                           18
MPI_COMM_NULL_DELETE_FN
                                                                                           19
   MPI_Comm_delete_attr_function
                                                                                           20
   / COMM_DELETE_ATTR_FUNCTION
                                   / {	t PROCEDURE(	t MPI\_Comm\_delete\_attr\_function)}^{-1})
                                                                                           21
MPI_WIN_NULL_COPY_FN
   MPI_Win_copy_attr_function
                                                                                           23
   / WIN_COPY_ATTR_FUNCTION
                                / PROCEDURE(MPI_Win_copy_attr_function) 1)
MPI_WIN_DUP_FN
   MPI_Win_copy_attr_function
   / WIN_COPY_ATTR_FUNCTION
                                / PROCEDURE(MPI_Win_copy_attr_function) 1)
                                                                                           27
MPI_WIN_NULL_DELETE_FN
                                                                                           28
   MPI_Win_delete_attr_function
   / WIN_DELETE_ATTR_FUNCTION
                                  / PROCEDURE(MPI_Win_delete_attr_function) 1)
                                                                                           30
MPI_TYPE_NULL_COPY_FN
   MPI_Type_copy_attr_function
   / TYPE_COPY_ATTR_FUNCTION
                                 / PROCEDURE(MPI_Type_copy_attr_function) 1)
MPI_TYPE_DUP_FN
                                                                                           34
  MPI_Type_copy_attr_function
                                                                                           35
   / TYPE_COPY_ATTR_FUNCTION
                                 / PROCEDURE(MPI_Type_copy_attr_function) 1)
                                                                                           36
MPI_TYPE_NULL_DELETE_FN
                                                                                           37
   MPI_Type_delete_attr_function
                                                                                           38
   / TYPE_DELETE_ATTR_FUNCTION
                                   / PROCEDURE(MPI_Type_delete_attr_function)^{-1})
                                                                                              #-error!
                                                                                           39
                                                           Many out-commented lines starting with
MPI_CONVERSION_FN_NULL
                                                           %DAN-PyMerge%...
                                                                                              Done
                                                                                           40
   MPI_Datarep_conversion_function
                                                           should be deleted????
                                                                                              in
   / DATAREP_CONVERSION_FUNCTION
                                     / PROCEDURE(MPI_Datarep_conversion_function) 1)
                                                                                              PR444
                                                                                           42
<sup>1</sup> See the advice to implementors (on page 363) and advice to users (on page 363)
                                                                                           43
   on the predefined Fortran functions MPI_COMM_NULL_COPY_FN, ... in
                                                                                           44
   Section 7.7.2.
```

Topologies
C type: const int (or unnamed enum)

Fortran type: INTEGER

All old-style Fortran callback

prototypes also referenced in

the callback prototype index

	1
	2
	3
	4
t-error!	5
Done	6
n PR449	7
11443	8
	9
	10
	11
	12
	13
	14
	15
	16
	17
	18
	19
	20
	21
	22
	23
	24
	25
	26
	27
	28
	29
	30
	31
	32
	33
	34
	35
	36
	37
	38
	39
	40
	41
	42
	43
	44
	45

47

C/Fortran name
C type / Fortran type with mpi module
MPI\_NULL\_COPY\_FN

MPI\_Copy\_function / COPY\_FUNCTION MPI\_DUP\_FN

MPI\_Copy\_function / COPY\_FUNCTION'
MPI\_NULL\_DELETE\_FN

MPI\_Delete\_function / DELETE\_FUNCTION

# Predefined Attribute Keys

C type: const int (or unnamed enum)

Fortran type: INTEGER

MPI\_APPNUM

MPI\_LASTUSEDCODE

MPI\_UNIVERSE\_SIZE

MPI\_WIN\_BASE

MPI\_WIN\_DISP\_UNIT

MPI\_WIN\_SIZE

MPI\_WIN\_CREATE\_FLAVOR

MPI\_WIN\_MODEL

#### **MPI** Window Create Flavors

C type: const int (or unnamed enum)

Fortran type: INTEGER

MPI\_WIN\_FLAVOR\_CREATE

MPI\_WIN\_FLAVOR\_ALLOCATE

MPI\_WIN\_FLAVOR\_DYNAMIC

MPI\_WIN\_FLAVOR\_SHARED

# **MPI** Window Models

C type: const int (or unnamed enum)

Fortran type: INTEGER

MPI\_WIN\_SEPARATE

MPI\_WIN\_UNIFIED

	Mode Constants	1
	C type: const int (or unnamed enum)	2
	Fortran type: INTEGER	3
-	MPI_MODE_APPEND	4
	MPI_MODE_CREATE	5
	MPI_MODE_DELETE_ON_CLOSE	$\epsilon$
	MPI_MODE_EXCL	7
	MPI_MODE_NOCHECK	8
	MPI_MODE_NOPRECEDE	9
	MPI_MODE_NOPUT	1
	MPI_MODE_NOSTORE	1
	MPI_MODE_NOSUCCEED	1
	MPI_MODE_RDONLY	1
	MPI_MODE_RDWR	1
	MPI_MODE_SEQUENTIAL	1
	MPI_MODE_UNIQUE_OPEN	1
_	MPI_MODE_WRONLY	1
		1
_	Datatype Decoding Constants	1
	C type: const int (or unnamed enum)	2
	Fortran type: INTEGER	2
	MPI_COMBINER_CONTIGUOUS	2
	MPI_COMBINER_DARRAY	2
	MPI_COMBINER_DUP	2
	MPI_COMBINER_F90_COMPLEX	2
	MPI_COMBINER_F90_INTEGER	2
	MPI_COMBINER_F90_REAL	2
	MPI_COMBINER_HINDEXED	2
	MPI_COMBINER_HVECTOR	2
	MPI_COMBINER_INDEXED_BLOCK	3
	MPI_COMBINER_HINDEXED_BLOCK	3
	MPI_COMBINER_INDEXED	3
	MPI_COMBINER_NAMED	3
l	MPI_COMBINER_RESIZED	3
	MPI_COMBINER_STRUCT	3
7	MPI_COMBINER_SUBARRAY	3
٧.	MPI_COMBINER_VECTOR	3
		3
_	Threads Constants	3
	C type: const int (or unnamed enum)	4
	Fortran type: INTEGER	4
	MPI_THREAD_FUNNELED	4
	MPI_THREAD_MULTIPLE	4
	MPI_THREAD_SERIALIZED	4
_	MPI_THREAD_SINGLE	4
		4

#-error! Done

PR444

1	File Operation Constants, Part 1	
2	C type: const MPI_Offset (or unnamed enum)	-
3	Fortran type: INTEGER (KIND=MPI_OFFSET_KIND)	
4	MPI_DISPLACEMENT_CURRENT	-
5		-
6	File Operation Constants, Part 2	
7	C type: const int (or unnamed enum)	
8	Fortran type: INTEGER	
9	MPI_DISTRIBUTE_BLOCK	
10	MPI_DISTRIBUTE_CYCLIC	
11	MPI_DISTRIBUTE_DFLT_DARG	
12	MPI_DISTRIBUTE_NONE	
13	MPI_ORDER_C	
14	MPI_ORDER_FORTRAN	
15	MPI_SEEK_CUR	
16	MPI_SEEK_END	
17	MPI_SEEK_SET	
18		
19	F90 Datatype Matching Constants	
20	C type: const int (or unnamed enum)	
21	Fortran type: INTEGER	
22	MPI_TYPECLASS_COMPLEX	
23	MPI_TYPECLASS_INTEGER	
24	MPI_TYPECLASS_REAL	
25		
26	Constants Specifying Empty or Ignored Inp	ut
27	C/Fortran name	
28	C type / Fortran type <sup>1</sup>	
29	MPI_ARGVS_NULL	
30	char*** / 2-dim, array of CHARACTER*(*)	
31	MPI_ARGV_NULL	
32	char** / array of CHARACTER*(*)	
33	MPI_ERRCODES_IGNORE	
34	int* / INTEGER array	
35	MPI_STATUSES_IGNORE	
36	MPI_Status* / INTEGER, DIMENSION(MPI_STATUS_SIZE,*)	
37		TYPE(MPI_Status) should be \mpiftype
38	MPL STATUS IGNORE	and ", DIMENSION(*)" should be
39	AND Co	formatted in the same style ??? Compare to here!
40	or TYPE(MPI_Status)	compare to here.
41	MPI_UNWEIGHTED	
42	int* / INTEGER array	
43	MPI_WEIGHTS_EMPTY	
44	int* / INTEGER array	
45	Note that in Fortran these constants are not usable for in	nitialization
46	expressions or assignment. See Section 2.5.4.	
	CIPIONICIA OI MONIAIIIOIIII NOO NOOTOII	

# C Constants Specifying Ignored Input (no Fortran)

\mpictype

\mpictype

	. ,
C type: MPI_Fint*	equivalent to Fortran
MPI_F_STATUSES_IGNORE	MPI_STATUSES_IGNORE in mpi / mpif.h
MPI_F_STATUS_IGNORE	${\sf MPI\_STATUS\_IGNORE~in~mpi~/~mpif.h}$
C type: MPI_F08_status*	equivalent to Fortran
MPI_F08_STATUSES_IGNORE	MPI_STATUSES_IGNORE in mpi_f08
MPI_F08_STATUS_IGNORE	MPI_STATUS_IGNORE in mpi_f08

# C preprocessor Constants and Fortran Parameters

C type: C-preprocessor macro that expands to an int value
Fortran type: INTEGER
MPI\_SUBVERSION
MPI\_VERSION

#### Null handles used in the MPI tool information interface

MPI\_T\_ENUM\_NULL
MPI\_T\_enum

MPI\_T\_CVAR\_HANDLE\_NULL
MPI\_T\_cvar\_handle

MPI\_T\_PVAR\_HANDLE\_NULL
MPI\_T\_pvar\_handle

MPI\_T\_PVAR\_SESSION\_NULL
MPI\_T\_pvar\_session

# Verbosity Levels in the MPI tool information interface

C type: const int (or unnamed enum)
MPI\_T\_VERBOSITY\_USER\_BASIC
MPI\_T\_VERBOSITY\_USER\_DETAIL
MPI\_T\_VERBOSITY\_USER\_ALL
MPI\_T\_VERBOSITY\_TUNER\_BASIC
MPI\_T\_VERBOSITY\_TUNER\_DETAIL
MPI\_T\_VERBOSITY\_TUNER\_ALL
MPI\_T\_VERBOSITY\_MPIDEV\_BASIC
MPI\_T\_VERBOSITY\_MPIDEV\_DETAIL
MPI\_T\_VERBOSITY\_MPIDEV\_DETAIL
MPI\_T\_VERBOSITY\_MPIDEV\_ALL

#-error Done in PR444

1	Constants to identify associations of variables	
2	in the MPI tool information interface	
3	C type: const int (or unnamed enum)	
4	MPI_T_BIND_NO_OBJECT	
5	MPI_T_BIND_MPI_COMM	
6	MPI_T_BIND_MPI_DATATYPE	
7	MPI_T_BIND_MPI_ERRHANDLER	
8	MPI_T_BIND_MPI_FILE	
9	MPI_T_BIND_MPI_GROUP	
10	MPI_T_BIND_MPI_OP	
11	MPI_T_BIND_MPI_REQUEST	
12	MPI_T_BIND_MPI_WIN	
13	MPI_T_BIND_MPI_MESSAGE	
14	MPI_T_BIND_MPI_INFO	
15		
16	Constants describing the scope of a control variable	
17	in the MPI tool information interface	
18	C type: const int (or unnamed enum)	
19	MPI_T_SCOPE_CONSTANT	
20	MPI_T_SCOPE_READONLY	
21	MPI_T_SCOPE_LOCAL	
22	MPI_T_SCOPE_GROUP	
23	MPI_T_SCOPE_GROUP_EQ	
24	MPI_T_SCOPE_ALL	
25	MPI_T_SCOPE_ALL_EQ	
26		
27	Additional constants used	
28	by the MPI tool information interface	
29	C type: MPI_T_pvar_handle	
30	MPI_T_PVAR_ALL_HANDLES	
31		
32 33	Performance variables classes used by the	
34	MPI tool information interface	
35	C type: const int (or unnamed enum)	
	MPI_T_PVAR_CLASS_STATE	
36 27	MPI_T_PVAR_CLASS_LEVEL	
37	MPI_T_PVAR_CLASS_SIZE	
38	MPI_T_PVAR_CLASS_PERCENTAGE	
39	MPI_T_PVAR_CLASS_HIGHWATERMARK	
40	MPI_T_PVAR_CLASS_LOWWATERMARK	
41	MPI_T_PVAR_CLASS_COUNTER	
42	MPI_T_PVAR_CLASS_AGGREGATE	
43	MPI_T_PVAR_CLASS_TIMER	
44	MPI_T_PVAR_CLASS_GENERIC	
45		

```
Source event ordering guarantees in the
                                                                                               #-???
                      MPI tool information interface
                      C type: MPI_T_source_order
                      MPI_T_SOURCE_ORDERED
                      MPI_T_SOURCE_UNORDERED
                  Callback safety requirement levels used in the
                  MPI tool information interface
                                                                                               ¥-error
                  C type: MPI_T_cb_safety
                                                                                               #-835
                  MPI_T_CB_REQUIRE_NONE
                                                                                               #-358+359
                                                            31 character
                  MPI_T_CB_REQUIRE_MPI_RESTRICTED
                                                                                               2.2. p10
                                                                                            12 18.1 p.777
                  MPI_T_CB_REQUIRE_THREAD_SAFE
                                                                                            13 19.1.5 p 89
                  MPI_T_CB_REQUIRE_ASYNC_SIGNAL_SAFE 34 character !!!
                                                                                             <sub>14</sub> B.1.2 p.10 1ff
                       Proposal: Change to MPI_T_CB_REQUIRE_ASYNC_SIG_SAFE (31 character)
                                                                                             15
A.1.2 Types
                                                                                             16
The following are defined C type definitions/included in the file mpi.h.
                                                                                                #-error
                                                                                             17
                                                                                                #-375
/* C opaque types */
                                                                                                #-update12
                                                                                             19
MPI_Aint
                                                                                            20
MPI_Count
                                                                                                Done
                                                                                            21
                                                                                                in
MPI_Fint
                                                                                                PR497
                                                                                             22
MPI_Offset
                                                                                            23
MPI_Status
                                                                                             24
MPI_F08_status
                                                                                             25
                                                                                             26
/* C handles to assorted structures *,
                                                                                             27
MPI_Comm
                                                                                             28
MPI_Datatype
                                                                                             29
MPI_Errhandler
                                                                                             30
MPI_File
                                                                                             31
MPI_Group
MPI_Info
                                                                                             33
MPI_Message
                                                                                            34
MPI_Op
                                                                                            35
MPI_Request
                                                                                                #-???
                                                                                             36
MPI_Session
                                                                                             37
MPI_Win
                                                                                             38
                                                                                             39
/* Types for the MPI_T interface */
MPI_T_enum
                                                                                             41
MPI_T_cvar_handle
                                                                                             42
MPI_T_pvar_handle
                                                                                             43
MPI_T_pvar_session
                                                                                               #-???
                                                                                             44
MPI_T_event_instance
                                                                                             45
MPI_T_event_registration
                                                                                             46
MPI_T_source_order
                                                                                             47
MPI_T_cb_safety
```

```
#-error
#-375
#-update12
                    The following are defined Fortran type definitions, included in the mpi_f08 and mpi
Done
                modules.
in
PR497
                ! Fortran opaque types in the mpi_f08 and mpi modules
   #-error
                TYPE(MPI_Status)
  Done
  lin
                   Fortran handles in the mpi_f08 and mpi modules
  PR444
                TYPE(MPI_Comm)
          10
                TYPE(MPI_Datatype)
                                         All such terms additionally indexed
                TYPE(MPI_Errhandler)
          12
                                         though \cdeclindex(MPI Xxxxxx).
                TYPE(MPI_File)
                                         and these should be removed.
          13
                TYPE(MPI_Group)
          14
                TYPE(MPI_Info)
          15
                TYPE(MPI_Message)
          16
                TYPE(MPI_Op)
          17
                TYPE(MPI_Request)
          18
                TYPE(MPI_Session)
          19
                TYPE(MPI_Win)
          21
                A.1.3 Prototype Definitions
          22
          23
                C Bindings
          24
                The following are defined C typedefs for user-defined functions, also included in the file
          25
                mpi.h.
          26
          27
                /* prototypes for user-defined functions */
          28
                typedef void MPI_User_function(void *invec, void *inoutvec, int *len,
          29
                              MPI_Datatype *datatype);
          30
          31
                typedef void MPI_User_function_c(void *invec, void *inoutvec,
          32
                              MPI_Count *len, MPI_Datatype *datatype);
          33
          34
                typedef int MPI_Comm_copy_attr_function(MPI_Comm oldcomm, int comm_keyval,
                              void *extra_state, void *attribute_val_in,
          35
                              void *attribute_val_out, int *flag);
          36
          37
                typedef int MPI_Comm_delete_attr_function(MPI_Comm comm, int comm_keyval,
          38
                               void *attribute_val, void *extra_state);
          39
                typedef int MPI_Win_copy_attr_function(MPI_Win oldwin, int win_keyval,
          41
                              void *extra_state, void *attribute_val_in,
          42
                              void *attribute_val_out, int *flag);
          43
                typedef int MPI_Win_delete_attr_function(MPI_Win win, int win_keyval,
          44
                              void *attribute_val, void *extra_state);
          45
          46
                typedef int MPI_Type_copy_attr_function(MPI_Datatype oldtype,
          47
                               int type_keyval, void *extra_state, void *attribute_val_in,
                              void *attribute_val_out, int *flag);
```

checked and may be removed.

in PR449

Many out-commented

```
typedef int MPI_Type_delete_attr_function(MPI_Datatype datatype,
                                                                                   lines starting with
                                                                                   %DAN-PyMerge%...
                   int type_keyval, void *attribute_val, void *extra_state);
                                                                                   should be deleted???
MPI_Session_delete_attr_function(...) is NOT missing
    typedef void MPI_Comm_errhandler_function(MPI_Comm *comm, int *error_code,
                                                                                            4 #-error!
                                                                                               Done
                                                                                            5
                                                                                               lin
    typedef void MPI_Win_errhandler_function(MPI_Win *win, int *error_code,
                                                                                               PR444
    typedef void MPI_File_errhandler_function(MPI_File *file, int *error_code,
                   ...);
                                                                                            10
                                                                                            11
   typedef void MPI_Session_errhandler_function(MPI_Session *session,
                                                                                            12
                  int *error_code, ...);
                                                                                            13
    typedef int MPI_Grequest_query_function(void *extra_state,
                                                                                            14
                  MPI_Status *status);
                                                                                            15
                                                                                            16
    typedef int MPI_Grequest_free_function(void *extra_state);
    typedef int MPI_Grequest_cancel_function(void *extra_state, int complete);
                                                                                            19
    typedef int MPI_Datarep_extent_function(MPI_Datatype datatype,
                                                                                            20
                  MPI_Aint *extent, void *extra_state);
                                                                                           21
    typedef int MPI_Datarep_conversion_function(void *userbuf,
                                                                                           22
                  MPI_Datatype datatype, int count, void *filebuf,
                                                                                           23
                  MPI_Offset position, void *extra_state);
                                                                                            24
    typedef int MPI_Datarep_conversion_function_c(void *userbuf,
                                                                                           <sub>26</sub> #-...
                  MPI_Datatype datatype, MPI_Count count, void *filebuf,
                                                                                           27
                  MPI_Offset position, void *extra_state);
                                                                                            28
                                                                                           29
    typedef void MPI_T_event_cb_function(
                                                                                            30
                                                                                              #-PR409
                  MPI_T_event_instance event_instance,
                                                                                              #-update4
                  MPI_T_event_registration event_registration,
                                                                                           32
                                                                                               Done
                  MPI_T_cb_safety cb_safety,
                                                                                           33
                                                                                               in
                  void *user_data);
                                                                                           34
                                                                                               PR409
                                                                   Formatting error:
                                                                   All three interfaces
                                                                                           35
                                                                   without
                                                                                           36
                                                                   pythonization !!!
    typedef void MPI_T_event_free_cb_function(
                                                                                            37
                                                                   Marc-Andre gives it to Rolf
                  MPI_T_event_registration event_registration,
                                                                                            38
                  MPI_T_cb_safety cb_safety,
                                                                                            39
                  void *user_data);
                                                                                            40
                                                                                            41
                                                                                            42
    typedef void MPI_T_event_dropped_cb_function(int count,
                                                                                           43
                  MPI_T_event_registration event_registration,
                                                                                               Done
                                                                                            44
                                                          int source_index,
                  MPI_T_cb_safety cb_safety,
                                                                                               lin
                                                                                           45
                  void *user_data);
                                                         is missing
                                                                                               PR409
                                                                    After the merge of PR409,
                                                                                                Done
                                                                    the remaining \typedef.. must be
```

Fortran 2008 Bindings with the mpi\_f08 Module

```
Done
lin
PR497
#-error
#-375
#-update12
  #-error!
  #-update5
   Done
   in
   PR444
```

```
and MPI_Op_create_c
      The callback prototypes when using the Fortran mpi/f08 module are shown below:
          The user-function argument to MPI_Op_create should be declared according to:
     ABSTRACT INTERFACE
        SUBROUTINE MPI_User_function(invec, inoutvec, len, datatype)
          USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
7
          TYPE(C_PTR), VALUE :: invec, inoutvec All mpi_f08 call back prototypes will be referenced in the
          INTEGER :: len
                                                   callback function prototype index
          TYPE(MPI_Datatype) :: datatype
10
11
      ABSTRACT INTERFACE
12
        SUBROUTINE MPI_User_function_c(invec, inoutvec, len, datatype)
13
          USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
14
          TYPE(C_PTR), VALUE :: invec, inoutvec
15
          INTEGER(KIND=MPI_COUNT_KIND) :: len
16
          TYPE(MPI_Datatype) :: datatype
17
          The copy and delete function arguments to MPI_Comm_create_keyval should be de-
18
     clared according to:
19
      ABSTRACT INTERFACE
20
        SUBROUTINE MPI_Comm_copy_attr_function(oldcomm, comm_keyval, extra_state,
21
                     attribute_val_in, attribute_val_out, flag, ierror)
22
          TYPE(MPI_Comm) :: oldcomm
23
          INTEGER :: comm_keyval, ierror
24
          INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
                     attribute_val_out
26
          LOGICAL :: flag
27
28
      ABSTRACT INTERFACE
29
        SUBROUTINE MPI_Comm_delete_attr_function(comm, comm_keyval,
30
                     attribute_val, extra_state, ierror)
31
          TYPE(MPI_Comm) :: comm
32
          INTEGER :: comm_keyval, ierror
33
          INTEGER(KIND=MPI_ADDRESS_KIND) :: attribute_val, extra_state
34
          The copy and delete function arguments to MPI_Win_create_keyval should be declared
35
     according to:
36
      ABSTRACT INTERFACE
37
        SUBROUTINE MPI_Win_copy_attr_function(oldwin, win_keyval, extra_state,
38
                     attribute_val_in, attribute_val_out, flag, ierror)
39
          TYPE(MPI_Win) :: oldwin
          INTEGER :: win_keyval, ierror
          INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
42
                     attribute_val_out
43
          LOGICAL :: flag
44
45
      ABSTRACT INTERFACE
46
        SUBROUTINE MPI_Win_delete_attr_function(win, win_keyval, attribute_val,
47
                     extra_state, ierror)
```

```
TYPE(MPI_Win) :: win
                                                                                Many out-commented
    INTEGER :: win_keyval, ierror
                                                                               lines starting with
                                                                                %DAN-PyMerge%...
    INTEGER(KIND=MPI_ADDRESS_KIND) :: attribute_val, extra_state
                                                                                should be deleted???
MPI Session delete attr function(...) is NOT missing
    The copy and delete function arguments to MPI_Type_create_keyval should be declared
                                                                                         5 #-error!
according to:
                                                                                         6
                                                                                            Done
ABSTRACT INTERFACE
                                                                                            in
  SUBROUTINE MPI_Type_copy_attr_function(oldtype, type_keyval, extra_state,
                                                                                            PR444
               attribute_val_in, attribute_val_out, flag, ierror)
    TYPE(MPI_Datatype) :: oldtype
    INTEGER :: type_keyval, ierror
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
                                                                                        12
               attribute_val_out
                                                                                        13
    LOGICAL :: flag
                                                                                        14
                                                                                        15
ABSTRACT INTERFACE
                                                                                        16
  SUBROUTINE MPI_Type_delete_attr_function(datatype, type_keyval,
               attribute_val, extra_state, ierror)
    TYPE(MPI_Datatype) :: datatype
                                                                                        19
    INTEGER :: type_keyval, ierror
                                                                                        20
    INTEGER(KIND=MPI_ADDRESS_KIND) :: attribute_val, extra_state
                                                                                        21
    The handler-function argument to MPI_Comm_create_errhandler should be declared
                                                                                        22
like this:
                                                                                        23
ABSTRACT INTERFACE
                                                                                        24
  SUBROUTINE MPI_Comm_errhandler_function(comm, error_code)
                                                                                        25
    TYPE(MPI_Comm) :: comm
                                                                                        26
    INTEGER :: error_code
                                                                                        27
                                                                                        28
    The handler-function argument to MPI_Win_create_errhandler should be declared like
                                                                                        29
this:
                                                                                        30
ABSTRACT INTERFACE
  SUBROUTINE MPI_Win_errhandler_function(win, error_code)
    TYPE(MPI_Win) :: win
    INTEGER :: error_code
    The handler-function argument to MPI_File_create_errhandler should be declared like
this:
                                                                                        36
ABSTRACT INTERFACE
                                                                                        37
  SUBROUTINE MPI_File_errhandler_function(file, error_code)
                                                                                        38
    TYPE(MPI_File) :: file
                                                                                        39
    INTEGER :: error_code
                                                                                        40
                                                                                        41
ABSTRACT INTERFACE
                                                                   Old-style-formatted
                                                                                        42
  SUBROUTINE_MPI_File_errhandler_function(file, error_code)
                                                                   duplicate should be
                                                                                           #-error!
                                                                   removed
                                                                                        43
    TYPE(MPI_File) :: file
                                                                                            Done
    INTEGER :: error_code
                                                                                            in
                                                                                            PR444
                                                                                        4.5
    The handler-function argument to MPI_Session_create_errhandler should be declared
                                                                                        46
like this:
                                                                                        47
```

ABSTRACT INTERFACE

lin

#-375

```
SUBROUTINE MPI_Session_errhandler_function(session, error_code)
                    TYPE(MPI_Session) :: session
                    INTEGER :: error_code
                ABSTRACT INTERFACE
  #-error!
                  SUBROUTINE_MF1_Session_errhandler_function(session, error_code) Old-style-formatted
  Done
                    TYPE(MPI Session) :: session
                                                                                       duplicate should be
                                                                                       removed
  PR444
                    INTEGER :: error_code
                    The query, free, and cancel function arguments to MPI_Grequest_start should be de-
           10
                clared according to:
           11
                ABSTRACT INTERFACE
          12
                  SUBROUTINE MPI_Grequest_query_function(extra_state, status, ierror)
           13
                    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state
          14
                    TYPE(MPI_Status) :: status
           15
                    INTEGER :: ierror
          16
                ABSTRACT INTERFACE
           17
                  SUBROUTINE MPI_Grequest_free_function(extra_state, ierror)
           18
                    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state
           19
                    INTEGER :: ierror
          20
          21
                ABSTRACT INTERFACE
          22
                  SUBROUTINE MPI_Grequest_cancel_function(extra_state, complete, ierror)
          23
                    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state
           24
                    LOGICAL :: complete
#-error
                    INTEGER :: ierror
                                                                                     and MPI_Register_datarep_c
                    The extent and conversion function arguments to MPI_Register_datarep'should be de-
#-update12
          27
                clared according to:
   Done
           28
   lin
                ABSTRACT INTERFACE
          29
   PR497
                  SUBROUTINE MPI_Datarep_extent_function(datatype, extent, extra_state,
           30
                               ierror)
          31
                    TYPE(MPI_Datatype) :: datatype
           32
                    INTEGER(KIND=MPI_ADDRESS_KIND) :: extent, extra_state
          33
                    INTEGER :: ierror
          34
          35
                ABSTRACT INTERFACE
          36
                  SUBROUTINE MPI_Datarep_conversion_function(userbuf, datatype, count,
          37
                               filebuf, position, extra_state, ierror)
          38
                    USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
          39
                    TYPE(C_PTR), VALUE :: userbuf, filebuf
                    TYPE(MPI_Datatype) :: datatype
          41
                    INTEGER :: count, ierror
          42
                    INTEGER(KIND=MPI_OFFSET_KIND) :: position
          43
                    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state
           44
      #-... 45
                ABSTRACT INTERFACE
                  SUBROUTINE MPI_Datarep_conversion_function_c(userbuf, datatype, count,
           46
                               filebuf, position, extra_state, ierror)
           47
                    USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
```

#-error!

in

10

12

13

14

15

16

17

19

20

21

22

23

27

28

34

35

37

42

43

44

45

46

#-update5

**PR444** 

TYPE(C\_PTR), VALUE :: userbuf, filebuf #-... TYPE(MPI\_Datatype) :: datatype INTEGER(KIND=MPI\_COUNT\_KIND) :: count INTEGER(KIND=MPI\_OFFSET\_KIND) :: position INTEGER(KIND=MPI\_ADDRESS\_KIND) :: extra\_state INTEGER :: ierror All mpi\_f08 call back prototypes will be Fortran Bindings with mpif.h or the mpi Module referenced in the callback function prototype With the Fortran mpi module or mpif.h, here are examples of how each of the user-defined subroutines should be declared. The user-function argument to MPI\_OP\_CREATE should be declared like this: Done — SUBROUTINE USER\_FUNCTION(INVEC, INOUTVEC, LEN, DATATYPE) lin PR449 <type> INVEC(LEN), INOUTVEC(LEN) INTEGER LEN, DATATYPE The copy and delete function arguments to MPI\_COMM\_CREATE\_KEYVAL should be declared like these: SUBROUTINE COMM\_COPY\_ATTR\_FUNCTION(OLDCOMM, COMM\_KEYVAL, EXTRA\_STATE, ATTRIBUTE\_VAL\_IN, ATTRIBUTE\_VAL\_OUT, FLAG, IERROR) INTEGER OLDCOMM, COMM\_KEYVAL, IERROR INTEGER(KIND=MPI\_ADDRESS\_KIND) EXTRA\_STATE, ATTRIBUTE\_VAL\_IN, ATTRIBUTE\_VAL\_OUT LOGICAL FLAG SUBROUTINE COMM\_DELETE\_ATTR\_FUNCTION(COMM, COMM\_KEYVAL, ATTRIBUTE\_VAL, EXTRA\_STATE, IERROR) INTEGER COMM, COMM\_KEYVAL, IERROR INTEGER(KIND=MPI\_ADDRESS\_KIND) ATTRIBUTE\_VAL, EXTRA\_STATE The copy and delete function arguments to MPI\_WIN\_CREATE\_KEYVAL should be declared like these: SUBROUTINE WIN\_COPY\_ATTR\_FUNCTION(OLDWIN, WIN\_KEYVAL, EXTRA\_STATE, ATTRIBUTE\_VAL\_IN, ATTRIBUTE\_VAL\_OUT, FLAG, IERROR) INTEGER OLDWIN, WIN\_KEYVAL, IERROR INTEGER(KIND=MPI\_ADDRESS\_KIND) EXTRA\_STATE, ATTRIBUTE\_VAL\_IN, ATTRIBUTE\_VAL\_OUT LOGICAL FLAG SUBROUTINE WIN\_DELETE\_ATTR\_FUNCTION(WIN, WIN\_KEYVAL, ATTRIBUTE\_VAL, EXTRA\_STATE, IERROR) INTEGER WIN, WIN\_KEYVAL, IERROR INTEGER(KIND=MPI\_ADDRESS\_KIND) ATTRIBUTE\_VAL, EXTRA\_STATE The delete function argument to MPI\_SESSION\_CREATE\_KEYVAL should be declared

#-error! Done in PR444

SUBROUTINE SESSION\_DELETE\_ATTR\_FUNCTION(SESSION, SESSION\_KEYVAL, ATTRIBUTE\_VAL, EXTRA\_STATE, IERROR)

INTEGER SESSION, SESSION\_KEYVAL, IERROR

like this:

MPI\_Session\_delete\_attr\_function(...) is NOT needed


Done

PR444

```
1
              INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
      2
               The copy and delete function arguments to MPI_TYPE_CREATE_KEYVAL should be
           declared like these:
           SUBROUTINE TYPE_COPY_ATTR_FUNCTION(OLDTYPE, TYPE_KEYVAL, EXTRA_STATE,
                          ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)
               INTEGER OLDTYPE, TYPE_KEYVAL, IERROR
                INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
                          ATTRIBUTE_VAL_OUT
               LOGICAL FLAG
      10
      11
           SUBROUTINE TYPE DELETE ATTR FUNCTION(DATATYPE, TYPE KEYVAL, ATTRIBUTE VAL.
      12
                          EXTRA_STATE, IERROR)
      13
               INTEGER DATATYPE, TYPE_KEYVAL, IERROR
      14
               INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
      15
      16
               The handler-function argument to MPI_COMM_CREATE_ERRHANDLER should be de-
      17
           clared like this:
      18
           SUBROUTINE COMM_ERRHANDLER_FUNCTION(COMM, ERROR_CODE)
      19
               INTEGER COMM, ERROR_CODE
      20
               The handler-function argument to MPI_WIN_CREATE_ERRHANDLER should be de-
      21
           clared like this:
      22
           SUBROUTINE WIN_ERRHANDLER_FUNCTION(WIN, ERROR_CODE)
      23
                INTEGER WIN, ERROR_CODE
      24
               The handler-function argument to MPI_FILE_CREATE_ERRHANDLER should be de-
      25
      26
           clared like this:
      27
           SUBROUTINE FILE_ERRHANDLER_FUNCTION(FILE, ERROR_CODE)
                INTEGER FILE, ERROR_CODE
      29
               The handler-function argument to MPI_SESSION_CREATE_ERRHANDLER should be
      30
           declared like this:
                                                                             Many out-commented
      31
           SUBROUTINE SESSION_ERRHANDLER_FUNCTION(SESSION, ERROR_CODE)
                                                                             lines starting with
      32
                                                                              %DAN-PyMerge%...
                INTEGER SESSION, ERROR_CODE
      33
                                                                              should be deleted???
#-error! 34
               The query, free, and cancel function arguments to MPI_GREQUEST_START should be
      35
           declared like these:
      36
           SUBROUTINE GREQUEST_QUERY_FUNCTION(EXTRA_STATE, STATUS, IERROR)
      37
                INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
      38
                INTEGER STATUS (MPI_STATUS_SIZE), IERROR
      39
           SUBROUTINE GREQUEST_FREE_FUNCTION(EXTRA_STATE, IERROR)
      40
                INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
      41
                INTEGER IERROR
      42
      43
           SUBROUTINE GREQUEST_CANCEL_FUNCTION(EXTRA_STATE, COMPLETE, IERROR)
      44
                INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
      45
               LOGICAL COMPLETE
      46
               INTEGER IERROR
      47
```

```
The extent and conversion function arguments to MPI_REGISTER_DATAREP should
be declared like these:
SUBROUTINE DATAREP_EXTENT_FUNCTION(DATATYPE, EXTENT, EXTRA_STATE, IERROR)
    INTEGER DATATYPE, IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTENT, EXTRA_STATE
SUBROUTINE DATAREP_CONVERSION_FUNCTION(USERBUF, DATATYPE, COUNT, FILEBUF,
               POSITION, EXTRA_STATE, IERROR)
    <TYPE> USERBUF(*), FILEBUF(*)
    INTEGER DATATYPE, COUNT, IERROR
    INTEGER(KIND=MPI_OFFSET_KIND) POSITION
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
                                                                                        12
                                                                                        13
                                                                                        14
A.1.4 Deprecated Prototype Definitions
                                                                                        15
The following are defined C typedefs for deprecated user-defined functions, also included in
the file mpi.h.
                                                                                        18
/* prototypes for user-defined functions */
                                                                                        19
                                                                                        20
typedef int MPI_Copy_function(MPI_Comm oldcomm, int keyval,
                                                                                        21
               void *extra_state, void *attribute_val_in,
                                                                                        22
               void *attribute_val_out, int *flag);
                                                                                        23
                                                                                        24
typedef int MPI_Delete_function(MPI_Comm comm, int keyval,
               void *attribute_val, void *extra_state);
    The following are deprecated Fortran user-defined callback subroutine prototypes. The
                                                                                        27
deprecated copy and delete function arguments to MPI_KEYVAL_CREATE should be de-
                                                                                        28
clared like these:
                                                                                        29
SUBROUTINE COPY_FUNCTION(OLDCOMM, KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,
                                                                                        30
               ATTRIBUTE_VAL_OUT, FLAG, IERR)
    INTEGER OLDCOMM, KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,
               ATTRIBUTE_VAL_OUT, IERR
    LOGICAL FLAG
                                                                                        34
                                                                                        35
SUBROUTINE DELETE_FUNCTION(COMM, KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE, IERR)
                                                                                        36
    INTEGER COMM, KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE, IERR
                                                                                           #-update5
A.1.5 Process Set Names
                                                                                             Done
A.1.5 Info Keys
                                                                                        39
                                                                                             lin
                                                                                             PR444
The following info keys are reserved. They are strings.
                                                   Other constants in the Index of Constants:
"access_style"
"accumulate_ops"
                                                    "hwloc://L3Cache" example for a PSET names
"accumulate_ordering"
                                                    "mpi://" reserved namespace for standardized PSET names
"alloc_shared_noncontig"
                                                                     standardized
                                                    "mpi://SELF"
"appnum"
                                                                     PSET names
                                                    "mpi://WORLD"
"arch"
                                                    "mpix://UNIVERSE" example for a PSET names
"cb_block_size"
                                                    "mpi_thread_support_level"
```

**Unofficial Draft for Comment Only** 



```
"reverse_sequential"
"same_op"
"same_op_no_op"
"sequential"
"true"
"war"
"waw"
"write_mostly"
"write_once"
```

## A.2 Summary of the Semantics of all Operation-Related MPI Procedures

A summary of the semantics of all operation-related MPI procedures can be found in [51].



## A.3 C Bindings

A.3.1 Point-to-Point Communication C Bindings missing --> Issue #4

The MPI-3.1 hyperrefs to the routine specification itself and to the primary references for all MPI type declarations are missing --> Issue #413

#-error! #-413 #-422

#-TODO

int MPI\_Buffer\_attach(void \*buffer, int size)

int MPI\_Buffer\_attach\_c(void \*buffer, MPI\_Count size)

int MPI\_Buffer\_detach(void \*buffer\_addr, int \*size)

int MPI\_Buffer\_detach\_c(void \*buffer\_addr, MPI\_Count \*size)

int MPI\_Cancel(MPI\_Request \*request)

- int MPI\_Probe(int source, int tag, MPI\_Comm comm, MPI\_Status \*status)

- int MPI\_Request\_free(MPI\_Request \*request)
- int MPI\_Rsend(const void \*buf, int count, MPI\_Datatype datatype, int dest,

```
1
                   int tag, MPI_Comm comm)
2
     int MPI_Rsend_c(const void *buf, MPI_Count count, MPI_Datatype datatype,
3
                   int dest, int tag, MPI_Comm comm)
4
5
     int MPI_Rsend_init(const void *buf, int count, MPI_Datatype datatype,
6
                   int dest, int tag, MPI_Comm comm, MPI_Request *request)
7
     int MPI_Rsend_init_c(const void *buf, MPI_Count count,
8
                   MPI_Datatype datatype, int dest, int tag, MPI_Comm comm,
9
                   MPI_Request *request)
10
11
     int MPI_Send(const void *buf, int count, MPI_Datatype datatype, int dest,
12
                   int tag, MPI_Comm comm)
13
     int MPI_Send_c(const void *buf, MPI_Count count, MPI_Datatype datatype,
14
                   int dest, int tag, MPI_Comm comm)
15
16
     int MPI_Send_init(const void *buf, int count, MPI_Datatype datatype,
17
                   int dest, int tag, MPI_Comm comm, MPI_Request *request)
18
     int MPI_Send_init_c(const void *buf, MPI_Count count,
19
                   MPI_Datatype datatype, int dest, int tag, MPI_Comm comm,
20
                   MPI_Request *request)
21
22
     int MPI_Sendrecv(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
23
                   int dest, int sendtag, void *recvbuf, int recvcount,
^{24}
                   MPI_Datatype recvtype, int source, int recvtag, MPI_Comm comm,
25
                   MPI_Status *status)
26
     int MPI_Sendrecv_replace(void *buf, int count, MPI_Datatype datatype,
27
                   int dest, int sendtag, int source, int recvtag, MPI_Comm comm,
28
                   MPI_Status *status)
29
30
     int MPI_Ssend(const void *buf, int count, MPI_Datatype datatype, int dest,
31
                   int tag, MPI_Comm comm)
32
     int MPI_Ssend_c(const void *buf, MPI_Count count, MPI_Datatype datatype,
33
34
                   int dest, int tag, MPI_Comm comm)
35
     int MPI_Ssend_init(const void *buf, int count, MPI_Datatype datatype,
36
                   int dest, int tag, MPI_Comm comm, MPI_Request *request)
37
     int MPI_Ssend_init_c(const void *buf, MPI_Count count,
38
                   MPI_Datatype datatype, int dest, int tag, MPI_Comm comm,
39
                  MPI_Request *request)
41
     int MPI_Start(MPI_Request *request)
42
     int MPI_Startall(int count, MPI_Request array_of_requests[])
43
44
     int MPI_Test(MPI_Request *request, int *flag, MPI_Status *status)
45
^{46}
     int MPI_Test_cancelled(const MPI_Status *status, int *flag)
47
     int MPI_Testall(int count, MPI_Request array_of_requests[], int *flag,
```

MPI\_Status array\_of\_statuses[])

```
int MPI_Testany(int count, MPI_Request array_of_requests[], int *index,
              int *flag, MPI_Status *status)
int MPI_Testsome(int incount, MPI_Request array_of_requests[],
              int *outcount, int array_of_indices[],
              MPI_Status array_of_statuses[])
int MPI_Wait(MPI_Request *request, MPI_Status *status)
int MPI_Waitall(int count, MPI_Request array_of_requests[],
              MPI_Status array_of_statuses[])
                                                                                   12
int MPI_Waitany(int count, MPI_Request array_of_requests[], int *index,
                                                                                   13
              MPI_Status *status)
                                                                                   14
                                                                                   15
int MPI_Waitsome(int incount, MPI_Request array_of_requests[],
                                                                                   16
              int *outcount, int array_of_indices[],
              MPI_Status array_of_statuses[])
                                                                                   18
                                                                                   19
A.3.2 Partitioned Communication C Bindings
                                                                                   20
                                                                                   21
int MPI_Parrived(MPI_Request *request, int partition, int *flag)
                                                                                   22
int MPI_Pready(int partition, MPI_Request *request)
                                                                                   23
                                                                                   24
int MPI_Pready_list(int length, int array_of_partitions[],
              MPI_Request *request)
                                                                                   26
int MPI_Pready_range(int partition_low, int partition_high,
                                                                                   27
              MPI_Request *request)
                                                                                   28
                                                                                   29
int MPI_Precv_init(void *buf, int partitions, MPI_Count count,
                                                                                   30
              MPI_Datatype datatype, int dest, int tag, MPI_Comm comm,
              MPI_Info info, MPI_Request *request)
                                                                                   33
int MPI_Psend_init(void *buf, int partitions, MPI_Count count,
                                                                                   34
             MPI_Datatype datatype, int dest, int tag, MPI_Comm comm,
                                                                                   35
              MPI_Info info, MPI_Request *request)
                                                                                   36
                                                                                   37
A.3.3 Datatypes C Bindings
                                                                                   38
                                                                                     #-error!
MPI_Aint MPI_Aint_add(MPI_Aint base, MPI_Aint disp)
                                                          These routine were lost due to
                                                          a bug in MAKE-APPLANG
MPI_Aint MPI_Aint_diff(MPI_Aint addr1, MPI_Aint addr2)
                                                                                   41
                                                                                   42 #-PR414
int MPI_Get_address(const void *location, MPI_Aint *address)
                                                                                   43 #-update2
int MPI_Get_elements(const MPI_Status *status, MPI_Datatype datatype,
                                                                                   44
                                                                                       Done
              int *count)
                                                                                   45
                                                                                       lin
                                                                                       PR431
                                                                                   46
```

47

int MPI\_Get\_elements\_c(const MPI\_Status \*status, MPI\_Datatype datatype,

MPI\_Count \*count)

```
1
     int MPI_Get_elements_x(const MPI_Status *status, MPI_Datatype datatype,
2
                  MPI_Count *count)
3
     int MPI_Pack(const void *inbuf, int incount, MPI_Datatype datatype,
                  void *outbuf, int outsize, int *position, MPI_Comm comm)
5
6
     int MPI_Pack_c(const void *inbuf, MPI_Count incount, MPI_Datatype datatype,
7
                  void *outbuf, MPI_Count outsize, MPI_Count *position,
8
                  MPI_Comm comm)
9
     int MPI_Pack_external(const char datarep[], const void *inbuf, int incount,
10
                  MPI_Datatype datatype, void *outbuf, MPI_Aint outsize,
11
                  MPI_Aint *position)
12
13
     int MPI_Pack_external_c(const char datarep[], const void *inbuf,
14
                  MPI_Count incount, MPI_Datatype datatype, void *outbuf,
15
                  MPI_Count outsize, MPI_Count *position)
16
     int MPI_Pack_external_size(const char datarep[], int incount,
17
                  MPI_Datatype datatype, MPI_Aint *size)
18
19
     int MPI_Pack_external_size_c(const char datarep[], MPI_Count incount,
20
                  MPI_Datatype datatype, MPI_Count *size)
21
     int MPI_Pack_size(int incount, MPI_Datatype datatype, MPI_Comm comm,
22
                   int *size)
23
24
     int MPI_Pack_size_c(MPI_Count incount, MPI_Datatype datatype,
25
                  MPI_Comm comm, MPI_Count *size)
26
     int MPI_Type_commit(MPI_Datatype *datatype)
27
28
     int MPI_Type_contiguous(int count, MPI_Datatype oldtype,
29
                  MPI_Datatype *newtype)
30
     int MPI_Type_contiguous_c(MPI_Count count, MPI_Datatype oldtype,
31
                  MPI_Datatype *newtype)
32
33
     int MPI_Type_create_darray(int size, int rank, int ndims,
34
                   const int array_of_gsizes[], const int array_of_distribs[],
35
                   const int array_of_dargs[], const int array_of_psizes[],
36
                   int order, MPI_Datatype oldtype, MPI_Datatype *newtype)
37
     int MPI_Type_create_darray_c(int size, int rank, int ndims,
38
                  const MPI_Count array_of_gsizes[],
39
                   const int array_of_distribs[], const int array_of_dargs[],
41
                   const int array_of_psizes[], int order, MPI_Datatype oldtype,
42
                  MPI_Datatype *newtype)
43
     int MPI_Type_create_hindexed(int count, const int array_of_blocklengths[],
44
                   const MPI_Aint array_of_displacements[], MPI_Datatype oldtype,
45
                  MPI_Datatype *newtype)
^{46}
47
     int MPI_Type_create_hindexed_block(int count, int blocklength,
                   const MPI_Aint array_of_displacements[], MPI_Datatype oldtype,
```

```
MPI_Datatype *newtype)
                                                                                  2
int MPI_Type_create_hindexed_block_c(MPI_Count count,
             MPI_Count blocklength,
             const MPI_Count array_of_displacements[],
             MPI_Datatype oldtype, MPI_Datatype *newtype)
int MPI_Type_create_hindexed_c(MPI_Count count,
             const MPI_Count array_of_blocklengths[],
             const MPI_Count array_of_displacements[],
             MPI_Datatype oldtype, MPI_Datatype *newtype)
int MPI_Type_create_hvector(int count, int blocklength, MPI_Aint stride,
                                                                                  12
             MPI_Datatype oldtype, MPI_Datatype *newtype)
                                                                                  13
                                                                                 14
int MPI_Type_create_hvector_c(MPI_Count count, MPI_Count blocklength,
                                                                                  15
             MPI_Count stride, MPI_Datatype oldtype, MPI_Datatype *newtype)
                                                                                  16
int MPI_Type_create_indexed_block(int count, int blocklength,
                                                                                  17
             const int array_of_displacements[], MPI_Datatype oldtype,
                                                                                  18
             MPI_Datatype *newtype)
                                                                                  19
                                                                                 20
int MPI_Type_create_indexed_block_c(MPI_Count count, MPI_Count blocklength,
                                                                                 21
             const MPI_Count array_of_displacements[],
                                                                                 22
             MPI_Datatype oldtype, MPI_Datatype *newtype)
                                                                                 23
int MPI_Type_create_resized(MPI_Datatype oldtype, MPI_Aint lb,
                                                                                  24
             MPI_Aint extent, MPI_Datatype *newtype)
                                                                                  26
int MPI_Type_create_resized_c(MPI_Datatype oldtype, MPI_Count lb,
                                                                                 27
             MPI_Count extent, MPI_Datatype *newtype)
                                                                                 28
int MPI_Type_create_struct(int count, const int array_of_blocklengths[],
                                                                                 29
             const MPI_Aint array_of_displacements[],
                                                                                 30
             const MPI_Datatype array_of_types[], MPI_Datatype *newtype)
                                                                                 31
int MPI_Type_create_struct_c(MPI_Count count,
                                                                                  33
             const MPI_Count array_of_blocklengths[],
                                                                                 34
             const MPI_Count array_of_displacements[],
                                                                                 35
             const MPI_Datatype array_of_types[], MPI_Datatype *newtype)
                                                                                 36
int MPI_Type_create_subarray(int ndims, const int array_of_sizes[],
                                                                                 37
             const int array_of_subsizes[], const int array_of_starts[],
                                                                                 38
             int order, MPI_Datatype oldtype, MPI_Datatype *newtype)
                                                                                  39
int MPI_Type_create_subarray_c(int ndims, const MPI_Count array_of_sizes[],
             const MPI_Count array_of_subsizes[],
                                                                                  42
             const MPI_Count array_of_starts[], int order,
                                                                                  43
             MPI_Datatype oldtype, MPI_Datatype *newtype)
                                                                                  44
int MPI_Type_dup(MPI_Datatype oldtype, MPI_Datatype *newtype)
                                                                                  45
                                                                                  46
int MPI_Type_free(MPI_Datatype *datatype)
                                                                                  47
int MPI_Type_get_contents(MPI_Datatype datatype, int max_integers,
```

```
1
                   int max_addresses, int max_datatypes, int array_of_integers[],
2
                   MPI_Aint array_of_addresses[],
3
                   MPI_Datatype array_of_datatypes[])
     int MPI_Type_get_contents_c(MPI_Datatype datatype, MPI_Count max_integers,
5
                   MPI_Count max_addresses, MPI_Count max_large_counts,
6
                   MPI_Count max_datatypes, int array_of_integers[],
7
                   MPI_Aint array_of_addresses[],
                   MPI_Count array_of_large_counts[],
9
                   MPI_Datatype array_of_datatypes[])
10
11
     int MPI_Type_get_envelope(MPI_Datatype datatype, int *num_integers,
12
                   int *num_addresses, int *num_datatypes, int *combiner)
13
     int MPI_Type_get_envelope_c(MPI_Datatype datatype, MPI_Count *num_integers,
14
                   MPI_Count *num_addresses, MPI_Count *num_large_counts,
15
                   MPI_Count *num_datatypes, int *combiner)
16
17
     int MPI_Type_get_extent(MPI_Datatype datatype, MPI_Aint *lb,
18
                  MPI_Aint *extent)
19
     int MPI_Type_get_extent_c(MPI_Datatype datatype, MPI_Count *lb,
20
                   MPI_Count *extent)
21
22
     int MPI_Type_get_extent_x(MPI_Datatype datatype, MPI_Count *lb,
23
                   MPI_Count *extent)
^{24}
     int MPI_Type_get_true_extent(MPI_Datatype datatype, MPI_Aint *true_lb,
25
                   MPI_Aint *true_extent)
26
27
     int MPI_Type_get_true_extent_c(MPI_Datatype datatype, MPI_Count *true_lb,
28
                   MPI_Count *true_extent)
29
     int MPI_Type_get_true_extent_x(MPI_Datatype datatype, MPI_Count *true_lb,
30
                   MPI_Count *true_extent)
31
32
     int MPI_Type_indexed(int count, const int array_of_blocklengths[],
33
                   const int array_of_displacements[], MPI_Datatype oldtype,
34
                   MPI_Datatype *newtype)
35
     int MPI_Type_indexed_c(MPI_Count count,
36
                   const MPI_Count array_of_blocklengths[],
37
                   const MPI_Count array_of_displacements[],
38
                   MPI_Datatype oldtype, MPI_Datatype *newtype)
39
40
     int MPI_Type_size(MPI_Datatype datatype, int *size)
41
42
     int MPI_Type_size_c(MPI_Datatype datatype, MPI_Count *size)
43
     int MPI_Type_size_x(MPI_Datatype datatype, MPI_Count *size)
44
45
     int MPI_Type_vector(int count, int blocklength, int stride,
46
                   MPI_Datatype oldtype, MPI_Datatype *newtype)
47
     int MPI_Type_vector_c(MPI_Count count, MPI_Count blocklength,
48
```

MPI\_Count stride, MPI\_Datatype oldtype, MPI\_Datatype \*newtype) int MPI\_Unpack(const void \*inbuf, int insize, int \*position, void \*outbuf, int outcount, MPI\_Datatype datatype, MPI\_Comm comm) int MPI\_Unpack\_c(const void \*inbuf, MPI\_Count insize, MPI\_Count \*position, void \*outbuf, MPI\_Count outcount, MPI\_Datatype datatype, MPI\_Comm comm) int MPI\_Unpack\_external(const char datarep[], const void \*inbuf, MPI\_Aint insize, MPI\_Aint \*position, void \*outbuf, int outcount, MPI\_Datatype datatype) 11 12 int MPI\_Unpack\_external\_c(const char datarep[], const void \*inbuf, 13 MPI\_Count insize, MPI\_Count \*position, void \*outbuf, 14 MPI\_Count outcount, MPI\_Datatype datatype) 15 16 A.3.4 Collective Communication C Bindings 18 int MPI\_Allgather(const void \*sendbuf, int sendcount, 19 MPI\_Datatype sendtype, void \*recvbuf, int recvcount, 20 MPI\_Datatype recvtype, MPI\_Comm comm) 21 int MPI\_Allgather\_c(const void \*sendbuf, MPI\_Count sendcount, 22 MPI\_Datatype sendtype, void \*recvbuf, MPI\_Count recvcount, 23 MPI\_Datatype recvtype, MPI\_Comm comm) 24 int MPI\_Allgather\_init(const void \*sendbuf, int sendcount, 26 MPI\_Datatype sendtype, void \*recvbuf, int recvcount, 27 MPI\_Datatype recvtype, MPI\_Comm comm, MPI\_Info info, 28 MPI\_Request \*request) 29 int MPI\_Allgather\_init\_c(const void \*sendbuf, MPI\_Count sendcount, 30 MPI\_Datatype sendtype, void \*recvbuf, MPI\_Count recvcount, MPI\_Datatype recvtype, MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request) 34 int MPI\_Allgatherv(const void \*sendbuf, int sendcount, 35 MPI\_Datatype sendtype, void \*recvbuf, const int recvcounts[], 36 const int displs[], MPI\_Datatype recvtype, MPI\_Comm comm) 37 int MPI\_Allgatherv\_c(const void \*sendbuf, MPI\_Count sendcount, MPI\_Datatype sendtype, void \*recvbuf, 39 const MPI\_Count recvcounts[], const MPI\_Aint displs[], MPI\_Datatype recvtype, MPI\_Comm comm) 42 int MPI\_Allgatherv\_init(const void \*sendbuf, int sendcount, 43 MPI\_Datatype sendtype, void \*recvbuf, const int recvcounts[], 44 const int displs[], MPI\_Datatype recvtype, MPI\_Comm comm, 45 MPI\_Info info, MPI\_Request \*request) 46 int MPI\_Allgatherv\_init\_c(const void \*sendbuf, MPI\_Count sendcount,

MPI\_Datatype sendtype, void \*recvbuf,

```
1
                   const MPI_Count recvcounts[], const MPI_Aint displs[],
2
                  MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
3
                  MPI_Request *request)
     int MPI_Allreduce(const void *sendbuf, void *recvbuf, int count,
5
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
6
7
     int MPI_Allreduce_c(const void *sendbuf, void *recvbuf, MPI_Count count,
8
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
9
     int MPI_Allreduce_init(const void *sendbuf, void *recvbuf, int count,
10
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
11
                  MPI_Info info, MPI_Request *request)
12
13
     int MPI_Allreduce_init_c(const void *sendbuf, void *recvbuf,
14
                  MPI_Count count, MPI_Datatype datatype, MPI_Op op,
15
                  MPI_Comm comm, MPI_Info info, MPI_Request *request)
16
     int MPI_Alltoall(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
17
                  void *recvbuf, int recvcount, MPI_Datatype recvtype,
                  MPI_Comm comm)
19
20
     int MPI_Alltoall_c(const void *sendbuf, MPI_Count sendcount,
21
                  MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
22
                  MPI_Datatype recvtype, MPI_Comm comm)
23
     int MPI_Alltoall_init(const void *sendbuf, int sendcount,
24
                  MPI_Datatype sendtype, void *recvbuf, int recvcount,
                  MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
26
                  MPI_Request *request)
27
28
     int MPI_Alltoall_init_c(const void *sendbuf, MPI_Count sendcount,
29
                  MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
30
                  MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
31
                  MPI_Request *request)
32
     int MPI_Alltoallv(const void *sendbuf, const int sendcounts[],
33
                   const int sdispls[], MPI_Datatype sendtype, void *recvbuf,
34
                   const int recvcounts[], const int rdispls[],
35
                   MPI_Datatype recvtype, MPI_Comm comm)
36
37
     int MPI_Alltoallv_c(const void *sendbuf, const MPI_Count sendcounts[],
38
                   const MPI_Aint sdispls[], MPI_Datatype sendtype,
39
                  void *recvbuf, const MPI_Count recvcounts[],
                   const MPI_Aint rdispls[], MPI_Datatype recvtype,
41
                  MPI_Comm comm)
42
     int MPI_Alltoallv_init(const void *sendbuf, const int sendcounts[],
43
                  const int sdispls[], MPI_Datatype sendtype, void *recvbuf,
44
                   const int recvcounts[], const int rdispls[],
45
                  MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
46
47
                  MPI_Request *request)
```

int MPI\_Alltoallv\_init\_c(const void \*sendbuf, const MPI\_Count sendcounts[], const MPI\_Aint sdispls[], MPI\_Datatype sendtype, void \*recvbuf, const MPI\_Count recvcounts[], const MPI\_Aint rdispls[], MPI\_Datatype recvtype, MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request) int MPI\_Alltoallw(const void \*sendbuf, const int sendcounts[], const int sdispls[], const MPI\_Datatype sendtypes[], void \*recvbuf, const int recvcounts[], const int rdispls[], const MPI\_Datatype recvtypes[], MPI\_Comm comm) 11 int MPI\_Alltoallw\_c(const void \*sendbuf, const MPI\_Count sendcounts[], const MPI\_Aint sdispls[], const MPI\_Datatype sendtypes[], 12 13 void \*recvbuf, const MPI\_Count recvcounts[], 14 const MPI\_Aint rdispls[], const MPI\_Datatype recvtypes[], 15 MPI\_Comm comm) 16 int MPI\_Alltoallw\_init(const void \*sendbuf, const int sendcounts[], const int sdispls[], const MPI\_Datatype sendtypes[], 18 void \*recvbuf, const int recvcounts[], const int rdispls[], 19 const MPI\_Datatype recvtypes[], MPI\_Comm comm, MPI\_Info info, 20 MPI\_Request \*request) 21 22 int MPI\_Alltoallw\_init\_c(const void \*sendbuf, const MPI\_Count sendcounts[], 23 const MPI\_Aint sdispls[], const MPI\_Datatype sendtypes[], 24 void \*recvbuf, const MPI\_Count recvcounts[], const MPI\_Aint rdispls[], const MPI\_Datatype recvtypes[], 26 MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request) 27 int MPI\_Barrier(MPI\_Comm comm) 28 29 int MPI\_Barrier\_init(MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request) 30 int MPI\_Bcast(void \*buffer, int count, MPI\_Datatype datatype, int root, 31 MPI\_Comm comm) 33 int MPI\_Bcast\_c(void \*buffer, MPI\_Count count, MPI\_Datatype datatype, 34 int root, MPI\_Comm comm) 35 int MPI\_Bcast\_init(void \*buffer, int count, MPI\_Datatype datatype, 36 int root, MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request) 37 38 int MPI\_Bcast\_init\_c(void \*buffer, MPI\_Count count, MPI\_Datatype datatype, int root, MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request) int MPI\_Exscan(const void \*sendbuf, void \*recvbuf, int count, MPI\_Datatype datatype, MPI\_Op op, MPI\_Comm comm) 42 43 int MPI\_Exscan\_c(const void \*sendbuf, void \*recvbuf, MPI\_Count count, 44 MPI\_Datatype datatype, MPI\_Op op, MPI\_Comm comm) 45 int MPI\_Exscan\_init(const void \*sendbuf, void \*recvbuf, int count, 46 MPI\_Datatype datatype, MPI\_Op op, MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request)

```
1
     int MPI_Exscan_init_c(const void *sendbuf, void *recvbuf, MPI_Count count,
2
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
3
                  MPI_Info info, MPI_Request *request)
4
     int MPI_Gather(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
5
                  void *recvbuf, int recvcount, MPI_Datatype recvtype, int root,
6
                  MPI Comm comm)
7
8
     int MPI_Gather_c(const void *sendbuf, MPI_Count sendcount,
9
                  MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
10
                  MPI_Datatype recvtype, int root, MPI_Comm comm)
11
     int MPI_Gather_init(const void *sendbuf, int sendcount,
12
                  MPI_Datatype sendtype, void *recvbuf, int recvcount,
13
                  MPI_Datatype recvtype, int root, MPI_Comm comm, MPI_Info info,
14
                  MPI_Request *request)
15
16
     int MPI_Gather_init_c(const void *sendbuf, MPI_Count sendcount,
17
                  MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
18
                  MPI_Datatype recvtype, int root, MPI_Comm comm, MPI_Info info,
19
                  MPI_Request *request)
20
     int MPI_Gatherv(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
21
                  void *recvbuf, const int recvcounts[], const int displs[],
22
                  MPI_Datatype recvtype, int root, MPI_Comm comm)
23
24
     int MPI_Gatherv_c(const void *sendbuf, MPI_Count sendcount,
25
                  MPI_Datatype sendtype, void *recvbuf,
26
                   const MPI_Count recvcounts[], const MPI_Aint displs[],
27
                  MPI_Datatype recvtype, int root, MPI_Comm comm)
28
     int MPI_Gatherv_init(const void *sendbuf, int sendcount,
29
                  MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
30
                   const int displs[], MPI_Datatype recvtype, int root,
31
                  MPI_Comm comm, MPI_Info info, MPI_Request *request)
32
33
     int MPI_Gatherv_init_c(const void *sendbuf, MPI_Count sendcount,
34
                  MPI_Datatype sendtype, void *recvbuf,
35
                   const MPI_Count recvcounts[], const MPI_Aint displs[],
36
                  MPI_Datatype recvtype, int root, MPI_Comm comm, MPI_Info info,
37
                  MPI_Request *request)
38
     int MPI_Iallgather(const void *sendbuf, int sendcount,
39
                  MPI_Datatype sendtype, void *recvbuf, int recvcount,
                  MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
41
42
     int MPI_Iallgather_c(const void *sendbuf, MPI_Count sendcount,
43
                  MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
44
                  MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
45
     int MPI_Iallgatherv(const void *sendbuf, int sendcount,
^{46}
                  MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
47
                   const int displs[], MPI_Datatype recvtype, MPI_Comm comm,
```

2

15

46

MPI\_Request \*request) int MPI\_Iallgatherv\_c(const void \*sendbuf, MPI\_Count sendcount, MPI\_Datatype sendtype, void \*recvbuf, const MPI\_Count recvcounts[], const MPI\_Aint displs[], MPI\_Datatype recvtype, MPI\_Comm comm, MPI\_Request \*request) int MPI\_Iallreduce(const void \*sendbuf, void \*recvbuf, int count, MPI\_Datatype datatype, MPI\_Op op, MPI\_Comm comm, MPI\_Request \*request) int MPI\_Iallreduce\_c(const void \*sendbuf, void \*recvbuf, MPI\_Count count, MPI\_Datatype datatype, MPI\_Op op, MPI\_Comm comm, 12 MPI\_Request \*request) 13 14 int MPI\_Ialltoall(const void \*sendbuf, int sendcount, MPI\_Datatype sendtype, void \*recvbuf, int recvcount, 16 MPI\_Datatype recvtype, MPI\_Comm comm, MPI\_Request \*request) int MPI\_Ialltoall\_c(const void \*sendbuf, MPI\_Count sendcount, 18 MPI\_Datatype sendtype, void \*recvbuf, MPI\_Count recvcount, 19 MPI\_Datatype recvtype, MPI\_Comm comm, MPI\_Request \*request) 20 21 int MPI\_Ialltoallv(const void \*sendbuf, const int sendcounts[], 22 const int sdispls[], MPI\_Datatype sendtype, void \*recvbuf, 23 const int recvcounts[], const int rdispls[], 24 MPI\_Datatype recvtype, MPI\_Comm comm, MPI\_Request \*request) int MPI\_Ialltoallv\_c(const void \*sendbuf, const MPI\_Count sendcounts[], 26 const MPI\_Aint sdispls[], MPI\_Datatype sendtype, 27 void \*recvbuf, const MPI\_Count recvcounts[], 28 const MPI\_Aint rdispls[], MPI\_Datatype recvtype, 29 MPI\_Comm comm, MPI\_Request \*request) 30 int MPI\_Ialltoallw(const void \*sendbuf, const int sendcounts[], const int sdispls[], const MPI\_Datatype sendtypes[], 33 void \*recvbuf, const int recvcounts[], const int rdispls[], 34 const MPI\_Datatype recvtypes[], MPI\_Comm comm, 35 MPI\_Request \*request) 36 int MPI\_Ialltoallw\_c(const void \*sendbuf, const MPI\_Count sendcounts[], 37 const MPI\_Aint sdispls[], const MPI\_Datatype sendtypes[], 38 void \*recvbuf, const MPI\_Count recvcounts[], 39 const MPI\_Aint rdispls[], const MPI\_Datatype recvtypes[], MPI\_Comm comm, MPI\_Request \*request) 42 int MPI\_Ibarrier(MPI\_Comm comm, MPI\_Request \*request) 43 int MPI\_Ibcast(void \*buffer, int count, MPI\_Datatype datatype, int root, 44 MPI\_Comm comm, MPI\_Request \*request) 45 int MPI\_Ibcast\_c(void \*buffer, MPI\_Count count, MPI\_Datatype datatype,

int root, MPI\_Comm comm, MPI\_Request \*request)

```
1
     int MPI_Iexscan(const void *sendbuf, void *recvbuf, int count,
2
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
3
                  MPI_Request *request)
4
     int MPI_Iexscan_c(const void *sendbuf, void *recvbuf, MPI_Count count,
5
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
6
                  MPI_Request *request)
7
8
     int MPI_Igather(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
9
                  void *recvbuf, int recvcount, MPI_Datatype recvtype, int root,
10
                  MPI_Comm comm, MPI_Request *request)
11
     int MPI_Igather_c(const void *sendbuf, MPI_Count sendcount,
12
                  MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
13
                  MPI_Datatype recvtype, int root, MPI_Comm comm,
14
                  MPI_Request *request)
15
16
     int MPI_Igatherv(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
17
                  void *recvbuf, const int recvcounts[], const int displs[],
18
                  MPI_Datatype recvtype, int root, MPI_Comm comm,
19
                  MPI_Request *request)
20
     int MPI_Igatherv_c(const void *sendbuf, MPI_Count sendcount,
21
                  MPI_Datatype sendtype, void *recvbuf,
22
                  const MPI_Count recvcounts[], const MPI_Aint displs[],
23
                  MPI_Datatype recvtype, int root, MPI_Comm comm,
24
                  MPI_Request *request)
26
     int MPI_Ireduce(const void *sendbuf, void *recvbuf, int count,
27
                  MPI_Datatype datatype, MPI_Op op, int root, MPI_Comm comm,
28
                  MPI_Request *request)
29
     int MPI_Ireduce_c(const void *sendbuf, void *recvbuf, MPI_Count count,
30
                  MPI_Datatype datatype, MPI_Op op, int root, MPI_Comm comm,
31
                  MPI_Request *request)
32
33
     int MPI_Ireduce_scatter(const void *sendbuf, void *recvbuf,
34
                   const int recvcounts[], MPI_Datatype datatype, MPI_Op op,
35
                  MPI_Comm comm, MPI_Request *request)
36
     int MPI_Ireduce_scatter_block(const void *sendbuf, void *recvbuf,
37
                   int recvcount, MPI_Datatype datatype, MPI_Op op,
38
                  MPI_Comm comm, MPI_Request *request)
39
40
     int MPI_Ireduce_scatter_block_c(const void *sendbuf, void *recvbuf,
41
                  MPI_Count recvcount, MPI_Datatype datatype, MPI_Op op,
42
                  MPI_Comm comm, MPI_Request *request)
43
     int MPI_Ireduce_scatter_c(const void *sendbuf, void *recvbuf,
44
                  const MPI_Count recvcounts[], MPI_Datatype datatype,
45
                  MPI_Op op, MPI_Comm comm, MPI_Request *request)
46
47
     int MPI_Iscan(const void *sendbuf, void *recvbuf, int count,
```

MPI\_Datatype datatype, MPI\_Op op, MPI\_Comm comm, 2 MPI\_Request \*request) int MPI\_Iscan\_c(const void \*sendbuf, void \*recvbuf, MPI\_Count count, MPI\_Datatype datatype, MPI\_Op op, MPI\_Comm comm, MPI\_Request \*request) int MPI\_Iscatter(const void \*sendbuf, int sendcount, MPI\_Datatype sendtype, void \*recvbuf, int recvcount, MPI\_Datatype recvtype, int root, MPI\_Comm comm, MPI\_Request \*request) int MPI\_Iscatter\_c(const void \*sendbuf, MPI\_Count sendcount, 11 MPI\_Datatype sendtype, void \*recvbuf, MPI\_Count recvcount, 12 MPI\_Datatype recvtype, int root, MPI\_Comm comm, 13 MPI\_Request \*request) 14 15 int MPI\_Iscatterv(const void \*sendbuf, const int sendcounts[], 16 const int displs[], MPI\_Datatype sendtype, void \*recvbuf, 17 int recvcount, MPI\_Datatype recvtype, int root, MPI\_Comm comm, 18 MPI\_Request \*request) 19 int MPI\_Iscatterv\_c(const void \*sendbuf, const MPI\_Count sendcounts[], 20 const MPI\_Aint displs[], MPI\_Datatype sendtype, void \*recvbuf, 21 MPI\_Count recvcount, MPI\_Datatype recvtype, int root, 22 MPI\_Comm comm, MPI\_Request \*request) 23 24 int MPI\_Op\_commutative(MPI\_Op op, int \*commute) int MPI\_Op\_create(MPI\_User\_function \*user\_fn, int commute, MPI\_Op \*op) 26 27 int MPI\_Op\_create\_c(MPI\_User\_function\_c \*user\_fn, int commute, MPI\_Op \*op) 28 int MPI\_Op\_free(MPI\_Op \*op) 29 30 int MPI\_Reduce(const void \*sendbuf, void \*recvbuf, int count, MPI\_Datatype datatype, MPI\_Op op, int root, MPI\_Comm comm) int MPI\_Reduce\_c(const void \*sendbuf, void \*recvbuf, MPI\_Count count, 33 MPI\_Datatype datatype, MPI\_Op op, int root, MPI\_Comm comm) 34 35 int MPI\_Reduce\_init(const void \*sendbuf, void \*recvbuf, int count, 36 MPI\_Datatype datatype, MPI\_Op op, int root, MPI\_Comm comm, 37 MPI\_Info info, MPI\_Request \*request) int MPI\_Reduce\_init\_c(const void \*sendbuf, void \*recvbuf, MPI\_Count count, MPI\_Datatype datatype, MPI\_Op op, int root, MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request) 42 int MPI\_Reduce\_local(const void \*inbuf, void \*inoutbuf, int count, 43 MPI\_Datatype datatype, MPI\_Op op) 44 int MPI\_Reduce\_local\_c(const void \*inbuf, void \*inoutbuf, MPI\_Count count, 45 MPI\_Datatype datatype, MPI\_Op op) 46 47

int MPI\_Reduce\_scatter(const void \*sendbuf, void \*recvbuf,

```
1
                   const int recvcounts[], MPI_Datatype datatype, MPI_Op op,
2
                  MPI_Comm comm)
3
     int MPI_Reduce_scatter_block(const void *sendbuf, void *recvbuf,
                   int recvcount, MPI_Datatype datatype, MPI_Op op,
5
                  MPI_Comm comm)
6
7
     int MPI_Reduce_scatter_block_c(const void *sendbuf, void *recvbuf,
8
                  MPI_Count recvcount, MPI_Datatype datatype, MPI_Op op,
9
                  MPI_Comm comm)
10
     int MPI_Reduce_scatter_block_init(const void *sendbuf, void *recvbuf,
11
                   int recvcount, MPI_Datatype datatype, MPI_Op op,
12
                  MPI_Comm comm, MPI_Info info, MPI_Request *request)
13
14
     int MPI_Reduce_scatter_block_init_c(const void *sendbuf, void *recvbuf,
15
                  MPI_Count recvcount, MPI_Datatype datatype, MPI_Op op,
16
                  MPI_Comm comm, MPI_Info info, MPI_Request *request)
17
     int MPI_Reduce_scatter_c(const void *sendbuf, void *recvbuf,
18
                   const MPI_Count recvcounts[], MPI_Datatype datatype,
19
                  MPI_Op op, MPI_Comm comm)
20
21
     int MPI_Reduce_scatter_init(const void *sendbuf, void *recvbuf,
22
                  const int recvcounts[], MPI_Datatype datatype, MPI_Op op,
23
                  MPI_Comm comm, MPI_Info info, MPI_Request *request)
^{24}
     int MPI_Reduce_scatter_init_c(const void *sendbuf, void *recvbuf,
25
                   const MPI_Count recvcounts[], MPI_Datatype datatype,
26
                  MPI_Op op, MPI_Comm comm, MPI_Info info, MPI_Request *request)
27
28
     int MPI_Scan(const void *sendbuf, void *recvbuf, int count,
29
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
30
     int MPI_Scan_c(const void *sendbuf, void *recvbuf, MPI_Count count,
31
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
32
33
     int MPI_Scan_init(const void *sendbuf, void *recvbuf, int count,
34
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
35
                  MPI_Info info, MPI_Request *request)
36
     int MPI_Scan_init_c(const void *sendbuf, void *recvbuf, MPI_Count count,
37
                  MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
                  MPI_Info info, MPI_Request *request)
39
40
     int MPI_Scatter(const void *sendbuf, int sendcount, MPI_Datatype sendtype,
                  void *recvbuf, int recvcount, MPI_Datatype recvtype, int root,
42
                  MPI_Comm comm)
43
     int MPI_Scatter_c(const void *sendbuf, MPI_Count sendcount,
44
                  MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
45
^{46}
                  MPI_Datatype recvtype, int root, MPI_Comm comm)
47
     int MPI_Scatter_init(const void *sendbuf, int sendcount,
48
```

MPI\_Datatype sendtype, void \*recvbuf, int recvcount, MPI\_Datatype recvtype, int root, MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request) int MPI\_Scatter\_init\_c(const void \*sendbuf, MPI\_Count sendcount, MPI\_Datatype sendtype, void \*recvbuf, MPI\_Count recvcount, MPI\_Datatype recvtype, int root, MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request) int MPI\_Scatterv(const void \*sendbuf, const int sendcounts[], const int displs[], MPI\_Datatype sendtype, void \*recvbuf, 11 int recvcount, MPI\_Datatype recvtype, int root, MPI\_Comm comm) 12 int MPI\_Scatterv\_c(const void \*sendbuf, const MPI\_Count sendcounts[], 13 const MPI\_Aint displs[], MPI\_Datatype sendtype, void \*recvbuf, 14 MPI\_Count recvcount, MPI\_Datatype recvtype, int root, 15 MPI\_Comm comm) 16 17 int MPI\_Scatterv\_init(const void \*sendbuf, const int sendcounts[], 18 const int displs[], MPI\_Datatype sendtype, void \*recvbuf, 19 int recvcount, MPI\_Datatype recvtype, int root, MPI\_Comm comm, 20 MPI\_Info info, MPI\_Request \*request) 21 int MPI\_Scatterv\_init\_c(const void \*sendbuf, const MPI\_Count sendcounts[], 22 const MPI\_Aint displs[], MPI\_Datatype sendtype, void \*recvbuf, 23 MPI\_Count recvcount, MPI\_Datatype recvtype, int root, 24 MPI\_Comm comm, MPI\_Info info, MPI\_Request \*request) 26 27 A.3.5 Groups, Contexts, Communicators, and Caching C Bindings 28 int MPI\_COMM\_DUP\_FN(MPI\_Comm oldcomm, int comm\_keyval, void \*extra\_state, 29 void \*attribute\_val\_in, void \*attribute\_val\_out, int \*flag) 30 31 int MPI\_COMM\_NULL\_COPY\_FN(MPI\_Comm oldcomm, int comm\_keyval, void \*extra\_state, void \*attribute\_val\_in, void \*attribute\_val\_out, int \*flag) 34 int MPI\_COMM\_NULL\_DELETE\_FN(MPI\_Comm comm, int comm\_keyval, 35 void \*attribute\_val, void \*extra\_state) 36 37 int MPI\_Comm\_compare(MPI\_Comm comm1, MPI\_Comm comm2, int \*result) 38 39 int MPI\_Comm\_create(MPI\_Comm comm, MPI\_Group group, MPI\_Comm \*newcomm) int MPI\_Comm\_create\_from\_group(MPI\_Group group, const char \*stringtag, MPI\_Info info, MPI\_Errhandler errhandler, MPI\_Comm \*newcomm) int MPI\_Comm\_create\_group(MPI\_Comm comm, MPI\_Group group, int tag, 43 44 MPI\_Comm \*newcomm) 45 int MPI\_Comm\_create\_keyval(MPI\_Comm\_copy\_attr\_function \*comm\_copy\_attr\_fn, 46 MPI\_Comm\_delete\_attr\_function \*comm\_delete\_attr\_fn, 47

int \*comm\_keyval, void \*extra\_state)

```
1
     int MPI_Comm_delete_attr(MPI_Comm comm, int comm_keyval)
2
     int MPI_Comm_dup(MPI_Comm comm, MPI_Comm *newcomm)
3
4
     int MPI_Comm_dup_with_info(MPI_Comm comm, MPI_Info info, MPI_Comm *newcomm)
5
     int MPI_Comm_free(MPI_Comm *comm)
6
7
     int MPI_Comm_free_keyval(int *comm_keyval)
8
     int MPI_Comm_get_attr(MPI_Comm comm, int comm_keyval, void *attribute_val,
9
                   int *flag)
10
11
     int MPI_Comm_get_info(MPI_Comm comm, MPI_Info *info_used)
12
     int MPI_Comm_get_name(MPI_Comm comm, char *comm_name, int *resultlen)
13
14
     int MPI_Comm_group(MPI_Comm comm, MPI_Group *group)
15
     int MPI_Comm_idup(MPI_Comm comm, MPI_Comm *newcomm, MPI_Request *request)
16
17
     int MPI_Comm_idup_with_info(MPI_Comm comm, MPI_Info info,
18
                   MPI_Comm *newcomm, MPI_Request *request)
19
     int MPI_Comm_rank(MPI_Comm comm, int *rank)
20
21
     int MPI_Comm_remote_group(MPI_Comm comm, MPI_Group *group)
22
23
     int MPI_Comm_remote_size(MPI_Comm comm, int *size)
^{24}
     int MPI_Comm_set_attr(MPI_Comm comm, int comm_keyval, void *attribute_val)
25
26
     int MPI_Comm_set_info(MPI_Comm comm, MPI_Info info)
27
     int MPI_Comm_set_name(MPI_Comm comm, const char *comm_name)
28
29
     int MPI_Comm_size(MPI_Comm comm, int *size)
30
     int MPI_Comm_split(MPI_Comm comm, int color, int key, MPI_Comm *newcomm)
31
32
     int MPI_Comm_split_type(MPI_Comm comm, int split_type, int key,
33
                   MPI_Info info, MPI_Comm *newcomm)
34
     int MPI_Comm_test_inter(MPI_Comm comm, int *flag)
35
36
     int MPI_Group_compare(MPI_Group group1, MPI_Group group2, int *result)
37
     int MPI_Group_difference(MPI_Group group1, MPI_Group group2,
38
                   MPI_Group *newgroup)
39
40
     int MPI_Group_excl(MPI_Group group, int n, const int ranks[],
41
                   MPI_Group *newgroup)
42
     int MPI_Group_free(MPI_Group *group)
43
44
     int MPI_Group_from_session_pset(MPI_Session session, const char *pset_name,
45
                   MPI_Group *newgroup)
^{46}
     int MPI_Group_incl(MPI_Group group, int n, const int ranks[],
47
                   MPI_Group *newgroup)
48
```

```
int MPI_Group_intersection(MPI_Group group1, MPI_Group group2,
                                                                                  2
             MPI_Group *newgroup)
int MPI_Group_range_excl(MPI_Group group, int n, int ranges[][3],
             MPI_Group *newgroup)
int MPI_Group_range_incl(MPI_Group group, int n, int ranges[][3],
             MPI_Group *newgroup)
int MPI_Group_rank(MPI_Group group, int *rank)
int MPI_Group_size(MPI_Group group, int *size)
int MPI_Group_translate_ranks(MPI_Group group1, int n, const int ranks1[],
                                                                                  12
             MPI_Group group2, int ranks2[])
                                                                                  13
                                                                                  14
int MPI_Group_union(MPI_Group group1, MPI_Group group2,
                                                                                  15
             MPI_Group *newgroup)
                                                                                  16
int MPI_Intercomm_create(MPI_Comm local_comm, int local_leader,
             MPI_Comm peer_comm, int remote_leader, int tag,
                                                                                  18
             MPI_Comm *newintercomm)
                                                                                  19
                                                                                  20
int MPI_Intercomm_create_from_groups(MPI_Group local_group,
                                                                                 21
             int local_leader, MPI_Group remote_group, int remote_leader,
                                                                                 22
             const char *stringtag, MPI_Info info,
                                                                                 23
             MPI_Errhandler errhandler, MPI_Comm *newintercomm)
                                                                                  24
int MPI_Intercomm_merge(MPI_Comm intercomm, int high,
                                                                                 25
             MPI_Comm *newintracomm)
                                                                                  26
                                                                                 27
int MPI_TYPE_DUP_FN(MPI_Datatype oldtype, int type_keyval,
                                                                                 28
             void *extra_state, void *attribute_val_in,
                                                                                 29
             void *attribute_val_out, int *flag)
                                                                                 30
int MPI_TYPE_NULL_COPY_FN(MPI_Datatype oldtype, int type_keyval,
                                                                                 31
             void *extra_state, void *attribute_val_in,
             void *attribute_val_out, int *flag)
                                                                                 34
int MPI_TYPE_NULL_DELETE_FN(MPI_Datatype datatype, int type_keyval,
                                                                                 35
             void *attribute_val, void *extra_state)
                                                                                 36
int MPI_Type_create_keyval(MPI_Type_copy_attr_function *type_copy_attr_fn,
                                                                                 37
             MPI_Type_delete_attr_function *type_delete_attr_fn,
                                                                                 38
             int *type_keyval, void *extra_state)
                                                                                 39
int MPI_Type_delete_attr(MPI_Datatype datatype, int type_keyval)
                                                                                 42
int MPI_Type_free_keyval(int *type_keyval)
                                                                                  43
int MPI_Type_get_attr(MPI_Datatype datatype, int type_keyval,
                                                                                  44
             void *attribute_val, int *flag)
                                                                                  45
                                                                                  46
int MPI_Type_get_name(MPI_Datatype datatype, char *type_name,
                                                                                  47
             int *resultlen)
```

```
1
     int MPI_Type_set_attr(MPI_Datatype datatype, int type_keyval,
2
                   void *attribute_val)
3
     int MPI_Type_set_name(MPI_Datatype datatype, const char *type_name)
4
5
     int MPI_WIN_DUP_FN(MPI_Win oldwin, int win_keyval, void *extra_state,
6
                   void *attribute_val_in, void *attribute_val_out, int *flag)
7
     int MPI_WIN_NULL_COPY_FN(MPI_Win oldwin, int win_keyval, void *extra_state,
8
                   void *attribute_val_in, void *attribute_val_out, int *flag)
9
10
     int MPI_WIN_NULL_DELETE_FN(MPI_Win win, int win_keyval,
11
                   void *attribute_val, void *extra_state)
12
     int MPI_Win_create_keyval(MPI_Win_copy_attr_function *win_copy_attr_fn,
13
                   MPI_Win_delete_attr_function *win_delete_attr_fn,
14
                   int *win_keyval, void *extra_state)
15
16
     int MPI_Win_delete_attr(MPI_Win win, int win_keyval)
17
     int MPI_Win_free_keyval(int *win_keyval)
18
19
     int MPI_Win_get_attr(MPI_Win win, int win_keyval, void *attribute_val,
20
                   int *flag)
21
     int MPI_Win_get_name(MPI_Win win, char *win_name, int *resultlen)
22
23
     int MPI_Win_set_attr(MPI_Win win, int win_keyval, void *attribute_val)
^{24}
     int MPI_Win_set_name(MPI_Win win, const char *win_name)
25
26
27
     A.3.6 Process Topologies C Bindings
28
29
     int MPI_Cart_coords(MPI_Comm comm, int rank, int maxdims, int coords[])
30
     int MPI_Cart_create(MPI_Comm comm_old, int ndims, const int dims[],
31
                   const int periods[], int reorder, MPI_Comm *comm_cart)
32
33
     int MPI_Cart_get(MPI_Comm comm, int maxdims, int dims[], int periods[],
34
                   int coords[])
35
     int MPI_Cart_map(MPI_Comm comm, int ndims, const int dims[],
36
                   const int periods[], int *newrank)
37
38
     int MPI_Cart_rank(MPI_Comm comm, const int coords[], int *rank)
39
     int MPI_Cart_shift(MPI_Comm comm, int direction, int disp,
40
                   int *rank_source, int *rank_dest)
41
42
     int MPI_Cart_sub(MPI_Comm comm, const int remain_dims[], MPI_Comm *newcomm)
43
     int MPI_Cartdim_get(MPI_Comm comm, int *ndims)
44
45
     int MPI_Dims_create(int nnodes, int ndims, int dims[])
^{46}
47
     int MPI_Dist_graph_create(MPI_Comm comm_old, int n, const int sources[],
                   const int degrees[], const int destinations[],
```

const int weights[], MPI\_Info info, int reorder, 2 MPI\_Comm \*comm\_dist\_graph) int MPI\_Dist\_graph\_create\_adjacent(MPI\_Comm comm\_old, int indegree, const int sources[], const int sourceweights[], int outdegree, const int destinations[], const int destweights[], MPI\_Info info, int reorder, MPI\_Comm \*comm\_dist\_graph) int MPI\_Dist\_graph\_neighbors(MPI\_Comm comm, int maxindegree, int sources[], int sourceweights[], int maxoutdegree, int destinations[], int destweights[]) 11 int MPI\_Dist\_graph\_neighbors\_count(MPI\_Comm comm, int \*indegree, 12 int \*outdegree, int \*weighted) 13 14 int MPI\_Graph\_create(MPI\_Comm comm\_old, int nnodes, const int index[], 15 const int edges[], int reorder, MPI\_Comm \*comm\_graph) 16 int MPI\_Graph\_get(MPI\_Comm comm, int maxindex, int maxedges, int index[], int edges[]) 18 19 int MPI\_Graph\_map(MPI\_Comm comm, int nnodes, const int index[], 20 const int edges[], int \*newrank) 21 int MPI\_Graph\_neighbors(MPI\_Comm comm, int rank, int maxneighbors, 22 int neighbors[]) 23 24 int MPI\_Graph\_neighbors\_count(MPI\_Comm comm, int rank, int \*nneighbors) int MPI\_Graphdims\_get(MPI\_Comm comm, int \*nnodes, int \*nedges) 26 27 int MPI\_Ineighbor\_allgather(const void \*sendbuf, int sendcount, 28 MPI\_Datatype sendtype, void \*recvbuf, int recvcount, 29 MPI\_Datatype recvtype, MPI\_Comm comm, MPI\_Request \*request) 30 int MPI\_Ineighbor\_allgather\_c(const void \*sendbuf, MPI\_Count sendcount, 31 MPI\_Datatype sendtype, void \*recvbuf, MPI\_Count recvcount, MPI\_Datatype recvtype, MPI\_Comm comm, MPI\_Request \*request) 33 34 int MPI\_Ineighbor\_allgatherv(const void \*sendbuf, int sendcount, 35 MPI\_Datatype sendtype, void \*recvbuf, const int recvcounts[], 36 const int displs[], MPI\_Datatype recvtype, MPI\_Comm comm, 37 MPI\_Request \*request) int MPI\_Ineighbor\_allgatherv\_c(const void \*sendbuf, MPI\_Count sendcount, MPI\_Datatype sendtype, void \*recvbuf, const MPI\_Count recvcounts[], const MPI\_Aint displs[], MPI\_Datatype recvtype, MPI\_Comm comm, MPI\_Request \*request) 42 43 int MPI\_Ineighbor\_alltoall(const void \*sendbuf, int sendcount, 44 MPI\_Datatype sendtype, void \*recvbuf, int recvcount, 45 MPI\_Datatype recvtype, MPI\_Comm comm, MPI\_Request \*request) 46 47 int MPI\_Ineighbor\_alltoall\_c(const void \*sendbuf, MPI\_Count sendcount,

MPI\_Datatype sendtype, void \*recvbuf, MPI\_Count recvcount,

```
1
                  MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
2
     int MPI_Ineighbor_alltoallv(const void *sendbuf, const int sendcounts[],
3
                   const int sdispls[], MPI_Datatype sendtype, void *recvbuf,
                   const int recvcounts[], const int rdispls[],
5
                  MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
6
7
     int MPI_Ineighbor_alltoallv_c(const void *sendbuf,
8
                   const MPI_Count sendcounts[], const MPI_Aint sdispls[],
9
                  MPI_Datatype sendtype, void *recvbuf,
10
                   const MPI_Count recvcounts[], const MPI_Aint rdispls[],
11
                  MPI_Datatype recvtype, MPI_Comm comm, MPI_Request *request)
12
     int MPI_Ineighbor_alltoallw(const void *sendbuf, const int sendcounts[],
13
                  const MPI_Aint sdispls[], const MPI_Datatype sendtypes[],
14
                  void *recvbuf, const int recvcounts[],
15
                   const MPI_Aint rdispls[], const MPI_Datatype recvtypes[],
16
                  MPI_Comm comm, MPI_Request *request)
17
18
     int MPI_Ineighbor_alltoallw_c(const void *sendbuf,
19
                  const MPI_Count sendcounts[], const MPI_Aint sdispls[],
20
                   const MPI_Datatype sendtypes[], void *recvbuf,
21
                   const MPI_Count recvcounts[], const MPI_Aint rdispls[],
22
                   const MPI_Datatype recvtypes[], MPI_Comm comm,
23
                  MPI_Request *request)
24
     int MPI_Neighbor_allgather(const void *sendbuf, int sendcount,
25
                  MPI_Datatype sendtype, void *recvbuf, int recvcount,
26
                  MPI_Datatype recvtype, MPI_Comm comm)
27
28
     int MPI_Neighbor_allgather_c(const void *sendbuf, MPI_Count sendcount,
29
                  MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
30
                  MPI_Datatype recvtype, MPI_Comm comm)
31
     int MPI_Neighbor_allgather_init(const void *sendbuf, int sendcount,
32
                  MPI_Datatype sendtype, void *recvbuf, int recvcount,
33
                  MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
34
                  MPI_Request *request)
35
36
     int MPI_Neighbor_allgather_init_c(const void *sendbuf, MPI_Count sendcount,
37
                  MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
38
                  MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
39
                  MPI_Request *request)
     int MPI_Neighbor_allgatherv(const void *sendbuf, int sendcount,
41
                  MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
42
                  const int displs[], MPI_Datatype recvtype, MPI_Comm comm)
43
44
     int MPI_Neighbor_allgatherv_c(const void *sendbuf, MPI_Count sendcount,
45
                  MPI_Datatype sendtype, void *recvbuf,
46
                  const MPI_Count recvcounts[], const MPI_Aint displs[],
47
                  MPI_Datatype recvtype, MPI_Comm comm)
```

```
int MPI_Neighbor_allgatherv_init(const void *sendbuf, int sendcount,
             MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
             const int displs[], MPI_Datatype recvtype, MPI_Comm comm,
             MPI_Info info, MPI_Request *request)
int MPI_Neighbor_allgatherv_init_c(const void *sendbuf,
             MPI_Count sendcount, MPI_Datatype sendtype, void *recvbuf,
             const MPI_Count recvcounts[], const MPI_Aint displs[],
             MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
             MPI_Request *request)
int MPI_Neighbor_alltoall(const void *sendbuf, int sendcount,
             MPI_Datatype sendtype, void *recvbuf, int recvcount,
                                                                                 12
                                                                                 13
             MPI_Datatype recvtype, MPI_Comm comm)
                                                                                 14
int MPI_Neighbor_alltoall_c(const void *sendbuf, MPI_Count sendcount,
                                                                                 15
             MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
                                                                                 16
             MPI_Datatype recvtype, MPI_Comm comm)
                                                                                 18
int MPI_Neighbor_alltoall_init(const void *sendbuf, int sendcount,
                                                                                 19
             MPI_Datatype sendtype, void *recvbuf, int recvcount,
                                                                                 20
             MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
                                                                                 21
             MPI_Request *request)
                                                                                 22
int MPI_Neighbor_alltoall_init_c(const void *sendbuf, MPI_Count sendcount,
             MPI_Datatype sendtype, void *recvbuf, MPI_Count recvcount,
                                                                                 24
             MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
             MPI_Request *request)
                                                                                 26
                                                                                 27
int MPI_Neighbor_alltoallv(const void *sendbuf, const int sendcounts[],
                                                                                 28
             const int sdispls[], MPI_Datatype sendtype, void *recvbuf,
                                                                                 29
             const int recvcounts[], const int rdispls[],
                                                                                 30
             MPI_Datatype recvtype, MPI_Comm comm)
int MPI_Neighbor_alltoallv_c(const void *sendbuf,
             const MPI_Count sendcounts[], const MPI_Aint sdispls[],
             MPI_Datatype sendtype, void *recvbuf,
                                                                                 34
             const MPI_Count recvcounts[], const MPI_Aint rdispls[],
                                                                                 35
             MPI_Datatype recvtype, MPI_Comm comm)
                                                                                 36
                                                                                 37
int MPI_Neighbor_alltoallv_init(const void *sendbuf,
             const int sendcounts[], const int sdispls[],
             MPI_Datatype sendtype, void *recvbuf, const int recvcounts[],
             const int rdispls[], MPI_Datatype recvtype, MPI_Comm comm,
             MPI_Info info, MPI_Request *request)
                                                                                 42
int MPI_Neighbor_alltoallv_init_c(const void *sendbuf,
                                                                                 43
             const MPI_Count sendcounts[], const MPI_Aint sdispls[],
                                                                                 44
             MPI_Datatype sendtype, void *recvbuf,
                                                                                 45
             const MPI_Count recvcounts[], const MPI_Aint rdispls[],
                                                                                 46
             MPI_Datatype recvtype, MPI_Comm comm, MPI_Info info,
             MPI_Request *request)
```

#-error!

#-PR414

#-PR431

Done

PR431

48

lin

#-update4

```
1
                int MPI_Neighbor_alltoallw(const void *sendbuf, const int sendcounts[],
           2
                              const MPI_Aint sdispls[], const MPI_Datatype sendtypes[],
           3
                              void *recvbuf, const int recvcounts[],
                              const MPI_Aint rdispls[], const MPI_Datatype recvtypes[],
           5
                              MPI_Comm comm)
           6
                int MPI_Neighbor_alltoallw_c(const void *sendbuf,
                              const MPI_Count sendcounts[], const MPI_Aint sdispls[],
                              const MPI_Datatype sendtypes[], void *recvbuf,
           9
                              const MPI_Count recvcounts[], const MPI_Aint rdispls[],
           10
                              const MPI_Datatype recvtypes[], MPI_Comm comm)
           11
           12
                int MPI_Neighbor_alltoallw_init(const void *sendbuf,
           13
                              const int sendcounts[], const MPI_Aint sdispls[],
           14
                              const MPI_Datatype sendtypes[], void *recvbuf,
           15
                              const int recvcounts[], const MPI_Aint rdispls[],
           16
                              const MPI_Datatype recvtypes[], MPI_Comm comm, MPI_Info info,
           17
                              MPI_Request *request)
           18
                int MPI_Neighbor_alltoallw_init_c(const void *sendbuf,
           19
                              const MPI_Count sendcounts[], const MPI_Aint sdispls[],
           20
                              const MPI_Datatype sendtypes[], void *recvbuf,
           21
                              const MPI_Count recvcounts[], const MPI_Aint rdispls[],
           22
                              const MPI_Datatype recvtypes[], MPI_Comm comm, MPI_Info info,
           23
                              MPI_Request *request)
           24
                int MPI_Topo_test(MPI_Comm comm, int *status)
           26
           27
                A.3.7 MPI Environmental Management C Bindings
           28
           29
                double MPI_Wtick(void)
                                         These routine were lost due to
           30
                                         a bug in MAKE-APPLANG
          31
                double MPI_Wtime(void)
#-update2
                int MPI_Add_error_class(int *errorclass)
Resolved in 33
           34
                int MPI_Add_error_code(int errorclass, int *errorcode)
           35
                int MPI_Add_error_string(int errorcode, const char *string)
           36
           37
                int MPI_Alloc_mem(MPI_Aint size, MPI_Info info, void *baseptr)
           38
                int MPI_Comm_call_errhandler(MPI_Comm comm, int errorcode)
           39
                int MPI_Comm_create_errhandler(
           41
                              MPI_Comm_errhandler_function *comm_errhandler_fn,
           42
                              MPI_Errhandler *errhandler)
           43
                int MPI_Comm_get_errhandler(MPI_Comm comm, MPI_Errhandler *errhandler)
          44
           45
                int MPI_Comm_set_errhandler(MPI_Comm comm, MPI_Errhandler errhandler)
           46
                int MPI_Errhandler_free(MPI_Errhandler *errhandler)
           47
```

```
int MPI_Error_class(int errorcode, int *errorclass)
int MPI_Error_string(int errorcode, char *string, int *resultlen)
int MPI_File_call_errhandler(MPI_File fh, int errorcode)
int MPI_File_create_errhandler(
             MPI_File_errhandler_function *file_errhandler_fn,
             MPI_Errhandler *errhandler)
int MPI_File_get_errhandler(MPI_File file, MPI_Errhandler *errhandler)
int MPI_File_set_errhandler(MPI_File file, MPI_Errhandler errhandler)
int MPI_Free_mem(void *base)
int MPI_Get_library_version(char *version, int *resultlen)
int MPI_Get_processor_name(char *name, int *resultlen)
int MPI_Get_version(int *version, int *subversion)
int MPI_Session_call_errhandler(MPI_Session session, int errorcode)
int MPI_Session_create_errhandler(
             MPI_Session_errhandler_function *session_errhandler_fn,
             MPI_Errhandler *errhandler)
int MPI_Session_get_errhandler(MPI_Session session,
             MPI_Errhandler *errhandler)
int MPI_Session_set_errhandler(MPI_Session session,
             MPI_Errhandler errhandler)
int MPI_Win_call_errhandler(MPI_Win win, int errorcode)
int MPI_Win_create_errhandler(
             MPI_Win_errhandler_function *win_errhandler_fn,
             MPI_Errhandler *errhandler)
int MPI_Win_get_errhandler(MPI_Win win, MPI_Errhandler *errhandler)
int MPI_Win_set_errhandler(MPI_Win win, MPI_Errhandler errhandler)
     The Info Object C Bindings
int MPI_Info_create(MPI_Info *info)
int MPI_Info_create_env(int argc, char argv[], MPI_Info *info)
                                                           Deprecated function
int MPI_Info_delete(MPI_Info info, const char *key)
                                                           descriptions must be
                                                           moved from the
int MPI_Info_dup(MPI_Info info, MPI_Info *newinfo)
                                                           original chapter to the
                                                           Deprecated Interfaces
int MPI_Info_free(MPI_Info *info)
                                                           chapter !!!
int MPI_Info_get(MPI_Info info, const char *key, int valuelen, char *value,
```

#-arror #-364

12

13

14 15

16

18

19

20

21

22 23

24

26

27 28

29

30

33

34 35

36 37

39

41

42

43

44

45

46



int \*flag)

```
1
            int MPI_Info_get_nkeys(MPI_Info info, int *nkeys)
       2
            int MPI_Info_get_nthkey(MPI_Info info, int n, char *key)
       3
       4
            int MPI_Info_get_string(MPI_Info info, const char *key, int *buflen,
                           char *value, int *flag)
#-error
            int MPI_Info_get_valuelen(MPI_Info info, const char *key, int *valuelen,
#-364
                           int *flag)
                                                                                    Deprecated function
Done
                                                                                    descriptions must be
            int MPI_Info_set(MPI_Info info, const char *key, const char *value)
                                                                                    moved from the
       10
PR443
                                                                                    original chapter to the
       11
                                                                                    Deprecated Interfaces
            A.3.9 Process Creation and Management C Bindings
       12
                                                                                    chapter !!!
       13
            int MPI_Abort(MPI_Comm comm, int errorcode)
       14
            int MPI_Close_port(const char *port_name)
       15
       16
            int MPI_Comm_accept(const char *port_name, MPI_Info info, int root,
       17
                          MPI_Comm comm, MPI_Comm *newcomm)
       18
       19
            int MPI_Comm_connect(const char *port_name, MPI_Info info, int root,
                          MPI_Comm comm, MPI_Comm *newcomm)
       20
       21
            int MPI_Comm_disconnect(MPI_Comm *comm)
       22
       23
            int MPI_Comm_get_parent(MPI_Comm *parent)
       ^{24}
            int MPI_Comm_join(int fd, MPI_Comm *intercomm)
       25
       26
            int MPI_Comm_spawn(const char *command, char *argv[], int maxprocs,
       27
                          MPI_Info info, int root, MPI_Comm comm, MPI_Comm *intercomm,
       28
                           int array_of_errcodes[])
       29
            int MPI_Comm_spawn_multiple(int count, char *array_of_commands[],
       30
                           char **array_of_argv[], const int array_of_maxprocs[],
       31
                           const MPI_Info array_of_info[], int root, MPI_Comm comm,
       32
                          MPI_Comm *intercomm, int array_of_errcodes[])
       33
       34
            int MPI_Finalize(void)
       35
            int MPI_Finalized(int *flag)
       36
       37
            int MPI_Init(int *argc, char ***argv)
       38
            int MPI_Init_thread(int *argc, char ***argv, int required, int *provided)
       39
            int MPI_Initialized(int *flag)
       41
            int MPI_Is_thread_main(int *flag)
       42
       43
            int MPI_Lookup_name(const char *service_name, MPI_Info info,
       44
                           char *port_name)
       45
            int MPI_Open_port(MPI_Info info, char *port_name)
       ^{46}
       47
```

```
int MPI_Publish_name(const char *service_name, MPI_Info info,
                                                                                  2
             const char *port_name)
int MPI_Query_thread(int *provided)
int MPI_Session_finalize(MPI_Session *session)
int MPI_Session_get_info(MPI_Session session, MPI_Info *info_used)
int MPI_Session_get_nth_pset(MPI_Session session, MPI_Info info, int n,
             int *pset_len, char *pset_name)
int MPI_Session_get_num_psets(MPI_Session session, MPI_Info info,
             int *npset_names)
                                                                                 12
                                                                                 13
int MPI_Session_get_pset_info(MPI_Session session, const char *pset_name,
                                                                                 14
             MPI_Info *info)
                                                                                  15
int MPI_Session_init(MPI_Info info, MPI_Errhandler errhandler,
                                                                                  16
             MPI_Session *session)
                                                                                 18
int MPI_Unpublish_name(const char *service_name, MPI_Info info,
                                                                                 19
             const char *port_name)
                                                                                 20
                                                                                 21
A.3.10 One-Sided Communications C Bindings
                                                                                 22
                                                                                 23
int MPI_Accumulate(const void *origin_addr, int origin_count,
                                                                                 24
             MPI_Datatype origin_datatype, int target_rank,
             MPI_Aint target_disp, int target_count,
                                                                                 26
             MPI_Datatype target_datatype, MPI_Op op, MPI_Win win)
                                                                                 27
int MPI_Accumulate_c(const void *origin_addr, MPI_Count origin_count,
                                                                                 28
                                                                                 29
             MPI_Datatype origin_datatype, int target_rank,
             MPI_Aint target_disp, MPI_Count target_count,
                                                                                 30
                                                                                 31
             MPI_Datatype target_datatype, MPI_Op op, MPI_Win win)
int MPI_Compare_and_swap(const void *origin_addr, const void *compare_addr,
             void *result_addr, MPI_Datatype datatype, int target_rank,
                                                                                 34
             MPI_Aint target_disp, MPI_Win win)
                                                                                 35
                                                                                 36
int MPI_Fetch_and_op(const void *origin_addr, void *result_addr,
                                                                                 37
             MPI_Datatype datatype, int target_rank, MPI_Aint target_disp,
                                                                                 38
             MPI_Op op, MPI_Win win)
                                                                                 39
int MPI_Get(void *origin_addr, int origin_count,
             MPI_Datatype origin_datatype, int target_rank,
             MPI_Aint target_disp, int target_count,
                                                                                 42
             MPI_Datatype target_datatype, MPI_Win win)
                                                                                 43
                                                                                 44
int MPI_Get_accumulate(const void *origin_addr, int origin_count,
                                                                                 45
             MPI_Datatype origin_datatype, void *result_addr,
                                                                                 46
             int result_count, MPI_Datatype result_datatype,
             int target_rank, MPI_Aint target_disp, int target_count,
```

```
1
                          MPI_Datatype target_datatype, MPI_Op op, MPI_Win win)
       2
            int MPI_Get_accumulate_c(const void *origin_addr, MPI_Count origin_count,
       3
                          MPI_Datatype origin_datatype, void *result_addr,
                          MPI_Count result_count, MPI_Datatype result_datatype,
       5
                          int target_rank, MPI_Aint target_disp, MPI_Count target_count,
       6
                          MPI_Datatype target_datatype, MPI_Op op, MPI_Win win)
            int MPI_Get_c(void *origin_addr, MPI_Count origin_count,
                                                                           Due to alphabetic rules,
#-364
                          MPI_Datatype origin_datatype, int target_rank,
                                                                           MPI_Get_c does not
#-error! 10
                          MPI_Aint target_disp, MPI_Count target_count,
                                                                           follow directly after
       11
                          MPI_Datatype target_datatype, MPI_Win win)
                                                                           MPI Get.
       12
            int MPI_Put(const void *origin_addr, int origin_count,
       13
                                                                           Should we fix this?
                          MPI_Datatype origin_datatype, int target_rank,
       14
                                                                           And can we fix this?
                          MPI_Aint target_disp, int target_count,
       15
                          MPI_Datatype target_datatype, MPI_Win win)
       16
       17
            int MPI_Put_c(const void *origin_addr, MPI_Count origin_count,
       18
                          MPI_Datatype origin_datatype, int target_rank,
       19
                          MPI_Aint target_disp, MPI_Count target_count,
       20
                          MPI_Datatype target_datatype, MPI_Win win)
       21
            int MPI_Raccumulate(const void *origin_addr, int origin_count,
       22
                          MPI_Datatype origin_datatype, int target_rank,
       23
                          MPI_Aint target_disp, int target_count,
       24
                          MPI_Datatype target_datatype, MPI_Op op, MPI_Win win,
                          MPI_Request *request)
       26
       27
            int MPI_Raccumulate_c(const void *origin_addr, MPI_Count origin_count,
       28
                          MPI_Datatype origin_datatype, int target_rank,
       29
                          MPI_Aint target_disp, MPI_Count target_count,
       30
                          MPI_Datatype target_datatype, MPI_Op op, MPI_Win win,
       31
                          MPI_Request *request)
       32
            int MPI_Rget(void *origin_addr, int origin_count,
       33
                          MPI_Datatype origin_datatype, int target_rank,
       34
                          MPI_Aint target_disp, int target_count,
       35
                          MPI_Datatype target_datatype, MPI_Win win,
       36
                          MPI_Request *request)
       37
            int MPI_Rget_accumulate(const void *origin_addr, int origin_count,
       39
                          MPI_Datatype origin_datatype, void *result_addr,
                          int result_count, MPI_Datatype result_datatype,
                          int target_rank, MPI_Aint target_disp, int target_count,
       42
                          MPI_Datatype target_datatype, MPI_Op op, MPI_Win win,
       43
                          MPI_Request *request)
       44
            int MPI_Rget_accumulate_c(const void *origin_addr, MPI_Count origin_count,
       45
                          MPI_Datatype origin_datatype, void *result_addr,
       46
                          MPI_Count result_count, MPI_Datatype result_datatype,
       47
                          int target_rank, MPI_Aint target_disp, MPI_Count target_count,
```

```
MPI_Datatype target_datatype, MPI_Op op, MPI_Win win,
             MPI_Request *request)
int MPI_Rget_c(void *origin_addr, MPI_Count origin_count,
             MPI_Datatype origin_datatype, int target_rank,
             MPI_Aint target_disp, MPI_Count target_count,
             MPI_Datatype target_datatype, MPI_Win win,
             MPI_Request *request)
int MPI_Rput(const void *origin_addr, int origin_count,
             MPI_Datatype origin_datatype, int target_rank,
                                                                                  11
             MPI_Aint target_disp, int target_count,
                                                                                 12
             MPI_Datatype target_datatype, MPI_Win win,
                                                                                  13
             MPI_Request *request)
                                                                                 14
int MPI_Rput_c(const void *origin_addr, MPI_Count origin_count,
                                                                                  15
             MPI_Datatype origin_datatype, int target_rank,
                                                                                  16
             MPI_Aint target_disp, MPI_Count target_count,
                                                                                  17
             MPI_Datatype target_datatype, MPI_Win win,
                                                                                 18
             MPI_Request *request)
                                                                                 19
                                                                                 20
int MPI_Win_allocate(MPI_Aint size, int disp_unit, MPI_Info info,
                                                                                 21
             MPI_Comm comm, void *baseptr, MPI_Win *win)
                                                                                 22
int MPI_Win_allocate_c(MPI_Aint size, MPI_Aint disp_unit, MPI_Info info,
                                                                                 23
             MPI_Comm comm, void *baseptr, MPI_Win *win)
                                                                                 24
int MPI_Win_allocate_shared(MPI_Aint size, int disp_unit, MPI_Info info,
                                                                                 26
             MPI_Comm comm, void *baseptr, MPI_Win *win)
                                                                                 27
int MPI_Win_allocate_shared_c(MPI_Aint size, MPI_Aint disp_unit,
                                                                                 28
             MPI_Info info, MPI_Comm comm, void *baseptr, MPI_Win *win)
                                                                                 29
                                                                                 30
int MPI_Win_attach(MPI_Win win, void *base, MPI_Aint size)
int MPI_Win_complete(MPI_Win win)
                                                                                 33
int MPI_Win_create(void *base, MPI_Aint size, int disp_unit, MPI_Info info,
                                                                                 34
             MPI_Comm comm, MPI_Win *win)
                                                                                 35
int MPI_Win_create_c(void *base, MPI_Aint size, MPI_Aint disp_unit,
                                                                                 36
             MPI_Info info, MPI_Comm comm, MPI_Win *win)
                                                                                 37
int MPI_Win_create_dynamic(MPI_Info info, MPI_Comm comm, MPI_Win *win)
                                                                                 39
int MPI_Win_detach(MPI_Win win, const void *base)
                                                                                 41
int MPI_Win_fence(int assert, MPI_Win win)
                                                                                 42
int MPI_Win_flush(int rank, MPI_Win win)
                                                                                 43
                                                                                 44
int MPI_Win_flush_all(MPI_Win win)
                                                                                  45
                                                                                  46
int MPI_Win_flush_local(int rank, MPI_Win win)
int MPI_Win_flush_local_all(MPI_Win win)
```

```
1
     int MPI_Win_free(MPI_Win *win)
2
     int MPI_Win_get_group(MPI_Win win, MPI_Group *group)
3
4
     int MPI_Win_get_info(MPI_Win win, MPI_Info *info_used)
5
     int MPI_Win_lock(int lock_type, int rank, int assert, MPI_Win win)
6
7
     int MPI_Win_lock_all(int assert, MPI_Win win)
8
     int MPI_Win_post(MPI_Group group, int assert, MPI_Win win)
9
10
     int MPI_Win_set_info(MPI_Win win, MPI_Info info)
11
     int MPI_Win_shared_query(MPI_Win win, int rank, MPI_Aint *size,
12
                   int *disp_unit, void *baseptr)
13
14
     int MPI_Win_shared_query_c(MPI_Win win, int rank, MPI_Aint *size,
15
                   MPI_Aint *disp_unit, void *baseptr)
16
     int MPI_Win_start(MPI_Group group, int assert, MPI_Win win)
17
18
     int MPI_Win_sync(MPI_Win win)
19
     int MPI_Win_test(MPI_Win win, int *flag)
20
21
     int MPI_Win_unlock(int rank, MPI_Win win)
22
23
     int MPI_Win_unlock_all(MPI_Win win)
^{24}
     int MPI_Win_wait(MPI_Win win)
25
26
27
     A.3.11 External Interfaces C Bindings
28
     int MPI_Grequest_complete(MPI_Request request)
29
30
     int MPI_Grequest_start(MPI_Grequest_query_function *query_fn,
31
                   MPI_Grequest_free_function *free_fn,
32
                   MPI_Grequest_cancel_function *cancel_fn, void *extra_state,
33
                   MPI_Request *request)
34
     int MPI_Status_set_cancelled(MPI_Status *status, int flag)
35
36
     int MPI_Status_set_elements(MPI_Status *status, MPI_Datatype datatype,
37
                   int count)
38
     int MPI_Status_set_elements_x(MPI_Status *status, MPI_Datatype datatype,
39
                   MPI_Count count)
41
42
     A.3.12 I/O C Bindings
43
44
     int MPI_CONVERSION_FN_NULL(void *userbuf, MPI_Datatype datatype, int count,
45
                   void *filebuf, MPI_Offset position, void *extra_state)
46
     int MPI_CONVERSION_FN_NULL_c(void *userbuf, MPI_Datatype datatype,
47
                   MPI_Count count, void *filebuf, MPI_Offset position,
```

```
void *extra_state)
int MPI_File_close(MPI_File *fh)
int MPI_File_delete(const char *filename, MPI_Info info)
int MPI_File_get_amode(MPI_File fh, int *amode)
int MPI_File_get_atomicity(MPI_File fh, int *flag)
int MPI_File_get_byte_offset(MPI_File fh, MPI_Offset offset,
             MPI_Offset *disp)
int MPI_File_get_group(MPI_File fh, MPI_Group *group)
                                                                                  12
int MPI_File_get_info(MPI_File fh, MPI_Info *info_used)
                                                                                  13
                                                                                  14
int MPI_File_get_position(MPI_File fh, MPI_Offset *offset)
                                                                     This is okay because
int MPI_File_get_position_shared(MPI_File fh, MPI_Offset *offset)
                                                                     embiggening is needed for
int MPI_File_get_size(MPI_File fh, MPI_Offset *size)
                                                                     datatype usage in
                                                                     MPI_Offset based MPI-IO
int MPI_File_get_type_extent(MPI_File fh, MPI_Datatype datatype,
                                                                     and MPI Offset can be
             MPI_Aint *extent)
                                                                    larger than MPI Aint.
                                                                                    #-364
int MPI_File_get_type_extent_c(MPI_File fh, MPI_Datatype datatype,
                                                                                  22
             MPI_Count *extent)
                                                                                  23
int MPI_File_get_view(MPI_File fh, MPI_Offset *disp, MPI_Datatype *etype,
             MPI_Datatype *filetype, char *datarep)
                                                                                  26
int MPI_File_iread(MPI_File fh, void *buf, int count,
                                                                                  27
             MPI_Datatype datatype, MPI_Request *request)
                                                                                  28
int MPI_File_iread_all(MPI_File fh, void *buf, int count,
                                                                                  29
                                                                                  30
             MPI_Datatype datatype, MPI_Request *request)
                                                                                  31
int MPI_File_iread_all_c(MPI_File fh, void *buf, MPI_Count count,
             MPI_Datatype datatype, MPI_Request *request)
                                                                                  34
int MPI_File_iread_at(MPI_File fh, MPI_Offset offset, void *buf, int count,
                                                                                  35
             MPI_Datatype datatype, MPI_Request *request)
                                                                                  36
int MPI_File_iread_at_all(MPI_File fh, MPI_Offset offset, void *buf,
                                                                                  37
             int count, MPI_Datatype datatype, MPI_Request *request)
                                                                                  38
int MPI_File_iread_at_all_c(MPI_File fh, MPI_Offset offset, void *buf,
             MPI_Count count, MPI_Datatype datatype, MPI_Request *request)
                                                                                  41
int MPI_File_iread_at_c(MPI_File fh, MPI_Offset offset, void *buf,
                                                                                  42
             MPI_Count count, MPI_Datatype datatype, MPI_Request *request)
                                                                                  43
                                                                                  44
int MPI_File_iread_c(MPI_File fh, void *buf, MPI_Count count,
                                                                                  45
             MPI_Datatype datatype, MPI_Request *request)
                                                                                  46
int MPI_File_iread_shared(MPI_File fh, void *buf, int count,
                                                                                  47
             MPI_Datatype datatype, MPI_Request *request)
```

48

```
1
     int MPI_File_iread_shared_c(MPI_File fh, void *buf, MPI_Count count,
2
                  MPI_Datatype datatype, MPI_Request *request)
3
     int MPI_File_iwrite(MPI_File fh, const void *buf, int count,
                  MPI_Datatype datatype, MPI_Request *request)
5
6
     int MPI_File_iwrite_all(MPI_File fh, const void *buf, int count,
7
                  MPI_Datatype datatype, MPI_Request *request)
8
     int MPI_File_iwrite_all_c(MPI_File fh, const void *buf, MPI_Count count,
9
                  MPI_Datatype datatype, MPI_Request *request)
10
11
     int MPI_File_iwrite_at(MPI_File fh, MPI_Offset offset, const void *buf,
12
                   int count, MPI_Datatype datatype, MPI_Request *request)
13
     int MPI_File_iwrite_at_all(MPI_File fh, MPI_Offset offset, const void *buf,
14
                   int count, MPI_Datatype datatype, MPI_Request *request)
15
16
     int MPI_File_iwrite_at_all_c(MPI_File fh, MPI_Offset offset,
17
                   const void *buf, MPI_Count count, MPI_Datatype datatype,
18
                  MPI_Request *request)
19
     int MPI_File_iwrite_at_c(MPI_File fh, MPI_Offset offset, const void *buf,
20
                  MPI_Count count, MPI_Datatype datatype, MPI_Request *request)
21
22
     int MPI_File_iwrite_c(MPI_File fh, const void *buf, MPI_Count count,
23
                  MPI_Datatype datatype, MPI_Request *request)
^{24}
     int MPI_File_iwrite_shared(MPI_File fh, const void *buf, int count,
25
                  MPI_Datatype datatype, MPI_Request *request)
26
27
     int MPI_File_iwrite_shared_c(MPI_File fh, const void *buf, MPI_Count count,
28
                  MPI_Datatype datatype, MPI_Request *request)
29
     int MPI_File_open(MPI_Comm comm, const char *filename, int amode,
30
                  MPI_Info info, MPI_File *fh)
31
     int MPI_File_preallocate(MPI_File fh, MPI_Offset size)
33
34
     int MPI_File_read(MPI_File fh, void *buf, int count, MPI_Datatype datatype,
                  MPI_Status *status)
35
36
     int MPI_File_read_all(MPI_File fh, void *buf, int count,
37
                  MPI_Datatype datatype, MPI_Status *status)
38
39
     int MPI_File_read_all_begin(MPI_File fh, void *buf, int count,
40
                  MPI_Datatype datatype)
41
     int MPI_File_read_all_begin_c(MPI_File fh, void *buf, MPI_Count count,
42
                  MPI_Datatype datatype)
43
44
     int MPI_File_read_all_c(MPI_File fh, void *buf, MPI_Count count,
45
                  MPI_Datatype datatype, MPI_Status *status)
^{46}
     int MPI_File_read_all_end(MPI_File fh, void *buf, MPI_Status *status)
47
```

int MPI\_File\_read\_at(MPI\_File fh, MPI\_Offset offset, void \*buf, int count, MPI\_Datatype datatype, MPI\_Status \*status) int MPI\_File\_read\_at\_all(MPI\_File fh, MPI\_Offset offset, void \*buf, int count, MPI\_Datatype datatype, MPI\_Status \*status) int MPI\_File\_read\_at\_all\_begin(MPI\_File fh, MPI\_Offset offset, void \*buf, int count, MPI\_Datatype datatype) int MPI\_File\_read\_at\_all\_begin\_c(MPI\_File fh, MPI\_Offset offset, void \*buf, MPI\_Count count, MPI\_Datatype datatype) 11 int MPI\_File\_read\_at\_all\_c(MPI\_File fh, MPI\_Offset offset, void \*buf, 12 MPI\_Count count, MPI\_Datatype datatype, MPI\_Status \*status) 13 int MPI\_File\_read\_at\_all\_end(MPI\_File fh, void \*buf, MPI\_Status \*status) 14 15int MPI\_File\_read\_at\_c(MPI\_File fh, MPI\_Offset offset, void \*buf, 16 MPI\_Count count, MPI\_Datatype datatype, MPI\_Status \*status) 17 int MPI\_File\_read\_c(MPI\_File fh, void \*buf, MPI\_Count count, 18 MPI\_Datatype datatype, MPI\_Status \*status) 19 20 int MPI\_File\_read\_ordered(MPI\_File fh, void \*buf, int count, 21 MPI\_Datatype datatype, MPI\_Status \*status) 22 int MPI\_File\_read\_ordered\_begin(MPI\_File fh, void \*buf, int count, 23 MPI\_Datatype datatype) 24 int MPI\_File\_read\_ordered\_begin\_c(MPI\_File fh, void \*buf, MPI\_Count count, 26 MPI\_Datatype datatype) 27 int MPI\_File\_read\_ordered\_c(MPI\_File fh, void \*buf, MPI\_Count count, 28 MPI\_Datatype datatype, MPI\_Status \*status) 29 30 int MPI\_File\_read\_ordered\_end(MPI\_File fh, void \*buf, MPI\_Status \*status) 31 int MPI\_File\_read\_shared(MPI\_File fh, void \*buf, int count, 33 MPI\_Datatype datatype, MPI\_Status \*status) 34 int MPI\_File\_read\_shared\_c(MPI\_File fh, void \*buf, MPI\_Count count, 35 MPI\_Datatype datatype, MPI\_Status \*status) 36 37 int MPI\_File\_seek(MPI\_File fh, MPI\_Offset offset, int whence) int MPI\_File\_seek\_shared(MPI\_File fh, MPI\_Offset offset, int whence) int MPI\_File\_set\_atomicity(MPI\_File fh, int flag) 41 int MPI\_File\_set\_info(MPI\_File fh, MPI\_Info info) 42 43 int MPI\_File\_set\_size(MPI\_File fh, MPI\_Offset size) 44 int MPI\_File\_set\_view(MPI\_File fh, MPI\_Offset disp, MPI\_Datatype etype, 45 MPI\_Datatype filetype, const char \*datarep, MPI\_Info info) 46 int MPI\_File\_sync(MPI\_File fh)

```
1
     int MPI_File_write(MPI_File fh, const void *buf, int count,
2
                  MPI_Datatype datatype, MPI_Status *status)
3
     int MPI_File_write_all(MPI_File fh, const void *buf, int count,
                  MPI_Datatype datatype, MPI_Status *status)
5
6
     int MPI_File_write_all_begin(MPI_File fh, const void *buf, int count,
7
                  MPI_Datatype datatype)
8
     int MPI_File_write_all_begin_c(MPI_File fh, const void *buf,
9
                  MPI_Count count, MPI_Datatype datatype)
10
11
     int MPI_File_write_all_c(MPI_File fh, const void *buf, MPI_Count count,
12
                  MPI_Datatype datatype, MPI_Status *status)
13
     int MPI_File_write_all_end(MPI_File fh, const void *buf,
14
                  MPI_Status *status)
15
16
     int MPI_File_write_at(MPI_File fh, MPI_Offset offset, const void *buf,
17
                   int count, MPI_Datatype datatype, MPI_Status *status)
18
     int MPI_File_write_at_all(MPI_File fh, MPI_Offset offset, const void *buf,
19
                   int count, MPI_Datatype datatype, MPI_Status *status)
20
21
     int MPI_File_write_at_all_begin(MPI_File fh, MPI_Offset offset,
22
                   const void *buf, int count, MPI_Datatype datatype)
23
     int MPI_File_write_at_all_begin_c(MPI_File fh, MPI_Offset offset,
^{24}
                   const void *buf, MPI_Count count, MPI_Datatype datatype)
25
26
     int MPI_File_write_at_all_c(MPI_File fh, MPI_Offset offset,
27
                   const void *buf, MPI_Count count, MPI_Datatype datatype,
28
                  MPI_Status *status)
29
     int MPI_File_write_at_all_end(MPI_File fh, const void *buf,
30
                  MPI_Status *status)
31
     int MPI_File_write_at_c(MPI_File fh, MPI_Offset offset, const void *buf,
33
                  MPI_Count count, MPI_Datatype datatype, MPI_Status *status)
34
     int MPI_File_write_c(MPI_File fh, const void *buf, MPI_Count count,
35
                  MPI_Datatype datatype, MPI_Status *status)
36
37
     int MPI_File_write_ordered(MPI_File fh, const void *buf, int count,
38
                  MPI_Datatype datatype, MPI_Status *status)
39
40
     int MPI_File_write_ordered_begin(MPI_File fh, const void *buf, int count,
41
                  MPI_Datatype datatype)
42
     int MPI_File_write_ordered_begin_c(MPI_File fh, const void *buf,
43
                  MPI_Count count, MPI_Datatype datatype)
44
45
     int MPI_File_write_ordered_c(MPI_File fh, const void *buf, MPI_Count count,
46
                  MPI_Datatype datatype, MPI_Status *status)
47
     int MPI_File_write_ordered_end(MPI_File fh, const void *buf,
48
```

```
MPI_Status *status)
int MPI_File_write_shared(MPI_File fh, const void *buf, int count,
             MPI_Datatype datatype, MPI_Status *status)
int MPI_File_write_shared_c(MPI_File fh, const void *buf, MPI_Count count,
             MPI_Datatype datatype, MPI_Status *status)
int MPI_Register_datarep(const char *datarep,
             MPI_Datarep_conversion_function *read_conversion_fn,
             MPI_Datarep_conversion_function *write_conversion_fn,
             MPI_Datarep_extent_function *dtype_file_extent_fn,
             void *extra_state)
int MPI_Register_datarep_c(const char *datarep,
             MPI_Datarep_conversion_function_c *read_conversion_fn,
             MPI_Datarep_conversion_function_c *write_conversion_fn,
             MPI_Datarep_extent_function *dtype_file_extent_fn,
             void *extra_state)
A.3.13 Language Bindings C Bindings
int MPI_Status_f082f(const MPI_F08_status *f08_status, MPI_Fint *f_status)
int MPI_Status_f2f08(const MPI_Fint *f_status, MPI_F08_status *f08_status)
int MPI_Type_create_f90_complex(int p, int r, MPI_Datatype *newtype)
int MPI_Type_create_f90_integer(int r, MPI_Datatype *newtype)
int MPI_Type_create_f90_real(int p, int r, MPI_Datatype *newtype)
int MPI_Type_match_size(int typeclass, int size, MPI_Datatype *datatype)
MPI_Fint MPI_Comm_c2f(MPI_Comm comm)
                                                      These routine were lost due to
                                                      a bug in MAKE-APPLANG
MPI_Comm MPI_Comm_f2c(MPI_Fint comm)
MPI_Fint MPI_Errhandler_c2f(MPI_Errhandler errhandler)
MPI_Errhandler MPI_Errhandler_f2c(MPI_Fint errhandler)
MPI_Fint MPI_File_c2f(MPI_File file)
MPI_File MPI_File_f2c(MPI_Fint file)
MPI_Fint MPI_Group_c2f(MPI_Group group)
MPI_Group_f2c(MPI_Fint group)
MPI_Fint MPI_Info_c2f(MPI_Info info)
MPI_Info MPI_Info_f2c(MPI_Fint info)
MPI_Fint MPI_Message_c2f(MPI_Message message)
```

12 13

14

15

16

18 19

20 21

22

23

24

25

26

27

28

29

31

32

33

34

35

36

37 38

39

41

42

43 44

45

 $\frac{46}{47}$ 

#-error!

#-update2

Done

PR431

#-error!

#-PR414

Done in

PR431

#-update2

lin

MPI\_Message MPI\_Message\_f2c(MPI\_Fint message)

47

```
#-error!
               MPI_Fint MPI_Op_c2f(MPI_Op op)
#-PR414
               MPI_Op MPI_Op_f2c(MPI_Fint op)
#-update2
               MPI_Fint MPI_Request_c2f(MPI_Request request)
 Done
 lin
               MPI_Request MPI_Request_f2c(MPI_Fint request)
 PR431
               MPI_Fint MPI_Session_c2f(MPI_Session session)
               MPI_Session MPI_Session_f2c(MPI_Fint session)
               int MPI_Status_c2f(const MPI_Status *c_status, MPI_Fint *f_status)
               int MPI_Status_c2f08(const MPI_Status *c_status,
                             MPI_F08_status *f08_status)
               int MPI_Status_f082c(const MPI_F08_status *f08_status,
          15
                             MPI_Status *c_status)
          17
               int MPI_Status_f2c(const MPI_Fint *f_status, MPI_Status *c_status)
               MPI_Fint MPI_Type_c2f(MPI_Datatype datatype)
          19
          20
               MPI_Datatype MPI_Type_f2c(MPI_Fint datatype)
          21
               MPI_Fint MPI_Win_c2f(MPI_Win win)
          22
          23
               MPI_Win MPI_Win_f2c(MPI_Fint win)
          ^{24}
          25
               A.3.14 Tools / Profiling Interface C Bindings
          26
          27
               int MPI_Pcontrol(const int level, ...)
          28
          29
               A.3.15 Tools / MPI Tool Information Interface C Bindings
          30
          31
               int MPI_T_category_changed(int *stamp)
          32
               int MPI_T_category_get_categories(int cat_index, int len, int indices[])
          33
          34
               int MPI_T_category_get_cvars(int cat_index, int len, int indices[])
          35
          36
               int MPI_T_category_get_events(int cat_index, int len, int indices[])
          37
               int MPI_T_category_get_index(const char *name, int *cat_index)
          38
          39
               int MPI_T_category_get_info(int cat_index, char *name, int *name_len,
          40
                             char *desc, int *desc_len, int *num_cvars, int *num_pvars,
          41
                             int *num_categories)
          42
               int MPI_T_category_get_num(int *num_cat)
          43
          44
               int MPI_T_category_get_num_events(int cat_index, int *num_events)
          45
               int MPI_T_category_get_pvars(int cat_index, int len, int indices[])
          46
```

int MPI\_T\_cvar\_get\_index(const char \*name, int \*cvar\_index)

```
int MPI_T_cvar_get_info(int cvar_index, char *name, int *name_len,
             int *verbosity, MPI_Datatype *datatype, MPI_T_enum *enumtype,
             char *desc, int *desc_len, int *bind, int *scope)
int MPI_T_cvar_get_num(int *num_cvar)
int MPI_T_cvar_handle_alloc(int cvar_index, void *obj_handle,
             MPI_T_cvar_handle *handle, int *count)
int MPI_T_cvar_handle_free(MPI_T_cvar_handle *handle)
int MPI_T_cvar_read(MPI_T_cvar_handle handle, void *buf)
                                                                                  11
int MPI_T_cvar_write(MPI_T_cvar_handle handle, const void *buf)
                                                                                 12
                                                                                 13
int MPI_T_enum_get_info(MPI_T_enum enumtype, int *num, char *name,
                                                                                 14
             int *name_len)
                                                                                  15
int MPI_T_enum_get_item(MPI_T_enum enumtype, int index, int *value,
                                                                                  16
             char *name, int *name_len)
                                                                                 18
int MPI_T_event_callback_get_info(
                                                                                 19
             MPI_T_event_registration event_registration,
                                                                                 20
             MPI_T_cb_safety cb_safety, MPI_Info *info_used)
                                                                                 21
int MPI_T_event_callback_set_info(
                                                                                 22
             MPI_T_event_registration event_registration,
                                                                                 23
             MPI_T_cb_safety cb_safety, MPI_Info info)
                                                                                 24
int MPI_T_event_copy(MPI_T_event_instance event_instance, void *buffer)
                                                                                 26
int MPI_T_event_get_index(const char *name, int *event_index)
                                                                                 27
                                                                                 28
int MPI_T_event_get_info(int event_index, char *name, int *name_len,
                                                                                 29
             int *verbosity, MPI_Datatype array_of_datatypes[],
                                                                                 30
             MPI_Aint array_of_displacements[], int *num_elements,
             MPI_T_enum *enumtype, MPI_Info *info, char *desc,
             int *desc_len, int *bind)
                                                                                 33
int MPI_T_event_get_num(int *num_events)
                                                                                 34
                                                                                 35
int MPI_T_event_get_source(MPI_T_event_instance event_instance,
                                                                                 36
             int *source_index)
                                                                                 37
int MPI_T_event_get_timestamp(MPI_T_event_instance event_instance,
                                                                                 39
             MPI_Count *event_timestamp)
int MPI_T_event_handle_alloc(int event_index, void *obj_handle,
             MPI_Info info, MPI_T_event_registration *event_registration)
                                                                                 42
                                                                                 43
int MPI_T_event_handle_free(MPI_T_event_registration event_registration,
                                                                                 44
             void *user_data,
                                                                                 45
             MPI_T_event_free_cb_function free_cb_function)
                                                                                  46
int MPI_T_event_handle_get_info(
             MPI_T_event_registration event_registration,
```

```
1
                   MPI_Info *info_used)
2
     int MPI_T_event_handle_set_info(
3
                   MPI_T_event_registration event_registration, MPI_Info info)
4
5
     int MPI_T_event_read(MPI_T_event_instance event_instance,
6
                   int element_index, void *buffer)
7
     int MPI_T_event_register_callback(
8
                  MPI_T_event_registration event_registration,
9
                   MPI_T_cb_safety cb_safety, MPI_Info info, void *user_data,
10
                   MPI_T_event_cb_function event_cb_function)
11
12
     int MPI_T_event_set_dropped_handler(
13
                   MPI_T_event_registration event_registration,
14
                   MPI_T_event_dropped_cb_function dropped_cb_function)
15
     int MPI_T_finalize(void)
16
17
     int MPI_T_init_thread(int required, int *provided)
18
     int MPI_T_pvar_get_index(const char *name, int var_class, int *pvar_index)
19
20
     int MPI_T_pvar_get_info(int pvar_index, char *name, int *name_len,
21
                   int *verbosity, int *var_class, MPI_Datatype *datatype,
22
                   MPI_T_enum *enumtype, char *desc, int *desc_len, int *bind,
23
                   int *readonly, int *continuous, int *atomic)
^{24}
     int MPI_T_pvar_get_num(int *num_pvar)
25
26
     int MPI_T_pvar_handle_alloc(MPI_T_pvar_session session, int pvar_index,
27
                   void *obj_handle, MPI_T_pvar_handle *handle, int *count)
28
     int MPI_T_pvar_handle_free(MPI_T_pvar_session session,
29
                   MPI_T_pvar_handle *handle)
30
31
     int MPI_T_pvar_read(MPI_T_pvar_session session, MPI_T_pvar_handle handle,
32
                   void *buf)
33
34
     int MPI_T_pvar_readreset(MPI_T_pvar_session session,
                   MPI_T_pvar_handle handle, void *buf)
35
36
     int MPI_T_pvar_reset(MPI_T_pvar_session session, MPI_T_pvar_handle handle)
37
38
     int MPI_T_pvar_session_create(MPI_T_pvar_session *session)
39
     int MPI_T_pvar_session_free(MPI_T_pvar_session *session)
40
41
     int MPI_T_pvar_start(MPI_T_pvar_session session, MPI_T_pvar_handle handle)
42
     int MPI_T_pvar_stop(MPI_T_pvar_session session, MPI_T_pvar_handle handle)
43
44
     int MPI_T_pvar_write(MPI_T_pvar_session session, MPI_T_pvar_handle handle,
45
                   const void *buf)
46
     int MPI_T_source_get_info(int source_index, char *name, int *name_len,
47
                   char *desc, int *desc_len, MPI_T_source_order *ordering,
48
```

MPI\_Count \*ticks\_per\_second, MPI\_Count \*max\_ticks, MPI\_Info \*info) int MPI\_T\_source\_get\_num(int \*num\_sources) int MPI\_T\_source\_get\_timestamp(int source\_index, MPI\_Count \*timestamp) A.3.16 Deprecated C Bindings int MPI\_Attr\_delete(MPI\_Comm comm, int keyval) int MPI\_Attr\_get(MPI\_Comm comm, int keyval, void \*attribute\_val, int \*flag) int MPI\_Attr\_put(MPI\_Comm comm, int keyval, void \*attribute\_val) int MPI\_DUP\_FN(MPI\_Comm oldcomm, int keyval, void \*extra\_state, void \*attribute\_val\_in, void \*attribute\_val\_out, int \*flag) int MPI\_Info\_get(MPI\_Info info, const char \*key, int valuelen, char \*value, int \*flag) int MPI\_Info\_get\_valuelen(MPI\_Info info, const char \*key, int \*valuelen, int \*flag) int MPI\_Keyval\_create(MPI\_Copy\_function \*copy\_fn, MPI\_Delete\_function \*delete\_fn, int \*keyval, void \*extra\_state) int MPI\_Keyval\_free(int \*keyval) int MPI\_NULL\_COPY\_FN(MPI\_Comm oldcomm, int keyval, void \*extra\_state, void \*attribute\_val\_in, void \*attribute\_val\_out, int \*flag) int MPI\_NULL\_DELETE\_FN(MPI\_Comm comm, int keyval, void \*attribute\_val, void \*extra\_state)

12

13

14

15 16

18

19

20 21

22

23

26

27

28 29

30

39

```
Fortran 2008 Bindings with the mpi_f08 Module
2
     A.4.1 Point-to-Point Communication Fortran 2008 Bindings
3
     MPI_Bsend(buf, count, datatype, dest, tag, comm, ierror)
5
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
6
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, INTENT(IN) :: dest, tag
         TYPE(MPI_Comm), INTENT(IN) :: comm
10
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
11
     MPI_Bsend(buf, count, datatype, dest, tag, comm, ierror)
12
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
13
         INTEGER, INTENT(IN) :: count, dest, tag
14
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
15
         TYPE(MPI_Comm), INTENT(IN) :: comm
16
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
17
18
     MPI_Bsend_init(buf, count, datatype, dest, tag, comm, request, ierror)
19
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
20
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
21
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, INTENT(IN) :: dest, tag
23
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
27
     MPI_Bsend_init(buf, count, datatype, dest, tag, comm, request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
28
         INTEGER, INTENT(IN) :: count, dest, tag
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
33
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
     MPI_Buffer_attach(buffer, size, ierror)
35
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
36
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: size
37
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
38
39
     MPI_Buffer_attach(buffer, size, ierror)
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
41
         INTEGER, INTENT(IN) :: size
42
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
43
     MPI_Buffer_detach(buffer_addr, size, ierror)
44
         USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
45
         TYPE(C_PTR), INTENT(OUT) :: buffer_addr
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: size
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
MPI_Buffer_detach(buffer_addr, size, ierror)
    USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
    TYPE(C_PTR), INTENT(OUT) :: buffer_addr
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Cancel(request, ierror)
    TYPE(MPI_Request), INTENT(IN) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Get_count(status, datatype, count, ierror)
    TYPE(MPI_Status), INTENT(IN) :: status
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 12
                                                                                 13
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: count
                                                                                 14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 15
MPI_Get_count(status, datatype, count, ierror)
                                                                                 16
    TYPE(MPI_Status), INTENT(IN) :: status
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 18
    INTEGER, INTENT(OUT) :: count
                                                                                 19
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 20
                                                                                 21
MPI_Ibsend(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                 22
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                 23
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: dest, tag
                                                                                 26
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 27
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 29
MPI_Ibsend(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                 30
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 34
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 35
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 36
                                                                                 37
MPI_Improbe(source, tag, comm, flag, message, status, ierror)
    INTEGER, INTENT(IN) :: source, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
    LOGICAL, INTENT(OUT) :: flag
    TYPE(MPI_Message), INTENT(OUT) :: message
                                                                                 42
    TYPE(MPI_Status) :: status
                                                                                 43
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 44
MPI_Imrecv(buf, count, datatype, message, request, ierror)
                                                                                 45
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
```

```
1
         TYPE(MPI_Message), INTENT(INOUT) :: message
2
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Imrecv(buf, count, datatype, message, request, ierror)
5
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
6
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Message), INTENT(INOUT) :: message
9
         TYPE(MPI_Request), INTENT(OUT) :: request
10
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
11
12
     MPI_Iprobe(source, tag, comm, flag, status, ierror)
13
         INTEGER, INTENT(IN) :: source, tag
14
         TYPE(MPI_Comm), INTENT(IN) :: comm
15
         LOGICAL, INTENT(OUT) :: flag
16
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Irecv(buf, count, datatype, source, tag, comm, request, ierror)
19
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
20
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
21
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
22
         INTEGER, INTENT(IN) :: source, tag
23
         TYPE(MPI_Comm), INTENT(IN) :: comm
24
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
27
     MPI_Irecv(buf, count, datatype, source, tag, comm, request, ierror)
28
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
29
         INTEGER, INTENT(IN) :: count, source, tag
30
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
33
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
     MPI_Irsend(buf, count, datatype, dest, tag, comm, request, ierror)
35
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
36
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
37
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, INTENT(IN) :: dest, tag
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
42
43
     MPI_Irsend(buf, count, datatype, dest, tag, comm, request, ierror)
44
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
45
         INTEGER, INTENT(IN) :: count, dest, tag
46
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
47
         TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Isend(buf, count, datatype, dest, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: dest, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Isend(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                 12
                                                                                 13
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                 14
    INTEGER, INTENT(IN) :: count, dest, tag
                                                                                 15
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 16
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 18
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 19
MPI_Isendrecv(sendbuf, sendcount, sendtype, dest, sendtag, recvbuf,
                                                                                 20
             recvcount, recvtype, source, recvtag, comm, request, ierror)
                                                                                 21
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 22
    INTEGER, INTENT(IN) :: sendcount, dest, sendtag, recvcount, source,
                                                                                 23
              recvtag
                                                                                 24
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 26
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 27
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 29
MPI_Isendrecv_replace(buf, count, datatype, dest, sendtag, source, recvtag,
             comm, request, ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
    INTEGER, INTENT(IN) :: count, dest, sendtag, source, recvtag
                                                                                 34
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 35
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 36
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 37
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Issend(buf, count, datatype, dest, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 42
    INTEGER, INTENT(IN) :: dest, tag
                                                                                 43
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 44
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 45
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Issend(buf, count, datatype, dest, tag, comm, request, ierror)
```

```
1
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
2
         INTEGER, INTENT(IN) :: count, dest, tag
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
6
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Mprobe(source, tag, comm, message, status, ierror)
         INTEGER, INTENT(IN) :: source, tag
9
         TYPE(MPI_Comm), INTENT(IN) :: comm
10
         TYPE(MPI_Message), INTENT(OUT) :: message
         TYPE(MPI_Status) :: status
12
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
14
     MPI_Mrecv(buf, count, datatype, message, status, ierror)
15
         TYPE(*), DIMENSION(..) :: buf
16
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
17
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
18
         TYPE(MPI_Message), INTENT(INOUT) :: message
19
         TYPE(MPI_Status) :: status
20
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
21
     MPI_Mrecv(buf, count, datatype, message, status, ierror)
22
         TYPE(*), DIMENSION(..) :: buf
23
         INTEGER, INTENT(IN) :: count
24
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Message), INTENT(INOUT) :: message
         TYPE(MPI_Status) :: status
27
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
28
29
     MPI_Probe(source, tag, comm, status, ierror)
30
         INTEGER, INTENT(IN) :: source, tag
31
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Status) :: status
33
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
     MPI_Recv(buf, count, datatype, source, tag, comm, status, ierror)
35
         TYPE(*), DIMENSION(..) :: buf
36
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
37
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, INTENT(IN) :: source, tag
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
42
43
     MPI_Recv(buf, count, datatype, source, tag, comm, status, ierror)
44
         TYPE(*), DIMENSION(..) :: buf
45
         INTEGER, INTENT(IN) :: count, source, tag
46
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
47
         TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Recv_init(buf, count, datatype, source, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: source, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Recv_init(buf, count, datatype, source, tag, comm, request, ierror)
                                                                                 12
                                                                                 13
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
                                                                                 14
    INTEGER, INTENT(IN) :: count, source, tag
                                                                                 15
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 16
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 18
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 19
MPI_Request_free(request, ierror)
                                                                                 20
    TYPE(MPI_Request), INTENT(INOUT) :: request
                                                                                 21
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 22
                                                                                 23
MPI_Request_get_status(request, flag, status, ierror)
    TYPE(MPI_Request), INTENT(IN) :: request
    LOGICAL, INTENT(OUT) :: flag
                                                                                 26
    TYPE(MPI_Status) :: status
                                                                                 27
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 28
MPI_Rsend(buf, count, datatype, dest, tag, comm, ierror)
                                                                                 29
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                 30
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: dest, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 35
                                                                                 36
MPI_Rsend(buf, count, datatype, dest, tag, comm, ierror)
                                                                                 37
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 42
MPI_Rsend_init(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                 43
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                 44
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                 45
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 46
    INTEGER, INTENT(IN) :: dest, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
1
         TYPE(MPI_Request), INTENT(OUT) :: request
2
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Rsend_init(buf, count, datatype, dest, tag, comm, request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
5
         INTEGER, INTENT(IN) :: count, dest, tag
6
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
9
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
10
11
     MPI_Send(buf, count, datatype, dest, tag, comm, ierror)
12
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
13
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
14
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
15
         INTEGER, INTENT(IN) :: dest, tag
16
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Send(buf, count, datatype, dest, tag, comm, ierror)
19
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
20
         INTEGER, INTENT(IN) :: count, dest, tag
21
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
22
         TYPE(MPI_Comm), INTENT(IN) :: comm
23
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
24
     MPI_Send_init(buf, count, datatype, dest, tag, comm, request, ierror)
26
         TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: buf
27
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
28
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, INTENT(IN) :: dest, tag
30
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Send_init(buf, count, datatype, dest, tag, comm, request, ierror)
34
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
35
         INTEGER, INTENT(IN) :: count, dest, tag
36
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
37
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
39
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
41
     MPI_Sendrecv(sendbuf, sendcount, sendtype, dest, sendtag, recvbuf,
42
                  recvcount, recvtype, source, recvtag, comm, status, ierror)
43
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
44
         INTEGER, INTENT(IN) :: sendcount, dest, sendtag, recvcount, source,
45
                   recvtag
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..) :: recvbuf
```

```
TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Sendrecv_replace(buf, count, datatype, dest, sendtag, source, recvtag,
             comm, status, ierror)
    TYPE(*). DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count, dest, sendtag, source, recvtag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 12
                                                                                 13
MPI_Ssend(buf, count, datatype, dest, tag, comm, ierror)
                                                                                 14
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                 15
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                 16
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: dest, tag
                                                                                 18
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 19
                                                                                 20
MPI_Ssend(buf, count, datatype, dest, tag, comm, ierror)
                                                                                 21
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                 22
    INTEGER, INTENT(IN) :: count, dest, tag
                                                                                 23
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 26
                                                                                 27
MPI_Ssend_init(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                 28
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                 29
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                 30
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: dest, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 35
MPI_Ssend_init(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                 36
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                 37
    INTEGER, INTENT(IN) :: count, dest, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 42
                                                                                 43
MPI_Start(request, ierror)
                                                                                 44
    TYPE(MPI_Request), INTENT(INOUT) :: request
                                                                                 45
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Startall(count, array_of_requests, ierror)
    INTEGER, INTENT(IN) :: count
```

```
1
         TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(count)
2
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Test(request, flag, status, ierror)
         TYPE(MPI_Request), INTENT(INOUT) :: request
         LOGICAL, INTENT(OUT) :: flag
6
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
9
     MPI_Test_cancelled(status, flag, ierror)
10
         TYPE(MPI_Status), INTENT(IN) :: status
11
         LOGICAL, INTENT(OUT) :: flag
12
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
     MPI_Testall(count, array_of_requests, flag, array_of_statuses, ierror)
14
         INTEGER, INTENT(IN) :: count
15
         TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(count)
16
         LOGICAL, INTENT(OUT) :: flag
         TYPE(MPI_Status) :: array_of_statuses(*)
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
19
20
     MPI_Testany(count, array_of_requests, index, flag, status, ierror)
21
         INTEGER, INTENT(IN) :: count
22
         TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(count)
23
         INTEGER, INTENT(OUT) :: index
24
         LOGICAL, INTENT(OUT) :: flag
         TYPE(MPI_Status) :: status
26
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
27
     MPI_Testsome(incount, array_of_requests, outcount, array_of_indices,
28
                  array_of_statuses, ierror)
29
         INTEGER, INTENT(IN) :: incount
30
         TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(incount)
         INTEGER, INTENT(OUT) :: outcount, array_of_indices(*)
         TYPE(MPI_Status) :: array_of_statuses(*)
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
35
     MPI_Wait(request, status, ierror)
36
         TYPE(MPI_Request), INTENT(INOUT) :: request
37
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
39
     MPI_Waitall(count, array_of_requests, array_of_statuses, ierror)
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(count)
         TYPE(MPI_Status) :: array_of_statuses(*)
43
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
44
45
     MPI_Waitany(count, array_of_requests, index, status, ierror)
46
         INTEGER, INTENT(IN) :: count
47
         TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(count)
```

```
INTEGER, INTENT(OUT) :: index
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Waitsome(incount, array_of_requests, outcount, array_of_indices,
             array_of_statuses, ierror)
    INTEGER, INTENT(IN) :: incount
    TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(incount)
    INTEGER, INTENT(OUT) :: outcount, array_of_indices(*)
    TYPE(MPI_Status) :: array_of_statuses(*)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 12
                                                                                 13
A.4.2 Partitioned Communication Fortran 2008 Bindings
                                                                                 14
MPI_Parrived(request, partition, flag, ierror)
                                                                                 15
    TYPE(MPI_Request), INTENT(INOUT) :: request
                                                                                 16
    INTEGER, INTENT(IN) :: partition
    LOGICAL, INTENT(OUT) :: flag
                                                                                 18
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 19
                                                                                 20
MPI_Pready(partition, request, ierror)
                                                                                 21
    INTEGER, INTENT(IN) :: partition
                                                                                 22
    TYPE(MPI_Request), INTENT(INOUT) :: request
                                                                                 23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 24
MPI_Pready_list(length, array_of_partitions, request, ierror)
    INTEGER, INTENT(IN) :: length
    INTEGER, INTENT(INOUT) :: array_of_partitions(length)
                                                                                 27
    TYPE(MPI_Request), INTENT(INOUT) :: request
                                                                                 28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 29
                                                                                 30
MPI_Pready_range(partition_low, partition_high, request, ierror)
    INTEGER, INTENT(IN) :: partition_low, partition_high
    TYPE(MPI_Request), INTENT(INOUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 34
MPI_Precv_init(buf, partitions, count, datatype, dest, tag, comm, info,
                                                                                 35
             request, ierror)
                                                                                 36
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                 37
    INTEGER, INTENT(IN) :: partitions, dest, tag
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 42
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 43
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 44
MPI_Psend_init(buf, partitions, count, datatype, dest, tag, comm, info,
             request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
```

```
1
         INTEGER, INTENT(IN) :: partitions, dest, tag
2
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     A.4.3 Datatypes Fortran 2008 Bindings
10
11
     INTEGER(KIND=MPI_ADDRESS_KIND) MPI_Aint_add(base, disp)
12
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: base, disp
13
     INTEGER(KIND=MPI_ADDRESS_KIND) MPI_Aint_diff(addr1, addr2)
14
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: addr1, addr2
15
16
     MPI_Get_address(location, address, ierror)
17
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: location
18
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: address
19
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
20
     MPI_Get_elements(status, datatype, count, ierror)
21
         TYPE(MPI_Status), INTENT(IN) :: status
22
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
23
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: count
24
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
     MPI_Get_elements(status, datatype, count, ierror)
27
         TYPE(MPI_Status), INTENT(IN) :: status
28
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
29
         INTEGER, INTENT(OUT) :: count
30
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
31
     MPI_Get_elements_x(status, datatype, count, ierror)
32
         TYPE(MPI_Status), INTENT(IN) :: status
33
34
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: count
35
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
36
37
     MPI_Pack(inbuf, incount, datatype, outbuf, outsize, position, comm, ierror)
38
         TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
39
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: incount, outsize
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
41
         TYPE(*), DIMENSION(..) :: outbuf
42
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(INOUT) :: position
43
         TYPE(MPI_Comm), INTENT(IN) :: comm
44
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
     MPI_Pack(inbuf, incount, datatype, outbuf, outsize, position, comm, ierror)
46
47
         TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
         INTEGER, INTENT(IN) :: incount, outsize
```

```
TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(*), DIMENSION(..) :: outbuf
    INTEGER, INTENT(INOUT) :: position
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Pack_external(datarep, inbuf, incount, datatype, outbuf, outsize,
             position, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: datarep
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: incount, outsize
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 12
    TYPE(*), DIMENSION(..) :: outbuf
                                                                                 13
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(INOUT) :: position
                                                                                 14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 15
MPI_Pack_external(datarep, inbuf, incount, datatype, outbuf, outsize,
                                                                                 16
             position, ierror)
                                                                                 18
    CHARACTER(LEN=*), INTENT(IN) :: datarep
                                                                                 19
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
    INTEGER, INTENT(IN) :: incount
                                                                                 20
                                                                                 21
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 22
    TYPE(*), DIMENSION(..) :: outbuf
                                                                                 23
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: outsize
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(INOUT) :: position
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Pack_external_size(datarep, incount, datatype, size, ierror)
                                                                                 27
    CHARACTER(LEN=*), INTENT(IN) :: datarep
                                                                                 28
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: incount
                                                                                 29
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 30
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Pack_external_size(datarep, incount, datatype, size, ierror)
                                                                                 34
    CHARACTER(LEN=*), INTENT(IN) :: datarep
                                                                                 35
    INTEGER, INTENT(IN) :: incount
                                                                                 36
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 37
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Pack_size(incount, datatype, comm, size, ierror)
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: incount
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 42
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 43
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: size
                                                                                 44
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 45
MPI_Pack_size(incount, datatype, comm, size, ierror)
    INTEGER, INTENT(IN) :: incount
```

```
1
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
2
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, INTENT(OUT) :: size
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Type_commit(datatype, ierror)
6
         TYPE(MPI_Datatype), INTENT(INOUT) :: datatype
7
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
8
9
     MPI_Type_contiguous(count, oldtype, newtype, ierror)
10
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
11
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
12
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
13
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
14
     MPI_Type_contiguous(count, oldtype, newtype, ierror)
15
         INTEGER, INTENT(IN) :: count
16
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
17
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
19
20
     MPI_Type_create_darray(size, rank, ndims, array_of_gsizes,
21
                  array_of_distribs, array_of_dargs, array_of_psizes, order,
22
                  oldtype, newtype, ierror)
23
         INTEGER, INTENT(IN) :: size, rank, ndims, array_of_distribs(ndims),
24
                   array_of_dargs(ndims), array_of_psizes(ndims), order
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: array_of_gsizes(ndims)
26
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
27
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
28
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
29
     MPI_Type_create_darray(size, rank, ndims, array_of_gsizes,
30
                   array_of_distribs, array_of_dargs, array_of_psizes, order,
31
                  oldtype, newtype, ierror)
         INTEGER, INTENT(IN) :: size, rank, ndims, array_of_gsizes(ndims),
                   array_of_distribs(ndims), array_of_dargs(ndims),
34
                   array_of_psizes(ndims), order
35
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
36
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
37
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
38
39
     MPI_Type_create_hindexed(count, array_of_blocklengths,
                   array_of_displacements, oldtype, newtype, ierror)
41
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count,
42
                   array_of_blocklengths(count), array_of_displacements(count)
43
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
44
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
45
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
46
     MPI_Type_create_hindexed(count, array_of_blocklengths,
47
                  array_of_displacements, oldtype, newtype, ierror)
```

```
INTEGER, INTENT(IN) :: count, array_of_blocklengths(count)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) ::
              array_of_displacements(count)
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Type_create_hindexed_block(count, blocklength, array_of_displacements,
             oldtype, newtype, ierror)
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count, blocklength,
              array_of_displacements(count)
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 12
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                 13
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 14
                                                                                 15
MPI_Type_create_hindexed_block(count, blocklength, array_of_displacements,
                                                                                 16
             oldtype, newtype, ierror)
    INTEGER, INTENT(IN) :: count, blocklength
                                                                                 18
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) ::
                                                                                 19
              array_of_displacements(count)
                                                                                 20
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 21
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                 22
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 23
MPI_Type_create_hvector(count, blocklength, stride, oldtype, newtype,
                                                                                 24
              ierror)
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count, blocklength, stride
                                                                                 26
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 27
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                 28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 29
                                                                                 30
MPI_Type_create_hvector(count, blocklength, stride, oldtype, newtype,
              ierror)
    INTEGER, INTENT(IN) :: count, blocklength
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: stride
                                                                                 34
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 35
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                 36
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 37
MPI_Type_create_indexed_block(count, blocklength, array_of_displacements,
              oldtype, newtype, ierror)
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count, blocklength,
              array_of_displacements(count)
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 42
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                 43
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 44
                                                                                 45
MPI_Type_create_indexed_block(count, blocklength, array_of_displacements,
             oldtype, newtype, ierror)
```

```
1
         INTEGER, INTENT(IN) :: count, blocklength,
2
                   array_of_displacements(count)
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
    MPI_Type_create_resized(oldtype, lb, extent, newtype, ierror)
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: lb, extent
9
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
10
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
11
12
     MPI_Type_create_resized(oldtype, lb, extent, newtype, ierror)
13
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
14
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: lb, extent
15
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
16
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
17
     MPI_Type_create_struct(count, array_of_blocklengths,
                  array_of_displacements, array_of_types, newtype, ierror)
19
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count,
20
                   array_of_blocklengths(count), array_of_displacements(count)
21
         TYPE(MPI_Datatype), INTENT(IN) :: array_of_types(count)
22
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
23
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
24
    MPI_Type_create_struct(count, array_of_blocklengths,
26
                  array_of_displacements, array_of_types, newtype, ierror)
27
         INTEGER, INTENT(IN) :: count, array_of_blocklengths(count)
28
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) ::
29
                   array_of_displacements(count)
30
         TYPE(MPI_Datatype), INTENT(IN) :: array_of_types(count)
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Type_create_subarray(ndims, array_of_sizes, array_of_subsizes,
34
                  array_of_starts, order, oldtype, newtype, ierror)
35
         INTEGER, INTENT(IN) :: ndims, array_of_sizes(ndims),
36
                   array_of_subsizes(ndims), array_of_starts(ndims), order
37
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
39
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
41
     MPI_Type_create_subarray(ndims, array_of_sizes, array_of_subsizes,
42
                  array_of_starts, order, oldtype, newtype, ierror)
43
         INTEGER, INTENT(IN) :: ndims, order
44
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: array_of_sizes(ndims),
45
                   array_of_subsizes(ndims), array_of_starts(ndims)
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
47
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Type_dup(oldtype, newtype, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Type_free(datatype, ierror)
    TYPE(MPI_Datatype), INTENT(INOUT) :: datatype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Type_get_contents(datatype, max_integers, max_addresses, max_datatypes,
             array_of_integers, array_of_addresses, array_of_datatypes,
             ierror)
                                                                                 13
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 14
    INTEGER, INTENT(IN) :: max_integers, max_addresses, max_datatypes
                                                                                 15
    INTEGER, INTENT(OUT) :: array_of_integers(max_integers)
                                                                                 16
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) ::
              array_of_addresses(max_addresses)
    TYPE(MPI_Datatype), INTENT(OUT) :: array_of_datatypes(max_datatypes)
                                                                                 19
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 20
                                                                                 21
MPI_Type_get_contents(datatype, max_integers, max_addresses,
                                                                                 22
             max_large_counts, max_datatypes, array_of_integers,
                                                                                 23
             array_of_addresses, array_of_large_counts, array_of_datatypes,
                                                                                 24
             ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: max_integers,
                                                                                 27
              max_addresses, max_large_counts, max_datatypes
                                                                                 28
    INTEGER, INTENT(OUT) :: array_of_integers(max_integers)
                                                                                 29
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) ::
                                                                                 30
              array_of_addresses(max_addresses)
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) ::
              array_of_large_counts(max_large_counts)
                                                                                 33
    TYPE(MPI_Datatype), INTENT(OUT) :: array_of_datatypes(max_datatypes)
                                                                                 34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 35
MPI_Type_get_envelope(datatype, num_integers, num_addresses, num_datatypes,
                                                                                 36
             combiner, ierror)
                                                                                 37
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(OUT) :: num_integers, num_addresses, num_datatypes,
              combiner
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 42
MPI_Type_get_envelope(datatype, num_integers, num_addresses,
                                                                                 43
             num_large_counts, num_datatypes, combiner, ierror)
                                                                                 44
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 45
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: num_integers,
                                                                                 46
              num_addresses, num_large_counts, num_datatypes
    INTEGER, INTENT(OUT) :: combiner
```

```
1
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
2
     MPI_Type_get_extent(datatype, lb, extent, ierror)
3
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: lb, extent
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
7
     MPI_Type_get_extent(datatype, lb, extent, ierror)
8
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
9
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: lb, extent
10
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
11
    MPI_Type_get_extent_x(datatype, lb, extent, ierror)
12
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
13
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: lb, extent
14
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
15
16
    MPI_Type_get_true_extent(datatype, true_lb, true_extent, ierror)
17
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
18
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: true_lb, true_extent
19
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
20
     MPI_Type_get_true_extent(datatype, true_lb, true_extent, ierror)
21
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
22
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: true_lb, true_extent
23
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
24
    MPI_Type_get_true_extent_x(datatype, true_lb, true_extent, ierror)
26
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
27
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: true_lb, true_extent
28
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
29
     MPI_Type_indexed(count, array_of_blocklengths, array_of_displacements,
30
                  oldtype, newtype, ierror)
31
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count,
                   array_of_blocklengths(count), array_of_displacements(count)
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
34
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
35
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
36
37
     MPI_Type_indexed(count, array_of_blocklengths, array_of_displacements,
38
                  oldtype, newtype, ierror)
39
         INTEGER, INTENT(IN) :: count, array_of_blocklengths(count),
                   array_of_displacements(count)
41
         TYPE(MPI_Datatype), INTENT(IN) :: oldtype
42
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
43
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
44
    MPI_Type_size(datatype, size, ierror)
45
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
46
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: size
47
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
MPI_Type_size(datatype, size, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Type_size_x(datatype, size, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Type_vector(count, blocklength, stride, oldtype, newtype, ierror)
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count, blocklength, stride
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 12
                                                                                 13
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                 14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 15
MPI_Type_vector(count, blocklength, stride, oldtype, newtype, ierror)
                                                                                 16
    INTEGER, INTENT(IN) :: count, blocklength, stride
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 18
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                 19
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 20
                                                                                 21
MPI_Unpack(inbuf, insize, position, outbuf, outcount, datatype, comm,
                                                                                 22
             ierror)
                                                                                 23
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: insize, outcount
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(INOUT) :: position
    TYPE(*), DIMENSION(..) :: outbuf
                                                                                 27
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 28
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 29
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Unpack(inbuf, insize, position, outbuf, outcount, datatype, comm,
             ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
    INTEGER, INTENT(IN) :: insize, outcount
                                                                                 34
    INTEGER, INTENT(INOUT) :: position
                                                                                 35
    TYPE(*), DIMENSION(..) :: outbuf
                                                                                 36
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 37
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Unpack_external(datarep, inbuf, insize, position, outbuf, outcount,
             datatype, ierror)
                                                                                 42
    CHARACTER(LEN=*), INTENT(IN) :: datarep
                                                                                 43
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
                                                                                 44
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: insize
                                                                                 45
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(INOUT) :: position
    TYPE(*), DIMENSION(..) :: outbuf
    INTEGER, INTENT(IN) :: outcount
```

```
1
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
2
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Unpack_external(datarep, inbuf, insize, position, outbuf, outcount,
                  datatype, ierror)
         CHARACTER(LEN=*), INTENT(IN) :: datarep
6
         TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: insize, outcount
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(INOUT) :: position
         TYPE(*), DIMENSION(..) :: outbuf
10
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
12
13
14
     A.4.4 Collective Communication Fortran 2008 Bindings
15
    MPI_Allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
16
                  comm, ierror)
17
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
19
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
20
         TYPE(*), DIMENSION(..) :: recvbuf
21
         TYPE(MPI_Comm), INTENT(IN) :: comm
22
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
23
24
     MPI_Allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
25
                  comm, ierror)
26
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
27
         INTEGER, INTENT(IN) :: sendcount, recvcount
28
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..) :: recvbuf
30
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Allgather_init(sendbuf, sendcount, sendtype, recvbuf, recvcount,
33
34
                  recvtype, comm, info, request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
35
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
36
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
37
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
42
43
     MPI_Allgather_init(sendbuf, sendcount, sendtype, recvbuf, recvcount,
44
                  recvtype, comm, info, request, ierror)
45
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
46
         INTEGER, INTENT(IN) :: sendcount, recvcount
47
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
```

```
TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
             recvtype, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recycounts(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..) :: recvbuf
                                                                                 12
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: displs(*)
                                                                                 13
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 15
MPI_Allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
                                                                                 16
             recvtype, comm, ierror)
    TYPE(*), DIMENSION(...), INTENT(IN) :: sendbuf
                                                                                 19
    INTEGER, INTENT(IN) :: sendcount, recvcounts(*), displs(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 20
                                                                                 21
    TYPE(*), DIMENSION(..) :: recvbuf
                                                                                 22
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Allgatherv_init(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
             displs, recvtype, comm, info, request, ierror)
                                                                                 26
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 27
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
                                                                                 28
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 29
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 34
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 35
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 36
                                                                                 37
MPI_Allgatherv_init(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
             displs, recvtype, comm, info, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN) :: sendcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 42
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 43
    INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*), displs(*)
                                                                                 44
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 45
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
1
    MPI_Allreduce(sendbuf, recvbuf, count, datatype, op, comm, ierror)
2
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
3
         TYPE(*), DIMENSION(..) :: recvbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
9
    MPI_Allreduce(sendbuf, recvbuf, count, datatype, op, comm, ierror)
10
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
11
         TYPE(*), DIMENSION(..) :: recvbuf
12
         INTEGER, INTENT(IN) :: count
13
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
14
         TYPE(MPI_Op), INTENT(IN) :: op
15
         TYPE(MPI_Comm), INTENT(IN) :: comm
16
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
17
18
     MPI_Allreduce_init(sendbuf, recvbuf, count, datatype, op, comm, info,
19
                  request, ierror)
20
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
21
         TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
22
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
23
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
26
         TYPE(MPI_Info), INTENT(IN) :: info
27
         TYPE(MPI_Request), INTENT(OUT) :: request
28
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
29
     MPI_Allreduce_init(sendbuf, recvbuf, count, datatype, op, comm, info,
30
                  request, ierror)
31
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
32
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: count
34
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
35
         TYPE(MPI_Op), INTENT(IN) :: op
36
         TYPE(MPI_Comm), INTENT(IN) :: comm
37
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
39
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
41
     MPI_Alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
42
                  comm, ierror)
43
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
44
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
45
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..) :: recvbuf
47
         TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
             comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    INTEGER, INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..) :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Alltoall_init(sendbuf, sendcount, sendtype, recvbuf, recvcount,
             recvtype, comm, info, request, ierror)
                                                                                 12
                                                                                 13
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 14
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
                                                                                 15
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 16
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 18
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 19
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 20
                                                                                 21
MPI_Alltoall_init(sendbuf, sendcount, sendtype, recvbuf, recvcount,
                                                                                 22
             recvtype, comm, info, request, ierror)
                                                                                 23
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 24
    INTEGER, INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 26
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 27
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 28
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 29
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 30
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf, recvcounts,
             rdispls, recvtype, comm, ierror)
                                                                                 34
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
                                                                                 35
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcounts(*),
                                                                                 36
              recvcounts(*)
                                                                                 37
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: sdispls(*), rdispls(*)
                                                                                 38
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..) :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf, recvcounts,
                                                                                 43
             rdispls, recvtype, comm, ierror)
                                                                                 44
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
                                                                                 45
    INTEGER, INTENT(IN) :: sendcounts(*), sdispls(*), recvcounts(*),
                                                                                 46
              rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
```

```
1
         TYPE(*), DIMENSION(..) :: recvbuf
2
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Alltoallv_init(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
5
                  recvcounts, rdispls, recvtype, comm, info, request, ierror)
6
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
                   sendcounts(*), recvcounts(*)
9
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
10
                   rdispls(*)
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
12
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
13
         TYPE(MPI_Comm), INTENT(IN) :: comm
14
         TYPE(MPI_Info), INTENT(IN) :: info
15
         TYPE(MPI_Request), INTENT(OUT) :: request
16
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
17
18
     MPI_Alltoallv_init(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
19
                  recvcounts, rdispls, recvtype, comm, info, request, ierror)
20
         TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: sendbuf
21
         INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),
22
                   recvcounts(*), rdispls(*)
23
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
26
         TYPE(MPI_Info), INTENT(IN) :: info
27
         TYPE(MPI_Request), INTENT(OUT) :: request
28
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
29
     MPI_Alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf, recvcounts,
30
                  rdispls, recvtypes, comm, ierror)
31
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
32
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcounts(*),
33
                   recvcounts(*)
34
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: sdispls(*), rdispls(*)
35
         TYPE(MPI_Datatype), INTENT(IN) :: sendtypes(*), recvtypes(*)
36
         TYPE(*), DIMENSION(..) :: recvbuf
37
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
39
40
     MPI_Alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf, recvcounts,
41
                  rdispls, recvtypes, comm, ierror)
42
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
43
         INTEGER, INTENT(IN) :: sendcounts(*), sdispls(*), recvcounts(*),
44
                   rdispls(*)
45
         TYPE(MPI_Datatype), INTENT(IN) :: sendtypes(*), recvtypes(*)
         TYPE(*), DIMENSION(..) :: recvbuf
47
         TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Alltoallw_init(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
             recvcounts, rdispls, recvtypes, comm, info, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
              sendcounts(*), recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
              rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
              recvtypes(*)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                  12
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  13
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 14
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  15
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  16
MPI_Alltoallw_init(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
                                                                                  18
             recvcounts, rdispls, recvtypes, comm, info, request, ierror)
                                                                                  19
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),
                                                                                 20
                                                                                 21
              recvcounts(*), rdispls(*)
                                                                                 22
    TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
                                                                                 23
              recvtypes(*)
                                                                                  24
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  26
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                  27
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 29
MPI_Barrier(comm, ierror)
                                                                                  30
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  33
MPI_Barrier_init(comm, info, request, ierror)
                                                                                 34
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 35
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 36
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 37
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Bcast(buffer, count, datatype, root, comm, ierror)
    TYPE(*), DIMENSION(..) :: buffer
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                  42
    INTEGER, INTENT(IN) :: root
                                                                                  43
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  44
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  45
                                                                                  46
MPI_Bcast(buffer, count, datatype, root, comm, ierror)
    TYPE(*), DIMENSION(..) :: buffer
```

```
1
         INTEGER, INTENT(IN) :: count, root
2
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
    MPI_Bcast_init(buffer, count, datatype, root, comm, info, request, ierror)
6
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, INTENT(IN) :: root
10
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
12
         TYPE(MPI_Request), INTENT(OUT) :: request
13
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
14
15
    MPI_Bcast_init(buffer, count, datatype, root, comm, info, request, ierror)
16
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
17
         INTEGER, INTENT(IN) :: count, root
18
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
19
         TYPE(MPI_Comm), INTENT(IN) :: comm
20
         TYPE(MPI_Info), INTENT(IN) :: info
21
         TYPE(MPI_Request), INTENT(OUT) :: request
22
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
23
     MPI_Exscan(sendbuf, recvbuf, count, datatype, op, comm, ierror)
24
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
         TYPE(*), DIMENSION(..) :: recvbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
27
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
28
         TYPE(MPI_Op), INTENT(IN) :: op
29
         TYPE(MPI_Comm), INTENT(IN) :: comm
30
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
31
     MPI_Exscan(sendbuf, recvbuf, count, datatype, op, comm, ierror)
33
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
34
         TYPE(*), DIMENSION(..) :: recvbuf
35
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
37
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Exscan_init(sendbuf, recvbuf, count, datatype, op, comm, info, request,
41
                  ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
43
         TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
44
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
45
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Exscan_init(sendbuf, recvbuf, count, datatype, op, comm, info, request,
             ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 12
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 13
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 15
                                                                                 16
MPI_Gather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
             root, comm, ierror)
                                                                                 18
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
                                                                                 19
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 20
                                                                                 21
    TYPE(*), DIMENSION(..) :: recvbuf
                                                                                 22
    INTEGER, INTENT(IN) :: root
                                                                                 23
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Gather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
                                                                                 26
             root, comm, ierror)
                                                                                 27
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
                                                                                 28
    INTEGER, INTENT(IN) :: sendcount, recvcount, root
                                                                                 29
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 30
    TYPE(*), DIMENSION(..) :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Gather_init(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
                                                                                 35
             root, comm, info, request, ierror)
                                                                                 36
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 37
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER, INTENT(IN) :: root
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 42
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 43
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 44
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Gather_init(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
             root, comm, info, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
```

```
1
         INTEGER, INTENT(IN) :: sendcount, recvcount, root
2
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
    MPI_Gatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
9
                  recvtype, root, comm, ierror)
10
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcounts(*)
12
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
13
         TYPE(*), DIMENSION(..) :: recvbuf
14
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: displs(*)
15
         INTEGER, INTENT(IN) :: root
16
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
18
19
    MPI_Gatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
20
                  recvtype, root, comm, ierror)
21
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
22
         INTEGER, INTENT(IN) :: sendcount, recvcounts(*), displs(*), root
23
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..) :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
26
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
27
    MPI_Gatherv_init(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
28
                  recvtype, root, comm, info, request, ierror)
29
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
30
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
34
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
35
         INTEGER, INTENT(IN) :: root
36
         TYPE(MPI_Comm), INTENT(IN) :: comm
37
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
41
     MPI_Gatherv_init(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
42
                  recvtype, root, comm, info, request, ierror)
43
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
44
         INTEGER, INTENT(IN) :: sendcount, root
45
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
47
         INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*), displs(*)
```

```
TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Iallgather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
             comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 12
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 13
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 14
                                                                                 15
MPI_Iallgather(sendbuf, sendcount, sendtype, recybuf, recycount, recytype,
             comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 18
    INTEGER, INTENT(IN) :: sendcount, recvcount
                                                                                 19
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 20
                                                                                 21
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 22
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Iallgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
             recvtype, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 27
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
                                                                                 28
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 29
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 35
                                                                                 36
MPI_Iallgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
                                                                                 37
             recvtype, comm, request, ierror)
    TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN) :: sendcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 42
    INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*), displs(*)
                                                                                 43
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 44
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 45
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Iallreduce(sendbuf, recvbuf, count, datatype, op, comm, request,
             ierror)
```

```
1
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
2
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
9
     MPI_Iallreduce(sendbuf, recvbuf, count, datatype, op, comm, request,
10
                  ierror)
11
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
12
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
13
         INTEGER, INTENT(IN) :: count
14
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
15
         TYPE(MPI_Op), INTENT(IN) :: op
16
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
19
20
     MPI_Ialltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
21
                  comm, request, ierror)
22
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
23
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
24
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
26
         TYPE(MPI_Comm), INTENT(IN) :: comm
27
         TYPE(MPI_Request), INTENT(OUT) :: request
28
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
29
     MPI_Ialltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
30
                  comm, request, ierror)
31
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
32
         INTEGER, INTENT(IN) :: sendcount, recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
34
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
35
         TYPE(MPI_Comm), INTENT(IN) :: comm
36
         TYPE(MPI_Request), INTENT(OUT) :: request
37
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
38
39
     MPI_Ialltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf, recvcounts,
                  rdispls, recvtype, comm, request, ierror)
41
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
42
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
43
                   sendcounts(*), recvcounts(*)
44
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
45
                   rdispls(*)
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
47
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
```

```
TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Ialltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf, recvcounts,
             rdispls, recvtype, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),
              recvcounts(*), rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 12
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 13
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 14
                                                                                 15
MPI_Ialltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
                                                                                 16
             recvcounts, rdispls, recvtypes, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 18
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
                                                                                 19
              sendcounts(*), recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
                                                                                 20
                                                                                 21
              rdispls(*)
                                                                                 22
    TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
                                                                                 23
              recvtypes(*)
                                                                                 24
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 26
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 27
                                                                                 28
MPI_Ialltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
                                                                                 29
             recvcounts, rdispls, recvtypes, comm, request, ierror)
                                                                                 30
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 31
    INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),
              recvcounts(*), rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
                                                                                 34
              recvtypes(*)
                                                                                 35
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 36
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 37
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Ibarrier(comm, request, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 42
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 43
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 44
MPI_Ibcast(buffer, count, datatype, root, comm, request, ierror)
                                                                                 45
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
                                                                                 46
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
```

```
1
         INTEGER, INTENT(IN) :: root
2
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
5
    MPI_Ibcast(buffer, count, datatype, root, comm, request, ierror)
6
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buffer
7
         INTEGER, INTENT(IN) :: count, root
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
9
         TYPE(MPI_Comm), INTENT(IN) :: comm
10
         TYPE(MPI_Request), INTENT(OUT) :: request
11
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
12
13
     MPI_Iexscan(sendbuf, recvbuf, count, datatype, op, comm, request, ierror)
14
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
15
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
16
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
18
         TYPE(MPI_Op), INTENT(IN) :: op
19
         TYPE(MPI_Comm), INTENT(IN) :: comm
20
         TYPE(MPI_Request), INTENT(OUT) :: request
21
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
22
     MPI_Iexscan(sendbuf, recvbuf, count, datatype, op, comm, request, ierror)
23
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
24
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
27
         TYPE(MPI_Op), INTENT(IN) :: op
28
         TYPE(MPI_Comm), INTENT(IN) :: comm
29
         TYPE(MPI_Request), INTENT(OUT) :: request
30
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
31
     MPI_Igather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
33
                  root, comm, request, ierror)
34
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
35
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
36
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
37
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: root
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
41
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Igather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
43
                  root, comm, request, ierror)
44
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
45
         INTEGER, INTENT(IN) :: sendcount, recvcount, root
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
```

```
TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Igatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
             recvtype, root, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
                                                                                 12
    INTEGER, INTENT(IN) :: root
                                                                                 13
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 14
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 15
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 16
MPI_Igatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
             recvtype, root, comm, request, ierror)
    TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 19
    INTEGER, INTENT(IN) :: sendcount, root
                                                                                 20
                                                                                 21
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 22
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*), displs(*)
                                                                                 24
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 27
MPI_Ireduce(sendbuf, recvbuf, count, datatype, op, root, comm, request,
                                                                                 28
             ierror)
                                                                                 29
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 30
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                 34
    INTEGER, INTENT(IN) :: root
                                                                                 35
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 36
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 37
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Ireduce(sendbuf, recvbuf, count, datatype, op, root, comm, request,
             ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 42
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 43
    INTEGER, INTENT(IN) :: count, root
                                                                                 44
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 45
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
```

```
1
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
2
     MPI_Ireduce_scatter(sendbuf, recvbuf, recvcounts, datatype, op, comm,
3
                  request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
5
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
6
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
9
         TYPE(MPI_Comm), INTENT(IN) :: comm
10
         TYPE(MPI_Request), INTENT(OUT) :: request
11
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
12
13
     MPI_Ireduce_scatter(sendbuf, recvbuf, recvcounts, datatype, op, comm,
14
                  request, ierror)
15
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
16
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
18
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
19
         TYPE(MPI_Op), INTENT(IN) :: op
20
         TYPE(MPI_Comm), INTENT(IN) :: comm
21
         TYPE(MPI_Request), INTENT(OUT) :: request
22
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
23
     MPI_Ireduce_scatter_block(sendbuf, recvbuf, recvcount, datatype, op, comm,
24
                  request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
26
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
27
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: recvcount
28
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
29
         TYPE(MPI_Op), INTENT(IN) :: op
30
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
33
34
     MPI_Ireduce_scatter_block(sendbuf, recvbuf, recvcount, datatype, op, comm,
35
                  request, ierror)
36
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
37
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
41
         TYPE(MPI_Comm), INTENT(IN) :: comm
42
         TYPE(MPI_Request), INTENT(OUT) :: request
43
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
44
     MPI_Iscan(sendbuf, recvbuf, count, datatype, op, comm, request, ierror)
45
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
46
         TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
47
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
```

```
TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Iscan(sendbuf, recvbuf, count, datatype, op, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                 12
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 13
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 15
                                                                                 16
MPI_Iscatter(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
             root, comm, request, ierror)
                                                                                 18
    TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 19
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 20
                                                                                 21
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 22
    INTEGER, INTENT(IN) :: root
                                                                                 23
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Iscatter(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
                                                                                 27
             root, comm, request, ierror)
                                                                                 28
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 29
    INTEGER, INTENT(IN) :: sendcount, recvcount, root
                                                                                 30
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 35
                                                                                 36
MPI Iscattery(sendbuf, sendcounts, displs, sendtype, recybuf, recycount,
                                                                                 37
             recvtype, root, comm, request, ierror)
    TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: sendcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 42
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 43
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: recvcount
                                                                                 44
    INTEGER, INTENT(IN) :: root
                                                                                 45
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
1
            MPI_Iscatterv(sendbuf, sendcounts, displs, sendtype, recvbuf, recvcount,
       2
                          recvtype, root, comm, request, ierror)
                TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), displs(*)
                TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                INTEGER, INTENT(IN) :: recvcount, root
                TYPE(MPI_Comm), INTENT(IN) :: comm
                TYPE(MPI_Request), INTENT(OUT) :: request
       10
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       11
            MPI_Op_commutative(op, commute, ierror)
       12
                TYPE(MPI_Op), INTENT(IN) :: op
       13
                LOGICAL, INTENT(OUT) :: commute
       14
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       15
            MPI_Op_create(user_fn, commute, op, ierror)
                                                                        Pythonization group will fix this globally!!!
#-error! 17
                PROCEDURE (MPI_User_function), INTENT(IN) :: user_fn
Done
                                                                         -> Dan.
                LOGICAL, INTENT(IN) :: commute
in
       19
                TYPE(MPI_Op), INTENT(OUT) :: op
PR414
       20
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       21
            MPI_Op_create_c(user_fn, commute, op, ierror)
       22
                PROCEDURE(MPI_User_function_c), INTENT(IN) :: user_fn
#-error 23
                LOGICAL, INTENT(IN) :: commute
Done
       24
lin
                TYPE(MPI_Op), INTENT(OUT) :: op
       25
PR414
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       26
       27
            MPI_Op_free(op, ierror)
       28
                TYPE(MPI_Op), INTENT(INOUT) :: op
       29
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       30
            MPI_Reduce(sendbuf, recvbuf, count, datatype, op, root, comm, ierror)
       31
                TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
       32
                TYPE(*), DIMENSION(..) :: recvbuf
                INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
       34
                TYPE(MPI_Datatype), INTENT(IN) :: datatype
       35
                TYPE(MPI_Op), INTENT(IN) :: op
       36
                INTEGER, INTENT(IN) :: root
       37
                TYPE(MPI_Comm), INTENT(IN) :: comm
       38
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       39
       40
            MPI_Reduce(sendbuf, recvbuf, count, datatype, op, root, comm, ierror)
       41
                TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
       42
                TYPE(*), DIMENSION(..) :: recvbuf
       43
                INTEGER, INTENT(IN) :: count, root
       44
                TYPE(MPI_Datatype), INTENT(IN) :: datatype
       45
                TYPE(MPI_Op), INTENT(IN) :: op
                TYPE(MPI_Comm), INTENT(IN) :: comm
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
MPI_Reduce_init(sendbuf, recvbuf, count, datatype, op, root, comm, info,
             request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    INTEGER, INTENT(IN) :: root
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 12
                                                                                 13
MPI_Reduce_init(sendbuf, recvbuf, count, datatype, op, root, comm, info,
                                                                                 14
             request, ierror)
                                                                                 15
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 16
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER, INTENT(IN) :: count, root
                                                                                 18
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 19
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                 20
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 21
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 22
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 24
MPI_Reduce_local(inbuf, inoutbuf, count, datatype, op, ierror)
                                                                                 26
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
                                                                                 27
    TYPE(*), DIMENSION(..) :: inoutbuf
                                                                                 28
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                 29
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                 30
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Reduce_local(inbuf, inoutbuf, count, datatype, op, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: inbuf
                                                                                 34
    TYPE(*), DIMENSION(..) :: inoutbuf
                                                                                 35
    INTEGER, INTENT(IN) :: count
                                                                                 36
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 37
    TYPE(MPI_Op), INTENT(IN) :: op
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Reduce_scatter(sendbuf, recvbuf, recvcounts, datatype, op, comm,
             ierror)
                                                                                 42
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
                                                                                 43
    TYPE(*), DIMENSION(..) :: recvbuf
                                                                                 44
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: recvcounts(*)
                                                                                 45
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 46
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
1
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
2
     MPI_Reduce_scatter(sendbuf, recvbuf, recvcounts, datatype, op, comm,
3
                  ierror)
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
         TYPE(*), DIMENSION(..) :: recvbuf
         INTEGER, INTENT(IN) :: recvcounts(*)
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
10
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
11
12
     MPI_Reduce_scatter_block(sendbuf, recvbuf, recvcount, datatype, op, comm,
13
                  ierror)
14
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
15
         TYPE(*), DIMENSION(..) :: recvbuf
16
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
19
         TYPE(MPI_Comm), INTENT(IN) :: comm
20
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
21
     MPI_Reduce_scatter_block(sendbuf, recvbuf, recvcount, datatype, op, comm,
22
                  ierror)
23
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
24
         TYPE(*), DIMENSION(..) :: recvbuf
         INTEGER, INTENT(IN) :: recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
27
         TYPE(MPI_Op), INTENT(IN) :: op
28
         TYPE(MPI_Comm), INTENT(IN) :: comm
29
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
30
31
     MPI_Reduce_scatter_block_init(sendbuf, recvbuf, recvcount, datatype, op,
32
                  comm, info, request, ierror)
33
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
34
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
35
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
37
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
41
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Reduce_scatter_block_init(sendbuf, recvbuf, recvcount, datatype, op,
43
                  comm, info, request, ierror)
44
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
45
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
```

```
TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Reduce_scatter_init(sendbuf, recvbuf, recvcounts, datatype, op, comm,
             info, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 12
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                 13
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 14
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 15
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 16
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Reduce_scatter_init(sendbuf, recvbuf, recvcounts, datatype, op, comm,
                                                                                 18
                                                                                 19
             info, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 20
                                                                                 21
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 22
    INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
                                                                                 23
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 24
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 26
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 27
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 29
MPI_Scan(sendbuf, recvbuf, count, datatype, op, comm, ierror)
                                                                                 30
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    TYPE(*), DIMENSION(..) :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 34
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                 35
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 36
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 37
MPI_Scan(sendbuf, recvbuf, count, datatype, op, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    TYPE(*), DIMENSION(..) :: recvbuf
    INTEGER, INTENT(IN) :: count
                                                                                 42
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 43
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                 44
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Scan_init(sendbuf, recvbuf, count, datatype, op, comm, info, request,
              ierror)
```

```
1
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
2
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
10
     MPI_Scan_init(sendbuf, recvbuf, count, datatype, op, comm, info, request,
11
                  ierror)
12
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
13
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
14
         INTEGER, INTENT(IN) :: count
15
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
16
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
19
         TYPE(MPI_Request), INTENT(OUT) :: request
20
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
21
22
     MPI_Scatter(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
23
                  root, comm, ierror)
24
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
26
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
27
         TYPE(*), DIMENSION(..) :: recvbuf
         INTEGER, INTENT(IN) :: root
         TYPE(MPI_Comm), INTENT(IN) :: comm
30
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
31
     MPI_Scatter(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
32
                  root, comm, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
34
         INTEGER, INTENT(IN) :: sendcount, recvcount, root
35
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
36
         TYPE(*), DIMENSION(..) :: recvbuf
37
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
39
40
     MPI_Scatter_init(sendbuf, sendcount, sendtype, recvbuf, recvcount,
41
                  recvtype, root, comm, info, request, ierror)
42
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
43
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
44
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
45
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: root
47
         TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Scatter_init(sendbuf, sendcount, sendtype, recvbuf, recvcount,
             recvtype, root, comm, info, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN) :: sendcount, recvcount, root
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 12
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 13
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 14
                                                                                 15
MPI_Scatterv(sendbuf, sendcounts, displs, sendtype, recvbuf, recvcount,
             recvtype, root, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcounts(*), recvcount
                                                                                 19
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: displs(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 20
                                                                                 21
    TYPE(*), DIMENSION(..) :: recvbuf
                                                                                 22
    INTEGER, INTENT(IN) :: root
                                                                                 23
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 24
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Scatterv(sendbuf, sendcounts, displs, sendtype, recvbuf, recvcount,
                                                                                 26
             recvtype, root, comm, ierror)
                                                                                 27
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
                                                                                 28
    INTEGER, INTENT(IN) :: sendcounts(*), displs(*), recvcount, root
                                                                                 29
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 30
    TYPE(*), DIMENSION(..) :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 34
MPI_Scatterv_init(sendbuf, sendcounts, displs, sendtype, recvbuf,
                                                                                 35
             recvcount, recvtype, root, comm, info, request, ierror)
                                                                                 36
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 37
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: sendcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: recvcount
                                                                                 42
    INTEGER, INTENT(IN) :: root
                                                                                 43
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 44
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 45
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
1
     MPI_Scatterv_init(sendbuf, sendcounts, displs, sendtype, recvbuf,
2
                  recvcount, recvtype, root, comm, info, request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), displs(*)
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER, INTENT(IN) :: recvcount, root
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
11
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
12
13
     A.4.5 Groups, Contexts, Communicators, and Caching Fortran 2008 Bindings
14
15
     MPI_COMM_DUP_FN(oldcomm, comm_keyval, extra_state, attribute_val_in,
16
                   attribute_val_out, flag, ierror)
17
         TYPE(MPI_Comm) :: oldcomm
18
         INTEGER :: comm_keyval, ierror
19
         INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
20
                   attribute_val_out
21
         LOGICAL :: flag
22
     MPI_COMM_NULL_COPY_FN(oldcomm, comm_keyval, extra_state, attribute_val_in,
23
                  attribute_val_out, flag, ierror)
24
         TYPE(MPI_Comm) :: oldcomm
         INTEGER :: comm_keyval, ierror
         INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
27
                   attribute_val_out
28
         LOGICAL :: flag
29
30
     MPI_COMM_NULL_DELETE_FN(comm, comm_keyval, attribute_val, extra_state,
31
                   ierror)
32
         TYPE(MPI_Comm) :: comm
33
         INTEGER :: comm_keyval, ierror
34
         INTEGER(KIND=MPI_ADDRESS_KIND) :: attribute_val, extra_state
35
     MPI_Comm_compare(comm1, comm2, result, ierror)
36
         TYPE(MPI_Comm), INTENT(IN) :: comm1, comm2
37
         INTEGER, INTENT(OUT) :: result
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
39
     MPI_Comm_create(comm, group, newcomm, ierror)
41
         TYPE(MPI_Comm), INTENT(IN) :: comm
42
         TYPE(MPI_Group), INTENT(IN) :: group
43
         TYPE(MPI_Comm), INTENT(OUT) :: newcomm
44
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
     MPI_Comm_create_from_group(group, stringtag, info, errhandler, newcomm,
46
47
                   ierror)
         TYPE(MPI_Group), INTENT(IN) :: group
```

```
CHARACTER(LEN=*), INTENT(IN) :: stringtag
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Comm_create_group(comm, group, tag, newcomm, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Group), INTENT(IN) :: group
    INTEGER, INTENT(IN) :: tag
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 12
                                                                                 13
MPI_Comm_create_keyval(comm_copy_attr_fn, comm_delete_attr_fn, comm_keyval,
                                                                                 14
             extra_state, ierror)
                                                                                 15 #-error
    PROCEDURE (MPI_Comm_copy_attr_function), INTENT(IN) :: comm_copy_attr_fn
    PROCEDURE (MPI_Comm_delete_attr_function), INTENT(IN) ::
                                                                                     Done
                                                                                 17
                                                                                     in
              comm_delete_attr_fn
                                                                                     PR414
                                                                                 18
    INTEGER, INTENT(OUT) :: comm_keyval
                                                                                 19
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 20
                                                                                 21
MPI_Comm_delete_attr(comm, comm_keyval, ierror)
                                                                                 22
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 23
    INTEGER, INTENT(IN) :: comm_keyval
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Comm_dup(comm, newcomm, ierror)
                                                                                 27
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 28
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
                                                                                 29
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 30
MPI_Comm_dup_with_info(comm, info, newcomm, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
                                                                                 34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 35
                                                                                 36
MPI_Comm_free(comm, ierror)
                                                                                 37
    TYPE(MPI_Comm), INTENT(INOUT) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Comm_free_keyval(comm_keyval, ierror)
    INTEGER, INTENT(INOUT) :: comm_keyval
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 42
                                                                                 43
MPI_Comm_get_attr(comm, comm_keyval, attribute_val, flag, ierror)
                                                                                 44
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 45
    INTEGER, INTENT(IN) :: comm_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val
    LOGICAL, INTENT(OUT) :: flag
```

```
1
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
2
    MPI_Comm_get_info(comm, info_used, ierror)
3
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(OUT) :: info_used
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
7
     MPI_Comm_get_name(comm, comm_name, resultlen, ierror)
         TYPE(MPI_Comm), INTENT(IN) :: comm
9
         CHARACTER(LEN=MPI_MAX_OBJECT_NAME), INTENT(OUT) :: comm_name
10
         INTEGER, INTENT(OUT) :: resultlen
11
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
12
     MPI_Comm_group(comm, group, ierror)
13
         TYPE(MPI_Comm), INTENT(IN) :: comm
14
         TYPE(MPI_Group), INTENT(OUT) :: group
15
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
16
17
     MPI_Comm_idup(comm, newcomm, request, ierror)
18
         TYPE(MPI_Comm), INTENT(IN) :: comm
19
         TYPE(MPI_Comm), INTENT(OUT), ASYNCHRONOUS :: newcomm
20
         TYPE(MPI_Request), INTENT(OUT) :: request
21
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
22
     MPI_Comm_idup_with_info(comm, info, newcomm, request, ierror)
23
         TYPE(MPI_Comm), INTENT(IN) :: comm
24
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Comm), INTENT(OUT), ASYNCHRONOUS :: newcomm
         TYPE(MPI_Request), INTENT(OUT) :: request
27
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
28
29
    MPI_Comm_rank(comm, rank, ierror)
30
         TYPE(MPI_Comm), INTENT(IN) :: comm
31
         INTEGER, INTENT(OUT) :: rank
32
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
33
    MPI_Comm_remote_group(comm, group, ierror)
34
         TYPE(MPI_Comm), INTENT(IN) :: comm
35
         TYPE(MPI_Group), INTENT(OUT) :: group
36
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
37
38
     MPI_Comm_remote_size(comm, size, ierror)
39
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, INTENT(OUT) :: size
41
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
42
    MPI_Comm_set_attr(comm, comm_keyval, attribute_val, ierror)
43
         TYPE(MPI_Comm), INTENT(IN) :: comm
44
         INTEGER, INTENT(IN) :: comm_keyval
45
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
47
```

```
MPI_Comm_set_info(comm, info, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Comm_set_name(comm, comm_name, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    CHARACTER(LEN=*), INTENT(IN) :: comm_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Comm_size(comm, size, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(OUT) :: size
                                                                                 12
                                                                                 13
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 14
MPI_Comm_split(comm, color, key, newcomm, ierror)
                                                                                 15
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 16
    INTEGER, INTENT(IN) :: color, key
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
                                                                                 18
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 19
                                                                                 20
MPI_Comm_split_type(comm, split_type, key, info, newcomm, ierror)
                                                                                 21
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 22
    INTEGER, INTENT(IN) :: split_type, key
                                                                                 23
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 24
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 26
MPI_Comm_test_inter(comm, flag, ierror)
                                                                                 27
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 28
    LOGICAL, INTENT(OUT) :: flag
                                                                                 29
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 30
MPI_Group_compare(group1, group2, result, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group1, group2
    INTEGER, INTENT(OUT) :: result
                                                                                 34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 35
MPI_Group_difference(group1, group2, newgroup, ierror)
                                                                                 36
    TYPE(MPI_Group), INTENT(IN) :: group1, group2
                                                                                 37
    TYPE(MPI_Group), INTENT(OUT) :: newgroup
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Group_excl(group, n, ranks, newgroup, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group
                                                                                 42
    INTEGER, INTENT(IN) :: n, ranks(n)
                                                                                 43
    TYPE(MPI_Group), INTENT(OUT) :: newgroup
                                                                                 44
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 45
MPI_Group_free(group, ierror)
                                                                                 46
    TYPE(MPI_Group), INTENT(INOUT) :: group
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
1
     MPI_Group_from_session_pset(session, pset_name, newgroup, ierror)
2
         TYPE(MPI_Session), INTENT(IN) :: session
3
         CHARACTER(LEN=*), INTENT(IN) :: pset_name
         TYPE(MPI_Group), INTENT(OUT) :: newgroup
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
     MPI_Group_incl(group, n, ranks, newgroup, ierror)
         TYPE(MPI_Group), INTENT(IN) :: group
         INTEGER, INTENT(IN) :: n, ranks(n)
9
         TYPE(MPI_Group), INTENT(OUT) :: newgroup
10
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
11
12
     MPI_Group_intersection(group1, group2, newgroup, ierror)
13
         TYPE(MPI_Group), INTENT(IN) :: group1, group2
14
         TYPE(MPI_Group), INTENT(OUT) :: newgroup
15
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
16
     MPI_Group_range_excl(group, n, ranges, newgroup, ierror)
17
         TYPE(MPI_Group), INTENT(IN) :: group
         INTEGER, INTENT(IN) :: n, ranges(3, n)
19
         TYPE(MPI_Group), INTENT(OUT) :: newgroup
20
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
21
22
     MPI_Group_range_incl(group, n, ranges, newgroup, ierror)
23
         TYPE(MPI_Group), INTENT(IN) :: group
24
         INTEGER, INTENT(IN) :: n, ranges(3, n)
         TYPE(MPI_Group), INTENT(OUT) :: newgroup
26
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
27
     MPI_Group_rank(group, rank, ierror)
28
         TYPE(MPI_Group), INTENT(IN) :: group
29
         INTEGER, INTENT(OUT) :: rank
30
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
31
     MPI_Group_size(group, size, ierror)
33
         TYPE(MPI_Group), INTENT(IN) :: group
34
         INTEGER, INTENT(OUT) :: size
35
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
36
     MPI_Group_translate_ranks(group1, n, ranks1, group2, ranks2, ierror)
37
         TYPE(MPI_Group), INTENT(IN) :: group1, group2
         INTEGER, INTENT(IN) :: n, ranks1(n)
         INTEGER, INTENT(OUT) :: ranks2(n)
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
41
42
     MPI_Group_union(group1, group2, newgroup, ierror)
43
         TYPE(MPI_Group), INTENT(IN) :: group1, group2
44
         TYPE(MPI_Group), INTENT(OUT) :: newgroup
45
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
46
     MPI_Intercomm_create(local_comm, local_leader, peer_comm, remote_leader,
47
                  tag, newintercomm, ierror)
```

```
TYPE(MPI_Comm), INTENT(IN) :: local_comm, peer_comm
    INTEGER, INTENT(IN) :: local_leader, remote_leader, tag
    TYPE(MPI_Comm), INTENT(OUT) :: newintercomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Intercomm_create_from_groups(local_group, local_leader, remote_group,
             remote_leader, stringtag, info, errhandler, newintercomm,
             ierror)
    TYPE(MPI_Group), INTENT(IN) :: local_group, remote_group
    INTEGER, INTENT(IN) :: local_leader, remote_leader
    CHARACTER(LEN=*), INTENT(IN) :: stringtag
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 12
    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
                                                                                 13
    TYPE(MPI_Comm), INTENT(OUT) :: newintercomm
                                                                                 14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 15
                                                                                 16
MPI_Intercomm_merge(intercomm, high, newintracomm, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: intercomm
                                                                                 18
    LOGICAL, INTENT(IN) :: high
    TYPE(MPI_Comm), INTENT(OUT) :: newintracomm
                                                                                 19
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 20
                                                                                 21
MPI_TYPE_DUP_FN(oldtype, type_keyval, extra_state, attribute_val_in,
                                                                                 22
             attribute_val_out, flag, ierror)
                                                                                 23
    TYPE(MPI_Datatype) :: oldtype
                                                                                 24
    INTEGER :: type_keyval, ierror
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
                                                                                 26
              attribute_val_out
                                                                                 27
    LOGICAL :: flag
                                                                                 28
                                                                                 29
MPI_TYPE_NULL_COPY_FN(oldtype, type_keyval, extra_state, attribute_val_in,
                                                                                 30
             attribute_val_out, flag, ierror)
    TYPE(MPI_Datatype) :: oldtype
    INTEGER :: type_keyval, ierror
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
                                                                                 34
              attribute_val_out
                                                                                 35
    LOGICAL :: flag
MPI_TYPE_NULL_DELETE_FN(datatype, type_keyval, attribute_val, extra_state,
                                                                                 37
             ierror)
    TYPE(MPI_Datatype) :: datatype
    INTEGER :: type_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND) :: attribute_val, extra_state
    INTEGER, INTENT(OUT) :: ierror
                                                                                 42
                                                                                 43
MPI_Type_create_keyval(type_copy_attr_fn, type_delete_attr_fn, type_keyval,
                                                                                 44
             extra_state, ierror)
                                                                                 45 #-error
    PROCEDURE (MPI_Type_copy_attr_function), INTENT(IN) :: type_copy_attr_fn
    PROCEDURE(MPI_Type_delete_attr_function), INTENT(IN) ::
                                                                                    Done
                                                                                    in
              type_delete_attr_fn
                                                                                    PR414
```

```
1
         INTEGER, INTENT(OUT) :: type_keyval
2
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Type_delete_attr(datatype, type_keyval, ierror)
5
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
6
         INTEGER, INTENT(IN) :: type_keyval
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
9
     MPI_Type_free_keyval(type_keyval, ierror)
10
         INTEGER, INTENT(INOUT) :: type_keyval
11
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
12
     MPI_Type_get_attr(datatype, type_keyval, attribute_val, flag, ierror)
13
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
14
         INTEGER, INTENT(IN) :: type_keyval
15
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val
16
         LOGICAL, INTENT(OUT) :: flag
17
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
18
19
     MPI_Type_get_name(datatype, type_name, resultlen, ierror)
20
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
21
         CHARACTER(LEN=MPI_MAX_OBJECT_NAME), INTENT(OUT) :: type_name
22
         INTEGER, INTENT(OUT) :: resultlen
23
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
24
     MPI_Type_set_attr(datatype, type_keyval, attribute_val, ierror)
25
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
26
         INTEGER, INTENT(IN) :: type_keyval
27
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val
28
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
29
30
     MPI_Type_set_name(datatype, type_name, ierror)
31
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
32
         CHARACTER(LEN=*), INTENT(IN) :: type_name
33
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
     MPI_WIN_DUP_FN(oldwin, win_keyval, extra_state, attribute_val_in,
35
                  attribute_val_out, flag, ierror)
36
         TYPE(MPI_Win) :: oldwin
37
         INTEGER :: win_keyval, ierror
         INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
                   attribute_val_out
         LOGICAL :: flag
41
42
     MPI_WIN_NULL_COPY_FN(oldwin, win_keyval, extra_state, attribute_val_in,
43
                  attribute_val_out, flag, ierror)
44
         TYPE(MPI_Win) :: oldwin
45
         INTEGER :: win_keyval, ierror
         INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state, attribute_val_in,
47
                   attribute_val_out
```

```
LOGICAL :: flag
MPI_WIN_NULL_DELETE_FN(win, win_keyval, attribute_val, extra_state, ierror)
    TYPE(MPI_Win) :: win
    INTEGER :: win_keyval, ierror
    INTEGER(KIND=MPI_ADDRESS_KIND) :: attribute_val, extra_state
MPI_Win_create_keyval(win_copy_attr_fn, win_delete_attr_fn, win_keyval,
             extra_state, ierror)
                                                                                  9 #-error
    PROCEDURE (MPI_Win_copy_attr_function), INTENT(IN) :: win_copy_attr_fn
    PROCEDURE(MPI_Win_delete_attr_function), INTENT(IN) ::
                                                                                    Done
                                                                                    in
              win_delete_attr_fn
                                                                                    PR414
                                                                                  12
    INTEGER, INTENT(OUT) :: win_keyval
                                                                                  13
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
                                                                                  14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  15
MPI_Win_delete_attr(win, win_keyval, ierror)
                                                                                  16
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, INTENT(IN) :: win_keyval
                                                                                  18
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  19
                                                                                  20
MPI_Win_free_keyval(win_keyval, ierror)
                                                                                 21
    INTEGER, INTENT(INOUT) :: win_keyval
                                                                                 22
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 23
MPI_Win_get_attr(win, win_keyval, attribute_val, flag, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, INTENT(IN) :: win_keyval
                                                                                  26
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val
                                                                                 27
    LOGICAL, INTENT(OUT) :: flag
                                                                                 28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 29
                                                                                  30
MPI_Win_get_name(win, win_name, resultlen, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    CHARACTER(LEN=MPI_MAX_OBJECT_NAME), INTENT(OUT) :: win_name
    INTEGER, INTENT(OUT) :: resultlen
                                                                                 34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 35
MPI_Win_set_attr(win, win_keyval, attribute_val, ierror)
                                                                                 36
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                 37
    INTEGER, INTENT(IN) :: win_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Win_set_name(win, win_name, ierror)
                                                                                  42
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                  43
    CHARACTER(LEN=*), INTENT(IN) :: win_name
                                                                                  44
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
A.4.6 Process Topologies Fortran 2008 Bindings
2
     MPI_Cart_coords(comm, rank, maxdims, coords, ierror)
3
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, INTENT(IN) :: rank, maxdims
         INTEGER, INTENT(OUT) :: coords(maxdims)
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Cart_create(comm_old, ndims, dims, periods, reorder, comm_cart, ierror)
         TYPE(MPI_Comm), INTENT(IN) :: comm_old
10
         INTEGER, INTENT(IN) :: ndims, dims(ndims)
11
         LOGICAL, INTENT(IN) :: periods(ndims), reorder
12
         TYPE(MPI_Comm), INTENT(OUT) :: comm_cart
13
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
14
     MPI_Cart_get(comm, maxdims, dims, periods, coords, ierror)
15
         TYPE(MPI_Comm), INTENT(IN) :: comm
16
         INTEGER, INTENT(IN) :: maxdims
17
         INTEGER, INTENT(OUT) :: dims(maxdims), coords(maxdims)
         LOGICAL, INTENT(OUT) :: periods(maxdims)
19
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
20
21
     MPI_Cart_map(comm, ndims, dims, periods, newrank, ierror)
22
         TYPE(MPI_Comm), INTENT(IN) :: comm
23
         INTEGER, INTENT(IN) :: ndims, dims(ndims)
24
         LOGICAL, INTENT(IN) :: periods(ndims)
         INTEGER, INTENT(OUT) :: newrank
26
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
27
     MPI_Cart_rank(comm, coords, rank, ierror)
28
         TYPE(MPI_Comm), INTENT(IN) :: comm
29
         INTEGER, INTENT(IN) :: coords(*)
30
         INTEGER, INTENT(OUT) :: rank
31
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
32
33
     MPI_Cart_shift(comm, direction, disp, rank_source, rank_dest, ierror)
34
         TYPE(MPI_Comm), INTENT(IN) :: comm
35
         INTEGER, INTENT(IN) :: direction, disp
36
         INTEGER, INTENT(OUT) :: rank_source, rank_dest
37
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Cart_sub(comm, remain_dims, newcomm, ierror)
39
         TYPE(MPI_Comm), INTENT(IN) :: comm
         LOGICAL, INTENT(IN) :: remain_dims(*)
         TYPE(MPI_Comm), INTENT(OUT) :: newcomm
42
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
43
44
     MPI_Cartdim_get(comm, ndims, ierror)
45
         TYPE(MPI_Comm), INTENT(IN) :: comm
46
         INTEGER, INTENT(OUT) :: ndims
47
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
MPI_Dims_create(nnodes, ndims, dims, ierror)
    INTEGER, INTENT(IN) :: nnodes, ndims
    INTEGER, INTENT(INOUT) :: dims(ndims)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Dist_graph_create(comm_old, n, sources, degrees, destinations, weights,
             info, reorder, comm_dist_graph, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm_old
    INTEGER, INTENT(IN) :: n, sources(n), degrees(n), destinations(*),
              weights(*)
    TYPE(MPI_Info), INTENT(IN) :: info
    LOGICAL, INTENT(IN) :: reorder
                                                                                 12
    TYPE(MPI_Comm), INTENT(OUT) :: comm_dist_graph
                                                                                 13
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 14
                                                                                 15
MPI_Dist_graph_create_adjacent(comm_old, indegree, sources, sourceweights,
                                                                                 16
             outdegree, destinations, destweights, info, reorder,
             comm_dist_graph, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm_old
                                                                                 19
    INTEGER, INTENT(IN) :: indegree, sources(indegree), sourceweights(*),
              outdegree, destinations(outdegree), destweights(*)
                                                                                 20
                                                                                 21
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 22
    LOGICAL, INTENT(IN) :: reorder
    TYPE(MPI_Comm), INTENT(OUT) :: comm_dist_graph
                                                                                 23
                                                                                 24
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Dist_graph_neighbors(comm, maxindegree, sources, sourceweights,
             maxoutdegree, destinations, destweights, ierror)
                                                                                 27
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 28
    INTEGER, INTENT(IN) :: maxindegree, maxoutdegree
                                                                                 29
    INTEGER, INTENT(OUT) :: sources(maxindegree),
                                                                                 30
              destinations (maxoutdegree)
    INTEGER :: sourceweights(*), destweights(*)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 34
MPI_Dist_graph_neighbors_count(comm, indegree, outdegree, weighted, ierror)
                                                                                 35
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 36
    INTEGER, INTENT(OUT) :: indegree, outdegree
                                                                                 37
    LOGICAL, INTENT(OUT) :: weighted
                                                                                 38
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Graph_create(comm_old, nnodes, index, edges, reorder, comm_graph,
              ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm_old
                                                                                 42
    INTEGER, INTENT(IN) :: nnodes, index(nnodes), edges(*)
                                                                                 43
    LOGICAL, INTENT(IN) :: reorder
                                                                                 44
    TYPE(MPI_Comm), INTENT(OUT) :: comm_graph
                                                                                 45
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 46
MPI_Graph_get(comm, maxindex, maxedges, index, edges, ierror)
```

```
1
         TYPE(MPI_Comm), INTENT(IN) :: comm
2
         INTEGER, INTENT(IN) :: maxindex, maxedges
         INTEGER, INTENT(OUT) :: index(maxindex), edges(maxedges)
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
5
     MPI_Graph_map(comm, nnodes, index, edges, newrank, ierror)
6
         TYPE(MPI_Comm), INTENT(IN) :: comm
7
         INTEGER, INTENT(IN) :: nnodes, index(nnodes), edges(*)
         INTEGER, INTENT(OUT) :: newrank
9
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
10
11
     MPI_Graph_neighbors(comm, rank, maxneighbors, neighbors, ierror)
12
         TYPE(MPI_Comm), INTENT(IN) :: comm
13
         INTEGER, INTENT(IN) :: rank, maxneighbors
14
         INTEGER, INTENT(OUT) :: neighbors(maxneighbors)
15
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
16
     MPI_Graph_neighbors_count(comm, rank, nneighbors, ierror)
17
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, INTENT(IN) :: rank
19
         INTEGER, INTENT(OUT) :: nneighbors
20
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
21
22
     MPI_Graphdims_get(comm, nnodes, nedges, ierror)
23
         TYPE(MPI_Comm), INTENT(IN) :: comm
24
         INTEGER, INTENT(OUT) :: nnodes, nedges
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
     MPI_Ineighbor_allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount,
27
                  recvtype, comm, request, ierror)
28
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
29
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
30
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
33
         TYPE(MPI_Request), INTENT(OUT) :: request
34
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
35
36
     MPI_Ineighbor_allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount,
37
                  recvtype, comm, request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         INTEGER, INTENT(IN) :: sendcount, recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
41
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
42
         TYPE(MPI_Comm), INTENT(IN) :: comm
43
         TYPE(MPI_Request), INTENT(OUT) :: request
44
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
     MPI_Ineighbor_allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
46
                  displs, recvtype, comm, request, ierror)
47
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
```

```
INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
                                                                                 2
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: displs(*)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Ineighbor_allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
             displs, recvtype, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 12
    INTEGER, INTENT(IN) :: sendcount
                                                                                 13
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 14
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 15
    INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*), displs(*)
                                                                                 16
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 18
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 19
MPI_Ineighbor_alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount,
                                                                                 20
                                                                                 21
             recvtype, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 22
                                                                                 23
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
                                                                                 24
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 26
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 27
                                                                                 28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 29
MPI_Ineighbor_alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount,
                                                                                 30
             recvtype, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 34
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 35
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 36
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 37
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Ineighbor_alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
             recvcounts, rdispls, recvtype, comm, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 42
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
                                                                                 43
              sendcounts(*), recvcounts(*)
                                                                                 44
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
                                                                                 45
              rdispls(*)
                                                                                 46
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(...), ASYNCHRONOUS :: recvbuf
```

```
1
         TYPE(MPI_Comm), INTENT(IN) :: comm
2
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Ineighbor_alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
                  recvcounts, rdispls, recvtype, comm, request, ierror)
6
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),
                   recvcounts(*), rdispls(*)
9
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
10
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
12
         TYPE(MPI_Request), INTENT(OUT) :: request
13
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
14
15
    MPI_Ineighbor_alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
16
                  recvcounts, rdispls, recvtypes, comm, request, ierror)
17
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
18
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
19
                   sendcounts(*), recvcounts(*)
20
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
21
                   rdispls(*)
         TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
23
                   recvtypes(*)
24
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
27
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
28
     MPI_Ineighbor_alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
29
                  recvcounts, rdispls, recvtypes, comm, request, ierror)
30
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), recvcounts(*)
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
                   rdispls(*)
34
         TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
35
                   recvtypes(*)
36
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
37
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Request), INTENT(OUT) :: request
39
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
41
     MPI_Neighbor_allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount,
42
                  recvtype, comm, ierror)
43
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
44
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
45
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..) :: recvbuf
47
         TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Neighbor_allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount,
             recvtype, comm, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    INTEGER, INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..) :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Neighbor_allgather_init(sendbuf, sendcount, sendtype, recvbuf,
             recvcount, recvtype, comm, info, request, ierror)
                                                                                 12
                                                                                 13
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 14
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
                                                                                 15
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 16
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 18
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 19
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 20
                                                                                 21
MPI_Neighbor_allgather_init(sendbuf, sendcount, sendtype, recvbuf,
                                                                                 22
             recvcount, recvtype, comm, info, request, ierror)
                                                                                 23
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
                                                                                 24
    INTEGER, INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recytype
                                                                                 26
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 27
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 28
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 29
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Neighbor_allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
             displs, recvtype, comm, ierror)
                                                                                 34
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
                                                                                 35
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcounts(*)
                                                                                 36
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 37
    TYPE(*), DIMENSION(..) :: recvbuf
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: displs(*)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Neighbor_allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts,
             displs, recvtype, comm, ierror)
                                                                                 43
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
                                                                                 44
    INTEGER, INTENT(IN) :: sendcount, recvcounts(*), displs(*)
                                                                                 45
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 46
    TYPE(*), DIMENSION(..) :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
1
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
2
     MPI_Neighbor_allgatherv_init(sendbuf, sendcount, sendtype, recvbuf,
3
                  recvcounts, displs, recvtype, comm, info, request, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount
6
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: displs(*)
10
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Info), INTENT(IN) :: info
12
         TYPE(MPI_Request), INTENT(OUT) :: request
13
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
14
15
    MPI_Neighbor_allgatherv_init(sendbuf, sendcount, sendtype, recvbuf,
16
                  recvcounts, displs, recvtype, comm, info, request, ierror)
17
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
18
         INTEGER, INTENT(IN) :: sendcount, displs(*)
19
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
20
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
21
         INTEGER, INTENT(IN), ASYNCHRONOUS :: recvcounts(*)
         TYPE(MPI_Comm), INTENT(IN) :: comm
23
         TYPE(MPI_Info), INTENT(IN) :: info
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
     MPI_Neighbor_alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount,
27
                  recvtype, comm, ierror)
28
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
29
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
30
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..) :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
35
     MPI_Neighbor_alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount,
36
                  recvtype, comm, ierror)
37
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
         INTEGER, INTENT(IN) :: sendcount, recvcount
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..) :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
42
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
43
     MPI_Neighbor_alltoall_init(sendbuf, sendcount, sendtype, recvbuf,
44
                  recvcount, recvtype, comm, info, request, ierror)
45
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
46
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcount, recvcount
47
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
```

```
TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Neighbor_alltoall_init(sendbuf, sendcount, sendtype, recvbuf,
             recvcount, recvtype, comm, info, request, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                 12
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 13
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 14
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 15
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 16
MPI_Neighbor_alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
             recvcounts, rdispls, recvtype, comm, ierror)
                                                                                 19
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcounts(*),
                                                                                 20
                                                                                 21
              recvcounts(*)
                                                                                 22
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: sdispls(*), rdispls(*)
                                                                                 23
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 24
    TYPE(*), DIMENSION(..) :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 26
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 27
MPI_Neighbor_alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf,
                                                                                 28
             recvcounts, rdispls, recvtype, comm, ierror)
                                                                                 29
    TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
                                                                                 30
    INTEGER, INTENT(IN) :: sendcounts(*), sdispls(*), recvcounts(*),
          rdispls(*)
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
    TYPE(*), DIMENSION(..) :: recvbuf
                                                                                 34
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 35
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 36
                                                                                 37
MPI_Neighbor_alltoallv_init(sendbuf, sendcounts, sdispls, sendtype,
             recvbuf, recvcounts, rdispls, recvtype, comm, info, request,
             ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
                                                                                 42
              sendcounts(*), recvcounts(*)
                                                                                 43
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
                                                                                 44
              rdispls(*)
                                                                                 45
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                                                                                 46
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
    TYPE(MPI_Comm), INTENT(IN) :: comm
```

```
1
         TYPE(MPI_Info), INTENT(IN) :: info
2
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Neighbor_alltoallv_init(sendbuf, sendcounts, sdispls, sendtype,
5
                  recvbuf, recvcounts, rdispls, recvtype, comm, info, request,
6
                   ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
         INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), sdispls(*),
9
                   recvcounts(*), rdispls(*)
10
         TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
12
         TYPE(MPI_Comm), INTENT(IN) :: comm
13
         TYPE(MPI_Info), INTENT(IN) :: info
14
         TYPE(MPI_Request), INTENT(OUT) :: request
15
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
16
17
     MPI_Neighbor_alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
18
                  recvcounts, rdispls, recvtypes, comm, ierror)
19
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
20
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: sendcounts(*),
21
                   recvcounts(*)
22
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: sdispls(*), rdispls(*)
23
         TYPE(MPI_Datatype), INTENT(IN) :: sendtypes(*), recvtypes(*)
         TYPE(*), DIMENSION(..) :: recvbuf
         TYPE(MPI_Comm), INTENT(IN) :: comm
26
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
27
     MPI_Neighbor_alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf,
28
                  recvcounts, rdispls, recvtypes, comm, ierror)
29
         TYPE(*), DIMENSION(..), INTENT(IN) :: sendbuf
30
         INTEGER, INTENT(IN) :: sendcounts(*), recvcounts(*)
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: sdispls(*), rdispls(*)
         TYPE(MPI_Datatype), INTENT(IN) :: sendtypes(*), recvtypes(*)
         TYPE(*), DIMENSION(..) :: recvbuf
34
         TYPE(MPI_Comm), INTENT(IN) :: comm
35
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
36
37
     MPI_Neighbor_alltoallw_init(sendbuf, sendcounts, sdispls, sendtypes,
38
                  recvbuf, recvcounts, rdispls, recvtypes, comm, info, request,
39
                  ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
41
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN), ASYNCHRONOUS ::
42
                   sendcounts(*), recvcounts(*)
43
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
44
                   rdispls(*)
45
         TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
                   recvtypes(*)
47
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
```

```
TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Neighbor_alltoallw_init(sendbuf, sendcounts, sdispls, sendtypes,
             recvbuf, recvcounts, rdispls, recvtypes, comm, info, request,
              ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: sendbuf
    INTEGER, INTENT(IN), ASYNCHRONOUS :: sendcounts(*), recvcounts(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN), ASYNCHRONOUS :: sdispls(*),
              rdispls(*)
                                                                                  12
    TYPE(MPI_Datatype), INTENT(IN), ASYNCHRONOUS :: sendtypes(*),
                                                                                  13
              recvtvpes(*)
                                                                                  14
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: recvbuf
                                                                                  15
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  16
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  18
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  19
                                                                                  20
MPI_Topo_test(comm, status, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  21
                                                                                  22
    INTEGER, INTENT(OUT) :: status
                                                                                  23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
A.4.7 MPI Environmental Management Fortran 2008 Bindings
                                                                                  26
                                                                                  27
DOUBLE PRECISION MPI_Wtick()
                                                                                  28
DOUBLE PRECISION MPI_Wtime()
                                                                                  29
                                                                                  30
MPI_Add_error_class(errorclass, ierror)
    INTEGER, INTENT(OUT) :: errorclass
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Add_error_code(errorclass, errorcode, ierror)
                                                                                  34
    INTEGER, INTENT(IN) :: errorclass
                                                                                  35
    INTEGER, INTENT(OUT) :: errorcode
                                                                                  36
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  37
MPI_Add_error_string(errorcode, string, ierror)
    INTEGER, INTENT(IN) :: errorcode
    CHARACTER(LEN=*), INTENT(IN) :: string
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  42
MPI_Alloc_mem(size, info, baseptr, ierror)
                                                                                  43
    USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
                                                                                  44
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
                                                                                  45
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                  46
    TYPE(C_PTR), INTENT(OUT) :: baseptr
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
1
            MPI_Comm_call_errhandler(comm, errorcode, ierror)
        2
                TYPE(MPI_Comm), INTENT(IN) :: comm
        3
                INTEGER, INTENT(IN) :: errorcode
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
            MPI_Comm_create_errhandler(comm_errhandler_fn, errhandler, ierror)
#-error
                PROCEDURE (MPI_Comm_errhandler_function), INTENT(IN) ::
Done
                           comm_errhandler_fn
                TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
PR414
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       10
       11
            MPI_Comm_get_errhandler(comm, errhandler, ierror)
       12
                TYPE(MPI_Comm), INTENT(IN) :: comm
       13
                TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
       14
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       15
            MPI_Comm_set_errhandler(comm, errhandler, ierror)
       16
                TYPE(MPI_Comm), INTENT(IN) :: comm
       17
                TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       19
       20
            MPI_Errhandler_free(errhandler, ierror)
       21
                TYPE(MPI_Errhandler), INTENT(INOUT) :: errhandler
       22
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       23
            MPI_Error_class(errorcode, errorclass, ierror)
       24
                 INTEGER, INTENT(IN) :: errorcode
                INTEGER, INTENT(OUT) :: errorclass
       26
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       27
       28
            MPI_Error_string(errorcode, string, resultlen, ierror)
       29
                INTEGER, INTENT(IN) :: errorcode
       30
                CHARACTER(LEN=MPI_MAX_ERROR_STRING), INTENT(OUT) :: string
       31
                INTEGER, INTENT(OUT) :: resultlen
       32
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       33
            MPI_File_call_errhandler(fh, errorcode, ierror)
       34
                TYPE(MPI_File), INTENT(IN) :: fh
       35
                INTEGER, INTENT(IN) :: errorcode
       36
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       37
       38
            MPI_File_create_errhandler(file_errhandler_fn, errhandler, ierror)
#-error
                PROCEDURE(MPI_File_errhandler_function), INTENT(IN) ::
Done
                           file_errhandler_fn
                TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
PR414
       42
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       43
            MPI_File_get_errhandler(file, errhandler, ierror)
       44
                TYPE(MPI_File), INTENT(IN) :: file
       45
                TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
       46
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
       47
```

Done

in PR414

```
MPI_File_set_errhandler(file, errhandler, ierror)
    TYPE(MPI_File), INTENT(IN) :: file
    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Free_mem(base, ierror)
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: base
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Get_library_version(version, resultlen, ierror)
    CHARACTER (LEN=MPI_MAX_LIBRARY_VERSION_STRING), INTENT(OUT) :: version
    INTEGER, INTENT(OUT) :: resultlen
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  12
                                                                                  13
MPI_Get_processor_name(name, resultlen, ierror)
                                                                                  14
    CHARACTER(LEN=MPI_MAX_PROCESSOR_NAME), INTENT(OUT) :: name
                                                                                  15
    INTEGER, INTENT(OUT) :: resultlen
                                                                                  16
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  18
MPI_Get_version(version, subversion, ierror)
                                                                                  19
    INTEGER, INTENT(OUT) :: version, subversion
                                                                                  20
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  21
MPI_Session_call_errhandler(session, errorcode, ierror)
    TYPE(MPI_Session), INTENT(IN) :: session
                                                                                  23
    INTEGER, INTENT(IN) :: errorcode
                                                                                  24
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  26
MPI_Session_create_errhandler(session_errhandler_fn, errhandler, ierror)
                                                                                  <sup>27</sup> #-error
    PROCEDURE (MPI_Session_errhandler_function), INTENT(IN) ::
                                                                                  28
                                                                                     Done
              session_errhandler_fn
                                                                                  29
                                                                                     in
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
                                                                                     PR414
                                                                                  30
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  31
MPI_Session_get_errhandler(session, errhandler, ierror)
    TYPE(MPI_Session), INTENT(IN) :: session
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
                                                                                  34
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  35
                                                                                  36
MPI_Session_set_errhandler(session, errhandler, ierror)
                                                                                  37
    TYPE(MPI_Session), INTENT(IN) :: session
    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Win_call_errhandler(win, errorcode, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                  42
    INTEGER, INTENT(IN) :: errorcode
                                                                                  43
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  44
                                                                                  45
MPI_Win_create_errhandler(win_errhandler_fn, errhandler, ierror)
                                                                                  46 #-error
    PROCEDURE (MPI_Win_errhandler_function), INTENT(IN) :: win_errhandler_fn
```

TYPE(MPI\_Errhandler), INTENT(OUT) :: errhandler

```
1
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
2
     MPI_Win_get_errhandler(win, errhandler, ierror)
3
         TYPE(MPI_Win), INTENT(IN) :: win
         TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
7
     MPI_Win_set_errhandler(win, errhandler, ierror)
         TYPE(MPI_Win), INTENT(IN) :: win
9
         TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
11
12
     A.4.8 The Info Object Fortran 2008 Bindings
13
14
     MPI_Info_create(info, ierror)
15
         TYPE(MPI_Info), INTENT(OUT) :: info
16
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
17
     MPI_Info_create_env(info, ierror)
18
         TYPE(MPI_Info), INTENT(OUT) :: info
19
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
20
21
     MPI_Info_delete(info, key, ierror)
22
         TYPE(MPI_Info), INTENT(IN) :: info
23
         CHARACTER(LEN=*), INTENT(IN) :: key
24
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Info_dup(info, newinfo, ierror)
26
         TYPE(MPI_Info), INTENT(IN) :: info
27
         TYPE(MPI_Info), INTENT(OUT) :: newinfo
28
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
29
30
     MPI_Info_free(info, ierror)
31
         TYPE(MPI_Info), INTENT(INOUT) :: info
32
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
33
34
     MPI_Info_get(info, key, valuelen, value, flag, ierror)
         TYPE(MPI_Info), INTENT(IN) :: info
35
         CHARACTER(LEN=*), INTENT(IN) :: key
36
37
         INTEGER, INTENT(IN) :: valuelen
         CHARACTER(LEN=valuelen), INTENT(OUT) :: value
         LOGICAL, INTENT(OUT) :: flag
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
41
     MPI_Info_get_nkeys(info, nkeys, ierror)
42
         TYPE(MPI_Info), INTENT(IN) :: info
43
         INTEGER, INTENT(OUT) :: nkeys
44
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
     MPI_Info_get_nthkey(info, n, key, ierror)
46
47
         TYPE(MPI_Info), INTENT(IN) :: info
         INTEGER, INTENT(IN) :: n
```

```
CHARACTER(LEN=*), INTENT(OUT) :: key
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Info_get_string(info, key, buflen, value, flag, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    CHARACTER(LEN=*), INTENT(IN) :: key
    INTEGER, INTENT(INOUT) :: buflen
    CHARACTER(LEN=*), INTENT(OUT) :: value
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Info_get_valuelen(info, key, valuelen, flag, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                  12
                                                                                  13
    CHARACTER(LEN=*), INTENT(IN) :: key
                                                                                  14
    INTEGER, INTENT(OUT) :: valuelen
                                                                                  15
    LOGICAL, INTENT(OUT) :: flag
                                                                                  16
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Info_set(info, key, value, ierror)
                                                                                  18
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                  19
    CHARACTER(LEN=*), INTENT(IN) :: key, value
                                                                                  20
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  21
                                                                                  22
                                                                                  23
A.4.9 Process Creation and Management Fortran 2008 Bindings
                                                                                  24
MPI_Abort(comm, errorcode, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  26
    INTEGER, INTENT(IN) :: errorcode
                                                                                  27
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  28
                                                                                  29
MPI_Close_port(port_name, ierror)
                                                                                  30
    CHARACTER(LEN=*), INTENT(IN) :: port_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Comm_accept(port_name, info, root, comm, newcomm, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: port_name
                                                                                  34
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                  35
    INTEGER, INTENT(IN) :: root
                                                                                  36
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  37
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Comm_connect(port_name, info, root, comm, newcomm, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: port_name
                                                                                  42
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                  43
    INTEGER, INTENT(IN) :: root
                                                                                  44
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  45
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Comm_disconnect(comm, ierror)
```

```
1
         TYPE(MPI_Comm), INTENT(INOUT) :: comm
2
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Comm_get_parent(parent, ierror)
         TYPE(MPI_Comm), INTENT(OUT) :: parent
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
7
     MPI_Comm_join(fd, intercomm, ierror)
         INTEGER, INTENT(IN) :: fd
9
         TYPE(MPI_Comm), INTENT(OUT) :: intercomm
10
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Comm_spawn(command, argv, maxprocs, info, root, comm, intercomm,
12
                   array_of_errcodes, ierror)
13
         CHARACTER(LEN=*), INTENT(IN) :: command, argv(*)
14
         INTEGER, INTENT(IN) :: maxprocs, root
15
         TYPE(MPI_Info), INTENT(IN) :: info
16
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Comm), INTENT(OUT) :: intercomm
         INTEGER :: array_of_errcodes(*)
19
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
20
21
     MPI_Comm_spawn_multiple(count, array_of_commands, array_of_argv,
22
                  array_of_maxprocs, array_of_info, root, comm, intercomm,
23
                  array_of_errcodes, ierror)
24
         INTEGER, INTENT(IN) :: count, array_of_maxprocs(*), root
         CHARACTER(LEN=*), INTENT(IN) :: array_of_commands(*),
26
                   array_of_argv(count, *)
27
         TYPE(MPI_Info), INTENT(IN) :: array_of_info(*)
28
         TYPE(MPI_Comm), INTENT(IN) :: comm
         TYPE(MPI_Comm), INTENT(OUT) :: intercomm
30
         INTEGER :: array_of_errcodes(*)
31
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI Finalize(ierror)
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
35
     MPI_Finalized(flag, ierror)
36
         LOGICAL, INTENT(OUT) :: flag
37
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
38
     MPI_Init(ierror)
39
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
40
41
     MPI_Init_thread(required, provided, ierror)
42
         INTEGER, INTENT(IN) :: required
43
         INTEGER, INTENT(OUT) :: provided
44
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
     MPI_Initialized(flag, ierror)
46
         LOGICAL, INTENT(OUT) :: flag
47
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
MPI_Is_thread_main(flag, ierror)
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Lookup_name(service_name, info, port_name, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: service_name
    TYPE(MPI_Info), INTENT(IN) :: info
    CHARACTER(LEN=MPI_MAX_PORT_NAME), INTENT(OUT) :: port_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Open_port(info, port_name, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    CHARACTER(LEN=MPI_MAX_PORT_NAME), INTENT(OUT) :: port_name
                                                                                 12
                                                                                 13
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 14
MPI_Publish_name(service_name, info, port_name, ierror)
                                                                                 15
    CHARACTER(LEN=*), INTENT(IN) :: service_name, port_name
                                                                                 16
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 18
                                                                                 19
MPI_Query_thread(provided, ierror)
                                                                                 20
    INTEGER, INTENT(OUT) :: provided
                                                                                 21
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 22
MPI_Session_finalize(session, ierror)
                                                                                 23
    TYPE(MPI_Session), INTENT(INOUT) :: session
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 26
MPI_Session_get_info(session, info_used, ierror)
                                                                                 27
    TYPE(MPI_Session), INTENT(IN) :: session
                                                                                 28
    TYPE(MPI_Info), INTENT(OUT) :: info_used
                                                                                 29
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Session_get_nth_pset(session, info, n, pset_len, pset_name, ierror)
    TYPE(MPI_Session), INTENT(IN) :: session
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, INTENT(IN) :: n
                                                                                 34
    INTEGER, INTENT(INOUT) :: pset_len
                                                                                 35
    CHARACTER(LEN=*), INTENT(OUT) :: pset_name
                                                                                 36
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 37
MPI_Session_get_num_psets(session, info, npset_names, ierror)
    TYPE(MPI_Session), INTENT(IN) :: session
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, INTENT(OUT) :: npset_names
                                                                                 42
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 43
MPI_Session_get_pset_info(session, pset_name, info, ierror)
                                                                                 44
    TYPE(MPI_Session), INTENT(IN) :: session
                                                                                 45
    CHARACTER(LEN=*), INTENT(IN) :: pset_name
    TYPE(MPI_Info), INTENT(OUT) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
1
    MPI_Session_init(info, errhandler, session, ierror)
2
         TYPE(MPI_Info), INTENT(IN) :: info
3
         TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
         TYPE(MPI_Session), INTENT(OUT) :: session
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
    MPI_Unpublish_name(service_name, info, port_name, ierror)
         CHARACTER(LEN=*), INTENT(IN) :: service_name, port_name
         TYPE(MPI_Info), INTENT(IN) :: info
9
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
10
11
12
     A.4.10 One-Sided Communications Fortran 2008 Bindings
13
     MPI_Accumulate(origin_addr, origin_count, origin_datatype, target_rank,
14
                  target_disp, target_count, target_datatype, op, win, ierror)
15
         TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: origin_addr
16
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, target_count
         TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
         INTEGER, INTENT(IN) :: target_rank
19
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
20
         TYPE(MPI_Op), INTENT(IN) :: op
21
         TYPE(MPI_Win), INTENT(IN) :: win
22
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
23
24
     MPI_Accumulate(origin_addr, origin_count, origin_datatype, target_rank,
25
                  target_disp, target_count, target_datatype, op, win, ierror)
26
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
27
         INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
28
         TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
30
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI Win), INTENT(IN) :: win
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
33
     MPI_Compare_and_swap(origin_addr, compare_addr, result_addr, datatype,
34
                  target_rank, target_disp, win, ierror)
35
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr,
36
                   compare_addr
37
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: result_addr
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, INTENT(IN) :: target_rank
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
         TYPE(MPI_Win), INTENT(IN) :: win
42
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
43
44
     MPI_Fetch_and_op(origin_addr, result_addr, datatype, target_rank,
45
                  target_disp, op, win, ierror)
46
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
47
         TYPE(*), DIMENSION(...), ASYNCHRONOUS :: result_addr
```

```
TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(IN) :: target_rank
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Get(origin_addr, origin_count, origin_datatype, target_rank,
             target_disp, target_count, target_datatype, win, ierror)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: origin_addr
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, target_count
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
                                                                                12
    INTEGER, INTENT(IN) :: target_rank
                                                                                 13
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
                                                                                14
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                 15
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 16
MPI_Get(origin_addr, origin_count, origin_datatype, target_rank,
                                                                                18
             target_disp, target_count, target_datatype, win, ierror)
                                                                                19
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: origin_addr
    INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
                                                                                20
                                                                                21
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
                                                                                22
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
                                                                                23
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                24
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Get_accumulate(origin_addr, origin_count, origin_datatype, result_addr,
             result_count, result_datatype, target_rank, target_disp,
                                                                                27
             target_count, target_datatype, op, win, ierror)
                                                                                28
    TYPE(*), DIMENSION(...), INTENT(IN), ASYNCHRONOUS :: origin_addr
                                                                                29
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, result_count,
              target_count
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, result_datatype,
              target_datatype
                                                                                33
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: result_addr
                                                                                34
    INTEGER, INTENT(IN) :: target_rank
                                                                                35
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
                                                                                36
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                37
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Get_accumulate(origin_addr, origin_count, origin_datatype, result_addr,
             result_count, result_datatype, target_rank, target_disp,
                                                                                42
             target_count, target_datatype, op, win, ierror)
                                                                                43
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
                                                                                44
    INTEGER, INTENT(IN) :: origin_count, result_count, target_rank,
                                                                                45
              target_count
    TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, result_datatype,
              target_datatype
```

```
1
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: result_addr
2
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Win), INTENT(IN) :: win
5
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
6
    MPI_Put(origin_addr, origin_count, origin_datatype, target_rank,
                  target_disp, target_count, target_datatype, win, ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
9
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, target_count
10
         TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
         INTEGER, INTENT(IN) :: target_rank
12
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
13
         TYPE(MPI_Win), INTENT(IN) :: win
14
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
15
16
     MPI_Put(origin_addr, origin_count, origin_datatype, target_rank,
17
                  target_disp, target_count, target_datatype, win, ierror)
18
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
19
         INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
20
         TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
21
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
         TYPE(MPI_Win), INTENT(IN) :: win
23
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
24
     MPI_Raccumulate(origin_addr, origin_count, origin_datatype, target_rank,
25
                  target_disp, target_count, target_datatype, op, win, request,
26
                  ierror)
27
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
28
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, target_count
29
         TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
30
         INTEGER, INTENT(IN) :: target_rank
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Win), INTENT(IN) :: win
34
         TYPE(MPI_Request), INTENT(OUT) :: request
35
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
36
37
     MPI_Raccumulate(origin_addr, origin_count, origin_datatype, target_rank,
38
                  target_disp, target_count, target_datatype, op, win, request,
39
                  ierror)
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
41
         INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
42
         TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
43
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
44
         TYPE(MPI_Op), INTENT(IN) :: op
45
         TYPE(MPI_Win), INTENT(IN) :: win
         TYPE(MPI_Request), INTENT(OUT) :: request
47
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

1st \_c version

#-error

#-364+405

#-update12

(#-TODO)

```
Proposal to add !( c)
             MPI_Rget(origin_addr, origin_count, origin_datatype, target_rank,
                           target_disp, target_count, target_datatype, win, request,
                                                                                                3
                           ierror) [( c) There is no hint, that this is the _c version
                                                                                                4
                 TYPE(*), DIMENSION(...), ASYNCHRONOUS :: origin_addr
                                                                                                5
                 INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, target_count
                                                                                                6
                 TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
                 INTEGER, INTENT(IN) :: target_rank
                 INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
Wrong sequence:
                                                                                                9
                 TYPE(MPI_Win), INTENT(IN) :: win
                                                                                                10
                 TYPE(MPI_Request), INTENT(OUT) :: request
2nd normal version
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                                11
                                                                                                12
             MPI_Rget(origin_addr, origin_count, origin_datatype, target_rank,
                                                                                                13
                           target_disp, target_count, target_datatype, win, request,
                                                                                                14
                           ierror)
                                          There is no hint, that this is the NORMAL version
                                                                                                15
                 TYPE(*), DIMENSION(..), ASYNCHRONOUS :: origin_addr
                                                                                                16
                 INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
                                                                                                17
                 TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
                                                                                                18
                 INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
                                                                                                19
                 TYPE(MPI_Win), INTENT(IN) :: win
                                                                                                20
                 TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                               21
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                               22
                                                                                               23
             MPI_Rget_accumulate(origin_addr, origin_count, origin_datatype,
                                                                                                24
                           result_addr, result_count, result_datatype, target_rank,
                           target_disp, target_count, target_datatype, op, win, request,
                                                                                                26
                 TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
                                                                                               27
                                                                                               28
                 INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, result_count,
                                                                                               29
                           target_count
                 TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, result_datatype,
                                                                                                30
                           target_datatype
                 TYPE(*), DIMENSION(..), ASYNCHRONOUS :: result_addr
                 INTEGER, INTENT(IN) :: target_rank
                                                                                               34
                 INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
                                                                                               35
                 TYPE(MPI_Op), INTENT(IN) :: op
                                                                                               36
                 TYPE(MPI_Win), INTENT(IN) :: win
                                                                                               37
                 TYPE(MPI_Request), INTENT(OUT) :: request
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
             MPI_Rget_accumulate(origin_addr, origin_count, origin_datatype,
                           result_addr, result_count, result_datatype, target_rank,
                           target_disp, target_count, target_datatype, op, win, request,
                           ierror)
                                                                                                43
                 TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
                                                                                                44
                 INTEGER, INTENT(IN) :: origin_count, result_count, target_rank,
                                                                                                45
                           target_count
                                                                                                46
                 TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, result_datatype,
                           target_datatype
```

```
1
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: result_addr
2
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
         TYPE(MPI_Op), INTENT(IN) :: op
         TYPE(MPI_Win), INTENT(IN) :: win
         TYPE(MPI_Request), INTENT(OUT) :: request
6
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Rput(origin_addr, origin_count, origin_datatype, target_rank,
                  target_disp, target_count, target_datatype, win, request,
9
                  ierror)
10
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
11
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: origin_count, target_count
12
         TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
13
         INTEGER, INTENT(IN) :: target_rank
14
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
15
         TYPE(MPI_Win), INTENT(IN) :: win
16
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
18
19
     MPI_Rput(origin_addr, origin_count, origin_datatype, target_rank,
20
                  target_disp, target_count, target_datatype, win, request,
21
                  ierror)
22
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: origin_addr
23
         INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
         TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype, target_datatype
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
26
         TYPE(MPI_Win), INTENT(IN) :: win
27
         TYPE(MPI_Request), INTENT(OUT) :: request
28
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
29
     MPI_Win_allocate(size, disp_unit, info, comm, baseptr, win, ierror)
30
         USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
31
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
         INTEGER, INTENT(IN) :: disp_unit
         TYPE(MPI_Info), INTENT(IN) :: info
34
         TYPE(MPI_Comm), INTENT(IN) :: comm
35
         TYPE(C_PTR), INTENT(OUT) :: baseptr
36
         TYPE(MPI_Win), INTENT(OUT) :: win
37
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
38
39
     MPI_Win_allocate(size, disp_unit, info, comm, baseptr, win, ierror)
40
         USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
41
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size, disp_unit
42
         TYPE(MPI_Info), INTENT(IN) :: info
43
         TYPE(MPI_Comm), INTENT(IN) :: comm
44
         TYPE(C_PTR), INTENT(OUT) :: baseptr
45
         TYPE(MPI_Win), INTENT(OUT) :: win
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
47
    MPI_Win_allocate_shared(size, disp_unit, info, comm, baseptr, win, ierror)
```

#-error

#-364+405

#-update12

(#-TODO)

```
USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
                INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
                INTEGER, INTENT(IN) :: disp_unit
                TYPE(MPI_Info), INTENT(IN) :: info
                TYPE(MPI_Comm), INTENT(IN) :: comm
                TYPE(C_PTR), INTENT(OUT) :: baseptr
                TYPE(MPI_Win), INTENT(OUT) :: win
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
            MPI_Win_allocate_shared(size, disp_unit, info, comm, baseptr, win, ierror)
                USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
                INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size, disp_unit
                                                                                               12
                TYPE(MPI_Info), INTENT(IN) :: info
                                                                                               13
                TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                               14
                TYPE(C_PTR), INTENT(OUT) :: baseptr
                                                                                               15
                TYPE(MPI_Win), INTENT(OUT) :: win
                                                                                               16
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                               18
            MPI_Win_attach(win, base, size, ierror)
                                                                                               19
                TYPE(MPI_Win), INTENT(IN) :: win
                TYPE(*), DIMENSION(..), ASYNCHRONOUS :: base
                                                                                               20
                INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
                                                                                              21
                                                                                               22
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                              23
            MPI_Win_complete(win, ierror)
                                                                                               24
                TYPE(MPI_Win), INTENT(IN) :: win
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
            MPI_Win_create(base, size, disp_unit, info, comm, win, ierror)
                 TYPE(*), DIMENSION(..), ASYNCHRONOUS :: base
Here, we have the
                INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
correct sequence
                 INTEGER, INTENT(IN) :: disp_unit
                                                                                               31
                TYPE(MPI_Info), INTENT(IN) :: info
                                                                                               32
                TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                               33
                 TYPE(MPI_Win), INTENT(OUT) :: win
                                                                   See page 975 for
                                                                                              34
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                   explanations
                                                                                              35
            MPI_Win_create(base, size, disp_unit, info, comm, win, ierror) !( c)
                                                                                               36
                TYPE(*), DIMENSION(..), ASYNCHRONOUS :: base
                                                                                               37
                INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size, disp_unit
                                                                                               38
                TYPE(MPI_Info), INTENT(IN) :: info
                                                                                               39
                TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                               40
                TYPE(MPI_Win), INTENT(OUT) :: win
                                                                                               41
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                               42
                                                                                               43
            MPI_Win_create_dynamic(info, comm, win, ierror)
                                                                                               44
                TYPE(MPI_Info), INTENT(IN) :: info
                                                                                               45
                TYPE(MPI_Comm), INTENT(IN) :: comm
                TYPE(MPI_Win), INTENT(OUT) :: win
                INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

1st normal

2nd c

```
1
    MPI_Win_detach(win, base, ierror)
2
         TYPE(MPI_Win), INTENT(IN) :: win
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: base
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
5
     MPI_Win_fence(assert, win, ierror)
6
         INTEGER, INTENT(IN) :: assert
7
         TYPE(MPI_Win), INTENT(IN) :: win
8
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
9
10
     MPI_Win_flush(rank, win, ierror)
11
         INTEGER, INTENT(IN) :: rank
12
         TYPE(MPI_Win), INTENT(IN) :: win
13
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
14
     MPI_Win_flush_all(win, ierror)
15
         TYPE(MPI_Win), INTENT(IN) :: win
16
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
17
18
     MPI_Win_flush_local(rank, win, ierror)
19
         INTEGER, INTENT(IN) :: rank
20
         TYPE(MPI_Win), INTENT(IN) :: win
21
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
22
     MPI_Win_flush_local_all(win, ierror)
23
         TYPE(MPI_Win), INTENT(IN) :: win
24
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
25
26
     MPI_Win_free(win, ierror)
27
         TYPE(MPI_Win), INTENT(INOUT) :: win
28
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
29
     MPI_Win_get_group(win, group, ierror)
30
         TYPE(MPI_Win), INTENT(IN) :: win
31
         TYPE(MPI_Group), INTENT(OUT) :: group
32
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
33
34
     MPI_Win_get_info(win, info_used, ierror)
35
         TYPE(MPI_Win), INTENT(IN) :: win
36
         TYPE(MPI_Info), INTENT(OUT) :: info_used
37
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
38
     MPI_Win_lock(lock_type, rank, assert, win, ierror)
39
         INTEGER, INTENT(IN) :: lock_type, rank, assert
         TYPE(MPI_Win), INTENT(IN) :: win
41
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
42
43
     MPI_Win_lock_all(assert, win, ierror)
44
         INTEGER, INTENT(IN) :: assert
45
         TYPE(MPI_Win), INTENT(IN) :: win
46
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
47
    MPI_Win_post(group, assert, win, ierror)
```

```
TYPE(MPI_Group), INTENT(IN) :: group
    INTEGER, INTENT(IN) :: assert
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Win_set_info(win, info, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Win_shared_query(win, rank, size, disp_unit, baseptr, ierror)
    USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                 12
                                                                                 13
    INTEGER, INTENT(IN) :: rank
                                                                                 14
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: size
                                                                                 15
    INTEGER, INTENT(OUT) :: disp_unit
                                                                                 16
    TYPE(C_PTR), INTENT(OUT) :: baseptr
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 18
MPI_Win_shared_query(win, rank, size, disp_unit, baseptr, ierror)
                                                                                 19
    USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
                                                                                 20
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                 21
    INTEGER, INTENT(IN) :: rank
                                                                                 22
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: size, disp_unit
                                                                                 23
    TYPE(C_PTR), INTENT(OUT) :: baseptr
                                                                                 24
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 26
MPI_Win_start(group, assert, win, ierror)
                                                                                 27
    TYPE(MPI_Group), INTENT(IN) :: group
                                                                                 28
    INTEGER, INTENT(IN) :: assert
                                                                                 29
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                 30
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Win_sync(win, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 34
                                                                                 35
MPI_Win_test(win, flag, ierror)
                                                                                 36
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                 37
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Win_unlock(rank, win, ierror)
    INTEGER, INTENT(IN) :: rank
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                 42
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 43
                                                                                 44
MPI_Win_unlock_all(win, ierror)
                                                                                 45
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Win_wait(win, ierror)
```

Done

PR414

```
1
                 TYPE(MPI_Win), INTENT(IN) :: win
        2
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
             A.4.11 External Interfaces Fortran 2008 Bindings
        6
            MPI_Grequest_complete(request, ierror)
        7
                 TYPE(MPI_Request), INTENT(IN) :: request
        8
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
        9
             MPI_Grequest_start(query_fn, free_fn, cancel_fn, extra_state, request,
        10
                           ierror)
#-error
                 PROCEDURE (MPI_Grequest_query_function), INTENT(IN) :: query_fn
                 PROCEDURE (MPI_Grequest_free_function), INTENT(IN) :: free_fn
        13
                 PROCEDURE(MPI_Grequest_cancel_function), INTENT(IN) :: cancel_fn
        14
                 INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
        15
                 TYPE(MPI_Request), INTENT(OUT) :: request
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
        17
        18
             MPI_Status_set_cancelled(status, flag, ierror)
        19
                 TYPE(MPI_Status), INTENT(INOUT) :: status
        20
                 LOGICAL, INTENT(IN) :: flag
        21
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
        22
             MPI_Status_set_elements(status, datatype, count, ierror)
        23
                 TYPE(MPI_Status), INTENT(INOUT) :: status
        24
                 TYPE(MPI_Datatype), INTENT(IN) :: datatype
                 INTEGER, INTENT(IN) :: count
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
        27
        28
             MPI_Status_set_elements_x(status, datatype, count, ierror)
        29
                 TYPE(MPI_Status), INTENT(INOUT) :: status
        30
                 TYPE(MPI_Datatype), INTENT(IN) :: datatype
                 INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                 INTEGER, OPTIONAL, INTENT(OUT) :: ierror
        33
        34
             A.4.12 I/O Fortran 2008 Bindings
        35
        36
             MPI_CONVERSION_FN_NULL(userbuf, datatype, count, filebuf, position,
        37
                           extra_state, ierror)
                 USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
        39
                 TYPE(C_PTR), VALUE :: userbuf, filebuf
                 TYPE(MPI_Datatype) :: datatype
                 INTEGER(KIND=MPI_COUNT_KIND) :: count
                 INTEGER(KIND=MPI_OFFSET_KIND) :: position
        43
                 INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state
        44
                 INTEGER :: ierror
        45
        46
             MPI_CONVERSION_FN_NULL(userbuf, datatype, count, filebuf, position,
        47
                           extra_state, ierror)
```

```
USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
    TYPE(C_PTR), VALUE :: userbuf, filebuf
    TYPE(MPI_Datatype) :: datatype
    INTEGER :: count, ierror
    INTEGER(KIND=MPI_OFFSET_KIND) :: position
    INTEGER(KIND=MPI_ADDRESS_KIND) :: extra_state
MPI_File_close(fh, ierror)
    TYPE(MPI_File), INTENT(INOUT) :: fh
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_delete(filename, info, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: filename
                                                                                 12
                                                                                 13
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 14
                                                                                 15
MPI_File_get_amode(fh, amode, ierror)
                                                                                 16
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER, INTENT(OUT) :: amode
                                                                                 18
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 19
                                                                                 20
MPI_File_get_atomicity(fh, flag, ierror)
                                                                                 21
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 22
    LOGICAL, INTENT(OUT) :: flag
                                                                                 23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 24
MPI_File_get_byte_offset(fh, offset, disp, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 26
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                 27
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: disp
                                                                                 28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 29
                                                                                 30
MPI_File_get_group(fh, group, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(MPI_Group), INTENT(OUT) :: group
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 34
MPI_File_get_info(fh, info_used, ierror)
                                                                                 35
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 36
    TYPE(MPI_Info), INTENT(OUT) :: info_used
                                                                                 37
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_get_position(fh, offset, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: offset
                                                                                 42
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 43
MPI_File_get_position_shared(fh, offset, ierror)
                                                                                 44
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 45
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: offset
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
1
    MPI_File_get_size(fh, size, ierror)
2
         TYPE(MPI_File), INTENT(IN) :: fh
3
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: size
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
5
    MPI_File_get_type_extent(fh, datatype, extent, ierror)
6
         TYPE(MPI_File), INTENT(IN) :: fh
7
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: extent
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
10
11
     MPI_File_get_type_extent(fh, datatype, extent, ierror)
12
         TYPE(MPI_File), INTENT(IN) :: fh
13
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
14
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(OUT) :: extent
15
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
16
     MPI_File_get_view(fh, disp, etype, filetype, datarep, ierror)
17
         TYPE(MPI_File), INTENT(IN) :: fh
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: disp
19
         TYPE(MPI_Datatype), INTENT(OUT) :: etype, filetype
20
         CHARACTER(LEN=*), INTENT(OUT) :: datarep
21
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
22
23
     MPI_File_iread(fh, buf, count, datatype, request, ierror)
^{24}
         TYPE(MPI_File), INTENT(IN) :: fh
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
26
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
27
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
28
         TYPE(MPI_Request), INTENT(OUT) :: request
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
30
     MPI_File_iread(fh, buf, count, datatype, request, ierror)
31
         TYPE(MPI_File), INTENT(IN) :: fh
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
         INTEGER, INTENT(IN) :: count
34
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
35
         TYPE(MPI_Request), INTENT(OUT) :: request
36
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
37
     MPI_File_iread_all(fh, buf, count, datatype, request, ierror)
39
         TYPE(MPI_File), INTENT(IN) :: fh
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
41
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
42
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Request), INTENT(OUT) :: request
44
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
    MPI_File_iread_all(fh, buf, count, datatype, request, ierror)
46
         TYPE(MPI_File), INTENT(IN) :: fh
47
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
```

```
INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_iread_at(fh, offset, buf, count, datatype, request, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 12
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 13
MPI_File_iread_at(fh, offset, buf, count, datatype, request, ierror)
                                                                                 14
                                                                                 15
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
                                                                                 18
    INTEGER, INTENT(IN) :: count
                                                                                 19
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 20
                                                                                 21
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 22
MPI_File_iread_at_all(fh, offset, buf, count, datatype, request, ierror)
                                                                                 23
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 24
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
                                                                                 26
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                 27
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 28
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 29
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_iread_at_all(fh, offset, buf, count, datatype, request, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                 34
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
                                                                                 35
    INTEGER, INTENT(IN) :: count
                                                                                 36
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 37
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_iread_shared(fh, buf, count, datatype, request, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
                                                                                 42
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                 43
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 44
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 45
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_iread_shared(fh, buf, count, datatype, request, ierror)
```

```
1
         TYPE(MPI_File), INTENT(IN) :: fh
2
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Request), INTENT(OUT) :: request
6
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
7
    MPI_File_iwrite(fh, buf, count, datatype, request, ierror)
8
         TYPE(MPI_File), INTENT(IN) :: fh
9
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
10
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
12
         TYPE(MPI_Request), INTENT(OUT) :: request
13
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
14
15
    MPI_File_iwrite(fh, buf, count, datatype, request, ierror)
16
         TYPE(MPI_File), INTENT(IN) :: fh
17
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
18
         INTEGER, INTENT(IN) :: count
19
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
20
         TYPE(MPI_Request), INTENT(OUT) :: request
21
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
22
     MPI_File_iwrite_all(fh, buf, count, datatype, request, ierror)
23
         TYPE(MPI_File), INTENT(IN) :: fh
24
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
27
         TYPE(MPI_Request), INTENT(OUT) :: request
28
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
29
30
     MPI_File_iwrite_all(fh, buf, count, datatype, request, ierror)
         TYPE(MPI_File), INTENT(IN) :: fh
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
33
         INTEGER, INTENT(IN) :: count
34
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
35
         TYPE(MPI_Request), INTENT(OUT) :: request
36
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
37
     MPI_File_iwrite_at(fh, offset, buf, count, datatype, request, ierror)
38
         TYPE(MPI_File), INTENT(IN) :: fh
39
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
43
         TYPE(MPI_Request), INTENT(OUT) :: request
44
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
46
     MPI_File_iwrite_at(fh, offset, buf, count, datatype, request, ierror)
47
         TYPE(MPI_File), INTENT(IN) :: fh
```

```
INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_iwrite_at_all(fh, offset, buf, count, datatype, request, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                 12
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 13
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 15
                                                                                 16
MPI_File_iwrite_at_all(fh, offset, buf, count, datatype, request, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 18
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                 19
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER, INTENT(IN) :: count
                                                                                 20
                                                                                 21
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 22
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 24
MPI_File_iwrite_shared(fh, buf, count, datatype, request, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 26
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                 27
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                 28
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 29
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                 30
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_iwrite_shared(fh, buf, count, datatype, request, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 34
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
                                                                                 35
    INTEGER, INTENT(IN) :: count
                                                                                 36
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 37
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_open(comm, filename, amode, info, fh, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    CHARACTER(LEN=*), INTENT(IN) :: filename
                                                                                 42
    INTEGER, INTENT(IN) :: amode
                                                                                 43
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 44
    TYPE(MPI_File), INTENT(OUT) :: fh
                                                                                 45
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_preallocate(fh, size, ierror)
```

```
1
         TYPE(MPI_File), INTENT(IN) :: fh
2
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: size
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_File_read(fh, buf, count, datatype, status, ierror)
5
         TYPE(MPI_File), INTENT(IN) :: fh
6
         TYPE(*), DIMENSION(..) :: buf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Status) :: status
10
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
11
12
     MPI_File_read(fh, buf, count, datatype, status, ierror)
13
         TYPE(MPI_File), INTENT(IN) :: fh
14
         TYPE(*), DIMENSION(..) :: buf
15
         INTEGER, INTENT(IN) :: count
16
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Status) :: status
18
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
19
     MPI_File_read_all(fh, buf, count, datatype, status, ierror)
20
         TYPE(MPI_File), INTENT(IN) :: fh
21
         TYPE(*), DIMENSION(..) :: buf
22
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
23
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
24
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
27
     MPI_File_read_all(fh, buf, count, datatype, status, ierror)
28
         TYPE(MPI_File), INTENT(IN) :: fh
29
         TYPE(*), DIMENSION(..) :: buf
30
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Status) :: status
33
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
     MPI_File_read_all_begin(fh, buf, count, datatype, ierror)
35
         TYPE(MPI_File), INTENT(IN) :: fh
36
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
37
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
39
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
41
     MPI_File_read_all_begin(fh, buf, count, datatype, ierror)
42
         TYPE(MPI_File), INTENT(IN) :: fh
43
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
44
         INTEGER, INTENT(IN) :: count
45
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
47
    MPI_File_read_all_end(fh, buf, status, ierror)
```

```
TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_read_at(fh, offset, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..) :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
                                                                                 12
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 13
                                                                                 14
MPI_File_read_at(fh, offset, buf, count, datatype, status, ierror)
                                                                                 15
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 16
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..) :: buf
                                                                                 18
    INTEGER, INTENT(IN) :: count
                                                                                 19
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
                                                                                 20
                                                                                 21
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 22
MPI_File_read_at_all(fh, offset, buf, count, datatype, status, ierror)
                                                                                 23
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 24
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..) :: buf
                                                                                 26
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                 27
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 28
    TYPE(MPI_Status) :: status
                                                                                 29
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_read_at_all(fh, offset, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                 34
    TYPE(*), DIMENSION(..) :: buf
                                                                                 35
    INTEGER, INTENT(IN) :: count
                                                                                 36
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 37
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_read_at_all_begin(fh, offset, buf, count, datatype, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                 42
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
                                                                                 43
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                 44
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 45
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_read_at_all_begin(fh, offset, buf, count, datatype, ierror)
```

```
1
         TYPE(MPI_File), INTENT(IN) :: fh
2
         INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
6
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_File_read_at_all_end(fh, buf, status, ierror)
         TYPE(MPI_File), INTENT(IN) :: fh
9
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
10
         TYPE(MPI_Status) :: status
11
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
12
13
     MPI_File_read_ordered(fh, buf, count, datatype, status, ierror)
14
         TYPE(MPI_File), INTENT(IN) :: fh
15
         TYPE(*), DIMENSION(..) :: buf
16
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Status) :: status
19
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
20
     MPI_File_read_ordered(fh, buf, count, datatype, status, ierror)
21
         TYPE(MPI_File), INTENT(IN) :: fh
22
         TYPE(*), DIMENSION(..) :: buf
23
         INTEGER, INTENT(IN) :: count
24
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
27
28
     MPI_File_read_ordered_begin(fh, buf, count, datatype, ierror)
29
         TYPE(MPI_File), INTENT(IN) :: fh
30
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
33
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
34
     MPI_File_read_ordered_begin(fh, buf, count, datatype, ierror)
35
         TYPE(MPI_File), INTENT(IN) :: fh
36
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
37
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
39
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
41
     MPI_File_read_ordered_end(fh, buf, status, ierror)
42
         TYPE(MPI_File), INTENT(IN) :: fh
43
         TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
44
         TYPE(MPI_Status) :: status
45
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
46
     MPI_File_read_shared(fh, buf, count, datatype, status, ierror)
47
         TYPE(MPI_File), INTENT(IN) :: fh
```

```
TYPE(*), DIMENSION(..) :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_read_shared(fh, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
                                                                                  12
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  13
                                                                                  14
MPI_File_seek(fh, offset, whence, ierror)
                                                                                  15
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                  16
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    INTEGER, INTENT(IN) :: whence
                                                                                  18
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  19
MPI_File_seek_shared(fh, offset, whence, ierror)
                                                                                  20
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 21
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                 22
    INTEGER, INTENT(IN) :: whence
                                                                                 23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  24
MPI_File_set_atomicity(fh, flag, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 27
    LOGICAL, INTENT(IN) :: flag
                                                                                 28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 29
MPI_File_set_info(fh, info, ierror)
                                                                                 30
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 34
MPI_File_set_size(fh, size, ierror)
                                                                                 35
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 36
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: size
                                                                                 37
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_set_view(fh, disp, etype, filetype, datarep, info, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: disp
    TYPE(MPI_Datatype), INTENT(IN) :: etype, filetype
                                                                                 42
    CHARACTER(LEN=*), INTENT(IN) :: datarep
                                                                                  43
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                  44
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  45
                                                                                  46
MPI_File_sync(fh, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
```

```
1
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
2
     MPI_File_write(fh, buf, count, datatype, status, ierror)
3
         TYPE(MPI_File), INTENT(IN) :: fh
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
9
10
     MPI_File_write(fh, buf, count, datatype, status, ierror)
11
         TYPE(MPI_File), INTENT(IN) :: fh
12
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
13
         INTEGER, INTENT(IN) :: count
14
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
15
         TYPE(MPI_Status) :: status
16
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
17
     MPI_File_write_all(fh, buf, count, datatype, status, ierror)
         TYPE(MPI_File), INTENT(IN) :: fh
19
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
20
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
21
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Status) :: status
23
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
24
     MPI_File_write_all(fh, buf, count, datatype, status, ierror)
26
         TYPE(MPI_File), INTENT(IN) :: fh
27
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
28
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
    MPI_File_write_all_begin(fh, buf, count, datatype, ierror)
33
         TYPE(MPI_File), INTENT(IN) :: fh
34
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
35
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
36
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
37
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
38
     MPI_File_write_all_begin(fh, buf, count, datatype, ierror)
         TYPE(MPI_File), INTENT(IN) :: fh
41
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
42
         INTEGER, INTENT(IN) :: count
43
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
44
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
45
    MPI_File_write_all_end(fh, buf, status, ierror)
46
         TYPE(MPI_File), INTENT(IN) :: fh
47
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
```

```
TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_write_at(fh, offset, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_write_at(fh, offset, buf, count, datatype, status, ierror)
                                                                                 12
                                                                                 13
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 14
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                 15
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                 16
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 18
    TYPE(MPI_Status) :: status
                                                                                 19
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 20
MPI_File_write_at_all(fh, offset, buf, count, datatype, status, ierror)
                                                                                 21
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 22
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                                                                                 23
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
                                                                                 24
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 26
    TYPE(MPI_Status) :: status
                                                                                 27
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 28
                                                                                 29
MPI_File_write_at_all(fh, offset, buf, count, datatype, status, ierror)
                                                                                 30
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
    INTEGER, INTENT(IN) :: count
                                                                                 34
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 35
    TYPE(MPI_Status) :: status
                                                                                 36
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 37
MPI_File_write_at_all_begin(fh, offset, buf, count, datatype, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
    INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
                                                                                 42
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 43
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 44
                                                                                 45
MPI_File_write_at_all_begin(fh, offset, buf, count, datatype, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
```

```
1
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
2
         INTEGER, INTENT(IN) :: count
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
5
    MPI_File_write_at_all_end(fh, buf, status, ierror)
6
         TYPE(MPI_File), INTENT(IN) :: fh
7
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
         TYPE(MPI_Status) :: status
9
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
10
11
     MPI_File_write_ordered(fh, buf, count, datatype, status, ierror)
12
         TYPE(MPI_File), INTENT(IN) :: fh
13
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
14
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
15
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
16
         TYPE(MPI_Status) :: status
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_File_write_ordered(fh, buf, count, datatype, status, ierror)
19
         TYPE(MPI_File), INTENT(IN) :: fh
20
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
21
         INTEGER, INTENT(IN) :: count
22
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
23
         TYPE(MPI_Status) :: status
24
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
26
     MPI_File_write_ordered_begin(fh, buf, count, datatype, ierror)
27
         TYPE(MPI_File), INTENT(IN) :: fh
28
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
30
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
    MPI_File_write_ordered_begin(fh, buf, count, datatype, ierror)
33
         TYPE(MPI_File), INTENT(IN) :: fh
34
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
35
         INTEGER, INTENT(IN) :: count
36
         TYPE(MPI_Datatype), INTENT(IN) :: datatype
37
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
38
39
     MPI_File_write_ordered_end(fh, buf, status, ierror)
40
         TYPE(MPI_File), INTENT(IN) :: fh
41
         TYPE(*), DIMENSION(..), INTENT(IN), ASYNCHRONOUS :: buf
42
         TYPE(MPI_Status) :: status
43
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
44
    MPI_File_write_shared(fh, buf, count, datatype, status, ierror)
45
         TYPE(MPI_File), INTENT(IN) :: fh
46
         TYPE(*), DIMENSION(..), INTENT(IN) :: buf
47
         INTEGER(KIND=MPI_COUNT_KIND), INTENT(IN) :: count
```

```
TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_File_write_shared(fh, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..), INTENT(IN) :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Register_datarep(datarep, read_conversion_fn, write_conversion_fn,
                                                                                   12
                                                                                   13
              dtype_file_extent_fn, extra_state, ierror)
                                                                                   14
    CHARACTER(LEN=*), INTENT(IN) :: datarep
    PROCEDURE (MPI_Datarep_conversion_function), INTENT(IN) ::
                                                                                     #-error!
              read_conversion_fn, write_conversion_fn
                                                                                   17 #-okay?
    PROCEDURE(MPI_Datarep_extent_function) :: dtype_file_extent_fn
                                                                                   18 Or
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
                                                                                   <sub>19</sub> #-error?
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      Done
                                                                                  20
MPI_Register_datarep_c(datarep, read_conversion_fn, write_conversion_fn,
                                                                                  21
                                                                                      PR414
              dtype_file_extent_fn, extra_state, ierror)
                                                                                  22
    CHARACTER(LEN=*), INTENT(IN) :: datarep
                                                                                  23
    PROCEDURE(MPI_Datarep_conversion_function_c), INTENT(IN) ::
                                                                                   24 #-error!
              read_conversion_fn, write_conversion_fn
    PROCEDURE(MPI_Datarep_extent_function) :: dtype_file_extent_fn
                                                                                     #-okay?
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
                                                                                     #-error?
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   28
                                                                                      Done
                                                   Pythonization group will fix this globally!!!
                                                                                      in
                                                    -> Dan.
                                                                                      PR414
A.4.13 Language Bindings Fortran 2008 Bindings
                                                                                   31
MPI_F_sync_reg(buf)
    TYPE(*), DIMENSION(..), ASYNCHRONOUS :: buf
                                                                                   34
MPI_Status_f082f(f08_status, f_status, ierror)
                                                                                   35
    TYPE(MPI_Status), INTENT(IN) :: f08_status
                                                                                   36
    INTEGER, INTENT(OUT) :: f_status(MPI_STATUS_SIZE)
                                                                                   37
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Status_f2f08(f_status, f08_status, ierror)
    INTEGER, INTENT(IN) :: f_status(MPI_STATUS_SIZE)
    TYPE(MPI_Status), INTENT(OUT) :: f08_status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   42
                                                                                   43
MPI_Type_create_f90_complex(p, r, newtype, ierror)
                                                                                   44
    INTEGER, INTENT(IN) :: p, r
                                                                                   45
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
MPI_Type_create_f90_integer(r, newtype, ierror)
```

47

```
1
         INTEGER, INTENT(IN) :: r
2
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
     MPI_Type_create_f90_real(p, r, newtype, ierror)
5
         INTEGER, INTENT(IN) :: p, r
6
         TYPE(MPI_Datatype), INTENT(OUT) :: newtype
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
9
     MPI_Type_match_size(typeclass, size, datatype, ierror)
10
         INTEGER, INTENT(IN) :: typeclass, size
11
         TYPE(MPI_Datatype), INTENT(OUT) :: datatype
12
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
13
14
     A.4.14 Tools / Profiling Interface Fortran 2008 Bindings
15
16
    MPI Pcontrol(level)
17
         INTEGER, INTENT(IN) :: level
18
19
     A.4.15 Deprecated Fortran 2008 Bindings
20
21
     MPI_Info_get(info, key, valuelen, value, flag, ierror)
22
         TYPE(MPI_Info), INTENT(IN) :: info
23
         CHARACTER(LEN=*), INTENT(IN) :: key
24
         INTEGER, INTENT(IN) :: valuelen
         CHARACTER(LEN=valuelen), INTENT(OUT) :: value
         LOGICAL, INTENT(OUT) :: flag
27
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
28
     MPI_Info_get_valuelen(info, key, valuelen, flag, ierror)
29
30
         TYPE(MPI_Info), INTENT(IN) :: info
31
         CHARACTER(LEN=*), INTENT(IN) :: key
         INTEGER, INTENT(OUT) :: valuelen
33
         LOGICAL, INTENT(OUT) :: flag
34
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
35
     MPI_Sizeof(x, size, ierror)
36
         TYPE(*), DIMENSION(..) :: x
37
         INTEGER, INTENT(OUT) :: size
         INTEGER, OPTIONAL, INTENT(OUT) :: ierror
43
```

A.5	Fortran	<b>Bindings</b>	with	mpif.h	or the	mpi	Module

- A.5.1 Point-to-Point Communication Fortran Bindings

- MPI\_CANCEL(REQUEST, IERROR)
  INTEGER REQUEST, IERROR
- MPI\_GET\_COUNT(STATUS, DATATYPE, COUNT, IERROR)
  INTEGER STATUS(MPI\_STATUS\_SIZE), DATATYPE, COUNT, IERROR
- MPI\_IMPROBE(SOURCE, TAG, COMM, FLAG, MESSAGE, STATUS, IERROR)
  INTEGER SOURCE, TAG, COMM, MESSAGE, STATUS(MPI\_STATUS\_SIZE), IERROR
  LOGICAL FLAG
- MPI\_IPROBE(SOURCE, TAG, COMM, FLAG, STATUS, IERROR)
   INTEGER SOURCE, TAG, COMM, STATUS(MPI\_STATUS\_SIZE), IERROR
   LOGICAL FLAG

```
1
    MPI_ISENDRECV(SENDBUF, SENDCOUNT, SENDTYPE, DEST, SENDTAG, RECVBUF,
2
                  RECVCOUNT, RECVTYPE, SOURCE, RECVTAG, COMM, REQUEST, IERROR)
3
         <type> SENDBUF(*), RECVBUF(*)
         INTEGER SENDCOUNT, SENDTYPE, DEST, SENDTAG, RECVCOUNT, RECVTYPE,
5
                   SOURCE, RECVTAG, COMM, REQUEST, IERROR
6
     MPI_ISENDRECV_REPLACE(BUF, COUNT, DATATYPE, DEST, SENDTAG, SOURCE, RECVTAG,
                  COMM, REQUEST, IERROR)
         <type> BUF(*)
9
         INTEGER COUNT, DATATYPE, DEST, SENDTAG, SOURCE, RECVTAG, COMM, REQUEST,
10
                   IERROR
11
12
     MPI_ISSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
13
         <type> BUF(*)
14
         INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
15
     MPI_MPROBE(SOURCE, TAG, COMM, MESSAGE, STATUS, IERROR)
16
         INTEGER SOURCE, TAG, COMM, MESSAGE, STATUS (MPI_STATUS_SIZE), IERROR
17
18
     MPI_MRECV(BUF, COUNT, DATATYPE, MESSAGE, STATUS, IERROR)
19
         <type> BUF(*)
20
         INTEGER COUNT, DATATYPE, MESSAGE, STATUS(MPI_STATUS_SIZE), IERROR
21
     MPI_PROBE(SOURCE, TAG, COMM, STATUS, IERROR)
22
         INTEGER SOURCE, TAG, COMM, STATUS (MPI_STATUS_SIZE), IERROR
23
^{24}
     MPI_RECV(BUF, COUNT, DATATYPE, SOURCE, TAG, COMM, STATUS, IERROR)
         <type> BUF(*)
26
         INTEGER COUNT, DATATYPE, SOURCE, TAG, COMM, STATUS(MPI_STATUS_SIZE),
27
                   IERROR
28
     MPI_RECV_INIT(BUF, COUNT, DATATYPE, SOURCE, TAG, COMM, REQUEST, IERROR)
29
         <type> BUF(*)
30
         INTEGER COUNT, DATATYPE, SOURCE, TAG, COMM, REQUEST, IERROR
31
     MPI_REQUEST_FREE(REQUEST, IERROR)
33
         INTEGER REQUEST, IERROR
34
     MPI_REQUEST_GET_STATUS(REQUEST, FLAG, STATUS, IERROR)
35
         INTEGER REQUEST, STATUS(MPI_STATUS_SIZE), IERROR
36
         LOGICAL FLAG
37
38
     MPI_RSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)
39
         <type> BUF(*)
         INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR
41
    MPI_RSEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
42
         <type> BUF(*)
43
         INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
44
45
    MPI_SEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)
46
         <type> BUF(*)
47
         INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR
```

MPI\_SENDRECV(SENDBUF, SENDCOUNT, SENDTYPE, DEST, SENDTAG, RECVBUF,
RECVCOUNT, RECVTYPE, SOURCE, RECVTAG, COMM, STATUS, IERROR)
<type> SENDBUF(\*), RECVBUF(\*)
INTEGER SENDCOUNT, SENDTYPE, DEST, SENDTAG, RECVCOUNT, RECVTYPE,
SOURCE, RECVTAG, COMM, STATUS(MPI\_STATUS\_SIZE), IERROR

MPI\_SENDRECV\_REPLACE(BUF, COUNT, DATATYPE, DEST, SENDTAG, SOURCE, RECVTAG, COMM, STATUS, IERROR)

<type> BUF(\*)

INTEGER COUNT, DATATYPE, DEST, SENDTAG, SOURCE, RECVTAG, COMM, STATUS(MPI\_STATUS\_SIZE), IERROR

MPI\_SSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)
<type> BUF(\*)
INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR

MPI\_START(REQUEST, IERROR)
INTEGER REQUEST, IERROR

MPI\_STARTALL(COUNT, ARRAY\_OF\_REQUESTS, IERROR)
 INTEGER COUNT, ARRAY\_OF\_REQUESTS(\*), IERROR

MPI\_TEST(REQUEST, FLAG, STATUS, IERROR)
 INTEGER REQUEST, STATUS(MPI\_STATUS\_SIZE), IERROR
 LOGICAL FLAG

LOGICAL FLAG

MPI\_TESTSOME(INCOUNT, ARRAY\_OF\_REQUESTS, OUTCOUNT, ARRAY\_OF\_INDICES, ARRAY\_OF\_STATUSES, IERROR)

MPI\_TEST\_CANCELLED(STATUS, FLAG, IERROR)
 INTEGER STATUS(MPI\_STATUS\_SIZE), IERROR
 LOGICAL FLAG

#-error
 #-364+405
 #-update12
 (#-TODO)

 $^{24}$ 

```
#-error
#-364+405
#-update12
(#-TODO)
```

MPI\_WAIT(REQUEST, STATUS, IERROR)
 INTEGER REQUEST, STATUS(MPI\_STATUS\_SIZE), IERROR

- MPI\_WAITALL(COUNT, ARRAY\_OF\_REQUESTS, ARRAY\_OF\_STATUSES, IERROR)
   INTEGER COUNT, ARRAY\_OF\_REQUESTS(\*), ARRAY\_OF\_STATUSES(MPI\_STATUS\_SIZE,
   \*), IERROR

- A.5.2 Partitioned Communication Fortran Bindings
- MPI\_PARRIVED(REQUEST, PARTITION, FLAG, IERROR)
  INTEGER REQUEST, PARTITION, IERROR
  LOGICAL FLAG
- MPI\_PREADY(PARTITION, REQUEST, IERROR)
  INTEGER PARTITION, REQUEST, IERROR
- MPI\_PREADY\_LIST(LENGTH, ARRAY\_OF\_PARTITIONS, REQUEST, IERROR)
  INTEGER LENGTH, ARRAY\_OF\_PARTITIONS(\*), REQUEST, IERROR
- MPI\_PREADY\_RANGE(PARTITION\_LOW, PARTITION\_HIGH, REQUEST, IERROR)
  INTEGER PARTITION\_LOW, PARTITION\_HIGH, REQUEST, IERROR
- MPI\_PRECV\_INIT(BUF, PARTITIONS, COUNT, DATATYPE, DEST, TAG, COMM, INFO, REQUEST, IERROR)

<type> BUF(\*)

INTEGER PARTITIONS, DATATYPE, DEST, TAG, COMM, INFO, REQUEST, IERROR INTEGER(KIND=MPI\_COUNT\_KIND) COUNT

MPI\_PSEND\_INIT(BUF, PARTITIONS, COUNT, DATATYPE, DEST, TAG, COMM, INFO, REQUEST, IERROR)

<type> BUF(\*)

INTEGER PARTITIONS, DATATYPE, DEST, TAG, COMM, INFO, REQUEST, IERROR INTEGER(KIND=MPI\_COUNT\_KIND) COUNT

## A.5.3 Datatypes Fortran Bindings

- INTEGER(KIND=MPI\_ADDRESS\_KIND) MPI\_AINT\_ADD(BASE, DISP)
   INTEGER(KIND=MPI\_ADDRESS\_KIND) BASE, DISP
- INTEGER(KIND=MPI\_ADDRESS\_KIND) MPI\_AINT\_DIFF(ADDR1, ADDR2)
   INTEGER(KIND=MPI\_ADDRESS\_KIND) ADDR1, ADDR2
- MPI\_GET\_ADDRESS(LOCATION, ADDRESS, IERROR)

<type> LUCATION(*) INTEGER(KIND=MPI_ADDRESS_KIND) ADDRESS INTEGER IERROR</type>
MPI_GET_ELEMENTS(STATUS, DATATYPE, COUNT, IERROR) INTEGER STATUS(MPI_STATUS_SIZE), DATATYPE, COUNT, IERROR
MPI_GET_ELEMENTS_X(STATUS, DATATYPE, COUNT, IERROR) INTEGER STATUS(MPI_STATUS_SIZE), DATATYPE, IERROR INTEGER(KIND=MPI_COUNT_KIND) COUNT
MPI_PACK(INBUF, INCOUNT, DATATYPE, OUTBUF, OUTSIZE, POSITION, COMM, IERROR) <type> INBUF(*), OUTBUF(*)  INTEGER INCOUNT, DATATYPE, OUTSIZE, POSITION, COMM, IERROR</type>
MPI_PACK_EXTERNAL(DATAREP, INBUF, INCOUNT, DATATYPE, OUTBUF, OUTSIZE,  POSITION, IERROR)  CHARACTER*(*) DATAREP <type> INBUF(*), OUTBUF(*)  INTEGER INCOUNT, DATATYPE, IERROR  INTEGER(KIND=MPI_ADDRESS_KIND) OUTSIZE, POSITION</type>
MPI_PACK_EXTERNAL_SIZE(DATAREP, INCOUNT, DATATYPE, SIZE, IERROR) CHARACTER*(*) DATAREP INTEGER INCOUNT, DATATYPE, IERROR INTEGER(KIND=MPI_ADDRESS_KIND) SIZE
MPI_PACK_SIZE(INCOUNT, DATATYPE, COMM, SIZE, IERROR) INTEGER INCOUNT, DATATYPE, COMM, SIZE, IERROR
MPI_TYPE_COMMIT(DATATYPE, IERROR) INTEGER DATATYPE, IERROR
MPI_TYPE_CONTIGUOUS(COUNT, OLDTYPE, NEWTYPE, IERROR) INTEGER COUNT, OLDTYPE, NEWTYPE, IERROR
MPI_TYPE_CREATE_DARRAY(SIZE, RANK, NDIMS, ARRAY_OF_GSIZES,  ARRAY_OF_DISTRIBS, ARRAY_OF_DARGS, ARRAY_OF_PSIZES, ORDER,  OLDTYPE, NEWTYPE, IERROR)  INTEGER SIZE, RANK, NDIMS, ARRAY_OF_GSIZES(*), ARRAY_OF_DISTRIBS(*),  ARRAY_OF_DARGS(*), ARRAY_OF_PSIZES(*), ORDER, OLDTYPE,  NEWTYPE, IERROR
MPI_TYPE_CREATE_HINDEXED(COUNT, ARRAY_OF_BLOCKLENGTHS,  ARRAY_OF_DISPLACEMENTS, OLDTYPE, NEWTYPE, IERROR)  INTEGER COUNT, ARRAY_OF_BLOCKLENGTHS(*), OLDTYPE, NEWTYPE, IERROR  INTEGER(KIND=MPI_ADDRESS_KIND) ARRAY_OF_DISPLACEMENTS(*)
MPI_TYPE_CREATE_HINDEXED_BLOCK(COUNT, BLOCKLENGTH, ARRAY_OF_DISPLACEMENTS, OLDTYPE, NEWTYPE, IERROR) INTEGER COUNT, BLOCKLENGTH, OLDTYPE, NEWTYPE, IERROR INTEGER(KIND=MPI_ADDRESS_KIND) ARRAY_OF_DISPLACEMENTS(*)

```
1
    MPI_TYPE_CREATE_HVECTOR(COUNT, BLOCKLENGTH, STRIDE, OLDTYPE, NEWTYPE,
2
                   IERROR)
3
         INTEGER COUNT, BLOCKLENGTH, OLDTYPE, NEWTYPE, IERROR
         INTEGER(KIND=MPI_ADDRESS_KIND) STRIDE
     MPI_TYPE_CREATE_INDEXED_BLOCK(COUNT, BLOCKLENGTH, ARRAY_OF_DISPLACEMENTS,
6
                  OLDTYPE, NEWTYPE, IERROR)
         INTEGER COUNT, BLOCKLENGTH, ARRAY_OF_DISPLACEMENTS(*), OLDTYPE,
8
                   NEWTYPE, IERROR
9
10
     MPI_TYPE_CREATE_RESIZED(OLDTYPE, LB, EXTENT, NEWTYPE, IERROR)
11
         INTEGER OLDTYPE, NEWTYPE, IERROR
12
         INTEGER(KIND=MPI_ADDRESS_KIND) LB, EXTENT
13
     MPI_TYPE_CREATE_STRUCT(COUNT, ARRAY_OF_BLOCKLENGTHS,
14
                   ARRAY_OF_DISPLACEMENTS, ARRAY_OF_TYPES, NEWTYPE, IERROR)
15
         INTEGER COUNT, ARRAY_OF_BLOCKLENGTHS(*), ARRAY_OF_TYPES(*), NEWTYPE,
16
                   IERROR
17
         INTEGER(KIND=MPI_ADDRESS_KIND) ARRAY_OF_DISPLACEMENTS(*)
18
19
     MPI_TYPE_CREATE_SUBARRAY(NDIMS, ARRAY_OF_SIZES, ARRAY_OF_SUBSIZES,
20
                   ARRAY_OF_STARTS, ORDER, OLDTYPE, NEWTYPE, IERROR)
21
         INTEGER NDIMS, ARRAY_OF_SIZES(*), ARRAY_OF_SUBSIZES(*),
22
                   ARRAY_OF_STARTS(*), ORDER, OLDTYPE, NEWTYPE, IERROR
23
     MPI_TYPE_DUP(OLDTYPE, NEWTYPE, IERROR)
24
         INTEGER OLDTYPE, NEWTYPE, IERROR
26
     MPI_TYPE_FREE(DATATYPE, IERROR)
27
         INTEGER DATATYPE, IERROR
28
     MPI_TYPE_GET_CONTENTS(DATATYPE, MAX_INTEGERS, MAX_ADDRESSES, MAX_DATATYPES,
29
                   ARRAY_OF_INTEGERS, ARRAY_OF_ADDRESSES, ARRAY_OF_DATATYPES,
30
31
         INTEGER DATATYPE, MAX_INTEGERS, MAX_ADDRESSES, MAX_DATATYPES,
                   ARRAY_OF_INTEGERS(*), ARRAY_OF_DATATYPES(*), IERROR
33
         INTEGER(KIND=MPI_ADDRESS_KIND) ARRAY_OF_ADDRESSES(*)
34
35
     MPI_TYPE_GET_ENVELOPE(DATATYPE, NUM_INTEGERS, NUM_ADDRESSES, NUM_DATATYPES,
36
                  COMBINER, IERROR)
37
         INTEGER DATATYPE, NUM_INTEGERS, NUM_ADDRESSES, NUM_DATATYPES, COMBINER,
38
                   IERROR
     MPI_TYPE_GET_EXTENT(DATATYPE, LB, EXTENT, IERROR)
         INTEGER DATATYPE, IERROR
41
         INTEGER(KIND=MPI_ADDRESS_KIND) LB, EXTENT
42
43
     MPI_TYPE_GET_EXTENT_X(DATATYPE, LB, EXTENT, IERROR)
44
         INTEGER DATATYPE, IERROR
45
         INTEGER(KIND=MPI_COUNT_KIND) LB, EXTENT
46
47
     MPI_TYPE_GET_TRUE_EXTENT(DATATYPE, TRUE_LB, TRUE_EXTENT, IERROR)
         INTEGER DATATYPE, IERROR
```

INTEGER(KIND=MPI_ADDRESS_KIND) TRUE_LB, TRUE_EXTENT	1
MPI_TYPE_GET_TRUE_EXTENT_X(DATATYPE, TRUE_LB, TRUE_EXTENT, IERROR) INTEGER DATATYPE, IERROR INTEGER(KIND=MPI_COUNT_KIND) TRUE_LB, TRUE_EXTENT	2 3 4 5
MPI_TYPE_INDEXED(COUNT, ARRAY_OF_BLOCKLENGTHS, ARRAY_OF_DISPLACEMENTS, OLDTYPE, NEWTYPE, IERROR) INTEGER COUNT, ARRAY_OF_BLOCKLENGTHS(*), ARRAY_OF_DISPLACEMENTS(*), OLDTYPE, NEWTYPE, IERROR	6 7 8 9
MPI_TYPE_SIZE(DATATYPE, SIZE, IERROR) INTEGER DATATYPE, SIZE, IERROR	11 12
MPI_TYPE_SIZE_X(DATATYPE, SIZE, IERROR) INTEGER DATATYPE, IERROR INTEGER(KIND=MPI_COUNT_KIND) SIZE	13 14 15 16
MPI_TYPE_VECTOR(COUNT, BLOCKLENGTH, STRIDE, OLDTYPE, NEWTYPE, IERROR) INTEGER COUNT, BLOCKLENGTH, STRIDE, OLDTYPE, NEWTYPE, IERROR	17 18
MPI_UNPACK(INBUF, INSIZE, POSITION, OUTBUF, OUTCOUNT, DATATYPE, COMM, IERROR) <type> INBUF(*), OUTBUF(*)    INTEGER INSIZE, POSITION, OUTCOUNT, DATATYPE, COMM, IERROR</type>	19 20 21 22 23
MPI_UNPACK_EXTERNAL(DATAREP, INBUF, INSIZE, POSITION, OUTBUF, OUTCOUNT,	24 25 26 27 28 29 30
A.5.4 Collective Communication Fortran Bindings	31 32
MPI_ALLGATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE, COMM, IERROR) <type> SENDBUF(*), RECVBUF(*)    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, IERROR</type>	33 34 35 36
MPI_ALLGATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS, RECVTYPE, COMM, IERROR) <type> SENDBUF(*), RECVBUF(*) INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, COMM, IERROR</type>	37 38 39 40 41 42
MPI_ALLGATHERV_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS,  DISPLS, RECVTYPE, COMM, INFO, REQUEST, IERROR) <type> SENDBUF(*), RECVBUF(*)  INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, COMM,  INFO, REQUEST, IERROR</type>	43 44 45 46 47

```
1
    MPI_ALLGATHER_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT,
2
                  RECVTYPE, COMM, INFO, REQUEST, IERROR)
         <type> SENDBUF(*), RECVBUF(*)
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST,
5
                   IERROR
6
    MPI ALLREDUCE (SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, IERROR)
         <type> SENDBUF(*), RECVBUF(*)
         INTEGER COUNT, DATATYPE, OP, COMM, IERROR
9
10
     MPI_ALLREDUCE_INIT(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, INFO,
11
                  REQUEST, IERROR)
12
         <type> SENDBUF(*), RECVBUF(*)
13
         INTEGER COUNT, DATATYPE, OP, COMM, INFO, REQUEST, IERROR
14
     MPI_ALLTOALL(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
15
                  COMM, IERROR)
16
         <type> SENDBUF(*), RECVBUF(*)
17
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, IERROR
18
19
     MPI_ALLTOALLV(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE, RECVBUF, RECVCOUNTS,
20
                  RDISPLS, RECVTYPE, COMM, IERROR)
21
         <type> SENDBUF(*), RECVBUF(*)
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*),
23
                   RECVTYPE, COMM, IERROR
24
     MPI_ALLTOALLV_INIT(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE, RECVBUF,
25
                  RECVCOUNTS, RDISPLS, RECVTYPE, COMM, INFO, REQUEST, IERROR)
26
         <type> SENDBUF(*), RECVBUF(*)
27
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*),
28
                   RECVTYPE, COMM, INFO, REQUEST, IERROR
29
30
     MPI_ALLTOALLW(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPES, RECVBUF, RECVCOUNTS,
31
                  RDISPLS, RECVTYPES, COMM, IERROR)
         <type> SENDBUF(*), RECVBUF(*)
33
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPES(*), RECVCOUNTS(*),
34
                   RDISPLS(*), RECVTYPES(*), COMM, IERROR
35
     MPI_ALLTOALLW_INIT(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPES, RECVBUF,
36
                  RECVCOUNTS, RDISPLS, RECVTYPES, COMM, INFO, REQUEST, IERROR)
37
         <type> SENDBUF(*), RECVBUF(*)
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPES(*), RECVCOUNTS(*),
                   RDISPLS(*), RECVTYPES(*), COMM, INFO, REQUEST, IERROR
41
     MPI_ALLTOALL_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT,
42
                  RECVTYPE, COMM, INFO, REQUEST, IERROR)
43
         <type> SENDBUF(*), RECVBUF(*)
44
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST,
45
                   IERROR
46
     MPI_BARRIER(COMM, IERROR)
47
         INTEGER COMM, IERROR
```

13

15

```
MPI_BARRIER_INIT(COMM, INFO, REQUEST, IERROR)
    INTEGER COMM, INFO, REQUEST, IERROR
MPI_BCAST(BUFFER, COUNT, DATATYPE, ROOT, COMM, IERROR)
    <type> BUFFER(*)
    INTEGER COUNT, DATATYPE, ROOT, COMM, IERROR
MPI_BCAST_INIT(BUFFER, COUNT, DATATYPE, ROOT, COMM, INFO, REQUEST, IERROR)
    <type> BUFFER(*)
    INTEGER COUNT, DATATYPE, ROOT, COMM, INFO, REQUEST, IERROR
MPI_EXSCAN(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER COUNT, DATATYPE, OP, COMM, IERROR
MPI_EXSCAN_INIT(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, INFO, REQUEST,
                                                                                14
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER COUNT, DATATYPE, OP, COMM, INFO, REQUEST, IERROR
MPI_GATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
                                                                                19
             ROOT, COMM, IERROR)
                                                                                20
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, IERROR
MPI_GATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS,
             RECVTYPE, ROOT, COMM, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, ROOT,
                                                                                27
              COMM, IERROR
MPI_GATHERV_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS,
             RECVTYPE, ROOT, COMM, INFO, REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, ROOT,
              COMM, INFO, REQUEST, IERROR
MPI_GATHER_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
             ROOT, COMM, INFO, REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, INFO,
              REQUEST, IERROR
MPI_IALLGATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
             COMM, REQUEST, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, REQUEST, IERROR
                                                                               43
MPI_IALLGATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS,
                                                                                45
             RECVTYPE, COMM, REQUEST, IERROR)
```

<type> SENDBUF(\*), RECVBUF(\*)

```
1
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, COMM,
2
                   REQUEST, IERROR
     MPI_IALLREDUCE(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, REQUEST,
                   IERROR)
         <type> SENDBUF(*), RECVBUF(*)
6
         INTEGER COUNT, DATATYPE, OP, COMM, REQUEST, IERROR
7
     MPI_IALLTOALL(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
                  COMM, REQUEST, IERROR)
10
         <type> SENDBUF(*), RECVBUF(*)
11
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, REQUEST, IERROR
12
     MPI_IALLTOALLV(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE, RECVBUF, RECVCOUNTS,
13
                  RDISPLS, RECVTYPE, COMM, REQUEST, IERROR)
14
         <type> SENDBUF(*), RECVBUF(*)
15
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*),
16
                   RECVTYPE, COMM, REQUEST, IERROR
17
18
     MPI_IALLTOALLW(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPES, RECVBUF,
19
                  RECVCOUNTS, RDISPLS, RECVTYPES, COMM, REQUEST, IERROR)
20
         <type> SENDBUF(*), RECVBUF(*)
21
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPES(*), RECVCOUNTS(*),
22
                   RDISPLS(*), RECVTYPES(*), COMM, REQUEST, IERROR
23
     MPI_IBARRIER(COMM, REQUEST, IERROR)
^{24}
         INTEGER COMM, REQUEST, IERROR
26
     MPI_IBCAST(BUFFER, COUNT, DATATYPE, ROOT, COMM, REQUEST, IERROR)
27
         <type> BUFFER(*)
28
         INTEGER COUNT, DATATYPE, ROOT, COMM, REQUEST, IERROR
29
     MPI_IEXSCAN(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, REQUEST, IERROR)
30
         <type> SENDBUF(*), RECVBUF(*)
31
         INTEGER COUNT, DATATYPE, OP, COMM, REQUEST, IERROR
32
33
     MPI_IGATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
34
                  ROOT, COMM, REQUEST, IERROR)
35
         <type> SENDBUF(*), RECVBUF(*)
36
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, REQUEST,
37
                   IERROR
38
     MPI_IGATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS,
39
                  RECVTYPE, ROOT, COMM, REQUEST, IERROR)
         <type> SENDBUF(*), RECVBUF(*)
41
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, ROOT,
42
                   COMM, REQUEST, IERROR
43
44
     MPI_IREDUCE(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, ROOT, COMM, REQUEST,
45
                   IERROR)
46
         <type> SENDBUF(*), RECVBUF(*)
47
         INTEGER COUNT, DATATYPE, OP, ROOT, COMM, REQUEST, IERROR
```

MPI_IREDUCE_SCATTER(SENDBUF, RECVBUF, RECVCOUNTS, DATATYPE, OP, COMM, REQUEST, IERROR) <type> SENDBUF(*), RECVBUF(*) INTEGER RECVCOUNTS(*), DATATYPE, OP, COMM, REQUEST, IERROR</type>
MPI_IREDUCE_SCATTER_BLOCK(SENDBUF, RECVBUF, RECVCOUNT, DATATYPE, OP, COMM, REQUEST, IERROR) <type> SENDBUF(*), RECVBUF(*) INTEGER RECVCOUNT, DATATYPE, OP, COMM, REQUEST, IERROR</type>
MPI_ISCAN(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, REQUEST, IERROR) <type> SENDBUF(*), RECVBUF(*)  INTEGER COUNT, DATATYPE, OP, COMM, REQUEST, IERROR  INTEGER COUNT, DATATYPE, OP, COMM, REQUEST, IERROR</type>
MPI_ISCATTER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,  ROOT, COMM, REQUEST, IERROR) <type> SENDBUF(*), RECVBUF(*)  INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, REQUEST,  IERROR</type>
MPI_ISCATTERV(SENDBUF, SENDCOUNTS, DISPLS, SENDTYPE, RECVBUF, RECVCOUNT,  RECVTYPE, ROOT, COMM, REQUEST, IERROR) <type> SENDBUF(*), RECVBUF(*)  INTEGER SENDCOUNTS(*), DISPLS(*), SENDTYPE, RECVCOUNT, RECVTYPE, ROOT,  COMM, REQUEST, IERROR</type>
MPI_OP_COMMUTATIVE(OP, COMMUTE, IERROR) INTEGER OP, IERROR LOGICAL COMMUTE
MPI_OP_CREATE(USER_FN, COMMUTE, OP, IERROR) EXTERNAL USER_FN LOGICAL COMMUTE INTEGER OP, IERROR
MPI_OP_FREE(OP, IERROR) INTEGER OP, IERROR
MPI_REDUCE(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, ROOT, COMM, IERROR) <type> SENDBUF(*), RECVBUF(*) INTEGER COUNT, DATATYPE, OP, ROOT, COMM, IERROR</type>
MPI_REDUCE_INIT(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, ROOT, COMM, INFO, REQUEST, IERROR) <type> SENDBUF(*), RECVBUF(*) INTEGER COUNT, DATATYPE, OP, ROOT, COMM, INFO, REQUEST, IERROR</type>
MPI_REDUCE_LOCAL(INBUF, INOUTBUF, COUNT, DATATYPE, OP, IERROR) <type> INBUF(*), INOUTBUF(*)    INTEGER COUNT, DATATYPE, OP, IERROR</type>
MPI_REDUCE_SCATTER(SENDBUF, RECVBUF, RECVCOUNTS, DATATYPE, OP, COMM, IERROR)

```
1
         <type> SENDBUF(*), RECVBUF(*)
2
         INTEGER RECVCOUNTS(*), DATATYPE, OP, COMM, IERROR
     MPI_REDUCE_SCATTER_BLOCK(SENDBUF, RECVBUF, RECVCOUNT, DATATYPE, OP, COMM,
                   IERROR)
5
         <type> SENDBUF(*), RECVBUF(*)
6
         INTEGER RECVCOUNT, DATATYPE, OP, COMM, IERROR
7
     MPI_REDUCE_SCATTER_BLOCK_INIT(SENDBUF, RECVBUF, RECVCOUNT, DATATYPE, OP,
9
                  COMM, INFO, REQUEST, IERROR)
10
         <type> SENDBUF(*), RECVBUF(*)
11
         INTEGER RECVCOUNT, DATATYPE, OP, COMM, INFO, REQUEST, IERROR
12
     MPI_REDUCE_SCATTER_INIT(SENDBUF, RECVBUF, RECVCOUNTS, DATATYPE, OP, COMM,
13
                   INFO, REQUEST, IERROR)
14
         <type> SENDBUF(*), RECVBUF(*)
15
         INTEGER RECVCOUNTS(*), DATATYPE, OP, COMM, INFO, REQUEST, IERROR
16
17
     MPI_SCAN(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, IERROR)
18
         <type> SENDBUF(*), RECVBUF(*)
19
         INTEGER COUNT, DATATYPE, OP, COMM, IERROR
20
     MPI_SCAN_INIT(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, INFO, REQUEST,
21
                   IERROR)
22
         <type> SENDBUF(*), RECVBUF(*)
23
         INTEGER COUNT, DATATYPE, OP, COMM, INFO, REQUEST, IERROR
24
     MPI_SCATTER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
26
                  ROOT, COMM, IERROR)
27
         <type> SENDBUF(*), RECVBUF(*)
28
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, IERROR
29
     MPI_SCATTERV(SENDBUF, SENDCOUNTS, DISPLS, SENDTYPE, RECVBUF, RECVCOUNT,
30
                  RECVTYPE, ROOT, COMM, IERROR)
31
         <type> SENDBUF(*), RECVBUF(*)
         INTEGER SENDCOUNTS(*), DISPLS(*), SENDTYPE, RECVCOUNT, RECVTYPE, ROOT,
33
                   COMM, IERROR
34
35
     MPI_SCATTERV_INIT(SENDBUF, SENDCOUNTS, DISPLS, SENDTYPE, RECVBUF,
36
                  RECVCOUNT, RECVTYPE, ROOT, COMM, INFO, REQUEST, IERROR)
37
         <type> SENDBUF(*), RECVBUF(*)
         INTEGER SENDCOUNTS(*), DISPLS(*), SENDTYPE, RECVCOUNT, RECVTYPE, ROOT,
39
                   COMM, INFO, REQUEST, IERROR
     MPI_SCATTER_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT,
41
                  RECVTYPE, ROOT, COMM, INFO, REQUEST, IERROR)
         <type> SENDBUF(*), RECVBUF(*)
43
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, INFO,
44
                   REQUEST, IERROR
```

A.5.5 Groups, Contexts, Communicators, and Caching Fortran Bindings	1
MPI_COMM_COMPARE(COMM1, COMM2, RESULT, IERROR) INTEGER COMM1, COMM2, RESULT, IERROR	3 4
MPI_COMM_CREATE(COMM, GROUP, NEWCOMM, IERROR) INTEGER COMM, GROUP, NEWCOMM, IERROR	5
MPI_COMM_CREATE_FROM_GROUP(GROUP, STRINGTAG, INFO, ERRHANDLER, NEWCOMM,	7 8
IERROR) INTEGER GROUP, INFO, ERRHANDLER, NEWCOMM, IERROR CHARACTER*(*) STRINGTAG	9 10 11
MPI_COMM_CREATE_GROUP(COMM, GROUP, TAG, NEWCOMM, IERROR) INTEGER COMM, GROUP, TAG, NEWCOMM, IERROR	12 13
MPI_COMM_CREATE_KEYVAL(COMM_COPY_ATTR_FN, COMM_DELETE_ATTR_FN, COMM_KEYVAL,	14 15 16 17 18
MPI_COMM_DELETE_ATTR(COMM, COMM_KEYVAL, IERROR) INTEGER COMM, COMM_KEYVAL, IERROR	20 21 22
MPI_COMM_DUP(COMM, NEWCOMM, IERROR) INTEGER COMM, NEWCOMM, IERROR	23 24
MPI_COMM_DUP_FN(OLDCOMM, COMM_KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,	25 26 27 28 29 30 31
MPI_COMM_DUP_WITH_INFO(COMM, INFO, NEWCOMM, IERROR) INTEGER COMM, INFO, NEWCOMM, IERROR	32 33
MPI_COMM_FREE(COMM, IERROR) INTEGER COMM, IERROR	34 35 36
MPI_COMM_FREE_KEYVAL(COMM_KEYVAL, IERROR) INTEGER COMM_KEYVAL, IERROR	37 38
MPI_COMM_GET_ATTR(COMM, COMM_KEYVAL, ATTRIBUTE_VAL, FLAG, IERROR) INTEGER COMM, COMM_KEYVAL, IERROR INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL LOGICAL FLAG	39 40 41 42 43
MPI_COMM_GET_INFO(COMM, INFO_USED, IERROR) INTEGER COMM, INFO_USED, IERROR	44 45
MPI_COMM_GET_NAME(COMM, COMM_NAME, RESULTLEN, IERROR) INTEGER COMM, RESULTLEN, IERROR	46 47

```
1
         CHARACTER*(*) COMM_NAME
2
     MPI_COMM_GROUP(COMM, GROUP, IERROR)
3
         INTEGER COMM, GROUP, IERROR
5
     MPI_COMM_IDUP(COMM, NEWCOMM, REQUEST, IERROR)
6
         INTEGER COMM, NEWCOMM, REQUEST, IERROR
7
     MPI_COMM_IDUP_WITH_INFO(COMM, INFO, NEWCOMM, REQUEST, IERROR)
8
         INTEGER COMM, INFO, NEWCOMM, REQUEST, IERROR
9
10
    MPI_COMM_NULL_COPY_FN(OLDCOMM, COMM_KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,
11
                   ATTRIBUTE_VAL_OUT, FLAG, IERROR)
12
         INTEGER OLDCOMM, COMM_KEYVAL, IERROR
13
         INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
14
                   ATTRIBUTE_VAL_OUT
15
         LOGICAL FLAG
16
    MPI_COMM_NULL_DELETE_FN(COMM, COMM_KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE,
17
                   IERROR)
         INTEGER COMM, COMM_KEYVAL, IERROR
19
         INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
20
21
     MPI_COMM_RANK(COMM, RANK, IERROR)
22
         INTEGER COMM, RANK, IERROR
23
    MPI_COMM_REMOTE_GROUP(COMM, GROUP, IERROR)
24
         INTEGER COMM, GROUP, IERROR
26
    MPI_COMM_REMOTE_SIZE(COMM, SIZE, IERROR)
27
         INTEGER COMM, SIZE, IERROR
28
    MPI_COMM_SET_ATTR(COMM, COMM_KEYVAL, ATTRIBUTE_VAL, IERROR)
29
         INTEGER COMM, COMM_KEYVAL, IERROR
30
         INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
31
     MPI_COMM_SET_INFO(COMM, INFO, IERROR)
33
         INTEGER COMM, INFO, IERROR
34
     MPI_COMM_SET_NAME(COMM, COMM_NAME, IERROR)
35
         INTEGER COMM, IERROR
36
         CHARACTER*(*) COMM_NAME
37
    MPI_COMM_SIZE(COMM, SIZE, IERROR)
39
         INTEGER COMM, SIZE, IERROR
     MPI_COMM_SPLIT(COMM, COLOR, KEY, NEWCOMM, IERROR)
41
42
         INTEGER COMM, COLOR, KEY, NEWCOMM, IERROR
43
     MPI_COMM_SPLIT_TYPE(COMM, SPLIT_TYPE, KEY, INFO, NEWCOMM, IERROR)
44
         INTEGER COMM, SPLIT_TYPE, KEY, INFO, NEWCOMM, IERROR
45
^{46}
     MPI_COMM_TEST_INTER(COMM, FLAG, IERROR)
47
         INTEGER COMM, IERROR
```

LOGICAL FLAG

MPI_GROUP_COMPARE(GROUP1, GROUP2, RESULT, IERROR) INTEGER GROUP1, GROUP2, RESULT, IERROR
MPI_GROUP_DIFFERENCE(GROUP1, GROUP2, NEWGROUP, IERROR) INTEGER GROUP1, GROUP2, NEWGROUP, IERROR
MPI_GROUP_EXCL(GROUP, N, RANKS, NEWGROUP, IERROR) INTEGER GROUP, N, RANKS(*), NEWGROUP, IERROR
MPI_GROUP_FREE(GROUP, IERROR) INTEGER GROUP, IERROR
MPI_GROUP_FROM_SESSION_PSET(SESSION, PSET_NAME, NEWGROUP, IERROR)  INTEGER SESSION, NEWGROUP, IERROR  CHARACTER*(*) PSET_NAME
MPI_GROUP_INCL(GROUP, N, RANKS, NEWGROUP, IERROR) INTEGER GROUP, N, RANKS(*), NEWGROUP, IERROR
MPI_GROUP_INTERSECTION(GROUP1, GROUP2, NEWGROUP, IERROR) INTEGER GROUP1, GROUP2, NEWGROUP, IERROR
MPI_GROUP_RANGE_EXCL(GROUP, N, RANGES, NEWGROUP, IERROR) INTEGER GROUP, N, RANGES(3, *), NEWGROUP, IERROR
MPI_GROUP_RANGE_INCL(GROUP, N, RANGES, NEWGROUP, IERROR) INTEGER GROUP, N, RANGES(3, *), NEWGROUP, IERROR
MPI_GROUP_RANK(GROUP, RANK, IERROR) INTEGER GROUP, RANK, IERROR
MPI_GROUP_SIZE(GROUP, SIZE, IERROR) INTEGER GROUP, SIZE, IERROR
MPI_GROUP_TRANSLATE_RANKS(GROUP1, N, RANKS1, GROUP2, RANKS2, IERROR) INTEGER GROUP1, N, RANKS1(*), GROUP2, RANKS2(*), IERROR
MPI_GROUP_UNION(GROUP1, GROUP2, NEWGROUP, IERROR) INTEGER GROUP1, GROUP2, NEWGROUP, IERROR
MPI_INTERCOMM_CREATE(LOCAL_COMM, LOCAL_LEADER, PEER_COMM, REMOTE_LEADER, TAG, NEWINTERCOMM, IERROR)  INTEGER LOCAL_COMM, LOCAL_LEADER, PEER_COMM, REMOTE_LEADER, TAG, NEWINTERCOMM, IERROR
MPI_INTERCOMM_CREATE_FROM_GROUPS(LOCAL_GROUP, LOCAL_LEADER, REMOTE_GROUP, REMOTE_LEADER, STRINGTAG, INFO, ERRHANDLER, NEWINTERCOMM, IERROR)
INTEGER LOCAL_GROUP, LOCAL_LEADER, REMOTE_GROUP, REMOTE_LEADER, INFO,  ERRHANDLER, NEWINTERCOMM, IERROR  CHARACTER*(*) STRINGTAG
MPI_INTERCOMM_MERGE(INTERCOMM, HIGH, NEWINTRACOMM, IERROR)  INTEGER INTERCOMM, NEWINTRACOMM, IERROR  4

LOGICAL HIGH

```
MPI_TYPE_CREATE_KEYVAL(TYPE_COPY_ATTR_FN, TYPE_DELETE_ATTR_FN, TYPE_KEYVAL,
2
                  EXTRA_STATE, IERROR)
         EXTERNAL TYPE_COPY_ATTR_FN, TYPE_DELETE_ATTR_FN
4
         INTEGER TYPE_KEYVAL, IERROR
5
         INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
6
    MPI TYPE DELETE ATTR(DATATYPE, TYPE KEYVAL, IERROR)
         INTEGER DATATYPE, TYPE_KEYVAL, IERROR
8
9
     MPI_TYPE_DUP_FN(OLDTYPE, TYPE_KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,
10
                   ATTRIBUTE_VAL_OUT, FLAG, IERROR)
11
         INTEGER OLDTYPE, TYPE_KEYVAL, IERROR
12
         INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
13
                   ATTRIBUTE_VAL_OUT
14
         LOGICAL FLAG
15
     MPI_TYPE_FREE_KEYVAL(TYPE_KEYVAL, IERROR)
16
         INTEGER TYPE_KEYVAL, IERROR
17
18
     MPI_TYPE_GET_ATTR(DATATYPE, TYPE_KEYVAL, ATTRIBUTE_VAL, FLAG, IERROR)
19
         INTEGER DATATYPE, TYPE_KEYVAL, IERROR
20
         INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
21
         LOGICAL FLAG
22
     MPI_TYPE_GET_NAME(DATATYPE, TYPE_NAME, RESULTLEN, IERROR)
23
         INTEGER DATATYPE, RESULTLEN, IERROR
24
         CHARACTER*(*) TYPE_NAME
26
     MPI_TYPE_NULL_COPY_FN(OLDTYPE, TYPE_KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,
27
                  ATTRIBUTE_VAL_OUT, FLAG, IERROR)
28
         INTEGER OLDTYPE, TYPE_KEYVAL, IERROR
         INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
30
                   ATTRIBUTE_VAL_OUT
         LOGICAL FLAG
     MPI_TYPE_NULL_DELETE_FN(DATATYPE, TYPE_KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE,
33
                  IERROR)
34
         INTEGER DATATYPE, TYPE_KEYVAL, IERROR
35
         INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
36
37
     MPI_TYPE_SET_ATTR(DATATYPE, TYPE_KEYVAL, ATTRIBUTE_VAL, IERROR)
         INTEGER DATATYPE, TYPE_KEYVAL, IERROR
39
         INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
     MPI_TYPE_SET_NAME(DATATYPE, TYPE_NAME, IERROR)
41
         INTEGER DATATYPE, IERROR
42
         CHARACTER*(*) TYPE_NAME
43
44
     MPI_WIN_CREATE_KEYVAL(WIN_COPY_ATTR_FN, WIN_DELETE_ATTR_FN, WIN_KEYVAL,
45
                  EXTRA_STATE, IERROR)
46
         EXTERNAL WIN_COPY_ATTR_FN, WIN_DELETE_ATTR_FN
47
         INTEGER WIN_KEYVAL, IERROR
```

INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE	1
MPI_WIN_DELETE_ATTR(WIN, WIN_KEYVAL, IERROR) INTEGER WIN, WIN_KEYVAL, IERROR	2 3 4
MPI_WIN_DUP_FN(OLDWIN, WIN_KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)	5 6 7
INTEGER OLDWIN, WIN_KEYVAL, IERROR INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT	8 9
LOGICAL FLAG	10 11
MPI_WIN_FREE_KEYVAL(WIN_KEYVAL, IERROR) INTEGER WIN_KEYVAL, IERROR	12
MPI_WIN_GET_ATTR(WIN, WIN_KEYVAL, ATTRIBUTE_VAL, FLAG, IERROR)	14
INTEGER WIN, WIN_KEYVAL, IERROR	15
INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL	16
LOGICAL FLAG	17 18
MPI_WIN_GET_NAME(WIN, WIN_NAME, RESULTLEN, IERROR)	19
INTEGER WIN, RESULTLEN, IERROR	20
CHARACTER*(*) WIN_NAME	21
MPI_WIN_NULL_COPY_FN(OLDWIN, WIN_KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,	22
ATTRIBUTE_VAL_OUT, FLAG, IERROR)	23 24
INTEGER OLDWIN, WIN_KEYVAL, IERROR	25
INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,	26
ATTRIBUTE_VAL_OUT LOGICAL FLAG	27
	28
MPI_WIN_NULL_DELETE_FN(WIN, WIN_KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE, IERROR) INTEGER WIN, WIN_KEYVAL, IERROR	29 30
INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE	31
MPI_WIN_SET_ATTR(WIN, WIN_KEYVAL, ATTRIBUTE_VAL, IERROR)	32
INTEGER WIN, WIN_KEYVAL, IERROR	33 34
INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL	35
MPI_WIN_SET_NAME(WIN, WIN_NAME, IERROR)	36
INTEGER WIN, IERROR	37
CHARACTER*(*) WIN_NAME	38
	39
A.5.6 Process Topologies Fortran Bindings	40
MDI CADTDIM CET(COMM NDIME TERROR)	41 42
MPI_CARTDIM_GET(COMM, NDIMS, IERROR) INTEGER COMM, NDIMS, IERROR	43
	44
MPI_CART_COORDS(COMM, RANK, MAXDIMS, COORDS, IERROR) INTEGER COMM, RANK, MAXDIMS, COORDS(*), IERROR	45 46
MPI_CART_CREATE(COMM_OLD, NDIMS, DIMS, PERIODS, REORDER, COMM_CART, IERROR)	47

	TEGER COMM_OLD, NDIMS, DIMS(*), COMM_CART, IERROR
LU	GICAL PERIODS(*), REORDER
	RT_GET(COMM, MAXDIMS, DIMS, PERIODS, COORDS, IERROR)
	TEGER COMM, MAXDIMS, DIMS(*), COORDS(*), IERROR
LO	GICAL PERIODS(*)
MPI_CAI	RT_MAP(COMM, NDIMS, DIMS, PERIODS, NEWRANK, IERROR)
	TEGER COMM, NDIMS, DIMS(*), NEWRANK, IERROR
LO	GICAL PERIODS(*)
MPI_CAI	RT_RANK(COMM, COORDS, RANK, IERROR)
IN	TEGER COMM, COORDS(*), RANK, IERROR
MPT CAI	RT_SHIFT(COMM, DIRECTION, DISP, RANK_SOURCE, RANK_DEST, IERROR)
	TEGER COMM, DIRECTION, DISP, RANK_SOURCE, RANK_DEST, IERROR
	RT_SUB(COMM, REMAIN_DIMS, NEWCOMM, IERROR) TEGER COMM, NEWCOMM, IERROR
	GICAL REMAIN_DIMS(*)
	MS_CREATE(NNODES, NDIMS, DIMS, IERROR)
IN	TEGER NNODES, NDIMS, DIMS(*), IERROR
MPI_DI	ST_GRAPH_CREATE(COMM_OLD, N, SOURCES, DEGREES, DESTINATIONS, WEIGHTS,
	INFO, REORDER, COMM_DIST_GRAPH, IERROR)
IN	TEGER COMM_OLD, N, SOURCES(*), DEGREES(*), DESTINATIONS(*),
	WEIGHTS(*), INFO, COMM_DIST_GRAPH, IERROR
LO	GICAL REORDER
MPI_DI	ST_GRAPH_CREATE_ADJACENT(COMM_OLD, INDEGREE, SOURCES, SOURCEWEIGHTS,
	OUTDEGREE, DESTINATIONS, DESTWEIGHTS, INFO, REORDER,
	COMM_DIST_GRAPH, IERROR)
IN	TEGER COMM_OLD, INDEGREE, SOURCES(*), SOURCEWEIGHTS(*), OUTDEGREE,
	DESTINATIONS(*), DESTWEIGHTS(*), INFO, COMM_DIST_GRAPH,
T 0	IERROR
L00	GICAL REORDER
MPI_DI	ST_GRAPH_NEIGHBORS(COMM, MAXINDEGREE, SOURCES, SOURCEWEIGHTS,
	MAXOUTDEGREE, DESTINATIONS, DESTWEIGHTS, IERROR)
IN	TEGER COMM, MAXINDEGREE, SOURCES(*), SOURCEWEIGHTS(*), MAXOUTDEGREE,
	DESTINATIONS(*), DESTWEIGHTS(*), IERROR
MPI_DI	ST_GRAPH_NEIGHBORS_COUNT(COMM, INDEGREE, OUTDEGREE, WEIGHTED, IERROR)
IN	TEGER COMM, INDEGREE, OUTDEGREE, IERROR
LO	GICAL WEIGHTED
MPT GR	APHDIMS_GET(COMM, NNODES, NEDGES, IERROR)
_	TEGER COMM, NNODES, NEDGES, IERROR
MPI_GK	APH_CREATE(COMM_OLD, NNODES, INDEX, EDGES, REORDER, COMM_GRAPH, IERROR)
TN	TEGER COMM OLD. NNODES. INDEX(*). EDGES(*). COMM GRAPH. TERROR

LOGICAL REORDER	1
<pre>MPI_GRAPH_GET(COMM, MAXINDEX, MAXEDGES, INDEX, EDGES, IERROR)     INTEGER COMM, MAXINDEX, MAXEDGES, INDEX(*), EDGES(*), IERROR</pre>	2 3 4
MPI_GRAPH_MAP(COMM, NNODES, INDEX, EDGES, NEWRANK, IERROR) INTEGER COMM, NNODES, INDEX(*), EDGES(*), NEWRANK, IERROR	5 6
MPI_GRAPH_NEIGHBORS(COMM, RANK, MAXNEIGHBORS, NEIGHBORS, IERROR) INTEGER COMM, RANK, MAXNEIGHBORS, NEIGHBORS(*), IERROR	7 8 9
MPI_GRAPH_NEIGHBORS_COUNT(COMM, RANK, NNEIGHBORS, IERROR) INTEGER COMM, RANK, NNEIGHBORS, IERROR	10 11
MPI_INEIGHBOR_ALLGATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE, COMM, REQUEST, IERROR) <type> SENDBUF(*), RECVBUF(*)    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, REQUEST, IERROR</type>	12 13 14 15 16
MPI_INEIGHBOR_ALLGATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS,  DISPLS, RECVTYPE, COMM, REQUEST, IERROR) <type> SENDBUF(*), RECVBUF(*)  INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, COMM,  REQUEST, IERROR</type>	17 18 19 20 21
MPI_INEIGHBOR_ALLTOALL(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE, COMM, REQUEST, IERROR) <type> SENDBUF(*), RECVBUF(*) INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, REQUEST, IERROR</type>	22 23 24 25 26
MPI_INEIGHBOR_ALLTOALLV(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE, RECVBUF, RECVCOUNTS, RDISPLS, RECVTYPE, COMM, REQUEST, IERROR) <type> SENDBUF(*), RECVBUF(*) INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*), RECVTYPE, COMM, REQUEST, IERROR</type>	27 28 29 30 31 32
<pre>MPI_INEIGHBOR_ALLTOALLW(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPES, RECVBUF,</pre>	33 34 35 36 37 38
MPI_NEIGHBOR_ALLGATHER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE, COMM, IERROR) <type> SENDBUF(*), RECVBUF(*)   INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, IERROR</type>	39 40 41 42 43
MPI_NEIGHBOR_ALLGATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS,  DISPLS, RECVTYPE, COMM, IERROR) <type> SENDBUF(*), RECVBUF(*)  INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, COMM.</type>	44 45 46 47

IERROR

```
1
     MPI_NEIGHBOR_ALLGATHERV_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF,
2
                  RECVCOUNTS, DISPLS, RECVTYPE, COMM, INFO, REQUEST, IERROR)
         <type> SENDBUF(*), RECVBUF(*)
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, COMM,
5
                   INFO, REQUEST, IERROR
6
     MPI NEIGHBOR ALLGATHER INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF,
                  RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST, IERROR)
         <type> SENDBUF(*), RECVBUF(*)
9
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST,
10
                   IERROR
11
12
    MPI_NEIGHBOR_ALLTOALL(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT,
13
                  RECVTYPE, COMM, IERROR)
14
         <type> SENDBUF(*), RECVBUF(*)
15
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, IERROR
16
     MPI_NEIGHBOR_ALLTOALLV(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE, RECVBUF,
17
                  RECVCOUNTS, RDISPLS, RECVTYPE, COMM, IERROR)
18
         <type> SENDBUF(*), RECVBUF(*)
19
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*),
20
                   RECVTYPE, COMM, IERROR
21
22
     MPI_NEIGHBOR_ALLTOALLV_INIT(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPE,
23
                  RECVBUF, RECVCOUNTS, RDISPLS, RECVTYPE, COMM, INFO, REQUEST,
24
                  IERROR)
         <type> SENDBUF(*), RECVBUF(*)
26
         INTEGER SENDCOUNTS(*), SDISPLS(*), SENDTYPE, RECVCOUNTS(*), RDISPLS(*),
27
                   RECVTYPE, COMM, INFO, REQUEST, IERROR
28
     MPI_NEIGHBOR_ALLTOALLW(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPES, RECVBUF,
29
                  RECVCOUNTS, RDISPLS, RECVTYPES, COMM, IERROR)
30
         <type> SENDBUF(*), RECVBUF(*)
31
         INTEGER SENDCOUNTS(*), SENDTYPES(*), RECVCOUNTS(*), RECVTYPES(*), COMM,
33
         INTEGER(KIND=MPI_ADDRESS_KIND) SDISPLS(*), RDISPLS(*)
34
35
     MPI_NEIGHBOR_ALLTOALLW_INIT(SENDBUF, SENDCOUNTS, SDISPLS, SENDTYPES,
36
                  RECVBUF, RECVCOUNTS, RDISPLS, RECVTYPES, COMM, INFO, REQUEST,
37
                  IERROR)
         <type> SENDBUF(*), RECVBUF(*)
         INTEGER SENDCOUNTS(*), SENDTYPES(*), RECVCOUNTS(*), RECVTYPES(*), COMM,
                   INFO, REQUEST, IERROR
41
         INTEGER(KIND=MPI_ADDRESS_KIND) SDISPLS(*), RDISPLS(*)
42
     MPI_NEIGHBOR_ALLTOALL_INIT(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF,
43
                  RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST, IERROR)
44
         <type> SENDBUF(*), RECVBUF(*)
45
         INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, COMM, INFO, REQUEST,
                   IERROR
47
```

MPI_TOPO_TEST(COMM, STATUS, IERROR)  INTEGER COMM, STATUS, IERROR	2
A.5.7 MPI Environmental Management Fortran Bindings	4 5
DOUBLE PRECISION MPI_WTICK()	$\epsilon$
DOUBLE PRECISION MPI_WTIME()	7
MPI_ADD_ERROR_CLASS(ERRORCLASS, IERROR) INTEGER ERRORCLASS, IERROR	1
MPI_ADD_ERROR_CODE(ERRORCLASS, ERRORCODE, IERROR) INTEGER ERRORCLASS, ERRORCODE, IERROR	1 1:
MPI_ADD_ERROR_STRING(ERRORCODE, STRING, IERROR) INTEGER ERRORCODE, IERROR CHARACTER*(*) STRING	1. 1. 1. 1.
MPI_ALLOC_MEM(SIZE, INFO, BASEPTR, IERROR) INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR INTEGER INFO, IERROR	1 1 2
If the Fortran compiler provides TYPE(C_PTR), then overloaded by:  INTERFACE MPI_ALLOC_MEM  SUBROUTINE MPI_ALLOC_MEM(SIZE, INFO, BASEPTR, IERROR)  IMPORT :: MPI_ADDRESS_KIND  INTEGER :: INFO, IERROR  INTEGER(KIND=MPI_ADDRESS_KIND) :: SIZE, BASEPTR  END SUBROUTINE  SUBROUTINE MPI_ALLOC_MEM_CPTR(SIZE, INFO, BASEPTR, IERROR)  USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR  IMPORT :: MPI_ADDRESS_KIND	2 2 2 2 2 2 2 2 2 2 3
INTEGER :: INFO, IERROR  INTEGER(KIND=MPI_ADDRESS_KIND) :: SIZE  TYPE(C_PTR) :: BASEPTR  END SUBROUTINE  END INTERFACE	3 3 3 3 3
MPI_COMM_CALL_ERRHANDLER(COMM, ERRORCODE, IERROR) INTEGER COMM, ERRORCODE, IERROR	3
MPI_COMM_CREATE_ERRHANDLER(COMM_ERRHANDLER_FN, ERRHANDLER, IERROR) EXTERNAL COMM_ERRHANDLER_FN INTEGER ERRHANDLER, IERROR	3 4 4 4 4
MPI_COMM_GET_ERRHANDLER(COMM, ERRHANDLER, IERROR) INTEGER COMM, ERRHANDLER, IERROR	4
MPI_COMM_SET_ERRHANDLER(COMM, ERRHANDLER, IERROR) INTEGER COMM, ERRHANDLER, IERROR	4 4
MPI_ERRHANDLER_FREE(ERRHANDLER, IERROR)	4

```
1
         INTEGER ERRHANDLER, IERROR
2
     MPI_ERROR_CLASS(ERRORCODE, ERRORCLASS, IERROR)
3
         INTEGER ERRORCODE, ERRORCLASS, IERROR
5
     MPI_ERROR_STRING(ERRORCODE, STRING, RESULTLEN, IERROR)
6
         INTEGER ERRORCODE, RESULTLEN, IERROR
         CHARACTER*(*) STRING
     MPI_FILE_CALL_ERRHANDLER(FH, ERRORCODE, IERROR)
         INTEGER FH, ERRORCODE, IERROR
10
11
    MPI_FILE_CREATE_ERRHANDLER(FILE_ERRHANDLER_FN, ERRHANDLER, IERROR)
12
         EXTERNAL FILE_ERRHANDLER_FN
13
         INTEGER ERRHANDLER, IERROR
14
     MPI_FILE_GET_ERRHANDLER(FILE, ERRHANDLER, IERROR)
15
         INTEGER FILE, ERRHANDLER, IERROR
16
17
     MPI_FILE_SET_ERRHANDLER(FILE, ERRHANDLER, IERROR)
18
         INTEGER FILE, ERRHANDLER, IERROR
19
     MPI_FREE_MEM(BASE, IERROR)
20
         <type> BASE(*)
21
         INTEGER IERROR
22
23
     MPI_GET_LIBRARY_VERSION(VERSION, RESULTLEN, IERROR)
^{24}
         CHARACTER*(*) VERSION
         INTEGER RESULTLEN, IERROR
26
     MPI_GET_PROCESSOR_NAME(NAME, RESULTLEN, IERROR)
27
         CHARACTER*(*) NAME
28
         INTEGER RESULTLEN, IERROR
29
30
     MPI_GET_VERSION(VERSION, SUBVERSION, IERROR)
31
         INTEGER VERSION, SUBVERSION, IERROR
32
     MPI_SESSION_CALL_ERRHANDLER(SESSION, ERRORCODE, IERROR)
33
34
         INTEGER SESSION, ERRORCODE, IERROR
35
     MPI_SESSION_CREATE_ERRHANDLER(SESSION_ERRHANDLER_FN, ERRHANDLER, IERROR)
36
         EXTERNAL SESSION_ERRHANDLER_FN
37
         INTEGER ERRHANDLER, IERROR
38
     MPI_SESSION_GET_ERRHANDLER(SESSION, ERRHANDLER, IERROR)
39
         INTEGER SESSION, ERRHANDLER, IERROR
40
41
     MPI_SESSION_SET_ERRHANDLER(SESSION, ERRHANDLER, IERROR)
         INTEGER SESSION, ERRHANDLER, IERROR
43
44
     MPI_WIN_CALL_ERRHANDLER(WIN, ERRORCODE, IERROR)
45
         INTEGER WIN, ERRORCODE, IERROR
    MPI_WIN_CREATE_ERRHANDLER(WIN_ERRHANDLER_FN, ERRHANDLER, IERROR)
47
         EXTERNAL WIN_ERRHANDLER_FN
```

INTEGER ERRHANDLER, IERROR	1
MPI_WIN_GET_ERRHANDLER(WIN, ERRHANDLER, IERROR)	3
INTEGER WIN, ERRHANDLER, IERROR	4
MPI_WIN_SET_ERRHANDLER(WIN, ERRHANDLER, IERROR)	5
INTEGER WIN, ERRHANDLER, IERROR	6
	7
A.5.8 The Info Object Fortran Bindings	9
MPI_INFO_CREATE(INFO, IERROR)	10
INTEGER INFO, IERROR	11
MPI_INFO_CREATE_ENV(INFO, IERROR)	1;
INTEGER INFO, IERROR	14
MPI_INFO_DELETE(INFO, KEY, IERROR)	18
INTEGER INFO, IERROR	1
CHARACTER*(*) KEY	18
MPI_INFO_DUP(INFO, NEWINFO, IERROR)	19
INTEGER INFO, NEWINFO, IERROR	20
MPI_INFO_FREE(INFO, IERROR)	2:
INTEGER INFO, IERROR	23
MPI_INFO_GET(INFO, KEY, VALUELEN, VALUE, FLAG, IERROR)	2
INTEGER INFO, VALUELEN, IERROR	25
CHARACTER*(*) KEY, VALUE LOGICAL FLAG	20
	28
MPI_INFO_GET_NKEYS(INFO, NKEYS, IERROR)	29
INTEGER INFO, NKEYS, IERROR	30
MPI_INFO_GET_NTHKEY(INFO, N, KEY, IERROR)	3: 3:
INTEGER INFO, N, IERROR CHARACTER*(*) KEY	33
	34
MPI_INFO_GET_STRING(INFO, KEY, BUFLEN, VALUE, FLAG, IERROR) INTEGER INFO, BUFLEN, IERROR	3
CHARACTER*(*) KEY, VALUE	36
LOGICAL FLAG	3' 38
MPI_INFO_GET_VALUELEN(INFO, KEY, VALUELEN, FLAG, IERROR)	39
INTEGER INFO, VALUELEN, IERROR	40
CHARACTER*(*) KEY	4
LOGICAL FLAG	42
MPI_INFO_SET(INFO, KEY, VALUE, IERROR)	4:
INTEGER INFO, IERROR	4
CHARACTER*(*) KEY, VALUE	46

```
1
     A.5.9 Process Creation and Management Fortran Bindings
2
     MPI_ABORT(COMM, ERRORCODE, IERROR)
3
         INTEGER COMM, ERRORCODE, IERROR
4
5
    MPI_CLOSE_PORT(PORT_NAME, IERROR)
6
         CHARACTER*(*) PORT_NAME
7
         INTEGER IERROR
     MPI_COMM_ACCEPT(PORT_NAME, INFO, ROOT, COMM, NEWCOMM, IERROR)
         CHARACTER*(*) PORT_NAME
10
         INTEGER INFO, ROOT, COMM, NEWCOMM, IERROR
11
12
     MPI_COMM_CONNECT(PORT_NAME, INFO, ROOT, COMM, NEWCOMM, IERROR)
13
         CHARACTER*(*) PORT_NAME
14
         INTEGER INFO, ROOT, COMM, NEWCOMM, IERROR
15
    MPI_COMM_DISCONNECT(COMM, IERROR)
16
         INTEGER COMM, IERROR
17
18
    MPI_COMM_GET_PARENT(PARENT, IERROR)
19
         INTEGER PARENT, IERROR
20
     MPI_COMM_JOIN(FD, INTERCOMM, IERROR)
21
         INTEGER FD, INTERCOMM, IERROR
22
23
     MPI_COMM_SPAWN(COMMAND, ARGV, MAXPROCS, INFO, ROOT, COMM, INTERCOMM,
^{24}
                   ARRAY_OF_ERRCODES, IERROR)
         CHARACTER*(*) COMMAND, ARGV(*)
26
         INTEGER MAXPROCS, INFO, ROOT, COMM, INTERCOMM, ARRAY_OF_ERRCODES(*),
27
                   IERROR
28
     MPI_COMM_SPAWN_MULTIPLE(COUNT, ARRAY_OF_COMMANDS, ARRAY_OF_ARGV,
29
                   ARRAY_OF_MAXPROCS, ARRAY_OF_INFO, ROOT, COMM, INTERCOMM,
30
                   ARRAY_OF_ERRCODES, IERROR)
31
         INTEGER COUNT, ARRAY_OF_MAXPROCS(*), ARRAY_OF_INFO(*), ROOT, COMM,
                   INTERCOMM, ARRAY_OF_ERRCODES(*), IERROR
33
         CHARACTER*(*) ARRAY_OF_COMMANDS(*), ARRAY_OF_ARGV(COUNT, *)
34
35
     MPI_FINALIZE(IERROR)
36
         INTEGER IERROR
37
     MPI_FINALIZED(FLAG, IERROR)
38
         LOGICAL FLAG
39
         INTEGER IERROR
41
    MPI_INIT(IERROR)
42
         INTEGER IERROR
43
    MPI_INITIALIZED(FLAG, IERROR)
44
45
         LOGICAL FLAG
^{46}
         INTEGER IERROR
47
```

MPI\_INIT\_THREAD(REQUIRED, PROVIDED, IERROR)

INTEGER REQUIRED, PROVIDED, IERROR	1
MPI_IS_THREAD_MAIN(FLAG, IERROR) LOGICAL FLAG	3
INTEGER IERROR	5
MPI_LOOKUP_NAME(SERVICE_NAME, INFO, PORT_NAME, IERROR) CHARACTER*(*) SERVICE_NAME, PORT_NAME	7
INTEGER INFO, IERROR	8
MPI_OPEN_PORT(INFO, PORT_NAME, IERROR) INTEGER INFO, IERROR	1
CHARACTER*(*) PORT_NAME	1
MPI_PUBLISH_NAME(SERVICE_NAME, INFO, PORT_NAME, IERROR) CHARACTER*(*) SERVICE_NAME, PORT_NAME INTEGER INFO, IERROR	1 1 1
INTEGER INFO, TERROR	1
MPI_QUERY_THREAD(PROVIDED, IERROR) INTEGER PROVIDED, IERROR	1
MPI_SESSION_FINALIZE(SESSION, IERROR) INTEGER SESSION, IERROR	2
MPI_SESSION_GET_INFO(SESSION, INFO_USED, IERROR) INTEGER SESSION, INFO_USED, IERROR	2
MPI_SESSION_GET_NTH_PSET(SESSION, INFO, N, PSET_LEN, PSET_NAME, IERROR) INTEGER SESSION, INFO, N, PSET_LEN, IERROR CHARACTER*(*) PSET_NAME	2 2 2
MPI_SESSION_GET_NUM_PSETS(SESSION, INFO, NPSET_NAMES, IERROR) INTEGER SESSION, INFO, NPSET_NAMES, IERROR	2
MPI_SESSION_GET_PSET_INFO(SESSION, PSET_NAME, INFO, IERROR) INTEGER SESSION, INFO, IERROR CHARACTER*(*) PSET_NAME	3 3 3
MPI_SESSION_INIT(INFO, ERRHANDLER, SESSION, IERROR) INTEGER INFO, ERRHANDLER, SESSION, IERROR	3
MPI_UNPUBLISH_NAME(SERVICE_NAME, INFO, PORT_NAME, IERROR) CHARACTER*(*) SERVICE_NAME, PORT_NAME INTEGER INFO, IERROR	3 3 3 4
A.5.10 One-Sided Communications Fortran Bindings	4
MPI_ACCUMULATE(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK,  TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, OP, WIN, IERROR) <type> ORIGIN_ADDR(*) INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK, TARGET_COUNT,</type>	4 4 4 4
TARGET_DATATYPE, OP, WIN, IERROR	4
INTEGER(KIND=MPI ADDRESS KIND) TARGET DISP	4

```
1
     MPI_COMPARE_AND_SWAP(ORIGIN_ADDR, COMPARE_ADDR, RESULT_ADDR, DATATYPE,
2
                  TARGET_RANK, TARGET_DISP, WIN, IERROR)
3
         <type> ORIGIN_ADDR(*), COMPARE_ADDR(*), RESULT_ADDR(*)
         INTEGER DATATYPE, TARGET_RANK, WIN, IERROR
5
         INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
6
     MPI FETCH AND OP(ORIGIN ADDR. RESULT ADDR. DATATYPE. TARGET RANK.
                  TARGET_DISP, OP, WIN, IERROR)
         <type> ORIGIN_ADDR(*), RESULT_ADDR(*)
         INTEGER DATATYPE, TARGET_RANK, OP, WIN, IERROR
10
         INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
11
12
    MPI_GET(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK,
13
                  TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, WIN, IERROR)
14
         <type> ORIGIN_ADDR(*)
15
         INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK, TARGET_COUNT,
16
                   TARGET_DATATYPE, WIN, IERROR
17
         INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
18
     MPI_GET_ACCUMULATE(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE, RESULT_ADDR,
19
                  RESULT_COUNT, RESULT_DATATYPE, TARGET_RANK, TARGET_DISP,
20
                  TARGET_COUNT, TARGET_DATATYPE, OP, WIN, IERROR)
21
         <type> ORIGIN_ADDR(*), RESULT_ADDR(*)
22
         INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, RESULT_COUNT, RESULT_DATATYPE,
23
                   TARGET_RANK, TARGET_COUNT, TARGET_DATATYPE, OP, WIN, IERROR
24
         INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
26
     MPI_PUT(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK,
27
                  TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, WIN, IERROR)
28
         <type> ORIGIN_ADDR(*)
         INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK, TARGET_COUNT,
                   TARGET_DATATYPE, WIN, IERROR
         INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
     MPI_RACCUMULATE(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK,
33
                  TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, OP, WIN, REQUEST,
34
                  IERROR)
35
         <type> ORIGIN_ADDR(*)
36
         INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK, TARGET_COUNT,
37
                   TARGET_DATATYPE, OP, WIN, REQUEST, IERROR
         INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
40
     MPI_RGET(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK,
41
                  TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, WIN, REQUEST,
42
                  IERROR)
43
         <type> ORIGIN_ADDR(*)
44
         INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK, TARGET_COUNT,
45
                   TARGET_DATATYPE, WIN, REQUEST, IERROR
         INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
47
    MPI_RGET_ACCUMULATE(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE,
```

```
RESULT_ADDR, RESULT_COUNT, RESULT_DATATYPE, TARGET_RANK,
             TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, OP, WIN, REQUEST,
              IERROR)
    <type> ORIGIN_ADDR(*), RESULT_ADDR(*)
    INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, RESULT_COUNT, RESULT_DATATYPE,
              TARGET_RANK, TARGET_COUNT, TARGET_DATATYPE, OP, WIN, REQUEST,
              IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
MPI_RPUT(ORIGIN_ADDR, ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK,
             TARGET_DISP, TARGET_COUNT, TARGET_DATATYPE, WIN, REQUEST,
              IERROR)
                                                                                  12
    <type> ORIGIN_ADDR(*)
                                                                                  13
    INTEGER ORIGIN_COUNT, ORIGIN_DATATYPE, TARGET_RANK, TARGET_COUNT,
                                                                                 14
              TARGET_DATATYPE, WIN, REQUEST, IERROR
                                                                                  15
    INTEGER(KIND=MPI_ADDRESS_KIND) TARGET_DISP
                                                                                  16
MPI_WIN_ALLOCATE(SIZE, DISP_UNIT, INFO, COMM, BASEPTR, WIN, IERROR)
                                                                                  18
    INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
    INTEGER DISP_UNIT, INFO, COMM, WIN, IERROR
                                                                                  19
                                                                                 20
If the Fortran compiler provides TYPE(C_PTR), then overloaded by:
                                                                                 21
  INTERFACE MPI_WIN_ALLOCATE
                                                                                 22
    SUBROUTINE MPI_WIN_ALLOCATE(SIZE, DISP_UNIT, INFO, COMM, BASEPTR, &
                                                                                 23
          WIN, IERROR)
                                                                                  24
      IMPORT :: MPI_ADDRESS_KIND
      INTEGER :: DISP_UNIT, INFO, COMM, WIN, IERROR
                                                                                  26
      INTEGER(KIND=MPI_ADDRESS_KIND) :: SIZE, BASEPTR
                                                                                 27
    END SUBROUTINE
                                                                                 28
    SUBROUTINE MPI_WIN_ALLOCATE_CPTR(SIZE, DISP_UNIT, INFO, COMM, BASEPTR, &
          WIN, IERROR)
                                                                                  30
      USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
      IMPORT :: MPI_ADDRESS_KIND
      INTEGER :: DISP_UNIT, INFO, COMM, WIN, IERROR
      INTEGER(KIND=MPI_ADDRESS_KIND) :: SIZE
                                                                                 34
      TYPE(C_PTR) :: BASEPTR
                                                                                 35
    END SUBROUTINE
                                                                                 36
  END INTERFACE
                                                                                 37
MPI_WIN_ALLOCATE_SHARED(SIZE, DISP_UNIT, INFO, COMM, BASEPTR, WIN, IERROR)
    INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
    INTEGER DISP_UNIT, INFO, COMM, WIN, IERROR
If the Fortran compiler provides TYPE(C_PTR), then overloaded by:
                                                                                 42
  INTERFACE MPI_WIN_ALLOCATE_SHARED
                                                                                 43
    SUBROUTINE MPI_WIN_ALLOCATE_SHARED(SIZE, DISP_UNIT, INFO, COMM, &
                                                                                  44
          BASEPTR, WIN, IERROR)
                                                                                  45
      IMPORT :: MPI_ADDRESS_KIND
                                                                                  46
      INTEGER :: DISP_UNIT, INFO, COMM, WIN, IERROR
      INTEGER(KIND=MPI_ADDRESS_KIND) :: SIZE, BASEPTR
```

```
1
         END SUBROUTINE
         SUBROUTINE MPI_WIN_ALLOCATE_SHARED_CPTR(SIZE, DISP_UNIT, INFO, COMM, &
               BASEPTR, WIN, IERROR)
           USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
           IMPORT :: MPI_ADDRESS_KIND
           INTEGER :: DISP_UNIT, INFO, COMM, WIN, IERROR
           INTEGER(KIND=MPI_ADDRESS_KIND) :: SIZE
           TYPE(C_PTR) :: BASEPTR
         END SUBROUTINE
10
       END INTERFACE
11
    MPI_WIN_ATTACH(WIN, BASE, SIZE, IERROR)
12
         INTEGER WIN, IERROR
13
         <type> BASE(*)
14
         INTEGER(KIND=MPI_ADDRESS_KIND) SIZE
15
16
     MPI_WIN_COMPLETE(WIN, IERROR)
17
         INTEGER WIN, IERROR
18
     MPI_WIN_CREATE(BASE, SIZE, DISP_UNIT, INFO, COMM, WIN, IERROR)
19
         <type> BASE(*)
20
         INTEGER(KIND=MPI_ADDRESS_KIND) SIZE
21
         INTEGER DISP_UNIT, INFO, COMM, WIN, IERROR
22
23
     MPI_WIN_CREATE_DYNAMIC(INFO, COMM, WIN, IERROR)
24
         INTEGER INFO, COMM, WIN, IERROR
     MPI_WIN_DETACH(WIN, BASE, IERROR)
26
         INTEGER WIN, IERROR
27
         <type> BASE(*)
28
29
     MPI_WIN_FENCE(ASSERT, WIN, IERROR)
30
         INTEGER ASSERT, WIN, IERROR
31
     MPI_WIN_FLUSH(RANK, WIN, IERROR)
32
         INTEGER RANK, WIN, IERROR
33
34
     MPI_WIN_FLUSH_ALL(WIN, IERROR)
35
         INTEGER WIN, IERROR
36
37
     MPI_WIN_FLUSH_LOCAL(RANK, WIN, IERROR)
         INTEGER RANK, WIN, IERROR
38
39
     MPI_WIN_FLUSH_LOCAL_ALL(WIN, IERROR)
40
         INTEGER WIN, IERROR
41
42
     MPI_WIN_FREE(WIN, IERROR)
         INTEGER WIN, IERROR
43
44
     MPI_WIN_GET_GROUP(WIN, GROUP, IERROR)
45
         INTEGER WIN, GROUP, IERROR
^{46}
47
     MPI_WIN_GET_INFO(WIN, INFO_USED, IERROR)
         INTEGER WIN, INFO_USED, IERROR
```

```
MPI_WIN_LOCK(LOCK_TYPE, RANK, ASSERT, WIN, IERROR)
    INTEGER LOCK_TYPE, RANK, ASSERT, WIN, IERROR
MPI_WIN_LOCK_ALL(ASSERT, WIN, IERROR)
    INTEGER ASSERT, WIN, IERROR
MPI_WIN_POST(GROUP, ASSERT, WIN, IERROR)
    INTEGER GROUP, ASSERT, WIN, IERROR
MPI_WIN_SET_INFO(WIN, INFO, IERROR)
    INTEGER WIN, INFO, IERROR
MPI_WIN_SHARED_QUERY(WIN, RANK, SIZE, DISP_UNIT, BASEPTR, IERROR)
    INTEGER WIN, RANK, DISP_UNIT, IERROR
                                                                                  12
                                                                                  13
    INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
                                                                                  14
If the Fortran compiler provides TYPE(C_PTR), then overloaded by:
                                                                                  15
  INTERFACE MPI WIN SHARED QUERY
                                                                                  16
    SUBROUTINE MPI_WIN_SHARED_QUERY(WIN, RANK, SIZE, DISP_UNIT, &
          BASEPTR, IERROR)
                                                                                  18
      IMPORT :: MPI_ADDRESS_KIND
                                                                                  19
      INTEGER :: WIN, RANK, DISP_UNIT, IERROR
                                                                                  20
      INTEGER(KIND=MPI_ADDRESS_KIND) :: SIZE, BASEPTR
                                                                                  21
    END SUBROUTINE
                                                                                  22
    SUBROUTINE MPI_WIN_SHARED_QUERY_CPTR(WIN, RANK, SIZE, DISP_UNIT, &
                                                                                  23
          BASEPTR, IERROR)
                                                                                  24
      USE, INTRINSIC :: ISO_C_BINDING, ONLY : C_PTR
      IMPORT :: MPI_ADDRESS_KIND
                                                                                  26
      INTEGER :: WIN, RANK, DISP_UNIT, IERROR
                                                                                  27
      INTEGER(KIND=MPI_ADDRESS_KIND) ::
                                          SIZE
                                                                                  28
      TYPE(C_PTR) :: BASEPTR
                                                                                  29
    END SUBROUTINE
                                                                                  30
  END INTERFACE
MPI_WIN_START(GROUP, ASSERT, WIN, IERROR)
                                                                                  33
    INTEGER GROUP, ASSERT, WIN, IERROR
                                                                                  34
MPI_WIN_SYNC(WIN, IERROR)
                                                                                  35
    INTEGER WIN, IERROR
                                                                                  36
                                                                                  37
MPI_WIN_TEST(WIN, FLAG, IERROR)
    INTEGER WIN, IERROR
    LOGICAL FLAG
MPI_WIN_UNLOCK(RANK, WIN, IERROR)
    INTEGER RANK, WIN, IERROR
                                                                                  42
                                                                                  43
MPI_WIN_UNLOCK_ALL(WIN, IERROR)
                                                                                  44
    INTEGER WIN, IERROR
                                                                                  45
MPI_WIN_WAIT(WIN, IERROR)
                                                                                  46
    INTEGER WIN, IERROR
```

```
1
     A.5.11 External Interfaces Fortran Bindings
2
     MPI_GREQUEST_COMPLETE(REQUEST, IERROR)
3
         INTEGER REQUEST, IERROR
4
5
     MPI_GREQUEST_START(QUERY_FN, FREE_FN, CANCEL_FN, EXTRA_STATE, REQUEST,
6
                   IERROR)
7
         EXTERNAL QUERY_FN, FREE_FN, CANCEL_FN
         INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
         INTEGER REQUEST, IERROR
10
     MPI_STATUS_SET_CANCELLED(STATUS, FLAG, IERROR)
11
         INTEGER STATUS(MPI_STATUS_SIZE), IERROR
12
         LOGICAL FLAG
13
14
     MPI_STATUS_SET_ELEMENTS(STATUS, DATATYPE, COUNT, IERROR)
15
         INTEGER STATUS(MPI_STATUS_SIZE), DATATYPE, COUNT, IERROR
16
     MPI_STATUS_SET_ELEMENTS_X(STATUS, DATATYPE, COUNT, IERROR)
17
         INTEGER STATUS (MPI_STATUS_SIZE), DATATYPE, IERROR
18
         INTEGER(KIND=MPI_COUNT_KIND) COUNT
19
20
21
     A.5.12 I/O Fortran Bindings
22
     MPI_CONVERSION_FN_NULL(USERBUF, DATATYPE, COUNT, FILEBUF, POSITION,
23
                   EXTRA_STATE, IERROR)
24
         <TYPE> USERBUF(*), FILEBUF(*)
         INTEGER DATATYPE, COUNT, IERROR
26
         INTEGER(KIND=MPI_OFFSET_KIND) POSITION
27
         INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
28
29
     MPI_FILE_CLOSE(FH, IERROR)
30
         INTEGER FH, IERROR
31
     MPI_FILE_DELETE(FILENAME, INFO, IERROR)
32
33
         CHARACTER*(*) FILENAME
34
         INTEGER INFO, IERROR
35
     MPI_FILE_GET_AMODE(FH, AMODE, IERROR)
36
         INTEGER FH, AMODE, IERROR
37
     MPI_FILE_GET_ATOMICITY(FH, FLAG, IERROR)
         INTEGER FH, IERROR
         LOGICAL FLAG
41
     MPI_FILE_GET_BYTE_OFFSET(FH, OFFSET, DISP, IERROR)
42
         INTEGER FH, IERROR
43
         INTEGER(KIND=MPI_OFFSET_KIND) OFFSET, DISP
44
45
     MPI_FILE_GET_GROUP(FH, GROUP, IERROR)
46
         INTEGER FH, GROUP, IERROR
47
     MPI_FILE_GET_INFO(FH, INFO_USED, IERROR)
```

INTEGER FH, INFO_USED, IERROR
MPI_FILE_GET_POSITION(FH, OFFSET, IERROR) INTEGER FH, IERROR INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
MPI_FILE_GET_POSITION_SHARED(FH, OFFSET, IERROR) INTEGER FH, IERROR INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
MPI_FILE_GET_SIZE(FH, SIZE, IERROR)  INTEGER FH, IERROR  INTEGER(KIND=MPI_OFFSET_KIND) SIZE
MPI_FILE_GET_TYPE_EXTENT(FH, DATATYPE, EXTENT, IERROR)  INTEGER FH, DATATYPE, IERROR  INTEGER(KIND=MPI_ADDRESS_KIND) EXTENT
MPI_FILE_GET_VIEW(FH, DISP, ETYPE, FILETYPE, DATAREP, IERROR)  INTEGER FH, ETYPE, FILETYPE, IERROR  INTEGER(KIND=MPI_OFFSET_KIND) DISP  CHARACTER*(*) DATAREP
MPI_FILE_IREAD(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)  INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR <type> BUF(*)</type>
MPI_FILE_IREAD_ALL(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)  INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR <type> BUF(*)</type>
MPI_FILE_IREAD_AT(FH, OFFSET, BUF, COUNT, DATATYPE, REQUEST, IERROR)  INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR  INTEGER(KIND=MPI_OFFSET_KIND) OFFSET <type> BUF(*)</type>
MPI_FILE_IREAD_AT_ALL(FH, OFFSET, BUF, COUNT, DATATYPE, REQUEST, IERROR)  INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR  INTEGER(KIND=MPI_OFFSET_KIND) OFFSET <type> BUF(*)</type>
MPI_FILE_IREAD_SHARED(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)  INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR <type> BUF(*)</type>
MPI_FILE_IWRITE(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)  INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR <type> BUF(*)</type>
MPI_FILE_IWRITE_ALL(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)  INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR <type> BUF(*)</type>
MPI_FILE_IWRITE_AT(FH, OFFSET, BUF, COUNT, DATATYPE, REQUEST, IERROR)

```
1
         INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
2
         INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
         <type> BUF(*)
     MPI_FILE_IWRITE_AT_ALL(FH, OFFSET, BUF, COUNT, DATATYPE, REQUEST, IERROR)
5
         INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
6
         INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
         <type> BUF(*)
8
9
     MPI_FILE_IWRITE_SHARED(FH, BUF, COUNT, DATATYPE, REQUEST, IERROR)
10
         INTEGER FH, COUNT, DATATYPE, REQUEST, IERROR
11
         <type> BUF(*)
12
     MPI_FILE_OPEN(COMM, FILENAME, AMODE, INFO, FH, IERROR)
13
         INTEGER COMM, AMODE, INFO, FH, IERROR
14
         CHARACTER*(*) FILENAME
15
16
     MPI_FILE_PREALLOCATE(FH, SIZE, IERROR)
17
         INTEGER FH, IERROR
18
         INTEGER(KIND=MPI_OFFSET_KIND) SIZE
19
    MPI_FILE_READ(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
20
         INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
21
         <type> BUF(*)
22
23
     MPI_FILE_READ_ALL(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
24
         INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
         <type> BUF(*)
26
     MPI_FILE_READ_ALL_BEGIN(FH, BUF, COUNT, DATATYPE, IERROR)
27
         INTEGER FH, COUNT, DATATYPE, IERROR
28
         <type> BUF(*)
29
30
     MPI_FILE_READ_ALL_END(FH, BUF, STATUS, IERROR)
31
         INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR
32
         <type> BUF(*)
33
     MPI_FILE_READ_AT(FH, OFFSET, BUF, COUNT, DATATYPE, STATUS, IERROR)
34
         INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
35
         INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
36
         <type> BUF(*)
37
     MPI_FILE_READ_AT_ALL(FH, OFFSET, BUF, COUNT, DATATYPE, STATUS, IERROR)
39
         INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
         INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
41
         <type> BUF(*)
42
     MPI_FILE_READ_AT_ALL_BEGIN(FH, OFFSET, BUF, COUNT, DATATYPE, IERROR)
43
         INTEGER FH, COUNT, DATATYPE, IERROR
44
         INTEGER(KIND=MPI_OFFSET_KIND) OFFSET
45
         <type> BUF(*)
46
```

MPI\_FILE\_READ\_AT\_ALL\_END(FH, BUF, STATUS, IERROR)

<pre>INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR <type> BUF(*)</type></pre>	1 2
MPI_FILE_READ_ORDERED(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)	3
INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR	4 5
<type> BUF(*)</type>	6
MPI_FILE_READ_ORDERED_BEGIN(FH, BUF, COUNT, DATATYPE, IERROR)	7
INTEGER FH, COUNT, DATATYPE, IERROR <type> BUF(*)</type>	9
MPI_FILE_READ_ORDERED_END(FH, BUF, STATUS, IERROR)	10 11
INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR	12
<type> BUF(*)</type>	13
MPI_FILE_READ_SHARED(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)	14
INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR	15 16
<type> BUF(*)</type>	17
MPI_FILE_SEEK(FH, OFFSET, WHENCE, IERROR)	18
INTEGER FH, WHENCE, IERROR	19
INTEGER(KIND=MPI_OFFSET_KIND) OFFSET	20
MPI_FILE_SEEK_SHARED(FH, OFFSET, WHENCE, IERROR)	21
INTEGER FH, WHENCE, IERROR	22 23
INTEGER(KIND=MPI_OFFSET_KIND) OFFSET	23
MPI_FILE_SET_ATOMICITY(FH, FLAG, IERROR)	25
INTEGER FH, IERROR	26
LOGICAL FLAG	27
MPI_FILE_SET_INFO(FH, INFO, IERROR)	28
INTEGER FH, INFO, IERROR	29
MPI_FILE_SET_SIZE(FH, SIZE, IERROR)	30 31
INTEGER FH, IERROR	32
INTEGER(KIND=MPI_OFFSET_KIND) SIZE	33
MPI_FILE_SET_VIEW(FH, DISP, ETYPE, FILETYPE, DATAREP, INFO, IERROR)	34
INTEGER FH, ETYPE, FILETYPE, INFO, IERROR	35
INTEGER(KIND=MPI_OFFSET_KIND) DISP	36
CHARACTER*(*) DATAREP	37 38
MPI_FILE_SYNC(FH, IERROR)	39
INTEGER FH, IERROR	40
MDI ETIE UDITE/EU DHE COUNT DATATVDE CTATHC TEDDOD)	41
MPI_FILE_WRITE(FH, BUF, COUNT, DATATYPE, STATUS, IERROR) INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR	42
<pre><type> BUF(*)</type></pre>	43
<b>v-</b>	44
MPI_FILE_WRITE_ALL(FH, BUF, COUNT, DATATYPE, STATUS, IERROR) INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR	45 46
THITCHE III, COOMI, DAIRIII D, DIRIUD(HI I_DIRIUD_DIZE/, IEIMUN	10

<type> BUF(\*)

1 2 3	<pre>MPI_FILE_WRITE_ALL_BEGIN(FH, BUF, COUNT, DATATYPE, IERROR)    INTEGER FH, COUNT, DATATYPE, IERROR    <type> BUF(*)</type></pre>
4 5 6 7	<pre>MPI_FILE_WRITE_ALL_END(FH, BUF, STATUS, IERROR)     INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR     <type> BUF(*)</type></pre>
8 9 10 11	<pre>MPI_FILE_WRITE_AT(FH, OFFSET, BUF, COUNT, DATATYPE, STATUS, IERROR)     INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR     INTEGER(KIND=MPI_OFFSET_KIND) OFFSET     <type> BUF(*)</type></pre>
12 13 14 15 16	<pre>MPI_FILE_WRITE_AT_ALL(FH, OFFSET, BUF, COUNT, DATATYPE, STATUS, IERROR)     INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR     INTEGER(KIND=MPI_OFFSET_KIND) OFFSET     <type> BUF(*)</type></pre>
17 18 19 20	<pre>MPI_FILE_WRITE_AT_ALL_BEGIN(FH, OFFSET, BUF, COUNT, DATATYPE, IERROR)     INTEGER FH, COUNT, DATATYPE, IERROR     INTEGER(KIND=MPI_OFFSET_KIND) OFFSET     <type> BUF(*)</type></pre>
21 22 23 24	<pre>MPI_FILE_WRITE_AT_ALL_END(FH, BUF, STATUS, IERROR)    INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR    <type> BUF(*)</type></pre>
25 26 27 28	<pre>MPI_FILE_WRITE_ORDERED(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)     INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR     <type> BUF(*)</type></pre>
29 30 31	<pre>MPI_FILE_WRITE_ORDERED_BEGIN(FH, BUF, COUNT, DATATYPE, IERROR)     INTEGER FH, COUNT, DATATYPE, IERROR     <type> BUF(*)</type></pre>
32 33 34 35	<pre>MPI_FILE_WRITE_ORDERED_END(FH, BUF, STATUS, IERROR)     INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR     <type> BUF(*)</type></pre>
36 37 38	<pre>MPI_FILE_WRITE_SHARED(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)     INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR     <type> BUF(*)</type></pre>
39 40 41 42 43 44	MPI_REGISTER_DATAREP(DATAREP, READ_CONVERSION_FN, WRITE_CONVERSION_FN,  DTYPE_FILE_EXTENT_FN, EXTRA_STATE, IERROR)  CHARACTER*(*) DATAREP  EXTERNAL READ_CONVERSION_FN, WRITE_CONVERSION_FN, DTYPE_FILE_EXTENT_FN  INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE  INTEGER IERROR

#-error!

#-update2


Done

PR431

#### A.5.13 Language Bindings Fortran Bindings The following procedure is not available with mpif.h: These routine were lost due to MPI\_STATUS\_F082F(F08\_STATUS, F\_STATUS, IERROR) a bug in MAKE-APPLANG 4 TYPE(MPI\_Status) :: F08\_STATUS 5 INTEGER :: F\_STATUS(MPI\_STATUS\_SIZE), IERROR 6 The following procedure is not available with mpif.h: MPI\_STATUS\_F2F08(F\_STATUS, F08\_STATUS, IERROR) INTEGER :: F\_STATUS(MPI\_STATUS\_SIZE), IERROR TYPE(MPI\_Status) :: F08\_STATUS MPI\_F\_SYNC\_REG(BUF) 12 <type> BUF(\*) 13 14 MPI\_TYPE\_CREATE\_F90\_COMPLEX(P, R, NEWTYPE, IERROR) 15 INTEGER P, R, NEWTYPE, IERROR 16 MPI\_TYPE\_CREATE\_F90\_INTEGER(R, NEWTYPE, IERROR) INTEGER R, NEWTYPE, IERROR 18 19 MPI\_TYPE\_CREATE\_F90\_REAL(P, R, NEWTYPE, IERROR) 20 INTEGER P, R, NEWTYPE, IERROR 21 MPI\_TYPE\_MATCH\_SIZE(TYPECLASS, SIZE, DATATYPE, IERROR) 22 INTEGER TYPECLASS, SIZE, DATATYPE, IERROR 23 A.5.14 Tools / Profiling Interface Fortran Bindings 26 MPI\_PCONTROL(LEVEL) 27 INTEGER LEVEL 28 30 A.5.15 Deprecated Fortran Bindings MPI\_ATTR\_DELETE(COMM, KEYVAL, IERROR) 33 INTEGER COMM, KEYVAL, IERROR 34 MPI\_ATTR\_GET(COMM, KEYVAL, ATTRIBUTE\_VAL, FLAG, IERROR) 35 INTEGER COMM, KEYVAL, ATTRIBUTE\_VAL, IERROR 36 LOGICAL FLAG 37 MPI\_ATTR\_PUT(COMM, KEYVAL, ATTRIBUTE\_VAL, IERROR) INTEGER COMM, KEYVAL, ATTRIBUTE\_VAL, IERROR MPI\_DUP\_FN(OLDCOMM, KEYVAL, EXTRA\_STATE, ATTRIBUTE\_VAL\_IN, ATTRIBUTE\_VAL\_OUT, FLAG, IERR) 42 INTEGER OLDCOMM, KEYVAL, EXTRA\_STATE, ATTRIBUTE\_VAL\_IN, 43 ATTRIBUTE\_VAL\_OUT, IERR 44 LOGICAL FLAG 45 46 MPI\_INFO\_GET(INFO, KEY, VALUELEN, VALUE, FLAG, IERROR)

INTEGER INFO, VALUELEN, IERROR

1 2	CHARACTER*(*) KEY, VALUE LOGICAL FLAG
3 4 5 6 7	MPI_INFO_GET_VALUELEN(INFO, KEY, VALUELEN, FLAG, IERROR) INTEGER INFO, VALUELEN, IERROR CHARACTER*(*) KEY LOGICAL FLAG
8 9 10 11	MPI_KEYVAL_CREATE(COPY_FN, DELETE_FN, KEYVAL, EXTRA_STATE, IERROR) EXTERNAL COPY_FN, DELETE_FN INTEGER KEYVAL, EXTRA_STATE, IERROR
12 13	MPI_KEYVAL_FREE(KEYVAL, IERROR) INTEGER KEYVAL, IERROR
14 15 16 17 18	MPI_NULL_COPY_FN(OLDCOMM, KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,
20 21	MPI_NULL_DELETE_FN(COMM, KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE, IERROR) INTEGER COMM, KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE, IERROR
22 23 24 25 26 27 28	MPI_SIZEOF(X, SIZE, IERROR) <type> X INTEGER SIZE, IERROR</type>
29 30 31 32	
33 34 35	
36 37 38	
39 40 41	
42 43 44	
45	



An execption for the specific Fortran names in the case of TS 29113 interface specifications in mpif.h for

MPI\_NEIGHBOR\_ALLTOALLW\_INIT, MPI\_NEIGHBOR\_ALLTOALLV\_INIT, and MPI\_NEIGHBOR\_ALLGATHERV\_INIT.

Done #-error lin #-update2 PR434

1. Section 19.1.5 on page 786.

Done in

PR434

Move

PSET, MPI COMM CREATE FROM GROUP, MPI INTERCOMM CREATE FROM GROUPS, and new conversion functions are MPI SESSION {C2F | F2C}. New declarations are MPI Session in C and TYPE(MPI Session) together with the related overloaded operators .EQ., .NE., == and /= in the Fortran mpi\_f08 and mpi modules, and the callback function prototype MPI\_Session\_errhandler\_function. New constants are MPI\_SESSION\_NULL, MPI\_ERR\_SESSION, MPI\_MAX\_PSET\_NAME\_LEN, MPI\_MAX\_STRINGTAG\_LEN, MPI\_T\_BIND\_MPI\_SESSION and the predefined info key "mpi\_size". 4. Section 7.4.2 on page 321. Done MPI\_COMM\_TYPE\_HW\_UNGUIDED was added as a new possible value for the split\_type parameter of the MPI\_COMM\_SPLIT\_TYPE function. PR434 with the MPI\_T\_{SOURCE|EVENT} {...} and MPI\_T\_CATEGORY\_{GET | GET\_NUM}\_EVENTS routines 5. Section 15.3.8. on page 745 #-update1 A callback-driven event interface was added to the MPI tool information interface. #-update8 Done in 6. Section 7.4.2 on page 321. PR461 MPI\_COMM\_TYPE\_HW\_GUIDED was added as a new possible value for the split\_type parameter of the MPI\_COMM\_SPLIT\_TYPE function, as well as a new info key "mpi\_hw\_resource\_type". A specific value associated with this new info key is also Done defined: "mpi\_shared\_memory". There seems to be absolutely in #-update9 PR461 no change for Sessions!!!! #-error!!! Chapter 11, Sections 28, 3.2.3, 7.2.4, 7.3.2, 7.4.2, 7.6.2, 8.4, 8.5.1, 8.5.3, 8.5.4, 9.1.1, 9.1.2, 9.3, 9.3.4, 9.5, 11.6, 14.2.1, 14.2.7, 14.7, 15.3.4, 19.3.4, 19.3.6, and Annex A on #-103 Done pages 479, 24, 33, 309, 312, 321, 352, 385, 386, 388, 390, 443, 445, 450, 458, 462, 508, 15 16 633, 639, 706, 722, 829, 834, and 845 The Sessions Model was added to the standard. #-update8 Done 8. Throughout the entire document. in 19 New large count functions and callbacks were introduced to accommodate large buffers PR461 20 and/or datatypes. 21 Clarifications were added to the behavior of INOUT/OUT parameters that cannot 22 represent the value to be returned for the MPI\_BUFFER\_DETACH and 23 MPI\_FILE\_GET\_TYPE\_EXTENT functions  $^{24}$ 25 A new error class MPI\_ERR\_VALUE\_TOO\_LARGE was introduced. 26 New large count functions MPI {...} c in C and 9. Section 11.2.1 on page 480. 27 through function overloading in the A new function MPI\_INFO\_CREATE\_ENV was added. Fortran mpi\_f08 module, (with the exception of the 28 explicit Fortran procedures 29 MPI\_Op\_create\_c and MPI\_Register\_datarep\_c) and 30 **B.2** Changes from Version 3.1 to Version 3.2 the new large count callbacks 31 Done MPI\_User\_function\_c and 32 Fixes to Errata in Previous Versions of MPI B.2.1 MPI\_Datarep\_conversion\_function\_c were ... 33 1. Sections 8.6.1, 8.6.2 and 8.9 on pages 410, 415 and 437, and MPI-3.1 Sections 7.6.1, 34 7.6.2 and 7.8 on pages 315, 318 and 329. Move this item MPI\_NEIGHBOR\_ALLTOALL{|V|W} and MPI\_NEIGHBOR\_ALLGATHER{|V} for Car-Done before B.1.1: 1. tesian virtual grids were clarified. An advice to implementors was added to illustrate a correct implementation for the case of periods[d]==1 or .TRUE. and dims[d]==1 or 38 2 in a direction d. 39 40 Done Sort the combined list by 41 B.2.2 Changes in MPI-3.2 their first related page 42 1. Section 3.7 on page 58. 43 The introduction of MPI nonblocking communication was changed to describe cor-44 rectness and performance reasons for the use of nonblocking communication. 45 #-error!  $^{46}$ 2. Section 3.8.4 on page 88. Sections 3.8.4 and 16.3 on pages 88 and 772. Done 47Cancelling a send request by calling MPI\_CANCEL has been deprecated and may be removed in a future version of the MPI specification.

New MPI procedures are MPI SESSION {INIT | FINALIZE}, MPI SESSION GET {...}, MPI SESSION {...} ERRHANDLER, MPI GROUP FROM SESSION

Done

fixed to be INTENT(IN).

Missing change-log for 1-sided passiv synchronization is now also allowed for memory allocated with MPI\_Win\_allocate\_shared #-error! 12.5.3 Proposed new item: | Section~\ref{sec:1sided-lock} on page~\pageref{sec:1sided-lock}. \newline p595:9-13 NRMA/ passive target synchronization using locks can now be used portably in memory allocated via 1034 #-update2  $\mbox{\colored} \mbox{\colored} \mbox{\color$ Done 15. Sections 9.3 and 9.4 on pages 450 and 461. PR434 Clarified definition of errors to say that MPI should continue whenever possible and allow the user to recover from errors. #-error! 16. Section 10. on page 471. Done Added a new function MPI\_INFO\_GET\_STRING that takes a buffer length argument for returning info value strings. This function returns the required buffer length for the requested string and guarantees null termination for C strings where buffer size is greater than 0. Remark: 16.3 and 16.4 are now one section #-error 17. Section 10 on page 471 and Section 16.4 on page 772. ==> here 16.4 -> 16.3 Done MPI\_INFO\_GET and MPI\_INFO\_GET\_VALUELEN were deprecated. 12 13 18. Section 9.4 on page 461. 14 Added text to clarify what is implied about the status of MPI and user visible buffers 15 when MPI functions return MPI\_SUCCESS or other error codes. 16 19. Section 11.2.1 on page 480 Section 11.10.4 on page 536. #-error!!! 17 Clarified the semantic of failure and error reporting before (and during) MPI\_INIT #-update1 and after MPI\_FINALIZE. Done 20. Section 11.8.4 on page 521. Section 11.8.4 on page 521. #-error!!! Added the "mpi\_initial\_errhandler" reserved info key with the reserved values #-update1 22 "mpi\_errors\_abort", "mpi\_errors\_are\_fatal", and "mpi\_errors\_return" to the launch keys in Done 23 MPI\_COMM\_SPAWN, MPI\_COMM\_SPAWN\_MULTIPLE, and mpiexec 24 3.7 and 3.9 60 and 90 #-error!!! 25 21. Section 3.9 and 3.7 on pages 90 and 60. 26 Addition of MPI\_ISENDRECV and MPI\_ISENDRECV\_REPLACE. #-update1 Done 27 Missing Change-log entries or lines will be added if new constants, types, callbacks Changes from Version 3.0 to Version 3.1 #-update2 B.3 and functions are added to MPI-4.0 and not Done in listed above. PR461, except B.3.1 Fixes to Errata in Previous Versions of MPI for new constants in 1. Chapters 3-19, Annex A.4 on page 908, and Example 6.21 on page 234, and MPI-3.0 MPI\_T Chapters 3–17, Annex A.3 on page 707, and Example 5.21 on page 187. 34 Within the mpi\_f08 Fortran support method, BIND(C) was removed from all SUBROUTINE, FUNCTION, and ABSTRACT INTERFACE definitions. 35 36 2. Section 3.2.5 on page 36, and MPI-3.0 Section 3.2.5 on page 30. 37 The three public fields MPI\_SOURCE, MPI\_TAG, and MPI\_ERROR of the Fortran derived 38 type TYPE(MPI\_Status) must be of type INTEGER. 3. Section 3.8.2 on page 83, and MPI-3.0 Section 3.8.2 on page 67. The flag arguments of the Fortran interfaces of MPI\_IMPROBE were originally incorrectly defined as INTEGER (instead as LOGICAL). 44 4. Section 7.4.2 on page 321, and MPI-3.0 Section 6.4.2 on page 237. 45 In the mpi\_f08 binding of MPI\_COMM\_IDUP, the output argument newcomm is declared as ASYNCHRONOUS. 46 #-error! xx. Section 15.3.9 on page nnn. #-PR429 #-update10 In the definition of \mpifunc{MPI\\_T\\_CATEGORY\\_CHANGED}, the name of the \OUT/ argument was changed from \mpiarg{timestamp} to \mpiarg{update\ number}. The #-TODO type of the argument (\code{int \*}) is unchanged. PR429

- 5. Section 7.4.4 on page 339, and MPI-3.0 Section 6.4.4 on page 248. In the mpi\_f08 binding of MPI\_COMM\_SET\_INFO, the intent of comm is IN, and the optional output argument ierror was missing.
- 6. Section 8.6 on page 410, and MPI-3.0 Sections 7.6, on pages 314. In the case of virtual general graph topolgies (created with MPI\_CART\_CREATE), the use of neighborhood collective communication is restricted to adjacency matrices with the number of edges between any two processes is defined to be the same for both processes (i.e., with a symmetric adjacency matrix).
- Section 9.1.1 on page 443, and MPI-3.0 Section 8.1.1 on page 335.
   In the mpi\_f08 binding of MPI\_GET\_LIBRARY\_VERSION, a typo in the resultlen argument was corrected.
- Sections 9.2 (MPI\_ALLOC\_MEM and MPI\_ALLOC\_MEM\_CPTR),
   12.2.2 (MPI\_WIN\_ALLOCATE and MPI\_WIN\_ALLOCATE\_CPTR),
   12.2.3 (MPI\_WIN\_ALLOCATE\_SHARED and MPI\_WIN\_ALLOCATE\_SHARED\_CPTR),
   12.2.3 (MPI\_WIN\_SHARED\_QUERY and MPI\_WIN\_SHARED\_QUERY\_CPTR),
   15.2.1 and 15.2.7 (Profiling interface), and corresponding sections in MPI-3.0.
   The linker name concept was substituted by defining specific procedure names.
- 9. Section 12.2.1 on page 543, and MPI-3.0 Section 11.2.2 on page 407.

  The "same\_size" info key can be used with all window flavors, and requires that all processes in the process group of the communicator have provided this info key with the same value.
- 10. Section 12.3.4 on page 566, and MPI-3.0 Section 11.3.4 on page 424. Origin buffer arguments to MPI\_GET\_ACCUMULATE are ignored when the MPI\_NO\_OP operation is used.
- 11. Section 12.3.4 on page 566, and MPI-3.0 Section 11.3.4 on page 424. Clarify the roles of origin, result, and target communication parameters in MPI\_GET\_ACCUMULATE.
- 12. Section 15.3 on page 719, and MPI-3.0 Section 14.3 on page 561

  New paragraph and advice to users clarifying intent of variable names in the tools information interface.
- 13. Section 15.3.3 on page 721, and MPI-3.0 Section 14.3.3 on page 563. New paragraph clarifying variable name equivalence in the tools information interface.
- 14. Sections 15.3.6, 15.3.7, and 15.3.9 on pages 726, 733, and 761, and MPI-3.0 Sections 14.3.6, 14.3.7, and 14.3.8 on pages 567, 573, and 584. In functions MPI\_T\_CVAR\_GET\_INFO, MPI\_T\_PVAR\_GET\_INFO, and MPI\_T\_CATEGORY\_GET\_INFO, clarification of parameters that must be identical for equivalent control variable / performance variable / category names across connected processes.
- 15. Section 15.3.7 on page 733, and MPI-3.0 Section 14.3.7 on page 573. Clarify return code of MPI\_T\_PVAR\_{START,STOP,RESET} routines.

- 16. Section 15.3.7 on page 733, and MPI-3.0 Section 14.3.7 on page 579, line 7. Clarify the return code when bad handle is passed to an MPI\_T\_PVAR\_\* routine.
- 17. Section 19.1.4 on page 785, and MPI-3.0 Section 17.1.4 on page 603.

  The advice to implementors at the end of the section was rewritten and moved into the following section.
- 18. Section 19.1.5 on page 786, and MPI-3.0 Section 17.1.5 on page 605.

  The section was fully rewritten. The linker name concept was substituted by defining specific procedure names.
- 19. Section 19.1.6 on page 791, and MPI-3.0 Section 17.1.6 on page 611. The requirements on BIND(C) procedure interfaces were removed.
- 20. Annexes A.3, A.4, and A.5 on pages 870, 908, and 995, and MPI-3.0 Annexes A.2, A.3, and A.4 on pages 685, 707, and 756. The predefined callback MPI\_CONVERSION\_FN\_NULL was added to all three annexes.
- 21. Annex A.4.5 on page 948, and MPI-3.0 Annex A.3.4 on page 724. In the mpi\_f08 binding of MPI\_{COMM|TYPE|WIN}\_{DUP|NULL\_COPY|NULL\_DELETE}\_FN, all INTENT(...) information was removed.

# B.3.2 Changes in MPI-3.1

- 1. Sections 2.6.4 and 5.1.5 on pages 24 and 137.

  The use of the intrinsic operators "+" and "-" for absolute addresses is substituted by MPI\_AINT\_ADD and MPI\_AINT\_DIFF. In C, they can be implemented as macros.
- 2. Sections 9.1.1, 11.2.1, and 11.6 on pages 443, 480, and 508. The routines MPI\_INITIALIZED, MPI\_FINALIZED, MPI\_QUERY\_THREAD, MPI\_IS\_THREAD\_MAIN, MPI\_GET\_VERSION, and MPI\_GET\_LIBRARY\_VERSION are callable from threads without restriction (in the sense of MPI\_THREAD\_MULTIPLE), irrespective of the actual level of thread support provided, in the case where the implementation supports threads.
- 3. Section 12.2.1 on page 543.

  The "same\_disp\_unit" info key was added for use in RMA window creation routines.
- Sections 14.4.2 and 14.4.3 on pages 650 and 657.
   Added MPI\_FILE\_IREAD\_AT\_ALL, MPI\_FILE\_IWRITE\_AT\_ALL, MPI\_FILE\_IREAD\_ALL, and MPI\_FILE\_IWRITE\_ALL
- Sections 15.3.6, 15.3.7, and 15.3.9 on pages 726, 733, and 761.
   Clarified that NULL parameters can be provided in MPI\_T\_{CVAR|PVAR|CATEGORY}\_GET\_INFO routines.
- 6. Sections 15.3.6, 15.3.7, 15.3.9, and 15.3.10 on pages 726, 733, 761, and 766. New routines MPI\_T\_CVAR\_GET\_INDEX, MPI\_T\_PVAR\_GET\_INDEX, MPI\_T\_CATEGORY\_GET\_INDEX, were added to support retrieving indices of variables and categories. The error codes MPI\_T\_ERR\_INVALID and MPI\_T\_ERR\_INVALID\_NAME were added to indicate invalid uses of the interface.

# B.4 Changes from Version 2.2 to Version 3.0

### B.4.1 Fixes to Errata in Previous Versions of MPI

- 1. Sections 2.6.2 and 2.6.3 on pages 22 and 23, and MPI-2.2 Section 2.6.2 on page 17, lines 41–42, Section 2.6.3 on page 18, lines 15–16, and Section 2.6.4 on page 18, lines 40–41.
  - This is an MPI-2 erratum: The scope for the reserved prefix MPI\_ and the C++ namespace MPI is now any name as originally intended in MPI-1.
- 2. Sections 3.2.2, 6.9.2, 14.5.2 Table 14.2, and Annex A.1.1 on pages 31, 222, 689, and 845, and MPI-2.2 Sections 3.2.2, 5.9.2, 13.5.2 Table 13.2, 16.1.16 Table 16.1, and Annex A.1.1 on pages 27, 164, 433, 472 and 513
  This is an MPI-2.2 erratum: New named predefined datatypes
  MPI\_CXX\_BOOL, MPI\_CXX\_FLOAT\_COMPLEX, MPI\_CXX\_DOUBLE\_COMPLEX, and MPI\_CXX\_LONG\_DOUBLE\_COMPLEX were added in C and Fortran corresponding to the C++ types bool, std::complex<float>, std::complex<double>, and std::complexlong double>. These datatypes also correspond to the deprecated C++ predefined datatypes MPI::BOOL, MPI::COMPLEX, MPI::DOUBLE\_COMPLEX, and MPI::LONG\_DOUBLE\_COMPLEX, which were removed in MPI-3.0. The non-standard C++ types Complex<...> were substituted by the standard types std::complex<...>
- 3. Sections 6.9.2 on pages 222 and MPI-2.2 Section 5.9.2, page 165, line 47. This is an MPI-2.2 erratum: MPI\_C\_COMPLEX was added to the "Complex" reduction group.
- 4. Section 8.5.5 on page 397, and MPI-2.2, Section 7.5.5 on page 257, C++ interface on page 264, line 3.
  This is an MPI-2.2 erratum: The argument rank was removed and in/outdegree are now defined as int& indegree and int& outdegree in the C++ interface of MPI\_DIST\_GRAPH\_NEIGHBORS\_COUNT.
- 5. Section 14.5.2, Table 14.2 on page 689, and MPI-2.2, Section 13.5.3, Table 13.2 on page 433.
  - This was an MPI-2.2 erratum: The MPI\_C\_BOOL "external32" representation is corrected to a 1-byte size.
- MPI-2.2 Section 16.1.16 on page 471, line 45.
   This is an MPI-2.2 erratum: The constant MPI::\_LONG\_LONG should be MPI::LONG\_LONG.
- 7. Annex A.1.1 on page 845, Table "Optional datatypes (Fortran)," and MPI-2.2, Annex A.1.1, Table on page 517, lines 34, and 37–41.

  This is an MPI-2.2 erratum: The C++ datatype handles MPI::INTEGER16, MPI::REAL16, MPI::F\_COMPLEX4, MPI::F\_COMPLEX8, MPI::F\_COMPLEX16, MPI::F\_COMPLEX32 were added to the table.

#-...

# B.4.2 Changes in MPI-3.0

- 1. Section 2.6.1 on page 22, Section 17.2 on page 776 and all other chapters.

  The C++ bindings were removed from the standard. See errata in Section B.4.1 on page 1037 for the latest changes to the MPI C++ binding defined in MPI-2.2.

  This change may affect backward compatibility.
- 2. Section 2.6.1 on page 22, Section 16.1 on page 769 and Section 17.1 on page 775. The deprecated functions MPI\_TYPE\_HVECTOR, MPI\_TYPE\_HINDEXED, MPI\_TYPE\_STRUCT, MPI\_ADDRESS, MPI\_TYPE\_EXTENT, MPI\_TYPE\_LB, MPI\_TYPE\_UB, MPI\_ERRHANDLER\_CREATE (and its callback function prototype MPI\_Handler\_function), MPI\_ERRHANDLER\_SET, MPI\_ERRHANDLER\_GET, the deprecated special datatype handles MPI\_LB, MPI\_UB, and the constants MPI\_COMBINER\_HINDEXED\_INTEGER, MPI\_COMBINER\_HVECTOR\_INTEGER, MPI\_COMBINER\_STRUCT\_INTEGER were removed from the standard. This change may affect backward compatibility.
- 3. Section 2.3 on page 10. Clarified parameter usage for IN parameters. C bindings are now const-correct where backward compatibility is preserved.
- 4. Section 2.5.4 on page 18 and Section 8.5.4 on page 390.

  The recommended C implementation value for MPI\_UNWEIGHTED changed from NULL to non-NULL. An additional weight array constant (MPI\_WEIGHTS\_EMPTY) was introduced.
- 5. Section 2.5.4 on page 18 and Section 9.1.1 on page 443. Added the new routine MPI\_GET\_LIBRARY\_VERSION to query library specific versions, and the new constant MPI\_MAX\_LIBRARY\_VERSION\_STRING.
- 6. Sections 2.5.8, 3.2.2, 3.3, 6.9.2, on pages 20, 31, 33, 222, Sections 5.1, 5.1.7, 5.1.8, 5.1.11, 13.3 on pages 115, 142, 144, 148, 628, and Annex A.1.1 on page 845. New inquiry functions, MPI\_TYPE\_SIZE\_X, MPI\_TYPE\_GET\_EXTENT\_X, MPI\_TYPE\_GET\_TRUE\_EXTENT\_X, and MPI\_GET\_ELEMENTS\_X, return their results as an MPI\_Count value, which is a new type large enough to represent element counts in memory, file views, etc. A new function, MPI\_STATUS\_SET\_ELEMENTS\_X, modifies the opaque part of an MPI\_Status object so that a call to MPI\_GET\_ELEMENTS\_X returns the provided MPI\_Count value (in Fortran, INTEGER(KIND=MPI\_COUNT\_KIND)). The corresponding predefined datatype is MPI\_COUNT.
- 7. Chapter 3 on page 29 through Chapter 19 on page 779.
  In the C language bindings, the array-arguments' interfaces were modified to consistently use use [] instead of \*.
  Exceptions are MPI\_INIT, which continues to use char \*\*\*argv (correct because of
- subtle rules regarding the use of the & operator with char \*argv[]), and MPI\_INIT\_THREAD, which is changed to be consistent with MPI\_INIT.
- 8. Sections 3.2.5, 5.1.5, 5.1.11, 5.2 on pages 36, 137, 148, 170.

  The functions MPI\_GET\_COUNT and MPI\_GET\_ELEMENTS were defined to set the

count argument to MPI\_UNDEFINED when that argument would overflow. The functions MPI\_PACK\_SIZE and MPI\_TYPE\_SIZE were defined to set the size argument to MPI\_UNDEFINED when that argument would overflow. In all other MPI-2.2 routines, the type and semantics of the count arguments remain unchanged, i.e., int or INTEGER.

- Section 3.2.6 on page 39, and Section 3.8 on page 80.
   MPI\_STATUS\_IGNORE can be also used in MPI\_IPROBE, MPI\_PROBE, MPI\_IMPROBE, and MPI\_MPROBE.
- 10. Section 3.8 on page 80 and Section 3.10 on page 96.

  The use of MPI\_PROC\_NULL in probe operations was clarified. A special predefined message MPI\_MESSAGE\_NO\_PROC was defined for the use of matching probe (i.e., the new MPI\_MPROBE and MPI\_IMPROBE) with MPI\_PROC\_NULL.
- 11. Sections 3.8.2, 3.8.3, 19.3.4, A.1.1 on pages 83, 85, 829, 845.

  Like MPI\_PROBE and MPI\_IPROBE, the new MPI\_MPROBE and MPI\_IMPROBE operations allow incoming messages to be queried without actually receiving them, except that MPI\_MPROBE and MPI\_IMPROBE provide a mechanism to receive the specific message with the new routines MPI\_MRECV and MPI\_IMRECV regardless of other intervening probe or receive operations. The opaque object MPI\_Message, the null handle MPI\_MESSAGE\_NULL, and the conversion functions MPI\_Message\_c2f and MPI\_Message\_f2c were defined.
- 12. Section 5.1.2 on page 117 and Section 5.1.13 on page 153.

  The routine MPI\_TYPE\_CREATE\_HINDEXED\_BLOCK and constant MPI\_COMBINER\_HINDEXED\_BLOCK were added.
- 13. Chapter 6 on page 183 and Section 6.12 on page 246.

  Added nonblocking interfaces to all collective operations.
- 14. Sections 7.4.2, 7.4.4, 12.2.7, on pages 321, 339, 557.

  The new routines MPI\_COMM\_DUP\_WITH\_INFO, MPI\_COMM\_SET\_INFO, MPI\_COMM\_GET\_INFO, MPI\_WIN\_SET\_INFO, and MPI\_WIN\_GET\_INFO were added. The routine MPI\_COMM\_DUP must also duplicate info hints.
- 15. Section 7.4.2 on page 321. Added MPI\_COMM\_IDUP.
- 16. Section 7.4.2 on page 321.

Added the new communicator construction routine MPI\_COMM\_CREATE\_GROUP, which is invoked only by the processes in the group of the new communicator being constructed.

- 17. Section 7.4.2 on page 321.

  Added the MPI\_COMM\_SPLIT\_TYPE routine and the communicator split type constant MPI\_COMM\_TYPE\_SHARED.
- 18. Section 7.6.2 on page 352. In MPI-2.2, communication involved in an MPI\_INTERCOMM\_CREATE operation could interfere with point-to-point communication on the parent communicator with the same tag or MPI\_ANY\_TAG. This interference has been removed in MPI-3.0.

- 19. Section 7.8 on page 375.

  Section 6.8 on page 238. The constant MPI\_MAX\_OBJECT\_NAME also applies for type and window names.
- 20. Section 8.5.8 on page 408.

  MPI\_CART\_MAP can also be used for a zero-dimensional topologies.
- 21. Section 8.6 on page 410 and Section 8.7 on page 422.

  The following neighborhood collective communication routines were added to support sparse communication on virtual topology grids: MPI\_NEIGHBOR\_ALLGATHER, MPI\_NEIGHBOR\_ALLGATHERV, MPI\_NEIGHBOR\_ALLTOALL, MPI\_NEIGHBOR\_ALLTOALLV, MPI\_NEIGHBOR\_ALLTOALLW and the nonblocking variants MPI\_INEIGHBOR\_ALLGATHER, MPI\_INEIGHBOR\_ALLGATHERV, MPI\_INEIGHBOR\_ALLTOALL, MPI\_INEIGHBOR\_ALLTOALLV, and MPI\_INEIGHBOR\_ALLTOALLW. The displacement arguments in MPI\_NEIGHBOR\_ALLTOALLW and MPI\_INEIGHBOR\_ALLTOALLW were defined as address size integers. In MPI\_DIST\_GRAPH\_NEIGHBORS, an ordering rule was added for communicators created with MPI\_DIST\_GRAPH\_CREATE\_ADJACENT.
- 22. Section 11.2.1 on page 480 and Section 11.2.1 on page 483.

  The use of MPI\_INIT, MPI\_INIT\_THREAD and MPI\_FINALIZE was clarified. After MPI is initialized, the application can access information about the execution environment by querying the new predefined info object MPI\_INFO\_ENV.
- 23. Section 11.2.1 on page 480.

  Allow calls to MPI\_T routines before MPI\_INIT and after MPI\_FINALIZE.
- 24. Chapter 12 on page 541.

  Substantial revision of the entire One-sided chapter, with new routines for window creation, additional synchronization methods in passive target communication, new one-sided communication routines, a new memory model, and other changes.
- 25. Section 15.3 on page 719.A new MPI Tool Information Interface was added.The following changes are related to the Fortran language support.
- 26. Section 2.3 on page 10, and Sections 19.1.1, 19.1.2, 19.1.7 on pages 779, 780, and 795. The new mpi\_08 Fortran module was introduced.
- 27. Section 2.5.1 on page 16, and Sections 19.1.2, 19.1.3, 19.1.7 on pages 780, 783, and 795. Handles to opaque objects were defined as named types within the mpi\_08 Fortran module. The operators .EQ., .NE., ==, and /= were overloaded to allow the comparison of these handles. The handle types and the overloaded operators are also available through the mpi Fortran module.
- 28. Sections 2.5.4, 2.5.5 on pages 18, 19, Sections 19.1.1, 19.1.10, 19.1.11, 19.1.12, 19.1.13 on pages 779, 805, 806, 807, 810, and Sections 19.1.2, 19.1.3, 19.1.7 on pages 780, 783, 795.
  - Within the mpi\_08 Fortran module, choice buffers were defined as assumed-type and assumed-rank according to Fortran 2008 TS 29113 [46], and the compile-time constant MPI\_SUBARRAYS\_SUPPORTED was set to .TRUE.. With this, Fortran subscript triplets

can be used in nonblocking MPI operations; vector subscripts are not supported in nonblocking operations. If the compiler does not support this Fortran TS 29113 feature, the constant is set to .FALSE..

- 29. Section 2.6.2 on page 22, Section 19.1.2 on page 780, and Section 19.1.7 on page 795. The ierror dummy arguments are OPTIONAL within the mpi\_08 Fortran module.
- 30. Section 3.2.5 on page 36, Sections 19.1.2, 19.1.3, 19.1.7, on pages 780, 783, 795, and Section 19.3.5 on page 831.

  Within the mpi\_08 Fortran module, the status was defined as TYPE(MPI\_Status). Additionally, within both the mpi and the mpi\_f08 modules, the constants MPI\_STATUS\_SIZE, MPI\_SOURCE, MPI\_TAG, MPI\_ERROR, and TYPE(MPI\_Status) are defined. New conversion routines were added: MPI\_STATUS\_F2F08, MPI\_STATUS\_F082F, MPI\_Status\_c2f08, and MPI\_Status\_f082c, In mpi.h, the new type MPI\_F08\_status, and the external variables MPI\_F08\_STATUS\_IGNORE and MPI\_F08\_STATUSES\_IGNORE were added.
- 31. Section 3.6 on page 55.

  In Fortran with the mpi module or mpif.h, the type of the buffer\_addr argument of MPI\_BUFFER\_DETACH is incorrectly defined and the argument is therefore unused.
- 32. Section 5.1 on page 115, Section 5.1.6 on page 140, and Section 19.1.15 on page 811. The Fortran alignments of basic datatypes within Fortran derived types are implementation dependent; therefore it is recommended to use the BIND(C) attribute for derived types in MPI communication buffers. If an array of structures (in C/C++) or derived types (in Fortran) is to be used in MPI communication buffers, it is recommended that the user creates a portable datatype handle and additionally applies MPI\_TYPE\_CREATE\_RESIZED to this datatype handle.
- 33. Sections 5.1.10, 6.9.5, 6.9.7, 7.7.4, 7.8, 9.3.1, 9.3.2, 9.3.3, 16.1, 19.1.9 on pages 148, 229, 236, 369, 375, 453, 455, 457, 769, and 797. In some routines, the dummy argument names were changed because they were identical to the Fortran keywords TYPE and FUNCTION. The new dummy argument names must be used because the mpi and mpi\_08 modules guarantee keyword-based actual argument lists. The argument name type was changed in MPI\_TYPE\_DUP, the Fortran USER\_FUNCTION of MPI\_OP\_CREATE, MPI\_TYPE\_SET\_ATTR, MPI\_TYPE\_SET\_NAME, MPI\_TYPE\_GET\_ATTR, MPI\_TYPE\_DELETE\_ATTR, MPI\_TYPE\_SET\_NAME, MPI\_TYPE\_GET\_NAME, MPI\_TYPE\_MATCH\_SIZE, the callback prototype definition MPI\_Type\_delete\_attr\_function, and the predefined callback function MPI\_TYPE\_NULL\_DELETE\_FN; function was changed in MPI\_OP\_CREATE, MPI\_COMM\_CREATE\_ERRHANDLER, MPI\_WIN\_CREATE\_ERRHANDLER, MPI\_FILE\_CREATE\_ERRHANDLER, and MPI\_ERRHANDLER\_CREATE. For consistency reasons, INOUBUF was changed to INOUTBUF in MPI\_REDUCE\_LOCAL, and intracomm to newintracomm in MPI\_INTERCOMM\_MERGE.
- 34. Section 7.7.2 on page 360.

  It was clarified that in Fortran, the flag values returned by a comm\_copy\_attr\_fn callback, including MPI\_COMM\_NULL\_COPY\_FN and MPI\_COMM\_DUP\_FN, are .FALSE. and .TRUE.; see MPI\_COMM\_CREATE\_KEYVAL.

35. Section 9.2 on page 447.

With the mpi and mpi\_f08 Fortran modules, MPI\_ALLOC\_MEM now also supports TYPE(C\_PTR) C-pointers instead of only returning an address-sized integer that may be usable together with a non-standard Cray-pointer.

36. Section 19.1.15 on page 811, and Section 19.1.7 on page 795.

Fortran SEQUENCE and BIND(C) derived application types can now be used as buffers in MPI operations.

37. Section 19.1.16 on page 812 to Section 19.1.19 on page 821, Section 19.1.7 on page 795, and Section 19.1.8 on page 796.

The sections about Fortran optimization problems and their solutions were partially rewritten and new methods are added, e.g., the use of the ASYNCHRONOUS attribute. The constant MPI\_ASYNC\_PROTECTS\_NONBLOCKING tells whether the semantics of the ASYNCHRONOUS attribute is extended to protect nonblocking operations. The Fortran routine MPI\_F\_SYNC\_REG is added. MPI-3.0 compliance for an MPI library together with a Fortran compiler is defined in Section 19.1.7.

- 38. Section 19.1.2 on page 780.
  - Within the mpi\_08 Fortran module, dummy arguments are now declared with INTENT=IN, OUT, or INOUT as defined in the mpi\_08 interfaces.

39. Section 19.1.3 on page 783, and Section 19.1.7 on page 795.

The existing mpi Fortran module must implement compile-time argument checking.

40. Section 19.1.4 on page 785.

The use of the mpif.h Fortran include file is now strongly discouraged.

41. Section A.1.1, Table "Predefined functions" on page 853, Section A.1.3 on page 860, and Section A.4.5 on page 948.

Within the new mpi\_f08 module, all callback prototype definitions are now defined with explicit interfaces PROCEDURE(MPI\_...) that have the BIND(C) attribute; user-written callbacks must be modified if the mpi\_f08 module is used.

42. Section A.1.3 on page 860.

In some routines, the Fortran callback prototype names were changed from ...\_FN to ...\_FUNCTION to be consistent with the other language bindings.

#### B.5 Changes from Version 2.1 to Version 2.2

1. Section 2.5.4 on page 18.

It is now guaranteed that predefined named constant handles (as other constants) can be used in initialization expressions or assignments, i.e., also before the call to MPI\_INIT.

2. Section 2.6 on page 21, and Section 17.2 on page 776.

The C++ language bindings have been deprecated and may be removed in a future version of the MPI specification.

3. Section 3.2.2 on page 31.

MPI\_CHAR for printable characters is now defined for C type char (instead of signed

13

14

15

16

17 18

19

20

21 22

23

24

26

27 28

29

30

34

35

36

37

38

39

43

44

45

46 47

char). This change should not have any impact on applications nor on MPI libraries (except some comment lines), because printable characters could and can be stored in any of the C types char, signed char, and unsigned char, and MPI\_CHAR is not allowed for predefined reduction operations.

4. Section 3.2.2 on page 31.

MPI\_(U)INT{8,16,32,64}\_T, MPI\_AINT, MPI\_OFFSET, MPI\_C\_BOOL, MPI\_C\_COMPLEX, MPI\_C\_FLOAT\_COMPLEX, MPI\_C\_DOUBLE\_COMPLEX, and MPI\_C\_LONG\_DOUBLE\_COMPLEX are now valid predefined MPI datatypes.

5. Section 3.4 on page 46, Section 3.7.2 on page 60, Section 3.9 on page 90, and Section 6.1 on page 183.

The read access restriction on the send buffer for blocking, non blocking and collective API has been lifted. It is permitted to access for read the send buffer while the operation is in progress.

- 6. Section 3.7 on page 58.
  - The Advice to users for IBSEND and IRSEND was slightly changed.
- 7. Section 3.7.3 on page 67.

The advice to free an active request was removed in the Advice to users for MPI\_REQUEST\_FREE.

- 8. Section 3.7.6 on page 79.

  MPI\_REQUEST\_GET\_STATUS changed to permit inactive or null requests as input.
- Section 6.8 on page 213.
   "In place" option is added to MPI\_ALLTOALL, MPI\_ALLTOALLV, and MPI\_ALLTOALLW for intra-communicators.
- 10. Section 6.9.2 on page 222.

Predefined parameterized datatypes (e.g., returned by MPI\_TYPE\_CREATE\_F90\_REAL) and optional named predefined datatypes (e.g. MPI\_REAL8) have been added to the list of valid datatypes in reduction operations.

11. Section 6.9.2 on page 222.

MPI\_(U)INT{8,16,32,64}\_T are all considered C integer types for the purposes of the predefined reduction operators. MPI\_AINT and MPI\_OFFSET are considered Fortran integer types. MPI\_C\_BOOL is considered a Logical type.

MPI\_C\_COMPLEX, MPI\_C\_FLOAT\_COMPLEX, MPI\_C\_DOUBLE\_COMPLEX, and MPI\_C\_LONG\_DOUBLE\_COMPLEX are considered Complex types.

12. Section 6.9.7 on page 236.

The local routines  $\mathsf{MPI\_REDUCE\_LOCAL}$  and  $\mathsf{MPI\_OP\_COMMUTATIVE}$  have been added.

- 13. Section 6.10.1 on page 238.
  - The collective function MPI\_REDUCE\_SCATTER\_BLOCK is added to the MPI standard.
- 14. Section 6.11.2 on page 243.

  Added in place argument to MPI\_EXSCAN.

 16. Section 7.4.2 on page 321.

MPI\_COMM\_CREATE is extended to allow several disjoint subgroups as input if comm is an intra-communicator. If comm is an inter-communicator it was clarified that all processes in the same local group of comm must specify the same value for group.

17. Section 8.5.4 on page 390.

New functions for a scalable distributed graph topology interface has been added. In this section, the functions  $MPI_DIST_GRAPH_CREATE_ADJACENT$  and  $MPI_DIST_GRAPH_CREATE$ , the constants  $MPI_UNWEIGHTED$ , and the derived C++ class Distgraphcomm were added.

18. Section 8.5.5 on page 397.

For the scalable distributed graph topology interface, the functions MPI\_DIST\_GRAPH\_NEIGHBORS\_COUNT and MPI\_DIST\_GRAPH\_NEIGHBORS and the constant MPI\_DIST\_GRAPH were added.

19. Section 8.5.5 on page 397.

Remove ambiguity regarding duplicated neighbors with MPI\_GRAPH\_NEIGHBORS and MPI\_GRAPH\_NEIGHBORS\_COUNT.

20. Section 9.1.1 on page 443.

The subversion number changed from 1 to 2.

21. Section 9.3 on page 450, Section 16.2 on page 772, and Annex A.1.3 on page 860. Changed function pointer typedef names MPI\_{Comm,File,Win}\_errhandler\_fn to MPI\_{Comm,File,Win}\_errhandler\_function. Deprecated old "\_fn" names.

22. Section 11.2.4 on page 490.

Attribute deletion callbacks on MPI\_COMM\_SELF are now called in LIFO order. Implementors must now also register all implementation-internal attribute deletion callbacks on MPI\_COMM\_SELF before returning from MPI\_INIT\_MPI\_INIT\_THREAD.

23. Section 12.3.4 on page 566.

The restriction added in MPI 2.1 that the operation MPI\_REPLACE in MPI\_ACCUMULATE can be used only with predefined datatypes has been removed. MPI\_REPLACE can now be used even with derived datatypes, as it was in MPI 2.0. Also, a clarification has been made that MPI\_REPLACE can be used only in MPI\_ACCUMULATE, not in collective operations that do reductions, such as MPI\_REDUCE and others.

24. Section 13.2 on page 621.

Add "\*" to the query\_fn, free\_fn, and cancel\_fn arguments to the C++ binding for MPI::Grequest::Start() for consistency with the rest of MPI functions that take function pointer arguments.



- 25. Section 14.5.2 on page 688, and Table 14.2 on page 689.

  MPI\_(U)INT{8,16,32,64}\_T, MPI\_AINT, MPI\_OFFSET, MPI\_C\_COMPLEX,

  MPI\_C\_FLOAT\_COMPLEX, MPI\_C\_DOUBLE\_COMPLEX,

  MPI\_C\_LONG\_DOUBLE\_COMPLEX, and MPI\_C\_BOOL are added as predefined datatypes in the "external32" representation.
- 26. Section 19.3.7 on page 837.

The description was modified that it only describes how an MPI implementation behaves, but not how MPI stores attributes internally. The erroneous MPI-2.1 Example 16.17 was replaced with three new examples 19.13, 19.14, and 19.15 on pages 837–839 explicitly detailing cross-language attribute behavior. Implementations that matched the behavior of the old example will need to be updated.

- 27. Annex A.1.1 on page 845.

  Removed type MPI::Fint (compare MPI\_Fint in Section A.1.2 on page 859).
- 28. Annex A.1.1 on page 845. Table Named Predefined Datatypes.

  Added MPI\_(U)INT{8,16,32,64}\_T, MPI\_AINT, MPI\_OFFSET, MPI\_C\_BOOL,

  MPI\_C\_FLOAT\_COMPLEX, MPI\_C\_COMPLEX, MPI\_C\_DOUBLE\_COMPLEX, and

  MPI\_C\_LONG\_DOUBLE\_COMPLEX are added as predefined datatypes.

#### B.6 Changes from Version 2.0 to Version 2.1

- 1. Section 3.2.2 on page 31, and Annex A.1 on page 845. In addition, the MPI\_LONG\_LONG should be added as an optional type; it is a synonym for MPI\_LONG\_LONG\_INT.
- Section 3.2.2 on page 31, and Annex A.1 on page 845.
   MPI\_LONG\_LONG\_INT, MPI\_LONG\_LONG (as synonym),
   MPI\_UNSIGNED\_LONG\_LONG, MPI\_SIGNED\_CHAR, and MPI\_WCHAR are moved from optional to official and they are therefore defined for all three language bindings.
- 3. Section 3.2.5 on page 36.

  MPI\_GET\_COUNT with zero-length datatypes: The value returned as the count argument of MPI\_GET\_COUNT for a datatype of length zero where zero bytes have been transferred is zero. If the number of bytes transferred is greater than zero, MPI\_UNDEFINED is returned.
- 4. Section **5.1** on page **115**.

General rule about derived datatypes: Most datatype constructors have replication count or block length arguments. Allowed values are non-negative integers. If the value is zero, no elements are generated in the type map and there is no effect on datatype bounds or extent.

- Section 5.3 on page 178.
   MPI\_BYTE should be used to send and receive data that is packed using MPI\_PACK\_EXTERNAL.
- 6. Section 6.9.6 on page 234.

  If comm is an inter-communicator in MPI\_ALLREDUCE, then both groups should

provide count and datatype arguments that specify the same type signature (i.e., it is not necessary that both groups provide the same count value).

7. Section 7.3.1 on page 310.

MPI\_GROUP\_TRANSLATE\_RANKS and MPI\_PROC\_NULL: MPI\_PROC\_NULL is a valid rank for input to MPI\_GROUP\_TRANSLATE\_RANKS, which returns MPI\_PROC\_NULL as the translated rank.

8. Section 7.7 on page 358.

About the attribute caching functions:

Advice to implementors. High-quality implementations should raise an error when a keyval that was created by a call to MPI\_XXX\_CREATE\_KEYVAL is used with an object of the wrong type with a call to

MPI\_YYY\_GET\_ATTR, MPI\_YYY\_SET\_ATTR, MPI\_YYY\_DELETE\_ATTR, or MPI\_YYY\_FREE\_KEYVAL. To do so, it is necessary to maintain, with each keyval, information on the type of the associated user function. (*End of advice to implementors.*)

9. Section 7.8 on page 375.

In MPI\_COMM\_GET\_NAME: In C, a null character is additionally stored at name[resultlen]. resultlen cannot be larger then MPI\_MAX\_OBJECT\_NAME-1. In Fortran, name is padded on the right with blank characters. resultlen cannot be larger then MPI\_MAX\_OBJECT\_NAME.

10. Section 8.4 on page 385.

About MPI\_GRAPH\_CREATE and MPI\_CART\_CREATE: All input arguments must have identical values on all processes of the group of comm\_old.

11. Section 8.5.1 on page 386.

In MPI\_CART\_CREATE: If ndims is zero then a zero-dimensional Cartesian topology is created. The call is erroneous if it specifies a grid that is larger than the group size or if ndims is negative.

12. Section 8.5.3 on page 388.

In MPI\_GRAPH\_CREATE: If the graph is empty, i.e., nnodes == 0, then MPI\_COMM\_NULL is returned in all processes.

13. Section 8.5.3 on page 388.

In MPI\_GRAPH\_CREATE: A single process is allowed to be defined multiple times in the list of neighbors of a process (i.e., there may be multiple edges between two processes). A process is also allowed to be a neighbor to itself (i.e., a self loop in the graph). The adjacency matrix is allowed to be non-symmetric.

Advice to users. Performance implications of using multiple edges or a non-symmetric adjacency matrix are not defined. The definition of a node-neighbor edge does not imply a direction of the communication. (End of advice to users.)

14. Section 8.5.5 on page 397.

In MPI\_CARTDIM\_GET and MPI\_CART\_GET: If comm is associated with a zero-dimensional Cartesian topology, MPI\_CARTDIM\_GET returns ndims=0 and MPI\_CART\_GET will keep all output arguments unchanged.

- 15. Section 8.5.5 on page 397.
  In MPI\_CART\_RANK: If comm is associated with a zero-dimensional Cartesian topology, coord is not significant and 0 is returned in rank.
- 16. Section 8.5.5 on page 397.
  In MPI\_CART\_COORDS: If comm is associated with a zero-dimensional Cartesian topology, coords will be unchanged.
- 17. Section 8.5.6 on page 405.

  In MPI\_CART\_SHIFT: It is erroneous to call MPI\_CART\_SHIFT with a direction that is either negative or greater than or equal to the number of dimensions in the Cartesian communicator. This implies that it is erroneous to call MPI\_CART\_SHIFT with a

comm that is associated with a zero-dimensional Cartesian topology.

- 18. Section 8.5.7 on page 407.

  In MPI\_CART\_SUB: If all entries in remain\_dims are false or comm is already associated with a zero-dimensional Cartesian topology then newcomm is associated with a zero-dimensional Cartesian topology.
- 18.1. Section 9.1.1 on page 443.

  The subversion number changed from 0 to 1.
  - 19. Section 9.1.2 on page 445.
    In MPI\_GET\_PROCESSOR\_NAME: In C, a null character is additionally stored at name[resultlen]. resultlen cannot be larger then MPI\_MAX\_PROCESSOR\_NAME-1. In Fortran, name is padded on the right with blank characters. resultlen cannot be larger then MPI\_MAX\_PROCESSOR\_NAME.
  - 20. Section 9.3 on page 450.
    MPI\_{COMM,WIN,FILE}\_GET\_ERRHANDLER behave as if a new error handler object is created. That is, once the error handler is no longer needed,
    MPI\_ERRHANDLER\_FREE should be called with the error handler returned from MPI\_ERRHANDLER\_GET or MPI\_{COMM,WIN,FILE}\_GET\_ERRHANDLER to mark the error handler for deallocation. This provides behavior similar to that of MPI\_COMM\_GROUP and MPI\_GROUP\_FREE.
  - 21. Section 11.2.1 on page 480, see explanations to MPI\_FINALIZE.

    MPI\_FINALIZE is collective over all connected processes. If no processes were spawned, accepted or connected then this means over MPI\_COMM\_WORLD; otherwise it is collective over the union of all processes that have been and continue to be connected, as explained in Section 11.10.4 on page 536.
  - 22. Section 11.2.1 on page 480. About MPI\_ABORT:

Advice to users. Whether the errorcode is returned from the executable or from the MPI process startup mechanism (e.g., mpiexec), is an aspect of quality of the MPI library but not mandatory. (End of advice to users.)

Advice to implementors. Where possible, a high-quality implementation will try to return the errorcode from the MPI process startup mechanism (e.g. mpiexec or singleton init). (End of advice to implementors.)

\mpictype #-error instead of

\const

2

23. Section 10 on page 471.

An implementation must support info objects as caches for arbitrary (key, value) pairs, regardless of whether it recognizes the key. Each function that takes hints in the form of an MPI\_Info must be prepared to ignore any key it does not recognize. This description of info objects does not attempt to define how a particular function should react if it recognizes a key but not the associated value. MPI\_INFO\_GET\_NKEYS, MPI\_INFO\_GET\_NTHKEY, MPI\_INFO\_GET\_VALUELEN, and MPI\_INFO\_GET must retain all (key,value) pairs so that layered functionality can also use the Info object.

The current entry in the indexes is correct.

10

11

12

13 14

15

16

17

18 19

20 21

22

23

24

25

26

27 28

29

30

31 32

33

34

35

36

37

39

40 41

42

43

44

45

46

47

- 24. Section 12.3 on page 559.
  - MPI\_PROC\_NULL is a valid target rank in the MPI RMA calls MPI\_ACCUMULATE, MPI\_GET, and MPI\_PUT. The effect is the same as for MPI\_PROC\_NULL in MPI pointto-point communication. See also item 25 in this list.
- 25. Section 12.3 on page 559.

After any RMA operation with rank MPI\_PROC\_NULL, it is still necessary to finish the RMA epoch with the synchronization method that started the epoch. See also item 24 in this list.

- 26. Section 12.3.4 on page 566. MPI\_REPLACE in MPI\_ACCUMULATE, like the other predefined operations, is defined only for the predefined MPI datatypes.
- 27. Section 14.2.8 on page 641. About MPI\_FILE\_SET\_VIEW and MPI\_FILE\_SET\_INFO: When an info object that specifies a subset of valid hints is passed to MPI\_FILE\_SET\_VIEW or MPI\_FILE\_SET\_INFO, there will be no effect on previously set or defaulted hints that the info does not specify.
- 28. Section 14.2.8 on page 641. About MPI\_FILE\_GET\_INFO: If no hint exists for the file associated with fh, a handle to a newly created info object is returned that contains no key/value pair.
- 29. Section 14.3 on page 644. If a file does not have the mode MPI\_MODE\_SEQUENTIAL, then MPI\_DISPLACEMENT\_CURRENT is invalid as disp in MPI\_FILE\_SET\_VIEW.
- 30. Section 14.5.2 on page 688. The bias of 16 byte doubles was defined with 10383. The correct value is 16383.
- 31. MPI-2.2, Section 16.1.4 (Section was removed in MPI-3.0). In the example in this section, the buffer should be declared as const void\* buf.
- 32. Section 19.1.9 on page 797. About MPI\_TYPE\_CREATE\_F90\_XXX:

Advice to implementors. An application may often repeat a call to MPI\_TYPE\_CREATE\_F90\_XXX with the same combination of (XXX,p,r). The application is not allowed to free the returned predefined, unnamed datatype handles. To prevent the creation of a potentially huge amount of handles, the MPI implementation should return the same datatype handle for the same (

REAL/COMPLEX/INTEGER,p,r) combination. Checking for the combination (p,r) in the preceding call to MPI\_TYPE\_CREATE\_F90\_XXX and using a hash-table to find formerly generated handles should limit the overhead of finding a previously generated datatype with same combination of (XXX,p,r). (End of advice to implementors.)

33. Section A.1.1 on page 845.

MPI\_BOTTOM is defined as void \* const MPI::BOTTOM.





### **Bibliography**

- [1] Reverse domain name notation convention. https://docs.oracle.com/javase/tutorial/java/package/namingpkgs.html. 7.4.2
- [2] V. Bala and S. Kipnis. Process groups: a mechanism for the coordination of and communication among processes in the Venus collective communication library. Technical report, IBM T. J. Watson Research Center, October 1992. Preprint. 1.2
- [3] V. Bala, S. Kipnis, L. Rudolph, and Marc Snir. Designing efficient, scalable, and portable collective communication libraries. Technical report, IBM T. J. Watson Research Center, October 1992. Preprint. 1.2
- [4] Purushotham V. Bangalore, Nathan E. Doss, and Anthony Skjellum. MPI++: Issues and Features. In OON-SKI '94, page in press, 1994. 7.1
- [5] A. Beguelin, J. Dongarra, A. Geist, R. Manchek, and V. Sunderam. Visualization and debugging in a heterogeneous environment. *IEEE Computer*, 26(6):88–95, June 1993. 1.2
- [6] Luc Bomans and Rolf Hempel. The Argonne/GMD macros in FORTRAN for portable parallel programming and their implementation on the Intel iPSC/2. *Parallel Computing*, 15:119–132, 1990. 1.2
- [7] Dan Bonachea and Jason Duell. Problems with using MPI 1.1 and 2.0 as compilation targets for parallel language implementations. IJHPCN, 1(1/2/3):91-99, 2004. 12.7
- [8] Rajesh Bordawekar, Juan Miguel del Rosario, and Alok Choudhary. Design and evaluation of primitives for parallel I/O. In *Proceedings of Supercomputing '93*, pages 452–461, 1993. 14.1
- [9] R. Butler and E. Lusk. User's guide to the p4 programming system. Technical Report TM-ANL-92/17, Argonne National Laboratory, 1992. 1.2
- [10] Ralph Butler and Ewing Lusk. Monitors, messages, and clusters: The p4 parallel programming system. *Parallel Computing*, 20(4):547–564, April 1994. Also Argonne National Laboratory Mathematics and Computer Science Division preprint P362-0493. 1.2
- [11] Robin Calkin, Rolf Hempel, Hans-Christian Hoppe, and Peter Wypior. Portable programming with the PARMACS message-passing library. *Parallel Computing*, 20(4):615–632, April 1994. 1.2

[12] S. Chittor and R. J. Enbody. Performance evaluation of mesh-connected wormhole-routed networks for interprocessor communication in multicomputers. In *Proceedings* of the 1990 Supercomputing Conference, pages 647–656, 1990. 8.1

- [13] S. Chittor and R. J. Enbody. Predicting the effect of mapping on the communication performance of large multicomputers. In *Proceedings of the 1991 International Conference on Parallel Processing*, vol. II (Software), pages II-1-II-4, 1991. 8.1
- [14] Parasoft Corporation. Express version 1.0: A communication environment for parallel computers, 1988. 1.2
- [15] Yiannis Cotronis, Anthony Danalis, Dimitrios S. Nikolopoulos, and Jack Dongarra, editors. Recent Advances in the Message Passing Interface 18th European MPI Users' Group Meeting, EuroMPI 2011, Santorini, Greece, September 18-21, 2011. Proceedings, volume 6960 of Lecture Notes in Computer Science. Springer, 2011. 17, 40
- [16] Juan Miguel del Rosario, Rajesh Bordawekar, and Alok Choudhary. Improved parallel I/O via a two-phase run-time access strategy. In *IPPS '93 Workshop on Input/Output in Parallel Computer Systems*, pages 56–70, 1993. Also published in Computer Architecture News 21(5), December 1993, pages 31–38. 14.1
- [17] James Dinan, Sriram Krishnamoorthy, Pavan Balaji, Jeff R. Hammond, Manojkumar Krishnan, Vinod Tipparaju, and Abhinav Vishnu. Noncollective communicator creation in MPI. In Cotronis et al. [15], pages 282–291. 7.4.2
- [18] J. Dongarra, A. Geist, R. Manchek, and V. Sunderam. Integrated PVM framework supports heterogeneous network computing. *Computers in Physics*, 7(2):166–75, April 1993. 1.2
- [19] J. J. Dongarra, R. Hempel, A. J. G. Hey, and D. W. Walker. A proposal for a user-level, message passing interface in a distributed memory environment. Technical Report TM-12231, Oak Ridge National Laboratory, February 1993. 1.2
- [20] Edinburgh Parallel Computing Centre, University of Edinburgh. CHIMP Concepts, June 1991. 1.2
- [21] Edinburgh Parallel Computing Centre, University of Edinburgh. CHIMP Version 1.0 Interface, May 1992. 1.2
- [22] D. Feitelson. Communicators: Object-based multiparty interactions for parallel programming. Technical Report 91-12, Dept. Computer Science, The Hebrew University of Jerusalem, November 1991. 7.1.2
- [23] Message Passing Interface Forum. MPI: A Message-Passing Interface standard. The International Journal of Supercomputer Applications and High Performance Computing, 8, 1994. 1.3
- [24] Message Passing Interface Forum. MPI: A Message-Passing Interface standard (version 1.1). Technical report, 1995. http://www.mpi-forum.org. 1.3
- [25] Al Geist, Adam Beguelin, Jack Dongarra, Weicheng Jiang, Bob Manchek, and Vaidy Sunderam. PVM: Parallel Virtual Machine—A User's Guide and Tutorial for Network Parallel Computing. MIT Press, 1994. 11.1

[26] G. A. Geist, M. T. Heath, B. W. Peyton, and P. H. Worley. PICL: A portable instrumented communications library, C reference manual. Technical Report TM-11130, Oak Ridge National Laboratory, Oak Ridge, TN, July 1990. 1.2

- [27] Brice Goglin, Emmanuel Jeannot, Farouk Mansouri, and Guillaume Mercier. Hardware topology management in MPI applications through hierarchical communicators. *Parallel Computing*, 76:70–90, 2018. 7.4.2
- [28] Ryan E. Grant, Matthew G. F. Dosanjh, Michael J. Levenhagen, Ron Brightwell, and Anthony Skjellum. Finepoints: Partitioned multithreaded MPI communication. In *ISC High Performance Conference (ISC)*, 2019. 4.1
- [29] Ryan E. Grant, Anthony Skjellum, and Purushotham V. Bangalore. Lightweight threading with MPI using persistent communications semantics. In *Workshop on Exascale MPI (ExaMPI)*. Held in conjunction with the 2015 International Conference for High Performance Computing, Networking, Storage and Analysis (SC15), 2015. 4.1
- [30] D. Gregor, T. Hoefler, B. Barrett, and A. Lumsdaine. Fixing probe for multi-threaded MPI applications. Technical Report 674, Indiana University, Jan. 2009. 3.8.2
- [31] William D. Gropp and Barry Smith. Chameleon parallel programming tools users manual. Technical Report ANL-93/23, Argonne National Laboratory, March 1993. 1.2
- [32] Michael Hennecke. A Fortran 90 interface to MPI version 1.1. Technical Report Internal Report 63/96, Rechenzentrum, Universität Karlsruhe, D-76128 Karlsruhe, Germany, June 1996. 19.1.3
- [33] T. Hoefler, G. Bronevetsky, B. Barrett, B. R. de Supinski, and A. Lumsdaine. Efficient MPI support for advanced hybrid programming models. In *Recent Advances in the Message Passing Interface (EuroMPI'10)*, volume LNCS 6305, pages 50–61. Springer, Sep. 2010. 3.8.1, 3.8.2
- [34] T. Hoefler, P. Gottschling, A. Lumsdaine, and W. Rehm. Optimizing a conjugate gradient solver with non-blocking collective operations. *Elsevier Journal of Parallel Computing (PARCO)*, 33(9):624–633, Sep. 2007. 6.12
- [35] T. Hoefler, F. Lorenzen, and A. Lumsdaine. Sparse non-blocking collectives in quantum mechanical calculations. In *Recent Advances in Parallel Virtual Machine and Message Passing Interface*, 15th European PVM/MPI Users' Group Meeting, volume LNCS 5205, pages 55–63. Springer, Sep. 2008. 8.6
- [36] T. Hoefler and A. Lumsdaine. Message progression in parallel computing to thread or not to thread? In *Proceedings of the 2008 IEEE International Conference on Cluster Computing*. IEEE Computer Society, Oct. 2008. 6.12
- [37] T. Hoefler, A. Lumsdaine, and W. Rehm. Implementation and performance analysis of non-blocking collective operations for MPI. In *Proceedings of the 2007 International Conference on High Performance Computing, Networking, Storage and Analysis, SC07.* IEEE Computer Society/ACM, Nov. 2007. 6.12

[38] T. Hoefler, M. Schellmann, S. Gorlatch, and A. Lumsdaine. Communication optimization for medical image reconstruction algorithms. In *Recent Advances in Parallel Virtual Machine and Message Passing Interface*, 15th European PVM/MPI Users' Group Meeting, volume LNCS 5205, pages 75–83. Springer, Sep. 2008. 6.12

- [39] T. Hoefler and J. L. Träff. Sparse collective operations for MPI. In *Proceedings of the 23rd IEEE International Parallel & Distributed Processing Symposium*, HIPS'09 Workshop, May 2009. 8.6
- [40] Torsten Hoefler and Marc Snir. Writing parallel libraries with MPI common practice, issues, and extensions. In Cotronis et al. [15], pages 345–355. 7.4.2
- [41] Daniel J. Holmes, Bradley Morgan, Anthony Skjellum, Purushotham V. Bangalore, and Srinivas Sridharan. Planning for performance: Enhancing achievable performance for MPI through persistent collective operations. *Parallel Computing*, 81:32 57, 2019. 6.13
- [42] Institute of Electrical and Electronics Engineers, New York. *IEEE Standard for Binary Floating-Point Arithmetic*, *IEEE Standard* 754-2008, 2008. 14.5.2
- [43] International Organization for Standardization, Geneva. ISO 8859-1:1987: Information processing 8-bit single-byte coded graphic character sets Part 1: Latin alphabet No. 1, February 1987. 14.5.2
- [44] International Organization for Standardization, Geneva. ISO/IEC 9945-1:1996: Information technology Portable Operating System Interface (POSIX) Part 1: System Application Program Interface (API) [C Language], December 1996. 11.6, 14.2.1
- [45] International Organization for Standardization, Geneva. ISO/IEC 1539-1:2010: Information technology Programming languages Fortran Part 1: Base language, November 2010. 19.1.1, 19.1.2
- [46] International Organization for Standardization, Geneva. *ISO/IEC TS 29113:2012:* Information technology Further interoperability of Fortran with C, December 2012. 19.1.1, 19.1.1, 19.1.2, 19.1.7, 28
- [47] Charles H. Koelbel, David B. Loveman, Robert S. Schreiber, Guy L. Steele Jr., and Mary E. Zosel. *The High Performance Fortran Handbook*. MIT Press, 1993. 5.1.4
- [48] David Kotz. Disk-directed I/O for MIMD multiprocessors. In *Proceedings of the 1994 Symposium on Operating Systems Design and Implementation*, pages 61–74, November 1994. Updated as Dartmouth TR PCS-TR94-226 on November 8, 1994. 14.1
- [49] O. Krämer and H. Mühlenbein. Mapping strategies in message-based multiprocessor systems. *Parallel Computing*, 9:213–225, 1989. 8.1
- [50] S. J. Lefflet, R. S. Fabry, W. N. Joy, P. Lapsley, S. Miller, and C. Torek. An advanced 4.4BSD interprocess communication tutorial, Unix programmer's supplementary documents (PSD) 21. Technical report, Computer Systems Research Group, Depertment of Electrical Engineering and Computer Science, University of California, Berkeley, 1993. Available online: https://docs.freebsd.org/44doc/psd/21.ipc/paper.pdf. 11.10.5

[51] Message Passing Interface Forum. Summary of the semantics of all operation-related MPI procedures, 2020. Available online: https://www.mpi-forum.org/docs. A.2

- [52] Bradley Morgan, Daniel J. Holmes, Anthony Skjellum, Purushotham Bangalore, and Srinivas Sridharan. Planning for performance: Persistent collective operations for MPI. In *Proceedings of the 24th European MPI Users' Group Meeting*, EuroMPI '17, pages 4:1–4:11, New York, NY, USA, 2017. ACM. 6.13
- [53] nCUBE Corporation. nCUBE 2 Programmers Guide, r2.0, December 1990. 1.2
- [54] Bill Nitzberg. Performance of the iPSC/860 Concurrent File System. Technical Report RND-92-020, NAS Systems Division, NASA Ames, December 1992. 14.1

10 11

12

13

14 15

16

17

18

19

20 21

22

23

24

26

27

28

29

30

31

34

35 36

37

38

39

41

42

43


44 45

46

- [55] William J. Nitzberg. Collective Parallel I/O. PhD thesis, Department of Computer and Information Science, University of Oregon, December 1995. 14.1
- [56] 4.4BSD Programmer's Supplementary Documents (PSD). O'Reilly and Associates, 1994. 11.10.5
- [57] Paul Pierce. The NX/2 operating system. In Proceedings of the Third Conference on Hypercube Concurrent Computers and Applications, pages 384–390. ACM Press, 1988.
  1.2
- [58] Martin Schulz and Bronis R. de Supinski.  $P^N$ MPI tools: A whole lot greater than the sum of their parts. In ACM/IEEE Supercomputing Conference (SC), pages 1–10. ACM, 2007. 15.2.8
- [59] K. E. Seamons, Y. Chen, P. Jones, J. Jozwiak, and M. Winslett. Server-directed collective I/O in Panda. In *Proceedings of Supercomputing '95*, December 1995. 14.1
- [60] A. Skjellum and A. Leung. Zipcode: a portable multicomputer communication library atop the reactive kernel. In D. W. Walker and Q. F. Stout, editors, *Proceedings of the* Fifth Distributed Memory Concurrent Computing Conference, pages 767–776. IEEE Press, 1990. 1.2, 7.1.2
- [61] A. Skjellum, S. Smith, C. Still, A. Leung, and M. Morari. The Zipcode message passing system. Technical report, Lawrence Livermore National Laboratory, September 1992.
  1.2
- [62] Anthony Skjellum, Nathan E. Doss, and Purushotham V. Bangalore. Writing Libraries in MPI. In Anthony Skjellum and Donna S. Reese, editors, *Proceedings of the Scalable Parallel Libraries Conference*, pages 166–173. IEEE Computer Society Press, October 1993. 7.1
- [63] Anthony Skjellum, Nathan E. Doss, and Kishore Viswanathan. Inter-communicator extensions to MPI in the MPIX (MPI eXtension) Library. Technical Report MSU-940722, Mississippi State University Dept. of Computer Science, August 1994. Archived at http://citeseerx.ist.psu.edu/viewdoc/summary?doi=10.1.1.49.6283. 6.2.2
- [64] Anthony Skjellum, Steven G. Smith, Nathan E. Doss, Alvin P. Leung, and Manfred Morari. The Design and Evolution of Zipcode. *Parallel Computing*, 20(4):565–596, April 1994. 7.1.2, 7.5.6

[65] The Internet Society. XDR: External Data Representation Standard, May 2006. http://www.rfc-editor.org/pdfrfc/rfc4506.txt.pdf. 14.5.2

- [66] Rajeev Thakur and Alok Choudhary. An extended two-phase method for accessing sections of out-of-core arrays. *Scientific Programming*, 5(4):301–317, Winter 1996. 14.1
- [67] Jesper Larsson Träff. SMP-aware message passing programming. In Eighth International Workshop on High-level Parallel Programming Models and Supportive Environments (HIPS), 17th International Parallel and Distributed Processing Symposium (IPDPS), pages 56–65, 2003. 7.4.2
- [68] The Unicode Standard, Version 2.0. Addison-Wesley, 1996. ISBN 0-201-48345-9. 14.5.2
- [69] D. Walker. Standards for message passing in a distributed memory environment. Technical Report TM-12147, Oak Ridge National Laboratory, August 1992. 1.2



This index lists mainly terms of the MPI specification. The underlined page numbers refer to the definitions or parts of the definition of the terms. Bold face numbers mark section titles.

absolute addresses, <b>20</b> , <u>137</u> , 815	language binding, 23
access epoch, $583$	caching, <b>305</b> , <u>306</u> , <b>358</b>
action	callback functions
in function names, $\underline{10}$	language interoperability, 836
active, <u>67</u> , 380	prototype definitions, 860
active target communication, <u>583</u>	deprecated, 867
addresses, <u>152</u>	cancel, 23, 68, <u>80</u> , <b>88</b> , 488, 772, 1032
absolute, <b>20</b> , 21, <u>137</u> , 815	canonical pack and unpack, 178
correct use, 152	Cartesian
relative displacement, 20, <u>137</u>	topology, <u>385</u> , <b>386</b>
alignment, 448, 547, 550, 1033	Chameleon, 2
all-reduce, 234	change-log, 1031
nonblocking, 265	Chimp, 2
persistent, 290	choice, 19
all-to-all, 213	class
nonblocking, 258	in function names, $\underline{10}$
persistent, 283	clock synchronization, 446
array arguments, 18	collective, 647
assertions, 598	split, <b>696</b>
ASYNCHRONOUS	collective communication, 183
Fortran attribute, 816	correctness, 296
attribute, <u>307</u> , <u>358</u> , <b>837</b>	file data access operations, 671
caching, <u>306</u>	neighborhood, 410
	nonblocking, 246
backward incompatibilies, 777	Collective operation, $\underline{12}$
barrier synchronization, 189	Collective procedure, <u>14</u>
nonblocking, 248	commit, <u>146</u>
persistent, 272	COMMON blocks, 819
blocking, <u>46</u> , 50, 647	communication, 541
I/O, 648	collective, 183
Blocking operation, $\underline{12}$	modes, <b>46</b>
Blocking procedure, $\underline{14}$	one-sided, $541$
bounds of datatypes, 142	overlap with computation, 58
broadcast, 190	partitioned point-to-point, 99
nonblocking, 248	point-to-point, 29
persistent, 273	$RMA, \underline{541}$
buffer allocation, 55	communicator, $\underline{34}$ , $\underline{305}$ , $\underline{306}$
buffered, $47, 59, 60$	hidden, 186, 298, 591
nonblocking, <u>59</u>	complete operation, $\underline{12}$
buffered send, 51	Completing procedure, $\underline{14}$
C	completion, 67
$\mathbf{C}$	•

1	multiple, <b>72</b>	transmission failure, $\underline{25}$
2	completion stage, $\underline{12}$	establishing communication, <b>523</b>
3	connected, $\underline{536}$	etype, <u>631</u> , 646
4	constants, 18, 841, 845	events
5	context, $305$ , $306$ , $308$	tools interface, <b>745</b>
6	control variables	exclusive scan
	tools interface, 726	nonblocking, 270
7	conversion, 45	persistent, 295
8	counts, 20	explicit offsets, $\underline{648}$ , $650$
9	create	exposure epoch, $\underline{583}$
10	in function names, 10	extent of datatypes, <u>116</u> , <u>141</u> , <b>142</b>
11		true extent, 144
12	data, <b>31</b>	external32
13	data conversion, 45	file data representation, $\underline{685}$
14	datatype	extra-state, 841
	derived, <u>15</u>	
15	equivalent, $\underline{15}$	fairness, 52, <u>77</u>
16	named, $\underline{15}$	file, <u>631</u>
17	portable, $\underline{15}$	data access, 647
18	predefined, $\underline{15}$	collective operations, 671
19	unnamed, $\underline{15}$	explicit offsets, 650
20	datatypes, <b>115</b> , <b>834</b>	individual file pointers, 657
21	deadlock	seek, <b>674</b>
	avoid, nonblocking communication, 58	shared file pointers, 667
22	default file error, <u>706</u>	split collective, 675
23	delete	end of file, <u>633</u>
24	in function names, $\underline{10}$	filetype, $\underline{632}$
25	deprecated interfaces, 22, 769	handle, <u>633</u>
26	derived datatype, <u>15</u> , <b>115</b> , <b>811</b>	interoperability, 684
27	disconnected, <u>537</u>	manipulation, 633
28	displacement, $\underline{631}$ , $645$	offset, <b>20</b> , $\underline{632}$
	distributed graph	pointer, <u>633</u>
29	topology, <u>385</u> , <b>390</b>	size, <u>633</u>
30	Dynamic Process Model, 479	view, 631, <u>632</u> , <b>644</b>
31	dynamically attached memory, <b>552</b>	file size, <b>701</b>
32	1 1 1 1 001 040	finalize, 486
33	elementary datatype, <u>631</u> , 646	finished, 489
34	empty, <u>67</u>	Fortran
35	end of file, <u>633</u>	language binding, 22, 779
36	envelope, 29, 33	Fortran support, 779
	environmental inquiries, 445	Freeing procedure, $\underline{14}$
37	equivalent datatypes, <u>15</u>	freeing stage, $\underline{12}$
38	error handling, <b>24</b> , <b>450</b>	
39	default file error handler, 634, 637, <u>706</u>	gather, 191
40	error codes and classes, 461, 462	nonblocking, 250
41	error handlers, <b>453</b> , <b>462</b> , <b>836</b>	persistent, 274
42	finalize, 25, 488, 537	gather-to-all, 209
43	I/O, <b>706</b> , <b>707</b>	nonblocking, 256
	initial error handler, <u>25</u> , 451, 481, 488, 521	persistent, 280
44	one-sided communication, <b>599</b>	general datatype, <u>115</u>
45	process failure, $\underline{25}$ , 537	generalized requests, <b>621</b> , <u>621</u>
46	program error, $\underline{25}$	get
47	resource error, $\underline{25}$	in function names, $\underline{10}$
48	startup, 25, <b>481</b> , 521	graph

topology, <u>385</u> , <b>388</b>	lower bound, $\underline{141}$	1
group, <b>305</b> , <u>306</u> , <u>308</u> , 350	lower-bound markers, 140	2
group objects, $308$		3
	macros, 24	4
handles, $16, 829$	main thread, $509$	5
hardware resource type, $333$ , $335$	matched receives, 85	
host rank, 445	matching	6
	type, <b>42</b> , <u>149</u> , <b>700</b>	7
immediate, $\underline{14}$ , $\underline{60}$	matching probe, 83	8
inactive, <u>67</u>	memory	9
inclusive scan, 241	alignment, 448, 547, 550, 1033	10
nonblocking, 269	allocation, <b>447</b> , 546, 548	
persistent, 294	system, <u>16</u>	11
incomplete, <u>14</u> , <u>60</u>	· · · —	12
Incomplete procedure, <u>14</u>	memory model, $542$ , $582$	13
independent, $\underline{537}$	separate, 542, 550	14
individual file pointers, <u>648</u> , <b>657</b>	unified, 542, 550	
info object, 471	message, 29	15
•	data, 31	16
file info, <b>641</b>	envelope, <b>33</b>	17
keys, <b>867</b>	modes, <b>46</b>	18
values, 868	module variables, 819	19
initial error handler, $\underline{25}$	mpi module	
Initialization procedure, $\underline{13}$	Fortran support, 783	20
initialization stage, $\underline{11}$	MPI operation, 11	21
initiation, <u>11</u> , <u><b>60</b></u>	MPI process initialization, 479	22
Initiation procedure, <u>14</u>	Dynamic Process Model, 479	23
inter-communication, 307, 349		
inter-communicator, 307, 349	Sessions Model, 309, 312, 445, 479, 509,	24
collective operations, 187, 188	634	25
interlanguage communication, 842	World Model, <b>309</b> , <b>312</b> , <b>445</b> , <b>479</b> , <b>509</b> ,	26
	634, 707	27
internal	mpi_f08 module	
file data representation, <u>685</u>	Fortran support, 780	28
interoperability, 684	MPI_SIZEOF and storage_size(), 23, 773,	29
intra-communication, <u>307</u> , <u>348</u>	803-805	30
intra-communicator, $306$ , $348$	mpiexec, 482, 505, 506	31
collective operations, 186	mpif.h include file	32
intra-communicator objects, <u>309</u>	Fortran support, 785	
I/O, <b>631</b>	mpirun, 506	33
IO rank, <b>446</b>	multiple completions, 72	34
is	muniple completions, 72	35
in function names, <u>10</u>	named datatype, $\underline{15}$	36
m ranson names, <u>ro</u>		37
language binding, 21, 779	names, <b>524</b>	
interoperability, 828	name publishing, 529	38
summary, 845	naming objects, 375	39
large	native	40
9	file data representation, $\underline{685}$	41
count, <u>21</u> , <b>827</b>	neighborhood collective communication, 410	
displacement, 827	nonblocking, 422	42
large count, $\underline{21}$	periodic and dims==1 or $2, 1032$	43
lb_marker, 130, 131, 135, <u>140</u> , 141, 146	non-local, 47	44
erased, <u>144</u>	Non-local procedure, <u>13</u>	45
local, 47	nonblocking, <b>58</b> , 559, 647	
local group, 322	communication, <u>58</u>	46
Local procedure, <u>13</u>		47
loosely synchronous model, 380	completion, 67	48
,		

1	Fortran problems, 813	probe, 80
2	I/O, 648	probe, matching, 83
3	initiation, 60	procedure
4	persistent	blocking, <u>14</u>
5	partitioned completion, 106	collective, <u>14</u>
6	request objects, 60	completing, $\underline{14}$
7	Nonblocking operation, $\underline{12}$	freeing, $\underline{14}$
8	Nonblocking procedure, <u>14</u>	incomplete, <u>14</u>
	Noncollective operation, $\underline{12}$	initialization, $\underline{13}$
9	null handle, <u>67</u>	initiation, <u>14</u>
10	null processes, 96	local, <u>13</u>
11	offset, <b>20</b> , <u>632</u>	non-local, 13
12	one-sided communication, <b>541</b>	nonblocking, $\underline{14}$
13	Fortran problems, 815	operation-related, $\underline{13}$
14	opaque objects, 16, 834	starting, $\underline{13}$
15	operation	process creation, 479
16	blocking, <u>12</u>	process failures, $\underline{25}$
	collective, <u>12</u>	process group, $\underline{34}$
17	complete, $\underline{12}$	processes, 24
18	nonblocking, 12	processor name, 446
19	noncollective, 12	profiling interface, <b>713</b>
20	operation-related, <u>13</u>	program error, $\underline{25}$ progress, $\underline{247}$
21	partitioned receive, 12	prototype definitions, 860
22	partitioned send, <u>12</u>	deprecated, 867
23	persistent, 12	public window copy, 581
24	origin, <u>542</u>	PVM, 2
25		1 (14)
26	pack, <b>170</b>	rank, <u>308</u>
27	canonical, 178	ready, $47, 59, 60$
	packing unit, $\underline{173}$	nonblocking, $\underline{59}$
28	parallel procedure, <u>380</u>	ready send, 51
29	partitioned completion, 106	receive, <u>29, 30,</u> <b>34</b>
30	partitioned point-to-point communication, 99	buffer, $30$
31	passive target communication, <u>583</u>	complete, $\underline{58}$
20	performance variables	
32	1 1	context, 350
33	tools interface, 733	start call, $\underline{58}$
	persistent communication requests, 90	start call, $\underline{58}$ reduce, $\underline{220}$
33	persistent communication requests, 90 collective persistent, 271, 429	start call, <u>58</u> reduce, <b>220</b> nonblocking, <b>264</b>
33 34 35	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815	start call, <u>58</u> reduce, <b>220</b> nonblocking, <b>264</b> persistent, <b>289</b>
33 34 35 36	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12	start call, <u>58</u> reduce, <b>220</b> nonblocking, <b>264</b> persistent, <b>289</b> reduce-scatter, <b>238</b>
33 34 35 36 37	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, $\underline{12}$ PICL, 2	start call, <u>58</u> reduce, <u>220</u> nonblocking, <u>264</u> persistent, <u>289</u> reduce-scatter, <u>238</u> nonblocking, <u>266</u> , <u>268</u>
33 34 35 36 37 38	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12 PICL, 2 PMPI_, 713	start call, <u>58</u> reduce, <b>220</b> nonblocking, <b>264</b> persistent, <b>289</b> reduce-scatter, <b>238</b> nonblocking, <b>266</b> , <b>268</b> persistent, <b>291</b> , <b>293</b>
33 34 35 36 37 38 39	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12 PICL, 2 PMPI_, 713 point-to-point communication, 29	start call, <u>58</u> reduce, <b>220</b> nonblocking, <b>264</b> persistent, <b>289</b> reduce-scatter, <b>238</b> nonblocking, <b>266</b> , <b>268</b> persistent, <b>291</b> , <b>293</b> reduction operations, <b>219</b> , <b>836</b>
33 34 35 36 37 38 39 40	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12 PICL, 2 PMPI_, 713 point-to-point communication, 29 portable datatype, 15	start call, <u>58</u> reduce, <b>220</b> nonblocking, <b>264</b> persistent, <b>289</b> reduce-scatter, <b>238</b> nonblocking, <b>266</b> , <b>268</b> persistent, <b>291</b> , <b>293</b> reduction operations, <b>219</b> , <b>836</b> predefined, <b>222</b>
33 34 35 36 37 38 39	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12 PICL, 2 PMPI_, 713 point-to-point communication, 29	start call, <u>58</u> reduce, <b>220</b> nonblocking, <b>264</b> persistent, <b>289</b> reduce-scatter, <b>238</b> nonblocking, <b>266</b> , <b>268</b> persistent, <b>291</b> , <b>293</b> reduction operations, <b>219</b> , <b>836</b> predefined, <b>222</b> process-local, <b>236</b>
33 34 35 36 37 38 39 40	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12 PICL, 2 PMPI_, 713 point-to-point communication, 29 portable datatype, 15 ports, 524 POSIX	start call, <u>58</u> reduce, <b>220</b> nonblocking, <b>264</b> persistent, <b>289</b> reduce-scatter, <b>238</b> nonblocking, <b>266</b> , <b>268</b> persistent, <b>291</b> , <b>293</b> reduction operations, <b>219</b> , <b>836</b> predefined, <b>222</b> process-local, <b>236</b> scan, <b>241</b>
33 34 35 36 37 38 39 40 41	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12 PICL, 2 PMPI_, 713 point-to-point communication, 29 portable datatype, 15 ports, 524	start call, <u>58</u> reduce, <u>220</u> nonblocking, <u>264</u> persistent, <u>289</u> reduce-scatter, <u>238</u> nonblocking, <u>266</u> , <u>268</u> persistent, <u>291</u> , <u>293</u> reduction operations, <u>219</u> , <u>836</u> predefined, <u>222</u> process-local, <u>236</u> scan, <u>241</u> user-defined, <u>229</u>
33 34 35 36 37 38 39 40 41 42	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12 PICL, 2 PMPI_, 713 point-to-point communication, 29 portable datatype, 15 ports, 524 POSIX environment, 469	start call, <u>58</u> reduce, <u>220</u> nonblocking, <u>264</u> persistent, <u>289</u> reduce-scatter, <u>238</u> nonblocking, <u>266</u> , <u>268</u> persistent, <u>291</u> , <u>293</u> reduction operations, <u>219</u> , <u>836</u> predefined, <u>222</u> process-local, <u>236</u> scan, <u>241</u> user-defined, <u>229</u> related, <u>173</u>
33 34 35 36 37 38 39 40 41 42 43	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12 PICL, 2 PMPI_, 713 point-to-point communication, 29 portable datatype, 15 ports, 524 POSIX environment, 469 FORTRAN, 17 I/O, 634, 635, 648, 684, 697 model, 631	start call, <u>58</u> reduce, <b>220</b> nonblocking, <b>264</b> persistent, <b>289</b> reduce-scatter, <b>238</b> nonblocking, <b>266</b> , <b>268</b> persistent, <b>291</b> , <b>293</b> reduction operations, <b>219</b> , <b>836</b> predefined, <b>222</b> process-local, <b>236</b> scan, <b>241</b> user-defined, <b>229</b> related, <u>173</u> relative displacement, <b>20</b> , <u>137</u>
33 34 35 36 37 38 39 40 41 42 43 44	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12 PICL, 2 PMPI_, 713 point-to-point communication, 29 portable datatype, 15 ports, 524 POSIX environment, 469 FORTRAN, 17 I/O, 634, 635, 648, 684, 697 model, 631 predefined datatype, 15	start call, <u>58</u> reduce, <u>220</u> nonblocking, <u>264</u> persistent, <u>289</u> reduce-scatter, <u>238</u> nonblocking, <u>266</u> , <u>268</u> persistent, <u>291</u> , <u>293</u> reduction operations, <u>219</u> , <u>836</u> predefined, <u>222</u> process-local, <u>236</u> scan, <u>241</u> user-defined, <u>229</u> related, <u>173</u>
33 34 35 36 37 38 39 40 41 42 43 44 45	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12 PICL, 2 PMPI_, 713 point-to-point communication, 29 portable datatype, 15 ports, 524 POSIX environment, 469 FORTRAN, 17 I/O, 634, 635, 648, 684, 697 model, 631 predefined datatype, 15 predefined reduction operations, 222	start call, <u>58</u> reduce, <b>220</b> nonblocking, <b>264</b> persistent, <b>289</b> reduce-scatter, <b>238</b> nonblocking, <b>266</b> , <b>268</b> persistent, <b>291</b> , <b>293</b> reduction operations, <b>219</b> , <b>836</b> predefined, <b>222</b> process-local, <b>236</b> scan, <b>241</b> user-defined, <b>229</b> related, <u>173</u> relative displacement, <b>20</b> , <u>137</u> remote group, 322
33 34 35 36 37 38 39 40 41 42 43 44 45 46	persistent communication requests, 90 collective persistent, 271, 429 Fortran problems, 815 Persistent operation, 12 PICL, 2 PMPI_, 713 point-to-point communication, 29 portable datatype, 15 ports, 524 POSIX environment, 469 FORTRAN, 17 I/O, 634, 635, 648, 684, 697 model, 631 predefined datatype, 15	start call, <u>58</u> reduce, <u>220</u> nonblocking, <u>264</u> persistent, <u>289</u> reduce-scatter, <u>238</u> nonblocking, <u>266</u> , <u>268</u> persistent, <u>291</u> , <u>293</u> reduction operations, <u>219</u> , <u>836</u> predefined, <u>222</u> process-local, <u>236</u> scan, <u>241</u> user-defined, <u>229</u> related, <u>173</u> relative displacement, <u>20</u> , <u>137</u> remote group, <u>322</u> Remote Memory Access

request complete	singleton init, 535	1
I/O, 648	size changing	2
request objects, 60	I/O, 701	3
resource error, $\underline{25}$	source, $350$	4
RMA, $541$	split collective, 647, 675	5
communication calls, <b>559</b>	stage	
request-based, 574	completion, $\underline{12}$	6
memory model, 581	freeing, $\underline{12}$	7
synchronization calls, 583	initialization, <u>11</u>	8
	starting, 11	9
scan, <b>241</b>	standard, $46, 59$	10
inclusive, 241	nonblocking, 59	11
scatter, 202	standard send, 51	
nonblocking, 253	started, 489	12
persistent, 277		13
seek, 674	Starting procedure, $\underline{13}$	14
semantics, 1031	starting processes, <b>512</b> , <b>513</b>	15
collective communications, 184	starting stage, <u>11</u>	16
file	startup, 480	
	portable, 506	17
collective, 700	state, 18	18
collective access, 671	status, <b>36</b> , <b>831</b>	19
conflicting access, 697	associating information, 628	20
consistency, 696	ignore, <b>39</b>	21
explicit offsets, 650	test, <b>79</b>	
nonblocking collective, 700	strong synchronization, $\underline{584}$	22
shared file pointer, 667	synchronization, 541, 559	23
split collective, 696	synchronization calls	24
inter-communicator, 322	RMA, <b>583</b>	25
MPI_COMM_IDUP, <b>324</b>	synchronous, <u>47</u> , 59, <u>60</u> , <u>67</u>	26
nonblocking communications, 71	nonblocking, $59$	
nonblocking partitioned communications,	synchronous send, 51	27
107	system memory, <u>16</u>	28
partitioned point-to-point communication,	bystem memory, <u>ro</u>	29
100	tag values, 445	30
point-to-point communication, <b>51</b>	target, $542$	31
process failure, 537	thread compliant, $484$ , $508$	32
semantics and correctness	threads, <b>508</b>	
one-sided communication, 600	thread-safe, <b>2</b> , <b>444</b> , <b>461</b> , <b>462</b> , <b>749</b>	33
send, 29, 30	timers and synchronization, 469	34
buffer, 29	tool information interface, 719	35
	tool support, 713	36
complete, $\underline{58}$		37
context, 350	topologies, 383	38
$\frac{58}{2}$	topology	
send-receive, 40	Cartesian, <u>385</u> , <b>386</b>	39
nonblocking, 65, 66	distributed graph, <u>385</u> , <b>390</b>	40
separate memory model, 542, 550, <u>582</u>	graph, <u>385</u> , <b>388</b>	41
sequential storage, <u>152</u>	virtual, 384	42
serialization, 58	transmission failures, $\underline{25}$	43
Sessions Model, <b>309</b> , <b>312</b> , <b>445</b> , <b>479</b> , <b>509</b> , <b>634</b>	true extent of datatypes, 144	44
set	TS 29113, 19, 22, 779–784, 786–789, 792–796,	
in function names, $\underline{10}$	805, 806, 812, 816, 817, 820, 821,	45
shared file pointers, $\underline{648}$ , $\underline{667}$	1040,1041	46
shared memory allocation, 548	type map, $\underline{116}$	47
signals, 27	type matching, $42$ , $\underline{149}$	48

```
1
      type signature, \underline{116}
2
       types, 859
3
      ub_marker, 130, 131, 135, \underline{140}, 141, 146
           erased, 144
5
      unified memory model, 542, 550, 582
6
      universe size, 534
7
      unnamed datatype, 15
8
      unpack, 170
           canonical, 178
9
      upper bound, 141
10
      upper-bound markers, 140
11
      user functions at process termination, 490
12
      user-defined data representations, 691
13
      user-defined reduction operations, 229
14
      verbosity levels
15
           tools interface, 720
16
       version inquiries, 443
17
      view, 631, 632, 644
18
       virtual topology, 306, 307, 384
19
20
      weak synchronization, 585
21
      window
           allocation, 546
22
           creation, 543
23
           dynamically attached memory, 552
24
           shared memory allocation, 548
25
      World Model, 309, 312, 445, 479, 509, 634,
26
                707
27
      XDR, 46
28
29
      Zipcode, 2
30
31
32
33
34
35
36
37
38
39
41
42
43
44
45
46
```

## **Examples Index**

This index lists code examples throughout the text. Some examples are referred to by content; others are listed by the major MPI function that they are demonstrating. MPI functions listed in all capital letter are Fortran examples; MPI functions listed in mixed case are C examples.

ASYNCHRONOUS, 616, 823, 825	Independence of nonblocking operations, 303	13
Attributes between languages, 837	Inter-communicator, 332	14
	Intercommunicator, 326	15
Blocking/Nonblocking collectives do not	Interlanguage communication, 842	16
match, 301	Intertwined matching pairs, 52	
C/E   1 11   1   001		17
C/Fortran handle conversion, 831	Message exchange (ping-pong), 53	18
Cartesian virtual topologies, 437	Mixing blocking and nonblocking collective	19
Client-server code, 78	operations, 299	20
with probe, 82	Mixing collective and point-to-point requests,	21
with probe, wrong, 82	301	22
Deteture	MPI_ACCUMULATE, 568	23
Datatype	MPI_Accumulate, 614, 615, 618	
3D array, 162	MPI_Aint, 164	24
absolute addresses, 167	MPI_Aint_add, 618	25
array of structures, 164	MPI_Allgather, 212	26
elaborate example, 175, 176	MPI_ALLOC_MEM, 449, 450	27
matching type, 149	MPI_Alloc_mem, 450, 618	28
matrix transpose, 163	MPI_ALLREDUCE, 235	29
union, 168	MPI_Alltoall, 301	30
Datatypes	MPI_ASYNC_PROTECTS_NONBLOCKING,	
matching, 43	616	31
not matching, 43	MPI_BARRIER, 502	32
untyped, 43	MPI_Barrier, 488, 605–608, 613–616	33
Deadlock	MPI_Bcast, 191, 296–299	34
if not buffered, 54	MPI_BSEND, 52	35
with MPI_Bcast, 296, 297	MPI_Buffer_attach, 56, 488	36
wrong message exchange, 53	MPI_Buffer_detach, 56	37
False matching of collective operations, 299	MPI_BYTE, 43	
Fortran 90	MPI_Cancel, 488	38
copying and sequence problem, 807, 809	MPI_CART_COORDS, 406	39
derived types, 811	MPI_CART_GET, 437	40
heterogeneous communication (unsafe),	MPI_CART_RANK, 406	41
804	MPI_CART_SHIFT, 406, 417, 437	42
invalid KIND, 800	MPI_CART_SUB, 407	43
MPI_TYPE_MATCH_SIZE	MPI_CARTDIM_GET, 417	44
implementation, 803	MPI_CHARACTER, 44	45
overlapping communication and	MPI_Comm_accept, 532, 533	
computation, 823, 824, 826	MPI_Comm_connect, 532, 533	46
register optimization, 814–816	MPI_Comm_create, 326, 343, 344, 346	47
register optimization, 014-010		10

1064 Examples Index

1	MPI_COMM_CREATE_FROM_GROUP, 498,	MPI_Ibarrier, 299–301
2	502	MPI_Ibcast, 249, 302, 303
3	MPI_Comm_create_keyval, 373	MPI_INFO_CREATE, 498
4	MPI_Comm_dup, 345	MPI_INFO_ENV, 482
	MPI_Comm_get_attr, 373	MPI_INFO_SET, 498
5	MPI_Comm_get_parent, 522	MPI_Intercomm_create, 356, 357
6	MPI_Comm_group, 326, 346, 373	MPI_Iprobe, 488
7	MPI_Comm_remote_size, 332	MPI_IRECV, 69–71, 78
8	MPI_Comm_set_attr, 373	MPI_Irecv, 301
9	MPI_COMM_SPAWN, 515	MPI_ISEND, 69–71, 78
10	MPI_Comm_spawn, 515, 522	MPI_NEIGHBOR_ALLGATHER, 413
11	MPI_COMM_SPAWN_MULTIPLE, 520	MPI_NEIGHBOR_ALLTOALL, 417
12	MPI_Comm_spawn_multiple, 520	MPI_Op_create, 233, 234, 244
	MPI_Comm_split, 332, 356, 357	MPI_Open_port, 532, 533
13	MPI_Comm_split_type, 334, 336	MPI_Pack, 175, 176
14	MPI_Compare_and_swap, 616, 618	MPI_Pack_size, 176
15	MPI_DIMS_CREATE, 388, 437	MPI_Parrived, 111
16	MPI_DIST_GRAPH_CREATE, 395	MPI_Pready, 100, 108, 109, 111
17	MPI_Dist_graph_create, 396	MPI_Precv_init, 100, 108, 109, 111
18	MPI_DIST_GRAPH_CREATE_ADJACENT,	MPI_PROBE, 82
19	395	MPI_Psend_init, 100, 108, 109, 111
20	MPI_F_sync_reg, 616	MPI_Publish_name, 532
21	MPI_FILE_CLOSE, 659, 663	MPI_Put, 589, 595, 606, 608, 612, 613
	MPI_FILE_GET_AMODE, 640	MPI_RECV, 43, 44, 52–54, 71, 82, 149
22	MPI_FILE_IREAD, 663	MPI_Recv, 300
23	MPI_FILE_OPEN, 659, 663	MPI_REDUCE, 224, 227
24	MPI_FILE_READ, 659	MPI_Reduce, 227, 228, 233, 234
25	MPI_FILE_SET_ATOMICITY, 702	MPI_REQUEST_FREE, 70
26	MPI_FILE_SET_VIEW, 659, 663	MPI_Request_free, 487
27	MPI_FILE_SYNC, 703	MPI_Rget, 617
28	MPI_Finalize, 487–489	MPI_Rput, 617
29	MPI_FREE_MEM, 449, 450	MPI_Scan, 244
30	MPI_Free_mem, 618	MPI_Scatter, 206
31	MPI_Gather, 176, 196, 197, 201	MPI_Scattery, 206, 207
32	MPI_Gathery, 176, 197–201 MPI_GET, 564, 566	MPI_SEND, 43, 44, 53, 54, 71, 82, 149
	MPI_Get, 605–607, 612, 613	MPI_Send, 164, 167, 168, 175, 300, 301 MPI_SENDRECV, 162, 163, 417
33	MPI_Get_accumulate, 614, 615, 618	MPI_SENDRECV_REPLACE, 406
34	MPI_GET_ADDRESS, 138, 811, 812, 834	MPI_SESSION_FINALIZE, 498, 500, 502
35	MPI_Get_address, 164, 167, 168, 175	MPI_SESSION_GET_NTH_PSET, 500, 502
36	MPI_GET_COUNT, 151	MPI_SESSION_GET_NUM_PSETS, 500, 502
37	MPI_GET_ELEMENTS, 151	MPI_SESSION_INIT, 498, 500, 502
38	MPI_GRAPH_CREATE, 389, 402	MPI_SSEND, 52, 71
39	MPI_GRAPH_NEIGHBORS, 402	MPI_Test_cancelled, 488
40	MPI_GRAPH_NEIGHBORS_COUNT, 402	MPI_TYPE_COMMIT, 147, 162, 163, 564,
41	MPI_Grequest_complete, 626	811, 812
	MPI_Grequest_start, 626	MPI_Type_commit, 164, 167, 168, 175,
42	MPI_Group_excl, 343	196–201, 207, 244
43	MPI_Group_free, 326, 343, 344	MPI_TYPE_CONTIGUOUS, 118, 140, 149,
44	MPI_GROUP_FROM_SESSION_PSET, 498,	151
45	500, 502	MPI_Type_contiguous, 196
46	MPI_Group_incl, 326, 344, 346	MPI_TYPE_CREATE_DARRAY, 136
47	MPI_Iallreduce, 302	MPI_TYPE_CREATE_HVECTOR, 162, 163
48	MPI_Ialltoall, 301	MPI_Type_create_hvector, 164, 167
		·

Examples Index 1065

MPI_TYPE_CREATE_INDEXED_BLOCK,	Nonblocking operations, 69, 70	1
564	message ordering, 71	2
MPI_TYPE_CREATE_RESIZED, 811, 812	progress, 71	3
MPI_TYPE_CREATE_STRUCT, 128, 140,		4
163, 811, 812	Overlapping Communicators, 302	5
MPI_Type_create_struct, 164, 167, 168, 175,		
199, 201, 244	Partitioned Communication	6
MPI_TYPE_CREATE_SUBARRAY, 709	Equal send/recv partitioning, 108	7
MPI_TYPE_EXTENT, 564	Partial completion notification, 111	8
MPI_TYPE_FREE, 564	Send with tasks, 109	9
MPI_Type_get_contents, 169	Simple example, 100	10
MPI_Type_get_envelope, 169	Pipelining nonblocking collective operations,	1:
MPI_TYPE_GET_EXTENT, 162, 163, 566,	302	
568	Profiling interface	12
MPI_Type_get_extent, 164	implementation using the C macro	13
MPI_TYPE_INDEXED, 123, 162	preprocessor, 717	14
MPI_Type_indexed, 164, 167	implementation using weak symbols, 716	15
MPI_TYPE_VECTOR, 119, 162, 163	measurement wrapper, 716	16
	Progression of nonblocking collective	17
MPI_Type_vector, 197, 198, 200, 207	operations, 300	
MPI_Unpack, 175, 176	Transfer and the second	18
MPI_Unpublish_name, 532	Shared memory windows	19
MPI_User_function, 234	MPI_Win_sync, 616	20
MPI_WAIT, 69–71, 78, 663		2
MPI_Wait, 299–301	Threads and MPI, 509	25
MPI_Waitall, 301, 302, 617	Tool information interface	23
MPI_WAITANY, 78	basic usage of performance variables, 743	
MPI_Waitany, 617	listing names of all control variables, 729	24
MPI_WAITSOME, 78	reading the value of a control variable, 732	25
MPI_Win_attach, 618	Topologies, 437	26
MPI_Win_complete, 589, 607, 608, 613	Typemap, 117–119, 123, 128, 136	27
MPI_WIN_CREATE, 564, 566, 568	J. P. C. S. P. C. S. P.	28
MPI_Win_create_dynamic, 618	Virtual topologies, 437	
MPI_Win_detach, 618		29
MPI_WIN_FENCE, 564, 566, 568		30
MPI_Win_fence, 612		3
MPI_Win_flush, 606, 614-616, 618		32
MPI_Win_flush_all, 615		33
MPI_Win_flush_local, 605		34
MPI_WIN_FREE, 566, 568		35
MPI_Win_lock, 595, 605-608		
MPI_Win_lock_all, 616-618		36
MPI_Win_post, 607, 608, 613		3'
MPI_Win_start, 589, 607, 608, 613		38
MPI_Win_sync, 605, 606, 614–616		39
shared memory windows, 616		40
MPI_Win_unlock, 595, 605–608		41
MPI_Win_unlock_all, 617, 618		
MPI_Win_wait, 607, 608, 613		42
mpiexec, 482, 507, 508		43
inpiezee, 402, 901, 900		4
Neighborhood collective communication, 437		4
Non-deterministic program with MPI_Bcast,		46
298		
Non-overtaking messages, 52		4'
1.011 0.0100001116 11100000500, 02		48

# MPI Constant and Predefined Handle Index

2

6

7

10 11

12

13 14

15

16

17

19

20

21

22

23

24

25

27

28

29

30

31

32

33

34

35

36

37

38

39

41

42

43

44

45

46

47

48

This index lists predefined MPI constants and handles, including info keys and values. Underlined page numbers give the location of the primary definition or use of the indexed term.

```
MPI::DOUBLE_COMPLEX, 1037
"access_style", 643
                                                 MPI::F_COMPLEX16, 1037
"accumulate_ops", 544
"accumulate_ordering", 544, 609
                                                 MPI::F_COMPLEX32, 1037
"alloc_shared_noncontig", 549, 550
                                                 MPI::F_COMPLEX4, 1037
                                                 MPI::F_COMPLEX8, 1037
"appnum", 536
"arch", 482, 521
                                                 MPI::INTEGER16, 1037
"argv", 482
                                                 MPI::LONG_DOUBLE_COMPLEX, 1037
                                                 MPI::LONG_LONG, 1037
"cb_block_size", 643
                                                 MPI::REAL16, 1037
"cb_buffer_size", 643
                                                 MPI_2DOUBLE_PRECISION, 226, 851
"cb_nodes", 643
                                                 MPI 2INT, 226, 851
"chunked", 643
                                                 MPI_2INTEGER, 226, 851
"chunked_item", 643
                                                 MPI_2REAL, 226, 851
"chunked_size", 643
                                                 MPI_ADDRESS_KIND, 19, 20, 33, 359, 806,
"collective_buffering", 643
                                                         837, 848
"command", 482
                                                 MPI_AINT, <u>33</u>, 117, 223, 553, 689, 827, 849,
                                                         850, 1043, 1045
"external32", 178, 685, 686, 688-690, 695,
                                                MPI_ANY_SOURCE, 35, 36, 40, 41, 51, 64-67,
        799–801, 804, 1037, 1045
                                                         80-85, 94, 339, 381, 446, 847
                                                 MPI_ANY_TAG, 18, 35, 36, 38, 40, 41, 64-67,
"false", 339, 340, 643
                                                         80, 81, 83-85, 87, 88, 94, 96, 97, 339,
"file", 482, 521
                                                         847, 1039
"file_perm", 643
                                                 MPI_APPNUM, 536, 854
"filename", 643
                                                 MPI_ARGV_NULL, 19, 515, 516, 520, 806, 856
                                                 MPI_ARGVS_NULL, 19, 519, 806, 856
"host", 482, 521
                                                 "mpi_assert_allow_overtaking", 340, 1033
"hwloc://L3Cache", 494
                                                 "mpi_assert_exact_length", 340, 1033
                                                 "mpi_assert_no_any_source", 339, 1033
"internal", 685, 686, 696
"io_node_list", 644
                                                 "mpi_assert_no_any_tag", 339, 1033
                                                 MPI_ASYNC_PROTECTS_NONBLOCKING,
"ip_address", 532
                                                          19, 616, 780, 781, 783, 785, 788, 795,
"ip_port", 531
                                                         797, 817, 848, 1042
"maxprocs", 482, 483
                                                 MPI_BAND, 222, 224, 852
                                                 MPI_BOR, 222, 224, 852
"mpi://", 494
"mpi://SELF", 494, 495, 634
                                                 MPI_BOTTOM, 10, 19, 20, 39, 107, 137, 152,
"mpi://WORLD", 494, 495, 500
                                                         153, 186, 392, 394, 517, 553, 557, 782,
MPI::_LONG_LONG, 1037
                                                         784, 791, 806, 810, 813-819, 822,
MPI::BOOL, 1037
                                                         834-836, 841, 847, 1049
MPI::COMPLEX, 1037
                                                 MPI_BSEND_OVERHEAD, 58, 847
```

```
MPI_BXOR, 222, 224, 852
                                               MPI_COMM_TYPE_HW_GUIDED, 333, 334,
MPI_BYTE, 31, 32, 43-45, 178, 223, 632, 685,
                                                       851, 1032
        686, 689, 700, 842, 849, 850, 1045
                                               MPI_COMM_TYPE_HW_UNGUIDED, 335,
MPI_C_BOOL, 32, 223, 689, 849, 1037, 1043,
                                                       337, 851, 1032
                                               MPI_COMM_TYPE_SHARED, 333, 334, 851,
        1045
MPI_C_COMPLEX, 32, 223, 689, 849, 1037,
                                                       1039
                                               MPI_COMM_WORLD, 18, 26, 34, 307,
        1043, 1045
MPI_C_DOUBLE_COMPLEX, <u>32</u>, <u>223</u>, <u>689</u>,
                                                       309-312, 320, 321, 334, 336, 337, 341,
                                                       344, 352, 377, 387, 445, 446, 454, 465,
        849, 1043, 1045
MPI_C_FLOAT_COMPLEX, 32, 223, 689, 849,
                                                       479-483, 485-489, 491, 505, 506,
                                                       512-514, 518, 520, 534-538, 684, 706,
        1043, 1045
                                                       707, 730, 739, 777, 829, 841, 851,
MPI_C_LONG_DOUBLE_COMPLEX, 32, 223,
        689, 849, 1043, 1045
                                                       1033, 1047
                                                                                              12
                                               MPI_COMPLEX, 31, 223, 688, 689, 798, 850
MPI_CART, 397, 853
                                                                                              13
                                               MPI_COMPLEX16, 33, 223, 690, 850
MPI_CHAR, 32, 45, 128, 225, 689, 724, 849,
                                                                                              14
        1042, 1043
                                               MPI_COMPLEX32, 33, 223, 690, 850
                                                                                              15
MPI_CHARACTER, 31, 44, 45, 225, 689, 850
                                               MPI_COMPLEX4, 33, 223, 690, 850
                                               MPI_COMPLEX8, <u>33</u>, 223, 690, 850
                                                                                              16
MPI_COMBINER_CONTIGUOUS, 155, 159, 855
                                               MPI_CONGRUENT, <u>321</u>, <u>351</u>, <u>851</u>
                                                                                              17
MPI_COMBINER_DARRAY, 155, 161, 855
                                               MPI_CONVERSION_FN_NULL, 695, 853
MPI_COMBINER_DUP, 155, 159, 855
                                                                                              18
MPI_COMBINER_F90_COMPLEX, 155, 161,
                                               MPI_COUNT, 33, 117, 223, 231, 689, 724, 827,
                                                                                              19
                                                       849, 850, 1038
                                                                                              20
MPI_COMBINER_F90_INTEGER, 155, 161, 855
                                               MPI_COUNT_KIND, 19, 20, 33, 848
                                                                                              21
MPI_COMBINER_F90_REAL, 155, 161, 855
                                               MPI_CXX_BOOL, 33, 223, 689, 690, 850, 1037
                                                                                              22
                                               MPI_CXX_DOUBLE_COMPLEX, 33, 223, 689,
MPI_COMBINER_HINDEXED, 23, 155, 160,
                                                                                              23
                                                       690, 850, 1037
MPI_COMBINER_HINDEXED_BLOCK, 155,
                                               MPI_CXX_FLOAT_COMPLEX, 33, 223, 689,
                                                                                              24
        160, 855, 1039
                                                       690, 850, 1037
MPI_COMBINER_HINDEXED_INTEGER, 23,
                                               MPI_CXX_LONG_DOUBLE_COMPLEX, 33,
                                                                                              26
        776, 1038
                                                       223, 689, 690, 850, 1037
                                                                                              27
MPI_COMBINER_HVECTOR, 23, 155, 160, 855
                                               MPI_DATATYPE_NULL, 147, 852
                                                                                              28
MPI_COMBINER_HVECTOR_INTEGER, 23,
                                               MPI_DISPLACEMENT_CURRENT, 645, 856,
                                                                                              29
        776, 1038
                                                       1048
MPI_COMBINER_INDEXED, 155, 160, 855
                                               MPI_DIST_GRAPH, 397, 853, 1044
MPI_COMBINER_INDEXED_BLOCK, 155, 160,
                                               MPI_DISTRIBUTE_BLOCK, 133, 134, 856
                                               MPI_DISTRIBUTE_CYCLIC, 133, 134, 856
MPI_COMBINER_NAMED, 154, 155, 159, 855
                                               MPI_DISTRIBUTE_DFLT_DARG, 133, 134, 856
                                                                                              33
MPI_COMBINER_RESIZED, 155, 162, 855
                                               MPI_DISTRIBUTE_NONE, 133, 134, 856
                                                                                              34
MPI_COMBINER_STRUCT, 23, 155, 160, 855
                                               MPI_DOUBLE, 32, 223, 689, 724, 734, 735,
                                                                                              35
MPI_COMBINER_STRUCT_INTEGER, 23, 776,
                                                       797, 849
                                                                                              36
        1038
                                               MPI_DOUBLE_COMPLEX, 32, 223, 688, 689,
                                                                                              37
MPI_COMBINER_SUBARRAY, 155, 161, 855
                                                       798, 850
                                                                                              38
MPI_COMBINER_VECTOR, 155, 159, 855
                                               MPI_DOUBLE_INT, 226, 227, 851
MPI_COMM_DUP_FN, 23, 362, 853, 1041
                                               MPI_DOUBLE_PRECISION, 31, 223, 689, 798,
MPI_COMM_NULL, 309, 325, 326, 328-330,
        333-335, 338, 339, 355, 377, 387, 389,
                                               MPI_DUP_FN, 23, 362, 770, 854
        517, 518, 538, 539, 830, 852, 1046
                                               MPI_ERR_ACCESS, 463, 637, 707, 846
                                                                                              42
MPI_COMM_NULL_COPY_FN, 23, 362, 782,
                                               MPI_ERR_AMODE, 463, 635, 707, 846
                                                                                              43
        836, 853, 1041
                                               MPI_ERR_ARG, 463, 845
                                                                                              44
MPI_COMM_NULL_DELETE_FN, 23, 362, 853
                                               MPI_ERR_ASSERT, 463, 600, 846
                                                                                              45
MPI_COMM_PARENT, 377
                                               MPI_ERR_BAD_FILE, 463, 707, 846
                                               MPI_ERR_BASE, 449, 463, 600, 846
                                                                                              46
MPI_COMM_SELF, 25, 309, 328, 341, 359, 377,
        451, 480, 481, 486, 488, 490, 538, 634,
                                               MPI_ERR_BUFFER, 463, 845
                                                                                              47
        777, 851, 1033, 1044
                                               MPI_ERR_COMM, 463, 845
```

Done

```
MPI_ERR_CONVERSION, 463, 695, 707, 846
                                                                MPI_ERR_UNSUPPORTED_OPERATION, 464,
         2
               MPI_ERR_COUNT, 463, 845
                                                                        707, 846
                                                                MPI_ERR_VALUE_TOO_LARGE, 464, 693,
              MPI_ERR_DIMS, 463, 845
                                                                        1032
               MPI_ERR_DISP, 463, 600, 846
              MPI_ERR_DUP_DATAREP, 463, 692, 707, 846
                                                                MPI_ERR_WIN, 464, 600, 846
                                                                MPI_ERRCODES_IGNORE, 19, 517, 806, 856
               MPI_ERR_FILE, 463, 707, 846
         6
               MPI_ERR_FILE_EXISTS, 463, 707, 846
                                                                MPI_ERRHANDLER_NULL, 460, 852
               MPI_ERR_FILE_IN_USE, 463, 637, 707, 846
                                                                MPI_ERROR, <u>37</u>, 67, 246, 574, 832, 848, 1034,
               MPI_ERR_GROUP, 463, 845
              MPI_ERR_IN_STATUS, 37, 39, 67, 74, 76, 453,
                                                                MPI_ERRORS_ABORT, 451, 481, 521, 1033
         10
                       461, 463, 625, 650, 846
                                                                "mpi_errors_abort", 521, 1034
               MPI_ERR_INFO, 463, 846
                                                                MPI_ERRORS_ARE_FATAL, 451, 452, 468, 521,
         11
              MPI_ERR_INFO_KEY, 463, 473, 846
                                                                        599, 706, 848, 1033
        12
                                                                "mpi_errors_are_fatal", 521, 1034
               MPI_ERR_INFO_NOKEY, 463, 473, 846
        13
               MPI_ERR_INFO_VALUE, 463, 473, 846
                                                                MPI_ERRORS_RETURN, 451, 452, 468, 505,
        14
               MPI_ERR_INTERN, 452, 463, 845
                                                                        521, 706, 841, 848
         15
               MPI_ERR_IO, 463, 707, 846
                                                                "mpi_errors_return", 521, 1034
                                                                MPI_F08_STATUS_IGNORE, 833, 857, 1041
               MPI_ERR_KEYVAL, 373, 463, 846
         17
               MPI_ERR_LASTCODE, 462, 464-466, 766, 847
                                                                MPI_F08_STATUSES_IGNORE, 833, 857, 1041
               MPI_ERR_LOCKTYPE, 463, 600, 846
                                                                MPI_F_ERROR, <u>832</u>, 848, 1031
               MPI_ERR_NAME, 463, 531, 846
                                                                MPI_F_SOURCE, 832, 848, 1031
         19
                                                                MPI_F_STATUS_IGNORE, 832, 857
               MPI_ERR_NO_MEM, 448, 463, 846
        20
               MPI_ERR_NO_SPACE, 463, 707, 846
                                                                MPI_F_STATUS_SIZE, 19, 832, 848, 1031
        21
              MPI_ERR_NO_SUCH_FILE, 463, 637, 707, 846
                                                                MPI_F_STATUSES_IGNORE, 832, 857
        ^{22}
               MPI_ERR_NOT_SAME, 463, 707, 846
                                                                MPI_F_TAG, 832, 848, 1031
        ^{23}
               MPI_ERR_OP, 464, 600, 845
                                                                MPI_FILE_NULL, 636, 706, 707, 852
        ^{24}
               MPI_ERR_OTHER, 462, 464, 845
                                                                MPI_FLOAT, <u>32</u>, 128, 221, 223, 687, 689, 849
               MPI_ERR_PENDING, 74, 464, 845
                                                                MPI_FLOAT_INT, 15, 226, 227, 851
              MPI_ERR_PORT, 464, 528, 846
                                                                MPI_GRAPH, 397, 853
        26
                                                                MPI_GROUP_EMPTY, 308, 314, 315, 325, 326,
               MPI_ERR_PROC_ABORTED, 464, 505, 846,
        27
                       1033
                                                                        328, 338, 355, 852
        28
               MPI_ERR_QUOTA, 464, 707, 846
                                                                MPI_GROUP_NULL, <u>308</u>, <u>318</u>, <u>319</u>, <u>852</u>
        29
               MPI_ERR_RANK, 464, 600, 845
                                                               MPI_HOST, 445, 851
        30
              MPI_ERR_READ_ONLY, 464, 707, 846
                                                                "mpi_hw_resource_type", 334, 335, 1032
        31
               MPI_ERR_REQUEST, 464, 845
                                                                MPI_IDENT, <u>312</u>, <u>321</u>, <u>851</u>
              MPI_ERR_RMA_ATTACH, 464, 600, 846
                                                                MPI_IN_PLACE, 19, 186, 216, 785, 806, 847
#-other 3
                                                               MPI_INFO, 272 \mpicdecl{MPI\_Info}
               MPI_ERR_RMA_CONFLICT, 464, 600, 846
               MPI_ERR_RMA_FLAVOR, 464, 551, 600, 846
                                                                MPI_INFO_ENV, 478, 482, 483, 491, 851, 1040
#-error! 34
              MPI_ERR_RMA_RANGE, 464, 600, 846
                                                                MPI_INFO_NULL, 395, 448, 477, 516, 526, 635,
        35
               MPI_ERR_RMA_SHARED, 464, 600, 846
                                                                        637, 646, 852
              MPI_ERR_RMA_SYNC, 464, 600, 846
                                                                "mpi_initial_errhandler", 481, 482, 521, 1034
        37
              MPI_ERR_ROOT, 464, 845
                                                                MPI_INT, 15, <u>32</u>, 116, 222, 687–689, 723, 724,
              MPI_ERR_SERVICE, 464, 531, 846
                                                                        727, 733, 737, 797, 841, 843, 849
               MPI_ERR_SESSION, 464
                                                                MPI_INT16_T, 32, 223, 689, 849, 1043, 1045
               MPI_ERR_SIZE, 464, 600, 846
                                                                MPI_INT32_T, <u>32</u>, 223, 689, 724, 849, 1043,
               MPI_ERR_SPAWN, 464, 516, 517, 846
                                                                        1045
        41
               MPI_ERR_TAG, 464, 845
                                                                MPI_INT64_T, <u>32</u>, 223, 689, 724, 849, 1043,
        42
              MPI_ERR_TOPOLOGY, 464, 845
                                                                        1045
        43
               MPI_ERR_TRUNCATE, 464, 845
                                                                MPI_INT8_T, <u>32</u>, 223, 689, 849, 1043, 1045
        44
               MPI_ERR_TYPE, 154, 157, 464, 707, 845
                                                                MPI_INTEGER, <u>31</u>, 42, 43, 223, 689, 797, 798,
        45
               MPI_ERR_UNKNOWN, 462, 464, 845
                                                                        843, 850
        ^{46}
               MPI_ERR_UNSUPPORTED_DATAREP, 464,
                                                                MPI_INTEGER1, <u>32</u>, 223, 690, 850
         47
                       707, 846
                                                                MPI_INTEGER16, 223, 690, 850
                                                                MPI_INTEGER2, <u>32</u>, <u>223</u>, <u>688</u>, <u>690</u>, <u>850</u>
```

 $^{23}$ 

MPI_INTEGER4, <u>32</u> , <u>223</u> , <u>690</u> , <u>850</u>	MPI_MODE_NOSTORE, 598, 599, 855
MPI_INTEGER8, <u>33</u> , <u>223</u> , <u>690</u> , <u>802</u> , <u>850</u>	MPI_MODE_NOSUCCEED, 598, 599, 855
MPI_INTEGER_KIND, 19, 848	MPI_MODE_RDONLY, 634, 635, 640, 855
MPI_IO, 445, 446, 851	MPI_MODE_RDWR, 634, 635, 855
MPI_KEYVAL_INVALID, <u>363</u> , 364, 365, 847	MPI_MODE_SEQUENTIAL, 634, 635, 638, 645,
MPI_LAND, 222, 223, 852	650, 658, 674, 699, 855, 1048
MPI_LASTUSEDCODE, 465, 854	MPI_MODE_UNIQUE_OPEN, 634, 635, 855
MPI_LB, 23, 776, 1038	MPI_MODE_WRONLY, 634, 635, 855
MPI_LOCK_EXCLUSIVE, 592, 847	MPI_NO_OP, 544, 571–573, 852, 1035
MPI_LOCK_SHARED, 592, 593, 847	MPI_NULL_COPY_FN, 23, 362, 770, 854
MPI_LOGICAL, <u>31</u> , 223, 689, 850	MPI_NULL_DELETE_FN, 23, 363, 770, 854
MPI_LONG, <u>32</u> , 222, 689, 849	MPI_OFFSET, 33, 223, 689, 849, 850, 1043,
MPI_LONG_DOUBLE, <u>32</u> , 223, 689, 849	1045
MPI_LONG_DOUBLE_INT, 226, 851	MPI_OFFSET_KIND, 19, <u>20</u> , 33, 701, 806, 848
MPI_LONG_INT, 226, 227, 851	MPI_OP_NULL, 233, 852
MPI_LONG_LONG, <u>32</u> , 223, 849, 1045	MPI_ORDER_C, 18, 130, 133, 134, 856
MPI_LONG_LONG_INT, 32, 223, 689, 849,	MPI_ORDER_FORTRAN, 18, 130, 133, 134,
· —· · · · ·	
1045	856
MPI_LOR, 222, 223, 852	MPI_PACKED, 15, 31, 32, 42, 43, 172–174, 178,
MPI_LXOR, 222, 223, 852	688, 689, 842, 849, 850
MPI_MAX, 221–223, 244, 852	MPI_PROC_NULL, 30, 34, 36, 81, 84, 87, 88,
MPI_MAX_DATAREP_STRING, 19, 647, 692,	<u>96,</u> 97, 188, 191, 193, 195, 204, 206,
848	222, 311, 406, 410, 445, 446, 550, 551,
MPI_MAX_ERROR_STRING, 19, 461, 466, 848	560, 847, 1039, 1046, 1048
MPI_MAX_FROM_GROUP_STRINGTAG, 355	MPI_PROD, 222, 223, 852
MPI_MAX_FROM_GROUP_TAG, 338, 848	MPI_REAL, <u>31</u> , 42, 223, 688, 689, 797, 798,
MPI_MAX_INFO_KEY, 19, 463, 471, 474, 475,	804, 850
848	MPI_REAL16, <u>32</u> , 223, 690, 850
MPI_MAX_INFO_VAL, 19, 463, 471, 848	MPI_REAL2, <u>32</u> , 223, 690, 850
MPI_MAX_LIBRARY_VERSION_STRING, 19,	MPI_REAL4, <u>32</u> , 223, 690, 797, 802, 850
444, 848, 1038	MPI_REAL8, <u>32</u> , 223, 690, 797, 850, 1043
MPI_MAX_OBJECT_NAME, 19, 376-379, 848,	MPI_REPLACE, 568, 569, 571, 573, 616, 852,
1040, 1046	1044, 1048
MPI_MAX_PORT_NAME, 19, 526, 848	MPI_REQUEST_NULL, 67-70, 73-76, 624, 852
MPI_MAX_PROCESSOR_NAME, 19, 447, 848,	MPI_ROOT, 188, 847
1047	MPI_SEEK_CUR, 666, 674, 856
MPI_MAX_PSET_NAME_LEN, 497, 848	MPI_SEEK_END, 666, 674, 856
MPI_MAXLOC, 222, 225, 226, 229, 852	MPI_SEEK_SET, 666, 667, 674, 856
MPI_MESSAGE_NO_PROC, <u>84</u> , 87, 88, 97,	MPI_SESSION_NULL, 494, 852
847, 1039	"mpi_shared_memory", 334, 1032
MPI_MESSAGE_NULL, <u>84</u> , 86–88, 852, 1039	MPI_SHORT, 32, 222, 689, 849
MPI_MESSAGE_PROC_NULL, 84	MPI_SHORT_INT, 226, 851
MPI_MIN, 222, 223, 852	MPI_SIGNED_CHAR, <u>32</u> , 223, 225, 689, 849,
"mpi_minimum_memory_alignment", 448, 547,	1045
550, 1033	MPI_SIMILAR, <u>312</u> , <u>321</u> , <u>351</u> , <u>851</u>
MPI_MINLOC, 222, 225, 226, 229, 852	"mpi_size", 494, 498, 502
MPI_MODE_APPEND, 634, 635, 855	MPI_SOURCE, <u>37</u> , 246, 832, 848, 1034, 1041
MPI_MODE_CREATE, 634, 635, 644, 855	MPI_STATUS_IGNORE, 10, 19, 39, 40, 623,
MPI_MODE_DELETE_ON_CLOSE, 634–636,	650, 784, 806, 832, 833, 841, 856, 857,
855	1039
MPI_MODE_EXCL, 634, 635, 855	MPI_STATUS_SIZE, 19, <u>37</u> , 786, 848, 1041
MPI_MODE_NOCHECK, 593, 598, 599, 855	MPI_STATUSES_IGNORE, 18, 19, <u>39</u> , 40, 623,
MPI_MODE_NOCHECK, 595, 598, 599, 855 MPI_MODE_NOPRECEDE, 588, 598, 599, 855	$10111_{-3}1_{-1}$
MPI_MODE_NOPUT, 598, 599, 855	625, 806, 832, 833, 856, 857

PR400

```
MPI_SUBARRAYS_SUPPORTED, 19, 780, 781,
                                                  MPI_T_ERR_PVAR_NO_ATOMIC, 742, 768,
2
             784–788, 792–795, 807–809, 848, 1040
                                                          847
     MPI_SUBVERSION, 19, 444, 857
                                                  MPI_T_ERR_PVAR_NO_STARTSTOP, 740,
3
     MPI\_SUCCESS, 22, 24, 67, 74, 76, 362-364,
                                                          741, 768, 847
             366, 367, 370, 371, 388, 461–463,
                                                  MPI_T_ERR_PVAR_NO_WRITE, 742, 768, 847
             467–469, 481, 517, 695, 720, 729, 738,
                                                  MPI_T_PVAR_ALL_HANDLES, 740, 741–743,
6
             740-742, 748, 752, 753, 757, 764, 766,
             768, 770, 845, 1033, 1034
                                                  MPI_T_PVAR_CLASS_AGGREGATE, 734, 735,
     MPI_SUM, 222, 223, 568, 841, 852
     MPI_T_BIND_MPI_COMM, 721, 858
                                                  MPI_T_PVAR_CLASS_COUNTER, 734, 858
     MPI_T_BIND_MPI_DATATYPE, 721, 858
10
                                                  MPI_T_PVAR_CLASS_GENERIC, 735, 858
     MPI_T_BIND_MPI_ERRHANDLER, 721, 858
                                                  MPI_T_PVAR_CLASS_HIGHWATERMARK,
11
     MPI_T_BIND_MPI_FILE, 721, 858
                                                          734, 858
12
     MPI_T_BIND_MPI_GROUP, 721, 858
                                                  MPI_T_PVAR_CLASS_LEVEL, 733, 858
13
     MPI_T_BIND_MPI_INFO, 721, 858
                                                  MPI_T_PVAR_CLASS_LOWWATERMARK,
14
     MPI_T_BIND_MPI_MESSAGE, 721, 858
                                                          734, 858
15
     MPI_T_BIND_MPI_OP, 721, 858
                                                  MPI_T_PVAR_CLASS_PERCENTAGE, 734, 858
     MPI_T_BIND_MPI_REQUEST, 721, 858
                                                  MPI_T_PVAR_CLASS_SIZE, 734, 858
17
     MPI_T_BIND_MPI_SESSION, 721
                                                  MPI_T_PVAR_CLASS_STATE, 733, 858
     MPI_T_BIND_MPI_WIN, <u>721</u>, 858
                                                  MPI_T_PVAR_CLASS_TIMER, 735, 858
     MPI_T_BIND_NO_OBJECT, 721, 728, 730,
                                                  MPI_T_PVAR_HANDLE_NULL, 740, 857
19
                                                  MPI_T_PVAR_SESSION_NULL, 738, 857
             737, 739, 752, 753, 858
20
     MPI_T_CB_REQUIRE_ASYNC_SIGNAL_SAFE,
                                                  MPI_T_SCOPE_ALL, <u>728</u>, 858
21
                                                  MPI_T_SCOPE_ALL_EQ, 728, 732, 858
             748, 749, 859
^{22}
     MPI_T_CB_REQUIRE_MPI_RESTRICTED,
                                                  MPI_T_SCOPE_CONSTANT, 728, 858
23
             <u>748</u>, 748, <u>749</u>, 859
                                                  MPI_T_SCOPE_GROUP, 728, 858
^{24}
     MPI_T_CB_REQUIRE_NONE, 748, 859
                                                  MPI_T_SCOPE_GROUP_EQ, 728, 732, 858
     MPI_T_CB_REQUIRE_THREAD_SAFE, 748,
                                                  MPI_T_SCOPE_LOCAL, 728, 858
                                                  MPI_T_SCOPE_READONLY, 728, 858
             749, 859
26
                                                  MPI_T_SOURCE_ORDERED, 747, 859
     MPI_T_CVAR_HANDLE_NULL, 731, 857
27
     MPI_T_ENUM_NULL, 727, 737, 752, 857
                                                  MPI_T_SOURCE_UNORDERED, 747, 859
28
     MPI_T_ERR_CANNOT_INIT, 768, 847
                                                  MPI_T_VERBOSITY_MPIDEV_ALL, 720, 721,
29
     MPI_T_ERR_CVAR_SET_NEVER, 732, 768,
30
                                                  MPI_T_VERBOSITY_MPIDEV_BASIC, 721,
31
     MPI_T_ERR_CVAR_SET_NOT_NOW, 732,
                                                  MPI_T_VERBOSITY_MPIDEV_DETAIL, 721,
             768, 847
     MPI_T_ERR_INVALID, <u>768</u>, 847, 1036
33
                                                  MPI_T_VERBOSITY_TUNER_ALL, 721, 857
     MPI_T_ERR_INVALID_HANDLE, 739, 757,
34
                                                  MPI_T_VERBOSITY_TUNER_BASIC, 721, 857
             768, 847
35
     MPI_T_ERR_INVALID_INDEX, 23, 748, 752,
                                                  MPI_T_VERBOSITY_TUNER_DETAIL, 721,
36
             768, 773, 847, 1033
37
     MPI_T_ERR_INVALID_ITEM, 23, <u>768</u>, 773,
                                                  MPI_T_VERBOSITY_USER_ALL, 721, 857
38
                                                  MPI_T_VERBOSITY_USER_BASIC, 720, 721,
             847, 1033
     MPI_T_ERR_INVALID_NAME, 729, 738, 753,
39
             764, 768, 847, 1036
                                                  MPI_T_VERBOSITY_USER_DETAIL, 720, 721,
40
     MPI_T_ERR_INVALID_SESSION, 768, 847
                                                          857
41
     MPI_T_ERR_MEMORY, 768, 847
                                                  MPI_TAG, 37, 246, 832, 848, 1034, 1041
42
     MPI_T_ERR_NOT_ACCESSIBLE, 749, 750,
                                                  MPI_TAG_UB, 34, 445, 837, 840, 851
43
                                                  MPI_THREAD_FUNNELED, 483, 855
             768, 847
44
     MPI_T_ERR_NOT_INITIALIZED, 768, 847
                                                  "MPI_THREAD_FUNNELED", 493
45
     MPI_T_ERR_NOT_SUPPORTED, 748, 768,
                                                  MPI_THREAD_MULTIPLE, 483, 484, 486, 855,
^{46}
47
     MPI_T_ERR_OUT_OF_HANDLES, 768, 847
                                                  "MPI_THREAD_MULTIPLE", 493
     MPI_T_ERR_OUT_OF_SESSIONS, 768, 847
                                                  MPI_THREAD_SERIALIZED, 483, 855
```

"MPI_THREAD_SERIALIZED", 493	MPI_WTIME_IS_GLOBAL, 445, 446, 470, 837,	1
MPI_THREAD_SINGLE, 483-485, 493, 855	851	2
"MPI_THREAD_SINGLE", 493	"mpix://UNIVERSE", 494	3
"mpi_thread_support_level", $493$		4
MPI_TYPE_DUP_FN, <u>370</u> , <u>853</u>	"native", 685, 686, 695, 696	5
MPI_TYPE_NULL_COPY_FN, 370, 853	"nb_proc", 644	
MPI_TYPE_NULL_DELETE_FN, 370, 853,	"no_locks", 544, 556	6
1041	"none", 609	7
MPI_TYPECLASS_COMPLEX, 803, 856	"num_io_nodes", 644	8
MPI_TYPECLASS_INTEGER, 803, 856		9
MPI_TYPECLASS_REAL, 803, 856	"path", 521	10
MPI_UB, 4, 23, 776, 1038	"random", 643	11
MPI_UINT16_T, <u>32</u> , 223, 689, 849, 1043, 1045	"rar", 609	12
MPI_UINT32_T, <u>32</u> , 223, 689, 724, 849, 1043,	"raw", 609	13
1045	"read_mostly", 643	14
MPI_UINT64_T, <u>32</u> , 223, 689, 724, 849, 1043,	"read_once", 643	
1045	"reverse_sequential", 643	15
MPI_UINT8_T, <u>32</u> , 223, 689, 849, 1043, 1045	reverse_sequential , 045	16
MPI_UNDEFINED, 21, 38, 39, 56, 73, 74, 76,	"same_disp_unit", 544, 1036	17
77, 140, 143, 146, 151, 175, 310, 311,	"same_op", 544	18
329, 330, 333, 397, 408, 409, 687, 693,	"same_op_no_op", 544	19
799, 847, 1039, 1045	"same_size", 544, 1035	20
MPI_UNEQUAL, <u>312</u> , <u>321</u> , <u>351</u> , <u>851</u>	"sequential", 643	
MPI_UNIVERSE_SIZE, 512, 534, 535, 854	"soft", 482, 516, 521	21
MPI_UNSIGNED, <u>32</u> , 222, 689, 724, 733–735,	"striping_factor", 644	22
849	"striping_unit", 644	23
MPI_UNSIGNED_CHAR, <u>32</u> , <u>223</u> , <u>225</u> , <u>689</u> , <u>849</u>	striping_unit, 044	24
MPI_UNSIGNED_LONG, <u>32</u> , <u>223</u> , <u>689</u> , <u>724</u> , <u>734</u> ,	"thread_level", 482	25
735, 849	"true", 339, 340, 556, 643	26
MPI_UNSIGNED_LONG_LONG, 32, 223, 689,	,	27
724, 734, 735, 849, 1045	"war", 609	28
MPI_UNSIGNED_SHORT, <u>32</u> , <u>222</u> , <u>689</u> , <u>849</u>	"waw", 609	
MPI_UNWEIGHTED, 19, 392, 394-396, 403,	"wdir", 482, 521	<sub>30</sub> #-other
405, 806, 856, 1038, 1044	"write_mostly", 643	
MPI_VAL, 16, 829	"write_once", 643	з1 #-error!
MPI_VERSION, 19, 444, 857	Are these constants really new constants?	
MPI_WCHAR, <u>32</u> , 225, 379, 688, 689, 849, 1045	+ = referenced in a new change-log entry	
MPI_WEIGHTS_EMPTY, 19, 392, 394, 806,	+ MPI_COMM_TYPE_HW_GUIDED	
856, 1038	+ MPI_COMM_TYPE_HW_UNGUIDED	
MPI_WIN_BASE, 556, 840, 854	+ MPI_ERRORS_ABORT	
MPI_WIN_CREATE_FLAVOR, 556, 854	+ MPI_ERR_PROC_ABORTED	
MPI_WIN_DISP_UNIT, 556, 854	- MPI_ERR_SESSION> Done in PR461	
MPI_WIN_DUP_FN, <u>366</u> , 853	+ MPI_ERR_VALUE_TOO_LARGE	
MPI_WIN_FLAVOR_ALLOCATE, 557, 854	+ MPI_F_ERROR	
MPI_WIN_FLAVOR_CREATE, 557, 854	+ MPI_F_SOURCE	
MPI_WIN_FLAVOR_DYNAMIC, 557, 854	+ MPI_F_STATUS_SIZE Done	
MPI_WIN_FLAVOR_SHARED, 551, 557, 854	+ MPI_F_TAG	NIT)
MPI_WIN_MODEL, 556, 583, 854	( MPI_INFO WRONG !!!! and removed: DO MPI_MAX_FROM_GROUP_STRINGTAG This	Done
MPI_WIN_NULL, 555, 852	MPI_MAX_FROM_GROUP_TAG or the	
MPI_WIN_NULL_COPY_FN, <u>366</u> , <u>853</u>	+ MPI_MAX_PSET_NAME_LEN	nat one????
MPI_WIN_NULL_DELETE_FN, 367, 853	- MPI_MESSAGE_PROC_NULL> use constskip	- Done in PR449
MPI_WIN_SEPARATE, 557, 582, 583, 602, 854	- MPI_SESSION_NULL -> Done in PR461	
MPI_WIN_SIZE, 556, 854	- MPI_T_BIND_MPI_SESSION	
MPI_WIN_UNIFIED, 557, 583, 603, 611, 854	- MPI_T_CB_REQUIRE_ASYNC_SIGNAL_SAFE	
	- MPI_T_CB_REQUIRE_MPI_RESTRICTED	
	- MPI_T_CB_REQUIRE_NONE	
Unofficial Draft for	r (- MPI_T_CB_REQUIRE_THREAD_SAFE	
	- MPI_T_ERR_NOT_ACCESSIBLE	
	- MPI_T_ERR_NOT_SUPPORTED	
	- MPI_T_SOURCE_ORDERED - MPI_T_SOURCE_UNORDERED	
	- MILITIZOONOE ONONDEKED	

#### MPI Declarations Index

1 2

10

11 12

13

14

15

16

17

18

19

20

23

24

25

26

27

28

29

30

31

32

33

34

35

36

37

38

39

40

41

42

43

44

45

46

47

#-other

#-error!

C types

primary

Fortran

Done

PR486

types.

in

#-update10 22

The primary

should also

be used as

This index refers to declarations needed in C and Fortran, such as address kind integers, handles, etc. The underlined page numbers is the "main" reference (sometimes there are more than one when key concepts are discussed in multiple areas). Fortran defined types are shown as  $\mathsf{TYPE}(name)$ .

```
MPI_Aint, 20, 20, 21, 33, 117, 120, 123, 127,
         137-139, 142-145, 155, 178-180, 543,
         546, 548, 552, 553, 556, 560, 563, 567,
         569, 572–574, 576, 577, 579, 687, 692,
         747, 806, 837, 849, 859
MPI_Comm, 16, 30, 312, 319, 320, 322-324,
         327, 329, 332, 338, 340, 341, 350, 351,
         353, 355, 361, 364, 365, 496, 851, 852,
         859, 860
TYPE(MPI_Comm), 793, 851, 852, 860
\mathsf{MPI\_Count},\ \underline{20},\ 21,\ 33,\ 746,\ 747,\ 849,\ 859,\ \underline{1038}
MPI_Datatype, 117, 370, 815, 849–852, 859, 860
TYPE(MPI_Datatype), 849-852, 860
MPI_Errhandler, 453, 454-460, 830, 848, 852,
         859, 860
TYPE(MPI_Errhandler), 848, 852, 860
MPI_F08_status, 832, 857, 859, 1041
MPI_File, 457, 458, 633, 636-639, 641, 642,
         644, 646, 650-656, 658-670, 672-674,
         676-683, 687, 697, 698, 830, 852, 859,
TYPE(MPI_File), 852, 860
MPI_Fint, 829, 857, 859, 1045
MPI_Group, <u>310</u>, <u>311–316</u>, <u>318</u>, <u>351</u>, <u>496</u>, <u>557</u>,
         588, 589, 639, 830, 852, 859, 860
TYPE(MPI_Group), 852, 860
MPI_Info, 447, 471, 472–477, 494, 498, 513,
         516, 518, 525, 529-531, 538, 558, 633,
         636, 641, 642, 644, 772, 830, 851, 852,
         859, 860, 1048
TYPE(MPI_Info), 851, 852, 860
MPI_Message, 83, 830, 847, 852, 859, 860, 1039
TYPE(MPI_Message), 847, 852, 860
MPI_Offset, 20, 20, 21, 33, 637-639, 644, 646,
         650-656, 665-667, 674, 676, 678, 693,
         701, 747, 829, 849, 859
MPI_Op, 220, 229, 232, 234, 236-239, 241, 243,
         244, 264-266, 268-270, 289-291,
```

293-295, 567, 569, 572, 577, 579, 830,

852, 859, 860

```
TYPE(MPI_Op), 852, 860
MPI_Request, 60-65, 67, 68, 69, 72-75, 77, 79,
         88-95, 102-106, 461, 622, 625,
         653-656, 662-665, 669, 670, 808, 830,
         852, 859, 860
TYPE(MPI_Request), 852, 860
MPI_Session, 459, 830, 852, 859, 860
TYPE(MPI_Session), 860
MPI_Status, 34, 37, 39-41, 67, 68, 72-75, 77,
         79-81, 83, 85, 89, 150, 623, 628, 629,
         650-653, 658-661, 668, 669, 672, 673,
         677, 679–683, 783, 831–834, 856, 859,
         860, 1034, 1038, 1041
TYPE(MPI_Status), 37, 793, 832-834, 856, 860,
         1031, 1034, 1041
MPI_T_cb_safety, 859
MPI_T_cvar_handle, 730, 731, 857
MPI_T_enum, <u>724</u>, 725, 726, 736, 750, 857
MPI_T_event_instance, 756
MPI_T_event_registration, 753
MPI_T_pvar_handle, 739, 740-742, 857, 858
MPI_T_pvar_session, <u>738</u>, <u>739-742</u>, <u>857</u>
MPI_T_source_order, 859
MPI_Win, 367-369, 455, 456, 543, 546, 548,
         552, 555, 557, 558, 560, 563, 567, 569,
         572-574, 576, 577, 579, 586, 588-590,
         592-597, 830, 852, 859, 860
TYPE(MPI_Win), 852, 860
```

#-other #-error! #-update5

Are these type declarations really new types? YES

- + = referenced in a new change-log entry
- + MPI\_T\_cb\_safety
- + MPI\_T\_event\_instance
- + MPI\_T\_event\_registration
- + MPI\_T\_source\_order

Do they all have correct primary and secondary references in the Declaration Index? YES

Done in PR422 and PR461

# MPI Callback Function Prototype Index

This index lists the C typedef names for callback routines, such as those used with attribute caching or user-defined reduction operations. Fortran example prototypes are given near the text of the C name.

```
MPI_Comm_copy_attr_function, 22, 23, 361,
                                                                                                      15
                                                                                                          #-other
         362, 782, 853, 860
                                                              The Fortran mpi module + mpif.h
                                                                                                      16
                                                                                                          #-error!
MPI_Comm_delete_attr_function, 23, 361, 362,
                                                              prototype names are missing
                                                                                                      17
         853, 860
                                                                                                          #-update5
MPI_Comm_errhandler_fn, 772, 1044
                                                                            In A.1.3 and A.1.4: secondary references
MPI_Comm_errhandler_function, 23, 453, 772,
         776, 861, 1044
                                                                            In the chapters: primary references
MPI_Copy_function, 23, 769, 854, 867
MPI_Datarep_conversion_function, 693, 853, 861
                                                                                                           Done
MPI_Datarep_conversion_function_c, 693, 861
                                                                                                      23
                                                                                                           in
MPI_Datarep_extent_function, 692, 861
                                                                                                           PR449
                                                                                                      24
MPI_Delete_function, 23, 770, 854, 867
                                                                                                      25
MPI_File_errhandler_fn, 772, 1044
                                                                                                      26
MPI_File_errhandler_function, 457, 772, 861,
                                                                                                      27
                                                                                                      28
MPI_Grequest_cancel_function, 624, 861
MPI_Grequest_free_function, 623, 861
MPI_Grequest_query_function, 623, 861
                                                                                                      30
MPI_Handler_function, 23, 776, 1038
                                                                                                      31
MPI_Session_errhandler_function, 459, 861
MPI_T_event_cb_function, 755, 861
                                                           The middle one should be:
                                         These are new
                                                                                                      33 #-other
MPI_T_event_dropped_function, 758, 861
                                         in MPI-4.0.
                                                           MPI T event dropped cb function
                                                                                                      34 #-error!
MPI_T_event_free_cb_function, 757, 861
                                         All correct??
MPI_Type_copy_attr_function, 369, 370, 853,
                                                                                                         Done
                                                                                                         in
                                                  New callbacks:
MPI_Type_delete_attr_function, 369, 370, 853,
                                                                                                         PR409
                                                  + = referenced in a new change-log entry
         861, 1041
                                                                                                         and
                                                   + MPI Session errhandler function, 459, 861
                                                                                                         PR449
MPI_User_function, 230, 234, 860
                                                   + MPI T event cb function, 755, 861
                                                                                                         and
MPI_User_function_c, 230, 860
                                                   + MPI T event dropped function, 758, 861 WRONG
                                                                                                         PR461
MPI_Win_copy_attr_function, 366, 367, 853,
                                                   + MPI T event dropped cb function, xxxx CORRECT
                                                   + MPI_T_event_free_cb_function, 757, 861
MPI_Win_delete_attr_function, 366, 367, 853,
                                                   + MPI User function c
                                                   + MPI Datarep conversion function c
MPI_Win_errhandler_fn, 772, 1044
MPI_Win_errhandler_function, 455, 772, 861,
                                                                                                      46
                                                                                                      47
```

12

13

Wrong macro is used.
Caused Function instead
of Callback Index!
See page 23

1 2

The underlined page numbers refer to the function definitions.

29

30

31

32

33

34

35

36

37

38

39

40

41

42

43

44

45

 $^{46}$ 

47

MPI\_BARRIER, 183, 187, <u>189</u>, 248, 503,

605-607, 703

```
COMM_COPY_ATTR_FUNCTION, 23
                                            MPI BARRIER INIT. 272
                                            MPI_BCAST, 14, 183, 187, 190, 191, 221, 249,
COMM_DELETE_ATTR_FUNCTION, 23
COPY_FUNCTION, 23
                                                    299, 300
                                            MPI_BCAST_INIT, 14, 273
DELETE_FUNCTION, 23
                                            MPI_BSEND, 14, 47, 48, 58
                                            MPI_BSEND_INIT, 91, 95
MPI_ABORT, 231, 451, 481, 487, 505, 537,
                                            MPI_BUFFER_ATTACH, 55, 68
        723, 829, 1047
                                            MPI_BUFFER_DETACH, 56, 1032, 1041
MPI_ACCUMULATE, 541, 559, <u>567</u>, 568, 572,
                                            MPI_CANCEL, 23, 51, 68, 80, 88, 89, 90, 247,
        579, 583, 609, 615, 616, 1044, 1048
                                                    272, 488, 574, 621, 624, 625, 772, 1032
MPI_ADD_ERROR_CLASS, 465
                                            MPI_CART_COORDS, 385, 400, 401, 1047
MPI_ADD_ERROR_CODE, 466
                                            MPI_CART_CREATE, 349, 385, 386,
MPI_ADD_ERROR_STRING, 466
                                                    387–389, 408, 410, 807, 1035, 1046
MPI_ADDRESS, 23, 775, 791, 1038
                                            MPI_CART_GET, 385, 399, 1046
MPI_AINT_ADD, 24, 137, 138, 553, 1036
                                            MPI_CART_MAP, 385, 408, 1040
MPI_AINT_DIFF, 24, 137, 138, 139, 553, 1036
                                            MPI_CART_RANK, 385, 400, 1047
MPI_ALLGATHER, 183, 187, 188, 209, 210,
                                            MPI_CART_SHIFT, 385, 405, 406, 410, 1047
        212, 214, 257
                                            MPI CART SUB, 385, 407, 409, 1047
MPI_ALLGATHER_INIT, 280
                                            MPI_CARTDIM_GET, 385, 398, 399, 1046
MPI_ALLGATHERV, 183, 187, 188, 211, 212,
                                            MPI_CLOSE_PORT, 526, 530
        258
                                            MPI_COMM_ACCEPT, 525, 527, 528, 535,
MPI_ALLGATHERV_INIT, 282
                                                    536
MPI_ALLOC_MEM, 447, 448-450, 463, 545,
                                            MPI_COMM_C2F, 830
        547, 549–551, 554, 562, 595, 792–794,
                                            MPI_COMM_CALL_ERRHANDLER, 467,
        806, 1033, 1035, 1042
                                                    469
MPI_ALLOC_MEM_CPTR, 448, 1035
                                            MPI_COMM_COMPARE, 321, 351
MPI_ALLREDUCE, 183, 186–188, 222, 230,
                                            MPI_COMM_CONNECT, 464, 528, 535, 536
        234, 235, 266, 1045
                                            MPI_COMM_CREATE, 319, 321, 325,
MPI_ALLREDUCE_INIT, 290
                                                    326-330, 385, 1044
MPI_ALLTOALL, 183, 187, 188, 213, 214,
                                            MPI_COMM_CREATE_ERRHANDLER, 23,
        216, 217, 259, 1043
                                                    452, 453, 454, 775, 863, 866, 1041
MPI_ALLTOALL_INIT, 283
                                            MPI_COMM_CREATE_FROM_GROUP, 321,
MPI_ALLTOALLV, 183, 187, 188, 215, 216,
                                                    336, 338, 355, 445
        217, 219, 261, 1043
                                            MPI_COMM_CREATE_GROUP, 321, 328,
MPI_ALLTOALLV_INIT, 285
                                                    329, 330, 338, 1039
MPI_ALLTOALLW, 183, 187, 188, 217, 218,
                                            MPI_COMM_CREATE_KEYVAL, 23, 359,
        219, 263, 1043
                                                    360, 362, 363, 373, 769, 836, 837, 862,
MPI_ALLTOALLW_INIT, 287
                                                    865, 1041, 1046
MPI_ATTR_DELETE, 23, 373, 770, 771
                                            MPI_COMM_DELETE_ATTR, 23, 359,
MPI_ATTR_GET, 23, 373, 771, 837
                                                    362-364, 365, 373, 771
MPI_ATTR_PUT, 23, 373, 771, 837, 840, 841
                                            MPI_COMM_DISCONNECT, 373, 494, 503,
```

518, 537, 538

MPI_COMM_DUP, 312, 319, 321, <u>322</u> , 323,	1032, 1039	1
324, 326, 352, 355, 359, 362, 366, 373,	MPI_COMM_TEST_INTER, 349, 350	2
381, 769, 777, 1033, 1039	MPI_COMPARE_AND_SWAP, 541, 559, <u>573</u> ,	3
MPI_COMM_DUP_FN, 23, <u>362</u> , 363, 787,	614	. 4
853, 1036, 1041	WII I_CON VENUDION_IN_INCEE, 000, 000,	s is a callback
MPI_COMM_DUP_WITH_INFO, 321, 323,	1036 pro	totype
324, 339, 777, 1039	MPI_DATAREP_CONVERSION_FUNCTION,	្នំ #-error!
MPI_COMM_F2C, <u>830</u>	693,827	* #-other
MPI_COMM_FREE, 319, 322, <u>338</u> , 352, 355,	MPI_DIMS_CREATE, 385, <u>387</u> , 388, 1033	
362–364, 366, 373, 487, 490, 494, 503,	MPI_DIST_GRAPH_CREATE, 339, 385, 390,	9 Done
518, 537, 538, 770	<u>393</u> , 394–396, 405, 410, 1044	10 PR449
MPI_COMM_FREE_KEYVAL, 23, 359, <u>363</u> ,	MPI_DIST_GRAPH_CREATE_ADJACENT,	11
373,770	$339, 385, 390, \underline{391}, 392, 396, 405, 410,$	12
MPI_COMM_GET_ATTR, 23, 359, <u>364</u> , 373,	1040,1044	13
445, 771, 788, 837, 840	MPI_DIST_GRAPH_NEIGHBORS, 385, 403,	14
MPI_COMM_GET_ERRHANDLER, 23, 452,	$\underline{404}$ , 405, 410, 1040, 1044	
$\underline{454}$ , 775, 1047	MPI_DIST_GRAPH_NEIGHBORS_COUNT,	15
MPI_COMM_GET_INFO, 339, <u>341</u> , 1033,	$385, \underline{403}, 405, 1037, 1044$	16
1039	MPI_DUP_FN, 23, 362, <u>770</u> , 854	17
MPI_COMM_GET_NAME, <u>376</u> , <u>377</u> , <u>378</u> ,	MPI_ERRHANDLER_C2F, 504, <u>830</u>	18
1046	MPI_ERRHANDLER_CREATE, 23, 775,	19
MPI_COMM_GET_PARENT, 377, 481, 482,	1038, 1041	20
487, 491, 514, <u>517</u> , 518	MPI_ERRHANDLER_F2C, 504, <u>830</u>	21
MPI_COMM_GROUP, 17, 310, <u>312</u> , 313, <u>319</u> ,	MPI_ERRHANDLER_FREE, 452, <u>460</u> , 487,	22
320, 351, 452, 1047	494, 504, 1047	
MPI_COMM_IDUP, 319, 321, <u>323</u> , 324, 349,	MPI_ERRHANDLER_GET, 23, 775, 1038,	23
359, 362, 366, 373, 777, 1033, 1034,	1047	24
1039	MPI_ERRHANDLER_SET, 23, 775, 1038	25
MPI_COMM_IDUP_WITH_INFO, 321, 324,	MPI_ERROR_CLASS, <u>462</u> , 465, 504, 766	26
339, 777, 1033	MPI_ERROR_STRING, <u>461</u> , <u>462</u> , <u>465</u> , <u>467</u> ,	27
MPI_COMM_JOIN, 491, <u>538</u> , 539	Must be MPI_T_EVENT	<sub>28</sub> #-error!
MPI_COMM_NULL_COPY_FN, 23, <u>362</u> , 363,	MPI_EVENT_CALLBACK_GET_INFO, 756	<sup>29</sup> #-update9
	MPI_EVENT_HANDLE_GET_INFO, 754	30 Done
MPI_COMM_NULL_DELETE_FN, 23, <u>362</u> ,	MPI_EXSCAN, 184, 187, 222, 230, <u>243</u> , 271, 1043	<sub>31</sub> in
363, 853, 1036 MDL COMM BANK 14, 220, 251, 780		PR449
MPI_COMM_RANK, 14, <u>320</u> , <u>351</u> , 789 MPI_COMM_RANK_F08, 789	MPI_EXSCAN_INIT, <u>295</u> MPI_F_SYNC_REG, 137, 616, 780, <u>796</u> , 797,	
MPI_COMM_REMOTE_GROUP, 352	816, 818, 819, 821, 1042	33
MPI_COMM_REMOTE_SIZE, 351, 352	MPI_FETCH_AND_OP, 541, 559, 568, 572	34
MPI_COMM_SET_ATTR, 23, 359, 362, 364,	MPI_FILE_C2F, <u>830</u>	35
373, 770, 788, 837, 841	MPI_FILE_CALL_ERRHANDLER, 468, 469	36
MPI_COMM_SET_ERRHANDLER, 23, 452,	MPI_FILE_CLOSE, 538, 633, 634, 636	37
454, 775	MPI_FILE_CREATE_ERRHANDLER, 452,	38
MPI_COMM_SET_INFO, 272, 339, 340, 341,	457, 458, 863, 866, 1041	39
1033, 1035, 1039	MPI_FILE_DELETE, 635, 636, 637, 641, 643,	40
MPI_COMM_SET_NAME, <u>375</u> , <u>376</u>	706, 707	41
MPI_COMM_SIZE, <u>319</u> , 320, 351, 614	MPI_FILE_F2C, <u>830</u>	
MPI_COMM_SPAWN, 481, 482, 506, 507, 512,	MPI_FILE_GET_AMODE, 640	42
<u>513</u> , 514, 516–522, 535, 536, 1034	MPI_FILE_GET_ATOMICITY, 698	43
MPI_COMM_SPAWN_MULTIPLE, 481, 482,	MPI_FILE_GET_BYTE_OFFSET, 658, 667,	44
507, 512, 517, <u>518,</u> 519, 520, 536, 1034	675	45
MPI_COMM_SPLIT, 321, 325, 326, 329, 330,	MPI_FILE_GET_ERRHANDLER, 452, 458,	46
331 381 385 387 389 407 409 1044	707 1047	47

MPI\_FILE\_GET\_GROUP, 639

MPI\_COMM\_SPLIT\_TYPE, <u>333</u>, <u>337</u>, <u>339</u>,

	1	MPI_FILE_GET_INFO, 641, 642, 643, 1033,	MPI_FILE_SET_INFO, <u>641</u> , 642, 643, 1033,
	2	1048	1048
	3	MPI_FILE_GET_POSITION, 666, 667	MPI_FILE_SET_SIZE, <u>637</u> , <u>638</u> , <u>697</u> , <u>699</u> ,
		MPI_FILE_GET_POSITION_SHARED, 674,	701, 702
	5	675, 699	MPI_FILE_SET_VIEW, 131, 464, 634,
		MPI_FILE_GET_SIZE, <u>639</u> , 702	641–643, 644, 645, 646, 667, 675, 685,
	6	MPI_FILE_GET_TYPE_EXTENT, 686, 687,	692, 701, 707, 1048
	7	695,1032	MPI_FILE_SYNC, 636, 648, 696, 697, <u>698</u> ,
		MPI_FILE_GET_VIEW, <u>646</u> , 647	699, 704
		MPI_FILE_IREAD, 647, <u>662</u> , 675, 696	MPI_FILE_WRITE, 647, 648, <u>660</u> , 661, 662,
		MPI_FILE_IREAD_ALL, 647, 663, 664, 1036	665, 701
		MPI_FILE_IREAD_AT, 647, 654	MPI_FILE_WRITE_ALL, 647, 661, 662, 665
	12	MPI_FILE_IREAD_AT_ALL, 647, 655, 1036	MPI_FILE_WRITE_ALL_BEGIN, 647, <u>680</u> ,
	1.3	MPI_FILE_IREAD_SHARED, 647, 670	808, 821
	1/	MPI_FILE_IWRITE, 647, 664, 665	MPI_FILE_WRITE_ALL_END, 647, 681, 821
		MPI_FILE_IWRITE_ALL, 647, <u>665</u> , 1036 MPI_FILE_IWRITE_AT, 647, <u>656</u>	MPI_FILE_WRITE_ALL_FN, 14 MPI_FILE_WRITE_AT, 647, 648, 652, 653,
		MPI_FILE_IWRITE_AT, 047, 050 MPI_FILE_IWRITE_AT_ALL, 647, 657, 1036	656
		MPI_FILE_IWRITE_SHARED, 647, 651, 1030	MPI_FILE_WRITE_AT_ALL, 647, 653, 657
		MPI_FILE_OPEN, 463, 511, 633, 634, 635,	MPI_FILE_WRITE_AT_ALL_BEGIN, 647,
	19	641, 643, 645, 667, 701, 702, 706, 707	678, 821
		MPI_FILE_PREALLOCATE, 637, 638, 697,	MPI_FILE_WRITE_AT_ALL_END, 647, 679,
	20	701, 702	821
	21	MPI_FILE_READ, 647, 648, 658, 659, 660,	MPI_FILE_WRITE_AT_ALL_FN, 14
	22	662, 701, 702	MPI_FILE_WRITE_ORDERED, 647, 672,
	23	MPI_FILE_READ_ALL, 647, 659, 660, 664,	<u>673</u>
	24	676	MPI_FILE_WRITE_ORDERED_BEGIN,
	25	MPI_FILE_READ_ALL_BEGIN, 647, 675,	647, <u>683</u> , 821
	26	676, <u>679</u> , 696, 821	MPI_FILE_WRITE_ORDERED_END, 647,
	27	MPI_FILE_READ_ALL_END, 647, 675, 676,	683, 821
	28	680, 696, 821	MPI_FILE_WRITE_ORDERED_FN, 14
		MPI_FILE_READ_ALL_FN, 14 MPI_FILE_READ_AT, 647, 650, 651, 652, 654	MPI_FILE_WRITE_SHARED, 647, 648, <u>669</u> , 671–673
		MPI_FILE_READ_AT, 047, 050, 051, 052, 054 MPI_FILE_READ_AT_ALL, 647, 651, 652,	MPI_FINALIZE, 18, 25, 26, 445, 451, 479,
	31	655	486, 487–491, 509, 537, 538, 634, 720,
	32	MPI_FILE_READ_AT_ALL_BEGIN, 647,	730, 743, 745, 829, 832, 833, 1034,
	33	677, 821	1040, 1047
	34	MPI_FILE_READ_AT_ALL_END, 647, 677,	MPI_FINALIZED, 489, <u>490</u> , 504, 829, 1036
	35	821	MPI_FREE_MEM, <u>449</u> , <u>463</u> , 547, 549
		MPI_FILE_READ_AT_ALL_FN, 14	MPI_GATHER, 183, 186, 187, <u>191</u> , 195, 196,
	36	MPI_FILE_READ_ORDERED, 647, <u>672</u> , 673	203, 210, 221, 251
	37	MPI_FILE_READ_ORDERED_BEGIN, 647,	MPI_GATHER_INIT, <u>274</u>
	38	681, 821	MPI_GATHERV, 183, 187, <u>194</u> , 195–197, 205,
	39	MPI_FILE_READ_ORDERED_END, 647,	212, 252
	40	682, 821	MPI_GATHERV_INIT, 276
	41	MPI_FILE_READ_ORDERED_FN, 14	MPI_GET, 541, 559, <u>563</u> , 564, 572, 577, 583,
	42	MPI_FILE_READ_SHARED, 647, <u>668</u> , 669,	605, 608, 616, 818, 1048 MPI_GET_ACCUMULATE, 541, 559, 568,
	43	670, 673 MPI_FILE_SEEK, <u>666</u> , 667	570, 571, 572, 581, 609, 614, 615, 1035
	44	MPI_FILE_SEEK_SHARED, <u>674</u> , 675, 699	MPI_GET_ADDRESS, 23, 117, <u>137</u> , 138, 139,
ا - ما،		MPI_FILE_SET_ATOMICITY, 635, 697, 698	152, 553, 775, 791, 810, 815, 834–836
her	46	MPI_FILE_SET_ERRHANDLER, 452, 457,	MPI_GET_COUNT, 37, <u>38</u> , 39, 67, 151, 574,
ror!	47	707	629, 650, 1038, 1045
MD		READ_ALL_FN	MPI_GET_ELEMENTS, 67, <u>150</u> , 151, 152,
		READ_ALL_FN all these must be	
		DEAD ODDEDED EN 1 1 1 DEOIN	r Comment Only
		WRITE_ALL_FN instead of _FN	i Commone Omy

#-other #-error!

MPI\_FILE\_WRITE\_ALL\_FN

MPI\_FILE\_WRITE\_AT\_ALL\_FN

MPI\_FILE\_WRITE\_ORDERED\_FN

instead of \_FN

on page 14, line 37

Done in PR449

629, 630, 650, 1038	MPI_INEIGHBOR_ALLGATHER, 386, 422,	1
MPI_GET_ELEMENTS_X, 67, <u>150</u> , 151, 152,	1040	2
629,650,1038	MPI_INEIGHBOR_ALLGATHERV, 386, 424,	3
MPI_GET_LIBRARY_VERSION, 444, 504,	1040	4
1035, 1036, 1038	MPI_INEIGHBOR_ALLTOALL, 386, 425,	_
MPI_GET_PROCESSOR_NAME, 446, 447,	1040	5
1047	MPI_INEIGHBOR_ALLTOALLV, 386, 426,	6
MPI_GET_VERSION, <u>443</u> , 444, 504, 795,	1040	7
1036	MPI_INEIGHBOR_ALLTOALLW, 386, 428,	8
MPI_GRAPH_CREATE, 385, 388, 390, 395,	1040	9
398, 402, 409, 410, 1046		10
MPI_GRAPH_GET, 385, 398	MDI INDO CDEATE ATO FOA	
MPI_GRAPH_MAP, 385, <u>409</u>	MPI_INFO_CREATE_ENV, <u>477</u> , 504, 1032	11
		12
MPI_GRAPH_NEIGHBORS, 385, <u>401</u> , 402,	MPI_INFO_DELETE, 463, <u>473</u> , 476, 504	13
410, 1044	MPI_INFO_DUP, <u>477</u> , 504	14
MPI_GRAPH_NEIGHBORS_COUNT, 385,	MPI_INFO_F2C, 504, <u>830</u>	15
<u>401,</u> 402, 1044	MPI_INFO_FREE, 341, <u>477</u> , 478, 487, 494,	
MPI_GRAPHDIMS_GET, 385, <u>397</u> , 398	497, 504, 559, 642, 748, 752, 754, 757	16
MPI_GREQUEST_COMPLETE, $622-624$ , $\underline{625}$	111 121 11 0 2 0 2 1 1 1 , <u>110 ,</u> 0 0 1 , <u>112 ,</u> 100 1 ,	17
MPI_GREQUEST_START, <u>622</u> , 864, 866,		18
1044		19
MPI_GROUP_C2F, <u>830</u>	MPI_INFO_GET_NTHKEY, 471, <u>476</u> , 504,	20
MPI_GROUP_COMPARE, <u>311</u> , <u>315</u>	1048	21
MPI_GROUP_DIFFERENCE, <u>314</u>	MPI_INFO_GET_STRING, 23, 471, <u>475</u> , 772,	
MPI_GROUP_EXCL, <u>315</u> , <u>317</u>	773, 1034	22
MPI_GROUP_F2C, <u>830</u>	MPI_INFO_GET_VALUELEN, 23, 471, <u>474</u> ,	23
MPI_GROUP_FREE, <u>318</u> , <u>319</u> , <u>320</u> , <u>452</u> , <u>487</u> ,	504, <u>773</u> , 1034, 1048	24
494, 1047		25
MPI_GROUP_FROM_SESSION_PSET, 318	MPI_INIT, 18, 25, 26, 309, 445, 451, 478, 479,	26
MPI_GROUP_INCL, <u>314</u> , <u>315</u> , <u>316</u>	400 401 402 406 400 400 504 510	27
MPI_GROUP_INTERSECTION, 313	514_517_534_535_790_799_730_743	
MPI_GROUP_RANGE_EXCL, 317	829 832 833 1034 1038 1040 1042	28
MPI_GROUP_RANGE_INCL, 316	1044	29
MPI_GROUP_RANK, 310, 320	MPI_INIT_THREAD, 25, 309, 451, 478–481,	30
MPI_GROUP_SIZE, <u>310</u> , <u>319</u>		31
MPI_GROUP_TRANSLATE_RANKS, 311,		32
1046		33
MPI_GROUP_UNION, 313	MPI_INITIALIZED, <u>489</u> , 490, 504, 829, 1036	-
MPI_IALLGATHER, 183, 187, 188, 256	MPI_INTERCOMM_CREATE, 322, 328, 329,	34
MPI_IALLGATHERV, 183, 187, 188, <u>250</u> MPI_IALLGATHERV, 183, 187, 188, <u>257</u>	352, <u>353</u> , 354, 355, 1039	35
		36
MPI_IALLTOALL_183_187, 188, <u>265</u>	MPI_INTERCOMM_CREATE_FROM_GROUPS,	37
MPI_IALLTOALL, 183, 187, 188, <u>258</u>	321, 322, 352, <u>354</u> , 445	38
MPI_IALLTOALLV, 183, 187, 188, 260	WII I_IIV I E1000WIMI_WIE103E, 321, 320, 343,	
MPI_IALLTOALLW, 183, 187, 188, <u>262</u>	352, 353, <u>355,</u> 1041	39
MPI_IBARRIER, 183, 187, 246, <u>248</u> , 300	<u> </u>	40
MPI_IBCAST, 14, 183, 187, <u>248</u> , 249, 303		41
MPI_IBSEND, <u>61</u> , 68, 95		42
MPI_IEXSCAN, 184, 187, <u>270</u>	MPI_IREDUCE, 183, 187, 188, <u>264</u> , 265	43
MPI_IGATHER, 183, 187, <u>250</u>	MPI_IREDUCE_SCATTER, 183, 187, 188,	44
MPI_IGATHERV, 183, 187, <u>251</u>	<u>268</u>	
MPI_IMPROBE, 14, 80, <u>83</u> , 84, 85, 88, 510,	MPI_IREDUCE_SCALTER_DLOCK, 185,	45
1034, 1039	167, 166, <u>266</u>	46
MPI_IMRECV, 83–85, <u>87</u> , 88, 1039	$MPI_{IRSEND}, \underline{63}$	47
	MPI_IS_THREAD_MAIN, 483, 485, 1036	48

1	MPI_ISCAN, 184, 187, <u>269</u>	MPI_PUBLISH_NAME, 525, 52	29, 530, 531
2	MPI_ISCATTER, 183, 187, <u>253</u>	MPI_PUT, 541, 559, <u>560</u> , 564, §	
	MPI_ISCATTERV, 183, 187, <u>254</u>	589, 599, 601, 606, 607	
3			, 010, 808, 818,
4	MPI_ISEND, 14, <u>60</u> , 95, 787, 788, 791,	1048	106 510 1096
5	807–809, 814	MPI_QUERY_THREAD, 485,	
6	$MPI\_ISENDRECV, \underline{65}, 1034$	MPI_RACCUMULATE, 541, 58	59, 568, 572,
	MPI_ISENDRECV_REPLACE, <u>66</u> , 1034	578, 579	
7	MPI_ISSEND, <u>62</u>	MPI_RECV, 14, 30, <u>35</u> , 37–39,	80, 83, 84, 87,
8	MPI_KEYVAL_CREATE, 23, 769, 771, 867	116, 149, 173, 184, 192	
9	MPI_KEYVAL_FREE, 23, 373, 770	743, 815, 818, 819	, ,,,
10	MPI_LOOKUP_NAME, 463, 525, 530, 531	MPI_RECV_INIT, 14, 94, 95, 1	04
	MPI_MESSAGE_C2F, 830, 1039	MPI_REDUCE, 183, 187, 188, 2	
11	· ——·		
12	MPI_MESSAGE_F2C, <u>830</u> , 1039	230–232, 235, 239, 241	, 242, 244, 265,
13	MPI_MPROBE, 14, 80, 83, 84, <u>85</u> , 88, 510,	568, 571-573, 1044	
	1039	MPI_REDUCE_INIT, 289	
14	MPI_MRECV, 14, 83–85, <u>86</u> , 87, 1039	MPI_REDUCE_LOCAL, 221, 2	22, 230, 236,
15	MPI_NEIGHBOR_ALLGATHER, 386, 411,	1041, 1043	
16	413, 415, 423, 1032, 1040	MPI_REDUCE_SCATTER, 18	3. 187. 188.
17	MPI_NEIGHBOR_ALLGATHER_INIT, 430	222, 230, 239, 240, 241	
18	MPI_NEIGHBOR_ALLGATHERV, 386, 413,	MPI_REDUCE_SCATTER_BL	
	425, 1032, 1040	187, 188, 222, 230, <u>238</u>	
19	MPI_NEIGHBOR_ALLGATHERV_INIT, 431	MPI_REDUCE_SCATTER_BL	
20	MPI_NEIGHBOR_ALLTOALL, 386, 415, 417,		OCK_INIT,
21	· · · · · · · · · · · · · · · · · · ·	MDI DEDLICE COATTED IN	TT 909
22	418, 426, 1032, 1040	MPI_REDUCE_SCATTER_IN	
23	MPI_NEIGHBOR_ALLTOALL_INIT, 433	MPI_REGISTER_DATAREP, 4	
20	MPI_NEIGHBOR_ALLTOALLV, 386, 418,	693, 695, 707, 864, 867	
	10 1000 1010		
24	427, 1032, 1040	MPI_Register_datarep_c, 828	
24 25	MPI_NEIGHBOR_ALLTOALLV_INIT, 434	MPI_REQUEST_C2F, 830	MPI_Register_datarep_c
	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, <u>830</u> MPI_REQUEST_F2C, <u>830</u>	MPI_Register_datarep_c shall also have primiry indexes h
25	MPI_NEIGHBOR_ALLTOALLV_INIT, 434	MPI_REQUEST_C2F, <u>830</u> MPI_REQUEST_F2C, <u>830</u> MPI_REQUEST_FREE, <u>69</u> , 70	MPI_Register_datarep_c shall also have primiry indexes by 88, 96, 247,
25 26 27	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, <u>830</u> MPI_REQUEST_F2C, <u>830</u>	MPI_Register_datarep_c shall also have primiry indexes by 88, 96, 247,
25 26 27 28	MPI_NEIGHBOR_ALLTOALLV_INIT, $\underline{434}$ MPI_NEIGHBOR_ALLTOALLW, $\underline{386}$ , $\underline{420}$ , $\underline{429}$ , $\underline{1032}$ , $\underline{1040}$	MPI_REQUEST_C2F, <u>830</u> MPI_REQUEST_F2C, <u>830</u> MPI_REQUEST_FREE, <u>69</u> , 70	MPI_Register_datarep_c shall also have primiry indexes h , 88, 96, 247, , 624, 625, 1043
25 26 27	MPI_NEIGHBOR_ALLTOALLV_INIT, <u>434</u> MPI_NEIGHBOR_ALLTOALLW, <u>386</u> , <u>420</u> ,	MPI_REQUEST_C2F, <u>830</u> MPI_REQUEST_F2C, <u>830</u> MPI_REQUEST_FREE, <u>69</u> , 70 271, 272, 487, 494, 574	MPI_Register_datarep_c shall also have primiry indexes h , 88, 96, 247, , 624, 625, 1043
25 26 27 28	MPI_NEIGHBOR_ALLTOALLV_INIT, <u>434</u> MPI_NEIGHBOR_ALLTOALLW, <u>386</u> , <u>420</u> ,	MPI_REQUEST_C2F, <u>830</u> MPI_REQUEST_F2C, <u>830</u> MPI_REQUEST_FREE, <u>69</u> , 70	MPI_Register_datarep_c shall also have primiry indexes h , 88, 96, 247, , 624, 625, 1043
25 26 27 28 29	MPI_NEIGHBOR_ALLTOALLV_INIT, <u>434</u> MPI_NEIGHBOR_ALLTOALLW, 386, <u>420</u> ,	MPI_REQUEST_C2F, <u>830</u> MPI_REQUEST_F2C, <u>830</u> MPI_REQUEST_FREE, <u>69</u> , 70	MPI_Register_datarep_c shall also have primiry indexes by 1,88,96,247,624,625,1043 S, 39, 79,623,
25 26 27 28 29 30 31	MPI_NEIGHBOR_ALLTOALLV_INIT, <u>434</u> MPI_NEIGHBOR_ALLTOALLW, <u>386</u> , <u>420</u> ,	MPI_REQUEST_C2F, <u>830</u> MPI_REQUEST_F2C, <u>830</u> MPI_REQUEST_FREE, <u>69</u> , 70	MPI_Register_datarep_c shall also have primiry indexes by 1,88,96,247,624,625,1043 S, 39, 79,623,
25 26 27 28 29 30 31 32	MPI_NEIGHBOR_ALLTOALLV_INIT, <u>434</u> MPI_NEIGHBOR_ALLTOALLW, <u>386</u> , <u>420</u> ,	MPI_REQUEST_C2F, <u>830</u> MPI_REQUEST_F2C, <u>830</u> MPI_REQUEST_FREE, <u>69</u> , 70	MPI_Register_datarep_c shall also have primiry indexes by 1,88,96,247,624,625,1043 S, 39, 79,623,
25 26 27 28 29 30 31 32	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420, 429, 1032, 1040 MPI_NEIGHBOR_ALLTOALLW_INIT, 436 MPI_NULL_COPY_FN, 22, 23, 362, 770, 854 MPI_NULL_DELETE_FN, 23, 363, 770, 854 MPI_OP_C2F, 830 MPI_OP_COMMUTATIVE, 237, 1043 MPI_OP_CREATE, 229, 230, 232, 787, 862, 865, 1041	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70 271, 272, 487, 494, 574 MPI_REQUEST_GET_STATU 1043 MPI_RGET, 541, 559, 576, 577 MPI_RGET_ACCUMULATE, 8 571, 580, 581 MPI_RPUT, 541, 559, 575, 576	MPI_Register_datarep_c shall also have primiry indexes by 1,88,96,247,624,625,1043 S, 39, 79,623,
25 26 27 28 29 30 31 32	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420, 429, 1032, 1040 MPI_NEIGHBOR_ALLTOALLW_INIT, 436 MPI_NULL_COPY_FN, 22, 23, 362, 770, 854 MPI_NULL_DELETE_FN, 23, 363, 770, 854 MPI_OP_C2F, 830 MPI_OP_COMMUTATIVE, 237, 1043 MPI_OP_CREATE, 229, 230, 232, 787, 862, 865, 1041 MPI_OP_create_c, 828	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70 271, 272, 487, 494, 574 MPI_REQUEST_GET_STATU 1043 MPI_RGET, 541, 559, 576, 577 MPI_RGET_ACCUMULATE, 8 571, 580, 581 MPI_RPUT, 541, 559, 575, 576 MPI_RSEND, 14, 50	MPI_Register_datarep_c shall also have primiry indexes by 1,88,96,247,624,625,1043 S, 39, 79,623,
25 26 27 28 29 30 31 32	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623,
25 26 27 28 29 30 31 32 33 34	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420, 429, 1032, 1040 MPI_NEIGHBOR_ALLTOALLW_INIT, 436 MPI_NULL_COPY_FN, 22, 23, 362, 770, 854 MPI_NULL_DELETE_FN, 23, 363, 770, 854 MPI_OP_C2F, 830 MPI_OP_COMMUTATIVE, 237, 1043 MPI_OP_CREATE, 229, 230, 232, 787, 862, 865, 1041 MPI_OP_create_c, 828 MPI_OP_F2C, 830 MPI_OP_FREE, 232, 487, 494	MPI_REQUEST_C2F, <u>830</u> MPI_REQUEST_F2C, <u>830</u> MPI_REQUEST_FREE, <u>69</u> , 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623,
25 26 27 28 29 30 31 32 33 34 35 36	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, <u>830</u> MPI_REQUEST_F2C, <u>830</u> MPI_REQUEST_FREE, <u>69</u> , 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623,
25 26 27 28 29 30 31 32 33 34 35 36 37	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 641, 559, 568,
25 26 27 28 29 30 31 32 33 34 35 36 37 38	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 641, 559, 568,
25 26 27 28 29 30 31 32 33 34 35 36 37	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 641, 559, 568,
25 26 27 28 29 30 31 32 33 34 35 36 37 38	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 541, 559, 568, 241, 242, 244, 203, 205, 206,
25 26 27 28 29 30 31 32 33 34 35 36 37 38	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 541, 559, 568, 241, 242, 244, 203, 205, 206,
25 26 27 28 29 30 31 32 33 34 35 36 37 38 39	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 541, 559, 568, 241, 242, 244, 203, 205, 206,
25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 541, 559, 568, 241, 242, 244, 203, 205, 206, 4, 205, 206,
25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 541, 559, 568, 241, 242, 244, 203, 205, 206, 4, 205, 206,
25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 541, 559, 568, 241, 242, 244, 203, 205, 206, 44, 116, 148,
25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 641, 559, 568, 241, 242, 244, 203, 205, 206, 44, 116, 148, 815, 816, 818
25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 641, 559, 568, 241, 242, 244, 203, 205, 206, 44, 116, 148, 815, 816, 818
25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44 45	MPI_NEIGHBOR_ALLTOALLV_INIT, 434 MPI_NEIGHBOR_ALLTOALLW, 386, 420,	MPI_REQUEST_C2F, 830 MPI_REQUEST_F2C, 830 MPI_REQUEST_FREE, 69, 70	MPI_Register_datarep_c shall also have primiry indexes h, 88, 96, 247, 624, 625, 1043 S, 39, 79, 623, 541, 559, 568, 241, 242, 244, 203, 205, 206, 44, 116, 148, 815, 816, 818 03

#-other #-error!

MPI_SESSION_CALL_ERRHANDLER, <u>468</u> ,	MPI_T_CVAR_GET_NUM, <u>726</u> , 731	1
469,504	MPI_T_CVAR_HANDLE_ALLOC, 724, 730,	2
MPI_SESSION_CREATE_ERRHANDLER,	731, 732, 768	3
452, 458, 459, 493, 504, 863, 866	MPI_T_CVAR_HANDLE_FREE, 731, 768	4
MPI_SESSION_CREATE_KEYVAL, 865	MPI_T_CVAR_READ, 731, 768	_
MPI_SESSION_F2C, 830	MPI_T_CVAR_WRITE, 731, 768	5
MPI_SESSION_FINALIZE, 493, 494, 503	MPI_T_ENUM_GET_INFO, 724, 725, 768	6
MPI_SESSION_GET_ERRHANDLER, 452,	MPI_T_ENUM_GET_ITEM, 725, 768	7
	MPI_T_EVENT_CALLBACK_GET_INFO,	8
$\frac{460}{\text{MDI GEGGION GET INFO}}  402,407$		0
MPI_SESSION_GET_INFO, 493, 497	756	Э
MPI_SESSION_GET_NTH_PSET, 318, 496,	MPI_T_EVENT_CALLBACK_SET_INFO,	10
497	<u>756</u>	11
MPI_SESSION_GET_NUM_PSETS, 495, 496	MPI_T_EVENT_COPY, 749, 752, <u>760</u>	12
MPI_SESSION_GET_PSET_INFO, 498	MPI_T_EVENT_GET_INDEX, <u>752</u> , 753, 768	13
MPI_SESSION_INIT, 452, 487, <u>492</u> , 493, 504,	MPI_T_EVENT_GET_INFO, 724, 750, <u>751</u> ,	14
510, 535, 723	753, 760, 768	
MPI_SESSION_SET_ERRHANDLER, 452,	MPI_T_EVENT_GET_NUM, 750	15
459	MPI_T_EVENT_GET_SOURCE, 749, 761	16
MPI_SIZEOF, 23, 773, 774, 1031	MPI_T_EVENT_GET_TIMESTAMP, 747,	17
MPI_SSEND, 49	749, 760	18
MPI_SSEND_INIT, 92	MPI_T_EVENT_HANDLE_ALLOC, 753, 756,	19
MPI_START, 95, 96, 99, 102, 105, 106, 271,	768	
272, 815	MPI_T_EVENT_HANDLE_FREE, 757, 768	20
MPI_STARTALL, <u>95</u> , 96, 99, 102, 105, 106,	MPI_T_EVENT_HANDLE_GET_INFO, 754	21
271, 272, 815	MPI_T_EVENT_HANDLE_SET_INFO, 754	22
MPI_STATUS_C2F, <u>832</u>	MPI_T_EVENT_READ, 749, 751, 759	23
MPI_STATUS_C2F08, <u>832</u> , 1041	MPI_T_EVENT_REGISTER_CALLBACK,	24
MPI_STATUS_F082C, <u>832</u> , 1041	755	25
MPI_STATUS_F082F, <u>834</u> , 1031, 1041	MPI_T_EVENT_SET_DROPPED_HANDLER,	26
MPI_STATUS_F2C, 831	758, 759	
MPI_STATUS_F2F08, <u>833</u> , 1031, 1041	MPI_T_FINALIZE, 723	27
MPI_STATUS_SET_CANCELLED, 629, 1033	MPI_T_INIT_THREAD, <u>722</u> , 723	28
MPI_STATUS_SET_ELEMENTS, 628, 629	MPI_T_PVAR_GET_INDEX, 737, 768, 1036	29
MPI_STATUS_SET_ELEMENTS_X, 629,	MPI_T_PVAR_GET_INFO, 724, 735, 736,	30
	· · · · · · · · · · · · · · · · · · ·	31
1038	739, 741–743, 766, 768, 1035, 1036	
MPI_T_CATEGORY_CHANGED, 766	MPI_T_PVAR_GET_NUM, 735, 739	32
MPI_T_CATEGORY_GET_CATEGORIES,	MPI_T_PVAR_HANDLE_ALLOC, 724, <u>739</u> ,	33
765, 766, 768	741, 742, 768	34
MPI_T_CATEGORY_GET_CVARS, <u>764</u> , 766,	MPI_T_PVAR_HANDLE_FREE, <u>740</u> , 768,	35
768	1036	36
MPI_T_CATEGORY_GET_EVENTS, 765	MPI_T_PVAR_READ, <u>741</u> , 742, 749, 768,	37
MPI_T_CATEGORY_GET_INDEX, <u>764</u> , <u>768</u> ,	1036	
1036	MPI_T_PVAR_READRESET, 737, <u>742</u> , 749,	38
$MPI\_T\_CATEGORY\_GET\_INFO, \underline{763}, 766,$	768, 1036	39
768,1035,1036	MPI_T_PVAR_RESET, <u>742</u> , 749, 768, 1035,	40
MPI_T_CATEGORY_GET_NUM, 762	1036	41
MPI_T_CATEGORY_GET_NUM_EVENTS,	MPI_T_PVAR_SESSION_CREATE, <u>738</u> , 768	42
763,764	MPI_T_PVAR_SESSION_FREE, <u>738</u> , 768	43
MPI_T_CATEGORY_GET_PVARS, <u>765</u> , 766,	MPI_T_PVAR_START, <u>740</u> , 749, 768, 1035,	
768	1036	44
MPI_T_CVAR_GET_INDEX, <u>728</u> , 729, 768,	MPI_T_PVAR_STOP, <u>740</u> , 749, 768, 1035,	45
1036	1036	46
MPI_T_CVAR_GET_INFO, 724, 726, 727,	MPI_T_PVAR_WRITE, <u>741</u> , 742, 749, 768,	47
728 730-732 766 768 1035 1036	1036	48

1	MPI_T_SOURCE_GET_INFO, <u>747</u> , 761, 768	MPI_TYPE_GET_ENVELOPE, <u>153</u> , 154,
2	MPI_T_SOURCE_GET_NUM, <u>746</u> , 768	157, 158, 800, 827
3	MPI_T_SOURCE_GET_TIMESTAMP, <u>748</u> ,	MPI_TYPE_GET_EXTENT, 23, <u>142</u> , 146,
4	749,768	775, 803, 834
5	MPI_TEST, 39, 67, <u>68</u> , 69, 70, 72, 74, 79, 88,	MPI_TYPE_GET_EXTENT_X, <u>143</u> , 1038
6	96, 99, 100, 106, 107, 272, 487, 625,	MPI_TYPE_GET_NAME, <u>378</u> , <u>1041</u>
	648, 649	MPI_TYPE_GET_TRUE_EXTENT, $144$ , $145$
7	MPI_TEST_CANCELLED, 67–69, <u>89</u> , 623,	MPI_TYPE_GET_TRUE_EXTENT_X, 144,
8	630,650	145, 1038
9	MPI_TESTALL, 72, <u>75</u> , 510, 623–625, 628	MPI_TYPE_HINDEXED, 23, 775, 1038
10	MPI_TESTANY, 72, <u>73</u> , 74, 77, 510, 623, 624,	MPI_TYPE_HVECTOR, 23, 775, 1038
11	628	MPI_TYPE_INDEXED, 15, <u>122</u> , 123, 125, 155
12	MPI_TESTSOME, 72, 77, 78, 510, 623–625,	MPI_TYPE_LB, 23, 775, 1038
	628	MPI_TYPE_MATCH_SIZE, 780, <u>802</u> , 803,
13	MPI_TOPO_TEST, 385, <u>397</u>	1041
14	MPI_TYPE_C2F, <u>830</u>	MPI_TYPE_NULL_COPY_FN, 370, 853,
15	MPI_TYPE_COMMIT, <u>146</u> , 147, 831	1036
16	MPI_TYPE_CONTIGUOUS, 15, 117, 120,	MPI_TYPE_NULL_DELETE_FN, 370, 853,
17	141, 155, 632, 686	1036, 1041
18	MPI_TYPE_CREATE_DARRAY, 15, 39, 132,	MPI_TYPE_SET_ATTR, 359, <u>372</u> , 373, 788,
	133, 155	837, 841, 1041
19	MPI_TYPE_CREATE_F90_COMPLEX, 15,	MPI_TYPE_SET_NAME, 378, 1041
20	155, 158, 223, 688, 780, <u>799,</u> 801	MPI_TYPE_SIZE, <u>139</u> , 140, 716, 1039
21	MPI_TYPE_CREATE_F90_INTEGER, 15,	MPI_TYPE_SIZE_X, <u>140</u> , 1038
22	155, 158, 223, 688, 780, 799, 801	MPI_TYPE_STRUCT, 23, 775, 1038
23	MPI_TYPE_CREATE_F90_REAL, 15, 155,	MPI_TYPE_UB, 23, 775, 1038
24	158, 223, 688, 780, 798, 799–801, 1043	MPI_TYPE_VECTOR, 15, 118, 119, 120, 123,
25	MPI_TYPE_CREATE_HINDEXED, 15, 23,	155
	117, 123, <u>124</u> , 127, 128, 155, 775, 827	MPI_UNPACK, <u>172</u> , 173, 174, 178, 694
26	MPI_TYPE_CREATE_HINDEXED_BLOCK,	MPI_UNPACK_EXTERNAL, 8, 179, 801
27	15, 117, 126, 155, 827, 1039	MDI TINDIDI ICH NAME 464 F20 F21
28	MPI_TYPE_CREATE_HVECTOR, 15, 23,	MDI LICED ELINCTION 220 827
29		MPI_WAIT, 37, 39, 67, 68–71, 73, 74, 88, 96,
30	MPI_TYPE_CREATE_INDEXED_BLOCK,	99, 100, 106, 107, 246, 272, 301, 487,
31	15, 125, 126, 155	510, 621, 625, 648, 649, 675, 696, 698,
32	MPI_TYPE_CREATE_KEYVAL, 359, 370,	807, 808, 814, 815, 818
	373, 837, 863, 866, 1046	MPI_WAITALL, 72, 74, 75, 246, 302, 510, 574,
33	MPI_TYPE_CREATE_RESIZED, 23, 117,	623–625, 628
34	140, 144, 155, 686, 776, 1041	MPI_WAITANY, 51, 72, 73, 78, 510, 623, 624,
35	MPI_TYPE_CREATE_STRUCT, 15, 23, 117,	628
36	127, 128, 141, 155, 218, 775, 827	MPI_WAITSOME, 72, <u>76,</u> 77, 78, 510,
37	MPI_TYPE_CREATE_SUBARRAY, 15, 18,	623–625, 628
38		
39	129, 131, 133, 155 MDI TVDE DELETE ATTR 250, 272, 1041	MPI_WIN_ALLOCATE, 542, <u>546</u> , 547, 549,
	MPI_TYPE_DELETE_ATTR, 359, <u>373</u> , 1041	555–557, 562, 595, 792, 794, 1033,
40	MPI_TYPE_DUP, 15, <u>148</u> , 155, 1041	1035
41	MPI_TYPE_DUP_FN, <u>370</u> , 853, 1036	MPI_WIN_ALLOCATE_CPTR, 547, 1035
42	MPI_TYPE_EXTENT, 23, 775, 1038	MPI_WIN_ALLOCATE_SHARED, 333, 542,
43	MPI_TYPE_F2C, <u>830</u> MPI_TYPE_FDEE_147_157_271_487_404	<u>548,</u> 549, 551, 556, 557, 595, 794,
44	MPI_TYPE_FREE, <u>147</u> , 157, 371, 487, 494	1033, 1035 MDI WIN ALLOCATE CHARED COTO
45	MPI_TYPE_FREE_KEYVAL, 359, <u>371</u> , 373	MPI_WIN_ALLOCATE_SHARED_CPTR,
46	MPI_TYPE_GET_ATTR, 359, <u>372</u> , 373, 788,	549, 1035
	837, 1041 MDI TYPE GET CONTENTS 154 156	MPI_WIN_COE_ 220
47	MPI_TYPE_GET_CONTENTS, 154, <u>156</u> , 157–159, 827	MPI_WIN_C2F, <u>830</u>
48	167 16U XT/	MPI_WIN_CALL_ERRHANDLER, 467, 469

#-error!

#-other

PR449

MPI_WIN_COMPLETE, 555, 584, <u>588</u> ,	$MPI\_WIN\_TEST, \underline{590}, 591$	1
589-592, 600, 601, 607	MPI_WIN_UNLOCK, 555, 576, 584, <u>593</u> , 595,	2
MPI_WIN_CREATE, 511, 542, 543, 545, 547,	600, 601, 604–606	3
549, 553–555, 557, 599	MPI_WIN_UNLOCK_ALL, 576, 584, 593,	
		4
MPI_WIN_CREATE_DYNAMIC, 464, 542,	<u>594,</u> 600, 601, 604, 615	5
552, $553$ , $554$ , $556$ , $557$ , $600$	MPI_WIN_WAIT, 555, 584, <u>590</u> , 591, 592,	6
MPI_WIN_CREATE_ERRHANDLER, 452,	594, 601, 604, 607, 608	· ·
<u>455</u> , 456, 863, 866, 1041	MPI_WTICK, 24, <u>470</u> , 748	7
MPI_WIN_CREATE_KEYVAL, 359, <u>366</u> , 373,	MPI_WTIME, 14, 24, 446, 469, 470, 716, 735,	8
		9
837, 862, 865, 1046	748	9
MPI_WIN_DELETE_ATTR, 359, <u>369</u> , 373	mpiexec, 481, 482, 484, 505, <u>506</u> , 1034	10
MPI_WIN_DETACH, 552, 554, 556	mpirun, 506	11
MPI_WIN_DUP_FN, <u>366</u> , <u>853</u> , <u>1036</u>		10
MPI_WIN_F2C, <u>830</u>	PMPI_, 713, 788	12
	PMPI_AINT_ADD, 24	13
MPI_WIN_FENCE, 555, 564, 584, <u>586</u> , 587,		14
588, 598-601, 604, 609, 818	PMPI_AINT_DIFF, 24	
MPI_WIN_FLUSH, 550, 574, 576, <u>595</u> , 596,	PMPI_ISEND, 788, 791	15
600, 601, 614, 616	PMPI_T_EVENT_COPY, 749	16
MPI_WIN_FLUSH_ALL, 574, 576, 596, 600,	PMPI_T_EVENT_GET_SOURCE, 749	17
	PMPI_T_EVENT_GET_TIMESTAMP, 749	
601		18
MPI_WIN_FLUSH_LOCAL, 574, <u>596</u> , 600	PMPI_T_EVENT_READ, 749	19
MPI_WIN_FLUSH_LOCAL_ALL, 574, 597,	PMPI_T_PVAR_READ, 749	20
600	PMPI_T_PVAR_READRESET, 749	
MPI_WIN_FREE, 367, 487, 494, 538, <u>555</u> , <u>556</u>	PMPI_T_PVAR_RESET, 749	21
	PMPI_T_PVAR_START, 749	22
MPI_WIN_FREE_KEYVAL, 359, <u>368</u> , <u>373</u>		0.0
MPI_WIN_GET_ATTR, 359, <u>368</u> , 373, 556,	PMPI_T_PVAR_STOP, 749	23
788, 837, 840	PMPI_T_PVAR_WRITE, 749	24
MPI_WIN_GET_ERRHANDLER, 452, 456,	PMPI_T_SOURCE_GET_TIMESTAMP, 749	25
1047	PMPI_WTICK, 24	#-other
	,	
MDI WIN CET CDOID **7	PMPL WTIME: 94	π-Δrrccri/
MPI_WIN_GET_GROUP, 557	PMPI_WTIME, 24	#-error!?
MPI_WIN_GET_INFO, 558, 559, 1033, 1039	·	#-error!?
	Are these functions really new functions?	#-error!!
MPI_WIN_GET_INFO, 558, 559, 1033, 1039	·	27 #-error! <i>?</i>
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, 555, 584, <u>592</u> ,	Are these functions really new functions? # 20 new routines	#-error! <i>?</i>
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, 555, 584, <u>592</u> , 593–595, 598, 599, 601, 605, 606	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS	#-error! <i>?</i>
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, 555, 584, <u>592</u> , 593–595, 598, 599, 601, 605, 606 MPI_WIN_LOCK_ALL, 544, 584, <u>593</u> , 594,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS	#-error! <i>?</i>
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592, 593-595, 598, 599, 601, 605, 606 MPI_WIN_LOCK_ALL, 544, 584, 593, 594, 598, 599, 601, 606, 614, 615	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO	#-error! <i>?</i>
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, 555, 584, <u>592</u> , 593-595, 598, 599, 601, 605, 606 MPI_WIN_LOCK_ALL, 544, 584, <u>593</u> , 594, 598, 599, 601, 606, 614, 615 MPI_WIN_NULL_COPY_FN, <u>366</u> , 853, 1036	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_COPY MPI_T_EVENT_GET_INDEX	<sub>27</sub> #-error!!
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592, 593-595, 598, 599, 601, 605, 606 MPI_WIN_LOCK_ALL, 544, 584, 593, 594, 598, 599, 601, 606, 614, 615	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_COPY MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO	#-error!!
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, 555, 584, <u>592</u> , 593-595, 598, 599, 601, 605, 606 MPI_WIN_LOCK_ALL, 544, 584, <u>593</u> , 594, 598, 599, 601, 606, 614, 615 MPI_WIN_NULL_COPY_FN, <u>366</u> , 853, 1036	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_COPY MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_NUM	#-error!!
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, 555, 584, <u>592</u> , 593-595, 598, 599, 601, 605, 606 MPI_WIN_LOCK_ALL, 544, 584, <u>593</u> , 594, 598, 599, 601, 606, 614, 615 MPI_WIN_NULL_COPY_FN, <u>366</u> , 853, 1036 MPI_WIN_NULL_DELETE_FN, <u>367</u> , 853, 1036	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_COPY MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_NUM MPI_T_EVENT_GET_SOURCE	27 #-error! <i>!</i>
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, 555, 584, <u>592</u> ,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_COPY MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_NUM MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP	27 #-error! <i>!</i>
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, 555, 584, <u>592</u> ,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_COPY MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_NUM MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_HANDLE_ALLOC	#-error!!
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, <u>555</u> , 584, <u>592</u> ,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_COPY MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE	#-error!!
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, 555, 584, <u>592</u> ,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_GET_INFO	27 #-error! <i>!</i>
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_COPY MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO	27 #-error! <i>!</i>
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, 555, 584, <u>592</u> ,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_COPY MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_NUM MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_GET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO	#-error!!
MPI_WIN_GET_INFO, 558, <u>559</u> , 1033, 1039 MPI_WIN_GET_NAME, <u>379</u> MPI_WIN_LOCK, 544, 555, 584, <u>592</u> ,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_COPY MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_NUM MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_GET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_READ	#-error!!
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_NUM MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_GET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_SET_DROPPED_HANDLER	27 #-error! <i>!</i>
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_NOM MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_GET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_SET_DROPPED_HANDLER MPI_T_SOURCE_GET_INFO	27 #-error! <i>!</i>
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_NUM MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_SET_DROPPED_HANDLER MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_NUM	27 #-error! <i>!</i>
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_NOM MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_GET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_SET_DROPPED_HANDLER MPI_T_SOURCE_GET_INFO	#-error!!
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_NUM MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_SET_DROPPED_HANDLER MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_NUM MPI_T_SOURCE_GET_TIMESTAMP	21
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_SET_DROPPED_HANDLER MPI_T_SOURCE_GET_NUM MPI_T_SOURCE_GET_NUM MPI_T_SOURCE_GET_TIMESTAMP  # 11 PMPI_T_ functions listed in index PMPI_T_EVENT_COPY  REMOVED  Removed	21
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_REGISTER_CALLBACK MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_NUM MPI_T_SOURCE_GET_TIMESTAMP  # 11 PMPI_T_ functions listed in index PMPI_T_EVENT_COPY PMPI_T_EVENT_GET_SOURCE  Removed PR423	21
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_REGISTER_CALLBACK MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_SOURCE PMPI_T_EVENT_COPY PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_TIMESTAMP  Removed PR423	21
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_TIMESTAMP MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_REGISTER_CALLBACK MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_TIMESTAMP  # 11 PMPI_T_ functions listed in index PMPI_T_EVENT_COPY PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_TIMESTAMP  PMPI_T_EVENT_GET_TIMESTAMP PMPI_T_EVENT_READ	21
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_REGISTER_CALLBACK MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_TIMESTAMP  # 11 PMPI_T_ functions listed in index PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_TIMESTAMP  PMPI_T_EVENT_GET_TIMESTAMP  PMPI_T_EVENT_READ PMPI_T_EVENT_READ PMPI_T_EVENT_READ	21
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_COPY MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_REGISTER_CALLBACK MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_TIMESTAMP  # 11 PMPI_T_ functions listed in index PMPI_T_SOURCE_GET_TIMESTAMP  # 11 PMPI_T_ functions listed in index PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_TIMESTAMP  PMPI_T_EVENT_GET_TIMESTAMP  PMPI_T_EVENT_READ PMPI_T_EVENT_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ	21
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INFO MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_REGISTER_CALLBACK MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_INFO MPI_T_SOURCE_GET_TIMESTAMP  # 11 PMPI_T_ functions listed in index PMPI_T_SOURCE_GET_TIMESTAMP  # 11 PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_TIMESTAMP  PMPI_T_EVENT_GET_TIMESTAMP  PMPI_T_EVENT_READ PMPI_T_EVENT_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_RESET	21
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_NUM MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_SET_DROPPED_HANDLER MPI_T_SOURCE_GET_NUM MPI_T_SOURCE_GET_NUM MPI_T_SOURCE_GET_TIMESTAMP  # 11 PMPI_T_ functions listed in index PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_TIMESTAMP  PMPI_T_EVENT_GET_TIMESTAMP PMPI_T_EVENT_READ PMPI_T_EVENT_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_RESET PMPI_T_PVAR_RESET PMPI_T_PVAR_START	21
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_SET_DROPPED_HANDLER MPI_T_SOURCE_GET_NUM MPI_T_SOURCE_GET_NUM MPI_T_SOURCE_GET_TIMESTAMP  # 11 PMPI_T_ functions listed in index PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_TIMESTAMP  # 11 PMPI_T_FURNT_GET_SOURCE PMPI_T_EVENT_GET_TIMESTAMP  # 11 PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_RESET PMPI_T_PVAR_RESET PMPI_T_PVAR_START PMPI_T_PVAR_START PMPI_T_PVAR_STOP	21
MPI_WIN_GET_INFO, 558, 559, 1033, 1039 MPI_WIN_GET_NAME, 379 MPI_WIN_LOCK, 544, 555, 584, 592,	Are these functions really new functions? # 20 new routines MPI_T_CATEGORY_GET_EVENTS MPI_T_CATEGORY_GET_NUM_EVENTS MPI_T_EVENT_CALLBACK_GET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_CALLBACK_SET_INFO MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_INDEX MPI_T_EVENT_GET_NUM MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_GET_SOURCE MPI_T_EVENT_HANDLE_ALLOC MPI_T_EVENT_HANDLE_FREE MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_HANDLE_SET_INFO MPI_T_EVENT_READ MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_REGISTER_CALLBACK MPI_T_EVENT_SET_DROPPED_HANDLER MPI_T_SOURCE_GET_NUM MPI_T_SOURCE_GET_NUM MPI_T_SOURCE_GET_TIMESTAMP  # 11 PMPI_T_ functions listed in index PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_SOURCE PMPI_T_EVENT_GET_TIMESTAMP  PMPI_T_EVENT_GET_TIMESTAMP PMPI_T_EVENT_READ PMPI_T_EVENT_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_READ PMPI_T_PVAR_RESET PMPI_T_PVAR_RESET PMPI_T_PVAR_START	21