



Mtree

Tree creation

About Mtree

Mtree is a tree creation tool that allows easy high quality tree creation inside unity editor.

Mtree consist of:

- User friendly step by step tree creation.
- Branches obstacle avoidance to make trees that adapt to the environment.
- Automatic material creation.
- Shader that supports wind vertex displacement, fast translucency, leaf color variation, and instancing.
- Automatic levels of details (LOD) creation.
- Automatic billboard creation.
- Automatic ambient occlusion bake into the vertex colors. o Prefab creation.

Index


1. Mtree - Getting Started	Page 3
Create a Tree	
The Mtree Component	
Functions Tab	
Add Branch Functions	
Add Leaf Functions	
Split and Grow Functions	
The Functions Parameter	
Quality Tab	
Save as Prefab Tab	
Vertex Color Multiplier	
2. Exhaustive List of function parameters.	Page 6
Trunk	
Add Branch	
Add Leaf	
Split	
Grow	
3. Shaders	Page 8
Types	
Shader Properties	
Global Wind Controller	
Vegetation Studio Pro	
Amplify Shader Editor	
4. Bezier Mode	Page 14
Using Bezier Mode	
5. Billboard	Page 15
Billboard Creation	
6. Branch Texture Editor	Page 16
Getting Started with the Branch Editor	
Opening the Branch Editor	
Create a basic Branch Texture	
Standard and Enhanced Mode	
7. Exhaustive list of the Branch Editor parameters.	Page 17
Branch Settings	
Leaf Settings	
8. Vertex Color Adjustment Editor	Page 18
Getting started with the Vertex Color Adjustment Editor	
9. Mtree Requirements for HDRP, LWRP, URP	Page 19
If HDRP / LWRP / URP doesn't work and common mistakes	
HDRP Translucency	
10. Creating your own Asset for the Asset Store	Page 20
What files can i use?	
Licencing	

1. Mtree - Getting Started

Create a Tree

In order to create a tree, rightclick in Hierarchy go to „3D Object/Create new Mtree...” and select this Option.


You can also add an empty object, and add the component MtreeComponent.



The Mtree Component

The Mtree component is what will guide the creation of the tree, and allow to save it as a prefab.

It can be found in the inspector when a tree is selected.



There are three tabs on the Mtree component:

- Functions – To create the tree level by level.
- Quality – To control the quality and polycount of the tree.
- Save as prefab – To export the tree as a prefab once it is finished.


Functions Tab

It is the most important tab, the one in which the tree is effectively created.

A tree follows an intuitive structure. First there is the trunk, then the branches, and finally the leafs. To each step is associated a function, and each function has parameters.

To select a function and change its parameters, click on it.

To add a function, click on Add function and select the function you wish to add. The function will be added on top of the previously selected function.



To remove a function, click on the X inside the function you wish to remove.

Add Branch Function

This function adds branches the active level of the tree; if the trunk function is selected, the branches will be added to the trunk, and if a branch function is selected, the new branches will be added on the selected ones.

Add Leafs Function

This function adds leafs to the active level of the tree. If a tree has a leaf function, it will have two sub meshes, and two materials

Split and Grow Functions

Those functions are used to have a greater control over the tree. They are not used often.

The Split function adds tiny splits to the selected levels. Those splits are very short branches that can be grown.

The Grow function make the extremities of the active level of the tree grow. It is mostly used after a Split function, but can be applied any other function except a Leafs function.

The Branch function is nothing more than a Split and Grow functions combined into one, with less parameters exposed.

The Functions parameters


Each function has a set of parameters which control how the function affects the tree. Playing with the parameters is probably the best way to discover their uses.

Here are the most important parameters:

- Seed – Changing the seed will give another result of the function, like throwing dices two times will give two different numbers. To change the seed of all functions at once, you can click on Randomize tree.
- Length – controls the length of the branches/trunk generated.
- Resolution – Increasing the resolution will give a more complex looking tree, with a higher number of triangles. Be wary as the poly-count rises quickly.
- Randomness – A higher value will give the tree a more jagged appearance.

Quality Tab

It is a seldom visited tab, it allows control over the quality of the tree. The settings of the quality tabs vary with the level of detail (LOD) of the tree. To visualize each LOD level, change the LOD settings.




- Radial resolution – Controls the amount of vertices that go around each branch. Lower is more performant.
- Simplify angle – Controls how much straight branches are simplified. Higher is more performant.
- Simplify radius – Threshold of the thinnest branch drawn. Higher is more performant.
- Simplify leaves – Controls the density of leafs after their creation. Higher is more performant.

In most uses, the default values of each LOD level are good enough.

Save as prefab Tab

The trees are created with the Mtree component. When you are satisfied with the tree and consider it finished, **you must save it as a prefab using this tab**, otherwise the tree will not be optimized.



Saving the tree as prefab will generate all 4 LOD levels with ambient occlusion, as well as render a billboard. The meshes are saved in the specified folder, and a prefab with a LOD group is created.

You can visualize the result of the ambient occlusion pass by clicking on Bake ambient occlusion. Note that the ambient occlusion information will be lost if you change the tree afterwards.

You can Select the folder to which save the prefab by clicking on Find folder.

Save the tree as a prefab by clicking on Save as Prefab and wait until the process is over. You can find the prefab in the specified location. Once the tree is saved, only use the prefab, you can delete the tree with Mtree-Component attached.

Save as prefab Tab

You can Adjust the Vertex Color of the Tree by those two sliders, this will affect the Wind Strength on the Bark and the Leafs!



2. Exhaustive list of function parameters.

Trunk

<i>Parameters</i>	<i>Description</i>
Seed	Changing the seed will give another result of the function, like throwing dices two times will give two different numbers.
Length	The length of the generated trunk.
Radius	The radius of the trunk.
Resolution	The amount of points per unit of length.
Axis attraction	How much the tree is drawn to its original axis. Prevents the trunk from diverging too much.
Shape	The variation of the trunk radius with its length.
Randomness	How irregular the trunk looks.
Displacement strength	How much noise affects the geometry of the trunk.
Displacement size	How large is the noise affecting the geometry of the trunk.
Spin amount	How much the trunk is twisted.
Height offset	How much the trunk goes inside the ground. Helps when a tree is placed on an uneven ground.
Root Shape	The evolution of the radius of the trunk near the ground.
Height	The height to which the root goes.
Root Radius	The radius of the trunk on the ground.
Additional Resolution	How much more resolution to add to the trunk near the ground.
Flare number	Number of flares near the ground.

Add Branch

<i>Parameters</i>	<i>Description</i>
Seed	Changing the seed will give another result of the function, like throwing dices two times will give two different numbers.
Number	Approximate number of how many branches to add.
Length	The length of the branches.
Resolution	The amount of points per unit of length. Warning: polygon count is very sensible to this parameter.
Randomness	How irregular the branches look.
Radius	The start radius of the branches, relative to the radius of what they grow on.
Split proba	The probability for a branch to fork into multiple branches. Warning: polygon count is very sensible to this parameter.
Max splits number	The max number of branches a branch can fork into.
Angle	The angle of the branches from what they grow on.
Up attraction	How much the branches tend to grow toward the sky.
Gravity strength	How much gravity affects the branches.
Start	The minimum height from which the branches are created.

Add Leaf

Parameters	Description
Mesh type	The geometry of the leaf.
Number	Approximately how many leafs to add.
Size	The size of each leaf.
Max branch radius	The maximum radius of the branches from which the leafs are created.
Leaf Weight	How much the leafs are drawn to the ground.
Override normals	If true, the leafs normal will be determined by their position on the tree. If false the default leaf mesh normal are used.

Split

Parameters	Description
Seed	Changing the seed will give another result of the function, like throwing dices two times will give two different numbers.
Number	Approximately how many splits to add.
Split angle	The angle of the splits from what they grow on.
Max splits at a time	The max number of splits that can occur on the same location.
Split radius	The radius of the split relative to the radius of its parent.
Start	The height
Height spread	The minimum height from which the splits are created.

Grow

Parameters	Description
Seed	Changing the seed will give another result of the function, like throwing dices two times will give two different numbers.
Length	The additional length to grow the parent.
Resolution	The amount of points per unit of length. Warning: polygon count is very sensible to this parameter.
Split proba	The probability to fork into multiple branches. Warning: polygon count is very sensible to this parameter.
Split angle	When forking, the angle between the newly created branches.
Shape	The evolution of the radius with the length.
Split radius	When forking, the radius of the newly created branches.
Max splits at a time	The max number of splits that can occur on the same location.
Randomness	How irregular the branches look.
Up attraction	How much the branches tend to grow toward the sky.
Gravity strength	How much gravity affects the branche

3. Shaders

Shader Types

Legacy Shaders:

- Bark Shader
- Bark Shader Outline
- Leaf Shader ⇒ forward only
- Leaf Shader Deferred ⇒ deferred only
- Leaf Shader Outline
- Billboard Shader

HDRP Shaders:

- Bark HDRP Shader
- Leaf HDRP Shader
- Billboard HDRP Shader


LWRP Shaders:

- Bark HDRP Shader
- Leaf HDRP Shader
- Billboard HDRP Shader

URP Shaders:


- Bark HDRP Shader
- Leaf HDRP Shader
- Billboard HDRP Shader

Albedo




Property	Explanenation			Bark LWRP							
Color	Color tint										
Albedo	Main Texture of the Material										
Cull Mode	Which Face is beeing rendered										
Double Sided Normal Mode	How the backface Normals are displayed										
Cutoff	Threshold of Alpha Cutout										

Normal




Property	Explanenation			Bark LWRP							
Normal	Main Normal Map of the Material										
Normal Strength	Intensity of the Normal Map										

Color Settings



Property	Explanenation			Bark LWRP							
Color Shifting	Color Shifting On / Off toggle										
Hue	Color										
Value	Brightness of the Color										
Saturation	Saturation of the Color										


Translucency Legacy & Outline Leaf



Used by following shaders:
[Leafs Legacy](#), [Leafs Outline](#)

Property	Explanation
Strength	Translucency effect strength, you can think of it as a multiplier slider.
Normal Distortion	Defines the amount of normal distortion on the translucency effect.
Scattering Falloff	Scattering falloff amount for the translucency effect.
Direct	Direct light influence on the translucency effect.
Ambient	GI/ambient light influence on the translucency effect.
Shadow	Self-shadowing influence on the translucency effect, reduces the translucency effect in shadowed areas.
Translucency Tint	Translucency Color
Transmission Tint	Transmission Color

Translucency Custom Leaf Shader



Used by following shaders:
[Leafs LWRP](#), [Leafs URP](#), [Leafs Legacy Deferred](#)

Property	Explanation
Translucency	On / Off toggle for Translucent effect.
Strength	Translucency effect strength, you can think of it as a multiplier slider.
Normal Distortion	Defines the amount of normal distortion on the translucency effect.
Scale	Size of the Effect
Scattering Falloff	Scattering falloff amount for the translucency effect.
Translucency Tint	Translucency Color, only works if custom color is selected as source.
Color Source	Select if global light color or custom color is used.

Translucency HDRP Leaf Shader

Used by following shaders:
[HDRP](#)

4.x	Diffusion Profile List
5.x / 6.x	Diffusion Profile Provided by Mtree, set directly in Shaders.
7.x	Diffusion Profile, which can be directly switched out in the Shaders.

Thickness Map is directly baked in to uv4.x Channel!
Mtree Documentation 2.3

Other Settings

Other Settings

AO strength

1

Metallic

0

Smoothness

0.5

Property	Explenation			Bark LWRP							
AO Strength	Ambient Occlusion Strength										
Metallic	Main Texture of the Material										

Wind

Wind

Global Wind Influence

1

Global Turbulence Influence

1

Wind Mode Leaves


Leaves 1

Property	Explenation			Bark LWRP							
Global Wind Influence	Global Wind influence (needs to be the same on Bark / Leaf Material)										
Global Turbulence Influen- ce	Global Leaftumbling influence										

Global Wind Controller

The Mtree Wind script works with or without a Wind Zone. If a Wind Zone is selected the Wind Zones Parameters are used for controlling the Wind and The Mtree Wind Offset is for fine tuning the Mtree Wind, if a behaviours is too much or anything other is not like desired.

Billboard Wind is by default off.




Property	Explanation
Wind Zone	If Wind Zone is assigned, Mtree Wind will execute from there.
Wind Strength	Main Global Wind Strength
Wind Direction	Main Wind Direction
Wind Pulse	Wave Speed
Wind Turbulence	Shivering of the Leaves
Billboard Wind	Toggle for Billboard Wind
Billboard Wind Influence	How much the Main Wind impacts on Billboards

Adding a Global Wind Controller

Mtree Wind Controller can either be attached by script, Add Component on a GameObject, or by opening the Menu: „Window/Mtree/ Add Mtree Global Wind Controller to Scene...”

This will add a WindZone and the Mtree Wind Script to the Scene at Position (0,0,0).



Vegetation Studio Pro

Mtree Works perfectly with Vegetation Studio Pro indirect instancing. Dueto non VSP licences holder, we moved the VSP ready shaders to a separate Package. Just open and replace the built in shaders with those from the package and you're good to go.




Path: *Mtree/Shaders/Legacy/VSPPro Shader Integration Mtree.untypackage*

Amplify Shader Editor

You can create your own tree shaders, working with Mtree!

Property	Path	Explanation
Wind Information	v.color.rgb	In Vertex Color we store on channel r the main bending of the Tree. On Channel g and b we have all information about how the leafs are shivering.
Ambient Occlusion	v.color.a	Ambient Occlusion is store in the Alpha channel of the Vertex Color.
Thickness Map	uv4.x	The approximate thickness Map is baked into uv4 channel x.


A Simple introduction to ASE Mtree Wind Node.

Property	Explanation	
Wind Properties 	<i>Select between Global or Local Properties.</i>	
	Local	will be shown directly on the Material.
	Global	has to be set through Script.
Material Types 	<i>Select between different type of Wind</i>	
	Bark Material	Only Main bending active.
	Leaf Material	Leaf, Palm, Grass or none Windmode selectabel in shader
	Leaf Standalone	Leaf only movement
	Palm Stand-alone	Palm only movement
	Grass Stand-alone	Grass only movement
Vertex Output 	<i>Select how the wind is applied. It needs to be the same as in ASE Vertex Output</i>	
	Relative	v.vertex += Wind Calculations;
	Absolute	v.vertex = Wind Calculations;

4. Bezier Mode

With Mtree 2.3 you are now able to design your trees along a Bezier curve.

Bezier Tool






Property	Explenation
Use Mtree	Returns back to Mtree and removes the Bezier manipulation.
Use Bezier	Adds Bezier manipulation.
Activate / Deactivate Bezier Mode	Button for toggle on and of the Mode.
Add Curve	Add an other Curve to the Bezier Spline.
Activate / Deactivae Leaf Direction	Button for toggle custom Branch direction on and off.
Branch Growth Direction	Direction of Branch growing.
Position	Position of the current Bezier Point selected.
Mode	Select between Free, Aligned and Mirrored. This has influence on how the Bezier manipulation is reacting.
Billboard Wind Influence	How much the Main Wind impacts on Billboards

5. Billboard


Overview

in Mtree 2.3 you can now select between 4 different Billboard types.



Type	Verts	Tris	Textures	Shader Culling	Explanation
Double Sided without Topcard	8	4	2	Off	Less geometry used.
Double Sided with Topcard	12	6	3	Off	Less geometry used & Looks good on fly overs.
Single Sided without Topcard	16	8	4	Back	More detailed.
Single Sided with Topcard	24	12	6	Back	More detailed & looks good on fly overs.

Functions



Property	Explanation
Brightness	Brightness of the Render captured from the Tree.
Double Sided / Single Sided	How the Mesh is created
No Top Card / Has Top Card	Adding a Topcard to the BB.
Top Card Position	Height position of the Top Card (0 = Bottom of BB, 1 = on Top of BB)


6. Branch Texture Editor

Preamble: as you maybe know, it is not difficult to find leaves textures on the internet. But to find branches textures, it is quite the opposite. However, using branches textures is known to be more optimal, that is why Mtree offers you a unique and simple tool that create a branch texture from a leaf texture, and then uses it as a leaf shader. Let us find how it works.

Getting started with the Branch Editor

Open the Branch Editor

To access the tool window, you must go in: „*Window/Mtree/BranchEditor*“.



Create a basic Branch Texture

The two most important settings are the leaf texture and the bark texture.

After assign those two textures, tweak all the other parameters until you are satisfied with the result. You can find the exhaustive description of all parameters in the next chapter.

Choose the Size of the Generated Texture.

Once you are satisfied with the result and want to save the texture, click on “save texture”.

Standard and Enhanced Mode


Since Mtree 2.2 you can switch between Standard (Procedural generated Normals) and Enhanced Mode, which is available when you add Normal Maps to the given Properties.

If any of the Bark or Leaf Normal Properties are empty, Enhanced Mode won't be available to use.

Use Normal Rotation only if the Normals in Enhanced Mode are incorrect. You can Hit Show Normals / Show Textures button to switch the view.

Attention!

If you are not on Legacy Pipeline and using the Branch Editor, Mtree will switch Automatically Pipelines aslong as you use the Branch Editor (your Materials get Pink), and switches back, when closing the Editor Window! This action does not break you Scene Setup!



7. Exhaustive list of the Branch Editor parameters

Branch Settings

<i>Parameter</i>	<i>Description</i>
Randomize	Change the seed of the branch.
Bark Texture	The texture to use for the bark
Bark Color	The color of the bark.
Fake Shading	How “3D” the bark appears.
Stem Length	The length of center branch.
Branch Length	The length of the side branches.
Radius	The radius of the branch.
Split angle	The angle between the newly created branches and the stem.
Randomness	How irregular the branch looks.
Branch Count	The number of side branches.
Split Proba	The probability for a branch to fork into multiple branches.

Leaf Settings

<i>Parameter</i>	<i>Description</i>
Leaf Texture	The texture of the leaf
Texture Alignment	The rotation of the leaf texture
Cut Off	Threshold at which a pixel is considered transparent.
Hue	The tint of the leaves
Saturation	How strong the colors are.
Value	How dark the leaves are.
Leaf Count	How many leaves there are on the branch.
Leaf covering	How the leafs are concentrated towards the extremities of the branches.
Leaf Length	How long the leaves are.
Leaf Size	The size of the leaves.
Leaf Angle	The max angle between a leaf and the branch it grew from

8. Vertex Color Adjustment Editor

This Editor is designed to make Meshes preferable Grasspatches working with Mtree Leaves shader!

Getting started with the Vertex Color Adjustment Editor

To begin with, this tool will paint Vertex Colors to your Mesh, which is not Undoable!

To properly preview what's done with your Mesh add, the Mtree Global Windcontroller to your scene.

Open the Vertex Color Adjustment Editor. Add then one or more GameObjects with meshes inside to the GameObjects property. For preview it can be aswell scene Objects, the Editor saves changes in any way!

Enable the „**Enable Override Mesh Options**“ and select a Vertex color. You can then switch between the Material Preview Leaves and Vertex Colors.

To apply the Color, hit „**Update all Vertex Colors**“.

9. Mtree Requirements for HDRP, LWRP, URP

In order to make Mtree work correctly with HDRP, LWRP and URP see the List below which SRP's are Supported:

Unity Version	SRP Version	Supported type
2017.4 - 2018.2	Ø	legacy
2018.3	4.10	legacy / HDRP / LWRP
2018.4	4.10	legacy / HDRP / LWRP
2019.1	5.16.1	legacy / HDRP / LWRP
2019.2	6.9.2	legacy / HDRP / LWRP
2019.3	7.1.6, 7.1.8	legacy / HDRP / URP
2020.1	untested	untested

legacy = Unity Standard Pipeline

If HDRP / LWRP / URP doesn't work and common mistakes

Be sure to download the correct supported SRP Version.

Be sure you've downloaded all the SRP dependency files from the Package Manager!

Be sure to switch to linear Space color when using HDRP.

10. Creating your own Asset for the Asset Store

What files can i use?


- All the Trees, which are saved as Prefabs and made with Mtree can be used for your Asset.
- The Leaves, Bark, Billboard Shader and all the Shaders in the SRP folders.
- The Mtree Wind Script.

You are not allowed to use anything else, to provide an new Asset on the Asset store!

(„For example: Source Code, Textures, etc.“)

If you're making a Game, and do not sell any Part of this Asset for production, you're free to use anything under the EULA from the Asset Store!

Licencing



This Asset is governed by the Asset Store EULA (https://unity3d.com/de/legal/as_terms); however, the following components are governed by the licenses indicated below:

2020©by Maxime following files are available under a Creative Commons Attribution-ShareAlike 4.0 Licence(international):

- Mtree/Shaders/Legacy/Leaves.shader
- Mtree/Shaders/Legacy/Bark.shader
- Mtree/Shaders/Legacy/Billboard.shader
- Mtree/Scripts/MtreeWind.cs
- Mtree/SRP/...

<https://creativecommons.org/licenses/by-sa/4.0/legalcode>
