





SIL Ethiopic Power-G Keyboard Help



The “SIL Ethiopic Power-G” keyboard enables typing in all Ethiopic Saba Fidel scripts using the keyboarding sequences found in the “Power Ge'ez (Phonetic)” keyboard from Concepts Data Systems. You can use this keyboard with any Ethiopic Unicode font unless you need to use the newer Unicode 6.0+ Ethiopic codepoints (for Basketo, Gumuz, and Gamo-Gofa-Dawro) or the two Private Use Area (PUA) characters of this keyboard:  and . In these cases, the [Abyssinica SIL](#) font (version 1.5+) is recommended.





































































































































Note on Power Ge'ez “Caps Lock” Compatibility

The original Power Ge'ez (Phonetic) keyboard from Concepts Data Systems used the **Caps Lock** key to produce less frequently used characters. SIL Ethiopic Power-G is not compatible with this keying method. Instead, multiple alternative methods for creating these less frequently used characters have been provided.

The preferred method for creating these less frequently used characters is by using the **[** key after the letter key to produce the desired character.

For example, to create  the chart shows **s [or J**. To produce this character using the preferred method, first press the **s** key, and then press the **[** key. Alternatively, a capital **J** can be typed to produce the  character.

As another example, to create  the chart shows **T [or V**. To produce this character using the preferred method, first type a capital **T**, and then press the **[** key. Alternatively, a capital **V** can be typed to produce the  character.

Syllables (including diphthongs)														
First type the keystrokes from the leftmost column, followed by the keystrokes at the top of the column. For example, to produce  first press the h key, and then press the u key. To produce  first press the h key, and then press the y key. The default form is the 1st form (you do not need to press the - key).														
keys:	-	u	i	a	y	e	o	O	W	Wu	Wi	Wy	Wo	WI
h	 1200	 1201	 1202	 1203	 1204	 1205	 1206	 1207						
l	 1208	 1209	 120a	 120b	 120c	 120d	 120e	 2d80	 120f					
H	 1210	 1211	 1212	 1213	 1214	 1215	 1216		 1217					
m	 1218	 1219	 121a	 121b	 121c	 121d	 121e	 2d81	 121f	 1383	 1381	 1382	 1380	 1359
s [or J	 1220	 1221	 1222	 1223	 1224	 1225	 1226		 1227					
r	 1228	 1229	 122a	 122b	 122c	 122d	 122e	 2d82	 122f					 1358
s	 1230	 1231	 1232	 1233	 1234	 1235	 1236	 2d83	 1237					
S	 1238	 1239	 123a	 123b	 123c	 123d	 123e	 2d84	 123f					
q	 1240	 1241	 1242	 1243	 1244	 1245	 1246	 1247	 124b	 124d	 124a	 124c	 1248	
Q	 1250	 1251	 1252	 1253	 1254	 1255	 1256		 125b	 125d	 125a	 125c	 1258	
b	 1260	 1261	 1262	 1263	 1264	 1265	 1266	 2d85	 1267	 1387	 1385	 1386	 1384	
v	 1268	 1269	 126a	 126b	 126c	 126d	 126e		 126f					
t	 	 	 	 	 	 	 	 	 					

	1270	1271	1272	1273	1274	1275	1276	2d86	1277					
c	ቸ	ቹ	ቺ	ቻ	ቼ	ች	ቸ	ቻ	ቼ					
	1278	1279	127a	127b	127c	127d	127e	2d87	127f					
h [or L	ሳ	ሑ	ሒ	ሓ	ሔ	ሕ	ሖ	ሗ	መ	ሙ	ሙ	ሞ	ሟ	
	1280	1281	1282	1283	1284	1285	1286	1287	128b	128d	128a	128c	1288	
n	ነ	ኑ	ኒ	ና	ኔ	ን	ኖ	ኖ	ኗ					
	1290	1291	1292	1293	1294	1295	1296	2d88	1297					
N	ኘ	ኙ	ኚ	ኛ	ኜ	ኝ	ኞ	ኟ	አ					
	1298	1299	129a	129b	129c	129d	129e	2d89	129f					
x	አ	አ	አ	አ	አ	እ	አ	አ	እ					
	12a0	12a1	12a2	12a3	12a4	12a5	12a6	2d8a	12a7					
k	ከ	ከ	ከ	ካ	ኬ	ክ	ኮ	ኰ	ኳ	ከ	ከ	ኰ	ኰ	
	12a8	12a9	12aa	12ab	12ac	12ad	12ae	12af	12b3	12b5	12b2	12b4	12b0	
H [or K	ኸ	ኹ	ኺ	ኻ	ኼ	ኽ	ኾ		ኻ	ኸ	ኹ	ኺ	ኻ	
	12b8	12b9	12ba	12bb	12bc	12bd	12be		12c3	12c5	12c2	12c4	12c0	
w	ወ	ወ	ወ	ወ	ወ	ወ	ወ	ወ						
	12c8	12c9	12ca	12cb	12cc	12cd	12ce	12cf						
X	ዐ	ዐ	ዐ	ዐ	ዐ	ዐ	ዐ							
	12d0	12d1	12d2	12d3	12d4	12d5	12d6							
z	ዘ	ዘ	ዘ	ዘ	ዘ	ዘ	ዘ	ዘ	ዘ					
	12d8	12d9	12da	12db	12dc	12dd	12de	2d8b	12df					
Z	ዠ	ዠ	ዠ	ዠ	ዠ	ዠ	ዠ		ዠ					
	12e0	12e1	12e2	12e3	12e4	12e5	12e6		12e7					
Y	የ	የ	የ	የ	የ	የ	የ	የ						
	12e8	12e9	12ea	12eb	12ec	12ed	12ee	12ef						
d	ደ	ደ	ደ	ደ	ደ	ደ	ደ	ደ	ደ					
	12f0	12f1	12f2	12f3	12f4	12f5	12f6	2d8c	12f7					
D	ደ	ደ	ደ	ደ	ደ	ደ	ደ	ደ	ደ					
	12f8	12f9	12fa	12fb	12fc	12fd	12fe	2d8d	12ff					
j	ጀ	ጀ	ጀ	ጀ	ጀ	ጀ	ጀ	ጀ	ጀ					
	1300	1301	1302	1303	1304	1305	1306	2d8e	1307					
g	ገ	ገ	ገ	ገ	ገ	ገ	ገ	ገ	ገ	ገ	ገ	ገ	ገ	
	1308	1309	130a	130b	130c	130d	130e	130f	1313	1315	1312	1314	1310	
G	ገ	ገ	ገ	ገ	ገ	ገ	ገ		ገ	ገ	ገ	ገ	ገ	
	1318	1319	131a	131b	131c	131d	131e		131f	2d96	2d94	2d95	2d93	
T	ጠ	ጠ	ጠ	ጠ	ጠ	ጠ	ጠ	ጠ	ጠ					
	1320	1321	1322	1323	1324	1325	1326	2d8f	1327					
C	ጨ	ጨ	ጨ	ጨ	ጨ	ጨ	ጨ	ጨ	ጨ					
	1328	1329	132a	132b	132c	132d	132e	2d90	132f					
P	ጰ	ጰ	ጰ	ጰ	ጰ	ጰ	ጰ	ጰ	ጰ					
	1330	1331	1332	1333	1334	1335	1336	2d91	1337					
t [or F	ጸ	ጸ	ጸ	ጸ	ጸ	ጸ	ጸ		ጸ					
	1338	1339	133a	133b	133c	133d	133e		133f					
T [or V	ፀ	ፀ	ፀ	ፀ	ፀ	ፀ	ፀ	ፀ						
	1340	1341	1342	1343	1344	1345	1346	1347						
f	ፈ	ፈ	ፈ	ፈ	ፈ	ፈ	ፈ		ፈ	ፈ	ፈ	ፈ	ፈ	ፈ
	1348	1349	134a	134b	134c	134d	134e		134f	138b	1389	138a	1388	135a
p	ፐ	ፐ	ፐ	ፐ	ፐ	ፐ	ፐ	ፐ	ፐ	ፐ	ፐ	ፐ	ፐ	
	1350	1351	1352	1353	1354	1355	1356	2d92	1357	138f	138d	138e	138c	
S #	ሸ	ሸ	ሸ	ሸ	ሸ	ሸ	ሸ							
	2da0	2da1	2da2	2da3	2da4	2da5	2da6							
c #	ቸ	ቸ	ቸ	ቸ	ቸ	ቸ	ቸ							
	2da8	2da9	2daa	2dab	2dac	2dad	2dae							
Z #	ጸ	ጸ	ጸ	ጸ	ጸ	ጸ	ጸ							
	2db0	2db1	2db2	2db3	2db4	2db5	2db6							
C #	ጨ	ጨ	ጨ	ጨ	ጨ	ጨ	ጨ							
	2db8	2db9	2dba	2dbb	2dbc	2dbd	2dbe							
q #	ቸ	ቸ	ቸ	ቸ	ቸ	ቸ	ቸ							
	2dc0	2dc1	2dc2	2dc3	2dc4	2dc5	2dc6							

k #	ሸ 2dc8	ሹ 2dc9	ሺ 2dca	ሻ 2dcb	ሼ 2dcc	ሽ 2dcd	ሾ 2dce						
H [# or K#	ሸ 2dd0	ሹ 2dd1	ሺ 2dd2	ሻ 2dd3	ሼ 2dd4	ሽ 2dd5	ሾ 2dd6						
g #	ሻ 2dd8	ሼ 2dd9	ሽ 2dda	ሾ 2ddb	ሿ 2ddc	ፀ 2ddd	ፁ 2dde						
C =	፳፬ ab20	፳፭ ab21	፳፮ ab22	፳፯ ab23	፳፰ ab24	፳፱ ab25	፳፺ ab26						
P =	፳፪ ab28	፳፫ ab29	፳፬ ab2a	፳፭ ab2b	፳፮ ab2c	፳፯ ab2d	፳፰ ab2e						
s =		ሰ ab01	ሱ ab02	ሲ ab03	ሴ ab04	ሶ ab05	ሸ ab06						
z =		ሸ ab11	ሺ ab12	ሻ ab13	ሼ ab14	ሽ ab15	ሾ ab16						
D =		ደ ab09	ደ ab0a	ደ ab0b	ደ ab0c	ደ ab0d	ደ ab0e						

Ethiopic Numbers

The keystrokes are at the top of the column.									
keys:	1 *	2 *	3 *	4 *	5 *	6 *	7 *	8 *	9 *
	፩ 1369	፪ 136a	፫ 136b	፬ 136c	፭ 136d	፮ 136e	፯ 136f	፰ 1370	፱ 1371
keys:	1*0	2*0	3*0	4*0	5*0	6*0	7*0	8*0	9*0
	፲ 1372	፳ 1373	፴ 1374	፵ 1375	፶ 1376	፷ 1377	፸ 1378	፹ 1379	፺ 137a
keys:	1*00	1*000	1*0000						
	፻ 137b	፿ e494	፽ 137c						

Punctuation

The keystrokes are at the top of the column.											
keys:	:	::	:-	:./	,	,,	;
	፡ 1361	። 1368	፣ 1366	፤ 1367	፪ 1362	፡ 0046	፡ 2022	፡ 1360	፡ 1365	፡ 1363	፡ 1364
keys:	< '	> '	< "	> "	m)						
	፫ 2039	፬ 203a	፭ 00ab	፮ 00bb	፯ e496						

Diacritics

First create the desired syllable, then add the diacritic by typing the keystrokes at the top of the column.													
keys:	. :	. '	. "	. 1	. 2	. 3	. 4	. 5	. 6	. 7	. 8	. 9	. 0
	፡ 135E	፡ 135F	፡ 135D	፡ 030f	፡ 0300	፡ 0304	፡ 0301	፡ 030b	፡ 0302	፡ 030c	፡ 0307	፡ 0308	፡ 0303