

The verb grid is handled through file **DISK\_0001/LECF/LFLF\_0010/SCRIP\_0022**  
All changes can be made through **hex editing**

## Verb grid structure

	16	48	7C
9B	Give	Pick up	Use
AB	Open	Look at	Push
BB	Close	Talk to	Pull

## Verb string structure

Ver b	Text Output	String	DEL	KB Shortcut	Char	Grid Coordinates	X	DEL	Y	DEL	EOL
Fx	09 02	%	00	13 12	XX	05	Gx	00	Gy	00	06 FF 7A

Example: **GIVE**

**04 09 02 47 69 76 65 00 13 12 67 05 16 00 9B 00 06 FF 7A**

[04] - **Function**

[47 69 76 65] - **“Give”** in hexadecimals

[67] - Letter **“g”** in hexadecimals

[16] - **Left** column

[9B] - **Top** row

## Verb functions

VERB	CODE
Give	04
Open	02
Close	03
Pick up	09
Look at	08
Talk to	0A
Use	07
Push	05
Pull	06